1 GeNN Documentation 1

1 GeNN Documentation

GeNN is a software package to enable neuronal network simulations on NVIDIA GPUs by code generation. Models are defined in a simple C-style API and the code for running them on either GPU or CPU hardware is generated by GeNN. GeNN can also be used through external interfaces. Currently there are interfaces for SpineML and SpineCreator and for Brian via Brian2GeNN.

GeNN is currently developed and maintained by

```
Dr James Knight (contact James)

James Turner (contact James)

Prof. Thomas Nowotny (contact Thomas)
```

Project homepage is http://genn-team.github.io/genn/.

The development of GeNN is partially supported by the EPSRC (grant numbers EP/P006094/1 - Brains on Board and EP/J019690/1 - Green Brain Project).

Note

This documentation is under construction. If you cannot find what you are looking for, please contact the project developers.

Next

2 Installation

You can download GeNN either as a zip file of a stable release or a snapshot of the most recent stable version or the unstable development version using the Git version control system.

2.1 Downloading a release

Point your browser to https://github.com/genn-team/genn/releases and download a release from the list by clicking the relevant source code button. Note that GeNN is only distributed in the form of source code due to its code generation design. Binary distributions would not make sense in this framework and are not provided. After downloading continue to install GeNN as described in the Installing GeNN section below.

2.2 Obtaining a Git snapshot

If it is not yet installed on your system, download and install Git (http://git-scm.com/). Then clone the GeNN repository from Github

```
git clone https://github.com/genn-team/genn.git
```

The github url of GeNN in the command above can be copied from the HTTPS clone URL displayed on the GeNN Github page (https://github.com/genn-team/genn).

This will clone the entire repository, including all open branches. By default git will check out the master branch which contains the source version upon which the next release will be based. There are other branches in the repository that are used for specific development purposes and are opened and closed without warning.

As an alternative to using git you can also download the full content of GeNN sources clicking on the "Download ZIP" button on the bottom right of the GeNN Github page (https://github.com/genn-team/genn).

2.3 Installing GeNN

Installing GeNN comprises a few simple steps to create the GeNN development environment.

Note

While GeNN models are normally simulated using CUDA on NVIDIA GPUs, if you want to use GeNN on a machine without an NVIDIA GPU, you can skip steps v and vi and use GeNN in "CPU_ONLY" mode.

- (i) If you have downloaded a zip file, unpack GeNN.zip in a convenient location. Otherwise enter the directory where you downloaded the Git repository.
- (ii) Add GeNN's "bin" directory to your path, e.g. if you are running Linux or Mac OS X and extracted/downloaded GeNN to \$HOME/GeNN, then you can add:

```
export PATH=$PATH:$HOME/GeNN/bin
```

to your login script (e.g. .profile or .bashrc. If you are using WINDOWS, the path should be a windows path as it will be interpreted by the Visual C++ compiler cl, and environment variables are best set using SETX in a Windows cmd window. To do so, open a Windows cmd window by typing cmd in the search field of the start menu, followed by the enter key. In the cmd window type:

```
setx PATH "C:\Users\me\GeNN\bin; %PATH%"
```

where C:\Users\me\GeNN is the path to your GeNN directory.

- (iv) Install the C++ compiler on the machine, if not already present. For Windows, download Microsoft Visual Studio Community Edition from https://www.visualstudio.com/en-us/downloads/download-visual-studio-vs.4 aspx. When installing Visual Studio, one should select the 'Desktop development with C++' configuration' and the 'Windows 8.1 SDK' and 'Windows Universal CRT' individual components. Mac users should download and set up Xcode from https://developer.apple.com/xcode/index.html Linux users should install the GNU compiler collection gcc and g++ from their Linux distribution repository, or alternatively from https://gcc.compu.org/index.html Be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (v) If your machine has a GPU and you haven't installed CUDA already, obtain a fresh installation of the NVIDIA C← UDA toolkit from https://developer.nvidia.com/cuda-downloads Again, be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (vi) Set the CUDA_PATH variable if it is not already set by the system, by putting

```
export CUDA_PATH=/usr/local/cuda
```

in your login script (or, if CUDA is installed in a non-standard location, the appropriate path to the main CUDA directory). For most people, this will be done by the CUDA install script and the default value of /usr/local/cuda is fine. In Windows, CUDA_PATH is normally already set after installing the CUDA toolkit. If not, set this variable with:

```
setx CUDA_PATH C:\path\to\cuda
```

This normally completes the installation. Windows useres must close and reopen their command window to ensure variables set using SETX are initialised.

If you are using GeNN in Windows, the Visual Studio development environment must be set up within every instance of the CMD.EXE command window used. One can open an instance of CMD.EXE with the development environment already set up by navigating to Start - All Programs - Microsoft Visual Studio - Visual Studio Tools - x64 Native Tools Command Prompt. You may wish to create a shortcut for this tool on the desktop, for convenience.

Top | Next

3 Quickstart

3 Quickstart

GeNN is based on the idea of code generation for the involved GPU or CPU simulation code for neuronal network models but leaves a lot of freedom how to use the generated code in the final application. To facilitate the use of GeNN on the background of this philosophy, it comes with a number of complete examples containing both the model description code that is used by GeNN for code generation and the "user side code" to run the generated model and safe the results. Some of the example models such as the Insect olfaction model use an <code>generate_\infty</code> run executable which automates the building and simulation of the model. Using these executables, running these complete examples should be achievable in a few minutes. The necessary steps are described below.

3.1 Running an Example Model

3.1.1 Unix

In order to build the <code>generate_run</code> executable as well as any additional tools required for the model, open a shell and navigate to the <code>userproject/MBody1_project</code> directory. Then type

make

to generate an executable that you can invoke with

```
./generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead invoke this executable with

```
./generate_run --cpu-only test1
```

3.1.2 Windows

While GeNN can be used from within Visual Studio, in this example we will use a <code>cmd</code> window. Open a Visual Studio <code>cmd</code> window via Start: All Programs: Visual Studio: Tools: x86 Native Tools Command Prompt, and navigate to the <code>userproject\tools</code> directory. Then compile the additional tools and the <code>generate_run</code> executable for creating and running the project:

```
msbuild ..\userprojects.sln /t:generate_mbody1_runner /p:Configuration=Release
```

to generate an executable that you can invoke with

```
generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead invoke this executable with

```
generate_run --cpu-only test1
```

3.1.3 Visualising results

These steps will build and simulate a model of the locust olfactory system with default parameters of 100 projection neurons, 1000 Kenyon cells, 20 lateral horn interneurons and 100 output neurons in the mushroom body lobes.

Note

If the model isn't build in CPU_ONLY mode it will be simulated on an automatically chosen GPU.

The generate_run tool generates input patterns and writes them to file, compiles and runs the model using these files as inputs and finally output the resulting spiking activity. For more information of the options passed to this command see the Insect olfaction model section. The results of the simulation can be plotted with

```
python plot.py test1
```

The MBody1 example is already a highly integrated example that showcases many of the features of GeNN and how to program the user-side code for a GeNN application. More details in the User Manual .

3.2 How to use GeNN for New Projects

Creating and running projects in GeNN involves a few steps ranging from defining the fundamentals of the model, inputs to the model, details of the model like specific connectivity matrices or initial values, running the model, and analyzing or saving the data.

GeNN code is generally created by passing the C++ model file (see below) directly to the genn-buildmodel script. Another way to use GeNN is to create or modify a script or executable such as $userproject/MBody1_\leftarrow project/generate_run.cc$ that wraps around the other programs that are used for each of the steps listed above. In more detail, the GeNN workflow consists of:

- 1. Either use external programs to generate connectivity and input files to be loaded into the user side code at runtime or generate these matrices directly inside the user side code.
- 2. Generating the model simulation code using <code>genn-buildmodel.sh</code> (On Linux or Mac) or <code>genn-buildmodel.bat</code> (on Windows). For example, inside the <code>generate_run</code> engine used by the MBody1_project, the following command is executed on Linux:

```
genn-buildmodel.sh MBodyl.cc
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, the following command is executed:

```
genn-buildmodel.sh -c MBody1.cc
```

The genn-buildmodel script compiles the GeNN code generator in conjunction with the user-provided model description model/MBodyl.cc. It then executes the GeNN code generator to generate the complete model simulation code for the model.

3. Provide a build script to compile the generated model simulation and the user side code into a simulator executable (in the case of the MBody1 example this consists the file MBody1Sim.cc). On Linux or Mac a suitable GNU makefile can be created by running:

```
{\tt genn-create-user-project.sh~MBody1~MBody1Sim.cc}
```

And on Windows an MSBuild project can be created by running:

```
genn-create-user-project.bat MBody1 MBody1Sim.cc
```

4. Compile the simulator executable by invoking GNU make on Linux or Mac:

```
make clean all
```

or MSbuild on Windows:

```
msbuild MBody1.sln /t:MBody1 /p:Configuration=Release
```

5. Finally, run the resulting stand-alone simulator executable. In the MBody1 example, this is called MBody1 on Linux and MBody1_Release.exe on Windows.

3.3 Defining a New Model in GeNN

According to the work flow outlined above, there are several steps to be completed to define a neuronal network model.

- 1. The neuronal network of interest is defined in a model definition file, e.g. Example1.cc.
- 2. Within the the model definition file Example1.cc, the following tasks need to be completed:
 - a) The GeNN file modelSpec.h needs to be included,

```
#include "modelSpec.h"
```

b) The values for initial variables and parameters for neuron and synapse populations need to be defined, e.g.

would define the (homogeneous) parameters for a population of Poisson neurons.

Note

The number of required parameters and their meaning is defined by the neuron or synapse type. Refer to the User Manual for details. We recommend, however, to use comments like in the above example to achieve maximal clarity of each parameter's meaning.

If heterogeneous parameter values are required for a particular population of neurons (or synapses), they need to be defined as "variables" rather than parameters. See the User Manual for how to define new neuron (or synapse) types and the Defining a new variable initialisation snippet section for more information on initialising these variables to hetererogenous values.

c) The actual network needs to be defined in the form of a function modelDefinition, i.e.

```
void modelDefinition(ModelSpec &model);
```

Note

The name modelDefinition and its parameter of type ModelSpec& are fixed and cannot be changed if GeNN is to recognize it as a model definition.

d) Inside modelDefinition(), The time step DT needs to be defined, e.g.

```
model.setDT(0.1);
```

Note

All provided examples and pre-defined model elements in GeNN work with units of mV, ms, nF and muS. However, the choice of units is entirely left to the user if custom model elements are used.

MBody1.cc shows a typical example of a model definition function. In its core it contains calls to Model← Spec::addNeuronPopulation and ModelSpec::addSynapsePopulation to build up the network. For a full range of options for defining a network, refer to the User Manual.

- 3. The programmer defines their own "user-side" modeling code similar to the code in userproject/M← Body1_project/model/MBody1Sim.cc. In this code,
 - a) They manually define the connectivity matrices between neuron groups. Refer to the Synaptic matrix types section for the required format of connectivity matrices for dense or sparse connectivities.
 - b) They define input patterns (e.g. for Poisson neurons like in the MBody1 example) or individual initial values for neuron and / or synapse variables.

Note

The initial values given in the modelDefinition are automatically applied homogeneously to every individual neuron or synapse in each of the neuron or synapse groups.

- c) They use stepTime() to run one time step on either the CPU or GPU depending on the options passed to genn-buildmodel.
- d) They use functions like <code>copyStateFromDevice()</code> etc to transfer the results from GPU calculations to the main memory of the host computer for further processing.
- e) They analyze the results. In the most simple case this could just be writing the relevant data to output files.

Previous | Top | Next

4 Examples

for Windows users, or:

GeNN comes with a number of complete examples. At the moment, there are seven such example projects provided with GeNN.

4.1 Single compartment Izhikevich neuron(s)

```
Izhikevich neuron(s) without any connections
This is a minimal example, with only one neuron population (with more or less
neurons depending on the command line, but without any synapses). The neurons
are Izhikevich neurons with homogeneous parameters across the neuron population.
This example project contains a helper executable called "generate_run",
which compiles and executes the model.
To compile it, navigate to genn/userproject/OneComp_project and type:
msbuild ..\userprojects.sln /t:generate one comp runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-neurons: Number of neurons to simulate (defaults to 1)
For a first minimal test, using these defaults and recording results with a base name of 'test', the system may
generate_run.exe test
```

```
./generate_run test

for Linux, Mac and other UNIX users.

This would create a set of tonic spiking Izhikevich neurons with no connectivity, receiving a constant identical 4 nA input.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and 4 neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=4 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=4 test

for Linux, Mac and other UNIX users.
```

4.2 Izhikevich neurons driven by Poisson input spike trains:

Izhikevich network receiving Poisson input spike trains _____ In this example project there is again a pool of non-connected Izhikevich model neurons that are connected to a pool of Poisson input neurons with a fixed probability. This example project contains a helper executable called "generate_run", which compiles and executes the model. To compile it, navigate to genn/userproject/PoissonIzh_project and type: msbuild ..\userprojects.sln /t:generate_poisson_izh_runner /p:Configuration=Release for Windows users, or: for Linux, Mac and other UNIX users. USAGE generate_run [OPTIONS] <outname> Mandatory arguments: outname: The base name of the output location and output files Optional arguments: --debug: Builds a debug version of the simulation and attaches the debugger --cpu-only: Uses CPU rather than CUDA backend for GeNN --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation --ftype: Sets the floating point precision of the model to either float or double (defaults to float) --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically) --num-poisson: Number of Poisson sources to simulate (defaults to 100) --num-izh: Number of Izhikievich neurons to simulate (defaults to 10) --pconn: Probability of connection between each pair of poisson sources and neurons (defaults to 0.5) -- qscale: Scaling of synaptic conductances (defaults to 2) --sparse: Use sparse rather than dense data structure to represent connectivity An example invocation of generate_run using these defaults and recording results with a base name of 'test': generate run.exe test

for Windows users, or:

./generate_run test

```
for Linux, Mac and other UNIX users.

This will generate a network of 100 Poisson neurons with 20 Hz firing rate connected to 10 Izhikevich neurons with a 0.5 probability.

The same network with sparse connectivity can be used by adding the --sparse flag to the command line. Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses sparse connectivity would be:

generate_run.exe --cpu-only --timing --sparse test

for Windows users, or:

./generate_run --cpu-only --timing --sparse test

for Linux, Mac and other UNIX users.

Izhikevich neuron model:[1]

4.3 Pulse-coupled Izhikevich network

Pulse-coupled Izhikevich network

This example model is inspired by simple thalamo-cortical network of Izhikevich with an excitatory and an inhibitory population of spiking neurons that are
```

with an excitatory and an inhibitory population of spiking neurons that are randomly connected. It creates a pulse-coupled network with 80% excitatory 20% inhibitory connections, each connecting to a fixed number of neurons with sparse connectivity. To compile it, navigate to genn/userproject/Izh_sparse_project and type: msbuild ..\userprojects.sln /t:generate_izh_sparse_runner /p:Configuration=Release for Windows users, or: make for Linux, Mac and other UNIX users. USAGE generate_run [OPTIONS] <outname> Mandatory arguments: outname: The base name of the output location and output files Optional arguments: --debug: Builds a debug version of the simulation and attaches the debugger --cpu-only: Uses CPU rather than CUDA backend for GeNN --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation --ftype: Sets the floating point precision of the model to either float or double (defaults to float) --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically) --num-neurons: Number of neurons (defaults to 10000) --num-connections: Number of connections per neuron (defaults to 1000) --gscale: General scaling of synaptic conductances (defaults to 1.0) An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo generate_run.exe test for Windows users, or:

./generate run test

```
a mixed alpha and gamma regime. For larger input factor, there is more input current and more irregular activity, for smaller factors less and less and more sparse activity. The synapses are of a simple pulse-coupling type. The results of the simulation are saved in the directory 'outdir_output'.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and doubles the number of neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=20000 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=20000 test

for Linux, Mac and other UNIX users.
```

4.4 Izhikevich network with delayed synapses

Izhikevich neuron model: [1]

```
Izhikevich network with delayed synapses
```

This example project demonstrates the synaptic delay feature of GeNN. It creates a network of three Izhikevich neuron groups, connected all-to-all with fast, medium and slow synapse groups. Neurons in the output group only spike if they are simultaneously innervated by the input neurons, via slow synapses, and the interneurons, via faster synapses.

```
COMPILE (WINDOWS)

To run this example project, first build the model into CUDA code by typing:

genn-buildmodel.bat SynDelay.cc

then compile the project by typing:

msbuild SynDelay.sln /t:SynDelay /p:Configuration=Release

COMPILE (MAC AND LINUX)

To run this example project, first build the model into CUDA code by typing:

genn-buildmodel.sh SynDelay.cc

then compile the project by typing:

make

USAGE

-----

syn_delay [directory to save output]
```

4.5 Insect olfaction model

Izhikevich neuron model: [1]

Locust olfactory system (Nowotny et al. 2005)

```
This project implements the insect olfaction model by Nowotny et
al. that demonstrates self-organized clustering of odours in a
simulation of the insect antennal lobe and mushroom body. As provided
the model works with conductance based Hodgkin-Huxley neurons and
several different synapse types, conductance based (but pulse-coupled)
excitatory synapses, graded inhibitory synapses and synapses with a
simplified STDP rule. This example project contains a helper executable called "generate_run", which
prepares input pattern data, before compiling and
executing the model.
To compile it, navigate to genn/userproject/MBody1_project and type:
msbuild ..\userprojects.sln /t:generate_mbody1_runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-al: Number of neurons in the antennal lobe (AL), the input neurons to this model (defaults to 100)
--num-kc: Number of Kenyon cells (KC) in the "hidden layer" (defaults to 1000)
--num-lhi: Number of lateral horn interneurons, implementing gain control (defaults to 20)
--num-dn: Number of decision neurons (DN) in the output layer (defaults to 100)
--gscale: A general rescaling factor for synaptic strength (defaults to 0.0025)
--bitmask: Use bitmasks to represent sparse PN->KC connectivity rather than dense connectivity
--delayed-synapses: Rather than use constant delays of DT throughough, use delays of (5 \star DT) ms on KC->DN and
An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo
generate run.exe test
```

for Windows users, or:

./generate_run test

for Linux, Mac and other UNIX users.

Such a command would generate a locust olfaction model with 100 antennal lobe neurons, 1000 mushroom body Kenyon cells, 20 lateral horn interneurons and 100 mushroom body output neurons, and launch a simulation of it on a CUDA-enabled GPU using single precision floating point numbers. All output files will be prefixed with "test" and will be created under the "test" directory. The model that is run is defined in 'model/MBody1.cc', debugging is switched off and the model would be simulated using float (single precision floating point) variables.

In more details, what generate_run program does is:

- a) use another tools to generate input patterns.
- b) build the source code for the model by writing neuron numbers into ./model/sizes.h, and executing "genn-buildmodel.sh ./model/MBody1.cc.
- c) compile the generated code by invoking "make clean && make" running the code, e.g. "./classol_sim r1".

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses bitmask connectivity would be:

```
generate_run.exe --cpu-only --timing --bitmask test
for Windows users, or:
./generate_run --cpu-only --timing --bitmask test
for Linux, Mac and other UNIX users.
As provided, the model outputs 'test.dn.st', 'test.kc.st', 'test.lhi.st' and 'test.pn.st' files which contain
the spiking activity observed in each population inthe simulation, There are two
columns in this ASCII file, the first one containing the time of
a spike and the second one the ID of the neuron that spiked. Users
of matlab can use the scripts in the 'matlab' directory to plot
the results of a simulation and users of python can use the plot_spikes.py script in userproject/python.
For more about the model itself and the scientific insights gained from it see Nowotny et al. referenced below
MODEL INFORMATION
For information regarding the locust olfaction model implemented in this example project, see:
T. Nowotny, R. Huerta, H. D. I. Abarbanel, and M. I. Rabinovich Self-organization in the
olfactory system: One shot odor recognition in insects, Biol Cyber, 93 (6): 436-446 (2005),
doi:10.1007/s00422-005-0019-7
Nowotny insect olfaction model: [4]; Traub-Miles Hodgkin-Huxley neuron model: [7]
```

Voltage clamp simulation to estimate Hodgkin-Huxley parameters

```
Genetic algorithm for tracking parameters in a HH model cell
______
```

This example simulates a population of Hodgkin-Huxley neuron models using GeNN and evolves them with a simple quided random search (simple GA) to mimic the dynamics of a separate Hodgkin-Huxley neuron that is simulated on the CPU. The parameters of the CPU simulated "true cell" are drifting according to a user-chosen protocol: Either one of the parameters gNa, ENa, gKd, EKd, gleak, Eleak, Cmem are modified by a sinusoidal addition (voltage parameters) or factor (conductance or capacitance) protocol 0-6. For protocol 7 all 7 parameters undergo a random walk concurrently.

```
To compile it, navigate to genn/userproject/HHVclampGA_project and type:
msbuild ..\userproject.sln /t:qenerate_hhvclamp_runner /p:Configuration=Release
for Windows users, or:s
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--protocol: Which changes to apply during the run to the parameters of the "true cell" (defaults to -1 which m
--num-pops: Number of neurons in the tracking population (defaults to 5000)
--total-time: Time in ms how long to run the simulation (defaults to 1000 ms)
```

```
An example invocation of generate_run is:

generate_run.exe test1

for Windows users, or:

./generate_run test1

for Linux, Mac and other UNIX users.

This will simulate 5000 Hodgkin-Huxley neurons on the GPU which will, for 1000 ms, be matched to a Hodgkin-Huxley neuron. The output files will be written into a directory of the name test1_output, which will be created if it does not yet exist.

Another example of an invocation that records timing information for the the simulation and runs it for 10000 generate_run.exe --timing --total-time 10000

for Windows users, or:

./generate_run --timing --total-time 10000

for Linux, Mac and other UNIX users.
```

Traub-Miles Hodgkin-Huxley neuron model: [7]

4.7 A neuromorphic network for generic multivariate data classification

```
Author: Alan Diamond, University of Sussex, 2014
This project recreates using GeNN the spiking classifier design used in the paper
"A neuromorphic network for generic multivariate data classification"
Authors: Michael Schmuker, Thomas Pfeil, Martin Paul Nawrota
The classifier design is based on an abstraction of the insect olfactory system.
This example uses the IRIS stadard data set as a test for the classifier
BUILD / RUN INSTRUCTIONS
Install GeNN from the internet released build, following instruction on setting your PATH etc
Start a terminal session
cd to this project directory (userproject/Model_Schmuker_2014_project)
To build the model using the GENN meta compiler type:
genn-buildmodel.sh Model_Schmuker_2014_classifier.cc
for Linux, Mac and other UNIX systems, or:
genn-buildmodel.bat Model_Schmuker_2014_classifier.cc
for Windows systems (add -d for a debug build).
You should only have to do this at the start, or when you change your actual network model (i.e. editing the
Then to compile the experiment plus the GeNN created C/CUDA code type:-
make
for Linux, Mac and other UNIX users (add DEBUG=1 if using debug mode), or:
msbuild Schmuker2014_classifier.vcxproj /p:Configuration=Release
for Windows users (change Release to Debug if using debug mode).
Once it compiles you should be able to run the classifier against the included Iris dataset.
```

type

```
./experiment .

for Linux, Mac and other UNIX systems, or:

Schmuker2014_classifier .

for Windows systems.

This is how it works roughly.
The experiment (experiment.cu) controls the experiment at a high level. It mostly does this by instructing the So the experiment first tells the classifier to set up the GPU with the model and synapse data.

Then it chooses the training and test set data.

It runs through the training set , with plasticity ON , telling the classifier to run with the specified observations.
```

Then it runs through the test set with plasticity OFF and collects the results in various reporting files.


At the highest level it also has a loop where you can cycle through a list of parameter values e.g. some three You should also note there is no option currently to run on CPU, this is not due to the demanding task, it just

Previous | Top | Next

5 SpineML and SpineCreator

GeNN now supports simulating models built using SpineML and includes scripts to fully integrate it with the SpineCreator graphical editor on Linux, Mac and Windows. After installing GeNN using the instructions in Installation, build SpineCreator for your platform.

From SpineCreator, select Edit->Settings->Simulators and add a new simulator using the following settings (replacing "/home/j/jk/jk421/genn" with the GeNN installation directory on your own system):



If you would like SpineCreator to use GeNN in CPU only mode, add an environment variable called "GENN_SPI↔ NEML_CPU_ONLY".

The best way to get started using SpineML with GeNN is to experiment with some example models. A number are available here although the "Striatal model" uses features not currently supported by GeNN and the two "Brette

Benchmark" models use a legacy syntax no longer supported by SpineCreator (or GeNN). Once you have loaded a model, click "Expts" from the menu on the left hand side of SpineCreator, choose the experiment you would like to run and then select your newly created GeNN simulator in the "Setup Simulator" panel:



Now click "Run experiment" and, after a short time, the results of your GeNN simulation will be available for plotting by clicking the "Graphs" option in the menu on the left hand side of SpineCreator.

Previous | Top | Next

6 Brian interface (Brian2GeNN)

GeNN can simulate models written for the Brian simulator via the Brian2GeNN interface [6]. The easiest way to install everything needed is to install the Anaconda or Miniconda Python distribution and then follow the instructions to install Brian2GeNN with the conda package manager. When Brian2GeNN is installed in this way, it comes with a bundled version of GeNN and no further configuration is required. In all other cases (e.g. an installation from source), the path to GeNN and the CUDA libraries has to be configured via the GECNN_PATH and CUDA_PATH environment variables as described in Installation or via the devices.genn.path and devices.genn.cuda_path Brian preferences.

To use GeNN to simulate a Brian script, import the brian2genn package and switch Brian to the genn device. As an example, the following Python script will simulate Leaky-integrate-and-fire neurons with varying input currents to construct an f/l curve:

Of course, your simulation should be more complex than the example above to actually benefit from the performance gains of using a GPU via GeNN.

Previous | Top | Next

7 Python interface (PyGeNN)

As well as being able to build GeNN models and user code directly from C++, you can also access all GeNN features from Python. The pygenn_genn_model.GeNNModel class provides a thin wrapper around
ModelSpec as well as providing support for loading and running simulations; and accessing their state.
SynapseGroup, NeuronGroup and CurrentSource are similarly wrapped by the pygenn.genngroups.SynapseGroup, pygenn.genn_groups.NeuronGroup and pygenn.genn_groups.
CurrentSource classes respectively.

8 Release Notes 15

PyGeNN can be built from source on Windows, Mac and Linux following the instructions in the README file in the pygenn directory of the GeNN repository. However, if you have a relatively recent version of Python and CUDA, we recommend that you instead downloading a suitable 'wheel' from our releases page (all wheels are build for CUDA 10 except for on Mac OS which is built for CUDA 9). These can then be installed using e.g. pip install pygenn-0.2.1-cp27-cp27mu-linux_x86_64.whl for a Linux system with Python 2.7. On Windows we recommend using the Python 3 version of Anaconda.

The following example shows how PyGeNN can be easily interfaced with standard Python packages such as numpy and matplotlib to plot 4 different Izhikevich neuron regimes:

```
import numpy as np
import matplotlib.pyplot as plt
from pygenn.genn_model import GeNNModel
# Create a single-precision GeNN model
model = GeNNModel("float", "pygenn")
# Set simulation timestep to 0.1ms
model.dT = 0.1
# Initialise IzhikevichVariable parameters - arrays will be automatically uploaded
izk\_init = {"V": -65.0, "U": -20.0,}
                                 0.1, 0.02, 0.02],
0.2, 0.2, 0.2],
-65.0, -50.0, -55.0],
2.0, 2.0, 4.0]}
               "a": [0.02,
              "b": [0.2,
"c": [-65.0, -65.0
2.0,
                              0.2,
# Add neuron populations and current source to model
pop = model.add_neuron_population("Neurons", 4, "IzhikevichVariable", {}, izk_init)
model.add_current_source("CurrentSource", "DC", "Neurons", {"amp": 10.0}, {})
# Build and load model
model.build()
model.load()
# Create a numpy view to efficiently access the membrane voltage from Python
voltage_view = pop.vars["V"].view
# Simulate
v = None
while model.t < 200.0:</pre>
     model.step_time()
    model.pull_state_from_device("Neurons")
        # Create plot
figure, axes = plt.subplots(4, sharex=True)
# Plot voltages
for i, t in enumerate(["RS", "FS", "CH", "IB"]):
     axes[i].set_title(t)
axes[i].set_ylabel("V [mV]")
     axes[i].plot(np.arange(0.0, 200.0, 0.1), v[:,i])
axes[-1].set_xlabel("Time [ms]")
# Show plot
plt.show()
```

Previous | Top | Next

8 Release Notes

Release Notes for GeNN v4.1.0

This release adds a number of new features to GeNN and its SpineML interface as well as fixing a number of bugs that have been identified since the 4.0.2 release.

User Side Changes

1. The SpineML simulator could previously only be used as a standalone application. This functionality is now provided by the spineml_simulator library and can be used via the SpineMLSimulator::Simulator

class.

- 2. When declaring a model's variables using SET_VAR, they can be marked as read-only by adding a 3rd parameter set to VarAccess::READ_ONLY to enable further optimisations. See Defining your own neuron type for more details.
- 3. Previously, unless models were very large or had very high spike rates, using SynapseGroup::
 SpanType::PRESYNAPTIC typically resulted in poor performance. When using the CUDA backend,
 SynapseGroup::setNumThreadsPerSpike can now be used to increase parallelism.
- 4. There were useful helpers for recording spikes (SpikeRecorder) and timing (Timer, Timer Accumulate) in "userproject\include" which were not easily usable to user projects. genn-create-userproject. sh and genn-create-userproject.bat now have a "-u" option which puts this in the include path of the generated project.
- 5. Timing information generated when ModelSpec::setTiming is enabled was not accesible to SpineML models. This is now exposed through the SpineMLSimulator::Simulator class.
- Neuron population state variables were not easily accessible if the populations had incoming or outgoing connections with synaptic delays. Additional helper functions are now generated. See Creating and simulating a network model for more details.
- 7. SpineML interface will now use heterogeneous dendritic delay system introduced in GeNN 3.2.0 if required.
- 8. Add CodeGenerator::CUDA::Preferences::generateLineInfo option to output CUDA line info for profiling.
- 9. CUDA backend supports half datatype allowing memory savings through reduced precision. Host C++ code does not support half-precision types so such state variables must have their location set to Var—Location::DEVICE.
- 10. If ModelSpec::setDefaultNarrowSparseIndEnabled is set on a model or SynapseGroup← ::setNarrowSparseIndEnabled is set on an individual synapse population with sparse connectivity, 16-bit numbers will be used for postsynaptic indices, almost halving memory requirements.
- 11. Manual selection of CUDA devices is now exposed to PyGeNN via the pygenn.genn_model.GeNN← Model.selected_gpu property.

Bug fixes:

- 1. Fixed incomaptibilies with GCC 4.9
- 2. Fixed bug that occured if derived parameters were used in spike-like-event threshold conditions.
- 3. Fixed bug that occured when merging of postsynaptic models is enabled and GeNN decides to employ specific CUDA optimizations.
- 4. Increase maximum supported CUDA kernel grid size a bug was limiting this to 65536.
- 5. Fixed bugs in timing system when used with synapse dynamics kernels.

Release Notes for GeNN v4.0.2

This release fixes several small issues with the generation of binary wheels for Python:

Bug fixes:

- 1. There was a conflict between the versions of numpy used to build the wheels and the version required for the PyGeNN packages
- 2. Wheels were renamed to include the CUDA version which broke them.

8 Release Notes 17

Release Notes for GeNN v4.0.1

This release fixes several small bugs found in GeNN 4.0.0 and implements some small features:

User Side Changes

- 1. Improved detection and handling of errors when specifying model parameters and values in PyGeNN.
- 2. SpineML simulator is now implemented as a library which can be used directly from user applications as well as from command line tool.

Bug fixes:

- 1. Fixed typo in pygenn.genn_model.GennModel.push_var_to_device function in PyGeNN.
- 2. Fixed broken support for Visual C++ 2013.
- 3. Fixed zero-copy mode.
- 4. Fixed typo in tutorial 2.

Release Notes for GeNN v4.0.0

This release is the result of a second round of fairly major refactoring which we hope will make GeNN easier to use and allow it to be extended more easily in future. However, especially if you have been using GeNN 2.XX syntax, it breaks backward compatibility.

User Side Changes

- 1. Totally new build system make install can be used to install GeNN to a system location on Linux and Mac and Windows projects work much better in the Visual Studio IDE.
- 2. Python interface now supports Windows and can be installed using binary 'wheels' (see Python interface (PyGeNN) for more details).
- 3. No need to call initGeNN() at start and model.finalize() at end of all models.
- 4. Initialisation system simplified if you specify a value or initialiser for a variable or sparse connectivity, it will be initialised by your chosen backend. If you mark it as uninitialised, it is up to you to initialize it in user code between the calls to initialize() and initializeSparse() (where it will be copied to device).
- 5. genn-create-user-project helper scripts to create Makefiles or MSBuild projects for building user code
- 6. State variables can now be pushed and pulled individually using the pull<var name><neuron or synapse name>FromDevice() and push<var name><neuron or synapse name>To← Device() functions.
- 7. Management of extra global parameter arrays has been somewhat automated (see Extra Global Parameters for more details).
- 8. GENN_PREFERENCES is no longer a namespace it's a global struct so members need to be accessed with . rather than ::.
- 9. NeuronGroup, SynapseGroup, CurrentSource and NNmodel all previously exposed a lot of methods that the user wasn't *supposed* to call but could. These have now all been made protected and are exposed to GeNN internals using derived classes (NeuronGroupInternal, SynapseGroupInternal, CurrentSourceInternal, ModelSpecInternal) that make them public using using directives.

- 10. Auto-refractory behaviour was controlled using GENN_PREFERENCES::autoRefractory, this is now controlled on a per-neuron-model basis using the SET_NEEDS_AUTO_REFRACTORY macro.
- 11. The functions used for pushing and pulling have been unified somewhat this means that copyState←
 ToDevice and copyStateFromDevice functions no longer copy spikes and pus<neuron or
 synapse name>SpikesToDevice and pull<neuron or synapse name>SpikesFrom←
 Device no longer copy spike times or spike-like events.
- 12. Standard models of leaky-integrate-and-fire neuron (NeuronModels::LIF) and of exponentially shaped postsynaptic current (PostsynapticModels::ExpCurr) have been added.
- 13. When a model is built using the CUDA backend, the device it was built for is stored using it's PCI bus ID so it will always use the same device.

Deprecations

- 1. Yale-format sparse matrices are no longer supported.
- 2. GeNN 2.X syntax for implementing neuron and synapse models is no longer supported.
- 3. \$(addtoinSyn) = X; \$(updatelinsyn); idiom in weight update models has been replaced by function style
 \$ (addToInSyn, X);.

Release Notes for GeNN v3.3.0

This release is intended as the last service release for GeNN 3.X.X. Fixes for serious bugs **may** be backported if requested but, otherwise, development will be switching to GeNN 4.

User Side Changes

- 1. Postsynaptic models can now have Extra Global Parameters.
- 2. Gamma distribution can now be sampled using \$ (gennrand_gamma, a). This can be used to initialise variables using InitVarSnippet::Gamma.
- 3. Experimental Python interface All features of GeNN are now exposed to Python through the pygenn module (see Python interface (PyGeNN) for more details).

Bug fixes:

- 1. Devices with Streaming Multiprocessor version 2.1 (compute capability 2.0) now work correctly in Windows.
- 2. Seeding of on-device RNGs now works correctly.
- 3. Improvements to accuracy of memory usage estimates provided by code generator.

Release Notes for GeNN v3.2.0

This release extends the initialisation system introduced in 3.1.0 to support the initialisation of sparse synaptic connectivity, adds support for networks with more sophisticated models of synaptic plasticity and delay as well as including several other small features, optimisations and bug fixes for certain system configurations. This release supports $GCC \ge 4.9.1$ on Linux, Visual Studio ≥ 2013 on Windows and recent versions of Clang on Mac OS X.

8 Release Notes 19

User Side Changes

Sparse synaptic connectivity can now be initialised using small snippets of code run either on GPU or CPU.
 This can save significant amounts of initialisation time for large models. See Sparse connectivity initialisation for more details.

- New 'ragged matrix' data structure for representing sparse synaptic connections supports initialisation using
 new sparse synaptic connectivity initialisation system and enables future optimisations. See Synaptic matrix
 types for more details.
- 3. Added support for pre and postsynaptic state variables for weight update models to allow more efficient implementatation of trace based STDP rules. See Defining a new weight update model for more details.
- 4. Added support for devices with Compute Capability 7.0 (Volta) to block-size optimizer.
- 5. Added support for a new class of 'current source' model which allows non-synaptic input to be efficiently injected into neurons. See Current source models for more details.
- 6. Added support for heterogeneous dendritic delays. See Defining a new weight update model for more details.
- 7. Added support for (homogeneous) synaptic back propagation delays using SynapseGroup::setBack← PropDelaySteps.
- 8. For long simulations, using single precision to represent simulation time does not work well. Added N← Nmodel::setTimePrecision to allow data type used to represent time to be set independently.

Optimisations

- GENN_PREFERENCES::mergePostsynapticModels flag can be used to enable the merging together of postsynaptic models from a neuron population's incoming synapse populations - improves performance and saves memory.
- 2. On devices with compute capability > 3.5 GeNN now uses the read only cache to improve performance of postsynaptic learning kernel.

Bug fixes:

- 1. Fixed bug enabling support for CUDA 9.1 and 9.2 on Windows.
- 2. Fixed bug in SynDelay example where membrane voltage went to NaN.
- 3. Fixed bug in code generation of SCALAR_MIN and SCALAR_MAX values.
- 4. Fixed bug in substitution of trancendental functions with single-precision variants.
- 5. Fixed various issues involving using spike times with delayed synapse projections.

Release Notes for GeNN v3.1.1

This release fixes several small bugs found in GeNN 3.1.0 and implements some small features:

User Side Changes

1. Added new synapse matrix types SPARSE_GLOBALG_INDIVIDUAL_PSM, DENSE_GLOBALG_IND IVIDUAL_PSM and BITMASK_GLOBALG_INDIVIDUAL_PSM to handle case where synapses with no individual state have a postsynaptic model with state variables e.g. an alpha synapse. See Synaptic matrix types for more details.

Bug fixes

- 1. Correctly handle aliases which refer to other aliases in SpineML models.
- 2. Fixed issues with presynaptically parallelised synapse populations where the postsynaptic population is small enough for input to be accumulated in shared memory.

Release Notes for GeNN v3.1.0

This release builds on the changes made in 3.0.0 to further streamline the process of building models with GeNN and includes several bug fixes for certain system configurations.

User Side Changes

- Support for simulating models described using the SpineML model description language with GeNN (see SpineML and SpineCreator for more details).
- 2. Neuron models can now sample from uniform, normal, exponential or log-normal distributions these calls are translated to cuRAND when run on GPUs and calls to the C++11 < random > library when run on CPU. See Defining your own neuron type for more details.
- 3. Model state variables can now be initialised using small *snippets* of code run either on GPU or CPU. This can save significant amounts of initialisation time for large models. See Defining a new variable initialisation snippet for more details.
- 4. New MSBuild build system for Windows makes developing user code from within Visual Studio much more streamlined. See Debugging suggestions for more details.

Bug fixes:

- 1. Workaround for bug found in Glibc 2.23 and 2.24 which causes poor performance on some 64-bit Linux systems (namely on Ubuntu 16.04 LTS).
- 2. Fixed bug encountered when using extra global variables in weight updates.

Release Notes for GeNN v3.0.0

This release is the result of some fairly major refactoring of GeNN which we hope will make it more user-friendly and maintainable in the future.

User Side Changes

- 1. Entirely new syntax for defining models hopefully terser and less error-prone (see updated documentation and examples for details).
- 2. Continuous integration testing using Jenkins automated testing and code coverage calculation calculated automatically for Github pull requests etc.
- 3. Support for using Zero-copy memory for model variables. Especially on devices such as NVIDIA Jetson TX1 with no physical GPU memory this can significantly improve performance when recording data or injecting it to the simulation from external sensors.

Release Notes for GeNN v2.2.3

This release includes minor new features and several bug fixes for certain system configurations.

8 Release Notes 21

User Side Changes

- 1. Transitioned feature tests to use Google Test framework.
- 2. Added support for CUDA shader model 6.X

Bug fixes:

- 1. Fixed problem using GeNN on systems running 32-bit Linux kernels on a 64-bit architecture (Nvidia Jetson modules running old software for example).
- 2. Fixed problem linking against CUDA on Mac OS X El Capitan due to SIP (System Integrity Protection).
- 3. Fixed problems with support code relating to its scope and usage in spike-like event threshold code.
- 4. Disabled use of C++ regular expressions on older versions of GCC.

Release Notes for GeNN v2.2.2

This release includes minor new features and several bug fixes for certain system configurations.

User Side Changes

- 1. Added support for the new version (2.0) of the Brian simulation package for Python.
- 2. Added a mechanism for setting user-defined flags for the C++ compiler and NVCC compiler, via GENN_PR← EFERENCES.

Bug fixes:

- 1. Fixed a problem with atomicAdd() redefinitions on certain CUDA runtime versions and GPU configurations
- 2. Fixed an incorrect bracket placement bug in code generation for certain models.
- 3. Fixed an incorrect neuron group indexing bug in the learning kernel, for certain models.
- 4. The dry-run compile phase now stores temporary files in the current directory, rather than the temp directory, solving issues on some systems.
- 5. The LINK_FLAGS and INCLUDE_FLAGS in the common windows makefile include 'makefile_commin
 win.mk' are now appended to, rather than being overwritten, fixing issues with custom user makefiles on
 Windows.

Release Notes for GeNN v2.2.1

This bugfix release fixes some critical bugs which occur on certain system configurations.

Bug fixes:

- 1. (important) Fixed a Windows-specific bug where the CL compiler terminates, incorrectly reporting that the nested scope limit has been exceeded, when a large number of device variables need to be initialised.
- 2. (important) Fixed a bug where, in certain circumstances, outdated generateALL objects are used by the Makefiles, rather than being cleaned and replaced by up-to-date ones.
- (important) Fixed an 'atomicAdd' redeclared or missing bug, which happens on certain CUDA architectures when using the newest CUDA 8.0 RC toolkit.

4. (minor) The SynDelay example project now correctly reports spike indexes for the input group.

Please refer to the full documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.2

This release includes minor new features, some core code improvements and several bug fixes on GeNN v2.1.

User Side Changes

1. GeNN now analyses automatically which parameters each kernel needs access to and these and only these are passed in the kernel argument list in addition to the global time t. These parameters can be a combination of extraGlobalNeuronKernelParameters and extraGlobalSynapseKernelParameters in either neuron or synapse kernel. In the unlikely case that users wish to call kernels directly, the correct call can be found in the stepTimeGPU() function.

Reflecting these changes, the predefined Poisson neurons now simply have two extraGlobalNeuron \leftarrow Parameter rates and offset which replace the previous custom pointer to the array of input rates and integer offset to indicate the current input pattern. These extraGlobalNeuronKernelParameters are passed to the neuron kernel automatically, but the rates themselves within the array are of course not updated automatically (this is exactly as before with the specifically generated kernel arguments for Poisson neurons).

The concept of "directInput" has been removed. Users can easily achieve the same functionality by adding an additional variable (if there are individual inputs to neurons), an extraGlobalNeuronParameter (if the input is homogeneous but time dependent) or, obviously, a simple parameter if it's homogeneous and constant.

Note

The global time variable "t" is now provided by GeNN; please make sure that you are not duplicating its definition or shadowing it. This could have severe consequences for simulation correctness (e.g. time not advancing in cases of over-shadowing).

- 2. We introduced the namespace GENN_PREFERENCES which contains variables that determine the behaviour of GeNN.
- 3. We introduced a new code snippet called "supportCode" for neuron models, weightupdate models and post-synaptic models. This code snippet is intended to contain user-defined functions that are used from the other code snippets. We advise where possible to define the support code functions with the CUDA keywords "__ host__ __device__" so that they are available for both GPU and CPU version. Alternatively one can define separate versions for **host** and **device** in the snippet. The snippets are automatically made available to the relevant code parts. This is regulated through namespaces so that name clashes between different models do not matter. An exception are hash defines. They can in principle be used in the supportCode snippet but need to be protected specifically using ifndef. For example

```
#ifndef clip(x)
#define clip(x) x > 10.0? 10.0 : x
#endif
```

Note

If there are conflicting definitions for hash defines, the one that appears first in the GeNN generated code will then prevail.

- 4. The new convenience macros spikeCount_XX and spike_XX where "XX" is the name of the neuron group are now also available for events: spikeEventCount_XX and spikeEvent_XX. They access the values for the current time step even if there are synaptic delays and spikes events are stored in circular queues.
- 5. The old buildmodel.[sh|bat] scripts have been superseded by new genn-buildmodel.[sh|bat] scripts. These scripts accept UNIX style option switches, allow both relative and absolute model file paths, and allow the user to specify the directory in which all output files are placed (-o <path>). Debug (-d), CPU-only (-c) and show help (-h) are also defined.

8 Release Notes 23

6. We have introduced a CPU-only "-c" genn-buildmodel switch, which, if it's defined, will generate a GeNN version that is completely independent from CUDA and hence can be used on computers without CUDA installation or CUDA enabled hardware. Obviously, this then can also only run on CPU. CPU only mode can either be switched on by defining CPU_ONLY in the model description file or by passing appropriate parameters during the build, in particular

```
genn-buildmodel.[sh|bat] \<modelfile\> -c
make release CPU ONLY=1
```

- 7. The new genn-buildmodel "-o" switch allows the user to specify the output directory for all generated files the default is the current directory. For example, a user project could be in '/home/genn_project', whilst the GeNN directory could be '/usr/local/genn'. The GeNN directory is kept clean, unless the user decides to build the sample projects inside of it without copying them elsewhere. This allows the deployment of GeNN to a read-only directory, like '/usr/local' or 'C:\Program Files'. It also allows multiple users i.e. on a compute cluster to use GeNN simultaneously, without overwriting each other's code-generation files, etcetera.
- 8. The ARM architecture is now supported e.g. the NVIDIA Jetson development platform.
- 9. The NVIDIA CUDA SM_5* (Maxwell) architecture is now supported.
- 10. An error is now thrown when the user tries to use double precision floating-point numbers on devices with architecture older than SM 13, since these devices do not support double precision.
- 11. All GeNN helper functions and classes, such as toString() and NNmodel, are defined in the header files at genn/lib/include/, for example stringUtils.h and modelSpec.h, which should be individually included before the functions and classes may be used. The functions and classes are actually implementated in the static library genn\lib\lib\genn.lib\(Windows)\) or genn/lib/lib/libgenn.a (Mac, Linux), which must be linked into the final executable if any GeNN functions or classes are used.
- 12. In the modelDefinition() file, only the header file modelSpec.h should be included i.e. not the source file modelSpec.cc. This is because the declaration and definition of NNmodel, and associated functions, has been separated into modelSpec.h and modelSpec.cc, respectively. This is to enable NNmodel code to be precompiled separately. Henceforth, only the header file modelSpec.h should be included in model definition files!
- 13. In the modelDefinition() file, DT is now preferrably defined using model.setDT(<val>);, rather than #defineDT(<val>), in order to prevent problems with DT macro redefinition. For backward-compatibility reasons, the old #defineDT(<val>) method may still be used, however users are advised to adopt the new method.
- 14. In preparation for multi-GPU support in GeNN, we have separated out the compilation of generated code from user-side code. This will eventually allow us to optimise and compile different parts of the model with different CUDA flags, depending on the CUDA device chosen to execute that particular part of the model. As such, we have had to use a header file definitions.h as the generated code interface, rather than the runner.cc file. In practice, this means that user-side code should include myModel_COD← E/definitions.h, rather than myModel_CODE/runner.cc. Including runner.cc will likely result in pages of linking errors at best!

Developer Side Changes

- Blocksize optimization and device choice now obtain the ptxas information on memory usage from a CUDA driver API call rather than from parsing ptxas output of the nvcc compiler. This adds robustness to any change in the syntax of the compiler output.
- 2. The information about device choice is now stored in variables in the namespace GENN_PREFERENCES. This includes chooseDevice, optimiseBlockSize, optimizeCode, debugCode, showPtxcInfo, defaultDevice. asGoodAsZero has also been moved into this namespace.
- 3. We have also introduced the namespace GENN_FLAGS that contains unsigned int variables that attach names to numeric flags that can be used within GeNN.

- 4. The definitions of all generated variables and functions such as pullXXXStateFromDevice etc, are now generated into definitions.h. This is useful where one wants to compile separate object files that cannot all include the full definitions in e.g. "runnerGPU.cc". One example where this is useful is the brian2genn interface.
- 5. A number of feature tests have been added that can be found in the featureTests directory. They can be run with the respective runTests.sh scripts. The cleanTests.sh scripts can be used to remove all generated code after testing.

Improvements

- 1. Improved method of obtaining ptxas compiler information on register and shared memory usage and an improved algorithm for estimating shared memory usage requirements for different block sizes.
- 2. Replaced pageable CPU-side memory with page-locked memory. This can significantly speed up simulations in which a lot of data is regularly copied to and from a CUDA device.
- 3. GeNN library objects and the main generateALL binary objects are now compiled separately, and only when a change has been made to an object's source, rather than recompiling all software for a minor change in a single source file. This should speed up compilation in some instances.

Bug fixes:

- 1. Fixed a minor bug with delayed synapses, where delaySlot is declared but not referenced.
- 2. We fixed a bug where on rare occasions a synchronisation problem occurred in sparse synapse populations.
- 3. We fixed a bug where the combined spike event condition from several synapse populations was not assembled correctly in the code generation phase (the parameter values of the first synapse population over-rode the values of all other populations in the combined condition).

Please refer to the $\verb|full|$ documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.1

This release includes some new features and several bug fixes on GeNN v2.0.

User Side Changes

- 1. Block size debugging flag and the asGoodAsZero variables are moved into include/global.h.
- 2. NGRADSYNAPSES dynamics have changed (See Bug fix #4) and this change is applied to the example projects. If you are using this synapse model, you may want to consider changing model parameters.
- 3. The delay slots are now such that NO_DELAY is 0 delay slots (previously 1) and 1 means an actual delay of 1 time step.
- 4. The convenience function convertProbabilityToRandomNumberThreshold(float *, uint64_t *, int) was changed so that it actually converts firing probability/timestep into a threshold value for the GeNN random number generator (as its name always suggested). The previous functionality of converting a *rate* in kHz into a firing threshold number for the GeNN random number generator is now provided with the name convertRateToRandomNumberThreshold(float *, uint64_t *, int)
- 5. Every model definition function modelDefinition() now needs to end with calling NNmodel←::finalize() for the defined network model. This will lock down the model and prevent any further changes to it by the supported methods. It also triggers necessary analysis of the model structure that should only be performed once. If the finalize() function is not called, GeNN will issue an error and exit before code generation.

8 Release Notes 25

6. To be more consistent in function naming the pull\<SYNAPSENAME\>FromDevice and push\<S\U0044 YNAPSENAME\>ToDevice have been renamed to pull\<SYNAPSENAME\>StateFromDevice and push\<SYNAPSENAME\>StateToDevice. The old versions are still supported through macro definitions to make the transition easier.

- 7. New convenience macros are now provided to access the current spike numbers and identities of neurons that spiked. These are called spikeCount_XX and spike_XX where "XX" is the name of the neuron group. They access the values for the current time step even if there are synaptic delays and spikes are stored in circular queues.
- 8. There is now a pre-defined neuron type "SPIKECOURCE" which is empty and can be used to define PyNN style spike source arrays.
- 9. The macros FLOAT and DOUBLE were replaced with GENN_FLOAT and GENN_DOUBLE due to name clashes with typedefs in Windows that define FLOAT and DOUBLE.

Developer Side Changes

1. We introduced a file definitions.h, which is generated and filled with useful macros such as spkQuePtrShift which tells users where in the circular spike queue their spikes start.

Improvements

- 1. Improved debugging information for block size optimisation and device choice.
- 2. Changed the device selection logic so that device occupancy has larger priority than device capability version.
- 3. A new HH model called TRAUBMILES_PSTEP where one can set the number of inner loops as a parameter is introduced. It uses the TRAUBMILES_SAFE method.
- 4. An alternative method is added for the insect olfaction model in order to fix the number of connections to a maximum of 10K in order to avoid negative conductance tails.
- 5. We introduced a preprocessor define directive for an "int_" function that translates floating points to integers.

Bug fixes:

- 1. AtomicAdd replacement for old GPUs were used by mistake if the model runs in double precision.
- 2. Timing of individual kernels is fixed and improved.
- 3. More careful setting of maximum number of connections in sparse connectivity, covering mixed dense/sparse network scenarios.
- 4. NGRADSYNAPSES was not scaling correctly with varying time step.
- 5. Fixed a bug where learning kernel with sparse connectivity was going out of range in an array.
- 6. Fixed synapse kernel name substitutions where the "dd" prefix was omitted by mistake.

Please refer to the full documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.0

Version 2.0 of GeNN comes with a lot of improvements and added features, some of which have necessitated some changes to the structure of parameter arrays among others.

User Side Changes

- 1. Users are now required to call initGeNN () in the model definition function before adding any populations to the neuronal network model.
- 2. glbscnt is now call glbSpkCnt for consistency with glbSpkEvntCnt.
- 3. There is no longer a privileged parameter Epre. Spike type events are now defined by a code string spk EvntThreshold, the same way proper spikes are. The only difference is that Spike type events are specific to a synapse type rather than a neuron type.
- 4. The function setSynapseG has been deprecated. In a GLOBALG scenario, the variables of a synapse group are set to the initial values provided in the modeldefinition function.
- 5. Due to the split of synaptic models into weightUpdateModel and postSynModel, the parameter arrays used during model definition need to be carefully split as well so that each side gets the right parameters. For example, previously

would define the parameter array of three parameters, Erev, Epre, and tau_S for a synapse of type NSYNAPSE. This now needs to be "split" into

i.e. parameters <code>Erev</code> and <code>tau_S</code> are moved to the post-synaptic model and its parameter array of two parameters. <code>Epre</code> is discontinued as a parameter for <code>NSYNAPSE</code>. As a consequence the weightupdate model of <code>NSYNAPSE</code> has no parameters and one can pass <code>NULL</code> for the parameter array in <code>addSynapse</code> <code>Population</code>. The correct parameter lists for all defined neuron and synapse model types are listed in the <code>User Manual</code>.

Note

If the parameters are not redefined appropriately this will lead to uncontrolled behaviour of models and likely to segmentation faults and crashes.

- 6. Advanced users can now define variables as type scalar when introducing new neuron or synapse types. This will at the code generation stage be translated to the model's floating point type (ftype), float or double. This works for defining variables as well as in all code snippets. Users can also use the expressions SCALAR_MAX and SCALAR_MIN for FLT_MIN, FLT_MAX, DBL_MIN and DBL_MAX, respectively. Corresponding definitions of scalar, SCALAR_MIN and SCALAR_MAX are also available for user-side code whenever the code-generated file runner.cc has been included.
- 7. The example projects have been re-organized so that wrapper scripts of the <code>generate_run</code> type are now all located together with the models they run instead of in a common <code>tools</code> directory. Generally the structure now is that each example project contains the wrapper script <code>generate_run</code> and a <code>model</code> subdirectory which contains the model description file and the user side code complete with Makefiles for Unix and Windows operating systems. The generated code will be deposited in the <code>model</code> subdirectory in its <code>own modelname_CODE</code> folder. Simulation results will always be deposited in a new sub-folder of the main project directory.
- 8. The addSynapsePopulation (...) function has now more mandatory parameters relating to the introduction of separate weightupdate models (pre-synaptic models) and postynaptic models. The correct syntax for the addSynapsePopulation (...) can be found with detailed explanations in teh User Manual.
- We have introduced a simple performance profiling method that users can employ to get an overview over the differential use of time by different kernels. To enable the timers in GeNN generated code, one needs to declare

9 User Manual 27

```
networkmodel.setTiming(TRUE);
```

This will make available and operate GPU-side cudeEvent based timers whose cumulative value can be found in the double precision variables <code>neuron_tme</code>, <code>synapse_tme</code> and <code>learning_tme</code>. They measure the accumulated time that has been spent calculating the neuron kernel, synapse kernel and learning kernel, respectively. CPU-side timers for the simulation functions are also available and their cumulative values can be obtained through

```
float x= sdkGetTimerValue(&neuron_timer);
float y= sdkGetTimerValue(&synapse_timer);
float z= sdkGetTimerValue(&learning_timer);
```

The Insect olfaction model example shows how these can be used in the user-side code. To enable timing profiling in this example, simply enable it for GeNN:

```
model.setTiming(TRUE);
```

in MBody1.cc's modelDefinition function and define the macro TIMING in classol_sim.h

```
#define TIMING
```

This will have the effect that timing information is output into $OUTNAME_output/OUTNAME.$ timingprofile.

Developer Side Changes

- 1. allocateSparseArrays() has been changed to take the number of connections, connN, as an argument rather than expecting it to have been set in the Connetion struct before the function is called as was the arrangement previously.
- 2. For the case of sparse connectivity, there is now a reverse mapping implemented with revers index arrays and a remap array that points to the original positions of variable values in teh forward array. By this mechanism, revers lookups from post to pre synaptic indices are possible but value changes in the sparse array values do only need to be done once.
- 3. SpkEvnt code is no longer generated whenever it is not actually used. That is also true on a somewhat finer granularity where variable queues for synapse delays are only maintained if the corresponding variables are used in synaptic code. True spikes on the other hand are always detected in case the user is interested in them.

Please refer to the full documentation for further details, tutorials and complete code documentation.

```
Previous | Top | Next
```

9 User Manual

9.1 Contents

- Introduction
- · Defining a network model
- · Neuron models
- · Weight update models

- · Postsynaptic integration methods
- · Current source models
- · Synaptic matrix types
- · Variable initialisation
- · Sparse connectivity initialisation

9.2 Introduction

GeNN is a software library for facilitating the simulation of neuronal network models on NVIDIA CUDA enabled GPU hardware. It was designed with computational neuroscience models in mind rather than artificial neural networks. The main philosophy of GeNN is two-fold:

- GeNN relies heavily on code generation to make it very flexible and to allow adjusting simulation code to the model of interest and the GPU hardware that is detected at compile time.
- 2. GeNN is lightweight in that it provides code for running models of neuronal networks on GPU hardware but it leaves it to the user to write a final simulation engine. It so allows maximal flexibility to the user who can use any of the provided code but can fully choose, inspect, extend or otherwise modify the generated code. They can also introduce their own optimisations and in particular control the data flow from and to the GPU in any desired granularity.

This manual gives an overview of how to use GeNN for a novice user and tries to lead the user to more expert use later on. With that we jump right in.

Previous | Top | Next

9.3 Defining a network model

A network model is defined by the user by providing the function

```
void modelDefinition(ModelSpec &model)
```

in a separate file, such as MyModel.cc. In this function, the following tasks must be completed:

1. The name of the model must be defined:

```
model.setName("MyModel");
```

- 2. Neuron populations (at least one) must be added (see Defining neuron populations). The user may add as many neuron populations as they wish. If resources run out, there will not be a warning but GeNN will fail. However, before this breaking point is reached, GeNN will make all necessary efforts in terms of block size optimisation to accommodate the defined models. All populations must have a unique name.
- 3. Synapse populations (zero or more) can be added (see Defining synapse populations). Again, the number of synaptic connection populations is unlimited other than by resources.

9.3.1 Defining neuron populations

Neuron populations are added using the function

```
model.addNeuronPopulation<NeuronModel>(name, num, paramValues, varInitialisers);
```

where the arguments are:

- NeuronModel: Template argument specifying the type of neuron model These should be derived off NeuronModels::Base and can either be one of the standard models or user-defined (see Neuron models).
- const string &name: Unique name of the neuron population
- \bullet unsigned int size: number of neurons in the population
- NeuronModel::ParamValues paramValues: Parameters of this neuron type
- NeuronModel::VarValues varInitialisers: Initial values or initialisation snippets for variables
 of this neuron type

The user may add as many neuron populations as the model necessitates. They must all have unique names. The possible values for the arguments, predefined models and their parameters and initial values are detailed Neuron models below.

9.3.2 Defining synapse populations

Synapse populations are added with the function

where the arguments are

- WeightUpdateModel: Template parameter specifying the type of weight update model. These should be derived off WeightUpdateModels::Base and can either be one of the standard models or user-defined (see Weight update models).
- PostsynapticModel: Template parameter specifying the type of postsynaptic integration model. These should be derived off PostsynapticModels::Base and can either be one of the standard models or user-defined (see Postsynaptic integration methods).
- const string &name: The name of the synapse population
- unsigned int mType: How the synaptic matrix is stored. See Synaptic matrix types for available options.
- unsigned int delay: Homogeneous (axonal) delay for synapse population (in terms of the simulation time step DT).
- const string preName: Name of the (existing!) pre-synaptic neuron population.
- const string postName: Name of the (existing!) post-synaptic neuron population.
- WeightUpdateModel::ParamValues weightParamValues: The parameter values (common to all synapses of the population) for the weight update model.
- WeightUpdateModel::VarValues weightVarInitialisers: Initial values or initialisation snippets for the weight update model's state variables
- WeightUpdateModel::PreVarValues weightPreVarInitialisers: Initial values or initialisation snippets for the weight update model's presynaptic state variables
- WeightUpdateModel::PostVarValues weightPostVarInitialisers: Initial values or initialisation snippets for the weight update model's postsynaptic state variables
- PostsynapticModel::ParamValues postsynapticParamValues: The parameter values (common to all postsynaptic neurons) for the postsynaptic model.

- PostsynapticModel::VarValues postsynapticVarInitialisers: Initial values or initialisation snippets for variables for the postsynaptic model's state variables
- InitSparseConnectivitySnippet::Init connectivityInitialiser: Optional argument, specifying the initialisation snippet for synapse population's sparse connectivity (see Sparse connectivity initialisation).

The ModelSpec::addSynapsePopulation() function returns a pointer to the newly created SynapseGroup object which can be further configured, namely with:

SynapseGroup::setMaxConnections() and SynapseGroup::setMaxSourceConnections() to configure the
maximum number of rows and columns respectively allowed in the synaptic matrix - this can improve performance and reduce memory usage when using SynapseMatrixConnectivity::SPARSE connectivity (see
Synaptic matrix types).

Note

When using a sparse connectivity initialisation snippet, these values are set automatically.

- SynapseGroup::setMaxDendriticDelayTimesteps() sets the maximum dendritic delay (in terms of the simulation time step DT) allowed for synapses in this population. No values larger than this should be passed to the delay parameter of the addToDenDelay function in user code (see Defining a new weight update model).
- SynapseGroup::setSpanType() sets how incoming spike processing is parallelised for this synapse group. The default SynapseGroup::SpanType::POSTSYNAPTIC is nearly always the best option, but SynapseGroup::SpanType::PRESYNAPTIC may perform better when there are large numbers of spikes every timestep or very few postsynaptic neurons.

Note

If the synapse matrix uses one of the "GLOBALG" types then the global value of the synapse parameters are taken from the initial value provided in weightVarInitialisers therefore these must be constant rather than sampled from a distribution etc.

Previous | Top | Next

9.4 Neuron models

There is a number of predefined models which can be used with the ModelSpec::addNeuronGroup function:

- NeuronModels::RulkovMap
- NeuronModels::Izhikevich
- NeuronModels::IzhikevichVariable
- · NeuronModels::LIF
- NeuronModels::SpikeSource
- NeuronModels::PoissonNew
- NeuronModels::TraubMiles
- NeuronModels::TraubMilesFast
- NeuronModels::TraubMilesAlt
- NeuronModels::TraubMilesNStep

9.4 Neuron models 31

9.4.1 Defining your own neuron type

In order to define a new neuron type for use in a GeNN application, it is necessary to define a new class derived from NeuronModels::Base. For convenience the methods this class should implement can be implemented using macros:

- DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS): declared the boilerplate code required for the model e.g. the correct specialisations of NewModels::ValueBase used to wrap the neuron model parameters and values.
- SET_SIM_CODE(SIM_CODE): where SIM_CODE contains the code for executing the integration of the
 model for one time stepWithin this code string, variables need to be referred to by \$(NAME), where NA

 ME is the name of the variable as defined in the vector varNames. The code may refer to the predefined
 primitives DT for the time step size and for the total incoming synaptic current. It can also refer to a unique
 ID (within the population) using .
- SET_THRESHOLD_CONDITION_CODE(THRESHOLD_CONDITION_CODE) defines the condition for true spike detection.
- SET_PARAM_NAMES() defines the names of the model parameters. If defined as NAME here, they can then
 be referenced as \$(NAME) in the code string. The length of this list should match the NUM_PARAM specified
 in DECLARE_MODEL. Parameters are assumed to be always of type double.
- SET_VARS() defines the names, type strings (e.g. "float", "double", etc) and (optionally) access mode of the neuron state variables. The type string "scalar" can be used for variables which should be implemented using the precision set globally for the model with ModelSpec::setPrecision. The variables defined here as NAME can then be used in the syntax \$(NAME) in the code string. If the access mode is set to VarAccess::ReelD_ONLY, GeNN applies additional optimisations and models should not write to it.
- SET_NEEDS_AUTO_REFRACTORY() defines whether the neuron should include an automatic refractory
 period to prevent it emitting spikes in successive timesteps.

For example, using these macros, we can define a leaky integrator $au rac{dV}{dt} = -V + I_{
m syn}$ solved using Euler's method:

```
class LeakyIntegrator : public NeuronModels::Base
{
public:
    DECLARE_MODEL(LeakyIntegrator, 1, 1);

    SET_SIM_CODE("$(V) += (-$(V) +$(Isyn)) *(DT/$(tau));");

    SET_THRESHOLD_CONDITION_CODE("$(V) >= 1.0");

    SET_PARAM_NAMES({"tau"});

    SET_VARS({{"V", "scalar", VarAccess::READ_WRITE}});
};
```

Additionally "dependent parameters" can be defined. Dependent parameters are a mechanism for enhanced efficiency when running neuron models. If parameters with model-side meaning, such as time constants or conductances always appear in a certain combination in the model, then it is more efficient to pre-compute this combination and define it as a dependent parameter.

For example, because the equation defining the previous leaky integrator example has an algebraic solution, it can be more accurately solved as follows - using a derived parameter to calculate $\exp\left(\frac{-t}{\tau}\right)$:

```
class LeakyIntegrator2 : public NeuronModels::Base
{
public:
    DECLARE_MODEL(LeakyIntegrator2, 1, 1);

SET_SIM_CODE("$(V) = $(Isyn) - $(ExpTC)*($(Isyn) - $(V));");

SET_THRESHOLD_CONDITION_CODE("$(V) >= 1.0");

SET_PARAM_NAMES({"tau"});
```

GeNN provides several additional features that might be useful when defining more complex neuron models.

9.4.1.1 Support code

Support code enables a code block to be defined that contains supporting code that will be utilized in multiple pieces of user code. Typically, these are functions that are needed in the sim code or threshold condition code. If possible, these should be defined as __host__ __device__ functions so that both GPU and CPU versions of GeNN code have an appropriate support code function available. The support code is protected with a namespace so that it is exclusively available for the neuron population whose neurons define it. Support code is added to a model using the SET_SUPPORT_CODE() macro, for example:

```
SET_SUPPORT_CODE("__device__ __host__ scalar mysin(float x){ return sin(x); }");
```

9.4.1.2 Extra global parameters

Extra global parameters are parameters common to all neurons in the population. However, unlike the standard neuron parameters, they can be varied at runtime meaning they could, for example, be used to provide a global reward signal. These parameters are defined by using the SET_EXTRA_GLOBAL_PARAMS() macro to specify a list of variable names and type strings (like the SET_VARS() macro). For example:

```
SET_EXTRA_GLOBAL_PARAMS({{"R", "float"}});
```

These variables are available to all neurons in the population. They can also be used in synaptic code snippets; in this case it need to be addressed with a _pre or _post postfix.

For example, if the model with the "R" parameter was used for the pre-synaptic neuron population, the weight update model of a synapse population could have simulation code like:

```
\label{eq:set_sim_code} \begin{split} \mathtt{SET\_SIM\_CODE}\,(\,\mathtt{"}\,\$\,\,(\mathtt{x}) = \,\,\$\,\,(\mathtt{x})\,+\$\,\,(\mathtt{R\_pre})\,\,;\,\mathtt{"}\,)\,\,; \end{split}
```

where we have assumed that the weight update model has a variable x and our synapse type will only be used in conjunction with pre-synaptic neuron populations that do have the extra global parameter R. If the pre-synaptic population does not have the required variable/parameter, GeNN will fail when compiling the kernels.

9.4.1.3 Additional input variables

Normally, neuron models receive the linear sum of the inputs coming from all of their synaptic inputs through the \$(inSyn) variable. However neuron models can define additional input variables - allowing input from different synaptic inputs to be combined non-linearly. For example, if we wanted our leaky integrator to operate on the the product of two input currents, it could be defined as follows:

```
 \begin{split} & \texttt{SET\_ADDITIONAL\_INPUT\_VARS} \left( \{ \texttt{"Isyn2", "scalar", 1.0} \} \right); \\ & \texttt{SET\_SIM\_CODE} \left( \texttt{"const scalar input} = \$ \left( \texttt{Isyn} \right) \, \star \, \$ \left( \texttt{Isyn2} \right); \setminus \texttt{n"} \\ & \texttt{"$(V) = input} - \$ \left( \texttt{ExpTC} \right) \star \left( \texttt{input} - \$ \left( V \right) \right); \texttt{"}); \\ \end{aligned}
```

Where the SET_ADDITIONAL_INPUT_VARS() macro defines the name, type and its initial value before postsynaptic inputs are applyed (see section Postsynaptic integration methods for more details).

9.4.1.4 Random number generation

Many neuron models have probabilistic terms, for example a source of noise or a probabilistic spiking mechanism. In GeNN this can be implemented by using the following functions in blocks of model code:

- \$ (gennrand_uniform) returns a number drawn uniformly from the interval [0.0, 1.0]

- \$ (gennrand_normal) returns a number drawn from a normal distribution with a mean of 0 and a standard deviation of 1.
- \$ (gennrand_exponential) returns a number drawn from an exponential distribution with $\lambda = 1$.
- \$ (gennrand_log_normal, MEAN, STDDEV) returns a number drawn from a log-normal distribution with the specified mean and standard deviation.
- \$ (gennrand_gamma, ALPHA) returns a number drawn from a gamma distribution with the specified shape.

Once defined in this way, new neuron models classes, can be used in network descriptions by referring to their type e.g.

Previous | Top | Next

9.5 Weight update models

Currently 4 predefined weight update models are available:

- · WeightUpdateModels::StaticPulse
- WeightUpdateModels::StaticPulseDendriticDelay
- · WeightUpdateModels::StaticGraded
- · WeightUpdateModels::PiecewiseSTDP

For more details about these built-in synapse models, see [3].

9.5.1 Defining a new weight update model

Like the neuron models discussed in Defining your own neuron type, new weight update models are created by defining a class. Weight update models should all be derived from WeightUpdateModel::Base and, for convenience, the methods a new weight update model should implement can be implemented using macros:

- SET_DERIVED_PARAMS(), SET_PARAM_NAMES(), SET_VARS() and SET_EXTRA_GLOBAL_PARAM
 S() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- DECLARE_WEIGHT_UPDATE_MODEL(TYPE, NUM_PARAMS, NUM_VARS, NUM_PRE_VARS, NUM_ POST_VARS) is an extended version of DECLARE_MODEL() which declares the boilerplate code required for a weight update model with pre and postsynaptic as well as per-synapse state variables.
- SET_PRE_VARS() and SET_POST_VARS() define state variables associated with pre or postsynaptic neurons rather than synapses. These are typically used to efficiently implement *trace* variables for use in STDP learning rules [2]. Like other state variables, variables defined here as NAME can be accessed in weight update model code strings using the \$(NAME) syntax.
- SET_SIM_CODE(SIM_CODE): defines the simulation code that is used when a true spike is detected. The update is performed only in timesteps after a neuron in the presynaptic population has fulfilled its threshold detection condition. Typically, spikes lead to update of synaptic variables that then lead to the activation of input into the post-synaptic neuron. Most of the time these inputs add linearly at the post-synaptic neuron. This is assumed in GeNN and the term to be added to the activation of the post-synaptic neuron should be applied using the the \$(addToInSyn, weight) function. For example

```
SET_SIM_CODE(
    "$(addToInSyn, $(inc));\n"
```

where "inc" is the increment of the synaptic input to a post-synaptic neuron for each pre-synaptic spike. The simulation code also typically contains updates to the internal synapse variables that may have contributed to . For an example, see WeightUpdateModels::StaticPulse for a simple synapse update model and Weight UpdateModels::PiecewiseSTDP for a more complicated model that uses STDP. To apply input to the post-synaptic neuron with a dendritic (i.e. between the synapse and the postsynaptic neuron) delay you can instead use the \$(addToInSynDelay, weight, delay) function. For example

```
SET_SIM_CODE(
   "$(addToInSynDelay, $(inc), $(delay));");
```

where, once again, inc is the magnitude of the input step to apply and delay is the length of the dendritic delay in timesteps. By implementing delay as a weight update model variable, heterogeneous synaptic delays can be implemented. For an example, see WeightUpdateModels::StaticPulseDendriticDelay for a simple synapse update model with heterogeneous dendritic delays.

Note

When using dendritic delays, the **maximum** dendritic delay for a synapse populations must be specified using the SynapseGroup::setMaxDendriticDelayTimesteps() function.

• SET_EVENT_THRESHOLD_CONDITION_CODE(EVENT_THRESHOLD_CONDITION_CODE) defines a condition for a synaptic event. This typically involves the pre-synaptic variables, e.g. the membrane potential:

```
SET_EVENT_THRESHOLD_CONDITION_CODE("$(V_pre) > -0.02");
```

Whenever this expression evaluates to true, the event code set using the SET_EVENT_CODE() macro is executed. For an example, see WeightUpdateModels::StaticGraded.

- SET_EVENT_CODE(EVENT_CODE) defines the code that is used when the event threshold condition is met (as set using the SET_EVENT_THRESHOLD_CONDITION_CODE() macro).
- SET_LEARN_POST_CODE(LEARN_POST_CODE) defines the code which is used in the learnSynapses Post kernel/function, which performs updates to synapses that are triggered by post-synaptic spikes. This is typically used in STDP-like models e.g. WeightUpdateModels::PiecewiseSTDP.
- SET_SYNAPSE_DYNAMICS_CODE(SYNAPSE_DYNAMICS_CODE) defines code that is run for each synapse, each timestep i.e. unlike the others it is not event driven. This can be used where synapses have internal variables and dynamics that are described in continuous time, e.g. by ODEs. However using this mechanism is typically computationally very costly because of the large number of synapses in a typical network. By using the \$(addtoinsyn), \$(updatelinsyn) and \$(addToDenDelay) mechanisms discussed in the context of SET_SIM_CODE(), the synapse dynamics can also be used to implement continuous synapses for rate-based models.
- SET_PRE_SPIKE_CODE() and SET_POST_SPIKE_CODE() define code that is called whenever there is a pre or postsynaptic spike. Typically these code strings are used to update any pre or postsynaptic state variables.
- SET_NEEDS_PRE_SPIKE_TIME(PRE_SPIKE_TIME_REQUIRED) and SET_NEEDS_POST_SPIKE_TI

 ME(POST_SPIKE_TIME_REQUIRED) define whether the weight update needs to know the times of the spikes emitted from the pre and postsynaptic populations. For example an STDP rule would be likely to require:

```
SET_NEEDS_PRE_SPIKE_TIME(true);
SET_NEEDS_POST_SPIKE_TIME(true);
```

All code snippets, aside from those defined with SET_PRE_SPIKE_CODE () and SET_POST_SPIKE_COD \leftarrow E (), can be used to manipulate any synapse variable and so learning rules can combine both time-drive and event-driven processes.

Previous | Top | Next

9.6 Postsynaptic integration methods

There are currently 3 built-in postsynaptic integration methods:

PostsynapticModels::ExpCurr

· PostsynapticModels::ExpCond

· PostsynapticModels::DeltaCurr

9.6.1 Defining a new postsynaptic model

The postsynaptic model defines how synaptic activation translates into an input current (or other input term for models that are not current based). It also can contain equations defining dynamics that are applied to the (summed) synaptic activation, e.g. an exponential decay over time.

In the same manner as to both the neuron and weight update models discussed in Defining your own neuron type and Defining a new weight update model, postsynamic model definitions are encapsulated in a class derived from PostsynapticModels::Base. Again, the methods that a postsynaptic model should implement can be implemented using the following macros:

- DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS), SET_DERIVED_PARAMS(), SET_PARAM_N
 AMES(), SET_VARS() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- SET_DECAY_CODE(DECAY_CODE) defines the code which provides the continuous time dynamics for the summed presynaptic inputs to the postsynaptic neuron. This usually consists of some kind of decay function.
- SET_APPLY_INPUT_CODE(APPLY_INPUT_CODE) defines the code specifying the conversion from synaptic inputs to a postsynaptic neuron input current. e.g. for a conductance model:

```
SET\_APPLY\_INPUT\_CODE("$(Isyn) += $(inSyn) * ($(E) - $(V))");
```

where \$(E) is a postsynaptic model parameter specifying reversal potential and \$(V) is the variable containing the postsynaptic neuron's membrane potential. As discussed in Built-in Variables in GeNN, \$(Isyn) is the built in variable used to sum neuron input. However additional input variables can be added to a neuron model using the SET_ADDITIONAL_INPUT_VARS() macro (see Defining your own neuron type for more details).

Previous | Top | Next

9.7 Current source models

There is a number of predefined models which can be used with the ModelSpec::addCurrentSource function:

- CurrentSourceModels::DC
- · CurrentSourceModels::GaussianNoise

9.7.1 Defining your own current source model

In order to define a new current source type for use in a GeNN application, it is necessary to define a new class derived from CurrentSourceModels::Base. For convenience the methods this class should implement can be implemented using macros:

DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS), SET_DERIVED_PARAMS(), SET_PARAM_N←
AMES(), SET_VARS() perform the same roles as they do in the neuron models discussed in Defining your
own neuron type.

• SET_INJECTION_CODE(INJECTION_CODE): where INJECTION_CODE contains the code for injecting current into the neuron every simulation timestep. The \$(injectCurrent,) function is used to inject current.

For example, using these macros, we can define a uniformly distributed noisy current source:

```
class UniformNoise : public CurrentSourceModels::Base
{
public:
    DECLARE_MODEL(UniformNoise, 1, 0);
    SET_SIM_CODE("$(injectCurrent, $(gennrand_uniform) * $(magnitude));");
    SET_PARAM_NAMES({"magnitude"});
};
```

Previous | Top | Next

9.8 Synaptic matrix types

Synaptic matrix types are made up of two components: SynapseMatrixConnectivity and SynapseMatrixWeight. SynapseMatrixConnectivity defines what data structure is used to store the synaptic matrix:

- SynapseMatrixConnectivity::DENSE stores synaptic matrices as a dense matrix. Large dense matrices require a large amount of memory and if they contain a lot of zeros it may be inefficient.
- SynapseMatrixConnectivity::SPARSE stores synaptic matrices in a(padded) 'ragged array' format. In general, this is less efficient to traverse using a GPU than the dense matrix format but does result in significant memory savings for large matrices. Ragged matrix connectivity is stored using several variables whose names, like state variables, have the name of the synapse population appended to them:
 - 1. const unsigned int maxRowLength: a constant set via the SynapseGroup::setMaxconnections method which specifies the maximum number of connections in any given row (this is the width the structure is padded to).
 - 2. unsigned int *rowLength (sized to number of presynaptic neurons): actual length of the row of connections associated with each presynaptic neuron
 - 3. unsigned int *ind (sized to maxRowLength * number of presynaptic neurons) ← : Indices of corresponding postsynaptic neurons concatenated for each presynaptic neuron. For example, consider a network of two presynaptic neurons connected to three postsynaptic neurons: 0th presynaptic neuron connected to 1st and 2nd postsynaptic neurons, the 1st presynaptic neuron connected only to the 0th neuron. The struct RaggedProjection should have these members, with indexing from 0 (where X represents a padding value):

```
maxRowLength = 2
ind = [1 2 0 X]
rowLength = [2 1]
```

Weight update model variables associated with the sparsely connected synaptic population will be kept in an array using the same indexing as ind. For example, a variable called g will be kept in an array such as: $g=[g_Pre0-Post1\ g_pre0-post2\ g_pre1-post0\ X]$

• SynapseMatrixConnectivity::BITMASK is an alternative sparse matrix implementation where which synapses within the matrix are present is specified as a binary array (see Insect olfaction model). This structure is somewhat less efficient than the SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::RAGGED formats and doesn't allow individual weights per synapse. However it does require the smallest amount of GPU memory for large networks.

Furthermore the SynapseMatrixWeight defines how

SynapseMatrixWeight::INDIVIDUAL allows each individual synapse to have unique weight update model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushXXXXXStateToDevice function, where XXXX is the name of the synapse population.

9.9 Variable initialisation 37

• SynapseMatrixWeight::INDIVIDUAL_PSM allows each postsynapic neuron to have unique post synaptic model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushxxxxxxstateToDevice function, where XXXX is the name of the synapse population.

• SynapseMatrixWeight::GLOBAL saves memory by only maintaining one copy of the weight update model variables. This is automatically initialized to the initial value passed to ModelSpec::addSynapsePopulation.

Only certain combinations of SynapseMatrixConnectivity and SynapseMatrixWeight are sensible therefore, to reduce confusion, the SynapseMatrixType enumeration defines the following options which can be passed to Model Spec::addSynapsePopulation:

- SynapseMatrixType::SPARSE_GLOBALG
- SynapseMatrixType::SPARSE_GLOBALG_INDIVIDUAL_PSM
- SynapseMatrixType::SPARSE_INDIVIDUALG
- SynapseMatrixType::DENSE GLOBALG
- SynapseMatrixType::DENSE_GLOBALG_INDIVIDUAL_PSM
- SynapseMatrixType::DENSE INDIVIDUALG
- SynapseMatrixType::BITMASK GLOBALG
- SynapseMatrixType::BITMASK_GLOBALG_INDIVIDUAL_PSM

Previous | Top | Next

9.9 Variable initialisation

Neuron, weight update and postsynaptic models all have state variables which GeNN can automatically initialise.

Previously we have shown variables being initialised to constant values such as:

state variables can also be left *uninitialised* leaving it up to the user code to initialise them between the calls to initialize() and initializeSparse():

or initialised using one of a number of predefined variable initialisation snippets:

- InitVarSnippet::Uniform
- InitVarSnippet::Normal
- InitVarSnippet::Exponential
- InitVarSnippet::Gamma

For example, to initialise a parameter using values drawn from the normal distribution:

9.9.1 Defining a new variable initialisation snippet

Similarly to neuron, weight update and postsynaptic models, new variable initialisation snippets can be created by simply defining a class in the model description. For example, when initialising excitatory (positive) synaptic weights with a normal distribution they should be clipped at 0 so the long tail of the normal distribution doesn't result in negative weights. This could be implemented using the following variable initialisation snippet which redraws until samples are within the desired bounds:

```
class NormalPositive : public InitVarSnippet::Base
{
public:
    DECLARE_SNIPPET(NormalPositive, 2);

SET_CODE(
        "scalar normal;"
        "do\n"
        "{\n"
        " normal = $(mean) + ($(gennrand_normal) * $(sd));\n"
        "} while (normal < 0.0);\n"
        "$(value) = normal;\n");

SET_PARAM_NAMES({"mean", "sd"});
};
IMPLEMENT_SNIPPET(NormalPositive);</pre>
```

Within the snippet of code specified using the SET_CODE () macro, when initialisising neuron and postaynaptic model state variables, the \$(id) variable can be used to access the id of the neuron being initialised. Similarly, when initialising weight update model state variables, the \$(id_pre) and \$(id_post) variables can used to access the ids of the pre and postsynaptic neurons connected by the synapse being initialised.

9.9.2 Variable locations

Once you have defined **how** your variables are going to be initialised you need to configure **where** they will be allocated. By default memory is allocated for variables on both the GPU and the host. However, the following alternative 'variable locations' are available:

- VarLocation::DEVICE Variables are only allocated on the GPU, saving memory but meaning that they can't easily be copied to the host best for internal state variables.
- VarLocation::HOST_DEVICE Variables are allocated on both the GPU and the host the default.
- VarLocation::HOST_DEVICE_ZERO_COPY Variables are allocated as 'zero-copy' memory accessible to the host and GPU - useful on devices such as Jetson TX1 where physical memory is shared between the GPU and CPU.

Note

'Zero copy' memory is only supported on newer embedded systems such as the Jetson TX1 where there is no physical seperation between GPU and host memory and thus the same block of memory can be shared between them.

These modes can be set as a model default using ModelSpec::setDefaultVarLocation or on a pervariable basis using one of the following functions:

- NeuronGroup::setSpikeLocation
- NeuronGroup::setSpikeEventLocation
- NeuronGroup::setSpikeTimeLocation
- NeuronGroup::setVarLocation
- SynapseGroup::setWUVarLocation
- SynapseGroup::setWUPreVarLocation

- SynapseGroup::setWUPostVarLocation
- SynapseGroup::setPSVarLocation
- SynapseGroup::setInSynVarLocation

Previous | Top | Next

9.10 Sparse connectivity initialisation

Synaptic connectivity implemented using SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::

BITMASK can be automatically initialised.

This can be done using one of a number of predefined sparse connectivity initialisation snippets:

- InitSparseConnectivitySnippet::OneToOne
- InitSparseConnectivitySnippet::FixedProbability
- InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

For example, to initialise synaptic connectivity with a 10% connection probability (allowing connections between neurons with the same id):

9.10.1 Defining a new sparse connectivity snippet

Similarly to variable initialisation snippets, sparse connectivity initialisation snippets can be created by simply defining a class in the model description.

For example, the following sparse connectivity initialisation snippet could be used to initialise a 'ring' of connectivity where each neuron is connected to a number of subsequent neurons specified using the numNeighbours parameter:

```
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 1);
    SET_ROW_BUILD_STATE_VARS({{"offset", {"unsigned int", 1}}});
    SET ROW BUILD CODE (
         const unsigned int target = ($(id_pre) + offset) % $(num_post); \n"
        "$(addSynapse, target);\n"
        "offset++;\n"
        "if(offset > (unsigned int)(numNeighbours)) {n"
           $ (endRow); \n"
        "}\n");
    SET_PARAM_NAMES({"numNeighbours"});
    SET_CALC_MAX_ROW_LENGTH_FUNC(
        [](unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
        });
    SET_CALC_MAX_COL_LENGTH_FUNC (
        [](unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
IMPLEMENT_SNIPPET(Ring);
```

Each *row* of sparse connectivity is initialised independantly by running the snippet of code specified using the Stet_ROW_BUILD_CODE () macro within a loop. The \$(num_post) variable can be used to access the number of

neurons in the postsynaptic population and the \$(id_pre) variable can be used to access the index of the presynaptic neuron associated with the row being generated. The SET_ROW_BUILD_STATE_VARS() macro can be used to initialise state variables outside of the loop - in this case offset which is used to count the number of synapses created in each row. Synapses are added to the row using the \$(addSynapse, target) function and iteration is stopped using the \$(endRow) function. To avoid having to manually call SynapseGroup::setMaxConnections and SynapseGroup::setMaxSourceConnections, sparse connectivity snippets can also provide code to calculate the maximum row and column lengths this connectivity will result in using the SET_CALC_MAX_ROW_LENGTH_F\to UNC() and SET_CALC_MAX_COL_LENGTH_FUNC() macros. Alternatively, if the maximum row or column length is constant, the SET_MAX_ROW_LENGTH() and SET_MAX_COL_LENGTH() shorthand macros can be used.

9.10.2 Sparse connectivity locations

Once you have defined **how** sparse connectivity is going to be initialised, similarly to variables, you can control **where** it is allocated. This is controlled using the same VarLocations options described in section Variable locations and can either be set using the model default specified with ModelSpec::setDefault SparseConnectivityLocation or on a per-synapse group basis using SynapseGroup::setSparsection ConnectivityLocation.

Previous | Top | Next

10 Tutorial 1

In this tutorial we will go through step by step instructions how to create and run your first GeNN simulation from scratch.

10.1 The Model Definition

In this tutorial we will use a pre-defined Hodgkin-Huxley neuron model (NeuronModels::TraubMiles) and create a simulation consisting of ten such neurons without any synaptic connections. We will run this simulation on a GPU and save the results - firstly to stdout and then to file.

The first step is to write a model definition function in a model definition file. Create a new directory and, within that, create a new empty file called tenHHModel.cc using your favourite text editor, e.g.

```
>> emacs tenHHModel.cc &
```

Note

The ">>" in the example code snippets refers to a shell prompt in a unix shell, do not enter them as part of your shell commands.

The model definition file contains the definition of the network model we want to simulate. First, we need to include the GeNN model specification code modelSpec.h. Then the model definition takes the form of a function named modelDefinition that takes one argument, passed by reference, of type ModelSpec. Type in your tenH \leftarrow HModel.cc file:

```
// Model definintion file tenHHModel.cc
#include "modelSpec.h"

void modelDefinition(ModelSpec &model)
{
    // definition of tenHHModel
```

Two standard elements to the 'modelDefinition function are setting the simulation step size and setting the name of the model:

```
model.setDT(0.1);
model.setName("tenHHModel");
```

10.1 The Model Definition 41

Note

With this we have fixed the integration time step to 0.1 in the usual time units. The typical units in GeNN are ms, mV, nF, and μ S. Therefore, this defines DT= 0.1 ms.

Making the actual model definition makes use of the ModelSpec::addNeuronPopulation and ModelSpec::add SynapsePopulation member functions of the ModelSpec object. The arguments to a call to ModelSpec::add NeuronPopulation are

- NeuronModel: template parameter specifying the neuron model class to use
- const std::string &name: the name of the population
- unsigned int size: The number of neurons in the population
- const NeuronModel::ParamValues ¶mValues: Parameter values for the neurons in the population
- const NeuronModel::VarValues &varInitialisers: Initial values or initialisation snippets for variables of this neuron type

We first create the parameter and initial variable arrays,

Note

The comments are obviously only for clarity, they can in principle be omitted. To avoid any confusion about the meaning of parameters and variables, however, we recommend strongly to always include comments of this type.

Having defined the parameter values and initial values we can now create the neuron population,

This completes the model definition in this example. The complete tenHHModel.cc file now should look like this:

This model definition suffices to generate code for simulating the ten Hodgkin-Huxley neurons on the a GPU or CPU. The second part of a GeNN simulation is the user code that sets up the simulation, does the data handling for input and output and generally defines the numerical experiment to be run.

10.2 Building the model

To use GeNN to build your model description into simulation code, use a terminal to navigate to the directory containing your tenHHModel.cc file and, on Linux or Mac, type:

```
>> genn-buildmodel.sh tenHHModel.cc
```

Alternatively, on Windows, type:

```
>> genn-buildmodel.bat tenHHModel.cc
```

If you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can invoke genn-buildmodel with a -c option so, on Linux or Mac:

```
>> genn-buildmodel.sh -c tenHHModel.cc
or on Windows:
```

```
>> genn-buildmodel.bat -c tenHHModel.cc
```

If GeNN has been added to your path and CUDA_PATH is correctly configured, you should see some compile output ending in Model build complete

10.3 User Code

GeNN will now have generated the code to simulate the model for one timestep using a function stepTime(). To make use of this code, we need to define a minimal C/C++ main function. For the purposes of this tutorial we will initially simply run the model for one simulated second and record the final neuron variables into a file. Open a new empty file tenHHSimulation.cc in an editor and type

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();
    return 0;
}
```

This boiler plate code includes the header file for the generated code definitions.h in the subdirectory $ten\leftarrow HHModel_CODE$ where GeNN deposits all generated code (this corresponds to the name passed to the Model \leftarrow Spec::setName function). Calling allocateMem() allocates the memory structures for all neuron variables and initialize() launches a GPU kernel which initialise all state variables to their initial values. Now we can use the generated code to integrate the neuron equations provided by GeNN for 1000ms. To do so, we add after initialize();

Note

The t variable is provided by GeNN to keep track of the current simulation time in milliseconds.

```
while (t < 1000.0f) {
    stepTime();
}</pre>
```

and we need to copy the result back to the host before outputting it to stdout (this will do nothing if you are running the model on a CPU),

```
pullPoplStateFromDevice();
for (int j= 0; j < 10; j++) {
    std::cout << VPopl[j] << " ";
    std::cout << mPopl[j] << " ";
    std::cout << hPopl[j] << " ";
    std::cout << nPopl[j] << std::endl;</pre>
```

pullPop1StateFromDevice() copies all relevant state variables of the Pop1 neuron group from the GPU to the CPU main memory. Then we can output the results to stdout by looping through all 10 neurons and outputting the state variables VPop1, mPop1, hPop1, nPop1.

Note

The naming convention for variables in GeNN is the variable name defined by the neuron type, here TraubMiles defining V, m, h, and n, followed by the population name, here Pop1.

This completes the user code. The complete tenHHSimulation.cc file should now look like

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();
    while (t < 1000.0f) {
        stepTime();
    }
    pullPoplStateFromDevice();

    for (int j= 0; j < 10; j++) {
        std::cout << VPopl[j] << " ";
        std::cout << mPopl[j] << " ";
        std::cout << hPopl[j] << " ";
        std::cout << nPopl[j] << " ";
        std::cout << nPopl[j] << std::endl;
    }
    return 0;
}</pre>
```

10.4 Building the simulator (Linux or Mac)

On Linux and Mac, GeNN simulations are typically built using a simple Makefile which can be generated with the following command:

```
genn-create-user-project.sh tennHHModel tenHHSimulation.cc
```

This defines that the model is named tennHHModel and the simulation code is given in the file $tenHH \leftarrow Simulation.cc$ that we completed above. Now type

make

10.5 Building the simulator (Windows)

So that projects can be easily debugged within the Visual Studio IDE (see section Debugging suggestions for more details), Windows projects are built using an MSBuild script typically with the same title as the final executable. A suitable solution and project can be generated automatically with the following command:

```
genn-create-user-project.bat tennHHModel tenHHSimulation.cc
```

his defines that the model is named tennHHModel and the simulation code is given in the file $tenHH \leftarrow Simulation.cc$ that we completed above. Now type

msbuild tennHHModel.sln /p:Configuration=Release /t:tennHHModel

10.6 Running the Simulation

You can now execute your newly-built simulator on Linux or Mac with

./tennHHModel

Or on Windows with

tennHHModel_Release

The output you obtain should look like

```
-63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243
```

10.7 Reading

This is not particularly interesting as we are just observing the final value of the membrane potentials. To see what is going on in the meantime, we need to copy intermediate values from the device and save them into a file. This can be done in many ways but one sensible way of doing this is to replace the calls to stepTime in tenHHSimulation.cc with something like this:

```
std::ofstream os("tenHH_output.V.dat");
while (t < 1000.0f) {
    stepTime();

    pullVPop1FromDevice();

    os << t << " ";
    for (int j= 0; j < 10; j++) {
        os << VPop1[j] << " ";
    }
    os << std::endl;
}
os.close();</pre>
```

Note


t is a global variable updated by the GeNN code to keep track of elapsed simulation time in ms. we switched from using pullPop1StateFromDevice() to pullVPop1FromDevice() as we are now only interested in the membrane voltage of the neuron.

You will also need to add:

```
#include <fstream>
```

to the top of tenHHSimulation.cc. After building the model; and building and running the simulator as described above there should be a file tenHH_output.V.dat in the same directory. If you plot column one (time) against the subsequent 10 columns (voltage of the 10 neurons), you should observe dynamics like this:

11 Tutorial 2 45



However so far, the neurons are not connected and do not receive input. As the NeuronModels::TraubMiles model is silent in such conditions, the membrane voltages of the 10 neurons will simply drift from the -60mV they were initialised at to their resting potential.

Previous | Top | Next

11 Tutorial 2

In this tutorial we will learn to add synapsePopulations to connect neurons in neuron groups to each other with synaptic models. As an example we will connect the ten Hodgkin-Huxley neurons from tutorial 1 in a ring of excitatory synapses.

First, copy the files from Tutorial 1 into a new directory and rename the tenHHModel.cc to tenHHRing Model.cc and tenHHSimulation.cc to tenHHRingSimulation.cc, e.g. on Linux or Mac:

```
>> cp -r tenHH_project tenHHRing_project
>> cd tenHHRing_project
>> mv tenHHModel.cc tenHHRingModel.cc
>> mv tenHHSimulation.cc tenHHRingSimulation.cc
```

Finally, to reduce confusion we should rename the model itself. Open tenHHRingModel.cc, change the model name inside,

```
model.setName("tenHHRing");
```

11.1 Defining the Detailed Synaptic Connections

We want to connect our ten neurons into a ring where each neuron connects to its neighbours. In order to initialise this connectivity we need to add a sparse connectivity initialisation snippet at the top of tenhHRingModel.cc:

The SET_ROW_BUILD_CODE code string will be called to generate each row of the synaptic matrix (connections coming from a single presynaptic neuron) and, in this case, each row consists of a single synapses from the presynaptic neuron \$(id_pre) to \$(id_pre) + 1 (the modulus operator is used to ensure that the final connection between neuron 9 and 0 is made correctly). In order to allow GeNN to better optimise the generated code we also provide a maximum row length. In this case each row always contains only one synapse but, when more complex connectivity is used, the number of neurons in the pre and postsynaptic population as well as any parameters used to configure the snippet can be accessed from this function.

Note

When defining GeNN code strings, the \$(VariableName) syntax is used to refer to variables provided by GeNN and the \$(FunctionName, Parameter1,...) syntax is used to call functions provided by GeNN.

11.2 Adding Synaptic connections

Now we need additional initial values and parameters for the synapse and post-synaptic models. We will use the standard WeightUpdateModels::StaticPulse weight update model and PostsynapticModels::ExpCond post-synaptic model. They need the following initial variables and parameters:

Note

the WeightUpdateModels::StaticPulse weight update model has no parameters and the PostsynapticModels.::ExpCond post-synaptic model has no state variables.

We can then add a synapse population at the end of the modelDefinition(...) function,

```
model.addSynapsePopulation<WeightUpdateModels::StaticPulse
    , PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 10,
    "Popl", "Popl",
    {}, s_ini,
    ps_p, {},
    initConnectivity<Ring>());
```

The addSynapsePopulation parameters are

- WeightUpdateModel: template parameter specifying the type of weight update model (derived from Weight
 — UpdateModels::Base).
- PostsynapticModel: template parameter specifying the type of postsynaptic model (derived from PostsynapticModels::Base).
- name string containing unique name of synapse population.
- mtype how the synaptic matrix associated with this synapse population should be represented. Here
 SynapseMatrixType::SPARSE_GLOBALG means that there will be sparse connectivity and each connection
 will have the same weight (-0.2 as specified previously).
- delayStep integer specifying number of timesteps of propagation delay that spikes travelling through this synapses population should incur (or NO DELAY for none)
- · src string specifying name of presynaptic (source) population
- trg string specifying name of postsynaptic (target) population
- weightParamValues parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.

- weightVarInitialisers initial values or initialisation snippets for the weight update model's state variables wrapped in a WeightUpdateModel::VarValues object.
- postsynapticParamValues parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
- postsynapticVarInitialisers initial values or initialisation snippets for the postsynaptic model wrapped in PostsynapticModel::VarValues object.
- connectivityInitialiser snippet and any paramaters (in this case there are none) used to initialise the synapse population's sparse connectivity.

Adding the addSynapsePopulation command to the model definition informs GeNN that there will be synapses between the named neuron populations, here between population Pop1 and itself. At this point our model definition file tenHHRingModel.cc should look like this

```
// Model definition file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET_ROW_BUILD_CODE(
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
"$(endRow);\n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET (Ring):
void modelDefinition(ModelSpec &model)
     // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
                 // 0 - gNa: Na conductance in muS
                      // 1 - ENa: Na equi potential in mV
                     // 2 - gK: K conductance in muS

// 3 - EK: K equi potential in mV
         1.43.
         -95.0,
                    // 4 - g1: leak conductance in muS
// 5 - E1: leak equi potential in mV
// 6 - Cmem: membr. capacity density in nF
         0.02672,
         -63.563.
         0.143);
    NeuronModels::TraubMiles::VarValues ini(
                        // 0 - membrane potential V // 1 - prob. for Na channel activation m
         -60.0,
0.0529324,
                         // 2 - prob. for not Na channel blocking h
         0.3176767,
                         // 3 - prob. for K channel activation n
         0.5961207);
    model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
       10, p, ini);
    WeightUpdateModels::StaticPulse::VarValues s ini(
          -0.2); // 0 - g: the synaptic conductance value
    PostsynapticModels::ExpCond::ParamValues ps_p(
         1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
    model.addSvnapsePopulation<
       WeightUpdateModels::StaticPulse,
       PostsynapticModels::ExpCond>(
         "Pop1self", SynapseMatrixType::SPARSE_GLOBALG, 100,
         "Pop1", "Pop1",
         {}, s_ini,
         ps p, {},
         initConnectivity<Ring>());
```

We can now build our new model:

```
>> genn-buildmodel.sh tenHHRingModel.cc
```

Note

Again, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead build with the -c option as described in Tutorial 1.


Now we can open the tenHHRingSimulation.cc file and update the file name of the model includes to match the name we set previously:

```
// tenHHRingModel simulation code
#include "tenHHRing_CODE/definitions.h"
```

Additionally, we need to add a call to a second initialisation function to main() after we call initialize():

```
initializeSparse();
```

This initializes any variables associated with the sparse connectivity we have added (and will also copy any manually initialised variables to the GPU). Then, after using the <code>genn-create-user-project</code> tool to create a new project with a model name of <code>tenhhRing</code> and using <code>tenhhRingSimulation.cc</code> rather than <code>tenhhesimulation.cc</code>, we can build and run our new simulator in the same way we did in Tutorial 1. However, even after all our hard work, if we plot the content of the first column against the subsequent 10 columns of <code>tenhesimple.V.dat</code> it looks very similar to the plot we obtained at the end of Tutorial 1.



This is because none of the neurons are spiking so there are no spikes to propagate around the ring.

11.3 Providing initial stimuli

We can use a NeuronModels::SpikeSource to inject an initial spike into the first neuron in the ring during the first timestep to start spikes propagating. Firstly we need to define another sparse connectivity initialisation snippet at the top of tenHHRingModel.cc which simply creates a single synapse on the first row of the synaptic matrix:

We then need to add it to the network by adding the following to the end of the modelDefinition(...) function:

and finally inject a spike in the first timestep (in the same way that the t variable is provided by GeNN to keep track of the current simulation time in milliseconds, iT is provided to keep track of it in timesteps):

```
if(iT == 0) {
    spikeCount_Stim = 1;
    spike_Stim[0] = 0;
    pushStimCurrentSpikesToDevice();
}
```

Note

 $spike_Stim[n]$ is used to specify the indices of the neurons in population Stim spikes which should emit spikes where $n \in [0, spikeCount_Stim)$.

At this point our user code tenHHRingModel.cc should look like this


```
// Model definintion file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET ROW BUILD CODE (
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
        "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT_SNIPPET(Ring);
class FirstToFirst : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(FirstToFirst, 0);
    SET_ROW_BUILD_CODE(
         "if($(id_pre) == 0) {\n"
           $ (addSynapse, $ (id_pre)); \n"
        "}\n"
        "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET(FirstToFirst);
void modelDefinition(ModelSpec &model)
    // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
                    // 0 - gNa: Na conductance in muS
         7.15,
                     // 1 - ENa: Na equi potential in mV
         1.43,
                     // 2 - gK: K conductance in muS
                     // 3 - EK: K equi potential in mV
        -95.0.
                    // 4 - gl: leak conductance in muS
// 5 - El: leak equi potential in mV
        0.02672.
         -63.563,
                     // 6 - Cmem: membr. capacity density in nF
        0.143);
    NeuronModels::TraubMiles::VarValues ini(
                   // 0 - membrane potential V // 1 - prob. for Na channel activation m
        -60.0,
        0.0529324.
                        // 2 - prob. for not Na channel blocking h
        0.3176767.
        0.5961207);
                        // 3 - prob. for K channel activation n
```

```
model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
  10, p, ini);
model.addNeuronPopulation<NeuronModels::SpikeSource>("Stim"
  , 1, {}, {});
WeightUpdateModels::StaticPulse::VarValues s_ini(
      -0.2); // 0 - g: the synaptic conductance value
PostsynapticModels::ExpCond::ParamValues ps_p(
    1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 100,
"Popl", "Popl",
{}, s_ini,
ps_p, {},
    initConnectivity<Ring>());
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
    "StimPop1", SynapseMatrixType::SPARSE_GLOBALG,
  NO_DELAY,
"Stim", "Pop1",
    {}, s_ini,
    ps_p, {},
initConnectivity<FirstToFirst>());
```

and tenHHRingSimulation.cc' should look like this:

```
// Standard C++ includes
#include <fstream>
// tenHHRing simulation code
#include "tenHHRing_CODE/definitions.h"
int main()
    allocateMem();
    initialize();
    initializeSparse();
    std::ofstream os("tenHHRing_output.V.dat");
    while(t < 200.0f) {
    if(iT == 0) {
             glbSpkStim[0] = 0;
glbSpkCntStim[0] = 1;
             pushStimCurrentSpikesToDevice();
        stepTimeU();
         pullVPop1FromDevice();
         os << t << " ";
         for (int j= 0; j < 10; j++) {
    os << VPop1[j] << " ";
         os << std::endl;
    os.close();
    return 0;
```

Finally if we build, make and run this model; and plot the first 200 ms of the ten neurons' membrane voltages - they now looks like this:



Previous | Top | Next

12 Best practices guide

GeNN generates code according to the network model defined by the user, and allows users to include the generated code in their programs as they want. Here we provide a guideline to setup GeNN and use generated functions. We recommend users to also have a look at the Examples, and to follow the tutorials Tutorial 1 and Tutorial 2.

12.1 Creating and simulating a network model

The user is first expected to create an object of class ModelSpec by creating the function modelDefinition() which includes calls to following methods:

- · ModelSpec::setDT();
- ModelSpec::setName();

Then add neuron populations by:

ModelSpec::addNeuronPopulation();

for each neuron population. Add synapse populations by:

ModelSpec::addSynapsePopulation();

for each synapse population.

Other optional functions are explained in ModelSpec class reference. At the end the function should look like this:

```
void modelDefinition(ModelSpec &model) {
  model.setDT(0.5);
  model.setName("YourModelName");
  model.addNeuronPopulation(...);
  ...
  model.addSynapsePopulation(...);
  ...
}
```

modelSpec.h should be included in the file where this function is defined.

This function will be called by generateALL.cc to create corresponding CPU and GPU simulation codes under the <YourModelName> CODE directory.

These functions can then be used in a .cc file which runs the simulation. This file should include <YourModel

Name>_CODE/definitions.h. Generated code differ from one model to the other, but core functions are the same
and they should be called in correct order. First, the following variables should be defined and initialized:

- ModelSpec model // initialized by calling modelDefinition(model)
- Array containing current input (if any)

Any variables marked as unintialised using the uninitialisedVar() function or sparse connectivity not initialised using a snippet must be initialised by the user between calls to initialize() and initialize \Leftrightarrow Sparse(). Core functions generated by GeNN to be included in the user code include:

```
• allocateMem()
```

- initialize()
- initializeSparse()
- push<neuron or synapse name>StateToDevice()
- pull<neuron or synapse name>StateFromDevice()
- push<neuron name>SpikesToDevice()
- pull<neuron name>SpikesFromDevice()
- push<neuron name>SpikesEventsToDevice()
- pull<neuron name>SpikesEventsFromDevice()
- push<neuron name>SpikeTimesToDevice()
- pull<neuron name>SpikeTimesFromDevice()
- push<neuron name>CurrentSpikesToDevice()
- pull<neuron name>CurrentSpikesFromDevice()
- push<neuron name>CurrentSpikesEventsToDevice()
- $\hbox{\bf \cdot} \ \verb"pull<" neuron name>CurrentSpikesEventsFromDevice()$
- get<neuron name>CurrentSpikes()
- get<neuron name>CurrentSpikeCount()
- pull<synapse name>ConnectivityFromDevice()
- push<synapse name>ConnectivityToDevice()
- pull<var name><neuron or synapse name>FromDevice()
- push<var name><neuron or synapse name>ToDevice()
- pushCurrent<var name><neuron name>ToDevice()
- pullCurrent<var name><neuron name>FromDevice()
- getCurrent<var name><neuron name>()
- copyStateToDevice()
- copyStateFromDevice()

- copyCurrentSpikesFromDevice()
- copyCurrentSpikesEventsFromDevice()
- stepTime()
- freeMem()

You can use the <code>push<neuron</code> or <code>synapse</code> <code>name>StateToDevice()</code> to copy from the host to the GPU. At the end of your simulation, if you want to access the variables you need to copy them back from the device using the <code>pull<neuron</code> or <code>synapse</code> <code>name>StateFromDevice()</code> function or one of the more fine-grained functions listed above. In order to correctly access neuron state and spikes for the current timestep, correctly accounting for delay buffering etc, you can use the <code>getCurrent<var</code> <code>name><neuron</code> <code>name>()</code>, <code>get<neuron</code> <code>name>CurrentSpikes()</code> and '<code>get<neuron</code> <code>name>CurrentSpikeCount()</code> functions. Copying elements between the GPU and the host memory is very costly in terms of performance and should only be done when needed and the amount of data being copied should be minimized.

12.1.1 Extra Global Parameters

If extra global parameters have a "scalar" type such as float they can be set directly from simulation code. For example the extra global parameter "reward" of population "Pop" could be set with:

```
rewardPop = 5.0f;
```

However, if extra global parameters have a pointer type such as float*, GeNN generates additional functions to allocate, free and copy these variables between host and device:

- allocate<var name><neuron or synapse name>
- free<var name><neuron or synapse name>
- push<var name><neuron or synapse name>ToDevice
- pull<var name><neuron or synapse name>FromDevice These operate in much the same manner as the functions for interacting with standard variables described above but the allocate, push and pull functions all take a "count" parameter specifying how many entries the extra global parameter array should be.

12.2 Floating point precision

Double precision floating point numbers are supported by devices with compute capability 1.3 or higher. If you have an older GPU, you need to use single precision floating point in your models and simulation.

GPUs are designed to work better with single precision while double precision is the standard for CPUs. This difference should be kept in mind while comparing performance.

While setting up the network for GeNN, double precision floating point numbers are used as this part is done on the CPU. For the simulation, GeNN lets users choose between single or double precision. Overall, new variables in the generated code are defined with the precision specified by ModelSpec::setPrecision(unsigned int), providing GENN_FLOAT or GENN_DOUBLE as argument. GENN_FLOAT is the default value. The keyword scalar can be used in the user-defined model codes for a variable that could either be single or double precision. This keyword is detected at code generation and substituted with "float" or "double" according to the precision set by ModelSpec::setPrecision(unsigned int).

There may be ambiguities in arithmetic operations using explicit numbers. Standard C compilers presume that any number defined as "X" is an integer and any number defined as "X.Y" is a double. Make sure to use the same precision in your operations in order to avoid performance loss.

12.3 Working with variables in GeNN

12.3.1 Model variables

User-defined model variables originate from classes derived off the NeuronModels::Base, WeightUpdateModels ::Base or PostsynapticModels::Base classes. The name of model variable is defined in the model type, i.e. with a statement such as

```
SET_VARS({{"V", "scalar"}});
```

When a neuron or synapse population using this model is added to the model, the full GeNN name of the variable will be obtained by concatenating the variable name with the name of the population. For example if we add a population called Pop using a model which contains our V variable, a variable VPop of type scalar* will be available in the global namespace of the simulation program. GeNN will pre-allocate this C array to the correct size of elements corresponding to the size of the neuron population. GeNN will also free these variables when the provided function freeMem() is called. Users can otherwise manipulate these variable arrays as they wish. For convenience, GeNN provides functions to copy each state variable from the device into host memory and vice versa e.g. pullVPopFromDevice() and pushVPoptoDevice(). Alternatively, all state variables associated with a population can be copied using a single call E.g.

```
pullPopStateFromDevice();
```

These conventions also apply to the the variables of postsynaptic and weight update models.

Note

Be aware that the above naming conventions do assume that variables from the weightupdate models and the postSynModels that are used together in a synapse population are unique. If both the weightupdate model and the postSynModel have a variable of the same name, the behaviour is undefined.

12.3.2 Built-in Variables in GeNN

GeNN has no explicitly hard-coded synapse and neuron variables. Users are free to name the variable of their models as they want. However, there are some reserved variables that are used for intermediary calculations and communication between different parts of the generated code. They can be used in the user defined code but no other variables should be defined with these names.

- DT: Time step (typically in ms) for simulation; Neuron integration can be done in multiple sub-steps inside the neuron model for numerical stability (see Traub-Miles and Izhikevich neuron model variations in Neuron models).
- inSyn: This is an intermediary synapse variable which contains the summed input into a postsynaptic neuron (originating from the addtoinSyn variables of the incoming synapses).
- Isyn: This is a local variable which contains the (summed) input current to a neuron. It is typically the sum
 of any explicit current input and all synaptic inputs. The way its value is calculated during the update of the
 postsynaptic neuron is defined by the code provided in the postsynaptic model. For example, the standard
 PostsynapticModels::ExpCond postsynaptic model defines

```
SET_APPLY_INPUT_CODE("$(Isyn) += $(inSyn) * ($(E) - $(V))");
```

which implements a conductance based synapse in which the postsynaptic current is given by $I_{\text{syn}} = g * s * (V_{\text{rev}} - V_{\text{post}})$.

The value resulting from the current converter code is assigned to Isyn and can then be used in neuron sim code like so:

```
(V) += (-(V) + (Isyn)) *DT
```

sT: This is a neuron variable containing the last spike time of each neuron and is automatically generated for
pre and postsynaptic neuron groups if they are connected using a synapse population with a weight update
model that has SET_NEEDS_PRE_SPIKE_TIME(true) or SET_NEEDS_POST_SPIKE_TIME(true) set.

In addition to these variables, neuron variables can be referred to in the synapse models by calling \$(<neuronVar~Name>_pre) for the presynaptic neuron population, and \$(<neuronVarName>_post) for the postsynaptic population. For example, \$(sT_pre), \$(sT_post), \$(V_pre), etc.

12.4 Debugging suggestions

In Linux, users can call <code>cuda-gdb</code> to debug on the GPU. Example projects in the <code>userproject</code> directory come with a flag to enable debugging (-debug). genn-buildmodel.sh has a debug flag (-d) to generate debugging data. If you are executing a project with debugging on, the code will be compiled with -g -G flags. In CPU mode the executable will be run in gdb, and in GPU mode it will be run in cuda-gdb in tui mode.

Note

Do not forget to switch debugging flags -g and -G off after debugging is complete as they may negatively affect performance.

On Mac, some versions of clang aren't supported by the CUDA toolkit. This is a recurring problem on Fedora as well, where CUDA doesn't keep up with GCC releases. You can either hack the CUDA header which checks compiler versions - cuda/include/host_config.h - or just use an older XCode version (6.4 works fine).

On Windows models can also be debugged and developed by opening the sln file used to build the model in Visual Studio. From here files can be added to the project, build settings can be adjusted and the full suite of Visual Studio debugging and profiling tools can be used.

Note

When opening the models in the userproject directory in Visual Studio, right-click on the project in the solution explorer, select 'Properties'. Then, making sure the desired configuration is selected, navigate to 'Debugging' under 'Configuration Properties', set the 'Working Directory' to '..' and the 'Command Arguments' to match those passed to genn-buildmodel e.g. 'outdir' to use an output directory called outdir.

Previous | Top | Next

13 Credits

GeNN was created by Thomas Nowotny.

GeNN is currently maintained and developed by James Knight.

Current sources and PyGeNN were first implemented by Anton Komissarov.

Izhikevich model and sparse connectivity by Esin Yavuz.

Block size optimisations, delayed synapses and page-locked memory by James Turner.

Automatic brackets and dense-to-sparse network conversion helper tools by Alan Diamond.

User-defined synaptic and postsynaptic methods by Alex Cope and Esin Yavuz.

Example projects were provided by Alan Diamond, James Turner, Esin Yavuz and Thomas Nowotny.

MPI support was largely developed by Mengchi Zhang.

Previous

14 Namespace Index

14.1 Namespace List

Here is a list of all namespaces with brief descriptions:

CodeGenerator Helper class for generating code - automatically inserts brackets, indents etc	69
CodeGenerator::CUDA	76
CodeGenerator::CUDA::Optimiser	77
CodeGenerator::CUDA::PresynapticUpdateStrategy	78
CodeGenerator::CUDA::Utils	78
CodeGenerator::SingleThreadedCPU	78
CodeGenerator::SingleThreadedCPU::Optimiser	79
CurrentSourceModels	79
filesystem	79
InitSparseConnectivitySnippet Base class for all sparse connectivity initialisation snippets	79
InitVarSnippet Base class for all value initialisation snippets	80
Models	80
NeuronModels	80
PostsynapticModels	81
pugi	81
pygenn	81
pygenn.genn_groups	81
pygenn.genn_model	82
pygenn.model_preprocessor	90
Snippet	94
SpineMLSimulator	94
SpineMLSimulator::Connectors	95
SpineMLSimulator::Input	95
SpineMLSimulator::InputValue	95
SpineMLSimulator::LogOutput	96
SpineMLSimulator::ModelProperty	96
Utils	97

15 Hierarchical Index 57

WeightUpdateModels	97
15 Hierarchical Index	
15.1 Class Hierarchy	
This inheritance list is sorted roughly, but not completely, alphabetically:	
AnalogueRecorder< T >	103
CodeGenerator::BackendBase	129
CodeGenerator::CUDA::Backend	104
CodeGenerator::SingleThreadedCPU::Backend	117
Snippet::Base	150
InitSparseConnectivitySnippet::Base	143
InitSparseConnectivitySnippet::FixedProbabilityBase	193
InitSparseConnectivitySnippet::FixedProbability	192
InitSparseConnectivitySnippet::FixedProbabilityNoAutap	ose 195
InitSparseConnectivitySnippet::OneToOne	254
InitSparseConnectivitySnippet::Uninitialised	345
InitVarSnippet::Base	145
InitVarSnippet::Constant	165
InitVarSnippet::Exponential	185
InitVarSnippet::Gamma	197
InitVarSnippet::Normal	252
InitVarSnippet::Uniform	343
InitVarSnippet::Uninitialised	345
Models::Base	146
CurrentSourceModels::Base	143
CurrentSourceModels::DC	175
CurrentSourceModels::GaussianNoise	198
NeuronModels::Base	147
NeuronModels::lzhikevich	215
NeuronModels::IzhikevichVariable	218
NeuronModels::LIF	220
NeuronModels::Poisson	260

NeuronModels::PoissonNew	263
NeuronModels::RulkovMap	275
NeuronModels::SpikeSource	289
NeuronModels::SpikeSourceArray	291
NeuronModels::TraubMiles	334
NeuronModels::TraubMilesAlt	337
NeuronModels::TraubMilesFast	339
NeuronModels::TraubMilesNStep	341
PostsynapticModels::Base	152
PostsynapticModels::DeltaCurr	177
PostsynapticModels::ExpCond	181
PostsynapticModels::ExpCurr	183
WeightUpdateModels::Base	154
WeightUpdateModels::PiecewiseSTDP	256
WeightUpdateModels::StaticGraded	298
WeightUpdateModels::StaticPulse	300
WeightUpdateModels::StaticPulseDendriticDelay	301
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base	153
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan	267
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan	272
SpineMLSimulator::Input::Base	158
SpineMLSimulator::Input::Analogue	98
SpineMLSimulator::Input::SpikeBase	286
SpineMLSimulator::Input::InterSpikeIntervalBase	214
SpineMLSimulator::Input::PoissonSpikeRate	265
SpineMLSimulator::Input::RegularSpikeRate	274
SpineMLSimulator::Input::SpikeTime	294
SpineMLSimulator::InputValue::Base	159
SpineMLSimulator::InputValue::ConstantArray	167
SpineMLSimulator::InputValue::External	187
SpineMLSimulator::InputValue::ExternalNetwork	188
SpineMLSimulator::InputValue::ScalarBase	278

SpineMLSimulator::InputValue::Constant	166
SpineMLSimulator::InputValue::TimeVarying	332
SpineMLSimulator::InputValue::TimeVaryingArray	333
SpineMLSimulator::LogOutput::Base	160
SpineMLSimulator::LogOutput::AnalogueBase	99
SpineMLSimulator::LogOutput::AnalogueExternal	100
SpineMLSimulator::LogOutput::AnalogueNetwork	102
SpineMLSimulator::LogOutput::AnalogueFile	101
SpineMLSimulator::LogOutput::Event	180
SpineMLSimulator::ModelProperty::Base	162
SpineMLSimulator::ModelProperty::ExponentialDistribution	186
SpineMLSimulator::ModelProperty::Fixed	191
SpineMLSimulator::ModelProperty::NormalDistribution	253
SpineMLSimulator::ModelProperty::UniformDistribution	344
SpineMLSimulator::ModelProperty::ValueList	348
CodeGenerator::CodeStream::CB	163
CurrentSource	171
CurrentSourceInternal	175
Snippet::Base::DerivedParam	179
Snippet::Base::EGP	179
CodeGenerator::FunctionTemplate	196
GenerateRunBase	200
Snippet::Init< SnippetBase >	213
Snippet::Init< Base >	213
InitSparseConnectivitySnippet::Init	212
Snippet::Init< InitVarSnippet::Base >	213
Models::VarInit	352
std::ios_base std::basic_ios	
std::basic_ios std::basic_ostream	
std::ostream	
CodeGenerator::CodeStream	164
CodeGenerator::TeeStream	329
CodeGenerator::MemAlloc	222

ModelSpec	224
ModelSpecInternal	237
SpineMLSimulator::NetworkClient	237
NeuronGroup	243
NeuronGroupInternal	251
CodeGenerator::CodeStream::OB object	254
pygenn.genn_groups.Group	210
pygenn.genn_groups.CurrentSource	168
pygenn.genn_groups.NeuronGroup	239
pygenn.genn_groups.SynapseGroup	306
pygenn.genn_model.GeNNModel	201
pygenn.model_preprocessor.ExtraGlobalVariable	189
pygenn.model_preprocessor.Variable	350
Snippet::Base::ParamVal	256
CodeGenerator::PreferencesBase	270
CodeGenerator::CUDA::Preferences	269
CodeGenerator::SingleThreadedCPU::Preferences	268
CodeGenerator::CodeStream::Scope	278
SharedLibraryModel < scalar >	279
SpineMLSimulator::Simulator	284
SpikeWriterText	295
SpikeWriterTextCached	295
SpineMLSimulator::StateVar< T >	296
SpineMLSimulator::StateVar< scalar > streambuf	296
CodeGenerator::TeeBuf	328
CodeGenerator::Substitutions	303
SynapseGroup	314
SynapseGroupInternal	327
SpineMLSimulator::Timer	329
Timer	330
TimerAccumulate	331

16 Class Index 61

	SpineMLSimulator::TimerAccumulate	332
	Snippet::ValueBase < NumVars >	346
	Snippet::ValueBase< 0 >	347
	Models::Base::Var	349
	Models::VarInitContainerBase< NumVars >	353
	Models::VarInitContainerBase< 0 > Writer	354
	SpikeRecorder < Writer >	288
16	Class Index	
16.	.1 Class List	
He	re are the classes, structs, unions and interfaces with brief descriptions:	
	SpineMLSimulator::Input::Analogue	98
	SpineMLSimulator::LogOutput::AnalogueBase	99
	SpineMLSimulator::LogOutput::AnalogueExternal	100
	SpineMLSimulator::LogOutput::AnalogueFile	101
	SpineMLSimulator::LogOutput::AnalogueNetwork	102
	AnalogueRecorder< T >	103
	CodeGenerator::CUDA::Backend	104
	CodeGenerator::SingleThreadedCPU::Backend	117
	CodeGenerator::BackendBase	129
	CurrentSourceModels::Base Base class for all current source models	143
	InitSparseConnectivitySnippet::Base	143
	InitVarSnippet::Base	145
	Models::Base Base class for all models - in addition to the parameters snippets have, models can have state variables	146
	NeuronModels::Base Base class for all neuron models	147
	Snippet::Base Base class for all code snippets	150
	PostsynapticModels::Base Base class for all postsynaptic models	152
	CodeGenerator::CUDA::PresynapticUpdateStrategy::Base	153

WeightUpdateModels::Base	
Base class for all weight update models	154
SpineMLSimulator::Input::Base	158
SpineMLSimulator::InputValue::Base	159
SpineMLSimulator::LogOutput::Base	160
SpineMLSimulator::ModelProperty::Base	162
CodeGenerator::CodeStream::CB A close bracket marker	163
CodeGenerator::CodeStream	164
InitVarSnippet::Constant Initialises variable to a constant value	165
SpineMLSimulator::InputValue::Constant	166
SpineMLSimulator::InputValue::ConstantArray	167
pygenn.genn_groups.CurrentSource Class representing a current injection into a group of neurons	168
CurrentSource	171
CurrentSourceInternal	175
CurrentSourceModels::DC DC source	175
PostsynapticModels::DeltaCurr Simple delta current synapse	177
Snippet::Base::DerivedParam A derived parameter has a name and a function for obtaining its value	179
Snippet::Base::EGP An extra global parameter has a name and a type	179
SpineMLSimulator::LogOutput::Event	180
PostsynapticModels::ExpCond Exponential decay with synaptic input treated as a conductance value	181
PostsynapticModels::ExpCurr Exponential decay with synaptic input treated as a current value	183
InitVarSnippet::Exponential Initialises variable by sampling from the exponential distribution	185
SpineMLSimulator::ModelProperty::ExponentialDistribution	186
SpineMLSimulator::InputValue::External	187
SpineMLSimulator::InputValue::ExternalNetwork	188
pygenn.model_preprocessor.ExtraGlobalVariable Class holding information about GeNN extra global pointer variable	189

16.1 Class List 63

SpineMLSimulator::ModelProperty::Fixed	191
InitSparseConnectivitySnippet::FixedProbability	192
InitSparseConnectivitySnippet::FixedProbabilityBase	193
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse	195
CodeGenerator::FunctionTemplate	196
InitVarSnippet::Gamma Initialises variable by sampling from the exponential distribution	197
CurrentSourceModels::GaussianNoise Noisy current source with noise drawn from normal distribution	198
GenerateRunBase	200
pygenn.genn_model.GeNNModel GeNNModel class This class helps to define, build and run a GeNN model from python	20 1
pygenn.genn_groups.Group Parent class of NeuronGroup, SynapseGroup and CurrentSource	210
InitSparseConnectivitySnippet::Init	212
Snippet::Init< SnippetBase >	213
SpineMLSimulator::Input::InterSpikeIntervalBase	214
NeuronModels::Izhikevich Izhikevich neuron with fixed parameters [1]	215
NeuronModels::IzhikevichVariable Izhikevich neuron with variable parameters [1]	218
NeuronModels::LIF	220
CodeGenerator::MemAlloc	222
ModelSpec Object used for specifying a neuronal network model	224
ModelSpecInternal	237
SpineMLSimulator::NetworkClient	237
pygenn.genn_groups.NeuronGroup Class representing a group of neurons	239
NeuronGroup	243
NeuronGroupInternal	25 1
InitVarSnippet::Normal Initialises variable by sampling from the normal distribution	252
SpineMLSimulator::ModelProperty::NormalDistribution	253
CodeGenerator::CodeStream::OB An open bracket marker	25 4

InitSparseConnectivitySnippet::OneToOne Initialises connectivity to a 'one-to-one' diagonal matrix	254
Snippet::Base::ParamVal Additional input variables, row state variables and other things have a name, a type and an initial value	256
WeightUpdateModels::PiecewiseSTDP This is a simple STDP rule including a time delay for the finite transmission speed of the synapse	256
NeuronModels::Poisson Poisson neurons	260
NeuronModels::PoissonNew Poisson neurons	263
SpineMLSimulator::Input::PoissonSpikeRate	265
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan Postsynaptic parallelism	267
CodeGenerator::SingleThreadedCPU::Preferences	268
CodeGenerator::CUDA::Preferences Preferences for CUDA backend	269
CodeGenerator::PreferencesBase Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator	270
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan Presynaptic parallelism	272
SpineMLSimulator::Input::RegularSpikeRate	274
NeuronModels::RulkovMap Rulkov Map neuron	275
SpineMLSimulator::InputValue::ScalarBase	278
CodeGenerator::CodeStream::Scope	278
SharedLibraryModel < scalar >	279
SpineMLSimulator::Simulator	284
SpineMLSimulator::Input::SpikeBase	286
SpikeRecorder < Writer > Class to read spikes from neuron groups	288
NeuronModels::SpikeSource Empty neuron which allows setting spikes from external sources	289
NeuronModels::SpikeSourceArray Spike source array	291
SpineMLSimulator::Input::SpikeTime	294
SpikeWriterText Class to write spikes to text file	295

16.1 Class List 65

SpikeWriterTextCached	
Class to write spikes to text file, caching in memory before writing	295
SpineMLSimulator::StateVar< T >	296
WeightUpdateModels::StaticGraded Graded-potential, static synapse	298
WeightUpdateModels::StaticPulse Pulse-coupled, static synapse	300
WeightUpdateModels::StaticPulseDendriticDelay Pulse-coupled, static synapse with heterogenous dendritic delays	301
CodeGenerator::Substitutions	303
pygenn.genn_groups.SynapseGroup Class representing synaptic connection between two groups of neurons	306
SynapseGroup	314
SynapseGroupInternal	327
CodeGenerator::TeeBuf	328
CodeGenerator::TeeStream	329
SpineMLSimulator::Timer	329
Timer A generic timer which can give the current elapsed time	330
TimerAccumulate A timer which adds its elapsed time to an accumulator variable on destruction	331
SpineMLSimulator::TimerAccumulate	332
SpineMLSimulator::InputValue::TimeVarying	332
SpineMLSimulator::InputValue::TimeVaryingArray	333
NeuronModels::TraubMiles Hodgkin-Huxley neurons with Traub & Miles algorithm	334
NeuronModels::TraubMilesAlt Hodgkin-Huxley neurons with Traub & Miles algorithm	337
NeuronModels::TraubMilesFast Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations	339
NeuronModels::TraubMilesNStep Hodgkin-Huxley neurons with Traub & Miles algorithm	341
InitVarSnippet::Uniform Initialises variable by sampling from the uniform distribution	343
SpineMLSimulator::ModelProperty::UniformDistribution	344
InitVarSnippet::Uninitialised Used to mark variables as uninitialised - no initialisation code will be run	345

InitSparseConnectivitySnippet::Uninitialised	
Used to mark connectivity as uninitialised - no initialisation code will be run	345
Snippet::ValueBase < NumVars >	346
Snippet::ValueBase < 0 >	347
SpineMLSimulator::ModelProperty::ValueList	348
Models::Base::Var A variable has a name, a type and an access type	349
pygenn.model_preprocessor.Variable Class holding information about GeNN variables	350
Models::VarInit	352
Models::VarInitContainerBase < NumVars >	353
Models::VarInitContainerBase< 0 >	354
17 File Index	
17.1 File List	
Here is a list of all files with brief descriptions:	
initpy	355
analogueRecorder.h	355
cuda/backend.cc	355
single_threaded_cpu/backend.cc	356
cuda/backend.h	356
single_threaded_cpu/backend.h	357
backendBase.cc	357
backendBase.h	358
backendExport.h	358
binomial.cc	358
binomial.h	359
codeGenUtils.cc	359
codeGenUtils.h	360
codeStream.cc	362
codeStream.h	362
connectors.cc	362
connectors.h	363

17.1 File List 67

currentSource.cc	363
currentSource.h	363
currentSourceInternal.h	364
currentSourceModels.cc	364
currentSourceModels.h	364
generateAll.cc	365
generateAll.h	365
generateInit.cc	366
generateInit.h	366
generateMakefile.cc	366
generateMakefile.h	366
generateMPl.cc Contains functions to generate code for running the simulation with MPl. Part of the code generation section	367
generateMPI.h Contains functions to generate code for running the simulation with MPI. Part of the code generation section	367
generateMSBuild.cc	367
generateMSBuild.h	367
generateNeuronUpdate.cc	368
generateNeuronUpdate.h	368
generateRun.h	368
generateRunner.cc	369
generateRunner.h	369
generateSupportCode.cc	369
generateSupportCode.h	369
generateSynapseUpdate.cc	369
generateSynapseUpdate.h	370
genn_groups.py	370
genn_model.py	370
gennExport.h	37 1
gennUtils.cc	372
gennUtils.h	372
initSparseConnectivitySnippet.cc	373

initSparseConnectivitySnippet.h	373
initVarSnippet.cc	375
initVarSnippet.h	376
input.cc	377
input.h	377
inputValue.cc	377
inputValue.h	378
logOutput.cc	378
logOutput.h	379
logWriter.h	379
model_preprocessor.py	379
modelProperty.cc	380
modelProperty.h	380
models.h	381
modelSpec.cc	382
modelSpec.h	
Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections	
model and the class definition of ModelSpec for defining a neuronal network model. Part of the	
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections	383
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h	383 386
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc	383 386 387
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h	383 386 387 387
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc	383 386 387 387
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc	383 386 387 387 387
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroup.h	383 386 387 387 387 388
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroup.h neuronGroupInternal.h	383 386 387 387 387 388 388
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroup.h neuronGroupInternal.h neuronModels.cc neuronModels.h	383 386 387 387 388 388 388
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroup.h neuronGroupInternal.h neuronModels.cc neuronModels.cc	383 386 387 387 388 388 389 391
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroupInternal.h neuronModels.cc neuronModels.cc neuronModels.h cuda/optimiser.cc	383 386 387 387 388 388 389 391 392
model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections modelSpecInternal.h networkClient.cc networkClient.h neuronGroup.cc neuronGroup.h neuronModels.cc neuronModels.h cuda/optimiser.cc single_threaded_cpu/optimiser.cc cuda/optimiser.h	383 386 387 387 388 388 389 391 392

presynapticUpdateStrategy.cc	395
presynapticUpdateStrategy.h	395
sharedLibraryModel.h	396
simulator.cc	396
simulator.h	396
snippet.h	397
spikeRecorder.h	398
stateVar.h	399
substitutions.h	399
synapseGroup.cc	399
synapseGroup.h	399
synapseGroupInternal.h	400
synapseMatrixType.h	400
teeStream.h	402
include/spineml/simulator/timer.h	402
userproject/include/timer.h	403
utils.h	403
variableMode.h	404
weightUpdateModels.cc	405
weightUpdateModels.h	405

18 Namespace Documentation

18.1 CodeGenerator Namespace Reference

Helper class for generating code - automatically inserts brackets, indents etc.

Namespaces

- CUDA
- SingleThreadedCPU

Classes

- class BackendBase
- class CodeStream
- struct FunctionTemplate
- class MemAlloc
- struct PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

- · class Substitutions
- · class TeeBuf
- · class TeeStream

Functions

void substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

• bool regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

This function substitutes function calls in the form:

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr> void writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr > std::string writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

std::string ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

• void preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postIdx, const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

• void postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &preldx, const std::string &preldx, const std::string &preldx, const std::string &postVarPrefix="", const std::string &postVarSuffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as Ida(&XXX)

void neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &preldx, const std::string &devPrefix, double dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

- GENN_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::CB &cb)
- GENN_EXPORT std::vector< std::string > generateAll (const ModelSpecInternal &model, const Backend←
 Base &backend, const filesystem::path &outputPath, bool standaloneModules=false)
- void generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- void GENN_EXPORT generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector
 std::string > &moduleNames)

A function that generates predominantly MPI infrastructure code.

- void GENN_EXPORT generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)
- void generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- MemAlloc generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)
- void generateSupportCode (CodeStream &os, const ModelSpecInternal &model)
- void generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

18.1.1 Detailed Description

Helper class for generating code - automatically inserts brackets, indents etc.

Based heavily on: https://stackoverflow.com/questions/15053753/writing-a-manipulator-for-a-cus

18.1.2 Function Documentation

18.1.2.1 checkUnreplacedVariables()

This function checks for unknown variable definitions and returns a gennError if any are found.

18.1.2.2 ensureFtype()

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

18.1.2.3 functionSubstitute()

```
void CodeGenerator::functionSubstitute (
    std::string & code,
    const std::string & funcName,
    unsigned int numParams,
    const std::string & replaceFuncTemplate )
```

This function substitutes function calls in the form:

\$(functionName, parameter1, param2Function(0.12, "string"))

with replacement templates in the form:

```
actualFunction(CONSTANT, $(0), $(1))
```

18.1.2.4 generateAll()

18.1.2.7 generateMPI()

A function that generates predominantly MPI infrastructure code.

In this function MPI infrastructure code are generated, including: MPI send and receive functions.

18.1.2.8 generateMSBuild()

```
void CodeGenerator::generateMSBuild (
    std::ostream & os,
    const BackendBase & backend,
    const std::string & projectGUID,
    const std::vector< std::string > & moduleNames )
```

18.1.2.9 generateNeuronUpdate()

18.1.2.10 generateRunner()

```
int localHostID )
```

18.1.2.11 generateSupportCode()

18.1.2.12 generateSynapseUpdate()

18.1.2.13 neuronSubstitutionsInSynapticCode()

```
void CodeGenerator::neuronSubstitutionsInSynapticCode (
    Substitutions & substitutions,
    const SynapseGroupInternal & sg,
    const std::string & preIdx,
    const std::string & postIdx,
    const std::string & devPrefix,
    double dt,
    const std::string & preVarPrefix = "",
    const std::string & preVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarSuffix = "")
```

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as $__ldg(\&XXX)$

Parameters

substitutions	the code string to work on	
sg	the synapse group connecting the pre and postsynaptic neuron populations whose parameters might need to be substituted	
preldx	index of the pre-synaptic neuron to be accessed for _pre variables; differs for different Span)	
postldx	index of the post-synaptic neuron to be accessed for _post variables; differs for different Span)	
devPrefix	device prefix, "dd_" for GPU, nothing for CPU	
dt	simulation timestep (ms)	
preVarPrefix prefix to be used for presynaptic variable accesses - typically combined with suffix to function call such asldg(&XXX)		
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	
postVarPrefix prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrater function call such asldg(&XXX)		
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	

18.1.2.16 postNeuronSubstitutionsInSynapticCode()

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

Parameters

substitutions	the code string to work on	
devPrefix	device prefix, "dd_" for GPU, nothing for CPU	
postVarPrefix	prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)	
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	

18.1.2.17 preNeuronSubstitutionsInSynapticCode()

```
void CodeGenerator::preNeuronSubstitutionsInSynapticCode (
    Substitutions & substitutions,
    const SynapseGroupInternal & sg,
    const std::string & offset,
    const std::string & axonalDelayOffset,
    const std::string & postIdx,
    const std::string & devPrefix,
    const std::string & preVarPrefix = "",
    const std::string & preVarSuffix = "")
```

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

Parameters

substitutions	the code string to work on	
devPrefix	device prefix, "dd_" for GPU, nothing for CPU	
preVarPrefix	prefix to be used for presynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)	
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	

18.1.2.18 regexFuncSubstitute()

```
bool CodeGenerator::regexFuncSubstitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

18.1.2.19 regexVarSubstitute()

```
bool CodeGenerator::regexVarSubstitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

18.1.2.20 substitute()

```
void CodeGenerator::substitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting strings in the neuron code strings or other templates.

18.1.2.21 writePreciseString() [1/2]

This function writes a floating point value to a stream -setting the precision so no digits are lost.

18.1.2.22 writePreciseString() [2/2]

This function writes a floating point value to a string - setting the precision so no digits are lost.

18.2 CodeGenerator::CUDA Namespace Reference

Namespaces

- Optimiser
- PresynapticUpdateStrategy
- Utils

Classes

- · class Backend
- struct Preferences

Preferences for CUDA backend.

Typedefs

using KernelBlockSize = std::array < size_t, KernelMax >
 Array of block sizes for each kernel.

Enumerations

- enum DeviceSelect { DeviceSelect::OPTIMAL, DeviceSelect::MOST_MEMORY, DeviceSelect::MANUAL }
 Methods for selecting CUDA device.
- enum BlockSizeSelect { BlockSizeSelect::OCCUPANCY, BlockSizeSelect::MANUAL }
 - Methods for selecting CUDA kernel block size.
- enum Kernel {

 $Kernel Neuron Update, \quad Kernel Presynaptic Update, \quad Kernel Postsynaptic Update, \quad Kernel Synapse Dynamics \leftarrow Update, \quad Vernel Presynaptic Update, \quad Vernel Pres$

KernelInitialize, KernelInitializeSparse, KernelPreNeuronReset, KernelPreSynapseReset, KernelMax }

Kernels generated by CUDA backend.

18.2.1 Typedef Documentation

18.2.1.1 KernelBlockSize

```
using CodeGenerator::CUDA::KernelBlockSize = typedef std::array<size_t, KernelMax>
```

Array of block sizes for each kernel.

18.2.2 Enumeration Type Documentation

18.2.2.1 BlockSizeSelect

```
enum CodeGenerator::CUDA::BlockSizeSelect [strong]
```

Methods for selecting CUDA kernel block size.

Enumerator

OCCUPANCY	Pick optimal blocksize for each kernel based on occupancy.	
MANUAL	Use block sizes specified by user.	

18.2.2.2 DeviceSelect

enum CodeGenerator::CUDA::DeviceSelect [strong]

Methods for selecting CUDA device.

Enumerator

OPTIMAL	Pick optimal device based on how well kernels can be simultaneously simulated and occupancy.
MOST_MEMORY	Pick device with most global memory.
MANUAL	Use device specified by user.

18.2.2.3 Kernel

enum CodeGenerator::CUDA::Kernel

Kernels generated by CUDA backend.

Enumerator

KernelNeuronUpdate	
KernelPresynapticUpdate	
KernelPostsynapticUpdate	
KernelSynapseDynamicsUpdate	
Kernellnitialize	
KernelInitializeSparse	
KernelPreNeuronReset	
KernelPreSynapseReset	
KernelMax	

18.3 CodeGenerator::CUDA::Optimiser Namespace Reference

Functions

• BACKEND_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

18.3.1 Function Documentation

18.3.1.1 createBackend()

18.4 CodeGenerator::CUDA::PresynapticUpdateStrategy Namespace Reference

Classes

- · class Base
- class PostSpan

Postsynaptic parallelism.

· class PreSpan

Presynaptic parallelism.

18.5 CodeGenerator::CUDA::Utils Namespace Reference

Functions

- size_t ceilDivide (size_t numerator, size_t denominator)
- size_t padSize (size_t size, size_t blockSize)

18.5.1 Function Documentation

18.5.1.1 ceilDivide()

18.6 CodeGenerator::SingleThreadedCPU Namespace Reference

Namespaces

Optimiser

Classes

- · class Backend
- struct Preferences

18.7 CodeGenerator::SingleThreadedCPU::Optimiser Namespace Reference

Functions

BACKEND_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

18.7.1 Function Documentation

18.7.1.1 createBackend()

18.8 CurrentSourceModels Namespace Reference

Classes

· class Base

Base class for all current source models.

class DC

DC source.

· class GaussianNoise

Noisy current source with noise drawn from normal distribution.

18.9 filesystem Namespace Reference

18.10 InitSparseConnectivitySnippet Namespace Reference

Base class for all sparse connectivity initialisation snippets.

Classes

- class Base
- class FixedProbability
- · class FixedProbabilityBase
- class FixedProbabilityNoAutapse
- class Init
- class OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

· class Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

18.10.1 Detailed Description

Base class for all sparse connectivity initialisation snippets.

18.11 InitVarSnippet Namespace Reference

Base class for all value initialisation snippets.

Classes

- · class Base
- class Constant

Initialises variable to a constant value.

class Exponential

Initialises variable by sampling from the exponential distribution.

· class Gamma

Initialises variable by sampling from the exponential distribution.

· class Normal

Initialises variable by sampling from the normal distribution.

class Uniform

Initialises variable by sampling from the uniform distribution.

· class Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

18.11.1 Detailed Description

Base class for all value initialisation snippets.

18.12 Models Namespace Reference

Classes

• class Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

- · class VarInit
- · class VarInitContainerBase
- class VarInitContainerBase< 0 >

18.12.1 Detailed Description

Class used to bind together everything required to initialise a variable:

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

18.13 NeuronModels Namespace Reference

Classes

· class Base

Base class for all neuron models.

· class Izhikevich

Izhikevich neuron with fixed parameters [1].

· class IzhikevichVariable

Izhikevich neuron with variable parameters [1].

- · class LIF
- · class Poisson

Poisson neurons.

class PoissonNew

Poisson neurons.

class RulkovMap

Rulkov Map neuron.

class SpikeSource

Empty neuron which allows setting spikes from external sources.

class SpikeSourceArray

Spike source array.

class TraubMiles

Hodgkin-Huxley neurons with Traub & Miles algorithm.

class TraubMilesAlt

Hodgkin-Huxley neurons with Traub & Miles algorithm.

class TraubMilesFast

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

· class TraubMilesNStep

Hodgkin-Huxley neurons with Traub & Miles algorithm.

18.14 PostsynapticModels Namespace Reference

Classes

· class Base

Base class for all postsynaptic models.

class DeltaCurr

Simple delta current synapse.

class ExpCond

Exponential decay with synaptic input treated as a conductance value.

class ExpCurr

Exponential decay with synaptic input treated as a current value.

18.15 pugi Namespace Reference

18.16 pygenn Namespace Reference

Namespaces

- genn_groups
- genn_model
- model_preprocessor

18.17 pygenn.genn_groups Namespace Reference

Classes

· class CurrentSource

Class representing a current injection into a group of neurons.

class Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

class NeuronGroup

Class representing a group of neurons.

class SynapseGroup

Class representing synaptic connection between two groups of neurons.

Variables

• xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

18.17.1 Variable Documentation

18.17.1.1 xrange

```
pygenn.genn_groups.xrange = range
```

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

18.18 pygenn.genn model Namespace Reference

Classes

· class GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

Functions

• def init var (init var snippet, param space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

def init_connectivity (init_sparse_connect_snippet, param_space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def create_custom_neuron_class (class_name, param_names=None, var_name_types=None, derived_
 params=None, sim_code=None, threshold_condition_code=None, reset_code=None, support_code=None,
 extra_global_params=None, additional_input_vars=None, is_auto_refractory_required=None, custom_
 body=None)

This helper function creates a custom NeuronModel class.

def create_custom_postsynaptic_class (class_name, param_names=None, var_name_types=None, derived_params=None, decay_code=None, apply_input_code=None, support_code=None, custom_
 body=None)

This helper function creates a custom PostsynapticModel class.

def create_custom_weight_update_class (class_name, param_names=None, var_name_types=None, pre
 _var_name_types=None, post_var_name_types=None, derived_params=None, sim_code=None, event
 _code=None, learn_post_code=None, synapse_dynamics_code=None, event_threshold_condition_
 code=None, pre_spike_code=None, post_spike_code=None, sim_support_code=None, learn_post_
 support_code=None, synapse_dynamics_suppport_code=None, extra_global_params=None, is_pre_
 spike time required=None, is post spike time required=None, custom body=None)

This helper function creates a custom WeightUpdateModel class.

def create_custom_current_source_class (class_name, param_names=None, var_name_types=None, derived_params=None, injection_code=None, extra_global_params=None, custom_body=None)

This helper function creates a custom NeuronModel class.

def create_custom_model_class (class_name, base, param_names, var_name_types, derived_params, custom_body)

This helper function completes a custom model class creation.

def create_dpf_class (dp_func)

Helper function to create derived parameter function class.

def create_cmlf_class (cml_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

def create_custom_init_var_snippet_class (class_name, param_names=None, derived_params=None, var
 __init_code=None, custom_body=None)

This helper function creates a custom InitVarSnippet class.

def create_custom_sparse_connect_init_snippet_class (class_name, param_names=None, derived_
 params=None, row_build_code=None, row_build_state_vars=None, calc_max_row_len_func=None, calc_
 max_col_len_func=None, extra_global_params=None, custom_body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

Variables

- backend_modules = OrderedDict()
- m = import_module(".genn_wrapper." + b + "Backend", "pygenn")

18.18.1 Function Documentation

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

Parameters

```
cml_func a function which computes the length and takes three args "num_pre" (unsigned int), "num_post" (unsigned int) and "pars" (vector of double)
```

18.18.1.2 create_custom_current_source_class()

This helper function creates a custom NeuronModel class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc
injection_code	string with the current injection code
extra_global_params	list of pairs of strings with names and types of additional parameters
custom_body	dictionary with additional attributes and methods of the new class

18.18.1.3 create_custom_init_var_snippet_class()

This helper function creates a custom InitVarSnippet class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class	
param_names	list of strings with param names of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the pygenn.genn_wrapper.DerivedParamFunc' class	
var_init_code	string with the variable initialization code	
custom_body	dictionary with additional attributes and methods of the new class	

18.18.1.4 create_custom_model_class()

```
def pygenn.genn_model.create_custom_model_class (
```

```
class_name,
base,
param_names,
var_name_types,
derived_params,
custom_body )
```

This helper function completes a custom model class creation.

This part is common for all model classes and is nearly useless on its own unless you specify custom_body.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class	
base	base class	
param_names	list of strings with param names of the model	
var_name_types	list of pairs of strings with varible names and types of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from the pygenn.genn_wrapper.DerivedParamFunc class	
custom_body	dictionary with attributes and methods of the new class	

18.18.1.5 create_custom_neuron_class()

This helper function creates a custom NeuronModel class.

See also

```
create_custom_postsynaptic_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.Snippet.DerivedParamFunc
sim_code	string with the simulation code
threshold_condition_code	string with the threshold condition code
reset_code	string with the reset code
support_code	string with the support code
extra_global_params	list of pairs of strings with names and types of additional parameters
additional_input_vars	list of tuples with names and types as strings and initial values of additional local input variables
is_auto_refractory_required	does this model require auto-refractory logic to be generated?
custom_body	dictionary with additional attributes and methods of the new class

18.18.1.6 create_custom_postsynaptic_class()

This helper function creates a custom PostsynapticModel class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.DerivedParamFunc
decay_code	string with the decay code
apply_input_code	string with the apply input code
support_code	string with the support code
custom_body	dictionary with additional attributes and methods of the new class

18.18.1.7 create_custom_sparse_connect_init_snippet_class()

This helper function creates a custom InitSparseConnectivitySnippet class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc
row_build_code	string with row building initialization code
row_build_state_vars	list of tuples of state variables, their types and their initial values to use across row building loop
calc_max_row_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum row length of synaptic matrix
calc_max_col_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum col length of synaptic matrix
extra_global_params	list of pairs of strings with names and types of additional parameters
custom_body	dictionary with additional attributes and methods of the new class

18.18.1.8 create_custom_weight_update_class()

```
event_threshold_condition_code = None,
pre_spike_code = None,
post_spike_code = None,
sim_support_code = None,
learn_post_support_code = None,
synapse_dynamics_suppport_code = None,
extra_global_params = None,
is_pre_spike_time_required = None,
is_post_spike_time_required = None,
custom_body = None )
```

This helper function creates a custom WeightUpdateModel class.

See also

```
create_custom_neuron_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with variable names and types of the model
pre_var_name_types	list of pairs of strings with presynaptic variable names and types of the model
post_var_name_types	list of pairs of strings with postsynaptic variable names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.DerivedParamFunc
sim_code	string with the simulation code
event_code	string with the event code
learn_post_code	string with the code to include in learn_synapse_post kernel/function
synapse_dynamics_code	string with the synapse dynamics code
event_threshold_condition_code	string with the event threshold condition code
pre_spike_code	string with the code run once per spiking presynaptic neuron
post_spike_code	string with the code run once per spiking postsynaptic neuron
sim_support_code	string with simulation support code
learn_post_support_code	string with support code for learn_synapse_post kernel/function
synapse_dynamics_suppport_code	string with synapse dynamics support code
extra_global_params	list of pairs of strings with names and types of additional parameters
is_pre_spike_time_required	boolean, is presynaptic spike time required in any weight update kernels?
is_post_spike_time_required	boolean, is postsynaptic spike time required in any weight update kernels?
custom_body	dictionary with additional attributes and methods of the new class

18.18.1.9 create_dpf_class()

```
def pygenn.genn_model.create_dpf_class (
```

```
dp_func )
```

Helper function to create derived parameter function class.

Parameters

dp_	func	a function which computes the derived parameter and takes two args "pars" (vector of double) and	
		"dt" (double)	

18.18.1.10 init_connectivity()

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

Parameters

init_sparse_connect_snippet	type of the InitSparseConnectivitySnippet class as string or instance of class derived from InitSparseConnectivitySnippet::Custom.
param_space	dict with param values for the InitSparseConnectivitySnippet class

18.18.1.11 init_var()

This helper function creates a VarInit object to easily initialise a variable using a snippet.

Parameters

init_var_snippet	type of the InitVarSnippet class as string or instance of class derived from InitVarSnippet::Custom class.
param_space	dict with param values for the InitVarSnippet class

18.18.2 Variable Documentation

18.18.2.1 backend_modules

```
pygenn.genn_model.backend_modules = OrderedDict()

18.18.2.2 m

pygenn.genn_model.m = import_module(".genn_wrapper." + b + "Backend", "pygenn")
```

18.19 pygenn.model_preprocessor Namespace Reference

Classes

· class ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

class Variable

Class holding information about GeNN variables.

Functions

def prepare_model (model, param_space, var_space, pre_var_space=None, post_var_space=None, model family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

def prepare_snippet (snippet, param_space, snippet_family)

Prepare a snippet by checking its validity and extracting information about parameters.

• def is model valid (model, model family)

Check whether the model is valid, i.e is native or derived from model_family.Custom.

def param_space_to_vals (model, param_space)

Convert a param_space dict to ParamValues.

def param_space_to_val_vec (model, param_space)

Convert a param_space dict to a std::vector<double>

def var_space_to_vals (model, var_space)

Convert a var_space dict to VarValues.

def pre_var_space_to_vals (model, var_space)

Convert a var_space dict to PreVarValues.

def post_var_space_to_vals (model, var_space)

Convert a var_space dict to PostVarValues.

Variables

dictionary genn_to_numpy_types

18.19.1 Function Documentation

18.19.1.1 is_model_valid()

Check whether the model is valid, i.e is native or derived from model_family.Custom.

Parameters

model	string or instance of model_family.Custom	
model_family	model family (NeuronModels, WeightUpdateModels or PostsynapticModels) to which model	
	should belong to	

Returns

instance of the model and its type as string

Raises ValueError if model is not valid (i.e. is not custom and is not natively available)

```
18.19.1.2 param_space_to_val_vec()
```

Convert a param_space dict to a std::vector<double>

Parameters

model	instance of the model
param_space	dict with parameters

Returns

native vector of parameters

18.19.1.3 param_space_to_vals()

Convert a param_space dict to ParamValues.

Parameters

model	instance of the model
param_space	dict with parameters

Returns

native model's ParamValues

18.19.1.4 post_var_space_to_vals()

Convert a var_space dict to PostVarValues.

Parameters

model	instance of the weight update model
var_space	dict with Variables

Returns

native model's VarValues

18.19.1.5 pre_var_space_to_vals()

Convert a var_space dict to PreVarValues.

Parameters

model	instance of the weight update model
var_space	dict with Variables

Returns

native model's VarValues

18.19.1.6 prepare_model()

Prepare a model by checking its validity and extracting information about variables and parameters.

Parameters

model	string or instance of a class derived from
	pygenn.genn_wrapper.NeuronModels.Custom or
	pygenn.genn_wrapper.WeightUpdateModels.Custom or
	pygenn.genn_wrapper.CurrentSourceModels.Custom
param_space	dict with model parameters
var_space	dict with model variables
pre_var_space	optional dict with (weight update) model presynaptic variables
post_var_space	optional dict with (weight update) model postsynaptic variables
model_family	pygenn.genn_wrapper.NeuronModels or
	pygenn.genn_wrapper.WeightUpdateModels or
	pygenn.genn_wrapper.CurrentSourceModels

Returns

tuple consisting of (model instance, model type, model parameter names, model parameters, list of variable names, dict mapping names of variables to instances of class Variable)

18.19.1.7 prepare_snippet()

Prepare a snippet by checking its validity and extracting information about parameters.

Parameters

snippet	string or instance of a class derived from	
	pygenn.genn_wrapper.InitVarSnippet.Customor	
	pygenn.genn_wrapper.InitSparseConnectivitySnippet.Custom	
param_space	dict with model parameters	
snippet_family	pygenn.genn_wrapper.InitVarSnippet or	
	pygenn.genn_wrapper.InitSparseConnectivitySnippet	

Returns

tuple consisting of (snippet instance, snippet type, snippet parameter names, snippet parameters)

18.19.1.8 var_space_to_vals()

Convert a var_space dict to VarValues.

Parameters

model	instance of the model
var_space	dict with Variables

Returns

native model's VarValues

18.19.2 Variable Documentation

18.19.2.1 genn_to_numpy_types

dictionary pygenn.model_preprocessor.genn_to_numpy_types

Initial value:

18.20 Snippet Namespace Reference

Classes

· class Base

Base class for all code snippets.

- · class Init
- class ValueBase
- class ValueBase< 0 >

18.20.1 Detailed Description

Wrapper to ensure at compile time that correct number of values are used when specifying the values of a model's parameters and initial state.

18.21 SpineMLSimulator Namespace Reference

Namespaces

- Connectors
- Input
- InputValue
- LogOutput
- ModelProperty

Classes

- class NetworkClient
- class Simulator
- class StateVar
- class Timer
- · class TimerAccumulate

Typedefs

· typedef float scalar

18.21.1 Typedef Documentation

18.21.1.1 scalar

typedef float SpineMLSimulator::scalar

18.22 SpineMLSimulator::Connectors Namespace Reference

Functions

 unsigned int create (const pugi::xml_node &node, double dt, unsigned int numPre, unsigned int numPost, unsigned int **rowLength, unsigned int **ind, uint8_t **delay, const unsigned int *maxRowLength, const filesystem::path &basePath, std::vector< unsigned int > &remapIndices)

18.22.1 Function Documentation

18.22.1.1 create()

18.23 SpineMLSimulator::Input Namespace Reference

Classes

- class Analogue
- class Base
- · class InterSpikeIntervalBase
- · class PoissonSpikeRate
- · class RegularSpikeRate
- · class SpikeBase
- class SpikeTime

18.24 SpineMLSimulator::InputValue Namespace Reference

Classes

- class Base
- class Constant
- class ConstantArray
- class External
- class ExternalNetwork
- · class ScalarBase
- · class TimeVarying
- class TimeVaryingArray

Functions

std::unique_ptr< Base > create (double dt, unsigned int numNeurons, const pugi::xml_node &node, std
 ::map< std::string, InputValue::External *> &externalInputs)

18.24.1 Function Documentation

18.24.1.1 create()

18.25 SpineMLSimulator::LogOutput Namespace Reference

Classes

- · class AnalogueBase
- · class AnalogueExternal
- · class AnalogueFile
- class AnalogueNetwork
- · class Base
- · class Event

18.26 SpineMLSimulator::ModelProperty Namespace Reference

Classes

- · class Base
- · class ExponentialDistribution
- class Fixed
- · class NormalDistribution
- · class UniformDistribution
- · class ValueList

Functions

std::unique_ptr< Base > create (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size, bool skipGeNNInitialised, const filesystem::path &basePath, const std::string &value
 Namespace, const std::vector< unsigned int > *remapIndices)

18.26.1 Function Documentation

18.26.1.1 create()

18.27 Utils Namespace Reference

Functions

GENN_EXPORT bool isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN EXPORT bool isInitRNGRequired (const std::vector < Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

GENN_EXPORT bool isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN_EXPORT std::string getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

18.27.1 Function Documentation

18.27.1.1 getUnderlyingType()

Assuming type is a string containing a pointer type, function to return the underlying type.

18.27.1.2 isInitRNGRequired()

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

18.27.1.3 isRNGRequired()

Does the code string contain any functions requiring random number generator.

18.27.1.4 isTypePointer()

Function to determine whether a string containing a type is a pointer.

18.28 WeightUpdateModels Namespace Reference

Classes

· class Base

Base class for all weight update models.

• class PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

class StaticGraded

Graded-potential, static synapse.

class StaticPulse

Pulse-coupled, static synapse.

class StaticPulseDendriticDelay

Pulse-coupled, static synapse with heterogenous dendritic delays.

19 Class Documentation

19.1 SpineMLSimulator::Input::Analogue Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::Analogue:

```
SpineMLSimulator::Input::Base

SpineMLSimulator::Input::Analogue
```

Public Member Functions

- virtual void apply (double dt, unsigned long long timestep) override

Additional Inherited Members

19.1.1 Constructor & Destructor Documentation

19.1.1.1 Analogue()

19.1.2 Member Function Documentation

19.1.2.1 apply()

Implements SpineMLSimulator::Input::Base.


The documentation for this class was generated from the following files:

- input.h
- · input.cc

19.2 SpineMLSimulator::LogOutput::AnalogueBase Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueBase:



Public Member Functions

- AnalogueBase (const pugi::xml_node &node, double dt, const ModelProperty::Base *modelProperty)
- const scalar * getStateVarBegin () const
- const scalar * getStateVarEnd () const
- unsigned int getModelPropertySize () const
- const std::vector< unsigned int > & getIndices () const

Protected Member Functions

· void pullModelPropertyFromDevice () const

19.2.1 Constructor & Destructor Documentation

19.2.1.1 AnalogueBase()

19.2.2 Member Function Documentation

19.2.2.1 getIndices()

```
const std::vector<unsigned int>& SpineMLSimulator::LogOutput::AnalogueBase::getIndices ( )
const [inline]
```

19.2.2.2 getModelPropertySize()

unsigned int SpineMLSimulator::LogOutput::AnalogueBase::getModelPropertySize () const [inline]

19.2.2.3 getStateVarBegin()

const scalar* SpineMLSimulator::LogOutput::AnalogueBase::getStateVarBegin () const [inline]

19.2.2.4 getStateVarEnd()

const scalar* SpineMLSimulator::LogOutput::AnalogueBase::getStateVarEnd () const [inline]

19.2.2.5 pullModelPropertyFromDevice()

void SpineMLSimulator::LogOutput::AnalogueBase::pullModelPropertyFromDevice () const [inline],
[protected]


The documentation for this class was generated from the following files:

- logOutput.h
- logOutput.cc

19.3 SpineMLSimulator::LogOutput::AnalogueExternal Class Reference

#include <logOutput.h>

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Log Output:: Analogue External:$



Public Member Functions

- AnalogueExternal (const pugi::xml_node &node, double dt, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)
- · virtual void record (double dt, unsigned long long timestep) final

Protected Member Functions

• virtual void recordInternal ()

19.3.1 Constructor & Destructor Documentation

19.3.1.1 AnalogueExternal()

19.3.2 Member Function Documentation

19.3.2.1 record()

```
void SpineMLSimulator::LogOutput::AnalogueExternal::record ( \label{eq:double} \ dt, \label{eq:double} \ unsigned \ long \ long \ timestep \ ) \ \ [final], \ [virtual]
```

Implements SpineMLSimulator::LogOutput::Base.

19.3.2.2 recordinternal()

```
virtual void SpineMLSimulator::LogOutput::AnalogueExternal::recordInternal ( ) [inline],
[protected], [virtual]
```

Reimplemented in SpineMLSimulator::LogOutput::AnalogueNetwork.


The documentation for this class was generated from the following files:

- logOutput.h
- · logOutput.cc

19.4 SpineMLSimulator::LogOutput::AnalogueFile Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueFile:



Public Member Functions

- AnalogueFile (const pugi::xml_node &node, double dt, unsigned long long numTimeSteps, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)
- · virtual void record (double dt, unsigned long long timestep) override

Additional Inherited Members

19.4.1 Constructor & Destructor Documentation

19.4.1.1 AnalogueFile()

19.4.2 Member Function Documentation

19.4.2.1 record()

Implements SpineMLSimulator::LogOutput::Base.

The documentation for this class was generated from the following files:

- logOutput.h
- · logOutput.cc

19.5 SpineMLSimulator::LogOutput::AnalogueNetwork Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueNetwork:

```
SpineMLSimulator::LogOutput::Base

SpineMLSimulator::LogOutput::AnalogueBase

SpineMLSimulator::LogOutput::AnalogueExternal

SpineMLSimulator::LogOutput::AnalogueNetwork
```

Public Member Functions

 AnalogueNetwork (const pugi::xml_node &node, double dt, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)

Protected Member Functions

· virtual void recordInternal () override

19.5.1 Constructor & Destructor Documentation

19.5.1.1 AnalogueNetwork()

19.5.2 Member Function Documentation

19.5.2.1 recordinternal()

```
void SpineMLSimulator::LogOutput::AnalogueNetwork::recordInternal ( ) [override], [protected],
[virtual]
```

Reimplemented from SpineMLSimulator::LogOutput::AnalogueExternal.

The documentation for this class was generated from the following files:

- logOutput.h
- logOutput.cc

19.6 AnalogueRecorder < T > Class Template Reference

```
#include <analogueRecorder.h>
```

Public Member Functions

- AnalogueRecorder (const std::string &filename, std::initializer_list< T *> variables, unsigned int popSize, const std::string &delimiter="")
- AnalogueRecorder (const std::string &filename, T *variable, unsigned int popSize, const std::string &delimiter="")
- void record (double t)

19.6.1 Constructor & Destructor Documentation

19.6.1.1 AnalogueRecorder() [1/2]

```
unsigned int popSize,
const std::string & delimiter = " ") [inline]
```

19.6.1.2 AnalogueRecorder() [2/2]

19.6.2 Member Function Documentation

19.6.2.1 record()

```
\label{template} \begin{tabular}{ll} template < typename T > \\ void Analogue Recorder < T >:: record ( \\ double t ) [inline] \end{tabular}
```


The documentation for this class was generated from the following file:

· analogueRecorder.h

19.7 CodeGenerator::CUDA::Backend Class Reference

```
#include <backend.h>
```

Inheritance diagram for CodeGenerator::CUDA::Backend:



Public Member Functions

- Backend (const KernelBlockSize &kernelBlockSizes, const Preferences &preferences, int localHostID, const std::string &scalarType, int device)
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
 Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const override

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const
 override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG←
 Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse←
 GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- virtual void genDefinitionsPreamble (CodeStream &os) const override

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

· virtual void genDefinitionsInternalPreamble (CodeStream &os) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- · virtual void genRunnerPreamble (CodeStream &os) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const override
- · virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const override

Generate code for pushing a variable to the 'device'.

• virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const override

Generate code for pulling a variable from the 'device'.

• virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pushing a variable's value in the current timestep to the 'device'.

 virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pulling a variable's value in the current timestep from the 'device'.

- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

• virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const override
- virtual MemAlloc genPopulationRNG (CodeStream &definitions, CodeStream &definitionsInternal, Code
 Stream &runner, CodeStream &allocations, CodeStream &free, const std::string &name, size_t count) const override
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override
- virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const override
- virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- · virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

virtual bool isSynRemapRequired () const override

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const override

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

virtual size_t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

- const cudaDeviceProp & getChosenCUDADevice () const
- int getChosenDeviceID () const
- int getRuntimeVersion () const
- std::string getNVCCFlags () const
- std::string getFloatAtomicAdd (const std::string &ftype) const
- size_t getKernelBlockSize (Kernel kernel) const

Static Public Member Functions

- static size_t getNumPresynapticUpdateThreads (const SynapseGroupInternal &sg)
- static size_t getNumPostsynapticUpdateThreads (const SynapseGroupInternal &sg)
- static size_t getNumSynapseDynamicsThreads (const SynapseGroupInternal &sg)
- static void addPresynapticUpdateStrategy (PresynapticUpdateStrategy::Base *strategy)

Register a new presynaptic update strategy.

Static Public Attributes

static const char * KernelNames [KernelMax]

Additional Inherited Members

19.7.1 Constructor & Destructor Documentation

19.7.1.1 Backend()

19.7.2 Member Function Documentation

19.7.2.1 addPresynapticUpdateStrategy()

Register a new presynaptic update strategy.

This function should be called with strategies in ascending order of preference

19.7.2.2 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

19.7.2.3 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.4 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.5 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.6 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.7 genCurrentVariablePull()

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.8 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.9 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

19.7.2.10 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

19.7.2.11 genExtraGlobalParamAllocation()

Implements CodeGenerator::BackendBase.

19.7.2.12 genExtraGlobalParamDefinition()

Implements CodeGenerator::BackendBase.

19.7.2.13 genExtraGlobalParamImplementation()

Implements CodeGenerator::BackendBase.

19.7.2.14 genExtraGlobalParamPull()

Implements CodeGenerator::BackendBase.

19.7.2.15 genExtraGlobalParamPush()

Implements CodeGenerator::BackendBase.

19.7.2.16 genGlobalRNG()

Implements CodeGenerator::BackendBase.

19.7.2.17 genInit()

Implements CodeGenerator::BackendBase.

19.7.2.18 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html _ node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

19.7.2.19 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

19.7.2.20 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

19.7.2.21 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

19.7.2.22 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties for more information.

Implements CodeGenerator::BackendBase.

19.7.2.23 genMSBuildImportProps()

Implements CodeGenerator::BackendBase.

19.7.2.24 genMSBuildImportTarget()

Implements CodeGenerator::BackendBase.

19.7.2.25 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items#item-definitions
for more information

Implements CodeGenerator::BackendBase.

19.7.2.26 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

19.7.2.27 genPopulationRNG()

Implements CodeGenerator::BackendBase.

19.7.2.28 genPopVariableInit()

Implements CodeGenerator::BackendBase.

19.7.2.29 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

19.7.2.30 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

19.7.2.31 genSynapseUpdate()

```
const ModelSpecInternal & model,
SynapseGroupHandler wumThreshHandler,
SynapseGroupHandler wumSimHandler,
SynapseGroupHandler wumEventHandler,
SynapseGroupHandler postLearnHandler,
SynapseGroupHandler synapseDynamicsHandler ) const [override], [virtual]
```

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes. "id_pre", "id_post" and "id_syn" variables will be provided to callback via Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implements CodeGenerator::BackendBase.

19.7.2.32 genSynapseVariableRowInit()

Implements CodeGenerator::BackendBase.

19.7.2.33 genTimer()

Implements CodeGenerator::BackendBase.

19.7.2.34 genVariableAllocation()

Implements CodeGenerator::BackendBase.

19.7.2.35 genVariableDefinition()

Implements CodeGenerator::BackendBase.

19.7.2.36 genVariableFree()

Implements CodeGenerator::BackendBase.

19.7.2.37 genVariableImplementation()

Implements CodeGenerator::BackendBase.

19.7.2.38 genVariableInit()

Implements CodeGenerator::BackendBase.

19.7.2.39 genVariablePull()

Generate code for pulling a variable from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.40 genVariablePush()

Generate code for pushing a variable to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.41 getChosenCUDADevice()

```
const cudaDeviceProp& CodeGenerator::CUDA::Backend::getChosenCUDADevice ( ) const [inline]
```

19.7.2.42 getChosenDeviceID()

```
int CodeGenerator::CUDA::Backend::getChosenDeviceID ( ) const [inline]
```

19.7.2.43 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::CUDA::Backend::getDeviceMemoryBytes ( ) const [inline], [override],
[virtual]
```

How many bytes of memory does 'device' have.

Implements CodeGenerator::BackendBase.

19.7.2.44 getFloatAtomicAdd()

19.7.2.45 getKernelBlockSize()

19.7.2.46 getNumPostsynapticUpdateThreads()

```
size_t CodeGenerator::CUDA::Backend::getNumPostsynapticUpdateThreads ( const SynapseGroupInternal & sg ) [static]
```

19.7.2.47 getNumPresynapticUpdateThreads()

19.7.2.48 getNumSynapseDynamicsThreads()

19.7.2.49 getNVCCFlags()

```
std::string CodeGenerator::CUDA::Backend::getNVCCFlags ( ) const
```

19.7.2.50 getRuntimeVersion()

```
int CodeGenerator::CUDA::Backend::getRuntimeVersion ( ) const [inline]
```

19.7.2.51 getVarPrefix()

```
virtual std::string CodeGenerator::CUDA::Backend::getVarPrefix ( ) const [inline], [override],
[virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

19.7.2.52 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

19.7.2.53 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isPostsynapticRemapRequired ( ) const [inline],
[override], [virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implements CodeGenerator::BackendBase.

19.7.2.54 isSynRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isSynRemapRequired ( ) const [inline], [override],
[virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

Implements CodeGenerator::BackendBase.

19.7.3 Member Data Documentation

19.7.3.1 KernelNames

```
const char * CodeGenerator::CUDA::Backend::KernelNames [static]
```

Initial value:

```
= {
    "updateNeuronsKernel",
    "updatePresynapticKernel",
    "updatePostsynapticKernel",
    "updateSynapseDynamicsKernel",
    "initializeKernel",
    "initializeSparseKernel",
    "preNeuronResetKernel",
    "preSynapseResetKernel"}
```


The documentation for this class was generated from the following files:

- · cuda/backend.h
- cuda/backend.cc

19.8 CodeGenerator::SingleThreadedCPU::Backend Class Reference

```
#include <backend.h>
```

 $Inheritance\ diagram\ for\ CodeGenerator :: Single Threaded CPU :: Backend:$



Public Member Functions

- Backend (int localHostID, const std::string &scalarType, const Preferences &preferences)

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG
 Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse
 GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- virtual void genDefinitionsPreamble (CodeStream &os) const override

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

virtual void genDefinitionsInternalPreamble (CodeStream &os) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- · virtual void genRunnerPreamble (CodeStream &os) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const override
- virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamDefinition (CodeStream &definitions, const std::string &type, const std
 ::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const override

Generate code for pushing a variable to the 'device'.

• virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const override

Generate code for pulling a variable from the 'device'.

 virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pushing a variable's value in the current timestep to the 'device'.

 virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pulling a variable's value in the current timestep from the 'device'.

- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override
 Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override
 - Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const override
- virtual MemAlloc genPopulationRNG (CodeStream &definitions, CodeStream &definitionsInternal, Code
 Stream &runner, CodeStream &allocations, CodeStream &free, const std::string &name, size_t count) const override
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override
- virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const override
- virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- · virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- · virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

• virtual bool isSynRemapRequired () const override

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const override

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

virtual size_t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

Additional Inherited Members

19.8.1 Constructor & Destructor Documentation

19.8.1.1 Backend()

19.8.2 Member Function Documentation

19.8.2.1 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

19.8.2.2 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.3 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.4 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.5 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.6 genCurrentVariablePull()

```
VarLocation loc ) const [override], [virtual]
```

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.7 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.8 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

19.8.2.9 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

19.8.2.10 genExtraGlobalParamAllocation()

Implements CodeGenerator::BackendBase.

19.8.2.11 genExtraGlobalParamDefinition()

```
122
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.12 genExtraGlobalParamImplementation()
void CodeGenerator::SingleThreadedCPU::Backend::genExtraGlobalParamImplementation (
            CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.13 genExtraGlobalParamPull()
CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.14 genExtraGlobalParamPush()
```

Implements CodeGenerator::BackendBase.

19.8.2.15 genGlobalRNG()

Implements CodeGenerator::BackendBase.

19.8.2.16 genInit()

```
SynapseGroupHandler sgDenseInitHandler,
SynapseGroupHandler sgSparseConnectHandler,
SynapseGroupHandler sgSparseInitHandler) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

19.8.2.17 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/htmle_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

19.8.2.18 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

19.8.2.19 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

19.8.2.20 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

19.8.2.21 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties for more information.

Implements CodeGenerator::BackendBase.

19.8.2.22 genMSBuildImportProps()

```
\label{local_code_generator} \mbox{void CodeGenerator::SingleThreadedCPU::Backend::genMSBuildImportProps (} \\ \mbox{std::ostream \& os ) const [override], [virtual] \\ \mbox{}
```

Implements CodeGenerator::BackendBase.

19.8.2.23 genMSBuildImportTarget()

Implements CodeGenerator::BackendBase.

19.8.2.24 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

 $\textbf{see} \ \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items\#item-definitions} \\ \textbf{for more information.}$

Implements CodeGenerator::BackendBase.

19.8.2.25 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

19.8.2.26 genPopulationRNG()

```
const std::string & name,
size_t count ) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

19.8.2.27 genPopVariableInit()

Implements CodeGenerator::BackendBase.

19.8.2.28 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

19.8.2.29 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

19.8.2.30 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Parameters

postLearnHandler	callback to write platform-independent code to process postsynaptic spikes.
	"id_pre", "id_post" and "id_syn" variables will be provided to callback via
	Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse
	dynamics. "id_pre", "id_post" and "id_syn" variables; and either
	"addToInSynDelay" or "addToInSyn" function will be provided to callback via
	Substitutions.

Implements CodeGenerator::BackendBase.

19.8.2.31 genSynapseVariableRowInit()

Implements CodeGenerator::BackendBase.

19.8.2.32 genTimer()

Implements CodeGenerator::BackendBase.

19.8.2.33 genVariableAllocation()

Implements CodeGenerator::BackendBase.

19.8.2.34 genVariableDefinition()

```
VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.35 genVariableFree()
\verb|void CodeGenerator::SingleThreadedCPU::Backend::genVariableFree | (
            CodeStream & os,
             const std::string & name,
             VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.36 genVariableImplementation()
CodeStream & os,
            const std::string & type,
             const std::string & name,
             VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.37 genVariableInit()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableInit (
            CodeStream & os,
            VarLocation loc,
             size_t count,
             const std::string & indexVarName,
             const Substitutions & kernelSubs,
             Handler handler ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.38 genVariablePull()
void CodeGenerator::SingleThreadedCPU::Backend::genVariablePull (
            CodeStream & os,
             const std::string & type,
             const std::string & name,
             VarLocation loc,
             size_t count ) const [override], [virtual]
Generate code for pulling a variable from the 'device'.
Implements CodeGenerator::BackendBase.
19.8.2.39 genVariablePush()
void CodeGenerator::SingleThreadedCPU::Backend::genVariablePush (
            CodeStream & os,
             const std::string & type,
```

const std::string & name,

VarLocation loc.

```
bool autoInitialized,
size_t count ) const [override], [virtual]
```

Generate code for pushing a variable to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.40 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::SingleThreadedCPU::Backend::getDeviceMemoryBytes ( ) const [inline],
[override], [virtual]
```

How many bytes of memory does 'device' have.

Implements CodeGenerator::BackendBase.

19.8.2.41 getVarPrefix()

```
virtual std::string CodeGenerator::SingleThreadedCPU::Backend::getVarPrefix ( ) const [inline],
[override], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

19.8.2.42 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

19.8.2.43 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::SingleThreadedCPU::Backend::isPostsynapticRemapRequired ( ) const
[inline], [override], [virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implements CodeGenerator::BackendBase.

19.8.2.44 isSynRemapRequired()

```
virtual bool CodeGenerator::SingleThreadedCPU::Backend::isSynRemapRequired ( ) const [inline],
[override], [virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

Implements CodeGenerator::BackendBase.

The documentation for this class was generated from the following files:


• single_threaded_cpu/backend.h

single_threaded_cpu/backend.cc

19.9 CodeGenerator::BackendBase Class Reference

#include <backendBase.h>

Inheritance diagram for CodeGenerator::BackendBase:



Public Types

- typedef std::function< void(CodeStream &, Substitutions &)> Handler
- template < typename T >
 using GroupHandler = std::function < void(CodeStream &, const T &, Substitutions &) >
- typedef GroupHandler< NeuronGroupInternal > NeuronGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron Group to.

- typedef GroupHandler < SynapseGroupInternal > SynapseGroupHandler
 - Standard callback type which provides a CodeStream to write platform-independent code for the specified Synapse-Group to.
- typedef std::function< void(CodeStream &, const NeuronGroupInternal &, Substitutions &, NeuronGroup

 Handler, NeuronGroupHandler)> NeuronGroupSimHandler

Callback function type for generation neuron group simulation code.

Public Member Functions

- BackendBase (int localHostID, const std::string &scalarType)
- virtual ∼BackendBase ()
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
 Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const =0

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const
 =0

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG← Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse← GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const =0
- virtual void genDefinitionsPreamble (CodeStream &os) const =0

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file

- virtual void genDefinitionsInternalPreamble (CodeStream &os) const =0
 - Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.
- virtual void genRunnerPreamble (CodeStream &os) const =0
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const =0
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const =0

After all timestep logic is complete.

- virtual void genVariableDefinition (CodeStream &definitions, CodeStream &definitionsInternal, const std
 ::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const =0
- virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const =0

Generate code for pushing a variable to the 'device'.

• virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const =0

Generate code for pulling a variable from the 'device'.

 virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const =0

Generate code for pushing a variable's value in the current timestep to the 'device'.

 virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const =0

Generate code for pulling a variable's value in the current timestep from the 'device'.

- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const =0
 - Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const =0

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const =0
- Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

 virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const =0

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const =0
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const =0
- virtual void genMakefilePreamble (std::ostream &os) const =0

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const =0
- virtual void genMakefileCompileRule (std::ostream &os) const =0
- virtual void genMSBuildConfigProperties (std::ostream &os) const =0
- virtual void genMSBuildImportProps (std::ostream &os) const =0
- virtual void genMSBuildItemDefinitions (std::ostream &os) const =0
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const =0
- virtual void genMSBuildImportTarget (std::ostream &os) const =0
- virtual std::string getVarPrefix () const
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const =0

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

virtual bool isSynRemapRequired () const =0

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const =0

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

virtual size t getDeviceMemoryBytes () const =0

How many bytes of memory does 'device' have.

void genVariablePushPull (CodeStream &push, CodeStream &pull, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size t count) const

Helper function to generate matching push and pull functions for a variable.

 void genCurrentVariablePushPull (CodeStream &push, CodeStream &pull, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const

Helper function to generate matching push and pull functions for the current state of a variable.

 MemAlloc genArray (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const std::string &type, const std::string &name, VarLocation loc, size_t count) const

Helper function to generate matching definition, declaration, allocation and free code for an array.

• void genScalar (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const std::string &type, const std::string &name, VarLocation loc) const

Helper function to generate matching definition and declaration code for a scalar variable.

• int getLocalHostID () const

Gets ID of local host backend is building code for.

Protected Member Functions

- void addType (const std::string &type, size_t size)
- size_t getSize (const std::string &type) const

19.9.1 Member Typedef Documentation

19.9.1.1 GroupHandler

```
template<typename T >
using CodeGenerator::BackendBase::GroupHandler = std::function <void(CodeStream &, const T &,
Substitutions&)>
```

19.9.1.2 Handler

typedef std::function<void(CodeStream &, Substitutions&)> CodeGenerator::BackendBase::Handler

19.9.1.3 NeuronGroupHandler

typedef GroupHandler<NeuronGroupInternal> CodeGenerator::BackendBase::NeuronGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron← Group to.

19.9.1.4 NeuronGroupSimHandler

```
typedef std::function<void(CodeStream &, const NeuronGroupInternal &, Substitutions&, Neuron↔ GroupHandler, NeuronGroupHandler)> CodeGenerator::BackendBase::NeuronGroupSimHandler
```

Callback function type for generation neuron group simulation code.

Provides additional callbacks to insert code to emit spikes

19.9.1.5 SynapseGroupHandler

```
typedef GroupHandler<SynapseGroupInternal> CodeGenerator::BackendBase::SynapseGroupHandler
```

Standard callback type which provides a CodeStream to write platform-independent code for the specified SynapseGroup to.

19.9.2 Constructor & Destructor Documentation

19.9.2.1 BackendBase()

```
CodeGenerator::BackendBase::BackendBase (
    int localHostID,
    const std::string & scalarType )
```

19.9.2.2 \sim BackendBase()

```
\verb|virtual CodeGenerator::BackendBase:: \sim BackendBase ( ) [inline], [virtual]|\\
```

19.9.3 Member Function Documentation

19.9.3.1 addType()

19.9.3.2 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.3 genArray()

Helper function to generate matching definition, declaration, allocation and free code for an array.

19.9.3.4 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.5 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.6 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.7 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.8 genCurrentVariablePull()

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.9 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.10 genCurrentVariablePushPull()

Helper function to generate matching push and pull functions for the current state of a variable.

19.9.3.11 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.12 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.13 genExtraGlobalParamAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.14 genExtraGlobalParamDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.15 genExtraGlobalParamImplementation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.16 genExtraGlobalParamPull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.17 genExtraGlobalParamPush()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.18 genGlobalRNG()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.19 genInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.20 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.21 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.22 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.23 genMSBuildCompileModule()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.24 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

 $\textbf{see} \quad \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties} \\ \textbf{for more information.} \\$

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.25 genMSBuildImportProps()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.26 genMSBuildImportTarget()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.27 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items#item-definitions
for more information.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.28 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.29 genPopulationRNG()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.30 genPopVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.31 genRunnerPreamble()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.32 genScalar()

Helper function to generate matching definition and declaration code for a scalar variable.

19.9.3.33 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.34 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes. "id_pre", "id_post" and "id_syn" variables will be provided to callback via Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.35 genSynapseVariableRowInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.36 genTimer()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.37 genVariableAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.38 genVariableDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.39 genVariableFree()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.40 genVariableImplementation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.41 genVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.42 genVariablePull()

Generate code for pulling a variable from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.43 genVariablePush()

Generate code for pushing a variable to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.44 genVariablePushPull()

Helper function to generate matching push and pull functions for a variable.

19.9.3.45 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::BackendBase::getDeviceMemoryBytes ( ) const [pure virtual]
```

How many bytes of memory does 'device' have.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

```
19.9.3.46 getLocalHostID()
```

```
int CodeGenerator::BackendBase::qetLocalHostID ( ) const [inline]
```

Gets ID of local host backend is building code for.

19.9.3.47 getSize()

19.9.3.48 getVarPrefix()

```
virtual std::string CodeGenerator::BackendBase::getVarPrefix ( ) const [inline], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.49 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.50 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isPostsynapticRemapRequired ( ) const [pure virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.51 isSynRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isSynRemapRequired ( ) const [pure virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

The documentation for this class was generated from the following files:


- · backendBase.h
- backendBase.cc

19.10 CurrentSourceModels::Base Class Reference

Base class for all current source models.

#include <currentSourceModels.h>

Inheritance diagram for CurrentSourceModels::Base:



Public Member Functions

virtual std::string getInjectionCode () const
 Gets the code that defines current injected each timestep.

Additional Inherited Members

19.10.1 Detailed Description

Base class for all current source models.

19.10.2 Member Function Documentation

19.10.2.1 getInjectionCode()

virtual std::string CurrentSourceModels::Base::getInjectionCode () const [inline], [virtual]

Gets the code that defines current injected each timestep.

The documentation for this class was generated from the following file:

• currentSourceModels.h

19.11 InitSparseConnectivitySnippet::Base Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::Base:



Public Types

typedef std::function< unsigned int(unsigned int, unsigned int, const std::vector< double > &)> CalcMax←
 LengthFunc

Public Member Functions

- · virtual std::string getRowBuildCode () const
- · virtual ParamValVec getRowBuildStateVars () const
- virtual CalcMaxLengthFunc getCalcMaxRowLengthFunc () const

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

• virtual CalcMaxLengthFunc getCalcMaxColLengthFunc () const

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

- virtual EGPVec getExtraGlobalParams () const
- size_t getExtraGlobalParamIndex (const std::string ¶mName) const

Find the index of a named extra global parameter.

Additional Inherited Members

19.11.1 Member Typedef Documentation

19.11.1.1 CalcMaxLengthFunc

typedef std::function<unsigned int(unsigned int, unsigned int, const std::vector<double> &)>
InitSparseConnectivitySnippet::Base::CalcMaxLengthFunc

19.11.2 Member Function Documentation

19.11.2.1 getCalcMaxColLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxColLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

19.11.2.2 getCalcMaxRowLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxRowLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

19.11.2.3 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

19.11.2.4 getExtraGlobalParams()

```
virtual EGPVec InitSparseConnectivitySnippet::Base::getExtraGlobalParams ( ) const [inline],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the connection initialisation snippet

19.11.2.5 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::Base::getRowBuildCode ( ) const [inline],
[virtual]
```

Reimplemented in InitSparseConnectivitySnippet::FixedProbabilityBase.

19.11.2.6 getRowBuildStateVars()

```
virtual ParamValVec InitSparseConnectivitySnippet::Base::getRowBuildStateVars ( ) const [inline],
[virtual]
```

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.12 InitVarSnippet::Base Class Reference

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Base:



Public Member Functions

• virtual std::string getCode () const

Additional Inherited Members

19.12.1 Member Function Documentation

19.12.1.1 getCode()

```
virtual std::string InitVarSnippet::Base::getCode ( ) const [inline], [virtual]
```

The documentation for this class was generated from the following file:

initVarSnippet.h

19.13 Models::Base Class Reference

Base class for all models - in addition to the parameters snippets have, models can have state variables.

#include <models.h>

Inheritance diagram for Models::Base:



Classes

struct Var

A variable has a name, a type and an access type.

Public Types

typedef std::vector< Var > VarVec

Public Member Functions

• virtual VarVec getVars () const

Gets names and types (as strings) of model variables.

- virtual EGPVec getExtraGlobalParams () const
- size_t getVarIndex (const std::string &varName) const

Find the index of a named variable.

• size_t getExtraGlobalParamIndex (const std::string ¶mName) const

Find the index of a named extra global parameter.

Additional Inherited Members

19.13.1 Detailed Description

Base class for all models - in addition to the parameters snippets have, models can have state variables.

19.13.2 Member Typedef Documentation

19.13.2.1 VarVec

typedef std::vector<Var> Models::Base::VarVec

19.13.3 Member Function Documentation

19.13.3.1 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

19.13.3.2 getExtraGlobalParams()

```
virtual EGPVec Models::Base::getExtraGlobalParams ( ) const [inline], [virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented in NeuronModels::Poisson, and NeuronModels::SpikeSourceArray.

19.13.3.3 getVarIndex()

Find the index of a named variable.

19.13.3.4 getVars()

```
virtual VarVec Models::Base::getVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Neuron Models::SpikeSourceArray, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, WeightUpdateModels::StaticGraded, NeuronModels::IzhikevichVariable, WeightUpdateModels::StaticPulseDendriticDelay, Neuron Models::Izhikevich, WeightUpdateModels::StaticPulse, and NeuronModels::RulkovMap.

The documentation for this class was generated from the following file:


• models.h

19.14 NeuronModels::Base Class Reference

Base class for all neuron models.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Base:



- virtual std::string getSimCode () const
 - Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const
 - Gets code which defines the condition for a true spike in the described neuron model.
- virtual std::string getResetCode () const
 - Gets code that defines the reset action taken after a spike occurred. This can be empty.
- virtual std::string getSupportCode () const
 - Gets support code to be made available within the neuron kernel/funcion.
- virtual Models::Base::ParamValVec getAdditionalInputVars () const
- · virtual bool isAutoRefractoryRequired () const
 - Does this model require auto-refractory logic?

Additional Inherited Members

19.14.1 Detailed Description

Base class for all neuron models.

19.14.2 Member Function Documentation

19.14.2.1 getAdditionalInputVars()

virtual Models::Base::ParamValVec NeuronModels::Base::getAdditionalInputVars () const [inline],
[virtual]

Gets names, types (as strings) and initial values of local variables into which the 'apply input code' of (potentially) multiple postsynaptic input models can apply input

19.14.2.2 getResetCode()

```
virtual std::string NeuronModels::Base::getResetCode ( ) const [inline], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented in NeuronModels::SpikeSourceArray, and NeuronModels::LIF.

19.14.2.3 getSimCode()

```
virtual std::string NeuronModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMilesAlt, NeuronModels::TraubMiles.—Fast, NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, NeuronModels::Spike.—SourceArray, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

19.14.2.4 getSupportCode()

```
virtual std::string NeuronModels::Base::getSupportCode ( ) const [inline], [virtual]
```

Gets support code to be made available within the neuron kernel/funcion.

This is intended to contain user defined device functions that are used in the neuron codes. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.14.2.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::Base::getThresholdConditionCode ( ) const [inline], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Neuron Models::SpikeSourceArray, NeuronModels::SpikeSource, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

19.14.2.6 isAutoRefractoryRequired()

```
virtual bool NeuronModels::Base::isAutoRefractoryRequired ( ) const [inline], [virtual]
```

Does this model require auto-refractory logic?

The documentation for this class was generated from the following file:

• neuronModels.h

19.15 Snippet::Base Class Reference

Base class for all code snippets.

```
#include <snippet.h>
```

Inheritance diagram for Snippet::Base:



Classes

struct DerivedParam

A derived parameter has a name and a function for obtaining its value.

• struct EGP

An extra global parameter has a name and a type.

struct ParamVal

Additional input variables, row state variables and other things have a name, a type and an initial value.

Public Types

- typedef std::vector< std::string > StringVec
- typedef std::vector< EGP > EGPVec
- typedef std::vector< ParamVal > ParamValVec
- typedef std::vector< DerivedParam > DerivedParamVec

Public Member Functions

- virtual ~Base ()
- virtual StringVec getParamNames () const

Gets names of of (independent) model parameters.

virtual DerivedParamVec getDerivedParams () const

Static Protected Member Functions

template<typename T >
 static size_t getNamedVecIndex (const std::string &name, const std::vector< T > &vec)

19.15.1 Detailed Description

Base class for all code snippets.

19.15.2 Member Typedef Documentation

```
19.15.2.1 DerivedParamVec

typedef std::vector<DerivedParam> Snippet::Base::DerivedParamVec

19.15.2.2 EGPVec

typedef std::vector<EGF> Snippet::Base::EGFVec

19.15.2.3 ParamValVec

typedef std::vector<ParamVal> Snippet::Base::ParamValVec

19.15.2.4 StringVec

typedef std::vector<std::string> Snippet::Base::StringVec

19.15.3 Constructor & Destructor Documentation

19.15.3.1 ~Base()

virtual Snippet::Base::~Base ( ) [inline], [virtual]

19.15.4 Member Function Documentation
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

virtual DerivedParamVec Snippet::Base::getDerivedParams () const [inline], [virtual]

Reimplemented in NeuronModels::PoissonNew, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, NeuronModels::RulkovMap, InitSparseConnectivitySnippet::FixedProbabilityBase, PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

19.15.4.2 getNamedVecIndex()

Gets names of of (independent) model parameters.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, WeightUpdateModels::

StaticGraded, NeuronModels::IzhikevichVariable, NeuronModels::Izhikevich, InitVarSnippet::Gamma, InitSparse ConnectivitySnippet::FixedProbabilityBase, NeuronModels::RulkovMap, InitVarSnippet::Exponential, InitVar Snippet::Normal, InitVarSnippet::Uniform, PostsynapticModels::ExpCond, CurrentSourceModels::GaussianNoise, InitVarSnippet::Constant, CurrentSourceModels::DC, and PostsynapticModels::ExpCurr.

The documentation for this class was generated from the following file:


· snippet.h

19.16 PostsynapticModels::Base Class Reference

Base class for all postsynaptic models.

#include <postsynapticModels.h>

Inheritance diagram for PostsynapticModels::Base:



Public Member Functions

- virtual std::string getDecayCode () const
- virtual std::string getApplyInputCode () const
- virtual std::string getSupportCode () const

Additional Inherited Members

19.16.1 Detailed Description

Base class for all postsynaptic models.

19.16.2 Member Function Documentation

19.16.2.1 getApplyInputCode()

virtual std::string PostsynapticModels::Base::getApplyInputCode () const [inline], [virtual]

Reimplemented in PostsynapticModels::DeltaCurr, PostsynapticModels::ExpCond, and PostsynapticModels::ExpCourr.

19.16.2.2 getDecayCode()

virtual std::string PostsynapticModels::Base::getDecayCode () const [inline], [virtual]

Reimplemented in PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

19.16.2.3 getSupportCode()

```
virtual std::string PostsynapticModels::Base::getSupportCode ( ) const [inline], [virtual]
```

The documentation for this class was generated from the following file:

· postsynapticModels.h

19.17 CodeGenerator::CUDA::PresynapticUpdateStrategy::Base Class Reference

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::Base:

```
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base

CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan

CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan
```

Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const =0
 Get the number of threads that presynaptic updates should be parallelised across.
- virtual bool isCompatible (const SynapseGroupInternal &sg) const =0

Is this presynaptic update strategy compatible with a given synapse group?

virtual bool shouldAccumulateInRegister (const SynapseGroupInternal &sg, const Backend &backend) const
 =0

Are input currents emitted by this presynaptic update accumulated into a register?

virtual bool shouldAccumulateInSharedMemory (const SynapseGroupInternal &sg, const Backend &backend) const =0

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

 virtual void genCode (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, BackendBase::SynapseGroup

Handler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler) const =0

Generate presynaptic update code.

19.17.1 Member Function Documentation

19.17.1.1 genCode()

Generate presynaptic update code.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::

PresynapticUpdateStrategy::PreSpan.

19.17.1.2 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::

PresynapticUpdateStrategy::PreSpan.

19.17.1.3 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::

PresynapticUpdateStrategy::PreSpan.

19.17.1.4 shouldAccumulateInRegister()

Are input currents emitted by this presynaptic update accumulated into a register?

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::

PresynapticUpdateStrategy::PreSpan.

19.17.1.5 shouldAccumulateInSharedMemory()

```
virtual bool CodeGenerator::CUDA::PresynapticUpdateStrategy::Base::shouldAccumulateInShared \leftarrow Memory ( const SynapseGroupInternal & sg, const Backend & backend ) const [pure virtual]
```

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::

PresynapticUpdateStrategy::PreSpan.

The documentation for this class was generated from the following file:


· presynapticUpdateStrategy.h

19.18 WeightUpdateModels::Base Class Reference

Base class for all weight update models.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::Base:



• virtual std::string getSimCode () const

Gets simulation code run when 'true' spikes are received.

virtual std::string getEventCode () const

Gets code run when events (all the instances where event threshold condition is met) are received.

virtual std::string getLearnPostCode () const

Gets code to include in the learnSynapsesPost kernel/function.

• virtual std::string getSynapseDynamicsCode () const

Gets code for synapse dynamics which are independent of spike detection.

virtual std::string getEventThresholdConditionCode () const

Gets codes to test for events.

virtual std::string getSimSupportCode () const

Gets support code to be made available within the synapse kernel/function.

virtual std::string getLearnPostSupportCode () const

Gets support code to be made available within learnSynapsesPost kernel/function.

virtual std::string getSynapseDynamicsSuppportCode () const

Gets support code to be made available within the synapse dynamics kernel/function.

- · virtual std::string getPreSpikeCode () const
- virtual std::string getPostSpikeCode () const
- · virtual VarVec getPreVars () const
- · virtual VarVec getPostVars () const
- virtual bool isPreSpikeTimeRequired () const

Whether presynaptic spike times are needed or not.

• virtual bool isPostSpikeTimeRequired () const

Whether postsynaptic spike times are needed or not.

size_t getPreVarIndex (const std::string &varName) const

Find the index of a named presynaptic variable.

size_t getPostVarIndex (const std::string &varName) const

Find the index of a named postsynaptic variable.

Additional Inherited Members

19.18.1 Detailed Description

Base class for all weight update models.

19.18.2 Member Function Documentation

19.18.2.1 getEventCode()

```
virtual std::string WeightUpdateModels::Base::getEventCode ( ) const [inline], [virtual]
```

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented in WeightUpdateModels::StaticGraded.

19.18.2.2 getEventThresholdConditionCode()

virtual std::string WeightUpdateModels::Base::getEventThresholdConditionCode () const [inline],
[virtual]

Gets codes to test for events.

Reimplemented in WeightUpdateModels::StaticGraded.

19.18.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostCode ( ) const [inline], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

19.18.2.4 getLearnPostSupportCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostSupportCode ( ) const [inline],
[virtual]
```

Gets support code to be made available within learnSynapsesPost kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.18.2.5 getPostSpikeCode()

```
virtual std::string WeightUpdateModels::Base::getPostSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking postsynaptic neuron before learn post code is run on synapses

This is typically for the code to update postsynaptic variables. Presynaptic and synapse variables are not accesible from within this code

19.18.2.6 getPostVarIndex()

Find the index of a named postsynaptic variable.

19.18.2.7 getPostVars()

```
virtual VarVec WeightUpdateModels::Base::getPostVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses going to the same postsynaptic neuron

19.18.2.8 getPreSpikeCode()

```
virtual std::string WeightUpdateModels::Base::getPreSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking presynaptic neuron before sim code is run on synapses

This is typically for the code to update presynaptic variables. Postsynaptic and synapse variables are not accesible from within this code

19.18.2.9 getPreVarIndex()

Find the index of a named presynaptic variable.

19.18.2.10 getPreVars()

```
virtual VarVec WeightUpdateModels::Base::getPreVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses coming from the same presynaptic neuron

19.18.2.11 getSimCode()

```
virtual std::string WeightUpdateModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented in WeightUpdateModels::PiecewiseSTDP, WeightUpdateModels::StaticPulseDendriticDelay, and WeightUpdateModels::StaticPulse.

19.18.2.12 getSimSupportCode()

```
virtual std::string WeightUpdateModels::Base::getSimSupportCode ( ) const [inline], [virtual]
```

Gets support code to be made available within the synapse kernel/function.

This is intended to contain user defined device functions that are used in the weight update code. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions; note that this support code is available to sim, event threshold and event code

19.18.2.13 getSynapseDynamicsCode()

```
virtual std::string WeightUpdateModels::Base::getSynapseDynamicsCode ( ) const [inline],
[virtual]
```

Gets code for synapse dynamics which are independent of spike detection.

19.18.2.14 getSynapseDynamicsSuppportCode()

```
virtual std::string WeightUpdateModels::Base::getSynapseDynamicsSuppportCode ( ) const [inline],
[virtual]
```

Gets support code to be made available within the synapse dynamics kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.18.2.15 isPostSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPostSpikeTimeRequired () const [inline], [virtual]

Whether postsynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

19.18.2.16 isPreSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPreSpikeTimeRequired () const [inline], [virtual]

Whether presynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.


The documentation for this class was generated from the following file:

· weightUpdateModels.h

19.19 SpineMLSimulator::Input::Base Class Reference

#include <input.h>

Inheritance diagram for SpineMLSimulator::Input::Base:



Public Member Functions

- virtual ~Base ()
- virtual void apply (double dt, unsigned long long timestep)=0

Protected Member Functions

- Base (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value)
- · bool shouldApply (unsigned long long timestep) const
- void updateValues (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) const

19.19.1 Constructor & Destructor Documentation

19.19.1.1 \sim Base()

SpineMLSimulator::Input::Base::~Base () [virtual]

19.19.1.2 Base()

19.19.2 Member Function Documentation

19.19.2.1 apply()

Implemented in SpineMLSimulator::Input::Analogue, SpineMLSimulator::Input::SpikeTime, and SpineML Simulator::Input

19.19.2.2 shouldApply()

std::function< void(unsigned int, double) > applyValueFunc) const [protected]

The documentation for this class was generated from the following files:

- input.h
- input.cc

19.20 SpineMLSimulator::InputValue::Base Class Reference

```
#include <inputValue.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Input Value:: Base:$



Public Member Functions

- virtual ~Base ()
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)>
 applyValueFunc)=0

Protected Member Functions

- Base (unsigned int numNeurons, const pugi::xml_node &node)
- const std::vector< unsigned int > & getTargetIndices () const
- unsigned int getNumNeurons () const

19.20.1 Constructor & Destructor Documentation

```
19.20.1.1 \sim Base()
virtual SpineMLSimulator::InputValue::Base::~Base ( ) [inline], [virtual]
19.20.1.2 Base()
SpineMLSimulator::InputValue::Base::Base (
             unsigned int numNeurons,
             const pugi::xml_node & node ) [protected]
19.20.2 Member Function Documentation
19.20.2.1 getNumNeurons()
unsigned int SpineMLSimulator::InputValue::Base::getNumNeurons ( ) const [inline], [protected]
19.20.2.2 getTargetIndices()
const std::vector<unsigned int>& SpineMLSimulator::InputValue::Base::getTargetIndices ( )
const [inline], [protected]
19.20.2.3 update()
virtual void SpineMLSimulator::InputValue::Base::update (
             double dt,
             unsigned long long timestep,
```

std::function< void(unsigned int, double)> applyValueFunc) [pure virtual]

SpineMLSimulator::InputValue::TimeVarying, SpineMLSimulator::InputValue::ConstantArray, and SpineML←

The documentation for this class was generated from the following files:

Implemented in SpineMLSimulator::InputValue::External,

- inputValue.h
- inputValue.cc


19.21 SpineMLSimulator::LogOutput::Base Class Reference

```
#include <logOutput.h>
```

Simulator::InputValue::Constant.

Inheritance diagram for SpineMLSimulator::LogOutput::Base:

SpineMLSimulator::InputValue::TimeVaryingArray,



- Base (const pugi::xml_node &node, double dt)
- virtual ∼Base ()
- virtual void record (double dt, unsigned long long timestep)=0

Protected Member Functions

- bool shouldRecord (unsigned long long timestep) const
- unsigned long long getEndTimestep () const

19.21.1 Constructor & Destructor Documentation

19.21.1.1 Base()

19.21.1.2 \sim Base()

```
virtual SpineMLSimulator::LogOutput::Base::~Base ( ) [inline], [virtual]
```

19.21.2 Member Function Documentation

19.21.2.1 getEndTimestep()

```
unsigned long long SpineMLSimulator::LogOutput::Base::getEndTimestep ( ) const [inline],
[protected]
```

19.21.2.2 record()

```
virtual void SpineMLSimulator::LogOutput::Base::record ( \label{eq:double} \ dt, \label{eq:double} \ unsigned \ long \ long \ timestep ) \ \ [pure \ virtual]
```

Implemented in SpineMLSimulator::LogOutput::Event, SpineMLSimulator::LogOutput::AnalogueExternal, and SpineMLSimulator::LogOutput::AnalogueFile.

19.21.2.3 shouldRecord()

```
bool SpineMLSimulator::LogOutput::Base::shouldRecord ( unsigned\ long\ long\ timestep\ )\ const\ [inline]\text{, [protected]}
```

The documentation for this class was generated from the following files:

- logOutput.h
- · logOutput.cc

19.22 SpineMLSimulator::ModelProperty::Base Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::Base:

```
SpiteAll Simulator: Model Property: Base

SpiteAll Simulator: Model Property: Especial Simulator: Model Property: Fised

SpiteAll Simulator: Model Property: Curiem Distribution

SpiteAll Simulator: Model Property: Value List

SpiteAll Simulator: Model Property: Value Li
```

Public Member Functions

- Base (const StateVar< scalar > &stateVar, unsigned int size)
- virtual ∼Base ()
- scalar * getHostStateVar ()
- const scalar * getHostStateVar () const
- void pushToDevice () const
- · void pullFromDevice () const
- unsigned int getSize () const

19.22.1 Constructor & Destructor Documentation

19.22.1.1 Base()

19.22.1.2 \sim Base()

```
virtual SpineMLSimulator::ModelProperty::Base::~Base ( ) [inline], [virtual]
```

19.22.2 Member Function Documentation

```
19.22.2.1 getHostStateVar() [1/2]
```

```
scalar* SpineMLSimulator::ModelProperty::Base::getHostStateVar ( ) [inline]
```

```
19.22.2.2 getHostStateVar() [2/2]
const scalar* SpineMLSimulator::ModelProperty::Base::getHostStateVar ( ) const [inline]
19.22.2.3 getSize()
unsigned int SpineMLSimulator::ModelProperty::Base::getSize () const [inline]
19.22.2.4 pullFromDevice()
void SpineMLSimulator::ModelProperty::Base::pullFromDevice ( ) const [inline]
19.22.2.5 pushToDevice()
void SpineMLSimulator::ModelProperty::Base::pushToDevice ( ) const [inline]
The documentation for this class was generated from the following file:

    modelProperty.h

      CodeGenerator::CodeStream::CB Struct Reference
A close bracket marker.
#include <codeStream.h>
Public Member Functions
   • CB (unsigned int level)
Public Attributes
    · const unsigned int Level
19.23.1 Detailed Description
A close bracket marker.
Write to code stream os using:
os << CB(16);
19.23.2 Constructor & Destructor Documentation
19.23.2.1 CB()
CodeGenerator::CodeStream::CB::CB (
              unsigned int level ) [inline]
```

19.23.3 Member Data Documentation

19.23.3.1 Level

const unsigned int CodeGenerator::CodeStream::CB::Level


The documentation for this struct was generated from the following file:

· codeStream.h

19.24 CodeGenerator::CodeStream Class Reference

#include <codeStream.h>

Inheritance diagram for CodeGenerator::CodeStream:



Classes

- struct CB
 - A close bracket marker.
- struct OB

An open bracket marker.

· class Scope

Public Member Functions

- CodeStream ()
- CodeStream (std::ostream &stream)
- void setSink (std::ostream &stream)

Friends

- GENN EXPORT friend std::ostream & operator << (std::ostream &s, const OB &ob)
- GENN_EXPORT friend std::ostream & operator<< (std::ostream &s, const CB &cb)

19.24.1 Constructor & Destructor Documentation

```
19.24.1.1 CodeStream() [1/2]

CodeGenerator::CodeStream::CodeStream ( ) [inline]

19.24.1.2 CodeStream() [2/2]

CodeGenerator::CodeStream::CodeStream ( std::ostream & stream ) [inline]

19.24.2 Member Function Documentation

19.24.2.1 setSink()

void CodeGenerator::CodeStream::setSink ( std::ostream & stream ) [inline]

19.24.3 Friends And Related Function Documentation

19.24.3.1 operator<< [1/2]

GENN_EXPORT friend std::ostream& operator<< ( std::ostream & s, const OB & ob ) [friend]
```

The documentation for this class was generated from the following file:

· codeStream.h

19.24.3.2 operator << [2/2]


19.25 InitVarSnippet::Constant Class Reference

const CB & cb) [friend]

Initialises variable to a constant value.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Constant:



- DECLARE_SNIPPET (InitVarSnippet::Constant, 1)
- SET_CODE ("\$(value) = \$(constant);")
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.25.1 Detailed Description

Initialises variable to a constant value.

This snippet takes 1 parameter:

· value - The value to intialise the variable to

Note

This snippet type is seldom used directly - Models::VarInit has an implicit constructor that, internally, creates one of these snippets

19.25.2 Member Function Documentation

19.25.2.1 DECLARE_SNIPPET()

19.25.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Constant::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.25.2.3 SET_CODE()
```

```
InitVarSnippet::Constant::SET_CODE ( )
```


The documentation for this class was generated from the following file:

· initVarSnippet.h

19.26 SpineMLSimulator::InputValue::Constant Class Reference

```
#include <inputValue.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator::Input Value::Constant:$



- Constant (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.26.1 Constructor & Destructor Documentation

19.26.1.1 Constant()

19.26.2 Member Function Documentation

19.26.2.1 update()

Implements SpineMLSimulator::InputValue::Base.

The documentation for this class was generated from the following files:

- inputValue.h
- · inputValue.cc

19.27 SpineMLSimulator::InputValue::ConstantArray Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ConstantArray:

```
SpineMLSimulator::InputValue::Base

SpineMLSimulator::InputValue::ConstantArray
```

- ConstantArray (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.27.1 Constructor & Destructor Documentation

19.27.1.1 ConstantArray()

19.27.2 Member Function Documentation

19.27.2.1 update()

Implements SpineMLSimulator::InputValue::Base.


The documentation for this class was generated from the following files:

- inputValue.h
- inputValue.cc

19.28 pygenn.genn_groups.CurrentSource Class Reference

Class representing a current injection into a group of neurons.

Inheritance diagram for pygenn.genn_groups.CurrentSource:



Public Member Functions

```
    def __init__ (self, name)
    Init CurrentSource.
```

def size (self)

Number of neuron in the injected population.

- def size (self, _)
- def set_current_source_model (self, model, param_space, var_space)

Set curront source model, its parameters and initial variables.

def add_to (self, nn_model, pop)

Inject this CurrentSource into population and add it to the GeNN NNmodel.

• def add_extra_global_param (self, param_name, param_values)

Add extra global parameter.

- def load (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise current source.

Public Attributes

- current_source_model
- target_pop
- pop

19.28.1 Detailed Description

Class representing a current injection into a group of neurons.

19.28.2 Constructor & Destructor Documentation

Init CurrentSource.

Parameters

name string name of the current source

19.28.3 Member Function Documentation

19.28.3.1 add_extra_global_param()

Add extra global parameter.

Parameters

param name string with the name of the extra global parameter

Parameters

param_values	iterable or a single value
--------------	----------------------------

19.28.3.2 add_to()

Inject this CurrentSource into population and add it to the GeNN NNmodel.

Parameters

рор	instance of NeuronGroup into which this CurrentSource should be injected
nn_model	GeNN NNmodel

19.28.3.3 load()

```
def pygenn.genn_groups.CurrentSource.load ( self, \\ slm, \\ scalar )
```

19.28.3.4 reinitialise()

```
def pygenn.genn_groups.CurrentSource.reinitialise ( self, \\ slm, \\ scalar )
```

Reinitialise current source.

Parameters

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

19.28.3.5 set_current_source_model()

Set curront source model, its parameters and initial variables.

Parameters

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

Number of neuron in the injected population.

19.28.4 Member Data Documentation

19.28.4.1 current_source_model

pygenn.genn_groups.CurrentSource.current_source_model

19.28.4.2 pop

pygenn.genn_groups.CurrentSource.pop

19.28.4.3 target_pop

pygenn.genn_groups.CurrentSource.target_pop


The documentation for this class was generated from the following file:

genn_groups.py

19.29 CurrentSource Class Reference

#include <currentSource.h>

Inheritance diagram for CurrentSource:



- CurrentSource (const CurrentSource &)=delete
- CurrentSource ()=delete
- void setVarLocation (const std::string &varName, VarLocation loc)

Set location of current source state variable.

void setExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of extra global parameter.

- · const std::string & getName () const
- const CurrentSourceModels::Base * getCurrentSourceModel () const

Gets the current source model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- VarLocation getVarLocation (const std::string &varName) const

Get variable location for current source model state variable.

• VarLocation getVarLocation (size_t index) const

Get variable location for current source model state variable.

VarLocation getExtraGlobalParamLocation (const std::string ¶mName) const

Get location of neuron model extra global parameter by name.

VarLocation getExtraGlobalParamLocation (size t index) const

Get location of neuron model extra global parameter by omdex.

Protected Member Functions

- CurrentSource (const std::string &name, const CurrentSourceModels::Base *currentSourceModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation default← VarLocation, VarLocation defaultExtraGlobalParamLocation)
- · void initDerivedParams (double dt)
- const std::vector< double > & getDerivedParams () const
- bool isSimRNGRequired () const

Does this current source require an RNG to simulate.

• bool isInitRNGRequired () const

Does this current source group require an RNG for it's init code.

19.29.1 Constructor & Destructor Documentation

```
19.29.1.2 CurrentSource() [2/3]
CurrentSource::CurrentSource ( ) [delete]
19.29.1.3 CurrentSource() [3/3]
CurrentSource::CurrentSource (
             const std::string & name,
             const CurrentSourceModels::Base * currentSourceModel,
             const std::vector< double > & params,
             const std::vector< Models::VarInit > & varInitialisers,
              VarLocation defaultVarLocation,
              VarLocation defaultExtraGlobalParamLocation ) [inline], [protected]
19.29.2 Member Function Documentation
19.29.2.1 getCurrentSourceModel()
const CurrentSourceModels::Base* CurrentSource::getCurrentSourceModel ( ) const [inline]
Gets the current source model used by this group.
19.29.2.2 getDerivedParams()
const std::vector<double>& CurrentSource::getDerivedParams ( ) const [inline], [protected]
19.29.2.3 getExtraGlobalParamLocation() [1/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
              const std::string & paramName ) const
Get location of neuron model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.29.2.4 getExtraGlobalParamLocation() [2/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.29.2.5 getName()
const std::string& CurrentSource::getName ( ) const [inline]
19.29.2.6 getParams()
const std::vector<double>& CurrentSource::getParams ( ) const [inline]
```

```
19.29.2.7 getVarInitialisers()
```

```
const std::vector<Models::VarInit>& CurrentSource::getVarInitialisers ( ) const [inline]

19.29.2.8 getVarLocation() [1/2]
```

Get variable location for current source model state variable.

Get variable location for current source model state variable.

19.29.2.10 initDerivedParams()

```
\begin{tabular}{ll} \begin{tabular}{ll} void CurrentSource::initDerivedParams ( & double $dt$ ) & [protected] \end{tabular}
```

19.29.2.11 isInitRNGRequired()

```
bool CurrentSource::isInitRNGRequired ( ) const [protected]
```

Does this current source group require an RNG for it's init code.

19.29.2.12 isSimRNGRequired()

```
bool CurrentSource::isSimRNGRequired ( ) const [protected]
```

Does this current source require an RNG to simulate.

19.29.2.13 setExtraGlobalParamLocation()

Set location of extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.29.2.14 setVarLocation()

Set location of current source state variable.


The documentation for this class was generated from the following files:

- · currentSource.h
- currentSource.cc

19.30 CurrentSourceInternal Class Reference

```
#include <currentSourceInternal.h>
```

Inheritance diagram for CurrentSourceInternal:



Public Member Functions

CurrentSourceInternal (const std::string &name, const CurrentSourceModels::Base *currentSourceModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation)

Additional Inherited Members

19.30.1 Constructor & Destructor Documentation

19.30.1.1 CurrentSourceInternal()

The documentation for this class was generated from the following file:


· currentSourceInternal.h

19.31 CurrentSourceModels::DC Class Reference

DC source.

```
#include <currentSourceModels.h>
```

Inheritance diagram for CurrentSourceModels::DC:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- SET INJECTION CODE ("\$(injectCurrent, \$(amp));\)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Static Public Member Functions

• static const DC * getInstance ()

Additional Inherited Members

19.31.1 Detailed Description

DC source.

It has a single parameter:

• amp - amplitude of the current [nA]

19.31.2 Member Typedef Documentation

19.31.2.1 ParamValues

typedef Snippet::ValueBase< 1 > CurrentSourceModels::DC::ParamValues

19.31.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PostVarValues

19.31.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PreVarValues

19.31.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::DC::VarValues

19.31.3 Member Function Documentation

19.31.3.1 getInstance()

```
static const DC* CurrentSourceModels::DC::getInstance ( ) [inline], [static]
```

19.31.3.2 getParamNames()

```
virtual StringVec CurrentSourceModels::DC::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.31.3.3 SET_INJECTION_CODE()

The documentation for this class was generated from the following file:


• currentSourceModels.h

19.32 PostsynapticModels::DeltaCurr Class Reference

Simple delta current synapse.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::DeltaCurr:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getApplyInputCode () const override

Static Public Member Functions

• static const DeltaCurr * getInstance ()

Additional Inherited Members

19.32.1 Detailed Description

Simple delta current synapse.

Synaptic input provides a direct inject of instantaneous current

19.32.2 Member Typedef Documentation

19.32.2.1 ParamValues

typedef Snippet::ValueBase< 0 > PostsynapticModels::DeltaCurr::ParamValues

19.32.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PostVarValues

19.32.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PreVarValues

19.32.2.4 VarValues

 ${\tt typedef\ Models::} {\tt VarInitContainerBase<\ 0\ >\ PostsynapticModels::} {\tt DeltaCurr::} {\tt VarValues}$

19.32.3 Member Function Documentation

19.32.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::DeltaCurr::getApplyInputCode () const [inline],
[override], [virtual]

Reimplemented from PostsynapticModels::Base.

19.32.3.2 getInstance()

```
static const DeltaCurr* PostsynapticModels::DeltaCurr::getInstance ( ) [inline], [static]
```

The documentation for this class was generated from the following file:

· postsynapticModels.h

19.33 Snippet::Base::DerivedParam Struct Reference

A derived parameter has a name and a function for obtaining its value.

```
#include <snippet.h>
```

Public Attributes

- · std::string name
- std::function< double(const std::vector< double > &, double)> func

19.33.1 Detailed Description

A derived parameter has a name and a function for obtaining its value.

19.33.2 Member Data Documentation

19.33.2.1 func

```
std::function<double(const std::vector<double> &, double)> Snippet::Base::DerivedParam::func
```

19.33.2.2 name

```
std::string Snippet::Base::DerivedParam::name
```

The documentation for this struct was generated from the following file:

· snippet.h

19.34 Snippet::Base::EGP Struct Reference

An extra global parameter has a name and a type.

```
#include <snippet.h>
```

Public Attributes

- std::string name
- std::string type

19.34.1 Detailed Description

An extra global parameter has a name and a type.

19.34.2 Member Data Documentation

```
19.34.2.1 name
std::string Snippet::Base::EGP::name
19.34.2.2 type
```

std::string Snippet::Base::EGP::type


The documentation for this struct was generated from the following file:

· snippet.h

19.35 SpineMLSimulator::LogOutput::Event Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::Event:



Public Member Functions

- Event (const pugi::xml_node &node, double dt, unsigned long long numTimeSteps, const std::string &port, unsigned int popSize, const filesystem::path &logPath, unsigned int *spikeQueuePtr, unsigned int *host← SpikeCount, unsigned int *hostSpikes, void(*pullCurrentSpikesFunc)(void))
- · virtual void record (double dt, unsigned long long timestep) override

Additional Inherited Members

19.35.1 Constructor & Destructor Documentation

19.35.1.1 Event()

19.35.2 Member Function Documentation

19.35.2.1 record()

Implements SpineMLSimulator::LogOutput::Base.

The documentation for this class was generated from the following files:


- logOutput.h
- logOutput.cc

19.36 PostsynapticModels::ExpCond Class Reference

Exponential decay with synaptic input treated as a conductance value.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::ExpCond:



Public Types

- typedef Snippet::ValueBase< 2 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

static const ExpCond * getInstance ()

Additional Inherited Members

19.36.1 Detailed Description

Exponential decay with synaptic input treated as a conductance value.

This model has no variables and two parameters:

- tau: Decay time constant
- E : Reversal potential

tau is used by the derived parameter expdecay which returns expf(-dt/tau).

19.36.2 Member Typedef Documentation

19.36.2.1 ParamValues

typedef Snippet::ValueBase< 2 > PostsynapticModels::ExpCond::ParamValues

19.36.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCond::PostVarValues

19.36.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCond::PreVarValues

19.36.2.4 VarValues

 ${\tt typedef\ Models::} {\tt VarInitContainerBase} < \ {\tt 0} \ > {\tt PostsynapticModels::} {\tt ExpCond::} {\tt VarValues}$

19.36.3 Member Function Documentation

19.36.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCond::getApplyInputCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.36.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCond::getDecayCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.36.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCond::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.36.3.4 getInstance()

```
static const ExpCond* PostsynapticModels::ExpCond::getInstance ( ) [inline], [static]
```

19.36.3.5 getParamNames()

```
virtual StringVec PostsynapticModels::ExpCond::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


· postsynapticModels.h

19.37 PostsynapticModels::ExpCurr Class Reference

Exponential decay with synaptic input treated as a current value.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::ExpCurr:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override

- virtual StringVec getParamNames () const override
 Gets names of of (independent) model parameters.
- · virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

• static const ExpCurr * getInstance ()

Additional Inherited Members

19.37.1 Detailed Description

Exponential decay with synaptic input treated as a current value.

19.37.2 Member Typedef Documentation

19.37.2.1 ParamValues

typedef Snippet::ValueBase< 1 > PostsynapticModels::ExpCurr::ParamValues

19.37.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PostVarValues

19.37.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PreVarValues

19.37.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > PostsynapticModels::ExpCurr::VarValues

19.37.3 Member Function Documentation

19.37.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCurr::getApplyInputCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.37.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCurr::getDecayCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.37.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCurr::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.37.3.4 getInstance()

```
static const ExpCurr* PostsynapticModels::ExpCurr::getInstance ( ) [inline], [static]
```

19.37.3.5 getParamNames()

```
virtual StringVec PostsynapticModels::ExpCurr::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


postsynapticModels.h

19.38 InitVarSnippet::Exponential Class Reference

Initialises variable by sampling from the exponential distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Exponential:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Exponential, 1)
- SET CODE ("\$(value) = \$(lambda) * \$(gennrand exponential);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.38.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

19.38.2 Member Function Documentation

19.38.2.1 DECLARE_SNIPPET()

19.38.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Exponential::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.38.2.3 SET_CODE()
```

```
InitVarSnippet::Exponential::SET_CODE ( )
```


The documentation for this class was generated from the following file:

initVarSnippet.h

19.39 SpineMLSimulator::ModelProperty::ExponentialDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::ExponentialDistribution:



Public Member Functions

- ExponentialDistribution (const pugi::xml_node &node, const StateVar < scalar > &stateVar, unsigned int size)
- void setValue (scalar lambda)

19.39.1 Constructor & Destructor Documentation

19.39.1.1 ExponentialDistribution()

```
SpineMLSimulator::ModelProperty::ExponentialDistribution::ExponentialDistribution ( const pugi::xml_node & node,
```

```
const StateVar< scalar > & stateVar,
unsigned int size )
```

19.39.2 Member Function Documentation

19.39.2.1 setValue()


The documentation for this class was generated from the following files:

- modelProperty.h
- · modelProperty.cc

19.40 SpineMLSimulator::InputValue::External Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::External:



Public Member Functions

- External (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) final
- std::vector< double >::iterator getBufferBegin ()
- std::vector< double >::iterator getBufferEnd ()

Protected Member Functions

- virtual void updateInternal ()
- unsigned int getSize () const
- std::vector< double > & getBuffer ()

19.40.1 Constructor & Destructor Documentation

19.40.1.1 External()

19.40.2 Member Function Documentation

```
19.40.2.1 getBuffer()
std::vector<double>& SpineMLSimulator::InputValue::External::getBuffer ( ) [inline], [protected]
19.40.2.2 getBufferBegin()
std::vector<double>::iterator SpineMLSimulator::InputValue::External::getBufferBegin ( ) [inline]
19.40.2.3 getBufferEnd()
std::vector<double>::iterator SpineMLSimulator::InputValue::External::getBufferEnd ( ) [inline]
19.40.2.4 getSize()
unsigned int SpineMLSimulator::InputValue::External::getSize ( ) const [inline], [protected]
19.40.2.5 update()
void SpineMLSimulator::InputValue::External::update (
             double dt,
             unsigned long long timestep,
             std::function< void(unsigned int, double)> applyValueFunc ) [final], [virtual]
Implements SpineMLSimulator::InputValue::Base.
19.40.2.6 updateInternal()
virtual void SpineMLSimulator::InputValue::External::updateInternal ( ) [inline], [protected],
```

Reimplemented in SpineMLSimulator::InputValue::ExternalNetwork.


The documentation for this class was generated from the following files:

- · inputValue.h
- · inputValue.cc

19.41 SpineMLSimulator::InputValue::ExternalNetwork Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ExternalNetwork:



Public Member Functions

• ExternalNetwork (double dt, unsigned int numNeurons, const pugi::xml_node &node)

Protected Member Functions

· virtual void updateInternal () override

19.41.1 Constructor & Destructor Documentation

19.41.1.1 ExternalNetwork()

19.41.2 Member Function Documentation

19.41.2.1 updateInternal()

```
void SpineMLSimulator::InputValue::ExternalNetwork::updateInternal ( ) [override], [protected],
[virtual]
```

Reimplemented from SpineMLSimulator::InputValue::External.


The documentation for this class was generated from the following files:

- inputValue.h
- inputValue.cc

19.42 pygenn.model_preprocessor.ExtraGlobalVariable Class Reference

Class holding information about GeNN extra global pointer variable.

Inheritance diagram for pygenn.model_preprocessor.ExtraGlobalVariable:



Public Member Functions

Set Variable's values.

```
    def __init__ (self, variable_name, variable_type, values=None)
        Init Variable.
    def set_values (self, values)
```

Public Attributes

- name
- type
- view
- values

19.42.1 Detailed Description

Class holding information about GeNN extra global pointer variable.

19.42.2 Constructor & Destructor Documentation

Init Variable.

Parameters

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable

19.42.3 Member Function Documentation

```
19.42.3.1 set_values()
```

Set Variable's values.

Parameters

19.42.4 Member Data Documentation

19.42.4.1 name

pygenn.model_preprocessor.ExtraGlobalVariable.name

19.42.4.2 type

pygenn.model_preprocessor.ExtraGlobalVariable.type

19.42.4.3 values

pygenn.model_preprocessor.ExtraGlobalVariable.values

19.42.4.4 view

pygenn.model_preprocessor.ExtraGlobalVariable.view


The documentation for this class was generated from the following file:

· model_preprocessor.py

19.43 SpineMLSimulator::ModelProperty::Fixed Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::Fixed:



Public Member Functions

- Fixed (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size)
- Fixed (double value, const StateVar< scalar > &stateVar, unsigned int size)
- void setValue (scalar value)

19.43.1 Constructor & Destructor Documentation

19.43.1.1 Fixed() [1/2]

19.43.1.2 Fixed() [2/2]

19.43.2 Member Function Documentation

19.43.2.1 setValue()


The documentation for this class was generated from the following files:

- modelProperty.h
- · modelProperty.cc

19.44 InitSparseConnectivitySnippet::FixedProbability Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbability:



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::FixedProbability, 1)
- SET_ROW_BUILD_CODE ("const scalar u = \$(gennrand_uniform);\ "prevJ+=(1+(int)(log(u) *\$(probLog← Recip)));\" "if(prevJ< \$(num_post)) {\" " \$(addSynapse, prevJ);\" "}\" "else {\" " \$(endRow);\" "}\")

Additional Inherited Members

19.44.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

19.44.2 Member Function Documentation

19.44.2.1 DECLARE_SNIPPET()

19.44.2.2 SET_ROW_BUILD_CODE()

```
InitSparseConnectivitySnippet::FixedProbability::SET_ROW_BUILD_CODE ( )
```


The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

19.45 InitSparseConnectivitySnippet::FixedProbabilityBase Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbabilityBase:



Public Member Functions

- virtual std::string getRowBuildCode () const override=0
- SET_ROW_BUILD_STATE_VARS ({{"prevJ", "int", -1}})
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- virtual DerivedParamVec getDerivedParams () const override
- SET_CALC_MAX_ROW_LENGTH_FUNC ([](unsigned int numPre, unsigned int numPost, const std ::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPre);return binomial ← InverseCDF(quantile, numPost, pars[0]);})
- SET_CALC_MAX_COL_LENGTH_FUNC ([](unsigned int numPre, unsigned int numPost, const std::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPost);return binomialInverseC← DF(quantile, numPre, pars[0]);})

Additional Inherited Members

19.45.1 Detailed Description

Base class for snippets which initialise connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

19.45.2 Member Function Documentation

19.45.2.1 getDerivedParams()

```
virtual DerivedParamVec InitSparseConnectivitySnippet::FixedProbabilityBase::getDerivedParams
( ) const [inline], [override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.45.2.2 getParamNames()

```
virtual StringVec InitSparseConnectivitySnippet::FixedProbabilityBase::getParamNames ( ) const
[inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.45.2.3 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::FixedProbabilityBase::getRowBuildCode ( )
const [override], [pure virtual]
```

Reimplemented from InitSparseConnectivitySnippet::Base.

19.45.2.4 SET_CALC_MAX_COL_LENGTH_FUNC()

19.45.2.5 SET_CALC_MAX_ROW_LENGTH_FUNC()

19.45.2.6 SET_ROW_BUILD_STATE_VARS()


The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.46 InitSparseConnectivitySnippet::FixedProbabilityNoAutapse Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbabilityNoAutapse:



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse, 1)
- SET_ROW_BUILD_CODE ("int nextJ;\"do {\" " const scalar u=\$(gennrand_uniform);\" " nextJ=prevJ+(1+(int)(log(u) *\$(probLogRecip)));\" "} while(nextJ==\$(id_pre));\" "prevJ=nextJ;\" "if(prevJ< \$(num_post)) {\" " \$(add← Synapse, prevJ);\" "}\" "else {\" " \$(endRow);\" "}\")

Additional Inherited Members

19.46.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons. This version ensures there are no autapses - connections between neurons with the same id so should be used for recurrent connections.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

19.46.2 Member Function Documentation

19.46.2.1 DECLARE_SNIPPET()

19.46.2.2 SET_ROW_BUILD_CODE()

```
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse::SET_ROW_BUILD_CODE ( )
```

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.47 CodeGenerator::FunctionTemplate Struct Reference

```
#include <codeGenUtils.h>
```

Public Member Functions

FunctionTemplate operator= (const FunctionTemplate &o)

Public Attributes

· const std::string genericName

Generic name used to refer to function in user code.

· const unsigned int numArguments

Number of function arguments.

• const std::string doublePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses double precision.

const std::string singlePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses single precision.

19.47.1 Detailed Description

Immutable structure for specifying how to implement a generic function e.g. gennrand_uniform

NOTE for the sake of easy initialisation first two parameters of GenericFunction are repeated (C++17 fixes)

19.47.2 Member Function Documentation

19.47.2.1 operator=()

19.47.3 Member Data Documentation

19.47.3.1 doublePrecisionTemplate

```
\verb|const| std::string| CodeGenerator::FunctionTemplate::doublePrecisionTemplate| \\
```

The function template (for use with functionSubstitute) used when model uses double precision.

19.47.3.2 genericName

```
const std::string CodeGenerator::FunctionTemplate::genericName
```

Generic name used to refer to function in user code.

19.47.3.3 numArguments

const unsigned int CodeGenerator::FunctionTemplate::numArguments

Number of function arguments.

19.47.3.4 singlePrecisionTemplate

```
const std::string CodeGenerator::FunctionTemplate::singlePrecisionTemplate
```

The function template (for use with functionSubstitute) used when model uses single precision.

The documentation for this struct was generated from the following file:


· codeGenUtils.h

19.48 InitVarSnippet::Gamma Class Reference

Initialises variable by sampling from the exponential distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Gamma:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Gamma, 2)
- SET_CODE ("\$(value) = \$(b) * \$(gennrand_gamma, \$(a));")
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.48.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

19.48.2 Member Function Documentation

19.48.2.1 DECLARE_SNIPPET()

19.48.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Gamma::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.48.2.3 SET_CODE()

```
InitVarSnippet::Gamma::SET_CODE ( )
```

The documentation for this class was generated from the following file:


• initVarSnippet.h

19.49 CurrentSourceModels::GaussianNoise Class Reference

Noisy current source with noise drawn from normal distribution.

```
#include <currentSourceModels.h>
```

Inheritance diagram for CurrentSourceModels::GaussianNoise:



Public Types

- typedef Snippet::ValueBase< 2 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- SET_INJECTION_CODE ("\$(injectCurrent, \$(mean) + \$(gennrand_normal) * \$(sd));\)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Static Public Member Functions

static const GaussianNoise * getInstance ()

Additional Inherited Members

19.49.1 Detailed Description

Noisy current source with noise drawn from normal distribution.

It has 2 parameters:

- mean mean of the normal distribution [nA]
- sd standard deviation of the normal distribution [nA]

19.49.2 Member Typedef Documentation

```
19.49.2.1 ParamValues
```

```
typedef Snippet::ValueBase< 2 > CurrentSourceModels::GaussianNoise::ParamValues
```

19.49.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PostVarValues
```

19.49.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PreVarValues
```

19.49.2.4 VarValues

```
typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::GaussianNoise::VarValues
```

19.49.3 Member Function Documentation

19.49.3.1 getInstance()

```
static const GaussianNoise* CurrentSourceModels::GaussianNoise::getInstance ( ) [inline],
[static]
```

19.49.3.2 getParamNames()

```
virtual StringVec CurrentSourceModels::GaussianNoise::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.49.3.3 SET_INJECTION_CODE()

The documentation for this class was generated from the following file:

· currentSourceModels.h

19.50 GenerateRunBase Class Reference

```
#include <generateRun.h>
```

Public Member Functions

- GenerateRunBase (const std::string &projectName)
- virtual void writeSizes (std::ofstream &sizes) const
- int getExitCode (const CLI::ParseError &e)
- void parseCommandLine (int argc, char **argv)
- $\bullet \ \ int \ \underline{buildAndRun} \ (std::initializer_list < std::string > runParams=\{\}) \ const$

Protected Member Functions

- · virtual int runTools () const
- CLI::App & getApp ()
- std::string getOutDir () const
- const std::string & getExperimentName () const

19.50.1 Constructor & Destructor Documentation

19.50.1.1 GenerateRunBase()

19.50.2 Member Function Documentation

19.50.2.1 buildAndRun()

19.50.2.2 getApp()

```
CLI::App& GenerateRunBase::getApp ( ) [inline], [protected]
```

The documentation for this class was generated from the following file:


• generateRun.h

19.51 pygenn.genn_model.GeNNModel Class Reference

GeNNModel class This class helps to define, build and run a GeNN model from python.

std::ofstream & sizes) const [inline], [virtual]

Inheritance diagram for pygenn.genn_model.GeNNModel:



Public Member Functions

def __init__ (self, precision=None, model_name="GeNNModel", enable_debug=False, backend=None, selected_gpu=None)

Init GeNNModel.

- def selected_gpu (self)
- def selected_gpu (self, v)

- def use_backend (self)
- def use_backend (self, backend)
- def default_var_location (self)

Default variable location - defines where state variables are initialised.

- def default var location (self, location)
- def default_sparse_connectivity_location (location)

Default sparse connectivity mode - where connectivity is initialised.

- · def default sparse connectivity location (self, location)
- def model name (self)

Name of the model.

- def model_name (self, model_name)
- def t (self)

Simulation time in ms.

- def t (self, t)
- · def timestep (self)

Simulation time step.

- def timestep (self, timestep)
- def dT (self)

Step size.

- def dT (self, dt)
- · def add neuron population (self, pop name, num neurons, neuron, param space, var space)

Add a neuron population to the GeNN model.

 def add_synapse_population (self, pop_name, matrix_type, delay_steps, source, target, w_update_model, wu_param_space, wu_var_space, wu_pre_var_space, wu_post_var_space, postsyn_model, ps_param_ space, ps_var_space, connectivity_initialiser=None)

Add a synapse population to the GeNN model.

def add_current_source (self, cs_name, current_source_model, pop_name, param_space, var_space)

Add a current source to the GeNN model.

def build (self, path_to_model="./")

Finalize and build a GeNN model.

· def load (self)

import the model as shared library and initialize it

• def reinitialise (self)

reinitialise model to its original state without re-loading

- def step_time (self)
- def pull_state_from_device (self, pop_name)

Pull state from the device for a given population.

def pull_spikes_from_device (self, pop_name)

Pull spikes from the device for a given population.

def pull_current_spikes_from_device (self, pop_name)

Pull spikes from the device for a given population.

def pull_connectivity_from_device (self, pop_name)

Pull connectivity from the device for a given population.

def pull_var_from_device (self, pop_name, var_name)

Pull variable from the device for a given population.

def push_state_to_device (self, pop_name)

Push state to the device for a given population.

def push_spikes_to_device (self, pop_name)

Push spikes to the device for a given population.

• def push current spikes to device (self, pop name)

Push current spikes to the device for a given population.

• def push_connectivity_to_device (self, pop_name)

Push connectivity to the device for a given population.

• def push_var_to_device (self, pop_name, var_name)

Push variable to the device for a given population.

• def end (self)

Free memory.

Public Attributes

- use_backend
- selected_gpu
- · default var location
- model_name
- neuron_populations
- synapse_populations
- current_sources
- dT

19.51.1 Detailed Description

GeNNModel class This class helps to define, build and run a GeNN model from python.

19.51.2 Constructor & Destructor Documentation

Init GeNNModel.

Parameters

precision	string precision as string ("float", "double" or "long double"). defaults to float.
model_name	string name of the model. Defaults to "GeNNModel".
enable_debug	boolean enable debug mode. Disabled by default.
backend	string specifying name of backend module to use Defaults to None to pick 'best' backend for your system
selected_gpu	integer specifying the id of the gpu in which the simulator wil run; None will select automatically

19.51.3 Member Function Documentation

19.51.3.1 add_current_source()

Add a current source to the GeNN model.

Parameters

cs_name	name of the new current source
current_source_model	type of the CurrentSourceModels class as string or instance of CurrentSourceModels class derived from
	<pre>pygenn.genn_wrapper.CurrentSourceModels.Custom (see also pygenn.genn_model.create_custom_current_source_class)</pre>
pop_name	name of the population into which the current source should be injected
param_space	dict with param values for the CurrentSourceModels class
var_space	dict with initial variable values for the CurrentSourceModels class

19.51.3.2 add_neuron_population()

Add a neuron population to the GeNN model.

Parameters

pop_name	name of the new population
num_neurons	number of neurons in the new population
neuron	type of the NeuronModels class as string or instance of neuron class derived from pygenn.genn_wrapper.NeuronModels.Custom (see also pygenn.genn_model.create_custom_neuron_class)
param_space	dict with param values for the NeuronModels class
var_space	dict with initial variable values for the NeuronModels class

19.51.3.3 add_synapse_population()

```
target,
w_update_model,
wu_param_space,
wu_var_space,
wu_pre_var_space,
wu_post_var_space,
postsyn_model,
ps_param_space,
ps_var_space,
connectivity_initialiser = None )
```

Add a synapse population to the GeNN model.

Parameters

pop_name	name of the new population
matrix_type	type of the matrix as string
delay_steps	delay in number of steps
source	source neuron group
target	target neuron group
w_update_model	type of the WeightUpdateModels class as string or instance of weight update model class derived from
	<pre>pygenn.genn_wrapper.WeightUpdateModels.Custom (see also pygenn.genn_model.create_custom_weight_update_class)</pre>
wu_param_space	dict with param values for the WeightUpdateModels class
wu_var_space	dict with initial values for WeightUpdateModels state variables
wu_pre_var_space	dict with initial values for WeightUpdateModels presynaptic variables
wu_post_var_space	dict with initial values for WeightUpdateModels postsynaptic variables
postsyn_model	type of the PostsynapticModels class as string or instance of postsynaptic model class derived from pygenn.genn_wrapper.PostsynapticModels.Custom (see also pygenn.genn_model.create_custom_postsynaptic_class)
ps_param_space	dict with param values for the PostsynapticModels class
ps_var_space	dict with initial variable values for the PostsynapticModels class
connectivity_initialiser	InitSparseConnectivitySnippet::Init for connectivity

19.51.3.4 build()

Finalize and build a GeNN model.

Parameters

```
path_to_model path where to place the generated model code. Defaults to the local directory.
```

```
19.51.3.5 default_sparse_connectivity_location() [1/2]
```

```
\label{location} \mbox{def pygenn.genn\_model.GeNNModel.default\_sparse\_connectivity\_location (} \\ \mbox{$location )$}
```

Default sparse connectivity mode - where connectivity is initialised.

```
19.51.3.6 default_sparse_connectivity_location() [2/2]
def pygenn.genn_model.GeNNModel.default_sparse_connectivity_location (
               self,
               location )
19.51.3.7 default_var_location() [1/2]
def pygenn.genn_model.GeNNModel.default_var_location (
Default variable location - defines where state variables are initialised.
19.51.3.8 default_var_location() [2/2]
{\tt def pygenn.genn\_model.GeNNModel.default\_var\_location} \ \ (
                self,
               location )
19.51.3.9 dT() [1/2]
def pygenn.genn_model.GeNNModel.dT (
               self )
Step size.
19.51.3.10 dT() [2/2]
def pygenn.genn_model.GeNNModel.dT (
               self,
               dt )
19.51.3.11 end()
{\tt def pygenn.genn\_model.GeNNModel.end} (
               self )
Free memory.
19.51.3.12 load()
def pygenn.genn_model.GeNNModel.load (
               self )
import the model as shared library and initialize it
19.51.3.13 model_name() [1/2]
```

def pygenn.genn_model.GeNNModel.model_name (

```
\label{eq:self} \textit{Self} \;\; ) Name of the model.
```

19.51.3.15 pull_connectivity_from_device()

```
def pygenn.genn_model.GeNNModel.pull_connectivity_from_device ( self, \\ pop_name \ )
```

Pull connectivity from the device for a given population.

19.51.3.16 pull_current_spikes_from_device()

```
def pygenn.genn_model.GeNNModel.pull_current_spikes_from_device ( self, \\ pop\_name \ )
```

Pull spikes from the device for a given population.

19.51.3.17 pull_spikes_from_device()

Pull spikes from the device for a given population.

19.51.3.18 pull_state_from_device()

```
def pygenn.genn_model.GeNNModel.pull_state_from_device ( self, \\ pop_name \ )
```

Pull state from the device for a given population.

19.51.3.19 pull_var_from_device()

Pull variable from the device for a given population.

```
19.51.3.20 push_connectivity_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_connectivity_to_device ( self, \\ pop\_name \ )
```

Push connectivity to the device for a given population.

```
19.51.3.21 push_current_spikes_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_current_spikes_to_device ( self, \\ pop_name \ )
```

Push current spikes to the device for a given population.

19.51.3.22 push_spikes_to_device()

```
def pygenn.genn_model.GeNNModel.push_spikes_to_device ( self, \\ pop_name \ )
```

Push spikes to the device for a given population.

19.51.3.23 push_state_to_device()

Push state to the device for a given population.

19.51.3.24 push_var_to_device()

Push variable to the device for a given population.

19.51.3.25 reinitialise()

```
\label{lem:continuous} \mbox{def pygenn.genn\_model.GeNNModel.reinitialise (} \\ self \mbox{)}
```

reinitialise model to its original state without re-loading

```
19.51.3.26 selected_gpu() [1/2]
```

```
19.51.3.27 selected_gpu() [2/2]
def pygenn.genn_model.GeNNModel.selected_gpu (
              self,
               v )
19.51.3.28 step_time()
def pygenn.genn_model.GeNNModel.step_time (
              self )
19.51.3.29 t() [1/2]
def pygenn.genn_model.GeNNModel.t (
              self )
Simulation time in ms.
19.51.3.30 t() [2/2]
def pygenn.genn_model.GeNNModel.t (
              self,
              t)
19.51.3.31 timestep() [1/2]
def pygenn.genn_model.GeNNModel.timestep (
              self )
Simulation time step.
19.51.3.32 timestep() [2/2]
def pygenn.genn_model.GeNNModel.timestep (
              self,
               timestep )
19.51.3.33 use_backend() [1/2]
def pygenn.genn_model.GeNNModel.use_backend (
              self )
19.51.3.34 use_backend() [2/2]
def pygenn.genn_model.GeNNModel.use_backend (
              self,
              backend )
```

19.51.4 Member Data Documentation

19.51.4.1 current_sources

pygenn.genn_model.GeNNModel.current_sources

19.51.4.2 default_var_location

pygenn.genn_model.GeNNModel.default_var_location

19.51.4.3 dT

pygenn.genn_model.GeNNModel.dT

19.51.4.4 model_name

pygenn.genn_model.GeNNModel.model_name

19.51.4.5 neuron_populations

pygenn.genn_model.GeNNModel.neuron_populations

19.51.4.6 selected_gpu

pygenn.genn_model.GeNNModel.selected_gpu

19.51.4.7 synapse_populations

 $\verb|pygenn.genn_model.GeNNModel.synapse_populations|\\$

19.51.4.8 use_backend

pygenn.genn_model.GeNNModel.use_backend


The documentation for this class was generated from the following file:

genn_model.py

19.52 pygenn.genn_groups.Group Class Reference

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

Inheritance diagram for pygenn.genn_groups.Group:



Public Member Functions

- def __init__ (self, name)
 Init Group.
- def set_var (self, var_name, values)

Set values for a Variable.

Public Attributes

- name
- vars
- extra_global_params

19.52.1 Detailed Description

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

19.52.2 Constructor & Destructor Documentation

Init Group.

Parameters

name string name of the Group

19.52.3 Member Function Documentation

19.52.3.1 set_var()

Set values for a Variable.

Parameters

var_name	string with the name of the variable
values	iterable or a single value

19.52.4 Member Data Documentation

19.52.4.1 extra_global_params

```
pygenn.genn_groups.Group.extra_global_params
```

19.52.4.2 name

pygenn.genn_groups.Group.name

19.52.4.3 vars

pygenn.genn_groups.Group.vars


The documentation for this class was generated from the following file:

genn_groups.py

19.53 InitSparseConnectivitySnippet::Init Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::Init:



Public Member Functions

Init (const Base *snippet, const std::vector< double > ¶ms)

19.53.1 Constructor & Destructor Documentation

19.53.1.1 Init()

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.54 Snippet::Init < SnippetBase > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

- Init (const SnippetBase *snippet, const std::vector< double > ¶ms)
- const SnippetBase * getSnippet () const
- const std::vector< double > & getParams () const
- const std::vector< double > & getDerivedParams () const
- void initDerivedParams (double dt)

19.54.1 Detailed Description

```
template<typename SnippetBase> class Snippet::Init< SnippetBase>
```

Class used to bind together everything required to utilize a snippet

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

19.54.2 Constructor & Destructor Documentation

19.54.2.1 Init()

19.54.3 Member Function Documentation

19.54.3.1 getDerivedParams()

```
template<typename SnippetBase>
const std::vector<double>& Snippet::Init< SnippetBase >::getDerivedParams ( ) const [inline]
```

19.54.3.2 getParams()

```
template<typename SnippetBase>
const std::vector<double>& Snippet::Init< SnippetBase >::getParams ( ) const [inline]
```

19.54.3.3 getSnippet()

```
template<typename SnippetBase>
const SnippetBase* Snippet::Init< SnippetBase >::getSnippet ( ) const [inline]
```

19.54.3.4 initDerivedParams()


The documentation for this class was generated from the following file:

· snippet.h

19.55 SpineMLSimulator::Input::InterSpikeIntervalBase Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::InterSpikeIntervalBase:



Public Member Functions

· virtual void apply (double dt, unsigned long long timestep) override

Protected Member Functions

- InterSpikeIntervalBase (double dt, const pugi::xml_node &node, std::unique_ptr < InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)
- virtual double getTimeToSpike (double isiMs)=0

Additional Inherited Members

19.55.1 Constructor & Destructor Documentation

19.55.1.1 InterSpikeIntervalBase()

19.55.2 Member Function Documentation

19.55.2.1 apply()

Implements SpineMLSimulator::Input::Base.

19.55.2.2 getTimeToSpike()

Implemented in SpineMLSimulator::Input::PoissonSpikeRate, and SpineMLSimulator::Input::RegularSpikeRate.

The documentation for this class was generated from the following files:


- input.h
- · input.cc

19.56 NeuronModels::Izhikevich Class Reference

Izhikevich neuron with fixed parameters [1].

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Izhikevich:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- $\bullet \ \ typedef \ Models:: VarInitContainer Base < 2 > VarValues \\$
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

- virtual std::string getThresholdConditionCode () const override
 - Gets code which defines the condition for a true spike in the described neuron model.
- virtual StringVec getParamNames () const override
 - Gets names of of (independent) model parameters.
- virtual VarVec getVars () const override
 - Gets names and types (as strings) of model variables.

Static Public Member Functions

static const NeuronModels::Izhikevich * getInstance ()

Additional Inherited Members

19.56.1 Detailed Description

Izhikevich neuron with fixed parameters [1].

It is usually described as

$$\begin{array}{lcl} \frac{dV}{dt} & = & 0.04V^2 + 5V + 140 - U + I, \\ \frac{dU}{dt} & = & a(bV - U), \end{array}$$

I is an external input current and the voltage V is reset to parameter c and U incremented by parameter d, whenever V >= 30 mV. This is paired with a particular integration procedure of two 0.5 ms Euler time steps for the V equation followed by one 1 ms time step of the U equation. Because of its popularity we provide this model in this form here event though due to the details of the usual implementation it is strictly speaking inconsistent with the displayed equations.

Variables are:

- V Membrane potential
- U Membrane recovery variable

Parameters are:

- · a time scale of U
- b sensitivity of U
- $_{\text{\tiny C}}$ after-spike reset value of V
- d after-spike reset value of U

19.56.2 Member Typedef Documentation

19.56.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::Izhikevich::ParamValues

19.56.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PostVarValues

19.56.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PreVarValues

19.56.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::Izhikevich::VarValues

19.56.3 Member Function Documentation

19.56.3.1 getInstance()

static const NeuronModels::Izhikevich* NeuronModels::Izhikevich::getInstance () [inline],
[static]

19.56.3.2 getParamNames()

virtual StringVec NeuronModels::Izhikevich::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

Reimplemented in NeuronModels::IzhikevichVariable.

19.56.3.3 getSimCode()

virtual std::string NeuronModels::Izhikevich::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.56.3.4 getThresholdConditionCode()

virtual std::string NeuronModels::Izhikevich::getThresholdConditionCode () const [inline],
[override], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.56.3.5 getVars()

virtual VarVec NeuronModels::Izhikevich::getVars () const [inline], [override], [virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

Reimplemented in NeuronModels::IzhikevichVariable.

The documentation for this class was generated from the following file:


neuronModels.h

19.57 NeuronModels::IzhikevichVariable Class Reference

Izhikevich neuron with variable parameters [1].

#include <neuronModels.h>

Inheritance diagram for NeuronModels::IzhikevichVariable:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 6 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual StringVec getParamNames () const override
 Gets names of of (independent) model parameters.
- virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

Static Public Member Functions

static const NeuronModels::IzhikevichVariable * getInstance ()

Additional Inherited Members

19.57.1 Detailed Description

Izhikevich neuron with variable parameters [1].

This is the same model as Izhikevich but parameters are defined as "variables" in order to allow users to provide individual values for each individual neuron instead of fixed values for all neurons across the population.

Accordingly, the model has the Variables:

- V Membrane potential
- U Membrane recovery variable
- · a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

and no parameters.

19.57.2 Member Typedef Documentation

19.57.2.1 ParamValues

typedef Snippet::ValueBase< 0 > NeuronModels::IzhikevichVariable::ParamValues

19.57.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::IzhikevichVariable::PostVarValues

19.57.2.3 PreVarValues

 ${\tt typedef\ Models::} Iz {\tt hikevichVariable::} Pre Var Values$

19.57.2.4 VarValues

typedef Models::VarInitContainerBase< 6 > NeuronModels::IzhikevichVariable::VarValues

19.57.3 Member Function Documentation

19.57.3.1 getInstance()

```
static const NeuronModels::IzhikevichVariable* NeuronModels::IzhikevichVariable::getInstance (
) [inline], [static]
```

19.57.3.2 getParamNames()

```
virtual StringVec NeuronModels::IzhikevichVariable::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::Izhikevich.

19.57.3.3 getVars()

virtual VarVec NeuronModels::IzhikevichVariable::getVars () const [inline], [override],
[virtual]

Gets names and types (as strings) of model variables.

Reimplemented from NeuronModels::Izhikevich.


The documentation for this class was generated from the following file:

· neuronModels.h

19.58 NeuronModels::LIF Class Reference

#include <neuronModels.h>

Inheritance diagram for NeuronModels::LIF:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getSimCode () const override
 - Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const override
 - Gets code which defines the condition for a true spike in the described neuron model.
- virtual std::string getResetCode () const override
 - Gets code that defines the reset action taken after a spike occurred. This can be empty.
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- virtual DerivedParamVec getDerivedParams () const override
- virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

• static const LIF * getInstance ()

Additional Inherited Members

19.58.1 Member Typedef Documentation

19.58.1.1 ParamValues

```
typedef Snippet::ValueBase< 7 > NeuronModels::LIF::ParamValues
```

19.58.1.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PostVarValues
```

19.58.1.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PreVarValues
```

19.58.1.4 VarValues

```
typedef Models::VarInitContainerBase< 2 > NeuronModels::LIF::VarValues
```

19.58.2 Member Function Documentation

19.58.2.1 getDerivedParams()

```
virtual DerivedParamVec NeuronModels::LIF::getDerivedParams ( ) const [inline], [override],
[virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.58.2.2 getInstance()

```
static const LIF* NeuronModels::LIF::getInstance ( ) [inline], [static]
```

19.58.2.3 getParamNames()

```
virtual StringVec NeuronModels::LIF::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.58.2.4 getResetCode()

```
virtual std::string NeuronModels::LIF::getResetCode ( ) const [inline], [override], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

19.58.2.5 getSimCode()

```
virtual std::string NeuronModels::LIF::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.58.2.6 getThresholdConditionCode()

```
virtual std::string NeuronModels::LIF::getThresholdConditionCode ( ) const [inline], [override],
[virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.58.2.7 getVars()

```
virtual VarVec NeuronModels::LIF::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.58.2.8 SET_NEEDS_AUTO_REFRACTORY()

The documentation for this class was generated from the following file:

neuronModels.h

19.59 CodeGenerator::MemAlloc Class Reference

```
#include <backendBase.h>
```

Public Member Functions

- size_t getHostBytes () const
- size_t getDeviceBytes () const
- size_t getZeroCopyBytes () const
- size_t getHostMBytes () const
- size_t getDeviceMBytes () const
- size_t getZeroCopyMBytes () const
- MemAlloc & operator+= (const MemAlloc &rhs)

Static Public Member Functions

- static MemAlloc zero ()
- static MemAlloc host (size_t hostBytes)
- static MemAlloc device (size t deviceBytes)
- static MemAlloc zeroCopy (size_t zeroCopyBytes)

19.59.1 Member Function Documentation

```
19.59.1.1 device()
static MemAlloc CodeGenerator::MemAlloc::device (
             size_t deviceBytes ) [inline], [static]
19.59.1.2 getDeviceBytes()
size_t CodeGenerator::MemAlloc::getDeviceBytes ( ) const [inline]
19.59.1.3 getDeviceMBytes()
size_t CodeGenerator::MemAlloc::getDeviceMBytes ( ) const [inline]
19.59.1.4 getHostBytes()
size_t CodeGenerator::MemAlloc::getHostBytes ( ) const [inline]
19.59.1.5 getHostMBytes()
size_t CodeGenerator::MemAlloc::getHostMBytes ( ) const [inline]
19.59.1.6 getZeroCopyBytes()
size_t CodeGenerator::MemAlloc::getZeroCopyBytes ( ) const [inline]
19.59.1.7 getZeroCopyMBytes()
size_t CodeGenerator::MemAlloc::getZeroCopyMBytes ( ) const [inline]
19.59.1.8 host()
static MemAlloc CodeGenerator::MemAlloc::host (
             size_t hostBytes ) [inline], [static]
19.59.1.9 operator+=()
MemAlloc& CodeGenerator::MemAlloc::operator+= (
```

```
const MemAlloc & rhs ) [inline]

19.59.1.10 zero()

static MemAlloc CodeGenerator::MemAlloc::zero ( ) [inline], [static]

19.59.1.11 zeroCopy()

static MemAlloc CodeGenerator::MemAlloc::zeroCopy (
```

size_t zeroCopyBytes) [inline], [static]

The documentation for this class was generated from the following file:


· backendBase.h

19.60 ModelSpec Class Reference

Object used for specifying a neuronal network model.

```
#include <modelSpec.h>
```

Inheritance diagram for ModelSpec:



Public Types

- typedef std::map< std::string, NeuronGroupInternal >::value_type NeuronGroupValueType
- typedef std::map< std::string, SynapseGroupInternal >::value_type SynapseGroupValueType

Public Member Functions

- ModelSpec ()
- ModelSpec (const ModelSpec &)=delete
- ModelSpec & operator= (const ModelSpec &)=delete
- ∼ModelSpec ()
- void setName (const std::string &name)

Method to set the neuronal network model name.

void setPrecision (FloatType)

Set numerical precision for floating point.

void setTimePrecision (TimePrecision timePrecision)

Set numerical precision for time.

void setDT (double dt)

Set the integration step size of the model.

void setTiming (bool timingEnabled)

Set whether timers and timing commands are to be included.

void setSeed (unsigned int rngSeed)

Set the random seed (disables automatic seeding if argument not 0).

void setDefaultVarLocation (VarLocation loc)

What is the default location for model state variables?

void setDefaultExtraGlobalParamLocation (VarLocation loc)

What is the default location for model extra global parameters?

void setDefaultSparseConnectivityLocation (VarLocation loc)

What is the default location for sparse synaptic connectivity?

void setDefaultNarrowSparseIndEnabled (bool enabled)

Sets default for whether narrow i.e. less than 32-bit types are used for sparse matrix indices.

void setMergePostsynapticModels (bool merge)

Should compatible postsynaptic models and dendritic delay buffers be merged?

const std::string & getName () const

Gets the name of the neuronal network model.

· const std::string & getPrecision () const

Gets the floating point numerical precision.

std::string getTimePrecision () const

Gets the floating point numerical precision used to represent time.

double getDT () const

Gets the model integration step size.

• unsigned int getSeed () const

Get the random seed.

bool isTimingEnabled () const

Are timers and timing commands enabled.

· unsigned int getNumLocalNeurons () const

How many neurons are simulated locally in this model.

unsigned int getNumRemoteNeurons () const

How many neurons are simulated remotely in this model.

• unsigned int getNumNeurons () const

How many neurons make up the entire model.

NeuronGroup * findNeuronGroup (const std::string &name)

Find a neuron group by name.

template<typename NeuronModel >

NeuronGroup * addNeuronPopulation (const std::string &name, unsigned int size, const NeuronModel *model, const typename NeuronModel::ParamValues ¶mValues, const typename NeuronModel::Var⊷ Values &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a neuron model managed by the user.

• template<typename NeuronModel >

NeuronGroup * addNeuronPopulation (const std::string &name, unsigned int size, const typename Neuron ← Model::ParamValues ¶mValues, const typename NeuronModel::VarValues &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

SynapseGroup * findSynapseGroup (const std::string &name)

Find a synapse group by name.

 $\bullet \ \ \text{template} < \text{typename WeightUpdateModel} \ , \ \text{typename PostsynapticModel} >$

SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const WeightUpdateModel *wum, const typename WeightUpdateModel::ParamValues &weightParamValues, const typename WeightUpdate &weight PreVarValues &weightVarInitialisers, const typename WeightUpdateModel::PreVarValues &weight PreVarInitialisers, const typename WeightUpdateModel::PostVarValues &weightPostVarInitialisers, const PostsynapticModel *psm, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticVarInitialisers, const InitSparseConnectivity Snippet::Init &connectivityInitialiser=uninitialisedConnectivity())

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

• template<typename WeightUpdateModel , typename PostsynapticModel > SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &trg, const typename WeightUpdateModel::Param

Values &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename Postsynaptic

Model::VarValues &postsynapticVarInitialisers, const InitSparseConnectivitySnippet::Init &connectivity

Initialiser=uninitialisedConnectivity())

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE MODEL and IMPLEMENT MODEL macros.

• template < typename WeightUpdateModel , typename PostsynapticModel > SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const typename WeightUpdateModel::
ParamValues &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename WeightUpdateModel::PreVarValues &weightPreVarInitialisers, const typename Weight
UpdateModel::PostVarValues &weightPostVarInitialisers, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticVarInitialisers, const InitSparseConnectivitySnippet::Init &connectivityInitialiser=uninitialisedConnectivity())

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

• CurrentSource * findCurrentSource (const std::string &name)

Find a current source by name.

• template<typename CurrentSourceModel >

CurrentSource * addCurrentSource (const std::string ¤tSourceName, const CurrentSourceModel *model, const std::string &targetNeuronGroupName, const typename CurrentSourceModel::ParamValues ¶mValues, const typename CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a current source model managed by the user.

 $\bullet \ \ template {<} typename \ Current Source Model >$

CurrentSource * addCurrentSource (const std::string ¤tSourceName, const std::string &target ← NeuronGroupName, const typename CurrentSourceModel::ParamValues ¶mValues, const typename CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a singleton current source model created using standard DECLARE← _MODEL and IMPLEMENT_MODEL macros.

Protected Member Functions

void finalize ()

Finalise model.

std::string scalarExpr (double) const

Get the string literal that should be used to represent a value in the model's floating-point type.

bool zeroCopyInUse () const

Are any variables in any populations in this model using zero-copy memory?

 $\bullet \ \ const \ std::map{<} \ std::string, \ NeuronGroupInternal > \& \ getLocalNeuronGroups \ () \ const$

Get std::map containing local named NeuronGroup objects in model.

 $\bullet \ \ const \ std::map{<} \ std::string, \ NeuronGroupInternal> \& \ getRemoteNeuronGroups \ () \ const$

Get std::map containing remote named NeuronGroup objects in model.

const std::map< std::string, SynapseGroupInternal > & getLocalSynapseGroups () const

Get std::map containing local named SynapseGroup objects in model.

const std::map< std::string, SynapseGroupInternal > & getRemoteSynapseGroups () const

Get std::map containing remote named SynapseGroup objects in model.

const std::map< std::string, CurrentSourceInternal > & getLocalCurrentSources () const

Get std::map containing local named CurrentSource objects in model.

const std::map< std::string, CurrentSourceInternal > & getRemoteCurrentSources () const

Get std::map containing remote named CurrentSource objects in model.

19.60.1 Detailed Description

Object used for specifying a neuronal network model.

19.60.2 Member Typedef Documentation

19.60.2.1 NeuronGroupValueType

```
typedef std::map<std::string, NeuronGroupInternal>::value_type ModelSpec::NeuronGroupValueType
```

19.60.2.2 SynapseGroupValueType

```
\label{typedef} \begin{tabular}{ll} type & to the constraint of the constraint of
```

19.60.3 Constructor & Destructor Documentation

19.60.4 Member Function Documentation

19.60.4.1 addCurrentSource() [1/2]

Adds a new current source to the model using a current source model managed by the user.

Template Parameters

CurrentSourceModel type of current source model (derived from CurrentSourceModels::Base).

currentSourceName	string containing unique name of current source.
model	current source model to use for current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in CurrentSource::VarValues object.

Returns

pointer to newly created CurrentSource

19.60.4.2 addCurrentSource() [2/2]

Adds a new current source to the model using a singleton current source model created using standard DECLAR ← E_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

CurrentSourceModel	type of neuron model (derived from CurrentSourceModel::Base).
--------------------	---

Parameters

currentSourceName	string containing unique name of current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in
	CurrentSourceModel::VarValues object.

Returns

pointer to newly created CurrentSource

19.60.4.3 addNeuronPopulation() [1/2]

Adds a new neuron group to the model using a neuron model managed by the user.

Template Parameters

NeuronModel	type of neuron model (derived from NeuronModels::Base).
-------------	---

Parameters

name	string containing unique name of neuron population.
size	integer specifying how many neurons are in the population.
model	neuron model to use for neuron group.
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.
varlnitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
hostID	if using MPI, the ID of the node to simulate this population on.

Returns

pointer to newly created NeuronGroup

19.60.4.4 addNeuronPopulation() [2/2]

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

NeuronModel	type of neuron model (derived from NeuronModels::Base).
-------------	---

name	string containing unique name of neuron population.
size	integer specifying how many neurons are in the population.
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
hostID	if using MPI, the ID of the node to simulate this population on.

Returns

pointer to newly created NeuronGroup

19.60.4.5 addSynapsePopulation() [1/3]

```
template<typename WeightUpdateModel , typename PostsynapticModel >
SynapseGroup* ModelSpec::addSynapsePopulation (
                                           const std::string & name,
                                           SynapseMatrixType mtype,
                                            unsigned int delaySteps,
                                            const std::string & src,
                                           const std::string & trg,
                                            const WeightUpdateModel * wum,
                                            const typename WeightUpdateModel::ParamValues & weightParamValues,
                                            const typename WeightUpdateModel::VarValues & weightVarInitialisers,
                                            \verb|const typename WeightUpdateModel::PreVarValues & weightPreVarInitialisers|, \\
                                            \verb|const typename WeightUpdateModel::PostVarValues & weightPostVarInitialisers|, \\
                                            const PostsynapticModel * psm,
                                            const typename PostsynapticModel::ParamValues & postsynapticParamValues,
                                            \verb|const typename PostsynapticModel::VarValues & postsynapticVarInitialisers|, \\
                                            \verb|const InitSparseConnectivitySnippet::Init & connectivityInitialiser = uninitialised \\ \leftarrow \\ |connectivityInitialiser = |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInit
Connectivity() ) [inline]
```

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

Template Parameters

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
wum	weight update model to use for synapse group.
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
psm	postsynaptic model to use for synapse group.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.

connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for	
	SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.	
	Typically wrapped with it's parameters using initConnectivity function	

Returns

pointer to newly created SynapseGroup

19.60.4.6 addSynapsePopulation() [2/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.

connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for
	SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.
	Typically wrapped with it's parameters using initConnectivity function

Returns

pointer to newly created SynapseGroup

19.60.4.7 addSynapsePopulation() [3/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

	I
name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model per-synapse state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.

postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK. Typically wrapped with it's parameters using initConnectivity function

Returns

pointer to newly created SynapseGroup

```
19.60.4.8 finalize()
```

```
void ModelSpec::finalize ( ) [protected]
```

Finalise model.

19.60.4.9 findCurrentSource()

Find a current source by name.

This function attempts to find an existing current source.

19.60.4.10 findNeuronGroup()

Find a neuron group by name.

19.60.4.11 findSynapseGroup()

Find a synapse group by name.

19.60.4.12 getDT()

```
double ModelSpec::getDT ( ) const [inline]
```

Gets the model integration step size.

19.60.4.13 getLocalCurrentSources()

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getLocalCurrentSources ( )
const [inline], [protected]
```

Get std::map containing local named CurrentSource objects in model.

19.60.4.14 getLocalNeuronGroups()

```
\label{localNeuronGroupInternal} $$ ModelSpec::getLocalNeuronGroups ( ) const[inline], [protected] $$
```

Get std::map containing local named NeuronGroup objects in model.

19.60.4.15 getLocalSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getLocalSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing local named SynapseGroup objects in model.

19.60.4.16 getName()

```
const std::string& ModelSpec::getName ( ) const [inline]
```

Gets the name of the neuronal network model.

19.60.4.17 getNumLocalNeurons()

```
unsigned int ModelSpec::getNumLocalNeurons ( ) const
```

How many neurons are simulated locally in this model.

19.60.4.18 getNumNeurons()

```
unsigned int ModelSpec::getNumNeurons ( ) const [inline]
```

How many neurons make up the entire model.

19.60.4.19 getNumRemoteNeurons()

```
unsigned int ModelSpec::getNumRemoteNeurons ( ) const
```

How many neurons are simulated remotely in this model.

19.60.4.20 getPrecision()

```
const std::string& ModelSpec::getPrecision ( ) const [inline]
```

Gets the floating point numerical precision.

19.60.4.21 getRemoteCurrentSources()

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getRemoteCurrentSources ( )
const [inline], [protected]
```

Get std::map containing remote named CurrentSource objects in model.

19.60.4.22 getRemoteNeuronGroups()

```
const std::map<std::string, NeuronGroupInternal>& ModelSpec::getRemoteNeuronGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named NeuronGroup objects in model.

19.60.4.23 getRemoteSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getRemoteSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named SynapseGroup objects in model.

19.60.4.24 getSeed()

```
unsigned int ModelSpec::getSeed ( ) const [inline]
```

Get the random seed.

19.60.4.25 getTimePrecision()

```
std::string ModelSpec::getTimePrecision ( ) const
```

Gets the floating point numerical precision used to represent time.

19.60.4.26 isTimingEnabled()

```
bool ModelSpec::isTimingEnabled ( ) const [inline]
```

Are timers and timing commands enabled.

19.60.4.27 operator=()

19.60.4.28 scalarExpr()

Get the string literal that should be used to represent a value in the model's floating-point type.

19.60.4.29 setDefaultExtraGlobalParamLocation()

What is the default location for model extra global parameters?

Historically, this was just left up to the user to handle

19.60.4.30 setDefaultNarrowSparseIndEnabled()

Sets default for whether narrow i.e. less than 32-bit types are used for sparse matrix indices.

19.60.4.31 setDefaultSparseConnectivityLocation()

What is the default location for sparse synaptic connectivity?

Historically, everything was allocated on both the host AND device

19.60.4.32 setDefaultVarLocation()

What is the default location for model state variables?

Historically, everything was allocated on both the host AND device

19.60.4.33 setDT()

Set the integration step size of the model.

19.60.4.34 setMergePostsynapticModels()

Should compatible postsynaptic models and dendritic delay buffers be merged?

This can significantly reduce the cost of updating neuron population but means that per-synapse group inSyn arrays can not be retrieved

19.60.4.35 setName()

Method to set the neuronal network model name.

19.60.4.36 setPrecision()

Set numerical precision for floating point.

This function sets the numerical precision of floating type variables. By default, it is GENN_GENN_FLOAT.

19.60.4.37 setSeed()

```
void ModelSpec::setSeed (
          unsigned int rngSeed ) [inline]
```

Set the random seed (disables automatic seeding if argument not 0).

19.60.4.38 setTimePrecision()

Set numerical precision for time.

19.60.4.39 setTiming()

```
void ModelSpec::setTiming (
          bool timingEnabled ) [inline]
```

Set whether timers and timing commands are to be included.

19.60.4.40 zeroCopyInUse()

```
bool ModelSpec::zeroCopyInUse ( ) const [protected]
```

Are any variables in any populations in this model using zero-copy memory?


The documentation for this class was generated from the following files:

- · modelSpec.h
- · modelSpec.cc

19.61 ModelSpecInternal Class Reference

```
#include <modelSpecInternal.h>
```

Inheritance diagram for ModelSpecInternal:



Additional Inherited Members

The documentation for this class was generated from the following file:

· modelSpecInternal.h

19.62 SpineMLSimulator::NetworkClient Class Reference

```
#include <networkClient.h>
```

Public Types

- enum Mode : char { Mode::Source = 45, Mode::Target = 46 }
- enum DataType : char { DataType::Analogue = 31, DataType::Events = 32, DataType::Impulses = 33 }

Public Member Functions

- NetworkClient ()
- NetworkClient (const std::string &hostname, unsigned int port, unsigned int size, DataType dataType, Mode mode, const std::string &connectionName)
- ∼NetworkClient ()
- bool connect (const std::string &hostname, unsigned int port, unsigned int size, DataType dataType, Mode mode, const std::string &connectionName)
- bool receive (std::vector< double > &buffer)
- bool send (const std::vector< double > &buffer)

19.62.1 Member Enumeration Documentation

19.62.1.1 DataType

```
enum SpineMLSimulator::NetworkClient::DataType : char [strong]
```

Enumerator

Analogue	
Events	
Impulses	

19.62.1.2 Mode

```
enum SpineMLSimulator::NetworkClient::Mode : char [strong]
```

Enumerator

Source Target

19.62.2 Constructor & Destructor Documentation

```
19.62.2.3 ∼NetworkClient()
SpineMLSimulator::NetworkClient::~NetworkClient ( )
19.62.3 Member Function Documentation
19.62.3.1 connect()
bool SpineMLSimulator::NetworkClient::connect (
             const std::string & hostname,
             unsigned int port,
             unsigned int size,
             DataType dataType,
             Mode mode,
             const std::string & connectionName )
19.62.3.2 receive()
bool SpineMLSimulator::NetworkClient::receive (
             std::vector< double > & buffer )
19.62.3.3 send()
bool SpineMLSimulator::NetworkClient::send (
```

The documentation for this class was generated from the following files:


const std::vector< double > & buffer)

- networkClient.h
- networkClient.cc

19.63 pygenn.genn_groups.NeuronGroup Class Reference

Class representing a group of neurons.

Inheritance diagram for pygenn.genn_groups.NeuronGroup:



Public Member Functions

- def __init__ (self, name)
 Init NeuronGroup.
- def current_spikes (self)

Current spikes from GeNN.

def delay_slots (self)

Maximum delay steps needed for this group.

- · def size (self)
- def set_neuron (self, model, param_space, var_space)

Set neuron, its parameters and initial variables.

def add_to (self, model_spec, num_neurons)

Add this NeuronGroup to a model.

def add_extra_global_param (self, param_name, param_values)

Add extra global parameter.

• def load (self, slm, scalar)

Loads neuron group.

• def reinitialise (self, slm, scalar)

Reinitialise neuron group.

Public Attributes

- neuron
- spikes
- · spike_count
- spike_que_ptr
- is_spike_source_array
- type
- pop

19.63.1 Detailed Description

Class representing a group of neurons.

19.63.2 Constructor & Destructor Documentation

Init NeuronGroup.

Parameters

```
name string name of the group
```

19.63.3 Member Function Documentation

19.63.3.1 add_extra_global_param()

```
param_name,
param_values )
```

Add extra global parameter.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.63.3.2 add_to()

Add this NeuronGroup to a model.

Parameters

model_spec	pygenn.genn_model.GeNNModel to add to	
num_neurons	int number of neurons	

19.63.3.3 current_spikes()

```
\label{lem:current_spikes} \mbox{ def pygenn.genn_groups.NeuronGroup.current_spikes (} \\ self \mbox{ )}
```

Current spikes from GeNN.

19.63.3.4 delay_slots()

```
\label{lem:condition} \mbox{def pygenn.genn\_groups.NeuronGroup.delay\_slots (} \\ self \mbox{)}
```

Maximum delay steps needed for this group.

19.63.3.5 load()

```
def pygenn.genn_groups.NeuronGroup.load ( self, \\ slm, \\ scalar )
```

Loads neuron group.

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

19.63.3.6 reinitialise()

```
def pygenn.genn_groups.NeuronGroup.reinitialise ( self, \\ slm, \\ scalar )
```

Reinitialise neuron group.

Parameters

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

19.63.3.7 set_neuron()

Set neuron, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

19.63.3.8 size()

```
\label{eq:condition} \mbox{def pygenn.genn\_groups.NeuronGroup.size (} \\ self \mbox{)}
```

19.63.4 Member Data Documentation

19.63.4.1 is_spike_source_array

pygenn.genn_groups.NeuronGroup.is_spike_source_array

19.63.4.2 neuron

pygenn.genn_groups.NeuronGroup.neuron

19.63.4.3 pop

pygenn.genn_groups.NeuronGroup.pop

19.63.4.4 spike_count

pygenn.genn_groups.NeuronGroup.spike_count

19.63.4.5 spike_que_ptr

pygenn.genn_groups.NeuronGroup.spike_que_ptr

19.63.4.6 spikes

pygenn.genn_groups.NeuronGroup.spikes

19.63.4.7 type

pygenn.genn_groups.NeuronGroup.type


The documentation for this class was generated from the following file:

• genn_groups.py

19.64 NeuronGroup Class Reference

#include <neuronGroup.h>

Inheritance diagram for NeuronGroup:



Public Member Functions

- NeuronGroup (const NeuronGroup &)=delete
- NeuronGroup ()=delete
- void setSpikeLocation (VarLocation loc)

Set location of this neuron group's output spikes.

void setSpikeEventLocation (VarLocation loc)

Set location of this neuron group's output spike events.

void setSpikeTimeLocation (VarLocation loc)

Set location of this neuron group's output spike times.

void setVarLocation (const std::string &varName, VarLocation loc)

Set variable location of neuron model state variable.

void setExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of neuron model extra global parameter.

const std::string & getName () const

unsigned int getNumNeurons () const

Gets number of neurons in group.

const NeuronModels::Base * getNeuronModel () const

Gets the neuron model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- int getClusterHostID () const
- bool isSpikeTimeRequired () const
- bool isTrueSpikeRequired () const
- bool isSpikeEventRequired () const
- unsigned int getNumDelaySlots () const
- bool isDelayRequired () const
- bool isZeroCopyEnabled () const
- · VarLocation getSpikeLocation () const

Get location of this neuron group's output spikes.

· VarLocation getSpikeEventLocation () const

Get location of this neuron group's output spike events.

VarLocation getSpikeTimeLocation () const

Get location of this neuron group's output spike times.

VarLocation getVarLocation (const std::string &varName) const

Get location of neuron model state variable by name.

VarLocation getVarLocation (size_t index) const

Get location of neuron model state variable by index.

VarLocation getExtraGlobalParamLocation (const std::string ¶mName) const

Get location of neuron model extra global parameter by name.

VarLocation getExtraGlobalParamLocation (size_t index) const

Get location of neuron model extra global parameter by omdex.

• bool isSimRNGRequired () const

Does this neuron group require an RNG to simulate?

· bool isInitRNGRequired () const

Does this neuron group require an RNG for it's init code?

bool hasOutputToHost (int targetHostID) const

Does this neuron group have outgoing connections specified host id?

Protected Member Functions

- NeuronGroup (const std::string &name, int numNeurons, const NeuronModels::Base *neuronModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation default← VarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)
- void checkNumDelaySlots (unsigned int requiredDelay)

Checks delay slots currently provided by the neuron group against a required delay and extends if required.

• void updatePreVarQueues (const std::string &code)

Update which presynaptic variables require queues based on piece of code.

void updatePostVarQueues (const std::string &code)

Update which postsynaptic variables require queues based on piece of code.

- void addSpkEventCondition (const std::string &code, const std::string &supportCodeNamespace)
- void addlnSyn (SynapseGroupInternal *synapseGroup)
- void addOutSyn (SynapseGroupInternal *synapseGroup)
- void initDerivedParams (double dt)
- void mergeIncomingPSM (bool merge)

Merge incoming postsynaptic models.

• void injectCurrent (CurrentSourceInternal *source)

add input current source

• const std::vector< SynapseGroupInternal * > & getInSyn () const

Gets pointers to all synapse groups which provide input to this neuron group.

- const std::vector< std::pair< SynapseGroupInternal *, std::vector< SynapseGroupInternal *>>> & get
 MergedInSyn () const
- const std::vector< SynapseGroupInternal * > & getOutSyn () const

Gets pointers to all synapse groups emanating from this neuron group.

const std::vector< CurrentSourceInternal * > & getCurrentSources () const

Gets pointers to all current sources which provide input to this neuron group.

- const std::vector< double > & getDerivedParams () const
- bool isParamRequiredBySpikeEventCondition (const std::string &pnamefull) const

Do any of the spike event conditions tested by this neuron require specified parameter?

• std::string getCurrentQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables this timestep.

• std::string getPrevQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables in previous timestep.

- bool isVarQueueRequired (const std::string &var) const
- bool isVarQueueRequired (size_t index) const

19.64.1 Constructor & Destructor Documentation

19.64.2 Member Function Documentation

```
19.64.2.1 addlnSyn()
void NeuronGroup::addInSyn (
              SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.64.2.2 addOutSyn()
void NeuronGroup::addOutSyn (
             SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.64.2.3 addSpkEventCondition()
void NeuronGroup::addSpkEventCondition (
             const std::string & code,
             const std::string & supportCodeNamespace ) [protected]
19.64.2.4 checkNumDelaySlots()
void NeuronGroup::checkNumDelaySlots (
             unsigned int requiredDelay ) [protected]
Checks delay slots currently provided by the neuron group against a required delay and extends if required.
19.64.2.5 getClusterHostID()
int NeuronGroup::getClusterHostID ( ) const [inline]
19.64.2.6 getCurrentQueueOffset()
std::string NeuronGroup::getCurrentQueueOffset (
             const std::string & devPrefix ) const [protected]
Get the expression to calculate the queue offset for accessing state of variables this timestep.
19.64.2.7 getCurrentSources()
const std::vector<CurrentSourceInternal*>& NeuronGroup::getCurrentSources ( ) const [inline],
[protected]
Gets pointers to all current sources which provide input to this neuron group.
19.64.2.8 getDerivedParams()
const std::vector<double>& NeuronGroup::getDerivedParams ( ) const [inline], [protected]
19.64.2.9 getExtraGlobalParamLocation() [1/2]
VarLocation NeuronGroup::getExtraGlobalParamLocation (
             const std::string & paramName ) const
```

Get location of neuron model extra global parameter by name.

This is only used by extra global parameters which are pointers

```
19.64.2.10 getExtraGlobalParamLocation() [2/2]
VarLocation NeuronGroup::getExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.64.2.11 getInSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getInSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups which provide input to this neuron group.
19.64.2.12 getMergedInSyn()
const std::vector<std::pair<SynapseGroupInternal*, std::vector<SynapseGroupInternal*> > >&
NeuronGroup::getMergedInSyn ( ) const [inline], [protected]
19.64.2.13 getName()
const std::string& NeuronGroup::getName ( ) const [inline]
19.64.2.14 getNeuronModel()
const NeuronModels::Base* NeuronGroup::getNeuronModel ( ) const [inline]
Gets the neuron model used by this group.
19.64.2.15 getNumDelaySlots()
unsigned int NeuronGroup::getNumDelaySlots ( ) const [inline]
19.64.2.16 getNumNeurons()
unsigned int NeuronGroup::getNumNeurons ( ) const [inline]
Gets number of neurons in group.
19.64.2.17 getOutSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getOutSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups emanating from this neuron group.
19.64.2.18 getParams()
const std::vector<double>& NeuronGroup::getParams ( ) const [inline]
```

```
19.64.2.19 getPrevQueueOffset()
```

Get the expression to calculate the queue offset for accessing state of variables in previous timestep.

```
19.64.2.20 getSpikeEventCondition()
```

```
const std::set<std::pair<std::string, std::string> >& NeuronGroup::getSpikeEventCondition ( )
const [inline], [protected]
```

19.64.2.21 getSpikeEventLocation()

```
VarLocation NeuronGroup::getSpikeEventLocation ( ) const [inline]
```

Get location of this neuron group's output spike events.

19.64.2.22 getSpikeLocation()

```
VarLocation NeuronGroup::getSpikeLocation ( ) const [inline]
```

Get location of this neuron group's output spikes.

19.64.2.23 getSpikeTimeLocation()

```
VarLocation NeuronGroup::getSpikeTimeLocation ( ) const [inline]
```

Get location of this neuron group's output spike times.

19.64.2.24 getVarInitialisers()

19.64.2.25 getVarLocation() [1/2]

Get location of neuron model state variable by name.

```
19.64.2.26 getVarLocation() [2/2]
```

Get location of neuron model state variable by index.

19.64.2.27 hasOutputToHost()

Does this neuron group have outgoing connections specified host id?

```
19.64.2.28 initDerivedParams()
void NeuronGroup::initDerivedParams (
              double dt ) [protected]
19.64.2.29 injectCurrent()
void NeuronGroup::injectCurrent (
              CurrentSourceInternal * source ) [protected]
add input current source
19.64.2.30 isDelayRequired()
bool NeuronGroup::isDelayRequired ( ) const [inline]
19.64.2.31 isInitRNGRequired()
bool NeuronGroup::isInitRNGRequired ( ) const
Does this neuron group require an RNG for it's init code?
19.64.2.32 isParamRequiredBySpikeEventCondition()
bool NeuronGroup::isParamRequiredBySpikeEventCondition (
              const std::string & pnamefull ) const [protected]
Do any of the spike event conditions tested by this neuron require specified parameter?
19.64.2.33 isSimRNGRequired()
bool NeuronGroup::isSimRNGRequired ( ) const
Does this neuron group require an RNG to simulate?
19.64.2.34 isSpikeEventRequired()
bool NeuronGroup::isSpikeEventRequired ( ) const
19.64.2.35 isSpikeTimeRequired()
bool NeuronGroup::isSpikeTimeRequired ( ) const
19.64.2.36 isTrueSpikeRequired()
bool NeuronGroup::isTrueSpikeRequired ( ) const
```

19.64.2.37 isVarQueueRequired() [1/2]

bool NeuronGroup::isVarQueueRequired (

```
const std::string & var ) const [protected]
```

19.64.2.38 isVarQueueRequired() [2/2]

19.64.2.39 isZeroCopyEnabled()

```
bool NeuronGroup::isZeroCopyEnabled ( ) const
```

19.64.2.40 mergeIncomingPSM()

Merge incoming postsynaptic models.

19.64.2.41 setExtraGlobalParamLocation()

Set location of neuron model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.64.2.42 setSpikeEventLocation()

Set location of this neuron group's output spike events.

This is ignored for simulations on hardware with a single memory space

19.64.2.43 setSpikeLocation()

Set location of this neuron group's output spikes.

This is ignored for simulations on hardware with a single memory space

19.64.2.44 setSpikeTimeLocation()

Set location of this neuron group's output spike times.

This is ignored for simulations on hardware with a single memory space

19.64.2.45 setVarLocation()

Set variable location of neuron model state variable.

This is ignored for simulations on hardware with a single memory space

19.64.2.46 updatePostVarQueues()

Update which postsynaptic variables require queues based on piece of code.

19.64.2.47 updatePreVarQueues()

Update which presynaptic variables require queues based on piece of code.


The documentation for this class was generated from the following files:

- · neuronGroup.h
- neuronGroup.cc

19.65 NeuronGroupInternal Class Reference

```
#include <neuronGroupInternal.h>
```

Inheritance diagram for NeuronGroupInternal:



Public Member Functions

NeuronGroupInternal (const std::string &name, int numNeurons, const NeuronModels::Base *neuronModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)

Additional Inherited Members

19.65.1 Constructor & Destructor Documentation

19.65.1.1 NeuronGroupInternal()

```
const NeuronModels::Base * neuronModel,
const std::vector< double > & params,
const std::vector< Models::VarInit > & varInitialisers,
VarLocation defaultVarLocation,
VarLocation defaultExtraGlobalParamLocation,
int hostID ) [inline]
```

The documentation for this class was generated from the following file:


· neuronGroupInternal.h

19.66 InitVarSnippet::Normal Class Reference

Initialises variable by sampling from the normal distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Normal:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Normal, 2)
- SET_CODE ("\$(value) = \$(mean) + (\$(gennrand_normal) * \$(sd));")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.66.1 Detailed Description

Initialises variable by sampling from the normal distribution.

This snippet takes 2 parameters:

- mean The mean
- sd The standard distribution

19.66.2 Member Function Documentation

19.66.2.1 DECLARE_SNIPPET()

19.66.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Normal::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.66.2.3 SET_CODE()

```
InitVarSnippet::Normal::SET_CODE ( )
```


The documentation for this class was generated from the following file:

· initVarSnippet.h

19.67 SpineMLSimulator::ModelProperty::NormalDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::NormalDistribution:



Public Member Functions

- NormalDistribution (const pugi::xml_node &node, const StateVar < scalar > &stateVar, unsigned int size)
- void setValue (scalar mean, scalar variance)

19.67.1 Constructor & Destructor Documentation

19.67.1.1 NormalDistribution()

19.67.2 Member Function Documentation

19.67.2.1 setValue()

The documentation for this class was generated from the following files:

modelProperty.h

modelProperty.cc

19.68 CodeGenerator::CodeStream::OB Struct Reference

An open bracket marker.

```
#include <codeStream.h>
```

Public Member Functions

• OB (unsigned int level)

Public Attributes

· const unsigned int Level

19.68.1 Detailed Description

An open bracket marker.

Write to code stream os using:

```
os << OB(16);
```

19.68.2 Constructor & Destructor Documentation

19.68.2.1 OB()

```
CodeGenerator::CodeStream::OB::OB (
     unsigned int level ) [inline]
```

19.68.3 Member Data Documentation

19.68.3.1 Level

```
const unsigned int CodeGenerator::CodeStream::OB::Level
```

The documentation for this struct was generated from the following file:


· codeStream.h

19.69 InitSparseConnectivitySnippet::OneToOne Class Reference

Initialises connectivity to a 'one-to-one' diagonal matrix.

```
#include <initSparseConnectivitySnippet.h>
```

 $Inheritance\ diagram\ for\ InitSparseConnectivitySnippet::OneToOne:$



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::OneToOne, 0)
- SET_ROW_BUILD_CODE ("\$(addSynapse, \$(id_pre));\ "\$(endRow);\")
- SET_MAX_ROW_LENGTH (1)
- SET_MAX_COL_LENGTH (1)

Additional Inherited Members

19.69.1 Detailed Description

Initialises connectivity to a 'one-to-one' diagonal matrix.

19.69.2 Member Function Documentation

19.69.2.1 DECLARE_SNIPPET()

19.69.2.2 SET_MAX_COL_LENGTH()

```
\label{lem:condition} In it Sparse Connectivity Snippet:: One To One:: SET\_MAX\_COL\_LENGTH \ ( \\ 1 \ )
```

19.69.2.3 SET_MAX_ROW_LENGTH()

```
\label{lem:conetivitySnippet::OneToOne::SET_MAX_ROW_LENGTH ( } 1 \quad )
```

19.69.2.4 SET_ROW_BUILD_CODE()

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.70 Snippet::Base::ParamVal Struct Reference

Additional input variables, row state variables and other things have a name, a type and an initial value.

```
#include <snippet.h>
```

Public Attributes

- std::string name
- · std::string type
- double value

19.70.1 Detailed Description

Additional input variables, row state variables and other things have a name, a type and an initial value.

19.70.2 Member Data Documentation

19.70.2.1 name

```
std::string Snippet::Base::ParamVal::name
```

19.70.2.2 type

```
std::string Snippet::Base::ParamVal::type
```

19.70.2.3 value

```
double Snippet::Base::ParamVal::value
```

The documentation for this struct was generated from the following file:


· snippet.h

19.71 WeightUpdateModels::PiecewiseSTDP Class Reference

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

```
#include <weightUpdateModels.h>
```

 $Inheritance\ diagram\ for\ Weight Update Models:: Piecewise STDP:$



Public Member Functions

- DECLARE_WEIGHT_UPDATE_MODEL (PiecewiseSTDP, 10, 2, 0, 0)
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

virtual std::string getLearnPostCode () const override

Gets code to include in the learnSynapsesPost kernel/function.

- virtual DerivedParamVec getDerivedParams () const override
- virtual bool isPreSpikeTimeRequired () const override

Whether presynaptic spike times are needed or not.

· virtual bool isPostSpikeTimeRequired () const override


Whether postsynaptic spike times are needed or not.


Additional Inherited Members

19.71.1 Detailed Description

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

The STDP window is defined as a piecewise function:





The STDP curve is applied to the raw synaptic conductance gRaw, which is then filtered through the sugmoidal filter displayed above to obtain the value of g.

Note

The STDP curve implies that unpaired pre- and post-synaptic spikes incur a negative increment in gRaw (and hence in g).

The time of the last spike in each neuron, "sTXX", where XX is the name of a neuron population is (somewhat arbitrarily) initialised to -10.0 ms. If neurons never spike, these spike times are used.

It is the raw synaptic conductance gRaw that is subject to the STDP rule. The resulting synaptic conductance is a sigmoid filter of gRaw. This implies that g is initialised but not gRaw, the synapse will revert to the value that corresponds to gRaw.

An example how to use this synapse correctly is given in map_classol.cc (MBody1 userproject):

```
for (int i= 0; i < model.neuronN[1]*model.neuronN[3]; i++) {
    if (gKCDN[i] < 2.0*SCALAR_MIN) {
        cnt++;
        fprintf(stdout, "Too low conductance value %e detected and set to 2*SCALAR_MIN= %e, at index %d
    \n", gKCDN[i], 2*SCALAR_MIN, i);
        gKCDN[i] = 2.0*SCALAR_MIN; //to avoid log(0)/0 below
    }
    scalar tmp = gKCDN[i] / myKCDN_p[5]*2.0;
    gRawKCDN[i] = 0.5 * log( tmp / (2.0 - tmp)) /myKCDN_p[7] + myKCDN_p[6];
}
cerr << "Total number of low value corrections: " << cnt << endl;</pre>
```

Note

One cannot set values of g fully to 0, as this leads to gRaw = -infinity and this is not support. I.e., 'g' needs to be some nominal value > 0 (but can be extremely small so that it acts like it's 0).

The model has 2 variables:

- g: conductance of scalar type
- gRaw: raw conductance of scalar type

Parameters are (compare to the figure above):

- tLrn: Time scale of learning changes
- · tChng: Width of learning window
- tDecay: Time scale of synaptic strength decay
- tPunish10: Time window of suppression in response to 1/0
- tPunish01: Time window of suppression in response to 0/1
- gMax: Maximal conductance achievable
- gMid: Midpoint of sigmoid g filter curve
- gSlope: Slope of sigmoid g filter curve
- tauShift: Shift of learning curve
- gSyn0: Value of syn conductance g decays to

19.71.2 Member Function Documentation

19.71.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.71.2.2 getDerivedParams()

```
virtual DerivedParamVec WeightUpdateModels::PiecewiseSTDP::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.71.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::PiecewiseSTDP::getLearnPostCode ( ) const [inline],
[override], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented from WeightUpdateModels::Base.

19.71.2.4 getParamNames()

```
virtual StringVec WeightUpdateModels::PiecewiseSTDP::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.71.2.5 getSimCode()

```
virtual std::string WeightUpdateModels::PiecewiseSTDP::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.71.2.6 getVars()

```
virtual VarVec WeightUpdateModels::PiecewiseSTDP::getVars ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.71.2.7 isPostSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPostSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether postsynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

19.71.2.8 isPreSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPreSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether presynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

The documentation for this class was generated from the following file:


· weightUpdateModels.h

19.72 NeuronModels::Poisson Class Reference

Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Poisson:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

• virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

· virtual EGPVec getExtraGlobalParams () const override

Static Public Member Functions

static const NeuronModels::Poisson * getInstance ()

Additional Inherited Members

19.72.1 Detailed Description

Poisson neurons.

Poisson neurons have constant membrane potential (Vrest) unless they are activated randomly to the Vspike value if (t-SpikeTime) > trefract.

It has 2 variables:

- ∨ Membrane potential (mV)
- SpikeTime Time at which the neuron spiked for the last time (ms)

and 4 parameters:

- trefract Refractory period (ms)
- tspike duration of spike (ms)
- Vspike Membrane potential at spike (mV)
- Vrest Membrane potential at rest (mV)

Note

The initial values array for the Poisson type needs two entries for V, and SpikeTime and the parameter array needs four entries for therate, trefract, Vspike and Vrest, *in that order*.

This model uses a linear approximation for the probability of firing a spike in a given time step of size DT, i.e. the probability of firing is λ times DT: $p = \lambda \Delta t$. This approximation is usually very good, especially for typical, quite small time steps and moderate firing rates. However, it is worth noting that the approximation becomes poor for very high firing rates and large time steps.

19.72.2 Member Typedef Documentation

19.72.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::Poisson::ParamValues

19.72.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Poisson::PostVarValues

19.72.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Poisson::PreVarValues

19.72.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::Poisson::VarValues

19.72.3 Member Function Documentation

19.72.3.1 getExtraGlobalParams()

```
virtual EGPVec NeuronModels::Poisson::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

19.72.3.2 getInstance()

static const NeuronModels::Poisson* NeuronModels::Poisson::getInstance () [inline], [static]

19.72.3.3 getParamNames()

virtual StringVec NeuronModels::Poisson::getParamNames () const [inline], [override], [virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.72.3.4 getSimCode()

```
virtual std::string NeuronModels::Poisson::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.72.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::Poisson::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.72.3.6 getVars()

```
virtual VarVec NeuronModels::Poisson::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


· neuronModels.h

19.73 NeuronModels::PoissonNew Class Reference

Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::PoissonNew:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 1 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

· virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- virtual DerivedParamVec getDerivedParams () const override
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

• static const NeuronModels::PoissonNew * getInstance ()

Additional Inherited Members

19.73.1 Detailed Description

Poisson neurons.

It has 1 state variable:

• timeStepToSpike - Number of timesteps to next spike

and 1 parameter:

• rate - Mean firing rate (Hz)

Note

Internally this samples from the exponential distribution using the C++ 11 <random> library on the CPU and by transforming the uniform distribution, generated using cuRAND, with a natural log on the GPU.

19.73.2 Member Typedef Documentation

19.73.2.1 ParamValues

```
typedef Snippet::ValueBase< 1 > NeuronModels::PoissonNew::ParamValues
```

19.73.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PostVarValues

19.73.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PreVarValues

19.73.2.4 VarValues

typedef Models::VarInitContainerBase< 1 > NeuronModels::PoissonNew::VarValues

19.73.3 Member Function Documentation

19.73.3.1 getDerivedParams()

```
virtual DerivedParamVec NeuronModels::PoissonNew::getDerivedParams ( ) const [inline], [override],
[virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.73.3.2 getInstance()

```
static const NeuronModels::PoissonNew* NeuronModels::PoissonNew::getInstance ( ) [inline],
[static]
```

19.73.3.3 getParamNames()

```
virtual StringVec NeuronModels::PoissonNew::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.73.3.4 getSimCode()

```
virtual std::string NeuronModels::PoissonNew::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.73.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::PoissonNew::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.73.3.6 getVars()

```
virtual VarVec NeuronModels::PoissonNew::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.73.3.7 SET_NEEDS_AUTO_REFRACTORY()


The documentation for this class was generated from the following file:

· neuronModels.h

19.74 SpineMLSimulator::Input::PoissonSpikeRate Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::PoissonSpikeRate:



Public Member Functions

PoissonSpikeRate (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)

Protected Member Functions

virtual double getTimeToSpike (double isiMs)

Additional Inherited Members

19.74.1 Constructor & Destructor Documentation

19.74.1.1 PoissonSpikeRate()

19.74.2 Member Function Documentation

19.74.2.1 getTimeToSpike()

```
\label{lem:constraint} \mbox{double SpineMLSimulator::Input::PoissonSpikeRate::getTimeToSpike (} \\ \mbox{double } isiMs \mbox{)} \mbox{ [protected], [virtual]}
```

Implements SpineMLSimulator::Input::InterSpikeIntervalBase.

The documentation for this class was generated from the following files:

- · input.h
- input.cc

19.75 CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan Class Reference

Postsynaptic parallelism.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan:

```
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base

CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan
```

Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override
 Get the number of threads that presynaptic updates should be parallelised across.
- virtual bool isCompatible (const SynapseGroupInternal &sg) const override

Is this presynaptic update strategy compatible with a given synapse group?

 virtual bool shouldAccumulateInRegister (const SynapseGroupInternal &sg, const Backend &backend) const override

Are input currents emitted by this presynaptic update accumulated into a register?

virtual bool shouldAccumulateInSharedMemory (const SynapseGroupInternal &sg, const Backend &backend) const override

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

 virtual void genCode (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, BackendBase::SynapseGroup

Handler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler) const override

Generate presynaptic update code.

19.75.1 Detailed Description

Postsynaptic parallelism.

19.75.2 Member Function Documentation

19.75.2.1 genCode()

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.2 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.3 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.4 shouldAccumulateInRegister()

Are input currents emitted by this presynaptic update accumulated into a register?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.5 shouldAccumulateInSharedMemory()

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.


The documentation for this class was generated from the following files:

- presynapticUpdateStrategy.h
- presynapticUpdateStrategy.cc

19.76 CodeGenerator::SingleThreadedCPU::Preferences Struct Reference

```
#include <backend.h>
```

 $Inheritance\ diagram\ for\ Code Generator :: Single Threaded CPU :: Preferences:$



Additional Inherited Members

The documentation for this struct was generated from the following file:


· single threaded cpu/backend.h

19.77 CodeGenerator::CUDA::Preferences Struct Reference

Preferences for CUDA backend.

#include <backend.h>

Inheritance diagram for CodeGenerator::CUDA::Preferences:



Public Member Functions

• Preferences ()

Public Attributes

• bool showPtxInfo = false

Should PTX assembler information be displayed for each CUDA kernel during compilation?

• bool generateLineInfo = false

Should line info be included in resultant executable for debugging/profiling purposes?

• DeviceSelect deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

• unsigned int manualDeviceID = 0

If device select method is set to DeviceSelect::MANUAL, id of device to use.

• BlockSizeSelect blockSizeSelectMethod = BlockSizeSelect::OCCUPANCY

How to select CUDA blocksize.

· KernelBlockSize manualBlockSizes

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

std::string userNvccFlags = ""

NVCC compiler options for all GPU code.

19.77.1 Detailed Description

Preferences for CUDA backend.

19.77.2 Constructor & Destructor Documentation

19.77.2.1 Preferences()

CodeGenerator::CUDA::Preferences::Preferences () [inline]

19.77.3 Member Data Documentation

19.77.3.1 blockSizeSelectMethod

BlockSizeSelect CodeGenerator::CUDA::Preferences::blockSizeSelectMethod = BlockSizeSelect::OC← CUPANCY

How to select CUDA blocksize.

19.77.3.2 deviceSelectMethod

DeviceSelect CodeGenerator::CUDA::Preferences::deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

19.77.3.3 generateLineInfo

```
bool CodeGenerator::CUDA::Preferences::generateLineInfo = false
```

Should line info be included in resultant executable for debugging/profiling purposes?

19.77.3.4 manualBlockSizes

```
KernelBlockSize CodeGenerator::CUDA::Preferences::manualBlockSizes
```

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

19.77.3.5 manualDeviceID

```
unsigned int CodeGenerator::CUDA::Preferences::manualDeviceID = 0
```

If device select method is set to DeviceSelect::MANUAL, id of device to use.

19.77.3.6 showPtxInfo

```
bool CodeGenerator::CUDA::Preferences::showPtxInfo = false
```

Should PTX assembler information be displayed for each CUDA kernel during compilation?

19.77.3.7 userNvccFlags

```
std::string CodeGenerator::CUDA::Preferences::userNvccFlags = ""
```

NVCC compiler options for all GPU code.

The documentation for this struct was generated from the following file:


· cuda/backend.h

19.78 CodeGenerator::PreferencesBase Struct Reference

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

#include <backendBase.h>

Inheritance diagram for CodeGenerator::PreferencesBase:



Public Attributes

bool optimizeCode = false

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

bool debugCode = false

Generate code with debug symbols.

std::string userCxxFlagsGNU = ""

C++ compiler options to be used for building all host side code (used for unix based platforms)

std::string userNvccFlagsGNU = ""

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

plog::Severity logLevel = plog::info

Logging level to use for code generation.

19.78.1 Detailed Description

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

19.78.2 Member Data Documentation

19.78.2.1 debugCode

bool CodeGenerator::PreferencesBase::debugCode = false

Generate code with debug symbols.

19.78.2.2 logLevel

plog::Severity CodeGenerator::PreferencesBase::logLevel = plog::info

Logging level to use for code generation.

19.78.2.3 optimizeCode

bool CodeGenerator::PreferencesBase::optimizeCode = false

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

19.78.2.4 userCxxFlagsGNU

std::string CodeGenerator::PreferencesBase::userCxxFlagsGNU = ""

C++ compiler options to be used for building all host side code (used for unix based platforms)

19.78.2.5 userNvccFlagsGNU

```
std::string CodeGenerator::PreferencesBase::userNvccFlagsGNU = ""
```

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

The documentation for this struct was generated from the following file:


· backendBase.h

19.79 CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan Class Reference

Presynaptic parallelism.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan:



Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override
 Get the number of threads that presynaptic updates should be parallelised across.
- virtual bool isCompatible (const SynapseGroupInternal &sg) const override
- Is this presynaptic update strategy compatible with a given synapse group?
- virtual bool shouldAccumulateInRegister (const SynapseGroupInternal &sg, const Backend &backend) const override

Are input currents emitted by this presynaptic update accumulated into a register?

virtual bool shouldAccumulateInSharedMemory (const SynapseGroupInternal &sg, const Backend &backend) const override

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

 virtual void genCode (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, BackendBase::SynapseGroup

Handler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler) const override

Generate presynaptic update code.

19.79.1 Detailed Description

Presynaptic parallelism.

19.79.2 Member Function Documentation

19.79.2.1 genCode()

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.79.2.2 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.79.2.3 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.79.2.4 shouldAccumulateInRegister()

Are input currents emitted by this presynaptic update accumulated into a register?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.79.2.5 shouldAccumulateInSharedMemory()

Are input currents emitted by this presynaptic update accumulated into a shared memory array?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.


The documentation for this class was generated from the following files:

- presynapticUpdateStrategy.h
- presynapticUpdateStrategy.cc

19.80 SpineMLSimulator::Input::RegularSpikeRate Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::RegularSpikeRate:



Public Member Functions

RegularSpikeRate (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)

Protected Member Functions

virtual double getTimeToSpike (double isiMs) override

Additional Inherited Members

19.80.1 Constructor & Destructor Documentation

19.80.1.1 RegularSpikeRate()

19.80.2 Member Function Documentation

19.80.2.1 getTimeToSpike()

```
\label{lem:condition} \mbox{double SpineMLSimulator::Input::RegularSpikeRate::getTimeToSpike (} \\ \mbox{double } isiMs \mbox{) [override], [protected], [virtual]}
```

Implements SpineMLSimulator::Input::InterSpikeIntervalBase.

The documentation for this class was generated from the following files:


- input.h
- · input.cc

19.81 NeuronModels::RulkovMap Class Reference

Rulkov Map neuron.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::RulkovMap:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

• virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

static const NeuronModels::RulkovMap * getInstance ()

Additional Inherited Members

19.81.1 Detailed Description

Rulkov Map neuron.

The RulkovMap type is a map based neuron model based on [5] but in the 1-dimensional map form used in [4]:

$$V(t + \Delta t) = \begin{cases} V_{\text{spike}} \left(\frac{\alpha V_{\text{spike}}}{V_{\text{spike}} - V(t)\beta I_{\text{syn}}} + y \right) & V(t) \leq 0 \\ V_{\text{spike}} \left(\alpha + y \right) & V(t) \leq V_{\text{spike}} \left(\alpha + y \right) \& V(t - \Delta t) \leq 0 \\ -V_{\text{spike}} & \text{otherwise} \end{cases}$$

Note

The RulkovMap type only works as intended for the single time step size of DT= 0.5.

The RulkovMap type has 2 variables:

- V the membrane potential
- $\ensuremath{\text{preV}}$ the membrane potential at the previous time step

and it has 4 parameters:

- Vspike determines the amplitude of spikes, typically -60mV
- alpha determines the shape of the iteration function, typically $\alpha=3$
- y "shift / excitation" parameter, also determines the iteration function, originally, y= -2.468
- beta roughly speaking equivalent to the input resistance, i.e. it regulates the scale of the input into the neuron, typically β = 2.64 M Ω .

Note

The initial values array for the RulkovMap type needs two entries for V and Vpre and the parameter array needs four entries for Vspike, alpha, y and beta, in that order.

19.81.2 Member Typedef Documentation

19.81.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::RulkovMap::ParamValues

19.81.2.2 PostVarValues

 $\verb|typedef| Models:: VarInitContainerBase < 0> NeuronModels:: RulkovMap:: PostVarValues | Pos$

19.81.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::RulkovMap::PreVarValues

19.81.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::RulkovMap::VarValues

19.81.3 Member Function Documentation

19.81.3.1 getDerivedParams()

```
virtual DerivedParamVec NeuronModels::RulkovMap::getDerivedParams ( ) const [inline], [override],
[virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.81.3.2 getInstance()

```
static const NeuronModels::RulkovMap* NeuronModels::RulkovMap::getInstance ( ) [inline], [static]
```

19.81.3.3 getParamNames()

```
virtual StringVec NeuronModels::RulkovMap::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.81.3.4 getSimCode()

```
virtual std::string NeuronModels::RulkovMap::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.81.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::RulkovMap::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V>20").

Reimplemented from NeuronModels::Base.

19.81.3.6 getVars()

```
virtual VarVec NeuronModels::RulkovMap::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:

neuronModels.h

19.82 SpineMLSimulator::InputValue::ScalarBase Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ScalarBase:

```
SpineMLSimulator::InputValue::Base

SpineMLSimulator::InputValue::ScalarBase

SpineMLSimulator::InputValue::Constant

SpineMLSimulator::InputValue::TimeVarying
```

Protected Member Functions

- ScalarBase (unsigned int numNeurons, const pugi::xml_node &node)
- void applyScalar (double value, std::function< void(unsigned int, double)> applyValueFunc) const

Additional Inherited Members

19.82.1 Constructor & Destructor Documentation

19.82.1.1 ScalarBase()

```
SpineMLSimulator::InputValue::ScalarBase::ScalarBase (
          unsigned int numNeurons,
          const pugi::xml_node & node ) [inline], [protected]
```

19.82.2 Member Function Documentation

19.82.2.1 applyScalar()

The documentation for this class was generated from the following files:

- inputValue.h
- inputValue.cc

19.83 CodeGenerator::CodeStream::Scope Class Reference

```
#include <codeStream.h>
```

Public Member Functions

- Scope (CodeStream &codeStream)
- ∼Scope ()

19.83.1 Constructor & Destructor Documentation

The documentation for this class was generated from the following files:

- codeStream.h
- · codeStream.cc

19.84 SharedLibraryModel < scalar > Class Template Reference

```
#include <sharedLibraryModel.h>
```

Public Member Functions

- SharedLibraryModel ()
- SharedLibraryModel (const std::string &pathToModel, const std::string &modelName)
- virtual ∼SharedLibraryModel ()
- bool open (const std::string &pathToModel, const std::string &modelName)
- void allocateExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- void freeExtraGlobalParam (const std::string &popName, const std::string &varName)
- void pullStateFromDevice (const std::string &popName)
- void pullSpikesFromDevice (const std::string &popName)
- void pullCurrentSpikesFromDevice (const std::string &popName)
- void pullConnectivityFromDevice (const std::string &popName)
- void pullVarFromDevice (const std::string &popName, const std::string &varName)
- · void pullExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- void pushStateToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushSpikesToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushCurrentSpikesToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushConnectivityToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushVarToDevice (const std::string &popName, const std::string &varName, bool uninitialisedOnly=false)
- void pushExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- template<typename T >

T * getArray (const std::string &varName)

 $\bullet \ \ template {<} typename \ T >$

T * getScalar (const std::string &varName)

- void allocateMem ()
- void freeMem ()
- void initialize ()
- void initializeSparse ()
- void stepTime ()
- scalar getTime () const
- unsigned long long getTimestep () const
- void setTime (scalar t)
- void setTimestep (unsigned long long iT)
- void * getSymbol (const std::string &symbolName, bool allowMissing=false, void *defaultSymbol=nullptr)

19.84.1 Constructor & Destructor Documentation

```
19.84.1.1 SharedLibraryModel() [1/2]
template<typename scalar = float>
SharedLibraryModel< scalar >::SharedLibraryModel ( ) [inline]
19.84.1.2 SharedLibraryModel() [2/2]
template<typename scalar = float>
SharedLibraryModel< scalar >::SharedLibraryModel (
             const std::string & pathToModel,
             const std::string & modelName ) [inline]
19.84.1.3 ~SharedLibraryModel()
template<typename scalar = float>
virtual SharedLibraryModel< scalar >::~SharedLibraryModel ( ) [inline], [virtual]
19.84.2 Member Function Documentation
19.84.2.1 allocateExtraGlobalParam()
template<typename scalar = float>
void SharedLibraryModel< scalar >::allocateExtraGlobalParam (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.84.2.2 allocateMem()
template<typename scalar = float>
void SharedLibraryModel< scalar >::allocateMem ( ) [inline]
19.84.2.3 freeExtraGlobalParam()
template<typename scalar = float>
void SharedLibraryModel< scalar >::freeExtraGlobalParam (
             const std::string & popName,
             const std::string & varName ) [inline]
19.84.2.4 freeMem()
template<typename scalar = float>
void SharedLibraryModel< scalar >::freeMem ( ) [inline]
```

```
19.84.2.5 getArray()
template<typename scalar = float>
template < typename T >
T* \ SharedLibraryModel< \ scalar >:: getArray \ (
             const std::string & varName ) [inline]
19.84.2.6 getScalar()
template<typename scalar = float>
template < typename T >
T* SharedLibraryModel< scalar >::getScalar (
             const std::string & varName ) [inline]
19.84.2.7 getSymbol()
template<typename scalar = float>
void* SharedLibraryModel< scalar >::getSymbol (
             const std::string & symbolName,
             bool allowMissing = false,
             void * defaultSymbol = nullptr ) [inline]
19.84.2.8 getTime()
template<typename scalar = float>
scalar SharedLibraryModel< scalar >::getTime ( ) const [inline]
19.84.2.9 getTimestep()
template<typename scalar = float>
unsigned long long SharedLibraryModel< scalar >::getTimestep ( ) const [inline]
19.84.2.10 initialize()
template<typename scalar = float>
void SharedLibraryModel< scalar >::initialize ( ) [inline]
19.84.2.11 initializeSparse()
template<typename scalar = float>
void SharedLibraryModel< scalar >::initializeSparse ( ) [inline]
19.84.2.12 open()
template<typename scalar = float>
bool SharedLibraryModel< scalar >::open (
```

const std::string & pathToModel,

const std::string & modelName) [inline]

```
19.84.2.13 pullConnectivityFromDevice()
```

```
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullConnectivityFromDevice (
             const std::string & popName ) [inline]
19.84.2.14 pullCurrentSpikesFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullCurrentSpikesFromDevice (
             const std::string & popName ) [inline]
19.84.2.15 pullExtraGlobalParam()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullExtraGlobalParam (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.84.2.16 pullSpikesFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullSpikesFromDevice (
            const std::string & popName ) [inline]
19.84.2.17 pullStateFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullStateFromDevice (
             const std::string & popName ) [inline]
19.84.2.18 pullVarFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullVarFromDevice (
             const std::string & popName,
             const std::string & varName ) [inline]
19.84.2.19 pushConnectivityToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushConnectivityToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
19.84.2.20 pushCurrentSpikesToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushCurrentSpikesToDevice (
```

```
const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
19.84.2.21 pushExtraGlobalParam()
template<typename scalar = float>
\verb|void SharedLibraryModel| < \verb|scalar| >:: pushExtraGlobalParam| (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.84.2.22 pushSpikesToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushSpikesToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false) [inline]
19.84.2.23 pushStateToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushStateToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
19.84.2.24 pushVarToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushVarToDevice (
             const std::string & popName,
             const std::string & varName,
             bool uninitialisedOnly = false ) [inline]
19.84.2.25 setTime()
template<typename scalar = float>
void SharedLibraryModel< scalar >::setTime (
             scalar t ) [inline]
19.84.2.26 setTimestep()
template<typename scalar = float>
void SharedLibraryModel< scalar >::setTimestep (
             unsigned long long iT ) [inline]
19.84.2.27 stepTime()
template<typename scalar = float>
void SharedLibraryModel< scalar >::stepTime ( ) [inline]
```

The documentation for this class was generated from the following file:

· sharedLibraryModel.h

19.85 SpineMLSimulator::Simulator Class Reference

```
#include <simulator.h>
```

Public Member Functions

- Simulator ()
- Simulator (const std::string &experimentXML, const std::string &overrideOutputPath="")
- ∼Simulator ()
- void load (const std::string &experimentXML, const std::string &overrideOutputPath="")
 Load model from XML file.
- void stepTime ()

Advance simulation by one timestep.

- const LogOutput::AnalogueExternal * getExternalLogger (const std::string &name) const Get an external logger by name.
- InputValue::External * getExternalInput (const std::string &name) const

Get an external input by name.

• double getDT () const

Get the simulation timestep (in ms)

double getDurationMs () const

Get duration of simulation read from experiment in ms.

• double getInputMs () const

Get the total times accumulated in each stage of the simulation.

- double getSimulateMs () const
- double getLogMs () const
- double getNeuronUpdateTime () const

Timings of individual kernels provided by GeNN.

- double getInitTime () const
- double getPresynapticUpdateTime () const
- double getPostsynapticUpdateTime () const
- double getSynapseDynamicsTime () const
- double getInitSparseTime () const
- unsigned long long calcNumTimesteps () const

Calculate duration of simulation read from experiment in timesteps.

19.85.1 Constructor & Destructor Documentation

```
19.85.1.3 \simSimulator()
SpineMLSimulator::Simulator::~Simulator ( )
19.85.2 Member Function Documentation
19.85.2.1 calcNumTimesteps()
unsigned long long SpineMLSimulator::Simulator::calcNumTimesteps ( ) const [inline]
Calculate duration of simulation read from experiment in timesteps.
19.85.2.2 getDT()
double SpineMLSimulator::Simulator::getDT ( ) const [inline]
Get the simulation timestep (in ms)
19.85.2.3 getDurationMs()
double SpineMLSimulator::Simulator::getDurationMs ( ) const [inline]
Get duration of simulation read from experiment in ms.
19.85.2.4 getExternalInput()
InputValue::External * SpineMLSimulator::Simulator::getExternalInput (
             const std::string & name ) const
Get an external input by name.
19.85.2.5 getExternalLogger()
const std::string & name ) const
Get an external logger by name.
19.85.2.6 getInitSparseTime()
double SpineMLSimulator::Simulator::getInitSparseTime ( ) const
19.85.2.7 getInitTime()
double SpineMLSimulator::Simulator::getInitTime ( ) const
19.85.2.8 getInputMs()
double SpineMLSimulator::Simulator::getInputMs ( ) const [inline]
```

Get the total times accumulated in each stage of the simulation.


```
19.85.2.9 getLogMs()
double SpineMLSimulator::Simulator::getLogMs ( ) const [inline]
19.85.2.10 getNeuronUpdateTime()
double SpineMLSimulator::Simulator::getNeuronUpdateTime ( ) const
Timings of individual kernels provided by GeNN.
19.85.2.11 getPostsynapticUpdateTime()
\verb|double SpineMLSimulator::Simulator::getPostsynapticUpdateTime () const|
19.85.2.12 getPresynapticUpdateTime()
double SpineMLSimulator::Simulator::getPresynapticUpdateTime ( ) const
19.85.2.13 getSimulateMs()
double SpineMLSimulator::Simulator::getSimulateMs ( ) const [inline]
19.85.2.14 getSynapseDynamicsTime()
double SpineMLSimulator::Simulator::getSynapseDynamicsTime ( ) const
19.85.2.15 load()
void SpineMLSimulator::Simulator::load (
              const std::string & experimentXML,
              const std::string & overrideOutputPath = "" )
Load model from XML file.
19.85.2.16 stepTime()
void SpineMLSimulator::Simulator::stepTime ( )
Advance simulation by one timestep.
The documentation for this class was generated from the following files:
```

simulator.hsimulator.cc

19.86 SpineMLSimulator::Input::SpikeBase Class Reference

#include <input.h>

Inheritance diagram for SpineMLSimulator::Input::SpikeBase:



Protected Types

typedef void(* PushCurrentSpikesFunc) ()

Protected Member Functions

- SpikeBase (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushcurrentSpikesFunc pushCurrentSpikes)
- void injectSpike (unsigned int neuronID)
- · void uploadSpikes ()

Additional Inherited Members

19.86.1 Member Typedef Documentation

19.86.1.1 PushCurrentSpikesFunc

```
typedef void(* SpineMLSimulator::Input::SpikeBase::PushCurrentSpikesFunc) () [protected]
```

19.86.2 Constructor & Destructor Documentation

19.86.2.1 SpikeBase()

19.86.3 Member Function Documentation

19.86.3.1 injectSpike()

19.86.3.2 uploadSpikes()

```
void SpineMLSimulator::Input::SpikeBase::uploadSpikes ( ) [protected]
```

The documentation for this class was generated from the following files:


- input.h
- · input.cc

19.87 SpikeRecorder < Writer > Class Template Reference

Class to read spikes from neuron groups.

```
#include <spikeRecorder.h>
```

Inheritance diagram for SpikeRecorder < Writer >:



Public Types

- typedef unsigned int &(* GetCurrentSpikeCountFunc) ()
- typedef unsigned int *(* GetCurrentSpikesFunc) ()

Public Member Functions

- template<typename... WriterArgs>
 SpikeRecorder (GetCurrentSpikesFunc getCurrentSpikes, GetCurrentSpikeCountFunc getCurrentSpike
 Count, WriterArgs &&... writerArgs)
- void record (double t)
- · unsigned int getSum () const

19.87.1 Detailed Description

```
template<typename Writer = SpikeWriterText> class SpikeRecorder< Writer >
```

Class to read spikes from neuron groups.

19.87.2 Member Typedef Documentation

19.87.2.1 GetCurrentSpikeCountFunc

```
template<typename Writer = SpikeWriterText>
typedef unsigned int&(* SpikeRecorder< Writer >::GetCurrentSpikeCountFunc) ()
```

19.87.2.2 GetCurrentSpikesFunc

```
template<typename Writer = SpikeWriterText>
typedef unsigned int*(* SpikeRecorder< Writer >::GetCurrentSpikesFunc) ()
```

19.87.3 Constructor & Destructor Documentation

19.87.3.1 SpikeRecorder()

19.87.4 Member Function Documentation

19.87.4.1 getSum()

```
template<typename Writer = SpikeWriterText>
unsigned int SpikeRecorder< Writer >::getSum ( ) const [inline]

19.87.4.2 record()

template<typename Writer = SpikeWriterText>
```

The documentation for this class was generated from the following file:

• spikeRecorder.h


19.88 NeuronModels::SpikeSource Class Reference

void SpikeRecorder< Writer >::record (double t) [inline]

Empty neuron which allows setting spikes from external sources.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::SpikeSource:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getThresholdConditionCode () const override
 Gets code which defines the condition for a true spike in the described neuron model.
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

static const NeuronModels::SpikeSource * getInstance ()

Additional Inherited Members

19.88.1 Detailed Description

Empty neuron which allows setting spikes from external sources.

This model does not contain any update code and can be used to implement the equivalent of a SpikeGenerator Group in Brian or a SpikeSourceArray in PyNN.

19.88.2 Member Typedef Documentation

19.88.2.1 ParamValues

typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSource::ParamValues

19.88.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PostVarValues

19.88.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PreVarValues

19.88.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > NeuronModels::SpikeSource::VarValues

19.88.3 Member Function Documentation

19.88.3.1 getInstance()

```
static const NeuronModels::SpikeSource* NeuronModels::SpikeSource::getInstance ( ) [inline],
[static]
```

19.88.3.2 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSource::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.88.3.3 SET_NEEDS_AUTO_REFRACTORY()

The documentation for this class was generated from the following file:


· neuronModels.h

19.89 NeuronModels::SpikeSourceArray Class Reference

Spike source array.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::SpikeSourceArray:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual std::string getResetCode () const override

Gets code that defines the reset action taken after a spike occurred. This can be empty.

· virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- virtual EGPVec getExtraGlobalParams () const override
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

• static const NeuronModels::SpikeSourceArray * getInstance ()

Additional Inherited Members

19.89.1 Detailed Description

Spike source array.

A neuron which reads spike times from a global spikes array It has 2 variables:

- startSpike Index of the next spike in the global array
- endSpike Index of the spike next to the last in the globel array

and 1 global parameter:

• spikeTimes - Array with all spike times

19.89.2 Member Typedef Documentation

19.89.2.1 ParamValues

```
typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSourceArray::ParamValues
```

19.89.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PostVarValues
```

19.89.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PreVarValues

19.89.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::SpikeSourceArray::VarValues

19.89.3 Member Function Documentation

19.89.3.1 getExtraGlobalParams()

```
virtual EGPVec NeuronModels::SpikeSourceArray::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

19.89.3.2 getInstance()

```
static const NeuronModels::SpikeSourceArray* NeuronModels::SpikeSourceArray::getInstance ( )
[inline], [static]
```

19.89.3.3 getResetCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getResetCode ( ) const [inline], [override],
[virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

19.89.3.4 getSimCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.89.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.89.3.6 getVars()

```
virtual VarVec NeuronModels::SpikeSourceArray::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.89.3.7 SET_NEEDS_AUTO_REFRACTORY()

```
NeuronModels::SpikeSourceArray::SET_NEEDS_AUTO_REFRACTORY (
```

```
false
```


The documentation for this class was generated from the following file:

neuronModels.h

19.90 SpineMLSimulator::Input::SpikeTime Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::SpikeTime:



Public Member Functions

- SpikeTime (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, Push← CurrentSpikesFunc pushCurrentSpikes)
- · virtual void apply (double dt, unsigned long long timestep) override

Additional Inherited Members

19.90.1 Constructor & Destructor Documentation

19.90.1.1 SpikeTime()

19.90.2 Member Function Documentation

19.90.2.1 apply()

Implements SpineMLSimulator::Input::Base.

The documentation for this class was generated from the following files:

- · input.h
- · input.cc

19.91 SpikeWriterText Class Reference

Class to write spikes to text file.

```
#include <spikeRecorder.h>
```

Public Member Functions

SpikeWriterText (const std::string &filename, const std::string &delimiter=" ", bool header=false)

Protected Member Functions

• void recordSpikes (double t, unsigned int spikeCount, const unsigned int *currentSpikes)

19.91.1 Detailed Description

Class to write spikes to text file.

19.91.2 Constructor & Destructor Documentation

19.91.2.1 SpikeWriterText()

19.91.3 Member Function Documentation

19.91.3.1 recordSpikes()

The documentation for this class was generated from the following file:

· spikeRecorder.h

19.92 SpikeWriterTextCached Class Reference

Class to write spikes to text file, caching in memory before writing.

```
#include <spikeRecorder.h>
```

Public Member Functions

- SpikeWriterTextCached (const std::string &filename, const std::string &delimiter=" ", bool header=false)
- ∼SpikeWriterTextCached ()
- void writeCache ()

Protected Member Functions

• void recordSpikes (double t, unsigned int spikeCount, const unsigned int *currentSpikes)

19.92.1 Detailed Description

Class to write spikes to text file, caching in memory before writing.

19.92.2 Constructor & Destructor Documentation

19.92.2.1 SpikeWriterTextCached()

19.92.2.2 ∼SpikeWriterTextCached()

```
SpikeWriterTextCached::~SpikeWriterTextCached ( ) [inline]
```

19.92.3 Member Function Documentation

19.92.3.1 recordSpikes()

19.92.3.2 writeCache()

```
void SpikeWriterTextCached::writeCache ( ) [inline]
```

The documentation for this class was generated from the following file:

· spikeRecorder.h

19.93 SpineMLSimulator::StateVar< T > Class Template Reference

```
#include <stateVar.h>
```

Public Member Functions

- StateVar (const std::string &stateVarName, std::function < void *(const char *, bool) > getLibrarySymbol ← Func)
- bool isAccessible () const
- · void push () const
- void pull () const
- T * get ()
- const T * get () const

19.93.1 Constructor & Destructor Documentation

```
19.93.1.1 StateVar()
{\tt template}{<}{\tt typename}~{\tt T}{>}
SpineMLSimulator::StateVar< T >::StateVar (
              const std::string & stateVarName,
               \verb|std::function| < \verb|void *(const char *, bool|) > \textit{getLibrarySymbolFunc} \;) \quad [inline]
19.93.2 Member Function Documentation
19.93.2.1 get() [1/2]
template<typename T>
T* SpineMLSimulator::StateVar< T >::get ( ) [inline]
19.93.2.2 get() [2/2]
template<typename T>
const T* SpineMLSimulator::StateVar< T >::get ( ) const [inline]
19.93.2.3 isAccessible()
template<typename T>
\verb|bool SpineMLSimulator::StateVar< T>::: is \verb|Accessible ( ) const [inline]|\\
19.93.2.4 pull()
template < typename T >
void SpineMLSimulator::StateVar< T >::pull ( ) const [inline]
19.93.2.5 push()
template<typename T>
```

void SpineMLSimulator::StateVar< T >::push () const [inline]

19.93.3 Member Data Documentation

19.93.3.1 m_Direct

```
template<typename T>
Direct SpineMLSimulator::StateVar< T >::m_Direct
```

19.93.3.2 m_Indirect

```
template<typename T>
Indirect SpineMLSimulator::StateVar< T >::m_Indirect
```

The documentation for this class was generated from the following file:


· stateVar.h

19.94 WeightUpdateModels::StaticGraded Class Reference

Graded-potential, static synapse.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::StaticGraded:



Public Member Functions

- DECLARE WEIGHT UPDATE MODEL (StaticGraded, 2, 1, 0, 0)
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getEventCode () const override

Gets code run when events (all the instances where event threshold condition is met) are received.

• virtual std::string getEventThresholdConditionCode () const override

Gets codes to test for events.

Additional Inherited Members

19.94.1 Detailed Description

Graded-potential, static synapse.

In a graded synapse, the conductance is updated gradually with the rule:

$$gSyn = g * tanh((V - E_{pre})/V_{slope})$$

whenever the membrane potential V is larger than the threshold E_{pre} . The model has 1 variable:

• g: conductance of scalar type

The parameters are:

- Epre: Presynaptic threshold potential
- Vslope: Activation slope of graded release

```
event code is:
```

```
(addToInSyn, (g) * tanh((((v_pre) - ((Epre)))*DT*2/((Vslope)));
```

event threshold condition code is:

```
$(V_pre) > $(Epre)
```

Note

The pre-synaptic variables are referenced with the suffix _pre in synapse related code such as an the event threshold test. Users can also access post-synaptic neuron variables using the suffix _post.

19.94.2 Member Function Documentation

19.94.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.94.2.2 getEventCode()

```
virtual std::string WeightUpdateModels::StaticGraded::getEventCode ( ) const [inline], [override],
[virtual]
```

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented from WeightUpdateModels::Base.

19.94.2.3 getEventThresholdConditionCode()

```
virtual std::string WeightUpdateModels::StaticGraded::getEventThresholdConditionCode ( ) const
[inline], [override], [virtual]
```

Gets codes to test for events.

Reimplemented from WeightUpdateModels::Base.

19.94.2.4 getParamNames()

virtual StringVec WeightUpdateModels::StaticGraded::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.94.2.5 getVars()

virtual VarVec WeightUpdateModels::StaticGraded::getVars () const [inline], [override],
[virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


• weightUpdateModels.h

19.95 WeightUpdateModels::StaticPulse Class Reference

Pulse-coupled, static synapse.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::StaticPulse:



Public Member Functions

- DECLARE_WEIGHT_UPDATE_MODEL (StaticPulse, 0, 1, 0, 0)
- · virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

Additional Inherited Members

19.95.1 Detailed Description

Pulse-coupled, static synapse.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 1 variable:

g - conductance of scalar type and no other parameters.

```
sim code is:
```

```
"\$(addToInSyn, \$(g));n"
```

19.95.2 Member Function Documentation

19.95.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.95.2.2 getSimCode()

```
virtual std::string WeightUpdateModels::StaticPulse::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.95.2.3 getVars()

```
virtual VarVec WeightUpdateModels::StaticPulse::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


weightUpdateModels.h

19.96 WeightUpdateModels::StaticPulseDendriticDelay Class Reference

Pulse-coupled, static synapse with heterogenous dendritic delays.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::StaticPulseDendriticDelay:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

Static Public Member Functions

• static const StaticPulseDendriticDelay * getInstance ()

Additional Inherited Members

19.96.1 Detailed Description

Pulse-coupled, static synapse with heterogenous dendritic delays.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 2 variables:

- g conductance of scalar type
- · d dendritic delay in timesteps and no other parameters.

sim code is:

```
" $(addToInSynDelay, $(g), $(d));\n\
```

19.96.2 Member Typedef Documentation

19.96.2.1 ParamValues

typedef Snippet::ValueBase< 0 > WeightUpdateModels::StaticPulseDendriticDelay::ParamValues

19.96.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> WeightUpdateModels::StaticPulseDendriticDelay::Post↔ VarValues

19.96.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> WeightUpdateModels::StaticPulseDendriticDelay::Pre↔ VarValues

19.96.2.4 VarValues

 $\label{typedef_Models::VarInitContainerBase< 2 > WeightUpdateModels::StaticPulseDendriticDelay::Var \leftarrow Values$

19.96.3 Member Function Documentation

19.96.3.1 getInstance()

```
static \ const \ \ StaticPulseDendriticDelay* \ \ WeightUpdateModels::StaticPulseDendriticDelay::get \leftarrow Instance \ ( ) \ [inline], \ [static]
```

19.96.3.2 getSimCode()

virtual std::string WeightUpdateModels::StaticPulseDendriticDelay::getSimCode () const [inline],
[override], [virtual]

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.96.3.3 getVars()

```
virtual VarVec WeightUpdateModels::StaticPulseDendriticDelay::getVars ( ) const [inline],
[override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:

weightUpdateModels.h

19.97 CodeGenerator::Substitutions Class Reference

```
#include <substitutions.h>
```

Public Member Functions

- Substitutions (const Substitutions *parent=nullptr)
- Substitutions (const std::vector < FunctionTemplate > &functions, const std::string &ftype)
- template<typename T >
 void addVarNameSubstitution (const std::vector< T > &variables, const std::string &sourceSuffix="", const std::string &destPrefix="", const std::string &destSuffix="")
- void addParamNameSubstitution (const std::vector < std::string > ¶mNames, const std::string &source ← Suffix="", const std::string &destPrefix="", const std::string &destSuffix="")
- template<typename T >
 void addVarValueSubstitution (const std::vector< T > &variables, const std::vector< double > &values, const std::string &sourceSuffix="")
- void addParamValueSubstitution (const std::vector< std::string > ¶mNames, const std::vector< double > &values, const std::string &sourceSuffix="")
- void addVarSubstitution (const std::string &source, const std::string &destionation, bool allowOverride=false)

- void addFuncSubstitution (const std::string &source, unsigned int numArguments, const std::string &func
 — Template, bool allowOverride=false)
- bool hasVarSubstitution (const std::string &source) const
- · const std::string & getVarSubstitution (const std::string &source) const
- · void apply (std::string &code) const
- void applyCheckUnreplaced (std::string &code, const std::string &context) const
- const std::string operator[] (const std::string &source) const

19.97.1 Constructor & Destructor Documentation

19.97.2 Member Function Documentation

19.97.2.1 addFuncSubstitution()

19.97.2.2 addParamNameSubstitution()

19.97.2.3 addParamValueSubstitution()

19.97.2.4 addVarNameSubstitution()

```
template < typename T >
void CodeGenerator::Substitutions::addVarNameSubstitution (
             const std::vector< T > & variables,
             const std::string & sourceSuffix = "",
             const std::string & destPrefix = "",
             const std::string & destSuffix = "" ) [inline]
19.97.2.5 addVarSubstitution()
void CodeGenerator::Substitutions::addVarSubstitution (
             const std::string & source,
             const std::string & destionation,
             bool allowOverride = false ) [inline]
19.97.2.6 addVarValueSubstitution()
template<typename T >
\verb"void CodeGenerator":: Substitutions:: add Var Value Substitution (
            const std::vector< T > & variables,
             const std::vector< double > & values,
             const std::string & sourceSuffix = "" ) [inline]
19.97.2.7 apply()
void CodeGenerator::Substitutions::apply (
             std::string & code ) const [inline]
19.97.2.8 applyCheckUnreplaced()
void CodeGenerator::Substitutions::applyCheckUnreplaced (
             std::string & code,
             const std::string & context ) const [inline]
19.97.2.9 getVarSubstitution()
const std::string& CodeGenerator::Substitutions::getVarSubstitution (
             const std::string & source ) const [inline]
19.97.2.10 hasVarSubstitution()
bool CodeGenerator::Substitutions::hasVarSubstitution (
             const std::string & source ) const [inline]
19.97.2.11 operator[]()
const std::string CodeGenerator::Substitutions::operator[] (
             const std::string & source ) const [inline]
```


The documentation for this class was generated from the following file:

· substitutions.h

19.98 pygenn.genn_groups.SynapseGroup Class Reference

Class representing synaptic connection between two groups of neurons.

Inheritance diagram for pygenn.genn_groups.SynapseGroup:



Public Member Functions

def __init__ (self, name)

Init SynapseGroup.

• def num_synapses (self)

Number of synapses in group.

def weight_update_var_size (self)

Size of each weight update variable.

- def max_row_length (self)
- def set_psm_var (self, var_name, values)

Set values for a postsynaptic model variable.

def set_pre_var (self, var_name, values)

Set values for a presynaptic variable.

def set_post_var (self, var_name, values)

Set values for a postsynaptic variable.

• def set_weight_update (self, model, param_space, var_space, pre_var_space, post_var_space)

Set weight update model, its parameters and initial variables.

def set_post_syn (self, model, param_space, var_space)

Set postsynaptic model, its parameters and initial variables.

- def get_var_values (self, var_name)
- · def is_connectivity_init_required (self)
- def matrix_type (self)

Type of the projection matrix.

- def matrix_type (self, matrix_type)
- def is_ragged (self)

Tests whether synaptic connectivity uses Ragged format.

• def is_bitmask (self)

Tests whether synaptic connectivity uses Bitmask format.

• def is_dense (self)

Tests whether synaptic connectivity uses dense format.

def has_individual_synapse_vars (self)

Tests whether synaptic connectivity has individual weights.

• def has_individual_postsynaptic_vars (self)

Tests whether synaptic connectivity has individual postsynaptic model variables.

• def set_sparse_connections (self, pre_indices, post_indices)

Set ragged format connections between two groups of neurons.

• def get_sparse_pre_inds (self)

Get presynaptic indices of synapse group connections.

• def get_sparse_post_inds (self)

Get postsynaptic indices of synapse group connections.

• def set_connected_populations (self, source, target)

Set two groups of neurons connected by this SynapseGroup.

def add_to (self, model_spec, delay_steps)

Add this SynapseGroup to the a model.

def add_extra_global_param (self, param_name, param_values)

Add extra global parameter.

- def load (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise synapse group.

Public Attributes

- connections_set
- w_update
- postsyn
- src
- trg
- psm_vars
- pre_vars
- post_vars
- connectivity_initialiser
- synapse_order
- ind
- row_lengths
- pop

19.98.1 Detailed Description

Class representing synaptic connection between two groups of neurons.

19.98.2 Constructor & Destructor Documentation

Init SynapseGroup.

Parameters

name string name of the group

19.98.3 Member Function Documentation

19.98.3.1 add_extra_global_param()

Add extra global parameter.

Parameters

param_nam	e stri	ng with the name of the extra global parameter
param_value	es iter	able or a single value

19.98.3.2 add_to()

Add this SynapseGroup to the a model.

Parameters

model_spec	pygenn.genn_model.GeNNModel to add to
delay_steps	number of axonal delay timesteps to simulate for this synapse group

19.98.3.3 get_sparse_post_inds()

```
\label{lem:constant} \mbox{def pygenn.genn\_groups.SynapseGroup.get\_sparse\_post\_inds (} \\ self )
```

Get postsynaptic indices of synapse group connections.

Returns

ndarrays of postsynaptic indices

19.98.3.4 get_sparse_pre_inds()

```
def pygenn.genn_groups.SynapseGroup.get_sparse_pre_inds ( self )
```

Get presynaptic indices of synapse group connections.

Returns

ndarray of presynaptic indices

```
19.98.3.5 get_var_values()
def pygenn.genn_groups.SynapseGroup.get_var_values (
               self,
                var_name )
19.98.3.6 has_individual_postsynaptic_vars()
{\tt def pygenn.genn\_groups.SynapseGroup.has\_individual\_postsynaptic\_vars} \ \ (
Tests whether synaptic connectivity has individual postsynaptic model variables.
19.98.3.7 has_individual_synapse_vars()
{\tt def pygenn.genn\_groups.SynapseGroup.has\_individual\_synapse\_vars \ (}
                self )
Tests whether synaptic connectivity has individual weights.
19.98.3.8 is_bitmask()
def pygenn.genn_groups.SynapseGroup.is_bitmask (
                self )
Tests whether synaptic connectivity uses Bitmask format.
19.98.3.9 is_connectivity_init_required()
def pygenn.genn_groups.SynapseGroup.is_connectivity_init_required (
               self )
19.98.3.10 is_dense()
def pygenn.genn_groups.SynapseGroup.is_dense (
                self )
Tests whether synaptic connectivity uses dense format.
19.98.3.11 is_ragged()
def pygenn.genn_groups.SynapseGroup.is_ragged (
                self )
Tests whether synaptic connectivity uses Ragged format.
19.98.3.12 load()
def pygenn.genn_groups.SynapseGroup.load (
               self,
               slm.
```

scalar)

```
19.98.3.13 matrix_type() [1/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
               self )
Type of the projection matrix.
19.98.3.14 matrix_type() [2/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
              self,
               matrix_type )
19.98.3.15 max_row_length()
def pygenn.genn_groups.SynapseGroup.max_row_length (
               self )
19.98.3.16 num_synapses()
def pygenn.genn_groups.SynapseGroup.num_synapses (
               self )
Number of synapses in group.
19.98.3.17 reinitialise()
def pygenn.genn_groups.SynapseGroup.reinitialise (
               self,
               slm,
               scalar )
Reinitialise synapse group.
Parameters
```

slm	SharedLibraryModel instance for accessing variables
scala	String specifying "scalar" type

19.98.3.18 set_connected_populations()

```
def pygenn.genn_groups.SynapseGroup.set_connected_populations ( self, \\ source, \\ target )
```

Set two groups of neurons connected by this SynapseGroup.

Parameters

source	string name of the presynaptic neuron group
target	string name of the postsynaptic neuron group

19.98.3.19 set_post_syn()

Set postsynaptic model, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

19.98.3.20 set_post_var()

Set values for a postsynaptic variable.

Parameters

var_name	string with the name of the presynaptic variable
values	iterable or a single value

19.98.3.21 set_pre_var()

Set values for a presynaptic variable.

Parameters

var_name	string with the name of the presynaptic variable
values	iterable or a single value

19.98.3.22 set_psm_var()

Set values for a postsynaptic model variable.

Parameters

var_name	string with the name of the postsynaptic model variable
values	iterable or a single value

19.98.3.23 set_sparse_connections()

Set ragged format connections between two groups of neurons.

Parameters

pre_indices	ndarray of presynaptic indices
post_indices	ndarray of postsynaptic indices

19.98.3.24 set_weight_update()

Set weight update model, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables
pre_var_space	dict with model presynaptic variables
post_var_space	dict with model postsynaptic variables

19.98.3.25 weight_update_var_size()

Size of each weight update variable.

19.98.4 Member Data Documentation

19.98.4.1 connections_set

 $\verb"pygenn.genn_groups.SynapseGroup.connections_set"$

19.98.4.2 connectivity_initialiser

 $\verb"pygenn.genn_groups.SynapseGroup.connectivity_initialiser"$

19.98.4.3 ind

pygenn.genn_groups.SynapseGroup.ind

19.98.4.4 pop

pygenn.genn_groups.SynapseGroup.pop

19.98.4.5 post_vars

pygenn.genn_groups.SynapseGroup.post_vars

19.98.4.6 postsyn

pygenn.genn_groups.SynapseGroup.postsyn

19.98.4.7 pre_vars

 $\verb"pygenn.genn_groups.SynapseGroup.pre_vars"$

19.98.4.8 psm_vars

pygenn.genn_groups.SynapseGroup.psm_vars

19.98.4.9 row_lengths

pygenn.genn_groups.SynapseGroup.row_lengths

19.98.4.10 src

pygenn.genn_groups.SynapseGroup.src

19.98.4.11 synapse_order

pygenn.genn_groups.SynapseGroup.synapse_order

19.98.4.12 trg

pygenn.genn_groups.SynapseGroup.trg

19.98.4.13 w_update

pygenn.genn_groups.SynapseGroup.w_update


The documentation for this class was generated from the following file:

• genn_groups.py

19.99 SynapseGroup Class Reference

#include <synapseGroup.h>

Inheritance diagram for SynapseGroup:



Public Types

enum SpanType { SpanType::POSTSYNAPTIC, SpanType::PRESYNAPTIC }

Public Member Functions

- SynapseGroup (const SynapseGroup &)=delete
- SynapseGroup ()=delete
- void setWUVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model state variable.

void setWUPreVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model presynaptic state variable.

void setWUPostVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model postsynaptic state variable.

• void setWUExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of weight update model extra global parameter.

• void setPSVarLocation (const std::string &varName, VarLocation loc)

Set location of postsynaptic model state variable.

• void setPSExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of postsynaptic model extra global parameter.

• void setSparseConnectivityExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of sparse connectivity initialiser extra global parameter.

void setInSynVarLocation (VarLocation loc)

Set location of variables used to combine input from this synapse group.

void setSparseConnectivityLocation (VarLocation loc)

Set variable mode used for sparse connectivity.

void setDendriticDelayLocation (VarLocation loc)

Set variable mode used for this synapse group's dendritic delay buffers.

void setMaxConnections (unsigned int maxConnections)

Sets the maximum number of target neurons any source neurons can connect to.

void setMaxSourceConnections (unsigned int maxPostConnections)

Sets the maximum number of source neurons any target neuron can connect to.

void setMaxDendriticDelayTimesteps (unsigned int maxDendriticDelay)

Sets the maximum dendritic delay for synapses in this synapse group.

void setSpanType (SpanType spanType)

Set how CUDA implementation is parallelised.

void setNumThreadsPerSpike (unsigned int numThreadsPerSpike)

Set how many threads CUDA implementation uses to process each spike when span type is PRESYNAPTIC.

void setBackPropDelaySteps (unsigned int timesteps)

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

void setNarrowSparseIndEnabled (bool enabled)

Enables or disables using narrow i.e. less than 32-bit types for sparse matrix indices.

- const std::string & getName () const
- SpanType getSpanType () const
- unsigned int getNumThreadsPerSpike () const
- unsigned int getDelaySteps () const
- · unsigned int getBackPropDelaySteps () const
- · unsigned int getMaxConnections () const
- · unsigned int getMaxSourceConnections () const
- unsigned int getMaxDendriticDelayTimesteps () const
- SynapseMatrixType getMatrixType () const
- VarLocation getInSynLocation () const

Get variable mode used for variables used to combine input from this synapse group.

VarLocation getSparseConnectivityLocation () const

Get variable mode used for sparse connectivity.

VarLocation getDendriticDelayLocation () const

Get variable mode used for this synapse group's dendritic delay buffers.

- · int getClusterHostID () const
- bool isTrueSpikeRequired () const

Does synapse group need to handle 'true' spikes.

• bool isSpikeEventRequired () const

Does synapse group need to handle spike-like events.

- const WeightUpdateModels::Base * getWUModel () const
- const std::vector< double > & getWUParams () const
- const std::vector< Models::VarInit > & getWUVarInitialisers () const
- const std::vector< Models::VarInit > & getWUPreVarInitialisers () const
- const std::vector< Models::VarInit > & getWUPostVarInitialisers () const
- const std::vector< double > getWUConstInitVals () const
- const PostsynapticModels::Base * getPSModel () const
- const std::vector< double > & getPSParams () const
- const std::vector< Models::VarInit > & getPSVarInitialisers () const
- const std::vector< double > getPSConstInitVals () const
- const InitSparseConnectivitySnippet::Init & getConnectivityInitialiser () const
- bool isZeroCopyEnabled () const
- VarLocation getWUVarLocation (const std::string &var) const

Get location of weight update model per-synapse state variable by name.

VarLocation getWUVarLocation (size_t index) const

Get location of weight update model per-synapse state variable by index.

VarLocation getWUPreVarLocation (const std::string &var) const

Get location of weight update model presynaptic state variable by name.

VarLocation getWUPreVarLocation (size_t index) const

Get location of weight update model presynaptic state variable by index.

VarLocation getWUPostVarLocation (const std::string &var) const

Get location of weight update model postsynaptic state variable by name.

VarLocation getWUPostVarLocation (size_t index) const

Get location of weight update model postsynaptic state variable by index.

VarLocation getWUExtraGlobalParamLocation (const std::string ¶mName) const

Get location of weight update model extra global parameter by name.

VarLocation getWUExtraGlobalParamLocation (size_t index) const

Get location of weight update model extra global parameter by index.

VarLocation getPSVarLocation (const std::string &var) const

Get location of postsynaptic model state variable.

VarLocation getPSVarLocation (size t index) const

Get location of postsynaptic model state variable.

VarLocation getPSExtraGlobalParamLocation (const std::string ¶mName) const

Get location of postsynaptic model extra global parameter by name.

VarLocation getPSExtraGlobalParamLocation (size t index) const

Get location of postsynaptic model extra global parameter by index.

· VarLocation getSparseConnectivityExtraGlobalParamLocation (const std::string ¶mName) const

Get location of sparse connectivity initialiser extra global parameter by name.

VarLocation getSparseConnectivityExtraGlobalParamLocation (size_t index) const

Get location of sparse connectivity initialiser extra global parameter by index.

· bool isDendriticDelayRequired () const

Does this synapse group require dendritic delay?

bool isPSInitRNGRequired () const

Does this synapse group require an RNG for it's postsynaptic init code?

· bool isWUInitRNGRequired () const

Does this synapse group require an RNG for it's weight update init code?

• bool isWUVarInitRequired () const

Is var init code required for any variables in this synapse group's weight update model?

bool isSparseConnectivityInitRequired () const

Is sparse connectivity initialisation code required for this synapse group?

Protected Member Functions

- NeuronGroupInternal * getSrcNeuronGroup ()
- NeuronGroupInternal * getTrgNeuronGroup ()
- void setEventThresholdReTestRequired (bool reg)
- void setPSModelMergeTarget (const std::string &targetName)

- · void initDerivedParams (double dt)
- const NeuronGroupInternal * getSrcNeuronGroup () const
- const NeuronGroupInternal * getTrgNeuronGroup () const
- const std::vector< double > & getWUDerivedParams () const
- const std::vector< double > & getPSDerivedParams () const

Does the event threshold needs to be retested in the synapse kernel?

- · bool isEventThresholdReTestRequired () const
- const std::string & getPSModelTargetName () const
- bool isPSModelMerged () const
- std::string getPresynapticAxonalDelaySlot (const std::string &devPrefix) const
- std::string getPostsynapticBackPropDelaySlot (const std::string &devPrefix) const
- std::string getDendriticDelayOffset (const std::string &devPrefix, const std::string &offset="") const
- std::string getSparseIndType () const

Get the type to use for sparse connectivity indices for synapse group.

19.99.1 Member Enumeration Documentation

19.99.1.1 SpanType

```
enum SynapseGroup::SpanType [strong]
```

Enumerator

```
POSTSYNAPTIC PRESYNAPTIC
```

19.99.2 Constructor & Destructor Documentation

const std::vector< Models::VarInit > & wuPostVarInitialisers,

[inline]

19.99.3.7 getInSynLocation()

```
const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trgNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation,
             bool defaultNarrowSparseIndEnabled ) [protected]
19.99.3 Member Function Documentation
19.99.3.1 getBackPropDelaySteps()
unsigned int SynapseGroup::getBackPropDelaySteps ( ) const [inline]
19.99.3.2 getClusterHostID()
int SynapseGroup::getClusterHostID ( ) const
19.99.3.3 getConnectivityInitialiser()
const InitSparseConnectivitySnippet::Init& SynapseGroup::getConnectivityInitialiser ( ) const
19.99.3.4 getDelaySteps()
unsigned int SynapseGroup::getDelaySteps ( ) const [inline]
19.99.3.5 getDendriticDelayLocation()
VarLocation SynapseGroup::getDendriticDelayLocation ( ) const [inline]
Get variable mode used for this synapse group's dendritic delay buffers.
19.99.3.6 getDendriticDelayOffset()
std::string SynapseGroup::getDendriticDelayOffset (
             const std::string & devPrefix,
             const std::string & offset = "" ) const [protected]
```

Get variable mode used for variables used to combine input from this synapse group.

VarLocation SynapseGroup::getInSynLocation () const [inline]

```
19.99.3.8 getMatrixType()
SynapseMatrixType SynapseGroup::getMatrixType ( ) const [inline]
19.99.3.9 getMaxConnections()
unsigned int SynapseGroup::getMaxConnections ( ) const [inline]
19.99.3.10 getMaxDendriticDelayTimesteps()
unsigned int SynapseGroup::getMaxDendriticDelayTimesteps ( ) const [inline]
19.99.3.11 getMaxSourceConnections()
unsigned int SynapseGroup::getMaxSourceConnections ( ) const [inline]
19.99.3.12 getName()
const std::string& SynapseGroup::getName ( ) const [inline]
19.99.3.13 getNumThreadsPerSpike()
unsigned int SynapseGroup::getNumThreadsPerSpike ( ) const [inline]
19.99.3.14 getPostsynapticBackPropDelaySlot()
std::string SynapseGroup::getPostsynapticBackPropDelaySlot (
              const std::string & devPrefix ) const [protected]
Get the expression to calculate the delay slot for accessing Postsynaptic neuron state variables, taking into account
back propagation delay
19.99.3.15 getPresynapticAxonalDelaySlot()
\verb|std::string SynapseGroup::getPresynapticAxonalDelaySlot (|\\
              const std::string & devPrefix ) const [protected]
Get the expression to calculate the delay slot for accessing Presynaptic neuron state variables, taking into account
axonal delay
19.99.3.16 getPSConstInitVals()
const std::vector< double > SynapseGroup::getPSConstInitVals ( ) const
19.99.3.17 getPSDerivedParams()
const std::vector<double>& SynapseGroup::getPSDerivedParams ( ) const [inline], [protected]
```

Does the event threshold needs to be retested in the synapse kernel?

```
19.99.3.18 getPSExtraGlobalParamLocation() [1/2]
VarLocation SynapseGroup::getPSExtraGlobalParamLocation (
              const std::string & paramName ) const
Get location of postsynaptic model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.99.3.19 getPSExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getPSExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of postsynaptic model extra global parameter by index.
This is only used by extra global parameters which are pointers
19.99.3.20 getPSModel()
const PostsynapticModels::Base* SynapseGroup::getPSModel ( ) const [inline]
19.99.3.21 getPSModelTargetName()
const std::string& SynapseGroup::getPSModelTargetName ( ) const [inline], [protected]
19.99.3.22 getPSParams()
\verb|const| std::vector<double>& SynapseGroup::getPSParams ( ) const [inline]|
19.99.3.23 getPSVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getPSVarInitialisers ( ) const [inline]
19.99.3.24 getPSVarLocation() [1/2]
VarLocation SynapseGroup::getPSVarLocation (
              const std::string & var ) const
Get location of postsynaptic model state variable.
19.99.3.25 getPSVarLocation() [2/2]
VarLocation SynapseGroup::getPSVarLocation (
              size_t index ) const [inline]
Get location of postsynaptic model state variable.
19.99.3.26 getSpanType()
SpanType SynapseGroup::getSpanType ( ) const [inline]
```

```
19.99.3.27 getSparseConnectivityExtraGlobalParamLocation() [1/2]
{\tt VarLocation} \  \, {\tt SynapseGroup::getSparseConnectivityExtraGlobalParamLocation} \  \, (
              const std::string & paramName ) const
Get location of sparse connectivity initialiser extra global parameter by name.
This is only used by extra global parameters which are pointers
19.99.3.28 getSparseConnectivityExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getSparseConnectivityExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of sparse connectivity initialiser extra global parameter by index.
This is only used by extra global parameters which are pointers
19.99.3.29 getSparseConnectivityLocation()
VarLocation SynapseGroup::getSparseConnectivityLocation ( ) const [inline]
Get variable mode used for sparse connectivity.
19.99.3.30 getSparseIndType()
std::string SynapseGroup::getSparseIndType ( ) const [protected]
Get the type to use for sparse connectivity indices for synapse group.
19.99.3.31 getSrcNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) [inline], [protected]
19.99.3.32 getSrcNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) const [inline], [protected]
19.99.3.33 getTrgNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) [inline], [protected]
19.99.3.34 getTrgNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) const [inline], [protected]
19.99.3.35 getWUConstInitVals()
const std::vector< double > SynapseGroup::getWUConstInitVals ( ) const
19.99.3.36 getWUDerivedParams()
const std::vector<double>& SynapseGroup::getWUDerivedParams ( ) const [inline], [protected]
```

```
19.99.3.37 getWUExtraGlobalParamLocation() [1/2]
VarLocation SynapseGroup::getWUExtraGlobalParamLocation (
              const std::string & paramName ) const
Get location of weight update model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.99.3.38 getWUExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getWUExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of weight update model extra global parameter by index.
This is only used by extra global parameters which are pointers
19.99.3.39 getWUModel()
const WeightUpdateModels::Base* SynapseGroup::getWUModel ( ) const [inline]
19.99.3.40 getWUParams()
const std::vector<double>& SynapseGroup::getWUParams ( ) const [inline]
19.99.3.41 getWUPostVarInitialisers()
\verb|const| std::vector < \verb|Models::VarInit>| & SynapseGroup::getWUPostVarInitialisers () const [inline]| \\
19.99.3.42 getWUPostVarLocation() [1/2]
VarLocation SynapseGroup::getWUPostVarLocation (
              const std::string & var ) const
Get location of weight update model postsynaptic state variable by name.
19.99.3.43 getWUPostVarLocation() [2/2]
VarLocation SynapseGroup::getWUPostVarLocation (
              size_t index ) const [inline]
Get location of weight update model postsynaptic state variable by index.
19.99.3.44 getWUPreVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUPreVarInitialisers ( ) const [inline]
19.99.3.45 getWUPreVarLocation() [1/2]
VarLocation SynapseGroup::getWUPreVarLocation (
              const std::string & var ) const
```

Get location of weight update model presynaptic state variable by name.

Get location of weight update model presynaptic state variable by index.

```
19.99.3.47 getWUVarInitialisers()
```

```
const std::vector<Models::VarInit>& SynapseGroup::getWUVarInitialisers ( ) const [inline]
```

```
19.99.3.48 getWUVarLocation() [1/2]
```

Get location of weight update model per-synapse state variable by name.

```
19.99.3.49 getWUVarLocation() [2/2]
```

Get location of weight update model per-synapse state variable by index.

```
19.99.3.50 initDerivedParams()
```

```
void SynapseGroup::initDerivedParams ( \label{eq:double_dt} \mbox{double } dt \; ) \; \; [\mbox{protected}]
```

19.99.3.51 isDendriticDelayRequired()

```
bool SynapseGroup::isDendriticDelayRequired ( ) const
```

Does this synapse group require dendritic delay?

19.99.3.52 isEventThresholdReTestRequired()

```
bool SynapseGroup::isEventThresholdReTestRequired ( ) const [inline], [protected]
```

This is required when the pre-synaptic neuron population's outgoing synapse groups require different event threshold

```
19.99.3.53 isPSInitRNGRequired()
```

```
bool SynapseGroup::isPSInitRNGRequired ( ) const
```

Does this synapse group require an RNG for it's postsynaptic init code?

19.99.3.54 isPSModelMerged() bool SynapseGroup::isPSModelMerged () const [inline], [protected] 19.99.3.55 isSparseConnectivityInitRequired() bool SynapseGroup::isSparseConnectivityInitRequired () const Is sparse connectivity initialisation code required for this synapse group? 19.99.3.56 isSpikeEventRequired() bool SynapseGroup::isSpikeEventRequired () const Does synapse group need to handle spike-like events. 19.99.3.57 isTrueSpikeRequired() bool SynapseGroup::isTrueSpikeRequired () const Does synapse group need to handle 'true' spikes. 19.99.3.58 isWUInitRNGRequired() bool SynapseGroup::isWUInitRNGRequired () const Does this synapse group require an RNG for it's weight update init code? 19.99.3.59 isWUVarInitRequired() bool SynapseGroup::isWUVarInitRequired () const Is var init code required for any variables in this synapse group's weight update model? 19.99.3.60 isZeroCopyEnabled() bool SynapseGroup::isZeroCopyEnabled () const 19.99.3.61 setBackPropDelaySteps() void SynapseGroup::setBackPropDelaySteps (unsigned int timesteps)

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

19.99.3.62 setDendriticDelayLocation()

```
void SynapseGroup::setDendriticDelayLocation ( {\tt VarLocation}\ loc\ )\ [{\tt inline}]
```

Set variable mode used for this synapse group's dendritic delay buffers.

19.99.3.63 setEventThresholdReTestRequired()

VarLocation *loc*) [inline]
Set location of variables used to combine input from this synapse group.

This is ignored for simulations on hardware with a single memory space

19.99.3.65 setMaxConnections()

```
void SynapseGroup::setMaxConnections (
          unsigned int maxConnections )
```

Sets the maximum number of target neurons any source neurons can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE to optimise CUDA implementation

19.99.3.66 setMaxDendriticDelayTimesteps()

Sets the maximum dendritic delay for synapses in this synapse group.

19.99.3.67 setMaxSourceConnections()

Sets the maximum number of source neurons any target neuron can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE and postsynaptic learning to optimise CUDA implementation

19.99.3.68 setNarrowSparseIndEnabled()

```
void SynapseGroup::setNarrowSparseIndEnabled ( bool\ enabled\ )
```

Enables or disables using narrow i.e. less than 32-bit types for sparse matrix indices.

19.99.3.69 setNumThreadsPerSpike()

Set how many threads CUDA implementation uses to process each spike when span type is PRESYNAPTIC.

19.99.3.70 setPSExtraGlobalParamLocation()

Set location of postsynaptic model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.99.3.71 setPSModelMergeTarget()

Set location of postsynaptic model state variable.

This is ignored for simulations on hardware with a single memory space

19.99.3.73 setSpanType()

Set how CUDA implementation is parallelised.

with a thread per target neuron (default) or a thread per source spike

19.99.3.74 setSparseConnectivityExtraGlobalParamLocation()

Set location of sparse connectivity initialiser extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.99.3.75 setSparseConnectivityLocation()

Set variable mode used for sparse connectivity.

This is ignored for simulations on hardware with a single memory space

19.99.3.76 setWUExtraGlobalParamLocation()

Set location of weight update model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.99.3.77 setWUPostVarLocation()

```
VarLocation loc )
```

Set location of weight update model postsynaptic state variable.

This is ignored for simulations on hardware with a single memory space

19.99.3.78 setWUPreVarLocation()

Set location of weight update model presynaptic state variable.

This is ignored for simulations on hardware with a single memory space

19.99.3.79 setWUVarLocation()

Set location of weight update model state variable.

This is ignored for simulations on hardware with a single memory space


The documentation for this class was generated from the following files:

- · synapseGroup.h
- · synapseGroup.cc

19.100 SynapseGroupInternal Class Reference

```
#include <synapseGroupInternal.h>
```

Inheritance diagram for SynapseGroupInternal:



Public Member Functions

SynapseGroupInternal (const std::string name, SynapseMatrixType matrixType, unsigned int delaySteps, const WeightUpdateModels::Base *wu, const std::vector< double > &wuParams, const std::vector< Models::VarInit > &wuParams, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &psVarInitialisers, const std::vector< double > &psParams, const std::vector< Models::VarInit > &psVarInitialisers, NeuronGroup← Internal *srcNeuronGroup, NeuronGroupInternal *trgNeuronGroup, const InitSparseConnectivitySnippet::← Init &connectivityInitialiser, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, VarLocation defaultSparseConnectivityLocation, bool defaultNarrowSparseIndEnabled)

Additional Inherited Members

19.100.1 Constructor & Destructor Documentation

19.100.1.1 SynapseGroupInternal()

```
SynapseGroupInternal::SynapseGroupInternal (
             const std::string name,
             SynapseMatrixType matrixType,
             unsigned int delaySteps,
             const WeightUpdateModels::Base * wu,
             const std::vector< double > & wuParams,
             const std::vector< Models::VarInit > & wuVarInitialisers,
             const std::vector< Models::VarInit > & wuPreVarInitialisers,
             const std::vector< Models::VarInit > & wuPostVarInitialisers,
             const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trgNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation,
             bool defaultNarrowSparseIndEnabled ) [inline]
```


The documentation for this class was generated from the following file:

· synapseGroupInternal.h

19.101 CodeGenerator::TeeBuf Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeBuf:



Public Member Functions

```
    template<typename... T>
        TeeBuf (T &&... streamBufs)
```

19.101.1 Constructor & Destructor Documentation

```
19.101.1.1 TeeBuf()
```


The documentation for this class was generated from the following file:

· teeStream.h

19.102 CodeGenerator::TeeStream Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeStream:



Public Member Functions

 template<typename... T>
 TeeStream (T &&... streamBufs)

19.102.1 Constructor & Destructor Documentation

19.102.1.1 TeeStream()

The documentation for this class was generated from the following file:

· teeStream.h

19.103 SpineMLSimulator::Timer Class Reference

```
#include <timer.h>
```

Public Member Functions

- Timer (const std::string &title)
- ∼Timer ()
- double get () const

19.103.1 Constructor & Destructor Documentation

19.103.1.1 Timer()

```
SpineMLSimulator::Timer::Timer (
const std::string & title ) [inline]

19.103.1.2 ~Timer()

SpineMLSimulator::Timer::~Timer ( ) [inline]

19.103.2 Member Function Documentation

19.103.2.1 get()
```

The documentation for this class was generated from the following file:

double SpineMLSimulator::Timer::get () const [inline]

• include/spineml/simulator/timer.h

19.104 Timer Class Reference

A generic timer which can give the current elapsed time.

```
#include <timer.h>
```

Public Member Functions

• Timer (const std::string &message, const std::string &filename="")

Create a new Timer with the specified name and optionally a filename to append time to.

• ∼Timer ()

Stop the timer and print current elapsed time to terminal.

· double get () const

Get the elapsed time since this object was created.

19.104.1 Detailed Description

A generic timer which can give the current elapsed time.

19.104.2 Constructor & Destructor Documentation

19.104.2.1 Timer()

Create a new Timer with the specified name and optionally a filename to append time to.

```
19.104.2.2 \simTimer()
```

Timer::~Timer () [inline]

Stop the timer and print current elapsed time to terminal.

19.104.3 Member Function Documentation

```
19.104.3.1 get()
double Timer::get ( ) const [inline]
```

Get the elapsed time since this object was created.

The documentation for this class was generated from the following file:

• userproject/include/timer.h

19.105 TimerAccumulate Class Reference

A timer which adds its elapsed time to an accumulator variable on destruction.

```
#include <timer.h>
```

Public Member Functions

- TimerAccumulate (double &accumulator)
- ∼TimerAccumulate ()
- double get () const

Get the elapsed time since this object was created.

19.105.1 Detailed Description

A timer which adds its elapsed time to an accumulator variable on destruction.

19.105.2 Constructor & Destructor Documentation

19.105.2.1 TimerAccumulate()

19.105.2.2 ∼TimerAccumulate()

```
\label{timerAccumulate::} \verb|TimerAccumulate::\sim| TimerAccumulate ( ) [inline] \\
```

19.105.3 Member Function Documentation

#include <timer.h>

Public Member Functions

- TimerAccumulate (double &accumulator)
- ∼TimerAccumulate ()
- · double get () const

19.106.1 Constructor & Destructor Documentation

```
19.106.1.1 TimerAccumulate()
```

19.106.1.2 ~TimerAccumulate()

```
SpineMLSimulator::TimerAccumulate::~TimerAccumulate ( ) [inline]
```

19.106.2 Member Function Documentation

```
19.106.2.1 get()
```

```
double SpineMLSimulator::TimerAccumulate::get ( ) const [inline]
```


The documentation for this class was generated from the following file:

· include/spineml/simulator/timer.h

19.107 SpineMLSimulator::InputValue::TimeVarying Class Reference

```
#include <inputValue.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator :: Input Value :: Time Varying :: Input Value :: Input$



Public Member Functions

- TimeVarying (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.107.1 Constructor & Destructor Documentation

19.107.1.1 TimeVarying()

19.107.2 Member Function Documentation

19.107.2.1 update()

Implements SpineMLSimulator::InputValue::Base.

The documentation for this class was generated from the following files:

- inputValue.h
- · inputValue.cc

19.108 SpineMLSimulator::InputValue::TimeVaryingArray Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::TimeVaryingArray:

```
SpineMLSimulator::InputValue::Base

SpineMLSimulator::InputValue::TimeVaryingArray
```

Public Member Functions

- TimeVaryingArray (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.108.1 Constructor & Destructor Documentation

19.108.1.1 TimeVaryingArray()

19.108.2 Member Function Documentation

19.108.2.1 update()

Implements SpineMLSimulator::InputValue::Base.

The documentation for this class was generated from the following files:


- inputValue.h
- inputValue.cc

19.109 NeuronModels::TraubMiles Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::TraubMiles:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

• virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

· virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

Static Public Member Functions

• static const NeuronModels::TraubMiles * getInstance ()

Additional Inherited Members

19.109.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

This conductance based model has been taken from [7] and can be described by the equations:

$$C\frac{dV}{dt} = -I_{Na} - I_K - I_{leak} - I_M - I_{i,DC} - I_{i,syn} - I_i,$$

$$I_{Na}(t) = g_{Na}m_i(t)^3 h_i(t)(V_i(t) - E_{Na})$$

$$I_K(t) = g_K n_i(t)^4 (V_i(t) - E_K)$$

$$\frac{dy(t)}{dt} = \alpha_y(V(t))(1 - y(t)) - \beta_y(V(t))y(t),$$

where $y_i = m, h, n$, and

$$\alpha_n = 0.032(-50-V)/(\exp((-50-V)/5)-1)$$

$$\beta_n = 0.5\exp((-55-V)/40)$$

$$\alpha_m = 0.32(-52-V)/(\exp((-52-V)/4)-1)$$

$$\beta_m = 0.28(25+V)/(\exp((25+V)/5)-1)$$

$$\alpha_h = 0.128\exp((-48-V)/18)$$

$$\beta_h = 4/(\exp((-25-V)/5)+1).$$

and typical parameters are C=0.143 nF, $g_{\rm leak}=0.02672~\mu$ S, $E_{\rm leak}=-63.563$ mV, $g_{\rm Na}=7.15~\mu$ S, $E_{\rm Na}=50$ mV, $g_{\rm K}=1.43~\mu$ S, $E_{\rm K}=-95$ mV.

It has 4 variables:

- ∨ membrane potential E
- \ensuremath{m} probability for Na channel activation \ensuremath{m}
- · h probability for not Na channel blocking h

• n - probability for K channel activation n

and 7 parameters:

- gNa Na conductance in 1/(mOhms * cm²)
- ENa Na equi potential in mV
- gK K conductance in 1/(mOhms * cm²)
- EK K equi potential in mV
- gl Leak conductance in 1/(mOhms * cm²)
- E1 Leak equi potential in mV
- Cmem Membrane capacity density in muF/cm²

Note

[static]

Internally, the ordinary differential equations defining the model are integrated with a linear Euler algorithm and GeNN integrates 25 internal time steps for each neuron for each network time step. I.e., if the network is simulated at DT = 0.1 ms, then the neurons are integrated with a linear Euler algorithm with 1DT = 0.004 ms. This variant uses IF statements to check for a value at which a singularity would be hit. If so, value calculated by L'Hospital rule is used.

19.109.2 Member Typedef Documentation

```
19.109.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMiles::ParamValues

19.109.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PostVarValues

19.109.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PreVarValues

19.109.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMiles::VarValues

19.109.3 Member Function Documentation

19.109.3.1 getInstance()
```

static const NeuronModels::TraubMiles* NeuronModels::TraubMiles::getInstance () [inline],

19.109.3.2 getParamNames()

virtual StringVec NeuronModels::TraubMiles::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

Reimplemented in NeuronModels::TraubMilesNStep.

19.109.3.3 getSimCode()

virtual std::string NeuronModels::TraubMiles::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMilesAlt, and NeuronModels::Traub MilesFast.

19.109.3.4 getThresholdConditionCode()

```
virtual std::string NeuronModels::TraubMiles::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

```
19.109.3.5 getVars()
```

```
virtual VarVec NeuronModels::TraubMiles::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


neuronModels.h

19.110 NeuronModels::TraubMilesAlt Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::TraubMilesAlt:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

Static Public Member Functions

• static const NeuronModels::TraubMilesAlt * getInstance ()

Additional Inherited Members

19.110.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Using a workaround to avoid singularity: adding the munimum numerical value of the floating point precision used.

19.110.2 Member Typedef Documentation

19.110.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesAlt::ParamValues

19.110.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PostVarValues

19.110.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PreVarValues

19.110.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesAlt::VarValues

19.110.3 Member Function Documentation

19.110.3.1 getInstance()

static const NeuronModels::TraubMilesAlt* NeuronModels::TraubMilesAlt::getInstance () [inline],
[static]

19.110.3.2 getSimCode()

virtual std::string NeuronModels::TraubMilesAlt::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


· neuronModels.h

19.111 NeuronModels::TraubMilesFast Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesFast:



Public Types

typedef Snippet::ValueBase< 7 > ParamValues

- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.

Static Public Member Functions

static const NeuronModels::TraubMilesFast * getInstance ()

Additional Inherited Members

19.111.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

There are singularities in this model, which can be easily hit in float precision

19.111.2 Member Typedef Documentation

19.111.2.1 ParamValues

```
typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesFast::ParamValues
```

19.111.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PostVarValues

19.111.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PreVarValues

19.111.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesFast::VarValues

19.111.3 Member Function Documentation

19.111.3.1 getInstance()

static const NeuronModels::TraubMilesFast* NeuronModels::TraubMilesFast::getInstance () [inline],
[static]

19.111.3.2 getSimCode()

virtual std::string NeuronModels::TraubMilesFast::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


neuronModels.h

19.112 NeuronModels::TraubMilesNStep Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesNStep:



Public Types

- typedef Snippet::ValueBase< 8 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Static Public Member Functions

• static const NeuronModels::TraubMilesNStep * getInstance ()

Additional Inherited Members

19.112.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Same as standard TraubMiles model but number of inner loops can be set using a parameter

19.112.2 Member Typedef Documentation

19.112.2.1 ParamValues

```
typedef Snippet::ValueBase< 8 > NeuronModels::TraubMilesNStep::ParamValues
```

19.112.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PostVarValues
```

19.112.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PreVarValues
```

19.112.2.4 VarValues

```
typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesNStep::VarValues
```

19.112.3 Member Function Documentation

19.112.3.1 getInstance()

```
static const NeuronModels::TraubMilesNStep* NeuronModels::TraubMilesNStep::getInstance ( )
[inline], [static]
```

19.112.3.2 getParamNames()

```
virtual StringVec NeuronModels::TraubMilesNStep::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::TraubMiles.

19.112.3.3 getSimCode()

```
virtual std::string NeuronModels::TraubMilesNStep::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


neuronModels.h

19.113 InitVarSnippet::Uniform Class Reference

Initialises variable by sampling from the uniform distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uniform:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Uniform, 2)
- SET_CODE ("const scalar scale = \$(max) \$(min);\ "\$(value)=\$(min)+(\$(gennrand_uniform) *scale);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.113.1 Detailed Description

Initialises variable by sampling from the uniform distribution.

This snippet takes 2 parameters:

- min The minimum value
- max The maximum value

19.113.2 Member Function Documentation

19.113.2.1 DECLARE_SNIPPET()

19.113.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Uniform::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.113.2.3 SET_CODE()
```

The documentation for this class was generated from the following file:

• initVarSnippet.h

19.114 SpineMLSimulator::ModelProperty::UniformDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::UniformDistribution:

```
SpineMLSimulator::ModelProperty::Base

SpineMLSimulator::ModelProperty::UniformDistribution
```

Public Member Functions

- UniformDistribution (const pugi::xml_node &node, const StateVar < scalar > &stateVar, unsigned int size)
- void setValue (scalar min, scalar max)

19.114.1 Constructor & Destructor Documentation

19.114.1.1 UniformDistribution()

19.114.2 Member Function Documentation

19.114.2.1 setValue()

The documentation for this class was generated from the following files:


- · modelProperty.h
- · modelProperty.cc

19.115 InitVarSnippet::Uninitialised Class Reference

Used to mark variables as uninitialised - no initialisation code will be run.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uninitialised:



Public Member Functions

• DECLARE_SNIPPET (InitVarSnippet::Uninitialised, 0)

Additional Inherited Members

19.115.1 Detailed Description

Used to mark variables as uninitialised - no initialisation code will be run.

19.115.2 Member Function Documentation

19.115.2.1 DECLARE_SNIPPET()

The documentation for this class was generated from the following file:


• initVarSnippet.h

19.116 InitSparseConnectivitySnippet::Uninitialised Class Reference

Used to mark connectivity as uninitialised - no initialisation code will be run.

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::Uninitialised:



Public Member Functions

• DECLARE_SNIPPET (InitSparseConnectivitySnippet::Uninitialised, 0)

Additional Inherited Members

19.116.1 Detailed Description

Used to mark connectivity as uninitialised - no initialisation code will be run.

19.116.2 Member Function Documentation

19.116.2.1 DECLARE_SNIPPET()

The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

19.117 Snippet::ValueBase < NumVars > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

```
    template<typename... T>
    ValueBase (T &&... vals)
```

const std::vector< double > & getValues () const

Gets values as a vector of doubles.

double operator[] (size_t pos) const

19.117.1 Constructor & Destructor Documentation

19.117.1.1 ValueBase()

19.117.2 Member Function Documentation

19.117.2.1 getValues()

```
template<size_t NumVars>
const std::vector<double>& Snippet::ValueBase< NumVars >::qetValues ( ) const [inline]
```

Gets values as a vector of doubles.

19.117.2.2 operator[]()

The documentation for this class was generated from the following file:

· snippet.h

19.118 Snippet::ValueBase < 0 > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

- template<typename... T>
 ValueBase (T &&... vals)
- std::vector< double > getValues () const

Gets values as a vector of doubles.

19.118.1 Detailed Description

```
template<> class Snippet::ValueBase< 0 >
```

Template specialisation of ValueBase to avoid compiler warnings in the case when a model requires no parameters or state variables

19.118.2 Constructor & Destructor Documentation

19.118.2.1 ValueBase()

19.118.3 Member Function Documentation

19.118.3.1 getValues()

```
std::vector<double> Snippet::ValueBase< 0 >::getValues () const [inline]
```

Gets values as a vector of doubles.


The documentation for this class was generated from the following file:

· snippet.h

19.119 SpineMLSimulator::ModelProperty::ValueList Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::ValueList:



Public Member Functions

- ValueList (const pugi::xml_node &node, const filesystem::path &basePath, const std::vector< unsigned int > *remapIndices, const StateVar< scalar > &stateVar, unsigned int size)
- void setValue (const std::vector< scalar > &values, const std::vector< unsigned int > *remapIndices)

19.119.1 Constructor & Destructor Documentation

19.119.1.1 ValueList()

19.119.2 Member Function Documentation

19.119.2.1 setValue()

The documentation for this class was generated from the following files:

- · modelProperty.h
- · modelProperty.cc

19.120 Models::Base::Var Struct Reference

A variable has a name, a type and an access type.

```
#include <models.h>
```

Public Member Functions

- Var ()
- Var (const std::string &n, const std::string &t, VarAccess a)
- Var (const std::string &n, const std::string &t)

Public Attributes

- std::string name
- std::string type
- VarAccess access

19.120.1 Detailed Description

A variable has a name, a type and an access type.

Explicit constructors required as although, through the wonders of C++ aggregate initialization, access would default to VarAccess::READ_WRITE if not specified, this results in a -Wmissing-field-initializers warning on GCC and Clang

19.120.2 Constructor & Destructor Documentation

19.120.3 Member Data Documentation

19.120.3.1 access

VarAccess Models::Base::Var::access

19.120.3.2 name

std::string Models::Base::Var::name

19.120.3.3 type

```
std::string Models::Base::Var::type
```


The documentation for this struct was generated from the following file:

· models.h

19.121 pygenn.model_preprocessor.Variable Class Reference

Class holding information about GeNN variables.

Inheritance diagram for pygenn.model_preprocessor.Variable:



Public Member Functions

- def __init__ (self, variable_name, variable_type, values=None)
 - Init Variable.
- def set_values (self, values)

Set Variable's values.

Public Attributes

- name
- type
- view
- needs_allocation
- · init_required
- init_val
- values

19.121.1 Detailed Description

Class holding information about GeNN variables.

19.121.2 Constructor & Destructor Documentation

```
19.121.2.1 __init__()
```

Init Variable.

Parameters

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable, single value or VarInit instance

19.121.3 Member Function Documentation

19.121.3.1 set_values()

Set Variable's values.

Parameters

	values	iterable, single value or VarInit instance
--	--------	--

19.121.4 Member Data Documentation

19.121.4.1 init_required

 $\verb|pygenn.model_preprocessor.Variable.init_required|\\$

19.121.4.2 init_val

 $\verb|pygenn.model_preprocessor.Variable.init_val|\\$

19.121.4.3 name

 $\verb|pygenn.model_preprocessor.Variable.name|\\$

19.121.4.4 needs_allocation

pygenn.model_preprocessor.Variable.needs_allocation

19.121.4.5 type

```
pygenn.model_preprocessor.Variable.type
```

19.121.4.6 values

pygenn.model_preprocessor.Variable.values

19.121.4.7 view

```
pygenn.model_preprocessor.Variable.view
```


The documentation for this class was generated from the following file:

· model_preprocessor.py

19.122 Models::VarInit Class Reference

```
#include <models.h>
```

Inheritance diagram for Models::VarInit:



Public Member Functions

- VarInit (const InitVarSnippet::Base *snippet, const std::vector< double > ¶ms)
- · VarInit (double constant)

19.122.1 Constructor & Destructor Documentation

The documentation for this class was generated from the following file:

models.h

19.123 Models::VarInitContainerBase < NumVars > Class Template Reference

```
#include <models.h>
```

Public Member Functions

- template<typename... T>
 VarInitContainerBase (T &&... initialisers)
- const std::vector< VarInit > & getInitialisers () const

Gets initialisers as a vector of Values.

const VarInit & operator[] (size_t pos) const

19.123.1 Detailed Description

```
template < size_t NumVars > class Models::VarInitContainerBase < NumVars >
```

Wrapper to ensure at compile time that correct number of value initialisers are used when specifying the values of a model's initial state.

19.123.2 Constructor & Destructor Documentation

19.123.2.1 VarInitContainerBase()

19.123.3 Member Function Documentation

19.123.3.1 getInitialisers()

```
template<size_t NumVars>
const std::vector<VarInit>& Models::VarInitContainerBase< NumVars >::getInitialisers ( )
const [inline]
```

Gets initialisers as a vector of Values.

19.123.3.2 operator[]()

The documentation for this class was generated from the following file:

· models.h

19.124 Models::VarInitContainerBase < 0 > Class Template Reference

```
#include <models.h>
```

Public Member Functions

- template<typename... T>
 VarInitContainerBase (T &&... initialisers)
- VarInitContainerBase (const Snippet::ValueBase< 0 > &)
- std::vector< VarInit > getInitialisers () const

Gets initialisers as a vector of Values.

19.124.1 Detailed Description

```
template<> class Models::VarInitContainerBase< 0 >
```

Template specialisation of ValueInitBase to avoid compiler warnings in the case when a model requires no variable initialisers

19.124.2 Constructor & Destructor Documentation

```
19.124.2.1 VarInitContainerBase() [1/2]
```

19.124.2.2 VarInitContainerBase() [2/2]

19.124.3 Member Function Documentation

19.124.3.1 getInitialisers()

```
std::vector<VarInit> Models::VarInitContainerBase< 0 >::getInitialisers ( ) const [inline]
```

Gets initialisers as a vector of Values.

The documentation for this class was generated from the following file:

models.h

20 File Documentation

20.1 00_MainPage.dox File Reference

- 20.2 01_Installation.dox File Reference
- 20.3 02 Quickstart.dox File Reference
- 20.4 03_Examples.dox File Reference
- 20.5 05_SpineML.dox File Reference
- 20.6 06_Brian2GeNN.dox File Reference
- 20.7 07_PyGeNN.dox File Reference
- 20.8 09_ReleaseNotes.dox File Reference
- 20.9 10_UserManual.dox File Reference
- 20.10 11_Tutorial.dox File Reference
- 20.11 12_Tutorial.dox File Reference
- 20.12 13_UserGuide.dox File Reference
- 20.13 14_Credits.dox File Reference
- 20.14 __init__.py File Reference

Namespaces

• pygenn

20.15 analogueRecorder.h File Reference

```
#include <fstream>
#include <initializer_list>
#include <string>
#include <vector>
```

Classes

class AnalogueRecorder< T >

20.16 backend.cc File Reference

```
#include "backend.h"
#include <algorithm>
#include <plog/Log.h>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
```

```
#include "utils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

• CodeGenerator::CUDA

20.17 backend.cc File Reference

```
#include "backend.h"
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::SingleThreadedCPU

20.18 backend.h File Reference

```
#include <algorithm>
#include <array>
#include <functional>
#include <map>
#include <string>
#include <unordered_set>
#include <cuda.h>
#include <cuda.runtime.h>
#include "backendExport.h"
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "presynapticUpdateStrategy.h"
```

Classes

struct CodeGenerator::CUDA::Preferences

Preferences for CUDA backend.

· class CodeGenerator::CUDA::Backend

Namespaces

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· CodeGenerator::CUDA

Typedefs

using CodeGenerator::CUDA::KernelBlockSize = std::array < size_t, KernelMax >
 Array of block sizes for each kernel.

Enumerations

enum CodeGenerator::CUDA::DeviceSelect { CodeGenerator::CUDA::DeviceSelect::OPTIMAL, Code
 Generator::CUDA::DeviceSelect::MOST_MEMORY, CodeGenerator::CUDA::DeviceSelect::MANUAL }

Methods for selecting CUDA device.

 enum CodeGenerator::CUDA::BlockSizeSelect { CodeGenerator::CUDA::BlockSizeSelect::OCCUPANCY, CodeGenerator::CUDA::BlockSizeSelect::MANUAL }

Methods for selecting CUDA kernel block size.

enum CodeGenerator::CUDA::Kernel {
 CodeGenerator::CUDA::KernelNeuronUpdate, CodeGenerator::CUDA::KernelPresynapticUpdate, CodeGenerator::CUDA::KernelSynapseDynamicsUpdate,
 Generator::CUDA::KernelPostsynapticUpdate, CodeGenerator::CUDA::KernelSynapseDynamicsUpdate,
 CodeGenerator::CUDA::KernelInitialize, CodeGenerator::CUDA::KernelInitializeSparse, CodeGenerator::CUDA::KernelPreSynapseReset,
 CodeGenerator::CUDA::KernelMax }

Kernels generated by CUDA backend.

20.19 backend.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include "backendExport.h"
#include "code_generator/backendBase.h"
```

Classes

- struct CodeGenerator::SingleThreadedCPU::Preferences
- · class CodeGenerator::SingleThreadedCPU::Backend

Namespaces

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::SingleThreadedCPU

20.20 backendBase.cc File Reference

```
#include "code_generator/backendBase.h"
#include <plog/Log.h>
#include "gennUtils.h"
```

Macros

• #define TYPE(T) {#T, sizeof(T)}

20.20.1 Macro Definition Documentation

20.21 backendBase.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include <unordered_map>
#include <vector>
#include <plog/Severity.h>
#include "codeStream.h"
#include "gennExport.h"
#include "variableMode.h"
```

Classes

• struct CodeGenerator::PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

- class CodeGenerator::MemAlloc
- class CodeGenerator::BackendBase

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.22 backendExport.h File Reference

Macros

• #define BACKEND EXPORT

20.22.1 Macro Definition Documentation

20.22.1.1 BACKEND_EXPORT

```
#define BACKEND_EXPORT
```

20.23 binomial.cc File Reference

```
#include "binomial.h"
#include <stdexcept>
#include <cassert>
```

```
#include <cmath>
#include <cstdint>
```

Functions

• unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

20.23.1 Function Documentation

20.23.1.1 binomialInverseCDF()

```
unsigned int binomialInverseCDF ( \label{eq:cdf} \mbox{double } cdf, \\ \mbox{unsigned int } n, \\ \mbox{double } p \mbox{)}
```

20.24 binomial.h File Reference

```
#include "gennExport.h"
```

Functions

• GENN_EXPORT unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

20.24.1 Function Documentation

20.24.1.1 binomialInverseCDF()

```
GENN_EXPORT unsigned int binomialInverseCDF ( \mbox{double } cdf, \\ \mbox{unsigned int } n, \\ \mbox{double } p \mbox{)}
```

20.25 codeGenUtils.cc File Reference

```
#include "code_generator/codeGenUtils.h"
#include <regex>
#include <cstring>
#include "modelSpec.h"
#include "code_generator/substitutions.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Enumerations

· enum MathsFunc

Functions

- void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

 Tool for substituting strings in the neuron code strings or other templates.
- bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

• bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void CodeGenerator::preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postldx,
 const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

 void CodeGenerator::postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std:: ::string &preldx, const std::string &devPrefix, const std::string &postVarPrefix="", const std::string &postVar← Suffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &preldx, const std::string &postldx, const std::string &devPrefix, double
 dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="",
 const std::string &postVarSuffix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

20.25.1 Enumeration Type Documentation

20.25.1.1 MathsFunc

enum MathsFunc

20.26 codeGenUtils.h File Reference

```
#include <iomanip>
#include <limits>
#include <string>
#include <sstream>
#include <vector>
#include "models.h"
```

```
#include "snippet.h"
#include "variableMode.h"
```

Classes

• struct CodeGenerator::FunctionTemplate

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

• bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr> void CodeGenerator::writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr>
std::string CodeGenerator::writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void CodeGenerator::preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postIdx,
 const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

 void CodeGenerator::postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std:: ::string &preldx, const std::string &devPrefix, const std::string &postVarPrefix="", const std::string &postVar Suffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &preldx, const std::string &postldx, const std::string &devPrefix, double
 dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="",
 const std::string &postVarSuffix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

20.27 codeStream.cc File Reference

```
#include "code_generator/codeStream.h"
#include <algorithm>
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

20.28 codeStream.h File Reference

```
#include <ostream>
#include <stdexcept>
#include <streambuf>
#include <string>
#include <vector>
#include <plog/Log.h>
#include "gennExport.h"
```

Classes

- class CodeGenerator::CodeStream
- struct CodeGenerator::CodeStream::OB

An open bracket marker.

• struct CodeGenerator::CodeStream::CB

A close bracket marker.

· class CodeGenerator::CodeStream::Scope

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

20.29 connectors.cc File Reference

```
#include "connectors.h"
#include <algorithm>
#include <fstream>
#include <iostream>
```

```
#include <numeric>
#include <random>
#include <tuple>
#include <vector>
#include <cassert>
#include <cstdint>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
```

20.30 connectors.h File Reference

```
#include <vector>
#include <cstdint>
```

Namespaces

- pugi
- filesystem
- SpineMLSimulator
- SpineMLSimulator::Connectors

Functions

unsigned int SpineMLSimulator::Connectors::create (const pugi::xml_node &node, double dt, unsigned int numPre, unsigned int numPost, unsigned int **rowLength, unsigned int **ind, uint8_t **delay, const unsigned int *maxRowLength, const filesystem::path &basePath, std::vector< unsigned int > &remapIndices)

20.31 currentSource.cc File Reference

```
#include "currentSource.h"
#include <algorithm>
#include <cmath>
#include "gennUtils.h"
```

20.32 currentSource.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "currentSourceModels.h"
#include "gennExport.h"
#include "variableMode.h"
```

Classes

class CurrentSource

20.33 currentSourceInternal.h File Reference

```
#include "currentSource.h"
```

Classes

· class CurrentSourceInternal

20.34 currentSourceModels.cc File Reference

```
#include "currentSourceModels.h"
```

Functions

- IMPLEMENT_MODEL (CurrentSourceModels::DC)
- IMPLEMENT_MODEL (CurrentSourceModels::GaussianNoise)

20.34.1 Function Documentation

20.35 currentSourceModels.h File Reference

```
#include <array>
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "gennExport.h"
#include "models.h"
```

Classes

· class CurrentSourceModels::Base

Base class for all current source models.

• class CurrentSourceModels::DC

DC source.

• class CurrentSourceModels::GaussianNoise

Noisy current source with noise drawn from normal distribution.

Namespaces

CurrentSourceModels

Macros

#define SET_INJECTION_CODE(INJECTION_CODE) virtual std::string getInjectionCode() const override{
 return INJECTION CODE;}

20.35.1 Macro Definition Documentation

20.35.1.1 SET_INJECTION_CODE

20.36 generateAll.cc File Reference

```
#include "code_generator/generateAll.h"
#include <fstream>
#include <vector>
#include <vplog/Log.h>
#include "path.h"
#include "code_generator/codeStream.h"
#include "code_generator/generateInit.h"
#include "code_generator/generateMPI.h"
#include "code_generator/generateNeuronUpdate.h"
#include "code_generator/generateSupportCode.h"
#include "code_generator/generateSynapseUpdate.h"
#include "code_generator/generateRunner.h"
```

20.37 generateAll.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· filesystem

Functions

GENN_EXPORT std::vector< std::string > CodeGenerator::generateAll (const ModelSpecInternal &model, const BackendBase &backend, const filesystem::path &outputPath, bool standaloneModules=false)

20.38 generateInit.cc File Reference

```
#include "code_generator/generateInit.h"
#include 'models.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.39 generatelnit.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void CodeGenerator::generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.40 generateMakefile.cc File Reference

```
#include "code_generator/generateMakefile.h"
#include <string>
#include "modelSpec.h"
#include "code_generator/backendBase.h"
```

20.41 generateMakefile.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void GENN_EXPORT CodeGenerator::generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector< std::string > &moduleNames)

20.42 generateMPI.cc File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include "code_generator/generateMPI.h"
#include <fstream>
#include <cstring>
#include "modelSpecInternal.h"
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
```

20.42.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

20.43 generateMPI.h File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include <string>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void GENN_EXPORT CodeGenerator::generateMPI (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

A function that generates predominantly MPI infrastructure code.

20.43.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

20.44 generateMSBuild.cc File Reference

```
#include "code_generator/generateMSBuild.h"
#include <string>
#include "code_generator/backendBase.h"
```

20.45 generateMSBuild.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

void GENN_EXPORT CodeGenerator::generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)

20.46 generateNeuronUpdate.cc File Reference

```
#include "code_generator/generateNeuronUpdate.h"
#include <iostream>
#include <string>
#include <plog/Log.h>
#include "models.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/substitutions.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.47 generateNeuronUpdate.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.48 generateRun.h File Reference

```
#include <algorithm>
#include <fstream>
#include <iostream>
#include <string>
#include <cstdlib>
#include "../../include/genn/third_party/CLI11.hpp"
```

Classes

• class GenerateRunBase

20.49 generateRunner.cc File Reference

```
#include "code_generator/generateRunner.h"
#include <sstream>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/teeStream.h"
#include "code_generator/backendBase.h"
```

20.50 generateRunner.h File Reference

```
#include "code_generator/backendBase.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• MemAlloc CodeGenerator::generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)

20.51 generateSupportCode.cc File Reference

```
#include "code_generator/generateSupportCode.h"
#include <string>
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
```

20.52 generateSupportCode.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateSupportCode (CodeStream &os, const ModelSpecInternal &model)

20.53 generateSynapseUpdate.cc File Reference

```
#include "code_generator/generateSynapseUpdate.h"
#include <string>
```

```
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.54 generateSynapseUpdate.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.55 genn_groups.py File Reference

Classes

class pygenn.genn_groups.Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

class pygenn.genn_groups.NeuronGroup

Class representing a group of neurons.

• class pygenn.genn_groups.SynapseGroup

Class representing synaptic connection between two groups of neurons.

• class pygenn.genn_groups.CurrentSource

Class representing a current injection into a group of neurons.

Namespaces

• pygenn.genn_groups

Variables

• pygenn.genn_groups.xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

20.56 genn_model.py File Reference

Classes

• class pygenn.genn_model.GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

Namespaces

• pygenn.genn_model

Functions

def pygenn.genn_model.init_var (init_var_snippet, param_space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

def pygenn.genn_model.init_connectivity (init_sparse_connect_snippet, param_space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def pygenn.genn_model.create_custom_neuron_class (class_name, param_names=None, var_name_
 types=None, derived_params=None, sim_code=None, threshold_condition_code=None, reset_code=None,
 support_code=None, extra_global_params=None, additional_input_vars=None, is_auto_refractory_
 required=None, custom_body=None)

This helper function creates a custom NeuronModel class.

def pygenn.genn_model.create_custom_postsynaptic_class (class_name, param_names=None, var
 __name_types=None, derived_params=None, decay_code=None, apply_input_code=None, support_
 code=None, custom body=None)

This helper function creates a custom PostsynapticModel class.

def pygenn_genn_model.create_custom_weight_update_class (class_name, param_names=None, var—name_types=None, pre_var_name_types=None, post_var_name_types=None, derived_params=None, sim_code=None, event_code=None, learn_post_code=None, synapse_dynamics_code=None, event_code=None, learn_post_spike_code=None, sim_support_code=None, learn_post_support_code=None, synapse_dynamics_support_code=None, extra_global_params=None, is_pre_spike_time_required=None, custom_body=None)

This helper function creates a custom WeightUpdateModel class.

def pygenn.genn_model.create_custom_current_source_class (class_name, param_names=None, var_
 name_types=None, derived_params=None, injection_code=None, extra_global_params=None, custom_
 body=None)

This helper function creates a custom NeuronModel class.

 def pygenn.genn_model.create_custom_model_class (class_name, base, param_names, var_name_types, derived params, custom body)

This helper function completes a custom model class creation.

def pygenn.genn_model.create_dpf_class (dp_func)

Helper function to create derived parameter function class.

def pygenn.genn_model.create_cmlf_class (cml_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

def pygenn.genn_model.create_custom_init_var_snippet_class (class_name, param_names=None, derived_params=None, var_init_code=None, custom_body=None)

This helper function creates a custom InitVarSnippet class.

def pygenn.genn_model.create_custom_sparse_connect_init_snippet_class (class_name, param_
 names=None, derived_params=None, row_build_code=None, row_build_state_vars=None, calc_max_
 row_len_func=None, calc_max_col_len_func=None, extra_global_params=None, custom_body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

Variables

- pygenn.genn_model.backend_modules = OrderedDict()
- pygenn.genn_model.m = import_module(".genn_wrapper." + b + "Backend", "pygenn")

20.57 gennExport.h File Reference

Macros

• #define GENN EXPORT

20.57.1 Macro Definition Documentation

20.57.1.1 GENN_EXPORT

```
#define GENN_EXPORT
```

20.58 gennUtils.cc File Reference

```
#include "gennUtils.h"
#include <algorithm>
```

Namespaces

Utils

Functions

• GENN_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN_EXPORT bool Utils::isInitRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

GENN_EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

20.59 gennUtils.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
#include "models.h"
```

Namespaces

Utils

Functions

• GENN_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

• GENN_EXPORT bool Utils::isInitRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

• GENN_EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

20.60 initSparseConnectivitySnippet.cc File Reference

```
#include "initSparseConnectivitySnippet.h"
```

Functions

- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::Uninitialised)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::OneToOne)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::FixedProbability)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse)

20.60.1 Function Documentation

20.61 initSparseConnectivitySnippet.h File Reference

```
#include <functional>
#include <vector>
#include <cassert>
#include <cmath>
#include "binomial.h"
#include "snippet.h"
```

Classes

- · class InitSparseConnectivitySnippet::Base
- · class InitSparseConnectivitySnippet::Init
- class InitSparseConnectivitySnippet::Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

class InitSparseConnectivitySnippet::OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

- class InitSparseConnectivitySnippet::FixedProbabilityBase
- class InitSparseConnectivitySnippet::FixedProbability
- class InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

Namespaces

InitSparseConnectivitySnippet

Base class for all sparse connectivity initialisation snippets.

Macros

- #define SET_ROW_BUILD_CODE(CODE) virtual std::string getRowBuildCode() const override{ return CO←DE: }
- #define SET_ROW_BUILD_STATE_VARS(...) virtual ParamValVec getRowBuildStateVars() const override{
 return VA ARGS ;}
- #define SET_CALC_MAX_ROW_LENGTH_FUNC(FUNC) virtual CalcMaxLengthFunc getCalcMaxRow
 LengthFunc() const override{ return FUNC; }
- #define SET_CALC_MAX_COL_LENGTH_FUNC(FUNC) virtual CalcMaxLengthFunc getCalcMaxCol ← LengthFunc() const override{ return FUNC; }
- #define SET_MAX_ROW_LENGTH(MAX_ROW_LENGTH) virtual CalcMaxLengthFunc getCalcMaxRow
 LengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return M←
 AX ROW LENGTH; }; }
- #define SET_MAX_COL_LENGTH(MAX_COL_LENGTH) virtual CalcMaxLengthFunc getCalcMaxCol
 LengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return
 MAX_COL_LENGTH; }; }
- #define SET_EXTRA_GLOBAL_PARAMS(...) virtual EGPVec getExtraGlobalParams() const override{ return __VA_ARGS__;}

20.61.1 Macro Definition Documentation

20.61.1.1 SET_CALC_MAX_COL_LENGTH_FUNC

20.61.1.2 SET_CALC_MAX_ROW_LENGTH_FUNC

```
\label{eq:func} \begin{tabular}{ll} \#define & SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC ( \\ & FUNC \end{tabular} \begin{tabular}{ll} FUNC \end{tabular} \begin{tabular}{ll} FUNC & GetCalcMaxRowLengthFunc () & Const override \end{tabular} \begin{tabular}{ll} FUNC; \end{tabular} \begin{tabular}{ll} FUNC & GetCalcMaxRowLengthFunc () & Const override \end{tabular} \begin{tabular}{ll} FUNC; \end{tabular}
```

20.61.1.3 SET_EXTRA_GLOBAL_PARAMS

20.61.1.4 SET_MAX_COL_LENGTH #define SET_MAX_COL_LENGTH(MAX_COL_LENGTH) virtual CalcMaxLengthFunc getCalcMaxColLengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return MAX_COL_LENGTH; }; 20.61.1.5 SET_MAX_ROW_LENGTH #define SET_MAX_ROW_LENGTH(MAX_ROW_LENGTH) virtual CalcMaxLengthFunc getCalcMaxRowLengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return MAX_ROW_LENGTH; }; 20.61.1.6 SET_ROW_BUILD_CODE #define SET_ROW_BUILD_CODE(CODE) virtual std::string getRowBuildCode() const override{ return CODE; } 20.61.1.7 SET_ROW_BUILD_STATE_VARS #define SET_ROW_BUILD_STATE_VARS(...) virtual ParamValVec getRowBuildStateVars() const override{ return __VA_A↔ RGS__; } 20.62 initVarSnippet.cc File Reference #include "initVarSnippet.h" **Functions** • IMPLEMENT_SNIPPET (InitVarSnippet::Uninitialised) IMPLEMENT_SNIPPET (InitVarSnippet::Constant) IMPLEMENT SNIPPET (InitVarSnippet::Uniform) IMPLEMENT_SNIPPET (InitVarSnippet::Normal) IMPLEMENT_SNIPPET (InitVarSnippet::Exponential) IMPLEMENT_SNIPPET (InitVarSnippet::Gamma) 20.62.1 Function Documentation **20.62.1.1 IMPLEMENT_SNIPPET()** [1/6] IMPLEMENT_SNIPPET (InitVarSnippet::Uninitialised)

InitVarSnippet::Constant)

20.62.1.2 IMPLEMENT_SNIPPET() [2/6]

IMPLEMENT_SNIPPET (

Classes

- class InitVarSnippet::Base
- class InitVarSnippet::Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

• class InitVarSnippet::Constant

Initialises variable to a constant value.

class InitVarSnippet::Uniform

Initialises variable by sampling from the uniform distribution.

· class InitVarSnippet::Normal

Initialises variable by sampling from the normal distribution.

class InitVarSnippet::Exponential

Initialises variable by sampling from the exponential distribution.

· class InitVarSnippet::Gamma

Initialises variable by sampling from the exponential distribution.

Namespaces

InitVarSnippet

Base class for all value initialisation snippets.

Macros

#define SET_CODE(CODE) virtual std::string getCode() const override{ return CODE; }

20.63.1 Macro Definition Documentation

20.64 input.cc File Reference

```
#include "input.h"
#include <limits>
#include <iostream>
#include <cmath>
#include "pugixml/pugixml.hpp"
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "inputValue.h"
#include "modelProperty.h"
```

20.65 input.h File Reference

```
#include <functional>
#include <map>
#include <memory>
#include <random>
```

Classes

- · class SpineMLSimulator::Input::Base
- class SpineMLSimulator::Input::SpikeBase
- · class SpineMLSimulator::Input::InterSpikeIntervalBase
- · class SpineMLSimulator::Input::RegularSpikeRate
- class SpineMLSimulator::Input::PoissonSpikeRate
- · class SpineMLSimulator::Input::SpikeTime
- · class SpineMLSimulator::Input::Analogue

Namespaces

- pugi
- SpineMLSimulator
- SpineMLSimulator::InputValue
- SpineMLSimulator::ModelProperty
- SpineMLSimulator::Input

20.66 inputValue.cc File Reference

```
#include "inputValue.h"
#include <iostream>
#include <sstream>
#include <cassert>
```

```
#include <cmath>
#include <cstring>
#include "pugixml/pugixml.hpp"
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "spineMLUtils.h"
```

20.67 inputValue.h File Reference

```
#include <functional>
#include <map>
#include <memory>
#include <string>
#include <vector>
#include "networkClient.h"
```

Classes

- class SpineMLSimulator::InputValue::Base
- class SpineMLSimulator::InputValue::ScalarBase
- class SpineMLSimulator::InputValue::Constant
- class SpineMLSimulator::InputValue::ConstantArray
- class SpineMLSimulator::InputValue::TimeVarying
- class SpineMLSimulator::InputValue::TimeVaryingArray
- class SpineMLSimulator::InputValue::External
- class SpineMLSimulator::InputValue::ExternalNetwork

Namespaces

- pugi
- SpineMLSimulator
- SpineMLSimulator::InputValue

Functions

• std::unique_ptr< Base > SpineMLSimulator::InputValue::create (double dt, unsigned int numNeurons, const pugi::xml_node &node, std::map< std::string, InputValue::External *> &externalInputs)

20.68 logOutput.cc File Reference

```
#include "logOutput.h"
#include <algorithm>
#include <limits>
#include <iostream>
#include <cassert>
#include <cmath>
#include "path.h"
#include "pugixml/pugixml.hpp"

#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "spineMLUtils.h"
```

20.69 logOutput.h File Reference

```
#include <fstream>
#include <set>
#include <string>
#include <vector>
#include "modelProperty.h"
#include "networkClient.h"
```

Classes

- · class SpineMLSimulator::LogOutput::Base
- class SpineMLSimulator::LogOutput::AnalogueBase
- class SpineMLSimulator::LogOutput::AnalogueFile
- class SpineMLSimulator::LogOutput::AnalogueExternal
- · class SpineMLSimulator::LogOutput::AnalogueNetwork
- · class SpineMLSimulator::LogOutput::Event

Namespaces

- pugi
- filesystem
- SpineMLSimulator
- · SpineMLSimulator::LogOutput

20.70 logWriter.h File Reference

20.71 model_preprocessor.py File Reference

Classes

• class pygenn.model_preprocessor.Variable

Class holding information about GeNN variables.

class pygenn.model_preprocessor.ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

Namespaces

· pygenn.model_preprocessor

Functions

def pygenn.model_preprocessor.prepare_model (model, param_space, var_space, pre_var_space=None, post_var_space=None, model_family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

• def pygenn.model preprocessor.prepare snippet (snippet, param space, snippet family)

Prepare a snippet by checking its validity and extracting information about parameters.

def pygenn.model_preprocessor.is_model_valid (model, model_family)

Check whether the model is valid, i.e is native or derived from model_family.Custom.

def pygenn.model_preprocessor.param_space_to_vals (model, param_space)

Convert a param_space dict to ParamValues.

- def pygenn.model_preprocessor.param_space_to_val_vec (model, param_space)
 - Convert a param_space dict to a std::vector<double>
- def pygenn.model_preprocessor.var_space_to_vals (model, var_space)

Convert a var_space dict to VarValues.

- def pygenn.model_preprocessor.pre_var_space_to_vals (model, var_space)
 - Convert a var_space dict to PreVarValues.
- def pygenn.model_preprocessor.post_var_space_to_vals (model, var_space)

Convert a var_space dict to PostVarValues.

Variables

dictionary pygenn.model_preprocessor.genn_to_numpy_types

20.72 modelProperty.cc File Reference

```
#include "modelProperty.h"
#include <algorithm>
#include <fstream>
#include <iostream>
#include <cassert>
#include <cstring>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include <ploy/Log.h>
```

20.73 modelProperty.h File Reference

```
#include <memory>
#include <random>
#include <vector>
#include "stateVar.h"
```

Classes

- class SpineMLSimulator::ModelProperty::Base
- · class SpineMLSimulator::ModelProperty::Fixed
- class SpineMLSimulator::ModelProperty::ValueList
- class SpineMLSimulator::ModelProperty::UniformDistribution
- class SpineMLSimulator::ModelProperty::NormalDistribution
- class SpineMLSimulator::ModelProperty::ExponentialDistribution

Namespaces

- pugi
- · filesystem
- SpineMLSimulator
- · SpineMLSimulator::ModelProperty

Typedefs

• typedef float SpineMLSimulator::scalar

Functions

• std::unique_ptr< Base > SpineMLSimulator::ModelProperty::create (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size, bool skipGeNNInitialised, const filesystem::path &basePath, const std::string &valueNamespace, const std::vector< unsigned int > *remapIndices)

20.74 models.h File Reference

```
#include <string>
#include <vector>
#include "snippet.h"
#include "initVarSnippet.h"
```

Classes

- · class Models::VarInit
- class Models::VarInitContainerBase< NumVars >
- class Models::VarInitContainerBase< 0 >
- · class Models::Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

· struct Models::Base::Var

A variable has a name, a type and an access type.

Namespaces

Models

Macros

- #define DECLARE MODEL(TYPE, NUM PARAMS, NUM VARS)
- #define IMPLEMENT_MODEL(TYPE) IMPLEMENT_SNIPPET(TYPE)
- #define SET_VARS(...) virtual VarVec getVars() const override{ return __VA_ARGS__; }
- #define SET_EXTRA_GLOBAL_PARAMS(...) virtual EGPVec getExtraGlobalParams() const override{ return __VA_ARGS__;}

Enumerations

enum VarAccess { VarAccess::READ_WRITE = 0, VarAccess::READ_ONLY }

20.74.1 Macro Definition Documentation

How is this variable accessed by model?

20.74.1.1 DECLARE_MODEL

Value:

```
DECLARE_SNIPPET(TYPE, NUM_PARAMS);
    typedef Models::VarInitContainerBase<NUM_VARS> VarValues;
    typedef Models::VarInitContainerBase<0> PreVarValues;
typedef Models::VarInitContainerBase<0> PostVarValues
20.74.1.2 IMPLEMENT_MODEL
#define IMPLEMENT_MODEL(
                TYPE ) IMPLEMENT_SNIPPET(TYPE)
20.74.1.3 SET_EXTRA_GLOBAL_PARAMS
#define SET_EXTRA_GLOBAL_PARAMS(
               ... ) virtual EGPVec getExtraGlobalParams() const override{ return __VA_ARGS__;
20.74.1.4 SET_VARS
#define SET_VARS(
                ... ) virtual VarVec getVars() const override{ return __VA_ARGS__; }
20.74.2 Enumeration Type Documentation
20.74.2.1 VarAccess
enum VarAccess [strong]
How is this variable accessed by model?
```

Enumerator

READ_WRITE	
READ_ONLY	This variable is both read and written by the model.

20.75 modelSpec.cc File Reference

```
#include <algorithm>
#include <numeric>
#include <typeinfo>
#include <cstdio>
#include <cmath>
#include <cassert>
#include "modelSpec.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/substitutions.h"
```

20.76 modelSpec.h File Reference

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections.

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronGroupInternal.h"
#include "synapseGroupInternal.h"
#include "currentSourceInternal.h"
```

Classes

· class ModelSpec

Object used for specifying a neuronal network model.

Macros

• #define NO DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

Typedefs

typedef ModelSpec NNmodel

Enumerations

enum FloatType { , GENN_LONG_DOUBLE }

Floating point precision to use for models.

enum TimePrecision { TimePrecision::DEFAULT, TimePrecision::FLOAT, TimePrecision::DOUBLE }

Precision to use for variables which store time.

Functions

 $\bullet \ \ template {<} typename \ S >$

Models::VarInit initVar (const typename S::ParamValues ¶ms)

Initialise a variable using an initialisation snippet.

template<typename S >

```
std::enable_if< std::is_same< typename S::ParamValues, Snippet::ValueBase< 0 > >::value, Models::\leftarrow VarInit >::type initVar ()
```

Initialise a variable using an initialisation snippet with no parameters.

Models::VarInit uninitialisedVar ()

Mark a variable as uninitialised.

template<typename S >

InitSparseConnectivitySnippet::Init initConnectivity (const typename S::ParamValues ¶ms)

Initialise connectivity using a sparse connectivity snippet.

• template<typename S >

 $std::enable_if < std::is_same < typename S::ParamValues, Snippet::ValueBase < 0 > >::value, InitSparse \leftarrow ConnectivitySnippet::Init >::type initConnectivity ()$

Initialise connectivity using a sparse connectivity snippet with no parameters.

• InitSparseConnectivitySnippet::Init uninitialisedConnectivity ()

Mark a synapse group's sparse connectivity as uninitialised.

20.76.1 Detailed Description

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections.

20.76.2 Macro Definition Documentation

20.76.2.1 NO_DELAY

#define NO_DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

20.76.3 Typedef Documentation

20.76.3.1 NNmodel

typedef ModelSpec NNmodel

20.76.4 Enumeration Type Documentation

20.76.4.1 FloatType

enum FloatType

Floating point precision to use for models.

Enumerator

GENN_LONG_DOUBLE

20.76.4.2 TimePrecision

enum TimePrecision [strong]

Precision to use for variables which store time.

Enumerator

DEFAULT	Time uses default model precision.
FLOAT	Time uses single precision - not suitable for long simulations.
DOUBLE	Time uses double precision - may reduce performance.

20.76.5 Function Documentation

Initialise connectivity using a sparse connectivity snippet.

Template Parameters

S type of sparse connectivity initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

Parameters

params parameters for snippet wrapped in S::ParamValues object.

Returns

InitSparseConnectivitySnippet::Init object for passing to ModelSpec::addSynapsePopulation

```
20.76.5.2 initConnectivity() [2/2]
```

```
template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Init←
SparseConnectivitySnippet::Init>::type initConnectivity ( ) [inline]
```

Initialise connectivity using a sparse connectivity snippet with no parameters.

Template Parameters

S type of sparse connectivity initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

Returns

 $In it Sparse Connectivity Snippet :: In it object for passing to \verb|ModelSpec::addSynapsePopulation| \\$

Initialise a variable using an initialisation snippet.

Template Parameters

S | type of variable initialisation snippet (derived from InitVarSnippet::Base).

Parameters

params	parameters for snippet wrapped in S::ParamValues object.
1	Legion in the property of the

Returns

Models::VarInit object for use within model's VarValues

```
20.76.5.4 initVar() [2/2]

template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Models←
::VarInit>::type initVar ( ) [inline]
```

Initialise a variable using an initialisation snippet with no parameters.

Template Parameters

S type of variable initialisation snippet (derived from InitVarSnippet::Base).

Returns

Models::VarInit object for use within model's VarValues

20.76.5.5 uninitialisedConnectivity()

```
InitSparseConnectivitySnippet::Init uninitialisedConnectivity ( ) [inline]
```

Mark a synapse group's sparse connectivity as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the connectivity from host to device during initializeSparse function (and, if necessary generate any additional data structures it requires)

20.76.5.6 uninitialisedVar()

```
Models::VarInit uninitialisedVar ( ) [inline]
```

Mark a variable as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the variable from host to device during initializeSparse function

20.77 modelSpecInternal.h File Reference

```
#include "modelSpec.h"
```

Classes

· class ModelSpecInternal

20.78 networkClient.cc File Reference

```
#include "networkClient.h"
#include <stdexcept>
#include <cstring>
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
```

20.79 networkClient.h File Reference

```
#include <iostream>
#include <string>
#include <vector>
#include <arpa/inet.h>
#include <netinet/in.h>
#include <netinet/tcp.h>
#include <sys/socket.h>
#include <sys/types.h>
#include <unistd.h>
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
```

Classes

· class SpineMLSimulator::NetworkClient

Namespaces

SpineMLSimulator

20.80 neuronGroup.cc File Reference

```
#include "neuronGroup.h"
#include <algorithm>
#include <cmath>
#include <plog/Log.h>
#include "currentSourceInternal.h"
#include "neuronGroupInternal.h"
#include "synapseGroupInternal.h"
#include "gennUtils.h"
```

20.81 neuronGroup.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronModels.h"
#include "variableMode.h"
```

Classes

· class NeuronGroup

20.82 neuronGroupInternal.h File Reference

```
#include "neuronGroup.h"
```

Classes

· class NeuronGroupInternal

20.83 neuronModels.cc File Reference

```
#include "neuronModels.h"
```

Functions

- IMPLEMENT_MODEL (NeuronModels::RulkovMap)
- IMPLEMENT_MODEL (NeuronModels::Izhikevich)
- IMPLEMENT_MODEL (NeuronModels::IzhikevichVariable)
- IMPLEMENT_MODEL (NeuronModels::LIF)
- IMPLEMENT MODEL (NeuronModels::SpikeSource)
- IMPLEMENT_MODEL (NeuronModels::SpikeSourceArray)
- IMPLEMENT_MODEL (NeuronModels::Poisson)
- IMPLEMENT_MODEL (NeuronModels::PoissonNew)
- IMPLEMENT_MODEL (NeuronModels::TraubMiles)
- IMPLEMENT_MODEL (NeuronModels::TraubMilesFast)
- IMPLEMENT_MODEL (NeuronModels::TraubMilesAlt)
- IMPLEMENT MODEL (NeuronModels::TraubMilesNStep)

20.83.1 Function Documentation

```
20.83.1.4 IMPLEMENT_MODEL() [4/12]
IMPLEMENT_MODEL (
            NeuronModels::LIF )
20.83.1.5 IMPLEMENT_MODEL() [5/12]
IMPLEMENT_MODEL (
            NeuronModels::SpikeSource )
20.83.1.6 IMPLEMENT_MODEL() [6/12]
IMPLEMENT_MODEL (
            NeuronModels::SpikeSourceArray )
20.83.1.7 IMPLEMENT_MODEL() [7/12]
IMPLEMENT_MODEL (
            NeuronModels::Poisson )
20.83.1.8 IMPLEMENT_MODEL() [8/12]
IMPLEMENT_MODEL (
            NeuronModels::PoissonNew )
20.83.1.9 IMPLEMENT_MODEL() [9/12]
IMPLEMENT_MODEL (
            NeuronModels::TraubMiles )
20.83.1.10 IMPLEMENT_MODEL() [10/12]
IMPLEMENT_MODEL (
            NeuronModels::TraubMilesFast )
20.83.1.11 IMPLEMENT_MODEL() [11/12]
IMPLEMENT_MODEL (
            NeuronModels::TraubMilesAlt )
20.83.1.12 IMPLEMENT_MODEL() [12/12]
IMPLEMENT_MODEL (
            NeuronModels::TraubMilesNStep )
20.84 neuronModels.h File Reference
```

Generated on November 5, 2019 for GeNN by Doxygen

#include <array>

```
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "models.h"
```

Classes

· class NeuronModels::Base

Base class for all neuron models.

class NeuronModels::RulkovMap

Rulkov Map neuron.

· class NeuronModels::Izhikevich

Izhikevich neuron with fixed parameters [1].

· class NeuronModels::IzhikevichVariable

Izhikevich neuron with variable parameters [1].

- · class NeuronModels::LIF
- class NeuronModels::SpikeSource

Empty neuron which allows setting spikes from external sources.

class NeuronModels::SpikeSourceArray

Spike source array.

• class NeuronModels::Poisson

Poisson neurons.

· class NeuronModels::PoissonNew

Poisson neurons.

class NeuronModels::TraubMiles

Hodgkin-Huxley neurons with Traub & Miles algorithm.

• class NeuronModels::TraubMilesFast

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

· class NeuronModels::TraubMilesAlt

Hodgkin-Huxley neurons with Traub & Miles algorithm.

· class NeuronModels::TraubMilesNStep

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Namespaces

NeuronModels

Macros

- #define SET_SIM_CODE(SIM_CODE) virtual std::string getSimCode() const override{ return SIM_CODE; }
- #define SET_THRESHOLD_CONDITION_CODE(THRESHOLD_CONDITION_CODE) virtual std::string getThresholdConditionCode() const override{ return THRESHOLD_CONDITION_CODE; }
- #define SET_RESET_CODE(RESET_CODE) virtual std::string getResetCode() const override{ return RE
 SET_CODE; }
- #define SET_SUPPORT_CODE(SUPPORT_CODE) virtual std::string getSupportCode() const override{ return SUPPORT_CODE;}
- #define SET_ADDITIONAL_INPUT_VARS(...) virtual ParamValVec getAdditionalInputVars() const override{
 return VA ARGS ;}
- #define SET_NEEDS_AUTO_REFRACTORY(AUTO_REFRACTORY_REQUIRED) virtual bool isAuto ← RefractoryRequired() const override{ return AUTO_REFRACTORY_REQUIRED; }

20.84.1 Macro Definition Documentation

```
20.84.1.1 SET_ADDITIONAL_INPUT_VARS
#define SET_ADDITIONAL_INPUT_VARS(
             ... ) virtual ParamValVec getAdditionalInputVars() const override{ return __VA↔
_ARGS__; }
20.84.1.2 SET_NEEDS_AUTO_REFRACTORY
#define SET_NEEDS_AUTO_REFRACTORY(
             AUTO_REFRACTORY_REQUIRED ) virtual bool isAutoRefractoryRequired() const override{
return AUTO_REFRACTORY_REQUIRED; }
20.84.1.3 SET_RESET_CODE
#define SET_RESET_CODE(
             RESET_CODE ) virtual std::string getResetCode() const override{ return RESET_CO↔
DE; }
20.84.1.4 SET_SIM_CODE
#define SET_SIM_CODE(
             SIM_CODE ) virtual std::string getSimCode() const override{ return SIM_CODE; }
20.84.1.5 SET_SUPPORT_CODE
#define SET_SUPPORT_CODE(
             SUPPORT\_CODE ) virtual std::string getSupportCode() const override{ return SUPP} \leftarrow
ORT_CODE; }
20.84.1.6 SET_THRESHOLD_CONDITION_CODE
#define SET_THRESHOLD_CONDITION_CODE(
             THRESHOLD_CONDITION_CODE ) virtual std::string getThresholdConditionCode() const
override{ return THRESHOLD_CONDITION_CODE; }
20.85 optimiser.cc File Reference
#include "optimiser.h"
#include <algorithm>
#include <iostream>
#include <map>
#include <numeric>
#include <cstdlib>
#include <cuda.h>
#include <cuda_runtime.h>
#include <plog/Log.h>
#include "path.h"
#include "modelSpecInternal.h"
```

```
#include "code_generator/generateAll.h"
#include "utils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- CodeGenerator::CUDA::Optimiser

Functions

• BACKEND_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

20.86 optimiser.cc File Reference

```
#include "optimiser.h"
#include "modelSpecInternal.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::SingleThreadedCPU
- CodeGenerator::SingleThreadedCPU::Optimiser

Functions

• BACKEND_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

20.87 optimiser.h File Reference

```
#include "backendExport.h"
#include "backend.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- · CodeGenerator::CUDA::Optimiser

Functions

• BACKEND_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

20.88 optimiser.h File Reference

```
#include "backendExport.h"
#include "backend.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::SingleThreadedCPU
- · CodeGenerator::SingleThreadedCPU::Optimiser

Functions

 BACKEND_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

20.89 postsynapticModels.cc File Reference

```
#include "postsynapticModels.h"
```

Functions

- IMPLEMENT_MODEL (PostsynapticModels::ExpCurr)
- IMPLEMENT_MODEL (PostsynapticModels::ExpCond)
- IMPLEMENT_MODEL (PostsynapticModels::DeltaCurr)

20.89.1 Function Documentation

20.90 postsynapticModels.h File Reference

```
#include <cmath>
#include "models.h"
```

Classes

· class PostsynapticModels::Base

Base class for all postsynaptic models.

· class PostsynapticModels::ExpCurr

Exponential decay with synaptic input treated as a current value.

· class PostsynapticModels::ExpCond

Exponential decay with synaptic input treated as a conductance value.

· class PostsynapticModels::DeltaCurr

Simple delta current synapse.

Namespaces

· PostsynapticModels

Macros

- #define SET_DECAY_CODE(DECAY_CODE) virtual std::string getDecayCode() const override{ return DE
 CAY_CODE; }
- #define SET_CURRENT_CONVERTER_CODE(CURRENT_CONVERTER_CODE) virtual std::string get
 ApplyInputCode() const override{ return "\$(Isyn) += " CURRENT_CONVERTER_CODE ";"; }
- #define SET_APPLY_INPUT_CODE(APPLY_INPUT_CODE) virtual std::string getApplyInputCode() const override{ return APPLY_INPUT_CODE; }
- #define SET_SUPPORT_CODE(SUPPORT_CODE) virtual std::string getSupportCode() const override{ return SUPPORT_CODE; }

20.90.1 Macro Definition Documentation

20.90.1.1 SET_APPLY_INPUT_CODE

20.90.1.2 SET_CURRENT_CONVERTER_CODE

20.90.1.3 SET_DECAY_CODE

```
#define SET_DECAY_CODE (  \textit{DECAY\_CODE} \text{ } ) \text{ } \text{virtual std::string getDecayCode() const override \{ \text{ return DECAY\_CO} \leftarrow \text{DE; } \}
```

20.90.1.4 SET_SUPPORT_CODE

20.91 presynapticUpdateStrategy.cc File Reference

```
#include "presynapticUpdateStrategy.h"
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "backend.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- · CodeGenerator::CUDA::PresynapticUpdateStrategy

20.92 presynapticUpdateStrategy.h File Reference

```
#include "code_generator/backendBase.h"
```

Classes

- class CodeGenerator::CUDA::PresynapticUpdateStrategy::Base
- class CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan

Presynaptic parallelism.

• class CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan

Postsynaptic parallelism.

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- · CodeGenerator::CUDA::PresynapticUpdateStrategy

20.93 sharedLibraryModel.h File Reference

```
#include <algorithm>
#include <array>
#include <iostream>
#include <string>
#include <vector>
#include <utility>
#include <utility>
#include <bitset>
#include <dlfcn.h>
```

Classes

class SharedLibraryModel< scalar >

20.94 simulator.cc File Reference

```
#include "simulator.h"
#include <functional>
#include <iostream>
#include <map>
#include <memory>
#include <random>
#include <set>
#include <string>
#include <cassert>
#include <cmath>
#include <cstdlib>
#include <dlfcn.h>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "spineMLUtils.h"
#include "connectors.h"
#include "input.h"
#include "inputValue.h"
#include "logOutput.h"
#include "modelProperty.h"
#include "stateVar.h"
#include "timer.h"
```

Namespaces

SpineMLSimulator

20.95 simulator.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <tuple>
```

```
#include "input.h"
#include "inputValue.h"
#include "logOutput.h"
#include "modelProperty.h"
```

Classes

· class SpineMLSimulator::Simulator

Namespaces

SpineMLSimulator

20.96 snippet.h File Reference

```
#include <algorithm>
#include <functional>
#include <string>
#include <vector>
#include <cassert>
#include "gennExport.h"
```

Classes

- class Snippet::ValueBase< NumVars >
- class Snippet::ValueBase< 0 >
- · class Snippet::Base

Base class for all code snippets.

struct Snippet::Base::EGP

An extra global parameter has a name and a type.

struct Snippet::Base::ParamVal

Additional input variables, row state variables and other things have a name, a type and an initial value.

• struct Snippet::Base::DerivedParam

A derived parameter has a name and a function for obtaining its value.

class Snippet::Init< SnippetBase >

Namespaces

Snippet

Macros

- #define DECLARE_SNIPPET(TYPE, NUM_PARAMS)
- #define IMPLEMENT_SNIPPET(TYPE) TYPE *TYPE::s_Instance = NULL
- #define SET_PARAM_NAMES(...) virtual StringVec getParamNames() const override{ return __VA_ARGS
 __;}
- #define SET_DERIVED_PARAMS(...) virtual DerivedParamVec getDerivedParams() const override{ return __VA_ARGS__;}

20.96.1 Macro Definition Documentation

```
20.96.1.1 DECLARE_SNIPPET
```

Value:

```
private:
    GENN_EXPORT static TYPE *s_Instance;
public:
    static const TYPE *getInstance()
    {
        if(s_Instance == NULL)
        {
            s_Instance = new TYPE;
        }
        return s_Instance;
    }
    typedef Snippet::ValueBase<NUM_PARAMS> ParamValues
```

20.96.1.2 IMPLEMENT_SNIPPET

20.96.1.3 SET_DERIVED_PARAMS

```
 \begin{tabular}{ll} \#define SET\_DERIVED\_PARAMS ( & ... ) virtual DerivedParamVec getDerivedParams () const override { return $\_$VA\_A$$$$ $$ RGS$$\_; }
```

20.96.1.4 SET_PARAM_NAMES

20.97 spikeRecorder.h File Reference

```
#include <algorithm>
#include <fstream>
#include <iterator>
#include <list>
#include <tuple>
#include <vector>
```

Classes

class SpikeWriterText

Class to write spikes to text file.

class SpikeWriterTextCached

Class to write spikes to text file, caching in memory before writing.

class SpikeRecorder
 Writer >

Class to read spikes from neuron groups.

20.98 stateVar.h File Reference

```
#include <functional>
#include <plog/Log.h>
```

Classes

class SpineMLSimulator::StateVar< T >

Namespaces

SpineMLSimulator

20.99 substitutions.h File Reference

```
#include <map>
#include <stdexcept>
#include <string>
#include <plog/Log.h>
#include <cassert>
#include "codeGenUtils.h"
```

Classes

• class CodeGenerator::Substitutions

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.100 synapseGroup.cc File Reference

```
#include "synapseGroup.h"
#include <algorithm>
#include <cmath>
#include <iostream>
#include "neuronGroupInternal.h"
#include "gennUtils.h"
```

20.101 synapseGroup.h File Reference

```
#include <map>
#include <set>
```

```
#include <string>
#include vector>
#include "gennExport.h"
#include "initSparseConnectivitySnippet.h"
#include "postsynapticModels.h"
#include "weightUpdateModels.h"
#include "synapseMatrixType.h"
#include "variableMode.h"
```

Classes

· class SynapseGroup

20.102 synapseGroupInternal.h File Reference

```
#include "synapseGroup.h"
```

Classes

· class SynapseGroupInternal

20.103 synapseMatrixType.h File Reference

Enumerations

- enum SynapseMatrixConnectivity:: unsigned int { SynapseMatrixConnectivity::DENSE = (1 << 0), SynapseMatrixConnectivity::BITMASK = (1 << 1), SynapseMatrixConnectivity::SPARSE = (1 << 2)}
 - < Flags defining differnet types of synaptic matrix connectivity
- enum SynapseMatrixWeight:: unsigned int { SynapseMatrixWeight::GLOBAL = (1 << 5), SynapseMatrix
 Weight::INDIVIDUAL = (1 << 6), SynapseMatrixWeight::INDIVIDUAL_PSM = (1 << 7) }
- enum SynapseMatrixType::unsigned int {
 SynapseMatrixType::DENSE_GLOBALG = static_cast<unsigned int>(SynapseMatrixType::DENSE_GL
 NSE) | static_cast<unsigned int>(SynapseMatrixWeight::GLOBAL), SynapseMatrixType::DENSE_GL
 OBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(SynapseMatrixConnectivity::DENSE) | static_cast<unsigned int>(SynapseMatrixWeight::GLOBAL) | static_cast<unsigned int>(SynapseMatrixWeight::INDIVIDUAL_PSM), SynapseMatrixType::DENSE_INDIVIDUALG = static_cast<unsigned int>(Synapse
 MatrixConnectivity::DENSE) | static_cast<unsigned int>(SynapseMatrixWeight::INDIVIDUAL) | static
 _cast<unsigned int>(SynapseMatrixWeight::INDIVIDUAL_PSM), SynapseMatrixType::BITMASK_GL
 OBALG = static_cast<unsigned int>(SynapseMatrixConnectivity::BITMASK) | static_cast<unsigned int>(SynapseMatrixType::BITMASK_GLOBAL),
 SynapseMatrixType::BITMASK_GLOBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(Synapse

MatrixConnectivity::BITMASK_GLOBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(Synapse MatrixConnectivity::BITMASK) | static_cast<unsigned int>(SynapseMatrixWeight::INDIVIDUAL_PSM), SynapseMatrixType::SPARSE_GL OBALG = static_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE) | static_cast<unsigned int>(SynapseMatrixType::SPARSE_GLOBALG_INDIVIDUAL_PSM) = static_cast<unsigned int>(SynapseMatrixType::SPARSE) | static_cast<unsigned int>(Synapse MatrixWeight::GLOBAL) | static_cast<unsigned int>(Synapse MatrixWeight::INDIVIDUAL_PSM), Synapse MatrixType::SPARSE_INDIVIDUALG = static_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE) | static_cast<unsigned int>(Synapse MatrixType::SPARSE_INDIVIDUALG = static_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE) | static_cast<un

Functions

- bool operator& (SynapseMatrixType type, SynapseMatrixConnectivity connType)
- bool operator& (SynapseMatrixType type, SynapseMatrixWeight weightType)
- SynapseMatrixType operator (SynapseMatrixWeight weightType, SynapseMatrixConnectivity connType)

20.103.1 Enumeration Type Documentation

20.103.1.1 SynapseMatrixConnectivity

```
enum SynapseMatrixConnectivity : unsigned int [strong]
```

< Flags defining differnet types of synaptic matrix connectivity

Enumerator

DENSE	
BITMASK	
SPARSE	

20.103.1.2 SynapseMatrixType

```
enum SynapseMatrixType : unsigned int [strong]
```

Enumerator

DENSE_GLOBALG	
DENSE_GLOBALG_INDIVIDUAL_PSM	
DENSE_INDIVIDUALG	
BITMASK_GLOBALG	
BITMASK_GLOBALG_INDIVIDUAL_PSM	
SPARSE_GLOBALG	
SPARSE_GLOBALG_INDIVIDUAL_PSM	
SPARSE_INDIVIDUALG	

20.103.1.3 SynapseMatrixWeight

```
enum SynapseMatrixWeight : unsigned int [strong]
```

Enumerator

GLOBAL	
INDIVIDUAL	
INDIVIDUAL_PSM	

20.103.2 Function Documentation

```
20.103.2.1 operator&() [1/2]
bool operator & (
             SynapseMatrixType type,
             SynapseMatrixConnectivity connType ) [inline]
20.103.2.2 operator&() [2/2]
bool operator & (
             SynapseMatrixType type,
             SynapseMatrixWeight weightType ) [inline]
20.103.2.3 operator " | ()
SynapseMatrixType operator| (
             SynapseMatrixWeight weightType,
             SynapseMatrixConnectivity connType ) [inline]
20.104 teeStream.h File Reference
#include <ostream>
#include <streambuf>
#include <vector>
```

Classes

- · class CodeGenerator::TeeBuf
- class CodeGenerator::TeeStream

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.105 timer.h File Reference

```
#include <chrono>
#include <iostream>
#include <string>
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
```

Classes

- class SpineMLSimulator::Timer
- · class SpineMLSimulator::TimerAccumulate

Namespaces

SpineMLSimulator

20.106 timer.h File Reference

```
#include <chrono>
#include <fstream>
#include <iostream>
#include <string>
```

Classes

class Timer

A generic timer which can give the current elapsed time.

· class TimerAccumulate

A timer which adds its elapsed time to an accumulator variable on destruction.

20.107 utils.h File Reference

```
#include <iostream>
#include <plog/Log.h>
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- CodeGenerator::CUDA::Utils

Macros

- #define CHECK_CU_ERRORS(call) call
- #define CHECK_CUDA_ERRORS(call)

Functions

- size_t CodeGenerator::CUDA::Utils::ceilDivide (size_t numerator, size_t denominator)
- size_t CodeGenerator::CUDA::Utils::padSize (size_t size, size_t blockSize)

20.107.1 Macro Definition Documentation

20.107.1.1 CHECK_CU_ERRORS

```
\begin{tabular}{ll} \# define CHECK\_CU\_ERRORS ( \\ & call \end{tabular}
```

20.107.1.2 CHECK_CUDA_ERRORS

20.108 variableMode.h File Reference

```
#include <cstdint>
```

Enumerations

```
    enum VarLocation: uint8_t {
        VarLocation::HOST = (1 << 0), VarLocation::DEVICE = (1 << 1), VarLocation::ZERO_COPY = (1 << 2),
        VarLocation::HOST_DEVICE = HOST | DEVICE,
        VarLocation::HOST_DEVICE_ZERO_COPY = HOST | DEVICE | ZERO_COPY }
        < Flags defining which memory space variables should be allocated in</li>
```

Functions

bool operator& (VarLocation locA, VarLocation locB)

20.108.1 Enumeration Type Documentation

20.108.1.1 VarLocation

```
enum VarLocation : uint8_t [strong]
```

< Flags defining which memory space variables should be allocated in

Enumerator

HOST	
DEVICE	
ZERO_COPY	
HOST_DEVICE	
HOST_DEVICE_ZERO_COPY	

20.108.2 Function Documentation

20.109 weightUpdateModels.cc File Reference

```
#include "weightUpdateModels.h"
```

Functions

- IMPLEMENT_MODEL (WeightUpdateModels::StaticPulse)
- IMPLEMENT_MODEL (WeightUpdateModels::StaticPulseDendriticDelay)
- IMPLEMENT_MODEL (WeightUpdateModels::StaticGraded)
- IMPLEMENT_MODEL (WeightUpdateModels::PiecewiseSTDP)

20.109.1 Function Documentation

20.110 weightUpdateModels.h File Reference

```
#include "models.h"
```

Classes

class WeightUpdateModels::Base

Base class for all weight update models.

class WeightUpdateModels::StaticPulse

Pulse-coupled, static synapse.

· class WeightUpdateModels::StaticPulseDendriticDelay

Pulse-coupled, static synapse with heterogenous dendritic delays.

class WeightUpdateModels::StaticGraded

Graded-potential, static synapse.

class WeightUpdateModels::PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

Namespaces

· WeightUpdateModels

Macros

- #define DECLARE_WEIGHT_UPDATE_MODEL(TYPE, NUM_PARAMS, NUM_VARS, NUM_PRE_VARS, NUM_POST_VARS)
- #define SET_SIM_CODE(SIM_CODE) virtual std::string getSimCode() const override{ return SIM_CODE; }
- #define SET_EVENT_CODE(EVENT_CODE) virtual std::string getEventCode() const override{ return EV
 ENT_CODE; }
- #define SET_LEARN_POST_CODE(LEARN_POST_CODE) virtual std::string getLearnPostCode() const override{ return LEARN_POST_CODE; }
- #define SET_SYNAPSE_DYNAMICS_CODE(SYNAPSE_DYNAMICS_CODE) virtual std::string get
 SynapseDynamicsCode() const override{ return SYNAPSE_DYNAMICS_CODE; }
- #define SET_EVENT_THRESHOLD_CONDITION_CODE(EVENT_THRESHOLD_CONDITION_CODE) virtual std::string getEventThresholdConditionCode() const override{ return EVENT_THRESHOLD_CONDITI
 ON CODE;}
- #define SET_SIM_SUPPORT_CODE(SIM_SUPPORT_CODE) virtual std::string getSimSupportCode() const override{ return SIM_SUPPORT_CODE; }
- #define SET_LEARN_POST_SUPPORT_CODE(LEARN_POST_SUPPORT_CODE) virtual std::string get
 LearnPostSupportCode() const override{ return LEARN_POST_SUPPORT_CODE; }
- #define SET_SYNAPSE_DYNAMICS_SUPPORT_CODE(SYNAPSE_DYNAMICS_SUPPORT_CODE) virtual std::string getSynapseDynamicsSuppportCode() const override{ return SYNAPSE_DYNAMICS_SUPPORT_CODE;}
- #define SET_PRE_SPIKE_CODE(PRE_SPIKE_CODE) virtual std::string getPreSpikeCode() const override{
 return PRE_SPIKE_CODE; }
- #define SET_POST_SPIKE_CODE(POST_SPIKE_CODE) virtual std::string getPostSpikeCode() const override{ return POST_SPIKE_CODE; }
- #define SET_PRE_VARS(...) virtual VarVec getPreVars() const override{ return __VA_ARGS__;}
- #define SET_POST_VARS(...) virtual VarVec getPostVars() const override{ return __VA_ARGS__; }
- #define SET_NEEDS_PRE_SPIKE_TIME(PRE_SPIKE_TIME_REQUIRED) virtual bool isPreSpikeTime
 Required() const override{ return PRE_SPIKE_TIME_REQUIRED; }

20.110.1 Macro Definition Documentation

```
20.110.1.1 DECLARE_WEIGHT_UPDATE_MODEL
```

```
#define DECLARE_WEIGHT_UPDATE_MODEL(
              TYPE,
              NUM_PARAMS,
              NUM_VARS,
              NUM_PRE_VARS,
              NUM POST VARS )
Value:
DECLARE_SNIPPET(TYPE, NUM_PARAMS);
   typedef Models::VarInitContainerBase<NUM_VARS> VarValues;
   typedef Models::VarInitContainerBase<NUM_PRE_VARS>
     PreVarValues;
   typedef Models::VarInitContainerBase<NUM_POST_VARS>
     PostVarValues
20.110.1.2 SET_EVENT_CODE
#define SET_EVENT_CODE(
              EVENT_CODE ) virtual std::string getEventCode() const override{ return EVENT_CO↔
DE; }
20.110.1.3 SET_EVENT_THRESHOLD_CONDITION_CODE
#define SET_EVENT_THRESHOLD_CONDITION_CODE(
             EVENT_THRESHOLD_CONDITION_CODE ) virtual std::string getEventThresholdCondition↔
Code() const override{ return EVENT_THRESHOLD_CONDITION_CODE; }
20.110.1.4 SET_LEARN_POST_CODE
#define SET_LEARN_POST_CODE(
              LEARN_POST_CODE ) virtual std::string getLearnPostCode() const override{ return
LEARN_POST_CODE; }
20.110.1.5 SET_LEARN_POST_SUPPORT_CODE
#define SET_LEARN_POST_SUPPORT_CODE(
             LEARN_POST_SUPPORT_CODE ) virtual std::string getLearnPostSupportCode() const
override{ return LEARN_POST_SUPPORT_CODE; }
20.110.1.6 SET_NEEDS_POST_SPIKE_TIME
#define SET_NEEDS_POST_SPIKE_TIME(
             POST_SPIKE_TIME_REQUIRED ) virtual bool isPostSpikeTimeRequired() const override{
return POST_SPIKE_TIME_REQUIRED; }
20.110.1.7 SET_NEEDS_PRE_SPIKE_TIME
```

PRE_SPIKE_TIME_REQUIRED) virtual bool isPreSpikeTimeRequired() const override{

#define SET_NEEDS_PRE_SPIKE_TIME(

```
return PRE_SPIKE_TIME_REQUIRED; }
20.110.1.8 SET_POST_SPIKE_CODE
#define SET_POST_SPIKE_CODE(
             POST_SPIKE_CODE ) virtual std::string getPostSpikeCode() const override{ return
POST_SPIKE_CODE; }
20.110.1.9 SET_POST_VARS
#define SET_POST_VARS(
              ... ) virtual VarVec getPostVars() const override{ return __VA_ARGS__; }
20.110.1.10 SET_PRE_SPIKE_CODE
#define SET_PRE_SPIKE_CODE(
             PRE\_SPIKE\_CODE ) virtual std::string getPreSpikeCode() const override{ return P} \leftarrow
RE_SPIKE_CODE; }
20.110.1.11 SET_PRE_VARS
#define SET_PRE_VARS(
              ... ) virtual VarVec getPreVars() const override{ return __VA_ARGS__; }
20.110.1.12 SET_SIM_CODE
#define SET_SIM_CODE(
             SIM_CODE ) virtual std::string getSimCode() const override{ return SIM_CODE; }
20.110.1.13 SET_SIM_SUPPORT_CODE
#define SET_SIM_SUPPORT_CODE(
             SIM_SUPPORT_CODE ) virtual std::string getSimSupportCode() const override{ return
SIM_SUPPORT_CODE; }
20.110.1.14 SET_SYNAPSE_DYNAMICS_CODE
#define SET_SYNAPSE_DYNAMICS_CODE(
              SYNAPSE_DYNAMICS_CODE ) virtual std::string getSynapseDynamicsCode() const override{
return SYNAPSE_DYNAMICS_CODE; }
20.110.1.15 SET_SYNAPSE_DYNAMICS_SUPPORT_CODE
#define SET_SYNAPSE_DYNAMICS_SUPPORT_CODE(
             SYNAPSE\_DYNAMICS\_SUPPORT\_CODE ) virtual std::string getSynapseDynamicsSuppport\leftrightarrow
Code() const override{ return SYNAPSE_DYNAMICS_SUPPORT_CODE; }
```

REFERENCES 409

References

[1] Eugene M Izhikevich. Simple model of spiking neurons. *IEEE Transactions on neural networks*, 14(6):1569–1572, 2003. 7, 8, 9, 63, 80, 81, 215, 216, 218, 390

- [2] Abigail Morrison, Markus Diesmann, and Wulfram Gerstner. Phenomenological models of synaptic plasticity based on spike timing. *Biological Cybernetics*, 98:459–478, 2008. 33
- [3] T. Nowotny. Parallel implementation of a spiking neuronal network model of unsupervised olfactory learning on NVidia CUDA. In P. Sobrevilla, editor, *IEEE World Congress on Computational Intelligence*, pages 3238–3245, Barcelona, 2010. IEEE. 33
- [4] Thomas Nowotny, Ramón Huerta, Henry DI Abarbanel, and Mikhail I Rabinovich. Self-organization in the olfactory system: one shot odor recognition in insects. *Biological cybernetics*, 93(6):436–446, 2005. 11, 276
- [5] Nikolai F Rulkov. Modeling of spiking-bursting neural behavior using two-dimensional map. *Physical Review E*, 65(4):041922, 2002. 276
- [6] Marcel Stimberg, Dan F. M. Goodman, and Thomas Nowotny. Brian2genn: a system for accelerating a large variety of spiking neural networks with graphics hardware. *bioRxiv*, 2018. 14
- [7] R. D. Traub and R. Miles. Neural Networks of the Hippocampus. Cambridge University Press, New York, 1991.11, 12, 335

Index

init	pygenn::genn_groups::CurrentSource, 169
pygenn::genn_groups::CurrentSource, 169	pygenn::genn_groups::NeuronGroup, 240
pygenn::genn_groups::Group, 211	pygenn::genn_groups::SynapseGroup, 308
pygenn::genn_groups::NeuronGroup, 240	add_neuron_population
pygenn::genn_groups::SynapseGroup, 307	pygenn::genn_model::GeNNModel, 204
pygenn::genn_model::GeNNModel, 203	add_synapse_population
pygenn::model_preprocessor::ExtraGlobal←	pygenn::genn_model::GeNNModel, 204
Variable, 190	add_to
pygenn::model_preprocessor::Variable, 350	pygenn::genn_groups::CurrentSource, 170
initpy, 355	pygenn::genn_groups::NeuronGroup, 241
\sim BackendBase	pygenn::genn_groups::SynapseGroup, 308
CodeGenerator::BackendBase, 132	addCurrentSource
\sim Base	ModelSpec, 227, 228
Snippet::Base, 151	addFuncSubstitution
SpineMLSimulator::Input::Base, 158	CodeGenerator::Substitutions, 304
SpineMLSimulator::InputValue::Base, 160	addlnSyn
SpineMLSimulator::LogOutput::Base, 161	NeuronGroup, 245
SpineMLSimulator::ModelProperty::Base, 162	addNeuronPopulation
\sim ModelSpec	ModelSpec, 228, 229
ModelSpec, 227	addOutSyn
~NetworkClient	NeuronGroup, 246
SpineMLSimulator::NetworkClient, 239	addParamNameSubstitution
~Scope	CodeGenerator::Substitutions, 304
CodeGenerator::CodeStream::Scope, 279	addParamValueSubstitution
~SharedLibraryModel	CodeGenerator::Substitutions, 304
SharedLibraryModel, 280	addPresynapticUpdateStrategy
~Simulator	CodeGenerator::CUDA::Backend, 107
SpineMLSimulator::Simulator, 284	addSpkEventCondition
~SpikeWriterTextCached	NeuronGroup, 246
SpikeWriterTextCached, 296	addSynapsePopulation
~Timer	ModelSpec, 230–232
SpineMLSimulator::Timer, 330	addType
Timer, 330	CodeGenerator::BackendBase, 132
~TimerAccumulate	addVarNameSubstitution
SpineMLSimulator::TimerAccumulate, 332	CodeGenerator::Substitutions, 304
TimerAccumulate, 331	addVarSubstitution
00_MainPage.dox, 354	CodeGenerator::Substitutions, 305
01_Installation.dox, 355	addVarValueSubstitution
02_Quickstart.dox, 355	CodeGenerator::Substitutions, 305
03 Examples.dox, 355	allocateExtraGlobalParam
05_SpineML.dox, 355	SharedLibraryModel, 280
06_Brian2GeNN.dox, 355	allocateMem
07_PyGeNN.dox, 355	SharedLibraryModel, 280
09_ReleaseNotes.dox, 355	Analogue
10_UserManual.dox, 355	SpineMLSimulator::Input::Analogue, 98
11 Tutorial.dox, 355	AnalogueBase
12 Tutorial.dox, 355	SpineMLSimulator::LogOutput::AnalogueBase, 99
13_UserGuide.dox, 355	AnalogueExternal
14 Credits.dox, 355	•
14_Orealis.dox, 333	SpineMLSimulator::LogOutput::AnalogueExternal
000000	100
access Madala::Paga::Var. 240	AnalogueFile
Models::Base::Var, 349	SpineMLSimulator::LogOutput::AnalogueFile, 102
add_current_source	AnalogueNetwork
pygenn::genn_model::GeNNModel, 203	SpineMLSimulator::LogOutput::AnalogueNetwork
add_extra_global_param	103

AnalogueRecorder	CalcMaxLengthFunc
AnalogueRecorder, 103, 104	InitSparseConnectivitySnippet::Base, 144
record, 104	calcNumTimesteps
AnalogueRecorder< T >, 103	SpineMLSimulator::Simulator, 285
analogueRecorder.h, 355	CB
apply	CodeGenerator::CodeStream::CB, 163
CodeGenerator::Substitutions, 305	ceilDivide
SpineMLSimulator::Input::Analogue, 98	CodeGenerator::CUDA::Utils, 78
SpineMLSimulator::Input::Base, 159	checkNumDelaySlots
SpineMLSimulator::Input::InterSpikeIntervalBase,	NeuronGroup, 246
215	checkUnreplacedVariables
SpineMLSimulator::Input::SpikeTime, 294	CodeGenerator, 71
applyCheckUnreplaced	codeGenUtils.cc, 359
CodeGenerator::Substitutions, 305	MathsFunc, 360
applyScalar	codeGenUtils.h, 360
SpineMLSimulator::InputValue::ScalarBase, 278	CodeGenerator, 69
BACKEND EXPORT	checkUnreplacedVariables, 71
backendExport.h, 358	ensureFtype, 71
Backend	functionSubstitute, 71
CodeGenerator::CUDA::Backend, 106	generateAll, 71
CodeGenerator::SingleThreadedCPU::Backend,	generateInit, 72
119	generateMPI, 72
backend.cc, 355, 356	generateMSBuild, 72
backend.h, 356, 357	generateMakefile, 72
backend_modules	generateNeuronUpdate, 72
pygenn::genn_model, 89	generateRunner, 72
BackendBase	generateSupportCode, 73
CodeGenerator::BackendBase, 132	generateSynapseUpdate, 73
backendBase.cc, 357	neuronSubstitutionsInSynapticCode, 73
TYPE, 358	operator<<, 74
backendBase.h, 358	postNeuronSubstitutionsInSynapticCode, 74
backendExport.h, 358	preNeuronSubstitutionsInSynapticCode, 74
BACKEND_EXPORT, 358	regexFuncSubstitute, 75
Base	regexVarSubstitute, 75
SpineMLSimulator::Input::Base, 158	substitute, 75
SpineMLSimulator::InputValue::Base, 160	writePreciseString, 75
SpineMLSimulator::LogOutput::Base, 161	CodeGenerator::BackendBase, 129
SpineMLSimulator::ModelProperty::Base, 162	\sim BackendBase, 132
binomial.cc, 358	addType, 132
binomialInverseCDF, 359	BackendBase, 132
binomial.h, 359	genAllocateMemPreamble, 132
binomialInverseCDF, 359	genArray, 133
binomialInverseCDF	genCurrentSpikeLikeEventPull, 133
binomial.cc, 359	genCurrentSpikeLikeEventPush, 133
binomial.h, 359	genCurrentTrueSpikePull, 133
BlockSizeSelect	genCurrentTrueSpikePush, 133
CodeGenerator::CUDA, 76	genCurrentVariablePull, 133
blockSizeSelectMethod	genCurrentVariablePush, 134
CodeGenerator::CUDA::Preferences, 270	genCurrentVariablePushPull, 134
build	genDefinitionsInternalPreamble, 134
pygenn::genn_model::GeNNModel, 205	genDefinitionsPreamble, 134
buildAndRun	genExtraGlobalParamAllocation, 135
GenerateRunBase, 200	genExtraGlobalParamDefinition, 135
OUEOK OU EDDOES	genExtraGlobalParamImplementation, 135
CHECK_CU_ERRORS	genExtraGlobalParamPull, 135
utils.h, 403	genExtraGlobalParamPush, 135
CHECK_CUDA_ERRORS	genGlobalRNG, 135
utils.h, 403	genInit, 136

genMSBuildCompileModule, 136	genMSBuildImportProps, 111
genMSBuildConfigProperties, 137	genMSBuildImportTarget, 111
genMSBuildImportProps, 137	genMSBuildItemDefinitions, 111
genMSBuildImportTarget, 137	genMakefileCompileRule, 110
genMSBuildItemDefinitions, 137	genMakefileLinkRule, 110
genMakefileCompileRule, 136	genMakefilePreamble, 110
genMakefileLinkRule, 136	genNeuronUpdate, 111
genMakefilePreamble, 136	genPopVariableInit, 112
genNeuronUpdate, 137	genPopulationRNG, 112
genPopVariableInit, 138	genRunnerPreamble, 112
genPopulationRNG, 138	genStepTimeFinalisePreamble, 112
genRunnerPreamble, 138	genSynapseUpdate, 112
genScalar, 138	genSynapseVariableRowInit, 113
genStepTimeFinalisePreamble, 138	genTimer, 113
genSynapseUpdate, 139	genVariableAllocation, 113
genSynapseVariableRowInit, 139	genVariableDefinition, 114
genTimer, 139	genVariableFree, 114
genVariableAllocation, 140	genVariableImplementation, 114
genVariableDefinition, 140	genVariableInit, 114
genVariableFree, 140	genVariablePull, 114
genVariableImplementation, 140	genVariablePush, 115
genVariableInit, 140	getChosenCUDADevice, 115
genVariablePull, 141	getChosenDeviceID, 115
genVariablePush, 141	getDeviceMemoryBytes, 115
genVariablePushPull, 141	getFloatAtomicAdd, 115
getDeviceMemoryBytes, 141	_
- · · · · · · · · · · · · · · · · · · ·	getKernelBlockSize, 115
getLocalHostID, 142	getNVCCFlags, 116
getSize, 142	getNumPostsynapticUpdateThreads, 115
getVarPrefix, 142	getNumPresynapticUpdateThreads, 116
GroupHandler, 131	getNumSynapseDynamicsThreads, 116
Handler, 131	getRuntimeVersion, 116
isGlobalRNGRequired, 142	getVarPrefix, 116
isPostsynapticRemapRequired, 142	isGlobalRNGRequired, 116
isSynRemapRequired, 142	isPostsynapticRemapRequired, 116
NeuronGroupHandler, 131	isSynRemapRequired, 116
NeuronGroupSimHandler, 132	KernelNames, 117
SynapseGroupHandler, 132	CodeGenerator::CUDA::Optimiser, 77
CodeGenerator::CUDA::Backend, 104	createBackend, 77
addPresynapticUpdateStrategy, 107	CodeGenerator::CUDA::Preferences, 269
Backend, 106	blockSizeSelectMethod, 270
genAllocateMemPreamble, 107	deviceSelectMethod, 270
genCurrentSpikeLikeEventPull, 107	generateLineInfo, 270
genCurrentSpikeLikeEventPush, 107	manualBlockSizes, 270
genCurrentTrueSpikePull, 107	manualDeviceID, 270
genCurrentTrueSpikePush, 108	Preferences, 269
genCurrentVariablePull, 108	showPtxInfo, 270
genCurrentVariablePush, 108	userNvccFlags, 270
genDefinitionsInternalPreamble, 108	CodeGenerator::CUDA::PresynapticUpdateStrategy, 78
genDefinitionsPreamble, 108	CodeGenerator::CUDA::PresynapticUpdateStrategy::←
genExtraGlobalParamAllocation, 109	Base, 153
genExtraGlobalParamDefinition, 109	genCode, 153
genExtraGlobalParamImplementation, 109	getNumThreads, 153
genExtraGlobalParamPull, 109	isCompatible, 154
genExtraGlobalParamPush, 109	shouldAccumulateInRegister, 154
genGlobalRNG, 110	shouldAccumulateInSharedMemory, 154
genInit, 110	CodeGenerator::CUDA::PresynapticUpdateStrategy::
genMSBuildCompileModule, 110	PostSpan, 267
genMSBuildConfigProperties, 111	genCode, 267

getNumThreads, 267	genAllocateMemPreamble, 119
isCompatible, 268	genCurrentSpikeLikeEventPull, 120
shouldAccumulateInRegister, 268	genCurrentSpikeLikeEventPush, 120
shouldAccumulateInSharedMemory, 268	genCurrentTrueSpikePull, 120
CodeGenerator::CUDA::PresynapticUpdateStrategy::	genCurrentTrueSpikePush, 120
PreSpan, 272	genCurrentVariablePull, 120
genCode, 272	genCurrentVariablePush, 121
getNumThreads, 273	genDefinitionsInternalPreamble, 121
isCompatible, 273	genDefinitionsPreamble, 121
shouldAccumulateInRegister, 273	genExtraGlobalParamAllocation, 121
shouldAccumulateInTlegister, 273	
•	genExtraGlobalParamDefinition, 121
CodeGenerator::CUDA::Utils, 78	genExtraGlobalParamImplementation, 122
ceilDivide, 78	genExtraGlobalParamPull, 122
padSize, 78	genExtraGlobalParamPush, 122
CodeGenerator::CUDA, 76	genGlobalRNG, 122
BlockSizeSelect, 76	genInit, 122
DeviceSelect, 77	genMSBuildCompileModule, 123
Kernel, 77	genMSBuildConfigProperties, 123
KernelBlockSize, 76	genMSBuildImportProps, 123
CodeGenerator::CodeStream, 164	genMSBuildImportTarget, 124
CodeStream, 164, 165	genMSBuildItemDefinitions, 124
operator<<, 165	genMakefileCompileRule, 123
setSink, 165	genMakefileLinkRule, 123
CodeGenerator::CodeStream::CB, 163	genMakefilePreamble, 123
CB, 163	genNeuronUpdate, 124
Level, 164	genPopVariableInit, 125
CodeGenerator::CodeStream::OB, 254	genPopulationRNG, 124
Level, 254	genRunnerPreamble, 125
OB, 254	genStepTimeFinalisePreamble, 125
CodeGenerator::CodeStream::Scope, 278	genSynapseUpdate, 125
·	
~Scope, 279	genSynapseVariableRowInit, 126
Scope, 279	genTimer, 126
CodeGenerator::FunctionTemplate, 196	genVariableAllocation, 126
doublePrecisionTemplate, 196	genVariableDefinition, 126
genericName, 196	genVariableFree, 127
numArguments, 196	genVariableImplementation, 127
operator=, 196	genVariableInit, 127
singlePrecisionTemplate, 197	genVariablePull, 127
CodeGenerator::MemAlloc, 222	genVariablePush, 127
device, 223	getDeviceMemoryBytes, 128
getDeviceBytes, 223	getVarPrefix, 128
getDeviceMBytes, 223	isGlobalRNGRequired, 128
getHostBytes, 223	isPostsynapticRemapRequired, 128
getHostMBytes, 223	isSynRemapRequired, 128
getZeroCopyBytes, 223	CodeGenerator::SingleThreadedCPU::Optimiser, 79
getZeroCopyMBytes, 223	createBackend, 79
host, 223	CodeGenerator::SingleThreadedCPU::Preferences, 268
operator+=, 223	CodeGenerator::SingleThreadedCPU, 78
zero, 224	CodeGenerator::Substitutions, 303
zeroCopy, 224	addFuncSubstitution, 304
CodeGenerator::PreferencesBase, 270	addParamNameSubstitution, 304
debugCode, 271	addParamValueSubstitution, 304
logLevel, 271	addVarNameSubstitution, 304
optimizeCode, 271	addVarSubstitution, 305
userCxxFlagsGNU, 271	addVarValueSubstitution, 305
userNvccFlagsGNU, 272	apply, 305
CodeGenerator::SingleThreadedCPU::Backend, 117	applyCheckUnreplaced, 305
Backend, 119	getVarSubstitution, 305

hasVarSubstitution, 305	getDerivedParams, 173
operator[], 305	getExtraGlobalParamLocation, 173
Substitutions, 304	getName, 173
CodeGenerator::TeeBuf, 328	getParams, 173
TeeBuf, 328	getVarInitialisers, 173
CodeGenerator::TeeStream, 329	getVarLocation, 174
TeeStream, 329	initDerivedParams, 174
CodeStream	isInitRNGRequired, 174
CodeGenerator::CodeStream, 164, 165	isSimRNGRequired, 174
codeStream.cc, 362	setExtraGlobalParamLocation, 174
	setVarLocation, 174
codeStream.h, 362	currentSource.cc, 363
connect	currentSource.h, 363
SpineMLSimulator::NetworkClient, 239	
connections_set	CurrentSourceInternal, 175
pygenn::genn_groups::SynapseGroup, 313	CurrentSourceInternal, 175
connectivity_initialiser	currentSourceInternal.h, 364
pygenn::genn_groups::SynapseGroup, 313	CurrentSourceModels, 79
connectors.cc, 362	currentSourceModels.cc, 364
connectors.h, 363	IMPLEMENT_MODEL, 364
Constant	currentSourceModels.h, 364
SpineMLSimulator::InputValue::Constant, 167	SET_INJECTION_CODE, 365
ConstantArray	CurrentSourceModels::Base, 143
SpineMLSimulator::InputValue::ConstantArray, 168	getInjectionCode, 143
create	CurrentSourceModels::DC, 175
	getInstance, 177
SpineMLSimulator::Connectors, 95	getParamNames, 177
SpineMLSimulator::InputValue, 96	ParamValues, 176
SpineMLSimulator::ModelProperty, 96	PostVarValues, 176
create_cmlf_class	PreVarValues, 176
pygenn::genn_model, 83	SET_INJECTION_CODE, 177
create_custom_current_source_class	VarValues, 177
pygenn::genn_model, 83	
create_custom_init_var_snippet_class	CurrentSourceModels::GaussianNoise, 198
pygenn::genn_model, 84	getInstance, 199
create custom model class	getParamNames, 199
pygenn::genn_model, 84	ParamValues, 199
create custom neuron class	PostVarValues, 199
pygenn::genn_model, 85	PreVarValues, 199
create_custom_postsynaptic_class	SET_INJECTION_CODE, 199
pygenn::genn_model, 86	VarValues, 199
create_custom_sparse_connect_init_snippet_class	DECLARE_MODEL
pygenn::genn_model, 87	models.h, 381
create_custom_weight_update_class	DECLARE_SNIPPET
pygenn::genn_model, 87	InitSparseConnectivitySnippet::FixedProbability,
create_dpf_class	193
pygenn::genn_model, 88	$In it Sparse Connectivity Snippet :: Fixed Probability \leftarrow Constant Connectivity Snippet :: Fixed Probability \leftarrow Connectivity Snippet :: Fixed Probability Only Sni$
createBackend	NoAutapse, 195
CodeGenerator::CUDA::Optimiser, 77	InitSparseConnectivitySnippet::OneToOne, 255
CodeGenerator::SingleThreadedCPU::Optimiser,	InitSparseConnectivitySnippet::Uninitialised, 346
79	InitVarSnippet::Constant, 166
current_source_model	InitVarSnippet::Exponential, 186
pygenn::genn_groups::CurrentSource, 171	InitVarSnippet::Gamma, 197
current_sources	InitVarSnippet::Normal, 252
pygenn::genn_model::GeNNModel, 210	InitVarSnippet::Uniform, 343
current_spikes	
— ·	InitVarSnippet::Uninitialised, 345
pygenn::genn_groups::NeuronGroup, 241	snippet.h, 398
CurrentSource, 171	DECLARE_WEIGHT_UPDATE_MODEL
CurrentSource, 172, 173	weightUpdateModels.h, 406
getCurrentSourceModel, 173	WeightUpdateModels::PiecewiseSTDP, 258

WeightUpdateModels::StaticGraded, 299	freeMem
WeightUpdateModels::StaticPulse, 301	SharedLibraryModel, 280
DataType	func
SpineMLSimulator::NetworkClient, 238	Snippet::Base::DerivedParam, 179
debugCode	functionSubstitute
CodeGenerator::PreferencesBase, 271	CodeGenerator, 71
default_sparse_connectivity_location	
pygenn::genn_model::GeNNModel, 205, 206	GENN_EXPORT
default_var_location	gennExport.h, 372
pygenn::genn_model::GeNNModel, 206, 210	genAllocateMemPreamble
delay_slots	CodeGenerator::BackendBase, 132
pygenn::genn_groups::NeuronGroup, 241 DerivedParamVec	CodeGenerator::CUDA::Backend, 107
Snippet::Base, 150	CodeGenerator::SingleThreadedCPU::Backend,
device	119
CodeGenerator::MemAlloc, 223	genArray
DeviceSelect	CodeGenerator::BackendBase, 133
CodeGenerator::CUDA, 77	genCode
deviceSelectMethod	CodeGenerator::CUDA::PresynapticUpdate← Strategy::Base, 153
CodeGenerator::CUDA::Preferences, 270	CodeGenerator::CUDA::PresynapticUpdate↔
doublePrecisionTemplate	Strategy::PostSpan, 267
CodeGenerator::FunctionTemplate, 196	CodeGenerator::CUDA::PresynapticUpdate↔
dT	Strategy::PreSpan, 272
pygenn::genn_model::GeNNModel, 206, 210	genCurrentSpikeLikeEventPull
	CodeGenerator::BackendBase, 133
EGPVec	CodeGenerator::CUDA::Backend, 107
Snippet::Base, 151	CodeGenerator::SingleThreadedCPU::Backend,
end	120
pygenn::genn_model::GeNNModel, 206	genCurrentSpikeLikeEventPush
ensureFtype	CodeGenerator::BackendBase, 133
CodeGenerator, 71	CodeGenerator::CUDA::Backend, 107
Event	CodeGenerator::SingleThreadedCPU::Backend,
SpineMLSimulator::LogOutput::Event, 180	120
ExponentialDistribution SpineMLSimulator::ModelProperty::Exponential↔	genCurrentTrueSpikePull
Distribution, 186	CodeGenerator::BackendBase, 133
External	CodeGenerator::CUDA::Backend, 107
SpineMLSimulator::InputValue::External, 187	Code Generator :: Single Threaded CPU :: Backend,
ExternalNetwork	120
SpineMLSimulator::InputValue::ExternalNetwork,	genCurrentTrueSpikePush
189	CodeGenerator::BackendBase, 133
extra_global_params	CodeGenerator::CUDA::Backend, 108
pygenn::genn_groups::Group, 212	CodeGenerator::SingleThreadedCPU::Backend,
	120
filesystem, 79	genCurrentVariablePull
finalize	CodeGenerator::BackendBase, 133
ModelSpec, 233	CodeGenerator::CUDA::Backend, 108
findCurrentSource	CodeGenerator::SingleThreadedCPU::Backend,
ModelSpec, 233	120 genCurrentVariablePush
findNeuronGroup	CodeGenerator::BackendBase, 134
ModelSpec, 233	CodeGenerator::CUDA::Backend, 108
findSynapseGroup ModelSpec, 233	CodeGenerator::SingleThreadedCPU::Backend,
Fixed	121
SpineMLSimulator::ModelProperty::Fixed, 191	genCurrentVariablePushPull
FloatType	CodeGenerator::BackendBase, 134
modelSpec.h, 384	genDefinitionsInternalPreamble
freeExtraGlobalParam	CodeGenerator::BackendBase, 134
SharedLibraryModel, 280	CodeGenerator::CUDA::Backend, 108

CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 137 CodeGenerator::CUDA::Backend, 111
genDefinitionsPreamble	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 134	124
CodeGenerator::CUDA::Backend, 108	genMSBuildItemDefinitions
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 137
121	CodeGenerator::CUDA::Backend, 111
genExtraGlobalParamAllocation	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	124
CodeGenerator::CUDA::Backend, 109	genMakefileCompileRule
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 136
121	CodeGenerator::CUDA::Backend, 110
genExtraGlobalParamDefinition	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	123
CodeGenerator::CUDA::Backend, 109	genMakefileLinkRule
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 136
121	CodeGenerator::CUDA::Backend, 110
genExtraGlobalParamImplementation	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	123
CodeGenerator::CUDA::Backend, 109	genMakefilePreamble
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 136
122	CodeGenerator::CUDA::Backend, 110
genExtraGlobalParamPull	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	123
CodeGenerator::CUDA::Backend, 109	genNeuronUpdate
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 137
122	CodeGenerator::CUDA::Backend, 111
genExtraGlobalParamPush	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	124
CodeGenerator::CUDA::Backend, 109	genPopVariableInit
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 138
122	CodeGenerator::CUDA::Backend, 112
genGlobalRNG	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 135	125
CodeGenerator::CUDA::Backend, 110	genPopulationRNG
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 138
122	CodeGenerator::CUDA::Backend, 112
genInit	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 136	124
CodeGenerator::CUDA::Backend, 110	genRunnerPreamble
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 138
122	CodeGenerator::CUDA::Backend, 112
genMSBuildCompileModule	Code Generator :: Single Threaded CPU :: Backend,
CodeGenerator::BackendBase, 136	125
CodeGenerator::CUDA::Backend, 110	genScalar
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 138
123	genStepTimeFinalisePreamble
genMSBuildConfigProperties	CodeGenerator::BackendBase, 138
CodeGenerator::BackendBase, 137	CodeGenerator::CUDA::Backend, 112
CodeGenerator::CUDA::Backend, 111	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	125
123	genSynapseUpdate
genMSBuildImportProps	CodeGenerator::BackendBase, 139
CodeGenerator::BackendBase, 137	CodeGenerator::CUDA::Backend, 112
CodeGenerator::CUDA::Backend, 111	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	125
123	genSynapseVariableRowInit
genMSBuildImportTarget	CodeGenerator::BackendBase, 139

CodeGenerator::CUDA::Backend, 113 CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator, 72 generateMSBuild
126	CodeGenerator, 72
genTimer	generateMSBuild.cc, 367
CodeGenerator::BackendBase, 139	generateMSBuild.h, 367
CodeGenerator::CUDA::Backend, 113	generateMakefile
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator, 72
126	generateMakefile.cc, 366
genVariableAllocation	generateMakefile.h, 366
CodeGenerator::BackendBase, 140	generateNeuronUpdate
CodeGenerator::CUDA::Backend, 113	CodeGenerator, 72
CodeGenerator::SingleThreadedCPU::Backend,	generateNeuronUpdate.cc, 368
126	generateNeuronUpdate.h, 368
genVariableDefinition	generateRun.h, 368
CodeGenerator::BackendBase, 140	GenerateRunBase, 200
CodeGenerator::CUDA::Backend, 114	buildAndRun, 200
CodeGenerator::SingleThreadedCPU::Backend,	GenerateRunBase, 200
126	getApp, 200
genVariableFree	getExitCode, 200
CodeGenerator::BackendBase, 140	getExperimentName, 201
CodeGenerator::CUDA::Backend, 114	getOutDir, 201
CodeGenerator::SingleThreadedCPU::Backend,	parseCommandLine, 201
127	runTools, 201
genVariableImplementation	writeSizes, 201
CodeGenerator::BackendBase, 140	generateRunner
CodeGenerator::CUDA::Backend, 114	CodeGenerator, 72
CodeGenerator::SingleThreadedCPU::Backend,	generateRunner.cc, 369
127	generateRunner.h, 369
genVariableInit	generateSupportCode
CodeGenerator::BackendBase, 140	CodeGenerator, 73
CodeGenerator::CUDA::Backend, 114	
	generateSupportCode.cc, 369
CodeGenerator::SingleThreadedCPU::Backend, 127	generateSupportCode.h, 369
	generateSynapseUpdate
genVariablePull	CodeGenerator, 73
CodeGenerator::BackendBase, 141	generateSynapseUpdate.cc, 369
CodeGenerator::CUDA::Backend, 114	generateSynapseUpdate.h, 370
CodeGenerator::SingleThreadedCPU::Backend,	genericName
127	CodeGenerator::FunctionTemplate, 196
genVariablePush	genn_groups.py, 370
CodeGenerator::BackendBase, 141	genn_model.py, 370
CodeGenerator::CUDA::Backend, 115	genn_to_numpy_types
CodeGenerator::SingleThreadedCPU::Backend,	pygenn::model_preprocessor, 93
127	gennExport.h, 371
genVariablePushPull	GENN_EXPORT, 372
CodeGenerator::BackendBase, 141	gennUtils.cc, 372
generateAll	gennUtils.h, 372
CodeGenerator, 71	get
generateAll.cc, 365	SpineMLSimulator::StateVar, 297
generateAll.h, 365	SpineMLSimulator::Timer, 330
generateInit	SpineMLSimulator::TimerAccumulate, 332
CodeGenerator, 72	Timer, 331
generateInit.cc, 366	TimerAccumulate, 331
generateInit.h, 366	get_sparse_post_inds
generateLineInfo	pygenn::genn_groups::SynapseGroup, 308
CodeGenerator::CUDA::Preferences, 270	get_sparse_pre_inds
generateMPI.cc, 367	pygenn::genn_groups::SynapseGroup, 308
generateMPI.h, 367	get_var_values
generateMPI	pygenn::genn_groups::SynapseGroup, 308

getAdditionalInputVars	NeuronGroup, 246
NeuronModels::Base, 148	NeuronModels::LIF, 221
getApp	NeuronModels::PoissonNew, 264
GenerateRunBase, 200	NeuronModels::RulkovMap, 276
getApplyInputCode	PostsynapticModels::ExpCond, 182
PostsynapticModels::Base, 152	PostsynapticModels::ExpCurr, 184
PostsynapticModels::DeltaCurr, 178	Snippet::Base, 151
PostsynapticModels::ExpCond, 182	Snippet::Init, 213
PostsynapticModels::ExpCurr, 184	WeightUpdateModels::PiecewiseSTDP, 259
getArray	getDeviceBytes
SharedLibraryModel, 280	CodeGenerator::MemAlloc, 223
getBackPropDelaySteps	getDeviceMBytes
SynapseGroup, 318	CodeGenerator::MemAlloc, 223
getBuffer	getDeviceMemoryBytes
SpineMLSimulator::InputValue::External, 188	CodeGenerator::BackendBase, 141
getBufferBegin	CodeGenerator::CUDA::Backend, 115
SpineMLSimulator::InputValue::External, 188	CodeGenerator::SingleThreadedCPU::Backend
getBufferEnd	128
_	getDT
SpineMLSimulator::InputValue::External, 188	<u> </u>
getCalcMaxColLengthFunc	ModelSpec, 233
InitSparseConnectivitySnippet::Base, 144	SpineMLSimulator::Simulator, 285
getCalcMaxRowLengthFunc	getDurationMs
InitSparseConnectivitySnippet::Base, 144	SpineMLSimulator::Simulator, 285
getChosenCUDADevice	getEndTimestep
CodeGenerator::CUDA::Backend, 115	SpineMLSimulator::LogOutput::Base, 161
getChosenDeviceID	getEventCode
CodeGenerator::CUDA::Backend, 115	WeightUpdateModels::Base, 155
getClusterHostID	WeightUpdateModels::StaticGraded, 299
NeuronGroup, 246	getEventThresholdConditionCode
SynapseGroup, 318	WeightUpdateModels::Base, 156
getCode	WeightUpdateModels::StaticGraded, 299
InitVarSnippet::Base, 145	getExitCode
getConnectivityInitialiser	GenerateRunBase, 200
SynapseGroup, 318	getExperimentName
getCurrentQueueOffset	GenerateRunBase, 201
NeuronGroup, 246	getExternalInput
getCurrentSourceModel	SpineMLSimulator::Simulator, 285
CurrentSource, 173	getExternalLogger
getCurrentSources	SpineMLSimulator::Simulator, 285
NeuronGroup, 246	getExtraGlobalParamIndex
GetCurrentSpikeCountFunc	InitSparseConnectivitySnippet::Base, 144
SpikeRecorder, 288	Models::Base, 146
GetCurrentSpikesFunc	getExtraGlobalParamLocation
SpikeRecorder, 288	CurrentSource, 173
getDecayCode	NeuronGroup, 246, 247
PostsynapticModels::Base, 152	getExtraGlobalParams
PostsynapticModels::ExpCond, 182	InitSparseConnectivitySnippet::Base, 145
· · · · · · · · · · · · · · · · · · ·	
PostsynapticModels::ExpCurr, 184	Models::Base, 147
getDelaySteps	NeuronModels::Poisson, 262
SynapseGroup, 318	NeuronModels::SpikeSourceArray, 292
getDendriticDelayLocation	getFloatAtomicAdd
SynapseGroup, 318	CodeGenerator::CUDA::Backend, 115
getDendriticDelayOffset	getHostBytes
SynapseGroup, 318	CodeGenerator::MemAlloc, 223
getDerivedParams	getHostMBytes
CurrentSource, 173	CodeGenerator::MemAlloc, 223
$In it Sparse Connectivity Snippet :: Fixed Probability \leftarrow$	getHostStateVar
Base, 194	SpineMLSimulator::ModelProperty::Base, 162

getInSyn	getMaxDendriticDelayTimesteps
NeuronGroup, 247	SynapseGroup, 319
getInSynLocation	getMaxSourceConnections
SynapseGroup, 318	SynapseGroup, 319
getIndices	getMergedInSyn
SpineMLSimulator::LogOutput::AnalogueBase, 99	NeuronGroup, 247
getInitSparseTime	getModelPropertySize
SpineMLSimulator::Simulator, 285	SpineMLSimulator::LogOutput::AnalogueBase, 99
getInitTime	getNVCCFlags
SpineMLSimulator::Simulator, 285	CodeGenerator::CUDA::Backend, 116
getInitialisers	getName
Models::VarInitContainerBase, 353	CurrentSource, 173
Models::VarInitContainerBase< 0 >, 354	ModelSpec, 234
getInjectionCode	NeuronGroup, 247
CurrentSourceModels::Base, 143	SynapseGroup, 319
getInputMs	getNamedVecIndex
SpineMLSimulator::Simulator, 285	Snippet::Base, 151
getInstance	getNeuronModel
CurrentSourceModels::DC, 177	NeuronGroup, 247
CurrentSourceModels::GaussianNoise, 199	getNeuronUpdateTime
NeuronModels::Izhikevich, 217	SpineMLSimulator::Simulator, 286
NeuronModels::IzhikevichVariable, 219	getNumDelaySlots
NeuronModels::LIF, 221	NeuronGroup, 247
NeuronModels::Poisson, 262	getNumLocalNeurons
NeuronModels::PoissonNew, 264	ModelSpec, 234
NeuronModels::RulkovMap, 277	getNumNeurons
NeuronModels::SpikeSource, 290	ModelSpec, 234
NeuronModels::SpikeSourceArray, 293	NeuronGroup, 247
NeuronModels::TraubMiles, 336	SpineMLSimulator::InputValue::Base, 160
NeuronModels::TraubMilesAlt, 339	getNumPostsynapticUpdateThreads
NeuronModels::TraubMilesFast, 340	CodeGenerator::CUDA::Backend, 115
NeuronModels::TraubMilesNStep, 342	getNumPresynapticUpdateThreads
PostsynapticModels::DeltaCurr, 179	CodeGenerator::CUDA::Backend, 116
PostsynapticModels::ExpCond, 183	getNumRemoteNeurons
PostsynapticModels::ExpCurr, 185	ModelSpec, 234
WeightUpdateModels::StaticPulseDendriticDelay,	·
303	getNumSynapseDynamicsThreads
	CodeGenerator::CUDA::Backend, 116
getKernelBlockSize	getNumThreads
CodeGenerator::CUDA::Backend, 115	CodeGenerator::CUDA::PresynapticUpdate ←
getLearnPostCode	Strategy::Base, 153
WeightUpdateModels::Base, 156	CodeGenerator::CUDA::PresynapticUpdate←
WeightUpdateModels::PiecewiseSTDP, 259	Strategy::PostSpan, 267
getLearnPostSupportCode	CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::PresynapticUpdate CodeGenerator::CUDA::CudA::PresynapticUpdate CodeGenerator::CUDA::CudA::Cu
WeightUpdateModels::Base, 156	Strategy::PreSpan, 273
getLocalCurrentSources	getNumThreadsPerSpike
ModelSpec, 233	SynapseGroup, 319
getLocalHostID	getOutDir
CodeGenerator::BackendBase, 142	GenerateRunBase, 201
getLocalNeuronGroups	getOutSyn
ModelSpec, 234	NeuronGroup, 247
getLocalSynapseGroups	getPSConstInitVals
ModelSpec, 234	SynapseGroup, 319
getLogMs	getPSDerivedParams
SpineMLSimulator::Simulator, 286	SynapseGroup, 319
getMatrixType	getPSExtraGlobalParamLocation
SynapseGroup, 318	SynapseGroup, 319, 320
getMaxConnections	getPSModel
SynapseGroup, 319	SynapseGroup, 320

getPSModelTargetName	NeuronGroup, 247
SynapseGroup, 320	getRemoteCurrentSources
getPSParams	ModelSpec, 234
SynapseGroup, 320	getRemoteNeuronGroups
getPSVarInitialisers	ModelSpec, 234
SynapseGroup, 320	getRemoteSynapseGroups
getPSVarLocation	ModelSpec, 235
SynapseGroup, 320	getResetCode
getParamNames	NeuronModels::Base, 149
CurrentSourceModels::DC, 177	NeuronModels::LIF, 221
CurrentSourceModels::GaussianNoise, 199	NeuronModels::SpikeSourceArray, 293
InitSparseConnectivitySnippet::FixedProbability←	getRowBuildCode
Base, 194	InitSparseConnectivitySnippet::Base, 145
InitVarSnippet::Constant, 166	InitSparseConnectivitySnippet::FixedProbability←
InitVarSnippet::Exponential, 186	Base, 194
InitVarSnippet::Gamma, 198	getRowBuildStateVars
InitVarSnippet::Normal, 252	InitSparseConnectivitySnippet::Base, 145
InitVarSnippet::Uniform, 343	getRuntimeVersion
NeuronModels::Izhikevich, 217	CodeGenerator::CUDA::Backend, 116
NeuronModels::Izhikevich\ariable, 219	getScalar
NeuronModels::LIF, 221	SharedLibraryModel, 281
	· · · · · · · · · · · · · · · · · · ·
NeuronModels::Poisson, 262	getSeed ModelSpee 235
NeuronModels::PoissonNew, 265	ModelSpec, 235
NeuronModels::RulkovMap, 277	getSimCode
NeuronModels::TraubMiles, 336	NeuronModels::Base, 149
NeuronModels::TraubMilesNStep, 342	NeuronModels::Izhikevich, 217
PostsynapticModels::ExpCond, 183	NeuronModels::LIF, 222
PostsynapticModels::ExpCurr, 185	NeuronModels::Poisson, 262
Snippet::Base, 151	NeuronModels::PoissonNew, 265
WeightUpdateModels::PiecewiseSTDP, 259	NeuronModels::RulkovMap, 277
WeightUpdateModels::StaticGraded, 299	NeuronModels::SpikeSourceArray, 293
getParams	NeuronModels::TraubMiles, 337
CurrentSource, 173	NeuronModels::TraubMilesAlt, 339
NeuronGroup, 247	NeuronModels::TraubMilesFast, 340
Snippet::Init, 213	NeuronModels::TraubMilesNStep, 342
getPostSpikeCode	WeightUpdateModels::Base, 157
WeightUpdateModels::Base, 156	WeightUpdateModels::PiecewiseSTDP, 259
getPostVarIndex	WeightUpdateModels::StaticPulse, 301
WeightUpdateModels::Base, 156	WeightUpdateModels::StaticPulseDendriticDelay,
getPostVars	303
WeightUpdateModels::Base, 156	getSimSupportCode
getPostsynapticBackPropDelaySlot	WeightUpdateModels::Base, 157
SynapseGroup, 319	getSimulateMs
getPostsynapticUpdateTime	SpineMLSimulator::Simulator, 286
SpineMLSimulator::Simulator, 286	getSize
getPreSpikeCode	CodeGenerator::BackendBase, 142
WeightUpdateModels::Base, 156	SpineMLSimulator::InputValue::External, 188
getPreVarIndex	SpineMLSimulator::ModelProperty::Base, 163
WeightUpdateModels::Base, 157	getSnippet
getPreVars	Snippet::Init, 213
WeightUpdateModels::Base, 157	getSpanType
getPrecision	SynapseGroup, 320
ModelSpec, 234	getSparseConnectivityExtraGlobalParamLocation
getPresynapticAxonalDelaySlot	SynapseGroup, 320, 321
SynapseGroup, 319	getSparseConnectivityLocation
getPresynapticUpdateTime	SynapseGroup, 321
SpineMLSimulator::Simulator, 286	getSparseIndType
getPrevQueueOffset	SynapseGroup, 321
goti 10 v Quodo Oligot	Cyriapacaroup, UZ I

getSpikeEventCondition	Snippet::ValueBase< 0 >, 347
NeuronGroup, 248	getVarIndex
getSpikeEventLocation	Models::Base, 147
NeuronGroup, 248	getVarInitialisers
getSpikeLocation	CurrentSource, 173
NeuronGroup, 248	NeuronGroup, 248
getSpikeTimeLocation	getVarLocation
NeuronGroup, 248	CurrentSource, 174
getSrcNeuronGroup	NeuronGroup, 248
SynapseGroup, 321	getVarPrefix
getStateVarBegin	CodeGenerator::BackendBase, 142
SpineMLSimulator::LogOutput::AnalogueBase,	CodeGenerator::CUDA::Backend, 116
100	CodeGenerator::SingleThreadedCPU::Backend,
getStateVarEnd	128
SpineMLSimulator::LogOutput::AnalogueBase,	getVarSubstitution
100	CodeGenerator::Substitutions, 305
getSum	getVars
SpikeRecorder, 289	Models::Base, 147
getSupportCode	NeuronModels::Izhikevich, 217
NeuronModels::Base, 149	NeuronModels::IzhikevichVariable, 219
PostsynapticModels::Base, 152	NeuronModels::LIF, 222
getSymbol	NeuronModels::Poisson, 262
SharedLibraryModel, 281	NeuronModels::PoissonNew, 265
getSynapseDynamicsCode	NeuronModels::RulkovMap, 277
WeightUpdateModels::Base, 157	NeuronModels::SpikeSourceArray, 293
getSynapseDynamicsSuppportCode	NeuronModels::TraubMiles, 337
WeightUpdateModels::Base, 157	WeightUpdateModels::PiecewiseSTDP, 259
getSynapseDynamicsTime	WeightUpdateModels::StaticGraded, 300
SpineMLSimulator::Simulator, 286	WeightUpdateModels::StaticPulse, 301
getTargetIndices	WeightUpdateModels::StaticPulseDendriticDelay,
SpineMLSimulator::InputValue::Base, 160	303
getThresholdConditionCode	getWUConstInitVals
gerriresholdoonallonoode	gctvoconstrutvals
NeuronModels::Base, 149	SynapseGroup, 321
	-
NeuronModels::Base, 149	SynapseGroup, 321
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217	SynapseGroup, 321 getWUDerivedParams
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::PulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase,	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::PoissonNew, 265 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274 getTimestep	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers SynapseGroup, 323
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274 getTimestep SharedLibraryModel, 281	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers SynapseGroup, 323 getWUVarLocation
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::RulkovMap, 277 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274 getTimestep SharedLibraryModel, 281 getTrgNeuronGroup	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers SynapseGroup, 323 getWUVarLocation SynapseGroup, 323 getWUVarLocation SynapseGroup, 323
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::PoissonNew, 265 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274 getTimestep SharedLibraryModel, 281 getTrgNeuronGroup SynapseGroup, 321	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers SynapseGroup, 323 getWUVarLocation SynapseGroup, 323 getWUVarLocation SynapseGroup, 323 getZeroCopyBytes
NeuronModels::Base, 149 NeuronModels::Izhikevich, 217 NeuronModels::LIF, 222 NeuronModels::Poisson, 262 NeuronModels::PoissonNew, 265 NeuronModels::PoissonNew, 265 NeuronModels::SpikeSource, 291 NeuronModels::SpikeSourceArray, 293 NeuronModels::TraubMiles, 337 getTime SharedLibraryModel, 281 getTimePrecision ModelSpec, 235 getTimeToSpike SpineMLSimulator::Input::InterSpikeIntervalBase, 215 SpineMLSimulator::Input::PoissonSpikeRate, 266 SpineMLSimulator::Input::RegularSpikeRate, 274 getTimestep SharedLibraryModel, 281 getTrgNeuronGroup SynapseGroup, 321 getUnderlyingType	SynapseGroup, 321 getWUDerivedParams SynapseGroup, 321 getWUExtraGlobalParamLocation SynapseGroup, 322 getWUModel SynapseGroup, 322 getWUParams SynapseGroup, 322 getWUPostVarInitialisers SynapseGroup, 322 getWUPostVarLocation SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarInitialisers SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322 getWUPreVarLocation SynapseGroup, 322, 323 getWUVarInitialisers SynapseGroup, 323 getWUVarLocation SynapseGroup, 323 getZeroCopyBytes CodeGenerator::MemAlloc, 223

CodeGenerator::BackendBase, 131	getCalcMaxRowLengthFunc, 144
	getExtraGlobalParamIndex, 144
Handler	getExtraGlobalParams, 145
CodeGenerator::BackendBase, 131	getRowBuildCode, 145
has_individual_postsynaptic_vars	getRowBuildStateVars, 145
pygenn::genn_groups::SynapseGroup, 309	InitSparseConnectivitySnippet::FixedProbability, 192
has_individual_synapse_vars	DECLARE SNIPPET, 193
pygenn::genn_groups::SynapseGroup, 309	-
hasOutputToHost	SET_ROW_BUILD_CODE, 193
NeuronGroup, 248	InitSparseConnectivitySnippet::FixedProbabilityBase
has Var Substitution	193
	getDerivedParams, 194
CodeGenerator::Substitutions, 305	getParamNames, 194
host	getRowBuildCode, 194
CodeGenerator::MemAlloc, 223	SET_CALC_MAX_COL_LENGTH_FUNC, 194
	SET CALC MAX ROW LENGTH FUNC, 194
IMPLEMENT_MODEL	SET ROW BUILD STATE VARS, 194
currentSourceModels.cc, 364	
models.h, 382	InitSparseConnectivitySnippet::FixedProbabilityNo⊷
neuronModels.cc, 388, 389	Autapse, 195
postsynapticModels.cc, 393	DECLARE_SNIPPET, 195
weightUpdateModels.cc, 405	SET_ROW_BUILD_CODE, 195
IMPLEMENT SNIPPET	InitSparseConnectivitySnippet::Init, 212
_	Init, 212
initSparseConnectivitySnippet.cc, 373	InitSparseConnectivitySnippet::OneToOne, 254
initVarSnippet.cc, 375, 376	DECLARE SNIPPET, 255
snippet.h, 398	SET_MAX_COL_LENGTH, 255
ind	
pygenn::genn_groups::SynapseGroup, 313	SET_MAX_ROW_LENGTH, 255
Init	SET_ROW_BUILD_CODE, 255
InitSparseConnectivitySnippet::Init, 212	InitSparseConnectivitySnippet::Uninitialised, 345
Snippet::Init, 213	DECLARE_SNIPPET, 346
init_connectivity	initVar
	modelSpec.h, 385, 386
pygenn::genn_model, 89	InitVarSnippet, 80
init_required	initVarSnippet.cc, 375
pygenn::model_preprocessor::Variable, 351	IMPLEMENT_SNIPPET, 375, 376
init_val	
pygenn::model_preprocessor::Variable, 351	initVarSnippet.h, 376
init_var	SET_CODE, 377
pygenn::genn_model, 89	InitVarSnippet::Base, 145
initConnectivity	getCode, 145
modelSpec.h, 385	InitVarSnippet::Constant, 165
initDerivedParams	DECLARE_SNIPPET, 166
CurrentSource, 174	getParamNames, 166
	SET CODE, 166
NeuronGroup, 249	InitVarSnippet::Exponential, 185
Snippet::Init, 213	···
SynapseGroup, 323	DECLARE_SNIPPET, 186
InitSparseConnectivitySnippet, 79	getParamNames, 186
initSparseConnectivitySnippet.cc, 373	SET_CODE, 186
IMPLEMENT_SNIPPET, 373	InitVarSnippet::Gamma, 197
initSparseConnectivitySnippet.h, 373	DECLARE_SNIPPET, 197
SET_CALC_MAX_COL_LENGTH_FUNC, 374	getParamNames, 198
SET CALC MAX ROW LENGTH FUNC, 374	SET_CODE, 198
SET EXTRA GLOBAL PARAMS, 374	InitVarSnippet::Normal, 252
	DECLARE_SNIPPET, 252
SET_MAX_COL_LENGTH, 374	
SET_MAX_ROW_LENGTH, 375	getParamNames, 252
SET_ROW_BUILD_CODE, 375	SET_CODE, 253
SET_ROW_BUILD_STATE_VARS, 375	InitVarSnippet::Uniform, 343
InitSparseConnectivitySnippet::Base, 143	DECLARE_SNIPPET, 343
CalcMaxLengthFunc, 144	getParamNames, 343
getCalcMaxColLengthFunc, 144	SET_CODE, 344

InitVarSnippet::Uninitialised, 345 DECLARE_SNIPPET, 345	SynapseGroup, 323 isParamRequiredBySpikeEventCondition
initialize	NeuronGroup, 249
SharedLibraryModel, 281	isPostSpikeTimeRequired
initializeSparse	WeightUpdateModels::Base, 157
SharedLibraryModel, 281	WeightUpdateModels::PiecewiseSTDP, 259
injectCurrent	isPostsynapticRemapRequired
NeuronGroup, 249	CodeGenerator::BackendBase, 142
injectSpike	CodeGenerator::CUDA::Backend, 116
SpineMLSimulator::Input::SpikeBase, 287	CodeGenerator::SingleThreadedCPU::Backend,
input.cc, 377	128
input.h, 377	isPreSpikeTimeRequired
inputValue.cc, 377	WeightUpdateModels::Base, 158
inputValue.h, 378	WeightUpdateModels::PiecewiseSTDP, 260
InterSpikeIntervalBase	isRNGRequired
SpineMLSimulator::Input::InterSpikeIntervalBase,	Utils, 97
214	isSimRNGRequired
is_bitmask	CurrentSource, 174
pygenn::genn_groups::SynapseGroup, 309	NeuronGroup, 249
is_connectivity_init_required	isSparseConnectivityInitRequired
pygenn::genn_groups::SynapseGroup, 309	SynapseGroup, 324
is_dense	isSpikeEventRequired
pygenn::genn_groups::SynapseGroup, 309	NeuronGroup, 249
is model valid	SynapseGroup, 324
pygenn::model_preprocessor, 90	isSpikeTimeRequired
is_ragged	NeuronGroup, 249
pygenn::genn_groups::SynapseGroup, 309	isSynRemapRequired
is_spike_source_array	CodeGenerator::BackendBase, 142
pygenn::genn_groups::NeuronGroup, 242	CodeGenerator::CUDA::Backend, 116
isAccessible	CodeGenerator::SingleThreadedCPU::Backend,
SpineMLSimulator::StateVar, 297	128
isAutoRefractoryRequired	isTimingEnabled
NeuronModels::Base, 149	ModelSpec, 235
isCompatible	isTrueSpikeRequired
CodeGenerator::CUDA::PresynapticUpdate↔	NeuronGroup, 249
Strategy::Base, 154	SynapseGroup, 324
CodeGenerator::CUDA::PresynapticUpdate ←	isTypePointer
Strategy::PostSpan, 268	Utils, 97
CodeGenerator::CUDA::PresynapticUpdate↔	isVarQueueRequired
Strategy::PreSpan, 273	NeuronGroup, 249, 250
isDelayRequired	isWUInitRNGRequired
NeuronGroup, 249	SynapseGroup, 324
isDendriticDelayRequired	isWUVarInitRequired
SynapseGroup, 323	SynapseGroup, 324
isEventThresholdReTestRequired	isZeroCopyEnabled
SynapseGroup, 323	NeuronGroup, 250
isGlobalRNGRequired	SynapseGroup, 324
CodeGenerator::BackendBase, 142	
CodeGenerator::CUDA::Backend, 116	Kernel
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA, 77
128	KernelBlockSize
isInitRNGRequired	CodeGenerator::CUDA, 76
CurrentSource, 174	KernelNames
NeuronGroup, 249	CodeGenerator::CUDA::Backend, 117
Utils, 97	Level
isPSInitRNGRequired	CodeGenerator::CodeStream::CB, 164
SynapseGroup, 323	CodeGenerator::CodeStream::OB, 254
isPSModelMerged	load

pygenn::genn_groups::CurrentSource, 170	isTimingEnabled, 235
pygenn::genn_groups::NeuronGroup, 241	ModelSpec, 227
pygenn::genn_groups::SynapseGroup, 309	NeuronGroupValueType, 227
pygenn::genn_model::GeNNModel, 206	operator=, 235
SpineMLSimulator::Simulator, 286	scalarExpr, 235
logLevel	setDefaultExtraGlobalParamLocation, 235
CodeGenerator::PreferencesBase, 271	setDefaultNarrowSparseIndEnabled, 235
logOutput.cc, 378	setDefaultSparseConnectivityLocation, 236
logOutput.h, 379	setDefaultVarLocation, 236
logWriter.h, 379	setDT, 236
	setMergePostsynapticModels, 236
m	setName, 236
pygenn::genn_model, 89	setPrecision, 236
m Direct	
SpineMLSimulator::StateVar, 298	setSeed, 236
m Indirect	setTimePrecision, 237
SpineMLSimulator::StateVar, 298	setTiming, 237
•	SynapseGroupValueType, 227
manualBlockSizes	zeroCopyInUse, 237
CodeGenerator::CUDA::Preferences, 270	modelSpec.cc, 382
manualDeviceID	modelSpec.h, 383
CodeGenerator::CUDA::Preferences, 270	FloatType, 384
MathsFunc	
codeGenUtils.cc, 360	initConnectivity, 385
matrix_type	initVar, 385, 386
pygenn::genn_groups::SynapseGroup, 310	NNmodel, 384
max_row_length	NO_DELAY, 384
pygenn::genn_groups::SynapseGroup, 310	TimePrecision, 384
mergeIncomingPSM	uninitialisedConnectivity, 386
NeuronGroup, 250	uninitialisedVar, 386
•	ModelSpecInternal, 237
Mode	modelSpecInternal.h, 386
SpineMLSimulator::NetworkClient, 238	Models, 80
model_name	models.h, 381
pygenn::genn_model::GeNNModel, 206, 207, 210	
model_preprocessor.py, 379	DECLARE_MODEL, 381
modelProperty.cc, 380	IMPLEMENT_MODEL, 382
modelProperty.h, 380	SET_EXTRA_GLOBAL_PARAMS, 382
ModelSpec, 224	SET_VARS, 382
~ModelSpec, 227	VarAccess, 382
addCurrentSource, 227, 228	Models::Base, 146
addNeuronPopulation, 228, 229	getExtraGlobalParamIndex, 146
addSynapsePopulation, 230–232	getExtraGlobalParams, 147
· · · · · · · · · · · · · · · · · · ·	getVarIndex, 147
finalize, 233	getVars, 147
findCurrentSource, 233	VarVec, 146
findNeuronGroup, 233	
findSynapseGroup, 233	Models::Base::Var, 349
getDT, 233	access, 349
getLocalCurrentSources, 233	name, 349
getLocalNeuronGroups, 234	type, 350
getLocalSynapseGroups, 234	Var, 349
getName, 234	Models::VarInit, 352
getNumLocalNeurons, 234	VarInit, 352
getNumNeurons, 234	Models::VarInitContainerBase
	getInitialisers, 353
getNumRemoteNeurons, 234	_
getPrecision, 234	operator[], 353
getRemoteCurrentSources, 234	VarInitContainerBase, 353
getRemoteNeuronGroups, 234	Models::VarInitContainerBase< 0 >, 354
getRemoteSynapseGroups, 235	getInitialisers, 354
getSeed, 235	VarInitContainerBase, 354
getTimePrecision, 235	Models::VarInitContainerBase< NumVars >, 353

NNmodel	isVarQueueRequired, 249, 250
modelSpec.h, 384	isZeroCopyEnabled, 250
NO_DELAY	mergeIncomingPSM, 250
modelSpec.h, 384	NeuronGroup, 245
name	setExtraGlobalParamLocation, 250
Models::Base::Var, 349	setSpikeEventLocation, 250
pygenn::genn_groups::Group, 212	setSpikeLocation, 250
pygenn::model_preprocessor::ExtraGlobal←	setSpikeTimeLocation, 250
Variable, 191	setVarLocation, 250
pygenn::model_preprocessor::Variable, 351	updatePostVarQueues, 251
Snippet::Base::DerivedParam, 179	updatePreVarQueues, 251
Snippet::Base::EGP, 180	neuronGroup.cc, 387
Snippet::Base::ParamVal, 256	neuronGroup.h, 387
needs_allocation	NeuronGroupHandler
pygenn::model_preprocessor::Variable, 351	CodeGenerator::BackendBase, 131
NetworkClient	NeuronGroupInternal, 251
SpineMLSimulator::NetworkClient, 238	NeuronGroupInternal, 251
networkClient.cc, 387	neuronGroupInternal.h, 388
networkClient.h, 387	NeuronGroupSimHandler
neuron	CodeGenerator::BackendBase, 132
pygenn::genn_groups::NeuronGroup, 242	NeuronGroupValueType
neuron_populations	ModelSpec, 227
pygenn::genn_model::GeNNModel, 210	NeuronModels, 80
NeuronGroup, 243	neuronModels.cc, 388
addlnSyn, 245	IMPLEMENT_MODEL, 388, 389
addOutSyn, 246	neuronModels.h, 389
addSpkEventCondition, 246	SET_ADDITIONAL_INPUT_VARS, 391
checkNumDelaySlots, 246	SET_NEEDS_AUTO_REFRACTORY, 391
getClusterHostID, 246	SET_RESET_CODE, 391
getCurrentQueueOffset, 246	SET_SIM_CODE, 391
getCurrentSources, 246	SET_SUPPORT_CODE, 391
getDerivedParams, 246	SET_THRESHOLD_CONDITION_CODE, 391
getExtraGlobalParamLocation, 246, 247	NeuronModels::Base, 147
getInSyn, 247	getAdditionalInputVars, 148
getMergedInSyn, 247	getResetCode, 149
getName, 247	getSimCode, 149
getNeuronModel, 247	getSupportCode, 149
getNumDelaySlots, 247	getThresholdConditionCode, 149
getNumNeurons, 247	isAutoRefractoryRequired, 149
getOutSyn, 247	NeuronModels::Izhikevich, 215
getParams, 247	getInstance, 217
getPrevQueueOffset, 247	getParamNames, 217
getSpikeEventCondition, 248	getSimCode, 217
getSpikeEventLocation, 248	getThresholdConditionCode, 217
getSpikeLocation, 248	getVars, 217
getSpikeTimeLocation, 248	ParamValues, 216
getVarInitialisers, 248	PostVarValues, 216
getVarLocation, 248	PreVarValues, 216
hasOutputToHost, 248	VarValues, 217
initDerivedParams, 249	NeuronModels::IzhikevichVariable, 218
injectCurrent, 249	getInstance, 219
isDelayRequired, 249	getParamNames, 219
isInitRNGRequired, 249	getVars, 219
isParamRequiredBySpikeEventCondition, 249	ParamValues, 219
isSimRNGRequired, 249	PostVarValues, 219
isSpikeEventRequired, 249	PreVarValues, 219
isSpikeTimeRequired, 249	VarValues, 219
isTrueSpikeRequired, 249	NeuronModels::LIF, 220

getDerivedParams, 221	getSimCode, 293
getInstance, 221	getThresholdConditionCode, 293
getParamNames, 221	getVars, 293
getResetCode, 221	ParamValues, 292
getSimCode, 222	PostVarValues, 292
getThresholdConditionCode, 222	PreVarValues, 292
getVars, 222	SET_NEEDS_AUTO_REFRACTORY, 293
ParamValues, 221	VarValues, 292
PostVarValues, 221	NeuronModels::TraubMiles, 334
PreVarValues, 221	getInstance, 336
SET_NEEDS_AUTO_REFRACTORY, 222	getParamNames, 336
VarValues, 221	getSimCode, 337
NeuronModels::Poisson, 260	getThresholdConditionCode, 337
getExtraGlobalParams, 262	getVars, 337
getInstance, 262	ParamValues, 336
getParamNames, 262	PostVarValues, 336
getSimCode, 262	PreVarValues, 336
getThresholdConditionCode, 262	VarValues, 336
getVars, 262	NeuronModels::TraubMilesAlt, 337
ParamValues, 261	getInstance, 339
PostVarValues, 261	getSimCode, 339
PreVarValues, 261	ParamValues, 338
VarValues, 262	PostVarValues, 338
NeuronModels::PoissonNew, 263	PreVarValues, 338
getDerivedParams, 264	VarValues, 339
getInstance, 264	NeuronModels::TraubMilesFast, 339
getParamNames, 265	getInstance, 340
getSimCode, 265	getSimCode, 340
getThresholdConditionCode, 265	ParamValues, 340
getVars, 265	PostVarValues, 340
ParamValues, 264	PreVarValues, 340
PostVarValues, 264	VarValues, 340
PreVarValues, 264	NeuronModels::TraubMilesNStep, 341
SET_NEEDS_AUTO_REFRACTORY, 265	getInstance, 342
VarValues, 264	getParamNames, 342
NeuronModels::RulkovMap, 275	getSimCode, 342
• •	ParamValues, 342
getDerivedParams, 276	PostVarValues, 342
getInstance, 277	PreVarValues, 342
getParamNames, 277	VarValues, 342
getSimCode, 277	neuronSubstitutionsInSynapticCode
getThresholdConditionCode, 277	CodeGenerator, 73
getVars, 277	NormalDistribution
ParamValues, 276	SpineMLSimulator::ModelProperty::Normal ←
PostVarValues, 276	Distribution, 253
PreVarValues, 276	num_synapses
VarValues, 276	pygenn::genn_groups::SynapseGroup, 310
NeuronModels::SpikeSource, 289	numArguments
getInstance, 290	CodeGenerator::FunctionTemplate, 196
getThresholdConditionCode, 291	,,,,,,,, .
ParamValues, 290	OB
PostVarValues, 290	CodeGenerator::CodeStream::OB, 254
PreVarValues, 290	open
SET_NEEDS_AUTO_REFRACTORY, 291	SharedLibraryModel, 281
VarValues, 290	operator<<
NeuronModels::SpikeSourceArray, 291	CodeGenerator, 74
getExtraGlobalParams, 292	CodeGenerator::CodeStream, 165
getInstance, 293	operator+=
getResetCode, 293	CodeGenerator::MemAlloc, 223

operator=	PostVarValues
•	
CodeGenerator::FunctionTemplate, 196	CurrentSourceModels::DC, 176
ModelSpec, 235	CurrentSourceModels::GaussianNoise, 199
operator&	NeuronModels::Izhikevich, 216
synapseMatrixType.h, 401, 402	NeuronModels::IzhikevichVariable, 219
variableMode.h, 405	NeuronModels::LIF, 221
operator[]	NeuronModels::Poisson, 261
CodeGenerator::Substitutions, 305	NeuronModels::PoissonNew, 264
Models::VarInitContainerBase, 353	NeuronModels::RulkovMap, 276
Snippet::ValueBase, 347	NeuronModels::SpikeSource, 290
operator	NeuronModels::SpikeSourceArray, 292
synapseMatrixType.h, 402	NeuronModels::TraubMiles, 336
optimiser.cc, 391, 392	NeuronModels::TraubMilesAlt, 338
optimiser.h, 392, 393	
optimizeCode	NeuronModels::TraubMilesFast, 340
CodeGenerator::PreferencesBase, 271	NeuronModels::TraubMilesNStep, 342
CodeGeneratorFreierencesbase, 271	PostsynapticModels::DeltaCurr, 178
padSize	PostsynapticModels::ExpCond, 182
CodeGenerator::CUDA::Utils, 78	PostsynapticModels::ExpCurr, 184
param_space_to_val_vec	WeightUpdateModels::StaticPulseDendriticDelay
	302
pygenn::model_preprocessor, 91	postsyn
param_space_to_vals	pygenn::genn_groups::SynapseGroup, 313
pygenn::model_preprocessor, 91	PostsynapticModels, 81
ParamValVec	postsynapticModels.cc, 393
Snippet::Base, 151	IMPLEMENT_MODEL, 393
ParamValues	
CurrentSourceModels::DC, 176	postsynapticModels.h, 394
CurrentSourceModels::GaussianNoise, 199	SET_APPLY_INPUT_CODE, 394
NeuronModels::Izhikevich, 216	SET_CURRENT_CONVERTER_CODE, 394
NeuronModels::IzhikevichVariable, 219	SET_DECAY_CODE, 394
NeuronModels::LIF, 221	SET_SUPPORT_CODE, 395
NeuronModels::Poisson, 261	PostsynapticModels::Base, 152
NeuronModels::PoissonNew, 264	getApplyInputCode, 152
NeuronModels::RulkovMap, 276	getDecayCode, 152
NeuronModels::SpikeSource, 290	getSupportCode, 152
	PostsynapticModels::DeltaCurr, 177
NeuronModels::SpikeSourceArray, 292	getApplyInputCode, 178
NeuronModels::TraubMiles, 336	getInstance, 179
NeuronModels::TraubMilesAlt, 338	ParamValues, 178
NeuronModels::TraubMilesFast, 340	
NeuronModels::TraubMilesNStep, 342	PostVarValues, 178
PostsynapticModels::DeltaCurr, 178	PreVarValues, 178
PostsynapticModels::ExpCond, 182	VarValues, 178
PostsynapticModels::ExpCurr, 184	PostsynapticModels::ExpCond, 181
WeightUpdateModels::StaticPulseDendriticDelay,	getApplyInputCode, 182
302	getDecayCode, 182
parseCommandLine	getDerivedParams, 182
GenerateRunBase, 201	getInstance, 183
PoissonSpikeRate	getParamNames, 183
SpineMLSimulator::Input::PoissonSpikeRate, 266	ParamValues, 182
	PostVarValues, 182
pygenn::genn_groups::CurrentSource, 171	PreVarValues, 182
	VarValues, 182
pygenn::genn_groups::NeuronGroup, 242	
pygenn::genn_groups::SynapseGroup, 313	PostsynapticModels::ExpCurr, 183
post_var_space_to_vals	getApplyInputCode, 184
pygenn::model_preprocessor, 91	getDecayCode, 184
post_vars	getDerivedParams, 184
pygenn::genn_groups::SynapseGroup, 313	getInstance, 185
postNeuronSubstitutionsInSynapticCode	getParamNames, 185
CodeGenerator, 74	ParamValues, 184

D 3/ 3/1 404	
PostVarValues, 184	pullFromDevice
PreVarValues, 184	SpineMLSimulator::ModelProperty::Base, 163
VarValues, 184	pullModelPropertyFromDevice
pre_var_space_to_vals	SpineMLSimulator::LogOutput::AnalogueBase,
pygenn::model_preprocessor, 92	100
pre_vars	pullSpikesFromDevice
pygenn::genn_groups::SynapseGroup, 313	SharedLibraryModel, 282
preNeuronSubstitutionsInSynapticCode	pullStateFromDevice
CodeGenerator, 74	SharedLibraryModel, 282
PreVarValues	pullVarFromDevice
CurrentSourceModels::DC, 176	SharedLibraryModel, 282
CurrentSourceModels::GaussianNoise, 199	push
NeuronModels::Izhikevich, 216	SpineMLSimulator::StateVar, 297
NeuronModels::IzhikevichVariable, 219	push_connectivity_to_device
NeuronModels::LIF, 221	pygenn::genn_model::GeNNModel, 207
NeuronModels::Poisson, 261	push_current_spikes_to_device
NeuronModels::PoissonNew, 264	pygenn::genn_model::GeNNModel, 208
NeuronModels::RulkovMap, 276	push_spikes_to_device
NeuronModels::SpikeSource, 290	pygenn::genn_model::GeNNModel, 208
NeuronModels::SpikeSourceArray, 292	push_state_to_device
NeuronModels::TraubMiles, 336	pygenn::genn_model::GeNNModel, 208
NeuronModels::TraubMilesAlt, 338	push_var_to_device
NeuronModels::TraubMilesFast, 340	pygenn::genn_model::GeNNModel, 208
NeuronModels::TraubMilesNStep, 342	pushConnectivityToDevice
PostsynapticModels::DeltaCurr, 178	SharedLibraryModel, 282
PostsynapticModels::ExpCond, 182	PushCurrentSpikesFunc
PostsynapticModels::ExpCurr, 184	SpineMLSimulator::Input::SpikeBase, 287
WeightUpdateModels::StaticPulseDendriticDelay,	pushCurrentSpikesToDevice
302	SharedLibraryModel, 282
Preferences	pushExtraGlobalParam
CodeGenerator::CUDA::Preferences, 269	SharedLibraryModel, 283
prepare_model	pushSpikesToDevice
pygenn::model_preprocessor, 92	SharedLibraryModel, 283
prepare_snippet	pushStateToDevice
pygenn::model_preprocessor, 92	·
	SharedLibraryModel, 283
presynapticUpdateStrategy.cc, 395	pushToDevice
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395	pushToDevice SpineMLSimulator::ModelProperty::Base, 163
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201 pygenn.model_preprocessor, 90
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model, 82 pygenn.genn_model_GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model, 82 pygenn.genn_model_GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn.model_preprocessor.Variable, 350
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn.model_preprocessor.Variable, 350 pygenn:genn_groups
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn.model_preprocessor.Variable, 350 pygenn::genn_groups xrange, 82
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn.model_preprocessor.Variable, 350 pygenn::genn_groups xrange, 82 pygenn::genn_groups::CurrentSource
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device SharedLibraryModel, 281	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model, 82 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn.model_preprocessor.Variable, 350 pygenn::genn_groups xrange, 82 pygenn::genn_groups::CurrentSourceinit, 169
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pullConnectivityFromDevice SharedLibraryModel, 281 pullCurrentSpikesFromDevice	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model, 82 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn::genn_groups xrange, 82 pygenn::genn_groups::CurrentSourceinit, 169 add_extra_global_param, 169
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device SharedLibraryModel, 281 pullCurrentSpikesFromDevice SharedLibraryModel, 282	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model.GeNNModel, 201 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn::genn_groups xrange, 82 pygenn::genn_groups::CurrentSourceinit, 169 add_extra_global_param, 169 add_to, 170
presynapticUpdateStrategy.cc, 395 presynapticUpdateStrategy.h, 395 psm_vars pygenn::genn_groups::SynapseGroup, 313 pugi, 81 pull SpineMLSimulator::StateVar, 297 pull_connectivity_from_device pygenn::genn_model::GeNNModel, 207 pull_current_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_spikes_from_device pygenn::genn_model::GeNNModel, 207 pull_state_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pull_var_from_device pygenn::genn_model::GeNNModel, 207 pullConnectivityFromDevice SharedLibraryModel, 281 pullCurrentSpikesFromDevice	pushToDevice SpineMLSimulator::ModelProperty::Base, 163 pushVarToDevice SharedLibraryModel, 283 pygenn, 81 pygenn.genn_groups, 81 pygenn.genn_groups.CurrentSource, 168 pygenn.genn_groups.Group, 210 pygenn.genn_groups.NeuronGroup, 239 pygenn.genn_groups.SynapseGroup, 306 pygenn.genn_model, 82 pygenn.genn_model, 82 pygenn.model_preprocessor, 90 pygenn.model_preprocessor.ExtraGlobalVariable, 189 pygenn::genn_groups xrange, 82 pygenn::genn_groups::CurrentSourceinit, 169 add_extra_global_param, 169

pop, 171	set_pre_var, 311
reinitialise, 170	set_psm_var, 311
set_current_source_model, 170	set_sparse_connections, 312
size, 171	set_weight_update, 312
target_pop, 171	src, 313
pygenn::genn_groups::Group	synapse_order, 313
init, 211	trg, 314
extra_global_params, 212	w_update, 314
name, 212	weight_update_var_size, 312
set_var, 211	pygenn::genn_model
vars, 212	backend_modules, 89
pygenn::genn_groups::NeuronGroup	create_cmlf_class, 83
init, 240	create_custom_current_source_class, 83
add_extra_global_param, 240	create_custom_init_var_snippet_class, 84
add_to, 241	create_custom_model_class, 84
current_spikes, 241	create_custom_neuron_class, 85
delay_slots, 241	create_custom_postsynaptic_class, 86
is_spike_source_array, 242	create_custom_sparse_connect_init_snippet_
load, 241	class, 87
neuron, 242	create_custom_weight_update_class, 87
pop, 242	create_dpf_class, 88
reinitialise, 242	init_connectivity, 89
set_neuron, 242	init_var, 89
size, 242	m, 89
spike_count, 243	pygenn::genn_model::GeNNModel
spike_que_ptr, 243	init, 203
spikes, 243	add_current_source, 203
type, 243	add_neuron_population, 204 add_synapse_population, 204
pygenn::genn_groups::SynapseGroup init, 307	build, 205
add_extra_global_param, 308	current_sources, 210
add_to, 308	default sparse connectivity location, 205, 206
connections_set, 313	default_var_location, 206, 210
connectivity initialiser, 313	dT, 206, 210
get_sparse_post_inds, 308	end, 206
get_sparse_pre_inds, 308	load, 206
get_var_values, 308	model_name, 206, 207, 210
has individual postsynaptic vars, 309	neuron_populations, 210
has_individual_synapse_vars, 309	pull_connectivity_from_device, 207
ind, 313	pull current spikes from device, 207
is bitmask, 309	pull_spikes_from_device, 207
is_connectivity_init_required, 309	pull state from device, 207
is_dense, 309	pull_var_from_device, 207
is_ragged, 309	push connectivity to device, 207
load, 309	push_current_spikes_to_device, 208
matrix_type, 310	push_spikes_to_device, 208
max_row_length, 310	push_state_to_device, 208
num_synapses, 310	push_var_to_device, 208
pop, 313	reinitialise, 208
post_vars, 313	selected_gpu, 208, 210
postsyn, 313	step_time, 209
pre_vars, 313	synapse_populations, 210
psm_vars, 313	t, 209
reinitialise, 310	timestep, 209
row_lengths, 313	use_backend, 209, 210
set_connected_populations, 310	pygenn::model_preprocessor
set_post_syn, 311	genn_to_numpy_types, 93
set_post_var, 311	is_model_valid, 90

param_space_to_val_vec, 91	SET_ADDITIONAL_INPUT_VARS
param_space_to_vals, 91	neuronModels.h, 391
post_var_space_to_vals, 91	SET_APPLY_INPUT_CODE
pre_var_space_to_vals, 92	postsynapticModels.h, 394
prepare_model, 92	SET_CALC_MAX_COL_LENGTH_FUNC
prepare_snippet, 92	initSparseConnectivitySnippet.h, 374
var_space_to_vals, 93	InitSparseConnectivitySnippet::FixedProbability-
pygenn::model_preprocessor::ExtraGlobalVariable	Base, 194
init, 190	SET_CALC_MAX_ROW_LENGTH_FUNC
name, 191	initSparseConnectivitySnippet.h, 374
set_values, 190	InitSparseConnectivitySnippet::FixedProbability-
type, 191	Base, 194
values, 191	SET_CODE
view, 191	initVarSnippet.h, 377
pygenn::model_preprocessor::Variable	InitVarSnippet::Constant, 166
init, 350	InitVarSnippet::Exponential, 186
init_required, 351	InitVarSnippet::Gamma, 198
init_val, 351	InitVarSnippet::Normal, 253
name, 351	InitVarSnippet::Uniform, 344
needs_allocation, 351	SET_CURRENT_CONVERTER_CODE
set values, 351	postsynapticModels.h, 394
type, 351	SET_DECAY_CODE
values, 352	postsynapticModels.h, 394
view, 352	SET_DERIVED_PARAMS
- ,	snippet.h, 398
receive	SET EVENT CODE
SpineMLSimulator::NetworkClient, 239	weightUpdateModels.h, 407
record	SET_EVENT_THRESHOLD_CONDITION_CODE
AnalogueRecorder, 104	weightUpdateModels.h, 407
SpikeRecorder, 289	SET_EXTRA_GLOBAL_PARAMS
SpineMLSimulator::LogOutput::AnalogueExternal,	initSparseConnectivitySnippet.h, 374
101	models.h, 382
SpineMLSimulator::LogOutput::AnalogueFile, 102	SET_INJECTION_CODE
SpineMLSimulator::LogOutput::Base, 161	currentSourceModels.h, 365
SpineMLSimulator::LogOutput::Event, 181	CurrentSourceModels::DC, 177
recordInternal	CurrentSourceModels::GaussianNoise, 199
SpineMLSimulator::LogOutput::AnalogueExternal,	SET_LEARN_POST_CODE
101	weightUpdateModels.h, 407
SpineMLSimulator::LogOutput::AnalogueNetwork,	SET_LEARN_POST_SUPPORT_CODE
103	weightUpdateModels.h, 407
recordSpikes	SET_MAX_COL_LENGTH
SpikeWriterText, 295	initSparseConnectivitySnippet.h, 374
SpikeWriterTextCached, 296	InitSparseConnectivitySnippet::OneToOne, 255
regexFuncSubstitute	SET_MAX_ROW_LENGTH
CodeGenerator, 75	initSparseConnectivitySnippet.h, 375
regexVarSubstitute	InitSparseConnectivitySnippet::OneToOne, 255
-	SET_NEEDS_AUTO_REFRACTORY
CodeGenerator, 75	
RegularSpikeRate	neuronModels.h, 391
SpineMLSimulator::Input::RegularSpikeRate, 274 reinitialise	NeuronModels::LIF, 222
	NeuronModels::PoissonNew, 265
pygenn::genn_groups::CurrentSource, 170	NeuronModels::SpikeSource, 291
pygenn::genn_groups::NeuronGroup, 242	NeuronModels::SpikeSourceArray, 293
pygenn::genn_groups::SynapseGroup, 310	SET_NEEDS_POST_SPIKE_TIME
pygenn::genn_model::GeNNModel, 208	weightUpdateModels.h, 407
row_lengths	SET_NEEDS_PRE_SPIKE_TIME
pygenn::genn_groups::SynapseGroup, 313	weightUpdateModels.h, 407
runTools	SET_PARAM_NAMES
GenerateRunBase, 201	snippet.h, 398

SET_POST_SPIKE_CODE	pygenn::genn_groups::SynapseGroup, 311
weightUpdateModels.h, 408	set_pre_var
SET_POST_VARS	pygenn::genn_groups::SynapseGroup, 311
weightUpdateModels.h, 408	set_psm_var
SET_PRE_SPIKE_CODE	pygenn::genn_groups::SynapseGroup, 311
weightUpdateModels.h, 408	set_sparse_connections
SET_PRE_VARS	pygenn::genn_groups::SynapseGroup, 312
weightUpdateModels.h, 408	set_values
SET_RESET_CODE	pygenn::model_preprocessor::ExtraGlobal-
neuronModels.h, 391	Variable, 190
SET ROW BUILD CODE	pygenn::model_preprocessor::Variable, 351
initSparseConnectivitySnippet.h, 375	set var
InitSparseConnectivitySnippet::FixedProbability,	_
193	pygenn::genn_groups::Group, 211
	set_weight_update
InitSparseConnectivitySnippet::FixedProbability 105	pygenn::genn_groups::SynapseGroup, 312
NoAutapse, 195	setBackPropDelaySteps
InitSparseConnectivitySnippet::OneToOne, 255	SynapseGroup, 324
SET_ROW_BUILD_STATE_VARS	setDefaultExtraGlobalParamLocation
initSparseConnectivitySnippet.h, 375	ModelSpec, 235
$In it Sparse Connectivity Snippet :: Fixed Probability \leftarrow$	setDefaultNarrowSparseIndEnabled
Base, 194	ModelSpec, 235
SET_SIM_CODE	setDefaultSparseConnectivityLocation
neuronModels.h, 391	ModelSpec, 236
weightUpdateModels.h, 408	setDefaultVarLocation
SET_SIM_SUPPORT_CODE	ModelSpec, 236
weightUpdateModels.h, 408	setDendriticDelayLocation
SET_SUPPORT_CODE	SynapseGroup, 324
neuronModels.h, 391	setDT
postsynapticModels.h, 395	ModelSpec, 236
SET_SYNAPSE_DYNAMICS_CODE	setEventThresholdReTestRequired
weightUpdateModels.h, 408	SynapseGroup, 324
SET_SYNAPSE_DYNAMICS_SUPPORT_CODE	setExtraGlobalParamLocation
weightUpdateModels.h, 408	CurrentSource, 174
SET_THRESHOLD_CONDITION_CODE	NeuronGroup, 250
neuronModels.h, 391	setInSynVarLocation
SET_VARS	SynapseGroup, 325
models.h, 382	setMaxConnections
scalar	SynapseGroup, 325
SpineMLSimulator, 94	setMaxDendriticDelayTimesteps
ScalarBase	SynapseGroup, 325
SpineMLSimulator::InputValue::ScalarBase, 278	setMaxSourceConnections
scalarExpr	SynapseGroup, 325
ModelSpec, 235	setMergePostsynapticModels
Scope	ModelSpec, 236
CodeGenerator::CodeStream::Scope, 279	setName
selected_gpu	ModelSpec, 236
pygenn::genn_model::GeNNModel, 208, 210	setNarrowSparseIndEnabled
send	SynapseGroup, 325
SpineMLSimulator::NetworkClient, 239	setNumThreadsPerSpike
set_connected_populations	SynapseGroup, 325
pygenn::genn_groups::SynapseGroup, 310	setPSExtraGlobalParamLocation
set_current_source_model	SynapseGroup, 325
pygenn::genn_groups::CurrentSource, 170	setPSModelMergeTarget
set neuron	SynapseGroup, 326
pygenn::genn_groups::NeuronGroup, 242	setPSVarLocation
	SynapseGroup, 326
set_post_syn pygenn::genn_groups::SynapseGroup, 311	setPrecision
set post var	ModelSpec. 236

setSeed	pullConnectivityFromDevice, 281
ModelSpec, 236	pullCurrentSpikesFromDevice, 282
setSink	pullExtraGlobalParam, 282
CodeGenerator::CodeStream, 165	pullSpikesFromDevice, 282
setSpanType	pullStateFromDevice, 282
SynapseGroup, 326	pullVarFromDevice, 282
setSparseConnectivityExtraGlobalParamLocation	pushConnectivityToDevice, 282
SynapseGroup, 326	pushCurrentSpikesToDevice, 282
setSparseConnectivityLocation	pushExtraGlobalParam, 283
SynapseGroup, 326	pushSpikesToDevice, 283
setSpikeEventLocation	pushStateToDevice, 283
NeuronGroup, 250	pushVarToDevice, 283
setSpikeLocation	setTime, 283
NeuronGroup, 250	setTimestep, 283
setSpikeTimeLocation	
•	SharedLibraryModel, 280
NeuronGroup, 250	stepTime, 283
setTime	SharedLibraryModel< scalar >, 279
SharedLibraryModel, 283	sharedLibraryModel.h, 396
setTimePrecision	shouldAccumulateInRegister
ModelSpec, 237	CodeGenerator::CUDA::PresynapticUpdate
setTimestep	Strategy::Base, 154
SharedLibraryModel, 283	CodeGenerator::CUDA::PresynapticUpdate ←
setTiming	Strategy::PostSpan, 268
ModelSpec, 237	CodeGenerator::CUDA::PresynapticUpdate ←
setValue	Strategy::PreSpan, 273
SpineMLSimulator::ModelProperty::Exponential ←	shouldAccumulateInSharedMemory
Distribution, 187	CodeGenerator::CUDA::PresynapticUpdate ←
SpineMLSimulator::ModelProperty::Fixed, 192	Strategy::Base, 154
SpineMLSimulator::ModelProperty::Normal←	CodeGenerator::CUDA::PresynapticUpdate←
Distribution, 253	Strategy::PostSpan, 268
SpineMLSimulator::ModelProperty::Uniform←	CodeGenerator::CUDA::PresynapticUpdate←
Distribution, 344	Strategy::PreSpan, 273
SpineMLSimulator::ModelProperty::ValueList, 348	shouldApply
setVarLocation	SpineMLSimulator::Input::Base, 159
CurrentSource, 174	shouldRecord
NeuronGroup, 250	SpineMLSimulator::LogOutput::Base, 161
setWUExtraGlobalParamLocation	showPtxInfo
SynapseGroup, 326	CodeGenerator::CUDA::Preferences, 270
setWUPostVarLocation	Simulator
SynapseGroup, 326	SpineMLSimulator::Simulator, 284
setWUPreVarLocation	simulator.cc, 396
SynapseGroup, 327 setWUVarLocation	simulator.h, 396
	singlePrecisionTemplate
SynapseGroup, 327	CodeGenerator::FunctionTemplate, 197
SharedLibraryModel	size
~SharedLibraryModel, 280	pygenn::genn_groups::CurrentSource, 171
allocateExtraGlobalParam, 280	pygenn::genn_groups::NeuronGroup, 242
allocateMem, 280	Snippet, 94
freeExtraGlobalParam, 280	snippet.h, 397
freeMem, 280	DECLARE_SNIPPET, 398
getArray, 280	IMPLEMENT_SNIPPET, 398
getScalar, 281	SET_DERIVED_PARAMS, 398
getSymbol, 281	SET_PARAM_NAMES, 398
getTime, 281	Snippet::Base, 150
getTimestep, 281	\sim Base, 151
initialize, 281	DerivedParamVec, 150
initializeSparse, 281	EGPVec, 151
open, 281	getDerivedParams, 151

getNamedVecIndex, 151	scalar, 94
getParamNames, 151	SpineMLSimulator::Connectors, 95
ParamValVec, 151	create, 95
StringVec, 151	SpineMLSimulator::Input, 95
Snippet::Base::DerivedParam, 179	SpineMLSimulator::Input::Analogue, 98
func, 179	Analogue, 98
name, 179	apply, 98
Snippet::Base::EGP, 179	SpineMLSimulator::Input::Base, 158
name, 180	∼Base, 158
type, 180	apply, 159
Snippet::Base::ParamVal, 256	Base, 158
name, 256	shouldApply, 159
type, 256	updateValues, 159
value, 256	SpineMLSimulator::Input::InterSpikeIntervalBase, 214
Snippet::Init	apply, 215
getDerivedParams, 213	getTimeToSpike, 215
getParams, 213	InterSpikeIntervalBase, 214
getSnippet, 213	SpineMLSimulator::Input::PoissonSpikeRate, 265
Init, 213	getTimeToSpike, 266
initDerivedParams, 213	PoissonSpikeRate, 266
Snippet::Init< SnippetBase >, 213	SpineMLSimulator::Input::RegularSpikeRate, 274
Snippet::ValueBase	getTimeToSpike, 274
getValues, 347	RegularSpikeRate, 274
operator[], 347	SpineMLSimulator::Input::SpikeBase, 286
ValueBase, 346	injectSpike, 287
Snippet::ValueBase< 0 >, 347	PushCurrentSpikesFunc, 287
getValues, 347	SpikeBase, 287
ValueBase, 347	uploadSpikes, 287
Snippet::ValueBase< NumVars >, 346	SpineMLSimulator::Input::SpikeTime, 294
SpanType	apply, 294
SynapseGroup, 317	SpikeTime, 294
spike_count	SpineMLSimulator::InputValue, 95
pygenn::genn_groups::NeuronGroup, 243	create, 96
spike_que_ptr	SpineMLSimulator::InputValue::Base, 159
pygenn::genn_groups::NeuronGroup, 243	\sim Base, 160
SpikeBase	Base, 160
SpineMLSimulator::Input::SpikeBase, 287	getNumNeurons, 160
SpikeRecorder	getTargetIndices, 160
GetCurrentSpikeCountFunc, 288	update, 160
GetCurrentSpikesFunc, 288	SpineMLSimulator::InputValue::Constant, 166
getSum, 289	Constant, 167
record, 289	update, 167
SpikeRecorder, 289	SpineMLSimulator::InputValue::ConstantArray, 167
SpikeRecorder< Writer >, 288	ConstantArray, 168
spikeRecorder.h, 398	update, 168
SpikeTime	SpineMLSimulator::InputValue::External, 187
SpineMLSimulator::Input::SpikeTime, 294	External, 187
SpikeWriterText, 295	getBuffer, 188
recordSpikes, 295	getBufferBegin, 188
SpikeWriterText, 295	getBufferEnd, 188
SpikeWriterTextCached, 295	getSize, 188
~SpikeWriterTextCached, 296	update, 188
recordSpikes, 296	updateInternal, 188
SpikeWriterTextCached, 296	SpineMLSimulator::InputValue::ExternalNetwork, 188
writeCache, 296	ExternalNetwork, 189
spikes	updateInternal, 189
pygenn::genn_groups::NeuronGroup, 243	SpineMLSimulator::InputValue::ScalarBase, 278
SpineMLSimulator, 94	applyScalar, 278

ScalarBase, 278	SpineMLSimulator::ModelProperty::ValueList, 348
SpineMLSimulator::InputValue::TimeVarying, 332	setValue, 348
TimeVarying, 333	ValueList, 348
update, 333	SpineMLSimulator::NetworkClient, 237
SpineMLSimulator::InputValue::TimeVaryingArray, 333	\sim NetworkClient, 239
TimeVaryingArray, 334	connect, 239
update, 334	DataType, 238
SpineMLSimulator::LogOutput, 96	Mode, 238
SpineMLSimulator::LogOutput::AnalogueBase, 99	NetworkClient, 238
AnalogueBase, 99	receive, 239
getIndices, 99	send, 239
getModelPropertySize, 99	SpineMLSimulator::Simulator, 284
getStateVarBegin, 100	\sim Simulator, 284
getStateVarEnd, 100	calcNumTimesteps, 285
pullModelPropertyFromDevice, 100	getDT, 285
SpineMLSimulator::LogOutput::AnalogueExternal, 100	getDurationMs, 285
AnalogueExternal, 100	getExternalInput, 285
record, 101	getExternalLogger, 285
recordInternal, 101	getInitSparseTime, 285
SpineMLSimulator::LogOutput::AnalogueFile, 101	getInitTime, 285
AnalogueFile, 102	getInputMs, 285
record, 102	getLogMs, 286
SpineMLSimulator::LogOutput::AnalogueNetwork, 102	getNeuronUpdateTime, 286
AnalogueNetwork, 103	getPostsynapticUpdateTime, 286
recordInternal, 103	getPresynapticUpdateTime, 286
SpineMLSimulator::LogOutput::Base, 160	getSimulateMs, 286
\sim Base, 161	getSynapseDynamicsTime, 286
Base, 161	load, 286
getEndTimestep, 161	Simulator, 284
record, 161	stepTime, 286
shouldRecord, 161	SpineMLSimulator::StateVar
SpineMLSimulator::LogOutput::Event, 180	get, 297
Event, 180	isAccessible, 297
record, 181	m_Direct, 298
SpineMLSimulator::ModelProperty, 96	m_Indirect, 298
create, 96	pull, 297
SpineMLSimulator::ModelProperty::Base, 162	push, 297
\sim Base, 162	StateVar, 297
Base, 162	SpineMLSimulator::StateVar< T >, 296
getHostStateVar, 162	SpineMLSimulator::Timer, 329
getSize, 163	\sim Timer, 330
pullFromDevice, 163	get, 330
pushToDevice, 163	Timer, 329
SpineMLSimulator::ModelProperty::Exponential ←	SpineMLSimulator::TimerAccumulate, 332
Distribution, 186	\sim TimerAccumulate, 332
ExponentialDistribution, 186	get, 332
setValue, 187	TimerAccumulate, 332
SpineMLSimulator::ModelProperty::Fixed, 191	src
Fixed, 191	pygenn::genn_groups::SynapseGroup, 313
setValue, 192	StateVar
SpineMLSimulator::ModelProperty::NormalDistribution,	SpineMLSimulator::StateVar, 297
253	stateVar.h, 399
NormalDistribution, 253	step_time
setValue, 253	pygenn::genn_model::GeNNModel, 209
SpineMLSimulator::ModelProperty::UniformDistribution,	stepTime
344	SharedLibraryModel, 283
setValue, 344	SpineMLSimulator::Simulator, 286
UniformDistribution, 344	StringVec

Snippet::Base, 151	isSpikeEventRequired, 324
substitute	isTrueSpikeRequired, 324
CodeGenerator, 75	isWUInitRNGRequired, 324
Substitutions	isWUVarInitRequired, 324
CodeGenerator::Substitutions, 304	isZeroCopyEnabled, 324
substitutions.h, 399	setBackPropDelaySteps, 324
synapse_order	setDendriticDelayLocation, 324
pygenn::genn_groups::SynapseGroup, 313	setEventThresholdReTestRequired, 324
synapse_populations	setInSynVarLocation, 325
pygenn::genn_model::GeNNModel, 210	setMaxConnections, 325
SynapseGroup, 314	setMaxDendriticDelayTimesteps, 325
getBackPropDelaySteps, 318	setMaxSourceConnections, 325
getClusterHostID, 318	setNarrowSparseIndEnabled, 325
getConnectivityInitialiser, 318	setNumThreadsPerSpike, 325
getDelaySteps, 318	setPSExtraGlobalParamLocation, 325
getDendriticDelayLocation, 318	setPSModelMergeTarget, 326
getDendriticDelayCocation, 516 getDendriticDelayOffset, 318	setPSVarLocation, 326
getInSynLocation, 318	setSpanType, 326
getMatrixType, 318	setSparseConnectivityExtraGlobalParamLocation,
getMaxConnections, 319	326
•	setSparseConnectivityLocation, 326
getMaxDendriticDelayTimesteps, 319	setWUExtraGlobalParamLocation, 326
getMaxSourceConnections, 319	setWUPostVarLocation, 326
getName, 319	setWUPreVarLocation, 327
getNumThreadsPerSpike, 319	setWUVarLocation, 327
getPSConstInitVals, 319	SpanType, 317
getPSDerivedParams, 319	SynapseGroup, 317
getPSExtraGlobalParamLocation, 319, 320	synapseGroup.cc, 399
getPSModel, 320	synapseGroup.h, 399
getPSModelTargetName, 320	SynapseGroupHandler
getPSParams, 320	CodeGenerator::BackendBase, 132
getPSVarInitialisers, 320	
getPSVarLocation, 320	SynapseGroupInternal, 327
getPostsynapticBackPropDelaySlot, 319	SynapseGroupInternal, 327
getPresynapticAxonalDelaySlot, 319	synapseGroupValuaTina
getSpanType, 320	SynapseGroupValueType
get Sparse Connectivity Extra Global Param Location,	ModelSpec, 227
320, 321	SynapseMatrixConnectivity
getSparseConnectivityLocation, 321	synapseMatrixType.h, 401
getSparseIndType, 321	SynapseMatrixType
getSrcNeuronGroup, 321	synapseMatrixType.h, 401
getTrgNeuronGroup, 321	synapseMatrixType.h, 400
getWUConstInitVals, 321	operator&, 401, 402
getWUDerivedParams, 321	operator , 402
getWUExtraGlobalParamLocation, 322	SynapseMatrixConnectivity, 401
getWUModel, 322	SynapseMatrixType, 401
getWUParams, 322	SynapseMatrixWeight, 401
getWUPostVarInitialisers, 322	SynapseMatrixWeight
getWUPostVarLocation, 322	synapseMatrixType.h, 401
getWUPreVarInitialisers, 322	t
getWUPreVarLocation, 322, 323	pygenn::genn_model::GeNNModel, 209
getWUVarInitialisers, 323	TYPE
getWUVarLocation, 323	
initDerivedParams, 323	backendBase.cc, 358
	target_pop
isDendriticDelayRequired, 323	pygenn::genn_groups::CurrentSource, 171
isEventThresholdReTestRequired, 323	TeeBuf
isPSInitRNGRequired, 323	CodeGenerator::TeeBuf, 328
isPSModelMerged, 323	TeeStream
isSparseConnectivityInitRequired, 324	CodeGenerator::TeeStream, 329

teeStream.h, 402	use_backend
TimePrecision	pygenn::genn_model::GeNNModel, 209, 210
modelSpec.h, 384	userCxxFlagsGNU
TimeVarying	CodeGenerator::PreferencesBase, 271
SpineMLSimulator::InputValue::TimeVarying, 333	userNvccFlags
TimeVaryingArray	CodeGenerator::CUDA::Preferences, 270
SpineMLSimulator::InputValue::TimeVaryingArray,	userNvccFlagsGNU
334 Ti	CodeGenerator::PreferencesBase, 272
Timer, 330	Utils, 97
∼Timer, 330	getUnderlyingType, 97
get, 331	isInitRNGRequired, 97
SpineMLSimulator::Timer, 329	isRNGRequired, 97
Timer, 330	isTypePointer, 97
timer.h, 402, 403	utils.h, 403
TimerAccumulate, 331	CHECK_CU_ERRORS, 403
~TimerAccumulate, 331	CHECK_CUDA_ERRORS, 403
get, 331	value
SpineMLSimulator::TimerAccumulate, 332	Snippet::Base::ParamVal, 256
TimerAccumulate, 331	ValueBase
timestep	Snippet::ValueBase, 346
pygenn::genn_model::GeNNModel, 209	Snippet::ValueBase $< 0 >$, 347
trg pygenn::genn_groups::SynapseGroup, 314	ValueList
	SpineMLSimulator::ModelProperty::ValueList, 348
Models::Base::Var, 350	values
pygenn::genn_groups::NeuronGroup, 243	pygenn::model_preprocessor::ExtraGlobal↔
pygenn::model_preprocessor::ExtraGlobal⇔	Variable, 191
Variable, 191	pygenn::model_preprocessor::Variable, 352
pygenn::model_preprocessor::Variable, 351	Var
Snippet::Base::EGP, 180	Models::Base::Var, 349
Snippet::Base::ParamVal, 256	var_space_to_vals
ompotibacom aramvai, 200	pygenn::model_preprocessor, 93
UniformDistribution	VarAccess
SpineMLSimulator::ModelProperty::Uniform←	models.h, 382
Distribution, 344	VarInit
uninitialisedConnectivity	Models::VarInit, 352
modelSpec.h, 386	VarInitContainerBase
uninitialisedVar	Models::VarInitContainerBase, 353
modelSpec.h, 386	Models::VarInitContainerBase< 0 >, 354
update	VarLocation
SpineMLSimulator::InputValue::Base, 160	variableMode.h, 404
SpineMLSimulator::InputValue::Constant, 167	VarValues
SpineMLSimulator::InputValue::ConstantArray, 168	CurrentSourceModels::DC, 177
SpineMLSimulator::InputValue::External, 188	CurrentSourceModels::GaussianNoise, 199
SpineMLSimulator::InputValue::TimeVarying, 333	NeuronModels::Izhikevich, 217
SpineMLSimulator::InputValue::TimeVaryingArray,	NeuronModels::IzhikevichVariable, 219
334	NeuronModels::LIF, 221
updateInternal	NeuronModels::Poisson, 262
SpineMLSimulator::InputValue::External, 188	NeuronModels::PoissonNew, 264
SpineMLSimulator::InputValue::ExternalNetwork,	NeuronModels::RulkovMap, 276
189	NeuronModels::SpikeSource, 290
updatePostVarQueues	NeuronModels::SpikeSourceArray, 292
NeuronGroup, 251	NeuronModels::TraubMiles, 336
updatePreVarQueues	NeuronModels::TraubMilesAlt, 339
NeuronGroup, 251	NeuronModels::TraubMilesFast, 340
updateValues	NeuronModels::TraubMilesNStep, 342
SpineMLSimulator::Input::Base, 159	PostsynapticModels::DeltaCurr, 178
uploadSpikes	PostsynapticModels::ExpCond, 182
SpineMLSimulator::Input::SpikeBase, 287	PostsynapticModels::ExpCurr, 184

WeightUpdateModels::StaticPulseDendriticDelay,	getLearnPostCode, 259
302	getParamNames, 259
VarVec	getSimCode, 259
Models::Base, 146	getVars, 259
variableMode.h, 404	isPostSpikeTimeRequired, 259
operator&, 405	isPreSpikeTimeRequired, 260
VarLocation, 404	WeightUpdateModels::StaticGraded, 298
vars	DECLARE_WEIGHT_UPDATE_MODEL, 299
pygenn::genn_groups::Group, 212	getEventCode, 299
view	getEventThresholdConditionCode, 299
pygenn::model_preprocessor::ExtraGlobal ↔	getParamNames, 299
Variable, 191	getVars, 300
pygenn::model_preprocessor::Variable, 352	WeightUpdateModels::StaticPulse, 300
pygeriiiiiiodei_preprocessorvariable, 332	DECLARE_WEIGHT_UPDATE_MODEL, 301
w_update	getSimCode, 301
pygenn::genn_groups::SynapseGroup, 314	
weight_update_var_size	getVars, 301
pygenn::genn_groups::SynapseGroup, 312	WeightUpdateModels::StaticPulseDendriticDelay, 301
WeightUpdateModels, 97	getInstance, 303
weightUpdateModels.cc, 405	getSimCode, 303
•	getVars, 303
IMPLEMENT_MODEL, 405	ParamValues, 302
weightUpdateModels.h, 405	PostVarValues, 302
DECLARE_WEIGHT_UPDATE_MODEL, 406	PreVarValues, 302
SET_EVENT_CODE, 407	VarValues, 302
SET_EVENT_THRESHOLD_CONDITION_CODE,	writeCache
407	SpikeWriterTextCached, 296
SET_LEARN_POST_CODE, 407	writePreciseString
SET_LEARN_POST_SUPPORT_CODE, 407	CodeGenerator, 75
SET_NEEDS_POST_SPIKE_TIME, 407	writeSizes
SET_NEEDS_PRE_SPIKE_TIME, 407	GenerateRunBase, 201
SET_POST_SPIKE_CODE, 408	
SET_POST_VARS, 408	xrange
SET_PRE_SPIKE_CODE, 408	pygenn::genn_groups, 82
SET_PRE_VARS, 408	
SET_SIM_CODE, 408	zero
SET_SIM_SUPPORT_CODE, 408	CodeGenerator::MemAlloc, 224
SET_SYNAPSE_DYNAMICS_CODE, 408	zeroCopy
SET_SYNAPSE_DYNAMICS_SUPPORT_CODE,	CodeGenerator::MemAlloc, 224
408	zeroCopyInUse
WeightUpdateModels::Base, 154	ModelSpec, 237
getEventCode, 155	
getEventThresholdConditionCode, 156	
getLearnPostCode, 156	
getLearnPostSupportCode, 156	
getPostSpikeCode, 156	
getPostVarIndex, 156	
getPostVars, 156	
getPreSpikeCode, 156	
getPreVarIndex, 157	
getPreVars, 157	
getSimCode, 157	
getSimSupportCode, 157	
getSynapseDynamicsCode, 157	
getSynapseDynamicsSuppportCode, 157	
isPostSpikeTimeRequired, 157	
isPreSpikeTimeRequired, 158	
WeightUpdateModels::PiecewiseSTDP, 256	
DECLARE_WEIGHT_UPDATE_MODEL, 258	
getDerivedParams, 259	