1 GeNN Documentation 1

## 1 GeNN Documentation

GeNN is a software package to enable neuronal network simulations on NVIDIA GPUs by code generation. Models are defined in a simple C-style API and the code for running them on either GPU or CPU hardware is generated by GeNN. GeNN can also be used through external interfaces. Currently there are interfaces for SpineML and SpineCreator and for Brian via Brian2GeNN.

GeNN is currently developed and maintained by

```
Dr James Knight (contact James)

James Turner (contact James)

Prof. Thomas Nowotny (contact Thomas)
```

Project homepage is http://genn-team.github.io/genn/.

The development of GeNN is partially supported by the EPSRC (grant numbers EP/P006094/1 - Brains on Board and EP/J019690/1 - Green Brain Project).

Note

This documentation is under construction. If you cannot find what you are looking for, please contact the project developers.

Next

# 2 Installation

You can download GeNN either as a zip file of a stable release or a snapshot of the most recent stable version or the unstable development version using the Git version control system.

# 2.1 Downloading a release

Point your browser to https://github.com/genn-team/genn/releases and download a release from the list by clicking the relevant source code button. Note that GeNN is only distributed in the form of source code due to its code generation design. Binary distributions would not make sense in this framework and are not provided. After downloading continue to install GeNN as described in the Installing GeNN section below.

# 2.2 Obtaining a Git snapshot

If it is not yet installed on your system, download and install Git (http://git-scm.com/). Then clone the GeNN repository from Github

```
git clone https://github.com/genn-team/genn.git
```

The github url of GeNN in the command above can be copied from the HTTPS clone URL displayed on the GeNN Github page (https://github.com/genn-team/genn).

This will clone the entire repository, including all open branches. By default git will check out the master branch which contains the source version upon which the next release will be based. There are other branches in the repository that are used for specific development purposes and are opened and closed without warning.

As an alternative to using git you can also download the full content of GeNN sources clicking on the "Download ZIP" button on the bottom right of the GeNN Github page (https://github.com/genn-team/genn).

# 2.3 Installing GeNN

Installing GeNN comprises a few simple steps to create the GeNN development environment.

Note

While GeNN models are normally simulated using CUDA on NVIDIA GPUs, if you want to use GeNN on a machine without an NVIDIA GPU, you can skip steps v and vi and use GeNN in "CPU\_ONLY" mode.

- (i) If you have downloaded a zip file, unpack GeNN.zip in a convenient location. Otherwise enter the directory where you downloaded the Git repository.
- (ii) Add GeNN's "bin" directory to your path, e.g. if you are running Linux or Mac OS X and extracted/downloaded GeNN to \$HOME/GeNN, then you can add:

```
export PATH=$PATH:$HOME/GeNN/bin
```

to your login script (e.g. .profile or .bashrc. If you are using WINDOWS, the path should be a windows path as it will be interpreted by the Visual C++ compiler cl, and environment variables are best set using SETX in a Windows cmd window. To do so, open a Windows cmd window by typing cmd in the search field of the start menu, followed by the enter key. In the cmd window type:

```
setx PATH "C:\Users\me\GeNN\bin; %PATH%"
```

where C:\Users\me\GeNN is the path to your GeNN directory.

- (iv) Install the C++ compiler on the machine, if not already present. For Windows, download Microsoft Visual Studio Community Edition from https://www.visualstudio.com/en-us/downloads/download-visual-studio-vs.4 aspx. When installing Visual Studio, one should select the 'Desktop development with C++' configuration' and the 'Windows 8.1 SDK' and 'Windows Universal CRT' individual components. Mac users should download and set up Xcode from https://developer.apple.com/xcode/index.html Linux users should install the GNU compiler collection gcc and g++ from their Linux distribution repository, or alternatively from https://gcc.compu.org/index.html Be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (v) If your machine has a GPU and you haven't installed CUDA already, obtain a fresh installation of the NVIDIA C← UDA toolkit from https://developer.nvidia.com/cuda-downloads Again, be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (vi) Set the CUDA\_PATH variable if it is not already set by the system, by putting

```
export CUDA_PATH=/usr/local/cuda
```

in your login script (or, if CUDA is installed in a non-standard location, the appropriate path to the main CUDA directory). For most people, this will be done by the CUDA install script and the default value of /usr/local/cuda is fine. In Windows, CUDA\_PATH is normally already set after installing the CUDA toolkit. If not, set this variable with:

```
setx CUDA_PATH C:\path\to\cuda
```

This normally completes the installation. Windows useres must close and reopen their command window to ensure variables set using SETX are initialised.

If you are using GeNN in Windows, the Visual Studio development environment must be set up within every instance of the CMD.EXE command window used. One can open an instance of CMD.EXE with the development environment already set up by navigating to Start - All Programs - Microsoft Visual Studio - Visual Studio Tools - x64 Native Tools Command Prompt. You may wish to create a shortcut for this tool on the desktop, for convenience.

```
Top | Next
```

3 Quickstart

# 3 Quickstart

GeNN is based on the idea of code generation for the involved GPU or CPU simulation code for neuronal network models but leaves a lot of freedom how to use the generated code in the final application. To facilitate the use of GeNN on the background of this philosophy, it comes with a number of complete examples containing both the model description code that is used by GeNN for code generation and the "user side code" to run the generated model and safe the results. Some of the example models such as the Insect olfaction model use an <code>generate\_\infty</code> run executable which automates the building and simulation of the model. Using these executables, running these complete examples should be achievable in a few minutes. The necessary steps are described below.

## 3.1 Running an Example Model

#### 3.1.1 Unix

In order to build the <code>generate\_run</code> executable as well as any additional tools required for the model, open a shell and navigate to the <code>userproject/MBody1\_project</code> directory. Then type

make

to generate an executable that you can invoke with

```
./generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU\_ONLY mode, you can instead invoke this executable with

```
./generate_run --cpu-only test1
```

# 3.1.2 Windows

While GeNN can be used from within Visual Studio, in this example we will use a <code>cmd</code> window. Open a Visual Studio <code>cmd</code> window via Start: All Programs: Visual Studio: Tools: x86 Native Tools Command Prompt, and navigate to the <code>userproject\tools</code> directory. Then compile the additional tools and the <code>generate\_run</code> executable for creating and running the project:

```
msbuild ..\userprojects.sln /t:generate_mbody1_runner /p:Configuration=Release
```

to generate an executable that you can invoke with

```
generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU\_ONLY mode, you can instead invoke this executable with

```
generate_run --cpu-only test1
```

## 3.1.3 Visualising results

These steps will build and simulate a model of the locust olfactory system with default parameters of 100 projection neurons, 1000 Kenyon cells, 20 lateral horn interneurons and 100 output neurons in the mushroom body lobes.

Note

If the model isn't build in CPU\_ONLY mode it will be simulated on an automatically chosen GPU.

The generate\_run tool generates input patterns and writes them to file, compiles and runs the model using these files as inputs and finally output the resulting spiking activity. For more information of the options passed to this command see the Insect olfaction model section. The results of the simulation can be plotted with

```
python plot.py test1
```

The MBody1 example is already a highly integrated example that showcases many of the features of GeNN and how to program the user-side code for a GeNN application. More details in the User Manual .

# 3.2 How to use GeNN for New Projects

Creating and running projects in GeNN involves a few steps ranging from defining the fundamentals of the model, inputs to the model, details of the model like specific connectivity matrices or initial values, running the model, and analyzing or saving the data.

GeNN code is generally created by passing the C++ model file (see below) directly to the genn-buildmodel script. Another way to use GeNN is to create or modify a script or executable such as  $userproject/MBody1\_\leftrightarrow project/generate\_run.cc$  that wraps around the other programs that are used for each of the steps listed above. In more detail, the GeNN workflow consists of:

- 1. Either use external programs to generate connectivity and input files to be loaded into the user side code at runtime or generate these matrices directly inside the user side code.
- 2. Generating the model simulation code using <code>genn-buildmodel.sh</code> (On Linux or Mac) or <code>genn-buildmodel.bat</code> (on Windows). For example, inside the <code>generate\_run</code> engine used by the MBody1\_project, the following command is executed on Linux:

```
genn-buildmodel.sh MBodyl.cc
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU\_ONLY mode, the following command is executed:

```
genn-buildmodel.sh -c MBody1.cc
```

The genn-buildmodel script compiles the GeNN code generator in conjunction with the user-provided model description model/MBodyl.cc. It then executes the GeNN code generator to generate the complete model simulation code for the model.

3. Provide a build script to compile the generated model simulation and the user side code into a simulator executable (in the case of the MBody1 example this consists the file MBody1Sim.cc). On Linux or Mac a suitable GNU makefile can be created by running:

```
{\tt genn-create-user-project.sh~MBody1~MBody1Sim.cc}
```

And on Windows an MSBuild project can be created by running:

```
genn-create-user-project.bat MBody1 MBody1Sim.cc
```

4. Compile the simulator executable by invoking GNU make on Linux or Mac:

```
make clean all
```

or MSbuild on Windows:

```
msbuild MBody1.sln /t:MBody1 /p:Configuration=Release
```

5. Finally, run the resulting stand-alone simulator executable. In the MBody1 example, this is called MBody1 on Linux and MBody1\_Release.exe on Windows.

# 3.3 Defining a New Model in GeNN

According to the work flow outlined above, there are several steps to be completed to define a neuronal network model.

- 1. The neuronal network of interest is defined in a model definition file, e.g. Example1.cc.
- 2. Within the the model definition file Example1.cc, the following tasks need to be completed:
  - a) The GeNN file modelSpec.h needs to be included,

```
#include "modelSpec.h"
```

b) The values for initial variables and parameters for neuron and synapse populations need to be defined, e.g.

would define the (homogeneous) parameters for a population of Poisson neurons.

#### Note

The number of required parameters and their meaning is defined by the neuron or synapse type. Refer to the User Manual for details. We recommend, however, to use comments like in the above example to achieve maximal clarity of each parameter's meaning.

If heterogeneous parameter values are required for a particular population of neurons (or synapses), they need to be defined as "variables" rather than parameters. See the User Manual for how to define new neuron (or synapse) types and the Defining a new variable initialisation snippet section for more information on initialising these variables to hetererogenous values.

c) The actual network needs to be defined in the form of a function modelDefinition, i.e.

```
void modelDefinition(ModelSpec &model);
```

#### Note

The name modelDefinition and its parameter of type ModelSpec& are fixed and cannot be changed if GeNN is to recognize it as a model definition.

d) Inside modelDefinition(), The time step DT needs to be defined, e.g.

```
model.setDT(0.1);
```

#### Note

All provided examples and pre-defined model elements in GeNN work with units of mV, ms, nF and muS. However, the choice of units is entirely left to the user if custom model elements are used.

MBody1.cc shows a typical example of a model definition function. In its core it contains calls to Model← Spec::addNeuronPopulation and ModelSpec::addSynapsePopulation to build up the network. For a full range of options for defining a network, refer to the User Manual.

- 3. The programmer defines their own "user-side" modeling code similar to the code in userproject/M↔ Body1\_project/model/MBody1Sim.cc. In this code,
  - a) They manually define the connectivity matrices between neuron groups. Refer to the Synaptic matrix types section for the required format of connectivity matrices for dense or sparse connectivities.
  - b) They define input patterns (e.g. for Poisson neurons like in the MBody1 example) or individual initial values for neuron and / or synapse variables.

Note

The initial values given in the modelDefinition are automatically applied homogeneously to every individual neuron or synapse in each of the neuron or synapse groups.

- c) They use stepTime () to run one time step on either the CPU or GPU depending on the options passed to genn-buildmodel.
- d) They use functions like <code>copyStateFromDevice()</code> etc to transfer the results from GPU calculations to the main memory of the host computer for further processing.
- e) They analyze the results. In the most simple case this could just be writing the relevant data to output files.

## Previous | Top | Next

# 4 Examples

for Windows users, or:

GeNN comes with a number of complete examples. At the moment, there are seven such example projects provided with GeNN.

# 4.1 Single compartment Izhikevich neuron(s)

```
Izhikevich neuron(s) without any connections
This is a minimal example, with only one neuron population (with more or less
neurons depending on the command line, but without any synapses). The neurons
are Izhikevich neurons with homogeneous parameters across the neuron population.
This example project contains a helper executable called "generate_run",
which compiles and executes the model.
To compile it, navigate to genn/userproject/OneComp_project and type:
msbuild ..\userprojects.sln /t:generate one comp runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-neurons: Number of neurons to simulate (defaults to 1)
For a first minimal test, using these defaults and recording results with a base name of 'test', the system may
generate_run.exe test
```

```
./generate_run test

for Linux, Mac and other UNIX users.

This would create a set of tonic spiking Izhikevich neurons with no connectivity, receiving a constant identical 4 nA input.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and 4 neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=4 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=4 test

for Linux, Mac and other UNIX users.
```

# Izhikevich neuron model: [1]

# 4.2 Izhikevich neurons driven by Poisson input spike trains:

```
Izhikevich network receiving Poisson input spike trains
_____
In this example project there is again a pool of non-connected Izhikevich model neurons
that are connected to a pool of Poisson input neurons with a fixed probability.
This example project contains a helper executable called "generate_run", which compiles and
executes the model.
To compile it, navigate to genn/userproject/PoissonIzh_project and type:
msbuild ..\userprojects.sln /t:generate_poisson_izh_runner /p:Configuration=Release
for Windows users, or:
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-poisson: Number of Poisson sources to simulate (defaults to 100)
--num-izh: Number of Izhikievich neurons to simulate (defaults to 10)
--pconn: Probability of connection between each pair of poisson sources and neurons (defaults to 0.5)
-- qscale: Scaling of synaptic conductances (defaults to 2)
--sparse: Use sparse rather than dense data structure to represent connectivity
An example invocation of generate_run using these defaults and recording results with a base name of 'test':
generate run.exe test
```

for Windows users, or:

./generate\_run test

```
for Linux, Mac and other UNIX users.

This will generate a network of 100 Poisson neurons with 20 Hz firing rate connected to 10 Izhikevich neurons with a 0.5 probability.

The same network with sparse connectivity can be used by adding the --sparse flag to the command line. Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses sparse connectivity would be:

generate_run.exe --cpu-only --timing --sparse test

for Windows users, or:

./generate_run --cpu-only --timing --sparse test

for Linux, Mac and other UNIX users.

Izhikevich neuron model: [1]

4.3 Pulse-coupled Izhikevich network

Pulse-coupled Izhikevich network

This example model is inspired by simple thalamo-cortical network of Izhikevich
```

```
with an excitatory and an inhibitory population of spiking neurons that are
randomly connected. It creates a pulse-coupled network with 80% excitatory 20%
inhibitory connections, each connecting to a fixed number of neurons with sparse connectivity.
To compile it, navigate to genn/userproject/Izh_sparse_project and type:
msbuild ..\userprojects.sln /t:generate_izh_sparse_runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-neurons: Number of neurons (defaults to 10000)
--num-connections: Number of connections per neuron (defaults to 1000)
--gscale: General scaling of synaptic conductances (defaults to 1.0)
An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo
generate_run.exe test
```

for Linux, Mac and other UNIX users.

This would create a pulse coupled network of 8000 excitatory 2000 inhibitory Izhikevich neurons, each making 1000 connections with other neurons, generating

for Windows users, or:

./generate run test

```
a mixed alpha and gamma regime. For larger input factor, there is more input current and more irregular activity, for smaller factors less and less and more sparse activity. The synapses are of a simple pulse-coupling type. The results of the simulation are saved in the directory 'outdir_output'.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and doubles the number of neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=20000 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=20000 test

for Linux, Mac and other UNIX users.
```

# Izhikevich neuron model: [1]

# 4.4 Izhikevich network with delayed synapses

```
Izhikevich network with delayed synapses
```

This example project demonstrates the synaptic delay feature of GeNN. It creates a network of three Izhikevich neuron groups, connected all-to-all with fast, medium and slow synapse groups. Neurons in the output group only spike if they are simultaneously innervated by the input neurons, via slow synapses, and the interneurons, via faster synapses.

```
COMPILE (WINDOWS)
------
To run this example project, first build the model into CUDA code by typing:
genn-buildmodel.bat SynDelay.cc
then compile the project by typing:
msbuild SynDelay.sln /t:SynDelay /p:Configuration=Release

COMPILE (MAC AND LINUX)
------
To run this example project, first build the model into CUDA code by typing:
genn-buildmodel.sh SynDelay.cc
then compile the project by typing:
make

USAGE
-----
syn_delay [directory to save output]
```

# 4.5 Insect olfaction model

Izhikevich neuron model: [1]

Locust olfactory system (Nowotny et al. 2005)

```
This project implements the insect olfaction model by Nowotny et
al. that demonstrates self-organized clustering of odours in a
simulation of the insect antennal lobe and mushroom body. As provided
the model works with conductance based Hodgkin-Huxley neurons and
several different synapse types, conductance based (but pulse-coupled)
excitatory synapses, graded inhibitory synapses and synapses with a
simplified STDP rule. This example project contains a helper executable called "generate_run", which
prepares input pattern data, before compiling and
executing the model.
To compile it, navigate to genn/userproject/MBody1_project and type:
msbuild ..\userprojects.sln /t:generate_mbody1_runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-al: Number of neurons in the antennal lobe (AL), the input neurons to this model (defaults to 100)
--num-kc: Number of Kenyon cells (KC) in the "hidden layer" (defaults to 1000)
--num-lhi: Number of lateral horn interneurons, implementing gain control (defaults to 20)
--num-dn: Number of decision neurons (DN) in the output layer (defaults to 100)
--gscale: A general rescaling factor for synaptic strength (defaults to 0.0025)
--bitmask: Use bitmasks to represent sparse PN->KC connectivity rather than dense connectivity
--delayed-synapses: Rather than use constant delays of DT throughough, use delays of (5 \star DT) ms on KC->DN and
An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo
generate run.exe test
for Windows users, or:
```

./generate\_run test

for Linux, Mac and other UNIX users.

Such a command would generate a locust olfaction model with 100 antennal lobe neurons, 1000 mushroom body Kenyon cells, 20 lateral horn interneurons and 100 mushroom body output neurons, and launch a simulation of it on a CUDA-enabled GPU using single precision floating point numbers. All output files will be prefixed with "test" and will be created under the "test" directory. The model that is run is defined in 'model/MBody1.cc', debugging is switched off and the model would be simulated using float (single precision floating point) variables.

In more details, what generate\_run program does is: a) use another tools to generate input patterns.

- b) build the source code for the model by writing neuron numbers into ./model/sizes.h, and executing "genn-buildmodel.sh ./model/MBody1.cc.
- c) compile the generated code by invoking "make clean && make" running the code, e.g. "./classol\_sim r1".

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses bitmask connectivity would be:

```
generate_run.exe --cpu-only --timing --bitmask test
for Windows users, or:
./generate_run --cpu-only --timing --bitmask test
for Linux, Mac and other UNIX users.
As provided, the model outputs 'test.dn.st', 'test.kc.st', 'test.lhi.st' and 'test.pn.st' files which contain
the spiking activity observed in each population inthe simulation, There are two
columns in this ASCII file, the first one containing the time of
a spike and the second one the ID of the neuron that spiked. Users
of matlab can use the scripts in the 'matlab' directory to plot
the results of a simulation and users of python can use the plot_spikes.py script in userproject/python.
For more about the model itself and the scientific insights gained from it see Nowotny et al. referenced below
MODEL INFORMATION
For information regarding the locust olfaction model implemented in this example project, see:
T. Nowotny, R. Huerta, H. D. I. Abarbanel, and M. I. Rabinovich Self-organization in the
olfactory system: One shot odor recognition in insects, Biol Cyber, 93 (6): 436-446 (2005),
doi:10.1007/s00422-005-0019-7
Nowotny insect olfaction model: [4]; Traub-Miles Hodgkin-Huxley neuron model: [7]
```

# 4.6 Voltage clamp simulation to estimate Hodgkin-Huxley parameters

Genetic algorithm for tracking parameters in a HH model cell

```
This example simulates a population of Hodgkin-Huxley neuron models using GeNN and evolves them with a simple guided random search (simple GA) to mimic the dynamics of a separate Hodgkin-Huxley neuron that is simulated on the CPU. The parameters of the CPU simulated "true cell" are drifting according to a user-chosen protocol: Either one of the parameters gNa, ENa, gKd, EKd, gleak,
```

Eleak, Cmem are modified by a sinusoidal addition (voltage parameters) or factor (conductance or capacitance)

protocol 0-6. For protocol 7 all 7 parameters undergo a random walk concurrently.

To compile it, navigate to genn/userproject/HHVclampGA\_project and type:

for Windows users, or:s

make

for Linux, Mac and other UNIX users.

USAGE

generate\_run [OPTIONS] <outname>

Mandatory arguments:

outname: The base name of the output location and output files

Optional arguments:

- --debug: Builds a debug version of the simulation and attaches the debugger
- --cpu-only: Uses CPU rather than CUDA backend for GeNN
- --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
- --ftype: Sets the floating point precision of the model to either float or double (defaults to float)
- --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
- --protocol: Which changes to apply during the run to the parameters of the "true cell" (defaults to -1 which m
- --num-pops: Number of neurons in the tracking population (defaults to 5000)
- --total-time: Time in ms how long to run the simulation (defaults to 1000 ms)

```
An example invocation of generate_run is:

generate_run.exe test1

for Windows users, or:

./generate_run test1

for Linux, Mac and other UNIX users.

This will simulate 5000 Hodgkin-Huxley neurons on the GPU which will, for 1000 ms, be matched to a Hodgkin-Huxley neuron. The output files will be written into a directory of the name test1_output, which will be created if it does not yet exist.

Another example of an invocation that records timing information for the the simulation and runs it for 10000 generate_run.exe --timing --total-time 10000

for Windows users, or:

./generate_run --timing --total-time 10000

for Linux, Mac and other UNIX users.
```

# Traub-Miles Hodgkin-Huxley neuron model: [7]

# 4.7 A neuromorphic network for generic multivariate data classification

```
Author: Alan Diamond, University of Sussex, 2014
This project recreates using GeNN the spiking classifier design used in the paper
"A neuromorphic network for generic multivariate data classification"
Authors: Michael Schmuker, Thomas Pfeil, Martin Paul Nawrota
The classifier design is based on an abstraction of the insect olfactory system.
This example uses the IRIS stadard data set as a test for the classifier
BUILD / RUN INSTRUCTIONS
Install GeNN from the internet released build, following instruction on setting your PATH etc
Start a terminal session
cd to this project directory (userproject/Model_Schmuker_2014_project)
To build the model using the GENN meta compiler type:
genn-buildmodel.sh Model_Schmuker_2014_classifier.cc
for Linux, Mac and other UNIX systems, or:
genn-buildmodel.bat Model_Schmuker_2014_classifier.cc
for Windows systems (add -d for a debug build).
You should only have to do this at the start, or when you change your actual network model (i.e. editing the
Then to compile the experiment plus the GeNN created C/CUDA code type:-
make
for Linux, Mac and other UNIX users (add DEBUG=1 if using debug mode), or:
msbuild Schmuker2014_classifier.vcxproj /p:Configuration=Release
for Windows users (change Release to Debug if using debug mode).
```

Once it compiles you should be able to run the classifier against the included Iris dataset.

type

./experiment .

```
for Linux, Mac and other UNIX systems, or:

Schmuker2014_classifier .

for Windows systems.

This is how it works roughly.
The experiment (experiment.cu) controls the experiment at a high level. It mostly does this by instructing the So the experiment first tells the classifier to set up the GPU with the model and synapse data.

Then it chooses the training and test set data.

It runs through the training set , with plasticity ON , telling the classifier to run with the specfied observed.
```

Then it runs through the test set with plasticity OFF and collects the results in various reporting files.


At the highest level it also has a loop where you can cycle through a list of parameter values e.g. some three You should also note there is no option currently to run on CPU, this is not due to the demanding task, it just

#### Previous | Top | Next

# 5 SpineML and SpineCreator

GeNN now supports simulating models built using SpineML and includes scripts to fully integrate it with the SpineCreator graphical editor on Linux, Mac and Windows. After installing GeNN using the instructions in Installation, build SpineCreator for your platform.

From SpineCreator, select Edit->Settings->Simulators and add a new simulator using the following settings (replacing "/home/j/jk/jk421/genn" with the GeNN installation directory on your own system):



If you would like SpineCreator to use GeNN in CPU only mode, add an environment variable called "GENN\_SPI⊷ NEML\_CPU\_ONLY".

The best way to get started using SpineML with GeNN is to experiment with some example models. A number are available <a href="here">here</a> although the "Striatal model" uses features not currently supported by GeNN and the two "Brette

Benchmark" models use a legacy syntax no longer supported by SpineCreator (or GeNN). Once you have loaded a model, click "Expts" from the menu on the left hand side of SpineCreator, choose the experiment you would like to run and then select your newly created GeNN simulator in the "Setup Simulator" panel:



Now click "Run experiment" and, after a short time, the results of your GeNN simulation will be available for plotting by clicking the "Graphs" option in the menu on the left hand side of SpineCreator.

Previous | Top | Next

# 6 Brian interface (Brian2GeNN)

GeNN can simulate models written for the Brian simulator via the Brian2GeNN interface [6]. The easiest way to install everything needed is to install the Anaconda or Miniconda Python distribution and then follow the instructions to install Brian2GeNN with the conda package manager. When Brian2GeNN is installed in this way, it comes with a bundled version of GeNN and no further configuration is required. In all other cases (e.g. an installation from source), the path to GeNN and the CUDA libraries has to be configured via the GECNN\_PATH and CUDA\_PATH environment variables as described in Installation or via the devices.genn.path and devices.genn.cuda\_path Brian preferences.

To use GeNN to simulate a Brian script, import the brian2genn package and switch Brian to the genn device. As an example, the following Python script will simulate Leaky-integrate-and-fire neurons with varying input currents to construct an f/l curve:

Of course, your simulation should be more complex than the example above to actually benefit from the performance gains of using a GPU via GeNN.

Previous | Top | Next

# 7 Python interface (PyGeNN)

As well as being able to build GeNN models and user code directly from C++, you can also access all GeNN features from Python. The pygenn\_genn\_model.GeNNModel class provides a thin wrapper around
ModelSpec as well as providing support for loading and running simulations; and accessing their state.
SynapseGroup, NeuronGroup and CurrentSource are similarly wrapped by the pygenn.genngroups.SynapseGroup, pygenn.genn\_groups.NeuronGroup and pygenn.genn\_groups.
CurrentSource classes respectively.

8 Release Notes 15

PyGeNN can be built from source on Windows, Mac and Linux following the instructions in the README file in the pygenn directory of the GeNN repository. However, if you have a relatively recent version of Python and CUDA, we recommend that you instead downloading a suitable 'wheel' from our releases page. These can then be installed using e.g. pip install cudal0-pygenn-0.2-cp27-cp27mu-linux\_x86\_64.whl for a Linux system with CUDA 10 and Python 2.7. On Windows we recommend using the Python 3 version of Anaconda.

The following example shows how PyGeNN can be easily interfaced with standard Python packages such as numpy and matplotlib to plot 4 different Izhikevich neuron regimes:

```
import numpy as np
import matplotlib.pyplot as plt
from pygenn,genn model import GeNNModel
# Create a single-precision GeNN model
model = GeNNModel("float", "pygenn")
# Set simulation timestep to 0.1ms
model.dT = 0.1
# Initialise IzhikevichVariable parameters - arrays will be automatically uploaded
izk_init = {"V": -65.0,}
              "U": -20.0,
                              0.1, 0.2,
             "a": [0.02,
                                        0.02, 0.02],
                             0.2,
              "b": [0.2,
                                                 0.2],
             "c": [-65.0, -65.0, -50.0, -55.0],
"d": [8.0, 2.0, 4.0]}
\ensuremath{\sharp} Add neuron populations and current source to model
pop = model.add_neuron_population("Neurons", 4, "IzhikevichVariable", {}, izk_init)
model.add_current_source("CurrentSource", "DC", "Neurons", {"amp": 10.0}, {})
# Build and load model
model.build()
model.load()
\sharp Create a numpy view to efficiently access the membrane voltage from Python
voltage_view = pop.vars["V"].view
# Simulate
while model.t < 200.0:
    model.step_time()
    model.pull state from device ("Neurons")
    v = np.copy(voltage view) if v is None else np.vstack((v, voltage view))
figure, axes = plt.subplots(4, sharex=True)
# Plot voltages
for i, t in enumerate(["RS", "FS", "CH", "IB"]):
    axes[i].set_title(t)
    axes[i].set_ylabel("V [mV]")
    axes[i].plot(np.arange(0.0, 200.0, 0.1), v[:,i])
axes[-1].set xlabel("Time [ms]")
# Show plot
plt.show()
```

#### Previous | Top | Next

# 8 Release Notes

## Release Notes for GeNN v4.0.2

This release fixes several small issues with the generation of binary wheels for Python:

#### Bug fixes:

- 1. There was a conflict between the versions of numpy used to build the wheels and the version required for the PyGeNN packages
- 2. Wheels were renamed to include the CUDA version which broke them.

#### Release Notes for GeNN v4.0.1

This release fixes several small bugs found in GeNN 4.0.0 and implements some small features:

## **User Side Changes**

- 1. Improved detection and handling of errors when specifying model parameters and values in PyGeNN.
- 2. SpineML simulator is now implemented as a library which can be used directly from user applications as well as from command line tool.

#### **Bug fixes:**

- 1. Fixed typo in GeNNModel.push\_var\_to\_device function in PyGeNN.
- 2. Fixed broken support for Visual C++ 2013.
- 3. Fixed zero-copy mode.
- 4. Fixed typo in tutorial 2.

#### Release Notes for GeNN v4.0.0

This release is the result of a second round of fairly major refactoring which we hope will make GeNN easier to use and allow it to be extended more easily in future. However, especially if you have been using GeNN 2.XX syntax, it breaks backward compatibility.

# **User Side Changes**

- 1. Totally new build system make install can be used to install GeNN to a system location on Linux and Mac and Windows projects work much better in the Visual Studio IDE.
- 2. Python interface now supports Windows and can be installed using binary 'wheels' (see Python interface (PyGeNN) for more details).
- 3. No need to call initGeNN() at start and model.finalize() at end of all models.
- 4. Initialisation system simplified if you specify a value or initialiser for a variable or sparse connectivity, it will be initialised by your chosen backend. If you mark it as uninitialised, it is up to you to initialize it in user code between the calls to initialize() and initializeSparse() (where it will be copied to device).
- 5. genn-create-user-project helper scripts to create Makefiles or MSBuild projects for building user code
- 6. State variables can now be pushed and pulled individually using the pull<var name><neuron or synapse name>FromDevice() and push<var name><neuron or synapse name>To← Device() functions.
- 7. Management of extra global parameter arrays has been somewhat automated (see Extra Global Parameters for more details).
- 8. GENN\_PREFERENCES is no longer a namespace it's a global struct so members need to be accessed with . rather than ::.
- 9. NeuronGroup, SynapseGroup, CurrentSource and NNmodel all previously exposed a lot of methods that the user wasn't *supposed* to call but could. These have now all been made protected and are exposed to GeNN internals using derived classes (NeuronGroupInternal, SynapseGroupInternal, CurrentSourceInternal, ModelSpecInternal) that make them public using using directives.

8 Release Notes 17

10. Auto-refractory behaviour was controlled using GENN\_PREFERENCES::autoRefractory, this is now controlled on a per-neuron-model basis using the SET\_NEEDS\_AUTO\_REFRACTORY macro.

- 11. The functions used for pushing and pulling have been unified somewhat this means that <code>copyState</code>

  ToDevice and <code>copyStateFromDevice</code> functions no longer copy spikes and <code>pus<neuron</code> or synapse <code>name>SpikesToDevice</code> and <code>pull<neuron</code> or synapse <code>name>SpikesFrom</code>

  Device no longer copy spike times or spike-like events.
- 12. Standard models of leaky-integrate-and-fire neuron (NeuronModels::LIF) and of exponentially shaped postsynaptic current (PostsynapticModels::ExpCurr) have been added.
- 13. When a model is built using the CUDA backend, the device it was built for is stored using it's PCI bus ID so it will always use the same device.

#### **Deprecations**

- 1. Yale-format sparse matrices are no longer supported.
- 2. GeNN 2.X syntax for implementing neuron and synapse models is no longer supported.
- 3. \$(addtoinSyn) = X; \$(updatelinsyn); idiom in weight update models has been replaced by function style \$(addToInSyn, X);.

#### Release Notes for GeNN v3.3.0

This release is intended as the last service release for GeNN 3.X.X. Fixes for serious bugs **may** be backported if requested but, otherwise, development will be switching to GeNN 4.

## **User Side Changes**

- 1. Postsynaptic models can now have Extra Global Parameters.
- 2. Gamma distribution can now be sampled using \$ (gennrand\_gamma, a). This can be used to initialise variables using InitVarSnippet::Gamma.
- 3. Experimental Python interface All features of GeNN are now exposed to Python through the pygenn module (see Python interface (PyGeNN) for more details).

## Bug fixes:

- 1. Devices with Streaming Multiprocessor version 2.1 (compute capability 2.0) now work correctly in Windows.
- 2. Seeding of on-device RNGs now works correctly.
- 3. Improvements to accuracy of memory usage estimates provided by code generator.

# Release Notes for GeNN v3.2.0

This release extends the initialisation system introduced in 3.1.0 to support the initialisation of sparse synaptic connectivity, adds support for networks with more sophisticated models of synaptic plasticity and delay as well as including several other small features, optimisations and bug fixes for certain system configurations. This release supports  $GCC \ge 4.9.1$  on Linux, Visual Studio  $\ge 2013$  on Windows and recent versions of Clang on Mac OS X.

## **User Side Changes**

- Sparse synaptic connectivity can now be initialised using small snippets of code run either on GPU or CPU.
   This can save significant amounts of initialisation time for large models. See Sparse connectivity initialisation for more details.
- 2. New 'ragged matrix' data structure for representing sparse synaptic connections supports initialisation using new sparse synaptic connectivity initialisation system and enables future optimisations. See Synaptic matrix types for more details.
- 3. Added support for pre and postsynaptic state variables for weight update models to allow more efficient implementatation of trace based STDP rules. See Defining a new weight update model for more details.
- 4. Added support for devices with Compute Capability 7.0 (Volta) to block-size optimizer.
- 5. Added support for a new class of 'current source' model which allows non-synaptic input to be efficiently injected into neurons. See Current source models for more details.
- 6. Added support for heterogeneous dendritic delays. See Defining a new weight update model for more details.
- 7. Added support for (homogeneous) synaptic back propagation delays using SynapseGroup::setBack← PropDelaySteps.
- 8. For long simulations, using single precision to represent simulation time does not work well. Added N← Nmodel::setTimePrecision to allow data type used to represent time to be set independently.

#### **Optimisations**

- 1. GENN\_PREFERENCES::mergePostsynapticModels flag can be used to enable the merging together of postsynaptic models from a neuron population's incoming synapse populations improves performance and saves memory.
- 2. On devices with compute capability > 3.5 GeNN now uses the read only cache to improve performance of postsynaptic learning kernel.

## Bug fixes:

- 1. Fixed bug enabling support for CUDA 9.1 and 9.2 on Windows.
- 2. Fixed bug in SynDelay example where membrane voltage went to NaN.
- 3. Fixed bug in code generation of SCALAR\_MIN and SCALAR\_MAX values.
- 4. Fixed bug in substitution of trancendental functions with single-precision variants.
- 5. Fixed various issues involving using spike times with delayed synapse projections.

## Release Notes for GeNN v3.1.1

This release fixes several small bugs found in GeNN 3.1.0 and implements some small features:

#### **User Side Changes**

1. Added new synapse matrix types SPARSE\_GLOBALG\_INDIVIDUAL\_PSM, DENSE\_GLOBALG\_IND → IVIDUAL\_PSM and BITMASK\_GLOBALG\_INDIVIDUAL\_PSM to handle case where synapses with no individual state have a postsynaptic model with state variables e.g. an alpha synapse. See Synaptic matrix types for more details.

8 Release Notes 19

#### **Bug fixes**

- 1. Correctly handle aliases which refer to other aliases in SpineML models.
- 2. Fixed issues with presynaptically parallelised synapse populations where the postsynaptic population is small enough for input to be accumulated in shared memory.

## Release Notes for GeNN v3.1.0

This release builds on the changes made in 3.0.0 to further streamline the process of building models with GeNN and includes several bug fixes for certain system configurations.

## **User Side Changes**

- 1. Support for simulating models described using the SpineML model description language with GeNN (see SpineML and SpineCreator for more details).
- 2. Neuron models can now sample from uniform, normal, exponential or log-normal distributions these calls are translated to cuRAND when run on GPUs and calls to the C++11 < random > library when run on CPU. See Defining your own neuron type for more details.
- 3. Model state variables can now be initialised using small *snippets* of code run either on GPU or CPU. This can save significant amounts of initialisation time for large models. See Defining a new variable initialisation snippet for more details.
- 4. New MSBuild build system for Windows makes developing user code from within Visual Studio much more streamlined. See Debugging suggestions for more details.

## **Bug fixes:**

- 1. Workaround for bug found in Glibc 2.23 and 2.24 which causes poor performance on some 64-bit Linux systems (namely on Ubuntu 16.04 LTS).
- 2. Fixed bug encountered when using extra global variables in weight updates.

## Release Notes for GeNN v3.0.0

This release is the result of some fairly major refactoring of GeNN which we hope will make it more user-friendly and maintainable in the future.

# **User Side Changes**

- 1. Entirely new syntax for defining models hopefully terser and less error-prone (see updated documentation and examples for details).
- 2. Continuous integration testing using Jenkins automated testing and code coverage calculation calculated automatically for Github pull requests etc.
- 3. Support for using Zero-copy memory for model variables. Especially on devices such as NVIDIA Jetson TX1 with no physical GPU memory this can significantly improve performance when recording data or injecting it to the simulation from external sensors.

# Release Notes for GeNN v2.2.3

This release includes minor new features and several bug fixes for certain system configurations.

## **User Side Changes**

- 1. Transitioned feature tests to use Google Test framework.
- 2. Added support for CUDA shader model 6.X

## Bug fixes:

- 1. Fixed problem using GeNN on systems running 32-bit Linux kernels on a 64-bit architecture (Nvidia Jetson modules running old software for example).
- 2. Fixed problem linking against CUDA on Mac OS X El Capitan due to SIP (System Integrity Protection).
- 3. Fixed problems with support code relating to its scope and usage in spike-like event threshold code.
- 4. Disabled use of C++ regular expressions on older versions of GCC.

#### Release Notes for GeNN v2.2.2

This release includes minor new features and several bug fixes for certain system configurations.

#### **User Side Changes**

- 1. Added support for the new version (2.0) of the Brian simulation package for Python.
- 2. Added a mechanism for setting user-defined flags for the C++ compiler and NVCC compiler, via GENN\_PR← EFERENCES.

## **Bug fixes:**

- 1. Fixed a problem with atomicAdd() redefinitions on certain CUDA runtime versions and GPU configurations
- 2. Fixed an incorrect bracket placement bug in code generation for certain models.
- 3. Fixed an incorrect neuron group indexing bug in the learning kernel, for certain models.
- 4. The dry-run compile phase now stores temporary files in the current directory, rather than the temp directory, solving issues on some systems.
- 5. The LINK\_FLAGS and INCLUDE\_FLAGS in the common windows makefile include 'makefile\_commin 
   win.mk' are now appended to, rather than being overwritten, fixing issues with custom user makefiles on 
  Windows.

# Release Notes for GeNN v2.2.1

This bugfix release fixes some critical bugs which occur on certain system configurations.

# Bug fixes:

- 1. (important) Fixed a Windows-specific bug where the CL compiler terminates, incorrectly reporting that the nested scope limit has been exceeded, when a large number of device variables need to be initialised.
- 2. (important) Fixed a bug where, in certain circumstances, outdated generateALL objects are used by the Makefiles, rather than being cleaned and replaced by up-to-date ones.
- 3. (important) Fixed an 'atomicAdd' redeclared or missing bug, which happens on certain CUDA architectures when using the newest CUDA 8.0 RC toolkit.

8 Release Notes 21

4. (minor) The SynDelay example project now correctly reports spike indexes for the input group.

Please refer to the full documentation for further details, tutorials and complete code documentation.

#### Release Notes for GeNN v2.2

This release includes minor new features, some core code improvements and several bug fixes on GeNN v2.1.

#### **User Side Changes**

1. GeNN now analyses automatically which parameters each kernel needs access to and these and only these are passed in the kernel argument list in addition to the global time t. These parameters can be a combination of extraGlobalNeuronKernelParameters and extraGlobalSynapseKernelParameters in either neuron or synapse kernel. In the unlikely case that users wish to call kernels directly, the correct call can be found in the stepTimeGPU() function.

Reflecting these changes, the predefined Poisson neurons now simply have two extraGlobalNeuron-Parameter rates and offset which replace the previous custom pointer to the array of input rates and integer offset to indicate the current input pattern. These extraGlobalNeuronKernelParameters are passed to the neuron kernel automatically, but the rates themselves within the array are of course not updated automatically (this is exactly as before with the specifically generated kernel arguments for Poisson neurons).

The concept of "directInput" has been removed. Users can easily achieve the same functionality by adding an additional variable (if there are individual inputs to neurons), an extraGlobalNeuronParameter (if the input is homogeneous but time dependent) or, obviously, a simple parameter if it's homogeneous and constant.

#### Note

The global time variable "t" is now provided by GeNN; please make sure that you are not duplicating its definition or shadowing it. This could have severe consequences for simulation correctness (e.g. time not advancing in cases of over-shadowing).

- 2. We introduced the namespace GENN\_PREFERENCES which contains variables that determine the behaviour of GeNN.
- 3. We introduced a new code snippet called "supportCode" for neuron models, weightupdate models and post-synaptic models. This code snippet is intended to contain user-defined functions that are used from the other code snippets. We advise where possible to define the support code functions with the CUDA keywords "\_ host \_\_ \_\_device\_\_" so that they are available for both GPU and CPU version. Alternatively one can define separate versions for **host** and **device** in the snippet. The snippets are automatically made available to the relevant code parts. This is regulated through namespaces so that name clashes between different models do not matter. An exception are hash defines. They can in principle be used in the supportCode snippet but need to be protected specifically using ifndef. For example

```
#ifndef clip(x)
#define clip(x) x > 10.0? 10.0 : x
#endif
```

## Note

If there are conflicting definitions for hash defines, the one that appears first in the GeNN generated code will then prevail.

- 4. The new convenience macros spikeCount\_XX and spike\_XX where "XX" is the name of the neuron group are now also available for events: spikeEventCount\_XX and spikeEvent\_XX. They access the values for the current time step even if there are synaptic delays and spikes events are stored in circular queues.
- 5. The old buildmodel.[sh|bat] scripts have been superseded by new genn-buildmodel.[sh|bat] scripts. These scripts accept UNIX style option switches, allow both relative and absolute model file paths, and allow the user to specify the directory in which all output files are placed (-o <path>). Debug (-d), CPU-only (-c) and show help (-h) are also defined.

6. We have introduced a CPU-only "-c" genn-buildmodel switch, which, if it's defined, will generate a GeNN version that is completely independent from CUDA and hence can be used on computers without CUDA installation or CUDA enabled hardware. Obviously, this then can also only run on CPU. CPU only mode can either be switched on by defining CPU\_ONLY in the model description file or by passing appropriate parameters during the build, in particular

```
genn-buildmodel.[sh|bat] \<modelfile\> -c
make release CPU ONLY=1
```

- 7. The new genn-buildmodel "-o" switch allows the user to specify the output directory for all generated files the default is the current directory. For example, a user project could be in '/home/genn\_project', whilst the GeNN directory could be '/usr/local/genn'. The GeNN directory is kept clean, unless the user decides to build the sample projects inside of it without copying them elsewhere. This allows the deployment of GeNN to a read-only directory, like '/usr/local' or 'C:\Program Files'. It also allows multiple users i.e. on a compute cluster to use GeNN simultaneously, without overwriting each other's code-generation files, etcetera.
- 8. The ARM architecture is now supported e.g. the NVIDIA Jetson development platform.
- 9. The NVIDIA CUDA SM 5\* (Maxwell) architecture is now supported.
- 10. An error is now thrown when the user tries to use double precision floating-point numbers on devices with architecture older than SM 13, since these devices do not support double precision.
- 11. All GeNN helper functions and classes, such as toString() and NNmodel, are defined in the header files at genn/lib/include/, for example stringUtils.h and modelSpec.h, which should be individually included before the functions and classes may be used. The functions and classes are actually implementated in the static library genn\lib\lib\genn.lib\(Windows)\) or genn/lib/lib/libgenn.a (Mac, Linux), which must be linked into the final executable if any GeNN functions or classes are used.
- 12. In the modelDefinition() file, only the header file modelSpec.h should be included i.e. not the source file modelSpec.cc. This is because the declaration and definition of NNmodel, and associated functions, has been separated into modelSpec.h and modelSpec.cc, respectively. This is to enable NNmodel code to be precompiled separately. Henceforth, only the header file modelSpec.h should be included in model definition files!
- 13. In the modelDefinition () file, DT is now preferrably defined using model.setDT (<val>);, rather than  $\#define\ DT\ <$ val>, in order to prevent problems with DT macro redefinition. For backward-compatibility reasons, the old  $\#define\ DT\ <$ val> method may still be used, however users are advised to adopt the new method.
- 14. In preparation for multi-GPU support in GeNN, we have separated out the compilation of generated code from user-side code. This will eventually allow us to optimise and compile different parts of the model with different CUDA flags, depending on the CUDA device chosen to execute that particular part of the model. As such, we have had to use a header file definitions.h as the generated code interface, rather than the runner.cc file. In practice, this means that user-side code should include myModel\_COD← E/definitions.h, rather than myModel\_CODE/runner.cc. Including runner.cc will likely result in pages of linking errors at best!

#### **Developer Side Changes**

- Blocksize optimization and device choice now obtain the ptxas information on memory usage from a CUDA driver API call rather than from parsing ptxas output of the nvcc compiler. This adds robustness to any change in the syntax of the compiler output.
- 2. The information about device choice is now stored in variables in the namespace GENN\_PREFERENCES. This includes chooseDevice, optimiseBlockSize, optimizeCode, debugCode, showPtxcInfo, defaultDevice. asGoodAsZero has also been moved into this namespace.
- 3. We have also introduced the namespace GENN\_FLAGS that contains unsigned int variables that attach names to numeric flags that can be used within GeNN.

8 Release Notes 23

4. The definitions of all generated variables and functions such as pullXXXStateFromDevice etc, are now generated into definitions.h. This is useful where one wants to compile separate object files that cannot all include the full definitions in e.g. "runnerGPU.cc". One example where this is useful is the brian2genn interface.

5. A number of feature tests have been added that can be found in the featureTests directory. They can be run with the respective runTests.sh scripts. The cleanTests.sh scripts can be used to remove all generated code after testing.

## Improvements

- 1. Improved method of obtaining ptxas compiler information on register and shared memory usage and an improved algorithm for estimating shared memory usage requirements for different block sizes.
- 2. Replaced pageable CPU-side memory with page-locked memory. This can significantly speed up simulations in which a lot of data is regularly copied to and from a CUDA device.
- 3. GeNN library objects and the main generateALL binary objects are now compiled separately, and only when a change has been made to an object's source, rather than recompiling all software for a minor change in a single source file. This should speed up compilation in some instances.

#### Bug fixes:

- 1. Fixed a minor bug with delayed synapses, where delaySlot is declared but not referenced.
- 2. We fixed a bug where on rare occasions a synchronisation problem occurred in sparse synapse populations.
- 3. We fixed a bug where the combined spike event condition from several synapse populations was not assembled correctly in the code generation phase (the parameter values of the first synapse population over-rode the values of all other populations in the combined condition).

Please refer to the full documentation for further details, tutorials and complete code documentation.

#### Release Notes for GeNN v2.1

This release includes some new features and several bug fixes on GeNN v2.0.

# **User Side Changes**

- 1. Block size debugging flag and the asGoodAsZero variables are moved into include/global.h.
- 2. NGRADSYNAPSES dynamics have changed (See Bug fix #4) and this change is applied to the example projects. If you are using this synapse model, you may want to consider changing model parameters.
- 3. The delay slots are now such that NO\_DELAY is 0 delay slots (previously 1) and 1 means an actual delay of 1 time step.
- 4. The convenience function convertProbabilityToRandomNumberThreshold(float \*, uint64\_t \*, int) was changed so that it actually converts firing probability/timestep into a threshold value for the GeNN random number generator (as its name always suggested). The previous functionality of converting a rate in kHz into a firing threshold number for the GeNN random number generator is now provided with the name convertRateToRandomNumberThreshold(float \*, uint64\_t \*, int)
- 5. Every model definition function modelDefinition() now needs to end with calling NNmodel←::finalize() for the defined network model. This will lock down the model and prevent any further changes to it by the supported methods. It also triggers necessary analysis of the model structure that should only be performed once. If the finalize() function is not called, GeNN will issue an error and exit before code generation.

- 6. To be more consistent in function naming the pull\<SYNAPSENAME\>FromDevice and push\<S\U004\SYNAPSENAME\>StateFromDevice and push\<SYNAPSENAME\>StateFromDevice and push\<SYNAPSENAME\>StateToDevice. The old versions are still supported through macro definitions to make the transition easier.
- 7. New convenience macros are now provided to access the current spike numbers and identities of neurons that spiked. These are called spikeCount\_XX and spike\_XX where "XX" is the name of the neuron group. They access the values for the current time step even if there are synaptic delays and spikes are stored in circular queues.
- 8. There is now a pre-defined neuron type "SPIKECOURCE" which is empty and can be used to define PyNN style spike source arrays.
- 9. The macros FLOAT and DOUBLE were replaced with GENN\_FLOAT and GENN\_DOUBLE due to name clashes with typedefs in Windows that define FLOAT and DOUBLE.

#### **Developer Side Changes**

1. We introduced a file definitions.h, which is generated and filled with useful macros such as spkQuePtrShift which tells users where in the circular spike queue their spikes start.

## Improvements

- 1. Improved debugging information for block size optimisation and device choice.
- 2. Changed the device selection logic so that device occupancy has larger priority than device capability version.
- 3. A new HH model called TRAUBMILES\_PSTEP where one can set the number of inner loops as a parameter is introduced. It uses the TRAUBMILES\_SAFE method.
- 4. An alternative method is added for the insect olfaction model in order to fix the number of connections to a maximum of 10K in order to avoid negative conductance tails.
- 5. We introduced a preprocessor define directive for an "int\_" function that translates floating points to integers.

# Bug fixes:

- 1. AtomicAdd replacement for old GPUs were used by mistake if the model runs in double precision.
- 2. Timing of individual kernels is fixed and improved.
- 3. More careful setting of maximum number of connections in sparse connectivity, covering mixed dense/sparse network scenarios.
- 4. NGRADSYNAPSES was not scaling correctly with varying time step.
- 5. Fixed a bug where learning kernel with sparse connectivity was going out of range in an array.
- 6. Fixed synapse kernel name substitutions where the "dd" prefix was omitted by mistake.

Please refer to the full documentation for further details, tutorials and complete code documentation.

# Release Notes for GeNN v2.0

Version 2.0 of GeNN comes with a lot of improvements and added features, some of which have necessitated some changes to the structure of parameter arrays among others.

8 Release Notes 25

**User Side Changes** 

1. Users are now required to call initGeNN () in the model definition function before adding any populations to the neuronal network model.

- 2. glbscnt is now call glbSpkCnt for consistency with glbSpkEvntCnt.
- 3. There is no longer a privileged parameter Epre. Spike type events are now defined by a code string spk EvntThreshold, the same way proper spikes are. The only difference is that Spike type events are specific to a synapse type rather than a neuron type.
- 4. The function setSynapseG has been deprecated. In a GLOBALG scenario, the variables of a synapse group are set to the initial values provided in the modeldefinition function.
- 5. Due to the split of synaptic models into weightUpdateModel and postSynModel, the parameter arrays used during model definition need to be carefully split as well so that each side gets the right parameters. For example, previously

would define the parameter array of three parameters, Erev, Epre, and tau\_S for a synapse of type NSYNAPSE. This now needs to be "split" into

i.e. parameters <code>Erev</code> and <code>tau\_S</code> are moved to the post-synaptic model and its parameter array of two parameters. <code>Epre</code> is discontinued as a parameter for <code>NSYNAPSE</code>. As a consequence the weightupdate model of <code>NSYNAPSE</code> has no parameters and one can pass <code>NULL</code> for the parameter array in <code>addSynapse</code> <code>Population</code>. The correct parameter lists for all defined neuron and synapse model types are listed in the <code>User Manual</code>.

Note

If the parameters are not redefined appropriately this will lead to uncontrolled behaviour of models and likely to segmentation faults and crashes.

- 6. Advanced users can now define variables as type scalar when introducing new neuron or synapse types. This will at the code generation stage be translated to the model's floating point type (ftype), float or double. This works for defining variables as well as in all code snippets. Users can also use the expressions SCALAR\_MAX and SCALAR\_MIN for FLT\_MIN, FLT\_MAX, DBL\_MIN and DBL\_MAX, respectively. Corresponding definitions of scalar, SCALAR\_MIN and SCALAR\_MAX are also available for user-side code whenever the code-generated file runner.cc has been included.
- 7. The example projects have been re-organized so that wrapper scripts of the <code>generate\_run</code> type are now all located together with the models they run instead of in a common <code>tools</code> directory. Generally the structure now is that each example project contains the wrapper script <code>generate\_run</code> and a <code>model</code> subdirectory which contains the model description file and the user side code complete with Makefiles for Unix and Windows operating systems. The generated code will be deposited in the <code>model subdirectory</code> in its <code>own modelname\_CODE</code> folder. Simulation results will always be deposited in a new sub-folder of the main project directory.
- 8. The addSynapsePopulation (...) function has now more mandatory parameters relating to the introduction of separate weightupdate models (pre-synaptic models) and postynaptic models. The correct syntax for the addSynapsePopulation (...) can be found with detailed explanations in teh User Manual.
- We have introduced a simple performance profiling method that users can employ to get an overview over the differential use of time by different kernels. To enable the timers in GeNN generated code, one needs to declare

```
networkmodel.setTiming(TRUE);
```

This will make available and operate GPU-side cudeEvent based timers whose cumulative value can be found in the double precision variables <code>neuron\_tme</code>, <code>synapse\_tme</code> and <code>learning\_tme</code>. They measure the accumulated time that has been spent calculating the neuron kernel, synapse kernel and learning kernel, respectively. CPU-side timers for the simulation functions are also available and their cumulative values can be obtained through

```
float x= sdkGetTimerValue(&neuron_timer);
float y= sdkGetTimerValue(&synapse_timer);
float z= sdkGetTimerValue(&learning_timer);
```

The Insect olfaction model example shows how these can be used in the user-side code. To enable timing profiling in this example, simply enable it for GeNN:

```
model.setTiming(TRUE);
```

in MBody1.cc's modelDefinition function and define the macro TIMING in classol\_sim.h

```
#define TIMING
```

This will have the effect that timing information is output into <code>OUTNAME\_output/OUTNAME.</code>
<code>timingprofile.</code>

## **Developer Side Changes**

- 1. allocateSparseArrays() has been changed to take the number of connections, connN, as an argument rather than expecting it to have been set in the Connetion struct before the function is called as was the arrangement previously.
- 2. For the case of sparse connectivity, there is now a reverse mapping implemented with revers index arrays and a remap array that points to the original positions of variable values in teh forward array. By this mechanism, revers lookups from post to pre synaptic indices are possible but value changes in the sparse array values do only need to be done once.
- 3. SpkEvnt code is no longer generated whenever it is not actually used. That is also true on a somewhat finer granularity where variable queues for synapse delays are only maintained if the corresponding variables are used in synaptic code. True spikes on the other hand are always detected in case the user is interested in them.

Please refer to the  $\verb|full|$  documentation for further details, tutorials and complete code documentation.

```
Previous | Top | Next
```

# 9 User Manual

## 9.1 Contents

- Introduction
- · Defining a network model
- · Neuron models
- · Weight update models

9.2 Introduction 27

- · Postsynaptic integration methods
- · Current source models
- Synaptic matrix types
- · Variable initialisation
- · Sparse connectivity initialisation

## 9.2 Introduction

GeNN is a software library for facilitating the simulation of neuronal network models on NVIDIA CUDA enabled GPU hardware. It was designed with computational neuroscience models in mind rather than artificial neural networks. The main philosophy of GeNN is two-fold:

- 1. GeNN relies heavily on code generation to make it very flexible and to allow adjusting simulation code to the model of interest and the GPU hardware that is detected at compile time.
- 2. GeNN is lightweight in that it provides code for running models of neuronal networks on GPU hardware but it leaves it to the user to write a final simulation engine. It so allows maximal flexibility to the user who can use any of the provided code but can fully choose, inspect, extend or otherwise modify the generated code. They can also introduce their own optimisations and in particular control the data flow from and to the GPU in any desired granularity.

This manual gives an overview of how to use GeNN for a novice user and tries to lead the user to more expert use later on. With that we jump right in.

## Previous | Top | Next

## 9.3 Defining a network model

A network model is defined by the user by providing the function

```
void modelDefinition(ModelSpec &model)
```

in a separate file, such as MyModel.cc. In this function, the following tasks must be completed:

1. The name of the model must be defined:

```
model.setName("MyModel");
```

- 2. Neuron populations (at least one) must be added (see <u>Defining neuron populations</u>). The user may add as many neuron populations as they wish. If resources run out, there will not be a warning but GeNN will fail. However, before this breaking point is reached, GeNN will make all necessary efforts in terms of block size optimisation to accommodate the defined models. All populations must have a unique name.
- 3. Synapse populations (zero or more) can be added (see Defining synapse populations). Again, the number of synaptic connection populations is unlimited other than by resources.

## 9.3.1 Defining neuron populations

Neuron populations are added using the function

```
model.addNeuronPopulation<NeuronModel>(name, num, paramValues, varInitialisers);
```

where the arguments are:

- NeuronModel: Template argument specifying the type of neuron model These should be derived off NeuronModels::Base and can either be one of the standard models or user-defined (see Neuron models).
- const string &name: Unique name of the neuron population
- $\bullet$  unsigned int size: number of neurons in the population
- NeuronModel::ParamValues paramValues: Parameters of this neuron type
- NeuronModel::VarValues varInitialisers: Initial values or initialisation snippets for variables of this neuron type

The user may add as many neuron populations as the model necessitates. They must all have unique names. The possible values for the arguments, predefined models and their parameters and initial values are detailed Neuron models below.

# 9.3.2 Defining synapse populations

Synapse populations are added with the function

#### where the arguments are

- WeightUpdateModel: Template parameter specifying the type of weight update model. These should be derived off WeightUpdateModels::Base and can either be one of the standard models or user-defined (see Weight update models).
- PostsynapticModel: Template parameter specifying the type of postsynaptic integration model. These should be derived off PostsynapticModels::Base and can either be one of the standard models or user-defined (see Postsynaptic integration methods).
- const string &name: The name of the synapse population
- unsigned int mType: How the synaptic matrix is stored. See Synaptic matrix types for available options.
- unsigned int delay: Homogeneous (axonal) delay for synapse population (in terms of the simulation time step DT).
- const string preName: Name of the (existing!) pre-synaptic neuron population.
- const string postName: Name of the (existing!) post-synaptic neuron population.
- WeightUpdateModel::ParamValues weightParamValues: The parameter values (common to all synapses of the population) for the weight update model.
- WeightUpdateModel::VarValues weightVarInitialisers: Initial values or initialisation snippets for the weight update model's state variables
- WeightUpdateModel::PreVarValues weightPreVarInitialisers: Initial values or initialisation snippets for the weight update model's presynaptic state variables
- WeightUpdateModel::PostVarValues weightPostVarInitialisers: Initial values or initialisation snippets for the weight update model's postsynaptic state variables
- PostsynapticModel::ParamValues postsynapticParamValues: The parameter values (common to all postsynaptic neurons) for the postsynaptic model.

9.4 Neuron models 29

• PostsynapticModel::VarValues postsynapticVarInitialisers: Initial values or initialisation snippets for variables for the postsynaptic model's state variables

• InitSparseConnectivitySnippet::Init connectivityInitialiser: Optional argument, specifying the initialisation snippet for synapse population's sparse connectivity (see Sparse connectivity initialisation).

The ModelSpec::addSynapsePopulation() function returns a pointer to the newly created SynapseGroup object which can be further configured, namely with:

• SynapseGroup::setMaxConnections() and SynapseGroup::setMaxSourceConnections() to configure the maximum number of rows and columns respectively allowed in the synaptic matrix - this can improve performance and reduce memory usage when using SynapseMatrixConnectivity::SPARSE connectivity (see Synaptic matrix types).

Note

When using a sparse connectivity initialisation snippet, these values are set automatically.

- SynapseGroup::setMaxDendriticDelayTimesteps() sets the maximum dendritic delay (in terms of the simulation time step DT) allowed for synapses in this population. No values larger than this should be passed to the delay parameter of the addToDenDelay function in user code (see Defining a new weight update model).
- SynapseGroup::setSpanType() sets how incoming spike processing is parallelised for this synapse group. The default SynapseGroup::SpanType::POSTSYNAPTIC is nearly always the best option, but Synapse← Group::SpanType::PRESYNAPTIC may perform better when there are large numbers of spikes every timestep or very few postsynaptic neurons.

#### Note

If the synapse matrix uses one of the "GLOBALG" types then the global value of the synapse parameters are taken from the initial value provided in weightVarInitialisers therefore these must be constant rather than sampled from a distribution etc.

# Previous | Top | Next

# 9.4 Neuron models

There is a number of predefined models which can be used with the ModelSpec::addNeuronGroup function:

• NeuronModels::RulkovMap

• NeuronModels::Izhikevich

· NeuronModels::IzhikevichVariable

· NeuronModels::LIF

• NeuronModels::SpikeSource

• NeuronModels::PoissonNew

NeuronModels::TraubMiles

• NeuronModels::TraubMilesFast

NeuronModels::TraubMilesAlt

NeuronModels::TraubMilesNStep

## 9.4.1 Defining your own neuron type

In order to define a new neuron type for use in a GeNN application, it is necessary to define a new class derived from NeuronModels::Base. For convenience the methods this class should implement can be implemented using macros:

- DECLARE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS): declared the boilerplate code required for the model e.g. the correct specialisations of NewModels::ValueBase used to wrap the neuron model parameters and values.
- SET\_SIM\_CODE(SIM\_CODE): where SIM\_CODE contains the code for executing the integration of the
  model for one time stepWithin this code string, variables need to be referred to by \$(NAME), where NA

  ME is the name of the variable as defined in the vector varNames. The code may refer to the predefined
  primitives DT for the time step size and for the total incoming synaptic current. It can also refer to a unique
  ID (within the population) using .
- SET\_THRESHOLD\_CONDITION\_CODE(THRESHOLD\_CONDITION\_CODE) defines the condition for true spike detection.
- SET\_PARAM\_NAMES() defines the names of the model parameters. If defined as NAME here, they can then
  be referenced as \$(NAME) in the code string. The length of this list should match the NUM\_PARAM specified
  in DECLARE MODEL. Parameters are assumed to be always of type double.
- SET\_VARS() defines the names and type strings (e.g. "float", "double", etc) of the neuron state variables. The type string "scalar" can be used for variables which should be implemented using the precision set globally for the model with ModelSpec::setPrecision. The variables defined here as NAME can then be used in the syntax \$(NAME) in the code string.
- SET\_NEEDS\_AUTO\_REFRACTORY() defines whether the neuron should include an automatic refractory period to prevent it emitting spikes in successive timesteps.

For example, using these macros, we can define a leaky integrator  $\tau \frac{dV}{dt} = -V + I_{\rm syn}$  solved using Euler's method:

```
class LeakyIntegrator : public NeuronModels::Base
{
public:
    DECLARE_MODEL(LeakyIntegrator, 1, 1);

    SET_SIM_CODE("$(V)+= (-$(V)+$(Isyn))*(DT/$(tau));");

    SET_THRESHOLD_CONDITION_CODE("$(V) >= 1.0");

    SET_PARAM_NAMES({"tau"});

    SET_VARS({{"V", "scalar"}});
};
```

Additionally "dependent parameters" can be defined. Dependent parameters are a mechanism for enhanced efficiency when running neuron models. If parameters with model-side meaning, such as time constants or conductances always appear in a certain combination in the model, then it is more efficient to pre-compute this combination and define it as a dependent parameter.

For example, because the equation defining the previous leaky integrator example has an algebraic solution, it can be more accurately solved as follows - using a derived parameter to calculate  $\exp\left(\frac{-t}{\tau}\right)$ :

9.4 Neuron models 31

GeNN provides several additional features that might be useful when defining more complex neuron models.

#### 9.4.1.1 Support code

Support code enables a code block to be defined that contains supporting code that will be utilized in multiple pieces of user code. Typically, these are functions that are needed in the sim code or threshold condition code. If possible, these should be defined as \_\_host\_\_ \_\_device\_\_ functions so that both GPU and CPU versions of GeNN code have an appropriate support code function available. The support code is protected with a namespace so that it is exclusively available for the neuron population whose neurons define it. Support code is added to a model using the SET\_SUPPORT\_CODE() macro, for example:

```
SET_SUPPORT_CODE("__device__ __host__ scalar mysin(float x) { return sin(x); }");
```

#### 9.4.1.2 Extra global parameters

Extra global parameters are parameters common to all neurons in the population. However, unlike the standard neuron parameters, they can be varied at runtime meaning they could, for example, be used to provide a global reward signal. These parameters are defined by using the SET\_EXTRA\_GLOBAL\_PARAMS() macro to specify a list of variable names and type strings (like the SET\_VARS() macro). For example:

```
SET_EXTRA_GLOBAL_PARAMS({{"R", "float"}});
```

These variables are available to all neurons in the population. They can also be used in synaptic code snippets; in this case it need to be addressed with a \_pre or \_post postfix.

For example, if the model with the "R" parameter was used for the pre-synaptic neuron population, the weight update model of a synapse population could have simulation code like:

```
SET_SIM_CODE("$(x) = $(x) + $(R_pre);");
```

where we have assumed that the weight update model has a variable x and our synapse type will only be used in conjunction with pre-synaptic neuron populations that do have the extra global parameter R. If the pre-synaptic population does not have the required variable/parameter, GeNN will fail when compiling the kernels.

#### 9.4.1.3 Additional input variables

Normally, neuron models receive the linear sum of the inputs coming from all of their synaptic inputs through the \$(inSyn) variable. However neuron models can define additional input variables - allowing input from different synaptic inputs to be combined non-linearly. For example, if we wanted our leaky integrator to operate on the the product of two input currents, it could be defined as follows:

```
 \begin{split} & \texttt{SET\_ADDITIONAL\_INPUT\_VARS} \left( \{ \texttt{"Isyn2", "scalar", 1.0} \} \right); \\ & \texttt{SET\_SIM\_CODE} \left( \texttt{"const scalar input} = \$ \left( \texttt{Isyn} \right) \, \star \, \$ \left( \texttt{Isyn2} \right); \middle \backslash n \\ & \texttt{"$(V)} = \texttt{input} - \$ \left( \texttt{ExpTC} \right) \star \left( \texttt{input} - \$ \left( V \right) \right); "); \\ \end{aligned}
```

Where the SET\_ADDITIONAL\_INPUT\_VARS() macro defines the name, type and its initial value before postsynaptic inputs are applyed (see section Postsynaptic integration methods for more details).

## 9.4.1.4 Random number generation

Many neuron models have probabilistic terms, for example a source of noise or a probabilistic spiking mechanism. In GeNN this can be implemented by using the following functions in blocks of model code:

- \$ (gennrand\_uniform) returns a number drawn uniformly from the interval [0.0, 1.0]
- \$ (gennrand\_normal) returns a number drawn from a normal distribution with a mean of 0 and a standard deviation of 1.
- \$ (gennrand\_exponential) returns a number drawn from an exponential distribution with  $\lambda = 1$ .
- \$ (gennrand\_log\_normal, MEAN, STDDEV) returns a number drawn from a log-normal distribution with the specified mean and standard deviation.

• \$ (gennrand\_gamma, ALPHA) returns a number drawn from a gamma distribution with the specified shape.

Once defined in this way, new neuron models classes, can be used in network descriptions by referring to their type e.g.

# Previous | Top | Next

# 9.5 Weight update models

Currently 4 predefined weight update models are available:

- WeightUpdateModels::StaticPulse
- WeightUpdateModels::StaticPulseDendriticDelay
- WeightUpdateModels::StaticGraded
- WeightUpdateModels::PiecewiseSTDP

For more details about these built-in synapse models, see [3].

#### 9.5.1 Defining a new weight update model

Like the neuron models discussed in Defining your own neuron type, new weight update models are created by defining a class. Weight update models should all be derived from WeightUpdateModel::Base and, for convenience, the methods a new weight update model should implement can be implemented using macros:

- SET\_DERIVED\_PARAMS(), SET\_PARAM\_NAMES(), SET\_VARS() and SET\_EXTRA\_GLOBAL\_PARAM 
  S() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- DECLARE\_WEIGHT\_UPDATE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS, NUM\_PRE\_VARS, NUM\_ POST\_VARS) is an extended version of DECLARE\_MODEL() which declares the boilerplate code required for a weight update model with pre and postsynaptic as well as per-synapse state variables.
- SET\_PRE\_VARS() and SET\_POST\_VARS() define state variables associated with pre or postsynaptic neurons rather than synapses. These are typically used to efficiently implement *trace* variables for use in STDP learning rules [2]. Like other state variables, variables defined here as NAME can be accessed in weight update model code strings using the \$(NAME) syntax.
- SET\_SIM\_CODE(SIM\_CODE): defines the simulation code that is used when a true spike is detected. The update is performed only in timesteps after a neuron in the presynaptic population has fulfilled its threshold detection condition. Typically, spikes lead to update of synaptic variables that then lead to the activation of input into the post-synaptic neuron. Most of the time these inputs add linearly at the post-synaptic neuron. This is assumed in GeNN and the term to be added to the activation of the post-synaptic neuron should be applied using the the \$(addToInSyn, weight) function. For example

```
SET_SIM_CODE(
    "$(addToInSyn, $(inc));\n"
```

where "inc" is the increment of the synaptic input to a post-synaptic neuron for each pre-synaptic spike. The simulation code also typically contains updates to the internal synapse variables that may have contributed to . For an example, see WeightUpdateModels::StaticPulse for a simple synapse update model and Weight← UpdateModels::PiecewiseSTDP for a more complicated model that uses STDP. To apply input to the post-synaptic neuron with a dendritic (i.e. between the synapse and the postsynaptic neuron) delay you can instead use the \$(addToInSynDelay, weight, delay) function. For example

```
SET_SIM_CODE(
    "$(addToInSynDelay, $(inc), $(delay));");
```

where, once again, inc is the magnitude of the input step to apply and delay is the length of the dendritic delay in timesteps. By implementing delay as a weight update model variable, heterogeneous synaptic delays can be implemented. For an example, see WeightUpdateModels::StaticPulseDendriticDelay for a simple synapse update model with heterogeneous dendritic delays.

Note

When using dendritic delays, the **maximum** dendritic delay for a synapse populations must be specified using the SynapseGroup::setMaxDendriticDelayTimesteps() function.

• SET\_EVENT\_THRESHOLD\_CONDITION\_CODE(EVENT\_THRESHOLD\_CONDITION\_CODE) defines a condition for a synaptic event. This typically involves the pre-synaptic variables, e.g. the membrane potential:

```
SET_EVENT_THRESHOLD_CONDITION_CODE("$(V_pre) > -0.02");
```

Whenever this expression evaluates to true, the event code set using the SET\_EVENT\_CODE() macro is executed. For an example, see WeightUpdateModels::StaticGraded.

- SET\_EVENT\_CODE(EVENT\_CODE) defines the code that is used when the event threshold condition is met (as set using the SET\_EVENT\_THRESHOLD\_CONDITION\_CODE() macro).
- SET\_LEARN\_POST\_CODE(LEARN\_POST\_CODE) defines the code which is used in the learnSynapses 
  Post kernel/function, which performs updates to synapses that are triggered by post-synaptic spikes. This is 
  typically used in STDP-like models e.g. WeightUpdateModels::PiecewiseSTDP.
- SET\_SYNAPSE\_DYNAMICS\_CODE(SYNAPSE\_DYNAMICS\_CODE) defines code that is run for each synapse, each timestep i.e. unlike the others it is not event driven. This can be used where synapses have internal variables and dynamics that are described in continuous time, e.g. by ODEs. However using this mechanism is typically computationally very costly because of the large number of synapses in a typical network. By using the \$(addtoinsyn), \$(updatelinsyn) and \$(addToDenDelay) mechanisms discussed in the context of SET\_SIM\_CODE(), the synapse dynamics can also be used to implement continuous synapses for rate-based models.
- SET\_PRE\_SPIKE\_CODE() and SET\_POST\_SPIKE\_CODE() define code that is called whenever there is a pre or postsynaptic spike. Typically these code strings are used to update any pre or postsynaptic state variables.
- SET\_NEEDS\_PRE\_SPIKE\_TIME(PRE\_SPIKE\_TIME\_REQUIRED) and SET\_NEEDS\_POST\_SPIKE\_TI

  ME(POST\_SPIKE\_TIME\_REQUIRED) define whether the weight update needs to know the times of the spikes emitted from the pre and postsynaptic populations. For example an STDP rule would be likely to require:

```
SET_NEEDS_PRE_SPIKE_TIME(true);
SET_NEEDS_POST_SPIKE_TIME(true);
```

All code snippets, aside from those defined with SET\_PRE\_SPIKE\_CODE () and SET\_POST\_SPIKE\_COD $\leftarrow$  E (), can be used to manipulate any synapse variable and so learning rules can combine both time-drive and event-driven processes.

Previous | Top | Next

# 9.6 Postsynaptic integration methods

There are currently 3 built-in postsynaptic integration methods:

- PostsynapticModels::ExpCurr
- PostsynapticModels::ExpCond
- · PostsynapticModels::DeltaCurr

## 9.6.1 Defining a new postsynaptic model

The postsynaptic model defines how synaptic activation translates into an input current (or other input term for models that are not current based). It also can contain equations defining dynamics that are applied to the (summed) synaptic activation, e.g. an exponential decay over time.

In the same manner as to both the neuron and weight update models discussed in Defining your own neuron type and Defining a new weight update model, postsynamic model definitions are encapsulated in a class derived from PostsynapticModels::Base. Again, the methods that a postsynaptic model should implement can be implemented using the following macros:

- DECLARE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS), SET\_DERIVED\_PARAMS(), SET\_PARAM\_N
   AMES(), SET\_VARS() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- SET\_DECAY\_CODE(DECAY\_CODE) defines the code which provides the continuous time dynamics for the summed presynaptic inputs to the postsynaptic neuron. This usually consists of some kind of decay function.
- SET\_APPLY\_INPUT\_CODE(APPLY\_INPUT\_CODE) defines the code specifying the conversion from synaptic inputs to a postsynaptic neuron input current. e.g. for a conductance model:

```
SET_APPLY_INPUT_CODE("\$(Isyn) += \$(inSyn) * (\$(E) - \$(V))");
```

where \$(E) is a postsynaptic model parameter specifying reversal potential and \$(V) is the variable containing the postsynaptic neuron's membrane potential. As discussed in Built-in Variables in GeNN, \$(Isyn) is the built in variable used to sum neuron input. However additional input variables can be added to a neuron model using the SET ADDITIONAL INPUT VARS() macro (see Defining your own neuron type for more details).

Previous | Top | Next

#### 9.7 Current source models

There is a number of predefined models which can be used with the ModelSpec::addCurrentSource function:

- CurrentSourceModels::DC
- · CurrentSourceModels::GaussianNoise

#### 9.7.1 Defining your own current source model

In order to define a new current source type for use in a GeNN application, it is necessary to define a new class derived from CurrentSourceModels::Base. For convenience the methods this class should implement can be implemented using macros:

- DECLARE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS), SET\_DERIVED\_PARAMS(), SET\_PARAM\_N
   AMES(), SET\_VARS() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- SET\_INJECTION\_CODE(INJECTION\_CODE): where INJECTION\_CODE contains the code for injecting current into the neuron every simulation timestep. The \$(injectCurrent, ) function is used to inject current.

For example, using these macros, we can define a uniformly distributed noisy current source:

```
class UniformNoise : public CurrentSourceModels::Base
{
public:
    DECLARE_MODEL(UniformNoise, 1, 0);
    SET_SIM_CODE("$(injectCurrent, $(gennrand_uniform) * $(magnitude));");
    SET_PARAM_NAMES({"magnitude"});
};
```

# Previous | Top | Next

# 9.8 Synaptic matrix types

Synaptic matrix types are made up of two components: SynapseMatrixConnectivity and SynapseMatrixWeight. SynapseMatrixConnectivity defines what data structure is used to store the synaptic matrix:

- SynapseMatrixConnectivity::DENSE stores synaptic matrices as a dense matrix. Large dense matrices require a large amount of memory and if they contain a lot of zeros it may be inefficient.
- SynapseMatrixConnectivity::SPARSE stores synaptic matrices in a(padded) 'ragged array' format. In general,
  this is less efficient to traverse using a GPU than the dense matrix format but does result in significant memory
  savings for large matrices. Ragged matrix connectivity is stored using several variables whose names, like
  state variables, have the name of the synapse population appended to them:
  - 1. const unsigned int maxRowLength: a constant set via the SynapseGroup::setMaxconnections method which specifies the maximum number of connections in any given row (this is the width the structure is padded to).
  - 2. unsigned int \*rowLength (sized to number of presynaptic neurons): actual length of the row of connections associated with each presynaptic neuron
  - 3. unsigned int \*ind (sized to maxRowLength \* number of presynaptic neurons) ← : Indices of corresponding postsynaptic neurons concatenated for each presynaptic neuron. For example, consider a network of two presynaptic neurons connected to three postsynaptic neurons: 0th presynaptic neuron connected to 1st and 2nd postsynaptic neurons, the 1st presynaptic neuron connected only to the 0th neuron. The struct RaggedProjection should have these members, with indexing from 0 (where X represents a padding value):

```
maxRowLength = 2
ind = [1 2 0 X]
rowLength = [2 1]
```

Weight update model variables associated with the sparsely connected synaptic population will be kept in an array using the same indexing as ind. For example, a variable called g will be kept in an array such as:  $g=[g\_Pre0-Post1\ g\_pre0-post2\ g\_pre1-post0\ X]$ 

• SynapseMatrixConnectivity::BITMASK is an alternative sparse matrix implementation where which synapses within the matrix are present is specified as a binary array (see Insect olfaction model). This structure is somewhat less efficient than the SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::RAGGED formats and doesn't allow individual weights per synapse. However it does require the smallest amount of GPU memory for large networks.

Furthermore the SynapseMatrixWeight defines how

- SynapseMatrixWeight::INDIVIDUAL allows each individual synapse to have unique weight update model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushXXXXXStateToDevice function, where XXXX is the name of the synapse population.
- SynapseMatrixWeight::INDIVIDUAL\_PSM allows each postsynapic neuron to have unique post synaptic model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushxxxxxxstateToDevice function, where XXXX is the name of the synapse population.
- SynapseMatrixWeight::GLOBAL saves memory by only maintaining one copy of the weight update model variables. This is automatically initialized to the initial value passed to ModelSpec::addSynapsePopulation.

Only certain combinations of SynapseMatrixConnectivity and SynapseMatrixWeight are sensible therefore, to reduce confusion, the SynapseMatrixType enumeration defines the following options which can be passed to Model Spec::addSynapsePopulation:

- SynapseMatrixType::SPARSE\_GLOBALG
- SynapseMatrixType::SPARSE\_GLOBALG\_INDIVIDUAL\_PSM

- SynapseMatrixType::SPARSE\_INDIVIDUALG
- SynapseMatrixType::DENSE\_GLOBALG
- SynapseMatrixType::DENSE\_GLOBALG\_INDIVIDUAL\_PSM
- SynapseMatrixType::DENSE\_INDIVIDUALG
- SynapseMatrixType::BITMASK\_GLOBALG
- SynapseMatrixType::BITMASK\_GLOBALG\_INDIVIDUAL\_PSM

Previous | Top | Next

#### 9.9 Variable initialisation

Neuron, weight update and postsynaptic models all have state variables which GeNN can automatically initialise.

Previously we have shown variables being initialised to constant values such as:

state variables can also be left *uninitialised* leaving it up to the user code to initialise them between the calls to initialize() and initializeSparse():

or initialised using one of a number of predefined variable initialisation snippets:

- InitVarSnippet::Uniform
- InitVarSnippet::Normal
- InitVarSnippet::Exponential
- InitVarSnippet::Gamma

For example, to initialise a parameter using values drawn from the normal distribution:

## 9.9.1 Defining a new variable initialisation snippet

Similarly to neuron, weight update and postsynaptic models, new variable initialisation snippets can be created by simply defining a class in the model description. For example, when initialising excitatory (positive) synaptic weights with a normal distribution they should be clipped at 0 so the long tail of the normal distribution doesn't result in negative weights. This could be implemented using the following variable initialisation snippet which redraws until samples are within the desired bounds:

9.9 Variable initialisation 37

```
class NormalPositive : public InitVarSnippet::Base
{
public:
    DECLARE_SNIPPET(NormalPositive, 2);

SET_CODE(
        "scalar normal;"
        "do\n"
        "{\n"
        " normal = $(mean) + ($(gennrand_normal) * $(sd));\n"
        "} while (normal < 0.0);\n"
        "$(value) = normal;\n");

SET_PARAM_NAMES({"mean", "sd"});
};
IMPLEMENT_SNIPPET(NormalPositive);</pre>
```

Within the snippet of code specified using the SET\_CODE () macro, when initialisising neuron and postaynaptic model state variables, the \$(id) variable can be used to access the id of the neuron being initialised. Similarly, when initialising weight update model state variables, the \$(id\_pre) and \$(id\_post) variables can used to access the ids of the pre and postsynaptic neurons connected by the synapse being initialised.

#### 9.9.2 Variable locations

Once you have defined **how** your variables are going to be initialised you need to configure **where** they will be allocated. By default memory is allocated for variables on both the GPU and the host. However, the following alternative 'variable locations' are available:

- VarLocation::DEVICE Variables are only allocated on the GPU, saving memory but meaning that they can't easily be copied to the host best for internal state variables.
- · VarLocation::HOST DEVICE Variables are allocated on both the GPU and the host the default.
- VarLocation::HOST\_DEVICE\_ZERO\_COPY Variables are allocated as 'zero-copy' memory accessible to
  the host and GPU useful on devices such as Jetson TX1 where physical memory is shared between the
  GPU and CPU.

### Note

'Zero copy' memory is only supported on newer embedded systems such as the Jetson TX1 where there is no physical seperation between GPU and host memory and thus the same block of memory can be shared between them.

These modes can be set as a model default using ModelSpec::setDefaultVarLocation or on a pervariable basis using one of the following functions:

- NeuronGroup::setSpikeLocation
- NeuronGroup::setSpikeEventLocation
- · NeuronGroup::setSpikeTimeLocation
- · NeuronGroup::setVarLocation
- · SynapseGroup::setWUVarLocation
- SynapseGroup::setWUPreVarLocation
- SynapseGroup::setWUPostVarLocation
- SynapseGroup::setPSVarLocation
- SynapseGroup::setInSynVarLocation

# Previous | Top | Next

## 9.10 Sparse connectivity initialisation

Synaptic connectivity implemented using SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::

BITMASK can be automatically initialised.

This can be done using one of a number of predefined sparse connectivity initialisation snippets:

- InitSparseConnectivitySnippet::OneToOne
- InitSparseConnectivitySnippet::FixedProbability
- InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

For example, to initialise synaptic connectivity with a 10% connection probability (allowing connections between neurons with the same id):

#### 9.10.1 Defining a new sparse connectivity snippet

Similarly to variable initialisation snippets, sparse connectivity initialisation snippets can be created by simply defining a class in the model description.

For example, the following sparse connectivity initialisation snippet could be used to initialise a 'ring' of connectivity where each neuron is connected to a number of subsequent neurons specified using the numNeighbours parameter:

```
{\tt class} \ {\tt Ring: public InitSparseConnectivitySnippet::Base}
public:
    DECLARE_SNIPPET(Ring, 1);
    SET_ROW_BUILD_STATE_VARS({{"offset", {"unsigned int", 1}}});
    SET_ROW_BUILD CODE (
         "const unsigned int target = ($(id_pre) + offset) % $(num_post);\n"
        "$(addSynapse, target);\n"
        "if(offset > (unsigned int)$(numNeighbours)) {\n"
            $ (endRow); \n"
        "}\n");
    SET PARAM NAMES({"numNeighbours"});
    SET_CALC_MAX_ROW_LENGTH_FUNC (
        [] (unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
        1):
    SET_CALC_MAX_COL_LENGTH_FUNC(
        [](unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
        });
IMPLEMENT_SNIPPET(Ring);
```

Each *row* of sparse connectivity is initialised independantly by running the snippet of code specified using the SET\_ROW\_BUILD\_CODE() macro within a loop. The \$(num\_post) variable can be used to access the number of neurons in the postsynaptic population and the \$(id\_pre) variable can be used to access the index of the presynaptic neuron associated with the row being generated. The SET\_ROW\_BUILD\_STATE\_VARS() macro can be used to initialise state variables outside of the loop - in this case offset which is used to count the number of synapses created in each row. Synapses are added to the row using the \$(addSynapse, target) function and iteration is stopped using the \$(endRow) function. To avoid having to manually call SynapseGroup::setMaxConnections and SynapseGroup::setMaxSourceConnections, sparse connectivity snippets can also provide code to calculate the maximum row and column lengths this connectivity will result in using the SET\_CALC\_MAX\_ROW\_LENGTH\_F UNC() and SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC() macros. Alternatively, if the maximum row or column length is constant, the SET\_MAX\_ROW\_LENGTH() and SET\_MAX\_COL\_LENGTH() shorthand macros can be used.

10 Tutorial 1 39

## 9.10.2 Sparse connectivity locations

Once you have defined **how** sparse connectivity is going to be initialised, similarly to variables, you can control **where** it is allocated. This is controlled using the same VarLocations options described in section Variable locations and can either be set using the model default specifiued with ModelSpec::setDefault SparseConnectivityLocation or on a per-synapse group basis using SynapseGroup::setSparseConnectivityLocation.

Previous | Top | Next

## 10 Tutorial 1

In this tutorial we will go through step by step instructions how to create and run your first GeNN simulation from scratch.

## 10.1 The Model Definition

In this tutorial we will use a pre-defined Hodgkin-Huxley neuron model (NeuronModels::TraubMiles) and create a simulation consisting of ten such neurons without any synaptic connections. We will run this simulation on a GPU and save the results - firstly to stdout and then to file.

The first step is to write a model definition function in a model definition file. Create a new directory and, within that, create a new empty file called tenHHModel.cc using your favourite text editor, e.g.

```
>> emacs tenHHModel.cc &
```

#### Note

The ">>" in the example code snippets refers to a shell prompt in a unix shell, do not enter them as part of your shell commands.

The model definition file contains the definition of the network model we want to simulate. First, we need to include the GeNN model specification code modelSpec.h. Then the model definition takes the form of a function named modelDefinition that takes one argument, passed by reference, of type ModelSpec. Type in your  $tenH \leftarrow HModel.cc$  file:

```
// Model definintion file tenHHModel.cc
#include "modelSpec.h"

void modelDefinition(ModelSpec &model)
{
    // definition of tenHHModel
```

Two standard elements to the 'modelDefinition function are setting the simulation step size and setting the name of the model:

```
model.setDT(0.1);
model.setName("tenHHModel");
```

# Note

With this we have fixed the integration time step to 0.1 in the usual time units. The typical units in GeNN are ms, mV, nF, and  $\mu$ S. Therefore, this defines DT= 0.1 ms.

Making the actual model definition makes use of the ModelSpec::addNeuronPopulation and ModelSpec::add SynapsePopulation member functions of the ModelSpec object. The arguments to a call to ModelSpec::add NeuronPopulation are

- NeuronModel: template parameter specifying the neuron model class to use
- const std::string &name: the name of the population
- unsigned int size: The number of neurons in the population
- const NeuronModel::ParamValues &paramValues: Parameter values for the neurons in the population
- const NeuronModel::VarValues &varInitialisers: Initial values or initialisation snippets for variables of this neuron type

We first create the parameter and initial variable arrays,

#### Note

The comments are obviously only for clarity, they can in principle be omitted. To avoid any confusion about the meaning of parameters and variables, however, we recommend strongly to always include comments of this type.

Having defined the parameter values and initial values we can now create the neuron population,

This completes the model definition in this example. The complete tenHHModel.cc file now should look like this:

```
// Model definintion file tenHHModel.cc
#include "modelSpec.h"
void modelDefinition(ModelSpec &model)
   // definition of tenHHModel
   model.setDT(0.1);
   model.setName("tenHHModel");
   NeuronModels::TraubMiles::ParamValues p(
       7.15,
               // 0 - gNa: Na conductance in muS
// 1 - ENa: Na equi potential in mV
       50.0.
       NeuronModels::TraubMiles::VarValues ini(
       -60.0, // 0 - membrane potential V 0.0529324, // 1 - prob. for Na channel activation m
       0.5961207); // 3 - prob. for K channel activation n
   model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
     10, p, ini);
```

This model definition suffices to generate code for simulating the ten Hodgkin-Huxley neurons on the a GPU or CPU. The second part of a GeNN simulation is the user code that sets up the simulation, does the data handling for input and output and generally defines the numerical experiment to be run.

# 10.2 Building the model

To use GeNN to build your model description into simulation code, use a terminal to navigate to the directory containing your tenHHModel.cc file and, on Linux or Mac, type:

```
>> genn-buildmodel.sh tenHHModel.cc
```

Alternatively, on Windows, type:

```
>> genn-buildmodel.bat tenHHModel.cc
```

If you don't have an NVIDIA GPU and are running GeNN in CPU\_ONLY mode, you can invoke genn-buildmodel with a -c option so, on Linux or Mac:

```
>> genn-buildmodel.sh -c tenHHModel.cc
```

or on Windows:

```
>> genn-buildmodel.bat -c tenHHModel.cc
```

If GeNN has been added to your path and CUDA\_PATH is correctly configured, you should see some compile output ending in Model build complete ....

## 10.3 User Code

GeNN will now have generated the code to simulate the model for one timestep using a function stepTime(). To make use of this code, we need to define a minimal C/C++ main function. For the purposes of this tutorial we will initially simply run the model for one simulated second and record the final neuron variables into a file. Open a new empty file tenHHSimulation.cc in an editor and type

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();
    return 0;
```

This boiler plate code includes the header file for the generated code definitions.h in the subdirectory teneror HHModel\_CODE where GeNN deposits all generated code (this corresponds to the name passed to the Modele Spec::setName function). Calling allocateMem() allocates the memory structures for all neuron variables and initialize() launches a GPU kernel which initialise all state variables to their initial values. Now we can use the generated code to integrate the neuron equations provided by GeNN for 1000ms. To do so, we add after initialize();

Note

The t variable is provided by GeNN to keep track of the current simulation time in milliseconds.

```
while (t < 1000.0f) {
    stepTime();
}</pre>
```

and we need to copy the result back to the host before outputting it to stdout (this will do nothing if you are running the model on a CPU),

```
pullPoplStateFromDevice();
for (int j= 0; j < 10; j++) {
    std::cout << VPopl[j] << " ";
    std::cout << mPopl[j] << " ";
    std::cout << hPopl[j] << " ";
    std::cout << nPopl[j] << std::endl;
}</pre>
```

pullPop1StateFromDevice() copies all relevant state variables of the Pop1 neuron group from the GPU to the CPU main memory. Then we can output the results to stdout by looping through all 10 neurons and outputting the state variables VPop1, mPop1, hPop1, nPop1.

Note

The naming convention for variables in GeNN is the variable name defined by the neuron type, here TraubMiles defining V, m, h, and n, followed by the population name, here Pop1.

This completes the user code. The complete tenHHSimulation.cc file should now look like

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();
    while (t < 1000.0f) {
        stepTime();
    }
    pullPoplStateFromDevice();

    for (int j= 0; j < 10; j++) {
        std::cout << VPopl[j] << " ";
        std::cout << mPopl[j] << " ";
        std::cout << nPopl[j] << " ";
        std::cout << nPopl[j] << std::endl;
    }
    return 0;
}</pre>
```

# 10.4 Building the simulator (Linux or Mac)

On Linux and Mac, GeNN simulations are typically built using a simple Makefile which can be generated with the following command:

```
genn-create-user-project.sh tennHHModel tenHHSimulation.cc
```

This defines that the model is named tennHHModel and the simulation code is given in the file tenHH $\leftrightarrow$  Simulation.cc that we completed above. Now type

make

## 10.5 Building the simulator (Windows)

So that projects can be easily debugged within the Visual Studio IDE (see section Debugging suggestions for more details), Windows projects are built using an MSBuild script typically with the same title as the final executable. A suitable solution and project can be generated automatically with the following command:

```
genn-create-user-project.bat tennHHModel tenHHSimulation.cc
```

his defines that the model is named tennHHModel and the simulation code is given in the file  $tenHH \leftarrow Simulation.cc$  that we completed above. Now type

```
msbuild tennHHModel.sln /p:Configuration=Release /t:tennHHModel
```

## 10.6 Running the Simulation

You can now execute your newly-built simulator on Linux or Mac with

```
./tennHHModel
```

10.7 Reading 43

#### Or on Windows with

```
tennHHModel_Release
```

The output you obtain should look like

```
-63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243
```

# 10.7 Reading

This is not particularly interesting as we are just observing the final value of the membrane potentials. To see what is going on in the meantime, we need to copy intermediate values from the device and save them into a file. This can be done in many ways but one sensible way of doing this is to replace the calls to stepTime in tenHHSimulation.cc with something like this:

```
std::ofstream os("tenHH_output.V.dat");
while (t < 1000.0f) {
    stepTime();

    pullVPop1FromDevice();

    os << t << " ";
    for (int j= 0; j < 10; j++) {
        os << VPop1[j] << " ";
    }
    os << std::endl;
}
os.close();</pre>
```


# Note

t is a global variable updated by the GeNN code to keep track of elapsed simulation time in ms. we switched from using pullPop1StateFromDevice() to pullVPop1FromDevice() as we are now only interested in the membrane voltage of the neuron.

You will also need to add:

```
#include <fstream>
```

to the top of tenHHSimulation.cc. After building the model; and building and running the simulator as described above there should be a file tenHH\_output.V.dat in the same directory. If you plot column one (time) against the subsequent 10 columns (voltage of the 10 neurons), you should observe dynamics like this:



However so far, the neurons are not connected and do not receive input. As the NeuronModels::TraubMiles model is silent in such conditions, the membrane voltages of the 10 neurons will simply drift from the -60mV they were initialised at to their resting potential.

Previous | Top | Next

# 11 Tutorial 2

In this tutorial we will learn to add synapsePopulations to connect neurons in neuron groups to each other with synaptic models. As an example we will connect the ten Hodgkin-Huxley neurons from tutorial 1 in a ring of excitatory synapses.

First, copy the files from Tutorial 1 into a new directory and rename the tenHHModel.cc to tenHHRing Model.cc and tenHHSimulation.cc to tenHHRingSimulation.cc, e.g. on Linux or Mac:

```
>> cp -r tenHH_project tenHHRing_project
>> cd tenHHRing_project
>> mv tenHHModel.cc tenHHRingModel.cc
>> mv tenHHSimulation.cc tenHHRingSimulation.cc
```

Finally, to reduce confusion we should rename the model itself. Open tenHHRingModel.cc, change the model name inside,

```
model.setName("tenHHRing");
```

# 11.1 Defining the Detailed Synaptic Connections

We want to connect our ten neurons into a ring where each neuron connects to its neighbours. In order to initialise this connectivity we need to add a sparse connectivity initialisation snippet at the top of tenHHRingModel.cc:

The SET\_ROW\_BUILD\_CODE code string will be called to generate each row of the synaptic matrix (connections coming from a single presynaptic neuron) and, in this case, each row consists of a single synapses from the presynaptic neuron \$(id\_pre) to \$(id\_pre) + 1 (the modulus operator is used to ensure that the final connection between neuron 9 and 0 is made correctly). In order to allow GeNN to better optimise the generated code we also provide a maximum row length. In this case each row always contains only one synapse but, when more complex connectivity is used, the number of neurons in the pre and postsynaptic population as well as any parameters used to configure the snippet can be accessed from this function.

#### Note

When defining GeNN code strings, the \$(VariableName) syntax is used to refer to variables provided by GeNN and the \$(FunctionName, Parameter1,...) syntax is used to call functions provided by GeNN.

## 11.2 Adding Synaptic connections

Now we need additional initial values and parameters for the synapse and post-synaptic models. We will use the standard WeightUpdateModels::StaticPulse weight update model and PostsynapticModels::ExpCond post-synaptic model. They need the following initial variables and parameters:

#### Note

the WeightUpdateModels::StaticPulse weight update model has no parameters and the PostsynapticModels
::ExpCond post-synaptic model has no state variables.

We can then add a synapse population at the end of the modelDefinition(...) function,

```
model.addSynapsePopulation<WeightUpdateModels::StaticPulse
    , PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 10,
    "Popl", "Popl",
    {}, s_ini,
    ps_p, {},
    initConnectivity<Ring>());
```

The addSynapsePopulation parameters are

- WeightUpdateModel: template parameter specifying the type of weight update model (derived from Weight
   — UpdateModels::Base).
- PostsynapticModel: template parameter specifying the type of postsynaptic model (derived from PostsynapticModels::Base).
- · name string containing unique name of synapse population.
- mtype how the synaptic matrix associated with this synapse population should be represented. Here
   SynapseMatrixType::SPARSE\_GLOBALG means that there will be sparse connectivity and each connection
   will have the same weight (-0.2 as specified previously).
- delayStep integer specifying number of timesteps of propagation delay that spikes travelling through this synapses population should incur (or NO DELAY for none)
- · src string specifying name of presynaptic (source) population
- · trg string specifying name of postsynaptic (target) population
- weightParamValues parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.

- weightVarInitialisers initial values or initialisation snippets for the weight update model's state variables wrapped in a WeightUpdateModel::VarValues object.
- postsynapticParamValues parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
- postsynapticVarInitialisers initial values or initialisation snippets for the postsynaptic model wrapped in PostsynapticModel::VarValues object.
- connectivityInitialiser snippet and any paramaters (in this case there are none) used to initialise the synapse population's sparse connectivity.

Adding the addSynapsePopulation command to the model definition informs GeNN that there will be synapses between the named neuron populations, here between population Pop1 and itself. At this point our model definition file tenHHRingModel.cc should look like this

```
// Model definition file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET_ROW_BUILD_CODE(
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
"$(endRow);\n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET (Ring):
void modelDefinition(ModelSpec &model)
     // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
         7.15, // 0 - gNa: Na conductance in muS
                      // 1 - ENa: Na equi potential in mV
                     // 2 - gK: K conductance in muS
// 3 - EK: K equi potential in mV
         1.43.
         -95.0,
                     // 4 - g1: leak conductance in mus
// 5 - E1: leak equi potential in mV
// 6 - Cmem: membr. capacity density in nF
         0.02672,
         -63.563.
         0.143);
    NeuronModels::TraubMiles::VarValues ini(
                        // 0 - membrane potential V // 1 - prob. for Na channel activation m
         -60.0,
0.0529324,
                         // 2 - prob. for not Na channel blocking h
         0.3176767,
         0.5961207);
                        // 3 - prob. for K channel activation n
    model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
       10, p, ini);
    WeightUpdateModels::StaticPulse::VarValues s ini(
          -0.2); // 0 - g: the synaptic conductance value
    PostsynapticModels::ExpCond::ParamValues ps_p(
         1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
    model.addSvnapsePopulation<
       WeightUpdateModels::StaticPulse,
       PostsynapticModels::ExpCond>(
         "Pop1self", SynapseMatrixType::SPARSE_GLOBALG, 100,
         "Pop1", "Pop1",
         {}, s_ini,
         ps p, {},
         initConnectivity<Ring>());
```

We can now build our new model:

```
>> genn-buildmodel.sh tenHHRingModel.cc
```

Note

Again, if you don't have an NVIDIA GPU and are running GeNN in CPU\_ONLY mode, you can instead build with the -c option as described in Tutorial 1.


Now we can open the tenHHRingSimulation.cc file and update the file name of the model includes to match the name we set previously:

```
// tenHHRingModel simulation code
#include "tenHHRing_CODE/definitions.h"
```

Additionally, we need to add a call to a second initialisation function to main() after we call initialize():

```
initializeSparse();
```

This initializes any variables associated with the sparse connectivity we have added (and will also copy any manually initialised variables to the GPU). Then, after using the <code>genn-create-user-project</code> tool to create a new project with a model name of <code>tenhhRing</code> and using <code>tenhhRingSimulation.cc</code> rather than <code>tenhhesimulation.cc</code>, we can build and run our new simulator in the same way we did in Tutorial 1. However, even after all our hard work, if we plot the content of the first column against the subsequent 10 columns of <code>tenhesimple.V.dat</code> it looks very similar to the plot we obtained at the end of Tutorial 1.



This is because none of the neurons are spiking so there are no spikes to propagate around the ring.

# 11.3 Providing initial stimuli

We can use a NeuronModels::SpikeSource to inject an initial spike into the first neuron in the ring during the first timestep to start spikes propagating. Firstly we need to define another sparse connectivity initialisation snippet at the top of tenHHRingModel.cc which simply creates a single synapse on the first row of the synaptic matrix:

We then need to add it to the network by adding the following to the end of the modelDefinition(...) function:

and finally inject a spike in the first timestep (in the same way that the t variable is provided by GeNN to keep track of the current simulation time in milliseconds, iT is provided to keep track of it in timesteps):

```
if(iT == 0) {
    spikeCount_Stim = 1;
    spike_Stim[0] = 0;
    pushStimCurrentSpikesToDevice();
}
```

Note

 $spike\_Stim[n]$  is used to specify the indices of the neurons in population Stim spikes which should emit spikes where  $n \in [0, spikeCount\_Stim)$ .

At this point our user code tenHHRingModel.cc should look like this


```
// Model definintion file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET ROW BUILD CODE (
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
        "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT_SNIPPET(Ring);
class FirstToFirst : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(FirstToFirst, 0);
    SET_ROW_BUILD_CODE(
   "if($(id_pre) == 0) {\n"
           $ (addSynapse, $ (id_pre)); \n"
         "}\n"
         "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET(FirstToFirst);
void modelDefinition(ModelSpec &model)
    // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
         7.15,
                     // 0 - gNa: Na conductance in muS
                      // 1 - ENa: Na equi potential in mV
         1.43,
                      // 2 - gK: K conductance in muS \,
                     // 3 - EK: K equi potential in mV
         -95.0.
                     // 4 - gl: leak conductance in muS
// 5 - El: leak equi potential in mV
        0.02672.
         -63.563,
                     // 6 - Cmem: membr. capacity density in nF
         0.143);
    NeuronModels::TraubMiles::VarValues ini(
         -60.0,
                   // 0 - membrane potential V , // 1 - prob. for Na channel activation m
         0.0529324.
                         // 2 - prob. for not Na channel blocking h
         0.3176767,
         0.5961207);
                        // 3 - prob. for K channel activation n
```

```
model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
  10, p, ini);
model.addNeuronPopulation<NeuronModels::SpikeSource>("Stim"
  , 1, {}, {});
WeightUpdateModels::StaticPulse::VarValues s_ini(
      -0.2); // 0 - g: the synaptic conductance value
PostsynapticModels::ExpCond::ParamValues ps_p(
    1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 100, "Popl", "Popl",
    {}, s_ini, ps_p, {},
    initConnectivity<Ring>());
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
     "StimPop1", SynapseMatrixType::SPARSE_GLOBALG,
  NO_DELAY,
"Stim", "Pop1",
    {}, s_ini,
    ps_p, {},
initConnectivity<FirstToFirst>());
```

and tenHHRingSimulation.cc' should look like this:

```
// Standard C++ includes
#include <fstream>
// tenHHRing simulation code
#include "tenHHRing_CODE/definitions.h"
int main()
    allocateMem();
    initialize();
    initializeSparse();
    std::ofstream os("tenHHRing_output.V.dat");
    while(t < 200.0f) {
    if(iT == 0) {
             glbSpkStim[0] = 0;
glbSpkCntStim[0] = 1;
              pushStimCurrentSpikesToDevice();
         stepTimeU();
         pullVPop1FromDevice();
         for (int j= 0; j < 10; j++) {
   os << VPop1[j] << " ";</pre>
         os << std::endl;
    os.close();
    return 0;
```

Finally if we build, make and run this model; and plot the first 200 ms of the ten neurons' membrane voltages - they now looks like this:



Previous | Top | Next

# 12 Best practices guide

GeNN generates code according to the network model defined by the user, and allows users to include the generated code in their programs as they want. Here we provide a guideline to setup GeNN and use generated functions. We recommend users to also have a look at the Examples, and to follow the tutorials Tutorial 1 and Tutorial 2.

# 12.1 Creating and simulating a network model

The user is first expected to create an object of class ModelSpec by creating the function modelDefinition() which includes calls to following methods:

- · ModelSpec::setDT();
- ModelSpec::setName();

Then add neuron populations by:

ModelSpec::addNeuronPopulation();

for each neuron population. Add synapse populations by:

ModelSpec::addSynapsePopulation();

for each synapse population.

Other optional functions are explained in ModelSpec class reference. At the end the function should look like this:

```
void modelDefinition(ModelSpec &model) {
  model.setDT(0.5);
  model.setName("YourModelName");
  model.addNeuronPopulation(...);
  ...
  model.addSynapsePopulation(...);
  ...
}
```

modelSpec.h should be included in the file where this function is defined.

This function will be called by generateALL.cc to create corresponding CPU and GPU simulation codes under the <YourModelName> CODE directory.

These functions can then be used in a .cc file which runs the simulation. This file should include <YourModel ← Name>\_CODE/definitions.h. Generated code differ from one model to the other, but core functions are the same and they should be called in correct order. First, the following variables should be defined and initialized:

- ModelSpec model // initialized by calling modelDefinition(model)
- Array containing current input (if any)

Any variables marked as unintialised using the uninitialisedVar() function or sparse connectivity not initialised using a snippet must be initialised by the user between calls to initialize() and initialize  $\leftarrow$  Sparse(). Core functions generated by GeNN to be included in the user code include:

```
allocateMem()
initialize()
initializeSparse()
push<neuron or synapse name>StateToDevice()
pull<neuron or synapse name>StateFromDevice()
push<neuron name>SpikesToDevice()
pull<neuron name>SpikesFromDevice()
push<neuron name>SpikesFromDevice()
push<neuron name>SpikesEventsToDevice()
pull<neuron name>SpikesEventsFromDevice()
push<neuron name>SpikeTimesToDevice()
push<neuron name>SpikeTimesFromDevice()
pull<neuron name>CurrentSpikesToDevice()
push<neuron name>CurrentSpikesFromDevice()
pull<neuron name>CurrentSpikesFromDevice()
```

• push<neuron name>CurrentSpikesEventsToDevice()

• pull<synapse name>ConnectivityFromDevice()

push<synapse name>ConnectivityToDevice()

• pull<neuron name>CurrentSpikesEventsFromDevice()

pull<var name><neuron or synapse name>FromDevice()

• push<var name><neuron or synapse name>ToDevice()

• copyCurrentSpikesFromDevice()

• copyStateToDevice()

• copyStateFromDevice()

You can use the <code>push<neuron</code> or <code>synapse</code> <code>name>StateToDevice()</code> to copy from the host to the  $G \leftarrow PU$ . At the end of your simulation, if you want to access the variables you need to copy them back from the device using the <code>pull<neuron</code> or <code>synapse</code> <code>name>StateFromDevice()</code> function or one of the more finegrained functions listed above. Copying elements between the GPU and the host memory is very costly in terms of performance and should only be done when needed and the amount of data being copied should be minimized.

#### 12.1.1 Extra Global Parameters

If extra global parameters have a "scalar" type such as float they can be set directly from simulation code. For example the extra global parameter "reward" of population "Pop" could be set with:

```
rewardPop = 5.0f;
```

However, if extra global parameters have a pointer type such as float\*, GeNN generates additional functions to allocate, free and copy these variables between host and device:

- allocate<var name><neuron or synapse name>
- free<var name><neuron or synapse name>
- push<var name><neuron or synapse name>ToDevice
- pull<var name><neuron or synapse name>FromDevice These operate in much the same manner as the functions for interacting with standard variables described above but the allocate, push and pull functions all take a "count" parameter specifying how many entries the extra global parameter array should be.

# 12.2 Floating point precision

Double precision floating point numbers are supported by devices with compute capability 1.3 or higher. If you have an older GPU, you need to use single precision floating point in your models and simulation.

GPUs are designed to work better with single precision while double precision is the standard for CPUs. This difference should be kept in mind while comparing performance.

While setting up the network for GeNN, double precision floating point numbers are used as this part is done on the CPU. For the simulation, GeNN lets users choose between single or double precision. Overall, new variables in the generated code are defined with the precision specified by ModelSpec::setPrecision(unsigned int), providing GENN\_FLOAT or GENN\_DOUBLE as argument. GENN\_FLOAT is the default value. The keyword scalar can be used in the user-defined model codes for a variable that could either be single or double precision. This keyword is detected at code generation and substituted with "float" or "double" according to the precision set by ModelSpec::setPrecision(unsigned int).

There may be ambiguities in arithmetic operations using explicit numbers. Standard C compilers presume that any number defined as "X" is an integer and any number defined as "X.Y" is a double. Make sure to use the same precision in your operations in order to avoid performance loss.

# 12.3 Working with variables in GeNN

# 12.3.1 Model variables

User-defined model variables originate from classes derived off the NeuronModels::Base, WeightUpdateModels ::Base or PostsynapticModels::Base classes. The name of model variable is defined in the model type, i.e. with a statement such as

```
SET_VARS({{"V", "scalar"}});
```

When a neuron or synapse population using this model is added to the model, the full GeNN name of the variable will be obtained by concatenating the variable name with the name of the population. For example if we a add a population called Pop using a model which contains our V variable, a variable VPop of type scalar\* will be available in the global namespace of the simulation program. GeNN will pre-allocate this C array to the correct size of elements corresponding to the size of the neuron population. GeNN will also free these variables when the provided function freeMem() is called. Users can otherwise manipulate these variable arrays as they wish. For convenience, GeNN provides functions to copy each state variable from the device into host memory and vice versa e.g. pullVPopFromDevice() and pushVPoptoDevice(). Alternatively, all state variables associated with a population can be copied using a single call E.g.

```
pullPopStateFromDevice();
```

These conventions also apply to the the variables of postsynaptic and weight update models.

#### Note

Be aware that the above naming conventions do assume that variables from the weightupdate models and the postSynModels that are used together in a synapse population are unique. If both the weightupdate model and the postSynModel have a variable of the same name, the behaviour is undefined.

### 12.3.2 Built-in Variables in GeNN

GeNN has no explicitly hard-coded synapse and neuron variables. Users are free to name the variable of their models as they want. However, there are some reserved variables that are used for intermediary calculations and communication between different parts of the generated code. They can be used in the user defined code but no other variables should be defined with these names.

- DT: Time step (typically in ms) for simulation; Neuron integration can be done in multiple sub-steps inside
  the neuron model for numerical stability (see Traub-Miles and Izhikevich neuron model variations in Neuron
  models).
- inSyn: This is an intermediary synapse variable which contains the summed input into a postsynaptic neuron (originating from the addtoinSyn variables of the incoming synapses).
- Isyn: This is a local variable which contains the (summed) input current to a neuron. It is typically the sum of any explicit current input and all synaptic inputs. The way its value is calculated during the update of the postsynaptic neuron is defined by the code provided in the postsynaptic model. For example, the standard PostsynapticModels::ExpCond postsynaptic model defines

which implements a conductance based synapse in which the postsynaptic current is given by  $I_{\text{syn}} = g * s * (V_{\text{rev}} - V_{\text{post}})$ .

The value resulting from the current converter code is assigned to Isyn and can then be used in neuron sim code like so:

```
(V) += (-(V) + (Isyn)) *DT
```

sT: This is a neuron variable containing the last spike time of each neuron and is automatically generated for
pre and postsynaptic neuron groups if they are connected using a synapse population with a weight update
model that has SET\_NEEDS\_PRE\_SPIKE\_TIME(true) or SET\_NEEDS\_POST\_SPIKE\_TIME(true) set.

In addition to these variables, neuron variables can be referred to in the synapse models by calling \$(<neuronVar~Name>\_pre) for the presynaptic neuron population, and \$(<neuronVarName>\_post) for the postsynaptic population. For example, \$(sT\_pre), \$(sT\_post), \$(V\_pre), etc.

# 12.4 Debugging suggestions

In Linux, users can call <code>cuda-gdb</code> to debug on the GPU. Example projects in the <code>userproject</code> directory come with a flag to enable debugging (-debug). genn-buildmodel.sh has a debug flag (-d) to generate debugging data. If you are executing a project with debugging on, the code will be compiled with -g -G flags. In CPU mode the executable will be run in gdb, and in GPU mode it will be run in cuda-gdb in tui mode.

Note

Do not forget to switch debugging flags -g and -G off after debugging is complete as they may negatively affect performance.

On Mac, some versions of clang aren't supported by the CUDA toolkit. This is a recurring problem on Fedora as well, where CUDA doesn't keep up with GCC releases. You can either hack the CUDA header which checks compiler versions - cuda/include/host\_config.h - or just use an older XCode version (6.4 works fine).

On Windows models can also be debugged and developed by opening the sln file used to build the model in Visual Studio. From here files can be added to the project, build settings can be adjusted and the full suite of Visual Studio debugging and profiling tools can be used.

Note

When opening the models in the userproject directory in Visual Studio, right-click on the project in the solution explorer, select 'Properties'. Then, making sure the desired configuration is selected, navigate to 'Debugging' under 'Configuration Properties', set the 'Working Directory' to '..' and the 'Command Arguments' to match those passed to genn-buildmodel e.g. 'outdir' to use an output directory called outdir.

## Previous | Top | Next

# 13 Credits

GeNN was created by Thomas Nowotny.

GeNN is currently maintained and developed by James Knight.

Current sources and PyGeNN were first implemented by Anton Komissarov.

Izhikevich model and sparse connectivity by Esin Yavuz.

Block size optimisations, delayed synapses and page-locked memory by James Turner.

Automatic brackets and dense-to-sparse network conversion helper tools by Alan Diamond.

User-defined synaptic and postsynaptic methods by Alex Cope and Esin Yavuz.

Example projects were provided by Alan Diamond, James Turner, Esin Yavuz and Thomas Nowotny.

MPI support was largely developed by Mengchi Zhang.

## **Previous**

# 14 Namespace Index

## 14.1 Namespace List

Here is a list of all namespaces with brief descriptions:

### CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc

15 Hierarchical Index 55

CodeGenerator::CUDA	72
CodeGenerator::CUDA::Optimiser	74
CodeGenerator::CUDA::Utils	74
CodeGenerator::SingleThreadedCPU	75
CodeGenerator::SingleThreadedCPU::Optimiser	75
CurrentSourceModels	75
filesystem	76
InitSparseConnectivitySnippet  Base class for all sparse connectivity initialisation snippets	76
InitVarSnippet  Base class for all value initialisation snippets	76
Models	77
NeuronModels	77
PostsynapticModels	77
pygenn	78
pygenn.genn_groups	78
pygenn.genn_model	78
pygenn.model_preprocessor	86
Snippet	90
Utils	90
WeightUpdateModels	91
15 Hierarchical Index	
15.1 Class Hierarchy	
This inheritance list is sorted roughly, but not completely, alphabetically:	
CodeGenerator::BackendBase	114
CodeGenerator::CUDA::Backend	91
CodeGenerator::SingleThreadedCPU::Backend	103
Snippet::Base	134
InitSparseConnectivitySnippet::Base	127
InitSparseConnectivitySnippet::FixedProbabilityBase	161
InitSparseConnectivitySnippet::FixedProbability	160
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse	163

	InitSparseConnectivitySnippet::OneToOne	218
	InitSparseConnectivitySnippet::Uninitialised	282
Ini	tVarSnippet::Base	129
	InitVarSnippet::Constant	142
	InitVarSnippet::Exponential	158
	InitVarSnippet::Gamma	165
	InitVarSnippet::Normal	216
	InitVarSnippet::Uniform	280
	InitVarSnippet::Uninitialised	281
Мо	odels::Base	130
	CurrentSourceModels::Base	127
	CurrentSourceModels::DC	150
	CurrentSourceModels::GaussianNoise	166
	NeuronModels::Base	131
	NeuronModels::lzhikevich	180
	NeuronModels::IzhikevichVariable	183
	NeuronModels::LIF	185
	NeuronModels::Poisson	223
	NeuronModels::PoissonNew	226
	NeuronModels::RulkovMap	232
	NeuronModels::SpikeSource	236
	NeuronModels::SpikeSourceArray	238
	NeuronModels::TraubMiles	<b>27</b> 1
	NeuronModels::TraubMilesAlt	275
	NeuronModels::TraubMilesFast	276
	NeuronModels::TraubMilesNStep	278
	PostsynapticModels::Base	133
	PostsynapticModels::DeltaCurr	151
	PostsynapticModels::ExpCond	154
	PostsynapticModels::ExpCurr	156
	WeightUpdateModels::Base	136
	WeightUndateModels::PiecewiseSTDP	220

WeightUpdateModels::StaticGraded	240
WeightUpdateModels::StaticPulse	242
WeightUpdateModels::StaticPulseDendriticDelay Baselter	244
CodeGenerator::StructNameConstIter< BaseIter >	246
CodeGenerator::CodeStream::CB	139
CurrentSource	146
CurrentSourceInternal	149
Snippet::Base::DerivedParam	153
CodeGenerator::FunctionTemplate	164
Snippet::Init< SnippetBase >	179
Snippet::Init< Base >	179
InitSparseConnectivitySnippet::Init	179
Snippet::Init< InitVarSnippet::Base >	179
Models::VarInit  std::ios_base   std::basic_ios   std::basic_ostream   std::ostream	287
CodeGenerator::CodeStream	140
CodeGenerator::TeeStream	271
CodeGenerator::MemAlloc	188
ModelSpec	189
ModelSpecInternal	202
CodeGenerator::NameIterCtx < Container >	203
NeuronGroup	208
NeuronGroupInternal	216
CodeGenerator::CodeStream::OB object	217
pygenn.genn_groups.Group	177
pygenn.genn_groups.CurrentSource	143
pygenn.genn_groups.NeuronGroup	204
pygenn.genn_groups.SynapseGroup	248
pygenn.genn_model.GeNNModel	168
pygenn.model preprocessor.ExtraGlobalVariable	159

pygenn.model_preprocessor.Variable	285
Snippet::Base::ParamVal	219
CodeGenerator::PreferencesBase	231
CodeGenerator::CUDA::Preferences	229
CodeGenerator::SingleThreadedCPU::Preferences	231
CodeGenerator::CodeStream::Scope streambuf	235
CodeGenerator::TeeBuf	270
CodeGenerator::Substitutions	247
SynapseGroup	257
SynapseGroupInternal	269
Snippet::ValueBase < NumVars >	283
Snippet::ValueBase < 0 >	283
Snippet::Base::Var	284
Models::VarInitContainerBase< NumVars >	288
Models::VarInitContainerBase< 0 >	289
16 Class Index	
16.1 Class List	
Here are the classes, structs, unions and interfaces with brief descriptions:	
CodeGenerator::CUDA::Backend	91
CodeGenerator::SingleThreadedCPU::Backend	103
CodeGenerator::BackendBase	114
CurrentSourceModels::Base Base class for all current source models	127
InitSparseConnectivitySnippet::Base	127
InitVarSnippet::Base	129
Models::Base  Base class for all models - in addition to the parameters snippets have, models can have state variables	130
NeuronModels::Base Base class for all neuron models	131
PostsynapticModels::Base Base class for all postsynaptic models	133

16.1 Class List 59

Snippet::Base Base class for all code snippets	134
WeightUpdateModels::Base Base class for all weight update models	136
CodeGenerator::CodeStream::CB A close bracket marker	139
CodeGenerator::CodeStream	140
InitVarSnippet::Constant Initialises variable to a constant value	142
pygenn.genn_groups.CurrentSource Class representing a current injection into a group of neurons	143
CurrentSource	146
CurrentSourceInternal	149
CurrentSourceModels::DC DC source	150
PostsynapticModels::DeltaCurr Simple delta current synapse	151
Snippet::Base::DerivedParam A derived parameter has a name and a function for obtaining its value	153
PostsynapticModels::ExpCond Exponential decay with synaptic input treated as a conductance value	154
PostsynapticModels::ExpCurr Exponential decay with synaptic input treated as a current value	156
InitVarSnippet::Exponential Initialises variable by sampling from the exponential distribution	158
pygenn.model_preprocessor.ExtraGlobalVariable Class holding information about GeNN extra global pointer variable	159
InitSparseConnectivitySnippet::FixedProbability	160
InitSparseConnectivitySnippet::FixedProbabilityBase	161
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse	163
CodeGenerator::FunctionTemplate	164
InitVarSnippet::Gamma Initialises variable by sampling from the exponential distribution	165
CurrentSourceModels::GaussianNoise Noisy current source with noise drawn from normal distribution	166
pygenn.genn_model.GeNNModel GeNNModel class This class helps to define, build and run a GeNN model from python	168
pygenn.genn_groups.Group Parent class of NeuronGroup, SynapseGroup and CurrentSource	177

InitSparseConnectivitySnippet::Init	179
Snippet::Init< SnippetBase >	179
NeuronModels::Izhikevich Izhikevich neuron with fixed parameters [1]	180
NeuronModels::IzhikevichVariable Izhikevich neuron with variable parameters [1]	183
NeuronModels::LIF	185
CodeGenerator::MemAlloc	188
ModelSpec Object used for specifying a neuronal network model	189
ModelSpecInternal	202
CodeGenerator::NameIterCtx < Container >	203
pygenn.genn_groups.NeuronGroup Class representing a group of neurons	204
NeuronGroup	208
NeuronGroupInternal	216
InitVarSnippet::Normal Initialises variable by sampling from the normal distribution	216
CodeGenerator::CodeStream::OB An open bracket marker	217
InitSparseConnectivitySnippet::OneToOne Initialises connectivity to a 'one-to-one' diagonal matrix	218
Snippet::Base::ParamVal	219
WeightUpdateModels::PiecewiseSTDP  This is a simple STDP rule including a time delay for the finite transmission speed of the synapse	220
NeuronModels::Poisson Poisson neurons	223
NeuronModels::PoissonNew Poisson neurons	226
CodeGenerator::CUDA::Preferences Preferences for CUDA backend	229
CodeGenerator::SingleThreadedCPU::Preferences	231
CodeGenerator::PreferencesBase  Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator	231
NeuronModels::RulkovMap Rulkov Map neuron	232
CodeGenerator::CodeStream::Scope	235

16.1 Class List 61

NeuronModels::SpikeSource Empty neuron which allows setting spikes from external sources	236
NeuronModels::SpikeSourceArray Spike source array	238
WeightUpdateModels::StaticGraded Graded-potential, static synapse	240
WeightUpdateModels::StaticPulse Pulse-coupled, static synapse	242
WeightUpdateModels::StaticPulseDendriticDelay Pulse-coupled, static synapse with heterogenous dendritic delays	244
CodeGenerator::StructNameConstIter< Baselter > Custom iterator for iterating through the containers of structs with 'name' members	246
CodeGenerator::Substitutions	247
pygenn.genn_groups.SynapseGroup Class representing synaptic connection between two groups of neurons	248
SynapseGroup	257
SynapseGroupInternal	269
CodeGenerator::TeeBuf	270
CodeGenerator::TeeStream	271
NeuronModels::TraubMiles Hodgkin-Huxley neurons with Traub & Miles algorithm	271
NeuronModels::TraubMilesAlt Hodgkin-Huxley neurons with Traub & Miles algorithm	275
NeuronModels::TraubMilesFast Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations	276
NeuronModels::TraubMilesNStep Hodgkin-Huxley neurons with Traub & Miles algorithm	278
InitVarSnippet::Uniform Initialises variable by sampling from the uniform distribution	280
InitVarSnippet::Uninitialised  Used to mark variables as uninitialised - no initialisation code will be run	281
InitSparseConnectivitySnippet::Uninitialised Used to mark connectivity as uninitialised - no initialisation code will be run	282
Snippet::ValueBase < NumVars >	283
Snippet::ValueBase < 0 >	283
Snippet::Base::Var A variable has a name and a type	284
pygenn.model_preprocessor.Variable Class holding information about GeNN variables	285

	Models::VarInit	287
	Models::VarInitContainerBase < NumVars >	288
	Models::VarInitContainerBase< 0 >	289
17	' File Index	
17	.1 File List	
He	ere is a list of all files with brief descriptions:	
	initpy	290
	cuda/backend.cc	290
	single_threaded_cpu/backend.cc	290
	cuda/backend.h	291
	single_threaded_cpu/backend.h	292
	backendBase.cc	292
	backendBase.h	293
	backendExport.h	293
	binomial.cc	293
	binomial.h	294
	codeGenUtils.cc	294
	codeGenUtils.h	295
	codeStream.cc	297
	codeStream.h	297
	currentSource.cc	298
	currentSource.h	298
	currentSourceInternal.h	298
	currentSourceModels.cc	298
	currentSourceModels.h	299
	generateAll.cc	300
	generateAll.h	300
	generateInit.cc	300
	generateInit.h	300
	generateMakefile.cc	301
	generateMakefile.h	301

17.1 File List 63

Contains functions to generate code for running the simulation with MPI. Part of the code generation section	<b>30</b> 1
generateMPI.h  Contains functions to generate code for running the simulation with MPI. Part of the code generation section	<b>30</b> 1
generateMSBuild.cc	302
generateMSBuild.h	302
generateNeuronUpdate.cc	302
generateNeuronUpdate.h	303
generateRunner.cc	303
generateRunner.h	303
generateSupportCode.cc	303
generateSupportCode.h	304
generateSynapseUpdate.cc	304
generateSynapseUpdate.h	304
generator.cc	304
genn_groups.py	305
genn_model.py	306
gennExport.h	307
gennUtils.cc	307
gennUtils.h	307
initSparseConnectivitySnippet.cc	308
initSparseConnectivitySnippet.h	309
initVarSnippet.cc	310
initVarSnippet.h	311
model_preprocessor.py	312
models.h	313
modelSpec.cc	314
modelSpec.h  Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections	314
modelSpecInternal.h	318
neuronGroup.cc	318

neuronGroup.h	319
neuronGroupInternal.h	319
neuronModels.cc	319
neuronModels.h	321
cuda/optimiser.cc	323
single_threaded_cpu/optimiser.cc	323
cuda/optimiser.h	324
single_threaded_cpu/optimiser.h	324
postsynapticModels.cc	324
postsynapticModels.h	325
snippet.h	326
substitutions.h	327
synapseGroup.cc	328
synapseGroup.h	328
synapseGroupInternal.h	328
synapseMatrixType.h	328
teeStream.h	330
utils.h	331
variableMode.h	331
weightUpdateModels.cc	332
weightUpdateModels.h	333

# 18 Namespace Documentation

# 18.1 CodeGenerator Namespace Reference

 $\label{lem:helper class} \mbox{ Helper class for generating code - automatically inserts brackets, indents etc.}$ 

# Namespaces

- CUDA
- SingleThreadedCPU

# Classes

- class BackendBase
- class CodeStream
- struct FunctionTemplate

- · class MemAlloc
- struct NameIterCtx
- · struct PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

class StructNameConstIter

Custom iterator for iterating through the containers of structs with 'name' members.

- · class Substitutions
- · class TeeBuf
- class TeeStream

## **Typedefs**

- typedef NamelterCtx < Snippet::Base::VarVec > VarNamelterCtx
- typedef NamelterCtx < Snippet::Base::DerivedParamVec > DerivedParamNamelterCtx
- typedef NameIterCtx < Snippet::Base::ParamValVec > ParamValIterCtx

#### **Functions**

void substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

bool regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

This function substitutes function calls in the form:

template<typename Namelter >

void name\_substitutions (std::string &code, const std::string &prefix, Namelter namesBegin, Namelter namesEnd, const std::string &postfix="", const std::string &ext="")

This function performs a list of name substitutions for variables in code snippets.

void name\_substitutions (std::string &code, const std::string &prefix, const std::vector< std::string > &names, const std::string &postfix="", const std::string &ext="")

This function performs a list of name substitutions for variables in code snippets.

template < class T , typename std::enable\_if < std::is\_floating\_point < T >::value >::type \* = nullptr > void writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

• template < class T , typename std::enable\_if < std::is\_floating\_point < T >::value >::type \* = nullptr > std::string writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

template<typename Namelter >

void value\_substitutions (std::string &code, Namelter namesBegin, Namelter namesEnd, const std::vector< double > &values, const std::string &ext="")

This function performs a list of value substitutions for parameters in code snippets.

void value\_substitutions (std::string &code, const std::vector< std::string > &names, const std::vector< double > &values, const std::string &ext="")

This function performs a list of value substitutions for parameters in code snippets.

std::string ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

 void preNeuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postldx, const std::string &dev← Prefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

 void postNeuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std::string &preldx, const std::string &dev← Prefix, const std::string &postVarPrefix="", const std::string &postVarSuffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

void neuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroupInternal &sg, const std
 ::string &preldx, const std::string &postIdx, const std::string &devPrefix, double dt, const std::string &preVar←
 Prefix="", const std::string &preVarSuffix="", const std::string &postVarPrefix="", const std::string &postVar←
 Suffix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

- GENN\_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN\_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::CB &cb)</li>
- GENN\_EXPORT std::vector< std::string > generateAll (const ModelSpecInternal &model, const Backend←
   Base &backend, const filesystem::path &outputPath, bool standaloneModules=false)
- void generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- void GENN\_EXPORT generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector
   std::string > &moduleNames)

A function that generates predominantly MPI infrastructure code.

- void GENN\_EXPORT generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)
- void generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- MemAlloc generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)
- void generateSupportCode (CodeStream &os, const ModelSpecInternal &model)
- void generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

## 18.1.1 Detailed Description

Helper class for generating code - automatically inserts brackets, indents etc.

Based heavily on: https://stackoverflow.com/questions/15053753/writing-a-manipulator-for-a-cus

#### 18.1.2 Typedef Documentation

#### 18.1.2.1 DerivedParamNameIterCtx

typedef NameIterCtx<Snippet::Base::DerivedParamVec> CodeGenerator::DerivedParamNameIterCtx

### 18.1.2.2 ParamVallterCtx

typedef NameIterCtx<Snippet::Base::ParamValVec> CodeGenerator::ParamValIterCtx

#### 18.1.2.3 VarNamelterCtx

```
typedef NameIterCtx<Snippet::Base::VarVec> CodeGenerator::VarNameIterCtx
```

#### 18.1.3 Function Documentation

#### 18.1.3.1 checkUnreplacedVariables()

This function checks for unknown variable definitions and returns a gennError if any are found.

#### 18.1.3.2 ensureFtype()

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

#### 18.1.3.3 functionSubstitute()

```
void CodeGenerator::functionSubstitute (
    std::string & code,
    const std::string & funcName,
    unsigned int numParams,
    const std::string & replaceFuncTemplate )
```

This function substitutes function calls in the form:

\$(functionName, parameter1, param2Function(0.12, "string"))

with replacement templates in the form:

```
actualFunction(CONSTANT, $(0), $(1))
```

## 18.1.3.4 generateAll()

## 18.1.3.5 generateInit()

## 18.1.3.6 generateMakefile()

A function that generates predominantly MPI infrastructure code.

In this function MPI infrastructure code are generated, including: MPI send and receive functions.

## 18.1.3.8 generateMSBuild()

```
void CodeGenerator::generateMSBuild (
    std::ostream & os,
    const BackendBase & backend,
    const std::string & projectGUID,
    const std::vector< std::string > & moduleNames )
```

# 18.1.3.9 generateNeuronUpdate()

## 18.1.3.10 generateRunner()

# 18.1.3.11 generateSupportCode()

## 18.1.3.12 generateSynapseUpdate()

```
void CodeGenerator::generateSynapseUpdate (
```

```
CodeStream & os,
const ModelSpecInternal & model,
const BackendBase & backend,
bool standaloneModules )
```

#### 18.1.3.13 name\_substitutions() [1/2]

```
template<typename NameIter >
void CodeGenerator::name_substitutions (
    std::string & code,
    const std::string & prefix,
    NameIter namesBegin,
    NameIter namesEnd,
    const std::string & postfix = "",
    const std::string & ext = "") [inline]
```

This function performs a list of name substitutions for variables in code snippets.

## 18.1.3.14 name\_substitutions() [2/2]

```
void CodeGenerator::name_substitutions (
    std::string & code,
    const std::string & prefix,
    const std::vector< std::string > & names,
    const std::string & postfix = "",
    const std::string & ext = "") [inline]
```

This function performs a list of name substitutions for variables in code snippets.

## 18.1.3.15 neuronSubstitutionsInSynapticCode()

```
void CodeGenerator::neuronSubstitutionsInSynapticCode (
    std::string & wCode,
    const SynapseGroupInternal & sg,
    const std::string & preIdx,
    const std::string & postIdx,
    const std::string & devPrefix,
    double dt,
    const std::string & preVarPrefix = "",
    const std::string & preVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarSuffix = "")
```

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

#### **Parameters**

wCode	the code string to work on
sg	the synapse group connecting the pre and postsynaptic neuron populations whose parameters might need to be substituted
preldx	index of the pre-synaptic neuron to be accessed for _pre variables; differs for different Span)
postldx	index of the post-synaptic neuron to be accessed for _post variables; differs for different Span)

#### **Parameters**

devPrefix	device prefix, "dd_" for GPU, nothing for CPU
dt	simulation timestep (ms)
preVarPrefix	prefix to be used for presynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)
postVarPrefix	prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)

# 18.1.3.18 postNeuronSubstitutionsInSynapticCode()

```
void CodeGenerator::postNeuronSubstitutionsInSynapticCode (
    std::string & wCode,
    const SynapseGroupInternal & sg,
    const std::string & offset,
    const std::string & backPropDelayOffset,
    const std::string & preIdx,
    const std::string & devPrefix,
    const std::string & postVarPrefix = "",
    const std::string & postVarSuffix = "")
```

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

## **Parameters**

wCode	the code string to work on
devPrefix	device prefix, "dd_" for GPU, nothing for CPU
postVarPrefix	prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)

## 18.1.3.19 preNeuronSubstitutionsInSynapticCode()

```
void CodeGenerator::preNeuronSubstitutionsInSynapticCode (
    std::string & wCode,
    const SynapseGroupInternal & sg,
    const std::string & offset,
    const std::string & axonalDelayOffset,
    const std::string & postIdx,
    const std::string & devPrefix,
    const std::string & preVarPrefix = "",
    const std::string & preVarSuffix = "")
```

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

## **Parameters**

wCode	the code string to work on
devPrefix	device prefix, "dd_" for GPU, nothing for CPU
preVarPrefix	prefix to be used for presynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)

# 18.1.3.20 regexFuncSubstitute()

```
bool CodeGenerator::regexFuncSubstitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

# 18.1.3.21 regexVarSubstitute()

```
bool CodeGenerator::regexVarSubstitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

# 18.1.3.22 substitute()

```
void CodeGenerator::substitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting strings in the neuron code strings or other templates.

## **18.1.3.23** value\_substitutions() [1/2]

```
template<typename NameIter >
void CodeGenerator::value_substitutions (
    std::string & code,
    NameIter namesBegin,
    NameIter namesEnd,
    const std::vector< double > & values,
    const std::string & ext = "" ) [inline]
```

This function performs a list of value substitutions for parameters in code snippets.

## **18.1.3.24** value\_substitutions() [2/2]

```
void CodeGenerator::value_substitutions (
    std::string & code,
    const std::vector< std::string > & names,
    const std::vector< double > & values,
    const std::string & ext = "") [inline]
```

This function performs a list of value substitutions for parameters in code snippets.

## **18.1.3.25** writePreciseString() [1/2]

This function writes a floating point value to a stream -setting the precision so no digits are lost.

# 18.1.3.26 writePreciseString() [2/2]

This function writes a floating point value to a string - setting the precision so no digits are lost.

# 18.2 CodeGenerator::CUDA Namespace Reference

# **Namespaces**

- Optimiser
- Utils

#### Classes

- · class Backend
- struct Preferences

Preferences for CUDA backend.

## **Typedefs**

using KernelBlockSize = std::array < size\_t, KernelMax >
 Array of block sizes for each kernel.

## **Enumerations**

- enum DeviceSelect { DeviceSelect::OPTIMAL, DeviceSelect::MOST\_MEMORY, DeviceSelect::MANUAL }
   Methods for selecting CUDA device.
- enum BlockSizeSelect { BlockSizeSelect::OCCUPANCY, BlockSizeSelect::MANUAL }
   Methods for selecting CUDA kernel block size.
- enum Kernel {

KernelNeuronUpdate, KernelPresynapticUpdate, KernelPostsynapticUpdate, KernelSynapseDynamics← Update,

KernelInitialize, KernelInitializeSparse, KernelPreNeuronReset, KernelPreSynapseReset, KernelMax }

Kernels generated by CUDA backend.

# 18.2.1 Typedef Documentation

#### 18.2.1.1 KernelBlockSize

using CodeGenerator::CUDA::KernelBlockSize = typedef std::array<size\_t, KernelMax>

Array of block sizes for each kernel.

# 18.2.2 Enumeration Type Documentation

# 18.2.2.1 BlockSizeSelect

```
enum CodeGenerator::CUDA::BlockSizeSelect [strong]
```

Methods for selecting CUDA kernel block size.

## **Enumerator**

OCCUPANCY	Pick optimal blocksize for each kernel based on occupancy.
MANUAL	Use block sizes specified by user.

#### 18.2.2.2 DeviceSelect

enum CodeGenerator::CUDA::DeviceSelect [strong]

Methods for selecting CUDA device.

### **Enumerator**

OPTIMAL	AL Pick optimal device based on how well kernels can be simultaneously simulated and occupancy.	
MOST_MEMORY	Pick device with most global memory.	
MANUAL Use device specified by user.		

## 18.2.2.3 Kernel

```
enum CodeGenerator::CUDA::Kernel
```

Kernels generated by CUDA backend.

#### **Enumerator**

KernelNeuronUpdate	
KernelPresynapticUpdate	
KernelPostsynapticUpdate	
KernelSynapseDynamicsUpdate	
Kernellnitialize	
KernelInitializeSparse	
KernelPreNeuronReset	
KernelPreSynapseReset	
KernelMax	

# 18.3 CodeGenerator::CUDA::Optimiser Namespace Reference

## **Functions**

 BACKEND\_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

## 18.3.1 Function Documentation

# 18.3.1.1 createBackend()

# 18.4 CodeGenerator::CUDA::Utils Namespace Reference

# **Functions**

- size\_t ceilDivide (size\_t numerator, size\_t denominator)
- size\_t padSize (size\_t size, size\_t blockSize)

## 18.4.1 Function Documentation

# 18.4.1.1 ceilDivide()

# 18.5 CodeGenerator::SingleThreadedCPU Namespace Reference

## Namespaces

Optimiser

#### Classes

- class Backend
- struct Preferences

# 18.6 CodeGenerator::SingleThreadedCPU::Optimiser Namespace Reference

## **Functions**

 BACKEND\_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

#### 18.6.1 Function Documentation

# 18.6.1.1 createBackend()

# 18.7 CurrentSourceModels Namespace Reference

## Classes

· class Base

Base class for all current source models.

· class DC

DC source.

· class GaussianNoise

Noisy current source with noise drawn from normal distribution.

# 18.8 filesystem Namespace Reference

# 18.9 InitSparseConnectivitySnippet Namespace Reference

Base class for all sparse connectivity initialisation snippets.

## Classes

- · class Base
- · class FixedProbability
- · class FixedProbabilityBase
- class FixedProbabilityNoAutapse
- · class Init
- class OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

· class Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

## 18.9.1 Detailed Description

Base class for all sparse connectivity initialisation snippets.

# 18.10 InitVarSnippet Namespace Reference

Base class for all value initialisation snippets.

# Classes

- class Base
- · class Constant

Initialises variable to a constant value.

class Exponential

Initialises variable by sampling from the exponential distribution.

• class Gamma

Initialises variable by sampling from the exponential distribution.

· class Normal

Initialises variable by sampling from the normal distribution.

· class Uniform

Initialises variable by sampling from the uniform distribution.

· class Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

# 18.10.1 Detailed Description

Base class for all value initialisation snippets.

# 18.11 Models Namespace Reference

#### Classes

· class Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

- · class VarInit
- · class VarInitContainerBase
- class VarInitContainerBase< 0 >

# 18.12 NeuronModels Namespace Reference

#### Classes

· class Base

Base class for all neuron models.

· class Izhikevich

Izhikevich neuron with fixed parameters [1].

· class IzhikevichVariable

Izhikevich neuron with variable parameters [1].

- class LIF
- · class Poisson

Poisson neurons.

class PoissonNew

Poisson neurons.

class RulkovMap

Rulkov Map neuron.

class SpikeSource

Empty neuron which allows setting spikes from external sources.

· class SpikeSourceArray

Spike source array.

class TraubMiles

Hodgkin-Huxley neurons with Traub & Miles algorithm.

· class TraubMilesAlt

Hodgkin-Huxley neurons with Traub & Miles algorithm.

· class TraubMilesFast

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

• class TraubMilesNStep

Hodgkin-Huxley neurons with Traub & Miles algorithm.

# 18.13 PostsynapticModels Namespace Reference

#### Classes

· class Base

Base class for all postsynaptic models.

· class DeltaCurr

Simple delta current synapse.

class ExpCond

Exponential decay with synaptic input treated as a conductance value.

· class ExpCurr

Exponential decay with synaptic input treated as a current value.

# 18.14 pygenn Namespace Reference

## **Namespaces**

- genn\_groups
- · genn model
- · model preprocessor

# 18.15 pygenn.genn\_groups Namespace Reference

#### Classes

• class CurrentSource

Class representing a current injection into a group of neurons.

class Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

class NeuronGroup

Class representing a group of neurons.

class SynapseGroup

Class representing synaptic connection between two groups of neurons.

## Variables

• xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

# 18.15.1 Variable Documentation

## 18.15.1.1 xrange

```
pygenn.genn_groups.xrange = range
```

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

# 18.16 pygenn.genn\_model Namespace Reference

## Classes

class GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

# **Functions**

def init\_var (init\_var\_snippet, param\_space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

• def init\_connectivity (init\_sparse\_connect\_snippet, param\_space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def create\_custom\_neuron\_class (class\_name, param\_names=None, var\_name\_types=None, derived\_
 params=None, sim\_code=None, threshold\_condition\_code=None, reset\_code=None, support\_code=None,
 extra\_global\_params=None, additional\_input\_vars=None, is\_auto\_refractory\_required=None, custom\_
 body=None)

This helper function creates a custom NeuronModel class.

def create\_custom\_postsynaptic\_class (class\_name, param\_names=None, var\_name\_types=None, derived\_params=None, decay\_code=None, apply\_input\_code=None, support\_code=None, custom\_
 body=None)

This helper function creates a custom PostsynapticModel class.

def create\_custom\_weight\_update\_class (class\_name, param\_names=None, var\_name\_types=None, pre
 \_var\_name\_types=None, post\_var\_name\_types=None, derived\_params=None, sim\_code=None, event
 \_code=None, learn\_post\_code=None, synapse\_dynamics\_code=None, event\_threshold\_condition\_
 code=None, pre\_spike\_code=None, post\_spike\_code=None, sim\_support\_code=None, learn\_post\_
 support\_code=None, synapse\_dynamics\_support\_code=None, extra\_global\_params=None, is\_pre\_
 spike\_time\_required=None, is\_post\_spike\_time\_required=None, custom\_body=None)

This helper function creates a custom WeightUpdateModel class.

def create\_custom\_current\_source\_class (class\_name, param\_names=None, var\_name\_types=None, derived\_params=None, injection\_code=None, extra\_global\_params=None, custom\_body=None)

This helper function creates a custom NeuronModel class.

def create\_custom\_model\_class (class\_name, base, param\_names, var\_name\_types, derived\_params, custom\_body)

This helper function completes a custom model class creation.

def create\_dpf\_class (dp\_func)

Helper function to create derived parameter function class.

def create\_cmlf\_class (cml\_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

def create\_custom\_init\_var\_snippet\_class (class\_name, param\_names=None, derived\_params=None, var
 \_\_init\_code=None, custom\_body=None)

This helper function creates a custom InitVarSnippet class.

def create\_custom\_sparse\_connect\_init\_snippet\_class (class\_name, param\_names=None, derived\_
 params=None, row\_build\_code=None, row\_build\_state\_vars=None, calc\_max\_row\_len\_func=None, calc\_
 max\_col\_len\_func=None, extra\_global\_params=None, custom\_body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

# **Variables**

- backend\_modules = OrderedDict()
- m = import\_module(".genn\_wrapper." + b + "Backend", "pygenn")

# 18.16.1 Function Documentation

#### 18.16.1.1 create\_cmlf\_class()

```
def pygenn.genn_model.create_cmlf_class ( \it{cml\_func} )
```

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

#### **Parameters**

cml_func	a function which computes the length and takes three args "num_pre" (unsigned int), "num_post"
	(unsigned int) and "pars" (vector of double)

## 18.16.1.2 create\_custom\_current\_source\_class()

This helper function creates a custom NeuronModel class.

#### See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

#### **Parameters**

class_name	name of the new class	
param_names	list of strings with param names of the model	
var_name_types	list of pairs of strings with varible names and types of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc	
injection_code	string with the current injection code	
extra_global_params	list of pairs of strings with names and types of additional parameters	
custom_body dictionary with additional attributes and methods of the new class		

# 18.16.1.3 create\_custom\_init\_var\_snippet\_class()

This helper function creates a custom InitVarSnippet class.

# See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_sparse_connect_init_snippet_class
```

class_name	name of the new class	
param_names	list of strings with param names of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the pygenn.genn_wrapper.DerivedParamFunc class	
var_init_code	string with the variable initialization code	
custom_body	dictionary with additional attributes and methods of the new class	

## 18.16.1.4 create\_custom\_model\_class()

This helper function completes a custom model class creation.

This part is common for all model classes and is nearly useless on its own unless you specify custom\_body.

## See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

# **Parameters**

class_name	name of the new class	
base	base class	
param_names	list of strings with param names of the model	
var_name_types	list of pairs of strings with varible names and types of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from the pygenn.genn_wrapper.DerivedParamFunc class	
custom_body	dictionary with attributes and methods of the new class	

# 18.16.1.5 create\_custom\_neuron\_class()

```
threshold_condition_code = None,
reset_code = None,
support_code = None,
extra_global_params = None,
additional_input_vars = None,
is_auto_refractory_required = None,
custom_body = None )
```

This helper function creates a custom NeuronModel class.

# See also

```
create_custom_postsynaptic_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

#### **Parameters**

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from
	"pygenn.genn_wrapper.Snippet.DerivedParamFunc" @param sim_code string with the simulation code @param threshold_condition_code string with the threshold condition code @param reset_code string with the reset code @param support_code string with the support code @param extra_global_params list of pairs of strings with names and
	types of additional parameters
additional_input_vars	list of tuples with names and types as strings and initial values of additional local
	input variables
is_auto_refractory_required	does this model require auto-refractory logic to be generated?
custom_body	dictionary with additional attributes and methods of the new class

# 18.16.1.6 create\_custom\_postsynaptic\_class()

This helper function creates a custom PostsynapticModel class.

## See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
```

create\_custom\_sparse\_connect\_init\_snippet\_class

#### **Parameters**

class_name	name of the new class	
param_names	list of strings with param names of the model	
var_name_types	list of pairs of strings with varible names and types of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.DerivedParamFunc	
decay_code	string with the decay code	
apply_input_code	string with the apply input code	
support_code	string with the support code	
custom_body	dictionary with additional attributes and methods of the new class	

## 18.16.1.7 create\_custom\_sparse\_connect\_init\_snippet\_class()

This helper function creates a custom InitSparseConnectivitySnippet class.

# See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
```

#### **Parameters**

class_name	name of the new class	
param_names	list of strings with param names of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc	
row_build_code	string with row building initialization code	
row_build_state_vars	list of tuples of state variables, their types and their initial values to use across row building loop	
calc_max_row_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum row length of synaptic matrix	
calc_max_col_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum col length of synaptic matrix	
extra_global_params	list of pairs of strings with names and types of additional parameters	

custom_body	dictionary with additional attributes and methods of the new class
-------------	--

# 18.16.1.8 create\_custom\_weight\_update\_class()

```
def pygenn.genn_model.create_custom_weight_update_class (
              class_name,
              param_names = None,
              var_name_types = None,
              pre_var_name_types = None,
              post_var_name_types = None,
              derived_params = None,
              sim\_code = None,
              event_code = None,
              learn_post_code = None,
              synapse_dynamics_code = None,
              event_threshold_condition_code = None,
              pre_spike_code = None,
              post_spike_code = None,
              sim_support_code = None,
              learn_post_support_code = None,
              synapse_dynamics_suppport_code = None,
              extra_global_params = None,
              is_pre_spike_time_required = None,
              is\_post\_spike\_time\_required = None,
              custom\_body = None)
```

This helper function creates a custom WeightUpdateModel class.

# See also

```
create_custom_neuron_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

# **Parameters**

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with variable names and types of the model
pre_var_name_types	list of pairs of strings with presynaptic variable names and types of the model
post_var_name_types	list of pairs of strings with postsynaptic variable names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from
	"pygenn.genn_wrapper.DerivedParamFunc" @param sim_code string with the simulation code @param event_code string with the event code @param learn_post_code string with the code to include in
	learn_synapse_post kernel/function
synapse_dynamics_code	string with the synapse dynamics code

event_threshold_condition_code	string with the event threshold condition code
pre_spike_code	string with the code run once per spiking presynaptic neuron
post_spike_code	string with the code run once per spiking postsynaptic neuron
sim_support_code	string with simulation support code
learn_post_support_code	string with support code for learn_synapse_post kernel/function
synapse_dynamics_suppport_code	string with synapse dynamics support code
extra_global_params	list of pairs of strings with names and types of additional parameters
is_pre_spike_time_required	boolean, is presynaptic spike time required in any weight update kernels?
is_post_spike_time_required	boolean, is postsynaptic spike time required in any weight update kernels?
custom_body	dictionary with additional attributes and methods of the new class

# 18.16.1.9 create\_dpf\_class()

```
def pygenn.genn_model.create_dpf_class ( dp\_func \ )
```

Helper function to create derived parameter function class.

#### **Parameters**

dp_func	a function which computes the derived parameter and takes two args "pars" (vector of double) and	
	"dt" (double)	

# 18.16.1.10 init\_connectivity()

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

# **Parameters**

init_sparse_connect_snippet	type of the InitSparseConnectivitySnippet class as string or instance of class derived from InitSparseConnectivitySnippet::Custom.
param_space	dict with param values for the InitSparseConnectivitySnippet class

# 18.16.1.11 init\_var()

This helper function creates a VarInit object to easily initialise a variable using a snippet.

init_var_snippet	type of the InitVarSnippet class as string or instance of class derived from InitVarSnippet::Custom class.
param_space	dict with param values for the InitVarSnippet class

#### 18.16.2 Variable Documentation

## 18.16.2.1 backend\_modules

```
pygenn.genn_model.backend_modules = OrderedDict()
```

#### 18.16.2.2 m

```
pygenn.genn_model.m = import_module(".genn_wrapper." + b + "Backend", "pygenn")
```

# 18.17 pygenn.model\_preprocessor Namespace Reference

#### Classes

· class ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

class Variable

Class holding information about GeNN variables.

# **Functions**

def prepare\_model (model, param\_space, var\_space, pre\_var\_space=None, post\_var\_space=None, model\_family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

def prepare\_snippet (snippet, param\_space, snippet\_family)

Prepare a snippet by checking its validity and extracting information about parameters.

def is\_model\_valid (model, model\_family)

Check whether the model is valid, i.e is native or derived from model\_family.Custom.

• def param space to vals (model, param space)

Convert a param\_space dict to ParamValues.

def param\_space\_to\_val\_vec (model, param\_space)

Convert a param\_space dict to a std::vector<double>

def var\_space\_to\_vals (model, var\_space)

Convert a var\_space dict to VarValues.

def pre\_var\_space\_to\_vals (model, var\_space)

Convert a var space dict to PreVarValues.

def post\_var\_space\_to\_vals (model, var\_space)

Convert a var\_space dict to PostVarValues.

#### Variables

dictionary genn\_to\_numpy\_types

## 18.17.1 Function Documentation

# 18.17.1.1 is\_model\_valid()

Check whether the model is valid, i.e is native or derived from model\_family.Custom.

#### **Parameters**

model	string or instance of model_family.Custom
model_family	model family (NeuronModels, WeightUpdateModels or PostsynapticModels) to which model
	should belong to

#### Returns

instance of the model and its type as string

Raises ValueError if model is not valid (i.e. is not custom and is not natively available)

## 18.17.1.2 param\_space\_to\_val\_vec()

Convert a param\_space dict to a std::vector<double>

# Parameters

model	instance of the model
param_space	dict with parameters

#### Returns

native vector of parameters

## 18.17.1.3 param\_space\_to\_vals()

Convert a param\_space dict to ParamValues.

## **Parameters**

model	instance of the model
param_space	dict with parameters

## Returns

native model's ParamValues

```
18.17.1.4 post_var_space_to_vals()
```

Convert a var\_space dict to PostVarValues.

# **Parameters**

model	instance of the weight update model
var_space	dict with Variables

## Returns

native model's VarValues

## 18.17.1.5 pre\_var\_space\_to\_vals()

Convert a var\_space dict to PreVarValues.

# **Parameters**

model	instance of the weight update model
var_space	dict with Variables

# Returns

native model's VarValues

## 18.17.1.6 prepare\_model()

Prepare a model by checking its validity and extracting information about variables and parameters.

model	string or instance of a class derived from
	pygenn.genn_wrapper.NeuronModels.Custom or
	pygenn.genn_wrapper.WeightUpdateModels.Custom or
	"pygenn.genn_wrapper.CurrentSourceModels.Custom" @param param_space dict with model parameters @param var_space dict with model variables @param pre_var_space optional dict with (weight update) model
	presynaptic variables
post_var_space	optional dict with (weight update) model postsynaptic variables
model_family	pygenn.genn_wrapper.NeuronModels or
	pygenn.genn_wrapper.WeightUpdateModels or
	"pygenn.genn_wrapper.CurrentSourceModels" @return
	tuple consisting of (model instance, model type, model parameter names, model parameters,

## 18.17.1.7 prepare\_snippet()

Prepare a snippet by checking its validity and extracting information about parameters.

### **Parameters**

```
snippet

string or instance of a class derived from

pygenn.genn_wrapper.InitVarSnippet.Custom or

"pygenn.genn_wrapper.InitSparseConnectivitySnippet.Custom" @param param_space dict
with model parameters @param snippet_family "pygenn.genn_wrapper.InitVarSnippet" or
"pygenn.genn_wrapper.InitSparseConnectivitySnippet"
@return

tuple consisting of (snippet instance, snippet type, snippet parameter names, snippet parameters)
```

# 18.17.1.8 var\_space\_to\_vals()

Convert a var\_space dict to VarValues.

## **Parameters**

model	instance of the model
var_space	dict with Variables

#### Returns

native model's VarValues

#### 18.17.2 Variable Documentation

## 18.17.2.1 genn\_to\_numpy\_types

dictionary pygenn.model\_preprocessor.genn\_to\_numpy\_types

#### Initial value:

```
{
            "scalar": np.float32,
"float": np.float32,
"double": np.float64,
"int": np.int32,
"unsigned int": np.uint32,
"short":
6
                                                           np.int16,
             "unsigned short": np.uint16,
8
         "unsigned char": np.uint8,
"uint64_t": np.uint64,
"int64_t": np.int64,
"int64_t": np.int64
12
             "uint32_t": np.uint32,
"int32_t": np.int32,
"uint16_t": np.uint16,
"int16_t": np.int16,
"uint8_t": np.uint8,
"int8_t": np.int8,
               "uint32_t":
1.3
14
15
16
17
18
19 }
```

# 18.18 Snippet Namespace Reference

#### Classes

· class Base

Base class for all code snippets.

- class Init
- class ValueBase
- class ValueBase< 0 >

#### 18.18.1 Detailed Description

Wrapper to ensure at compile time that correct number of values are used when specifying the values of a model's parameters and initial state.

# 18.19 Utils Namespace Reference

## **Functions**

• GENN\_EXPORT bool isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN\_EXPORT bool isInitRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

GENN\_EXPORT bool isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN\_EXPORT std::string getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

#### 18.19.1 Function Documentation

## 18.19.1.1 getUnderlyingType()

Assuming type is a string containing a pointer type, function to return the underlying type.

# 18.19.1.2 isInitRNGRequired()

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

# 18.19.1.3 isRNGRequired()

Does the code string contain any functions requiring random number generator.

### 18.19.1.4 isTypePointer()

Function to determine whether a string containing a type is a pointer.

# 18.20 WeightUpdateModels Namespace Reference

### Classes

· class Base

Base class for all weight update models.

class PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

· class StaticGraded

Graded-potential, static synapse.

class StaticPulse

Pulse-coupled, static synapse.

· class StaticPulseDendriticDelay


Pulse-coupled, static synapse with heterogenous dendritic delays.

# 19 Class Documentation

# 19.1 CodeGenerator::CUDA::Backend Class Reference

```
#include <backend.h>
```

Inheritance diagram for CodeGenerator::CUDA::Backend:



#### **Public Member Functions**

- Backend (const KernelBlockSize &kernelBlockSizes, const Preferences &preferences, int localHostID, const std::string &scalarType, int device)
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim← Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const override

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const
 override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG
   Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse
   GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- virtual void genDefinitionsPreamble (CodeStream &os) const override

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

virtual void genDefinitionsInternalPreamble (CodeStream &os) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- virtual void genRunnerPreamble (CodeStream &os) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size\_t count) const override
- · virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size\_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override

- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size\_t count) const override
- virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size\_t count) const override
- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const override
- virtual MemAlloc genPopulationRNG (CodeStream &definitions, CodeStream &definitionsInternal, Code
   Stream &runner, CodeStream &allocations, CodeStream &free, const std::string &name, size\_t count) const override
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override
- virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const override
- virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

- virtual bool isSynRemapRequired () const override
- · virtual bool isPostsynapticRemapRequired () const override
- virtual size t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

- const cudaDeviceProp & getChosenCUDADevice () const
- int getChosenDeviceID () const
- int getRuntimeVersion () const
- std::string getNVCCFlags () const

# **Static Public Member Functions**

- static size\_t getNumPresynapticUpdateThreads (const SynapseGroupInternal &sg)
- static size\_t getNumPostsynapticUpdateThreads (const SynapseGroupInternal &sg)
- static size\_t getNumSynapseDynamicsThreads (const SynapseGroupInternal &sg)

# Static Public Attributes

• static const char \* KernelNames [KernelMax]

#### **Additional Inherited Members**

#### 19.1.1 Constructor & Destructor Documentation

## 19.1.1.1 Backend()

#### 19.1.2 Member Function Documentation

## 19.1.2.1 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

#### 19.1.2.2 genCurrentSpikeLikeEventPull()

Implements CodeGenerator::BackendBase.

# 19.1.2.3 genCurrentSpikeLikeEventPush()

Implements CodeGenerator::BackendBase.

## 19.1.2.4 genCurrentTrueSpikePull()

Implements CodeGenerator::BackendBase.

# 19.1.2.5 genCurrentTrueSpikePush()

Implements CodeGenerator::BackendBase.

#### 19.1.2.6 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

# 19.1.2.7 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

### 19.1.2.8 genExtraGlobalParamAllocation()

Implements CodeGenerator::BackendBase.

### 19.1.2.9 genExtraGlobalParamDefinition()

Implements CodeGenerator::BackendBase.

# 19.1.2.10 genExtraGlobalParamImplementation()

```
const std::string & type,
             const std::string & name,
             VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.1.2.11 genExtraGlobalParamPull()
void CodeGenerator::CUDA::Backend::genExtraGlobalParamPull (
             CodeStream & os,
             const std::string & type,
             const std::string & name,
             VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.1.2.12 genExtraGlobalParamPush()
void CodeGenerator::CUDA::Backend::genExtraGlobalParamPush (
             CodeStream & os,
             const std::string & type,
             const std::string & name,
             VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.1.2.13 genGlobalRNG()
MemAlloc CodeGenerator::CUDA::Backend::genGlobalRNG (
             CodeStream & definitions,
             CodeStream & definitionsInternal,
             CodeStream & runner,
             CodeStream & allocations,
             CodeStream & free,
             const ModelSpecInternal & model ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.1.2.14 genInit()
void CodeGenerator::CUDA::Backend::genInit (
             CodeStream & os,
             const ModelSpecInternal & model,
             NeuronGroupHandler localNGHandler,
             NeuronGroupHandler remoteNGHandler,
             SynapseGroupHandler sgDenseInitHandler,
             {\tt SynapseGroupHandler}\ sgSparseConnectHandler,
             SynapseGroupHandler sgSparseInitHandler ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
```

19.1.2.15 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-\_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

#### 19.1.2.16 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

#### 19.1.2.17 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

#### 19.1.2.18 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

## 19.1.2.19 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties
for more information.

Implements CodeGenerator::BackendBase.

#### 19.1.2.20 genMSBuildImportProps()

Implements CodeGenerator::BackendBase.

## 19.1.2.21 genMSBuildImportTarget()

```
void CodeGenerator::CUDA::Backend::genMSBuildImportTarget (
```

```
std::ostream & os ) const [override], [virtual]
```

#### 19.1.2.22 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

 $\textbf{See} \ \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items\#item-definitions} \ \ \textbf{for more information.}$ 

Implements CodeGenerator::BackendBase.

## 19.1.2.23 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

#### **Parameters**

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

# 19.1.2.24 genPopulationRNG()

Implements CodeGenerator::BackendBase.

### 19.1.2.25 genPopVariableInit()

```
VarLocation loc,
const Substitutions & kernelSubs,
Handler handler ) const [override], [virtual]
```

#### 19.1.2.26 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

## 19.1.2.27 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

### 19.1.2.28 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

# **Parameters**

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes.  "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or  "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes.  "id_pre", "id_post" and "id_syn" variables will be provided to callback via  Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implements CodeGenerator::BackendBase.

```
19.1.2.29 genSynapseVariableRowInit()
```

# 19.1.2.30 genTimer()

Implements CodeGenerator::BackendBase.

#### 19.1.2.31 genVariableAllocation()

Implements CodeGenerator::BackendBase.

# 19.1.2.32 genVariableDefinition()

Implements CodeGenerator::BackendBase.

# 19.1.2.33 genVariableFree()

```
19.1.2.34 genVariableImplementation()
```

Implements CodeGenerator::BackendBase.

# 19.1.2.35 genVariableInit()

Implements CodeGenerator::BackendBase.

## 19.1.2.36 genVariablePull()

Implements CodeGenerator::BackendBase.

## 19.1.2.37 genVariablePush()

Implements CodeGenerator::BackendBase.

## 19.1.2.38 getChosenCUDADevice()

```
const cudaDeviceProp& CodeGenerator::CUDA::Backend::getChosenCUDADevice ( ) const [inline]
```

```
19.1.2.39 getChosenDeviceID()
```

```
int CodeGenerator::CUDA::Backend::getChosenDeviceID ( ) const [inline]
```

#### 19.1.2.40 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::CUDA::Backend::getDeviceMemoryBytes ( ) const [inline], [override],
[virtual]
```

How many bytes of memory does 'device' have.

Implements CodeGenerator::BackendBase.

## 19.1.2.41 getNumPostsynapticUpdateThreads()

```
\label{lem:size_tode} size\_t \ \mbox{CodeGenerator::CUDA::Backend::getNumPostsynapticUpdateThreads (} \\ const \ \mbox{SynapseGroupInternal \& $sg$ ) [static]
```

# 19.1.2.42 getNumPresynapticUpdateThreads()

## 19.1.2.43 getNumSynapseDynamicsThreads()

# 19.1.2.44 getNVCCFlags()

```
std::string CodeGenerator::CUDA::Backend::getNVCCFlags ( ) const
```

# 19.1.2.45 getRuntimeVersion()

```
\verb|int CodeGenerator::CUDA::Backend::getRuntimeVersion () const [inline]|\\
```

# 19.1.2.46 getVarPrefix()

```
virtual std::string CodeGenerator::CUDA::Backend::getVarPrefix ( ) const [inline], [override],
[virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

### 19.1.2.47 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

## 19.1.2.48 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isPostsynapticRemapRequired ( ) const [inline],
[override], [virtual]
```

Implements CodeGenerator::BackendBase.

## 19.1.2.49 isSynRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isSynRemapRequired ( ) const [inline], [override],
[virtual]
```

Implements CodeGenerator::BackendBase.

#### 19.1.3 Member Data Documentation

#### 19.1.3.1 KernelNames

```
const char * CodeGenerator::CUDA::Backend::KernelNames [static]
```

#### Initial value:

```
"updateNeuronsKernel",
"updatePresynapticKernel",
"updatePostsynapticKernel",
"updateSynapseDynamicsKernel",
"initializeKernel",
"initializeSparseKernel",
"preNeuronResetKernel",
"preSynapseResetKernel"}
```

The documentation for this class was generated from the following files:

- · cuda/backend.h
- · cuda/backend.cc

# 19.2 CodeGenerator::SingleThreadedCPU::Backend Class Reference

```
#include <backend.h>
```

 $Inheritance\ diagram\ for\ Code Generator :: Single Threaded CPU :: Backend:$ 

```
CodeGenerator::BackendBase

CodeGenerator::SingleThreadedCPU::Backend
```

# **Public Member Functions**

• Backend (int localHostID, const std::string &scalarType, const Preferences &preferences)

virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
 Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const override

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const
 override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG←
   Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse←
   GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- · virtual void genDefinitionsPreamble (CodeStream &os) const override

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

· virtual void genDefinitionsInternalPreamble (CodeStream &os) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- virtual void genRunnerPreamble (CodeStream &os) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name,
   VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name,
   VarLocation loc, size\_t count) const override
- · virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size\_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size t count) const override
- virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const override
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const override

- virtual MemAlloc genPopulationRNG (CodeStream &definitions, CodeStream &definitionsInternal, Code
   Stream &runner, CodeStream &allocations, CodeStream &free, const std::string &name, size\_t count) const override
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override
- virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const override
- · virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- · virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

- virtual bool isSynRemapRequired () const override
- virtual bool isPostsynapticRemapRequired () const override
- virtual size\_t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

#### **Additional Inherited Members**

#### 19.2.1 Constructor & Destructor Documentation

#### 19.2.1.1 Backend()

### 19.2.2 Member Function Documentation

# 19.2.2.1 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

# 19.2.2.2 genCurrentSpikeLikeEventPull()

Implements CodeGenerator::BackendBase.

#### 19.2.2.3 genCurrentSpikeLikeEventPush()

Implements CodeGenerator::BackendBase.

#### 19.2.2.4 genCurrentTrueSpikePull()

Implements CodeGenerator::BackendBase.

## 19.2.2.5 genCurrentTrueSpikePush()

Implements CodeGenerator::BackendBase.

## 19.2.2.6 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

# 19.2.2.7 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

```
19.2.2.8 genExtraGlobalParamAllocation()
```

#### 19.2.2.9 genExtraGlobalParamDefinition()

Implements CodeGenerator::BackendBase.

# 19.2.2.10 genExtraGlobalParamImplementation()

Implements CodeGenerator::BackendBase.

## 19.2.2.11 genExtraGlobalParamPull()

Implements CodeGenerator::BackendBase.

## 19.2.2.12 genExtraGlobalParamPush()

Implements CodeGenerator::BackendBase.

# 19.2.2.13 genGlobalRNG()

```
CodeStream & runner,
CodeStream & allocations,
CodeStream & free,
const ModelSpecInternal & model ) const [override], [virtual]
```

### 19.2.2.14 genInit()

Implements CodeGenerator::BackendBase.

## 19.2.2.15 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-\_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

## 19.2.2.16 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

#### 19.2.2.17 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

# 19.2.2.18 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

### 19.2.2.19 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

**see** https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties for more information.

Implements CodeGenerator::BackendBase.

#### 19.2.2.20 genMSBuildImportProps()

Implements CodeGenerator::BackendBase.

#### 19.2.2.21 genMSBuildImportTarget()

Implements CodeGenerator::BackendBase.

#### 19.2.2.22 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items#item-definitions
for more information.

Implements CodeGenerator::BackendBase.

### 19.2.2.23 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

#### **Parameters**

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup

#### **Parameters**

wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight
	update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

#### 19.2.2.24 genPopulationRNG()

Implements CodeGenerator::BackendBase.

### 19.2.2.25 genPopVariableInit()

Implements CodeGenerator::BackendBase.

# 19.2.2.26 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

# 19.2.2.27 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

### 19.2.2.28 genSynapseUpdate()

```
SynapseGroupHandler wumEventHandler,
SynapseGroupHandler postLearnHandler,
SynapseGroupHandler synapseDynamicsHandler) const [override], [virtual]
```

Generate platform-specific function to update the state of all synapses.

#### **Parameters**

OS	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes.  "id_pre", "id_post" and "id_syn" variables will be provided to callback via  Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implements CodeGenerator::BackendBase.

# 19.2.2.29 genSynapseVariableRowInit()

Implements CodeGenerator::BackendBase.

# 19.2.2.30 genTimer()

 $Implements\ Code Generator :: Backend Base.$ 

#### 19.2.2.31 genVariableAllocation()

```
{\tt MemAlloc}\ {\tt CodeGenerator::SingleThreadedCPU::Backend::genVariableAllocation}\ (
```

```
CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc,
            size_t count ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.2.2.32 genVariableDefinition()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableDefinition (
            CodeStream & definitions,
            CodeStream & definitionsInternal,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.2.2.33 genVariableFree()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableFree (
            CodeStream & os,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.2.2.34 genVariableImplementation()
CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.2.2.35 genVariableInit()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableInit (
            CodeStream & os,
            VarLocation loc,
            size_t count,
            const std::string & indexVarName,
            const Substitutions & kernelSubs,
            Handler handler ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.2.2.36 genVariablePull()
void CodeGenerator::SingleThreadedCPU::Backend::genVariablePull (
            CodeStream & os,
            const std::string & type,
```

```
const std::string & name,
VarLocation loc,
size_t count ) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

#### 19.2.2.37 genVariablePush()

Implements CodeGenerator::BackendBase.

### 19.2.2.38 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::SingleThreadedCPU::Backend::getDeviceMemoryBytes ( ) const [inline],
[override], [virtual]
```

How many bytes of memory does 'device' have.

Implements CodeGenerator::BackendBase.

#### 19.2.2.39 getVarPrefix()

```
virtual std::string CodeGenerator::SingleThreadedCPU::Backend::getVarPrefix ( ) const [inline],
[override], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

# 19.2.2.40 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

# 19.2.2.41 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::SingleThreadedCPU::Backend::isPostsynapticRemapRequired ( ) const
[inline], [override], [virtual]
```

Implements CodeGenerator::BackendBase.

#### 19.2.2.42 isSynRemapRequired()

virtual bool CodeGenerator::SingleThreadedCPU::Backend::isSynRemapRequired ( ) const [inline],
[override], [virtual]

Implements CodeGenerator::BackendBase.


The documentation for this class was generated from the following files:

- single\_threaded\_cpu/backend.h
- single\_threaded\_cpu/backend.cc

#### 19.3 CodeGenerator::BackendBase Class Reference

#include <backendBase.h>

Inheritance diagram for CodeGenerator::BackendBase:



### **Public Types**

- typedef std::function< void(CodeStream &, Substitutions &)> Handler
- template<typename T >
   using GroupHandler = std::function< void(CodeStream &, const T &, Substitutions &)>
- typedef GroupHandler< NeuronGroupInternal > NeuronGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron Group to.

- typedef GroupHandler< SynapseGroupInternal > SynapseGroupHandler
  - Standard callback type which provides a CodeStream to write platform-independent code for the specified Synapse-Group to.
- typedef std::function< void(CodeStream &, const NeuronGroupInternal &, Substitutions &, NeuronGroup

   Handler, NeuronGroupHandler)> NeuronGroupSimHandler

Callback function type for generation neuron group simulation code.

### **Public Member Functions**

- BackendBase (int localHostID, const std::string &scalarType)
- virtual ∼BackendBase ()
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
   Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const =0

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler postLearnHandler, SynapseGroupHandler synapseDynamicsHandler) const
 =0

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG
   Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, SynapseGroupHandler sgSparseInitHandler) const =0
- virtual void genDefinitionsPreamble (CodeStream &os) const =0

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

virtual void genDefinitionsInternalPreamble (CodeStream &os) const =0

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- virtual void genRunnerPreamble (CodeStream &os) const =0
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const =0
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const =0
   After all timestep logic is complete.
- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size\_t count) const =0
- virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamDefinition (CodeStream &definitions, const std::string &type, const std
  ::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size\_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size\_t count) const =0
- virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size\_t count) const =0
- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const =0
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const =0
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const =0
- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const =0
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const ModelSpecInternal &model) const =0
- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const =0
- virtual void genMakefilePreamble (std::ostream &os) const =0

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const =0
- virtual void genMakefileCompileRule (std::ostream &os) const =0
- virtual void genMSBuildConfigProperties (std::ostream &os) const =0
- virtual void genMSBuildImportProps (std::ostream &os) const =0
- virtual void genMSBuildItemDefinitions (std::ostream &os) const =0

- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const =0
- virtual void genMSBuildImportTarget (std::ostream &os) const =0
- virtual std::string getVarPrefix () const
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const =0

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

- virtual bool isSynRemapRequired () const =0
- virtual bool isPostsynapticRemapRequired () const =0
- virtual size\_t getDeviceMemoryBytes () const =0

How many bytes of memory does 'device' have.

void genVariablePushPull (CodeStream &push, CodeStream &pull, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size t count) const

Helper function to generate matching push and pull functions for a variable.

 MemAlloc genArray (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const std::string &type, const std::string &name, VarLocation loc, size\_t count) const

Helper function to generate matching definition, declaration, allocation and free code for an array.

• void genScalar (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const std::string &type, const std::string &name, VarLocation loc) const

Helper function to generate matching definition and declaration code for a scalar variable.

int getLocalHostID () const

Gets ID of local host backend is building code for.

# **Protected Member Functions**

- void addType (const std::string &type, size\_t size)
- size\_t getSize (const std::string &type) const

# 19.3.1 Member Typedef Documentation

#### 19.3.1.1 GroupHandler

```
template<typename T >
using CodeGenerator::BackendBase::GroupHandler = std::function <void(CodeStream &, const T &,
Substitutions&)>
```

#### 19.3.1.2 Handler

typedef std::function<void(CodeStream &, Substitutions&)> CodeGenerator::BackendBase::Handler

### 19.3.1.3 NeuronGroupHandler

typedef GroupHandler<NeuronGroupInternal> CodeGenerator::BackendBase::NeuronGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron← Group to.

### 19.3.1.4 NeuronGroupSimHandler

typedef std::function<void(CodeStream &, const NeuronGroupInternal &, Substitutions&, Neuron↔ GroupHandler, NeuronGroupHandler)> CodeGenerator::BackendBase::NeuronGroupSimHandler

Callback function type for generation neuron group simulation code.

Provides additional callbacks to insert code to emit spikes

### 19.3.1.5 SynapseGroupHandler

typedef GroupHandler<SynapseGroupInternal> CodeGenerator::BackendBase::SynapseGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified SynapseGroup to.

#### 19.3.2 Constructor & Destructor Documentation

# 19.3.2.1 BackendBase()

```
CodeGenerator::BackendBase::BackendBase (
    int localHostID,
    const std::string & scalarType )
```

### 19.3.2.2 $\sim$ BackendBase()

```
virtual CodeGenerator::BackendBase::~BackendBase ( ) [inline], [virtual]
```

# 19.3.3 Member Function Documentation

### 19.3.3.1 addType()

#### 19.3.3.2 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.3 genArray()

```
CodeStream & allocations,
CodeStream & free,
const std::string & type,
const std::string & name,
VarLocation loc,
size_t count ) const [inline]
```

Helper function to generate matching definition, declaration, allocation and free code for an array.

# 19.3.3.4 genCurrentSpikeLikeEventPull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.5 genCurrentSpikeLikeEventPush()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.6 genCurrentTrueSpikePull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.7 genCurrentTrueSpikePush()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.8 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.9 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.10 genExtraGlobalParamAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.11 genExtraGlobalParamDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.12 genExtraGlobalParamImplementation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.13 genExtraGlobalParamPull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.14 genExtraGlobalParamPush()

```
const std::string & type,
const std::string & name,
VarLocation loc ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.15 genGlobalRNG()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.16 genInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.17 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-\_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.18 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

 $Implemented\ in\ Code Generator :: CUDA :: Backend,\ and\ Code Generator :: Single Threaded CPU :: Backend.$ 

# 19.3.3.19 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.20 genMSBuildCompileModule()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.21 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

 $\textbf{see} \quad \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties} \\ \textbf{for more information.} \\$ 

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.22 genMSBuildImportProps()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.23 genMSBuildImportTarget()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.24 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

 $\textbf{see} \ \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items\#item-definitions} \\ \textbf{for more information.}$ 

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.25 genNeuronUpdate()

```
virtual void CodeGenerator::BackendBase::genNeuronUpdate (
```

```
CodeStream & os,
const ModelSpecInternal & model,
NeuronGroupSimHandler simHandler,
NeuronGroupHandler wuVarUpdateHandler ) const [pure virtual]
```

Generate platform-specific function to update the state of all neurons.

#### **Parameters**

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.26 genPopulationRNG()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.27 genPopVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.28 genRunnerPreamble()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.29 genScalar()

```
const std::string & name,
VarLocation loc ) const [inline]
```

Helper function to generate matching definition and declaration code for a scalar variable.

# 19.3.3.30 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.31 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

#### **Parameters**

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes.  "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or  "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes.  "id_pre", "id_post" and "id_syn" variables will be provided to callback via  Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.32 genSynapseVariableRowInit()

```
const Substitutions & kernelSubs,
Handler handler ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.33 genTimer()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.34 genVariableAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.35 genVariableDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.36 genVariableFree()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

#### 19.3.3.37 genVariableImplementation()

```
const std::string & name,
VarLocation loc ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.38 genVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.39 genVariablePull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.40 genVariablePush()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.41 genVariablePushPull()

Helper function to generate matching push and pull functions for a variable.

### 19.3.3.42 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::BackendBase::getDeviceMemoryBytes ( ) const [pure virtual]
```

How many bytes of memory does 'device' have.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.43 getLocalHostID()

```
int CodeGenerator::BackendBase::getLocalHostID ( ) const [inline]
```

Gets ID of local host backend is building code for.

#### 19.3.3.44 getSize()

### 19.3.3.45 getVarPrefix()

```
virtual std::string CodeGenerator::BackendBase::getVarPrefix ( ) const [inline], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

### 19.3.3.46 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.47 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isPostsynapticRemapRequired ( ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

# 19.3.3.48 isSynRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isSynRemapRequired ( ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

The documentation for this class was generated from the following files:


- · backendBase.h
- · backendBase.cc

# 19.4 CurrentSourceModels::Base Class Reference

Base class for all current source models.

#include <currentSourceModels.h>

Inheritance diagram for CurrentSourceModels::Base:



#### **Public Member Functions**

virtual std::string getInjectionCode () const
 Gets the code that defines current injected each timestep.

**Additional Inherited Members** 

# 19.4.1 Detailed Description

Base class for all current source models.

#### 19.4.2 Member Function Documentation

# 19.4.2.1 getInjectionCode()

virtual std::string CurrentSourceModels::Base::getInjectionCode ( ) const [inline], [virtual]

Gets the code that defines current injected each timestep.

The documentation for this class was generated from the following file:

• currentSourceModels.h

# 19.5 InitSparseConnectivitySnippet::Base Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::Base:



### **Public Types**

typedef std::function< unsigned int(unsigned int, unsigned int, const std::vector< double > &)> CalcMax←
 LengthFunc

#### **Public Member Functions**

- · virtual std::string getRowBuildCode () const
- · virtual ParamValVec getRowBuildStateVars () const
- virtual CalcMaxLengthFunc getCalcMaxRowLengthFunc () const

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

• virtual CalcMaxLengthFunc getCalcMaxColLengthFunc () const

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

- virtual VarVec getExtraGlobalParams () const
- size\_t getExtraGlobalParamIndex (const std::string &paramName) const

Find the index of a named extra global parameter.

#### **Additional Inherited Members**

#### 19.5.1 Member Typedef Documentation

# 19.5.1.1 CalcMaxLengthFunc

typedef std::function<unsigned int(unsigned int, unsigned int, const std::vector<double> &)>
InitSparseConnectivitySnippet::Base::CalcMaxLengthFunc

### 19.5.2 Member Function Documentation

#### 19.5.2.1 getCalcMaxColLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxColLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

# 19.5.2.2 getCalcMaxRowLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxRowLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

#### 19.5.2.3 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

#### 19.5.2.4 getExtraGlobalParams()

```
virtual VarVec InitSparseConnectivitySnippet::Base::getExtraGlobalParams ( ) const [inline],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the connection initialisation snippet

# 19.5.2.5 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::Base::getRowBuildCode ( ) const [inline],
[virtual]
```

Reimplemented in InitSparseConnectivitySnippet::FixedProbabilityBase.

#### 19.5.2.6 getRowBuildStateVars()

```
virtual ParamValVec InitSparseConnectivitySnippet::Base::getRowBuildStateVars ( ) const [inline],
[virtual]
```

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

### 19.6 InitVarSnippet::Base Class Reference

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Base:



### **Public Member Functions**

• virtual std::string getCode () const

#### **Additional Inherited Members**

#### 19.6.1 Member Function Documentation

# 19.6.1.1 getCode()

```
virtual std::string InitVarSnippet::Base::getCode ( ) const [inline], [virtual]
```

The documentation for this class was generated from the following file:

• initVarSnippet.h

### 19.7 Models::Base Class Reference

Base class for all models - in addition to the parameters snippets have, models can have state variables.

```
#include <models.h>
```

Inheritance diagram for Models::Base:



#### **Public Member Functions**

· virtual VarVec getVars () const

Gets names and types (as strings) of model variables.

- virtual VarVec getExtraGlobalParams () const
- size\_t getVarIndex (const std::string &varName) const

Find the index of a named variable.

• size\_t getExtraGlobalParamIndex (const std::string &paramName) const

Find the index of a named extra global parameter.

# **Additional Inherited Members**

### 19.7.1 Detailed Description

Base class for all models - in addition to the parameters snippets have, models can have state variables.

#### 19.7.2 Member Function Documentation

### 19.7.2.1 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

# 19.7.2.2 getExtraGlobalParams()

```
virtual VarVec Models::Base::getExtraGlobalParams ( ) const [inline], [virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

 $Reimplemented \ in \ Neuron Models:: Poisson, \ and \ Neuron Models:: Spike Source Array.$ 

### 19.7.2.3 getVarIndex()

Find the index of a named variable.

#### 19.7.2.4 getVars()

```
virtual VarVec Models::Base::getVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Weight UpdateModels::PiecewiseSTDP, NeuronModels::SpikeSourceArray, NeuronModels::LIF, WeightUpdateModels::StaticGraded, NeuronModels::IzhikevichVariable, WeightUpdateModels::StaticPulseDendriticDelay, Neuron Models::Izhikevich, WeightUpdateModels::StaticPulse, and NeuronModels::RulkovMap.

The documentation for this class was generated from the following file:


models.h

### 19.8 NeuronModels::Base Class Reference

Base class for all neuron models.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::Base:



### **Public Member Functions**

- virtual std::string getSimCode () const
  - Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const

Gets code which defines the condition for a true spike in the described neuron model.

virtual std::string getResetCode () const

Gets code that defines the reset action taken after a spike occurred. This can be empty.

virtual std::string getSupportCode () const

Gets support code to be made available within the neuron kernel/funcion.

- virtual Models::Base::ParamValVec getAdditionalInputVars () const
- · virtual bool isAutoRefractoryRequired () const

Does this model require auto-refractory logic?

**Additional Inherited Members** 

#### 19.8.1 Detailed Description

Base class for all neuron models.

19.8.2 Member Function Documentation

#### 19.8.2.1 getAdditionalInputVars()

```
virtual Models::Base::ParamValVec NeuronModels::Base::getAdditionalInputVars ( ) const [inline],
[virtual]
```

Gets names, types (as strings) and initial values of local variables into which the 'apply input code' of (potentially) multiple postsynaptic input models can apply input

#### 19.8.2.2 getResetCode()

```
virtual std::string NeuronModels::Base::getResetCode ( ) const [inline], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented in NeuronModels::SpikeSourceArray, and NeuronModels::LIF.

### 19.8.2.3 getSimCode()

```
virtual std::string NeuronModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMilesAlt, NeuronModels::TraubMiles ← Fast, NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, NeuronModels::Spike ← SourceArray, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

#### 19.8.2.4 getSupportCode()

```
virtual std::string NeuronModels::Base::getSupportCode ( ) const [inline], [virtual]
```

Gets support code to be made available within the neuron kernel/funcion.

This is intended to contain user defined device functions that are used in the neuron codes. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "\_\_host\_\_ \_\_device\_\_" to be available for both GPU and CPU versions.

### 19.8.2.5 getThresholdConditionCode()

virtual std::string NeuronModels::Base::getThresholdConditionCode ( ) const [inline], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Neuron Models::SpikeSourceArray, NeuronModels::SpikeSource, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

### 19.8.2.6 isAutoRefractoryRequired()

virtual bool NeuronModels::Base::isAutoRefractoryRequired ( ) const [inline], [virtual]

Does this model require auto-refractory logic?

The documentation for this class was generated from the following file:


neuronModels.h

# 19.9 PostsynapticModels::Base Class Reference

Base class for all postsynaptic models.

#include <postsynapticModels.h>

Inheritance diagram for PostsynapticModels::Base:



#### **Public Member Functions**

- virtual std::string getDecayCode () const
- virtual std::string getApplyInputCode () const
- · virtual std::string getSupportCode () const

# **Additional Inherited Members**

# 19.9.1 Detailed Description

Base class for all postsynaptic models.

# 19.9.2 Member Function Documentation

### 19.9.2.1 getApplyInputCode()

virtual std::string PostsynapticModels::Base::getApplyInputCode ( ) const [inline], [virtual]

Reimplemented in PostsynapticModels::DeltaCurr, PostsynapticModels::ExpCond, and PostsynapticModels::Exp Curr.

# 19.9.2.2 getDecayCode()

virtual std::string PostsynapticModels::Base::getDecayCode ( ) const [inline], [virtual]

Reimplemented in PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

### 19.9.2.3 getSupportCode()

virtual std::string PostsynapticModels::Base::getSupportCode ( ) const [inline], [virtual]

The documentation for this class was generated from the following file:


· postsynapticModels.h

### 19.10 Snippet::Base Class Reference

Base class for all code snippets.

#include <snippet.h>

Inheritance diagram for Snippet::Base:



### Classes

- struct DerivedParam
  - A derived parameter has a name and a function for obtaining its value.
- struct ParamVal
- struct Var

A variable has a name and a type.

# **Public Types**

- typedef std::vector< std::string > StringVec
- typedef std::vector< Var > VarVec
- typedef std::vector< ParamVal > ParamValVec
- $\bullet \ \ typedef \ std:: vector < {\tt DerivedParam} > {\tt DerivedParamVec}\\$

### **Public Member Functions**

virtual ∼Base ()

virtual StringVec getParamNames () const
 Gets names of of (independent) model parameters.

• virtual DerivedParamVec getDerivedParams () const

**Static Protected Member Functions** 

static size t getVarVecIndex (const std::string &varName, const VarVec &vars)

19.10.1 Detailed Description

Base class for all code snippets.

19.10.2 Member Typedef Documentation

```
19.10.2.1 DerivedParamVec
```

typedef std::vector<DerivedParam> Snippet::Base::DerivedParamVec

#### 19.10.2.2 ParamValVec

typedef std::vector<ParamVal> Snippet::Base::ParamValVec

### 19.10.2.3 StringVec

typedef std::vector<std::string> Snippet::Base::StringVec

# 19.10.2.4 VarVec

typedef std::vector<Var> Snippet::Base::VarVec

19.10.3 Constructor & Destructor Documentation

```
19.10.3.1 \sim Base()
```

virtual Snippet::Base::~Base ( ) [inline], [virtual]

19.10.4 Member Function Documentation

# 19.10.4.1 getDerivedParams()

```
virtual DerivedParamVec Snippet::Base::getDerivedParams ( ) const [inline], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented in NeuronModels::PoissonNew, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, NeuronModels::RulkovMap, InitSparseConnectivitySnippet::FixedProbabilityBase, PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

### 19.10.4.2 getParamNames()

```
virtual StringVec Snippet::Base::getParamNames ( ) const [inline], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, WeightUpdateModels::⇔ StaticGraded, NeuronModels::IzhikevichVariable, NeuronModels::Izhikevich, InitVarSnippet::Gamma, InitSparse⇔ ConnectivitySnippet::FixedProbabilityBase, NeuronModels::RulkovMap, InitVarSnippet::Exponential, InitVar⇔ Snippet::Normal, InitVarSnippet::Uniform, PostsynapticModels::ExpCond, CurrentSourceModels::GaussianNoise, InitVarSnippet::Constant, CurrentSourceModels::DC, and PostsynapticModels::ExpCurr.

### 19.10.4.3 getVarVecIndex()

The documentation for this class was generated from the following file:


· snippet.h

# 19.11 WeightUpdateModels::Base Class Reference

Base class for all weight update models.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::Base:



### **Public Member Functions**

• virtual std::string getSimCode () const

Gets simulation code run when 'true' spikes are received.

virtual std::string getEventCode () const

Gets code run when events (all the instances where event threshold condition is met) are received.

• virtual std::string getLearnPostCode () const

Gets code to include in the learnSynapsesPost kernel/function.

• virtual std::string getSynapseDynamicsCode () const

Gets code for synapse dynamics which are independent of spike detection.

virtual std::string getEventThresholdConditionCode () const

Gets codes to test for events.

virtual std::string getSimSupportCode () const

Gets support code to be made available within the synapse kernel/function.

virtual std::string getLearnPostSupportCode () const

Gets support code to be made available within learnSynapsesPost kernel/function.

virtual std::string getSynapseDynamicsSuppportCode () const

Gets support code to be made available within the synapse dynamics kernel/function.

- virtual std::string getPreSpikeCode () const
- virtual std::string getPostSpikeCode () const
- virtual VarVec getPreVars () const
- virtual VarVec getPostVars () const
- virtual bool isPreSpikeTimeRequired () const

Whether presynaptic spike times are needed or not.

virtual bool isPostSpikeTimeRequired () const

Whether postsynaptic spike times are needed or not.

size t getPreVarIndex (const std::string &varName) const

Find the index of a named presynaptic variable.

size\_t getPostVarIndex (const std::string &varName) const

Find the index of a named postsynaptic variable.

**Additional Inherited Members** 

#### 19.11.1 Detailed Description

Base class for all weight update models.

### 19.11.2 Member Function Documentation

### 19.11.2.1 getEventCode()

```
virtual std::string WeightUpdateModels::Base::getEventCode ( ) const [inline], [virtual]
```

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented in WeightUpdateModels::StaticGraded.

# 19.11.2.2 getEventThresholdConditionCode()

virtual std::string WeightUpdateModels::Base::getEventThresholdConditionCode ( ) const [inline],
[virtual]

Gets codes to test for events.

Reimplemented in WeightUpdateModels::StaticGraded.

# 19.11.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostCode ( ) const [inline], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

### 19.11.2.4 getLearnPostSupportCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostSupportCode ( ) const [inline],
[virtual]
```

Gets support code to be made available within learnSynapsesPost kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as " host device " to be available for both GPU and CPU versions.

```
19.11.2.5 getPostSpikeCode()
```

```
virtual std::string WeightUpdateModels::Base::getPostSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking postsynaptic neuron before learn post code is run on synapses

This is typically for the code to update postsynaptic variables. Presynaptic and synapse variables are not accesible from within this code

### 19.11.2.6 getPostVarIndex()

Find the index of a named postsynaptic variable.

#### 19.11.2.7 getPostVars()

```
virtual VarVec WeightUpdateModels::Base::getPostVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses going to the same postsynaptic neuron

### 19.11.2.8 getPreSpikeCode()

```
virtual std::string WeightUpdateModels::Base::getPreSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking presynaptic neuron before sim code is run on synapses

This is typically for the code to update presynaptic variables. Postsynaptic and synapse variables are not accesible from within this code

### 19.11.2.9 getPreVarIndex()

Find the index of a named presynaptic variable.

### 19.11.2.10 getPreVars()

```
virtual VarVec WeightUpdateModels::Base::getPreVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses coming from the same presynaptic neuron

### 19.11.2.11 getSimCode()

```
virtual std::string WeightUpdateModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented in WeightUpdateModels::PiecewiseSTDP, WeightUpdateModels::StaticPulseDendriticDelay, and WeightUpdateModels::StaticPulse.

#### 19.11.2.12 getSimSupportCode()

virtual std::string WeightUpdateModels::Base::getSimSupportCode ( ) const [inline], [virtual]

Gets support code to be made available within the synapse kernel/function.

This is intended to contain user defined device functions that are used in the weight update code. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "\_\_host\_\_ \_\_device\_\_" to be available for both GPU and CPU versions; note that this support code is available to sim, event threshold and event code

#### 19.11.2.13 getSynapseDynamicsCode()

virtual std::string WeightUpdateModels::Base::getSynapseDynamicsCode ( ) const [inline],
[virtual]

Gets code for synapse dynamics which are independent of spike detection.

#### 19.11.2.14 getSynapseDynamicsSuppportCode()

virtual std::string WeightUpdateModels::Base::getSynapseDynamicsSuppportCode ( ) const [inline],
[virtual]

Gets support code to be made available within the synapse dynamics kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "\_\_host\_\_ \_\_device\_\_" to be available for both GPU and CPU versions.

#### 19.11.2.15 isPostSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPostSpikeTimeRequired ( ) const [inline], [virtual]

Whether postsynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

# 19.11.2.16 isPreSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPreSpikeTimeRequired ( ) const [inline], [virtual]

Whether presynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

The documentation for this class was generated from the following file:

• weightUpdateModels.h

# 19.12 CodeGenerator::CodeStream::CB Struct Reference

### A close bracket marker.

#include <codeStream.h>

#### **Public Member Functions**

CB (unsigned int level)

### **Public Attributes**

• const unsigned int Level

# 19.12.1 Detailed Description

A close bracket marker.

Write to code stream os using:

```
os << CB(16);
```

### 19.12.2 Constructor & Destructor Documentation

### 19.12.2.1 CB()

```
CodeGenerator::CodeStream::CB::CB (
     unsigned int level ) [inline]
```

### 19.12.3 Member Data Documentation

### 19.12.3.1 Level

```
const unsigned int CodeGenerator::CodeStream::CB::Level
```


The documentation for this struct was generated from the following file:

• codeStream.h

# 19.13 CodeGenerator::CodeStream Class Reference

```
#include <codeStream.h>
```

Inheritance diagram for CodeGenerator::CodeStream:



### Classes

• struct CB

A close bracket marker.

• struct OB

An open bracket marker.

class Scope

### **Public Member Functions**

- CodeStream ()
- CodeStream (std::ostream &stream)
- void setSink (std::ostream &stream)

#### Friends

```
    GENN_EXPORT friend std::ostream & operator<< (std::ostream &s, const OB &ob)</li>
```

```
• GENN_EXPORT friend std::ostream & operator<< (std::ostream &s, const CB &cb)
```

#### 19.13.1 Constructor & Destructor Documentation

#### 19.13.2 Member Function Documentation

```
19.13.2.1 setSink()
```

# 19.13.3 Friends And Related Function Documentation

The documentation for this class was generated from the following file:


· codeStream.h

# 19.14 InitVarSnippet::Constant Class Reference

Initialises variable to a constant value.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Constant:



#### **Public Member Functions**

- DECLARE\_SNIPPET (InitVarSnippet::Constant, 1)
- SET\_CODE ("\$(value) = \$(constant);")
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

**Additional Inherited Members** 

# 19.14.1 Detailed Description

Initialises variable to a constant value.

This snippet takes 1 parameter:

• value - The value to intialise the variable to

Note

This snippet type is seldom used directly - Models::VarInit has an implicit constructor that, internally, creates one of these snippets

# 19.14.2 Member Function Documentation

# 19.14.2.1 DECLARE\_SNIPPET()

### 19.14.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Constant::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.14.2.3 SET\_CODE()

```
InitVarSnippet::Constant::SET_CODE ( )
```


The documentation for this class was generated from the following file:

initVarSnippet.h

# 19.15 pygenn.genn\_groups.CurrentSource Class Reference

Class representing a current injection into a group of neurons.

Inheritance diagram for pygenn.genn\_groups.CurrentSource:



#### **Public Member Functions**

• def \_\_init\_\_ (self, name)

Init CurrentSource.

• def size (self)

Number of neuron in the injected population.

- def size (self, \_)
- def set\_current\_source\_model (self, model, param\_space, var\_space)

Set curront source model, its parameters and initial variables.

def add\_to (self, nn\_model, pop)

Inject this CurrentSource into population and add it to the GeNN NNmodel.

def add\_extra\_global\_param (self, param\_name, param\_values)

Add extra global parameter.

- def load (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise current source.

#### **Public Attributes**

- · current\_source\_model
- target pop
- pop

# 19.15.1 Detailed Description

Class representing a current injection into a group of neurons.

### 19.15.2 Constructor & Destructor Documentation

# Init CurrentSource.

#### **Parameters**

name	string name of the current source
------	-----------------------------------

# 19.15.3 Member Function Documentation

# 19.15.3.1 add\_extra\_global\_param()

Add extra global parameter.

# **Parameters**

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

# 19.15.3.2 add\_to()

Inject this CurrentSource into population and add it to the GeNN NNmodel.

### **Parameters**

рор	instance of NeuronGroup into which this CurrentSource should be injected
nn_model	GeNN NNmodel

## 19.15.3.3 load()

```
def pygenn.genn_groups.CurrentSource.load ( self, \\ slm, \\ scalar )
```

## 19.15.3.4 reinitialise()

```
def pygenn.genn_groups.CurrentSource.reinitialise ( self, \\ slm, \\ scalar )
```

Reinitialise current source.

#### **Parameters**

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

# 19.15.3.5 set\_current\_source\_model()

Set curront source model, its parameters and initial variables.

# **Parameters**

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

```
19.15.3.6 size() [1/2]  \label{eq:size}  \mbox{def pygenn.genn\_groups.CurrentSource.size (} \\  \mbox{self )}
```

Number of neuron in the injected population.

#### 19.15.4 Member Data Documentation

#### 19.15.4.1 current\_source\_model

pygenn.genn\_groups.CurrentSource.current\_source\_model

#### 19.15.4.2 pop

pygenn.genn\_groups.CurrentSource.pop

#### 19.15.4.3 target\_pop

pygenn.genn\_groups.CurrentSource.target\_pop


The documentation for this class was generated from the following file:

· genn groups.py

#### 19.16 CurrentSource Class Reference

#include <currentSource.h>

Inheritance diagram for CurrentSource:



#### **Public Member Functions**

- CurrentSource (const CurrentSource &)=delete
- CurrentSource ()=delete
- void setVarLocation (const std::string &varName, VarLocation loc)

Set location of current source state variable.

• void setExtraGlobalParamLocation (const std::string &paramName, VarLocation loc)

Set location of extra global parameter.

- const std::string & getName () const
- const CurrentSourceModels::Base \* getCurrentSourceModel () const

Gets the current source model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- VarLocation getVarLocation (const std::string &varName) const

Get variable location for current source model state variable.

VarLocation getVarLocation (size\_t index) const

Get variable location for current source model state variable.

VarLocation getExtraGlobalParamLocation (const std::string &paramName) const

Get location of neuron model extra global parameter by name.

VarLocation getExtraGlobalParamLocation (size\_t index) const

Get location of neuron model extra global parameter by omdex.

#### **Protected Member Functions**

- CurrentSource (const std::string &name, const CurrentSourceModels::Base \*currentSourceModel, const std::vector< double > &params, const std::vector< Models::VarInit > &varInitialisers, VarLocation default← VarLocation, VarLocation defaultExtraGlobalParamLocation)
- void initDerivedParams (double dt)
- const std::vector< double > & getDerivedParams () const
- bool isSimRNGRequired () const

Does this current source require an RNG to simulate.

· bool isInitRNGRequired () const

Does this current source group require an RNG for it's init code.

#### 19.16.1 Constructor & Destructor Documentation

```
19.16.1.1 CurrentSource() [1/3]
CurrentSource::CurrentSource (
             const CurrentSource & ) [delete]
19.16.1.2 CurrentSource() [2/3]
CurrentSource::CurrentSource ( ) [delete]
19.16.1.3 CurrentSource() [3/3]
CurrentSource::CurrentSource (
             const std::string & name,
             const CurrentSourceModels::Base * currentSourceModel,
             const std::vector< double > & params,
             const std::vector< Models::VarInit > & varInitialisers,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation ) [inline], [protected]
19.16.2 Member Function Documentation
19.16.2.1 getCurrentSourceModel()
const CurrentSourceModels::Base* CurrentSource::getCurrentSourceModel ( ) const [inline]
Gets the current source model used by this group.
19.16.2.2 getDerivedParams()
const std::vector<double>& CurrentSource::getDerivedParams ( ) const [inline], [protected]
19.16.2.3 getExtraGlobalParamLocation() [1/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
```

const std::string & paramName ) const

19.16.2.12 isSimRNGRequired()

bool CurrentSource::isSimRNGRequired ( ) const [protected]

```
Get location of neuron model extra global parameter by name.

This is only used by extra global parameters which are pointers.
```

```
This is only used by extra global parameters which are pointers
19.16.2.4 getExtraGlobalParamLocation() [2/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.16.2.5 getName()
const std::string& CurrentSource::getName ( ) const [inline]
19.16.2.6 getParams()
const std::vector<double>& CurrentSource::getParams ( ) const [inline]
19.16.2.7 getVarInitialisers()
const std::vector<Models::VarInit>& CurrentSource::getVarInitialisers ( ) const [inline]
19.16.2.8 getVarLocation() [1/2]
VarLocation CurrentSource::getVarLocation (
              const std::string & varName ) const
Get variable location for current source model state variable.
19.16.2.9 getVarLocation() [2/2]
VarLocation CurrentSource::getVarLocation (
              size_t index ) const [inline]
Get variable location for current source model state variable.
19.16.2.10 initDerivedParams()
void CurrentSource::initDerivedParams (
              double dt ) [protected]
19.16.2.11 isInitRNGRequired()
bool CurrentSource::isInitRNGRequired ( ) const [protected]
Does this current source group require an RNG for it's init code.
```

Does this current source require an RNG to simulate.

#### 19.16.2.13 setExtraGlobalParamLocation()

Set location of extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

#### 19.16.2.14 setVarLocation()

Set location of current source state variable.


The documentation for this class was generated from the following files:

- · currentSource.h
- · currentSource.cc

#### 19.17 CurrentSourceInternal Class Reference

```
#include <currentSourceInternal.h>
```

Inheritance diagram for CurrentSourceInternal:



#### **Public Member Functions**

CurrentSourceInternal (const std::string &name, const CurrentSourceModels::Base \*currentSourceModel, const std::vector< double > &params, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation)

**Additional Inherited Members** 

## 19.17.1 Constructor & Destructor Documentation

#### 19.17.1.1 CurrentSourceInternal()

```
VarLocation defaultVarLocation,
VarLocation defaultExtraGlobalParamLocation ) [inline]
```

The documentation for this class was generated from the following file:


· currentSourceInternal.h

#### 19.18 CurrentSourceModels::DC Class Reference

#### DC source.

#include <currentSourceModels.h>

Inheritance diagram for CurrentSourceModels::DC:



## **Public Types**

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- $\bullet \ \ typedef \ Models:: VarInitContainer Base < 0 > PostVarValues \\$

#### **Public Member Functions**

- SET\_INJECTION\_CODE ("\$(injectCurrent, \$(amp));\)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

## Static Public Member Functions

• static const DC \* getInstance ()

#### **Additional Inherited Members**

## 19.18.1 Detailed Description

## DC source.

It has a single parameter:

• amp - amplitude of the current [nA]

## 19.18.2 Member Typedef Documentation

# 19.18.2.1 ParamValues typedef Snippet::ValueBase< 1 > CurrentSourceModels::DC::ParamValues 19.18.2.2 PostVarValues typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PostVarValues 19.18.2.3 PreVarValues typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PreVarValues 19.18.2.4 VarValues typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::DC::VarValues 19.18.3 Member Function Documentation 19.18.3.1 getInstance() static const DC\* CurrentSourceModels::DC::getInstance ( ) [inline], [static] 19.18.3.2 getParamNames() virtual StringVec CurrentSourceModels::DC::getParamNames ( ) const [inline], [override], Gets names of of (independent) model parameters. Reimplemented from Snippet::Base. 19.18.3.3 SET\_INJECTION\_CODE()

The documentation for this class was generated from the following file:

"\$(injectCurrent, \$(amp));\ )

· currentSourceModels.h


## 19.19 PostsynapticModels::DeltaCurr Class Reference

CurrentSourceModels::DC::SET\_INJECTION\_CODE (

Simple delta current synapse.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::DeltaCurr:



## **Public Types**

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

• virtual std::string getApplyInputCode () const override

#### Static Public Member Functions

• static const DeltaCurr \* getInstance ()

#### **Additional Inherited Members**

19.19.1 Detailed Description

Simple delta current synapse.

Synaptic input provides a direct inject of instantaneous current

## 19.19.2 Member Typedef Documentation

#### 19.19.2.1 ParamValues

 ${\tt typedef~Snippet::ValueBase<~0~>~PostsynapticModels::DeltaCurr::ParamValues}$ 

# 19.19.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PostVarValues

#### 19.19.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PreVarValues

#### 19.19.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > PostsynapticModels::DeltaCurr::VarValues

#### 19.19.3 Member Function Documentation

#### 19.19.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::DeltaCurr::getApplyInputCode ( ) const [inline],
[override], [virtual]

Reimplemented from PostsynapticModels::Base.

#### 19.19.3.2 getInstance()

static const DeltaCurr\* PostsynapticModels::DeltaCurr::getInstance ( ) [inline], [static]

The documentation for this class was generated from the following file:

postsynapticModels.h

## 19.20 Snippet::Base::DerivedParam Struct Reference

A derived parameter has a name and a function for obtaining its value.

```
#include <snippet.h>
```

# **Public Attributes**

- std::string name
- std::function< double(const std::vector< double > &, double)> func

## 19.20.1 Detailed Description

A derived parameter has a name and a function for obtaining its value.

# 19.20.2 Member Data Documentation

#### 19.20.2.1 func

std::function<double(const std::vector<double> &, double)> Snippet::Base::DerivedParam::func

#### 19.20.2.2 name

std::string Snippet::Base::DerivedParam::name

The documentation for this struct was generated from the following file:


snippet.h

# 19.21 PostsynapticModels::ExpCond Class Reference

Exponential decay with synaptic input treated as a conductance value.

#include <postsynapticModels.h>

Inheritance diagram for PostsynapticModels::ExpCond:



#### **Public Types**

- typedef Snippet::ValueBase< 2 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- $\bullet \ \ type def \ Models:: VarInit Container Base < 0 > Post Var Values \\$

#### **Public Member Functions**

- virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override
- virtual StringVec getParamNames () const override
   Gets names of of (independent) model parameters.
- virtual DerivedParamVec getDerivedParams () const override

# **Static Public Member Functions**

static const ExpCond \* getInstance ()

# **Additional Inherited Members**

## 19.21.1 Detailed Description

Exponential decay with synaptic input treated as a conductance value.

This model has no variables and two parameters:

- · tau: Decay time constant
- E : Reversal potential

tau is used by the derived parameter expdecay which returns expf(-dt/tau).

#### 19.21.2 Member Typedef Documentation

#### 19.21.2.1 ParamValues

typedef Snippet::ValueBase< 2 > PostsynapticModels::ExpCond::ParamValues

#### 19.21.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCond::PostVarValues

#### 19.21.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCond::PreVarValues

#### 19.21.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > PostsynapticModels::ExpCond::VarValues

#### 19.21.3 Member Function Documentation

## 19.21.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCond::getApplyInputCode ( ) const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

# 19.21.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCond::getDecayCode ( ) const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

## 19.21.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCond::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

## 19.21.3.4 getInstance()

static const ExpCond\* PostsynapticModels::ExpCond::getInstance ( ) [inline], [static]

#### 19.21.3.5 getParamNames()

virtual StringVec PostsynapticModels::ExpCond::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


· postsynapticModels.h

## 19.22 PostsynapticModels::ExpCurr Class Reference

Exponential decay with synaptic input treated as a current value.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::ExpCurr:



## **Public Types**

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- $\bullet \ \ typedef \ Models:: VarInitContainer Base < 0 > PostVarValues \\$

## **Public Member Functions**

- virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override
- virtual StringVec getParamNames () const override
   Gets names of of (independent) model parameters.
- virtual DerivedParamVec getDerivedParams () const override

#### **Static Public Member Functions**

• static const ExpCurr \* getInstance ()

## **Additional Inherited Members**

# 19.22.1 Detailed Description

Exponential decay with synaptic input treated as a current value.

#### 19.22.2 Member Typedef Documentation

#### 19.22.2.1 ParamValues

typedef Snippet::ValueBase< 1 > PostsynapticModels::ExpCurr::ParamValues

#### 19.22.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PostVarValues

#### 19.22.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PreVarValues

#### 19.22.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > PostsynapticModels::ExpCurr::VarValues

#### 19.22.3 Member Function Documentation

## 19.22.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCurr::getApplyInputCode ( ) const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

# 19.22.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCurr::getDecayCode ( ) const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

## 19.22.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCurr::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

## 19.22.3.4 getInstance()

static const ExpCurr\* PostsynapticModels::ExpCurr::getInstance ( ) [inline], [static]

#### 19.22.3.5 getParamNames()

virtual StringVec PostsynapticModels::ExpCurr::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


· postsynapticModels.h

# 19.23 InitVarSnippet::Exponential Class Reference

Initialises variable by sampling from the exponential distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Exponential:



#### **Public Member Functions**

- DECLARE\_SNIPPET (InitVarSnippet::Exponential, 1)
- SET\_CODE ("\$(value) = \$(lambda) \* \$(gennrand\_exponential);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

## 19.23.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

#### 19.23.2 Member Function Documentation

#### 19.23.2.1 DECLARE\_SNIPPET()

## 19.23.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Exponential::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.23.2.3 SET_CODE()
```

```
InitVarSnippet::Exponential::SET_CODE ( )
```


The documentation for this class was generated from the following file:

· initVarSnippet.h

## 19.24 pygenn.model\_preprocessor.ExtraGlobalVariable Class Reference

Class holding information about GeNN extra global pointer variable.

Inheritance diagram for pygenn.model\_preprocessor.ExtraGlobalVariable:



#### **Public Member Functions**

- def \_\_init\_\_ (self, variable\_name, variable\_type, values=None)
   Init Variable.
- def set\_values (self, values)
   Set Variable's values.

#### **Public Attributes**

- name
- type
- view
- values

## 19.24.1 Detailed Description

Class holding information about GeNN extra global pointer variable.

#### 19.24.2 Constructor & Destructor Documentation

Init Variable.

#### **Parameters**

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable

#### 19.24.3 Member Function Documentation

## 19.24.3.1 set\_values()

```
def pygenn.model_preprocessor.ExtraGlobalVariable.set_values ( self, \\ values \ )
```

## Set Variable's values.

#### **Parameters**

values	iterable, single value or VarInit instance
--------	--

## 19.24.4 Member Data Documentation

#### 19.24.4.1 name

 $\verb|pygenn.model_preprocessor.ExtraGlobalVariable.name|\\$ 

# 19.24.4.2 type

pygenn.model\_preprocessor.ExtraGlobalVariable.type

# 19.24.4.3 values

pygenn.model\_preprocessor.ExtraGlobalVariable.values

#### 19.24.4.4 view

pygenn.model\_preprocessor.ExtraGlobalVariable.view


The documentation for this class was generated from the following file:

model\_preprocessor.py

# 19.25 InitSparseConnectivitySnippet::FixedProbability Class Reference

#include <initSparseConnectivitySnippet.h>

 $Inheritance\ diagram\ for\ InitSparseConnectivitySnippet:: FixedProbability:$ 



#### **Public Member Functions**

- DECLARE\_SNIPPET (InitSparseConnectivitySnippet::FixedProbability, 1)
- SET\_ROW\_BUILD\_CODE ("const scalar u = \$(gennrand\_uniform);\ "prevJ+=(1+(int)(log(u) \*\$(probLog← Recip)));\" "if(prevJ< \$(num\_post)) {\" " \$(addSynapse, prevJ);\" "}\" "else {\" " \$(endRow);\" "}\")

#### **Additional Inherited Members**

#### 19.25.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

#### 19.25.2 Member Function Documentation

# 19.25.2.1 DECLARE\_SNIPPET()

## 19.25.2.2 SET\_ROW\_BUILD\_CODE()

```
InitSparseConnectivitySnippet::FixedProbability::SET_ROW_BUILD_CODE ( )
```


The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

# 19.26 InitSparseConnectivitySnippet::FixedProbabilityBase Class Reference

```
#include <initSparseConnectivitySnippet.h>
```

 $Inheritance\ diagram\ for\ Init Sparse Connectivity Snippet :: Fixed Probability Base: The probability Base is the probabili$ 



#### **Public Member Functions**

- virtual std::string getRowBuildCode () const override=0
- SET\_ROW\_BUILD\_STATE\_VARS ({{"prevJ", "int", -1}})
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- virtual DerivedParamVec getDerivedParams () const override
- SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC ([](unsigned int numPre, unsigned int numPost, const std ::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPre);return binomial ← InverseCDF(quantile, numPost, pars[0]);})
- SET\_CALC\_MAX\_COL\_LENGTH\_FUNC ([](unsigned int numPre, unsigned int numPost, const std::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPost);return binomialInverseC← DF(quantile, numPre, pars[0]);})

#### **Additional Inherited Members**

# 19.26.1 Detailed Description

Base class for snippets which initialise connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

#### 19.26.2 Member Function Documentation

#### 19.26.2.1 getDerivedParams()

```
virtual DerivedParamVec InitSparseConnectivitySnippet::FixedProbabilityBase::getDerivedParams
( ) const [inline], [override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

#### 19.26.2.2 getParamNames()

```
virtual StringVec InitSparseConnectivitySnippet::FixedProbabilityBase::getParamNames ( ) const
[inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

## 19.26.2.3 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::FixedProbabilityBase::getRowBuildCode ( )
const [override], [pure virtual]
```

Reimplemented from InitSparseConnectivitySnippet::Base.

#### 19.26.2.4 SET\_CALC\_MAX\_COL\_LENGTH\_FUNC()

# 19.26.2.5 SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC()

## 19.26.2.6 SET\_ROW\_BUILD\_STATE\_VARS()


The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

#### 19.27 InitSparseConnectivitySnippet::FixedProbabilityNoAutapse Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbabilityNoAutapse:



# **Public Member Functions**

- DECLARE\_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse, 1)
- SET\_ROW\_BUILD\_CODE ("int nextJ;\ "do {\" " const scalar u=\$(gennrand\_uniform);\" " nextJ=prevJ+(1+(int)(log(u) \*\$(probLogRecip)));\" "} while(nextJ==\$(id\_pre));\" "prevJ=nextJ;\" "if(prevJ< \$(num\_post)) {\" " \$(add \color Synapse, prevJ);\" "}\" "else {\" " \$(endRow);\" "}\")</li>

#### **Additional Inherited Members**

#### 19.27.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons. This version ensures there are no autapses - connections between neurons with the same id so should be used for recurrent connections.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

#### 19.27.2 Member Function Documentation

#### 19.27.2.1 DECLARE\_SNIPPET()

#### 19.27.2.2 SET\_ROW\_BUILD\_CODE()

```
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse::SET_ROW_BUILD_CODE ( )
```

The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

#### 19.28 CodeGenerator::FunctionTemplate Struct Reference

```
#include <codeGenUtils.h>
```

#### **Public Member Functions**

• FunctionTemplate operator= (const FunctionTemplate &o)

#### **Public Attributes**

• const std::string genericName

Generic name used to refer to function in user code.

• const unsigned int numArguments

Number of function arguments.

const std::string doublePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses double precision.

const std::string singlePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses single precision.

#### 19.28.1 Detailed Description

Immutable structure for specifying how to implement a generic function e.g. gennrand\_uniform

NOTE for the sake of easy initialisation first two parameters of GenericFunction are repeated (C++17 fixes)

#### 19.28.2 Member Function Documentation

## 19.28.2.1 operator=()

```
FunctionTemplate CodeGenerator::FunctionTemplate::operator= ( const FunctionTemplate & o ) [inline]
```

#### 19.28.3 Member Data Documentation

#### 19.28.3.1 doublePrecisionTemplate

```
const std::string CodeGenerator::FunctionTemplate::doublePrecisionTemplate
```

The function template (for use with functionSubstitute) used when model uses double precision.

#### 19.28.3.2 genericName

```
const std::string CodeGenerator::FunctionTemplate::genericName
```

Generic name used to refer to function in user code.

## 19.28.3.3 numArguments

```
const unsigned int CodeGenerator::FunctionTemplate::numArguments
```

Number of function arguments.

#### 19.28.3.4 singlePrecisionTemplate

```
const std::string CodeGenerator::FunctionTemplate::singlePrecisionTemplate
```

The function template (for use with functionSubstitute) used when model uses single precision.

The documentation for this struct was generated from the following file:


• codeGenUtils.h

# 19.29 InitVarSnippet::Gamma Class Reference

Initialises variable by sampling from the exponential distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Gamma:



#### **Public Member Functions**

- DECLARE\_SNIPPET (InitVarSnippet::Gamma, 2)
- SET\_CODE ("\$(value) = \$(b) \* \$(gennrand\_gamma, \$(a));")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

#### **Additional Inherited Members**

#### 19.29.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

#### 19.29.2 Member Function Documentation

## 19.29.2.1 DECLARE\_SNIPPET()

## 19.29.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Gamma::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

#### 19.29.2.3 SET\_CODE()

```
InitVarSnippet::Gamma::SET_CODE ( )
```

The documentation for this class was generated from the following file:


• initVarSnippet.h

# 19.30 CurrentSourceModels::GaussianNoise Class Reference

Noisy current source with noise drawn from normal distribution.

#include <currentSourceModels.h>

Inheritance diagram for CurrentSourceModels::GaussianNoise:



## **Public Types**

- typedef Snippet::ValueBase< 2 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

- SET\_INJECTION\_CODE ("\$(injectCurrent, \$(mean) + \$(gennrand\_normal) \* \$(sd));\)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

# **Static Public Member Functions**

• static const GaussianNoise \* getInstance ()

#### **Additional Inherited Members**

## 19.30.1 Detailed Description

Noisy current source with noise drawn from normal distribution.

## It has 2 parameters:

- mean mean of the normal distribution [nA]
- sd standard deviation of the normal distribution [nA]

## 19.30.2 Member Typedef Documentation

#### 19.30.2.1 ParamValues

typedef Snippet::ValueBase< 2 > CurrentSourceModels::GaussianNoise::ParamValues

#### 19.30.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PostVarValues

#### 19.30.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PreVarValues

#### 19.30.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::GaussianNoise::VarValues

#### 19.30.3 Member Function Documentation

## 19.30.3.1 getInstance()

static const GaussianNoise\* CurrentSourceModels::GaussianNoise::getInstance ( ) [inline],
[static]

#### 19.30.3.2 getParamNames()

virtual StringVec CurrentSourceModels::GaussianNoise::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

## 19.30.3.3 SET\_INJECTION\_CODE()

```
CurrentSourceModels::GaussianNoise::SET_INJECTION_CODE (
    "$(injectCurrent, $(mean) + $(gennrand_normal) * $(sd));\ )
```


The documentation for this class was generated from the following file:

· currentSourceModels.h

# 19.31 pygenn.genn\_model.GeNNModel Class Reference

GeNNModel class This class helps to define, build and run a GeNN model from python.

Inheritance diagram for pygenn.genn\_model.GeNNModel:



#### **Public Member Functions**

- def \_\_init\_\_ (self, precision=None, model\_name="GeNNModel", enable\_debug=False, backend=None)
   Init GeNNModel.
- def use backend (self)
- · def use\_backend (self, backend)
- def default var location (self)

Default variable location - defines where state variables are initialised.

- def default var location (self, location)
- def default\_sparse\_connectivity\_location (location)

Default sparse connectivity mode - where connectivity is initialised.

- def default\_sparse\_connectivity\_location (self, location)
- def model\_name (self)

Name of the model.

- def model\_name (self, model\_name)
- · def t (self)

Simulation time in ms.

- def t (self, t)
- · def timestep (self)

Simulation time step.

- def timestep (self, timestep)
- def dT (self)

Step size.

- def dT (self, dt)
- def add\_neuron\_population (self, pop\_name, num\_neurons, neuron, param\_space, var\_space)

Add a neuron population to the GeNN model.

 def add\_synapse\_population (self, pop\_name, matrix\_type, delay\_steps, source, target, w\_update\_model, wu\_param\_space, wu\_var\_space, wu\_pre\_var\_space, wu\_post\_var\_space, postsyn\_model, ps\_param\_ space, ps\_var\_space, connectivity\_initialiser=None)

Add a synapse population to the GeNN model.

• def add current source (self, cs name, current source model, pop name, param space, var space)

Add a current source to the GeNN model.

def build (self, path\_to\_model="./")

Finalize and build a GeNN model.

· def load (self)

import the model as shared library and initialize it

def reinitialise (self)

reinitialise model to its original state without re-loading

- def step\_time (self)
- def pull\_state\_from\_device (self, pop\_name)

Pull state from the device for a given population.

• def pull\_spikes\_from\_device (self, pop\_name)

Pull spikes from the device for a given population.

def pull\_current\_spikes\_from\_device (self, pop\_name)

Pull spikes from the device for a given population.

def pull\_connectivity\_from\_device (self, pop\_name)

Pull connectivity from the device for a given population.

def pull\_var\_from\_device (self, pop\_name, var\_name)

Pull variable from the device for a given population.

• def push state to device (self, pop name)

Push state to the device for a given population.

def push\_spikes\_to\_device (self, pop\_name)

Push spikes to the device for a given population.

def push\_current\_spikes\_to\_device (self, pop\_name)

Push current spikes to the device for a given population.

def push\_connectivity\_to\_device (self, pop\_name)

Push connectivity to the device for a given population.

def push\_var\_to\_device (self, pop\_name, var\_name)

Push variable to the device for a given population.

• def end (self)

Free memory.

#### **Public Attributes**

- use\_backend
- · default var location
- model\_name
- neuron\_populations
- synapse\_populations
- current\_sources
- dT
- T

## 19.31.1 Detailed Description

GeNNModel class This class helps to define, build and run a GeNN model from python.

## 19.31.2 Constructor & Destructor Documentation

#### Init GeNNModel.

# **Parameters**

precision	string precision as string ("float", "double" or "long double"). defaults to float.
model_name	string name of the model. Defaults to "GeNNModel".
enable_debug	boolean enable debug mode. Disabled by default.
backend	string specifying name of backend module to use Defaults to None to pick 'best' backend for your system

#### 19.31.3 Member Function Documentation

## 19.31.3.1 add\_current\_source()

Add a current source to the GeNN model.

#### **Parameters**

cs_name	name of the new current source
current_source_model	type of the CurrentSourceModels class as string or instance of CurrentSourceModels class derived from
	<pre>pygenn.genn_wrapper.CurrentSourceModels.Custom (see also pygenn.genn_model.create_custom_current_source_class)</pre>
pop_name	name of the population into which the current source should be injected
param_space	dict with param values for the CurrentSourceModels class
var_space	dict with initial variable values for the CurrentSourceModels class

# 19.31.3.2 add\_neuron\_population()

Add a neuron population to the GeNN model.

## **Parameters**

pop_name	name of the new population
num_neurons	number of neurons in the new population
neuron	type of the NeuronModels class as string or instance of neuron class derived from pygenn.genn_wrapper.NeuronModels.Custom (see also pygenn.genn_model.create_custom_neuron_class)
param_space	dict with param values for the NeuronModels class
var_space	dict with initial variable values for the NeuronModels class

# 19.31.3.3 add\_synapse\_population()

```
target,
w_update_model,
wu_param_space,
wu_var_space,
wu_pre_var_space,
wu_post_var_space,
postsyn_model,
ps_param_space,
ps_var_space,
connectivity_initialiser = None )
```

Add a synapse population to the GeNN model.

#### **Parameters**

pop_name	name of the new population
matrix_type	type of the matrix as string
delay_steps	delay in number of steps
source	source neuron group
target	target neuron group
w_update_model	type of the WeightUpdateModels class as string or instance of weight update model class derived from
	pygenn.genn_wrapper.WeightUpdateModels.Custom (see also
	pygenn.genn_model.create_custom_weight_update_class)
wu_param_space	dict with param values for the WeightUpdateModels class
wu_var_space	dict with initial values for WeightUpdateModels state variables
wu_pre_var_space	dict with initial values for WeightUpdateModels presynaptic variables
wu_post_var_space	dict with initial values for WeightUpdateModels postsynaptic variables
postsyn_model	type of the PostsynapticModels class as string or instance of postsynaptic model class derived from pygenn.genn_wrapper.PostsynapticModels.Custom (see also pygenn.genn_model.create_custom_postsynaptic_class)
ps_param_space	dict with param values for the PostsynapticModels class
ps_var_space	dict with initial variable values for the PostsynapticModels class
connectivity_initialiser	InitSparseConnectivitySnippet::Init for connectivity

# 19.31.3.4 build()

Finalize and build a GeNN model.

# **Parameters**

path\_to\_model path where to place the generated model code. Defaults to the local directory.

```
19.31.3.5 default_sparse_connectivity_location() [1/2]
```

```
\label{location} \mbox{def pygenn.genn\_model.GeNNModel.default\_sparse\_connectivity\_location (} \\ \mbox{$location )$}
```

Default sparse connectivity mode - where connectivity is initialised.

```
19.31.3.6 default_sparse_connectivity_location() [2/2]
def pygenn.genn_model.GeNNModel.default_sparse_connectivity_location (
               self.
               location )
19.31.3.7 default_var_location() [1/2]
def pygenn.genn_model.GeNNModel.default_var_location (
               self )
Default variable location - defines where state variables are initialised.
19.31.3.8 default_var_location() [2/2]
def pygenn.genn_model.GeNNModel.default_var_location (
               self,
               location )
19.31.3.9 dT() [1/2]
def pygenn.genn_model.GeNNModel.dT (
              self )
Step size.
19.31.3.10 dT() [2/2]
def pygenn.genn_model.GeNNModel.dT (
              self,
               dt )
19.31.3.11 end()
{\tt def pygenn.genn\_model.GeNNModel.end} (
               self )
Free memory.
19.31.3.12 load()
def pygenn.genn_model.GeNNModel.load (
               self )
import the model as shared library and initialize it
19.31.3.13 model_name() [1/2]
def pygenn.genn_model.GeNNModel.model_name (
```

```
self )
```

Name of the model.

Pull connectivity from the device for a given population.

```
19.31.3.16 pull_current_spikes_from_device()
```

```
def pygenn.genn_model.GeNNModel.pull_current_spikes_from_device ( self, \\ pop\_name \ )
```

Pull spikes from the device for a given population.

```
19.31.3.17 pull_spikes_from_device()
```

Pull spikes from the device for a given population.

```
19.31.3.18 pull_state_from_device()
```

```
def pygenn.genn_model.GeNNModel.pull_state_from_device ( self, \\ pop_name \ )
```

Pull state from the device for a given population.

```
19.31.3.19 pull_var_from_device()
```

Pull variable from the device for a given population.

```
19.31.3.20 push_connectivity_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_connectivity_to_device ( self, \\ pop\_name \ )
```

Push connectivity to the device for a given population.

```
19.31.3.21 push_current_spikes_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_current_spikes_to_device ( self, \\ pop_name \ )
```

Push current spikes to the device for a given population.

#### 19.31.3.22 push\_spikes\_to\_device()

```
def pygenn.genn_model.GeNNModel.push_spikes_to_device ( self, \\ pop_name \ )
```

Push spikes to the device for a given population.

#### 19.31.3.23 push\_state\_to\_device()

Push state to the device for a given population.

#### 19.31.3.24 push\_var\_to\_device()

Push variable to the device for a given population.

#### 19.31.3.25 reinitialise()

```
\label{lem:continuous} \mbox{def pygenn.genn\_model.GeNNModel.reinitialise (} \\ self \mbox{)}
```

reinitialise model to its original state without re-loading

#### 19.31.3.26 step\_time()

```
\begin{tabular}{ll} \tt def pygenn.genn\_model.GeNNModel.step\_time ( \\ self ) \end{tabular}
```

```
19.31.3.27 t() [1/2]
def pygenn.genn_model.GeNNModel.t (
               self )
Simulation time in ms.
19.31.3.28 t() [2/2]
def pygenn.genn_model.GeNNModel.t (
              self,
               t)
19.31.3.29 timestep() [1/2]
def pygenn.genn_model.GeNNModel.timestep (
               self )
Simulation time step.
19.31.3.30 timestep() [2/2]
def pygenn.genn_model.GeNNModel.timestep (
               self,
               timestep )
19.31.3.31 use_backend() [1/2]
def pygenn.genn_model.GeNNModel.use_backend (
               self )
19.31.3.32 use_backend() [2/2]
def pygenn.genn_model.GeNNModel.use_backend (
              self,
               backend )
19.31.4 Member Data Documentation
19.31.4.1 current_sources
pygenn.genn_model.GeNNModel.current_sources
19.31.4.2 default_var_location
```

pygenn.genn\_model.GeNNModel.default\_var\_location

#### 19.31.4.3 dT

pygenn.genn\_model.GeNNModel.dT

#### 19.31.4.4 model\_name

pygenn.genn\_model.GeNNModel.model\_name

## 19.31.4.5 neuron\_populations

pygenn.genn\_model.GeNNModel.neuron\_populations

# 19.31.4.6 synapse\_populations

pygenn.genn\_model.GeNNModel.synapse\_populations

#### 19.31.4.7 T

pygenn.genn\_model.GeNNModel.T

#### 19.31.4.8 use\_backend

pygenn.genn\_model.GeNNModel.use\_backend


The documentation for this class was generated from the following file:

· genn\_model.py

## 19.32 pygenn.genn\_groups.Group Class Reference

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

Inheritance diagram for pygenn.genn\_groups.Group:



## **Public Member Functions**

- def \_\_init\_\_ (self, name)
   Init Group.
- def set\_var (self, var\_name, values)
   Set values for a Variable.

# **Public Attributes**

name

- vars
- extra\_global\_params

## 19.32.1 Detailed Description

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

## 19.32.2 Constructor & Destructor Documentation

Init Group.

#### **Parameters**

name	string name of the Group
------	--------------------------

# 19.32.3 Member Function Documentation

```
19.32.3.1 set_var()
```

Set values for a Variable.

## **Parameters**

var_name	string with the name of the variable
values	iterable or a single value

## 19.32.4 Member Data Documentation

# 19.32.4.1 extra\_global\_params

```
pygenn.genn_groups.Group.extra_global_params
```

# 19.32.4.2 name

pygenn.genn\_groups.Group.name

#### 19.32.4.3 vars

```
pygenn.genn_groups.Group.vars
```


The documentation for this class was generated from the following file:

• genn\_groups.py

#### 19.33 InitSparseConnectivitySnippet::Init Class Reference

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::Init:



#### **Public Member Functions**

Init (const Base \*snippet, const std::vector< double > &params)

#### 19.33.1 Constructor & Destructor Documentation

#### 19.33.1.1 Init()

The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

# 19.34 Snippet::Init < SnippetBase > Class Template Reference

```
#include <snippet.h>
```

## **Public Member Functions**

- Init (const SnippetBase \*snippet, const std::vector< double > &params)
- const SnippetBase \* getSnippet () const
- const std::vector< double > & getParams () const
- const std::vector< double > & getDerivedParams () const
- void initDerivedParams (double dt)

# 19.34.1 Detailed Description

```
template<typename SnippetBase> class Snippet::Init< SnippetBase>
```

Class used to bind together everything required to utilize a snippet

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

#### 19.34.2 Constructor & Destructor Documentation

```
19.34.2.1 Init()
```

#### 19.34.3 Member Function Documentation

template<typename SnippetBase>

```
19.34.3.1 getDerivedParams()
```

```
const std::vector<double>& Snippet::Init< SnippetBase >::getDerivedParams ( ) const [inline]
19.34.3.2 getParams()
```

```
template<typename SnippetBase>
const std::vector<double>& Snippet::Init< SnippetBase >::getParams ( ) const [inline]
```

#### 19.34.3.3 getSnippet()

```
template<typename SnippetBase>
const SnippetBase* Snippet::Init< SnippetBase >::getSnippet ( ) const [inline]
```

## 19.34.3.4 initDerivedParams()

The documentation for this class was generated from the following file:


· snippet.h

## 19.35 NeuronModels::Izhikevich Class Reference

Izhikevich neuron with fixed parameters [1].

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Izhikevich:



## **Public Types**

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

#### **Static Public Member Functions**

static const NeuronModels::Izhikevich \* getInstance ()

### Additional Inherited Members

### 19.35.1 Detailed Description

Izhikevich neuron with fixed parameters [1].

It is usually described as

$$\begin{array}{lcl} \frac{dV}{dt} & = & 0.04V^2 + 5V + 140 - U + I, \\ \frac{dU}{dt} & = & a(bV - U), \end{array}$$

I is an external input current and the voltage V is reset to parameter c and U incremented by parameter d, whenever V >= 30 mV. This is paired with a particular integration procedure of two 0.5 ms Euler time steps for the V equation followed by one 1 ms time step of the U equation. Because of its popularity we provide this model in this form here event though due to the details of the usual implementation it is strictly speaking inconsistent with the displayed equations.

Variables are:

- V Membrane potential
- U Membrane recovery variable

## Parameters are:

- · a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

## 19.35.2 Member Typedef Documentation

```
19.35.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::Izhikevich::ParamValues

19.35.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PostVarValues

19.35.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PreVarValues

19.35.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::Izhikevich::VarValues

19.35.3 Member Function Documentation

19.35.3.1 getInstance()

static const NeuronModels::Izhikevich* NeuronModels::Izhikevich::getInstance ( ) [inline], [static]

19.35.3.2 getParamNames()

virtual StringVec NeuronModels::Izhikevich::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

Reimplemented in NeuronModels::IzhikevichVariable.

#### 19.35.3.3 getSimCode()

virtual std::string NeuronModels::Izhikevich::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

## 19.35.3.4 getThresholdConditionCode()

virtual std::string NeuronModels::Izhikevich::getThresholdConditionCode ( ) const [inline],
[override], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

## 19.35.3.5 getVars()

virtual VarVec NeuronModels::Izhikevich::getVars ( ) const [inline], [override], [virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

Reimplemented in NeuronModels::IzhikevichVariable.

The documentation for this class was generated from the following file:


• neuronModels.h

### 19.36 NeuronModels::IzhikevichVariable Class Reference

Izhikevich neuron with variable parameters [1].

#include <neuronModels.h>

Inheritance diagram for NeuronModels::IzhikevichVariable:



### **Public Types**

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 6 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

- virtual StringVec getParamNames () const override
   Gets names of of (independent) model parameters.
- virtual VarVec getVars () const override
   Gets names and types (as strings) of model variables.

### Static Public Member Functions

• static const NeuronModels::IzhikevichVariable \* getInstance ()

### **Additional Inherited Members**

## 19.36.1 Detailed Description

Izhikevich neuron with variable parameters [1].

This is the same model as Izhikevich but parameters are defined as "variables" in order to allow users to provide individual values for each individual neuron instead of fixed values for all neurons across the population.

Accordingly, the model has the Variables:

- $\ensuremath{\,\vee\,}$  Membrane potential
- U Membrane recovery variable
- · a time scale of U
- b sensitivity of U
- $_{\mbox{\scriptsize C}}$  after-spike reset value of V
- d after-spike reset value of U

and no parameters.

## 19.36.2 Member Typedef Documentation

#### 19.36.2.1 ParamValues

typedef Snippet::ValueBase< 0 > NeuronModels::IzhikevichVariable::ParamValues

### 19.36.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::IzhikevichVariable::PostVarValues

## 19.36.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::IzhikevichVariable::PreVarValues

#### 19.36.2.4 VarValues

typedef Models::VarInitContainerBase< 6 > NeuronModels::IzhikevichVariable::VarValues

#### 19.36.3 Member Function Documentation

#### 19.36.3.1 getInstance()

static const NeuronModels::IzhikevichVariable\* NeuronModels::IzhikevichVariable::getInstance (
) [inline], [static]

### 19.36.3.2 getParamNames()

virtual StringVec NeuronModels::IzhikevichVariable::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::Izhikevich.

## 19.36.3.3 getVars()

virtual VarVec NeuronModels::IzhikevichVariable::getVars ( ) const [inline], [override],

Gets names and types (as strings) of model variables.

Reimplemented from NeuronModels::Izhikevich.


The documentation for this class was generated from the following file:

neuronModels.h

## 19.37 NeuronModels::LIF Class Reference

#include <neuronModels.h>

Inheritance diagram for NeuronModels::LIF:



### **Public Types**

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

· virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual std::string getResetCode () const override

Gets code that defines the reset action taken after a spike occurred. This can be empty.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- virtual DerivedParamVec getDerivedParams () const override
- virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

SET\_NEEDS\_AUTO\_REFRACTORY (false)

#### **Static Public Member Functions**

static const LIF \* getInstance ()

# **Additional Inherited Members**

### 19.37.1 Member Typedef Documentation

## 19.37.1.1 ParamValues

```
typedef Snippet::ValueBase< 7 > NeuronModels::LIF::ParamValues
```

## 19.37.1.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PostVarValues
```

### 19.37.1.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PreVarValues

#### 19.37.1.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::LIF::VarValues

### 19.37.2 Member Function Documentation

### 19.37.2.1 getDerivedParams()

```
virtual DerivedParamVec NeuronModels::LIF::getDerivedParams ( ) const [inline], [override],
[virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

### 19.37.2.2 getInstance()

```
static const LIF* NeuronModels::LIF::getInstance ( ) [inline], [static]
```

#### 19.37.2.3 getParamNames()

```
virtual StringVec NeuronModels::LIF::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

#### 19.37.2.4 getResetCode()

```
virtual std::string NeuronModels::LIF::getResetCode ( ) const [inline], [override], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

### 19.37.2.5 getSimCode()

```
virtual std::string NeuronModels::LIF::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

# 19.37.2.6 getThresholdConditionCode()

```
virtual std::string NeuronModels::LIF::getThresholdConditionCode ( ) const [inline], [override],
[virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

### 19.37.2.7 getVars()

```
virtual VarVec NeuronModels::LIF::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

### 19.37.2.8 SET\_NEEDS\_AUTO\_REFRACTORY()

The documentation for this class was generated from the following file:

• neuronModels.h

### 19.38 CodeGenerator::MemAlloc Class Reference

```
#include <backendBase.h>
```

#### **Public Member Functions**

- size\_t getHostBytes () const
- size\_t getDeviceBytes () const
- size\_t getZeroCopyBytes () const
- size\_t getHostMBytes () const
- size\_t getDeviceMBytes () const
- size\_t getZeroCopyMBytes () const
- MemAlloc & operator+= (const MemAlloc &rhs)

### **Static Public Member Functions**

- static MemAlloc zero ()
- static MemAlloc host (size\_t hostBytes)
- static MemAlloc device (size\_t deviceBytes)
- static MemAlloc zeroCopy (size\_t zeroCopyBytes)

#### 19.38.1 Member Function Documentation

```
19.38.1.1 device()
```

## 19.38.1.2 getDeviceBytes()

```
size_t CodeGenerator::MemAlloc::getDeviceBytes ( ) const [inline]
```

## 19.38.1.3 getDeviceMBytes()

```
size_t CodeGenerator::MemAlloc::getDeviceMBytes ( ) const [inline]
```

```
19.38.1.4 getHostBytes()
size_t CodeGenerator::MemAlloc::getHostBytes ( ) const [inline]
19.38.1.5 getHostMBytes()
size_t CodeGenerator::MemAlloc::getHostMBytes ( ) const [inline]
19.38.1.6 getZeroCopyBytes()
size_t CodeGenerator::MemAlloc::getZeroCopyBytes ( ) const [inline]
19.38.1.7 getZeroCopyMBytes()
size_t CodeGenerator::MemAlloc::getZeroCopyMBytes ( ) const [inline]
19.38.1.8 host()
static MemAlloc CodeGenerator::MemAlloc::host (
            size_t hostBytes ) [inline], [static]
19.38.1.9 operator+=()
MemAlloc& CodeGenerator::MemAlloc::operator+= (
             const MemAlloc & rhs ) [inline]
19.38.1.10 zero()
static MemAlloc CodeGenerator::MemAlloc::zero ( ) [inline], [static]
19.38.1.11 zeroCopy()
static MemAlloc CodeGenerator::MemAlloc::zeroCopy (
             size_t zeroCopyBytes ) [inline], [static]
```

The documentation for this class was generated from the following file:


backendBase.h

## 19.39 ModelSpec Class Reference

Object used for specifying a neuronal network model.

```
#include <modelSpec.h>
```

Inheritance diagram for ModelSpec:



## **Public Types**

- typedef std::map< std::string, NeuronGroupInternal >::value\_type NeuronGroupValueType
- typedef std::map< std::string, SynapseGroupInternal >::value\_type SynapseGroupValueType

### **Public Member Functions**

- ModelSpec ()
- ModelSpec (const ModelSpec &)=delete
- ModelSpec & operator= (const ModelSpec &)=delete
- ∼ModelSpec ()
- void setName (const std::string &name)

Method to set the neuronal network model name.

void setPrecision (FloatType)

Set numerical precision for floating point.

• void setTimePrecision (TimePrecision timePrecision)

Set numerical precision for time.

void setDT (double dt)

Set the integration step size of the model.

void setTiming (bool timingEnabled)

Set whether timers and timing commands are to be included.

void setSeed (unsigned int rngSeed)

Set the random seed (disables automatic seeding if argument not 0).

void setDefaultVarLocation (VarLocation loc)

What is the default location for model state variables?

void setDefaultExtraGlobalParamLocation (VarLocation loc)

What is the default location for model extra global parameters?

void setDefaultSparseConnectivityLocation (VarLocation loc)

What is the default location for sparse synaptic connectivity?

void setMergePostsynapticModels (bool merge)

Should compatible postsynaptic models and dendritic delay buffers be merged?

• const std::string & getName () const

Gets the name of the neuronal network model.

const std::string & getPrecision () const

Gets the floating point numerical precision.

• std::string getTimePrecision () const

Gets the floating point numerical precision used to represent time.

double getDT () const

Gets the model integration step size.

• unsigned int getSeed () const

Get the random seed.

bool isTimingEnabled () const

Are timers and timing commands enabled.

unsigned int getNumLocalNeurons () const

How many neurons are simulated locally in this model.

unsigned int getNumRemoteNeurons () const

How many neurons are simulated remotely in this model.

• unsigned int getNumNeurons () const

How many neurons make up the entire model.

NeuronGroup \* findNeuronGroup (const std::string &name)

Find a neuron group by name.

• template<typename NeuronModel >

NeuronGroup \* addNeuronPopulation (const std::string &name, unsigned int size, const NeuronModel \*model, const typename NeuronModel::ParamValues &paramValues, const typename NeuronModel::Var← Values &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a neuron model managed by the user.

 $\bullet \ \ \text{template}{<} \text{typename NeuronModel} >$ 

NeuronGroup \* addNeuronPopulation (const std::string &name, unsigned int size, const typename Neuron ← Model::ParamValues &paramValues, const typename NeuronModel::VarValues &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE\_MODEL and IMPLEMENT\_MODEL macros.

SynapseGroup \* findSynapseGroup (const std::string &name)

Find a synapse group by name.

• template < typename WeightUpdateModel , typename PostsynapticModel > SynapseGroup \* addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const WeightUpdateModel \*wum, const typename WeightUpdateModel::ParamValues &weightParamValues, const typename WeightUpdate &weightUpdateModel::PreVarValues &weight PreVarInitialisers, const typename WeightUpdateModel::PreVarValues &weightPostVarInitialisers, const PostsynapticModel \*psm, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticModel::VarValues &postsynapticModel::VarVal

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

template<typename WeightUpdateModel , typename PostsynapticModel >
 SynapseGroup \* addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &rg, const typename WeightUpdateModel::Param
 Values &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename Postsynaptic
 Model::VarValues &postsynapticVarInitialisers, const InitSparseConnectivitySnippet::Init &connectivity
 Initialiser=uninitialisedConnectivity())

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE MODEL and IMPLEMENT MODEL macros.

• template<typename WeightUpdateModel , typename PostsynapticModel > SynapseGroup \* addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const typename WeightUpdateModel::

ParamValues &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename WeightUpdateModel::PreVarValues &weightPreVarInitialisers, const typename Weight

UpdateModel::PostVarValues &weightPostVarInitialisers, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticVarInitialisers,

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE\_MODEL and IMPLEMENT\_MODEL macros.

CurrentSource \* findCurrentSource (const std::string &name)

Find a current source by name.

• template<typename CurrentSourceModel >

CurrentSource \* addCurrentSource (const std::string &currentSourceName, const CurrentSourceModel \*model, const std::string &targetNeuronGroupName, const typename CurrentSourceModel::ParamValues &paramValues, const typename CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a current source model managed by the user.

const InitSparseConnectivitySnippet::Init &connectivityInitialiser=uninitialisedConnectivity())

template<typename CurrentSourceModel >
 CurrentSource \* addCurrentSource (const std::string &currentSourceName, const std::string &target
 NeuronGroupName, const typename CurrentSourceModel::ParamValues &paramValues, const typename
 CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a singleton current source model created using standard DECLARE← \_MODEL and IMPLEMENT\_MODEL macros.

#### **Protected Member Functions**

• void finalize ()

Finalise model.

• std::string scalarExpr (double) const

Get the string literal that should be used to represent a value in the model's floating-point type.

• bool zeroCopyInUse () const

Are any variables in any populations in this model using zero-copy memory?

- const std::map< std::string, NeuronGroupInternal > & getLocalNeuronGroups () const Get std::map containing local named NeuronGroup objects in model.
- const std::map< std::string, NeuronGroupInternal > & getRemoteNeuronGroups () const
   Get std::map containing remote named NeuronGroup objects in model.
- const std::map < std::string, SynapseGroupInternal > & getLocalSynapseGroups () const Get std::map containing local named SynapseGroup objects in model.
- const std::map < std::string, SynapseGroupInternal > & getRemoteSynapseGroups () const
   Get std::map containing remote named SynapseGroup objects in model.
- const std::map < std::string, CurrentSourceInternal > & getLocalCurrentSources () const
   Get std::map containing local named CurrentSource objects in model.
- const std::map < std::string, CurrentSourceInternal > & getRemoteCurrentSources () const Get std::map containing remote named CurrentSource objects in model.

#### 19.39.1 Detailed Description

Object used for specifying a neuronal network model.

## 19.39.2 Member Typedef Documentation

## 19.39.2.1 NeuronGroupValueType

 $\verb|typedef| std::map| < std::string, NeuronGroupInternal>::value\_type ModelSpec::NeuronGroupValueType | typedef| | typed$ 

## 19.39.2.2 SynapseGroupValueType

typedef std::map<std::string, SynapseGroupInternal>::value\_type ModelSpec::SynapseGroupValue← Type

## 19.39.3 Constructor & Destructor Documentation

```
19.39.3.1 ModelSpec() [1/2]
ModelSpec::ModelSpec ( )
19.39.3.2 ModelSpec() [2/2]
ModelSpec::ModelSpec (
             const ModelSpec & ) [delete]
19.39.3.3 \sim ModelSpec()
ModelSpec::~ModelSpec ( )
19.39.4 Member Function Documentation
19.39.4.1 addCurrentSource() [1/2]
template<typename CurrentSourceModel >
CurrentSource* ModelSpec::addCurrentSource (
             const std::string & currentSourceName,
             const CurrentSourceModel * model,
             const std::string & targetNeuronGroupName,
             const typename CurrentSourceModel::ParamValues & paramValues,
             const typename CurrentSourceModel::VarValues & varInitialisers ) [inline]
```

Adds a new current source to the model using a current source model managed by the user.

## **Template Parameters**

### **Parameters**

currentSourceName	string containing unique name of current source.
model	current source model to use for current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in CurrentSource::VarValues object.

## Returns

pointer to newly created CurrentSource

## 19.39.4.2 addCurrentSource() [2/2]

```
const typename CurrentSourceModel::ParamValues & paramValues,
const typename CurrentSourceModel::VarValues & varInitialisers ) [inline]
```

Adds a new current source to the model using a singleton current source model created using standard DECLAR  $\leftarrow$  E\_MODEL and IMPLEMENT\_MODEL macros.

## **Template Parameters**

CurrentSourceModel	type of neuron model (derived from CurrentSourceModel::Base).
--------------------	---

#### **Parameters**

currentSourceName	string containing unique name of current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in CurrentSourceModel::VarValues object.

## Returns

pointer to newly created CurrentSource

## 19.39.4.3 addNeuronPopulation() [1/2]

Adds a new neuron group to the model using a neuron model managed by the user.

## **Template Parameters**

	NeuronModel	type of neuron model (derived from NeuronModels::Base).	1
--	-------------	---	---

#### **Parameters**

name	string containing unique name of neuron population.
size	integer specifying how many neurons are in the population.
model	neuron model to use for neuron group.
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.
varlnitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
hostID	if using MPI, the ID of the node to simulate this population on.

#### Returns

pointer to newly created NeuronGroup

#### 19.39.4.4 addNeuronPopulation() [2/2]

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE\_MODEL and IMPLEMENT\_MODEL macros.

#### **Template Parameters**

NeuronModel	type of neuron model (derived from NeuronModels::Base).
-------------	---

#### **Parameters**

name	string containing unique name of neuron population.	
size	integer specifying how many neurons are in the population.	
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.	
varInitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.	
hostID	if using MPI, the ID of the node to simulate this population on.	

#### Returns

pointer to newly created NeuronGroup

### 19.39.4.5 addSynapsePopulation() [1/3]

```
{\tt template}{<} {\tt typename WeightUpdateModel , typename PostsynapticModel >}
SynapseGroup* ModelSpec::addSynapsePopulation (
             const std::string & name,
             SynapseMatrixType mtype,
             unsigned int delaySteps,
             const std::string & src,
             const std::string & trg,
             const WeightUpdateModel * wum,
             const typename WeightUpdateModel::ParamValues & weightParamValues,
             const typename WeightUpdateModel::VarValues & weightVarInitialisers,
             const typename WeightUpdateModel::PreVarValues & weightPreVarInitialisers,
             const typename WeightUpdateModel::PostVarValues & weightPostVarInitialisers,
             const PostsynapticModel * psm,
             const typename PostsynapticModel::ParamValues & postsynapticParamValues,
             const typename PostsynapticModel::VarValues & postsynapticVarInitialisers,
             {\tt const\ InitSparseConnectivitySnippet::Init\ \&\ connectivityInitialiser=uninitialised} {\longleftrightarrow}
Connectivity() ) [inline]
```

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

## **Template Parameters**

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

#### **Parameters**

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
wum	weight update model to use for synapse group.
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
psm	postsynaptic model to use for synapse group.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.  Typically wrapped with it's parameters using initConnectivity function

# Returns

pointer to newly created SynapseGroup

## 19.39.4.6 addSynapsePopulation() [2/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE\_MODEL and IMPLEMENT\_MODEL macros.

#### **Template Parameters**

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

### **Parameters**

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
	represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
weightParamValues	parameters for weight update model wrapped in
	WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.  Typically wrapped with it's parameters using initConnectivity function

#### Returns

pointer to newly created SynapseGroup

## 19.39.4.7 addSynapsePopulation() [3/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE\_MODEL and IMPLEMENT\_MODEL macros.

# **Template Parameters**

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

### **Parameters**

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model per-synapse state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.  Typically wrapped with it's parameters using initConnectivity function

## Returns

pointer to newly created SynapseGroup

# 19.39.4.8 finalize()

```
void ModelSpec::finalize ( ) [protected]
```

Finalise model.

## 19.39.4.9 findCurrentSource()

Find a current source by name.

This function attempts to find an existing current source.

# 19.39.4.10 findNeuronGroup()

Find a neuron group by name.

#### 19.39.4.11 findSynapseGroup()

Find a synapse group by name.

### 19.39.4.12 getDT()

```
double ModelSpec::getDT ( ) const [inline]
```

Gets the model integration step size.

## 19.39.4.13 getLocalCurrentSources()

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getLocalCurrentSources ( )
const [inline], [protected]
```

Get std::map containing local named CurrentSource objects in model.

### 19.39.4.14 getLocalNeuronGroups()

```
const std::map<std::string, NeuronGroupInternal>& ModelSpec::getLocalNeuronGroups ( ) const
[inline], [protected]
```

Get std::map containing local named NeuronGroup objects in model.

### 19.39.4.15 getLocalSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getLocalSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing local named SynapseGroup objects in model.

# 19.39.4.16 getName()

```
const std::string& ModelSpec::getName ( ) const [inline]
```

Gets the name of the neuronal network model.

#### 19.39.4.17 getNumLocalNeurons()

```
unsigned int ModelSpec::getNumLocalNeurons ( ) const
```

How many neurons are simulated locally in this model.

### 19.39.4.18 getNumNeurons()

```
unsigned int ModelSpec::getNumNeurons ( ) const [inline]
```

How many neurons make up the entire model.

### 19.39.4.19 getNumRemoteNeurons()

```
unsigned int ModelSpec::getNumRemoteNeurons ( ) const
```

How many neurons are simulated remotely in this model.

## 19.39.4.20 getPrecision()

```
const std::string& ModelSpec::getPrecision ( ) const [inline]
```

Gets the floating point numerical precision.

## 19.39.4.21 getRemoteCurrentSources()

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getRemoteCurrentSources ( )
const [inline], [protected]
```

Get std::map containing remote named CurrentSource objects in model.

### 19.39.4.22 getRemoteNeuronGroups()

```
const std::map<std::string, NeuronGroupInternal>& ModelSpec::getRemoteNeuronGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named NeuronGroup objects in model.

## 19.39.4.23 getRemoteSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getRemoteSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named SynapseGroup objects in model.

## 19.39.4.24 getSeed()

```
unsigned int ModelSpec::getSeed ( ) const [inline]
```

Get the random seed.

#### 19.39.4.25 getTimePrecision()

```
std::string ModelSpec::getTimePrecision ( ) const
```

Gets the floating point numerical precision used to represent time.

## 19.39.4.26 isTimingEnabled()

```
bool ModelSpec::isTimingEnabled ( ) const [inline]
```

Are timers and timing commands enabled.

### 19.39.4.27 operator=()

Get the string literal that should be used to represent a value in the model's floating-point type.

#### 19.39.4.29 setDefaultExtraGlobalParamLocation()

double val ) const [protected]

What is the default location for model extra global parameters?

Historically, this was just left up to the user to handle

### 19.39.4.30 setDefaultSparseConnectivityLocation()

What is the default location for sparse synaptic connectivity?

Historically, everything was allocated on both the host AND device

### 19.39.4.31 setDefaultVarLocation()

What is the default location for model state variables?

Historically, everything was allocated on both the host AND device

## 19.39.4.32 setDT()

Set the integration step size of the model.

### 19.39.4.33 setMergePostsynapticModels()

Should compatible postsynaptic models and dendritic delay buffers be merged?

This can significantly reduce the cost of updating neuron population but means that per-synapse group inSyn arrays can not be retrieved

# 19.39.4.34 setName()

Method to set the neuronal network model name.

### 19.39.4.35 setPrecision()

Set numerical precision for floating point.

This function sets the numerical precision of floating type variables. By default, it is GENN\_GENN\_FLOAT.

## 19.39.4.36 setSeed()

Set the random seed (disables automatic seeding if argument not 0).

### 19.39.4.37 setTimePrecision()

Set numerical precision for time.

### 19.39.4.38 setTiming()

```
void ModelSpec::setTiming (
          bool timingEnabled ) [inline]
```

Set whether timers and timing commands are to be included.

## 19.39.4.39 zeroCopylnUse()

```
bool ModelSpec::zeroCopyInUse ( ) const [protected]
```

Are any variables in any populations in this model using zero-copy memory?


The documentation for this class was generated from the following files:

- · modelSpec.h
- modelSpec.cc

## 19.40 ModelSpecInternal Class Reference

```
#include <modelSpecInternal.h>
```

Inheritance diagram for ModelSpecInternal:



#### **Additional Inherited Members**

The documentation for this class was generated from the following file:

· modelSpecInternal.h

## 19.41 CodeGenerator::NamelterCtx < Container > Struct Template Reference

```
#include <codeGenUtils.h>
```

### **Public Types**

• typedef StructNameConstIter< typename Container::const\_iterator > NameIter

#### **Public Member Functions**

• NamelterCtx (const Container &c)

### **Public Attributes**

- · const Container container
- · const Namelter nameBegin
- · const Namelter nameEnd

## 19.41.1 Member Typedef Documentation

# 19.41.1.1 Namelter

```
template<typename Container >
typedef StructNameConstIter<typename Container::const_iterator> CodeGenerator::NameIterCtx<
Container >::NameIter
```

## 19.41.2 Constructor & Destructor Documentation

### 19.41.2.1 NamelterCtx()

### 19.41.3 Member Data Documentation

## 19.41.3.1 container

```
template<typename Container >
const Container CodeGenerator::NameIterCtx< Container >::container
```

### 19.41.3.2 nameBegin

```
template<typename Container >
const NameIter CodeGenerator::NameIterCtx< Container >::nameBegin
```

#### 19.41.3.3 nameEnd

```
template<typename Container >
const NameIter CodeGenerator::NameIterCtx< Container >::nameEnd
```


The documentation for this struct was generated from the following file:

· codeGenUtils.h

# 19.42 pygenn.genn\_groups.NeuronGroup Class Reference

Class representing a group of neurons.

Inheritance diagram for pygenn.genn\_groups.NeuronGroup:



## **Public Member Functions**

def \_\_init\_\_ (self, name)

Init NeuronGroup.

def current\_spikes (self)

Current spikes from GeNN.

• def delay\_slots (self)

Maximum delay steps needed for this group.

- def size (self)
- def set\_neuron (self, model, param\_space, var\_space)

Set neuron, its parameters and initial variables.

def add\_to (self, model\_spec, num\_neurons)

Add this NeuronGroup to a model.

def add\_extra\_global\_param (self, param\_name, param\_values)

Add extra global parameter.

• def load (self, slm, scalar)

Loads neuron group.

• def reinitialise (self, slm, scalar)

Reinitialise neuron group.

#### **Public Attributes**

- neuron
- spikes

- spike\_count
- spike\_que\_ptr
- is\_spike\_source\_array
- type
- pop

## 19.42.1 Detailed Description

Class representing a group of neurons.

## 19.42.2 Constructor & Destructor Documentation

### Init NeuronGroup.

#### **Parameters**

name	string name of the group
------	--------------------------

## 19.42.3 Member Function Documentation

# 19.42.3.1 add\_extra\_global\_param()

Add extra global parameter.

## **Parameters**

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

# 19.42.3.2 add\_to()

Add this NeuronGroup to a model.

### **Parameters**

model_spec	pygenn.genn_model.GeNNModel to add to
num_neurons	int number of neurons

## 19.42.3.3 current\_spikes()

```
\label{lem:current_spikes} \mbox{ def pygenn.genn_groups.NeuronGroup.current_spikes (} \\ self \mbox{ )}
```

Current spikes from GeNN.

## 19.42.3.4 delay\_slots()

```
\label{lem:condition} \mbox{def pygenn.genn\_groups.NeuronGroup.delay\_slots (} \\ self \mbox{)}
```

Maximum delay steps needed for this group.

# 19.42.3.5 load()

```
def pygenn.genn_groups.NeuronGroup.load ( self, \\ slm, \\ scalar )
```

Loads neuron group.

## **Parameters**

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

## 19.42.3.6 reinitialise()

Reinitialise neuron group.

#### **Parameters**

5	slm	SharedLibraryModel instance for accessing variables
5	scalar	String specifying "scalar" type

# 19.42.3.7 set\_neuron()

```
def pygenn.genn_groups.NeuronGroup.set_neuron (
```

```
self,
model,
param_space,
var_space )
```

Set neuron, its parameters and initial variables.

#### **Parameters**

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

## 19.42.3.8 size()

```
\label{eq:condition} \mbox{def pygenn.genn\_groups.NeuronGroup.size (} \\ self \mbox{)}
```

### 19.42.4 Member Data Documentation

## 19.42.4.1 is\_spike\_source\_array

pygenn.genn\_groups.NeuronGroup.is\_spike\_source\_array

#### 19.42.4.2 neuron

pygenn.genn\_groups.NeuronGroup.neuron

# 19.42.4.3 pop

pygenn.genn\_groups.NeuronGroup.pop

## 19.42.4.4 spike\_count

pygenn.genn\_groups.NeuronGroup.spike\_count

# 19.42.4.5 spike\_que\_ptr

pygenn.genn\_groups.NeuronGroup.spike\_que\_ptr

## 19.42.4.6 spikes

 $\verb"pygenn.genn_groups.NeuronGroup.spikes"$ 

#### 19.42.4.7 type

pygenn.genn\_groups.NeuronGroup.type


The documentation for this class was generated from the following file:

· genn\_groups.py

# 19.43 NeuronGroup Class Reference

#include <neuronGroup.h>

Inheritance diagram for NeuronGroup:



#### **Public Member Functions**

- NeuronGroup (const NeuronGroup &)=delete
- NeuronGroup ()=delete
- void setSpikeLocation (VarLocation loc)

Set location of this neuron group's output spikes.

void setSpikeEventLocation (VarLocation loc)

Set location of this neuron group's output spike events.

void setSpikeTimeLocation (VarLocation loc)

Set location of this neuron group's output spike times.

void setVarLocation (const std::string &varName, VarLocation loc)

Set variable location of neuron model state variable.

• void setExtraGlobalParamLocation (const std::string &paramName, VarLocation loc)

Set location of neuron model extra global parameter.

- const std::string & getName () const
- unsigned int getNumNeurons () const

Gets number of neurons in group.

const NeuronModels::Base \* getNeuronModel () const

Gets the neuron model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- int getClusterHostID () const
- bool isSpikeTimeRequired () const
- bool isTrueSpikeRequired () const
- bool isSpikeEventRequired () const
- unsigned int getNumDelaySlots () const
- bool isDelayRequired () const
- bool isZeroCopyEnabled () const
- VarLocation getSpikeLocation () const

Get location of this neuron group's output spikes.

VarLocation getSpikeEventLocation () const

Get location of this neuron group's output spike events.

VarLocation getSpikeTimeLocation () const

Get location of this neuron group's output spike times.

VarLocation getVarLocation (const std::string &varName) const

Get location of neuron model state variable by name.

VarLocation getVarLocation (size t index) const

Get location of neuron model state variable by index.

• VarLocation getExtraGlobalParamLocation (const std::string &paramName) const

Get location of neuron model extra global parameter by name.

VarLocation getExtraGlobalParamLocation (size t index) const

Get location of neuron model extra global parameter by omdex.

bool isSimRNGRequired () const

Does this neuron group require an RNG to simulate?

• bool isInitRNGRequired () const

Does this neuron group require an RNG for it's init code?

bool hasOutputToHost (int targetHostID) const

Does this neuron group have outgoing connections specified host id?

#### **Protected Member Functions**

- NeuronGroup (const std::string &name, int numNeurons, const NeuronModels::Base \*neuronModel, const std::vector< double > &params, const std::vector< Models::VarInit > &varInitialisers, VarLocation default VarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)
- void checkNumDelaySlots (unsigned int requiredDelay)

Checks delay slots currently provided by the neuron group against a required delay and extends if required.

void updatePreVarQueues (const std::string &code)

Update which presynaptic variables require queues based on piece of code.

void updatePostVarQueues (const std::string &code)

Update which postsynaptic variables require queues based on piece of code.

- void addSpkEventCondition (const std::string &code, const std::string &supportCodeNamespace)
- void addlnSyn (SynapseGroupInternal \*synapseGroup)
- void addOutSyn (SynapseGroupInternal \*synapseGroup)
- void initDerivedParams (double dt)
- void mergeIncomingPSM (bool merge)

Merge incoming postsynaptic models.

void injectCurrent (CurrentSourceInternal \*source)

add input current source

const std::vector< SynapseGroupInternal \* > & getInSyn () const

Gets pointers to all synapse groups which provide input to this neuron group.

- const std::vector< std::pair< SynapseGroupInternal \*, std::vector< SynapseGroupInternal \* > > & get
   MergedInSyn () const
- const std::vector< SynapseGroupInternal \* > & getOutSyn () const

Gets pointers to all synapse groups emanating from this neuron group.

const std::vector< CurrentSourceInternal \* > & getCurrentSources () const

Gets pointers to all current sources which provide input to this neuron group.

- const std::vector< double > & getDerivedParams () const
- const std::set< std::pair< std::string, std::string > > & getSpikeEventCondition () const
- · bool isParamRequiredBySpikeEventCondition (const std::string &pnamefull) const

Do any of the spike event conditions tested by this neuron require specified parameter?

std::string getCurrentQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables this timestep.

• std::string getPrevQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables in previous timestep.

- bool isVarQueueRequired (const std::string &var) const
- bool isVarQueueRequired (size\_t index) const

#### 19.43.1 Constructor & Destructor Documentation

```
19.43.1.1 NeuronGroup() [1/3]
NeuronGroup::NeuronGroup (
             const NeuronGroup & ) [delete]
19.43.1.2 NeuronGroup() [2/3]
NeuronGroup::NeuronGroup ( ) [delete]
19.43.1.3 NeuronGroup() [3/3]
NeuronGroup::NeuronGroup (
             const std::string & name,
             int numNeurons,
             const NeuronModels::Base * neuronModel,
             const std::vector< double > & params,
             const std::vector< Models::VarInit > & varInitialisers,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             int hostID ) [inline], [protected]
19.43.2 Member Function Documentation
19.43.2.1 addlnSyn()
void NeuronGroup::addInSyn (
             SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.43.2.2 addOutSyn()
void NeuronGroup::addOutSyn (
             SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.43.2.3 addSpkEventCondition()
void NeuronGroup::addSpkEventCondition (
             const std::string & code,
             const std::string & supportCodeNamespace ) [protected]
19.43.2.4 checkNumDelaySlots()
void NeuronGroup::checkNumDelaySlots (
             unsigned int requiredDelay ) [protected]
```

Checks delay slots currently provided by the neuron group against a required delay and extends if required.

```
19.43.2.5 getClusterHostID()
int NeuronGroup::getClusterHostID ( ) const [inline]
19.43.2.6 getCurrentQueueOffset()
std::string NeuronGroup::getCurrentQueueOffset (
                               const std::string & devPrefix ) const [protected]
Get the expression to calculate the queue offset for accessing state of variables this timestep.
19.43.2.7 getCurrentSources()
const std::vector<CurrentSourceInternal*>& NeuronGroup::getCurrentSources ( ) const [inline],
 [protected]
Gets pointers to all current sources which provide input to this neuron group.
19.43.2.8 getDerivedParams()
const std::vector<double>& NeuronGroup::getDerivedParams ( ) const [inline], [protected]
19.43.2.9 getExtraGlobalParamLocation() [1/2]
{\tt VarLocation\ NeuronGroup::} {\tt getExtraGlobalParamLocation\ (}
                               const std::string & paramName ) const
Get location of neuron model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.43.2.10 getExtraGlobalParamLocation() [2/2]
VarLocation NeuronGroup::getExtraGlobalParamLocation (
                               size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.43.2.11 getInSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getInSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups which provide input to this neuron group.
19.43.2.12 getMergedInSyn()
\verb|const| std::vector < std::pair < Synapse Group Internal*, std::vector < Synapse Group Internal*> > > \& Const| Synapse Group Internal*> > > & Const| Synapse Group Internal*> > > & Const| Synapse Group Internal*> & Const| Synapse Gr
NeuronGroup::getMergedInSyn ( ) const [inline], [protected]
19.43.2.13 getName()
const std::string& NeuronGroup::getName ( ) const [inline]
```

```
19.43.2.14 getNeuronModel()
const NeuronModels::Base* NeuronGroup::getNeuronModel ( ) const [inline]
Gets the neuron model used by this group.
19.43.2.15 getNumDelaySlots()
unsigned int NeuronGroup::getNumDelaySlots ( ) const [inline]
19.43.2.16 getNumNeurons()
unsigned int NeuronGroup::getNumNeurons ( ) const [inline]
Gets number of neurons in group.
19.43.2.17 getOutSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getOutSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups emanating from this neuron group.
19.43.2.18 getParams()
const std::vector<double>& NeuronGroup::getParams ( ) const [inline]
19.43.2.19 getPrevQueueOffset()
{\tt std::string\ NeuronGroup::getPrevQueueOffset} (
             const std::string & devPrefix ) const [protected]
Get the expression to calculate the queue offset for accessing state of variables in previous timestep.
19.43.2.20 getSpikeEventCondition()
const [inline], [protected]
19.43.2.21 getSpikeEventLocation()
VarLocation NeuronGroup::getSpikeEventLocation ( ) const [inline]
Get location of this neuron group's output spike events.
19.43.2.22 getSpikeLocation()
VarLocation NeuronGroup::getSpikeLocation ( ) const [inline]
```

Get location of this neuron group's output spikes.

```
19.43.2.23 getSpikeTimeLocation()
VarLocation NeuronGroup::getSpikeTimeLocation ( ) const [inline]
Get location of this neuron group's output spike times.
19.43.2.24 getVarInitialisers()
const std::vector<Models::VarInit>& NeuronGroup::getVarInitialisers ( ) const [inline]
19.43.2.25 getVarLocation() [1/2]
VarLocation NeuronGroup::getVarLocation (
             const std::string & varName ) const
Get location of neuron model state variable by name.
19.43.2.26 getVarLocation() [2/2]
VarLocation NeuronGroup::getVarLocation (
              size_t index ) const [inline]
Get location of neuron model state variable by index.
19.43.2.27 hasOutputToHost()
bool NeuronGroup::hasOutputToHost (
              int targetHostID ) const
Does this neuron group have outgoing connections specified host id?
19.43.2.28 initDerivedParams()
void NeuronGroup::initDerivedParams (
              double dt ) [protected]
19.43.2.29 injectCurrent()
void NeuronGroup::injectCurrent (
              {\tt CurrentSourceInternal} \ * \ source \ ) \quad [{\tt protected}]
add input current source
19.43.2.30 isDelayRequired()
bool NeuronGroup::isDelayRequired ( ) const [inline]
19.43.2.31 isInitRNGRequired()
bool NeuronGroup::isInitRNGRequired ( ) const
```

Does this neuron group require an RNG for it's init code?

```
19.43.2.32 isParamRequiredBySpikeEventCondition()
bool NeuronGroup::isParamRequiredBySpikeEventCondition (
              const std::string & pnamefull ) const [protected]
Do any of the spike event conditions tested by this neuron require specified parameter?
19.43.2.33 isSimRNGRequired()
bool NeuronGroup::isSimRNGRequired ( ) const
Does this neuron group require an RNG to simulate?
19.43.2.34 isSpikeEventRequired()
bool NeuronGroup::isSpikeEventRequired ( ) const
19.43.2.35 isSpikeTimeRequired()
bool NeuronGroup::isSpikeTimeRequired ( ) const
19.43.2.36 isTrueSpikeRequired()
bool NeuronGroup::isTrueSpikeRequired ( ) const
19.43.2.37 isVarQueueRequired() [1/2]
bool NeuronGroup::isVarQueueRequired (
              const std::string & var ) const [protected]
19.43.2.38 isVarQueueRequired() [2/2]
bool NeuronGroup::isVarQueueRequired (
             size_t index ) const [inline], [protected]
19.43.2.39 isZeroCopyEnabled()
bool NeuronGroup::isZeroCopyEnabled ( ) const
19.43.2.40 mergeIncomingPSM()
void NeuronGroup::mergeIncomingPSM (
             bool merge ) [protected]
```

Merge incoming postsynaptic models.

#### 19.43.2.41 setExtraGlobalParamLocation()

Set location of neuron model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

#### 19.43.2.42 setSpikeEventLocation()

Set location of this neuron group's output spike events.

This is ignored for simulations on hardware with a single memory space

#### 19.43.2.43 setSpikeLocation()

Set location of this neuron group's output spikes.

This is ignored for simulations on hardware with a single memory space

### 19.43.2.44 setSpikeTimeLocation()

Set location of this neuron group's output spike times.

This is ignored for simulations on hardware with a single memory space

## 19.43.2.45 setVarLocation()

Set variable location of neuron model state variable.

This is ignored for simulations on hardware with a single memory space

#### 19.43.2.46 updatePostVarQueues()

Update which postsynaptic variables require queues based on piece of code.

#### 19.43.2.47 updatePreVarQueues()

Update which presynaptic variables require queues based on piece of code.


The documentation for this class was generated from the following files:

- neuronGroup.h
- neuronGroup.cc

# 19.44 NeuronGroupInternal Class Reference

#include <neuronGroupInternal.h>

Inheritance diagram for NeuronGroupInternal:



#### **Public Member Functions**

NeuronGroupInternal (const std::string &name, int numNeurons, const NeuronModels::Base \*neuronModel, const std::vector< double > &params, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)

**Additional Inherited Members** 

#### 19.44.1 Constructor & Destructor Documentation

## 19.44.1.1 NeuronGroupInternal()

The documentation for this class was generated from the following file:


· neuronGroupInternal.h

# 19.45 InitVarSnippet::Normal Class Reference

Initialises variable by sampling from the normal distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Normal:



# **Public Member Functions**

- DECLARE\_SNIPPET (InitVarSnippet::Normal, 2)
- SET\_CODE ("\$(value) = \$(mean) + (\$(gennrand\_normal) \* \$(sd));")
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

# **Additional Inherited Members**

# 19.45.1 Detailed Description

Initialises variable by sampling from the normal distribution.

This snippet takes 2 parameters:

- mean The mean
- sd The standard distribution

### 19.45.2 Member Function Documentation

# 19.45.2.1 DECLARE\_SNIPPET()

# 19.45.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Normal::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

# 19.45.2.3 SET\_CODE()

```
InitVarSnippet::Normal::SET_CODE ( )
```

The documentation for this class was generated from the following file:

· initVarSnippet.h

# 19.46 CodeGenerator::CodeStream::OB Struct Reference

# An open bracket marker.

```
#include <codeStream.h>
```

### **Public Member Functions**

OB (unsigned int level)

### **Public Attributes**

· const unsigned int Level

# 19.46.1 Detailed Description

An open bracket marker.

Write to code stream os using:

```
os << OB(16);
```

# 19.46.2 Constructor & Destructor Documentation

# 19.46.2.1 OB()

```
CodeGenerator::CodeStream::OB::OB (
          unsigned int level ) [inline]
```

### 19.46.3 Member Data Documentation

# 19.46.3.1 Level

```
const unsigned int CodeGenerator::CodeStream::OB::Level
```

The documentation for this struct was generated from the following file:


· codeStream.h

# 19.47 InitSparseConnectivitySnippet::OneToOne Class Reference

Initialises connectivity to a 'one-to-one' diagonal matrix.

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::OneToOne:



# **Public Member Functions**

- DECLARE\_SNIPPET (InitSparseConnectivitySnippet::OneToOne, 0)
- SET\_ROW\_BUILD\_CODE ("\$(addSynapse, \$(id\_pre));\ "\$(endRow);\")
- SET\_MAX\_ROW\_LENGTH (1)
- SET\_MAX\_COL\_LENGTH (1)

**Additional Inherited Members** 

# 19.47.1 Detailed Description

Initialises connectivity to a 'one-to-one' diagonal matrix.

### 19.47.2 Member Function Documentation

# 19.47.2.1 DECLARE\_SNIPPET()

# 19.47.2.2 SET\_MAX\_COL\_LENGTH()

# 19.47.2.3 SET\_MAX\_ROW\_LENGTH()

# 19.47.2.4 SET\_ROW\_BUILD\_CODE()

The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

# 19.48 Snippet::Base::ParamVal Struct Reference

```
#include <snippet.h>
```

# **Public Attributes**

- std::string name
- std::string type
- double value

# 19.48.1 Member Data Documentation

# 19.48.1.1 name

```
std::string Snippet::Base::ParamVal::name
```

# 19.48.1.2 type

std::string Snippet::Base::ParamVal::type

### 19.48.1.3 value

double Snippet::Base::ParamVal::value

The documentation for this struct was generated from the following file:


· snippet.h

# 19.49 WeightUpdateModels::PiecewiseSTDP Class Reference

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::PiecewiseSTDP:



# **Public Member Functions**

- DECLARE\_WEIGHT\_UPDATE\_MODEL (PiecewiseSTDP, 10, 2, 0, 0)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

· virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

· virtual std::string getLearnPostCode () const override

Gets code to include in the learnSynapsesPost kernel/function.

- virtual DerivedParamVec getDerivedParams () const override
- virtual bool isPreSpikeTimeRequired () const override

Whether presynaptic spike times are needed or not.


• virtual bool isPostSpikeTimeRequired () const override


Whether postsynaptic spike times are needed or not.


### **Additional Inherited Members**

### 19.49.1 Detailed Description

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.







The STDP curve is applied to the raw synaptic conductance gRaw, which is then filtered through the sugmoidal filter displayed above to obtain the value of g.

### Note

The STDP curve implies that unpaired pre- and post-synaptic spikes incur a negative increment in gRaw (and hence in g).

The time of the last spike in each neuron, "sTXX", where XX is the name of a neuron population is (somewhat arbitrarily) initialised to -10.0 ms. If neurons never spike, these spike times are used.

It is the raw synaptic conductance gRaw that is subject to the STDP rule. The resulting synaptic conductance is a sigmoid filter of gRaw. This implies that g is initialised but not gRaw, the synapse will revert to the value that corresponds to gRaw.

An example how to use this synapse correctly is given in map\_classol.cc (MBody1 userproject):

```
for (int i= 0; i < model.neuronN[1]*model.neuronN[3]; i++) {
    if (gKCDN[i] < 2.0*SCALAR_MIN) {
        cnt++;
        fprintf(stdout, "Too low conductance value %e detected and set to 2*SCALAR_MIN= %e, at index %d
    \n", gKCDN[i], 2*SCALAR_MIN, i);
        gKCDN[i] = 2.0*SCALAR_MIN; //to avoid log(0)/0 below
    }
    scalar tmp = gKCDN[i] / myKCDN_p[5]*2.0;
    gRawKCDN[i] = 0.5 * log( tmp / (2.0 - tmp)) /myKCDN_p[7] + myKCDN_p[6];
}
cerr << "Total number of low value corrections: " << cnt << endl;</pre>
```

# Note

One cannot set values of g fully to 0, as this leads to gRaw= -infinity and this is not support. I.e., 'g' needs to be some nominal value > 0 (but can be extremely small so that it acts like it's 0).

The model has 2 variables:

• g: conductance of scalar type

gRaw: raw conductance of scalar type

Parameters are (compare to the figure above):

- tLrn: Time scale of learning changes
- · tChng: Width of learning window
- tDecay: Time scale of synaptic strength decay
- tPunish10: Time window of suppression in response to 1/0
- tPunish01: Time window of suppression in response to 0/1
- gMax: Maximal conductance achievable
- gMid: Midpoint of sigmoid g filter curve
- gSlope: Slope of sigmoid g filter curve
- tauShift: Shift of learning curve
- gSyn0: Value of syn conductance g decays to

### 19.49.2 Member Function Documentation

# 19.49.2.1 DECLARE\_WEIGHT\_UPDATE\_MODEL()

# 19.49.2.2 getDerivedParams()

```
virtual DerivedParamVec WeightUpdateModels::PiecewiseSTDP::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

# 19.49.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::PiecewiseSTDP::getLearnPostCode ( ) const [inline],
[override], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented from WeightUpdateModels::Base.

# 19.49.2.4 getParamNames()

virtual StringVec WeightUpdateModels::PiecewiseSTDP::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.49.2.5 getSimCode()

virtual std::string WeightUpdateModels::PiecewiseSTDP::getSimCode ( ) const [inline], [override],
[virtual]

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

### 19.49.2.6 getVars()

```
virtual VarVec WeightUpdateModels::PiecewiseSTDP::getVars ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

# 19.49.2.7 isPostSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPostSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether postsynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

### 19.49.2.8 isPreSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPreSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether presynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

The documentation for this class was generated from the following file:


· weightUpdateModels.h

# 19.50 NeuronModels::Poisson Class Reference

# Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Poisson:



# **Public Types**

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

### **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual VarVec getExtraGlobalParams () const override

# **Static Public Member Functions**

static const NeuronModels::Poisson \* getInstance ()

### **Additional Inherited Members**

# 19.50.1 Detailed Description

# Poisson neurons.

Poisson neurons have constant membrane potential (Vrest) unless they are activated randomly to the Vspike value if (t-SpikeTime) > trefract.

### It has 2 variables:

- V Membrane potential (mV)
- SpikeTime Time at which the neuron spiked for the last time (ms)

# and 4 parameters:

- trefract Refractory period (ms)
- tspike duration of spike (ms)

- Vspike Membrane potential at spike (mV)
- Vrest Membrane potential at rest (mV)

### Note

The initial values array for the Poisson type needs two entries for V, and SpikeTime and the parameter array needs four entries for therate, trefract, Vspike and Vrest, in that order.

This model uses a linear approximation for the probability of firing a spike in a given time step of size DT, i.e. the probability of firing is  $\lambda$  times DT:  $p = \lambda \Delta t$ . This approximation is usually very good, especially for typical, quite small time steps and moderate firing rates. However, it is worth noting that the approximation becomes poor for very high firing rates and large time steps.

### 19.50.2 Member Typedef Documentation

# typedef Snippet::ValueBase< 4 > NeuronModels::Poisson::ParamValues

### 19.50.2.2 PostVarValues

19.50.2.1 ParamValues

 ${\tt typedef\ Models::} VarInitContainerBase < 0 > \ NeuronModels::Poisson::PostVarValues$ 

# 19.50.2.3 PreVarValues

 ${\tt typedef\ Models::VarInitContainerBase} < 0 {\gt NeuronModels::Poisson::PreVarValues}$ 

### 19.50.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::Poisson::VarValues

### 19.50.3 Member Function Documentation

# 19.50.3.1 getExtraGlobalParams()

```
virtual VarVec NeuronModels::Poisson::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

# 19.50.3.2 getInstance()

```
static const NeuronModels::Poisson* NeuronModels::Poisson::getInstance ( ) [inline], [static]
```

### 19.50.3.3 getParamNames()

virtual StringVec NeuronModels::Poisson::getParamNames ( ) const [inline], [override], [virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.50.3.4 getSimCode()

```
virtual std::string NeuronModels::Poisson::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

# 19.50.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::Poisson::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

### 19.50.3.6 getVars()

```
virtual VarVec NeuronModels::Poisson::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


• neuronModels.h

# 19.51 NeuronModels::PoissonNew Class Reference

# Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::PoissonNew:



# **Public Types**

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 1 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

### **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

• virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- virtual DerivedParamVec getDerivedParams () const override
- SET\_NEEDS\_AUTO\_REFRACTORY (false)

# **Static Public Member Functions**

• static const NeuronModels::PoissonNew \* getInstance ()

### **Additional Inherited Members**

# 19.51.1 Detailed Description

# Poisson neurons.

# It has 1 state variable:

-  $\label{timeStepToSpike} \mbox{-} \mbox{Number of timesteps to next spike}$ 

# and 1 parameter:

• rate - Mean firing rate (Hz)

### Note

Internally this samples from the exponential distribution using the C++ 11 < random > library on the CPU and by transforming the uniform distribution, generated using cuRAND, with a natural log on the GPU.

# 19.51.2 Member Typedef Documentation

### 19.51.2.1 ParamValues

typedef Snippet::ValueBase< 1 > NeuronModels::PoissonNew::ParamValues

### 19.51.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PostVarValues

### 19.51.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PreVarValues

# 19.51.2.4 VarValues

typedef Models::VarInitContainerBase< 1 > NeuronModels::PoissonNew::VarValues

### 19.51.3 Member Function Documentation

# 19.51.3.1 getDerivedParams()

virtual DerivedParamVec NeuronModels::PoissonNew::getDerivedParams ( ) const [inline], [override],
[virtual]

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

# 19.51.3.2 getInstance()

static const NeuronModels::PoissonNew\* NeuronModels::PoissonNew::getInstance ( ) [inline],
[static]

# 19.51.3.3 getParamNames()

virtual StringVec NeuronModels::PoissonNew::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

# 19.51.3.4 getSimCode()

virtual std::string NeuronModels::PoissonNew::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

### 19.51.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::PoissonNew::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

# 19.51.3.6 getVars()

```
virtual VarVec NeuronModels::PoissonNew::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

### 19.51.3.7 SET\_NEEDS\_AUTO\_REFRACTORY()

The documentation for this class was generated from the following file:


neuronModels.h

# 19.52 CodeGenerator::CUDA::Preferences Struct Reference

# Preferences for CUDA backend.

```
#include <backend.h>
```

Inheritance diagram for CodeGenerator::CUDA::Preferences:



### **Public Member Functions**

· Preferences ()

### **Public Attributes**

• bool showPtxInfo = false

Should PTX assembler information be displayed for each CUDA kernel during compilation.

• DeviceSelect deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

• unsigned int manualDeviceID = 0

If device select method is set to DeviceSelect::MANUAL, id of device to use.

• BlockSizeSelect blockSizeSelectMethod = BlockSizeSelect::OCCUPANCY

How to select CUDA blocksize.

· KernelBlockSize manualBlockSizes

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

• std::string userNvccFlags = ""

NVCC compiler options for all GPU code.

### 19.52.1 Detailed Description

Preferences for CUDA backend.

# 19.52.2 Constructor & Destructor Documentation

# 19.52.2.1 **Preferences()**

CodeGenerator::CUDA::Preferences::Preferences ( ) [inline]

### 19.52.3 Member Data Documentation

### 19.52.3.1 blockSizeSelectMethod

BlockSizeSelect CodeGenerator::CUDA::Preferences::blockSizeSelectMethod = BlockSizeSelect::OC← CUPANCY

How to select CUDA blocksize.

### 19.52.3.2 deviceSelectMethod

DeviceSelect CodeGenerator::CUDA::Preferences::deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

### 19.52.3.3 manualBlockSizes

KernelBlockSize CodeGenerator::CUDA::Preferences::manualBlockSizes

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

# 19.52.3.4 manualDeviceID

```
unsigned int CodeGenerator::CUDA::Preferences::manualDeviceID = 0
```

If device select method is set to DeviceSelect::MANUAL, id of device to use.

# 19.52.3.5 showPtxInfo

bool CodeGenerator::CUDA::Preferences::showPtxInfo = false

Should PTX assembler information be displayed for each CUDA kernel during compilation.

### 19.52.3.6 userNvccFlags

std::string CodeGenerator::CUDA::Preferences::userNvccFlags = ""

NVCC compiler options for all GPU code.


The documentation for this struct was generated from the following file:

· cuda/backend.h

# 19.53 CodeGenerator::SingleThreadedCPU::Preferences Struct Reference

#include <backend.h>

Inheritance diagram for CodeGenerator::SingleThreadedCPU::Preferences:



# **Additional Inherited Members**

The documentation for this struct was generated from the following file:


single\_threaded\_cpu/backend.h

### 19.54 CodeGenerator::PreferencesBase Struct Reference

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

#include <backendBase.h>

Inheritance diagram for CodeGenerator::PreferencesBase:



# **Public Attributes**

bool optimizeCode = false

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

bool debugCode = false

Generate code with debug symbols.

• std::string userCxxFlagsGNU = ""

C++ compiler options to be used for building all host side code (used for unix based platforms)

std::string userNvccFlagsGNU = ""

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

• plog::Severity logLevel = plog::info

Logging level to use for code generation.

# 19.54.1 Detailed Description

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

# 19.54.2 Member Data Documentation

# 19.54.2.1 debugCode

bool CodeGenerator::PreferencesBase::debugCode = false

Generate code with debug symbols.

### 19.54.2.2 logLevel

plog::Severity CodeGenerator::PreferencesBase::logLevel = plog::info

Logging level to use for code generation.

# 19.54.2.3 optimizeCode

bool CodeGenerator::PreferencesBase::optimizeCode = false

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

# 19.54.2.4 userCxxFlagsGNU

```
std::string CodeGenerator::PreferencesBase::userCxxFlagsGNU = ""
```

C++ compiler options to be used for building all host side code (used for unix based platforms)

# 19.54.2.5 userNvccFlagsGNU

```
std::string CodeGenerator::PreferencesBase::userNvccFlagsGNU = ""
```

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

The documentation for this struct was generated from the following file:


# · backendBase.h

# 19.55 NeuronModels::RulkovMap Class Reference

Rulkov Map neuron.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::RulkovMap:



# **Public Types**

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

### **Public Member Functions**

virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual DerivedParamVec getDerivedParams () const override

# Static Public Member Functions

static const NeuronModels::RulkovMap \* getInstance ()

# **Additional Inherited Members**

### 19.55.1 Detailed Description

Rulkov Map neuron.

The RulkovMap type is a map based neuron model based on [5] but in the 1-dimensional map form used in [4]:

$$V(t + \Delta t) = \begin{cases} V_{\text{spike}} \left( \frac{\alpha V_{\text{spike}}}{V_{\text{spike}} - V(t)\beta I_{\text{syn}}} + y \right) & V(t) \leq 0 \\ V_{\text{spike}} \left( \alpha + y \right) & V(t) \leq V_{\text{spike}} \left( \alpha + y \right) & \& V(t - \Delta t) \leq 0 \\ -V_{\text{spike}} & \text{otherwise} \end{cases}$$

Note

The RulkovMap type only works as intended for the single time step size of DT= 0.5.

The RulkovMap type has 2 variables:

• V - the membrane potential

• preV - the membrane potential at the previous time step

# and it has 4 parameters:

- $\ensuremath{\texttt{Vspike}}$  determines the amplitude of spikes, typically -60mV
- alpha determines the shape of the iteration function, typically  $\alpha$ = 3
- y "shift / excitation" parameter, also determines the iteration function, originally, y= -2.468
- beta roughly speaking equivalent to the input resistance, i.e. it regulates the scale of the input into the neuron, typically  $\beta$ = 2.64 M $\Omega$ .

# Note

The initial values array for the RulkovMap type needs two entries for V and Vpre and the parameter array needs four entries for Vspike, alpha, y and beta, in that order.

# 19.55.2 Member Typedef Documentation

### 19.55.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::RulkovMap::ParamValues

# 19.55.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::RulkovMap::PostVarValues

# 19.55.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::RulkovMap::PreVarValues

# 19.55.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::RulkovMap::VarValues

# 19.55.3 Member Function Documentation

# 19.55.3.1 getDerivedParams()

virtual DerivedParamVec NeuronModels::RulkovMap::getDerivedParams ( ) const [inline], [override],
[virtual]

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

# 19.55.3.2 getInstance()

static const NeuronModels::RulkovMap\* NeuronModels::RulkovMap::getInstance ( ) [inline], [static]

# 19.55.3.3 getParamNames()

virtual StringVec NeuronModels::RulkovMap::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.55.3.4 getSimCode()

virtual std::string NeuronModels::RulkovMap::getSimCode ( ) const [inline], [override], [virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

# 19.55.3.5 getThresholdConditionCode()

virtual std::string NeuronModels::RulkovMap::getThresholdConditionCode ( ) const [inline],
[override], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

# 19.55.3.6 getVars()

```
virtual VarVec NeuronModels::RulkovMap::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:

· neuronModels.h

# 19.56 CodeGenerator::CodeStream::Scope Class Reference

```
#include <codeStream.h>
```

# **Public Member Functions**

- Scope (CodeStream &codeStream)
- ~Scope ()

### 19.56.1 Constructor & Destructor Documentation

# 

The documentation for this class was generated from the following files:


- · codeStream.h
- · codeStream.cc

# 19.57 NeuronModels::SpikeSource Class Reference

Empty neuron which allows setting spikes from external sources.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::SpikeSource:



# **Public Types**

- typedef Snippet::ValueBase< 0 > ParamValues
- $\bullet \ \ typedef \ Models:: VarInitContainer Base < 0 > VarValues \\$
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

# **Public Member Functions**

- virtual std::string getThresholdConditionCode () const override
   Gets code which defines the condition for a true spike in the described neuron model.
- SET\_NEEDS\_AUTO\_REFRACTORY (false)

### **Static Public Member Functions**

• static const NeuronModels::SpikeSource \* getInstance ()

### **Additional Inherited Members**

# 19.57.1 Detailed Description

Empty neuron which allows setting spikes from external sources.

This model does not contain any update code and can be used to implement the equivalent of a SpikeGenerator Group in Brian or a SpikeSourceArray in PyNN.

### 19.57.2 Member Typedef Documentation

# 19.57.2.1 ParamValues

```
typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSource::ParamValues
```

# 19.57.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PostVarValues
```

### 19.57.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PreVarValues
```

# 19.57.2.4 VarValues

```
typedef Models::VarInitContainerBase< 0 > NeuronModels::SpikeSource::VarValues
```

# 19.57.3 Member Function Documentation

### 19.57.3.1 getInstance()

```
static const NeuronModels::SpikeSource* NeuronModels::SpikeSource::getInstance ( ) [inline],
[static]
```

# 19.57.3.2 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSource::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

# 19.57.3.3 SET\_NEEDS\_AUTO\_REFRACTORY()

The documentation for this class was generated from the following file:


· neuronModels.h

# 19.58 NeuronModels::SpikeSourceArray Class Reference

# Spike source array.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::SpikeSourceArray:



# **Public Types**

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

# **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual std::string getResetCode () const override

Gets code that defines the reset action taken after a spike occurred. This can be empty.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- virtual VarVec getExtraGlobalParams () const override
- SET\_NEEDS\_AUTO\_REFRACTORY (false)

### **Static Public Member Functions**

static const NeuronModels::SpikeSourceArray \* getInstance ()

# Additional Inherited Members

19.58.1 Detailed Description

# Spike source array.

A neuron which reads spike times from a global spikes array It has 2 variables:

- startSpike Index of the next spike in the global array
- endSpike Index of the spike next to the last in the globel array

# and 1 global parameter:

• spikeTimes - Array with all spike times

# 19.58.2 Member Typedef Documentation

### 19.58.2.1 ParamValues

```
typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSourceArray::ParamValues
```

### 19.58.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PostVarValues
```

### 19.58.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PreVarValues
```

### 19.58.2.4 VarValues

```
{\tt typedef\ Models::} {\tt VarInitContainerBase} < 2 > {\tt NeuronModels::} {\tt SpikeSourceArray::} {\tt VarValues} \\
```

### 19.58.3 Member Function Documentation

# 19.58.3.1 getExtraGlobalParams()

```
virtual VarVec NeuronModels::SpikeSourceArray::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

### 19.58.3.2 getInstance()

```
static const NeuronModels::SpikeSourceArray* NeuronModels::SpikeSourceArray::getInstance ( )
[inline], [static]
```

# 19.58.3.3 getResetCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getResetCode ( ) const [inline], [override],
[virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

# 19.58.3.4 getSimCode()

virtual std::string NeuronModels::SpikeSourceArray::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

### 19.58.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

# 19.58.3.6 getVars()

```
virtual VarVec NeuronModels::SpikeSourceArray::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

# 19.58.3.7 SET\_NEEDS\_AUTO\_REFRACTORY()

The documentation for this class was generated from the following file:


• neuronModels.h

# 19.59 WeightUpdateModels::StaticGraded Class Reference

Graded-potential, static synapse.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::StaticGraded:



# **Public Member Functions**

- DECLARE\_WEIGHT\_UPDATE\_MODEL (StaticGraded, 2, 1, 0, 0)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual std::string getEventCode () const override

Gets code run when events (all the instances where event threshold condition is met) are received.

virtual std::string getEventThresholdConditionCode () const override

Gets codes to test for events.

# **Additional Inherited Members**

# 19.59.1 Detailed Description

Graded-potential, static synapse.

In a graded synapse, the conductance is updated gradually with the rule:

$$gSyn = g * tanh((V - E_{pre})/V_{slope})$$

whenever the membrane potential V is larger than the threshold  $E_{\it pre}$ . The model has 1 variable:

• q: conductance of scalar type

The parameters are:

- Epre: Presynaptic threshold potential
- Vslope: Activation slope of graded release

# event code is:

```
\label{eq:condition} $$ (addToInSyn, $(g)* tanh(($(V_pre)-($(Epre)))*DT*2/$(Vslope))); $$
```

event threshold condition code is:

```
$(V_pre) > $(Epre)
```

### Note

The pre-synaptic variables are referenced with the suffix \_pre in synapse related code such as an the event threshold test. Users can also access post-synaptic neuron variables using the suffix \_post.

# 19.59.2 Member Function Documentation

# 19.59.2.1 DECLARE\_WEIGHT\_UPDATE\_MODEL()

### 19.59.2.2 getEventCode()

virtual std::string WeightUpdateModels::StaticGraded::getEventCode ( ) const [inline], [override],
[virtual]

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented from WeightUpdateModels::Base.

### 19.59.2.3 getEventThresholdConditionCode()

virtual std::string WeightUpdateModels::StaticGraded::getEventThresholdConditionCode ( ) const
[inline], [override], [virtual]

Gets codes to test for events.

Reimplemented from WeightUpdateModels::Base.

### 19.59.2.4 getParamNames()

virtual StringVec WeightUpdateModels::StaticGraded::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.59.2.5 getVars()

virtual VarVec WeightUpdateModels::StaticGraded::getVars ( ) const [inline], [override],
[virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


· weightUpdateModels.h

# 19.60 WeightUpdateModels::StaticPulse Class Reference

Pulse-coupled, static synapse.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::StaticPulse:



**Public Member Functions** 

- DECLARE\_WEIGHT\_UPDATE\_MODEL (StaticPulse, 0, 1, 0, 0)
- · virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

**Additional Inherited Members** 

19.60.1 Detailed Description

Pulse-coupled, static synapse.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 1 variable:

• g - conductance of scalar type and no other parameters.

sim code is:

```
"$(addToInSyn, $(g)); n"
```

# 19.60.2 Member Function Documentation

### 19.60.2.1 DECLARE WEIGHT UPDATE MODEL()

# 19.60.2.2 getSimCode()

```
virtual std::string WeightUpdateModels::StaticPulse::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

```
19.60.2.3 getVars()
```

```
virtual VarVec WeightUpdateModels::StaticPulse::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


• weightUpdateModels.h

# 19.61 WeightUpdateModels::StaticPulseDendriticDelay Class Reference

Pulse-coupled, static synapse with heterogenous dendritic delays.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::StaticPulseDendriticDelay:



# **Public Types**

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

# **Public Member Functions**

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

# **Static Public Member Functions**

static const StaticPulseDendriticDelay \* getInstance ()

# **Additional Inherited Members**

# 19.61.1 Detailed Description

Pulse-coupled, static synapse with heterogenous dendritic delays.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 2 variables:

- g conductance of scalar type
- · d dendritic delay in timesteps and no other parameters.

# sim code is:

" \$(addToInSynDelay, \$(g), \$(d));\n\

### 19.61.2 Member Typedef Documentation

# 19.61.2.1 ParamValues

typedef Snippet::ValueBase< 0 > WeightUpdateModels::StaticPulseDendriticDelay::ParamValues

### 19.61.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> WeightUpdateModels::StaticPulseDendriticDelay::Post←
VarValues

### 19.61.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> WeightUpdateModels::StaticPulseDendriticDelay::Pre↔ VarValues

### 19.61.2.4 VarValues

 $\label{typedef_Models::VarInitContainerBase< 2 > WeightUpdateModels::StaticPulseDendriticDelay::Var \leftarrow Values$ 

### 19.61.3 Member Function Documentation

# 19.61.3.1 getInstance()

 $static \ const \ StaticPulseDendriticDelay* \ WeightUpdateModels::StaticPulseDendriticDelay::get \\ \leftarrow Instance \ (\ ) \ \ [inline], \ [static]$ 

# 19.61.3.2 getSimCode()

virtual std::string WeightUpdateModels::StaticPulseDendriticDelay::getSimCode ( ) const [inline],
[override], [virtual]

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

# 19.61.3.3 getVars()

virtual VarVec WeightUpdateModels::StaticPulseDendriticDelay::getVars ( ) const [inline],
[override], [virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


weightUpdateModels.h

# 19.62 CodeGenerator::StructNameConstiter < Baselter > Class Template Reference

Custom iterator for iterating through the containers of structs with 'name' members.

```
#include <codeGenUtils.h>
```

Inheritance diagram for CodeGenerator::StructNameConstIter< BaseIter >:



# **Public Member Functions**

- StructNameConstIter ()
- StructNameConstIter (BaseIter iter)
- const std::string \* operator-> () const
- · const std::string & operator\* () const

# 19.62.1 Detailed Description

```
template < typename Baselter > class CodeGenerator::StructNameConstiter < Baselter >
```

Custom iterator for iterating through the containers of structs with 'name' members.

# 19.62.2 Constructor & Destructor Documentation

```
19.62.2.1 StructNameConstiter() [1/2]
```

```
template<typename BaseIter >
CodeGenerator::StructNameConstIter< BaseIter >::StructNameConstIter ( ) [inline]
```

# 19.62.2.2 StructNameConstIter() [2/2]

### 19.62.3 Member Function Documentation

```
19.62.3.1 operator*()
```

```
template<typename BaseIter >
const std::string& CodeGenerator::StructNameConstIter< BaseIter >::operator* ( ) const [inline]
```

```
19.62.3.2 operator->()
template<typename BaseIter >
const std::string* CodeGenerator::StructNameConstIter< BaseIter >::operator-> ( ) const [inline]
```

The documentation for this class was generated from the following file:

codeGenUtils.h

### 19.63 CodeGenerator::Substitutions Class Reference

```
#include <substitutions.h>
```

### **Public Member Functions**

- Substitutions (const Substitutions \*parent=nullptr)
- Substitutions (const std::vector< FunctionTemplate > &functions, const std::string &ftype)
- void addVarSubstitution (const std::string &source, const std::string &destionation, bool allowOverride=false)
- void addFuncSubstitution (const std::string &source, unsigned int numArguments, const std::string &func
   — Template, bool allowOverride=false)
- bool hasVarSubstitution (const std::string &source) const
- const std::string & getVarSubstitution (const std::string &source) const
- · void apply (std::string &code) const
- const std::string operator[] (const std::string &source) const

### 19.63.1 Constructor & Destructor Documentation

### 19.63.2.1 addFuncSubstitution()

# 19.63.2.2 addVarSubstitution()

```
void CodeGenerator::Substitutions::addVarSubstitution (
             const std::string & source,
             const std::string & destionation,
             bool allowOverride = false ) [inline]
19.63.2.3 apply()
void CodeGenerator::Substitutions::apply (
             std::string & code ) const [inline]
19.63.2.4 getVarSubstitution()
const std::string& CodeGenerator::Substitutions::getVarSubstitution (
             const std::string & source ) const [inline]
19.63.2.5 hasVarSubstitution()
bool CodeGenerator::Substitutions::hasVarSubstitution (
             const std::string & source ) const [inline]
19.63.2.6 operator[]()
const std::string CodeGenerator::Substitutions::operator[] (
             const std::string & source ) const [inline]
```


The documentation for this class was generated from the following file:

• substitutions.h

# 19.64 pygenn.genn\_groups.SynapseGroup Class Reference

Class representing synaptic connection between two groups of neurons.

Inheritance diagram for pygenn.genn\_groups.SynapseGroup:



# **Public Member Functions**

- def \_\_init\_\_ (self, name)
   Init SynapseGroup.
- def num\_synapses (self)

Number of synapses in group.

def weight\_update\_var\_size (self)

Size of each weight update variable.

- def max\_row\_length (self)
- def set\_psm\_var (self, var\_name, values)

Set values for a postsynaptic model variable.

• def set pre var (self, var name, values)

Set values for a presynaptic variable.

def set\_post\_var (self, var\_name, values)

Set values for a postsynaptic variable.

def set\_weight\_update (self, model, param\_space, var\_space, pre\_var\_space, post\_var\_space)

Set weight update model, its parameters and initial variables.

def set\_post\_syn (self, model, param\_space, var\_space)

Set postsynaptic model, its parameters and initial variables.

- def get var values (self, var name)
- · def is\_connectivity\_init\_required (self)
- def matrix\_type (self)

Type of the projection matrix.

- def matrix\_type (self, matrix\_type)
- def is\_ragged (self)

Tests whether synaptic connectivity uses Ragged format.

def is bitmask (self)

Tests whether synaptic connectivity uses Bitmask format.

def is dense (self)

Tests whether synaptic connectivity uses dense format.

def has\_individual\_synapse\_vars (self)

Tests whether synaptic connectivity has individual weights.

def has\_individual\_postsynaptic\_vars (self)

Tests whether synaptic connectivity has individual postsynaptic model variables.

def set\_sparse\_connections (self, pre\_indices, post\_indices)

Set ragged format connections between two groups of neurons.

• def get\_sparse\_pre\_inds (self)

Get presynaptic indices of synapse group connections.

def get\_sparse\_post\_inds (self)

Get postsynaptic indices of synapse group connections.

def set\_connected\_populations (self, source, target)

Set two groups of neurons connected by this SynapseGroup.

def add\_to (self, model\_spec, delay\_steps)

Add this SynapseGroup to the a model.

def add\_extra\_global\_param (self, param\_name, param\_values)

Add extra global parameter.

- def load (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise synapse group.

# **Public Attributes**

- · connections\_set
- w\_update
- postsyn
- src
- trg
- psm\_vars
- pre\_vars
- post\_vars
- · connectivity\_initialiser
- synapse\_order
- ind
- row\_lengths
- pop

# 19.64.1 Detailed Description

Class representing synaptic connection between two groups of neurons.

# 19.64.2 Constructor & Destructor Documentation

Init SynapseGroup.

# **Parameters**

name string name of the group
-------------------------------

# 19.64.3 Member Function Documentation

# 19.64.3.1 add\_extra\_global\_param()

```
def pygenn.genn_groups.SynapseGroup.add_extra_global_param ( self, \\ param_name, \\ param_values )
```

# Add extra global parameter.

# Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

# 19.64.3.2 add\_to()

Add this SynapseGroup to the a model.

### **Parameters**

model_spec	pygenn.genn_model.GeNNModel to add to
delay_steps	number of axonal delay timesteps to simulate for this synapse group

# 19.64.3.3 get\_sparse\_post\_inds()

```
\label{lem:constant} \mbox{def pygenn.genn\_groups.SynapseGroup.get\_sparse\_post\_inds (} \\ self )
```

Get postsynaptic indices of synapse group connections.

### Returns

ndarrays of postsynaptic indices

### 19.64.3.4 get\_sparse\_pre\_inds()

```
def pygenn.genn_groups.SynapseGroup.get_sparse_pre_inds ( self )
```

Get presynaptic indices of synapse group connections.

# Returns

ndarray of presynaptic indices

# 19.64.3.5 get\_var\_values()

```
def pygenn.genn_groups.SynapseGroup.get_var_values ( self, \\ var_name \ )
```

# 19.64.3.6 has\_individual\_postsynaptic\_vars()

```
\label{lem:continuous} $\operatorname{def pygenn.genn\_groups.SynapseGroup.has\_individual\_postsynaptic\_vars} \ ( \\ \operatorname{\mathit{self}} \ )
```

Tests whether synaptic connectivity has individual postsynaptic model variables.

```
19.64.3.7 has_individual_synapse_vars()
def pygenn.genn_groups.SynapseGroup.has_individual_synapse_vars (
               self )
Tests whether synaptic connectivity has individual weights.
19.64.3.8 is_bitmask()
def pygenn.genn_groups.SynapseGroup.is_bitmask (
               self )
Tests whether synaptic connectivity uses Bitmask format.
19.64.3.9 is_connectivity_init_required()
def pygenn.genn_groups.SynapseGroup.is_connectivity_init_required (
               self )
19.64.3.10 is_dense()
def pygenn.genn_groups.SynapseGroup.is_dense (
               self )
Tests whether synaptic connectivity uses dense format.
19.64.3.11 is_ragged()
def pygenn.genn_groups.SynapseGroup.is_ragged (
               self )
Tests whether synaptic connectivity uses Ragged format.
19.64.3.12 load()
def pygenn.genn_groups.SynapseGroup.load (
               self,
               slm,
               scalar )
19.64.3.13 matrix_type() [1/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
               self )
Type of the projection matrix.
19.64.3.14 matrix_type() [2/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
               self,
```

matrix\_type )

### 19.64.3.15 max\_row\_length()

Number of synapses in group.

self )

### 19.64.3.17 reinitialise()

```
def pygenn.genn_groups.SynapseGroup.reinitialise ( self, \\ slm, \\ scalar )
```

Reinitialise synapse group.

#### **Parameters**

slm	SharedLibraryModel instance for acccessing variables
scalar	String specifying "scalar" type

## 19.64.3.18 set\_connected\_populations()

```
def pygenn.genn_groups.SynapseGroup.set_connected_populations ( self, \\ source, \\ target \ )
```

Set two groups of neurons connected by this SynapseGroup.

### **Parameters**

source	string name of the presynaptic neuron group
target	string name of the postsynaptic neuron group

## 19.64.3.19 set\_post\_syn()

Set postsynaptic model, its parameters and initial variables.

## **Parameters**

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

# 19.64.3.20 set\_post\_var()

```
def pygenn.genn_groups.SynapseGroup.set_post_var ( self, \\ var_name, \\ values )
```

Set values for a postsynaptic variable.

## **Parameters**

var_name	string with the name of the presynaptic variable
values	iterable or a single value

## 19.64.3.21 set\_pre\_var()

Set values for a presynaptic variable.

### **Parameters**

var_name	string with the name of the presynaptic variable
values	iterable or a single value

# 19.64.3.22 set\_psm\_var()

Set values for a postsynaptic model variable.

## **Parameters**

var_name	string with the name of the postsynaptic model variable
values	iterable or a single value

### 19.64.3.23 set\_sparse\_connections()

Set ragged format connections between two groups of neurons.

#### **Parameters**

pre_indices	ndarray of presynaptic indices
post_indices	ndarray of postsynaptic indices

## 19.64.3.24 set\_weight\_update()

Set weight update model, its parameters and initial variables.

#### **Parameters**

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables
pre_var_space	dict with model presynaptic variables
post_var_space	dict with model postsynaptic variables

## 19.64.3.25 weight\_update\_var\_size()

```
\label{lem:constraint} $\operatorname{def pygenn.genn\_groups.SynapseGroup.weight\_update\_var\_size} \ ($\operatorname{\it self}$ )
```

Size of each weight update variable.

### 19.64.4 Member Data Documentation

# 19.64.4.1 connections\_set

pygenn.genn\_groups.SynapseGroup.connections\_set

# 19.64.4.2 connectivity\_initialiser

 $\verb"pygenn.genn_groups.SynapseGroup.connectivity_initialiser"$ 

```
19.64.4.3 ind
pygenn.genn_groups.SynapseGroup.ind
19.64.4.4 pop
pygenn.genn_groups.SynapseGroup.pop
19.64.4.5 post_vars
pygenn.genn_groups.SynapseGroup.post_vars
19.64.4.6 postsyn
pygenn.genn_groups.SynapseGroup.postsyn
19.64.4.7 pre_vars
pygenn.genn_groups.SynapseGroup.pre_vars
19.64.4.8 psm_vars
pygenn.genn_groups.SynapseGroup.psm_vars
19.64.4.9 row_lengths
pygenn.genn_groups.SynapseGroup.row_lengths
19.64.4.10 src
pygenn.genn_groups.SynapseGroup.src
19.64.4.11 synapse_order
pygenn.genn_groups.SynapseGroup.synapse_order
19.64.4.12 trg
pygenn.genn_groups.SynapseGroup.trg
19.64.4.13 w_update
```

pygenn.genn\_groups.SynapseGroup.w\_update


The documentation for this class was generated from the following file:

· genn\_groups.py

### 19.65 SynapseGroup Class Reference

#include <synapseGroup.h>

Inheritance diagram for SynapseGroup:



#### **Public Types**

enum SpanType { SpanType::POSTSYNAPTIC, SpanType::PRESYNAPTIC }

#### **Public Member Functions**

- SynapseGroup (const SynapseGroup &)=delete
- SynapseGroup ()=delete
- void setWUVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model state variable.

void setWUPreVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model presynaptic state variable.

void setWUPostVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model postsynaptic state variable.

void setWUExtraGlobalParamLocation (const std::string &paramName, VarLocation loc)

Set location of weight update model extra global parameter.

void setPSVarLocation (const std::string &varName, VarLocation loc)

Set location of postsynaptic model state variable.

void setPSExtraGlobalParamLocation (const std::string &paramName, VarLocation loc)

Set location of postsynaptic model extra global parameter.

void setSparseConnectivityExtraGlobalParamLocation (const std::string &paramName, VarLocation loc)

Set location of sparse connectivity initialiser extra global parameter.

void setInSynVarLocation (VarLocation loc)

Set location of variables used to combine input from this synapse group.

void setSparseConnectivityLocation (VarLocation loc)

Set variable mode used for sparse connectivity.

void setDendriticDelayLocation (VarLocation loc)

Set variable mode used for this synapse group's dendritic delay buffers.

· void setMaxConnections (unsigned int maxConnections)

Sets the maximum number of target neurons any source neurons can connect to.

void setMaxSourceConnections (unsigned int maxPostConnections)

Sets the maximum number of source neurons any target neuron can connect to.

void setMaxDendriticDelayTimesteps (unsigned int maxDendriticDelay)

Sets the maximum dendritic delay for synapses in this synapse group.

void setSpanType (SpanType spanType)

Set how CUDA implementation is parallelised.

void setBackPropDelaySteps (unsigned int timesteps)

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

- const std::string & getName () const
- SpanType getSpanType () const
- unsigned int getDelaySteps () const
- unsigned int getBackPropDelaySteps () const
- unsigned int getMaxConnections () const
- unsigned int getMaxSourceConnections () const
- unsigned int getMaxDendriticDelayTimesteps () const
- SynapseMatrixType getMatrixType () const
- VarLocation getInSynLocation () const

Get variable mode used for variables used to combine input from this synapse group.

VarLocation getSparseConnectivityLocation () const

Get variable mode used for sparse connectivity.

VarLocation getDendriticDelayLocation () const

Get variable mode used for this synapse group's dendritic delay buffers.

- · int getClusterHostID () const
- bool isTrueSpikeRequired () const

Does synapse group need to handle 'true' spikes.

bool isSpikeEventRequired () const

Does synapse group need to handle spike-like events.

- const WeightUpdateModels::Base \* getWUModel () const
- const std::vector< double > & getWUParams () const
- const std::vector< Models::VarInit > & getWUVarInitialisers () const
- const std::vector< Models::VarInit > & getWUPreVarInitialisers () const
- const std::vector< Models::VarInit > & getWUPostVarInitialisers () const
- const std::vector< double > getWUConstInitVals () const
- const PostsynapticModels::Base \* getPSModel () const
- const std::vector< double > & getPSParams () const
- const std::vector< Models::VarInit > & getPSVarInitialisers () const
- const std::vector< double > getPSConstInitVals () const
- const InitSparseConnectivitySnippet::Init & getConnectivityInitialiser () const
- bool isZeroCopyEnabled () const
- VarLocation getWUVarLocation (const std::string &var) const

Get location of weight update model per-synapse state variable by name.

VarLocation getWUVarLocation (size\_t index) const

Get location of weight update model per-synapse state variable by index.

VarLocation getWUPreVarLocation (const std::string &var) const

Get location of weight update model presynaptic state variable by name.

VarLocation getWUPreVarLocation (size\_t index) const

Get location of weight update model presynaptic state variable by index.

VarLocation getWUPostVarLocation (const std::string &var) const

Get location of weight update model postsynaptic state variable by name.

VarLocation getWUPostVarLocation (size\_t index) const

Get location of weight update model postsynaptic state variable by index.

VarLocation getWUExtraGlobalParamLocation (const std::string &paramName) const

Get location of weight update model extra global parameter by name.

VarLocation getWUExtraGlobalParamLocation (size\_t index) const

Get location of weight update model extra global parameter by index.

VarLocation getPSVarLocation (const std::string &var) const

Get location of postsynaptic model state variable.

VarLocation getPSVarLocation (size\_t index) const

Get location of postsynaptic model state variable.

VarLocation getPSExtraGlobalParamLocation (const std::string &paramName) const

Get location of postsynaptic model extra global parameter by name.

VarLocation getPSExtraGlobalParamLocation (size t index) const

Get location of postsynaptic model extra global parameter by index.

VarLocation getSparseConnectivityExtraGlobalParamLocation (const std::string &paramName) const

Get location of sparse connectivity initialiser extra global parameter by name.

VarLocation getSparseConnectivityExtraGlobalParamLocation (size\_t index) const

Get location of sparse connectivity initialiser extra global parameter by index.

bool isDendriticDelayRequired () const

Does this synapse group require dendritic delay?

· bool isPSInitRNGRequired () const

Does this synapse group require an RNG for it's postsynaptic init code?

bool isWUInitRNGRequired () const

Does this synapse group require an RNG for it's weight update init code?

bool isWUVarInitRequired () const

Is var init code required for any variables in this synapse group's weight update model?

bool isSparseConnectivityInitRequired () const

Is sparse connectivity initialisation code required for this synapse group?

#### **Protected Member Functions**

- NeuronGroupInternal \* getSrcNeuronGroup ()
- NeuronGroupInternal \* getTrgNeuronGroup ()
- void setEventThresholdReTestRequired (bool req)
- void setPSModelMergeTarget (const std::string &targetName)
- void initDerivedParams (double dt)
- const NeuronGroupInternal \* getSrcNeuronGroup () const
- const NeuronGroupInternal \* getTrgNeuronGroup () const
- const std::vector< double > & getWUDerivedParams () const
- const std::vector< double > & getPSDerivedParams () const

Does the event threshold needs to be retested in the synapse kernel?

- bool isEventThresholdReTestRequired () const
- const std::string & getPSModelTargetName () const
- bool isPSModelMerged () const
- std::string getPresynapticAxonalDelaySlot (const std::string &devPrefix) const
- std::string getPostsynapticBackPropDelaySlot (const std::string &devPrefix) const
- std::string getDendriticDelayOffset (const std::string &devPrefix, const std::string &offset="") const

## 19.65.1 Member Enumeration Documentation

#### 19.65.1.1 SpanType

enum SynapseGroup::SpanType [strong]

#### Enumerator

```
POSTSYNAPTIC PRESYNAPTIC
```

#### 19.65.2 Constructor & Destructor Documentation

```
19.65.2.1 SynapseGroup() [1/3]
SynapseGroup::SynapseGroup (
            const SynapseGroup & ) [delete]
19.65.2.2 SynapseGroup() [2/3]
SynapseGroup::SynapseGroup ( ) [delete]
19.65.2.3 SynapseGroup() [3/3]
SynapseGroup::SynapseGroup (
            const std::string name,
             SynapseMatrixType matrixType,
             unsigned int delaySteps,
             const WeightUpdateModels::Base * wu,
             const std::vector< double > & wuParams,
             const std::vector< Models::VarInit > & wuVarInitialisers,
             const std::vector< Models::VarInit > & wuPreVarInitialisers,
             const std::vector< Models::VarInit > & wuPostVarInitialisers,
             const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trgNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation ) [protected]
```

## 19.65.3 Member Function Documentation

# 19.65.3.1 getBackPropDelaySteps()

```
unsigned int SynapseGroup::getBackPropDelaySteps ( ) const [inline]
```

## 19.65.3.2 getClusterHostID()

```
int SynapseGroup::getClusterHostID ( ) const
```

```
19.65.3.3 getConnectivityInitialiser()
```

```
const InitSparseConnectivitySnippet::Init& SynapseGroup::getConnectivityInitialiser ( ) const
[inline]
```

### 19.65.3.4 getDelaySteps()

```
unsigned int SynapseGroup::getDelaySteps ( ) const [inline]
```

## 19.65.3.5 getDendriticDelayLocation()

```
VarLocation SynapseGroup::getDendriticDelayLocation ( ) const [inline]
```

Get variable mode used for this synapse group's dendritic delay buffers.

#### 19.65.3.6 getDendriticDelayOffset()

# 19.65.3.7 getInSynLocation()

```
VarLocation SynapseGroup::getInSynLocation ( ) const [inline]
```

Get variable mode used for variables used to combine input from this synapse group.

### 19.65.3.8 getMatrixType()

```
SynapseMatrixType SynapseGroup::getMatrixType ( ) const [inline]
```

### 19.65.3.9 getMaxConnections()

```
unsigned int SynapseGroup::getMaxConnections ( ) const [inline]
```

# 19.65.3.10 getMaxDendriticDelayTimesteps()

```
unsigned\ int\ SynapseGroup:: get \texttt{MaxDendriticDelayTimesteps}\ (\ )\ const\ \ [inline]
```

### 19.65.3.11 getMaxSourceConnections()

```
unsigned int SynapseGroup::getMaxSourceConnections ( ) const [inline]
```

### 19.65.3.12 getName()

```
const std::string& SynapseGroup::getName ( ) const [inline]
```

```
19.65.3.13 getPostsynapticBackPropDelaySlot()
```

Get the expression to calculate the delay slot for accessing Postsynaptic neuron state variables, taking into account back propagation delay

### 19.65.3.14 getPresynapticAxonalDelaySlot()

Get the expression to calculate the delay slot for accessing Presynaptic neuron state variables, taking into account axonal delay

### 19.65.3.15 getPSConstInitVals()

```
const std::vector< double > SynapseGroup::getPSConstInitVals ( ) const
```

### 19.65.3.16 getPSDerivedParams()

```
const std::vector<double>& SynapseGroup::getPSDerivedParams ( ) const [inline], [protected]
```

Does the event threshold needs to be retested in the synapse kernel?

#### 19.65.3.17 getPSExtraGlobalParamLocation() [1/2]

Get location of postsynaptic model extra global parameter by name.

This is only used by extra global parameters which are pointers

```
19.65.3.18 getPSExtraGlobalParamLocation() [2/2]
```

Get location of postsynaptic model extra global parameter by index.

This is only used by extra global parameters which are pointers

### 19.65.3.19 getPSModel()

```
const PostsynapticModels::Base* SynapseGroup::getPSModel ( ) const [inline]
```

## 19.65.3.20 getPSModelTargetName()

```
const std::string& SynapseGroup::getPSModelTargetName ( ) const [inline], [protected]
```

#### 19.65.3.21 getPSParams()

```
const std::vector<double>& SynapseGroup::getPSParams ( ) const [inline]
```

```
19.65.3.22 getPSVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getPSVarInitialisers ( ) const [inline]
19.65.3.23 getPSVarLocation() [1/2]
VarLocation SynapseGroup::getPSVarLocation (
              const std::string & var ) const
Get location of postsynaptic model state variable.
19.65.3.24 getPSVarLocation() [2/2]
VarLocation SynapseGroup::getPSVarLocation (
              size_t index ) const [inline]
Get location of postsynaptic model state variable.
19.65.3.25 getSpanType()
SpanType SynapseGroup::getSpanType ( ) const [inline]
19.65.3.26 getSparseConnectivityExtraGlobalParamLocation() [1/2]
{\tt VarLocation} \  \, {\tt SynapseGroup::getSparseConnectivityExtraGlobalParamLocation} \  \, (
              const std::string & paramName ) const
Get location of sparse connectivity initialiser extra global parameter by name.
This is only used by extra global parameters which are pointers
19.65.3.27 getSparseConnectivityExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getSparseConnectivityExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of sparse connectivity initialiser extra global parameter by index.
This is only used by extra global parameters which are pointers
19.65.3.28 getSparseConnectivityLocation()
VarLocation SynapseGroup::getSparseConnectivityLocation ( ) const [inline]
Get variable mode used for sparse connectivity.
19.65.3.29 getSrcNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) [inline], [protected]
19.65.3.30 getSrcNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) const [inline], [protected]
```

```
19.65.3.31 getTrgNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) [inline], [protected]
19.65.3.32 getTrgNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) const [inline], [protected]
19.65.3.33 getWUConstInitVals()
const std::vector< double > SynapseGroup::getWUConstInitVals ( ) const
19.65.3.34 getWUDerivedParams()
const std::vector<double>& SynapseGroup::getWUDerivedParams ( ) const [inline], [protected]
19.65.3.35 getWUExtraGlobalParamLocation() [1/2]
VarLocation SynapseGroup::getWUExtraGlobalParamLocation (
             const std::string & paramName ) const
Get location of weight update model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.65.3.36 getWUExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getWUExtraGlobalParamLocation (
             size_t index ) const [inline]
Get location of weight update model extra global parameter by index.
This is only used by extra global parameters which are pointers
19.65.3.37 getWUModel()
const WeightUpdateModels::Base* SynapseGroup::getWUModel ( ) const [inline]
19.65.3.38 getWUParams()
const std::vector<double>& SynapseGroup::getWUParams ( ) const [inline]
19.65.3.39 getWUPostVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUPostVarInitialisers ( ) const [inline]
19.65.3.40 getWUPostVarLocation() [1/2]
VarLocation SynapseGroup::getWUPostVarLocation (
             const std::string & var ) const
```

Get location of weight update model postsynaptic state variable by name.

```
19.65.3.41 getWUPostVarLocation() [2/2]
VarLocation SynapseGroup::getWUPostVarLocation (
              size_t index ) const [inline]
Get location of weight update model postsynaptic state variable by index.
19.65.3.42 getWUPreVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUPreVarInitialisers ( ) const [inline]
19.65.3.43 getWUPreVarLocation() [1/2]
VarLocation SynapseGroup::getWUPreVarLocation (
              const std::string & var ) const
Get location of weight update model presynaptic state variable by name.
19.65.3.44 getWUPreVarLocation() [2/2]
VarLocation SynapseGroup::getWUPreVarLocation (
              size_t index ) const [inline]
Get location of weight update model presynaptic state variable by index.
19.65.3.45 getWUVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUVarInitialisers ( ) const [inline]
19.65.3.46 getWUVarLocation() [1/2]
VarLocation SynapseGroup::getWUVarLocation (
              const std::string & var ) const
Get location of weight update model per-synapse state variable by name.
19.65.3.47 getWUVarLocation() [2/2]
VarLocation SynapseGroup::getWUVarLocation (
              size_t index ) const [inline]
Get location of weight update model per-synapse state variable by index.
19.65.3.48 initDerivedParams()
void SynapseGroup::initDerivedParams (
              double dt ) [protected]
19.65.3.49 isDendriticDelayRequired()
bool SynapseGroup::isDendriticDelayRequired ( ) const
```

Does this synapse group require dendritic delay?

```
19.65.3.50 isEventThresholdReTestRequired()
```

```
bool SynapseGroup::isEventThresholdReTestRequired ( ) const [inline], [protected]
```

This is required when the pre-synaptic neuron population's outgoing synapse groups require different event threshold

```
19.65.3.51 isPSInitRNGRequired()
```

```
bool SynapseGroup::isPSInitRNGRequired ( ) const
```

Does this synapse group require an RNG for it's postsynaptic init code?

#### 19.65.3.52 isPSModelMerged()

```
bool SynapseGroup::isPSModelMerged ( ) const [inline], [protected]
```

## 19.65.3.53 isSparseConnectivityInitRequired()

```
bool SynapseGroup::isSparseConnectivityInitRequired ( ) const
```

Is sparse connectivity initialisation code required for this synapse group?

### 19.65.3.54 isSpikeEventRequired()

```
bool SynapseGroup::isSpikeEventRequired ( ) const
```

Does synapse group need to handle spike-like events.

### 19.65.3.55 isTrueSpikeRequired()

```
bool SynapseGroup::isTrueSpikeRequired ( ) const
```

Does synapse group need to handle 'true' spikes.

# 19.65.3.56 isWUInitRNGRequired()

```
bool SynapseGroup::isWUInitRNGRequired ( ) const
```

Does this synapse group require an RNG for it's weight update init code?

## 19.65.3.57 isWUVarInitRequired()

```
bool SynapseGroup::isWUVarInitRequired ( ) const
```

Is var init code required for any variables in this synapse group's weight update model?

### 19.65.3.58 isZeroCopyEnabled()

bool SynapseGroup::isZeroCopyEnabled ( ) const

## 19.65.3.59 setBackPropDelaySteps()

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

## 19.65.3.60 setDendriticDelayLocation()

Set variable mode used for this synapse group's dendritic delay buffers.

#### 19.65.3.61 setEventThresholdReTestRequired()

#### 19.65.3.62 setInSynVarLocation()

Set location of variables used to combine input from this synapse group.

This is ignored for simulations on hardware with a single memory space

# 19.65.3.63 setMaxConnections()

```
void SynapseGroup::setMaxConnections (
          unsigned int maxConnections )
```

Sets the maximum number of target neurons any source neurons can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE to optimise CUDA implementation

# 19.65.3.64 setMaxDendriticDelayTimesteps()

Sets the maximum dendritic delay for synapses in this synapse group.

## 19.65.3.65 setMaxSourceConnections()

```
void SynapseGroup::setMaxSourceConnections ( unsigned\ int\ \textit{maxPostConnections}\ )
```

Sets the maximum number of source neurons any target neuron can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE and postsynaptic learning to optimise CUDA implementation

### 19.65.3.66 setPSExtraGlobalParamLocation()

```
void SynapseGroup::setPSExtraGlobalParamLocation (
```

```
const std::string & paramName,
VarLocation loc )
```

Set location of postsynaptic model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

#### 19.65.3.67 setPSModelMergeTarget()

#### 19.65.3.68 setPSVarLocation()

Set location of postsynaptic model state variable.

This is ignored for simulations on hardware with a single memory space

#### 19.65.3.69 setSpanType()

Set how CUDA implementation is parallelised.

with a thread per target neuron (default) or a thread per source spike

# 19.65.3.70 setSparseConnectivityExtraGlobalParamLocation()

Set location of sparse connectivity initialiser extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

## 19.65.3.71 setSparseConnectivityLocation()

Set variable mode used for sparse connectivity.

This is ignored for simulations on hardware with a single memory space

## 19.65.3.72 setWUExtraGlobalParamLocation()

Set location of weight update model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

### 19.65.3.73 setWUPostVarLocation()

Set location of weight update model postsynaptic state variable.

This is ignored for simulations on hardware with a single memory space

#### 19.65.3.74 setWUPreVarLocation()

Set location of weight update model presynaptic state variable.

This is ignored for simulations on hardware with a single memory space

#### 19.65.3.75 setWUVarLocation()

Set location of weight update model state variable.

This is ignored for simulations on hardware with a single memory space


The documentation for this class was generated from the following files:

- synapseGroup.h
- synapseGroup.cc

### 19.66 SynapseGroupInternal Class Reference

```
#include <synapseGroupInternal.h>
```

Inheritance diagram for SynapseGroupInternal:



### **Public Member Functions**

SynapseGroupInternal (const std::string name, SynapseMatrixType matrixType, unsigned int delaySteps, const WeightUpdateModels::Base \*wu, const std::vector< double > &wuParams, const std::vector< Models::VarInit > &wuVarInitialisers, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< double > &psParams, const std::vector< Models::VarInit > &psVarInitialisers, NeuronGroup← Internal \*srcNeuronGroup, NeuronGroupInternal \*trgNeuronGroup, const InitSparseConnectivitySnippet::← Init &connectivityInitialiser, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, VarLocation defaultSparseConnectivityLocation)

#### **Additional Inherited Members**

#### 19.66.1 Constructor & Destructor Documentation

## 19.66.1.1 SynapseGroupInternal()

```
{\tt SynapseGroupInternal::SynapseGroupInternal} \ \ (
             const std::string name,
             SynapseMatrixType matrixType,
             unsigned int delaySteps,
             const WeightUpdateModels::Base * wu,
             const std::vector< double > & wuParams,
             const std::vector< Models::VarInit > & wuVarInitialisers,
             const std::vector< Models::VarInit > & wuPreVarInitialisers,
             const std::vector< Models::VarInit > & wuPostVarInitialisers,
             const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trqNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation ) [inline]
```


The documentation for this class was generated from the following file:

· synapseGroupInternal.h

## 19.67 CodeGenerator::TeeBuf Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeBuf:



**Public Member Functions** 

template<typename... T>
 TeeBuf (T &&... streamBufs)

## 19.67.1 Constructor & Destructor Documentation

### 19.67.1.1 TeeBuf()


The documentation for this class was generated from the following file:

· teeStream.h

## 19.68 CodeGenerator::TeeStream Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeStream:



**Public Member Functions** 

 template<typename... T>
 TeeStream (T &&... streamBufs)

## 19.68.1 Constructor & Destructor Documentation

### 19.68.1.1 TeeStream()

The documentation for this class was generated from the following file:


· teeStream.h

## 19.69 NeuronModels::TraubMiles Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMiles:



### **Public Types**

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

### **Static Public Member Functions**

static const NeuronModels::TraubMiles \* getInstance ()

## **Additional Inherited Members**

### 19.69.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

This conductance based model has been taken from [7] and can be described by the equations:

$$C\frac{dV}{dt} = -I_{Na} - I_K - I_{leak} - I_M - I_{i,DC} - I_{i,syn} - I_i,$$

$$I_{Na}(t) = g_{Na}m_i(t)^3 h_i(t)(V_i(t) - E_{Na})$$

$$I_K(t) = g_K n_i(t)^4 (V_i(t) - E_K)$$

$$\frac{dy(t)}{dt} = \alpha_y(V(t))(1 - y(t)) - \beta_y(V(t))y(t),$$

where  $y_i = m, h, n$ , and

$$\alpha_n = 0.032(-50-V)/(\exp((-50-V)/5)-1)$$
  
 $\beta_n = 0.5 \exp((-55-V)/40)$   
 $\alpha_m = 0.32(-52-V)/(\exp((-52-V)/4)-1)$ 

$$\beta_m = 0.28(25+V)/(\exp((25+V)/5)-1)$$
 $\alpha_h = 0.128 \exp((-48-V)/18)$ 
 $\beta_h = 4/(\exp((-25-V)/5)+1).$ 

and typical parameters are C=0.143 nF,  $g_{\rm leak}=0.02672~\mu$ S,  $E_{\rm leak}=-63.563$  mV,  $g_{\rm Na}=7.15~\mu$ S,  $E_{\rm Na}=50$  mV,  $g_{\rm K}=1.43~\mu$ S,  $E_{\rm K}=-95$  mV.

It has 4 variables:

- ∨ membrane potential E
- m probability for Na channel activation m
- · h probability for not Na channel blocking h
- n probability for K channel activation n

### and 7 parameters:

- gNa Na conductance in 1/(mOhms \* cm<sup>^2</sup>)
- ENa Na equi potential in mV
- gK K conductance in 1/(mOhms \* cm<sup>2</sup>)
- EK K equi potential in mV
- gl Leak conductance in 1/(mOhms \* cm<sup>^</sup>2)
- El Leak equi potential in mV
- Cmem Membrane capacity density in muF/cm<sup>2</sup>

### Note

Internally, the ordinary differential equations defining the model are integrated with a linear Euler algorithm and GeNN integrates 25 internal time steps for each neuron for each network time step. I.e., if the network is simulated at DT = 0.1 ms, then the neurons are integrated with a linear Euler algorithm with 1DT = 0.004 ms. This variant uses IF statements to check for a value at which a singularity would be hit. If so, value calculated by L'Hospital rule is used.

### 19.69.2 Member Typedef Documentation

### 19.69.2.1 ParamValues

```
{\tt typedef~Snippet::ValueBase<~7~>~NeuronModels::TraubMiles::ParamValues}
```

#### 19.69.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PostVarValues

#### 19.69.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PreVarValues

#### 19.69.2.4 VarValues

```
typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMiles::VarValues
```

#### 19.69.3 Member Function Documentation

#### 19.69.3.1 getInstance()

```
static const NeuronModels::TraubMiles* NeuronModels::TraubMiles::getInstance ( ) [inline],
[static]
```

#### 19.69.3.2 getParamNames()

```
virtual StringVec NeuronModels::TraubMiles::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

Reimplemented in NeuronModels::TraubMilesNStep.

### 19.69.3.3 getSimCode()

```
virtual std::string NeuronModels::TraubMiles::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMilesAlt, and NeuronModels::Traub MilesFast.

#### 19.69.3.4 getThresholdConditionCode()

```
virtual std::string NeuronModels::TraubMiles::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

# 19.69.3.5 getVars()

```
virtual VarVec NeuronModels::TraubMiles::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


neuronModels.h

### 19.70 NeuronModels::TraubMilesAlt Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesAlt:



## **Public Types**

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

## **Public Member Functions**

virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.

### **Static Public Member Functions**

static const NeuronModels::TraubMilesAlt \* getInstance ()

# **Additional Inherited Members**

## 19.70.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Using a workaround to avoid singularity: adding the munimum numerical value of the floating point precision used.

### 19.70.2 Member Typedef Documentation

#### 19.70.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesAlt::ParamValues

#### 19.70.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PostVarValues

#### 19.70.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PreVarValues

### 19.70.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesAlt::VarValues

### 19.70.3 Member Function Documentation

### 19.70.3.1 getInstance()

static const NeuronModels::TraubMilesAlt\* NeuronModels::TraubMilesAlt::getInstance ( ) [inline],
[static]

## 19.70.3.2 getSimCode()

virtual std::string NeuronModels::TraubMilesAlt::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


#### · neuronModels.h

### 19.71 NeuronModels::TraubMilesFast Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesFast:



## **Public Types**

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

### **Public Member Functions**

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

## **Static Public Member Functions**

static const NeuronModels::TraubMilesFast \* getInstance ()

#### **Additional Inherited Members**

## 19.71.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

There are singularities in this model, which can be easily hit in float precision

# 19.71.2 Member Typedef Documentation

#### 19.71.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesFast::ParamValues

#### 19.71.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PostVarValues

#### 19.71.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PreVarValues

#### 19.71.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesFast::VarValues

#### 19.71.3 Member Function Documentation

### 19.71.3.1 getInstance()

static const NeuronModels::TraubMilesFast\* NeuronModels::TraubMilesFast::getInstance ( ) [inline],
[static]

### 19.71.3.2 getSimCode()

virtual std::string NeuronModels::TraubMilesFast::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


· neuronModels.h

## 19.72 NeuronModels::TraubMilesNStep Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesNStep:



## **Public Types**

typedef Snippet::ValueBase< 8 > ParamValues

- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

#### **Public Member Functions**

- virtual std::string getSimCode () const override
  - Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

#### Static Public Member Functions

static const NeuronModels::TraubMilesNStep \* getInstance ()

### **Additional Inherited Members**

### 19.72.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Same as standard TraubMiles model but number of inner loops can be set using a parameter

#### 19.72.2 Member Typedef Documentation

#### 19.72.2.1 ParamValues

```
typedef Snippet::ValueBase< 8 > NeuronModels::TraubMilesNStep::ParamValues
```

### 19.72.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PostVarValues
```

### 19.72.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PreVarValues
```

### 19.72.2.4 VarValues

```
typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesNStep::VarValues
```

# 19.72.3 Member Function Documentation

## 19.72.3.1 getInstance()

```
static const NeuronModels::TraubMilesNStep* NeuronModels::TraubMilesNStep::getInstance ( )
[inline], [static]
```

#### 19.72.3.2 getParamNames()

virtual StringVec NeuronModels::TraubMilesNStep::getParamNames ( ) const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::TraubMiles.

#### 19.72.3.3 getSimCode()

virtual std::string NeuronModels::TraubMilesNStep::getSimCode ( ) const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


• neuronModels.h

## 19.73 InitVarSnippet::Uniform Class Reference

Initialises variable by sampling from the uniform distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uniform:



### **Public Member Functions**

- DECLARE\_SNIPPET (InitVarSnippet::Uniform, 2)
- SET\_CODE ("const scalar scale = \$(max) \$(min);\ "\$(value)=\$(min)+(\$(gennrand\_uniform) \*scale);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

## **Additional Inherited Members**

### 19.73.1 Detailed Description

Initialises variable by sampling from the uniform distribution.

This snippet takes 2 parameters:

- min The minimum value
- max The maximum value

#### 19.73.2 Member Function Documentation

## 19.73.2.1 DECLARE\_SNIPPET()

# 19.73.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Uniform::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

### 19.73.2.3 SET\_CODE()

The documentation for this class was generated from the following file:


· initVarSnippet.h

# 19.74 InitVarSnippet::Uninitialised Class Reference

Used to mark variables as uninitialised - no initialisation code will be run.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uninitialised:



**Public Member Functions** 

• DECLARE\_SNIPPET (InitVarSnippet::Uninitialised, 0)

**Additional Inherited Members** 

### 19.74.1 Detailed Description

Used to mark variables as uninitialised - no initialisation code will be run.

#### 19.74.2 Member Function Documentation

## 19.74.2.1 DECLARE\_SNIPPET()

The documentation for this class was generated from the following file:


· initVarSnippet.h

## 19.75 InitSparseConnectivitySnippet::Uninitialised Class Reference

Used to mark connectivity as uninitialised - no initialisation code will be run.

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::Uninitialised:



### **Public Member Functions**

• DECLARE\_SNIPPET (InitSparseConnectivitySnippet::Uninitialised, 0)

**Additional Inherited Members** 

# 19.75.1 Detailed Description

Used to mark connectivity as uninitialised - no initialisation code will be run.

## 19.75.2 Member Function Documentation

## 19.75.2.1 DECLARE\_SNIPPET()

The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

## 19.76 Snippet::ValueBase < NumVars > Class Template Reference

```
#include <snippet.h>
```

#### **Public Member Functions**

- template<typename... T>
   ValueBase (T &&... vals)
- const std::vector< double > & getValues () const

Gets values as a vector of doubles.

• double operator[] (size\_t pos) const

### 19.76.1 Constructor & Destructor Documentation

#### 19.76.1.1 ValueBase()

### 19.76.2 Member Function Documentation

## 19.76.2.1 getValues()

```
template<size_t NumVars>
const std::vector<double>& Snippet::ValueBase< NumVars >::getValues ( ) const [inline]
```

Gets values as a vector of doubles.

## 19.76.2.2 operator[]()

The documentation for this class was generated from the following file:

· snippet.h

# 19.77 Snippet::ValueBase < 0 > Class Template Reference

```
#include <snippet.h>
```

### **Public Member Functions**

- template<typename... T>
   ValueBase (T &&... vals)
- std::vector< double > getValues () const

Gets values as a vector of doubles.

### 19.77.1 Detailed Description

```
template<> class Snippet::ValueBase< 0 >
```

Template specialisation of ValueBase to avoid compiler warnings in the case when a model requires no parameters or state variables

### 19.77.2 Constructor & Destructor Documentation

### 19.77.2.1 ValueBase()

### 19.77.3 Member Function Documentation

```
19.77.3.1 getValues()
```

```
std::vector<double> Snippet::ValueBase< 0 >::getValues ( ) const [inline]
```

Gets values as a vector of doubles.

The documentation for this class was generated from the following file:

• snippet.h

## 19.78 Snippet::Base::Var Struct Reference

A variable has a name and a type.

```
#include <snippet.h>
```

### **Public Attributes**

- std::string name
- std::string type

## 19.78.1 Detailed Description

A variable has a name and a type.

#### 19.78.2 Member Data Documentation

### 19.78.2.1 name

```
std::string Snippet::Base::Var::name
```

```
19.78.2.2 type
```

```
std::string Snippet::Base::Var::type
```


The documentation for this struct was generated from the following file:

· snippet.h

# 19.79 pygenn.model\_preprocessor.Variable Class Reference

Class holding information about GeNN variables.

Inheritance diagram for pygenn.model\_preprocessor.Variable:



### **Public Member Functions**

- def \_\_init\_\_ (self, variable\_name, variable\_type, values=None)
   Init Variable.
- def set\_values (self, values)

Set Variable's values.

### **Public Attributes**

- name
- type
- view
- · needs\_allocation
- init\_required
- init\_val
- values

# 19.79.1 Detailed Description

Class holding information about GeNN variables.

### 19.79.2 Constructor & Destructor Documentation

Init Variable.

### **Parameters**

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable, single value or VarInit instance

## 19.79.3 Member Function Documentation

## 19.79.3.1 set\_values()

```
def pygenn.model_preprocessor.Variable.set_values ( self, \\ values \ )
```

## Set Variable's values.

### **Parameters**

values iterable, sing	le value or VarInit instance
-----------------------	------------------------------

### 19.79.4 Member Data Documentation

### 19.79.4.1 init\_required

pygenn.model\_preprocessor.Variable.init\_required

### 19.79.4.2 init\_val

pygenn.model\_preprocessor.Variable.init\_val

## 19.79.4.3 name

 $\verb|pygenn.model_preprocessor.Variable.name| \\$ 

## 19.79.4.4 needs\_allocation

 $\verb|pygenn.model_preprocessor.Variable.needs_allocation|\\$ 

# 19.79.4.5 type

pygenn.model\_preprocessor.Variable.type

# 19.79.4.6 values

 $\verb|pygenn.model_preprocessor.Variable.values|\\$ 

#### 19.79.4.7 view

```
pygenn.model_preprocessor.Variable.view
```


The documentation for this class was generated from the following file:

model\_preprocessor.py

### 19.80 Models::VarInit Class Reference

```
#include <models.h>
```

Inheritance diagram for Models::VarInit:



#### **Public Member Functions**

- VarInit (const InitVarSnippet::Base \*snippet, const std::vector< double > &params)
- · VarInit (double constant)

## 19.80.1 Detailed Description

Class used to bind together everything required to initialise a variable:

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

## 19.80.2 Constructor & Destructor Documentation

The documentation for this class was generated from the following file:

· models.h

# 19.81 Models::VarInitContainerBase < NumVars > Class Template Reference

```
#include <models.h>
```

#### **Public Member Functions**

- template<typename... T>
   VarInitContainerBase (T &&... initialisers)
- const std::vector< VarInit > & getInitialisers () const

Gets initialisers as a vector of Values.

const VarInit & operator[] (size\_t pos) const

#### 19.81.1 Detailed Description

```
template < size_t NumVars > class Models::VarInitContainerBase < NumVars >
```

Wrapper to ensure at compile time that correct number of value initialisers are used when specifying the values of a model's initial state.

#### 19.81.2 Constructor & Destructor Documentation

### 19.81.2.1 VarInitContainerBase()

### 19.81.3 Member Function Documentation

#### 19.81.3.1 getInitialisers()

```
template<size_t NumVars>
const std::vector<VarInit>& Models::VarInitContainerBase< NumVars >::getInitialisers ( )
const [inline]
```

Gets initialisers as a vector of Values.

# 19.81.3.2 operator[]()

The documentation for this class was generated from the following file:

· models.h

## 19.82 Models::VarInitContainerBase < 0 > Class Template Reference

```
#include <models.h>
```

#### **Public Member Functions**

- template<typename... T>
   VarInitContainerBase (T &&... initialisers)
- VarInitContainerBase (const Snippet::ValueBase< 0 > &)
- std::vector< VarInit > getInitialisers () const

Gets initialisers as a vector of Values.

#### 19.82.1 Detailed Description

```
template<> class Models::VarInitContainerBase< 0 >
```

Template specialisation of ValueInitBase to avoid compiler warnings in the case when a model requires no variable initialisers

#### 19.82.2 Constructor & Destructor Documentation

### 19.82.3 Member Function Documentation

```
19.82.3.1 getInitialisers()
```

```
std::vector<VarInit> Models::VarInitContainerBase< 0 >::getInitialisers ( ) const [inline]
```

Gets initialisers as a vector of Values.

The documentation for this class was generated from the following file:

models.h

## 20 File Documentation

## 20.1 00\_MainPage.dox File Reference

- 20.2 01\_Installation.dox File Reference
- 20.3 02\_Quickstart.dox File Reference
- 20.4 03\_Examples.dox File Reference
- 20.5 05\_SpineML.dox File Reference
- 20.6 06\_Brian2GeNN.dox File Reference
- 20.7 07\_PyGeNN.dox File Reference
- 20.8 09\_ReleaseNotes.dox File Reference
- 20.9 10\_UserManual.dox File Reference
- 20.10 11\_Tutorial.dox File Reference
- 20.11 12\_Tutorial.dox File Reference
- 20.12 13\_UserGuide.dox File Reference
- 20.13 14 Credits.dox File Reference
- 20.14 \_\_init\_\_.py File Reference

### Namespaces

pygenn

## 20.15 backend.cc File Reference

```
#include "backend.h"
#include <algorithm>
#include <plog/Log.h>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
#include "utils.h"
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::CUDA

## 20.16 backend.cc File Reference

```
#include "backend.h"
#include "gennUtils.h"
```

```
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

• CodeGenerator::SingleThreadedCPU

## 20.17 backend.h File Reference

```
#include <algorithm>
#include <array>
#include <functional>
#include <map>
#include <string>
#include <cuda.h>
#include <cuda_runtime.h>
#include "backendExport.h"
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
```

### Classes

• struct CodeGenerator::CUDA::Preferences

Preferences for CUDA backend.

· class CodeGenerator::CUDA::Backend

## **Namespaces**

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· CodeGenerator::CUDA

## **Typedefs**

using CodeGenerator::CUDA::KernelBlockSize = std::array < size\_t, KernelMax >
 Array of block sizes for each kernel.

### **Enumerations**

enum CodeGenerator::CUDA::DeviceSelect { CodeGenerator::CUDA::DeviceSelect::OPTIMAL, Code
 Generator::CUDA::DeviceSelect::MOST\_MEMORY, CodeGenerator::CUDA::DeviceSelect::MANUAL }

Methods for selecting CUDA device.

 enum CodeGenerator::CUDA::BlockSizeSelect { CodeGenerator::CUDA::BlockSizeSelect::OCCUPANCY, CodeGenerator::CUDA::BlockSizeSelect::MANUAL } Methods for selecting CUDA kernel block size.

enum CodeGenerator::CUDA::Kernel {
 CodeGenerator::CUDA::KernelNeuronUpdate, CodeGenerator::CUDA::KernelPresynapticUpdate, CodeGenerator::CUDA::KernelPresynapticUpdate, CodeGenerator::CUDA::KernelSynapseDynamicsUpdate,
 CodeGenerator::CUDA::KernelInitialize, CodeGenerator::CUDA::KernelInitializeSparse, CodeGenerator::CUDA::KernelPreSynapseReset,
 CodeGenerator::CUDA::KernelMax }

Kernels generated by CUDA backend.

#### 20.18 backend.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include "backendExport.h"
#include "code_generator/backendBase.h"
```

#### Classes

- struct CodeGenerator::SingleThreadedCPU::Preferences
- · class CodeGenerator::SingleThreadedCPU::Backend

## Namespaces

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::SingleThreadedCPU

## 20.19 backendBase.cc File Reference

```
#include "code_generator/backendBase.h"
#include <plog/Log.h>
#include "gennUtils.h"
```

#### Macros

#define TYPE(T) {#T, sizeof(T)}

# 20.19.1 Macro Definition Documentation

### 20.19.1.1 TYPE

## 20.20 backendBase.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include <unordered_map>
#include <vector>
#include <plog/Severity.h>
#include "codeStream.h"
#include "gennExport.h"
#include "variableMode.h"
```

#### Classes

· struct CodeGenerator::PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

- class CodeGenerator::MemAlloc
- · class CodeGenerator::BackendBase

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

# 20.21 backendExport.h File Reference

### Macros

#define BACKEND\_EXPORT

### 20.21.1 Macro Definition Documentation

## 20.21.1.1 BACKEND\_EXPORT

```
#define BACKEND_EXPORT
```

### 20.22 binomial.cc File Reference

```
#include "binomial.h"
#include <stdexcept>
#include <cassert>
#include <cmath>
#include <cstdint>
```

#### **Functions**

unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

#### 20.22.1 Function Documentation

## 20.22.1.1 binomialInverseCDF()

```
unsigned int binomialInverseCDF ( double cdf, unsigned int n, double p)
```

### 20.23 binomial.h File Reference

```
#include "gennExport.h"
```

### **Functions**

• GENN\_EXPORT unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

#### 20.23.1 Function Documentation

### 20.23.1.1 binomialInverseCDF()

```
GENN_EXPORT unsigned int binomialInverseCDF ( \label{eq:cdf} \mbox{double } cdf, \\ \mbox{unsigned int } n, \\ \mbox{double } p \mbox{)}
```

## 20.24 codeGenUtils.cc File Reference

```
#include "code_generator/codeGenUtils.h"
#include <regex>
#include <cstring>
#include "modelSpec.h"
```

### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

### **Enumerations**

• enum MathsFunc

## **Functions**

- void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

  Tool for substituting strings in the neuron code strings or other templates.
- bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void CodeGenerator::preNeuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroup← Internal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postldx, const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_\_ldg(&XXX)

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroupInternal &sg, const std::string &postldx, const std::string &devPrefix, double dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

#### 20.24.1 Enumeration Type Documentation

### 20.24.1.1 MathsFunc

enum MathsFunc

## 20.25 codeGenUtils.h File Reference

```
#include <iomanip>
#include <limits>
#include <string>
#include <sstream>
#include <vector>
#include "snippet.h"
#include "variableMode.h"
```

### Classes

- struct CodeGenerator::FunctionTemplate
- class CodeGenerator::StructNameConstIter< BaseIter >

Custom iterator for iterating through the containers of structs with 'name' members.

struct CodeGenerator::NameIterCtx< Container >

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Typedefs**

- typedef NamelterCtx < Snippet::Base::VarVec > CodeGenerator::VarNamelterCtx
- $\bullet \ \, typedef \ Namelter Ctx < Snippet:: Base:: Derived Param Vec > Code Generator:: Derived Param Namelter Ctx \\$
- typedef NamelterCtx < Snippet::Base::ParamValVec > CodeGenerator::ParamValIterCtx

#### **Functions**

void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

template<typename Namelter >

void CodeGenerator::name\_substitutions (std::string &code, const std::string &prefix, NameIter namesBegin, NameIter namesEnd, const std::string &postfix="", const std::string &ext="")

This function performs a list of name substitutions for variables in code snippets.

This function performs a list of name substitutions for variables in code snippets.

• template<class T , typename std::enable\_if< std::is\_floating\_point< T >::value >::type \* = nullptr> void CodeGenerator::writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

template < class T , typename std::enable\_if < std::is\_floating\_point < T >::value >::type \* = nullptr > std::string CodeGenerator::writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

template<typename Namelter >

void CodeGenerator::value\_substitutions (std::string &code, Namelter namesBegin, Namelter namesEnd, const std::vector< double > &values, const std::string &ext="")

This function performs a list of value substitutions for parameters in code snippets.

• void CodeGenerator::value\_substitutions (std::string &code, const std::vector< std::string > &names, const std::vector< double > &values, const std::string &ext="")

This function performs a list of value substitutions for parameters in code snippets.

std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as ldq(&XXX)

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as \_\_ldg(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (std::string &wCode, const SynapseGroupInternal &sg, const std::string &postldx, const std::string &devPrefix, double dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

### 20.26 codeStream.cc File Reference

```
#include "code_generator/codeStream.h"
#include <algorithm>
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

- GENN\_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN\_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

### 20.27 codeStream.h File Reference

```
#include <ostream>
#include <streambuf>
#include <string>
#include <vector>
#include <plog/Log.h>
#include "gennExport.h"
```

#### Classes

- · class CodeGenerator::CodeStream
- struct CodeGenerator::CodeStream::OB

An open bracket marker.

• struct CodeGenerator::CodeStream::CB

A close bracket marker.

· class CodeGenerator::CodeStream::Scope

### Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

- GENN\_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN\_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

#### 20.28 currentSource.cc File Reference

```
#include "currentSource.h"
#include <algorithm>
#include <cmath>
#include "gennUtils.h"
```

#### 20.29 currentSource.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "currentSourceModels.h"
#include "gennExport.h"
#include "variableMode.h"
```

### Classes

class CurrentSource

## 20.30 currentSourceInternal.h File Reference

```
#include "currentSource.h"
```

## Classes

· class CurrentSourceInternal

## 20.31 currentSourceModels.cc File Reference

```
#include "currentSourceModels.h"
```

### **Functions**

- IMPLEMENT\_MODEL (CurrentSourceModels::DC)
- IMPLEMENT\_MODEL (CurrentSourceModels::GaussianNoise)

## 20.31.1 Function Documentation

## 20.32 currentSourceModels.h File Reference

```
#include <array>
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "gennExport.h"
#include "models.h"
```

#### Classes

class CurrentSourceModels::Base

Base class for all current source models.

class CurrentSourceModels::DC

DC source.

· class CurrentSourceModels::GaussianNoise

Noisy current source with noise drawn from normal distribution.

### **Namespaces**

CurrentSourceModels

## Macros

#define SET\_INJECTION\_CODE(INJECTION\_CODE) virtual std::string getInjectionCode() const override{ return INJECTION\_CODE; }

## 20.32.1 Macro Definition Documentation

## 20.32.1.1 SET\_INJECTION\_CODE

## 20.33 generateAll.cc File Reference

```
#include "code_generator/generateAll.h"
#include <fstream>
#include <vector>
#include <vplog/Log.h>
#include "path.h"
#include "code_generator/codeStream.h"
#include "code_generator/generateInit.h"
#include "code_generator/generateMPI.h"
#include "code_generator/generateNeuronUpdate.h"
#include "code_generator/generateSupportCode.h"
#include "code_generator/generateSynapseUpdate.h"
#include "code_generator/generateSunapseUpdate.h"
#include "code_generator/generateRunner.h"
```

## 20.34 generateAll.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· filesystem

#### **Functions**

• GENN\_EXPORT std::vector< std::string > CodeGenerator::generateAll (const ModelSpecInternal &model, const BackendBase &backend, const filesystem::path &outputPath, bool standaloneModules=false)

## 20.35 generateInit.cc File Reference

```
#include "code_generator/generateInit.h"
#include 'models.h"
#include "models.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

### 20.36 generateInit.h File Reference

## Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

 void CodeGenerator::generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

### 20.37 generateMakefile.cc File Reference

```
#include "code_generator/generateMakefile.h"
#include <string>
#include "modelSpec.h"
#include "code_generator/backendBase.h"
```

# 20.38 generateMakefile.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

## **Functions**

void GENN\_EXPORT CodeGenerator::generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector< std::string > &moduleNames)

### 20.39 generateMPI.cc File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include "code_generator/generateMPI.h"
#include <fstream>
#include <cstring>
#include "modelSpecInternal.h"
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
```

#### 20.39.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

## 20.40 generateMPI.h File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include <string>
#include "gennExport.h"
```

### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

### **Functions**

 void GENN\_EXPORT CodeGenerator::generateMPI (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

A function that generates predominantly MPI infrastructure code.

#### 20.40.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

### 20.41 generateMSBuild.cc File Reference

```
#include "code_generator/generateMSBuild.h"
#include <string>
#include "code_generator/backendBase.h"
```

## 20.42 generateMSBuild.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

## Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

void GENN\_EXPORT CodeGenerator::generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)

## 20.43 generateNeuronUpdate.cc File Reference

```
#include "code_generator/generateNeuronUpdate.h"
#include <iostream>
#include <string>
#include <plog/Log.h>
#include "models.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

## 20.44 generateNeuronUpdate.h File Reference

### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

• void CodeGenerator::generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

## 20.45 generateRunner.cc File Reference

```
#include "code_generator/generateRunner.h"
#include <sstream>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/teeStream.h"
#include "code_generator/backendBase.h"
```

## 20.46 generateRunner.h File Reference

```
#include "code_generator/backendBase.h"
```

## Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

### **Functions**

 MemAlloc CodeGenerator::generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)

# 20.47 generateSupportCode.cc File Reference

```
#include "code_generator/generateSupportCode.h"
#include <string>
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
```

## 20.48 generateSupportCode.h File Reference

### Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

#### **Functions**

void CodeGenerator::generateSupportCode (CodeStream &os, const ModelSpecInternal &model)

## 20.49 generateSynapseUpdate.cc File Reference

```
#include "code_generator/generateSynapseUpdate.h"
#include <string>
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

## 20.50 generateSynapseUpdate.h File Reference

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

### **Functions**

• void CodeGenerator::generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

## 20.51 generator.cc File Reference

```
#include <fstream>
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "path.h"
#include "modelSpecInternal.h"
#include "code_generator/generateAll.h"
#include "code_generator/generateMakefile.h"
#include "code_generator/generateMSBuild.h"
#include "optimiser.h"
#include <MODEL>
```

## **Functions**

• int main (int argc, char \*argv[])

### **Variables**

Preferences GENN\_PREFERENCES

#### 20.51.1 Function Documentation

# 

#### **Parameters**

argc	number of arguments; expected to be 2
argv	Arguments; expected to contain the target directory for code generation.

### 20.51.2 Variable Documentation

### 20.51.2.1 GENN\_PREFERENCES

```
Preferences GENN_PREFERENCES
```

## 20.52 genn\_groups.py File Reference

### Classes

• class pygenn.genn\_groups.Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

• class pygenn.genn\_groups.NeuronGroup

Class representing a group of neurons.

• class pygenn.genn\_groups.SynapseGroup

Class representing synaptic connection between two groups of neurons.

• class pygenn.genn\_groups.CurrentSource

Class representing a current injection into a group of neurons.

## Namespaces

• pygenn.genn\_groups

### **Variables**

• pygenn.genn\_groups.xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

# 20.53 genn\_model.py File Reference

#### Classes

· class pygenn.genn\_model.GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

#### Namespaces

· pygenn.genn\_model

#### **Functions**

• def pygenn.genn model.init var (init var snippet, param space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

def pygenn.genn\_model.init\_connectivity (init\_sparse\_connect\_snippet, param\_space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def pygenn\_genn\_model.create\_custom\_neuron\_class (class\_name, param\_names=None, var\_name\_
 types=None, derived\_params=None, sim\_code=None, threshold\_condition\_code=None, reset\_code=None,
 support\_code=None, extra\_global\_params=None, additional\_input\_vars=None, is\_auto\_refractory\_
 required=None, custom\_body=None)

This helper function creates a custom NeuronModel class.

def pygenn.genn\_model.create\_custom\_postsynaptic\_class (class\_name, param\_names=None, var
 \_\_name\_types=None, derived\_params=None, decay\_code=None, apply\_input\_code=None, support\_
 code=None, custom body=None)

This helper function creates a custom PostsynapticModel class.

def pygenn\_genn\_model.create\_custom\_weight\_update\_class (class\_name, param\_names=None, var
 \_name\_types=None, pre\_var\_name\_types=None, post\_var\_name\_types=None, derived\_params=None,
 sim\_code=None, event\_code=None, learn\_post\_code=None, synapse\_dynamics\_code=None, event\_
 threshold\_condition\_code=None, pre\_spike\_code=None, post\_spike\_code=None, sim\_support\_code=None,
 learn\_post\_support\_code=None, synapse\_dynamics\_support\_code=None, extra\_global\_params=None,
 is\_pre\_spike\_time\_required=None, is\_post\_spike\_time\_required=None, custom\_body=None)

This helper function creates a custom WeightUpdateModel class.

def pygenn.genn\_model.create\_custom\_current\_source\_class (class\_name, param\_names=None, var\_
 name\_types=None, derived\_params=None, injection\_code=None, extra\_global\_params=None, custom\_
 body=None)

This helper function creates a custom NeuronModel class.

 def pygenn.genn\_model.create\_custom\_model\_class (class\_name, base, param\_names, var\_name\_types, derived params, custom body)

This helper function completes a custom model class creation.

def pygenn.genn\_model.create\_dpf\_class (dp\_func)

Helper function to create derived parameter function class.

def pygenn.genn\_model.create\_cmlf\_class (cml\_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

• def pygenn.genn\_model.create\_custom\_init\_var\_snippet\_class (class\_name, param\_names=None, derived\_params=None, var\_init\_code=None, custom\_body=None)

This helper function creates a custom InitVarSnippet class.

def pygenn.genn\_model.create\_custom\_sparse\_connect\_init\_snippet\_class (class\_name, param\_
 names=None, derived\_params=None, row\_build\_code=None, row\_build\_state\_vars=None, calc\_max\_
 row len func=None, calc max col len func=None, extra global params=None, custom body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

#### **Variables**

- pygenn.genn model.backend modules = OrderedDict()
- pygenn.genn\_model.m = import\_module(".genn\_wrapper." + b + "Backend", "pygenn")

### 20.54 gennExport.h File Reference

#### Macros

#define GENN EXPORT

### 20.54.1 Macro Definition Documentation

### 20.54.1.1 GENN\_EXPORT

#define GENN\_EXPORT

## 20.55 gennUtils.cc File Reference

```
#include "gennUtils.h"
#include <algorithm>
```

#### **Namespaces**

Utils

### **Functions**

• GENN\_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN\_EXPORT bool Utils::isInitRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

GENN\_EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

• GENN\_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

## 20.56 gennUtils.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
#include "models.h"
```

### Namespaces

Utils

#### **Functions**

• GENN\_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

• GENN\_EXPORT bool Utils::isInitRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

GENN EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN\_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

## 20.57 initSparseConnectivitySnippet.cc File Reference

```
#include "initSparseConnectivitySnippet.h"
```

#### **Functions**

- IMPLEMENT\_SNIPPET (InitSparseConnectivitySnippet::Uninitialised)
- IMPLEMENT\_SNIPPET (InitSparseConnectivitySnippet::OneToOne)
- IMPLEMENT\_SNIPPET (InitSparseConnectivitySnippet::FixedProbability)
- IMPLEMENT\_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse)

## 20.57.1 Function Documentation

## 20.58 initSparseConnectivitySnippet.h File Reference

```
#include <functional>
#include <vector>
#include <cassert>
#include <cmath>
#include "binomial.h"
#include "snippet.h"
```

### Classes

- class InitSparseConnectivitySnippet::Base
- class InitSparseConnectivitySnippet::Init
- · class InitSparseConnectivitySnippet::Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

· class InitSparseConnectivitySnippet::OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

- class InitSparseConnectivitySnippet::FixedProbabilityBase
- class InitSparseConnectivitySnippet::FixedProbability
- class InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

#### **Namespaces**

InitSparseConnectivitySnippet

Base class for all sparse connectivity initialisation snippets.

#### Macros

- #define SET\_ROW\_BUILD\_CODE(CODE) virtual std::string getRowBuildCode() const override{ return CO← DE; }
- #define SET\_ROW\_BUILD\_STATE\_VARS(...) virtual ParamValVec getRowBuildStateVars() const override{
   return VA ARGS ;}
- #define SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC(FUNC) virtual CalcMaxLengthFunc getCalcMaxRow
   LengthFunc() const override{ return FUNC; }

- #define SET\_MAX\_COL\_LENGTH(MAX\_COL\_LENGTH) virtual CalcMaxLengthFunc getCalcMaxCol
   LengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return
   MAX\_COL\_LENGTH; }; }
- #define SET\_EXTRA\_GLOBAL\_PARAMS(...) virtual VarVec getExtraGlobalParams() const override{ return \_\_VA\_ARGS\_\_;}

## 20.58.1 Macro Definition Documentation

# 20.58.1.1 SET\_CALC\_MAX\_COL\_LENGTH\_FUNC

```
\label{eq:func} \mbox{\#define SET\_CALC\_MAX\_COL\_LENGTH\_FUNC()} \\ FUNC \mbox{) virtual CalcMaxLengthFunc getCalcMaxColLengthFunc() const override{ return FUNC; }}
```

## 20.58.1.2 SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC

### 20.58.1.3 SET\_EXTRA\_GLOBAL\_PARAMS

### 20.58.1.4 SET\_MAX\_COL\_LENGTH

#### 20.58.1.5 SET\_MAX\_ROW\_LENGTH

# 20.58.1.6 SET\_ROW\_BUILD\_CODE

## 20.58.1.7 SET\_ROW\_BUILD\_STATE\_VARS

## 20.59 initVarSnippet.cc File Reference

```
#include "initVarSnippet.h"
```

#### **Functions**

- IMPLEMENT\_SNIPPET (InitVarSnippet::Uninitialised)
- IMPLEMENT\_SNIPPET (InitVarSnippet::Constant)
- IMPLEMENT\_SNIPPET (InitVarSnippet::Uniform)
- IMPLEMENT\_SNIPPET (InitVarSnippet::Normal)
- IMPLEMENT\_SNIPPET (InitVarSnippet::Exponential)
- IMPLEMENT\_SNIPPET (InitVarSnippet::Gamma)

#### 20.59.1 Function Documentation

```
20.59.1.1 IMPLEMENT_SNIPPET() [1/6]
IMPLEMENT_SNIPPET (
            InitVarSnippet::Uninitialised )
20.59.1.2 IMPLEMENT_SNIPPET() [2/6]
IMPLEMENT_SNIPPET (
             InitVarSnippet::Constant )
20.59.1.3 IMPLEMENT_SNIPPET() [3/6]
IMPLEMENT_SNIPPET (
             InitVarSnippet::Uniform )
20.59.1.4 IMPLEMENT_SNIPPET() [4/6]
IMPLEMENT_SNIPPET (
             InitVarSnippet::Normal )
20.59.1.5 IMPLEMENT_SNIPPET() [5/6]
IMPLEMENT_SNIPPET (
            InitVarSnippet::Exponential )
20.59.1.6 IMPLEMENT_SNIPPET() [6/6]
IMPLEMENT_SNIPPET (
             InitVarSnippet::Gamma )
20.60 initVarSnippet.h File Reference
```

#include "snippet.h"

#### Classes

- · class InitVarSnippet::Base
- · class InitVarSnippet::Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

class InitVarSnippet::Constant

Initialises variable to a constant value.

· class InitVarSnippet::Uniform

Initialises variable by sampling from the uniform distribution.

• class InitVarSnippet::Normal

Initialises variable by sampling from the normal distribution.

· class InitVarSnippet::Exponential

Initialises variable by sampling from the exponential distribution.

· class InitVarSnippet::Gamma

Initialises variable by sampling from the exponential distribution.

## Namespaces

InitVarSnippet

Base class for all value initialisation snippets.

#### Macros

• #define SET\_CODE(CODE) virtual std::string getCode() const override{ return CODE; }

### 20.60.1 Macro Definition Documentation

## 20.61 model\_preprocessor.py File Reference

### Classes

• class pygenn.model\_preprocessor.Variable

Class holding information about GeNN variables.

• class pygenn.model\_preprocessor.ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

## Namespaces

pygenn.model\_preprocessor

#### **Functions**

def pygenn.model\_preprocessor.prepare\_model (model, param\_space, var\_space, pre\_var\_space=None, post\_var\_space=None, model\_family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

• def pygenn.model\_preprocessor.prepare\_snippet (snippet, param\_space, snippet\_family)

Prepare a snippet by checking its validity and extracting information about parameters.

def pygenn.model\_preprocessor.is\_model\_valid (model, model\_family)

Check whether the model is valid, i.e is native or derived from model family. Custom.

• def pygenn.model\_preprocessor.param\_space\_to\_vals (model, param\_space)

Convert a param\_space dict to ParamValues.

def pygenn.model\_preprocessor.param\_space\_to\_val\_vec (model, param\_space)

Convert a param\_space dict to a std::vector<double>

def pygenn.model\_preprocessor.var\_space\_to\_vals (model, var\_space)

Convert a var\_space dict to VarValues.

def pygenn.model\_preprocessor.pre\_var\_space\_to\_vals (model, var\_space)

Convert a var\_space dict to PreVarValues.

def pygenn.model\_preprocessor.post\_var\_space\_to\_vals (model, var\_space)

Convert a var\_space dict to PostVarValues.

#### **Variables**

dictionary pygenn.model\_preprocessor.genn\_to\_numpy\_types

#### 20.62 models.h File Reference

```
#include <string>
#include <vector>
#include "snippet.h"
#include "initVarSnippet.h"
```

### Classes

- · class Models::VarInit
- class Models::VarInitContainerBase< NumVars >
- class Models::VarInitContainerBase< 0 >
- · class Models::Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

## Namespaces

Models

### Macros

- #define DECLARE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS)
- #define IMPLEMENT MODEL(TYPE) IMPLEMENT SNIPPET(TYPE)
- #define SET\_VARS(...) virtual VarVec getVars() const override{ return \_\_VA\_ARGS\_\_; }
- #define SET\_EXTRA\_GLOBAL\_PARAMS(...) virtual VarVec getExtraGlobalParams() const override{ return \_\_VA\_ARGS\_\_;}

#### 20.62.1 Macro Definition Documentation

```
20.62.1.1 DECLARE_MODEL
#define DECLARE_MODEL(
              TYPE,
              NUM_PARAMS,
              NUM_VARS )
Value:
DECLARE_SNIPPET(TYPE, NUM_PARAMS);
   typedef Models::VarInitContainerBase<NUM_VARS> VarValues;
   typedef Models::VarInitContainerBase<0> PreVarValues;
typedef Models::VarInitContainerBase<0> PostVarValues
20.62.1.2 IMPLEMENT_MODEL
#define IMPLEMENT_MODEL(
              TYPE ) IMPLEMENT_SNIPPET(TYPE)
20.62.1.3 SET_EXTRA_GLOBAL_PARAMS
#define SET_EXTRA_GLOBAL_PARAMS(
              ... ) virtual VarVec getExtraGlobalParams() const override{ return __VA_ARGS__;
20.62.1.4 SET_VARS
#define SET_VARS(
              ... ) virtual VarVec getVars() const override{ return __VA_ARGS__; }
20.63 modelSpec.cc File Reference
#include <algorithm>
#include <numeric>
#include <typeinfo>
#include <cstdio>
#include <cmath>
#include <cassert>
#include "modelSpec.h"
#include "code_generator/codeGenUtils.h"
```

## 20.64 modelSpec.h File Reference

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections.

```
#include <map>
#include <set>
```

```
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronGroupInternal.h"
#include "synapseGroupInternal.h"
#include "currentSourceInternal.h"
```

#### Classes

class ModelSpec

Object used for specifying a neuronal network model.

#### Macros

#define NO DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

### **Typedefs**

typedef ModelSpec NNmodel

#### **Enumerations**

enum FloatType { , GENN\_LONG\_DOUBLE }

Floating point precision to use for models.

• enum TimePrecision { TimePrecision::DEFAULT, TimePrecision::FLOAT, TimePrecision::DOUBLE }

Precision to use for variables which store time.

### **Functions**

• template<typename S >

Models::VarInit initVar (const typename S::ParamValues &params)

Initialise a variable using an initialisation snippet.

• template<typename S>

```
std::enable_if< std::is_same< typename S::ParamValues, Snippet::ValueBase< 0 > >::value, Models::

VarInit >::type initVar ()
```

Initialise a variable using an initialisation snippet with no parameters.

• Models::VarInit uninitialisedVar ()

Mark a variable as uninitialised.

• template<typename S >

InitSparseConnectivitySnippet::Init initConnectivity (const typename S::ParamValues &params)

Initialise connectivity using a sparse connectivity snippet.

template<typename S >

```
std::enable_if< std::is_same< typename S::ParamValues, Snippet::ValueBase< 0 > >::value, InitSparse ConnectivitySnippet::Init >::type initConnectivity ()
```

Initialise connectivity using a sparse connectivity snippet with no parameters.

InitSparseConnectivitySnippet::Init uninitialisedConnectivity ()

Mark a synapse group's sparse connectivity as uninitialised.

### 20.64.1 Detailed Description

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections

### 20.64.2 Macro Definition Documentation

## 20.64.2.1 NO\_DELAY

#define NO\_DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

## 20.64.3 Typedef Documentation

### 20.64.3.1 NNmodel

typedef ModelSpec NNmodel

### 20.64.4 Enumeration Type Documentation

## 20.64.4.1 FloatType

enum FloatType

Floating point precision to use for models.

#### Enumerator

GENN\_LONG\_DOUBLE

# 20.64.4.2 TimePrecision

enum TimePrecision [strong]

Precision to use for variables which store time.

#### Enumerator

DEFAULT	Time uses default model precision.
FLOAT	Time uses single precision - not suitable for long simulations.
DOUBLE	Time uses double precision - may reduce performance.

## 20.64.5 Function Documentation

### 20.64.5.1 initConnectivity() [1/2]

Initialise connectivity using a sparse connectivity snippet.

### **Template Parameters**

S type of sparse connectivity initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

#### **Parameters**

params parameters for snippet wrapped in S::ParamValues object.

#### Returns

InitSparseConnectivitySnippet::Init object for passing to ModelSpec::addSynapsePopulation

# **20.64.5.2** initConnectivity() [2/2]

```
template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Init←
SparseConnectivitySnippet::Init>::type initConnectivity ( ) [inline]
```

Initialise connectivity using a sparse connectivity snippet with no parameters.

### **Template Parameters**

S | type of sparse connectivity initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

## Returns

InitSparseConnectivitySnippet::Init object for passing to ModelSpec::addSynapsePopulation

```
20.64.5.3 initVar() [1/2]
```

Initialise a variable using an initialisation snippet.

### **Template Parameters**

S | type of variable initialisation snippet (derived from InitVarSnippet::Base).

#### **Parameters**

params parameters for snippet wrapped in S::ParamValues object.

#### Returns

Models::VarInit object for use within model's VarValues

```
20.64.5.4 initVar() [2/2]

template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Models←
::VarInit>::type initVar ( ) [inline]
```

Initialise a variable using an initialisation snippet with no parameters.

#### **Template Parameters**

S | type of variable initialisation snippet (derived from InitVarSnippet::Base).

#### Returns

Models::VarInit object for use within model's VarValues

### 20.64.5.5 uninitialisedConnectivity()

```
InitSparseConnectivitySnippet::Init uninitialisedConnectivity ( ) [inline]
```

Mark a synapse group's sparse connectivity as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the connectivity from host to device during initializeSparse function (and, if necessary generate any additional data structures it requires)

## 20.64.5.6 uninitialisedVar()

```
Models::VarInit uninitialisedVar ( ) [inline]
```

Mark a variable as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the variable from host to device during <code>initializeSparse</code> function

# 20.65 modelSpecInternal.h File Reference

```
#include "modelSpec.h"
```

### Classes

• class ModelSpecInternal

### 20.66 neuronGroup.cc File Reference

```
#include "neuronGroup.h"
#include <algorithm>
#include <cmath>
#include "currentSourceInternal.h"
#include "neuronGroupInternal.h"
```

```
#include "synapseGroupInternal.h"
#include "gennUtils.h"
```

## 20.67 neuronGroup.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronModels.h"
#include "variableMode.h"
```

### Classes

class NeuronGroup

## 20.68 neuronGroupInternal.h File Reference

```
#include "neuronGroup.h"
```

### Classes

· class NeuronGroupInternal

### 20.69 neuronModels.cc File Reference

```
#include "neuronModels.h"
```

#### **Functions**

- IMPLEMENT\_MODEL (NeuronModels::RulkovMap)
- IMPLEMENT\_MODEL (NeuronModels::Izhikevich)
- IMPLEMENT MODEL (NeuronModels::IzhikevichVariable)
- IMPLEMENT\_MODEL (NeuronModels::LIF)
- IMPLEMENT\_MODEL (NeuronModels::SpikeSource)
- IMPLEMENT\_MODEL (NeuronModels::SpikeSourceArray)
- IMPLEMENT MODEL (NeuronModels::Poisson)
- IMPLEMENT\_MODEL (NeuronModels::PoissonNew)
- IMPLEMENT\_MODEL (NeuronModels::TraubMiles)
- IMPLEMENT\_MODEL (NeuronModels::TraubMilesFast)
- IMPLEMENT MODEL (NeuronModels::TraubMilesAlt)
- IMPLEMENT\_MODEL (NeuronModels::TraubMilesNStep)

#### 20.69.1 Function Documentation

```
20.69.1.1 IMPLEMENT_MODEL() [1/12]
IMPLEMENT_MODEL (
            NeuronModels::RulkovMap )
20.69.1.2 IMPLEMENT_MODEL() [2/12]
IMPLEMENT_MODEL (
            NeuronModels::Izhikevich )
20.69.1.3 IMPLEMENT_MODEL() [3/12]
IMPLEMENT_MODEL (
            NeuronModels::IzhikevichVariable )
20.69.1.4 IMPLEMENT_MODEL() [4/12]
IMPLEMENT_MODEL (
            NeuronModels::LIF )
20.69.1.5 IMPLEMENT_MODEL() [5/12]
IMPLEMENT_MODEL (
            NeuronModels::SpikeSource )
20.69.1.6 IMPLEMENT_MODEL() [6/12]
IMPLEMENT_MODEL (
            NeuronModels::SpikeSourceArray )
20.69.1.7 IMPLEMENT_MODEL() [7/12]
IMPLEMENT_MODEL (
            NeuronModels::Poisson )
20.69.1.8 IMPLEMENT_MODEL() [8/12]
IMPLEMENT_MODEL (
            NeuronModels::PoissonNew )
20.69.1.9 IMPLEMENT_MODEL() [9/12]
IMPLEMENT_MODEL (
            NeuronModels::TraubMiles )
20.69.1.10 IMPLEMENT_MODEL() [10/12]
IMPLEMENT_MODEL (
```

```
NeuronModels::TraubMilesFast
20.69.1.11 IMPLEMENT_MODEL() [11/12]
IMPLEMENT_MODEL (
              NeuronModels::TraubMilesAlt )
20.69.1.12 IMPLEMENT_MODEL() [12/12]
IMPLEMENT_MODEL (
              NeuronModels::TraubMilesNStep )
20.70 neuronModels.h File Reference
#include <array>
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "models.h"
Classes
    · class NeuronModels::Base
         Base class for all neuron models.
    · class NeuronModels::RulkovMap
         Rulkov Map neuron.

    class NeuronModels::Izhikevich

         Izhikevich neuron with fixed parameters [1].

    class NeuronModels::IzhikevichVariable

         Izhikevich neuron with variable parameters [1].
    · class NeuronModels::LIF
    • class NeuronModels::SpikeSource
         Empty neuron which allows setting spikes from external sources.

    class NeuronModels::SpikeSourceArray

         Spike source array.

    class NeuronModels::Poisson

         Poisson neurons.
    · class NeuronModels::PoissonNew
         Poisson neurons.

    class NeuronModels::TraubMiles

         Hodgkin-Huxley neurons with Traub & Miles algorithm.
    · class NeuronModels::TraubMilesFast
         Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

    class NeuronModels::TraubMilesAlt

         Hodgkin-Huxley neurons with Traub & Miles algorithm.
    · class NeuronModels::TraubMilesNStep
```

Hodgkin-Huxley neurons with Traub & Miles algorithm.

### **Namespaces**

NeuronModels

#### **Macros**

- #define SET\_SIM\_CODE(SIM\_CODE) virtual std::string getSimCode() const override{ return SIM\_CODE; }
- #define SET\_THRESHOLD\_CONDITION\_CODE(THRESHOLD\_CONDITION\_CODE) virtual std::string getThresholdConditionCode() const override{ return THRESHOLD\_CONDITION\_CODE; }
- #define SET\_RESET\_CODE(RESET\_CODE) virtual std::string getResetCode() const override{ return RE
   SET\_CODE; }
- #define SET\_SUPPORT\_CODE(SUPPORT\_CODE) virtual std::string getSupportCode() const override{ return SUPPORT\_CODE; }
- #define SET\_ADDITIONAL\_INPUT\_VARS(...) virtual ParamValVec getAdditionalInputVars() const override{
   return VA ARGS ;}

#### 20.70.1 Macro Definition Documentation

```
20.70.1.1 SET_ADDITIONAL_INPUT_VARS
```

#### 20.70.1.2 SET\_NEEDS\_AUTO\_REFRACTORY

### 20.70.1.3 SET\_RESET\_CODE

```
#define SET_RESET_CODE( RESET\_CODE\ ) \ \ virtual\ \ std::string\ getResetCode() \ \ const\ \ override\{\ return\ RESET\_CO\leftarrow\ DE;\ \}
```

## 20.70.1.4 SET\_SIM\_CODE

### 20.70.1.5 SET\_SUPPORT\_CODE

### 20.70.1.6 SET\_THRESHOLD\_CONDITION\_CODE

## 20.71 optimiser.cc File Reference

```
#include "optimiser.h"
#include <algorithm>
#include <iostream>
#include <map>
#include <numeric>
#include <cstdlib>
#include <cuda.h>
#include <cuda_runtime.h>
#include <plog/Log.h>
#include "path.h"
#include "modelSpecInternal.h"
#include "code_generator/generateAll.h"
#include "utils.h"
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- CodeGenerator::CUDA::Optimiser

#### **Functions**

 BACKEND\_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

## 20.72 optimiser.cc File Reference

```
#include "optimiser.h"
#include "modelSpecInternal.h"
```

### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- · CodeGenerator::SingleThreadedCPU
- CodeGenerator::SingleThreadedCPU::Optimiser

#### **Functions**

 BACKEND\_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

## 20.73 optimiser.h File Reference

```
#include "backendExport.h"
#include "backend.h"
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- CodeGenerator::CUDA::Optimiser

### **Functions**

• BACKEND\_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

# 20.74 optimiser.h File Reference

```
#include "backendExport.h"
#include "backend.h"
```

## Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::SingleThreadedCPU
- · CodeGenerator::SingleThreadedCPU::Optimiser

#### **Functions**

• BACKEND\_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, int localHostID, const Preferences &preferences)

## 20.75 postsynapticModels.cc File Reference

```
#include "postsynapticModels.h"
```

## **Functions**

- IMPLEMENT\_MODEL (PostsynapticModels::ExpCurr)
- IMPLEMENT\_MODEL (PostsynapticModels::ExpCond)
- IMPLEMENT\_MODEL (PostsynapticModels::DeltaCurr)

#### 20.75.1 Function Documentation

### 20.76 postsynapticModels.h File Reference

```
#include <cmath>
#include "models.h"
```

#### Classes

· class PostsynapticModels::Base

Base class for all postsynaptic models.

• class PostsynapticModels::ExpCurr

Exponential decay with synaptic input treated as a current value.

· class PostsynapticModels::ExpCond

Exponential decay with synaptic input treated as a conductance value.

class PostsynapticModels::DeltaCurr

Simple delta current synapse.

#### Namespaces

PostsynapticModels

# Macros

- #define SET\_DECAY\_CODE(DECAY\_CODE) virtual std::string getDecayCode() const override{ return DE
   CAY\_CODE; }
- #define SET\_CURRENT\_CONVERTER\_CODE(CURRENT\_CONVERTER\_CODE) virtual std::string get
   ApplyInputCode() const override{ return "\$(Isyn) += " CURRENT\_CONVERTER\_CODE ";"; }
- #define SET\_APPLY\_INPUT\_CODE(APPLY\_INPUT\_CODE) virtual std::string getApplyInputCode() const override{ return APPLY\_INPUT\_CODE; }
- #define SET\_SUPPORT\_CODE(SUPPORT\_CODE) virtual std::string getSupportCode() const override{ return SUPPORT\_CODE; }

#### 20.76.1 Macro Definition Documentation

### 20.76.1.1 SET\_APPLY\_INPUT\_CODE

# 20.76.1.2 SET\_CURRENT\_CONVERTER\_CODE

#### 20.76.1.3 SET\_DECAY\_CODE

```
#define SET_DECAY_CODE ( {\it DECAY\_CODE}~)~ {\it virtual std::string getDecayCode()}~ {\it const override} \{~ {\it return DECAY\_CO} \leftarrow {\it DE;}~ \}
```

#### 20.76.1.4 SET\_SUPPORT\_CODE

# 20.77 snippet.h File Reference

```
#include <algorithm>
#include <functional>
#include <string>
#include <vector>
#include <cassert>
#include "gennExport.h"
```

# Classes

- class Snippet::ValueBase< NumVars >
- class Snippet::ValueBase< 0 >
- class Snippet::Base

Base class for all code snippets.

struct Snippet::Base::Var

A variable has a name and a type.

- struct Snippet::Base::ParamVal
- struct Snippet::Base::DerivedParam

A derived parameter has a name and a function for obtaining its value.

 $\bullet \ \ {\it class Snippet::Init}{< SnippetBase} >$ 

#### **Namespaces**

Snippet

#### Macros

- #define DECLARE\_SNIPPET(TYPE, NUM\_PARAMS)
- #define IMPLEMENT SNIPPET(TYPE) TYPE \*TYPE::s Instance = NULL
- #define SET\_PARAM\_NAMES(...) virtual StringVec getParamNames() const override{ return \_\_VA\_ARGS←
   ;}
- #define SET\_DERIVED\_PARAMS(...) virtual DerivedParamVec getDerivedParams() const override{ return \_\_VA\_ARGS\_\_;}

#### 20.77.1 Macro Definition Documentation

#### 20.77.1.1 DECLARE\_SNIPPET

#### Value:

```
private:
    GENN_EXPORT static TYPE *s_Instance;
public:
    static const TYPE *getInstance()
    {
        if(s_Instance == NULL)
        {
            s_Instance = new TYPE;
        }
        return s_Instance;
    }
    typedef Snippet::ValueBase<NUM_PARAMS> ParamValues
```

#### 20.77.1.2 IMPLEMENT\_SNIPPET

### 20.77.1.3 SET\_DERIVED\_PARAMS

#### 20.77.1.4 SET\_PARAM\_NAMES

# 20.78 substitutions.h File Reference

```
#include <map>
#include <stdexcept>
#include <string>
#include <cassert>
#include "codeGenUtils.h"
```

#### Classes

· class CodeGenerator::Substitutions

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

# 20.79 synapseGroup.cc File Reference

```
#include "synapseGroup.h"
#include <algorithm>
#include <cmath>
#include <iostream>
#include "neuronGroupInternal.h"
#include "gennUtils.h"
```

# 20.80 synapseGroup.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "initSparseConnectivitySnippet.h"
#include "postsynapticModels.h"
#include "weightUpdateModels.h"
#include "synapseMatrixType.h"
#include "variableMode.h"
```

# Classes

· class SynapseGroup

# 20.81 synapseGroupInternal.h File Reference

```
#include "synapseGroup.h"
```

#### Classes

· class SynapseGroupInternal

# 20.82 synapseMatrixType.h File Reference

# Enumerations

 enum SynapseMatrixConnectivity:: unsigned int { SynapseMatrixConnectivity::DENSE = (1 << 0), SynapseMatrixConnectivity::BITMASK = (1 << 1), SynapseMatrixConnectivity::SPARSE = (1 << 2) }</li>

- < Flags defining differnet types of synaptic matrix connectivity
- enum SynapseMatrixWeight:: unsigned int { SynapseMatrixWeight::GLOBAL = (1 << 5), SynapseMatrix
   Weight::INDIVIDUAL = (1 << 6), SynapseMatrixWeight::INDIVIDUAL\_PSM = (1 << 7) }</li>
- enum SynapseMatrixType::unsigned int {
   SynapseMatrixType::DENSE\_GLOBALG = static\_cast<unsigned int>(SynapseMatrixTonnectivity::DE\to NSE) | static\_cast<unsigned int>(SynapseMatrixWeight::GLOBAL), SynapseMatrixType::DENSE\_GL\to OBALG\_INDIVIDUAL\_PSM = static\_cast<unsigned int>(SynapseMatrixConnectivity::DENSE) | static\_\to cast<unsigned int>(SynapseMatrixWeight::GLOBAL) | static\_cast<unsigned int>(SynapseMatrixWeight\to ::INDIVIDUAL\_PSM), SynapseMatrixType::DENSE\_INDIVIDUALG = static\_cast<unsigned int>(Synapse\to MatrixConnectivity::DENSE) | static\_cast<unsigned int>(SynapseMatrixWeight::INDIVIDUAL) | static\to cast<unsigned int>(SynapseMatrixType::BITMASK\_GL\to OBALG = static\_cast<unsigned int>(SynapseMatrixConnectivity::BITMASK) | static\_cast<unsigned int>(SynapseMatrixWeight::GLOBAL),

SynapseMatrixType::BITMASK\_GLOBALG\_INDIVIDUAL\_PSM = static\_cast<unsigned int>(Synapse MatrixConnectivity::BITMASK) | static\_cast<unsigned int>(SynapseMatrixWeight::GLOBAL) | static cast<unsigned int>(SynapseMatrixType::SPARSE\_GL OBALG = static\_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static\_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static\_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE\_GLOBALG\_INDIVIDUAL\_PSM = static\_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static\_cast<unsigned int>(Synapse MatrixWeight::INDIVIDUAL\_PSM), Synapse MatrixWeight::INDIVIDUAL\_PSM), Synapse MatrixType::SPARSE\_INDIVIDUALG = static\_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE) | stat

#### **Functions**

- bool operator& (SynapseMatrixType type, SynapseMatrixConnectivity connType)
- bool operator& (SynapseMatrixType type, SynapseMatrixWeight weightType)

#### 20.82.1 Enumeration Type Documentation

#### 20.82.1.1 SynapseMatrixConnectivity

 $\verb"enum SynapseMatrixConnectivity: unsigned int [strong]"$ 

< Flags defining differnet types of synaptic matrix connectivity

#### Enumerator

DENSE	
BITMASK	
SPARSE	

#### 20.82.1.2 SynapseMatrixType

enum SynapseMatrixType : unsigned int [strong]

#### Enumerator

DENSE_GLOBALG	
DENSE_GLOBALG_INDIVIDUAL_PSM	
DENSE_INDIVIDUALG	
BITMASK_GLOBALG	

#### Enumerator

BITMASK_GLOBALG_INDIVIDUAL_PSM	
SPARSE_GLOBALG	
SPARSE_GLOBALG_INDIVIDUAL_PSM	
SPARSE_INDIVIDUALG	

# 20.82.1.3 SynapseMatrixWeight

```
enum SynapseMatrixWeight : unsigned int [strong]
```

#### Enumerator

GLOBAL	
INDIVIDUAL	
INDIVIDUAL_PSM	

#### 20.82.2 Function Documentation

# 20.83 teeStream.h File Reference

```
#include <ostream>
#include <streambuf>
#include <vector>
```

# Classes

- class CodeGenerator::TeeBuf
- class CodeGenerator::TeeStream

# Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

# 20.84 utils.h File Reference

```
#include <iostream>
#include <plog/Log.h>
```

#### **Namespaces**

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- · CodeGenerator::CUDA::Utils

#### Macros

- #define CHECK\_CU\_ERRORS(call) call
- #define CHECK\_CUDA\_ERRORS(call)

#### **Functions**

- size\_t CodeGenerator::CUDA::Utils::ceilDivide (size\_t numerator, size\_t denominator)
- size\_t CodeGenerator::CUDA::Utils::padSize (size\_t size, size\_t blockSize)

#### 20.84.1 Macro Definition Documentation

# 20.84.1.1 CHECK\_CU\_ERRORS

```
\begin{tabular}{ll} \# define & CHECK\_CU\_ERRORS ( \\ & call \end{tabular} ) & call \end{tabular}
```

### 20.84.1.2 CHECK\_CUDA\_ERRORS

```
\begin{tabular}{ll} \# define \ CHECK\_CUDA\_ERRORS ( \\ call \ ) \end{tabular}
```

### Value:

```
cudaError_t error = call;
if (error != cudaSuccess) {
    LOGE << __FILE__ << ": " << __LINE__ << ": cuda runtime error " << error << ": " << cudaGetErrorString(error); \
    exit(EXIT_FAILURE);
}</pre>
```

# 20.85 variableMode.h File Reference

```
#include <cstdint>
```

#### **Enumerations**

```
    enum VarLocation::uint8_t {
        VarLocation::HOST = (1 << 0), VarLocation::DEVICE = (1 << 1), VarLocation::ZERO_COPY = (1 << 2),
        VarLocation::HOST_DEVICE = HOST | DEVICE,
        VarLocation::HOST_DEVICE_ZERO_COPY = HOST | DEVICE | ZERO_COPY }
        < Flags defining which memory space variables should be allocated in</li>
```

#### **Functions**

bool operator& (VarLocation locA, VarLocation locB)

# 20.85.1 Enumeration Type Documentation

#### 20.85.1.1 VarLocation

```
enum VarLocation : uint8_t [strong]
```

< Flags defining which memory space variables should be allocated in

#### Enumerator

HOST	
DEVICE	
ZERO_COPY	
HOST_DEVICE	
HOST_DEVICE_ZERO_COPY	

### 20.85.2 Function Documentation

# 20.85.2.1 operator&()

# 20.86 weightUpdateModels.cc File Reference

```
#include "weightUpdateModels.h"
```

# **Functions**

- IMPLEMENT\_MODEL (WeightUpdateModels::StaticPulse)
- IMPLEMENT\_MODEL (WeightUpdateModels::StaticPulseDendriticDelay)
- IMPLEMENT\_MODEL (WeightUpdateModels::StaticGraded)
- IMPLEMENT\_MODEL (WeightUpdateModels::PiecewiseSTDP)

#### 20.86.1 Function Documentation

# Classes

• class WeightUpdateModels::Base

#include "models.h"

Base class for all weight update models.

class WeightUpdateModels::StaticPulse

Pulse-coupled, static synapse.

class WeightUpdateModels::StaticPulseDendriticDelay

Pulse-coupled, static synapse with heterogenous dendritic delays.

• class WeightUpdateModels::StaticGraded

Graded-potential, static synapse.

· class WeightUpdateModels::PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

# Namespaces

· WeightUpdateModels

#### **Macros**

- #define DECLARE\_WEIGHT\_UPDATE\_MODEL(TYPE, NUM\_PARAMS, NUM\_VARS, NUM\_PRE\_VARS, NUM\_POST\_VARS)
- #define SET\_SIM\_CODE(SIM\_CODE) virtual std::string getSimCode() const override{ return SIM\_CODE; }

- #define SET\_EVENT\_CODE(EVENT\_CODE) virtual std::string getEventCode() const override{ return EV
   ENT\_CODE; }
- #define SET\_LEARN\_POST\_CODE(LEARN\_POST\_CODE) virtual std::string getLearnPostCode() const override{ return LEARN\_POST\_CODE; }
- #define SET\_SYNAPSE\_DYNAMICS\_CODE(SYNAPSE\_DYNAMICS\_CODE) virtual std::string get
   SynapseDynamicsCode() const override{ return SYNAPSE\_DYNAMICS\_CODE; }
- #define SET\_EVENT\_THRESHOLD\_CONDITION\_CODE(EVENT\_THRESHOLD\_CONDITION\_CODE) virtual std::string getEventThresholdConditionCode() const override{ return EVENT\_THRESHOLD\_CONDITI
   ON\_CODE; }
- #define SET\_SIM\_SUPPORT\_CODE(SIM\_SUPPORT\_CODE) virtual std::string getSimSupportCode() const override{ return SIM\_SUPPORT\_CODE; }
- #define SET\_LEARN\_POST\_SUPPORT\_CODE(LEARN\_POST\_SUPPORT\_CODE) virtual std::string get
   LearnPostSupportCode() const override{ return LEARN\_POST\_SUPPORT\_CODE; }
- #define SET\_SYNAPSE\_DYNAMICS\_SUPPORT\_CODE(SYNAPSE\_DYNAMICS\_SUPPORT\_CODE) virtual std::string getSynapseDynamicsSuppportCode() const override{ return SYNAPSE\_DYNAMICS\_SUPPORT\_CODE;}
- #define SET\_PRE\_SPIKE\_CODE(PRE\_SPIKE\_CODE) virtual std::string getPreSpikeCode() const override{
   return PRE\_SPIKE\_CODE;}
- #define SET\_POST\_SPIKE\_CODE(POST\_SPIKE\_CODE) virtual std::string getPostSpikeCode() const override{ return POST\_SPIKE\_CODE; }
- #define SET\_PRE\_VARS(...) virtual VarVec getPreVars() const override{ return \_\_VA\_ARGS\_\_; }
- #define SET\_POST\_VARS(...) virtual VarVec getPostVars() const override{ return \_\_VA\_ARGS\_\_; }
- #define SET\_NEEDS\_PRE\_SPIKE\_TIME(PRE\_SPIKE\_TIME\_REQUIRED) virtual bool isPreSpikeTime ← Required() const override{ return PRE\_SPIKE\_TIME\_REQUIRED; }

### 20.87.1 Macro Definition Documentation

#### 20.87.1.1 DECLARE\_WEIGHT\_UPDATE\_MODEL

#### Value:

```
DECLARE_SNIPPET(TYPE, NUM_PARAMS);

typedef Models::VarInitContainerBase<NUM_VARS> VarValues;

typedef Models::VarInitContainerBase<NUM_PRE_VARS>
    PreVarValues;

typedef Models::VarInitContainerBase<NUM_POST_VARS>
    PostVarValues
```

#### 20.87.1.2 SET\_EVENT\_CODE

```
#define SET_EVENT_CODE(  {\it EVENT\_CODE} \ ) \ \ {\it virtual std::string getEventCode()} \ \ {\it const override} \{ \ \ {\it return EVENT\_CO} \leftarrow {\it DE; } \}
```

### 20.87.1.3 SET\_EVENT\_THRESHOLD\_CONDITION\_CODE

#define SET\_EVENT\_THRESHOLD\_CONDITION\_CODE(

EVENT\_THRESHOLD\_CONDITION\_CODE) virtual std::string getEventThresholdCondition←

Code() const override{ return EVENT\_THRESHOLD\_CONDITION\_CODE; }

# 20.87.1.4 SET\_LEARN\_POST\_CODE

#### 20.87.1.5 SET LEARN POST SUPPORT CODE

#### 20.87.1.6 SET\_NEEDS\_POST\_SPIKE\_TIME

### 20.87.1.7 SET\_NEEDS\_PRE\_SPIKE\_TIME

# 20.87.1.8 SET\_POST\_SPIKE\_CODE

# 20.87.1.9 SET\_POST\_VARS

# 20.87.1.10 SET\_PRE\_SPIKE\_CODE

#define SET\_PRE\_SPIKE\_CODE (  $PRE\_SPIKE\_CODE \ ) \ \ virtual \ \ std::string \ getPreSpikeCode() \ \ const \ \ override \{ \ return \ P \leftarrow RE\_SPIKE\_CODE; \}$ 

# 20.87.1.11 SET\_PRE\_VARS

# 20.87.1.12 SET\_SIM\_CODE

# 20.87.1.13 SET\_SIM\_SUPPORT\_CODE

# 20.87.1.14 SET\_SYNAPSE\_DYNAMICS\_CODE

#### 20.87.1.15 SET\_SYNAPSE\_DYNAMICS\_SUPPORT\_CODE

REFERENCES 337

# References

[1] Eugene M Izhikevich. Simple model of spiking neurons. *IEEE Transactions on neural networks*, 14(6):1569–1572, 2003. 7, 8, 9, 60, 77, 180, 181, 183, 184, 321

- [2] Abigail Morrison, Markus Diesmann, and Wulfram Gerstner. Phenomenological models of synaptic plasticity based on spike timing. *Biological Cybernetics*, 98:459–478, 2008. 32
- [3] T. Nowotny. Parallel implementation of a spiking neuronal network model of unsupervised olfactory learning on NVidia CUDA. In P. Sobrevilla, editor, *IEEE World Congress on Computational Intelligence*, pages 3238–3245, Barcelona, 2010. IEEE. 32
- [4] Thomas Nowotny, Ramón Huerta, Henry DI Abarbanel, and Mikhail I Rabinovich. Self-organization in the olfactory system: one shot odor recognition in insects. *Biological cybernetics*, 93(6):436–446, 2005. 11, 233
- [5] Nikolai F Rulkov. Modeling of spiking-bursting neural behavior using two-dimensional map. *Physical Review E*, 65(4):041922, 2002. 233
- [6] Marcel Stimberg, Dan F. M. Goodman, and Thomas Nowotny. Brian2genn: a system for accelerating a large variety of spiking neural networks with graphics hardware. *bioRxiv*, 2018. 14
- [7] R. D. Traub and R. Miles. Neural Networks of the Hippocampus. Cambridge University Press, New York, 1991. 11, 12, 272

# Index

init	NeuronGroup, 210
pygenn::genn_groups::CurrentSource, 144	addSpkEventCondition
pygenn::genn_groups::Group, 178	NeuronGroup, 210
pygenn::genn_groups::NeuronGroup, 205	addSynapsePopulation
pygenn::genn_groups::SynapseGroup, 250	ModelSpec, 195–197
pygenn::genn_model::GeNNModel, 170	addType
pygenn::model_preprocessor::ExtraGlobal↔	CodeGenerator::BackendBase, 117
Variable, 159	addVarSubstitution
pygenn::model_preprocessor::Variable, 285	CodeGenerator::Substitutions, 247
initpy, 290	apply
~BackendBase	CodeGenerator::Substitutions, 248
CodeGenerator::BackendBase, 117	
~Base	BACKEND_EXPORT
Snippet::Base, 135	backendExport.h, 293
~ModelSpec	Backend
ModelSpec, 193	CodeGenerator::CUDA::Backend, 94
~Scope	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::CodeStream::Scope, 236	105
00_MainPage.dox, 289	backend.cc, 290
01_Installation.dox, 290	backend.h, 291, 292
02_Quickstart.dox, 290	backend_modules
03_Examples.dox, 290	pygenn::genn_model, 86
05 SpineML.dox, 290	BackendBase
06_Brian2GeNN.dox, 290	CodeGenerator::BackendBase, 117
07 PyGeNN.dox, 290	backendBase.cc, 292
09 ReleaseNotes.dox, 290	TYPE, 292
<del>-</del>	backendBase.h, 293
10_UserManual.dox, 290	backendExport.h, 293
11_Tutorial.dox, 290	BACKEND_EXPORT, 293
12_Tutorial.dox, 290	binomial.cc, 293
13_UserGuide.dox, 290	binomialInverseCDF, 294
14_Credits.dox, 290	binomial.h, 294
	binomialInverseCDF, 294
add_current_source	binomialInverseCDF
pygenn::genn_model::GeNNModel, 170	binomial.cc, 294
add_extra_global_param	binomial.h, 294
pygenn::genn_groups::CurrentSource, 144	BlockSizeSelect
pygenn::genn_groups::NeuronGroup, 205	CodeGenerator::CUDA, 73
pygenn::genn_groups::SynapseGroup, 250	blockSizeSelectMethod
add_neuron_population	CodeGenerator::CUDA::Preferences, 230
pygenn::genn_model::GeNNModel, 171	build
add_synapse_population	pygenn::genn_model::GeNNModel, 172
pygenn::genn_model::GeNNModel, 171	
add_to	CHECK_CU_ERRORS
pygenn::genn_groups::CurrentSource, 144	utils.h, 331
pygenn::genn_groups::NeuronGroup, 205	CHECK_CUDA_ERRORS
pygenn::genn_groups::SynapseGroup, 251	utils.h, 331
addCurrentSource	CalcMaxLengthFunc
ModelSpec, 193	InitSparseConnectivitySnippet::Base, 128
addFuncSubstitution	CB
CodeGenerator::Substitutions, 247	CodeGenerator::CodeStream::CB, 140
addInSyn	ceilDivide
NeuronGroup, 210	CodeGenerator::CUDA::Utils, 74
addNeuronPopulation	checkNumDelaySlots
ModelSpec, 194, 195	NeuronGroup, 210
addOutSyn	checkUnreplacedVariables

CodeGenerator, 67	genPopVariableInit, 122
codeGenUtils.cc, 294	genPopulationRNG, 122
MathsFunc, 295	genRunnerPreamble, 122
codeGenUtils.h, 295	genScalar, 122
CodeGenerator, 64	genStepTimeFinalisePreamble, 123
checkUnreplacedVariables, 67	genSynapseUpdate, 123
DerivedParamNameIterCtx, 66	genSynapseVariableRowInit, 123
ensureFtype, 67	genTimer, 124
functionSubstitute, 67	genVariableAllocation, 124
generateAll, 67	genVariableDefinition, 124
generateInit, 67	genVariableFree, 124
generateMPI, 68	genVariableImplementation, 124
generateMSBuild, 68	genVariableInit, 125
generateMakefile, 67	genVariablePull, 125
generateNeuronUpdate, 68	genVariablePush, 125
generateRunner, 68	genVariablePushPull, 125
generateSupportCode, 68	getDeviceMemoryBytes, 125
generateSynapseUpdate, 68	getLocalHostID, 126
name_substitutions, 69	getSize, 126
neuronSubstitutionsInSynapticCode, 69	getVarPrefix, 126
operator<<, 70	GroupHandler, 116
ParamVallterCtx, 66	Handler, 116
postNeuronSubstitutionsInSynapticCode, 70	isGlobalRNGRequired, 126
preNeuronSubstitutionsInSynapticCode, 70	isPostsynapticRemapRequired, 126
regexFuncSubstitute, 71	isSynRemapRequired, 126
regexVarSubstitute, 71	NeuronGroupHandler, 116
substitute, 71	NeuronGroupSimHandler, 116
value_substitutions, 71, 72	SynapseGroupHandler, 117
VarNameIterCtx, 66	CodeGenerator::CUDA::Backend, 91
writePreciseString, 72	Backend, 94
CodeGenerator::BackendBase, 114	
	genAllocateMemPreamble, 94
~BackendBase, 117	genCurrentSpikeLikeEventPull, 94
addType, 117	genCurrentSpikeLikeEventPush, 94
BackendBase, 117	genCurrentTrueSpikePull, 94
genAllocateMemPreamble, 117	genCurrentTrueSpikePush, 94
genArray, 117	genDefinitionsInternalPreamble, 95
genCurrentSpikeLikeEventPull, 118	genDefinitionsPreamble, 95
genCurrentSpikeLikeEventPush, 118	genExtraGlobalParamAllocation, 95
genCurrentTrueSpikePull, 118	genExtraGlobalParamDefinition, 95
genCurrentTrueSpikePush, 118	genExtraGlobalParamImplementation, 95
genDefinitionsInternalPreamble, 118	genExtraGlobalParamPull, 96
genDefinitionsPreamble, 118	genExtraGlobalParamPush, 96
genExtraGlobalParamAllocation, 119	genGlobalRNG, 96
genExtraGlobalParamDefinition, 119	genInit, 96
genExtraGlobalParamImplementation, 119	genMSBuildCompileModule, 97
genExtraGlobalParamPull, 119	genMSBuildConfigProperties, 97
genExtraGlobalParamPush, 119	genMSBuildImportProps, 97
genGlobalRNG, 120	genMSBuildImportTarget, 97
genInit, 120	genMSBuildItemDefinitions, 98
genMSBuildCompileModule, 121	genMakefileCompileRule, 96
genMSBuildConfigProperties, 121	genMakefileLinkRule, 97
genMSBuildImportProps, 121	genMakefilePreamble, 97
genMSBuildImportTarget, 121	genNeuronUpdate, 98
genMSBuildItemDefinitions, 121	genPopVariableInit, 98
genMakefileCompileRule, 120	genPopulationRNG, 98
genMakefileLinkRule, 120	genRunnerPreamble, 99
genMakefilePreamble, 120	genStepTimeFinalisePreamble, 99
•	
genNeuronUpdate, 121	genSynapseUpdate, 99

genSynapseVariableRowInit, 100	singlePrecisionTemplate, 165
genTimer, 100	CodeGenerator::MemAlloc, 188
genVariableAllocation, 100	device, 188
genVariableDefinition, 100	getDeviceBytes, 188
genVariableFree, 100	getDeviceMBytes, 188
genVariableImplementation, 101	getHostBytes, 188
genVariableInit, 101	getHostMBytes, 189
genVariablePull, 101	getZeroCopyBytes, 189
genVariablePush, 101	getZeroCopyMBytes, 189
getChosenCUDADevice, 101	host, 189
getChosenDeviceID, 101	operator+=, 189
getDeviceMemoryBytes, 102	zero, 189
getNVCCFlags, 102	zeroCopy, 189
getNumPostsynapticUpdateThreads, 102	CodeGenerator::NameIterCtx
getNumPresynapticUpdateThreads, 102	container, 203
getNumSynapseDynamicsThreads, 102	nameBegin, 203
getRuntimeVersion, 102	nameEnd, 204
getVarPrefix, 102	Namelter, 203
isGlobalRNGRequired, 102	NamelterCtx, 203
isPostsynapticRemapRequired, 103	CodeGenerator::NameIterCtx < Container >, 203
isSynRemapRequired, 103	CodeGenerator::PreferencesBase, 231
KernelNames, 103	debugCode, 232
CodeGenerator::CUDA::Optimiser, 74	logLevel, 232
createBackend, 74	optimizeCode, 232
CodeGenerator::CUDA::Preferences, 229	userCxxFlagsGNU, 232
blockSizeSelectMethod, 230	userNvccFlagsGNU, 232
deviceSelectMethod, 230	CodeGenerator::SingleThreadedCPU::Backend, 103
manualBlockSizes, 230	Backend, 105
manualDeviceID, 230	genAllocateMemPreamble, 105
Preferences, 230	genCurrentSpikeLikeEventPull, 105
showPtxInfo, 230	genCurrentSpikeLikeEventPush, 106
userNvccFlags, 230	genCurrentTrueSpikePull, 106
CodeGenerator::CUDA::Utils, 74	genCurrentTrueSpikePush, 106
ceilDivide, 74	genDefinitionsInternalPreamble, 106
padSize, 75	genDefinitionsPreamble, 106
CodeGenerator::CUDA, 72	genExtraGlobalParamAllocation, 106
BlockSizeSelect, 73	genExtraGlobalParamDefinition, 107
DeviceSelect, 73	genExtraGlobalParamImplementation, 107
Kernel, 74	genExtraGlobalParamPull, 107
KernelBlockSize, 73	genExtraGlobalParamPush, 107
CodeGenerator::CodeStream, 140	genGlobalRNG, 107
CodeStream, 141	genlnit, 108
operator<<, 141	genMSBuildCompileModule, 108
setSink, 141	genMSBuildConfigProperties, 109
CodeGenerator::CodeStream::CB, 139	genMSBuildImportProps, 109
CB, 140	genMSBuildImportTarget, 109
Level, 140	genMSBuildItemDefinitions, 109
CodeGenerator::CodeStream::OB, 217	genMakefileCompileRule, 108
Level, 218	genMakefileLinkRule, 108
OB, 218	genMakefilePreamble, 108
CodeGenerator::CodeStream::Scope, 235	genNeuronUpdate, 109
~Scope, 236	genPopVariableInit, 110
Scope, 236	genPopulationRNG, 110
CodeGenerator::FunctionTemplate, 164	genRunnerPreamble, 110
doublePrecisionTemplate, 165	genStepTimeFinalisePreamble, 110
genericName, 165	genSynapseUpdate, 110
numArguments, 165	genSynapseVariableRowInit, 111
operator=, 165	genTimer, 111

genVariableAllocation, 111	create_custom_weight_update_class
genVariableDefinition, 112	pygenn::genn_model, 84
genVariableFree, 112	create_dpf_class
genVariableImplementation, 112	pygenn::genn_model, 85
genVariableInit, 112	createBackend
genVariablePull, 112	CodeGenerator::CUDA::Optimiser, 74
genVariablePush, 113	CodeGenerator::SingleThreadedCPU::Optimiser,
getDeviceMemoryBytes, 113	75
getVarPrefix, 113	current_source_model
isGlobalRNGRequired, 113	pygenn::genn_groups::CurrentSource, 146
isPostsynapticRemapRequired, 113	current_sources
isSynRemapRequired, 113	pygenn::genn_model::GeNNModel, 176
CodeGenerator::SingleThreadedCPU::Optimiser, 75	current_spikes
createBackend, 75	pygenn::genn_groups::NeuronGroup, 206
CodeGenerator::SingleThreadedCPU::Preferences, 231	CurrentSource, 146
CodeGenerator::SingleThreadedCPU, 75	CurrentSource, 147
CodeGenerator::StructNameConstIter	getCurrentSourceModel, 147
operator*, 246	getDerivedParams, 147
	getExtraGlobalParamLocation, 147, 148
operator->, 246	getName, 148
StructNameConstiter, 246	getParams, 148
CodeGenerator::StructNameConstIter< Baselter >,	getVarInitialisers, 148
246	getVarLocation, 148
CodeGenerator::Substitutions, 247	initDerivedParams, 148
addFuncSubstitution, 247	isInitRNGRequired, 148
addVarSubstitution, 247	isSimRNGRequired, 148
apply, 248	setExtraGlobalParamLocation, 149
getVarSubstitution, 248	setVarLocation, 149
hasVarSubstitution, 248	
operator[], 248	currentSource.cc, 298
Substitutions, 247	currentSource.h, 298
CodeGenerator::TeeBuf, 270	CurrentSourceInternal, 149
TeeBuf, 270	CurrentSourceInternal, 149
CodeGenerator::TeeStream, 271	currentSourceInternal.h, 298
TeeStream, 271	CurrentSourceModels, 75
CodeStream	currentSourceModels.cc, 298
CodeGenerator::CodeStream, 141	IMPLEMENT_MODEL, 298, 299
codeStream.cc, 297	currentSourceModels.h, 299
codeStream.h, 297	SET_INJECTION_CODE, 299
connections set	CurrentSourceModels::Base, 127
pygenn::genn_groups::SynapseGroup, 255	getInjectionCode, 127
connectivity_initialiser	CurrentSourceModels::DC, 150
pygenn::genn_groups::SynapseGroup, 255	getInstance, 151
container	getParamNames, 151
CodeGenerator::NameIterCtx, 203	ParamValues, 150
create_cmlf_class	PostVarValues, 151
pygenn::genn_model, 79	PreVarValues, 151
create_custom_current_source_class	SET_INJECTION_CODE, 151
	VarValues, 151
pygenn::genn_model, 80	CurrentSourceModels::GaussianNoise, 166
create_custom_init_var_snippet_class	getInstance, 168
pygenn::genn_model, 80	getParamNames, 168
create_custom_model_class	ParamValues, 167
pygenn::genn_model, 81	PostVarValues, 167
create_custom_neuron_class	PreVarValues, 168
pygenn::genn_model, 81	SET_INJECTION_CODE, 168
create_custom_postsynaptic_class	VarValues, 168
pygenn::genn_model, 82	
create_custom_sparse_connect_init_snippet_class	DECLARE_MODEL
pygenn::genn_model, 83	models.h, 314

DECLARE_SNIPPET	modelSpec.h, 316
InitSparseConnectivitySnippet::FixedProbability,	func
161	Snippet::Base::DerivedParam, 153
$In it Sparse Connectivity Snippet :: Fixed Probability \leftarrow$	functionSubstitute
NoAutapse, 164	CodeGenerator, 67
InitSparseConnectivitySnippet::OneToOne, 219	OFNIN EVPORT
InitSparseConnectivitySnippet::Uninitialised, 282	GENN_EXPORT
InitVarSnippet::Constant, 142	gennExport.h, 307
InitVarSnippet::Exponential, 158	GENN_PREFERENCES
InitVarSnippet::Gamma, 166	generator.cc, 305
InitVarSnippet::Normal, 217	genAllocateMemPreamble
InitVarSnippet::Uniform, 281	CodeGenerator::BackendBase, 117
InitVarSnippet::Uninitialised, 282	CodeGenerator::CUDA::Backend, 94
snippet.h, 327	CodeGenerator::SingleThreadedCPU::Backend,
DECLARE_WEIGHT_UPDATE_MODEL	105
weightUpdateModels.h, 334	genArray
WeightUpdateModels::PiecewiseSTDP, 222	CodeGenerator::BackendBase, 117
WeightUpdateModels::StaticGraded, 241	genCurrentSpikeLikeEventPull
WeightUpdateModels::StaticPulse, 243	CodeGenerator::BackendBase, 118 CodeGenerator::CUDA::Backend, 94
debugCode	•
CodeGenerator::PreferencesBase, 232	CodeGenerator::SingleThreadedCPU::Backend, 105
default_sparse_connectivity_location	genCurrentSpikeLikeEventPush
pygenn::genn_model::GeNNModel, 172, 173	CodeGenerator::BackendBase, 118
default_var_location	CodeGenerator::CUDA::Backend, 94
pygenn::genn_model::GeNNModel, 173, 176	CodeGenerator::SingleThreadedCPU::Backend,
delay_slots	106
pygenn::genn_groups::NeuronGroup, 206	genCurrentTrueSpikePull
DerivedParamNameIterCtx	CodeGenerator::BackendBase, 118
CodeGenerator, 66	CodeGenerator::CUDA::Backend, 94
DerivedParamVec	CodeGenerator::SingleThreadedCPU::Backend,
Snippet::Base, 135	106
device	genCurrentTrueSpikePush
CodeGenerator::MemAlloc, 188	CodeGenerator::BackendBase, 118
DeviceSelect CodeGenerator::CUDA, 73	CodeGenerator::CUDA::Backend, 94
deviceSelectMethod	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::CUDA::Preferences, 230	106
doublePrecisionTemplate	genDefinitionsInternalPreamble
CodeGenerator::FunctionTemplate, 165	CodeGenerator::BackendBase, 118
dT	CodeGenerator::CUDA::Backend, 95
pygenn::genn_model::GeNNModel, 173, 176	CodeGenerator::SingleThreadedCPU::Backend,
pygeriigeriii_moderderviviioder, 170, 170	106
end	genDefinitionsPreamble
pygenn::genn model::GeNNModel, 173	CodeGenerator::BackendBase, 118
ensureFtype	CodeGenerator::CUDA::Backend, 95
CodeGenerator, 67	CodeGenerator::SingleThreadedCPU::Backend,
extra_global_params	106
pygenn::genn_groups::Group, 178	genExtraGlobalParamAllocation
	CodeGenerator::BackendBase, 119
filesystem, 76	CodeGenerator::CUDA::Backend, 95
finalize	Code Generator :: Single Threaded CPU :: Backend,
ModelSpec, 198	106
findCurrentSource	genExtraGlobalParamDefinition
ModelSpec, 198	CodeGenerator::BackendBase, 119
findNeuronGroup	CodeGenerator::CUDA::Backend, 95
ModelSpec, 198	CodeGenerator::SingleThreadedCPU::Backend,
findSynapseGroup	107
ModelSpec, 199	genExtraGlobalParamImplementation
FloatType	CodeGenerator::BackendBase, 119

CodeGenerator::CUDA::Backend, 95 CodeGenerator::SingleThreadedCPU::Backend, 107	genMakefilePreamble CodeGenerator::BackendBase, 120 CodeGenerator::CUDA::Backend, 97
genExtraGlobalParamPull	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 119	108
CodeGenerator::CUDA::Backend, 96	genNeuronUpdate
CodeGenerator::SingleThreadedCPU::Backend, 107	CodeGenerator::BackendBase, 121 CodeGenerator::CUDA::Backend, 98
genExtraGlobalParamPush	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 119	109
CodeGenerator::CUDA::Backend, 96	genPopVariableInit
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 122
107	CodeGenerator::CUDA::Backend, 98
genGlobalRNG	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 120	110
CodeGenerator::CUDA::Backend, 96	genPopulationRNG
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 122
107	CodeGenerator::CUDA::Backend, 98
genInit	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 120	110
CodeGenerator::CUDA::Backend, 96	genRunnerPreamble
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 122
108	CodeGenerator::CUDA::Backend, 99
genMSBuildCompileModule	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 121	110
CodeGenerator::CUDA::Backend, 97	genScalar
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 122
108	genStepTimeFinalisePreamble
genMSBuildConfigProperties	CodeGenerator::BackendBase, 123
CodeGenerator::BackendBase, 121	CodeGenerator::CUDA::Backend, 99
CodeGenerator::CUDA::Backend, 97	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	110
109	genSynapseUpdate
genMSBuildImportProps	CodeGenerator::BackendBase, 123
CodeGenerator::BackendBase, 121	CodeGenerator::CUDA::Backend, 99
CodeGenerator::CUDA::Backend, 97	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	110
109	genSynapseVariableRowlnit
genMSBuildImportTarget	CodeGenerator::BackendBase, 123
CodeGenerator::BackendBase, 121	CodeGenerator::CUDA::Backend, 100
CodeGenerator::CUDA::Backend, 97	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	111
109	genTimer
genMSBuildItemDefinitions	CodeGenerator::BackendBase, 124
CodeGenerator::BackendBase, 121	CodeGenerator::CUDA::Backend, 100
CodeGenerator::CUDA::Backend, 98	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	111
109	genVariableAllocation
genMakefileCompileRule	CodeGenerator::BackendBase, 124
CodeGenerator::BackendBase, 120	CodeGenerator::CUDA::Backend, 100
CodeGenerator::CUDA::Backend, 96	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	111
108	genVariableDefinition
genMakefileLinkRule	CodeGenerator::BackendBase, 124
CodeGenerator::BackendBase, 120	CodeGenerator::CUDA::Backend, 100
CodeGenerator::CUDA::Backend, 97	
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::SingleThreadedCPU::Backend,
108	genVariableFree
100	gontanabiorio

CodeGenerator::BackendBase, 124	generateSynapseUpdate
CodeGenerator::CUDA::Backend, 100	CodeGenerator, 68
CodeGenerator::SingleThreadedCPU::Backend,	generateSynapseUpdate.cc, 304
112	generateSynapseUpdate.h, 304
genVariableImplementation	generator.cc, 304
CodeGenerator::BackendBase, 124	GENN_PREFERENCES, 305
CodeGenerator::CUDA::Backend, 101	main, 305
CodeGenerator::SingleThreadedCPU::Backend,	genericName
112	CodeGenerator::FunctionTemplate, 165
genVariableInit	genn_groups.py, 305
CodeGenerator::BackendBase, 125	genn_model.py, 306
CodeGenerator::CUDA::Backend, 101	genn_to_numpy_types
CodeGenerator::SingleThreadedCPU::Backend,	pygenn::model_preprocessor, 90
112	gennExport.h, 307
genVariablePull	GENN_EXPORT, 307
CodeGenerator::BackendBase, 125	gennUtils.cc, 307
CodeGenerator::CUDA::Backend, 101	gennUtils.h, 307
CodeGenerator::SingleThreadedCPU::Backend,	get_sparse_post_inds
112	pygenn::genn_groups::SynapseGroup, 251
genVariablePush	get_sparse_pre_inds
CodeGenerator::BackendBase, 125	pygenn::genn_groups::SynapseGroup, 251
CodeGenerator::CUDA::Backend, 101	get_var_values
CodeGenerator::SingleThreadedCPU::Backend,	pygenn::genn_groups::SynapseGroup, 251
113	getAdditionalInputVars
genVariablePushPull	NeuronModels::Base, 132
CodeGenerator::BackendBase, 125	getApplyInputCode
generateAll	PostsynapticModels::Base, 133
CodeGenerator, 67	PostsynapticModels::DeltaCurr, 153
generateAll.cc, 300	PostsynapticModels::ExpCond, 155
generateAll.h, 300	PostsynapticModels::ExpCurr, 157
generateInit	getBackPropDelaySteps
CodeGenerator, 67	SynapseGroup, 260
generateInit.cc, 300	getCalcMaxColLengthFunc
generateInit.h, 300	InitSparseConnectivitySnippet::Base, 128
generateMPI.cc, 301	getCalcMaxRowLengthFunc
generateMPI.h, 301	InitSparseConnectivitySnippet::Base, 128
generateMPI	getChosenCUDADevice
CodeGenerator, 68	CodeGenerator::CUDA::Backend, 101
generateMSBuild	getChosenDeviceID
CodeGenerator, 68	CodeGenerator::CUDA::Backend, 101
generateMSBuild.cc, 302	getClusterHostID
generateMSBuild.h, 302	NeuronGroup, 210
generateMakefile	SynapseGroup, 260
CodeGenerator, 67	
	getCode
generateMakefile.cc, 301	InitVarSnippet::Base, 129
generateMakefile.h, 301	getConnectivityInitialiser
generateNeuronUpdate	SynapseGroup, 260
CodeGenerator, 68	getCurrentQueueOffset
generateNeuronUpdate.cc, 302	NeuronGroup, 211
generateNeuronUpdate.h, 303	getCurrentSourceModel
generateRunner	CurrentSource, 147
CodeGenerator, 68	getCurrentSources
generateRunner.cc, 303	NeuronGroup, 211
generateRunner.h, 303	getDecayCode
generateSupportCode	PostsynapticModels::Base, 134
CodeGenerator, 68	PostsynapticModels::ExpCond, 155
generateSupportCode.cc, 303	PostsynapticModels::ExpCurr, 157
generateSupportCode.h, 304	getDelaySteps

SynapseGroup, 261	CurrentSourceModels::Base, 127
getDendriticDelayLocation	getInstance
SynapseGroup, 261	CurrentSourceModels::DC, 151
getDendriticDelayOffset	CurrentSourceModels::GaussianNoise, 168
SynapseGroup, 261	NeuronModels::Izhikevich, 182
getDerivedParams	NeuronModels::IzhikevichVariable, 185
CurrentSource, 147	NeuronModels::LIF, 187
InitSparseConnectivitySnippet::FixedProbability←	NeuronModels::Poisson, 225
Base, 162	NeuronModels::PoissonNew, 228
NeuronGroup, 211	NeuronModels::RulkovMap, 234
NeuronModels::LIF, 186	NeuronModels::SpikeSource, 237
NeuronModels::PoissonNew, 228	NeuronModels::SpikeSourceArray, 239
NeuronModels::RulkovMap, 234	NeuronModels::TraubMiles, 274
PostsynapticModels::ExpCond, 155	NeuronModels::TraubMilesAlt, 276
PostsynapticModels::ExpCurr, 157	NeuronModels::TraubMilesFast, 278
Snippet::Base, 135	NeuronModels::TraubMilesNStep, 279
• •	PostsynapticModels::DeltaCurr, 153
Snippet::Init, 180	• •
WeightUpdateModels::PiecewiseSTDP, 222	PostsynapticModels::ExpCond, 155
getDeviceBytes	PostsynapticModels::ExpCurr, 157
CodeGenerator::MemAlloc, 188	WeightUpdateModels::StaticPulseDendriticDelay
getDeviceMBytes	245
CodeGenerator::MemAlloc, 188	getLearnPostCode
getDeviceMemoryBytes	Weight UpdateModels::Base, 137
CodeGenerator::BackendBase, 125	WeightUpdateModels::PiecewiseSTDP, 222
CodeGenerator::CUDA::Backend, 102	getLearnPostSupportCode
CodeGenerator::SingleThreadedCPU::Backend,	WeightUpdateModels::Base, 137
113	getLocalCurrentSources
getDT	ModelSpec, 199
ModelSpec, 199	getLocalHostID
getEventCode	CodeGenerator::BackendBase, 126
WeightUpdateModels::Base, 137	getLocalNeuronGroups
WeightUpdateModels::StaticGraded, 241	ModelSpec, 199
getEventThresholdConditionCode	getLocalSynapseGroups
WeightUpdateModels::Base, 137	ModelSpec, 199
WeightUpdateModels::StaticGraded, 242	getMatrixType
getExtraGlobalParamIndex	SynapseGroup, 261
InitSparseConnectivitySnippet::Base, 128	getMaxConnections
Models::Base, 130	SynapseGroup, 261
getExtraGlobalParamLocation	getMaxDendriticDelayTimesteps
CurrentSource, 147, 148	SynapseGroup, 261
NeuronGroup, 211	getMaxSourceConnections
getExtraGlobalParams	SynapseGroup, 261
InitSparseConnectivitySnippet::Base, 129	getMergedInSyn
Models::Base, 130	NeuronGroup, 211
NeuronModels::Poisson, 225	getNVCCFlags
NeuronModels::SpikeSourceArray, 239	CodeGenerator::CUDA::Backend, 102
getHostBytes	getName
CodeGenerator::MemAlloc, 188	CurrentSource, 148
getHostMBytes	ModelSpec, 199
CodeGenerator::MemAlloc, 189	NeuronGroup, 211
getInSyn	SynapseGroup, 261
NeuronGroup, 211	getNeuronModel
getInSynLocation	NeuronGroup, 211
SynapseGroup, 261	getNumDelaySlots
getInitialisers	NeuronGroup, 212
Models::VarInitContainerBase, 288	getNumLocalNeurons
Models::VarInitContainerBase< 0 >, 289	ModelSpec, 199
getInjectionCode	getNumNeurons

ModelSpec, 199	WeightUpdateModels::Base, 138
NeuronGroup, 212	getPostVars
getNumPostsynapticUpdateThreads	WeightUpdateModels::Base, 138
CodeGenerator::CUDA::Backend, 102	getPostsynapticBackPropDelaySlot
getNumPresynapticUpdateThreads	SynapseGroup, 261
CodeGenerator::CUDA::Backend, 102	getPreSpikeCode
	- ,
getNumRemoteNeurons	WeightUpdateModels::Base, 138
ModelSpec, 200	getPreVarIndex
getNumSynapseDynamicsThreads	WeightUpdateModels::Base, 138
CodeGenerator::CUDA::Backend, 102	getPreVars
getOutSyn	WeightUpdateModels::Base, 138
NeuronGroup, 212	getPrecision
getPSConstInitVals	ModelSpec, 200
SynapseGroup, 262	getPresynapticAxonalDelaySlot
getPSDerivedParams	SynapseGroup, 262
SynapseGroup, 262	getPrevQueueOffset
getPSExtraGlobalParamLocation	NeuronGroup, 212
SynapseGroup, 262	getRemoteCurrentSources
getPSModel	ModelSpec, 200
SynapseGroup, 262	getRemoteNeuronGroups
getPSModelTargetName	ModelSpec, 200
SynapseGroup, 262	getRemoteSynapseGroups
getPSParams	ModelSpec, 200
SynapseGroup, 262	getResetCode
getPSVarInitialisers	NeuronModels::Base, 132
SynapseGroup, 262	NeuronModels::LIF, 187
getPSVarLocation	NeuronModels::SpikeSourceArray, 239
SynapseGroup, 263	getRowBuildCode
getParamNames	InitSparseConnectivitySnippet::Base, 129
CurrentSourceModels::DC, 151	InitSparseConnectivitySnippet::FixedProbability←
CurrentSourceModels::GaussianNoise, 168	Base, 162
InitSparseConnectivitySnippet::FixedProbability←	getRowBuildStateVars
Base, 162	
InitVarSnippet::Constant, 142	InitSparseConnectivitySnippet::Base, 129 getRuntimeVersion
	<u> </u>
InitVarSnippet::Exponential, 158	CodeGenerator::CUDA::Backend, 102
InitVarSnippet::Gamma, 166	getSeed
InitVarSnippet::Normal, 217	ModelSpec, 200
InitVarSnippet::Uniform, 281	getSimCode
NeuronModels::Izhikevich, 182	NeuronModels::Base, 132
NeuronModels::IzhikevichVariable, 185	NeuronModels::Izhikevich, 182
NeuronModels::LIF, 187	NeuronModels::LIF, 187
NeuronModels::Poisson, 225	NeuronModels::Poisson, 226
NeuronModels::PoissonNew, 228	NeuronModels::PoissonNew, 228
NeuronModels::RulkovMap, 235	NeuronModels::RulkovMap, 235
NeuronModels::TraubMiles, 274	NeuronModels::SpikeSourceArray, 240
NeuronModels::TraubMilesNStep, 279	NeuronModels::TraubMiles, 274
PostsynapticModels::ExpCond, 155	NeuronModels::TraubMilesAlt, 276
PostsynapticModels::ExpCurr, 157	NeuronModels::TraubMilesFast, 278
Snippet::Base, 136	NeuronModels::TraubMilesNStep, 280
WeightUpdateModels::PiecewiseSTDP, 222	WeightUpdateModels::Base, 138
WeightUpdateModels::StaticGraded, 242	WeightUpdateModels::PiecewiseSTDP, 223
getParams	WeightUpdateModels::StaticPulse, 243
CurrentSource, 148	WeightUpdateModels::StaticPulseDendriticDelay,
NeuronGroup, 212	245
Snippet::Init, 180	getSimSupportCode
• •	
getPostSpikeCode	WeightUpdateModels::Base, 139
WeightUpdateModels::Base, 138	getSize CodeGenerator::BackendBase, 126
getPostVarIndex	

getSnippet	CodeGenerator::Substitutions, 248
Snippet::Init, 180	getVarVecIndex
getSpanType	Snippet::Base, 136
SynapseGroup, 263	getVars
getSparseConnectivityExtraGlobalParamLocation	Models::Base, 131
SynapseGroup, 263	NeuronModels::Izhikevich, 183
getSparseConnectivityLocation	NeuronModels::IzhikevichVariable, 185
SynapseGroup, 263	NeuronModels::LIF, 187
getSpikeEventCondition	NeuronModels::Poisson, 226
NeuronGroup, 212	NeuronModels::PoissonNew, 229
getSpikeEventLocation	NeuronModels::RulkovMap, 235
NeuronGroup, 212	NeuronModels::SpikeSourceArray, 240
getSpikeLocation	NeuronModels::TraubMiles, 274
	WeightUpdateModels::PiecewiseSTDP, 223
NeuronGroup, 212	WeightUpdateModels::StaticGraded, 242
getSpikeTimeLocation	WeightUpdateModels::StaticPulse, 243
NeuronGroup, 212	WeightUpdateModels::StaticPulseDendriticDelay,
getSrcNeuronGroup	245
SynapseGroup, 263	
getSupportCode	getWUConstInitVals
NeuronModels::Base, 132	SynapseGroup, 264
PostsynapticModels::Base, 134	getWUDerivedParams
getSynapseDynamicsCode	SynapseGroup, 264
WeightUpdateModels::Base, 139	getWUExtraGlobalParamLocation
getSynapseDynamicsSuppportCode	SynapseGroup, 264
WeightUpdateModels::Base, 139	getWUModel
getThresholdConditionCode	SynapseGroup, 264
NeuronModels::Base, 132	getWUParams
NeuronModels::Izhikevich, 183	SynapseGroup, 264
NeuronModels::LIF, 187	getWUPostVarInitialisers
NeuronModels::Poisson, 226	SynapseGroup, 264
NeuronModels::PoissonNew, 228	getWUPostVarLocation
NeuronModels::RulkovMap, 235	SynapseGroup, 264
NeuronModels::SpikeSource, 237	getWUPreVarInitialisers
NeuronModels::SpikeSourceArray, 240	SynapseGroup, 265
NeuronModels::TraubMiles, 274	getWUPreVarLocation
getTimePrecision	SynapseGroup, 265
ModelSpec, 200	getWUVarInitialisers
getTrgNeuronGroup	SynapseGroup, 265
SynapseGroup, 263, 264	getWUVarLocation
	SynapseGroup, 265
getUnderlyingType Utils, 91	getZeroCopyBytes
	CodeGenerator::MemAlloc, 189
getValues	getZeroCopyMBytes
Snippet::ValueBase, 283	CodeGenerator::MemAlloc, 189
Snippet::ValueBase< 0 >, 284	GroupHandler
getVarIndex	CodeGenerator::BackendBase, 116
Models::Base, 130	
getVarInitialisers	Handler
CurrentSource, 148	CodeGenerator::BackendBase, 116
NeuronGroup, 213	has_individual_postsynaptic_vars
getVarLocation	pygenn::genn_groups::SynapseGroup, 251
CurrentSource, 148	has_individual_synapse_vars
NeuronGroup, 213	pygenn::genn_groups::SynapseGroup, 251
getVarPrefix	hasOutputToHost
CodeGenerator::BackendBase, 126	NeuronGroup, 213
CodeGenerator::CUDA::Backend, 102	hasVarSubstitution
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::Substitutions, 248
113	host
getVarSubstitution	CodeGenerator::MemAlloc, 189

IMPLEMENT_MODEL	SET_CALC_MAX_ROW_LENGTH_FUNC, 163
currentSourceModels.cc, 298, 299	SET_ROW_BUILD_STATE_VARS, 163
models.h, 314	InitSparseConnectivitySnippet::FixedProbabilityNo⊷
neuronModels.cc, 319–321	Autapse, 163
postsynapticModels.cc, 324, 325	DECLARE_SNIPPET, 164
weightUpdateModels.cc, 333	SET_ROW_BUILD_CODE, 164
IMPLEMENT_SNIPPET	InitSparseConnectivitySnippet::Init, 179
initSparseConnectivitySnippet.cc, 308	Init, 179
initVarSnippet.cc, 311	InitSparseConnectivitySnippet::OneToOne, 218
snippet.h, 327	DECLARE_SNIPPET, 219
ind	SET_MAX_COL_LENGTH, 219
pygenn::genn_groups::SynapseGroup, 256	SET_MAX_ROW_LENGTH, 219
Init	SET_ROW_BUILD_CODE, 219
InitSparseConnectivitySnippet::Init, 179	InitSparseConnectivitySnippet::Uninitialised, 282
Snippet::Init, 180	DECLARE_SNIPPET, 282
init_connectivity	initVar
pygenn::genn_model, 85	modelSpec.h, 317, 318
init_required	InitVarSnippet, 76
pygenn::model_preprocessor::Variable, 286	initVarSnippet.cc, 310
init_val	IMPLEMENT_SNIPPET, 311
pygenn::model_preprocessor::Variable, 286	initVarSnippet.h, 311
init_var	SET_CODE, 312
pygenn::genn_model, 85	InitVarSnippet::Base, 129
initConnectivity	getCode, 129
modelSpec.h, 316, 317	InitVarSnippet::Constant, 142
initDerivedParams	DECLARE_SNIPPET, 142
CurrentSource, 148	getParamNames, 142
NeuronGroup, 213	SET CODE, 143
Snippet::Init, 180	InitVarSnippet::Exponential, 158
SynapseGroup, 265	DECLARE_SNIPPET, 158
InitSparseConnectivitySnippet, 76	getParamNames, 158
initSparseConnectivitySnippet.cc, 308	SET CODE, 159
IMPLEMENT SNIPPET, 308	InitVarSnippet::Gamma, 165
initSparseConnectivitySnippet.h, 309	DECLARE_SNIPPET, 166
SET_CALC_MAX_COL_LENGTH_FUNC, 309	getParamNames, 166
SET_CALC_MAX_ROW_LENGTH_FUNC, 310	SET_CODE, 166
SET EXTRA GLOBAL PARAMS, 310	InitVarSnippet::Normal, 216
SET MAX COL LENGTH, 310	DECLARE_SNIPPET, 217
SET_MAX_GOU_LENGTH, 310	getParamNames, 217
SET ROW BUILD CODE, 310	SET_CODE, 217
SET_ROW_BUILD_CODE, \$10 SET_ROW_BUILD_STATE_VARS, 310	InitVarSnippet::Uniform, 280
	DECLARE_SNIPPET, 281
InitSparseConnectivitySnippet::Base, 127	getParamNames, 281
CalcMaxLengthFunc, 128	•
getCalcMaxColLengthFunc, 128	SET_CODE, 281
getCalcMaxRowLengthFunc, 128	InitVarSnippet::Uninitialised, 281
getExtraGlobalParamIndex, 128	DECLARE_SNIPPET, 282
getExtraGlobalParams, 129	injectCurrent
getRowBuildCode, 129	NeuronGroup, 213
getRowBuildStateVars, 129	is_bitmask
InitSparseConnectivitySnippet::FixedProbability, 160	pygenn::genn_groups::SynapseGroup, 252
DECLARE_SNIPPET, 161	is_connectivity_init_required
SET_ROW_BUILD_CODE, 161	pygenn::genn_groups::SynapseGroup, 252
In it Sparse Connectivity Snippet :: Fixed Probability Base,	is_dense
161	pygenn::genn_groups::SynapseGroup, 252
getDerivedParams, 162	is_model_valid
getParamNames, 162	pygenn::model_preprocessor, 87
getRowBuildCode, 162	is_ragged
SET_CALC_MAX_COL_LENGTH_FUNC, 163	pygenn::genn_groups::SynapseGroup, 252

1	io Torre Deliatera
is_spike_source_array	isTypePointer
pygenn::genn_groups::NeuronGroup, 207	Utils, 91
isAutoRefractoryRequired	isVarQueueRequired
NeuronModels::Base, 133	NeuronGroup, 214
isDelayRequired	isWUInitRNGRequired
NeuronGroup, 213	SynapseGroup, 266
isDendriticDelayRequired	isWUVarInitRequired
SynapseGroup, 265	SynapseGroup, 266
isEventThresholdReTestRequired	isZeroCopyEnabled
SynapseGroup, 266	NeuronGroup, 214
isGlobalRNGRequired	SynapseGroup, 266
CodeGenerator::BackendBase, 126	, 1
CodeGenerator::CUDA::Backend, 102	Kernel
	CodeGenerator::CUDA, 74
CodeGenerator::SingleThreadedCPU::Backend,	KernelBlockSize
113	CodeGenerator::CUDA, 73
isInitRNGRequired	KernelNames
CurrentSource, 148	
NeuronGroup, 213	CodeGenerator::CUDA::Backend, 103
Utils, 91	Lovel
isPSInitRNGRequired	Level
SynapseGroup, 266	CodeGenerator::CodeStream::CB, 140
isPSModelMerged	CodeGenerator::CodeStream::OB, 218
SynapseGroup, 266	load
isParamRequiredBySpikeEventCondition	pygenn::genn_groups::CurrentSource, 144
NeuronGroup, 214	pygenn::genn_groups::NeuronGroup, 206
•	pygenn::genn_groups::SynapseGroup, 252
isPostSpikeTimeRequired	pygenn::genn_model::GeNNModel, 173
WeightUpdateModels::Base, 139	logLevel
WeightUpdateModels::PiecewiseSTDP, 223	CodeGenerator::PreferencesBase, 232
isPostsynapticRemapRequired	
CodeGenerator::BackendBase, 126	m
CodeGenerator::CUDA::Backend, 103	pygenn::genn_model, 86
CodeGenerator::SingleThreadedCPU::Backend,	main
113	generator.cc, 305
isPreSpikeTimeRequired	manualBlockSizes
WeightUpdateModels::Base, 139	
WeightUpdateModels::PiecewiseSTDP, 223	CodeGenerator::CUDA::Preferences, 230
- '	manualDeviceID
isRNGRequired	CodeGenerator::CUDA::Preferences, 230
Utils, 91	MathsFunc
isSimRNGRequired	codeGenUtils.cc, 295
CurrentSource, 148	matrix_type
NeuronGroup, 214	pygenn::genn_groups::SynapseGroup, 252
isSparseConnectivityInitRequired	max_row_length
SynapseGroup, 266	pygenn::genn_groups::SynapseGroup, 253
isSpikeEventRequired	mergeIncomingPSM
NeuronGroup, 214	NeuronGroup, 214
SynapseGroup, 266	model_name
isSpikeTimeRequired	pygenn::genn_model::GeNNModel, 173, 174, 177
NeuronGroup, 214	
•	model_preprocessor.py, 312
isSynRemapRequired	ModelSpec, 189
CodeGenerator::BackendBase, 126	$\sim$ ModelSpec, 193
CodeGenerator::CUDA::Backend, 103	addCurrentSource, 193
CodeGenerator::SingleThreadedCPU::Backend,	addNeuronPopulation, 194, 195
113	addSynapsePopulation, 195–197
isTimingEnabled	finalize, 198
ModelSpec, 200	findCurrentSource, 198
isTrueSpikeRequired	findNeuronGroup, 198
NeuronGroup, 214	findSynapseGroup, 199
SynapseGroup, 266	getDT, 199
• • • • • • • • • • • • • • • • • • •	<del>-</del>

getLocalCurrentSources, 199	VarInitContainerBase, 288
getLocalNeuronGroups, 199	Models::VarInitContainerBase< 0 >, 289
getLocalSynapseGroups, 199	getInitialisers, 289
getName, 199	VarInitContainerBase, 289
getNumLocalNeurons, 199	Models::VarInitContainerBase< NumVars >, 288
getNumNeurons, 199	
getNumRemoteNeurons, 200	NNmodel
getPrecision, 200	modelSpec.h, 316
getRemoteCurrentSources, 200	NO_DELAY
getRemoteNeuronGroups, 200	modelSpec.h, 316
getRemoteSynapseGroups, 200	name
getSeed, 200	pygenn::genn_groups::Group, 178
getTimePrecision, 200	pygenn::model_preprocessor::ExtraGlobal ←
isTimingEnabled, 200	Variable, 160
ModelSpec, 192, 193	pygenn::model_preprocessor::Variable, 286
NeuronGroupValueType, 192	Snippet::Base::DerivedParam, 153
operator=, 200	Snippet::Base::ParamVal, 219
scalarExpr, 201	Snippet::Base::Var, 284
setDefaultExtraGlobalParamLocation, 201	name_substitutions
setDefaultSparseConnectivityLocation, 201	CodeGenerator, 69
setDefaultVarLocation, 201	nameBegin
setDT, 201	CodeGenerator::NameIterCtx, 203
setMergePostsynapticModels, 201	nameEnd
setName, 201	CodeGenerator::NameIterCtx, 204
setPrecision, 202	Namelter
setSeed, 202	CodeGenerator::NameIterCtx, 203 NameIterCtx
setTimePrecision, 202	
setTiming, 202	CodeGenerator::NameIterCtx, 203 needs allocation
SynapseGroupValueType, 192	<del>_</del>
zeroCopyInUse, 202	pygenn::model_preprocessor::Variable, 286
modelSpec.cc, 314	neuron
modelSpec.h, 314	pygenn::genn_groups::NeuronGroup, 207
FloatType, 316	neuron_populations
initConnectivity, 316, 317	pygenn::genn_model::GeNNModel, 177 NeuronGroup, 208
initVar, 317, 318	addlnSyn, 210
NNmodel, 316	addOutSyn, 210
NO_DELAY, 316	addSpkEventCondition, 210
TimePrecision, 316	checkNumDelaySlots, 210
uninitialisedConnectivity, 318	getClusterHostID, 210
uninitialisedVar, 318	getCurrentQueueOffset, 211
ModelSpecInternal, 202	getCurrentSources, 211
modelSpecInternal.h, 318	getDerivedParams, 211
Models, 77	getExtraGlobalParamLocation, 211
models.h, 313	getInSyn, 211
DECLARE_MODEL, 314	getMergedInSyn, 211
IMPLEMENT_MODEL, 314	getName, 211
SET EXTRA GLOBAL PARAMS, 314	getNeuronModel, 211
SET_VARS, 314	getNumDelaySlots, 212
Models::Base, 130	getNumNeurons, 212
getExtraGlobalParamIndex, 130	getOutSyn, 212
getExtraGlobalParams, 130	getParams, 212
getVarIndex, 130	getPrevQueueOffset, 212
getVars, 131	getSpikeEventCondition, 212
Models::VarInit, 287	getSpikeEventLocation, 212
VarInit, 287	getSpikeLocation, 212
Models::VarInitContainerBase	getSpikeTimeLocation, 212
getInitialisers, 288	getVarInitialisers, 213
operator[], 288	getVarLocation, 213
, bar	,

has Outrout Tallact 040	VarValues 100
hasOutputToHost, 213	VarValues, 182
initDerivedParams, 213	NeuronModels::IzhikevichVariable, 183
injectCurrent, 213	getInstance, 185
isDelayRequired, 213	getParamNames, 185
isInitRNGRequired, 213	getVars, 185
isParamRequiredBySpikeEventCondition, 214	ParamValues, 184
isSimRNGRequired, 214	PostVarValues, 184
isSpikeEventRequired, 214	PreVarValues, 184
isSpikeTimeRequired, 214	VarValues, 185
isTrueSpikeRequired, 214	NeuronModels::LIF, 185
isVarQueueRequired, 214	getDerivedParams, 186
isZeroCopyEnabled, 214	getInstance, 187
mergeIncomingPSM, 214	getParamNames, 187
NeuronGroup, 210	getResetCode, 187
setExtraGlobalParamLocation, 214	getSimCode, 187
setSpikeEventLocation, 215	getThresholdConditionCode, 187
setSpikeLocation, 215	getVars, 187
setSpikeTimeLocation, 215	ParamValues, 186
setVarLocation, 215	PostVarValues, 186
updatePostVarQueues, 215	PreVarValues, 186
updatePreVarQueues, 215	SET_NEEDS_AUTO_REFRACTORY, 188
neuronGroup.cc, 318	VarValues, 186
neuronGroup.h, 319	NeuronModels::Poisson, 223
NeuronGroupHandler	getExtraGlobalParams, 225
CodeGenerator::BackendBase, 116	getInstance, 225
NeuronGroupInternal, 216	getParamNames, 225
NeuronGroupInternal, 216	getSimCode, 226
neuronGroupInternal.h, 319	getThresholdConditionCode, 226
NeuronGroupSimHandler	getVars, 226
CodeGenerator::BackendBase, 116	ParamValues, 225
NeuronGroupValueType	PostVarValues, 225
ModelSpec, 192	PreVarValues, 225
NeuronModels, 77	VarValues, 225
neuronModels.cc, 319	NeuronModels::PoissonNew, 226
IMPLEMENT_MODEL, 319–321	getDerivedParams, 228
neuronModels.h, 321	getInstance, 228
SET_ADDITIONAL_INPUT_VARS, 322	getParamNames, 228
SET_NEEDS_AUTO_REFRACTORY, 322	getSimCode, 228
SET_RESET_CODE, 322	getThresholdConditionCode, 228
SET_SIM_CODE, 322	getVars, 229
SET_SUPPORT_CODE, 322	ParamValues, 227
SET_THRESHOLD_CONDITION_CODE, 322	PostVarValues, 227
NeuronModels::Base, 131	PreVarValues, 228
getAdditionalInputVars, 132	SET_NEEDS_AUTO_REFRACTORY, 229
getResetCode, 132	VarValues, 228
getSimCode, 132	NeuronModels::RulkovMap, 232
getSupportCode, 132	getDerivedParams, 234
getThresholdConditionCode, 132	getInstance, 234
isAutoRefractoryRequired, 133	getParamNames, 235
NeuronModels::Izhikevich, 180	getSimCode, 235
getInstance, 182	getThresholdConditionCode, 235
getParamNames, 182	getVars, 235
getSimCode, 182	ParamValues, 234
getThresholdConditionCode, 183	PostVarValues, 234
getVars, 183	PreVarValues, 234
ParamValues, 182	VarValues, 234
PostVarValues, 182	NeuronModels::SpikeSource, 236
PreVarValues, 182	getInstance, 237

getThresholdConditionCode, 237	operator<<
ParamValues, 237	CodeGenerator, 70
PostVarValues, 237	CodeGenerator::CodeStream, 141
PreVarValues, 237	operator*
SET_NEEDS_AUTO_REFRACTORY, 237	CodeGenerator::StructNameConstIter, 246
VarValues, 237	operator+=
NeuronModels::SpikeSourceArray, 238	CodeGenerator::MemAlloc, 189
getExtraGlobalParams, 239	operator->
getInstance, 239	CodeGenerator::StructNameConstIter, 246
getResetCode, 239	operator=
getSimCode, 240	CodeGenerator::FunctionTemplate, 165
getThresholdConditionCode, 240	ModelSpec, 200
getVars, 240	operator&
ParamValues, 239	synapseMatrixType.h, 330
PostVarValues, 239	variableMode.h, 332
PreVarValues, 239	operator[]
SET_NEEDS_AUTO_REFRACTORY, 240	CodeGenerator::Substitutions, 248
VarValues, 239	Models::VarInitContainerBase, 288
NeuronModels::TraubMiles, 271	Snippet::ValueBase, 283
getInstance, 274	optimiser.cc, 323
getParamNames, 274 getSimCode, 274	optimiser.h, 324
•	optimizeCode
getThresholdConditionCode, 274	CodeGenerator::PreferencesBase, 232
getVars, 274	padSize
ParamValues, 273	CodeGenerator::CUDA::Utils, 75
PostVarValues, 273	param_space_to_val_vec
PreVarValues, 273	pygenn::model_preprocessor, 87
VarValues, 273	param_space_to_vals
NeuronModels::TraubMilesAlt, 275	pygenn::model_preprocessor, 87
getInstance, 276	ParamVallterCtx
getSimCode, 276	CodeGenerator, 66
ParamValues, 275	ParamValVec
PostVarValues, 275	
PreVarValues, 276	Snippet::Base, 135 ParamValues
VarValues, 276	CurrentSourceModels::DC, 150
NeuronModels::TraubMilesFast, 276	CurrentSourceModels::GaussianNoise, 167
getInstance, 278	NeuronModels::Izhikevich, 182
getSimCode, 278	
ParamValues, 277	NeuronModels::IzhikevichVariable, 184
PostVarValues, 277	NeuronModels::LIF, 186
PreVarValues, 277	NeuronModels::Poisson, 225
VarValues, 278	NeuronModels::PoissonNew, 227
NeuronModels::TraubMilesNStep, 278	NeuronModels::RulkovMap, 234
getInstance, 279	NeuronModels::SpikeSource, 237
getParamNames, 279	NeuronModels::SpikeSourceArray, 239
getSimCode, 280	NeuronModels::TraubMiles, 273
ParamValues, 279	NeuronModels::TraubMilesAlt, 275
PostVarValues, 279	NeuronModels::TraubMilesFast, 277
PreVarValues, 279	NeuronModels::TraubMilesNStep, 279
VarValues, 279	PostsynapticModels::DeltaCurr, 152
neuronSubstitutionsInSynapticCode	PostsynapticModels::ExpCond, 154
CodeGenerator, 69	PostsynapticModels::ExpCurr, 156
num synapses	WeightUpdateModels::StaticPulseDendriticDelay
pygenn::genn_groups::SynapseGroup, 253	245
numArguments	рор
CodeGenerator::FunctionTemplate, 165	pygenn::genn_groups::CurrentSource, 146
	pygenn::genn_groups::NeuronGroup, 207
OB	pygenn::genn_groups::SynapseGroup, 256
CodeGenerator::CodeStream::OB, 218	post_var_space_to_vals

pygenn::model_preprocessor, 88	getDecayCode, 157
post_vars	getDerivedParams, 157
pygenn::genn_groups::SynapseGroup, 256	getInstance, 157
postNeuronSubstitutionsInSynapticCode	getParamNames, 157
CodeGenerator, 70	ParamValues, 156
PostVarValues	PostVarValues, 157
CurrentSourceModels::DC, 151	PreVarValues, 157
CurrentSourceModels::GaussianNoise, 167	VarValues, 157
NeuronModels::Izhikevich, 182	pre_var_space_to_vals
NeuronModels::IzhikevichVariable, 184	pygenn::model_preprocessor, 88
NeuronModels::LIF, 186	pre_vars
NeuronModels::Poisson, 225	pygenn::genn_groups::SynapseGroup, 256
NeuronModels::PoissonNew, 227	preNeuronSubstitutionsInSynapticCode
NeuronModels::RulkovMap, 234	CodeGenerator, 70
NeuronModels::SpikeSource, 237	PreVarValues No. 151
NeuronModels::SpikeSourceArray, 239	CurrentSourceModels::DC, 151
NeuronModels::TraubMiles, 273	CurrentSourceModels::GaussianNoise, 168
NeuronModels::TraubMilesAlt, 275	NeuronModels::Izhikevich, 182
NeuronModels::TraubMilesFast, 277	NeuronModels::IzhikevichVariable, 184
NeuronModels::TraubMilesNStep, 279	NeuronModels::LIF, 186
PostsynapticModels::DeltaCurr, 152	NeuronModels::Poisson, 225
PostsynapticModels::ExpCond, 155	NeuronModels::PoissonNew, 228
PostsynapticModels::ExpCurr, 157	NeuronModels::RulkovMap, 234
WeightUpdateModels::StaticPulseDendriticDelay,	NeuronModels::SpikeSource, 237
245	NeuronModels::SpikeSourceArray, 239
postsyn	NeuronModels::TraubMiles, 273
pygenn::genn_groups::SynapseGroup, 256	NeuronModels::TraubMilesAlt, 276
PostsynapticModels, 77	NeuronModels::TraubMilesFast, 277
postsynapticModels.cc, 324	NeuronModels::TraubMilesNStep, 279
IMPLEMENT_MODEL, 324, 325	PostsynapticModels::DeltaCurr, 152
postsynapticModels.h, 325	PostsynapticModels::ExpCond, 155
SET_APPLY_INPUT_CODE, 325	PostsynapticModels::ExpCurr, 157
SET_CURRENT_CONVERTER_CODE, 326	WeightUpdateModels::StaticPulseDendriticDelay
SET_DECAY_CODE, 326	245
SET_SUPPORT_CODE, 326	Preferences
PostsynapticModels::Base, 133	CodeGenerator::CUDA::Preferences, 230
getApplyInputCode, 133	prepare_model
getDecayCode, 134	pygenn::model_preprocessor, 88
getSupportCode, 134	prepare_snippet
PostsynapticModels::DeltaCurr, 151	pygenn::model_preprocessor, 89
getApplyInputCode, 153	psm_vars
getInstance, 153	pygenn::genn_groups::SynapseGroup, 256
ParamValues, 152	pull_connectivity_from_device
PostVarValues, 152	pygenn::genn_model::GeNNModel, 174
PreVarValues, 152	pull_current_spikes_from_device
VarValues, 152	pygenn::genn_model::GeNNModel, 174
PostsynapticModels::ExpCond, 154	pull_spikes_from_device
getApplyInputCode, 155	pygenn::genn_model::GeNNModel, 174
getDecayCode, 155	pull_state_from_device
getDerivedParams, 155	pygenn::genn_model::GeNNModel, 174
getInstance, 155	pull_var_from_device
getParamNames, 155	pygenn::genn_model::GeNNModel, 174
ParamValues, 154	push_connectivity_to_device
PostVarValues, 155	pygenn::genn_model::GeNNModel, 174
PreVarValues, 155	push_current_spikes_to_device
VarValues, 155	pygenn::genn_model::GeNNModel, 175
PostsynapticModels::ExpCurr, 156	push_spikes_to_device
getApplyInputCode, 157	pygenn::genn_model::GeNNModel, 175

push_state_to_device	get_sparse_pre_inds, 251
pygenn::genn_model::GeNNModel, 175	get_var_values, 251
push_var_to_device	has_individual_postsynaptic_vars, 251
pygenn::genn_model::GeNNModel, 175	has_individual_synapse_vars, 251
pygenn, 78	ind, 256
pygenn.genn_groups, 78	is_bitmask, 252
pygenn.genn_groups.CurrentSource, 143	is_connectivity_init_required, 252
pygenn.genn_groups.Group, 177	is_dense, 252
pygenn.genn_groups.NeuronGroup, 204	is_ragged, 252
pygenn.genn_groups.SynapseGroup, 248	load, 252
pygenn.genn_model, 78	matrix_type, 252
pygenn.genn_model.GeNNModel, 168	max_row_length, 253
pygenn.model_preprocessor, 86	num_synapses, 253
pygenn.model_preprocessor.ExtraGlobalVariable, 159	pop, 256
pygenn.model_preprocessor.Variable, 285	post_vars, 256
pygenn::genn_groups	postsyn, 256
xrange, 78	pre_vars, 256
pygenn::genn_groups::CurrentSource	psm_vars, 256
init , 144	reinitialise, 253
add_extra_global_param, 144	row_lengths, 256
add to, 144	set connected populations, 253
current_source_model, 146	set_post_syn, 253
load, 144	set_post_var, 254
pop, 146	set_pre_var, 254
reinitialise, 145	set_psm_var, 254
set_current_source_model, 145	set_sparse_connections, 254
size, 145	set_weight_update, 255
target_pop, 146	src, 256
pygenn::genn_groups::Group	synapse_order, 256
init, 178	trg, 256
extra_global_params, 178	w_update, 256
name, 178	weight_update_var_size, 255
set_var, 178	pygenn::genn_model
vars, 178	backend_modules, 86
pygenn::genn_groups::NeuronGroup	create_cmlf_class, 79
init, 205	create_custom_current_source_class, 80
add_extra_global_param, 205	create_custom_init_var_snippet_class, 80
add_to, 205	create custom model class, 81
current_spikes, 206	create_custom_neuron_class, 81
delay slots, 206	create_custom_postsynaptic_class, 82
is_spike_source_array, 207	create_custom_sparse_connect_init_snippet_←
load, 206	class, 83
neuron, 207	create_custom_weight_update_class, 84
pop, 207	create_dpf_class, 85
reinitialise, 206	init_connectivity, 85
set_neuron, 206	init_var, 85
size, 207	m, 86
spike_count, 207	pygenn::genn_model::GeNNModel
spike_que_ptr, 207	init, 170
spikes, 207	add_current_source, 170
type, 207	add_neuron_population, 171
pygenn::genn_groups::SynapseGroup	add_synapse_population, 171
init, 250	build, 172
add_extra_global_param, 250	current_sources, 176
add_extra_global_param, 250 add_to, 251	default_sparse_connectivity_location, 172, 173
connections_set, 255	default_var_location, 173, 176
	delauli_var_location, 173, 176 dT, 173, 176
connectivity_initialiser, 255	
get_sparse_post_inds, 251	end, 173

load, 173	SET_ADDITIONAL_INPUT_VARS
model_name, 173, 174, 177	neuronModels.h, 322
neuron_populations, 177	SET_APPLY_INPUT_CODE
pull_connectivity_from_device, 174	postsynapticModels.h, 325
pull_current_spikes_from_device, 174	SET_CALC_MAX_COL_LENGTH_FUNC
pull_spikes_from_device, 174	initSparseConnectivitySnippet.h, 309
pull_state_from_device, 174	InitSparseConnectivitySnippet::FixedProbability-
pull_var_from_device, 174	Base, 163
push connectivity to device, 174	SET CALC MAX ROW LENGTH FUNC
push_current_spikes_to_device, 175	initSparseConnectivitySnippet.h, 310
push_spikes_to_device, 175	InitSparseConnectivitySnippet::FixedProbability-
push_state_to_device, 175	Base, 163
push_var_to_device, 175	SET_CODE
reinitialise, 175	initVarSnippet.h, 312
step_time, 175	InitVarSnippet::Constant, 143
synapse_populations, 177	InitVarSnippet::Exponential, 159
T, 177	InitVarSnippet::Gamma, 166
t, 175, 176	InitVarSnippet::Normal, 217
timestep, 176	InitVarSnippet::Uniform, 281
use_backend, 176, 177	SET CURRENT CONVERTER CODE
pygenn::model_preprocessor	postsynapticModels.h, 326
genn_to_numpy_types, 90	SET_DECAY_CODE
is_model_valid, 87	postsynapticModels.h, 326
param_space_to_val_vec, 87	SET_DERIVED_PARAMS
param_space_to_vals, 87	snippet.h, 327
post_var_space_to_vals, 88	SET EVENT CODE
pre_var_space_to_vals, 88	weightUpdateModels.h, 334
prepare_model, 88	SET_EVENT_THRESHOLD_CONDITION_CODE
prepare_snippet, 89	weightUpdateModels.h, 334
var_space_to_vals, 89	SET_EXTRA_GLOBAL_PARAMS
pygenn::model_preprocessor::ExtraGlobalVariable	initSparseConnectivitySnippet.h, 310
init, 159	models.h, 314
name, 160	SET_INJECTION_CODE
set_values, 160	currentSourceModels.h, 299
type, 160	CurrentSourceModels::h, 299 CurrentSourceModels::DC, 151
values, 160	CurrentSourceModels::GaussianNoise, 168
view, 160	SET_LEARN_POST_CODE
pygenn::model_preprocessor::Variable	weightUpdateModels.h, 335
init, 285	SET_LEARN_POST_SUPPORT_CODE
init_required, 286	weightUpdateModels.h, 335
init_val, 286	SET_MAX_COL_LENGTH
name, 286	initSparseConnectivitySnippet.h, 310
needs_allocation, 286	InitSparseConnectivitySnippet::OneToOne, 219
set_values, 286	SET_MAX_ROW_LENGTH
type, 286	initSparseConnectivitySnippet.h, 310
values, 286	InitSparseConnectivitySnippet::0neToOne, 219
view, 287	SET NEEDS AUTO REFRACTORY
F 0 1 11 1	neuronModels.h, 322
regexFuncSubstitute	NeuronModels::LIF, 188
CodeGenerator, 71	NeuronModels::PoissonNew, 229
regexVarSubstitute	NeuronModels::SpikeSource, 237
CodeGenerator, 71	•
reinitialise	NeuronModels::SpikeSourceArray, 240
pygenn::genn_groups::CurrentSource, 145	SET_NEEDS_POST_SPIKE_TIME
pygenn::genn_groups::NeuronGroup, 206	weightUpdateModels.h, 335 SET_NEEDS_PRE_SPIKE_TIME
pygenn::genn_groups::SynapseGroup, 253	
pygenn::genn_model::GeNNModel, 175	weightUpdateModels.h, 335
row_lengths	SET_PARAM_NAMES
pygenn::genn_groups::SynapseGroup, 256	snippet.h, 327

SET_POST_SPIKE_CODE	pygenn::model_preprocessor::ExtraGlobal⇔
weightUpdateModels.h, 335	Variable, 160
SET_POST_VARS	pygenn::model_preprocessor::Variable, 286
weightUpdateModels.h, 335	set_var
SET_PRE_SPIKE_CODE	pygenn::genn_groups::Group, 178
weightUpdateModels.h, 335	set_weight_update
SET_PRE_VARS	pygenn::genn_groups::SynapseGroup, 255
weightUpdateModels.h, 335	setBackPropDelaySteps
SET_RESET_CODE	SynapseGroup, 267
neuronModels.h, 322	setDefaultExtraGlobalParamLocation
SET_ROW_BUILD_CODE	ModelSpec, 201
initSparseConnectivitySnippet.h, 310	setDefaultSparseConnectivityLocation
InitSparseConnectivitySnippet::FixedProbability,	ModelSpec, 201
161	setDefaultVarLocation
InitSparseConnectivitySnippet::FixedProbability←	ModelSpec, 201
NoAutapse, 164	setDendriticDelayLocation
InitSparseConnectivitySnippet::OneToOne, 219	SynapseGroup, 267
SET_ROW_BUILD_STATE_VARS	setDT
initSparseConnectivitySnippet.h, 310	ModelSpec, 201
InitSparseConnectivitySnippet::FixedProbability  ✓	setEventThresholdReTestRequired
Base, 163	SynapseGroup, 267
SET_SIM_CODE	setExtraGlobalParamLocation
neuronModels.h, 322	CurrentSource, 149
weightUpdateModels.h, 336	NeuronGroup, 214
SET_SIM_SUPPORT_CODE	setInSynVarLocation
weightUpdateModels.h, 336	SynapseGroup, 267
SET_SUPPORT_CODE	setMaxConnections
neuronModels.h, 322	SynapseGroup, 267
postsynapticModels.h, 326	setMaxDendriticDelayTimesteps
SET_SYNAPSE_DYNAMICS_CODE	SynapseGroup, 267
weightUpdateModels.h, 336	setMaxSourceConnections
SET_SYNAPSE_DYNAMICS_SUPPORT_CODE	SynapseGroup, 267
weightUpdateModels.h, 336	setMergePostsynapticModels
SET_THRESHOLD_CONDITION_CODE	ModelSpec, 201
neuronModels.h, 322	setName
SET VARS	ModelSpec, 201
models.h, 314	setPSExtraGlobalParamLocation
scalarExpr	SynapseGroup, 267
ModelSpec, 201	setPSModelMergeTarget
_	
Scope Code Construction Code Street Street Code Code Code Code Code Code Code Code	SynapseGroup, 268
CodeGenerator::CodeStream::Scope, 236	setPSVarLocation
set_connected_populations	SynapseGroup, 268
pygenn::genn_groups::SynapseGroup, 253	setPrecision
set_current_source_model	ModelSpec, 202
pygenn::genn_groups::CurrentSource, 145	setSeed
set_neuron	ModelSpec, 202
pygenn::genn_groups::NeuronGroup, 206	setSink
set_post_syn	CodeGenerator::CodeStream, 141
pygenn::genn_groups::SynapseGroup, 253	setSpanType
set_post_var	SynapseGroup, 268
pygenn::genn_groups::SynapseGroup, 254	setSparseConnectivityExtraGlobalParamLocation
set_pre_var	SynapseGroup, 268
pygenn::genn_groups::SynapseGroup, 254	setSparseConnectivityLocation
set_psm_var	SynapseGroup, 268
pygenn::genn_groups::SynapseGroup, 254	setSpikeEventLocation
set_sparse_connections	NeuronGroup, 215
pygenn::genn_groups::SynapseGroup, 254	setSpikeLocation
set_values	NeuronGroup, 215

setSpikeTimeLocation	operator[], 283
NeuronGroup, 215	ValueBase, 283
setTimePrecision	Snippet::ValueBase< 0 >, 283
ModelSpec, 202	getValues, 284
setTiming	ValueBase, 284
ModelSpec, 202	Snippet::ValueBase< NumVars >, 283
setVarLocation	SpanType
CurrentSource, 149	SynapseGroup, 259
NeuronGroup, 215	spike_count
setWUExtraGlobalParamLocation	pygenn::genn_groups::NeuronGroup, 207
SynapseGroup, 268	spike que ptr
setWUPostVarLocation	pygenn::genn groups::NeuronGroup, 207
SynapseGroup, 268	spikes
setWUPreVarLocation	pygenn::genn_groups::NeuronGroup, 207
SynapseGroup, 269 setWUVarLocation	STC
	pygenn::genn_groups::SynapseGroup, 256
SynapseGroup, 269	step_time
showPtxInfo	pygenn::genn_model::GeNNModel, 175
CodeGenerator::CUDA::Preferences, 230	StringVec
singlePrecisionTemplate	Snippet::Base, 135
CodeGenerator::FunctionTemplate, 165	StructNameConstIter
size	CodeGenerator::StructNameConstIter, 246
pygenn::genn_groups::CurrentSource, 145	substitute
pygenn::genn_groups::NeuronGroup, 207	CodeGenerator, 71
Snippet, 90	Substitutions
snippet.h, 326	CodeGenerator::Substitutions, 247
DECLARE_SNIPPET, 327	substitutions.h, 327
IMPLEMENT_SNIPPET, 327	synapse_order
SET_DERIVED_PARAMS, 327	pygenn::genn_groups::SynapseGroup, 256
SET_PARAM_NAMES, 327	synapse_populations
Snippet::Base, 134	pygenn::genn_model::GeNNModel, 177
∼Base, 135	SynapseGroup, 257
DerivedParamVec, 135	getBackPropDelaySteps, 260
getDerivedParams, 135	getClusterHostID, 260
getParamNames, 136	getConnectivityInitialiser, 260
getVarVecIndex, 136	getDelaySteps, 261
ParamValVec, 135	getDendriticDelayLocation, 261
StringVec, 135	getDendriticDelayOffset, 261
VarVec, 135	getInSynLocation, 261
Snippet::Base::DerivedParam, 153	getMatrixType, 261
func, 153	getMaxConnections, 261
name, 153	getMaxDendriticDelayTimesteps, 261
Snippet::Base::ParamVal, 219	getMaxSourceConnections, 261
name, 219	getName, 261
type, 220	getPSConstInitVals, 262
value, 220	getPSDerivedParams, 262
Snippet::Base::Var, 284	getPSExtraGlobalParamLocation, 262
name, 284	getPSModel, 262
type, 284	getPSModelTargetName, 262
Snippet::Init	getPSParams, 262
getDerivedParams, 180	getPSVarInitialisers, 262
getParams, 180	getPSVarLocation, 263
getSnippet, 180	getPostsynapticBackPropDelaySlot, 261
Init, 180	getPresynapticAxonalDelaySlot, 262
initDerivedParams, 180	getSpanType, 263
Snippet::Init< SnippetBase >, 179	getSparseConnectivityExtraGlobalParamLocation
Snippet::ValueBase	263
getValues, 283	getSparseConnectivityLocation, 263
30.74.400, 200	gotoparocornicotivity Location, Loc

matCraNauranCraun 060	aparatar <sup>9</sup> 220
getSrcNeuronGroup, 263	operator&, 330
getTrgNeuronGroup, 263, 264	SynapseMatrixConnectivity, 329
getWUConstInitVals, 264	SynapseMatrixType, 329
getWUDerivedParams, 264	SynapseMatrixWeight, 330
getWUExtraGlobalParamLocation, 264	SynapseMatrixWeight
getWUModel, 264	synapseMatrixType.h, 330
getWUParams, 264	
getWUPostVarInitialisers, 264	T
getWUPostVarLocation, 264	pygenn::genn model::GeNNModel, 177
getWUPreVarInitialisers, 265	t
getWUPreVarLocation, 265	pygenn::genn_model::GeNNModel, 175, 176
getWUVarInitialisers, 265	TYPE
getWUVarLocation, 265	backendBase.cc, 292
initDerivedParams, 265	target_pop
isDendriticDelayRequired, 265	pygenn::genn_groups::CurrentSource, 146
isEventThresholdReTestRequired, 266	TeeBuf
•	
isPSInitRNGRequired, 266	CodeGenerator::TeeBuf, 270
isPSModelMerged, 266	TeeStream
isSparseConnectivityInitRequired, 266	CodeGenerator::TeeStream, 271
isSpikeEventRequired, 266	teeStream.h, 330
isTrueSpikeRequired, 266	TimePrecision
isWUInitRNGRequired, 266	modelSpec.h, 316
isWUVarInitRequired, 266	timestep
isZeroCopyEnabled, 266	pygenn::genn_model::GeNNModel, 176
setBackPropDelaySteps, 267	trg
setDendriticDelayLocation, 267	pygenn::genn_groups::SynapseGroup, 256
setEventThresholdReTestRequired, 267	type
setInSynVarLocation, 267	pygenn::genn_groups::NeuronGroup, 207
setMaxConnections, 267	pygenn::model_preprocessor::ExtraGlobal ←
setMaxDendriticDelayTimesteps, 267	Variable, 160
setMaxSourceConnections, 267	pygenn::model_preprocessor::Variable, 286
setPSExtraGlobalParamLocation, 267	Snippet::Base::ParamVal, 220
	Snippet::Base::Var, 284
setPSModelMergeTarget, 268	Shippetbasevar, 204
setPSVarLocation, 268	
setSpanType, 268	uninitialisedConnectivity
setSparseConnectivityExtraGlobalParamLocation,	modelSpec.h, 318
268	uninitialisedVar
setSparseConnectivityLocation, 268	modelSpec.h, 318
setWUExtraGlobalParamLocation, 268	updatePostVarQueues
setWUPostVarLocation, 268	NeuronGroup, 215
setWUPreVarLocation, 269	updatePreVarQueues
setWUVarLocation, 269	NeuronGroup, 215
SpanType, 259	use_backend
SynapseGroup, 260	pygenn::genn_model::GeNNModel, 176, 177
synapseGroup.cc, 328	userCxxFlagsGNU
synapseGroup.h, 328	CodeGenerator::PreferencesBase, 232
SynapseGroupHandler	userNvccFlags
CodeGenerator::BackendBase, 117	CodeGenerator::CUDA::Preferences, 230
SynapseGroupInternal, 269	userNvccFlagsGNU
SynapseGroupInternal, 270	CodeGenerator::PreferencesBase, 232
synapseGroupInternal.h, 328	Utils, 90
• •	
SynapseGroupValueType  MadalSpace 102	getUnderlyingType, 91
ModelSpec, 192	isInitRNGRequired, 91
SynapseMatrixConnectivity	isRNGRequired, 91
synapseMatrixType.h, 329	isTypePointer, 91
SynapseMatrixType	utils.h, 331
synapseMatrixType.h, 329	CHECK_CU_ERRORS, 331
synapseMatrixType.h, 328	CHECK_CUDA_ERRORS, 331

value	weightUpdateModels.cc, 332
Snippet::Base::ParamVal, 220	IMPLEMENT MODEL, 333
• •	weightUpdateModels.h, 333
value_substitutions	•
CodeGenerator, 71, 72	DECLARE_WEIGHT_UPDATE_MODEL, 334
ValueBase	SET_EVENT_CODE, 334
Snippet::ValueBase, 283	SET_EVENT_THRESHOLD_CONDITION_CODE
Snippet::ValueBase< 0 >, 284	334
values	SET_LEARN_POST_CODE, 335
pygenn::model_preprocessor::ExtraGlobal←	SET_LEARN_POST_SUPPORT_CODE, 335
Variable, 160	SET_NEEDS_POST_SPIKE_TIME, 335
pygenn::model_preprocessor::Variable, 286	SET_NEEDS_PRE_SPIKE_TIME, 335
var_space_to_vals	SET_POST_SPIKE_CODE, 335
pygenn::model_preprocessor, 89	SET_POST_VARS, 335
VarInit	SET_PRE_SPIKE_CODE, 335
Models::VarInit, 287	SET PRE VARS, 335
VarInitContainerBase	SET_SIM_CODE, 336
Models::VarInitContainerBase, 288	SET_SIM_SUPPORT_CODE, 336
Models::VarInitContainerBase< 0 >, 289	SET SYNAPSE DYNAMICS CODE, 336
VarLocation	SET_SYNAPSE_DYNAMICS_SUPPORT_CODE,
variableMode.h, 332	336
VarNamelterCtx	
CodeGenerator, 66	WeightUpdateModels::Base, 136
VarValues	getEventCode, 137
CurrentSourceModels::DC, 151	getEventThresholdConditionCode, 137
CurrentSourceModels::GaussianNoise, 168	getLearnPostCode, 137
	getLearnPostSupportCode, 137
NeuronModels::Izhikevich, 182	getPostSpikeCode, 138
NeuronModels::IzhikevichVariable, 185	getPostVarIndex, 138
NeuronModels::LIF, 186	getPostVars, 138
NeuronModels::Poisson, 225	getPreSpikeCode, 138
NeuronModels::PoissonNew, 228	getPreVarIndex, 138
NeuronModels::RulkovMap, 234	getPreVars, 138
NeuronModels::SpikeSource, 237	getSimCode, 138
NeuronModels::SpikeSourceArray, 239	getSimSupportCode, 139
NeuronModels::TraubMiles, 273	getSynapseDynamicsCode, 139
NeuronModels::TraubMilesAlt, 276	getSynapseDynamicsSuppportCode, 139
NeuronModels::TraubMilesFast, 278	isPostSpikeTimeRequired, 139
NeuronModels::TraubMilesNStep, 279	isPreSpikeTimeRequired, 139
PostsynapticModels::DeltaCurr, 152	·
PostsynapticModels::ExpCond, 155	WeightUpdateModels::PiecewiseSTDP, 220
PostsynapticModels::ExpCurr, 157	DECLARE_WEIGHT_UPDATE_MODEL, 222
WeightUpdateModels::StaticPulseDendriticDelay,	getDerivedParams, 222
245	getLearnPostCode, 222
VarVec	getParamNames, 222
Snippet::Base, 135	getSimCode, 223
variableMode.h, 331	getVars, 223
operator&, 332	isPostSpikeTimeRequired, 223
VarLocation, 332	isPreSpikeTimeRequired, 223
vars	WeightUpdateModels::StaticGraded, 240
pygenn::genn_groups::Group, 178	DECLARE_WEIGHT_UPDATE_MODEL, 241
view	getEventCode, 241
pygenn::model_preprocessor::ExtraGlobal↔	getEventThresholdConditionCode, 242
Variable, 160	getParamNames, 242
	getVars, 242
pygenn::model_preprocessor::Variable, 287	WeightUpdateModels::StaticPulse, 242
w_update	DECLARE_WEIGHT_UPDATE_MODEL, 243
pygenn::genn_groups::SynapseGroup, 256	getSimCode, 243
weight_update_var_size	getVars, 243
pygenn::genn_groups::SynapseGroup, 255	WeightUpdateModels::StaticPulseDendriticDelay, 244
WeightUpdateModels, 91	getInstance, 245

```
getSimCode, 245
    getVars, 245
    ParamValues, 245
    PostVarValues, 245
    PreVarValues, 245
    VarValues, 245
writePreciseString
    CodeGenerator, 72
xrange
    pygenn::genn_groups, 78
zero
    CodeGenerator::MemAlloc, 189
zeroCopy
    CodeGenerator::MemAlloc, 189
zeroCopyInUse
    ModelSpec, 202
```