1 GeNN Documentation 1

1 GeNN Documentation

GeNN is a software package to enable neuronal network simulations on NVIDIA GPUs by code generation. Models are defined in a simple C-style API and the code for running them on either GPU or CPU hardware is generated by GeNN. GeNN can also be used through external interfaces. Currently there are interfaces for SpineML and SpineCreator and for Brian via Brian2GeNN.

GeNN is currently developed and maintained by

```
Dr James Knight (contact James)

James Turner (contact James)

Prof. Thomas Nowotny (contact Thomas)
```

Project homepage is http://genn-team.github.io/genn/.

The development of GeNN is partially supported by the EPSRC (grant numbers EP/P006094/1 - Brains on Board and EP/J019690/1 - Green Brain Project).

Note

This documentation is under construction. If you cannot find what you are looking for, please contact the project developers.

Next

2 Installation

You can download GeNN either as a zip file of a stable release or a snapshot of the most recent stable version or the unstable development version using the Git version control system.

2.1 Downloading a release

Point your browser to https://github.com/genn-team/genn/releases and download a release from the list by clicking the relevant source code button. Note that GeNN is only distributed in the form of source code due to its code generation design. Binary distributions would not make sense in this framework and are not provided. After downloading continue to install GeNN as described in the Installing GeNN section below.

2.2 Obtaining a Git snapshot

If it is not yet installed on your system, download and install Git (http://git-scm.com/). Then clone the GeNN repository from Github

```
git clone https://github.com/genn-team/genn.git
```

The github url of GeNN in the command above can be copied from the HTTPS clone URL displayed on the GeNN Github page (https://github.com/genn-team/genn).

This will clone the entire repository, including all open branches. By default git will check out the master branch which contains the source version upon which the next release will be based. There are other branches in the repository that are used for specific development purposes and are opened and closed without warning.

As an alternative to using git you can also download the full content of GeNN sources clicking on the "Download ZIP" button on the bottom right of the GeNN Github page (https://github.com/genn-team/genn).

2.3 Installing GeNN

Installing GeNN comprises a few simple steps to create the GeNN development environment.

Note

While GeNN models are normally simulated using CUDA on NVIDIA GPUs, if you want to use GeNN on a machine without an NVIDIA GPU, you can skip steps v and vi and use GeNN in "CPU_ONLY" mode.

- (i) If you have downloaded a zip file, unpack GeNN.zip in a convenient location. Otherwise enter the directory where you downloaded the Git repository.
- (ii) Add GeNN's "bin" directory to your path, e.g. if you are running Linux or Mac OS X and extracted/downloaded GeNN to \$HOME/GeNN, then you can add:

```
export PATH=$PATH:$HOME/GeNN/bin
```

to your login script (e.g. .profile or .bashrc. If you are using WINDOWS, the path should be a windows path as it will be interpreted by the Visual C++ compiler cl, and environment variables are best set using SETX in a Windows cmd window. To do so, open a Windows cmd window by typing cmd in the search field of the start menu, followed by the enter key. In the cmd window type:

```
setx PATH "C:\Users\me\GeNN\bin; %PATH%"
```

where C:\Users\me\GeNN is the path to your GeNN directory.

- (iv) Install the C++ compiler on the machine, if not already present. For Windows, download Microsoft Visual Studio Community Edition from https://www.visualstudio.com/en-us/downloads/download-visual-studio-vs.4 aspx. When installing Visual Studio, one should select the 'Desktop development with C++' configuration' and the 'Windows 8.1 SDK' and 'Windows Universal CRT' individual components. Mac users should download and set up Xcode from https://developer.apple.com/xcode/index.html Linux users should install the GNU compiler collection gcc and g++ from their Linux distribution repository, or alternatively from https://gcc.compu.org/index.html Be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (v) If your machine has a GPU and you haven't installed CUDA already, obtain a fresh installation of the NVIDIA C← UDA toolkit from https://developer.nvidia.com/cuda-downloads Again, be sure to pick CUDA and C++ compiler versions which are compatible with each other. The latest C++ compiler is not necessarily compatible with the latest CUDA toolkit.
- (vi) Set the CUDA_PATH variable if it is not already set by the system, by putting

```
export CUDA_PATH=/usr/local/cuda
```

in your login script (or, if CUDA is installed in a non-standard location, the appropriate path to the main CUDA directory). For most people, this will be done by the CUDA install script and the default value of /usr/local/cuda is fine. In Windows, CUDA_PATH is normally already set after installing the CUDA toolkit. If not, set this variable with:

```
setx CUDA_PATH C:\path\to\cuda
```

This normally completes the installation. Windows useres must close and reopen their command window to ensure variables set using SETX are initialised.

If you are using GeNN in Windows, the Visual Studio development environment must be set up within every instance of the CMD.EXE command window used. One can open an instance of CMD.EXE with the development environment already set up by navigating to Start - All Programs - Microsoft Visual Studio - Visual Studio Tools - x64 Native Tools Command Prompt. You may wish to create a shortcut for this tool on the desktop, for convenience.

Top | Next

3 Quickstart

3 Quickstart

GeNN is based on the idea of code generation for the involved GPU or CPU simulation code for neuronal network models but leaves a lot of freedom how to use the generated code in the final application. To facilitate the use of GeNN on the background of this philosophy, it comes with a number of complete examples containing both the model description code that is used by GeNN for code generation and the "user side code" to run the generated model and safe the results. Some of the example models such as the Insect olfaction model use an <code>generate_\infty</code> run executable which automates the building and simulation of the model. Using these executables, running these complete examples should be achievable in a few minutes. The necessary steps are described below.

3.1 Running an Example Model

3.1.1 Unix

In order to build the <code>generate_run</code> executable as well as any additional tools required for the model, open a shell and navigate to the <code>userproject/MBody1_project</code> directory. Then type

make

to generate an executable that you can invoke with

```
./generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead invoke this executable with

```
./generate_run --cpu-only test1
```

3.1.2 Windows

While GeNN can be used from within Visual Studio, in this example we will use a <code>cmd</code> window. Open a Visual Studio <code>cmd</code> window via Start: All Programs: Visual Studio: Tools: x86 Native Tools Command Prompt, and navigate to the <code>userproject\tools</code> directory. Then compile the additional tools and the <code>generate_run</code> executable for creating and running the project:

to generate an executable that you can invoke with

```
generate_run test1
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead invoke this executable with

```
generate_run --cpu-only test1
```

3.1.3 Visualising results

These steps will build and simulate a model of the locust olfactory system with default parameters of 100 projection neurons, 1000 Kenyon cells, 20 lateral horn interneurons and 100 output neurons in the mushroom body lobes.

Note

If the model isn't build in CPU_ONLY mode it will be simulated on an automatically chosen GPU.

The generate_run tool generates input patterns and writes them to file, compiles and runs the model using these files as inputs and finally output the resulting spiking activity. For more information of the options passed to this command see the Insect olfaction model section. The results of the simulation can be plotted with

```
python plot.py test1
```

The MBody1 example is already a highly integrated example that showcases many of the features of GeNN and how to program the user-side code for a GeNN application. More details in the User Manual .

3.2 How to use GeNN for New Projects

Creating and running projects in GeNN involves a few steps ranging from defining the fundamentals of the model, inputs to the model, details of the model like specific connectivity matrices or initial values, running the model, and analyzing or saving the data.

GeNN code is generally created by passing the C++ model file (see below) directly to the genn-buildmodel script. Another way to use GeNN is to create or modify a script or executable such as $userproject/MBody1_\leftrightarrow project/generate_run.cc$ that wraps around the other programs that are used for each of the steps listed above. In more detail, the GeNN workflow consists of:

- 1. Either use external programs to generate connectivity and input files to be loaded into the user side code at runtime or generate these matrices directly inside the user side code.
- 2. Generating the model simulation code using <code>genn-buildmodel.sh</code> (On Linux or Mac) or <code>genn-buildmodel.bat</code> (on Windows). For example, inside the <code>generate_run</code> engine used by the MBody1_project, the following command is executed on Linux:

```
genn-buildmodel.sh MBodyl.cc
```

or, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, the following command is executed:

```
genn-buildmodel.sh -c MBody1.cc
```

The genn-buildmodel script compiles the GeNN code generator in conjunction with the user-provided model description model/MBodyl.cc. It then executes the GeNN code generator to generate the complete model simulation code for the model.

3. Provide a build script to compile the generated model simulation and the user side code into a simulator executable (in the case of the MBody1 example this consists the file MBody1Sim.cc). On Linux or Mac a suitable GNU makefile can be created by running:

```
{\tt genn-create-user-project.sh~MBody1~MBody1Sim.cc}
```

And on Windows an MSBuild project can be created by running:

```
genn-create-user-project.bat MBody1 MBody1Sim.cc
```

4. Compile the simulator executable by invoking GNU make on Linux or Mac:

```
make clean all
```

or MSbuild on Windows:

```
msbuild MBody1.sln /t:MBody1 /p:Configuration=Release
```

5. Finally, run the resulting stand-alone simulator executable. In the MBody1 example, this is called MBody1 on Linux and MBody1_Release.exe on Windows.

3.3 Defining a New Model in GeNN

According to the work flow outlined above, there are several steps to be completed to define a neuronal network model.

- 1. The neuronal network of interest is defined in a model definition file, e.g. Example1.cc.
- 2. Within the the model definition file Example1.cc, the following tasks need to be completed:
 - a) The GeNN file modelSpec.h needs to be included,

```
#include "modelSpec.h"
```

b) The values for initial variables and parameters for neuron and synapse populations need to be defined, e.g.

would define the (homogeneous) parameters for a population of Poisson neurons.

Note

The number of required parameters and their meaning is defined by the neuron or synapse type. Refer to the User Manual for details. We recommend, however, to use comments like in the above example to achieve maximal clarity of each parameter's meaning.

If heterogeneous parameter values are required for a particular population of neurons (or synapses), they need to be defined as "variables" rather than parameters. See the User Manual for how to define new neuron (or synapse) types and the Defining a new variable initialisation snippet section for more information on initialising these variables to hetererogenous values.

c) The actual network needs to be defined in the form of a function modelDefinition, i.e.

```
void modelDefinition(ModelSpec &model);
```

Note

The name modelDefinition and its parameter of type ModelSpec& are fixed and cannot be changed if GeNN is to recognize it as a model definition.

d) Inside modelDefinition(), The time step DT needs to be defined, e.g.

```
model.setDT(0.1);
```

Note

All provided examples and pre-defined model elements in GeNN work with units of mV, ms, nF and muS. However, the choice of units is entirely left to the user if custom model elements are used.

MBody1.cc shows a typical example of a model definition function. In its core it contains calls to Model← Spec::addNeuronPopulation and ModelSpec::addSynapsePopulation to build up the network. For a full range of options for defining a network, refer to the User Manual.

- 3. The programmer defines their own "user-side" modeling code similar to the code in userproject/M← Body1_project/model/MBody1Sim.cc. In this code,
 - a) They manually define the connectivity matrices between neuron groups. Refer to the Synaptic matrix types section for the required format of connectivity matrices for dense or sparse connectivities.
 - b) They define input patterns (e.g. for Poisson neurons like in the MBody1 example) or individual initial values for neuron and / or synapse variables.

Note

The initial values given in the modelDefinition are automatically applied homogeneously to every individual neuron or synapse in each of the neuron or synapse groups.

- c) They use stepTime () to run one time step on either the CPU or GPU depending on the options passed to genn-buildmodel.
- d) They use functions like <code>copyStateFromDevice()</code> etc to transfer the results from GPU calculations to the main memory of the host computer for further processing.
- e) They analyze the results. In the most simple case this could just be writing the relevant data to output files.

Previous | Top | Next

4 Examples

for Windows users, or:

GeNN comes with a number of complete examples. At the moment, there are seven such example projects provided with GeNN.

4.1 Single compartment Izhikevich neuron(s)

```
Izhikevich neuron(s) without any connections
This is a minimal example, with only one neuron population (with more or less
neurons depending on the command line, but without any synapses). The neurons
are Izhikevich neurons with homogeneous parameters across the neuron population.
This example project contains a helper executable called "generate_run",
which compiles and executes the model.
To compile it, navigate to genn/userproject/OneComp_project and type:
msbuild ..\userprojects.sln /t:generate one comp runner /p:Configuration=Release
for Windows users, or:
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--num-neurons: Number of neurons to simulate (defaults to 1)
For a first minimal test, using these defaults and recording results with a base name of 'test', the system may
generate_run.exe test
```

```
./generate_run test

for Linux, Mac and other UNIX users.

This would create a set of tonic spiking Izhikevich neurons with no connectivity, receiving a constant identical 4 nA input.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and 4 neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=4 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=4 test

for Linux, Mac and other UNIX users.
```

4.2 Izhikevich neurons driven by Poisson input spike trains:

Izhikevich network receiving Poisson input spike trains

_____ In this example project there is again a pool of non-connected Izhikevich model neurons that are connected to a pool of Poisson input neurons with a fixed probability. This example project contains a helper executable called "generate_run", which compiles and executes the model. To compile it, navigate to genn/userproject/PoissonIzh_project and type: msbuild ..\userprojects.sln /t:generate_poisson_izh_runner /p:Configuration=Release for Windows users, or: for Linux, Mac and other UNIX users. USAGE generate_run [OPTIONS] <outname> Mandatory arguments: outname: The base name of the output location and output files Optional arguments: --debug: Builds a debug version of the simulation and attaches the debugger --cpu-only: Uses CPU rather than CUDA backend for GeNN --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation --ftype: Sets the floating point precision of the model to either float or double (defaults to float) --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically) --num-poisson: Number of Poisson sources to simulate (defaults to 100) --num-izh: Number of Izhikievich neurons to simulate (defaults to 10) --pconn: Probability of connection between each pair of poisson sources and neurons (defaults to 0.5) -- qscale: Scaling of synaptic conductances (defaults to 2) --sparse: Use sparse rather than dense data structure to represent connectivity An example invocation of generate_run using these defaults and recording results with a base name of 'test': generate run.exe test

for Windows users, or:

./generate_run test

```
for Linux, Mac and other UNIX users.

This will generate a network of 100 Poisson neurons with 20 Hz firing rate connected to 10 Izhikevich neurons with a 0.5 probability.

The same network with sparse connectivity can be used by adding the --sparse flag to the command line.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses sparse connectivity would be:

generate_run.exe --cpu-only --timing --sparse test

for Windows users, or:

./generate_run --cpu-only --timing --sparse test

for Linux, Mac and other UNIX users.

Izhikevich neuron model:[1]

4.3 Pulse-coupled Izhikevich network

Pulse-coupled Izhikevich network

This example model is inspired by simple thalamo-cortical network of Izhikevich with an excitatory and an inhibitory population of spiking neurons that are
```

Pulse-coupled Izhikevich network This example model is inspired by simple thalamo-cortical network of Izhikevich with an excitatory and an inhibitory population of spiking neurons that are randomly connected. It creates a pulse-coupled network with 80% excitatory 20% inhibitory connections, each connecting to a fixed number of neurons with sparse connectivity. To compile it, navigate to genn/userproject/Izh_sparse_project and type: msbuild ..\userprojects.sln /t:generate_izh_sparse_runner /p:Configuration=Release for Windows users, or: make for Linux, Mac and other UNIX users. USAGE generate_run [OPTIONS] <outname> Mandatory arguments: outname: The base name of the output location and output files Optional arguments: --debug: Builds a debug version of the simulation and attaches the debugger --cpu-only: Uses CPU rather than CUDA backend for GeNN --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation --ftype: Sets the floating point precision of the model to either float or double (defaults to float) --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically) --num-neurons: Number of neurons (defaults to 10000) --num-connections: Number of connections per neuron (defaults to 1000) --gscale: General scaling of synaptic conductances (defaults to 1.0) An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo generate_run.exe test

This would create a pulse coupled network of 8000 excitatory 2000 inhibitory Izhikevich neurons, each making 1000 connections with other neurons, generating

for Windows users, or:

for Linux, Mac and other UNIX users.

./generate run test

```
a mixed alpha and gamma regime. For larger input factor, there is more input current and more irregular activity, for smaller factors less and less and more sparse activity. The synapses are of a simple pulse-coupling type. The results of the simulation are saved in the directory 'outdir_output'.

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and doubles the number of neurons would be:

generate_run.exe --cpu-only --timing --num_neurons=20000 test

for Windows users, or:

./generate_run --cpu-only --timing --num_neurons=20000 test

for Linux, Mac and other UNIX users.
```

Izhikevich neuron model: [1]

4.4 Izhikevich network with delayed synapses

```
Izhikevich network with delayed synapses
```

This example project demonstrates the synaptic delay feature of GeNN. It creates a network of three Izhikevich neuron groups, connected all-to-all with fast, medium and slow synapse groups. Neurons in the output group only spike if they are simultaneously innervated by the input neurons, via slow synapses, and the interneurons, via faster synapses.

```
COMPILE (WINDOWS)
------
To run this example project, first build the model into CUDA code by typing:
genn-buildmodel.bat SynDelay.cc
then compile the project by typing:
msbuild SynDelay.sln /t:SynDelay /p:Configuration=Release

COMPILE (MAC AND LINUX)
------
To run this example project, first build the model into CUDA code by typing:
genn-buildmodel.sh SynDelay.cc
then compile the project by typing:
make

USAGE
-----
syn_delay [directory to save output]
```

Izhikevich neuron model: [1]

4.5 Insect olfaction model

Locust olfactory system (Nowotny et al. 2005)

This project implements the insect olfaction model by Nowotny et al. that demonstrates self-organized clustering of odours in a simulation of the insect antennal lobe and mushroom body. As provided the model works with conductance based Hodgkin-Huxley neurons and several different synapse types, conductance based (but pulse-coupled) excitatory synapses, graded inhibitory synapses and synapses with a simplified STDP rule. This example project contains a helper executable called "generate_run", which prepares input pattern data, before compiling and executing the model. To compile it, navigate to genn/userproject/MBody1_project and type: msbuild ..\userprojects.sln /t:generate_mbody1_runner /p:Configuration=Release for Windows users, or: make for Linux, Mac and other UNIX users. USAGE generate_run [OPTIONS] <outname> Mandatory arguments: outname: The base name of the output location and output files Optional arguments: --debug: Builds a debug version of the simulation and attaches the debugger --cpu-only: Uses CPU rather than CUDA backend for GeNN --timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation --ftype: Sets the floating point precision of the model to either float or double (defaults to float) --gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically) --num-al: Number of neurons in the antennal lobe (AL), the input neurons to this model (defaults to 100) --num-kc: Number of Kenyon cells (KC) in the "hidden layer" (defaults to 1000) --num-lhi: Number of lateral horn interneurons, implementing gain control (defaults to 20) --num-dn: Number of decision neurons (DN) in the output layer (defaults to 100) --gscale: A general rescaling factor for synaptic strength (defaults to 0.0025) --bitmask: Use bitmasks to represent sparse PN->KC connectivity rather than dense connectivity --delayed-synapses: Rather than use constant delays of DT throughough, use delays of $(5 \star DT)$ ms on KC->DN and An example invocation of generate_run using these defaults and recording results with a base name of 'test' wo generate run.exe test for Windows users, or:

./generate_run test

for Linux, Mac and other UNIX users.

Such a command would generate a locust olfaction model with 100 antennal lobe neurons, 1000 mushroom body Kenyon cells, 20 lateral horn interneurons and 100 mushroom body output neurons, and launch a simulation of it on a CUDA-enabled GPU using single precision floating point numbers. All output files will be prefixed with "test" and will be created under the "test" directory. The model that is run is defined in 'model/MBodyl.cc', debugging is switched off and the model would be simulated using float (single precision floating point) variables.

In more details, what generate_run program does is:

- a) use another tools to generate input patterns.
- b) build the source code for the model by writing neuron numbers into ./model/sizes.h, and executing "genn-buildmodel.sh ./model/MBodyl.cc.
- c) compile the generated code by invoking "make clean && make" running the code, e.g. "./classol_sim r1".

Another example of an invocation that runs the simulation using the CPU rather than GPU, records timing information and uses bitmask connectivity would be:

```
generate_run.exe --cpu-only --timing --bitmask test
for Windows users, or:
./generate_run --cpu-only --timing --bitmask test
for Linux, Mac and other UNIX users.
As provided, the model outputs 'test.dn.st', 'test.kc.st', 'test.lhi.st' and 'test.pn.st' files which contain
the spiking activity observed in each population inthe simulation, There are two
columns in this ASCII file, the first one containing the time of
a spike and the second one the ID of the neuron that spiked. Users
of matlab can use the scripts in the 'matlab' directory to plot
the results of a simulation and users of python can use the plot_spikes.py script in userproject/python.
For more about the model itself and the scientific insights gained from it see Nowotny et al. referenced below
MODEL INFORMATION
For information regarding the locust olfaction model implemented in this example project, see:
T. Nowotny, R. Huerta, H. D. I. Abarbanel, and M. I. Rabinovich Self-organization in the
olfactory system: One shot odor recognition in insects, Biol Cyber, 93 (6): 436-446 (2005),
doi:10.1007/s00422-005-0019-7
Nowotny insect olfaction model: [4]; Traub-Miles Hodgkin-Huxley neuron model: [7]
```

Voltage clamp simulation to estimate Hodgkin-Huxley parameters

```
Genetic algorithm for tracking parameters in a HH model cell
______
```

This example simulates a population of Hodgkin-Huxley neuron models using GeNN and evolves them with a simple quided random search (simple GA) to mimic the dynamics of a separate Hodgkin-Huxley neuron that is simulated on the CPU. The parameters of the CPU simulated "true cell" are drifting according to a user-chosen protocol: Either one of the parameters gNa, ENa, gKd, EKd, gleak, Eleak, Cmem are modified by a sinusoidal addition (voltage parameters) or factor (conductance or capacitance) protocol 0-6. For protocol 7 all 7 parameters undergo a random walk concurrently.

```
To compile it, navigate to genn/userproject/HHVclampGA_project and type:
msbuild ..\userproject.sln /t:qenerate_hhvclamp_runner /p:Configuration=Release
for Windows users, or:s
make
for Linux, Mac and other UNIX users.
USAGE
generate_run [OPTIONS] <outname>
Mandatory arguments:
outname: The base name of the output location and output files
Optional arguments:
--debug: Builds a debug version of the simulation and attaches the debugger
--cpu-only: Uses CPU rather than CUDA backend for GeNN
--timing: Uses GeNN's timing mechanism to measure performance and displays it at the end of the simulation
--ftype: Sets the floating point precision of the model to either float or double (defaults to float)
--gpu-device: Sets which GPU device to use for the simulation (defaults to -1 which picks automatically)
--protocol: Which changes to apply during the run to the parameters of the "true cell" (defaults to -1 which m
--num-pops: Number of neurons in the tracking population (defaults to 5000)
--total-time: Time in ms how long to run the simulation (defaults to 1000 ms)
```

```
An example invocation of generate_run is:

generate_run.exe test1

for Windows users, or:

./generate_run test1

for Linux, Mac and other UNIX users.

This will simulate 5000 Hodgkin-Huxley neurons on the GPU which will, for 1000 ms, be matched to a Hodgkin-Huxley neuron. The output files will be written into a directory of the name test1_output, which will be created if it does not yet exist.

Another example of an invocation that records timing information for the the simulation and runs it for 10000 generate_run.exe --timing --total-time 10000

for Windows users, or:

./generate_run --timing --total-time 10000

for Linux, Mac and other UNIX users.
```

Traub-Miles Hodgkin-Huxley neuron model: [7]

4.7 A neuromorphic network for generic multivariate data classification

```
Author: Alan Diamond, University of Sussex, 2014
This project recreates using GeNN the spiking classifier design used in the paper
"A neuromorphic network for generic multivariate data classification"
Authors: Michael Schmuker, Thomas Pfeil, Martin Paul Nawrota
The classifier design is based on an abstraction of the insect olfactory system.
This example uses the IRIS stadard data set as a test for the classifier
BUILD / RUN INSTRUCTIONS
Install GeNN from the internet released build, following instruction on setting your PATH etc
Start a terminal session
cd to this project directory (userproject/Model_Schmuker_2014_project)
To build the model using the GENN meta compiler type:
genn-buildmodel.sh Model_Schmuker_2014_classifier.cc
for Linux, Mac and other UNIX systems, or:
genn-buildmodel.bat Model_Schmuker_2014_classifier.cc
for Windows systems (add -d for a debug build).
You should only have to do this at the start, or when you change your actual network model (i.e. editing the
Then to compile the experiment plus the GeNN created C/CUDA code type:-
make
for Linux, Mac and other UNIX users (add DEBUG=1 if using debug mode), or:
msbuild Schmuker2014_classifier.vcxproj /p:Configuration=Release
for Windows users (change Release to Debug if using debug mode).
Once it compiles you should be able to run the classifier against the included Iris dataset.
```

type

./experiment .

```
for Linux, Mac and other UNIX systems, or:

Schmuker2014_classifier .

for Windows systems.

This is how it works roughly.

The experiment (experiment.cu) controls the experiment at a high level. It mostly does this by instructing the So the experiment first tells the classifier to set up the GPU with the model and synapse data.

Then it chooses the training and test set data.

It runs through the training set , with plasticity ON , telling the classifier to run with the specfied observa
```

At the highest level it also has a loop where you can cycle through a list of parameter values e.g. some thres

Then it runs through the test set with plasticity OFF and collects the results in various reporting files.


You should also note there is no option currently to run on CPU, this is not due to the demanding task, it just

Previous | Top | Next

5 SpineML and SpineCreator

GeNN now supports simulating models built using SpineML and includes scripts to fully integrate it with the SpineCreator graphical editor on Linux, Mac and Windows. After installing GeNN using the instructions in Installation, build SpineCreator for your platform.

From SpineCreator, select Edit->Settings->Simulators and add a new simulator using the following settings (replacing "/home/j/jk/jk421/genn" with the GeNN installation directory on your own system):



If you would like SpineCreator to use GeNN in CPU only mode, add an environment variable called "GENN_SPI⊷ NEML_CPU_ONLY".

The best way to get started using SpineML with GeNN is to experiment with some example models. A number are available here although the "Striatal model" uses features not currently supported by GeNN and the two "Brette

Benchmark" models use a legacy syntax no longer supported by SpineCreator (or GeNN). Once you have loaded a model, click "Expts" from the menu on the left hand side of SpineCreator, choose the experiment you would like to run and then select your newly created GeNN simulator in the "Setup Simulator" panel:



Now click "Run experiment" and, after a short time, the results of your GeNN simulation will be available for plotting by clicking the "Graphs" option in the menu on the left hand side of SpineCreator.

Previous | Top | Next

6 Brian interface (Brian2GeNN)

GeNN can simulate models written for the Brian simulator via the Brian2GeNN interface [6]. The easiest way to install everything needed is to install the Anaconda or Miniconda Python distribution and then follow the instructions to install Brian2GeNN with the conda package manager. When Brian2GeNN is installed in this way, it comes with a bundled version of GeNN and no further configuration is required. In all other cases (e.g. an installation from source), the path to GeNN and the CUDA libraries has to be configured via the GECNN_PATH and CUDA_PATH environment variables as described in Installation or via the devices.genn.path and devices.genn.cuda_path Brian preferences.

To use GeNN to simulate a Brian script, import the brian2genn package and switch Brian to the genn device. As an example, the following Python script will simulate Leaky-integrate-and-fire neurons with varying input currents to construct an f/l curve:

Of course, your simulation should be more complex than the example above to actually benefit from the performance gains of using a GPU via GeNN.

Previous | Top | Next

7 Python interface (PyGeNN)

As well as being able to build GeNN models and user code directly from C++, you can also access all GeNN features from Python. The pygenn_genn_model.GeNNModel class provides a thin wrapper around
ModelSpec as well as providing support for loading and running simulations; and accessing their state.
SynapseGroup, NeuronGroup and CurrentSource are similarly wrapped by the pygenn.genn_groups.SynapseGroup, pygenn.genn_groups.NeuronGroup and pygenn.genn_groups.
CurrentSource classes respectively.

8 Release Notes 15

PyGeNN can be built from source on Windows, Mac and Linux following the instructions in the README file in the pygenn directory of the GeNN repository. However, if you have a relatively recent version of Python and CUDA, we recommend that you instead downloading a suitable 'wheel' from our releases page (all wheels are build for CUDA 10 except for on Mac OS which is built for CUDA 9). These can then be installed using e.g. pip install pygenn-0.2.1-cp27-cp27mu-linux_x86_64.whl for a Linux system with Python 2.7. On Windows we recommend using the Python 3 version of Anaconda.

The following example shows how PyGeNN can be easily interfaced with standard Python packages such as numpy and matplotlib to plot 4 different Izhikevich neuron regimes:

```
import numpy as np
import matplotlib.pyplot as plt
from pygenn.genn_model import GeNNModel
# Create a single-precision GeNN model
model = GeNNModel("float", "pygenn")
# Set simulation timestep to 0.1ms
model.dT = 0.1
# Initialise IzhikevichVariable parameters - arrays will be automatically uploaded
izk\_init = {"V": -65.0, "U": -20.0,}
                                 0.1, 0.02, 0.02],
0.2, 0.2, 0.2],
-65.0, -50.0, -55.0],
2.0, 2.0, 4.0]}
               "a": [0.02,
              "b": [0.2,
"c": [-65.0, -65.0
2.0,
                               0.2,
# Add neuron populations and current source to model
pop = model.add_neuron_population("Neurons", 4, "IzhikevichVariable", {}, izk_init)
model.add_current_source("CurrentSource", "DC", "Neurons", {"amp": 10.0}, {})
# Build and load model
model.build()
model.load()
# Create a numpy view to efficiently access the membrane voltage from Python
voltage_view = pop.vars["V"].view
# Simulate
v = None
while model.t < 200.0:</pre>
    model.step_time()
    model.pull_state_from_device("Neurons")
        # Create plot
figure, axes = plt.subplots(4, sharex=True)
# Plot voltages
for i, t in enumerate(["RS", "FS", "CH", "IB"]):
     axes[i].set_title(t)
axes[i].set_ylabel("V [mV]")
     axes[i].plot(np.arange(0.0, 200.0, 0.1), v[:,i])
axes[-1].set_xlabel("Time [ms]")
# Show plot
plt.show()
```

Previous | Top | Next

8 Release Notes

Release Notes for GeNN v4.2.0 (PyGeNN 0.3)

This release adds a number of new features to GeNN and its Python interface as well as fixing a number of bugs that have been identified since the 4.1.0 release.

User Side Changes

1. Kernel timings can now be enabled from python with pygenn.genn_model.GeNNModel.

timing_enabled and subsequently accessed with pygenn.genn_model.GeNNModel.

→

neuron_update_time, pygenn.genn_model.GeNNModel.init_time, pygenn.genn← _model.GeNNModel.presynaptic_update_time, pygenn.genn_model.GeNNModel.← postsynaptic_update_time, pygenn.genn_model.GeNNModel.synapse_dynamics_← time and pygenn.genn_model.GeNNModel.init_sparse_time.

- 2. Backends now generate <code>getFreeDeviceMemBytes()</code> function to allow free device memory to be queried from user simulation code. This is also exposed to Python via <code>GeNNModel.free_device_comem_bytes</code> property.
- GeNN preferences are now fully exposed to PyGeNN by passing kwargs to pygenn.genn_model.Ge
 NNModel. init .
- 4. Logging level can now be seperately specified for GeNN, the code generator, the SpineML generator and the backend and is accessible from PyGeNN.
- 5. CodeGenerator::PreferencesBase::enableBitmaskOptimisations flag enables an alternative algorithm for updating synaptic matrices implemented with SynapseMatrixConnectivity
 ::BITMASK which performs better on smaller GPUs and CPUs. If you are manually initialising matrices this adds padding to align words to rows of the matrix.
- 6. SynapseMatrixConnectivity::PROCEDURAL and SynapseMatrixWeight::PROCEDURAL allow connectivity and synaptic weights to be generated on the fly rather than stored in memory.
- 7. CodeGenerator::PreferencesBase::automaticCopy flag allows models to be built without the need for explicitly copying data between host and device. For CUDA backend this uses unified memory (https://devblogs.nvidia.com/unified-memory-cuda-beginners/).
- 8. Speed of code compilation can be improved by building using multiple threads. This is now done everywhere where make or MSBuild is invocated automatically.

Bug fixes:

- 1. Fixed several bugs in extra global parameter implementation in PyGeNN.
- 2. Floating point min and max should be calculated with fmax and fmin in code snippets fixed in several models and user projects.
- 3. Fixed issues with version of numpy required in PyGeNN (previously held back by an issue with PyNN)

Release Notes for GeNN v4.1.0

This release adds a number of new features to GeNN and its SpineML interface as well as fixing a number of bugs that have been identified since the 4.0.2 release.

User Side Changes

- 1. The SpineML simulator could previously only be used as a standalone application. This functionality is now provided by the spineml_simulator library and can be used via the SpineMLSimulator::Simulator class.
- 2. When declaring a model's variables using SET_VAR, they can be marked as read-only by adding a 3rd parameter set to VarAccess::READ_ONLY to enable further optimisations. See Defining your own neuron type for more details.
- 3. Previously, unless models were very large or had very high spike rates, using SynapseGroup::
 SpanType::PRESYNAPTIC typically resulted in poor performance. When using the CUDA backend,
 SynapseGroup::setNumThreadsPerSpike can now be used to increase parallelism.

8 Release Notes 17

4. There were useful helpers for recording spikes (SpikeRecorder) and timing (Timer, Timer Accumulate) in "userproject\include" which were not easily usable to user projects. genn-create-userproject. sh and genn-create-userproject.bat now have a "-u" option which puts this in the include path of the generated project.

- 5. Timing information generated when ModelSpec::setTiming is enabled was not accesible to SpineML models. This is now exposed through the SpineMLSimulator::Simulator class.
- 6. Neuron population state variables were not easily accessible if the populations had incoming or outgoing connections with synaptic delays. Additional helper functions are now generated. See Creating and simulating a network model for more details.
- 7. SpineML interface will now use heterogeneous dendritic delay system introduced in GeNN 3.2.0 if required.
- 8. Add CodeGenerator::CUDA::Preferences::generateLineInfo option to output CUDA line info for profiling.
- 9. CUDA backend supports half datatype allowing memory savings through reduced precision. Host C++ code does not support half-precision types so such state variables must have their location set to Varc-Location::DEVICE.
- 10. If ModelSpec::setDefaultNarrowSparseIndEnabled is set on a model or SynapseGroup← ::setNarrowSparseIndEnabled is set on an individual synapse population with sparse connectivity, 16-bit numbers will be used for postsynaptic indices, almost halving memory requirements.
- 11. Manual selection of CUDA devices is now exposed to PyGeNN via the pygenn.genn_model.GeNN← Model.selected_gpu property.

Bug fixes:

- 1. Fixed incomaptibilies with GCC 4.9
- 2. Fixed bug that occured if derived parameters were used in spike-like-event threshold conditions.
- Fixed bug that occured when merging of postsynaptic models is enabled and GeNN decides to employ specific CUDA optimizations.
- 4. Increase maximum supported CUDA kernel grid size a bug was limiting this to 65536.
- 5. Fixed bugs in timing system when used with synapse dynamics kernels.

Release Notes for GeNN v4.0.2

This release fixes several small issues with the generation of binary wheels for Python:

Bug fixes:

- 1. There was a conflict between the versions of numpy used to build the wheels and the version required for the PyGeNN packages
- 2. Wheels were renamed to include the CUDA version which broke them.

Release Notes for GeNN v4.0.1

This release fixes several small bugs found in GeNN 4.0.0 and implements some small features:

User Side Changes

- 1. Improved detection and handling of errors when specifying model parameters and values in PyGeNN.
- 2. SpineML simulator is now implemented as a library which can be used directly from user applications as well as from command line tool.

Bug fixes:

- 1. Fixed typo in pygenn.genn_model.GennModel.push_var_to_device function in PyGeNN.
- 2. Fixed broken support for Visual C++ 2013.
- 3. Fixed zero-copy mode.
- 4. Fixed typo in tutorial 2.

Release Notes for GeNN v4.0.0

This release is the result of a second round of fairly major refactoring which we hope will make GeNN easier to use and allow it to be extended more easily in future. However, especially if you have been using GeNN 2.XX syntax, it breaks backward compatibility.

User Side Changes

- 1. Totally new build system make install can be used to install GeNN to a system location on Linux and Mac and Windows projects work much better in the Visual Studio IDE.
- 2. Python interface now supports Windows and can be installed using binary 'wheels' (see Python interface (PyGeNN) for more details).
- 3. No need to call ${\tt initGeNN}$ () at start and ${\tt model.finalize}$ () at end of all models.
- 4. Initialisation system simplified if you specify a value or initialiser for a variable or sparse connectivity, it will be initialised by your chosen backend. If you mark it as uninitialised, it is up to you to initialize it in user code between the calls to initialize() and initializeSparse() (where it will be copied to device).
- genn-create-user-project helper scripts to create Makefiles or MSBuild projects for building user code
- 6. State variables can now be pushed and pulled individually using the pull<var name><neuron or synapse name>FromDevice() and push<var name><neuron or synapse name>To← Device() functions.
- 7. Management of extra global parameter arrays has been somewhat automated (see Extra Global Parameters for more details).
- 8. GENN_PREFERENCES is no longer a namespace it's a global struct so members need to be accessed with . rather than ::.
- 9. NeuronGroup, SynapseGroup, CurrentSource and NNmodel all previously exposed a lot of methods that the user wasn't *supposed* to call but could. These have now all been made protected and are exposed to GeNN internals using derived classes (NeuronGroupInternal, SynapseGroupInternal, CurrentSourceInternal, ModelSpecInternal) that make them public using using directives.
- 10. Auto-refractory behaviour was controlled using GENN_PREFERENCES::autoRefractory, this is now controlled on a per-neuron-model basis using the SET_NEEDS_AUTO_REFRACTORY macro.
- 11. The functions used for pushing and pulling have been unified somewhat this means that copyState←
 ToDevice and copyStateFromDevice functions no longer copy spikes and pus<neuron or
 synapse name>SpikesToDevice and pull<neuron or synapse name>SpikesFrom←
 Device no longer copy spike times or spike-like events.

8 Release Notes 19

12. Standard models of leaky-integrate-and-fire neuron (NeuronModels::LIF) and of exponentially shaped postsynaptic current (PostsynapticModels::ExpCurr) have been added.

13. When a model is built using the CUDA backend, the device it was built for is stored using it's PCI bus ID so it will always use the same device.

Deprecations

- Yale-format sparse matrices are no longer supported.
- 2. GeNN 2.X syntax for implementing neuron and synapse models is no longer supported.
- \$(addtoinSyn) = X; \$(updatelinsyn); idiom in weight update models has been replaced by function style \$(addToInSyn, X);.

Release Notes for GeNN v3.3.0

This release is intended as the last service release for GeNN 3.X.X. Fixes for serious bugs **may** be backported if requested but, otherwise, development will be switching to GeNN 4.

User Side Changes

- 1. Postsynaptic models can now have Extra Global Parameters.
- 2. Gamma distribution can now be sampled using \$ (gennrand_gamma, a). This can be used to initialise variables using InitVarSnippet::Gamma.
- 3. Experimental Python interface All features of GeNN are now exposed to Python through the pygenn module (see Python interface (PyGeNN) for more details).

Bug fixes:

- 1. Devices with Streaming Multiprocessor version 2.1 (compute capability 2.0) now work correctly in Windows.
- 2. Seeding of on-device RNGs now works correctly.
- 3. Improvements to accuracy of memory usage estimates provided by code generator.

Release Notes for GeNN v3.2.0

This release extends the initialisation system introduced in 3.1.0 to support the initialisation of sparse synaptic connectivity, adds support for networks with more sophisticated models of synaptic plasticity and delay as well as including several other small features, optimisations and bug fixes for certain system configurations. This release supports $GCC \ge 4.9.1$ on Linux, Visual Studio ≥ 2013 on Windows and recent versions of Clang on Mac OS X.

User Side Changes

- Sparse synaptic connectivity can now be initialised using small snippets of code run either on GPU or CPU.
 This can save significant amounts of initialisation time for large models. See Sparse connectivity initialisation for more details.
- New 'ragged matrix' data structure for representing sparse synaptic connections supports initialisation using
 new sparse synaptic connecivity initialisation system and enables future optimisations. See Synaptic matrix
 types for more details.
- 3. Added support for pre and postsynaptic state variables for weight update models to allow more efficient implementatation of trace based STDP rules. See Defining a new weight update model for more details.

- 4. Added support for devices with Compute Capability 7.0 (Volta) to block-size optimizer.
- 5. Added support for a new class of 'current source' model which allows non-synaptic input to be efficiently injected into neurons. See Current source models for more details.
- 6. Added support for heterogeneous dendritic delays. See Defining a new weight update model for more details.
- 7. Added support for (homogeneous) synaptic back propagation delays using SynapseGroup::setBack← PropDelaySteps.
- 8. For long simulations, using single precision to represent simulation time does not work well. Added N← Nmodel::setTimePrecision to allow data type used to represent time to be set independently.

Optimisations

- 1. GENN_PREFERENCES::mergePostsynapticModels flag can be used to enable the merging together of postsynaptic models from a neuron population's incoming synapse populations improves performance and saves memory.
- 2. On devices with compute capability > 3.5 GeNN now uses the read only cache to improve performance of postsynaptic learning kernel.

Bug fixes:

- 1. Fixed bug enabling support for CUDA 9.1 and 9.2 on Windows.
- 2. Fixed bug in SynDelay example where membrane voltage went to NaN.
- 3. Fixed bug in code generation of ${\tt SCALAR_MIN}$ and ${\tt SCALAR_MAX}$ values.
- 4. Fixed bug in substitution of trancendental functions with single-precision variants.
- 5. Fixed various issues involving using spike times with delayed synapse projections.

Release Notes for GeNN v3.1.1

This release fixes several small bugs found in GeNN 3.1.0 and implements some small features:

User Side Changes

1. Added new synapse matrix types SPARSE_GLOBALG_INDIVIDUAL_PSM, DENSE_GLOBALG_IND

IVIDUAL_PSM and BITMASK_GLOBALG_INDIVIDUAL_PSM to handle case where synapses with no
individual state have a postsynaptic model with state variables e.g. an alpha synapse. See Synaptic matrix
types for more details.

Bug fixes

- 1. Correctly handle aliases which refer to other aliases in SpineML models.
- 2. Fixed issues with presynaptically parallelised synapse populations where the postsynaptic population is small enough for input to be accumulated in shared memory.

Release Notes for GeNN v3.1.0

This release builds on the changes made in 3.0.0 to further streamline the process of building models with GeNN and includes several bug fixes for certain system configurations.

8 Release Notes 21

User Side Changes

1. Support for simulating models described using the SpineML model description language with GeNN (see SpineML and SpineCreator for more details).

- 2. Neuron models can now sample from uniform, normal, exponential or log-normal distributions these calls are translated to cuRAND when run on GPUs and calls to the C++11 < random > library when run on CPU. See Defining your own neuron type for more details.
- 3. Model state variables can now be initialised using small *snippets* of code run either on GPU or CPU. This can save significant amounts of initialisation time for large models. See Defining a new variable initialisation snippet for more details.
- 4. New MSBuild build system for Windows makes developing user code from within Visual Studio much more streamlined. See Debugging suggestions for more details.

Bug fixes:

- 1. Workaround for bug found in Glibc 2.23 and 2.24 which causes poor performance on some 64-bit Linux systems (namely on Ubuntu 16.04 LTS).
- 2. Fixed bug encountered when using extra global variables in weight updates.

Release Notes for GeNN v3.0.0

This release is the result of some fairly major refactoring of GeNN which we hope will make it more user-friendly and maintainable in the future.

User Side Changes

- 1. Entirely new syntax for defining models hopefully terser and less error-prone (see updated documentation and examples for details).
- 2. Continuous integration testing using Jenkins automated testing and code coverage calculation calculated automatically for Github pull requests etc.
- Support for using Zero-copy memory for model variables. Especially on devices such as NVIDIA Jetson TX1
 with no physical GPU memory this can significantly improve performance when recording data or injecting it
 to the simulation from external sensors.

Release Notes for GeNN v2.2.3

This release includes minor new features and several bug fixes for certain system configurations.

User Side Changes

- 1. Transitioned feature tests to use Google Test framework.
- 2. Added support for CUDA shader model 6.X

Bug fixes:

- 1. Fixed problem using GeNN on systems running 32-bit Linux kernels on a 64-bit architecture (Nvidia Jetson modules running old software for example).
- 2. Fixed problem linking against CUDA on Mac OS X El Capitan due to SIP (System Integrity Protection).
- 3. Fixed problems with support code relating to its scope and usage in spike-like event threshold code.
- 4. Disabled use of C++ regular expressions on older versions of GCC.

Release Notes for GeNN v2.2.2

This release includes minor new features and several bug fixes for certain system configurations.

User Side Changes

- 1. Added support for the new version (2.0) of the Brian simulation package for Python.
- 2. Added a mechanism for setting user-defined flags for the C++ compiler and NVCC compiler, via GENN_PR← EFERENCES.

Bug fixes:

- 1. Fixed a problem with atomicAdd() redefinitions on certain CUDA runtime versions and GPU configurations.
- 2. Fixed an incorrect bracket placement bug in code generation for certain models.
- 3. Fixed an incorrect neuron group indexing bug in the learning kernel, for certain models.
- 4. The dry-run compile phase now stores temporary files in the current directory, rather than the temp directory, solving issues on some systems.
- 5. The LINK_FLAGS and INCLUDE_FLAGS in the common windows makefile include 'makefile_commin
 —win.mk' are now appended to, rather than being overwritten, fixing issues with custom user makefiles on
 Windows.

Release Notes for GeNN v2.2.1

This bugfix release fixes some critical bugs which occur on certain system configurations.

Bug fixes:

- 1. (important) Fixed a Windows-specific bug where the CL compiler terminates, incorrectly reporting that the nested scope limit has been exceeded, when a large number of device variables need to be initialised.
- 2. (important) Fixed a bug where, in certain circumstances, outdated generateALL objects are used by the Makefiles, rather than being cleaned and replaced by up-to-date ones.
- 3. (important) Fixed an 'atomicAdd' redeclared or missing bug, which happens on certain CUDA architectures when using the newest CUDA 8.0 RC toolkit.
- 4. (minor) The SynDelay example project now correctly reports spike indexes for the input group.

Please refer to the full documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.2

This release includes minor new features, some core code improvements and several bug fixes on GeNN v2.1.

8 Release Notes 23

User Side Changes

1. GeNN now analyses automatically which parameters each kernel needs access to and these and only these are passed in the kernel argument list in addition to the global time t. These parameters can be a combination of extraGlobalNeuronKernelParameters and extraGlobalSynapseKernelParameters in either neuron or synapse kernel. In the unlikely case that users wish to call kernels directly, the correct call can be found in the stepTimeGPU() function.

Reflecting these changes, the predefined Poisson neurons now simply have two extraGlobalNeuron Parameter rates and offset which replace the previous custom pointer to the array of input rates and integer offset to indicate the current input pattern. These extraGlobalNeuronKernelParameters are passed to the neuron kernel automatically, but the rates themselves within the array are of course not updated automatically (this is exactly as before with the specifically generated kernel arguments for Poisson neurons).

The concept of "directInput" has been removed. Users can easily achieve the same functionality by adding an additional variable (if there are individual inputs to neurons), an extraGlobalNeuronParameter (if the input is homogeneous but time dependent) or, obviously, a simple parameter if it's homogeneous and constant.

Note

The global time variable "t" is now provided by GeNN; please make sure that you are not duplicating its definition or shadowing it. This could have severe consequences for simulation correctness (e.g. time not advancing in cases of over-shadowing).

- 2. We introduced the namespace GENN_PREFERENCES which contains variables that determine the behaviour of GeNN.
- 3. We introduced a new code snippet called "supportCode" for neuron models, weightupdate models and post-synaptic models. This code snippet is intended to contain user-defined functions that are used from the other code snippets. We advise where possible to define the support code functions with the CUDA keywords "__ host__ __device__" so that they are available for both GPU and CPU version. Alternatively one can define separate versions for **host** and **device** in the snippet. The snippets are automatically made available to the relevant code parts. This is regulated through namespaces so that name clashes between different models do not matter. An exception are hash defines. They can in principle be used in the supportCode snippet but need to be protected specifically using ifndef. For example

```
#ifndef clip(x)
#define clip(x) x > 10.0? 10.0 : x
#endif
```

Note

If there are conflicting definitions for hash defines, the one that appears first in the GeNN generated code will then prevail.

- 4. The new convenience macros spikeCount_XX and spike_XX where "XX" is the name of the neuron group are now also available for events: spikeEventCount_XX and spikeEvent_XX. They access the values for the current time step even if there are synaptic delays and spikes events are stored in circular queues.
- 5. The old buildmodel.[sh|bat] scripts have been superseded by new genn-buildmodel.[sh|bat] scripts. These scripts accept UNIX style option switches, allow both relative and absolute model file paths, and allow the user to specify the directory in which all output files are placed (-o <path>). Debug (-d), CPU-only (-c) and show help (-h) are also defined.
- 6. We have introduced a CPU-only "-c" genn-buildmodel switch, which, if it's defined, will generate a GeNN version that is completely independent from CUDA and hence can be used on computers without CUDA installation or CUDA enabled hardware. Obviously, this then can also only run on CPU. CPU only mode can either be switched on by defining CPU_ONLY in the model description file or by passing appropriate parameters during the build, in particular

```
\label{local_general} $$\operatorname{genn-buildmodel.[sh|bat] \ \cdotspace} $$\operatorname{cpu_ONLY=1}$$
```

- 7. The new genn-buildmodel "-o" switch allows the user to specify the output directory for all generated files the default is the current directory. For example, a user project could be in '/home/genn_project', whilst the GeNN directory could be '/usr/local/genn'. The GeNN directory is kept clean, unless the user decides to build the sample projects inside of it without copying them elsewhere. This allows the deployment of GeNN to a read-only directory, like '/usr/local' or 'C:\Program Files'. It also allows multiple users i.e. on a compute cluster to use GeNN simultaneously, without overwriting each other's code-generation files, etcetera.
- 8. The ARM architecture is now supported e.g. the NVIDIA Jetson development platform.
- 9. The NVIDIA CUDA SM 5* (Maxwell) architecture is now supported.
- 10. An error is now thrown when the user tries to use double precision floating-point numbers on devices with architecture older than SM 13, since these devices do not support double precision.
- 11. All GeNN helper functions and classes, such as toString() and NNmodel, are defined in the header files at genn/lib/include/, for example stringUtils.h and modelSpec.h, which should be individually included before the functions and classes may be used. The functions and classes are actually implementated in the static library genn\lib\lib\genn.lib (Windows) or genn/lib/lib/libgenn.a (Mac, Linux), which must be linked into the final executable if any GeNN functions or classes are used.
- 12. In the modelDefinition() file, only the header file modelSpec.h should be included i.e. not the source file modelSpec.cc. This is because the declaration and definition of NNmodel, and associated functions, has been separated into modelSpec.h and modelSpec.cc, respectively. This is to enable NNmodel code to be precompiled separately. Henceforth, only the header file modelSpec.h should be included in model definition files!
- 13. In the modelDefinition() file, DT is now preferrably defined using model.setDT(<val>);, rather than #defineDT(<val>), in order to prevent problems with DT macro redefinition. For backward-compatibility reasons, the old #defineDT(<val>) method may still be used, however users are advised to adopt the new method.
- 14. In preparation for multi-GPU support in GeNN, we have separated out the compilation of generated code from user-side code. This will eventually allow us to optimise and compile different parts of the model with different CUDA flags, depending on the CUDA device chosen to execute that particular part of the model. As such, we have had to use a header file definitions.h as the generated code interface, rather than the runner.cc file. In practice, this means that user-side code should include myModel_CODE / E/definitions.h, rather than myModel_CODE/runner.cc. Including runner.cc will likely result in pages of linking errors at best!

Developer Side Changes

- Blocksize optimization and device choice now obtain the ptxas information on memory usage from a CUDA driver API call rather than from parsing ptxas output of the nvcc compiler. This adds robustness to any change in the syntax of the compiler output.
- 2. The information about device choice is now stored in variables in the namespace GENN_PREFERENCES. This includes chooseDevice, optimiseBlockSize, optimizeCode, debugCode, showPtxcolor, defaultDevice. asGoodAsZero has also been moved into this namespace.
- 3. We have also introduced the namespace GENN_FLAGS that contains unsigned int variables that attach names to numeric flags that can be used within GeNN.
- 4. The definitions of all generated variables and functions such as pullXXXStateFromDevice etc, are now generated into definitions.h. This is useful where one wants to compile separate object files that cannot all include the full definitions in e.g. "runnerGPU.cc". One example where this is useful is the brian2genn interface.
- 5. A number of feature tests have been added that can be found in the featureTests directory. They can be run with the respective runTests.sh scripts. The cleanTests.sh scripts can be used to remove all generated code after testing.

8 Release Notes 25

Improvements

1. Improved method of obtaining ptxas compiler information on register and shared memory usage and an improved algorithm for estimating shared memory usage requirements for different block sizes.

- 2. Replaced pageable CPU-side memory with page-locked memory. This can significantly speed up simulations in which a lot of data is regularly copied to and from a CUDA device.
- 3. GeNN library objects and the main generateALL binary objects are now compiled separately, and only when a change has been made to an object's source, rather than recompiling all software for a minor change in a single source file. This should speed up compilation in some instances.

Bug fixes:

- 1. Fixed a minor bug with delayed synapses, where delaySlot is declared but not referenced.
- 2. We fixed a bug where on rare occasions a synchronisation problem occurred in sparse synapse populations.
- 3. We fixed a bug where the combined spike event condition from several synapse populations was not assembled correctly in the code generation phase (the parameter values of the first synapse population over-rode the values of all other populations in the combined condition).

Please refer to the $\verb|full|$ documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.1

This release includes some new features and several bug fixes on GeNN v2.0.

User Side Changes

- 1. Block size debugging flag and the asGoodAsZero variables are moved into include/global.h.
- 2. NGRADSYNAPSES dynamics have changed (See Bug fix #4) and this change is applied to the example projects. If you are using this synapse model, you may want to consider changing model parameters.
- 3. The delay slots are now such that NO_DELAY is 0 delay slots (previously 1) and 1 means an actual delay of 1 time step.
- 4. The convenience function convertProbabilityToRandomNumberThreshold(float *, uint64_t *, int) was changed so that it actually converts firing probability/timestep into a threshold value for the GeNN random number generator (as its name always suggested). The previous functionality of converting a *rate* in kHz into a firing threshold number for the GeNN random number generator is now provided with the name convertRateToRandomNumberThreshold(float *, uint64_t *, int)
- 5. Every model definition function modelDefinition() now needs to end with calling NNmodel←::finalize() for the defined network model. This will lock down the model and prevent any further changes to it by the supported methods. It also triggers necessary analysis of the model structure that should only be performed once. If the finalize() function is not called, GeNN will issue an error and exit before code generation.
- 6. To be more consistent in function naming the pull\<SYNAPSENAME\>FromDevice and push\<S\U0048 YNAPSENAME\>ToDevice have been renamed to pull\<SYNAPSENAME\>StateFromDevice and push\<SYNAPSENAME\>StateToDevice. The old versions are still supported through macro definitions to make the transition easier.
- 7. New convenience macros are now provided to access the current spike numbers and identities of neurons that spiked. These are called spikeCount_XX and spike_XX where "XX" is the name of the neuron group. They access the values for the current time step even if there are synaptic delays and spikes are stored in circular queues.

- 8. There is now a pre-defined neuron type "SPIKECOURCE" which is empty and can be used to define PyNN style spike source arrays.
- 9. The macros FLOAT and DOUBLE were replaced with GENN_FLOAT and GENN_DOUBLE due to name clashes with typedefs in Windows that define FLOAT and DOUBLE.

Developer Side Changes

1. We introduced a file definitions.h, which is generated and filled with useful macros such as spkQuePtrShift which tells users where in the circular spike queue their spikes start.

Improvements

- 1. Improved debugging information for block size optimisation and device choice.
- 2. Changed the device selection logic so that device occupancy has larger priority than device capability version.
- 3. A new HH model called TRAUBMILES_PSTEP where one can set the number of inner loops as a parameter is introduced. It uses the TRAUBMILES_SAFE method.
- 4. An alternative method is added for the insect olfaction model in order to fix the number of connections to a maximum of 10K in order to avoid negative conductance tails.
- 5. We introduced a preprocessor define directive for an "int_" function that translates floating points to integers.

Bug fixes:

- 1. AtomicAdd replacement for old GPUs were used by mistake if the model runs in double precision.
- 2. Timing of individual kernels is fixed and improved.
- 3. More careful setting of maximum number of connections in sparse connectivity, covering mixed dense/sparse network scenarios.
- 4. NGRADSYNAPSES was not scaling correctly with varying time step.
- 5. Fixed a bug where learning kernel with sparse connectivity was going out of range in an array.
- 6. Fixed synapse kernel name substitutions where the "dd_" prefix was omitted by mistake.

Please refer to the full documentation for further details, tutorials and complete code documentation.

Release Notes for GeNN v2.0

Version 2.0 of GeNN comes with a lot of improvements and added features, some of which have necessitated some changes to the structure of parameter arrays among others.

User Side Changes

- 1. Users are now required to call initGeNN () in the model definition function before adding any populations to the neuronal network model.
- 2. glbscnt is now call glbSpkCnt for consistency with glbSpkEvntCnt.
- 3. There is no longer a privileged parameter Epre. Spike type events are now defined by a code string spk EvntThreshold, the same way proper spikes are. The only difference is that Spike type events are specific to a synapse type rather than a neuron type.

8 Release Notes 27

4. The function setSynapseG has been deprecated. In a GLOBALG scenario, the variables of a synapse group are set to the initial values provided in the modeldefinition function.

 Due to the split of synaptic models into weightUpdateModel and postSynModel, the parameter arrays used during model definition need to be carefully split as well so that each side gets the right parameters. For example, previously

would define the parameter array of three parameters, Erev, Epre, and tau_S for a synapse of type NSYNAPSE. This now needs to be "split" into

i.e. parameters <code>Erev</code> and <code>tau_S</code> are moved to the post-synaptic model and its parameter array of two parameters. <code>Epre</code> is discontinued as a parameter for <code>NSYNAPSE</code>. As a consequence the weightupdate model of <code>NSYNAPSE</code> has no parameters and one can pass <code>NULL</code> for the parameter array in <code>addSynapse</code> <code>Population</code>. The correct parameter lists for all defined neuron and synapse model types are listed in the <code>User Manual</code>.

Note

If the parameters are not redefined appropriately this will lead to uncontrolled behaviour of models and likely to segmentation faults and crashes.

- 6. Advanced users can now define variables as type scalar when introducing new neuron or synapse types. This will at the code generation stage be translated to the model's floating point type (ftype), float or double. This works for defining variables as well as in all code snippets. Users can also use the expressions SCALAR_MAX and SCALAR_MIN for FLT_MIN, FLT_MAX, DBL_MIN and DBL_MAX, respectively. Corresponding definitions of scalar, SCALAR_MIN and SCALAR_MAX are also available for user-side code whenever the code-generated file runner.cc has been included.
- 7. The example projects have been re-organized so that wrapper scripts of the <code>generate_run</code> type are now all located together with the models they run instead of in a common <code>tools</code> directory. Generally the structure now is that each example project contains the wrapper script <code>generate_run</code> and a <code>model</code> subdirectory which contains the model description file and the user side code complete with Makefiles for Unix and Windows operating systems. The generated code will be deposited in the <code>model subdirectory</code> in its <code>own modelname_CODE</code> folder. Simulation results will always be deposited in a new sub-folder of the main project directory.
- 8. The addSynapsePopulation (...) function has now more mandatory parameters relating to the introduction of separate weightupdate models (pre-synaptic models) and postynaptic models. The correct syntax for the addSynapsePopulation (...) can be found with detailed explanations in teh User Manual.
- We have introduced a simple performance profiling method that users can employ to get an overview over the differential use of time by different kernels. To enable the timers in GeNN generated code, one needs to declare

```
networkmodel.setTiming(TRUE);
```

This will make available and operate GPU-side cudeEvent based timers whose cumulative value can be found in the double precision variables <code>neuron_tme</code>, <code>synapse_tme</code> and <code>learning_tme</code>. They measure the accumulated time that has been spent calculating the neuron kernel, synapse kernel and learning kernel, respectively. CPU-side timers for the simulation functions are also available and their cumulative values can be obtained through

```
float x= sdkGetTimerValue(&neuron_timer);
float y= sdkGetTimerValue(&synapse_timer);
float z= sdkGetTimerValue(&learning_timer);
```

The Insect olfaction model example shows how these can be used in the user-side code. To enable timing profiling in this example, simply enable it for GeNN:

```
in MBodyl.cc's modelDefinition function and define the macro TIMING in classol_sim.h
#define TIMING
```

This will have the effect that timing information is output into $OUTNAME_output/OUTNAME. \leftarrow timingprofile.$

Developer Side Changes

- allocateSparseArrays() has been changed to take the number of connections, connN, as an argument rather than expecting it to have been set in the Connetion struct before the function is called as was the arrangement previously.
- 2. For the case of sparse connectivity, there is now a reverse mapping implemented with revers index arrays and a remap array that points to the original positions of variable values in teh forward array. By this mechanism, revers lookups from post to pre synaptic indices are possible but value changes in the sparse array values do only need to be done once.
- 3. SpkEvnt code is no longer generated whenever it is not actually used. That is also true on a somewhat finer granularity where variable queues for synapse delays are only maintained if the corresponding variables are used in synaptic code. True spikes on the other hand are always detected in case the user is interested in them.

Please refer to the full documentation for further details, tutorials and complete code documentation.

Previous | Top | Next

9 User Manual

9.1 Contents

- · Introduction
- · Defining a network model
- Neuron models
- · Weight update models
- Postsynaptic integration methods
- · Current source models
- · Synaptic matrix types
- · Variable initialisation
- · Sparse connectivity initialisation

9.2 Introduction 29

9.2 Introduction

GeNN is a software library for facilitating the simulation of neuronal network models on NVIDIA CUDA enabled GPU hardware. It was designed with computational neuroscience models in mind rather than artificial neural networks. The main philosophy of GeNN is two-fold:

- 1. GeNN relies heavily on code generation to make it very flexible and to allow adjusting simulation code to the model of interest and the GPU hardware that is detected at compile time.
- 2. GeNN is lightweight in that it provides code for running models of neuronal networks on GPU hardware but it leaves it to the user to write a final simulation engine. It so allows maximal flexibility to the user who can use any of the provided code but can fully choose, inspect, extend or otherwise modify the generated code. They can also introduce their own optimisations and in particular control the data flow from and to the GPU in any desired granularity.

This manual gives an overview of how to use GeNN for a novice user and tries to lead the user to more expert use later on. With that we jump right in.

Previous | Top | Next

9.3 Defining a network model

A network model is defined by the user by providing the function

```
void modelDefinition(ModelSpec &model)
```

in a separate file, such as MyModel.cc. In this function, the following tasks must be completed:

1. The name of the model must be defined:

```
model.setName("MyModel");
```

- 2. Neuron populations (at least one) must be added (see <u>Defining neuron populations</u>). The user may add as many neuron populations as they wish. If resources run out, there will not be a warning but GeNN will fail. However, before this breaking point is reached, GeNN will make all necessary efforts in terms of block size optimisation to accommodate the defined models. All populations must have a unique name.
- 3. Synapse populations (zero or more) can be added (see Defining synapse populations). Again, the number of synaptic connection populations is unlimited other than by resources.

9.3.1 Defining neuron populations

Neuron populations are added using the function

```
model.addNeuronPopulation<NeuronModel>(name, num, paramValues, varInitialisers);
```

where the arguments are:

- NeuronModel: Template argument specifying the type of neuron model These should be derived off NeuronModels::Base and can either be one of the standard models or user-defined (see Neuron models).
- const string &name: Unique name of the neuron population
- \bullet unsigned int size: number of neurons in the population
- NeuronModel::ParamValues paramValues: Parameters of this neuron type

• NeuronModel::VarValues varInitialisers: Initial values or initialisation snippets for variables of this neuron type

The user may add as many neuron populations as the model necessitates. They must all have unique names. The possible values for the arguments, predefined models and their parameters and initial values are detailed Neuron models below.

9.3.2 Defining synapse populations

Synapse populations are added with the function

where the arguments are

- WeightUpdateModel: Template parameter specifying the type of weight update model. These should be derived off WeightUpdateModels::Base and can either be one of the standard models or user-defined (see Weight update models).
- PostsynapticModel: Template parameter specifying the type of postsynaptic integration model. These should be derived off PostsynapticModels::Base and can either be one of the standard models or user-defined (see Postsynaptic integration methods).
- const string &name: The name of the synapse population
- unsigned int mType: How the synaptic matrix is stored. See Synaptic matrix types for available options.
- unsigned int delay: Homogeneous (axonal) delay for synapse population (in terms of the simulation time step DT).
- const string preName: Name of the (existing!) pre-synaptic neuron population.
- const string postName: Name of the (existing!) post-synaptic neuron population.
- WeightUpdateModel::ParamValues weightParamValues: The parameter values (common to all synapses of the population) for the weight update model.
- WeightUpdateModel::VarValues weightVarInitialisers: Initial values or initialisation snippets for the weight update model's state variables
- WeightUpdateModel::PreVarValues weightPreVarInitialisers: Initial values or initialisation snippets for the weight update model's presynaptic state variables
- WeightUpdateModel::PostVarValues weightPostVarInitialisers: Initial values or initialisation snippets for the weight update model's postsynaptic state variables
- PostsynapticModel::ParamValues postsynapticParamValues: The parameter values (common to all postsynaptic neurons) for the postsynaptic model.
- PostsynapticModel::VarValues postsynapticVarInitialisers: Initial values or initialisation snippets for variables for the postsynaptic model's state variables
- InitSparseConnectivitySnippet::Init connectivityInitialiser: Optional argument, specifying the initialisation snippet for synapse population's sparse connectivity (see Sparse connectivity initialisation).

The ModelSpec::addSynapsePopulation() function returns a pointer to the newly created SynapseGroup object which can be further configured, namely with:

9.4 Neuron models 31

• SynapseGroup::setMaxConnections() and SynapseGroup::setMaxSourceConnections() to configure the maximum number of rows and columns respectively allowed in the synaptic matrix - this can improve performance and reduce memory usage when using SynapseMatrixConnectivity::SPARSE connectivity (see Synaptic matrix types).

Note

When using a sparse connectivity initialisation snippet, these values are set automatically.

- SynapseGroup::setMaxDendriticDelayTimesteps() sets the maximum dendritic delay (in terms of the simulation time step DT) allowed for synapses in this population. No values larger than this should be passed to the delay parameter of the addToDenDelay function in user code (see Defining a new weight update model).
- SynapseGroup::setSpanType() sets how incoming spike processing is parallelised for this synapse group.
 The default SynapseGroup::SpanType::POSTSYNAPTIC is nearly always the best option, but SynapseGroup::SpanType::PRESYNAPTIC may perform better when there are large numbers of spikes every timestep or very few postsynaptic neurons.

Note

If the synapse matrix uses one of the "GLOBALG" types then the global value of the synapse parameters are taken from the initial value provided in weightVarInitialisers therefore these must be constant rather than sampled from a distribution etc.

Previous | Top | Next

9.4 Neuron models

There is a number of predefined models which can be used with the ModelSpec::addNeuronGroup function:

• NeuronModels::RulkovMap

• NeuronModels::Izhikevich

· NeuronModels::IzhikevichVariable

• NeuronModels::LIF

• NeuronModels::SpikeSource

· NeuronModels::PoissonNew

• NeuronModels::TraubMiles

NeuronModels::TraubMilesFast

· NeuronModels::TraubMilesAlt

NeuronModels::TraubMilesNStep

9.4.1 Defining your own neuron type

In order to define a new neuron type for use in a GeNN application, it is necessary to define a new class derived from NeuronModels::Base. For convenience the methods this class should implement can be implemented using macros:

• DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS): declared the boilerplate code required for the model e.g. the correct specialisations of NewModels::ValueBase used to wrap the neuron model parameters and values.

- SET_SIM_CODE(SIM_CODE): where SIM_CODE contains the code for executing the integration of the
 model for one time stepWithin this code string, variables need to be referred to by \$(NAME), where NA

 ME is the name of the variable as defined in the vector varNames. The code may refer to the predefined
 primitives DT for the time step size and for the total incoming synaptic current. It can also refer to a unique
 ID (within the population) using .
- SET_THRESHOLD_CONDITION_CODE(THRESHOLD_CONDITION_CODE) defines the condition for true spike detection.
- SET_PARAM_NAMES() defines the names of the model parameters. If defined as NAME here, they can then be referenced as \$(NAME) in the code string. The length of this list should match the NUM_PARAM specified in DECLARE_MODEL. Parameters are assumed to be always of type double.
- SET_VARS() defines the names, type strings (e.g. "float", "double", etc) and (optionally) access mode of the neuron state variables. The type string "scalar" can be used for variables which should be implemented using the precision set globally for the model with ModelSpec::setPrecision. The variables defined here as NAME can then be used in the syntax \$(NAME) in the code string. If the access mode is set to VarAccess::Reelan_ONLY, GeNN applies additional optimisations and models should not write to it.
- SET_NEEDS_AUTO_REFRACTORY() defines whether the neuron should include an automatic refractory
 period to prevent it emitting spikes in successive timesteps.

For example, using these macros, we can define a leaky integrator $\tau \frac{dV}{dt} = -V + I_{\rm syn}$ solved using Euler's method:

```
class LeakyIntegrator : public NeuronModels::Base
{
public:
    DECLARE_MODEL(LeakyIntegrator, 1, 1);

    SET_SIM_CODE("$(V)+= (-$(V)+$(Isyn))*(DT/$(tau));");

    SET_THRESHOLD_CONDITION_CODE("$(V) >= 1.0");

    SET_PARAM_NAMES({"tau"});

    SET_VARS({{"V", "scalar", VarAccess::READ_WRITE}});
};
```

Additionally "dependent parameters" can be defined. Dependent parameters are a mechanism for enhanced efficiency when running neuron models. If parameters with model-side meaning, such as time constants or conductances always appear in a certain combination in the model, then it is more efficient to pre-compute this combination and define it as a dependent parameter.

For example, because the equation defining the previous leaky integrator example has an algebraic solution, it can be more accurately solved as follows - using a derived parameter to calculate $\exp\left(\frac{-t}{\tau}\right)$:

GeNN provides several additional features that might be useful when defining more complex neuron models.

9.4.1.1 Support code

Support code enables a code block to be defined that contains supporting code that will be utilized in multiple pieces of user code. Typically, these are functions that are needed in the sim code or threshold condition code. If possible,

9.4 Neuron models 33

these should be defined as __host__ __device__ functions so that both GPU and CPU versions of GeNN code have an appropriate support code function available. The support code is protected with a namespace so that it is exclusively available for the neuron population whose neurons define it. Support code is added to a model using the SET_SUPPORT_CODE() macro, for example:

9.4.1.2 Extra global parameters

Extra global parameters are parameters common to all neurons in the population. However, unlike the standard neuron parameters, they can be varied at runtime meaning they could, for example, be used to provide a global reward signal. These parameters are defined by using the SET_EXTRA_GLOBAL_PARAMS() macro to specify a list of variable names and type strings (like the SET_VARS() macro). For example:

```
SET_EXTRA_GLOBAL_PARAMS({{"R", "float"}});
```

These variables are available to all neurons in the population. They can also be used in synaptic code snippets; in this case it need to be addressed with a _pre or _post postfix.

For example, if the model with the "R" parameter was used for the pre-synaptic neuron population, the weight update model of a synapse population could have simulation code like:

```
SET_SIM_CODE("$(x) = $(x) + $(R_pre);");
```

where we have assumed that the weight update model has a variable x and our synapse type will only be used in conjunction with pre-synaptic neuron populations that do have the extra global parameter R. If the pre-synaptic population does not have the required variable/parameter, GeNN will fail when compiling the kernels.

9.4.1.3 Additional input variables

Normally, neuron models receive the linear sum of the inputs coming from all of their synaptic inputs through the \$(inSyn) variable. However neuron models can define additional input variables - allowing input from different synaptic inputs to be combined non-linearly. For example, if we wanted our leaky integrator to operate on the the product of two input currents, it could be defined as follows:

Where the SET_ADDITIONAL_INPUT_VARS() macro defines the name, type and its initial value before postsynaptic inputs are applyed (see section Postsynaptic integration methods for more details).

9.4.1.4 Random number generation

Many neuron models have probabilistic terms, for example a source of noise or a probabilistic spiking mechanism. In GeNN this can be implemented by using the following functions in blocks of model code:

- \$ (gennrand_uniform) returns a number drawn uniformly from the interval [0.0, 1.0]
- \$ (gennrand_normal) returns a number drawn from a normal distribution with a mean of 0 and a standard deviation of 1.
- \$ (gennrand_exponential) returns a number drawn from an exponential distribution with $\lambda=1.$
- \$ (gennrand_log_normal, MEAN, STDDEV) returns a number drawn from a log-normal distribution with the specified mean and standard deviation.
- \$ (gennrand_gamma, ALPHA) returns a number drawn from a gamma distribution with the specified shape.

Once defined in this way, new neuron models classes, can be used in network descriptions by referring to their type e.g.

Previous | Top | Next

9.5 Weight update models

Currently 4 predefined weight update models are available:

- WeightUpdateModels::StaticPulse
- WeightUpdateModels::StaticPulseDendriticDelay
- WeightUpdateModels::StaticGraded
- · WeightUpdateModels::PiecewiseSTDP

For more details about these built-in synapse models, see [3].

9.5.1 Defining a new weight update model

Like the neuron models discussed in Defining your own neuron type, new weight update models are created by defining a class. Weight update models should all be derived from WeightUpdateModel::Base and, for convenience, the methods a new weight update model should implement can be implemented using macros:

- SET_DERIVED_PARAMS(), SET_PARAM_NAMES(), SET_VARS() and SET_EXTRA_GLOBAL_PARAM
 S() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- DECLARE_WEIGHT_UPDATE_MODEL(TYPE, NUM_PARAMS, NUM_VARS, NUM_PRE_VARS, NUM_
 POST_VARS) is an extended version of DECLARE_MODEL() which declares the boilerplate code required for a weight update model with pre and postsynaptic as well as per-synapse state variables.
- SET_PRE_VARS() and SET_POST_VARS() define state variables associated with pre or postsynaptic neurons rather than synapses. These are typically used to efficiently implement *trace* variables for use in STDP learning rules [2]. Like other state variables, variables defined here as NAME can be accessed in weight update model code strings using the \$(NAME) syntax.
- SET_SIM_CODE(SIM_CODE): defines the simulation code that is used when a true spike is detected. The update is performed only in timesteps after a neuron in the presynaptic population has fulfilled its threshold detection condition. Typically, spikes lead to update of synaptic variables that then lead to the activation of input into the post-synaptic neuron. Most of the time these inputs add linearly at the post-synaptic neuron. This is assumed in GeNN and the term to be added to the activation of the post-synaptic neuron should be applied using the the \$(addToInSyn, weight) function. For example

```
SET_SIM_CODE(
    "$(addToInSyn, $(inc));\n"
```

where "inc" is the increment of the synaptic input to a post-synaptic neuron for each pre-synaptic spike. The simulation code also typically contains updates to the internal synapse variables that may have contributed to . For an example, see WeightUpdateModels::StaticPulse for a simple synapse update model and Weight UpdateModels::PiecewiseSTDP for a more complicated model that uses STDP. To apply input to the post-synaptic neuron with a dendritic (i.e. between the synapse and the postsynaptic neuron) delay you can instead use the \$(addToInSynDelay, weight, delay) function. For example

```
SET_SIM_CODE(
    "$(addToInSynDelay, $(inc), $(delay));");
```

where, once again, inc is the magnitude of the input step to apply and delay is the length of the dendritic delay in timesteps. By implementing delay as a weight update model variable, heterogeneous synaptic delays can be implemented. For an example, see WeightUpdateModels::StaticPulseDendriticDelay for a simple synapse update model with heterogeneous dendritic delays.

Note

When using dendritic delays, the **maximum** dendritic delay for a synapse populations must be specified using the SynapseGroup::setMaxDendriticDelayTimesteps() function.

• SET_EVENT_THRESHOLD_CONDITION_CODE(EVENT_THRESHOLD_CONDITION_CODE) defines a condition for a synaptic event. This typically involves the pre-synaptic variables, e.g. the membrane potential:

```
SET_EVENT_THRESHOLD_CONDITION_CODE("$(V_pre) > -0.02");
```

Whenever this expression evaluates to true, the event code set using the SET_EVENT_CODE() macro is executed. For an example, see WeightUpdateModels::StaticGraded.

- SET_EVENT_CODE(EVENT_CODE) defines the code that is used when the event threshold condition is met (as set using the SET_EVENT_THRESHOLD_CONDITION_CODE() macro).
- SET_LEARN_POST_CODE(LEARN_POST_CODE) defines the code which is used in the learnSynapses Post kernel/function, which performs updates to synapses that are triggered by post-synaptic spikes. This is typically used in STDP-like models e.g. WeightUpdateModels::PiecewiseSTDP.
- SET_SYNAPSE_DYNAMICS_CODE(SYNAPSE_DYNAMICS_CODE) defines code that is run for each synapse, each timestep i.e. unlike the others it is not event driven. This can be used where synapses have internal variables and dynamics that are described in continuous time, e.g. by ODEs. However using this mechanism is typically computationally very costly because of the large number of synapses in a typical network. By using the \$(addtoinsyn), \$(updatelinsyn) and \$(addToDenDelay) mechanisms discussed in the context of SET_SIM_CODE(), the synapse dynamics can also be used to implement continuous synapses for rate-based models.
- SET_PRE_SPIKE_CODE() and SET_POST_SPIKE_CODE() define code that is called whenever there is a pre or postsynaptic spike. Typically these code strings are used to update any pre or postsynaptic state variables.
- SET_NEEDS_PRE_SPIKE_TIME(PRE_SPIKE_TIME_REQUIRED) and SET_NEEDS_POST_SPIKE_TI
 ME(POST_SPIKE_TIME_REQUIRED) define whether the weight update needs to know the times of the
 spikes emitted from the pre and postsynaptic populations. For example an STDP rule would be likely to
 require:

```
SET_NEEDS_PRE_SPIKE_TIME(true);
SET_NEEDS_POST_SPIKE_TIME(true);
```

All code snippets, aside from those defined with SET_PRE_SPIKE_CODE () and SET_POST_SPIKE_COD← E (), can be used to manipulate any synapse variable and so learning rules can combine both time-drive and event-driven processes.

```
Previous | Top | Next
```

9.6 Postsynaptic integration methods

There are currently 3 built-in postsynaptic integration methods:

- PostsynapticModels::ExpCurr
- PostsynapticModels::ExpCond
- PostsynapticModels::DeltaCurr

9.6.1 Defining a new postsynaptic model

The postsynaptic model defines how synaptic activation translates into an input current (or other input term for models that are not current based). It also can contain equations defining dynamics that are applied to the (summed) synaptic activation, e.g. an exponential decay over time.

In the same manner as to both the neuron and weight update models discussed in Defining your own neuron type and Defining a new weight update model, postsynamic model definitions are encapsulated in a class derived from PostsynapticModels::Base. Again, the methods that a postsynaptic model should implement can be implemented using the following macros:

- DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS), SET_DERIVED_PARAMS(), SET_PARAM_N
 AMES(), SET_VARS() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- SET_DECAY_CODE(DECAY_CODE) defines the code which provides the continuous time dynamics for the summed presynaptic inputs to the postsynaptic neuron. This usually consists of some kind of decay function.
- SET_APPLY_INPUT_CODE(APPLY_INPUT_CODE) defines the code specifying the conversion from synaptic inputs to a postsynaptic neuron input current. e.g. for a conductance model:

```
SET_APPLY_INPUT_CODE("\$(Isyn) += \$(inSyn) * (\$(E) - \$(V))");
```

where \$(E) is a postsynaptic model parameter specifying reversal potential and \$(V) is the variable containing the postsynaptic neuron's membrane potential. As discussed in Built-in Variables in GeNN, \$(Isyn) is the built in variable used to sum neuron input. However additional input variables can be added to a neuron model using the SET_ADDITIONAL_INPUT_VARS() macro (see Defining your own neuron type for more details).

Previous | Top | Next

9.7 Current source models

There is a number of predefined models which can be used with the ModelSpec::addCurrentSource function:

- CurrentSourceModels::DC
- · CurrentSourceModels::GaussianNoise

9.7.1 Defining your own current source model

In order to define a new current source type for use in a GeNN application, it is necessary to define a new class derived from CurrentSourceModels::Base. For convenience the methods this class should implement can be implemented using macros:

- DECLARE_MODEL(TYPE, NUM_PARAMS, NUM_VARS), SET_DERIVED_PARAMS(), SET_PARAM_N
 AMES(), SET_VARS() perform the same roles as they do in the neuron models discussed in Defining your own neuron type.
- SET_INJECTION_CODE(INJECTION_CODE): where INJECTION_CODE contains the code for injecting current into the neuron every simulation timestep. The \$(injectCurrent,) function is used to inject current.

For example, using these macros, we can define a uniformly distributed noisy current source:

```
class UniformNoise : public CurrentSourceModels::Base
{
public:
    DECLARE_MODEL(UniformNoise, 1, 0);
    SET_SIM_CODE("$(injectCurrent, $(gennrand_uniform) * $(magnitude));");
    SET_PARAM_NAMES({"magnitude"});
};
```

Previous | Top | Next

9.8 Synaptic matrix types

Synaptic matrix types are made up of two components: SynapseMatrixConnectivity and SynapseMatrixWeight. SynapseMatrixConnectivity defines what data structure is used to store the synaptic matrix:

- SynapseMatrixConnectivity::DENSE stores synaptic matrices as a dense matrix. Large dense matrices require a large amount of memory and if they contain a lot of zeros it may be inefficient.
- SynapseMatrixConnectivity::SPARSE stores synaptic matrices in a(padded) 'ragged array' format. In general, this is less efficient to traverse using a GPU than the dense matrix format but does result in significant memory savings for large matrices. Ragged matrix connectivity is stored using several variables whose names, like state variables, have the name of the synapse population appended to them:
 - 1. const unsigned int maxRowLength: a constant set via the SynapseGroup::setMaxconnections method which specifies the maximum number of connections in any given row (this is the width the structure is padded to).
 - 2. unsigned int *rowLength (sized to number of presynaptic neurons): actual length of the row of connections associated with each presynaptic neuron
 - 3. unsigned int *ind(sized to maxRowLength * number of presynaptic neurons)

 : Indices of corresponding postsynaptic neurons concatenated for each presynaptic neuron. For
 example, consider a network of two presynaptic neurons connected to three postsynaptic neurons:

 Oth presynaptic neuron connected to 1st and 2nd postsynaptic neurons, the 1st presynaptic neuron
 connected only to the 0th neuron. The struct RaggedProjection should have these members, with
 indexing from 0 (where X represents a padding value):

```
maxRowLength = 2
ind = [1 2 0 X]
rowLength = [2 1]
```

Weight update model variables associated with the sparsely connected synaptic population will be kept in an array using the same indexing as ind. For example, a variable called g will be kept in an array such as: $g=[g_Pre0-Post1\ g_pre0-post2\ g_pre1-post0\ X]$

• SynapseMatrixConnectivity::BITMASK is an alternative sparse matrix implementation where which synapses within the matrix are present is specified as a binary array (see Insect olfaction model). This structure is somewhat less efficient than the SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::RAGGED formats and doesn't allow individual weights per synapse. However it does require the smallest amount of GPU memory for large networks.

Furthermore the SynapseMatrixWeight defines how

- SynapseMatrixWeight::INDIVIDUAL allows each individual synapse to have unique weight update model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushXXXXXStateToDevice function, where XXXX is the name of the synapse population.
- SynapseMatrixWeight::INDIVIDUAL_PSM allows each postsynapic neuron to have unique post synaptic model variables. Their values must be initialised at runtime and, if running on the GPU, copied across from the user side code, using the pushxxxxxxstateToDevice function, where XXXX is the name of the synapse population.
- SynapseMatrixWeight::GLOBAL saves memory by only maintaining one copy of the weight update model variables. This is automatically initialized to the initial value passed to ModelSpec::addSynapsePopulation.

Only certain combinations of SynapseMatrixConnectivity and SynapseMatrixWeight are sensible therefore, to reduce confusion, the SynapseMatrixType enumeration defines the following options which can be passed to Model Spec::addSynapsePopulation:

- SynapseMatrixType::SPARSE_GLOBALG
- SynapseMatrixType::SPARSE_GLOBALG_INDIVIDUAL_PSM

- SynapseMatrixType::SPARSE_INDIVIDUALG
- SynapseMatrixType::DENSE_GLOBALG
- SynapseMatrixType::DENSE_GLOBALG_INDIVIDUAL_PSM
- SynapseMatrixType::DENSE_INDIVIDUALG
- SynapseMatrixType::BITMASK_GLOBALG
- SynapseMatrixType::BITMASK_GLOBALG_INDIVIDUAL_PSM

Previous | Top | Next

9.9 Variable initialisation

Neuron, weight update and postsynaptic models all have state variables which GeNN can automatically initialise.

Previously we have shown variables being initialised to constant values such as:

state variables can also be left *uninitialised* leaving it up to the user code to initialise them between the calls to initialize() and initializeSparse():

or initialised using one of a number of predefined variable initialisation snippets:

- InitVarSnippet::Uniform
- InitVarSnippet::Normal
- InitVarSnippet::Exponential
- InitVarSnippet::Gamma

For example, to initialise a parameter using values drawn from the normal distribution:

9.9.1 Defining a new variable initialisation snippet

Similarly to neuron, weight update and postsynaptic models, new variable initialisation snippets can be created by simply defining a class in the model description. For example, when initialising excitatory (positive) synaptic weights with a normal distribution they should be clipped at 0 so the long tail of the normal distribution doesn't result in negative weights. This could be implemented using the following variable initialisation snippet which redraws until samples are within the desired bounds:

9.9 Variable initialisation 39

```
class NormalPositive : public InitVarSnippet::Base
{
public:
    DECLARE_SNIPPET(NormalPositive, 2);

SET_CODE(
        "scalar normal;"
        "do\n"
        "{\n"
        " normal = $(mean) + ($(gennrand_normal) * $(sd));\n"
        "$ (value) = normal;\n");

SET_PARAM_NAMES({"mean", "sd"});
};
IMPLEMENT_SNIPPET(NormalPositive);
```

Within the snippet of code specified using the SET_CODE () macro, when initialisising neuron and postaynaptic model state variables, the \$(id) variable can be used to access the id of the neuron being initialised. Similarly, when initialising weight update model state variables, the \$(id_pre) and \$(id_post) variables can used to access the ids of the pre and postsynaptic neurons connected by the synapse being initialised.

9.9.2 Variable locations

Once you have defined **how** your variables are going to be initialised you need to configure **where** they will be allocated. By default memory is allocated for variables on both the GPU and the host. However, the following alternative 'variable locations' are available:

- VarLocation::DEVICE Variables are only allocated on the GPU, saving memory but meaning that they can't easily be copied to the host best for internal state variables.
- · VarLocation::HOST DEVICE Variables are allocated on both the GPU and the host the default.
- VarLocation::HOST_DEVICE_ZERO_COPY Variables are allocated as 'zero-copy' memory accessible to
 the host and GPU useful on devices such as Jetson TX1 where physical memory is shared between the
 GPU and CPU.

Note

'Zero copy' memory is only supported on newer embedded systems such as the Jetson TX1 where there is no physical seperation between GPU and host memory and thus the same block of memory can be shared between them.

These modes can be set as a model default using ModelSpec::setDefaultVarLocation or on a pervariable basis using one of the following functions:

- NeuronGroup::setSpikeLocation
- · NeuronGroup::setSpikeEventLocation
- · NeuronGroup::setSpikeTimeLocation
- · NeuronGroup::setVarLocation
- · SynapseGroup::setWUVarLocation
- SynapseGroup::setWUPreVarLocation
- SynapseGroup::setWUPostVarLocation
- SynapseGroup::setPSVarLocation
- SynapseGroup::setInSynVarLocation

Previous | Top | Next

9.10 Sparse connectivity initialisation

Synaptic connectivity implemented using SynapseMatrixConnectivity::SPARSE and SynapseMatrixConnectivity::

BITMASK can be automatically initialised.

This can be done using one of a number of predefined sparse connectivity initialisation snippets:

- InitSparseConnectivitySnippet::OneToOne
- InitSparseConnectivitySnippet::FixedProbability
- InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

For example, to initialise synaptic connectivity with a 10% connection probability (allowing connections between neurons with the same id):

9.10.1 Defining a new sparse connectivity snippet

Similarly to variable initialisation snippets, sparse connectivity initialisation snippets can be created by simply defining a class in the model description.

For example, the following sparse connectivity initialisation snippet could be used to initialise a 'ring' of connectivity where each neuron is connected to a number of subsequent neurons specified using the numNeighbours parameter:

```
{\tt class} \ {\tt Ring: public InitSparseConnectivitySnippet::Base}
public:
    DECLARE_SNIPPET(Ring, 1);
    SET_ROW_BUILD_STATE_VARS({{"offset", {"unsigned int", 1}}});
    SET_ROW_BUILD CODE (
         "const unsigned int target = ($(id_pre) + offset) % $(num_post);\n"
        "$(addSynapse, target);\n"
        "if(offset > (unsigned int)$(numNeighbours)) {\n"
            $ (endRow); \n"
        "}\n");
    SET PARAM NAMES({"numNeighbours"});
    SET_CALC_MAX_ROW_LENGTH_FUNC (
        [] (unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
        1):
    SET_CALC_MAX_COL_LENGTH_FUNC(
        [](unsigned int numPre, unsigned int numPost, const std::vector<double> &pars)
            return (unsigned int)pars[0];
        });
IMPLEMENT_SNIPPET(Ring);
```

Each *row* of sparse connectivity is initialised independantly by running the snippet of code specified using the SET_ROW_BUILD_CODE() macro within a loop. The \$(num_post) variable can be used to access the number of neurons in the postsynaptic population and the \$(id_pre) variable can be used to access the index of the presynaptic neuron associated with the row being generated. The SET_ROW_BUILD_STATE_VARS() macro can be used to initialise state variables outside of the loop - in this case offset which is used to count the number of synapses created in each row. Synapses are added to the row using the \$(addSynapse, target) function and iteration is stopped using the \$(endRow) function. To avoid having to manually call SynapseGroup::setMaxConnections and SynapseGroup::setMaxSourceConnections, sparse connectivity snippets can also provide code to calculate the maximum row and column lengths this connectivity will result in using the SET_CALC_MAX_ROW_LENGTH_F UNC() and SET_CALC_MAX_ROW_LENGTH_FUNC() macros. Alternatively, if the maximum row or column length is constant, the SET_MAX_ROW_LENGTH() and SET_MAX_COL_LENGTH() shorthand macros can be used.

10 Tutorial 1 41

9.10.2 Sparse connectivity locations

Once you have defined **how** sparse connectivity is going to be initialised, similarly to variables, you can control **where** it is allocated. This is controlled using the same VarLocations options described in section Variable locations and can either be set using the model default specifiued with ModelSpec::setDefault SparseConnectivityLocation or on a per-synapse group basis using SynapseGroup::setSparseConnectivityLocation.

Previous | Top | Next

10 Tutorial 1

In this tutorial we will go through step by step instructions how to create and run your first GeNN simulation from scratch.

10.1 The Model Definition

In this tutorial we will use a pre-defined Hodgkin-Huxley neuron model (NeuronModels::TraubMiles) and create a simulation consisting of ten such neurons without any synaptic connections. We will run this simulation on a GPU and save the results - firstly to stdout and then to file.

The first step is to write a model definition function in a model definition file. Create a new directory and, within that, create a new empty file called tenHHModel.cc using your favourite text editor, e.g.

```
>> emacs tenHHModel.cc &
```

Note

The ">>" in the example code snippets refers to a shell prompt in a unix shell, do not enter them as part of your shell commands.

The model definition file contains the definition of the network model we want to simulate. First, we need to include the GeNN model specification code modelSpec.h. Then the model definition takes the form of a function named modelDefinition that takes one argument, passed by reference, of type ModelSpec. Type in your $tenH \leftarrow HModel.cc$ file:

```
// Model definintion file tenHHModel.cc
#include "modelSpec.h"

void modelDefinition(ModelSpec &model)
{
    // definition of tenHHModel
```

Two standard elements to the 'modelDefinition function are setting the simulation step size and setting the name of the model:

```
model.setDT(0.1);
model.setName("tenHHModel");
```

Note

With this we have fixed the integration time step to 0.1 in the usual time units. The typical units in GeNN are ms, mV, nF, and μ S. Therefore, this defines DT= 0.1 ms.

Making the actual model definition makes use of the ModelSpec::addNeuronPopulation and ModelSpec::add SynapsePopulation member functions of the ModelSpec object. The arguments to a call to ModelSpec::add NeuronPopulation are

- NeuronModel: template parameter specifying the neuron model class to use
- const std::string &name: the name of the population
- unsigned int size: The number of neurons in the population
- const NeuronModel::ParamValues ¶mValues: Parameter values for the neurons in the population
- const NeuronModel::VarValues &varInitialisers: Initial values or initialisation snippets for variables of this neuron type

We first create the parameter and initial variable arrays,

Note

The comments are obviously only for clarity, they can in principle be omitted. To avoid any confusion about the meaning of parameters and variables, however, we recommend strongly to always include comments of this type.

Having defined the parameter values and initial values we can now create the neuron population,

This completes the model definition in this example. The complete tenHHModel.cc file now should look like this:

```
// Model definintion file tenHHModel.cc
#include "modelSpec.h"
void modelDefinition(ModelSpec &model)
   // definition of tenHHModel
   model.setDT(0.1);
   model.setName("tenHHModel");
   NeuronModels::TraubMiles::ParamValues p(
       7.15,
               // 0 - gNa: Na conductance in muS
// 1 - ENa: Na equi potential in mV
       50.0.
       NeuronModels::TraubMiles::VarValues ini(
       -60.0, // 0 - membrane potential V 0.0529324, // 1 - prob. for Na channel activation m
       0.5961207); // 3 - prob. for K channel activation n
   model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
     10, p, ini);
```

This model definition suffices to generate code for simulating the ten Hodgkin-Huxley neurons on the a GPU or CPU. The second part of a GeNN simulation is the user code that sets up the simulation, does the data handling for input and output and generally defines the numerical experiment to be run.

10.2 Building the model

To use GeNN to build your model description into simulation code, use a terminal to navigate to the directory containing your tenHHModel.cc file and, on Linux or Mac, type:

```
>> genn-buildmodel.sh tenHHModel.cc
```

Alternatively, on Windows, type:

```
>> genn-buildmodel.bat tenHHModel.cc
```

If you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can invoke genn-buildmodel with a -c option so, on Linux or Mac:

```
>> genn-buildmodel.sh -c tenHHModel.cc
```

or on Windows:

```
>> genn-buildmodel.bat -c tenHHModel.cc
```

If GeNN has been added to your path and CUDA_PATH is correctly configured, you should see some compile output ending in Model build complete

10.3 User Code

GeNN will now have generated the code to simulate the model for one timestep using a function stepTime(). To make use of this code, we need to define a minimal C/C++ main function. For the purposes of this tutorial we will initially simply run the model for one simulated second and record the final neuron variables into a file. Open a new empty file tenHHSimulation.cc in an editor and type

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();
    return 0;
```

This boiler plate code includes the header file for the generated code definitions.h in the subdirectory tenerous HHModel_CODE where GeNN deposits all generated code (this corresponds to the name passed to the Modele Spec::setName function). Calling allocateMem() allocates the memory structures for all neuron variables and initialize() launches a GPU kernel which initialise all state variables to their initial values. Now we can use the generated code to integrate the neuron equations provided by GeNN for 1000ms. To do so, we add after initialize();

Note

The t variable is provided by GeNN to keep track of the current simulation time in milliseconds.

```
while (t < 1000.0f) {
    stepTime();
}</pre>
```

and we need to copy the result back to the host before outputting it to stdout (this will do nothing if you are running the model on a CPU),

```
pullPop1StateFromDevice();
for (int j= 0; j < 10; j++) {
    std::cout << VPop1[j] << " ";
    std::cout << mPop1[j] << " ";
    std::cout << hPop1[j] << " ";
    std::cout << nPop1[j] << std::endl;
}</pre>
```

pullPop1StateFromDevice() copies all relevant state variables of the Pop1 neuron group from the GPU to the CPU main memory. Then we can output the results to stdout by looping through all 10 neurons and outputting the state variables VPop1, mPop1, hPop1, nPop1.

Note

The naming convention for variables in GeNN is the variable name defined by the neuron type, here TraubMiles defining V, m, h, and n, followed by the population name, here Pop1.

This completes the user code. The complete tenHHSimulation.cc file should now look like

```
// tenHHModel simulation code
#include "tenHHModel_CODE/definitions.h"
int main()
{
    allocateMem();
    initialize();

    while (t < 1000.0f) {
        stepTime();
    }
    pullPoplStateFromDevice();

    for (int j= 0; j < 10; j++) {
        std::cout << VPopl[j] << " ";
        std::cout << mPopl[j] << " ";
        std::cout << nPopl[j] << " ";
        std::cout << nPopl[j] << std::endl;
    }
    return 0;
}</pre>
```

10.4 Building the simulator (Linux or Mac)

On Linux and Mac, GeNN simulations are typically built using a simple Makefile which can be generated with the following command:

```
genn-create-user-project.sh tennHHModel tenHHSimulation.cc
```

This defines that the model is named tennHHModel and the simulation code is given in the file $tenHH \leftarrow Simulation.cc$ that we completed above. Now type

make

10.5 Building the simulator (Windows)

So that projects can be easily debugged within the Visual Studio IDE (see section Debugging suggestions for more details), Windows projects are built using an MSBuild script typically with the same title as the final executable. A suitable solution and project can be generated automatically with the following command:

```
genn-create-user-project.bat tennHHModel tenHHSimulation.cc
```

his defines that the model is named tennHHModel and the simulation code is given in the file $tenHH \leftarrow Simulation.cc$ that we completed above. Now type

```
msbuild tennHHModel.sln /p:Configuration=Release /t:tennHHModel
```

10.6 Running the Simulation

You can now execute your newly-built simulator on Linux or Mac with

```
./tennHHModel
```

10.7 Reading 45

Or on Windows with

```
tennHHModel_Release
```

The output you obtain should look like

```
-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243

-63.7838 0.0350042 0.336314 0.563243
```

10.7 Reading

This is not particularly interesting as we are just observing the final value of the membrane potentials. To see what is going on in the meantime, we need to copy intermediate values from the device and save them into a file. This can be done in many ways but one sensible way of doing this is to replace the calls to stepTime in tenHHSimulation.cc with something like this:

```
std::ofstream os("tenHH_output.V.dat");
while (t < 1000.0f) {
    stepTime();

    pullVPop1FromDevice();

    os << t << " ";
    for (int j= 0; j < 10; j++) {
        os << VPop1[j] << " ";
    }
    os << std::endl;
}
os.close();</pre>
```


Note

t is a global variable updated by the GeNN code to keep track of elapsed simulation time in ms. we switched from using pullPop1StateFromDevice() to pullVPop1FromDevice() as we are now only interested in the membrane voltage of the neuron.

You will also need to add:

```
#include <fstream>
```

to the top of tenHHSimulation.cc. After building the model; and building and running the simulator as described above there should be a file tenHH_output.V.dat in the same directory. If you plot column one (time) against the subsequent 10 columns (voltage of the 10 neurons), you should observe dynamics like this:



However so far, the neurons are not connected and do not receive input. As the NeuronModels::TraubMiles model is silent in such conditions, the membrane voltages of the 10 neurons will simply drift from the -60mV they were initialised at to their resting potential.

Previous | Top | Next

11 Tutorial 2

In this tutorial we will learn to add synapsePopulations to connect neurons in neuron groups to each other with synaptic models. As an example we will connect the ten Hodgkin-Huxley neurons from tutorial 1 in a ring of excitatory synapses.

First, copy the files from Tutorial 1 into a new directory and rename the tenHHModel.cc to tenHHRing Model.cc and tenHHSimulation.cc to tenHHRingSimulation.cc, e.g. on Linux or Mac:

```
>> cp -r tenHH_project tenHHRing_project
>> cd tenHHRing_project
>> mv tenHHModel.cc tenHHRingModel.cc
>> mv tenHHSimulation.cc tenHHRingSimulation.cc
```

Finally, to reduce confusion we should rename the model itself. Open tenHHRingModel.cc, change the model name inside,

```
model.setName("tenHHRing");
```

11.1 Defining the Detailed Synaptic Connections

We want to connect our ten neurons into a ring where each neuron connects to its neighbours. In order to initialise this connectivity we need to add a sparse connectivity initialisation snippet at the top of tenHHRingModel.cc:

The SET_ROW_BUILD_CODE code string will be called to generate each row of the synaptic matrix (connections coming from a single presynaptic neuron) and, in this case, each row consists of a single synapses from the presynaptic neuron \$(id_pre) to \$(id_pre) + 1 (the modulus operator is used to ensure that the final connection between neuron 9 and 0 is made correctly). In order to allow GeNN to better optimise the generated code we also provide a maximum row length. In this case each row always contains only one synapse but, when more complex connectivity is used, the number of neurons in the pre and postsynaptic population as well as any parameters used to configure the snippet can be accessed from this function.

Note

When defining GeNN code strings, the \$(VariableName) syntax is used to refer to variables provided by GeNN and the \$(FunctionName, Parameter1,...) syntax is used to call functions provided by GeNN.

11.2 Adding Synaptic connections

Now we need additional initial values and parameters for the synapse and post-synaptic models. We will use the standard WeightUpdateModels::StaticPulse weight update model and PostsynapticModels::ExpCond post-synaptic model. They need the following initial variables and parameters:

Note

the WeightUpdateModels::StaticPulse weight update model has no parameters and the PostsynapticModels
::ExpCond post-synaptic model has no state variables.

We can then add a synapse population at the end of the modelDefinition(...) function,

```
model.addSynapsePopulation<WeightUpdateModels::StaticPulse
    , PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 10,
    "Popl", "Popl",
    {}, s_ini,
    ps_p, {},
    initConnectivity<Ring>());
```

The addSynapsePopulation parameters are

- WeightUpdateModel: template parameter specifying the type of weight update model (derived from Weight
 — UpdateModels::Base).
- PostsynapticModel: template parameter specifying the type of postsynaptic model (derived from PostsynapticModels::Base).
- · name string containing unique name of synapse population.
- mtype how the synaptic matrix associated with this synapse population should be represented. Here
 SynapseMatrixType::SPARSE_GLOBALG means that there will be sparse connectivity and each connection
 will have the same weight (-0.2 as specified previously).
- delayStep integer specifying number of timesteps of propagation delay that spikes travelling through this synapses population should incur (or NO DELAY for none)
- · src string specifying name of presynaptic (source) population
- · trg string specifying name of postsynaptic (target) population
- weightParamValues parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.

- weightVarInitialisers initial values or initialisation snippets for the weight update model's state variables wrapped in a WeightUpdateModel::VarValues object.
- postsynapticParamValues parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
- postsynapticVarInitialisers initial values or initialisation snippets for the postsynaptic model wrapped in PostsynapticModel::VarValues object.
- connectivityInitialiser snippet and any paramaters (in this case there are none) used to initialise the synapse population's sparse connectivity.

Adding the addSynapsePopulation command to the model definition informs GeNN that there will be synapses between the named neuron populations, here between population Pop1 and itself. At this point our model definition file tenHHRingModel.cc should look like this

```
// Model definition file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET_ROW_BUILD_CODE(
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
"$(endRow);\n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET (Ring):
void modelDefinition(ModelSpec &model)
     // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
         7.15, // 0 - gNa: Na conductance in muS
                      // 1 - ENa: Na equi potential in mV
                     // 2 - gK: K conductance in muS

// 3 - EK: K equi potential in mV
         1.43.
         -95.0,
                    // 4 - g1: leak conductance in mus
// 5 - E1: leak equi potential in mV
// 6 - Cmem: membr. capacity density in nF
         0.02672,
         -63.563.
         0.143);
    NeuronModels::TraubMiles::VarValues ini(
                        // 0 - membrane potential V // 1 - prob. for Na channel activation m
         -60.0,
0.0529324,
                         // 2 - prob. for not Na channel blocking h
         0.3176767,
         0.5961207);
                        // 3 - prob. for K channel activation n
    model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
       10, p, ini);
    WeightUpdateModels::StaticPulse::VarValues s ini(
          -0.2); // 0 - g: the synaptic conductance value
    PostsynapticModels::ExpCond::ParamValues ps_p(
         1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
    model.addSvnapsePopulation<
       WeightUpdateModels::StaticPulse,
       PostsynapticModels::ExpCond>(
         "Pop1self", SynapseMatrixType::SPARSE_GLOBALG, 100,
         "Pop1", "Pop1",
         {}, s_ini,
         ps p, {},
         initConnectivity<Ring>());
```

We can now build our new model:

```
>> genn-buildmodel.sh tenHHRingModel.cc
```

Note

Again, if you don't have an NVIDIA GPU and are running GeNN in CPU_ONLY mode, you can instead build with the -c option as described in Tutorial 1.


Now we can open the tenHHRingSimulation.cc file and update the file name of the model includes to match the name we set previously:

```
// tenHHRingModel simulation code
#include "tenHHRing_CODE/definitions.h"
```

Additionally, we need to add a call to a second initialisation function to main() after we call initialize():

```
initializeSparse();
```

This initializes any variables associated with the sparse connectivity we have added (and will also copy any manually initialised variables to the GPU). Then, after using the <code>genn-create-user-project</code> tool to create a new project with a model name of <code>tenhhRing</code> and using <code>tenhhRingSimulation.cc</code> rather than <code>tenhhesimulation.cc</code>, we can build and run our new simulator in the same way we did in Tutorial 1. However, even after all our hard work, if we plot the content of the first column against the subsequent 10 columns of <code>tenhesimple.V.dat</code> it looks very similar to the plot we obtained at the end of Tutorial 1.



This is because none of the neurons are spiking so there are no spikes to propagate around the ring.

11.3 Providing initial stimuli

We can use a NeuronModels::SpikeSource to inject an initial spike into the first neuron in the ring during the first timestep to start spikes propagating. Firstly we need to define another sparse connectivity initialisation snippet at the top of tenHHRingModel.cc which simply creates a single synapse on the first row of the synaptic matrix:

We then need to add it to the network by adding the following to the end of the modelDefinition(...) function:

and finally inject a spike in the first timestep (in the same way that the t variable is provided by GeNN to keep track of the current simulation time in milliseconds, iT is provided to keep track of it in timesteps):

```
if(iT == 0) {
    spikeCount_Stim = 1;
    spike_Stim[0] = 0;
    pushStimCurrentSpikesToDevice();
}
```

Note

 $spike_Stim[n]$ is used to specify the indices of the neurons in population Stim spikes which should emit spikes where $n \in [0, spikeCount_Stim)$.

At this point our user code tenHHRingModel.cc should look like this


```
// Model definintion file tenHHRing.cc
#include "modelSpec.h"
class Ring : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(Ring, 0);
    SET ROW BUILD CODE (
         "$(addSynapse, ($(id_pre) + 1) % $(num_post));\n"
        "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT_SNIPPET(Ring);
class FirstToFirst : public InitSparseConnectivitySnippet::Base
public:
    DECLARE_SNIPPET(FirstToFirst, 0);
    SET_ROW_BUILD_CODE(
   "if($(id_pre) == 0) {\n"
           $ (addSynapse, $ (id_pre)); \n"
         "}\n"
         "$ (endRow); \n");
    SET_MAX_ROW_LENGTH(1);
IMPLEMENT SNIPPET(FirstToFirst);
void modelDefinition(ModelSpec &model)
    // definition of tenHHRing
    model.setDT(0.1);
    model.setName("tenHHRing");
    NeuronModels::TraubMiles::ParamValues p(
         7.15,
                     // 0 - gNa: Na conductance in muS
                      // 1 - ENa: Na equi potential in mV
         1.43,
                      // 2 - gK: K conductance in muS \,
                     // 3 - EK: K equi potential in mV
         -95.0.
                     // 4 - gl: leak conductance in muS
// 5 - El: leak equi potential in mV
        0.02672.
         -63.563,
                      // 6 - Cmem: membr. capacity density in nF
         0.143);
    NeuronModels::TraubMiles::VarValues ini(
         -60.0,
                    // 0 - membrane potential V // 1 - prob. for Na channel activation m
         0.0529324.
                         // 2 - prob. for not Na channel blocking h
         0.3176767,
         0.5961207);
                        // 3 - prob. for K channel activation n
```

```
model.addNeuronPopulation<NeuronModels::TraubMiles>("Pop1",
  10, p, ini);
model.addNeuronPopulation<NeuronModels::SpikeSource>("Stim"
  , 1, {}, {});
WeightUpdateModels::StaticPulse::VarValues s_ini(
      -0.2); // 0 - g: the synaptic conductance value
PostsynapticModels::ExpCond::ParamValues ps_p(
    1.0, // 0 - tau_S: decay time constant for S [ms] -80.0); // 1 - Erev: Reversal potential
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
    "Poplself", SynapseMatrixType::SPARSE_GLOBALG, 100, "Popl", "Popl",
    {}, s_ini, ps_p, {},
    initConnectivity<Ring>());
model.addSynapsePopulation<
  WeightUpdateModels::StaticPulse,
  PostsynapticModels::ExpCond>(
     "StimPop1", SynapseMatrixType::SPARSE_GLOBALG,
  NO_DELAY,
"Stim", "Pop1",
    {}, s_ini,
    ps_p, {},
initConnectivity<FirstToFirst>());
```

and tenHHRingSimulation.cc' should look like this:

```
// Standard C++ includes
#include <fstream>
// tenHHRing simulation code
#include "tenHHRing_CODE/definitions.h"
int main()
    allocateMem();
    initialize();
    initializeSparse();
    std::ofstream os("tenHHRing_output.V.dat");
    while(t < 200.0f) {
    if(iT == 0) {
             glbSpkStim[0] = 0;
glbSpkCntStim[0] = 1;
             pushStimCurrentSpikesToDevice();
         stepTimeU();
         pullVPop1FromDevice();
         os << t << " ";
         for (int j= 0; j < 10; j++) {
   os << VPop1[j] << " ";</pre>
         os << std::endl;
    os.close();
    return 0;
```

Finally if we build, make and run this model; and plot the first 200 ms of the ten neurons' membrane voltages - they now looks like this:



Previous | Top | Next

12 Best practices guide

GeNN generates code according to the network model defined by the user, and allows users to include the generated code in their programs as they want. Here we provide a guideline to setup GeNN and use generated functions. We recommend users to also have a look at the Examples, and to follow the tutorials Tutorial 1 and Tutorial 2.

12.1 Creating and simulating a network model

The user is first expected to create an object of class ModelSpec by creating the function modelDefinition() which includes calls to following methods:

- · ModelSpec::setDT();
- ModelSpec::setName();

Then add neuron populations by:

ModelSpec::addNeuronPopulation();

for each neuron population. Add synapse populations by:

ModelSpec::addSynapsePopulation();

for each synapse population.

Other optional functions are explained in ModelSpec class reference. At the end the function should look like this:

```
void modelDefinition(ModelSpec &model) {
  model.setDT(0.5);
  model.setName("YourModelName");
  model.addNeuronPopulation(...);
  ...
  model.addSynapsePopulation(...);
  ...
}
```

modelSpec.h should be included in the file where this function is defined.

This function will be called by generateALL.cc to create corresponding CPU and GPU simulation codes under the <YourModelName> CODE directory.

These functions can then be used in a .cc file which runs the simulation. This file should include <YourModel ← Name>_CODE/definitions.h. Generated code differ from one model to the other, but core functions are the same and they should be called in correct order. First, the following variables should be defined and initialized:

- ModelSpec model // initialized by calling modelDefinition(model)
- Array containing current input (if any)

Any variables marked as unintialised using the uninitialisedVar() function or sparse connectivity not initialised using a snippet must be initialised by the user between calls to initialize() and initialize \Leftrightarrow Sparse(). Core functions generated by GeNN to be included in the user code include:

```
allocateMem()
initialize()
initializeSparse()
get<neuron name>CurrentSpikes()
get<neuron name>CurrentSpikeCount()
stepTime()
freeMem()
```

In order to correctly access neuron state and spikes for the current timestep, correctly accounting for delay buffering etc, you can use the getCurrent<var name><neuron name>(), get<neuron name>CurrentSpikeCount() functions. By setting GENN_PREFERENCES::automaticCopy, GeNN can be used in a simple mode where CUDA automatically transfers data between the GPU and CPU when required (see https://devblogs.nvidia.com/unified-memory-cuda-beginners/). However, copying elements between the GPU and the host memory is costly in terms of performance and the automatic copying operates on a fairly coarse grain (pages are approximately 4 bytes). Therefore, in order to maximise performance, we recommend you do not use automatic copying and instead manually call the following functions when required:

```
push<neuron or synapse name>StateToDevice()
pull<neuron or synapse name>StateFromDevice()
push<neuron name>SpikesToDevice()
pull<neuron name>SpikesFromDevice()
push<neuron name>SpikesEventsToDevice()
pull<neuron name>SpikesEventsFromDevice()
push<neuron name>SpikesEventsFromDevice()
push<neuron name>SpikeTimesToDevice()
pull<neuron name>CurrentSpikesToDevice()
pull<neuron name>CurrentSpikesFromDevice()
push<neuron name>CurrentSpikesEventsToDevice()
push<neuron name>CurrentSpikesEventsToDevice()
pull<neuron name>CurrentSpikesEventsToDevice()
```

- pull<synapse name>ConnectivityFromDevice()
- push<synapse name>ConnectivityToDevice()
- pull<var name><neuron or synapse name>FromDevice()
- push<var name><neuron or synapse name>ToDevice()
- pushCurrent<var name><neuron name>ToDevice()
- pullCurrent<var name><neuron name>FromDevice()
- getCurrent<var name><neuron name>()
- copyStateToDevice()
- copyStateFromDevice()
- copyCurrentSpikesFromDevice()
- copyCurrentSpikesEventsFromDevice()

You can use the <code>push<neuron</code> or <code>synapse</code> <code>name>StateToDevice()</code> to copy from the host to the GPU. At the end of your simulation, if you want to access the variables you need to copy them back from the device using the <code>pull<neuron</code> or <code>synapse</code> <code>name>StateFromDevice()</code> function or one of the more fine-grained functions listed above.

12.1.1 Extra Global Parameters

If extra global parameters have a "scalar" type such as float they can be set directly from simulation code. For example the extra global parameter "reward" of population "Pop" could be set with:

```
rewardPop = 5.0f;
```

However, if extra global parameters have a pointer type such as float*, GeNN generates additional functions to allocate, free and copy these variables between host and device:

- allocate<var name><neuron or synapse name>
- free<var name><neuron or synapse name>
- push<var name><neuron or synapse name>ToDevice
- pull<var name><neuron or synapse name>FromDevice These operate in much the same manner as the functions for interacting with standard variables described above but the allocate, push and pull functions all take a "count" parameter specifying how many entries the extra global parameter array should be.

12.2 Floating point precision

Double precision floating point numbers are supported by devices with compute capability 1.3 or higher. If you have an older GPU, you need to use single precision floating point in your models and simulation.

GPUs are designed to work better with single precision while double precision is the standard for CPUs. This difference should be kept in mind while comparing performance.

While setting up the network for GeNN, double precision floating point numbers are used as this part is done on the CPU. For the simulation, GeNN lets users choose between single or double precision. Overall, new variables in the generated code are defined with the precision specified by ModelSpec::setPrecision(unsigned int), providing GENN_FLOAT or GENN_DOUBLE as argument. GENN_FLOAT is the default value. The keyword scalar can be used in the user-defined model codes for a variable that could either be single or double precision. This keyword is

detected at code generation and substituted with "float" or "double" according to the precision set by ModelSpec

∴:setPrecision(unsigned int).

There may be ambiguities in arithmetic operations using explicit numbers. Standard C compilers presume that any number defined as "X" is an integer and any number defined as "X.Y" is a double. Make sure to use the same precision in your operations in order to avoid performance loss.

12.3 Working with variables in GeNN

12.3.1 Model variables

User-defined model variables originate from classes derived off the NeuronModels::Base, WeightUpdateModels ::Base or PostsynapticModels::Base classes. The name of model variable is defined in the model type, i.e. with a statement such as

```
SET_VARS({{"V", "scalar"}});
```

When a neuron or synapse population using this model is added to the model, the full GeNN name of the variable will be obtained by concatenating the variable name with the name of the population. For example if we add a population called Pop using a model which contains our V variable, a variable VPop of type scalar* will be available in the global namespace of the simulation program. GeNN will pre-allocate this C array to the correct size of elements corresponding to the size of the neuron population. GeNN will also free these variables when the provided function freeMem() is called. Users can otherwise manipulate these variable arrays as they wish. For convenience, GeNN provides functions to copy each state variable from the device into host memory and vice versa e.g. pullVPopFromDevice() and pushVPoptoDevice(). Alternatively, all state variables associated with a population can be copied using a single call E.g.

```
pullPopStateFromDevice();
```

These conventions also apply to the the variables of postsynaptic and weight update models.

Note

Be aware that the above naming conventions do assume that variables from the weightupdate models and the postSynModels that are used together in a synapse population are unique. If both the weightupdate model and the postSynModel have a variable of the same name, the behaviour is undefined.

12.3.2 Built-in Variables in GeNN

GeNN has no explicitly hard-coded synapse and neuron variables. Users are free to name the variable of their models as they want. However, there are some reserved variables that are used for intermediary calculations and communication between different parts of the generated code. They can be used in the user defined code but no other variables should be defined with these names.

- DT: Time step (typically in ms) for simulation; Neuron integration can be done in multiple sub-steps inside the neuron model for numerical stability (see Traub-Miles and Izhikevich neuron model variations in Neuron models).
- inSyn: This is an intermediary synapse variable which contains the summed input into a postsynaptic neuron (originating from the addtoinSyn variables of the incoming synapses).
- Isyn: This is a local variable which contains the (summed) input current to a neuron. It is typically the sum
 of any explicit current input and all synaptic inputs. The way its value is calculated during the update of the
 postsynaptic neuron is defined by the code provided in the postsynaptic model. For example, the standard
 PostsynapticModels::ExpCond postsynaptic model defines

which implements a conductance based synapse in which the postsynaptic current is given by $I_{\text{syn}} = g * s * (V_{\text{rev}} - V_{\text{post}})$.

The value resulting from the current converter code is assigned to Isyn and can then be used in neuron sim code like so:

```
(V) += (-(V) + (Isyn)) *DT
```

sT: This is a neuron variable containing the last spike time of each neuron and is automatically generated for
pre and postsynaptic neuron groups if they are connected using a synapse population with a weight update
model that has SET_NEEDS_PRE_SPIKE_TIME(true) or SET_NEEDS_POST_SPIKE_TIME(true) set.

In addition to these variables, neuron variables can be referred to in the synapse models by calling (<neuronVar \rightarrow Name>_pre) for the presynaptic neuron population, and (<neuronVarName>_post) for the postsynaptic population. For example, (sT_pre) , (v_pre) , etc.

12.4 Debugging suggestions

In Linux, users can call <code>cuda-gdb</code> to debug on the GPU. Example projects in the <code>userproject</code> directory come with a flag to enable debugging (-debug). genn-buildmodel.sh has a debug flag (-d) to generate debugging data. If you are executing a project with debugging on, the code will be compiled with -g -G flags. In CPU mode the executable will be run in gdb, and in GPU mode it will be run in cuda-gdb in tui mode.

Note

Do not forget to switch debugging flags -g and -G off after debugging is complete as they may negatively affect performance.

On Mac, some versions of clang aren't supported by the CUDA toolkit. This is a recurring problem on Fedora as well, where CUDA doesn't keep up with GCC releases. You can either hack the CUDA header which checks compiler versions - cuda/include/host_config.h - or just use an older XCode version (6.4 works fine).

On Windows models can also be debugged and developed by opening the sln file used to build the model in Visual Studio. From here files can be added to the project, build settings can be adjusted and the full suite of Visual Studio debugging and profiling tools can be used.

Note

When opening the models in the userproject directory in Visual Studio, right-click on the project in the solution explorer, select 'Properties'. Then, making sure the desired configuration is selected, navigate to 'Debugging' under 'Configuration Properties', set the 'Working Directory' to '..' and the 'Command Arguments' to match those passed to genn-buildmodel e.g. 'outdir' to use an output directory called outdir.

Previous | Top | Next

13 Credits

GeNN was created by Thomas Nowotny.

GeNN is currently maintained and developed by James Knight.

Current sources and PyGeNN were first implemented by Anton Komissarov.

Izhikevich model and sparse connectivity by Esin Yavuz.

Block size optimisations, delayed synapses and page-locked memory by James Turner.

Automatic brackets and dense-to-sparse network conversion helper tools by Alan Diamond.

14 Namespace Index 57

User-defined synaptic and postsynaptic methods by Alex Cope and Esin Yavuz.

Example projects were provided by Alan Diamond, James Turner, Esin Yavuz and Thomas Nowotny. MPI support was largely developed by Mengchi Zhang.

Previous

14 Namespace Index

14.1 Namespace List

Here is a list of all namespaces with brief descriptions:

CodeGenerator	
Helper class for generating code - automatically inserts brackets, indents etc	71
CodeGenerator::CUDA	77
CodeGenerator::CUDA::Optimiser	79
CodeGenerator::CUDA::PresynapticUpdateStrategy	79
CodeGenerator::SingleThreadedCPU	80
CodeGenerator::SingleThreadedCPU::Optimiser	80
CurrentSourceModels	80
filesystem	81
InitSparseConnectivitySnippet Base class for all sparse connectivity initialisation snippets	81
InitVarSnippet Base class for all value initialisation snippets	8 1
Logging	82
Models	82
NeuronModels	83
plog	83
PostsynapticModels	83
pugi	84
pygenn	84
pygenn.genn_groups	84
pygenn.genn_model	84
pygenn.model_preprocessor	92
Snippet	96

SpineMLSimulator	97
SpineMLSimulator::Connectors	97
SpineMLSimulator::Input	98
SpineMLSimulator::InputValue	98
SpineMLSimulator::LogOutput	98
SpineMLSimulator::ModelProperty	99
Utils	99
WeightUpdateModels	100
15 Hierarchical Index	
15.1 Class Hierarchy	
This inheritance list is sorted roughly, but not completely, alphabe	etically:
AnalogueRecorder< T >	106
CodeGenerator::BackendBase	133
CodeGenerator::CUDA::Backend	107
CodeGenerator::SingleThreadedCPU::Backend	121
Snippet::Base	155
InitSparseConnectivitySnippet::Base	149
InitSparseConnectivitySnippet::FixedProbabilityB	ase 199
InitSparseConnectivitySnippet::FixedProbability	ty 198
InitSparseConnectivitySnippet::FixedProbability	tyNoAutapse 201
InitSparseConnectivitySnippet::OneToOne	262
InitSparseConnectivitySnippet::Uninitialised	361
InitVarSnippet::Base	151
InitVarSnippet::Constant	171
InitVarSnippet::Exponential	191
InitVarSnippet::Gamma	203
InitVarSnippet::Normal	259
InitVarSnippet::Uniform	358
InitVarSnippet::Uninitialised	360
Models::Base	151
CurrentSourceModels::Base	148

CurrentSourceModels::DC	181
CurrentSourceModels::GaussianNoise	204
NeuronModels::Base	153
NeuronModels::Izhikevich	222
NeuronModels::IzhikevichVariable	225
NeuronModels::LIF	227
NeuronModels::Poisson	267
NeuronModels::PoissonNew	270
NeuronModels::RulkovMap	288
NeuronModels::SpikeSource	304
NeuronModels::SpikeSourceArray	306
NeuronModels::TraubMiles	350
NeuronModels::TraubMilesAlt	353
NeuronModels::TraubMilesFast	355
NeuronModels::TraubMilesNStep	356
PostsynapticModels::Base	157
PostsynapticModels::DeltaCurr	183
PostsynapticModels::ExpCond	187
PostsynapticModels::ExpCurr	189
WeightUpdateModels::Base	160
WeightUpdateModels::PiecewiseSTDP	26 ²
WeightUpdateModels::StaticGraded	312
WeightUpdateModels::StaticPulse	314
WeightUpdateModels::StaticPulseDendriticDelay	316
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base	158
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan	274
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask	276
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan	283
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural	285
SpineMLSimulator::Input::Base	164
SpineMLSimulator::Input::Analogue	100
SpineMLSimulator::Input::SpikeBase	30 1

SpineMLSimulator::Input::InterSpikeIntervalBase	221
SpineMLSimulator::Input::PoissonSpikeRate	273
SpineMLSimulator::Input::RegularSpikeRate	287
SpineMLSimulator::Input::SpikeTime	308
SpineMLSimulator::InputValue::Base	165
SpineMLSimulator::InputValue::ConstantArray	173
SpineMLSimulator::InputValue::External	193
SpineMLSimulator::InputValue::ExternalNetwork	194
SpineMLSimulator::InputValue::ScalarBase	291
SpineMLSimulator::InputValue::Constant	172
SpineMLSimulator::InputValue::TimeVarying	348
SpineMLSimulator::InputValue::TimeVaryingArray	349
SpineMLSimulator::LogOutput::Base	166
SpineMLSimulator::LogOutput::AnalogueBase	101
SpineMLSimulator::LogOutput::AnalogueExternal	103
SpineMLSimulator::LogOutput::AnalogueNetwork	105
SpineMLSimulator::LogOutput::AnalogueFile	104
SpineMLSimulator::LogOutput::Event	186
SpineMLSimulator::ModelProperty::Base	168
SpineMLSimulator::ModelProperty::ExponentialDistribution	192
SpineMLSimulator::ModelProperty::Fixed	197
SpineMLSimulator::ModelProperty::NormalDistribution	260
SpineMLSimulator::ModelProperty::UniformDistribution	359
SpineMLSimulator::ModelProperty::ValueList	363
CodeGenerator::CodeStream::CB	169
CurrentSource	178
CurrentSourceInternal	181
Snippet::Base::DerivedParam	185
Snippet::Base::EGP	185
CodeGenerator::FunctionTemplate	202
GenerateRunBase	206
Snippet::Init< SnippetBase >	220

Snippet::Init< InitSparseConnectivitySnippet::Base >	220
InitSparseConnectivitySnippet::Init	219
Snippet::Init< InitVarSnippet::Base >	220
Models::VarInit std::ios_base std::basic ios	368
std::basic_ios std::basic_ostream std::ostream	
CodeGenerator::CodeStream	170
CodeGenerator::TeeStream	344
CodeGenerator::MemAlloc	230
ModelSpec	231
ModelSpecInternal	244
SpineMLSimulator::NetworkClient	245
NeuronGroup	251
NeuronGroupInternal	259
CodeGenerator::CodeStream::OB object	261
pygenn.genn_groups.Group	218
pygenn.genn_groups.CurrentSource	174
pygenn.genn_groups.NeuronGroup	246
pygenn.genn_groups.SynapseGroup	320
pygenn.genn_model.GeNNModel	207
pygenn.model_preprocessor.ExtraGlobalVariable	195
pygenn.model_preprocessor.Variable	365
Snippet::Base::ParamVal	263
CodeGenerator::PreferencesBase	281
CodeGenerator::CUDA::Preferences	279
CodeGenerator::SingleThreadedCPU::Preferences	281
CodeGenerator::CodeStream::Scope	292
SharedLibraryModel< scalar >	292
SpineMLSimulator::Simulator	298
SpikeWriterText	309
SpikeWriterTextCached	310

SpineMLSimulator::Sta	atevar< 1 >	311
SpineMLSimulator::Statement	ateVar< scalar >	311
CodeGenerator::Te	eBuf	343
CodeGenerator::Subst	titutions	317
SynapseGroup		329
SynapseGroupInte	rnal	342
Timer		345
SpineMLSimulator::Tir	mer	346
TimerAccumulate		346
SpineMLSimulator::Tir	merAccumulate	347
Snippet::ValueBase<	NumVars >	362
Snippet::ValueBase<	0 >	363
Models::Base::Var		364
Models::VarInitContair	nerBase< NumVars >	368
Models::VarInitContair Writer	nerBase< 0 >	369
SpikeRecorder< W	/riter >	302
16 Class Index		
16.1 Class List		
Here are the classes, struct	ts, unions and interfaces with brief descriptions:	
SpineMLSimulator::Inp	put::Analogue	100
SpineMLSimulator::Lo	ogOutput::AnalogueBase	101
SpineMLSimulator::Lo	gOutput::AnalogueExternal	103
SpineMLSimulator::Lo	ogOutput::AnalogueFile	104
SpineMLSimulator::Lo	gOutput::AnalogueNetwork	105
AnalogueRecorder< T	·>	106
CodeGenerator::CUDA	A::Backend	107
CodeGenerator::Single	eThreadedCPU::Backend	121
CodeGenerator::Backe	endBase	133
CurrentSourceModels Base class for all c	::Base current source models	148

16.1 Class List 63

InitSparseConnectivitySnippet::Base	149
InitVarSnippet::Base	151
Models::Base Base class for all models - in addition to the parameters snippets have, models can have state variables	151
NeuronModels::Base Base class for all neuron models	153
Snippet::Base Base class for all code snippets	155
PostsynapticModels::Base Base class for all postsynaptic models	157
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base	158
WeightUpdateModels::Base Base class for all weight update models	160
SpineMLSimulator::Input::Base	164
SpineMLSimulator::InputValue::Base	165
SpineMLSimulator::LogOutput::Base	166
SpineMLSimulator::ModelProperty::Base	168
CodeGenerator::CodeStream::CB A close bracket marker	169
CodeGenerator::CodeStream	170
InitVarSnippet::Constant Initialises variable to a constant value	171
SpineMLSimulator::InputValue::Constant	172
SpineMLSimulator::InputValue::ConstantArray	173
pygenn.genn_groups.CurrentSource Class representing a current injection into a group of neurons	174
CurrentSource	178
CurrentSourceInternal	181
CurrentSourceModels::DC DC source	181
PostsynapticModels::DeltaCurr Simple delta current synapse	183
Snippet::Base::DerivedParam A derived parameter has a name and a function for obtaining its value	185
Snippet::Base::EGP An extra global parameter has a name and a type	185
SpineMLSimulator::LogOutput::Event	186

PostsynapticModels::ExpCond Exponential decay with synaptic input treated as a conductance value	187
PostsynapticModels::ExpCurr Exponential decay with synaptic input treated as a current value	189
InitVarSnippet::Exponential Initialises variable by sampling from the exponential distribution	19 1
SpineMLSimulator::ModelProperty::ExponentialDistribution	192
SpineMLSimulator::InputValue::External	193
SpineMLSimulator::InputValue::ExternalNetwork	194
pygenn.model_preprocessor.ExtraGlobalVariable Class holding information about GeNN extra global pointer variable	195
SpineMLSimulator::ModelProperty::Fixed	197
InitSparseConnectivitySnippet::FixedProbability	198
InitSparseConnectivitySnippet::FixedProbabilityBase	199
InitSparseConnectivitySnippet::FixedProbabilityNoAutapse	20 1
CodeGenerator::FunctionTemplate	202
InitVarSnippet::Gamma Initialises variable by sampling from the exponential distribution	203
CurrentSourceModels::GaussianNoise Noisy current source with noise drawn from normal distribution	204
GenerateRunBase	206
pygenn.genn_model.GeNNModel GeNNModel class This class helps to define, build and run a GeNN model from python	207
pygenn.genn_groups.Group Parent class of NeuronGroup, SynapseGroup and CurrentSource	218
InitSparseConnectivitySnippet::Init	219
Snippet::Init< SnippetBase >	220
SpineMLSimulator::Input::InterSpikeIntervalBase	221
NeuronModels::Izhikevich Izhikevich neuron with fixed parameters [1]	222
NeuronModels::IzhikevichVariable Izhikevich neuron with variable parameters [1]	225
NeuronModels::LIF	227
CodeGenerator::MemAlloc	230
ModelSpec Object used for specifying a neuronal network model	23 1
ModelSpecInternal	244

16.1 Class List 65

SpineMLSimulator::NetworkClient	245
pygenn.genn_groups.NeuronGroup Class representing a group of neurons	246
NeuronGroup	251
NeuronGroupInternal	259
InitVarSnippet::Normal Initialises variable by sampling from the normal distribution	259
SpineMLSimulator::ModelProperty::NormalDistribution	260
CodeGenerator::CodeStream::OB An open bracket marker	261
InitSparseConnectivitySnippet::OneToOne Initialises connectivity to a 'one-to-one' diagonal matrix	262
Snippet::Base::ParamVal Additional input variables, row state variables and other things have a name, a type and an initial value	263
WeightUpdateModels::PiecewiseSTDP This is a simple STDP rule including a time delay for the finite transmission speed of the synapse	264
NeuronModels::Poisson Poisson neurons	267
NeuronModels::PoissonNew Poisson neurons	270
SpineMLSimulator::Input::PoissonSpikeRate	273
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan Postsynaptic parallelism	274
CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask Postsynaptic parallelism	276
CodeGenerator::CUDA::Preferences Preferences for CUDA backend	279
CodeGenerator::SingleThreadedCPU::Preferences	281
CodeGenerator::PreferencesBase Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator	281
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan Presynaptic parallelism	283
CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural Presynaptic parallelism with procedural connectivity	285
SpineMLSimulator::Input::RegularSpikeRate	287
NeuronModels::RulkovMap Rulkov Map neuron	288

SpineMLSimulator::InputValue::ScalarBase	29 1
CodeGenerator::CodeStream::Scope	292
SharedLibraryModel < scalar >	292
SpineMLSimulator::Simulator	298
SpineMLSimulator::Input::SpikeBase	30 1
SpikeRecorder < Writer > Class to read spikes from neuron groups	302
NeuronModels::SpikeSource	
Empty neuron which allows setting spikes from external sources	304
NeuronModels::SpikeSourceArray Spike source array	306
SpineMLSimulator::Input::SpikeTime	308
SpikeWriterText Class to write spikes to text file	309
SpikeWriterTextCached Class to write spikes to text file, caching in memory before writing	310
SpineMLSimulator::StateVar< T >	31 1
WeightUpdateModels::StaticGraded Graded-potential, static synapse	312
WeightUpdateModels::StaticPulse Pulse-coupled, static synapse	314
WeightUpdateModels::StaticPulseDendriticDelay Pulse-coupled, static synapse with heterogenous dendritic delays	316
CodeGenerator::Substitutions	317
pygenn.genn_groups.SynapseGroup Class representing synaptic connection between two groups of neurons	320
SynapseGroup	329
SynapseGroupInternal	342
CodeGenerator::TeeBuf	343
CodeGenerator::TeeStream	344
Timer A generic timer which can give the current elapsed time	345
SpineMLSimulator::Timer	346
TimerAccumulate A timer which adds its elapsed time to an accumulator variable on destruction	346
SpineMLSimulator::TimerAccumulate	347
SpineMLSimulator::InputValue::TimeVarving	348

17 File Index 67

SpineMLSimulator::InputValue::TimeVaryingArray	349
NeuronModels::TraubMiles Hodgkin-Huxley neurons with Traub & Miles algorithm	350
NeuronModels::TraubMilesAlt Hodgkin-Huxley neurons with Traub & Miles algorithm	353
NeuronModels::TraubMilesFast Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations	355
NeuronModels::TraubMilesNStep Hodgkin-Huxley neurons with Traub & Miles algorithm	356
InitVarSnippet::Uniform Initialises variable by sampling from the uniform distribution	358
SpineMLSimulator::ModelProperty::UniformDistribution	359
InitVarSnippet::Uninitialised Used to mark variables as uninitialised - no initialisation code will be run	360
InitSparseConnectivitySnippet::Uninitialised Used to mark connectivity as uninitialised - no initialisation code will be run	361
Snippet::ValueBase < NumVars >	362
Snippet::ValueBase < 0 >	363
SpineMLSimulator::ModelProperty::ValueList	363
Models::Base::Var A variable has a name, a type and an access type	364
pygenn.model_preprocessor.Variable Class holding information about GeNN variables	365
Models::VarInit	368
Models::VarInitContainerBase< NumVars >	368
Models::VarInitContainerBase< 0 >	369
17 File Index	
17.1 File List	
Here is a list of all files with brief descriptions:	
initpy	371
analogueRecorder.h	371
cuda/backend.cc	371
single_threaded_cpu/backend.cc	371
cuda/backend.h	372

single_threaded_cpu/backend.h	373
backendBase.cc	373
backendBase.h	374
backendExport.h	374
binomial.cc	374
binomial.h	375
codeGenUtils.cc	375
codeGenUtils.h	376
codeStream.cc	377
codeStream.h	378
connectors.cc	378
connectors.h	379
currentSource.cc	379
currentSource.h	379
currentSourceInternal.h	379
currentSourceModels.cc	380
currentSourceModels.h	380
generateAll.cc	381
generateAll.h	381
generateInit.cc	381
generateInit.h	382
generateMakefile.cc	382
generateMakefile.h	382
generateMPI.cc Contains functions to generate code for running the simulation with MPI. Part of the code generation section	382
generateMPI.h Contains functions to generate code for running the simulation with MPI. Part of the code generation section	383
generateMSBuild.cc	383
generateMSBuild.h	383
generateNeuronUpdate.cc	384
generateNeuronUpdate.h	384
generateRun.h	384

17.1 File List 69

modelSpec.cc modelSpec.h	401
models.h	399
modelProperty.h	399
modelProperty.cc	399
model_preprocessor.py	398
logWriter.h	398
logOutput.h	397
logOutput.cc	397
logging.h	394
logging.cc	394
inputValue.h	394
inputValue.cc	393
input.h	393
input.cc	393
initVarSnippet.h	392
initVarSnippet.cc	391
initSparseConnectivitySnippet.h	389
initSparseConnectivitySnippet.cc	389
gennUtils.h	388
gennUtils.cc	388
gennExport.h	387
genn_model.py	386
genn_groups.py	386
generateSynapseUpdate.h	386
generateSynapseUpdate.cc	385
generateSupportCode.h	385
generateSupportCode.cc	385
generateRunner.h	385
generateRunner.cc	384

modelSpecInternal.h	405
networkClient.cc	405
networkClient.h	405
neuronGroup.cc	406
neuronGroup.h	406
neuronGroupInternal.h	406
neuronModels.cc	406
neuronModels.h	408
cuda/optimiser.cc	410
single_threaded_cpu/optimiser.cc	411
cuda/optimiser.h	411
single_threaded_cpu/optimiser.h	411
postsynapticModels.cc	412
postsynapticModels.h	412
presynapticUpdateStrategy.cc	413
presynapticUpdateStrategy.h	414
sharedLibraryModel.h	414
simulator.cc	415
simulator.h	415
snippet.h	416
spikeRecorder.h	417
stateVar.h	417
substitutions.h	418
synapseGroup.cc	418
synapseGroup.h	418
synapseGroupInternal.h	419
synapseMatrixType.h	419
teeStream.h	42 1
include/spineml/simulator/timer.h	421
userproject/include/timer.h	422
utils.h	422
variableMode.h	423

weightUpdateModels.cc	423
weightUpdateModels.h	424

18 Namespace Documentation

18.1 CodeGenerator Namespace Reference

Helper class for generating code - automatically inserts brackets, indents etc.

Namespaces

- CUDA
- SingleThreadedCPU

Classes

- class BackendBase
- · class CodeStream
- struct FunctionTemplate
- class MemAlloc
- struct PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

- · class Substitutions
- · class TeeBuf
- · class TeeStream

Functions

• void substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

• bool regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

bool regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

This function substitutes function calls in the form:

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr> void writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

• template<class T , typename std::enable_if< std::is_floating_point< T >::value >::type * = nullptr> std::string writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

• size t ceilDivide (size t numerator, size t denominator)

Divide two integers, rounding up i.e. effectively taking ceil.

size_t padSize (size_t size, size_t blockSize)

Pad an integer to a multiple of another.

std::string ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postIdx, const std::string &devPrefix, const std::string &preVarPrefix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as ___ldg(&XXX)

void postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std::string &preldx, const std::string &postVarPrefix="", const std::string &postVarSuffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

void neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &preldx, const std::string &devPrefix, double dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="", const std::string &postVarPrefix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

- GENN_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & operator<< (std::ostream &s, const CodeStream::CB &cb)
- GENN_EXPORT std::vector< std::string > generateAll (const ModelSpecInternal &model, const Backend←
 Base &backend, const filesystem::path &outputPath, bool standaloneModules=false)
- void generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- void GENN_EXPORT generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector
 std::string > &moduleNames)

A function that generates predominantly MPI infrastructure code.

- void GENN_EXPORT generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)
- void generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)
- MemAlloc generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)
- void generateSupportCode (CodeStream &os, const ModelSpecInternal &model)
- void generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

18.1.1 Detailed Description

Helper class for generating code - automatically inserts brackets, indents etc.

Based heavily on: https://stackoverflow.com/questions/15053753/writing-a-manipulator-for-a-cus

18.1.2 Function Documentation

18.1.2.1 ceilDivide()

Divide two integers, rounding up i.e. effectively taking ceil.

18.1.2.2 checkUnreplacedVariables()

This function checks for unknown variable definitions and returns a gennError if any are found.

18.1.2.3 ensureFtype()

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

18.1.2.4 functionSubstitute()

```
void CodeGenerator::functionSubstitute (
    std::string & code,
    const std::string & funcName,
    unsigned int numParams,
    const std::string & replaceFuncTemplate )
```

This function substitutes function calls in the form:

\$(functionName, parameter1, param2Function(0.12, "string"))

with replacement templates in the form:

actualFunction(CONSTANT, \$(0), \$(1))

18.1.2.5 generateAll()

18.1.2.6 generateInit()

18.1.2.7 generateMakefile()

```
void CodeGenerator::generateMakefile (
    std::ostream & os,
    const BackendBase & backend,
    const std::vector< std::string > & moduleNames )
```

18.1.2.8 generateMPI()

A function that generates predominantly MPI infrastructure code.

In this function MPI infrastructure code are generated, including: MPI send and receive functions.

18.1.2.9 generateMSBuild()

```
void CodeGenerator::generateMSBuild (
    std::ostream & os,
    const BackendBase & backend,
    const std::string & projectGUID,
    const std::vector< std::string > & moduleNames )
```

18.1.2.10 generateNeuronUpdate()

18.1.2.11 generateRunner()

18.1.2.12 generateSupportCode()

18.1.2.13 generateSynapseUpdate()

18.1.2.14 neuronSubstitutionsInSynapticCode()

```
void CodeGenerator::neuronSubstitutionsInSynapticCode (
    Substitutions & substitutions,
    const SynapseGroupInternal & sg,
    const std::string & preIdx,
    const std::string & postIdx,
    const std::string & devPrefix,
    double dt,
    const std::string & preVarPrefix = "",
    const std::string & preVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarPrefix = "",
    const std::string & postVarSuffix = "")
```

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

Parameters

substitutions	the code string to work on	
sg	the synapse group connecting the pre and postsynaptic neuron populations whose parameters might need to be substituted	
preldx	index of the pre-synaptic neuron to be accessed for _pre variables; differs for different Span)	
postldx	index of the post-synaptic neuron to be accessed for _post variables; differs for different Span)	
devPrefix	device prefix, "dd_" for GPU, nothing for CPU	
dt	simulation timestep (ms)	
preVarPrefix	prefix to be used for presynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)	
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	
postVarPrefix	prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)	
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)	

```
size_t size,
size_t blockSize ) [inline]
```

Pad an integer to a multiple of another.

18.1.2.18 postNeuronSubstitutionsInSynapticCode()

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

Parameters

substitutions	the code string to work on
devPrefix	device prefix, "dd_" for GPU, nothing for CPU
postVarPrefix	prefix to be used for postsynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
postVarSuffix	suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)

18.1.2.19 preNeuronSubstitutionsInSynapticCode()

```
void CodeGenerator::preNeuronSubstitutionsInSynapticCode (
    Substitutions & substitutions,
    const SynapseGroupInternal & sg,
    const std::string & offset,
    const std::string & axonalDelayOffset,
    const std::string & postIdx,
    const std::string & devPrefix,
    const std::string & preVarPrefix = "",
    const std::string & preVarSuffix = "")
```

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

Parameters

substitutions	the code string to work on
devPrefix	device prefix, "dd_" for GPU, nothing for CPU
preVarPrefix	prefix to be used for presynaptic variable accesses - typically combined with suffix to wrap in function call such asldg(&XXX)
preVarSuffix	suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such asldg(&XXX)

18.1.2.20 regexFuncSubstitute()

```
bool CodeGenerator::regexFuncSubstitute (  std::string \ \& \ s,  const std::string & trg, const std::string & rep )
```

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

18.1.2.21 regexVarSubstitute()

```
bool CodeGenerator::regexVarSubstitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

18.1.2.22 substitute()

```
void CodeGenerator::substitute (
    std::string & s,
    const std::string & trg,
    const std::string & rep )
```

Tool for substituting strings in the neuron code strings or other templates.

18.1.2.23 writePreciseString() [1/2]

This function writes a floating point value to a stream -setting the precision so no digits are lost.

18.1.2.24 writePreciseString() [2/2]

This function writes a floating point value to a string - setting the precision so no digits are lost.

18.2 CodeGenerator::CUDA Namespace Reference

Namespaces

- Optimiser
- PresynapticUpdateStrategy

Classes

- · class Backend
- struct Preferences

Preferences for CUDA backend.

Typedefs

using KernelBlockSize = std::array < size_t, KernelMax >
 Array of block sizes for each kernel.

Enumerations

- enum DeviceSelect { DeviceSelect::OPTIMAL, DeviceSelect::MOST_MEMORY, DeviceSelect::MANUAL }
 Methods for selecting CUDA device.
- enum BlockSizeSelect { BlockSizeSelect::OCCUPANCY, BlockSizeSelect::MANUAL }
 Methods for selecting CUDA kernel block size.
- enum Kernel {

KernelNeuronUpdate, KernelPresynapticUpdate, KernelPostsynapticUpdate, KernelSynapseDynamics⇔ Update,

KernelInitialize, KernelInitializeSparse, KernelPreNeuronReset, KernelPreSynapseReset, KernelMax }

Kernels generated by CUDA backend.

18.2.1 Typedef Documentation

18.2.1.1 KernelBlockSize

using CodeGenerator::CUDA::KernelBlockSize = typedef std::array<size_t, KernelMax>

Array of block sizes for each kernel.

18.2.2 Enumeration Type Documentation

18.2.2.1 BlockSizeSelect

```
enum CodeGenerator::CUDA::BlockSizeSelect [strong]
```

Methods for selecting CUDA kernel block size.

Enumerator

OCCUPANCY	Pick optimal blocksize for each kernel based on occupancy.
MANUAL	Use block sizes specified by user.

18.2.2.2 DeviceSelect

enum CodeGenerator::CUDA::DeviceSelect [strong]

Methods for selecting CUDA device.

Enumerator

OPTIMAL	Pick optimal device based on how well kernels can be simultaneously simulated and	
	occupancy.	
MOST_MEMORY	Pick device with most global memory.	
MANUAL	Use device specified by user.	

18.2.2.3 Kernel

```
enum CodeGenerator::CUDA::Kernel
```

Kernels generated by CUDA backend.

Enumerator

KernelNeuronUpdate	
KernelPresynapticUpdate	
KernelPostsynapticUpdate	
KernelSynapseDynamicsUpdate	
KernelInitialize	
KernelInitializeSparse	
KernelPreNeuronReset	
KernelPreSynapseReset	
KernelMax	

18.3 CodeGenerator::CUDA::Optimiser Namespace Reference

Functions

BACKEND_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::IAppender *backendAppender, int localHostID, const Preferences &preferences)

18.3.1 Function Documentation

18.3.1.1 createBackend()

18.4 CodeGenerator::CUDA::PresynapticUpdateStrategy Namespace Reference

Classes

- · class Base
- class PostSpan

Postsynaptic parallelism.

class PostSpanBitmask

Postsynaptic parallelism.

class PreSpan

Presynaptic parallelism.

· class PreSpanProcedural

Presynaptic parallelism with procedural connectivity.

18.5 CodeGenerator::SingleThreadedCPU Namespace Reference

Namespaces

Optimiser

Classes

- class Backend
- struct Preferences

18.6 CodeGenerator::SingleThreadedCPU::Optimiser Namespace Reference

Functions

BACKEND_EXPORT Backend createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::IAppender *backendAppender, int localHostID, const Preferences &preferences)

18.6.1 Function Documentation

18.6.1.1 createBackend()

18.7 CurrentSourceModels Namespace Reference

Classes

· class Base

Base class for all current source models.

class DC

DC source.

· class GaussianNoise

Noisy current source with noise drawn from normal distribution.

18.8 filesystem Namespace Reference

18.9 InitSparseConnectivitySnippet Namespace Reference

Base class for all sparse connectivity initialisation snippets.

Classes

- · class Base
- · class FixedProbability
- · class FixedProbabilityBase
- class FixedProbabilityNoAutapse
- · class Init
- class OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

· class Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

18.9.1 Detailed Description

Base class for all sparse connectivity initialisation snippets.

18.10 InitVarSnippet Namespace Reference

Base class for all value initialisation snippets.

Classes

- class Base
- · class Constant

Initialises variable to a constant value.

· class Exponential

Initialises variable by sampling from the exponential distribution.

class Gamma

Initialises variable by sampling from the exponential distribution.

· class Normal

Initialises variable by sampling from the normal distribution.

· class Uniform

Initialises variable by sampling from the uniform distribution.

· class Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

18.10.1 Detailed Description

Base class for all value initialisation snippets.

18.11 Logging Namespace Reference

Enumerations

 enum Channel { CHANNEL_GENN = 0, CHANNEL_CODE_GEN = 1, CHANNEL_BACKEND = 2, CHANN← EL MAX }

Functions

 GENN_EXPORT void init (plog::Severity gennLevel, plog::Severity codeGeneratorLevel, plog::IAppender *gennAppender, plog::IAppender *codeGeneratorAppender)

18.11.1 Enumeration Type Documentation

18.11.1.1 Channel

```
enum Logging::Channel
```

Enumerator

CHANNEL_GENN	
CHANNEL_CODE_GEN	
CHANNEL_BACKEND	
CHANNEL_MAX	

18.11.2 Function Documentation

18.11.2.1 init()

18.12 Models Namespace Reference

Classes

· class Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

- · class VarInit
- · class VarInitContainerBase
- class VarInitContainerBase< 0 >

18.12.1 Detailed Description

Class used to bind together everything required to initialise a variable:

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

18.13 NeuronModels Namespace Reference

Classes

· class Base

Base class for all neuron models.

· class Izhikevich

Izhikevich neuron with fixed parameters [1].

· class IzhikevichVariable

Izhikevich neuron with variable parameters [1].

- class LIF
- · class Poisson

Poisson neurons.

class PoissonNew

Poisson neurons.

class RulkovMap

Rulkov Map neuron.

class SpikeSource

Empty neuron which allows setting spikes from external sources.

· class SpikeSourceArray

Spike source array.

· class TraubMiles

Hodgkin-Huxley neurons with Traub & Miles algorithm.

· class TraubMilesAlt

Hodgkin-Huxley neurons with Traub & Miles algorithm.

· class TraubMilesFast

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

• class TraubMilesNStep

Hodgkin-Huxley neurons with Traub & Miles algorithm.

18.14 plog Namespace Reference

18.15 PostsynapticModels Namespace Reference

Classes

· class Base

Base class for all postsynaptic models.

class DeltaCurr

Simple delta current synapse.

class ExpCond

Exponential decay with synaptic input treated as a conductance value.

class ExpCurr

Exponential decay with synaptic input treated as a current value.

18.16 pugi Namespace Reference

18.17 pygenn Namespace Reference

Namespaces

- genn_groups
- genn_model
- model_preprocessor

18.18 pygenn.genn_groups Namespace Reference

Classes

· class CurrentSource

Class representing a current injection into a group of neurons.

· class Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

class NeuronGroup

Class representing a group of neurons.

class SynapseGroup

Class representing synaptic connection between two groups of neurons.

Variables

• xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

18.18.1 Variable Documentation

18.18.1.1 xrange

```
pygenn.genn_groups.xrange = range
```

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

18.19 pygenn.genn_model Namespace Reference

Classes

class GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

Functions

def init_var (init_var_snippet, param_space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

• definit connectivity (init sparse connect snippet, param space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def create_custom_neuron_class (class_name, param_names=None, var_name_types=None, derived_
 params=None, sim_code=None, threshold_condition_code=None, reset_code=None, support_code=None,
 extra_global_params=None, additional_input_vars=None, is_auto_refractory_required=None, custom_
 body=None)

This helper function creates a custom NeuronModel class.

def create_custom_postsynaptic_class (class_name, param_names=None, var_name_types=None, derived_params=None, decay_code=None, apply_input_code=None, support_code=None, custom_
 body=None)

This helper function creates a custom PostsynapticModel class.

def create_custom_weight_update_class (class_name, param_names=None, var_name_types=None, pre
 _var_name_types=None, post_var_name_types=None, derived_params=None, sim_code=None, event
 _code=None, learn_post_code=None, synapse_dynamics_code=None, event_threshold_condition_
 code=None, pre_spike_code=None, post_spike_code=None, sim_support_code=None, learn_post_
 support_code=None, synapse_dynamics_support_code=None, extra_global_params=None, is_pre_
 spike_time_required=None, is_post_spike_time_required=None, custom_body=None)

This helper function creates a custom WeightUpdateModel class.

def create_custom_current_source_class (class_name, param_names=None, var_name_types=None, derived_params=None, injection_code=None, extra_global_params=None, custom_body=None)

This helper function creates a custom NeuronModel class.

def create_custom_model_class (class_name, base, param_names, var_name_types, derived_params, custom_body)

This helper function completes a custom model class creation.

def create_dpf_class (dp_func)

Helper function to create derived parameter function class.

def create_cmlf_class (cml_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

def create_custom_init_var_snippet_class (class_name, param_names=None, derived_params=None, var
 __init_code=None, custom_body=None)

This helper function creates a custom InitVarSnippet class.

def create_custom_sparse_connect_init_snippet_class (class_name, param_names=None, derived_
 params=None, row_build_code=None, row_build_state_vars=None, calc_max_row_len_func=None, calc_
 max_col_len_func=None, extra_global_params=None, custom_body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

Variables

- backend_modules = OrderedDict()
- m = import_module(".genn_wrapper." + b + "Backend", "pygenn")

18.19.1 Function Documentation

18.19.1.1 create_cmlf_class()

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

Parameters

a function which computes the length and takes three args "num_pre" (unsigned int), "num_post" (unsigned int) and "pars" (vector of double)

18.19.1.2 create_custom_current_source_class()

This helper function creates a custom NeuronModel class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc
injection_code	string with the current injection code
extra_global_params	list of pairs of strings with names and types of additional parameters
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.3 create_custom_init_var_snippet_class()

This helper function creates a custom InitVarSnippet class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_sparse_connect_init_snippet_class
```

class_name	name of the new class
param_names	list of strings with param names of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the pygenn.genn_wrapper.DerivedParamFunc' class
var_init_code	string with the variable initialization code
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.4 create_custom_model_class()

This helper function completes a custom model class creation.

This part is common for all model classes and is nearly useless on its own unless you specify custom_body.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class	
base	base class	
param_names	list of strings with param names of the model	
var_name_types	list of pairs of strings with varible names and types of the model	
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from the pygenn.genn_wrapper.DerivedParamFunc class	
custom_body	dictionary with attributes and methods of the new class	

18.19.1.5 create_custom_neuron_class()

```
threshold_condition_code = None,
reset_code = None,
support_code = None,
extra_global_params = None,
additional_input_vars = None,
is_auto_refractory_required = None,
custom_body = None )
```

This helper function creates a custom NeuronModel class.

See also

```
create_custom_postsynaptic_class
create_custom_weight_update_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.Snippet.DerivedParamFunc
sim_code	string with the simulation code
threshold_condition_code	string with the threshold condition code
reset_code	string with the reset code
support_code	string with the support code
extra_global_params	list of pairs of strings with names and types of additional parameters
additional_input_vars	list of tuples with names and types as strings and initial values of additional local input variables
is_auto_refractory_required	does this model require auto-refractory logic to be generated?
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.6 create_custom_postsynaptic_class()

This helper function creates a custom PostsynapticModel class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_current_source_class
```

```
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with varible names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.DerivedParamFunc
decay_code	string with the decay code
apply_input_code	string with the apply input code
support_code	string with the support code
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.7 create_custom_sparse_connect_init_snippet_class()

This helper function creates a custom InitSparseConnectivitySnippet class.

See also

```
create_custom_neuron_class
create_custom_weight_update_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of the class which inherits from pygenn.genn_wrapper.DerivedParamFunc
row_build_code	string with row building initialization code
row_build_state_vars	list of tuples of state variables, their types and their initial values to use across row building loop
calc_max_row_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum row length of synaptic matrix
calc_max_col_len_func	instance of class inheriting from CalcMaxLengthFunc used to calculate maximum col length of synaptic matrix

extra_global_params	list of pairs of strings with names and types of additional parameters
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.8 create_custom_weight_update_class()

```
def pygenn.genn_model.create_custom_weight_update_class (
             class_name,
             param_names = None,
             var_name_types = None,
             pre_var_name_types = None,
             post_var_name_types = None,
             derived_params = None,
              sim_code = None,
              event_code = None,
              learn_post_code = None,
              synapse_dynamics_code = None,
              event_threshold_condition_code = None,
             pre_spike_code = None,
             post_spike_code = None,
              sim_support_code = None,
              learn_post_support_code = None,
              synapse_dynamics_suppport_code = None,
              extra_global_params = None,
              is_pre_spike_time_required = None,
              is_post_spike_time_required = None,
              custom\_body = None)
```

This helper function creates a custom WeightUpdateModel class.

See also

```
create_custom_neuron_class
create_custom_postsynaptic_class
create_custom_current_source_class
create_custom_init_var_snippet_class
create_custom_sparse_connect_init_snippet_class
```

Parameters

class_name	name of the new class
param_names	list of strings with param names of the model
var_name_types	list of pairs of strings with variable names and types of the model
pre_var_name_types	list of pairs of strings with presynaptic variable names and types of the model
post_var_name_types	list of pairs of strings with postsynaptic variable names and types of the model
derived_params	list of pairs, where the first member is string with name of the derived parameter and the second MUST be an instance of a class which inherits from pygenn.genn_wrapper.DerivedParamFunc
sim_code	string with the simulation code
event_code	string with the event code
learn_post_code	string with the code to include in learn_synapse_post kernel/function
synapse_dynamics_code	string with the synapse dynamics code

event_threshold_condition_code	string with the event threshold condition code
pre_spike_code	string with the code run once per spiking presynaptic neuron
post_spike_code	string with the code run once per spiking postsynaptic neuron
sim_support_code	string with simulation support code
learn_post_support_code	string with support code for learn_synapse_post kernel/function
synapse_dynamics_suppport_code	string with synapse dynamics support code
extra_global_params	list of pairs of strings with names and types of additional parameters
is_pre_spike_time_required	boolean, is presynaptic spike time required in any weight update kernels?
is_post_spike_time_required	boolean, is postsynaptic spike time required in any weight update kernels?
custom_body	dictionary with additional attributes and methods of the new class

18.19.1.9 create_dpf_class()

```
def pygenn.genn_model.create_dpf_class ( dp\_func \ )
```

Helper function to create derived parameter function class.

Parameters

dp_func	a function which computes the derived parameter and takes two args "pars" (vector of double) and	
	"dt" (double)	

18.19.1.10 init_connectivity()

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

Parameters

init_sparse_connect_snippet	type of the InitSparseConnectivitySnippet class as string or instance of class derived from InitSparseConnectivitySnippet::Custom.
param_space	dict with param values for the InitSparseConnectivitySnippet class

18.19.1.11 init_var()

This helper function creates a VarInit object to easily initialise a variable using a snippet.

init_var_snippet	type of the InitVarSnippet class as string or instance of class derived from InitVarSnippet::Custom class.
param_space	dict with param values for the InitVarSnippet class

18.19.2 Variable Documentation

18.19.2.1 backend_modules

```
pygenn.genn_model.backend_modules = OrderedDict()
```

18.19.2.2 m

```
pygenn.genn_model.m = import_module(".genn_wrapper." + b + "Backend", "pygenn")
```

18.20 pygenn.model_preprocessor Namespace Reference

Classes

· class ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

class Variable

Class holding information about GeNN variables.

Functions

def prepare_model (model, param_space, var_space, pre_var_space=None, post_var_space=None, model_family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

• def prepare_snippet (snippet, param_space, snippet_family)

Prepare a snippet by checking its validity and extracting information about parameters.

def is_model_valid (model, model_family)

Check whether the model is valid, i.e is native or derived from model_family.Custom.

def param_space_to_vals (model, param_space)

Convert a param_space dict to ParamValues.

def param_space_to_val_vec (model, param_space)

Convert a param_space dict to a std::vector<double>

def var_space_to_vals (model, var_space)

Convert a var_space dict to VarValues.

• def pre_var_space_to_vals (model, var_space)

Convert a var_space dict to PreVarValues.

• def post_var_space_to_vals (model, var_space)

Convert a var_space dict to PostVarValues.

Variables

- GeNNType = namedtuple("GeNNType", ["np_dtype", "assign_ext_ptr_array", "assign_ext_ptr_single"])
- dictionary genn_types

18.20.1 Function Documentation

18.20.1.1 is_model_valid()

Check whether the model is valid, i.e is native or derived from model_family.Custom.

Parameters

model	string or instance of model_family.Custom	
model_family	model family (NeuronModels, WeightUpdateModels or PostsynapticModels) to which model	
	should belong to	

Returns

instance of the model and its type as string

Raises ValueError if model is not valid (i.e. is not custom and is not natively available)

18.20.1.2 param_space_to_val_vec()

Convert a param_space dict to a std::vector<double>

Parameters

model	instance of the model
param_space	dict with parameters

Returns

native vector of parameters

18.20.1.3 param_space_to_vals()

Convert a param_space dict to ParamValues.

Parameters

model	instance of the model
param_space	dict with parameters

Returns

native model's ParamValues

```
18.20.1.4 post_var_space_to_vals()
```

Convert a var_space dict to PostVarValues.

Parameters

model	instance of the weight update model
var_space	dict with Variables

Returns

native model's VarValues

```
18.20.1.5 pre_var_space_to_vals()
```

Convert a var_space dict to PreVarValues.

Parameters

model	instance of the weight update model
var_space	dict with Variables

Returns

native model's VarValues

18.20.1.6 prepare_model()

Prepare a model by checking its validity and extracting information about variables and parameters.

model	string or instance of a class derived from	
	pygenn.genn_wrapper.NeuronModels.Custom or	
	pygenn.genn_wrapper.WeightUpdateModels.Custom or	
	pygenn.genn_wrapper.CurrentSourceModels.Custom	
param_space	dict with model parameters	
var_space	dict with model variables	
pre_var_space	optional dict with (weight update) model presynaptic variables	
post_var_space	optional dict with (weight update) model postsynaptic variables	
model_family	pygenn.genn_wrapper.NeuronModels or	
	pygenn.genn_wrapper.WeightUpdateModels or	
	pygenn.genn_wrapper.CurrentSourceModels	

Returns

tuple consisting of (model instance, model type, model parameter names, model parameters, list of variable names, dict mapping names of variables to instances of class Variable)

18.20.1.7 prepare_snippet()

Prepare a snippet by checking its validity and extracting information about parameters.

Parameters

snippet	string or instance of a class derived from	
	<pre>pygenn.genn_wrapper.InitVarSnippet.Custom or</pre>	
	pygenn.genn_wrapper.InitSparseConnectivitySnippet.Custom	
param_space	dict with model parameters	
snippet_family	pygenn.genn_wrapper.InitVarSnippet or	
	pygenn.genn_wrapper.InitSparseConnectivitySnippet	

Returns

tuple consisting of (snippet instance, snippet type, snippet parameter names, snippet parameters)

18.20.1.8 var_space_to_vals()

Convert a var_space dict to VarValues.

Parameters

model	instance of the model
var_space	dict with Variables

Returns

native model's VarValues

18.20.2 Variable Documentation

18.20.2.1 genn_types

dictionary pygenn.model_preprocessor.genn_types

Initial value:

```
1 =
      "scalar":
                           GeNNType(np.float32, slm.assign_external_pointer_array_f,
      slm.assign_external_pointer_single_f),
3
      "float":
                          GeNNType(np.float32, slm.assign_external_pointer_array_f,
      slm.assign_external_pointer_single_f),
                           GeNNType(np.float64, slm.assign_external_pointer_array_d,
4
      slm.assign_external_pointer_single_d),
5
      "int":
                           GeNNType(np.int32, slm.assign_external_pointer_array_i,
      slm.assign_external_pointer_single_i),
      "unsigned int":
                          GeNNType(np.uint32, slm.assign_external_pointer_array_ui,
6
      slm.assign_external_pointer_single_ui),
      "short":
                           GeNNType(np.int16, slm.assign_external_pointer_array_s,
      slm.assign_external_pointer_single_s),
      "unsigned short":
8
                          GennType(np.uint16, slm.assign_external_pointer_array_us,
      slm.assign_external_pointer_single_us),
9
      "char":
                          GennType(np.int8, slm.assign_external_pointer_array_sc,
      slm.assign_external_pointer_single_sc),
10
       "unsigned char":
                           GeNNType(np.uint8, slm.assign_external_pointer_array_uc,
      slm.assign_external_pointer_single_uc),
                     GennType(np.uint64, None, None),
GennType(np.int64, None, None),
GennType(np.uint32, slm.assign_external_pointer_array_ui,
11
       "uint64_t":
12
       "int64_t":
       "uint32_t":
13
      slm.assign_external_pointer_single_ui),
14
                            GeNNType(np.int32, slm.assign_external_pointer_array_i,
      slm.assign_external_pointer_single_i),
15
                            GeNNType(np.uint16, slm.assign_external_pointer_array_us,
      {\tt slm.assign\_external\_pointer\_single\_us)}\,,
16
       "int16 t":
                           GeNNType(np.int16, slm.assign_external_pointer_array_s,
      slm.assign_external_pointer_single_s),
17
       "uint8_t":
                           GeNNType(np.uint8, slm.assign_external_pointer_array_uc,
      slm.assign_external_pointer_single_uc),
                            GeNNType(np.int8, slm.assign_external_pointer_array_sc,
18
      slm.assign_external_pointer_single_sc) }
```

18.20.2.2 GeNNType

```
pygenn.model_preprocessor.GeNNType = namedtuple("GeNNType", ["np_dtype", "assign_ext_ptr_
array", "assign_ext_ptr_single"])
```

18.21 Snippet Namespace Reference

Classes

· class Base

Base class for all code snippets.

- · class Init
- class ValueBase
- class ValueBase< 0 >

18.21.1 Detailed Description

Wrapper to ensure at compile time that correct number of values are used when specifying the values of a model's parameters and initial state.

18.22 SpineMLSimulator Namespace Reference

Namespaces

- Connectors
- Input
- InputValue
- LogOutput
- ModelProperty

Classes

- · class NetworkClient
- · class Simulator
- class StateVar
- class Timer
- · class TimerAccumulate

Typedefs

· typedef float scalar

18.22.1 Typedef Documentation

```
18.22.1.1 scalar
```

```
typedef float SpineMLSimulator::scalar
```

18.23 SpineMLSimulator::Connectors Namespace Reference

Functions

• unsigned int create (const pugi::xml_node &node, double dt, unsigned int numPre, unsigned int numPost, unsigned int **rowLength, unsigned int **ind, uint8_t **delay, const unsigned int *maxRowLength, const filesystem::path &basePath, std::vector< unsigned int > &remapIndices)

18.23.1 Function Documentation

18.23.1.1 create()

18.24 SpineMLSimulator::Input Namespace Reference

Classes

- class Analogue
- · class Base
- · class InterSpikeIntervalBase
- · class PoissonSpikeRate
- · class RegularSpikeRate
- class SpikeBase
- class SpikeTime

18.25 SpineMLSimulator::InputValue Namespace Reference

Classes

- · class Base
- · class Constant
- · class ConstantArray
- class External
- class ExternalNetwork
- · class ScalarBase
- class TimeVarying
- · class TimeVaryingArray

Functions

18.25.1 Function Documentation

18.25.1.1 create()

18.26 SpineMLSimulator::LogOutput Namespace Reference

Classes

- class AnalogueBase
- · class AnalogueExternal
- · class AnalogueFile
- class AnalogueNetwork
- · class Base
- · class Event

18.27 SpineMLSimulator::ModelProperty Namespace Reference

Classes

- · class Base
- · class ExponentialDistribution
- class Fixed
- · class NormalDistribution
- · class UniformDistribution
- · class ValueList

Functions

std::unique_ptr< Base > create (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size, bool skipGeNNInitialised, const filesystem::path &basePath, const std::string &value
 Namespace, const std::vector< unsigned int > *remapIndices)

18.27.1 Function Documentation

18.27.1.1 create()

18.28 Utils Namespace Reference

Functions

• GENN_EXPORT bool isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN_EXPORT bool isRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device

GENN_EXPORT bool isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

• GENN_EXPORT std::string getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

18.28.1 Function Documentation

18.28.1.1 getUnderlyingType()

Assuming type is a string containing a pointer type, function to return the underlying type.

Does the code string contain any functions requiring random number generator.

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

18.28.1.4 isTypePointer()

Function to determine whether a string containing a type is a pointer.

18.29 WeightUpdateModels Namespace Reference

Classes

· class Base

Base class for all weight update models.

class PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

· class StaticGraded

Graded-potential, static synapse.

· class StaticPulse

Pulse-coupled, static synapse.

· class StaticPulseDendriticDelay

Pulse-coupled, static synapse with heterogenous dendritic delays.

19 Class Documentation

19.1 SpineMLSimulator::Input::Analogue Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::Analogue:

```
SpineMLSimulator::Input::Base

SpineMLSimulator::Input::Analogue
```

Public Member Functions

- · virtual void apply (double dt, unsigned long long timestep) override

Additional Inherited Members

19.1.1 Constructor & Destructor Documentation

19.1.1.1 Analogue()

19.1.2 Member Function Documentation

19.1.2.1 apply()

Implements SpineMLSimulator::Input::Base.


The documentation for this class was generated from the following files:

- input.h
- input.cc

19.2 SpineMLSimulator::LogOutput::AnalogueBase Class Reference

```
#include <logOutput.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator :: LogOutput :: Analogue Base:$



Public Member Functions

- AnalogueBase (const pugi::xml_node &node, double dt, const ModelProperty::Base *modelProperty)
- const scalar * getStateVarBegin () const
- const scalar * getStateVarEnd () const
- unsigned int getModelPropertySize () const
- const std::vector< unsigned int > & getIndices () const

Protected Member Functions

• void pullModelPropertyFromDevice () const

19.2.1 Constructor & Destructor Documentation

19.2.1.1 AnalogueBase()

19.2.2 Member Function Documentation

19.2.2.1 getIndices()

```
const std::vector<unsigned int>& SpineMLSimulator::LogOutput::AnalogueBase::getIndices ( )
const [inline]
```

19.2.2.2 getModelPropertySize()

```
unsigned int SpineMLSimulator::LogOutput::AnalogueBase::getModelPropertySize ( ) const [inline]
```

19.2.2.3 getStateVarBegin()

```
const scalar* SpineMLSimulator::LogOutput::AnalogueBase::getStateVarBegin ( ) const [inline]
```

19.2.2.4 getStateVarEnd()

```
const scalar* SpineMLSimulator::LogOutput::AnalogueBase::getStateVarEnd ( ) const [inline]
```

19.2.2.5 pullModelPropertyFromDevice()

void SpineMLSimulator::LogOutput::AnalogueBase::pullModelPropertyFromDevice () const [inline],
[protected]


The documentation for this class was generated from the following files:

- · logOutput.h
- logOutput.cc

19.3 SpineMLSimulator::LogOutput::AnalogueExternal Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueExternal:



Public Member Functions

- AnalogueExternal (const pugi::xml_node &node, double dt, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)
- virtual void record (double dt, unsigned long long timestep) final

Protected Member Functions

• virtual void recordInternal ()

19.3.1 Constructor & Destructor Documentation

19.3.1.1 AnalogueExternal()

19.3.2 Member Function Documentation

19.3.2.1 record()

Implements SpineMLSimulator::LogOutput::Base.

19.3.2.2 recordInternal()

```
virtual void SpineMLSimulator::LogOutput::AnalogueExternal::recordInternal ( ) [inline],
[protected], [virtual]
```

 $Reimplemented \ in \ Spine MLS imulator:: Log Output:: Analogue Network.$


The documentation for this class was generated from the following files:

- logOutput.h
- logOutput.cc

19.4 SpineMLSimulator::LogOutput::AnalogueFile Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueFile:



Public Member Functions

- AnalogueFile (const pugi::xml_node &node, double dt, unsigned long long numTimeSteps, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)
- · virtual void record (double dt, unsigned long long timestep) override

Additional Inherited Members

19.4.1 Constructor & Destructor Documentation

19.4.1.1 AnalogueFile()

```
const std::string & port,
unsigned int popSize,
const filesystem::path & logPath,
const ModelProperty::Base * modelProperty )
```

19.4.2 Member Function Documentation

19.4.2.1 record()

```
void SpineMLSimulator::LogOutput::AnalogueFile::record ( \mbox{double $dt$,} \mbox{unsigned long long $timestep$ ) [override], [virtual]}
```

Implements SpineMLSimulator::LogOutput::Base.


The documentation for this class was generated from the following files:

- logOutput.h
- · logOutput.cc

19.5 SpineMLSimulator::LogOutput::AnalogueNetwork Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::AnalogueNetwork:



Public Member Functions

 AnalogueNetwork (const pugi::xml_node &node, double dt, const std::string &port, unsigned int popSize, const filesystem::path &logPath, const ModelProperty::Base *modelProperty)

Protected Member Functions

· virtual void recordInternal () override

19.5.1 Constructor & Destructor Documentation

19.5.1.1 AnalogueNetwork()

```
double dt,
const std::string & port,
unsigned int popSize,
const filesystem::path & logPath,
const ModelProperty::Base * modelProperty )
```

19.5.2 Member Function Documentation

19.5.2.1 recordinternal()

```
void SpineMLSimulator::LogOutput::AnalogueNetwork::recordInternal ( ) [override], [protected],
```

Reimplemented from SpineMLSimulator::LogOutput::AnalogueExternal.

The documentation for this class was generated from the following files:

- · logOutput.h
- logOutput.cc

19.6 AnalogueRecorder < T > Class Template Reference

```
#include <analogueRecorder.h>
```

Public Member Functions

- AnalogueRecorder (const std::string &filename, std::initializer_list< T *> variables, unsigned int popSize, const std::string &delimiter="")
- AnalogueRecorder (const std::string &filename, T *variable, unsigned int popSize, const std::string &delimiter="")
- void record (double t)

19.6.1 Constructor & Destructor Documentation

19.6.1.1 AnalogueRecorder() [1/2]

19.6.1.2 AnalogueRecorder() [2/2]

19.6.2 Member Function Documentation

19.6.2.1 record()

```
\label{template} \begin{tabular}{ll} template < typename T > \\ void Analogue Recorder < T >:: record ( \\ double t ) [inline] \end{tabular}
```


The documentation for this class was generated from the following file:

· analogueRecorder.h

19.7 CodeGenerator::CUDA::Backend Class Reference

```
#include <backend.h>
```

Inheritance diagram for CodeGenerator::CUDA::Backend:



Public Member Functions

- Backend (const KernelBlockSize &kernelBlockSizes, const Preferences &preferences, int localHostID, const std::string &scalarType, int device)
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
 Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const override

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler wumProceduralConnectHandler, SynapseGroupHandler postLearnHandler,
 SynapseGroupHandler synapseDynamicsHandler) const override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG←
 Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse←
 GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

- virtual void genDefinitionsPreamble (CodeStream &os, const ModelSpecInternal &model) const override
 Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file
- virtual void genDefinitionsInternalPreamble (CodeStream &os, const ModelSpecInternal &model) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

- virtual void genRunnerPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const override
- · virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamDefinition (CodeStream &definitions, const std::string &type, const std
 ::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size t count) const override

Generate code for pushing a variable to the 'device'.

 virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const override

Generate code for pulling a variable from the 'device'.

 virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pushing a variable's value in the current timestep to the 'device'.

 virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pulling a variable's value in the current timestep from the 'device'.

- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override

 Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.
- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override
 Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free) const override

Generate a single RNG instance.

Generate an RNG with a state per population member.

 virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override virtual void genReturnFreeDeviceMemoryBytes (CodeStream &os) const override

Generate code to return amount of free 'device' memory in bytes.

virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const override
- · virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- · virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- · virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

virtual bool isSynRemapRequired () const override

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const override

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

• virtual bool isAutomaticCopyEnabled () const override

Is automatic copy mode enabled in the preferences?

• virtual size_t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

- const cudaDeviceProp & getChosenCUDADevice () const
- int getChosenDeviceID () const
- int getRuntimeVersion () const
- std::string getNVCCFlags () const
- std::string getFloatAtomicAdd (const std::string &ftype) const
- size_t getNumInitialisationRNGStreams (const ModelSpecInternal &model) const

Get total number of RNG streams potentially used to initialise model.

size_t getKernelBlockSize (Kernel kernel) const

Static Public Member Functions

- static size_t getNumPresynapticUpdateThreads (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences)
- static size_t getNumPostsynapticUpdateThreads (const SynapseGroupInternal &sg)
- static size_t getNumSynapseDynamicsThreads (const SynapseGroupInternal &sg)
- static void addPresynapticUpdateStrategy (PresynapticUpdateStrategy::Base *strategy)

Register a new presynaptic update strategy.

Static Public Attributes

static const char * KernelNames [KernelMax]

Additional Inherited Members

19.7.1 Constructor & Destructor Documentation

19.7.1.1 Backend()

19.7.2 Member Function Documentation

19.7.2.1 addPresynapticUpdateStrategy()

Register a new presynaptic update strategy.

This function should be called with strategies in ascending order of preference

19.7.2.2 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

19.7.2.3 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.4 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.5 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.6 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.7 genCurrentVariablePull()

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.8 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

 $Implements\ Code Generator :: Backend Base.$

19.7.2.9 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

19.7.2.10 genDefinitionsPreamble()

```
void CodeGenerator::CUDA::Backend::genDefinitionsPreamble (
```

```
CodeStream & os,
const ModelSpecInternal & model ) const [override], [virtual]
```

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

19.7.2.11 genExtraGlobalParamAllocation()

Implements CodeGenerator::BackendBase.

19.7.2.12 genExtraGlobalParamDefinition()

Implements CodeGenerator::BackendBase.

19.7.2.13 genExtraGlobalParamImplementation()

 $Implements\ Code Generator :: Backend Base.$

19.7.2.14 genExtraGlobalParamPull()

Implements CodeGenerator::BackendBase.

19.7.2.15 genExtraGlobalParamPush()

```
VarLocation loc ) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

19.7.2.16 genGlobalRNG()

Generate a single RNG instance.

On single-threaded platforms this can be a standard RNG like M.T. but, on parallel platforms, it is likely to be a counter-based RNG

Implements CodeGenerator::BackendBase.

19.7.2.17 genInit()

Implements CodeGenerator::BackendBase.

19.7.2.18 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

19.7.2.19 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

19.7.2.20 genMakefilePreamble()

```
void CodeGenerator::CUDA::Backend::genMakefilePreamble (
```

```
std::ostream & os ) const [override], [virtual]
```

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

19.7.2.21 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

19.7.2.22 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

 $\textbf{see} \quad \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties} \\ \textbf{for more information.}$

Implements CodeGenerator::BackendBase.

19.7.2.23 genMSBuildImportProps()

Implements CodeGenerator::BackendBase.

19.7.2.24 genMSBuildImportTarget()

Implements CodeGenerator::BackendBase.

19.7.2.25 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items#item-definitions for more information.

Implements CodeGenerator::BackendBase.

19.7.2.26 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

19.7.2.27 genPopulationRNG()

Generate an RNG with a state per population member.

Implements CodeGenerator::BackendBase.

19.7.2.28 genPopVariableInit()

Implements CodeGenerator::BackendBase.

19.7.2.29 genReturnFreeDeviceMemoryBytes()

Generate code to return amount of free 'device' memory in bytes.

 $Implements\ Code Generator :: Backend Base.$

19.7.2.30 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

19.7.2.31 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

19.7.2.32 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumProceduralConnectHandler	callback to write platform-indepent code to procedurally generate connectivity "id_pre" variable and "addSynapse" function will be provided to callback via Substitutions. callback needs to implement loop over synapses in row, providing "synAddress" variable if INDIVIDUALG
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes. "id_pre", "id_post" and "id_syn" variables will be provided to callback via Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implements CodeGenerator::BackendBase.

```
19.7.2.33 genSynapseVariableRowInit()
```

Implements CodeGenerator::BackendBase.

19.7.2.34 genTimer()

Implements CodeGenerator::BackendBase.

19.7.2.35 genVariableAllocation()

Implements CodeGenerator::BackendBase.

19.7.2.36 genVariableDefinition()

 $Implements\ Code Generator :: Backend Base.$

19.7.2.37 genVariableFree()

```
VarLocation loc ) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

19.7.2.38 genVariableImplementation()

Implements CodeGenerator::BackendBase.

19.7.2.39 genVariableInit()

Implements CodeGenerator::BackendBase.

19.7.2.40 genVariablePull()

Generate code for pulling a variable from the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.41 genVariablePush()

Generate code for pushing a variable to the 'device'.

Implements CodeGenerator::BackendBase.

19.7.2.42 getChosenCUDADevice()

```
const cudaDeviceProp& CodeGenerator::CUDA::Backend::getChosenCUDADevice ( ) const [inline]
```

```
19.7.2.43 getChosenDeviceID()
int CodeGenerator::CUDA::Backend::getChosenDeviceID ( ) const [inline]
19.7.2.44 getDeviceMemoryBytes()
virtual size_t CodeGenerator::CUDA::Backend::getDeviceMemoryBytes ( ) const [inline], [override],
[virtual]
How many bytes of memory does 'device' have.
Implements CodeGenerator::BackendBase.
19.7.2.45 getFloatAtomicAdd()
std::string CodeGenerator::CUDA::Backend::getFloatAtomicAdd (
              const std::string & ftype ) const
19.7.2.46 getKernelBlockSize()
size_t CodeGenerator::CUDA::Backend::getKernelBlockSize (
              Kernel kernel ) const [inline]
19.7.2.47 getNumInitialisationRNGStreams()
size_t CodeGenerator::CUDA::Backend::getNumInitialisationRNGStreams (
              const ModelSpecInternal & model ) const
Get total number of RNG streams potentially used to initialise model.
NOTE because RNG supports 2<sup>6</sup>4 streams, we are overly conservative
19.7.2.48 getNumPostsynapticUpdateThreads()
size_t CodeGenerator::CUDA::Backend::getNumPostsynapticUpdateThreads (
             const SynapseGroupInternal & sg ) [static]
19.7.2.49 getNumPresynapticUpdateThreads()
size_t CodeGenerator::CUDA::Backend::getNumPresynapticUpdateThreads (
             const SynapseGroupInternal & sg,
             const cudaDeviceProp & deviceProps,
              const Preferences & preferences ) [static]
19.7.2.50 getNumSynapseDynamicsThreads()
```

19.7.2.51 getNVCCFlags()

```
std::string CodeGenerator::CUDA::Backend::getNVCCFlags ( ) const
```

19.7.2.52 getRuntimeVersion()

```
int CodeGenerator::CUDA::Backend::getRuntimeVersion ( ) const [inline]
```

19.7.2.53 getSynapticMatrixRowStride()

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implements CodeGenerator::BackendBase.

19.7.2.54 getVarPrefix()

```
virtual std::string CodeGenerator::CUDA::Backend::getVarPrefix ( ) const [inline], [override],
[virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

19.7.2.55 isAutomaticCopyEnabled()

```
virtual bool CodeGenerator::CUDA::Backend::isAutomaticCopyEnabled ( ) const [inline], [override],
[virtual]
```

Is automatic copy mode enabled in the preferences?

Implements CodeGenerator::BackendBase.

19.7.2.56 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

19.7.2.57 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isPostsynapticRemapRequired ( ) const [inline],
[override], [virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implements CodeGenerator::BackendBase.

19.7.2.58 isSynRemapRequired()

```
virtual bool CodeGenerator::CUDA::Backend::isSynRemapRequired ( ) const [inline], [override],
[virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

Implements CodeGenerator::BackendBase.

19.7.3 Member Data Documentation

19.7.3.1 KernelNames

```
const char * CodeGenerator::CUDA::Backend::KernelNames [static]
```

Initial value:

```
= {
    "updateNeuronsKernel",
    "updatePresynapticKernel",
    "updatePostsynapticKernel",
    "updateSynapseDynamicsKernel",
    "initializeKernel",
    "initializeSparseKernel",
    "preNeuronResetKernel",
    "preSynapseResetKernel"}
```


The documentation for this class was generated from the following files:

- · cuda/backend.h
- cuda/backend.cc

19.8 CodeGenerator::SingleThreadedCPU::Backend Class Reference

```
#include <backend.h>
```

 $Inheritance\ diagram\ for\ CodeGenerator:: Single Threaded CPU:: Backend:$



Public Member Functions

- Backend (int localHostID, const std::string &scalarType, const Preferences &preferences)

Generate platform-specific function to update the state of all neurons.

virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler wumProceduralConnectHandler, SynapseGroupHandler postLearnHandler,
 SynapseGroupHandler synapseDynamicsHandler) const override

Generate platform-specific function to update the state of all synapses.

- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG
 Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse
 GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const override
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

- virtual void genDefinitionsPreamble (CodeStream &os, const ModelSpecInternal &model) const override
 Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file
- virtual void genDefinitionsInternalPreamble (CodeStream &os, const ModelSpecInternal &model) const override

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file

- · virtual void genRunnerPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const override
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const override

After all timestep logic is complete.

- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const override
- · virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const override
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const override
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const override

Generate code for pushing a variable to the 'device'.

• virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const override

Generate code for pulling a variable from the 'device'.

 virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pushing a variable's value in the current timestep to the 'device'.

 virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const override

Generate code for pulling a variable's value in the current timestep from the 'device'.

- virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const override

 Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

 virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const override

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const override Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.
- virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free) const override

Generate a single RNG instance.

Generate an RNG with a state per population member.

- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const override
- · virtual void genReturnFreeDeviceMemoryBytes (CodeStream &os) const override

Generate code to return amount of free 'device' memory in bytes.

virtual void genMakefilePreamble (std::ostream &os) const override

This function can be used to generate a preamble for the GNU makefile used to build.

- · virtual void genMakefileLinkRule (std::ostream &os) const override
- virtual void genMakefileCompileRule (std::ostream &os) const override
- virtual void genMSBuildConfigProperties (std::ostream &os) const override
- virtual void genMSBuildImportProps (std::ostream &os) const override
- virtual void genMSBuildItemDefinitions (std::ostream &os) const override
- · virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const override
- virtual void genMSBuildImportTarget (std::ostream &os) const override
- virtual std::string getVarPrefix () const override
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const override

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

• virtual bool isSynRemapRequired () const override

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const override

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

virtual bool isAutomaticCopyEnabled () const override

Is automatic copy mode enabled in the preferences?

virtual size_t getDeviceMemoryBytes () const override

How many bytes of memory does 'device' have.

Additional Inherited Members

19.8.1 Constructor & Destructor Documentation

19.8.1.1 Backend()

19.8.2 Member Function Documentation

19.8.2.1 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implements CodeGenerator::BackendBase.

19.8.2.2 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.3 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.4 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.5 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.6 genCurrentVariablePull()

```
CodeStream & os,
const NeuronGroupInternal & ng,
const std::string & type,
const std::string & name,
VarLocation loc ) const [override], [virtual]
```

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.7 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.8 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implements CodeGenerator::BackendBase.

19.8.2.9 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implements CodeGenerator::BackendBase.

19.8.2.10 genExtraGlobalParamAllocation()

Implements CodeGenerator::BackendBase.

19.8.2.11 genExtraGlobalParamDefinition()

Implements CodeGenerator::BackendBase.

19.8.2.12 genExtraGlobalParamImplementation()

Implements CodeGenerator::BackendBase.

19.8.2.13 genExtraGlobalParamPull()

Implements CodeGenerator::BackendBase.

19.8.2.14 genExtraGlobalParamPush()

 $Implements\ Code Generator :: Backend Base.$

19.8.2.15 genGlobalRNG()

Generate a single RNG instance.

On single-threaded platforms this can be a standard RNG like M.T. but, on parallel platforms, it is likely to be a counter-based RNG

Implements CodeGenerator::BackendBase.

19.8.2.16 genInit()

Implements CodeGenerator::BackendBase.

19.8.2.17 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implements CodeGenerator::BackendBase.

19.8.2.18 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implements CodeGenerator::BackendBase.

19.8.2.19 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implements CodeGenerator::BackendBase.

19.8.2.20 genMSBuildCompileModule()

Implements CodeGenerator::BackendBase.

19.8.2.21 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties for more information.

Implements CodeGenerator::BackendBase.

19.8.2.22 genMSBuildImportProps()

```
\label{local_code_generator} \begin{tabular}{ll} void CodeGenerator::SingleThreadedCPU::Backend::genMSBuildImportProps ( std::ostream & os ) const [override], [virtual] \end{tabular}
```

Implements CodeGenerator::BackendBase.

19.8.2.23 genMSBuildImportTarget()

Implements CodeGenerator::BackendBase.

19.8.2.24 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

 $\textbf{see} \ \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items\#item-definitions} \\ \textbf{for more information.}$

Implements CodeGenerator::BackendBase.

19.8.2.25 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implements CodeGenerator::BackendBase.

19.8.2.26 genPopulationRNG()

Generate an RNG with a state per population member.

Implements CodeGenerator::BackendBase.

19.8.2.27 genPopVariableInit()

Implements CodeGenerator::BackendBase.

19.8.2.28 genReturnFreeDeviceMemoryBytes()

Generate code to return amount of free 'device' memory in bytes.

Implements CodeGenerator::BackendBase.

19.8.2.29 genRunnerPreamble()

Implements CodeGenerator::BackendBase.

19.8.2.30 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implements CodeGenerator::BackendBase.

19.8.2.31 genSynapseUpdate()

```
SynapseGroupHandler wumThreshHandler,
SynapseGroupHandler wumSimHandler,
SynapseGroupHandler wumEventHandler,
SynapseGroupHandler wumProceduralConnectHandler,
SynapseGroupHandler postLearnHandler,
SynapseGroupHandler synapseDynamicsHandler) const [override], [virtual]
```

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumProceduralConnectHandler	callback to write platform-indepent code to procedurally generate connectivity "id_pre" variable and "addSynapse" function will be provided to callback via Substitutions. callback needs to implement loop over synapses in row, providing "synAddress" variable if INDIVIDUALG
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes. "id_pre", "id_post" and "id_syn" variables will be provided to callback via Substitutions.
synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse dynamics. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.

Implements CodeGenerator::BackendBase.

19.8.2.32 genSynapseVariableRowInit()

Implements CodeGenerator::BackendBase.

19.8.2.33 genTimer()

```
CodeStream & stepTimeFinalise,
            const std::string & name,
            bool updateInStepTime ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.34 genVariableAllocation()
MemAlloc CodeGenerator::SingleThreadedCPU::Backend::genVariableAllocation (
            CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc,
            size_t count ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.35 genVariableDefinition()
CodeStream & definitions,
            CodeStream & definitionsInternal,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.36 genVariableFree()
\verb|void CodeGenerator::SingleThreadedCPU::Backend::genVariableFree | (
            CodeStream & os,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.37 genVariableImplementation()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableImplementation (
            CodeStream & os,
            const std::string & type,
            const std::string & name,
            VarLocation loc ) const [override], [virtual]
Implements CodeGenerator::BackendBase.
19.8.2.38 genVariableInit()
void CodeGenerator::SingleThreadedCPU::Backend::genVariableInit (
            CodeStream & os,
            VarLocation loc,
            size_t count,
```

const std::string & indexVarName,
const Substitutions & kernelSubs,

```
Handler handler ) const [override], [virtual]
```

Implements CodeGenerator::BackendBase.

19.8.2.39 genVariablePull()

Generate code for pulling a variable from the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.40 genVariablePush()

Generate code for pushing a variable to the 'device'.

Implements CodeGenerator::BackendBase.

19.8.2.41 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::SingleThreadedCPU::Backend::getDeviceMemoryBytes ( ) const [inline],
[override], [virtual]
```

How many bytes of memory does 'device' have.

Implements CodeGenerator::BackendBase.

19.8.2.42 getSynapticMatrixRowStride()

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implements CodeGenerator::BackendBase.

19.8.2.43 getVarPrefix()

```
virtual std::string CodeGenerator::SingleThreadedCPU::Backend::getVarPrefix ( ) const [inline],
[override], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

Reimplemented from CodeGenerator::BackendBase.

19.8.2.44 isAutomaticCopyEnabled()

virtual bool CodeGenerator::SingleThreadedCPU::Backend::isAutomaticCopyEnabled () const [inline],
[override], [virtual]

Is automatic copy mode enabled in the preferences?

Implements CodeGenerator::BackendBase.

19.8.2.45 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implements CodeGenerator::BackendBase.

19.8.2.46 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::SingleThreadedCPU::Backend::isPostsynapticRemapRequired ( ) const
[inline], [override], [virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implements CodeGenerator::BackendBase.

19.8.2.47 isSynRemapRequired()

```
virtual bool CodeGenerator::SingleThreadedCPU::Backend::isSynRemapRequired ( ) const [inline],
[override], [virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

Implements CodeGenerator::BackendBase.


The documentation for this class was generated from the following files:

- single threaded cpu/backend.h
- single_threaded_cpu/backend.cc

19.9 CodeGenerator::BackendBase Class Reference

```
#include <backendBase.h>
```

Inheritance diagram for CodeGenerator::BackendBase:



Public Types

- typedef std::function< void(CodeStream &, Substitutions &)> Handler
- template<typename T >
 - using GroupHandler = std::function < void(CodeStream &, const T &, Substitutions &)>
- typedef GroupHandler < NeuronGroupInternal > NeuronGroupHandler
 - Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron-Group to.
- typedef GroupHandler < SynapseGroupInternal > SynapseGroupHandler
 - Standard callback type which provides a CodeStream to write platform-independent code for the specified Synapse-Group to.
- typedef std::function< void(CodeStream &, const NeuronGroupInternal &, Substitutions &, NeuronGroup

 Handler, NeuronGroupHandler)> NeuronGroupSimHandler
 - Callback function type for generation neuron group simulation code.

Public Member Functions

- BackendBase (int localHostID, const std::string &scalarType)
- virtual ∼BackendBase ()
- virtual void genNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, NeuronGroupSim
 Handler simHandler, NeuronGroupHandler wuVarUpdateHandler) const =0
 - Generate platform-specific function to update the state of all neurons.
- virtual void genSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, SynapseGroup
 Handler wumThreshHandler, SynapseGroupHandler wumSimHandler, SynapseGroupHandler wumEvent
 Handler, SynapseGroupHandler wumProceduralConnectHandler, SynapseGroupHandler postLearnHandler,
 SynapseGroupHandler synapseDynamicsHandler) const =0
 - Generate platform-specific function to update the state of all synapses.
- virtual void genInit (CodeStream &os, const ModelSpecInternal &model, NeuronGroupHandler localNG
 Handler, NeuronGroupHandler remoteNGHandler, SynapseGroupHandler sgDenseInitHandler, Synapse
 GroupHandler sgSparseConnectHandler, SynapseGroupHandler sgSparseInitHandler) const =0
- virtual size t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const =0
 - Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.
- virtual void genDefinitionsPreamble (CodeStream &os, const ModelSpecInternal &model) const =0
 - Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.
- virtual void genDefinitionsInternalPreamble (CodeStream &os, const ModelSpecInternal &model) const =0

 Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this
- virtual void genRunnerPreamble (CodeStream &os, const ModelSpecInternal &model) const =0
- virtual void genAllocateMemPreamble (CodeStream &os, const ModelSpecInternal &model) const =0
- virtual void genStepTimeFinalisePreamble (CodeStream &os, const ModelSpecInternal &model) const =0

 After all timestep logic is complete.
- virtual void genVariableImplementation (CodeStream &os, const std::string &type, const std::string &name,
 VarLocation loc) const =0
- virtual MemAlloc genVariableAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size_t count) const =0
- virtual void genVariableFree (CodeStream &os, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamDefinition (CodeStream &definitions, const std::string &type, const std
 ::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamImplementation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamAllocation (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0

- virtual void genExtraGlobalParamPush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genExtraGlobalParamPull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc) const =0
- virtual void genPopVariableInit (CodeStream &os, VarLocation loc, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariableInit (CodeStream &os, VarLocation loc, size_t count, const std::string &indexVarName, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genSynapseVariableRowInit (CodeStream &os, VarLocation loc, const SynapseGroupInternal &sg, const Substitutions &kernelSubs, Handler handler) const =0
- virtual void genVariablePush (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const =0

Generate code for pushing a variable to the 'device'.

• virtual void genVariablePull (CodeStream &os, const std::string &type, const std::string &name, VarLocation loc, size t count) const =0

Generate code for pulling a variable from the 'device'.

 virtual void genCurrentVariablePush (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const =0

Generate code for pushing a variable's value in the current timestep to the 'device'.

virtual void genCurrentVariablePull (CodeStream &os, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const =0

Generate code for pulling a variable's value in the current timestep from the 'device'.

virtual void genCurrentTrueSpikePush (CodeStream &os, const NeuronGroupInternal &ng) const =0

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

virtual void genCurrentTrueSpikePull (CodeStream &os, const NeuronGroupInternal &ng) const =0

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

- virtual void genCurrentSpikeLikeEventPush (CodeStream &os, const NeuronGroupInternal &ng) const =0
 Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.
- virtual void genCurrentSpikeLikeEventPull (CodeStream &os, const NeuronGroupInternal &ng) const =0

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

virtual MemAlloc genGlobalRNG (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free) const =0

Generate a single RNG instance.

Generate an RNG with a state per population member.

- virtual void genTimer (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, CodeStream &stepTimeFinalise, const std::string &name, bool updateInStepTime) const =0
- virtual void genReturnFreeDeviceMemoryBytes (CodeStream &os) const =0

Generate code to return amount of free 'device' memory in bytes.

virtual void genMakefilePreamble (std::ostream &os) const =0

This function can be used to generate a preamble for the GNU makefile used to build.

- virtual void genMakefileLinkRule (std::ostream &os) const =0
- virtual void genMakefileCompileRule (std::ostream &os) const =0
- virtual void genMSBuildConfigProperties (std::ostream &os) const =0
- virtual void genMSBuildImportProps (std::ostream &os) const =0
- virtual void genMSBuildItemDefinitions (std::ostream &os) const =0
- virtual void genMSBuildCompileModule (const std::string &moduleName, std::ostream &os) const =0
- virtual void genMSBuildImportTarget (std::ostream &os) const =0
- virtual std::string getVarPrefix () const
- virtual bool isGlobalRNGRequired (const ModelSpecInternal &model) const =0

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

virtual bool isSynRemapRequired () const =0

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

virtual bool isPostsynapticRemapRequired () const =0

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

virtual bool isAutomaticCopyEnabled () const =0

Is automatic copy mode enabled in the preferences?

virtual size_t getDeviceMemoryBytes () const =0

How many bytes of memory does 'device' have.

void genVariablePushPull (CodeStream &push, CodeStream &pull, const std::string &type, const std::string &name, VarLocation loc, bool autoInitialized, size_t count) const

Helper function to generate matching push and pull functions for a variable.

 void genCurrentVariablePushPull (CodeStream &push, CodeStream &pull, const NeuronGroupInternal &ng, const std::string &type, const std::string &name, VarLocation loc) const

Helper function to generate matching push and pull functions for the current state of a variable.

 MemAlloc genArray (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, CodeStream &allocations, CodeStream &free, const std::string &type, const std::string &name, VarLocation loc, size_t count) const

Helper function to generate matching definition, declaration, allocation and free code for an array.

• void genScalar (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const std::string &type, const std::string &name, VarLocation loc) const

Helper function to generate matching definition and declaration code for a scalar variable.

int getLocalHostID () const

Gets ID of local host backend is building code for.

Protected Member Functions

- void addType (const std::string &type, size t size)
- size t getSize (const std::string &type) const

19.9.1 Member Typedef Documentation

19.9.1.1 GroupHandler

```
template<typename T >
using CodeGenerator::BackendBase::GroupHandler = std::function <void(CodeStream &, const T &,
Substitutions&) >
```

19.9.1.2 Handler

typedef std::function<void(CodeStream &, Substitutions&)> CodeGenerator::BackendBase::Handler

19.9.1.3 NeuronGroupHandler

typedef GroupHandler<NeuronGroupInternal> CodeGenerator::BackendBase::NeuronGroupHandler

Standard callback type which provides a CodeStream to write platform-independent code for the specified Neuron← Group to.

19.9.1.4 NeuronGroupSimHandler

typedef std::function<void(CodeStream &, const NeuronGroupInternal &, Substitutions&, Neuron↔ GroupHandler, NeuronGroupHandler)> CodeGenerator::BackendBase::NeuronGroupSimHandler

Callback function type for generation neuron group simulation code.

Provides additional callbacks to insert code to emit spikes

19.9.1.5 SynapseGroupHandler

```
typedef GroupHandler<SynapseGroupInternal> CodeGenerator::BackendBase::SynapseGroupHandler
```

Standard callback type which provides a CodeStream to write platform-independent code for the specified SynapseGroup to.

19.9.2 Constructor & Destructor Documentation

19.9.2.1 BackendBase()

19.9.2.2 \sim BackendBase()

```
virtual CodeGenerator::BackendBase::~BackendBase ( ) [inline], [virtual]
```

19.9.3 Member Function Documentation

19.9.3.1 addType()

19.9.3.2 genAllocateMemPreamble()

Allocate memory is the first function in GeNN generated code called by usercode and it should only ever be called once. Therefore it's a good place for any global initialisation. This function generates a 'preamble' to this function.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.3 genArray()

```
CodeStream & allocations,
CodeStream & free,
const std::string & type,
const std::string & name,
VarLocation loc,
size_t count ) const [inline]
```

Helper function to generate matching definition, declaration, allocation and free code for an array.

19.9.3.4 genCurrentSpikeLikeEventPull()

Generate code for pulling spike-like events emitted by a neuron group in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.5 genCurrentSpikeLikeEventPush()

Generate code for pushing spike-like events emitted by a neuron group in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.6 genCurrentTrueSpikePull()

Generate code for pulling true spikes emitted by a neuron group in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.7 genCurrentTrueSpikePush()

Generate code for pushing true spikes emitted by a neuron group in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.8 genCurrentVariablePull()

Generate code for pulling a variable's value in the current timestep from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.9 genCurrentVariablePush()

Generate code for pushing a variable's value in the current timestep to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.10 genCurrentVariablePushPull()

Helper function to generate matching push and pull functions for the current state of a variable.

19.9.3.11 genDefinitionsInternalPreamble()

Definitions internal is the internal header file for the generated code. This function generates a 'preamble' to this header file.

This will only be included by the platform-specific compiler used to build this backend so can include platform-specific types or headers

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.12 genDefinitionsPreamble()

Definitions is the usercode-facing header file for the generated code. This function generates a 'preamble' to this header file.

This will be included from a standard C++ compiler so shouldn't include any platform-specific types or headers Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.13 genExtraGlobalParamAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.14 genExtraGlobalParamDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.15 genExtraGlobalParamImplementation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.16 genExtraGlobalParamPull()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.17 genExtraGlobalParamPush()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.18 genGlobalRNG()

```
CodeStream & runner,
CodeStream & allocations,
CodeStream & free ) const [pure virtual]
```

Generate a single RNG instance.

On single-threaded platforms this can be a standard RNG like M.T. but, on parallel platforms, it is likely to be a counter-based RNG

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.19 genInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.20 genMakefileCompileRule()

The GNU make build system uses 'pattern rules' (https://www.gnu.org/software/make/manual/html-_node/Pattern-Intro.html) to build backend modules into objects. This function should generate a GNU make pattern rule capable of building each module (i.e. compiling .cc file \$< into .o file \$@).

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.21 genMakefileLinkRule()

The GNU make build system will populate a variable called with a list of objects to link. This function should generate a GNU make rule to build these objects into a shared library.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.22 genMakefilePreamble()

This function can be used to generate a preamble for the GNU makefile used to build.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.23 genMSBuildCompileModule()

```
virtual void CodeGenerator::BackendBase::genMSBuildCompileModule (
```

```
const std::string & moduleName,
std::ostream & os ) const [pure virtual]
```

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.24 genMSBuildConfigProperties()

In MSBuild, 'properties' are used to configure global project settings e.g. whether the MSBuild project builds a static or dynamic library This function can be used to add additional XML properties to this section.

 $\textbf{see} \quad \texttt{https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-properties} \\ \textbf{for more information.}$

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.25 genMSBuildImportProps()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.26 genMSBuildImportTarget()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.27 genMSBuildItemDefinitions()

In MSBuild, the 'item definitions' are used to override the default properties of 'items' such as <ClCompile> or <Link>. This function should generate XML to correctly configure the 'items' required to build the generated code, taking into account etc.

see https://docs.microsoft.com/en-us/visualstudio/msbuild/msbuild-items#item-definitions
for more information.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.28 genNeuronUpdate()

Generate platform-specific function to update the state of all neurons.

Parameters

Parameters

os	CodeStream to write function to
model	model to generate code for
simHandler	callback to write platform-independent code to update an individual NeuronGroup
wuVarUpdateHandler	callback to write platform-independent code to update pre and postsynaptic weight update model variables when neuron spikes

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.29 genPopulationRNG()

Generate an RNG with a state per population member.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.30 genPopVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.31 genReturnFreeDeviceMemoryBytes()

Generate code to return amount of free 'device' memory in bytes.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.32 genRunnerPreamble()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.33 genScalar()

Helper function to generate matching definition and declaration code for a scalar variable.

19.9.3.34 genStepTimeFinalisePreamble()

After all timestep logic is complete.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.35 genSynapseUpdate()

Generate platform-specific function to update the state of all synapses.

Parameters

os	CodeStream to write function to
model	model to generate code for
wumThreshHandler	callback to write platform-independent code to update an individual NeuronGroup
wumSimHandler	callback to write platform-independent code to process presynaptic spikes. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumEventHandler	callback to write platform-independent code to process presynaptic spike-like events. "id_pre", "id_post" and "id_syn" variables; and either "addToInSynDelay" or "addToInSyn" function will be provided to callback via Substitutions.
wumProceduralConnectHandler	callback to write platform-indepent code to procedurally generate connectivity "id_pre" variable and "addSynapse" function will be provided to callback via Substitutions. callback needs to implement loop over synapses in row, providing "synAddress" variable if INDIVIDUALG
postLearnHandler	callback to write platform-independent code to process postsynaptic spikes. "id_pre", "id_post" and "id_syn" variables will be provided to callback via Substitutions.

Parameters

synapseDynamicsHandler	callback to write platform-independent code to update time-driven synapse	
	dynamics. "id_pre", "id_post" and "id_syn" variables; and either	
	"addToInSynDelay" or "addToInSyn" function will be provided to callback via	
	Substitutions.	

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.36 genSynapseVariableRowInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.37 genTimer()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.38 genVariableAllocation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.39 genVariableDefinition()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.40 genVariableFree()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.41 genVariableImplementation()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.42 genVariableInit()

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.43 genVariablePull()

Generate code for pulling a variable from the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.44 genVariablePush()

Generate code for pushing a variable to the 'device'.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.45 genVariablePushPull()

Helper function to generate matching push and pull functions for a variable.

19.9.3.46 getDeviceMemoryBytes()

```
virtual size_t CodeGenerator::BackendBase::getDeviceMemoryBytes ( ) const [pure virtual]
```

How many bytes of memory does 'device' have.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.47 getLocalHostID()

```
int CodeGenerator::BackendBase::getLocalHostID ( ) const [inline]
```

Gets ID of local host backend is building code for.

19.9.3.48 getSize()

19.9.3.49 getSynapticMatrixRowStride()

```
\label{lem:const_synapseGroupInternal & sg ) const [pure virtual]} \\
```

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.50 getVarPrefix()

```
virtual std::string CodeGenerator::BackendBase::getVarPrefix ( ) const [inline], [virtual]
```

When backends require separate 'device' and 'host' versions of variables, they are identified with a prefix. This function returns this prefix so it can be used in otherwise platform-independent code.

 $Reimplemented\ in\ Code Generator :: CUDA :: Backend,\ and\ Code Generator :: Single Threaded CPU :: Backend.$

19.9.3.51 isAutomaticCopyEnabled()

virtual bool CodeGenerator::BackendBase::isAutomaticCopyEnabled () const [pure virtual]

Is automatic copy mode enabled in the preferences?

 $Implemented\ in\ Code Generator :: CUDA :: Backend,\ and\ Code Generator :: Single Threaded CPU :: Backend.$

19.9.3.52 isGlobalRNGRequired()

Different backends use different RNGs for different things. Does this one require a global RNG for the specified model?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.53 isPostsynapticRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isPostsynapticRemapRequired ( ) const [pure virtual]
```

Different backends may implement synaptic plasticity differently. Does this one require a postsynaptic remapping data structure?

Implemented in CodeGenerator::CUDA::Backend, and CodeGenerator::SingleThreadedCPU::Backend.

19.9.3.54 isSynRemapRequired()

```
virtual bool CodeGenerator::BackendBase::isSynRemapRequired ( ) const [pure virtual]
```

Different backends may implement synapse dynamics differently. Does this one require a synapse remapping data structure?

 $Implemented\ in\ Code Generator:: CUDA:: Backend,\ and\ Code Generator:: Single Threaded CPU:: Backend.$

The documentation for this class was generated from the following files:


- · backendBase.h
- backendBase.cc

19.10 CurrentSourceModels::Base Class Reference

Base class for all current source models.

```
#include <currentSourceModels.h>
```

Inheritance diagram for CurrentSourceModels::Base:



virtual std::string getInjectionCode () const
 Gets the code that defines current injected each timestep.

Additional Inherited Members

19.10.1 Detailed Description

Base class for all current source models.

19.10.2 Member Function Documentation

19.10.2.1 getInjectionCode()

virtual std::string CurrentSourceModels::Base::getInjectionCode () const [inline], [virtual]

Gets the code that defines current injected each timestep.

The documentation for this class was generated from the following file:

· currentSourceModels.h

19.11 InitSparseConnectivitySnippet::Base Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::Base:



Public Types

typedef std::function< unsigned int(unsigned int, unsigned int, const std::vector< double > &)> CalcMax←
 LengthFunc

Public Member Functions

- virtual std::string getRowBuildCode () const
- virtual ParamValVec getRowBuildStateVars () const
- virtual CalcMaxLengthFunc getCalcMaxRowLengthFunc () const

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

virtual CalcMaxLengthFunc getCalcMaxColLengthFunc () const

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

- virtual EGPVec getExtraGlobalParams () const
- size_t getExtraGlobalParamIndex (const std::string ¶mName) const

Find the index of a named extra global parameter.

Additional Inherited Members

19.11.1 Member Typedef Documentation

19.11.1.1 CalcMaxLengthFunc

typedef std::function<unsigned int(unsigned int, unsigned int, const std::vector<double> &)>
InitSparseConnectivitySnippet::Base::CalcMaxLengthFunc

19.11.2 Member Function Documentation

19.11.2.1 getCalcMaxColLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxColLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum column length of this connector based on the parameters and the size of the pre and postsynaptic population.

19.11.2.2 getCalcMaxRowLengthFunc()

```
virtual CalcMaxLengthFunc InitSparseConnectivitySnippet::Base::getCalcMaxRowLengthFunc ( )
const [inline], [virtual]
```

Get function to calculate the maximum row length of this connector based on the parameters and the size of the pre and postsynaptic population.

19.11.2.3 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

19.11.2.4 getExtraGlobalParams()

```
virtual EGPVec InitSparseConnectivitySnippet::Base::getExtraGlobalParams ( ) const [inline],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the connection initialisation snippet

19.11.2.5 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::Base::getRowBuildCode ( ) const [inline],
[virtual]
```

 $Reimplemented \ in \ In it Sparse Connectivity Snippet:: Fixed Probability Base.$

19.11.2.6 getRowBuildStateVars()

virtual ParamValVec InitSparseConnectivitySnippet::Base::getRowBuildStateVars () const [inline],
[virtual]


The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

19.12 InitVarSnippet::Base Class Reference

#include <initVarSnippet.h>

Inheritance diagram for InitVarSnippet::Base:



Public Member Functions

• virtual std::string getCode () const

Additional Inherited Members

19.12.1 Member Function Documentation

19.12.1.1 getCode()

```
virtual std::string InitVarSnippet::Base::getCode ( ) const [inline], [virtual]
```

The documentation for this class was generated from the following file:


• initVarSnippet.h

19.13 Models::Base Class Reference

Base class for all models - in addition to the parameters snippets have, models can have state variables.

```
#include <models.h>
```

Inheritance diagram for Models::Base:



Classes

struct Var

A variable has a name, a type and an access type.

Public Types

typedef std::vector< Var > VarVec

Public Member Functions

- · virtual VarVec getVars () const
 - Gets names and types (as strings) of model variables.
- virtual EGPVec getExtraGlobalParams () const
- size_t getVarIndex (const std::string &varName) const

Find the index of a named variable.

• size_t getExtraGlobalParamIndex (const std::string ¶mName) const

Find the index of a named extra global parameter.

Additional Inherited Members

19.13.1 Detailed Description

Base class for all models - in addition to the parameters snippets have, models can have state variables.

19.13.2 Member Typedef Documentation

```
19.13.2.1 VarVec
```

```
typedef std::vector<Var> Models::Base::VarVec
```

19.13.3 Member Function Documentation

19.13.3.1 getExtraGlobalParamIndex()

Find the index of a named extra global parameter.

19.13.3.2 getExtraGlobalParams()

```
virtual EGPVec Models::Base::getExtraGlobalParams ( ) const [inline], [virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented in NeuronModels::Poisson, and NeuronModels::SpikeSourceArray.

19.13.3.3 getVarIndex()

Find the index of a named variable.

19.13.3.4 getVars()

```
virtual VarVec Models::Base::getVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Neuron Models::SpikeSourceArray, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, WeightUpdateModels::StaticGraded, NeuronModels::IzhikevichVariable, WeightUpdateModels::StaticPulseDendriticDelay, Neuron Models::Izhikevich, WeightUpdateModels::StaticPulse, and NeuronModels::RulkovMap.

The documentation for this class was generated from the following file:


· models.h

19.14 NeuronModels::Base Class Reference

Base class for all neuron models.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::Base:



Public Member Functions

- virtual std::string getSimCode () const
 - Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const
 - Gets code which defines the condition for a true spike in the described neuron model.
- virtual std::string getResetCode () const
 - Gets code that defines the reset action taken after a spike occurred. This can be empty.

virtual std::string getSupportCode () const

Gets support code to be made available within the neuron kernel/funcion.

- virtual Models::Base::ParamValVec getAdditionalInputVars () const
- · virtual bool isAutoRefractoryRequired () const

Does this model require auto-refractory logic?

Additional Inherited Members

19.14.1 Detailed Description

Base class for all neuron models.

19.14.2 Member Function Documentation

19.14.2.1 getAdditionalInputVars()

virtual Models::Base::ParamValVec NeuronModels::Base::getAdditionalInputVars () const [inline],
[virtual]

Gets names, types (as strings) and initial values of local variables into which the 'apply input code' of (potentially) multiple postsynaptic input models can apply input

19.14.2.2 getResetCode()

```
virtual std::string NeuronModels::Base::getResetCode ( ) const [inline], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented in NeuronModels::SpikeSourceArray, and NeuronModels::LIF.

19.14.2.3 getSimCode()

```
virtual std::string NeuronModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMilesAlt, NeuronModels::TraubMiles Heart, NeuronModels::Poisson, NeuronModels::Spike SourceArray, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

19.14.2.4 getSupportCode()

```
virtual std::string NeuronModels::Base::getSupportCode ( ) const [inline], [virtual]
```

Gets support code to be made available within the neuron kernel/funcion.

This is intended to contain user defined device functions that are used in the neuron codes. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.14.2.5 getThresholdConditionCode()

virtual std::string NeuronModels::Base::getThresholdConditionCode () const [inline], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented in NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, Neuron Models::SpikeSourceArray, NeuronModels::SpikeSource, NeuronModels::LIF, NeuronModels::Izhikevich, and NeuronModels::RulkovMap.

19.14.2.6 isAutoRefractoryRequired()

```
virtual bool NeuronModels::Base::isAutoRefractoryRequired ( ) const [inline], [virtual]
```

Does this model require auto-refractory logic?

The documentation for this class was generated from the following file:


· neuronModels.h

19.15 Snippet::Base Class Reference

Base class for all code snippets.

#include <snippet.h>

Inheritance diagram for Snippet::Base:



Classes

· struct DerivedParam

A derived parameter has a name and a function for obtaining its value.

• struct EGP

An extra global parameter has a name and a type.

struct ParamVal

Additional input variables, row state variables and other things have a name, a type and an initial value.

Public Types

- typedef std::vector< std::string > StringVec
- typedef std::vector< EGP > EGPVec
- typedef std::vector< ParamVal > ParamValVec
- typedef std::vector< DerivedParam > DerivedParamVec

Public Member Functions

- virtual ~Base ()
- virtual StringVec getParamNames () const

Gets names of of (independent) model parameters.

virtual DerivedParamVec getDerivedParams () const

Static Protected Member Functions

template<typename T >
 static size_t getNamedVecIndex (const std::string &name, const std::vector< T > &vec)

19.15.1 Detailed Description

Base class for all code snippets.

19.15.2 Member Typedef Documentation

19.15.2.1 DerivedParamVec

typedef std::vector<DerivedParam> Snippet::Base::DerivedParamVec

19.15.2.2 EGPVec

typedef std::vector<EGP> Snippet::Base::EGPVec

19.15.2.3 ParamValVec

typedef std::vector<ParamVal> Snippet::Base::ParamValVec

19.15.2.4 StringVec

typedef std::vector<std::string> Snippet::Base::StringVec

19.15.3 Constructor & Destructor Documentation

```
19.15.3.1 ∼Base()
```

virtual Snippet::Base::~Base () [inline], [virtual]

19.15.4 Member Function Documentation

19.15.4.1 getDerivedParams()

```
virtual DerivedParamVec Snippet::Base::getDerivedParams ( ) const [inline], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented in NeuronModels::PoissonNew, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, NeuronModels::RulkovMap, InitSparseConnectivitySnippet::FixedProbabilityBase, PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

19.15.4.2 getNamedVecIndex()

Gets names of of (independent) model parameters.

Reimplemented in NeuronModels::TraubMilesNStep, NeuronModels::TraubMiles, NeuronModels::PoissonNew, NeuronModels::Poisson, WeightUpdateModels::PiecewiseSTDP, NeuronModels::LIF, WeightUpdateModels::CstaticGraded, NeuronModels::IzhikevichVariable, NeuronModels::Izhikevich, InitVarSnippet::Gamma, InitSparseconnectivitySnippet::FixedProbabilityBase, NeuronModels::RulkovMap, InitVarSnippet::Exponential, InitVarCsnippet::Uniform, PostsynapticModels::ExpCond, CurrentSourceModels::GaussianNoise, InitVarSnippet::Constant, CurrentSourceModels::DC, and PostsynapticModels::ExpCurr.

The documentation for this class was generated from the following file:


· snippet.h

19.16 PostsynapticModels::Base Class Reference

Base class for all postsynaptic models.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::Base:



Public Member Functions

- · virtual std::string getDecayCode () const
- virtual std::string getApplyInputCode () const
- virtual std::string getSupportCode () const

Additional Inherited Members

19.16.1 Detailed Description

Base class for all postsynaptic models.

19.16.2 Member Function Documentation

19.16.2.1 getApplyInputCode()

virtual std::string PostsynapticModels::Base::getApplyInputCode () const [inline], [virtual]

Reimplemented in PostsynapticModels::DeltaCurr, PostsynapticModels::ExpCond, and PostsynapticModels::ExpCourr.

19.16.2.2 getDecayCode()

virtual std::string PostsynapticModels::Base::getDecayCode () const [inline], [virtual]

Reimplemented in PostsynapticModels::ExpCond, and PostsynapticModels::ExpCurr.

19.16.2.3 getSupportCode()

virtual std::string PostsynapticModels::Base::getSupportCode () const [inline], [virtual]

The documentation for this class was generated from the following file:

· postsynapticModels.h

19.17 CodeGenerator::CUDA::PresynapticUpdateStrategy::Base Class Reference

#include ynapticUpdateStrategy.h>

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::Base:



Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const =0
 - Get the number of threads that presynaptic updates should be parallelised across.
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const =0

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

• virtual bool isCompatible (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences) const =0

Is this presynaptic update strategy compatible with a given synapse group?

virtual size_t getSharedMemoryPerThread (const SynapseGroupInternal &sg, const Backend &backend)
 const =0

How many neurons does each thread accumulate the outputs of into shared memory.

- virtual void genPreamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const =0
- virtual void genUpdate (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, size_t idStart, Backend
 Base::SynapseGroupHandler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler,
 BackendBase::SynapseGroupHandler wumProceduralConnectHandler) const =0

Generate presynaptic update code.

 virtual void genPostamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const =0

19.17.1 Member Function Documentation

19.17.1.1 genPostamble()

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan.

19.17.1.2 genPreamble()

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan.

19.17.1.3 genUpdate()

Generate presynaptic update code.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan.

19.17.1.4 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUD← A::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan.

19.17.1.5 getSharedMemoryPerThread()

How many neurons does each thread accumulate the outputs of into shared memory.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUD← A::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan.

19.17.1.6 getSynapticMatrixRowStride()

```
 \begin{tabular}{ll} virtual size\_t CodeGenerator::CUDA::PresynapticUpdateStrategy::Base::getSynapticMatrixRow $\end{tabular} \\ Stride ( & const SynapseGroupInternal & sg ) const [pure virtual] \\ \end{tabular}
```

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan.

19.17.1.7 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implemented in CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask, CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan, and CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan.

The documentation for this class was generated from the following file:

· presynapticUpdateStrategy.h

19.18 WeightUpdateModels::Base Class Reference

Base class for all weight update models.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::Base:



virtual std::string getSimCode () const

Gets simulation code run when 'true' spikes are received.

virtual std::string getEventCode () const

Gets code run when events (all the instances where event threshold condition is met) are received.

virtual std::string getLearnPostCode () const

Gets code to include in the learnSynapsesPost kernel/function.

• virtual std::string getSynapseDynamicsCode () const

Gets code for synapse dynamics which are independent of spike detection.

• virtual std::string getEventThresholdConditionCode () const

Gets codes to test for events.

virtual std::string getSimSupportCode () const

Gets support code to be made available within the synapse kernel/function.

virtual std::string getLearnPostSupportCode () const

Gets support code to be made available within learnSynapsesPost kernel/function.

• virtual std::string getSynapseDynamicsSuppportCode () const

Gets support code to be made available within the synapse dynamics kernel/function.

- · virtual std::string getPreSpikeCode () const
- virtual std::string getPostSpikeCode () const
- · virtual VarVec getPreVars () const
- · virtual VarVec getPostVars () const
- virtual bool isPreSpikeTimeRequired () const

Whether presynaptic spike times are needed or not.

• virtual bool isPostSpikeTimeRequired () const

Whether postsynaptic spike times are needed or not.

size_t getPreVarIndex (const std::string &varName) const

Find the index of a named presynaptic variable.

size_t getPostVarIndex (const std::string &varName) const

Find the index of a named postsynaptic variable.

Additional Inherited Members

19.18.1 Detailed Description

Base class for all weight update models.

19.18.2 Member Function Documentation

19.18.2.1 getEventCode()

```
virtual std::string WeightUpdateModels::Base::getEventCode ( ) const [inline], [virtual]
```

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented in WeightUpdateModels::StaticGraded.

19.18.2.2 getEventThresholdConditionCode()

virtual std::string WeightUpdateModels::Base::getEventThresholdConditionCode () const [inline],
[virtual]

Gets codes to test for events.

Reimplemented in WeightUpdateModels::StaticGraded.

19.18.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostCode ( ) const [inline], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

19.18.2.4 getLearnPostSupportCode()

```
virtual std::string WeightUpdateModels::Base::getLearnPostSupportCode ( ) const [inline],
[virtual]
```

Gets support code to be made available within learnSynapsesPost kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.18.2.5 getPostSpikeCode()

```
virtual std::string WeightUpdateModels::Base::getPostSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking postsynaptic neuron before learn post code is run on synapses

This is typically for the code to update postsynaptic variables. Presynaptic and synapse variables are not accesible from within this code

19.18.2.6 getPostVarIndex()

Find the index of a named postsynaptic variable.

19.18.2.7 getPostVars()

```
virtual VarVec WeightUpdateModels::Base::getPostVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses going to the same postsynaptic neuron

19.18.2.8 getPreSpikeCode()

```
virtual std::string WeightUpdateModels::Base::getPreSpikeCode ( ) const [inline], [virtual]
```

Gets code to be run once per spiking presynaptic neuron before sim code is run on synapses

This is typically for the code to update presynaptic variables. Postsynaptic and synapse variables are not accesible from within this code

19.18.2.9 getPreVarIndex()

Find the index of a named presynaptic variable.

19.18.2.10 getPreVars()

```
virtual VarVec WeightUpdateModels::Base::getPreVars ( ) const [inline], [virtual]
```

Gets names and types (as strings) of state variables that are common across all synapses coming from the same presynaptic neuron

19.18.2.11 getSimCode()

```
virtual std::string WeightUpdateModels::Base::getSimCode ( ) const [inline], [virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented in WeightUpdateModels::PiecewiseSTDP, WeightUpdateModels::StaticPulseDendriticDelay, and WeightUpdateModels::StaticPulse.

19.18.2.12 getSimSupportCode()

```
virtual std::string WeightUpdateModels::Base::getSimSupportCode ( ) const [inline], [virtual]
```

Gets support code to be made available within the synapse kernel/function.

This is intended to contain user defined device functions that are used in the weight update code. Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions; note that this support code is available to sim, event threshold and event code

19.18.2.13 getSynapseDynamicsCode()

```
virtual std::string WeightUpdateModels::Base::getSynapseDynamicsCode ( ) const [inline],
[virtual]
```

Gets code for synapse dynamics which are independent of spike detection.

19.18.2.14 getSynapseDynamicsSuppportCode()

```
virtual std::string WeightUpdateModels::Base::getSynapseDynamicsSuppportCode ( ) const [inline],
[virtual]
```

Gets support code to be made available within the synapse dynamics kernel/function.

Preprocessor defines are also allowed if appropriately safeguarded against multiple definition by using ifndef; functions should be declared as "__host__ __device__" to be available for both GPU and CPU versions.

19.18.2.15 isPostSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPostSpikeTimeRequired () const [inline], [virtual]

Whether postsynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.

19.18.2.16 isPreSpikeTimeRequired()

virtual bool WeightUpdateModels::Base::isPreSpikeTimeRequired () const [inline], [virtual]

Whether presynaptic spike times are needed or not.

Reimplemented in WeightUpdateModels::PiecewiseSTDP.


The documentation for this class was generated from the following file:

· weightUpdateModels.h

19.19 SpineMLSimulator::Input::Base Class Reference

#include <input.h>

Inheritance diagram for SpineMLSimulator::Input::Base:



Public Member Functions

- virtual ~Base ()
- virtual void apply (double dt, unsigned long long timestep)=0

Protected Member Functions

- Base (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value)
- bool shouldApply (unsigned long long timestep) const
- void updateValues (double dt, unsigned long long timestep, std::function< void(unsigned int, double)>
 applyValueFunc) const

19.19.1 Constructor & Destructor Documentation

19.19.1.1 ∼Base()

SpineMLSimulator::Input::Base::~Base () [virtual]

19.19.1.2 Base()

19.19.2 Member Function Documentation

19.19.2.1 apply()

Implemented in SpineMLSimulator::Input::Analogue, SpineMLSimulator::Input::SpikeTime, and SpineML Simulator::Input

19.19.2.2 shouldApply()

std::function< void(unsigned int, double) > applyValueFunc) const [protected]

The documentation for this class was generated from the following files:

- input.h
- input.cc

19.20 SpineMLSimulator::InputValue::Base Class Reference

```
#include <inputValue.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Input Value:: Base:$



Public Member Functions

- virtual ~Base ()
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)>
 applyValueFunc)=0

Protected Member Functions

- Base (unsigned int numNeurons, const pugi::xml_node &node)
- const std::vector< unsigned int > & getTargetIndices () const
- unsigned int getNumNeurons () const

19.20.1 Constructor & Destructor Documentation

```
19.20.1.1 \sim Base()
virtual SpineMLSimulator::InputValue::Base::~Base ( ) [inline], [virtual]
19.20.1.2 Base()
SpineMLSimulator::InputValue::Base::Base (
             unsigned int numNeurons,
             const pugi::xml_node & node ) [protected]
19.20.2 Member Function Documentation
19.20.2.1 getNumNeurons()
unsigned int SpineMLSimulator::InputValue::Base::getNumNeurons ( ) const [inline], [protected]
19.20.2.2 getTargetIndices()
const std::vector<unsigned int>& SpineMLSimulator::InputValue::Base::getTargetIndices ( )
const [inline], [protected]
19.20.2.3 update()
virtual void SpineMLSimulator::InputValue::Base::update (
             double dt,
             unsigned long long timestep,
```

std::function< void(unsigned int, double)> applyValueFunc) [pure virtual]

SpineMLSimulator::InputValue::TimeVarying, SpineMLSimulator::InputValue::ConstantArray, and SpineML←

The documentation for this class was generated from the following files:

Implemented in SpineMLSimulator::InputValue::External,

- inputValue.h
- inputValue.cc


19.21 SpineMLSimulator::LogOutput::Base Class Reference

```
#include <logOutput.h>
```

Simulator::InputValue::Constant.

Inheritance diagram for SpineMLSimulator::LogOutput::Base:

SpineMLSimulator::InputValue::TimeVaryingArray,



- Base (const pugi::xml_node &node, double dt)
- virtual ∼Base ()
- virtual void record (double dt, unsigned long long timestep)=0

Protected Member Functions

- bool shouldRecord (unsigned long long timestep) const
- unsigned long long getEndTimestep () const

19.21.1 Constructor & Destructor Documentation

```
19.21.1.1 Base()
```

19.21.1.2 \sim Base()

```
virtual SpineMLSimulator::LogOutput::Base::~Base ( ) [inline], [virtual]
```

19.21.2 Member Function Documentation

19.21.2.1 getEndTimestep()

```
unsigned long long SpineMLSimulator::LogOutput::Base::getEndTimestep ( ) const [inline],
[protected]
```

19.21.2.2 record()

```
virtual void SpineMLSimulator::LogOutput::Base::record ( \label{eq:double} \ dt, \label{eq:double} \ unsigned \ long \ long \ timestep ) \ \ [pure \ virtual]
```

Implemented in SpineMLSimulator::LogOutput::Event, SpineMLSimulator::LogOutput::AnalogueExternal, and SpineMLSimulator::LogOutput::AnalogueFile.

19.21.2.3 shouldRecord()

The documentation for this class was generated from the following files:

- logOutput.h
- · logOutput.cc

19.22 SpineMLSimulator::ModelProperty::Base Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::Base:

```
SpineML Similator: ModelProperty: Base

SpineML Similator: ModelProperty: ExponentialDistribution SpineML Similator: ModelProperty: NormalDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: VisionalDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: VisionalDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: ExponentialDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: NormalDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: ExponentialDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: NormalDistribution SpineML Similator: ModelProperty: ValueList

SpineML Similator: ModelProperty: ModelProperty: NormalDistribution SpineML Similator: ModelProperty: Mo
```

Public Member Functions

- Base (const StateVar< scalar > &stateVar, unsigned int size)
- virtual ∼Base ()
- scalar * getHostStateVar ()
- const scalar * getHostStateVar () const
- void pushToDevice () const
- · void pullFromDevice () const
- unsigned int getSize () const

19.22.1 Constructor & Destructor Documentation

19.22.1.1 Base()

19.22.1.2 \sim Base()

```
virtual SpineMLSimulator::ModelProperty::Base::~Base ( ) [inline], [virtual]
```

19.22.2 Member Function Documentation

```
19.22.2.1 getHostStateVar() [1/2]
```

```
scalar* SpineMLSimulator::ModelProperty::Base::getHostStateVar ( ) [inline]
```

```
19.22.2.2 getHostStateVar() [2/2]
const scalar* SpineMLSimulator::ModelProperty::Base::getHostStateVar ( ) const [inline]
19.22.2.3 getSize()
unsigned int SpineMLSimulator::ModelProperty::Base::getSize () const [inline]
19.22.2.4 pullFromDevice()
void SpineMLSimulator::ModelProperty::Base::pullFromDevice ( ) const [inline]
19.22.2.5 pushToDevice()
void SpineMLSimulator::ModelProperty::Base::pushToDevice ( ) const [inline]
The documentation for this class was generated from the following file:

    modelProperty.h

      CodeGenerator::CodeStream::CB Struct Reference
A close bracket marker.
#include <codeStream.h>
Public Member Functions
   • CB (unsigned int level)
Public Attributes
    · const unsigned int Level
19.23.1 Detailed Description
A close bracket marker.
Write to code stream os using:
os << CB(16);
19.23.2 Constructor & Destructor Documentation
19.23.2.1 CB()
CodeGenerator::CodeStream::CB::CB (
              unsigned int level ) [inline]
```

19.23.3 Member Data Documentation

19.23.3.1 Level

const unsigned int CodeGenerator::CodeStream::CB::Level


The documentation for this struct was generated from the following file:

· codeStream.h

19.24 CodeGenerator::CodeStream Class Reference

#include <codeStream.h>

Inheritance diagram for CodeGenerator::CodeStream:



Classes

- struct CB
 - A close bracket marker.
- struct OB

An open bracket marker.

· class Scope

Public Member Functions

- CodeStream ()
- CodeStream (std::ostream &stream)
- void setSink (std::ostream &stream)

Friends

- GENN EXPORT friend std::ostream & operator << (std::ostream &s, const OB &ob)
- GENN_EXPORT friend std::ostream & operator<< (std::ostream &s, const CB &cb)

19.24.1 Constructor & Destructor Documentation

The documentation for this class was generated from the following file:


· codeStream.h

19.25 InitVarSnippet::Constant Class Reference

Initialises variable to a constant value.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Constant:



- DECLARE_SNIPPET (InitVarSnippet::Constant, 1)
- SET_CODE ("\$(value) = \$(constant);")
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.25.1 Detailed Description

Initialises variable to a constant value.

This snippet takes 1 parameter:

· value - The value to intialise the variable to

Note

This snippet type is seldom used directly - Models::VarInit has an implicit constructor that, internally, creates one of these snippets

19.25.2 Member Function Documentation

19.25.2.1 DECLARE_SNIPPET()

19.25.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Constant::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.25.2.3 SET_CODE()
```

```
InitVarSnippet::Constant::SET_CODE ( )
```


The documentation for this class was generated from the following file:

· initVarSnippet.h

19.26 SpineMLSimulator::InputValue::Constant Class Reference

```
#include <inputValue.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Input Value:: Constant:$



- Constant (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.26.1 Constructor & Destructor Documentation

19.26.1.1 Constant()

19.26.2 Member Function Documentation

19.26.2.1 update()

Implements SpineMLSimulator::InputValue::Base.

The documentation for this class was generated from the following files:

- inputValue.h
- · inputValue.cc

19.27 SpineMLSimulator::InputValue::ConstantArray Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ConstantArray:

```
SpineMLSimulator::InputValue::Base

SpineMLSimulator::InputValue::ConstantArray
```

- ConstantArray (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.27.1 Constructor & Destructor Documentation

19.27.1.1 ConstantArray()

19.27.2 Member Function Documentation

19.27.2.1 update()

Implements SpineMLSimulator::InputValue::Base.


The documentation for this class was generated from the following files:

- inputValue.h
- inputValue.cc

19.28 pygenn.genn_groups.CurrentSource Class Reference

Class representing a current injection into a group of neurons.

Inheritance diagram for pygenn.genn_groups.CurrentSource:



Public Member Functions

```
    def __init__ (self, name)
    Init CurrentSource.
```

def size (self)

Number of neuron in the injected population.

- def size (self, _)
- def set_current_source_model (self, model, param_space, var_space)

Set curront source model, its parameters and initial variables.

def add_to (self, nn_model, pop)

Inject this CurrentSource into population and add it to the GeNN NNmodel.

def add_extra_global_param (self, param_name, param_values)

Set extra global parameter.

def set_extra_global_param (self, param_name, param_values)

Set extra global parameter.

- def load (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise current source.

Public Attributes

- · current_source_model
- · target_pop
- pop

19.28.1 Detailed Description

Class representing a current injection into a group of neurons.

19.28.2 Constructor & Destructor Documentation

Init CurrentSource.

Parameters

name string name of the current source

19.28.3 Member Function Documentation

19.28.3.1 add_extra_global_param()

Set extra global parameter.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.28.3.2 add_to()

```
def pygenn.genn_groups.CurrentSource.add_to ( self, \\ nn\_model, \\ pop )
```

Inject this CurrentSource into population and add it to the GeNN NNmodel.

Parameters

рор	instance of NeuronGroup into which this CurrentSource should be injected
nn_model	GeNN NNmodel

19.28.3.3 load()

```
def pygenn.genn_groups.CurrentSource.load ( self, \\ slm, \\ scalar )
```

19.28.3.4 reinitialise()

Reinitialise current source.

Parameters

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

19.28.3.5 set_current_source_model()

Set curront source model, its parameters and initial variables.

Parameters

model	type as string of intance of the mode	
param_space	dict with model parameters	
var_space	dict with model variables	

19.28.3.6 set_extra_global_param()

```
def pygenn.genn_groups.CurrentSource.set_extra_global_param ( self, \\ param_name, \\ param_values )
```

Set extra global parameter.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.28.3.7 size() [1/2]

```
def pygenn.genn_groups.CurrentSource.size ( self )
```

Number of neuron in the injected population.

```
19.28.3.8 size() [2/2]
```

19.28.4 Member Data Documentation

19.28.4.1 current_source_model

```
\verb|pygenn.genn_groups.CurrentSource.current_source_model|\\
```

19.28.4.2 pop

```
\verb"pygenn.genn_groups.CurrentSource.pop"
```

19.28.4.3 target_pop

```
pygenn.genn_groups.CurrentSource.target_pop
```


The documentation for this class was generated from the following file:

· genn_groups.py

19.29 CurrentSource Class Reference

#include <currentSource.h>

Inheritance diagram for CurrentSource:



Public Member Functions

- CurrentSource (const CurrentSource &)=delete
- CurrentSource ()=delete
- void setVarLocation (const std::string &varName, VarLocation loc)

Set location of current source state variable.

• void setExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of extra global parameter.

- const std::string & getName () const
- const CurrentSourceModels::Base * getCurrentSourceModel () const

Gets the current source model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- VarLocation getVarLocation (const std::string &varName) const

Get variable location for current source model state variable.

VarLocation getVarLocation (size_t index) const

Get variable location for current source model state variable.

VarLocation getExtraGlobalParamLocation (const std::string ¶mName) const

Get location of neuron model extra global parameter by name.

• VarLocation getExtraGlobalParamLocation (size_t index) const

Get location of neuron model extra global parameter by omdex.

Protected Member Functions

- CurrentSource (const std::string &name, const CurrentSourceModels::Base *currentSourceModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation default← VarLocation, VarLocation defaultExtraGlobalParamLocation)
- void initDerivedParams (double dt)
- const std::vector< double > & getDerivedParams () const
- bool isSimRNGRequired () const

Does this current source require an RNG to simulate.

• bool isInitRNGRequired () const

Does this current source group require an RNG for it's init code.

19.29.1 Constructor & Destructor Documentation

```
19.29.1.1 CurrentSource() [1/3]
CurrentSource::CurrentSource (
             const CurrentSource & ) [delete]
19.29.1.2 CurrentSource() [2/3]
CurrentSource::CurrentSource ( ) [delete]
19.29.1.3 CurrentSource() [3/3]
CurrentSource::CurrentSource (
             const std::string & name,
             const CurrentSourceModels::Base * currentSourceModel,
             const std::vector< double > & params,
              const std::vector< Models::VarInit > & varInitialisers,
              VarLocation defaultVarLocation,
              VarLocation defaultExtraGlobalParamLocation ) [inline], [protected]
19.29.2 Member Function Documentation
19.29.2.1 getCurrentSourceModel()
const CurrentSourceModels::Base* CurrentSource::getCurrentSourceModel ( ) const [inline]
Gets the current source model used by this group.
19.29.2.2 getDerivedParams()
const std::vector<double>& CurrentSource::getDerivedParams ( ) const [inline], [protected]
19.29.2.3 getExtraGlobalParamLocation() [1/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
             const std::string & paramName ) const
Get location of neuron model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.29.2.4 getExtraGlobalParamLocation() [2/2]
VarLocation CurrentSource::getExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.29.2.5 getName()
const std::string& CurrentSource::getName ( ) const [inline]
```

```
19.29.2.6 getParams()
const std::vector<double>& CurrentSource::getParams ( ) const [inline]
19.29.2.7 getVarInitialisers()
const std::vector<Models::VarInit>& CurrentSource::getVarInitialisers ( ) const [inline]
19.29.2.8 getVarLocation() [1/2]
VarLocation CurrentSource::getVarLocation (
              const std::string & varName ) const
Get variable location for current source model state variable.
19.29.2.9 getVarLocation() [2/2]
VarLocation CurrentSource::getVarLocation (
              size_t index ) const [inline]
Get variable location for current source model state variable.
19.29.2.10 initDerivedParams()
void CurrentSource::initDerivedParams (
              double dt ) [protected]
19.29.2.11 isInitRNGRequired()
bool CurrentSource::isInitRNGRequired ( ) const [protected]
Does this current source group require an RNG for it's init code.
19.29.2.12 isSimRNGRequired()
bool CurrentSource::isSimRNGRequired ( ) const [protected]
Does this current source require an RNG to simulate.
19.29.2.13 setExtraGlobalParamLocation()
void CurrentSource::setExtraGlobalParamLocation (
              const std::string & paramName,
              VarLocation loc )
Set location of extra global parameter.
This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters
which are pointers.
19.29.2.14 setVarLocation()
```

void CurrentSource::setVarLocation (

```
const std::string & varName,
VarLocation loc )
```

Set location of current source state variable.


The documentation for this class was generated from the following files:

- · currentSource.h
- · currentSource.cc

19.30 CurrentSourceInternal Class Reference

```
#include <currentSourceInternal.h>
```

Inheritance diagram for CurrentSourceInternal:



Public Member Functions

CurrentSourceInternal (const std::string &name, const CurrentSourceModels::Base *currentSourceModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation)

Additional Inherited Members

19.30.1 Constructor & Destructor Documentation

19.30.1.1 CurrentSourceInternal()

The documentation for this class was generated from the following file:


· currentSourceInternal.h

19.31 CurrentSourceModels::DC Class Reference

DC source.

```
#include <currentSourceModels.h>
```

Inheritance diagram for CurrentSourceModels::DC:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- SET_INJECTION_CODE ("\$(injectCurrent, \$(amp));\)
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Static Public Member Functions

• static const DC * getInstance ()

Additional Inherited Members

19.31.1 Detailed Description

DC source.

It has a single parameter:

• amp - amplitude of the current [nA]

19.31.2 Member Typedef Documentation

19.31.2.1 ParamValues

typedef Snippet::ValueBase< 1 > CurrentSourceModels::DC::ParamValues

19.31.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PostVarValues

19.31.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::DC::PreVarValues

19.31.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::DC::VarValues

19.31.3 Member Function Documentation

19.31.3.1 getInstance()

```
static const DC* CurrentSourceModels::DC::getInstance ( ) [inline], [static]
```

19.31.3.2 getParamNames()

```
virtual StringVec CurrentSourceModels::DC::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.31.3.3 SET_INJECTION_CODE()

The documentation for this class was generated from the following file:


• currentSourceModels.h

19.32 PostsynapticModels::DeltaCurr Class Reference

Simple delta current synapse.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::DeltaCurr:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getApplyInputCode () const override

Static Public Member Functions

• static const DeltaCurr * getInstance ()

Additional Inherited Members

19.32.1 Detailed Description

Simple delta current synapse.

Synaptic input provides a direct inject of instantaneous current

19.32.2 Member Typedef Documentation

19.32.2.1 ParamValues

typedef Snippet::ValueBase< 0 > PostsynapticModels::DeltaCurr::ParamValues

19.32.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PostVarValues

19.32.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::DeltaCurr::PreVarValues

19.32.2.4 VarValues

 ${\tt typedef\ Models::} {\tt VarInitContainerBase<\ 0\ >\ PostsynapticModels::} {\tt DeltaCurr::} {\tt VarValues}$

19.32.3 Member Function Documentation

19.32.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::DeltaCurr::getApplyInputCode () const [inline],
[override], [virtual]

Reimplemented from PostsynapticModels::Base.

19.32.3.2 getInstance()

static const DeltaCurr* PostsynapticModels::DeltaCurr::getInstance () [inline], [static]

The documentation for this class was generated from the following file:

· postsynapticModels.h

19.33 Snippet::Base::DerivedParam Struct Reference

A derived parameter has a name and a function for obtaining its value.

```
#include <snippet.h>
```

Public Attributes

- · std::string name
- std::function< double(const std::vector< double > &, double)> func

19.33.1 Detailed Description

A derived parameter has a name and a function for obtaining its value.

19.33.2 Member Data Documentation

19.33.2.1 func

```
std::function<double(const std::vector<double> &, double)> Snippet::Base::DerivedParam::func
```

19.33.2.2 name

```
std::string Snippet::Base::DerivedParam::name
```

The documentation for this struct was generated from the following file:

· snippet.h

19.34 Snippet::Base::EGP Struct Reference

An extra global parameter has a name and a type.

```
#include <snippet.h>
```

Public Attributes

- std::string name
- std::string type

19.34.1 Detailed Description

An extra global parameter has a name and a type.

19.34.2 Member Data Documentation

```
19.34.2.1 name
std::string Snippet::Base::EGP::name
19.34.2.2 type
```

std::string Snippet::Base::EGP::type


The documentation for this struct was generated from the following file:

· snippet.h

19.35 SpineMLSimulator::LogOutput::Event Class Reference

```
#include <logOutput.h>
```

Inheritance diagram for SpineMLSimulator::LogOutput::Event:



Public Member Functions

- Event (const pugi::xml_node &node, double dt, unsigned long long numTimeSteps, const std::string &port, unsigned int popSize, const filesystem::path &logPath, unsigned int *spikeQueuePtr, unsigned int *host← SpikeCount, unsigned int *hostSpikes, void(*pullCurrentSpikesFunc)(void))
- · virtual void record (double dt, unsigned long long timestep) override

Additional Inherited Members

19.35.1 Constructor & Destructor Documentation

19.35.1.1 Event()

19.35.2 Member Function Documentation

19.35.2.1 record()

Implements SpineMLSimulator::LogOutput::Base.

The documentation for this class was generated from the following files:


- logOutput.h
- logOutput.cc

19.36 PostsynapticModels::ExpCond Class Reference

Exponential decay with synaptic input treated as a conductance value.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::ExpCond:



Public Types

- typedef Snippet::ValueBase< 2 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- · virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

static const ExpCond * getInstance ()

Additional Inherited Members

19.36.1 Detailed Description

Exponential decay with synaptic input treated as a conductance value.

This model has no variables and two parameters:

- tau: Decay time constant
- E : Reversal potential

tau is used by the derived parameter expdecay which returns expf(-dt/tau).

19.36.2 Member Typedef Documentation

19.36.2.1 ParamValues

typedef Snippet::ValueBase< 2 > PostsynapticModels::ExpCond::ParamValues

19.36.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCond::PostVarValues

19.36.2.3 PreVarValues

 ${\tt typedef\ Models::} {\tt VarInitContainerBase} < 0 {\tt > PostsynapticModels::ExpCond::} {\tt PreVarValues}$

19.36.2.4 VarValues

 ${\tt typedef\ Models::} {\tt VarInitContainerBase} < \ {\tt 0} \ > {\tt PostsynapticModels::} {\tt ExpCond::} {\tt VarValues}$

19.36.3 Member Function Documentation

19.36.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCond::getApplyInputCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.36.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCond::getDecayCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.36.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCond::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.36.3.4 getInstance()

```
static const ExpCond* PostsynapticModels::ExpCond::getInstance ( ) [inline], [static]
```

19.36.3.5 getParamNames()

```
virtual StringVec PostsynapticModels::ExpCond::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


· postsynapticModels.h

19.37 PostsynapticModels::ExpCurr Class Reference

Exponential decay with synaptic input treated as a current value.

```
#include <postsynapticModels.h>
```

Inheritance diagram for PostsynapticModels::ExpCurr:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getDecayCode () const override
- virtual std::string getApplyInputCode () const override

- virtual StringVec getParamNames () const override
 Gets names of of (independent) model parameters.
- · virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

• static const ExpCurr * getInstance ()

Additional Inherited Members

19.37.1 Detailed Description

Exponential decay with synaptic input treated as a current value.

19.37.2 Member Typedef Documentation

19.37.2.1 ParamValues

typedef Snippet::ValueBase< 1 > PostsynapticModels::ExpCurr::ParamValues

19.37.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PostVarValues

19.37.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> PostsynapticModels::ExpCurr::PreVarValues

19.37.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > PostsynapticModels::ExpCurr::VarValues

19.37.3 Member Function Documentation

19.37.3.1 getApplyInputCode()

virtual std::string PostsynapticModels::ExpCurr::getApplyInputCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.37.3.2 getDecayCode()

virtual std::string PostsynapticModels::ExpCurr::getDecayCode () const [inline], [override],
[virtual]

Reimplemented from PostsynapticModels::Base.

19.37.3.3 getDerivedParams()

```
virtual DerivedParamVec PostsynapticModels::ExpCurr::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.37.3.4 getInstance()

```
static const ExpCurr* PostsynapticModels::ExpCurr::getInstance ( ) [inline], [static]
```

19.37.3.5 getParamNames()

```
virtual StringVec PostsynapticModels::ExpCurr::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

The documentation for this class was generated from the following file:


postsynapticModels.h

19.38 InitVarSnippet::Exponential Class Reference

Initialises variable by sampling from the exponential distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Exponential:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Exponential, 1)
- SET CODE ("\$(value) = \$(lambda) * \$(gennrand exponential);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.38.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

19.38.2 Member Function Documentation

19.38.2.1 DECLARE_SNIPPET()

19.38.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Exponential::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.38.2.3 SET_CODE()
```

```
InitVarSnippet::Exponential::SET_CODE ( )
```


The documentation for this class was generated from the following file:

• initVarSnippet.h

19.39 SpineMLSimulator::ModelProperty::ExponentialDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::ExponentialDistribution:



Public Member Functions

- ExponentialDistribution (const pugi::xml_node &node, const StateVar < scalar > &stateVar, unsigned int size)
- void setValue (scalar lambda)

19.39.1 Constructor & Destructor Documentation

19.39.1.1 ExponentialDistribution()

```
SpineMLSimulator::ModelProperty::ExponentialDistribution::ExponentialDistribution ( const pugi::xml_node & node,
```

```
const StateVar< scalar > & stateVar,
unsigned int size )
```

19.39.2 Member Function Documentation

19.39.2.1 setValue()


The documentation for this class was generated from the following files:

- modelProperty.h
- · modelProperty.cc

19.40 SpineMLSimulator::InputValue::External Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::External:



Public Member Functions

- External (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) final
- std::vector< double >::iterator getBufferBegin ()
- std::vector< double >::iterator getBufferEnd ()

Protected Member Functions

- virtual void updateInternal ()
- unsigned int getSize () const
- std::vector< double > & getBuffer ()

19.40.1 Constructor & Destructor Documentation

19.40.1.1 External()

19.40.2 Member Function Documentation

```
19.40.2.1 getBuffer()
std::vector<double>& SpineMLSimulator::InputValue::External::getBuffer ( ) [inline], [protected]
19.40.2.2 getBufferBegin()
std::vector<double>::iterator SpineMLSimulator::InputValue::External::getBufferBegin ( ) [inline]
19.40.2.3 getBufferEnd()
std::vector<double>::iterator SpineMLSimulator::InputValue::External::getBufferEnd ( ) [inline]
19.40.2.4 getSize()
unsigned int SpineMLSimulator::InputValue::External::getSize ( ) const [inline], [protected]
19.40.2.5 update()
void SpineMLSimulator::InputValue::External::update (
             double dt,
             unsigned long long timestep,
             std::function< void(unsigned int, double)> applyValueFunc ) [final], [virtual]
Implements SpineMLSimulator::InputValue::Base.
19.40.2.6 updateInternal()
virtual void SpineMLSimulator::InputValue::External::updateInternal ( ) [inline], [protected],
Reimplemented in SpineMLSimulator::InputValue::ExternalNetwork.
```


- · inputValue.h
- · inputValue.cc

19.41 SpineMLSimulator::InputValue::ExternalNetwork Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ExternalNetwork:

The documentation for this class was generated from the following files:



Public Member Functions

• ExternalNetwork (double dt, unsigned int numNeurons, const pugi::xml_node &node)

Protected Member Functions

· virtual void updateInternal () override

19.41.1 Constructor & Destructor Documentation

19.41.1.1 ExternalNetwork()

19.41.2 Member Function Documentation

19.41.2.1 updateInternal()

```
void SpineMLSimulator::InputValue::ExternalNetwork::updateInternal ( ) [override], [protected],
[virtual]
```

Reimplemented from SpineMLSimulator::InputValue::External.


The documentation for this class was generated from the following files:

- inputValue.h
- inputValue.cc

19.42 pygenn.model_preprocessor.ExtraGlobalVariable Class Reference

Class holding information about GeNN extra global pointer variable.

 $Inheritance\ diagram\ for\ pygenn.model_preprocessor. Extra Global Variable:$



Public Member Functions

Set Variable's values.

```
    def __init__ (self, variable_name, variable_type, values=None)
        Init Variable.
    def set_values (self, values)
```

Public Attributes

- · is_scalar
- type
- name
- view
- values

19.42.1 Detailed Description

Class holding information about GeNN extra global pointer variable.

19.42.2 Constructor & Destructor Documentation

Init Variable.

Parameters

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable

19.42.3 Member Function Documentation

19.42.3.1 set_values()

Set Variable's values.

Parameters

values iterable or single value)
---------------------------------	---

19.42.4 Member Data Documentation

19.42.4.1 is_scalar

pygenn.model_preprocessor.ExtraGlobalVariable.is_scalar

19.42.4.2 name

 $\verb|pygenn.model_preprocessor.ExtraGlobalVariable.name|\\$

19.42.4.3 type

 $\verb|pygenn.model_preprocessor.ExtraGlobalVariable.type|$

19.42.4.4 values

pygenn.model_preprocessor.ExtraGlobalVariable.values

19.42.4.5 view

pygenn.model_preprocessor.ExtraGlobalVariable.view


The documentation for this class was generated from the following file:

model_preprocessor.py

19.43 SpineMLSimulator::ModelProperty::Fixed Class Reference

#include <modelProperty.h>

Inheritance diagram for SpineMLSimulator::ModelProperty::Fixed:



Public Member Functions

- Fixed (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size)
- Fixed (double value, const StateVar< scalar > &stateVar, unsigned int size)
- void setValue (scalar value)

19.43.1 Constructor & Destructor Documentation

19.43.1.1 Fixed() [1/2]

19.43.2 Member Function Documentation

19.43.2.1 setValue()


The documentation for this class was generated from the following files:

- modelProperty.h
- · modelProperty.cc

19.44 InitSparseConnectivitySnippet::FixedProbability Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbability:



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::FixedProbability, 1)
- SET_ROW_BUILD_CODE ("const scalar u = \$(gennrand_uniform);\ "prevJ+=(1+(int)(log(u) *\$(probLog ← Recip)));\" "if(prevJ < \$(num_post)) {\" " \$(addSynapse, prevJ+\$(id_post_begin));\" "}\" "else {\" " \$(endRow);\" "}\")

Additional Inherited Members

19.44.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

19.44.2 Member Function Documentation

19.44.2.1 DECLARE_SNIPPET()

19.44.2.2 SET_ROW_BUILD_CODE()

```
InitSparseConnectivitySnippet::FixedProbability::SET_ROW_BUILD_CODE ( )
```


The documentation for this class was generated from the following file:

initSparseConnectivitySnippet.h

19.45 InitSparseConnectivitySnippet::FixedProbabilityBase Class Reference

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbabilityBase:



Public Member Functions

- virtual std::string getRowBuildCode () const override=0
- SET_ROW_BUILD_STATE_VARS ({{"prevJ", "int", -1}})
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- virtual DerivedParamVec getDerivedParams () const override
- SET_CALC_MAX_ROW_LENGTH_FUNC ([](unsigned int numPre, unsigned int numPost, const std ::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPre);return binomial ← InverseCDF(quantile, numPost, pars[0]);})

• SET_CALC_MAX_COL_LENGTH_FUNC ([](unsigned int numPre, unsigned int numPost, const std::vector < double > &pars) { const double quantile=pow(0.9999, 1.0/(double) numPost);return binomialInverseC← DF(quantile, numPre, pars[0]);})

Additional Inherited Members

19.45.1 Detailed Description

Base class for snippets which initialise connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons.

19.45.2 Member Function Documentation

19.45.2.1 getDerivedParams()

```
virtual DerivedParamVec InitSparseConnectivitySnippet::FixedProbabilityBase::getDerivedParams
( ) const [inline], [override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.45.2.2 getParamNames()

```
virtual StringVec InitSparseConnectivitySnippet::FixedProbabilityBase::getParamNames ( ) const
[inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.45.2.3 getRowBuildCode()

```
virtual std::string InitSparseConnectivitySnippet::FixedProbabilityBase::getRowBuildCode ( )
const [override], [pure virtual]
```

Reimplemented from InitSparseConnectivitySnippet::Base.

19.45.2.4 SET_CALC_MAX_COL_LENGTH_FUNC()

19.45.2.5 SET_CALC_MAX_ROW_LENGTH_FUNC()

19.45.2.6 SET_ROW_BUILD_STATE_VARS()


The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

19.46 InitSparseConnectivitySnippet::FixedProbabilityNoAutapse Class Reference

#include <initSparseConnectivitySnippet.h>

Inheritance diagram for InitSparseConnectivitySnippet::FixedProbabilityNoAutapse:



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse, 1)
- SET_ROW_BUILD_CODE ("int nextJ;\ "do {\" " const scalar u=\$(gennrand_uniform);\" " nextJ=prevJ+(1+(int)(log(u) *\$(probLogRecip)));\" "} while(nextJ==\$(id_pre));\" "prevJ=nextJ;\" "if(prevJ< \$(num_post)) {\" " \$(add← Synapse, prevJ+\$(id_post_begin));\" "}\" "else {\" " \$(endRow);\" "}\")

Additional Inherited Members

19.46.1 Detailed Description

Initialises connectivity with a fixed probability of a synapse existing between a pair of pre and postsynaptic neurons. This version ensures there are no autapses - connections between neurons with the same id so should be used for recurrent connections.

Whether a synapse exists between a pair of pre and a postsynaptic neurons can be modelled using a Bernoulli distribution. While this COULD br sampling directly by repeatedly drawing from the uniform distribution, this is innefficient. Instead we sample from the gemetric distribution which describes "the probability distribution of the number of Bernoulli trials needed to get one success" – essentially the distribution of the 'gaps' between synapses. We do this using the "inversion method" described by Devroye (1986) – essentially inverting the CDF of the equivalent continuous distribution (in this case the exponential distribution)

19.46.2 Member Function Documentation

19.46.2.1 DECLARE_SNIPPET()

 $\label{limitsparseConnectivitySnippet::FixedProbabilityNoAutapse::SET_ROW_BUILD_CODE \ (\)$

The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

19.47 CodeGenerator::FunctionTemplate Struct Reference

```
#include <codeGenUtils.h>
```

Public Member Functions

• FunctionTemplate operator= (const FunctionTemplate &o)

Public Attributes

• const std::string genericName

Generic name used to refer to function in user code.

const unsigned int numArguments

Number of function arguments.

• const std::string doublePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses double precision.

· const std::string singlePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses single precision.

19.47.1 Detailed Description

Immutable structure for specifying how to implement a generic function e.g. gennrand_uniform

NOTE for the sake of easy initialisation first two parameters of GenericFunction are repeated (C++17 fixes)

19.47.2 Member Function Documentation

19.47.2.1 operator=()

19.47.3 Member Data Documentation

19.47.3.1 doublePrecisionTemplate

const std::string CodeGenerator::FunctionTemplate::doublePrecisionTemplate

The function template (for use with functionSubstitute) used when model uses double precision.

19.47.3.2 genericName

const std::string CodeGenerator::FunctionTemplate::genericName

Generic name used to refer to function in user code.

19.47.3.3 numArguments

const unsigned int CodeGenerator::FunctionTemplate::numArguments

Number of function arguments.

19.47.3.4 singlePrecisionTemplate

 $\verb|const| std::string| CodeGenerator::FunctionTemplate::singlePrecisionTemplate| \\$

The function template (for use with functionSubstitute) used when model uses single precision.

The documentation for this struct was generated from the following file:


· codeGenUtils.h

19.48 InitVarSnippet::Gamma Class Reference

Initialises variable by sampling from the exponential distribution.

#include <initVarSnippet.h>

Inheritance diagram for InitVarSnippet::Gamma:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Gamma, 2)
- SET_CODE ("\$(value) = \$(b) * \$(gennrand_gamma, \$(a));")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.48.1 Detailed Description

Initialises variable by sampling from the exponential distribution.

This snippet takes 1 parameter:

• lambda - mean event rate (events per unit time/distance)

19.48.2 Member Function Documentation

19.48.2.1 DECLARE_SNIPPET()

19.48.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Gamma::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.48.2.3 SET_CODE()

```
InitVarSnippet::Gamma::SET_CODE ( )
```

The documentation for this class was generated from the following file:


• initVarSnippet.h

19.49 CurrentSourceModels::GaussianNoise Class Reference

Noisy current source with noise drawn from normal distribution.

```
#include <currentSourceModels.h>
```

Inheritance diagram for CurrentSourceModels::GaussianNoise:



Public Types

typedef Snippet::ValueBase< 2 > ParamValues

- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- SET_INJECTION_CODE ("\$(injectCurrent, \$(mean) + \$(gennrand_normal) * \$(sd));\)
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Static Public Member Functions

static const GaussianNoise * getInstance ()

Additional Inherited Members

19.49.1 Detailed Description

Noisy current source with noise drawn from normal distribution.

It has 2 parameters:

- mean mean of the normal distribution [nA]
- sd standard deviation of the normal distribution [nA]

19.49.2 Member Typedef Documentation

19.49.2.1 ParamValues

 ${\tt typedef~Snippet::ValueBase<~2~>~CurrentSourceModels::GaussianNoise::ParamValues}$

19.49.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PostVarValues

19.49.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> CurrentSourceModels::GaussianNoise::PreVarValues

19.49.2.4 VarValues

typedef Models::VarInitContainerBase< 0 > CurrentSourceModels::GaussianNoise::VarValues

19.49.3 Member Function Documentation

19.49.3.1 getInstance()

```
static const GaussianNoise* CurrentSourceModels::GaussianNoise::getInstance ( ) [inline],
[static]
```

19.49.3.2 getParamNames()

```
virtual StringVec CurrentSourceModels::GaussianNoise::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.49.3.3 SET_INJECTION_CODE()

The documentation for this class was generated from the following file:

currentSourceModels.h

19.50 GenerateRunBase Class Reference

```
#include <generateRun.h>
```

Public Member Functions

- GenerateRunBase (const std::string &projectName)
- virtual void writeSizes (std::ofstream &sizes) const
- int getExitCode (const CLI::ParseError &e)
- void parseCommandLine (int argc, char **argv)
- int buildAndRun (std::initializer_list< std::string > runParams={}) const

Protected Member Functions

- virtual int runTools () const
- CLI::App & getApp ()
- std::string getOutDir () const
- const std::string & getExperimentName () const

19.50.1 Constructor & Destructor Documentation

19.50.1.1 GenerateRunBase()

19.50.2 Member Function Documentation

```
19.50.2.1 buildAndRun()
int GenerateRunBase::buildAndRun (
             std::initializer_list< std::string > runParams = {} ) const [inline]
19.50.2.2 getApp()
CLI::App& GenerateRunBase::getApp ( ) [inline], [protected]
19.50.2.3 getExitCode()
int GenerateRunBase::getExitCode (
            const CLI::ParseError & e ) [inline]
19.50.2.4 getExperimentName()
const std::string& GenerateRunBase::getExperimentName ( ) const [inline], [protected]
19.50.2.5 getOutDir()
std::string GenerateRunBase::getOutDir ( ) const [inline], [protected]
19.50.2.6 parseCommandLine()
void GenerateRunBase::parseCommandLine (
             int argc,
             char ** argv ) [inline]
19.50.2.7 runTools()
virtual int GenerateRunBase::runTools () const [inline], [protected], [virtual]
19.50.2.8 writeSizes()
virtual void GenerateRunBase::writeSizes (
             std::ofstream & sizes ) const [inline], [virtual]
```


The documentation for this class was generated from the following file:

generateRun.h

19.51 pygenn.genn_model.GeNNModel Class Reference

GeNNModel class This class helps to define, build and run a GeNN model from python.

Inheritance diagram for pygenn.genn_model.GeNNModel:



Public Member Functions

def __init__ (self, precision=None, model_name="GeNNModel", backend=None, genn_log_level=genn—wrapper.warning, backend_log_level=genn_wrapper.warning, backend_log_level=genn_wrapper.warning, preference_kwargs)

Init GeNNModel.

- def use_backend (self)
- · def use_backend (self, backend)
- def timing enabled (self)
- · def timing enabled (self, timing)
- · def default var location (self)

Default variable location - defines where state variables are initialised.

- · def default var location (self, location)
- def default sparse connectivity location (location)

Default sparse connectivity mode - where connectivity is initialised.

- def default_sparse_connectivity_location (self, location)
- def model name (self)

Name of the model.

- def model_name (self, model_name)
- def t (self)

Simulation time in ms.

- def t (self, t)
- def timestep (self)

Simulation time step.

- def timestep (self, timestep)
- · def free_device_mem_bytes (self)
- def dT (self)

Step size.

- def dT (self, dt)
- def neuron_update_time (self)
- · def init time (self)
- def presynaptic_update_time (self)
- def postsynaptic_update_time (self)
- def synapse dynamics time (self)
- · def init sparse time (self)
- def add_neuron_population (self, pop_name, num_neurons, neuron, param_space, var_space)

Add a neuron population to the GeNN model.

 def add_synapse_population (self, pop_name, matrix_type, delay_steps, source, target, w_update_model, wu_param_space, wu_var_space, wu_pre_var_space, wu_post_var_space, postsyn_model, ps_param_ space, ps var space, connectivity initialiser=None)

Add a synapse population to the GeNN model.

- def add_current_source (self, cs_name, current_source_model, pop_name, param_space, var_space)
 - Add a current source to the GeNN model.
- def build (self, path_to_model="./")

Finalize and build a GeNN model.

• def load (self)

import the model as shared library and initialize it

• def reinitialise (self)

reinitialise model to its original state without re-loading

- def step_time (self)
- def pull_state_from_device (self, pop_name)

Pull state from the device for a given population.

• def pull_spikes_from_device (self, pop_name)

Pull spikes from the device for a given population.

def pull_current_spikes_from_device (self, pop_name)

Pull spikes from the device for a given population.

• def pull_connectivity_from_device (self, pop_name)

Pull connectivity from the device for a given population.

def pull_var_from_device (self, pop_name, var_name)

Pull variable from the device for a given population.

• def push_state_to_device (self, pop_name)

Push state to the device for a given population.

def push_spikes_to_device (self, pop_name)

Push spikes to the device for a given population.

def push_current_spikes_to_device (self, pop_name)

Push current spikes to the device for a given population.

def push_connectivity_to_device (self, pop_name)

Push connectivity to the device for a given population.

• def push_var_to_device (self, pop_name, var_name)

Push variable to the device for a given population.

• def end (self)

Free memory.

Public Attributes

- · use_backend
- · backend_log_level
- · default_var_location
- · model_name
- neuron populations
- synapse_populations
- current_sources
- dT

19.51.1 Detailed Description

GeNNModel class This class helps to define, build and run a GeNN model from python.

19.51.2 Constructor & Destructor Documentation

19.51.2.1 __init__()

Init GeNNModel.

Parameters

precision	string precision as string ("float", "double" or "long double"). defaults to float.
model_name	string name of the model. Defaults to "GeNNModel".
backend	string specifying name of backend module to use Defaults to None to pick 'best' backend for your system
selected_gpu	integer specifying the id of the gpu in which the simulator wil run; None will select automatically

19.51.3 Member Function Documentation

19.51.3.1 add_current_source()

Add a current source to the GeNN model.

Parameters

cs_name	name of the new current source
current_source_model	type of the CurrentSourceModels class as string or instance of CurrentSourceModels class derived from
	<pre>pygenn.genn_wrapper.CurrentSourceModels.Custom (see also pygenn.genn_model.create_custom_current_source_class)</pre>
pop_name	name of the population into which the current source should be injected
param_space	dict with param values for the CurrentSourceModels class
var_space	dict with initial variable values for the CurrentSourceModels class

19.51.3.2 add_neuron_population()

```
def pygenn.genn_model.GeNNModel.add_neuron_population ( self, \\ pop_name,
```

```
num_neurons,
neuron,
param_space,
var_space )
```

Add a neuron population to the GeNN model.

Parameters

pop_name	name of the new population
num_neurons	number of neurons in the new population
neuron	<pre>type of the NeuronModels class as string or instance of neuron class derived from pygenn.genn_wrapper.NeuronModels.Custom (see also pygenn.genn_model.create_custom_neuron_class)</pre>
param_space	dict with param values for the NeuronModels class
var_space	dict with initial variable values for the NeuronModels class

19.51.3.3 add_synapse_population()

```
{\tt def pygenn.genn\_model.GeNNModel.add\_synapse\_population} \ \ (
               self,
              pop_name,
              matrix_type,
              delay_steps,
              source,
              target,
              w_update_model,
               wu_param_space,
               wu_var_space,
               wu_pre_var_space,
               wu_post_var_space,
              postsyn_model,
              ps_param_space,
              ps_var_space,
               connectivity_initialiser = None )
```

Add a synapse population to the GeNN model.

Parameters

pop_name	name of the new population
matrix_type	type of the matrix as string
delay_steps	delay in number of steps
source	source neuron group
target	target neuron group
w_update_model	type of the WeightUpdateModels class as string or instance of weight update model class derived from pygenn.genn_wrapper.WeightUpdateModels.Custom (see also pygenn.genn_model.create_custom_weight_update_class)
wu_param_space	dict with param values for the WeightUpdateModels class
wu_var_space	dict with initial values for WeightUpdateModels state variables
wu_pre_var_space	dict with initial values for WeightUpdateModels presynaptic variables
wu_post_var_space	dict with initial values for WeightUpdateModels postsynaptic variables

Parameters

postsyn_model	type of the PostsynapticModels class as string or instance of postsynaptic model class derived from pygenn.genn_wrapper.PostsynapticModels.Custom (see also pygenn.genn_model.create_custom_postsynaptic_class)
ps_param_space	dict with param values for the PostsynapticModels class
ps_var_space	dict with initial variable values for the PostsynapticModels class
connectivity_initialiser	InitSparseConnectivitySnippet::Init for connectivity

19.51.3.4 build()

Finalize and build a GeNN model.

Parameters

```
path_to_model path where to place the generated model code. Defaults to the local directory.
```

```
19.51.3.5 default_sparse_connectivity_location() [1/2]
```

```
\label{location} \begin{tabular}{l} $\operatorname{default\_sparse\_connectivity\_location} \end{tabular} \begin{tabular}{l} $\operatorname{location} \end{tabular} \end{tabular}
```

Default sparse connectivity mode - where connectivity is initialised.

```
19.51.3.6 default_sparse_connectivity_location() [2/2]
```

```
def pygenn.genn_model.GeNNModel.default_sparse_connectivity_location ( self, \\ location \ )
```

```
19.51.3.7 default_var_location() [1/2]
```

```
\label{local_default_var_location} \mbox{def pygenn.genn_model.GeNNModel.default\_var_location (} \\ self \mbox{)}
```

Default variable location - defines where state variables are initialised.

```
19.51.3.8 default_var_location() [2/2]
```

```
\label{location} \begin{tabular}{ll} $\operatorname{def pygenn.genn\_model.GeNNModel.default\_var\_location} & \\ & self, \\ & location \end{tabular}
```

```
19.51.3.9 dT() [1/2]
```

```
{\tt def pygenn.genn\_model.GeNNModel.dT} \ (
```

```
self )
Step size.
19.51.3.10 dT() [2/2]
def pygenn.genn_model.GeNNModel.dT (
              self,
              dt )
19.51.3.11 end()
def pygenn.genn_model.GeNNModel.end (
              self )
Free memory.
19.51.3.12 free_device_mem_bytes()
def pygenn.genn_model.GeNNModel.free_device_mem_bytes (
               self )
19.51.3.13 init_sparse_time()
def pygenn.genn_model.GeNNModel.init_sparse_time (
              self )
19.51.3.14 init_time()
def pygenn.genn_model.GeNNModel.init_time (
              self )
19.51.3.15 load()
def pygenn.genn_model.GeNNModel.load (
               self )
import the model as shared library and initialize it
19.51.3.16 model_name() [1/2]
def pygenn.genn_model.GeNNModel.model_name (
               self )
Name of the model.
19.51.3.17 model_name() [2/2]
def pygenn.genn_model.GeNNModel.model_name (
               model_name )
```

```
19.51.3.18 neuron_update_time()
def pygenn.genn_model.GeNNModel.neuron_update_time (
               self )
19.51.3.19 postsynaptic_update_time()
def pygenn.genn_model.GeNNModel.postsynaptic_update_time (
               self )
19.51.3.20 presynaptic_update_time()
def pygenn.genn_model.GeNNModel.presynaptic_update_time (
               self )
19.51.3.21 pull_connectivity_from_device()
def pygenn.genn_model.GeNNModel.pull_connectivity_from_device (
               self,
               pop_name )
Pull connectivity from the device for a given population.
19.51.3.22 pull_current_spikes_from_device()
def pygenn.genn_model.GeNNModel.pull_current_spikes_from_device (
               self,
               pop_name )
Pull spikes from the device for a given population.
19.51.3.23 pull_spikes_from_device()
def pygenn.genn_model.GeNNModel.pull_spikes_from_device (
               self,
               pop_name )
Pull spikes from the device for a given population.
19.51.3.24 pull_state_from_device()
def pygenn.genn_model.GeNNModel.pull_state_from_device (
               self,
               pop_name )
Pull state from the device for a given population.
19.51.3.25 pull_var_from_device()
def pygenn.genn_model.GeNNModel.pull_var_from_device (
```

```
self,
pop_name,
var_name )
```

Pull variable from the device for a given population.

```
19.51.3.26 push_connectivity_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_connectivity_to_device ( self, \\ pop_name \ )
```

Push connectivity to the device for a given population.

```
19.51.3.27 push_current_spikes_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_current_spikes_to_device ( self, \\ pop_name \ )
```

Push current spikes to the device for a given population.

```
19.51.3.28 push_spikes_to_device()
```

Push spikes to the device for a given population.

```
19.51.3.29 push_state_to_device()
```

```
def pygenn.genn_model.GeNNModel.push_state_to_device ( self, \\ pop_name \ )
```

Push state to the device for a given population.

```
19.51.3.30 push_var_to_device()
```

Push variable to the device for a given population.

```
19.51.3.31 reinitialise()
```

```
\label{lem:continuous} \mbox{def pygenn.genn\_model.GeNNModel.reinitialise (} \\ self \mbox{)}
```

reinitialise model to its original state without re-loading

```
19.51.3.32 step_time()
def pygenn.genn_model.GeNNModel.step_time (
               self )
19.51.3.33 synapse_dynamics_time()
def pygenn.genn_model.GeNNModel.synapse_dynamics_time (
              self )
19.51.3.34 t() [1/2]
def pygenn.genn_model.GeNNModel.t (
               self )
Simulation time in ms.
19.51.3.35 t() [2/2]
def pygenn.genn_model.GeNNModel.t (
               self,
               t)
19.51.3.36 timestep() [1/2]
def pygenn.genn_model.GeNNModel.timestep (
               self )
Simulation time step.
19.51.3.37 timestep() [2/2]
def pygenn.genn_model.GeNNModel.timestep (
               self,
               timestep )
19.51.3.38 timing_enabled() [1/2]
{\tt def pygenn.genn\_model.GeNNModel.timing\_enabled} \ \ (
               self )
19.51.3.39 timing_enabled() [2/2]
def pygenn.genn_model.GeNNModel.timing_enabled (
               self,
               timing )
19.51.3.40 use_backend() [1/2]
def pygenn.genn_model.GeNNModel.use_backend (
```

```
self )
19.51.3.41 use_backend() [2/2]
def pygenn.genn_model.GeNNModel.use_backend (
               self.
               backend )
19.51.4 Member Data Documentation
19.51.4.1 backend_log_level
pygenn.genn_model.GeNNModel.backend_log_level
19.51.4.2 current_sources
pygenn.genn_model.GeNNModel.current_sources
19.51.4.3 default_var_location
pygenn.genn_model.GeNNModel.default_var_location
19.51.4.4 dT
\verb"pygenn.genn_model.GeNNModel.dT"
19.51.4.5 model_name
pygenn.genn_model.GeNNModel.model_name
19.51.4.6 neuron_populations
pygenn.genn_model.GeNNModel.neuron_populations
19.51.4.7 synapse_populations
pygenn.genn_model.GeNNModel.synapse_populations
```

19.51.4.8 use_backend

pygenn.genn_model.GeNNModel.use_backend


The documentation for this class was generated from the following file:

genn_model.py

19.52 pygenn.genn_groups.Group Class Reference

 $Parent\ class\ of\ NeuronGroup,\ SynapseGroup\ and\ CurrentSource.$

Inheritance diagram for pygenn.genn_groups.Group:



Public Member Functions

- def __init__ (self, name)
 Init Group.
- def set_var (self, var_name, values)
 Set values for a Variable.

Public Attributes

- name
- vars
- extra_global_params

19.52.1 Detailed Description

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

19.52.2 Constructor & Destructor Documentation

Init Group.

Parameters

name string name of the Group

19.52.3 Member Function Documentation

19.52.3.1 set_var()

Set values for a Variable.

Parameters

var_name	string with the name of the variable
values	iterable or a single value

19.52.4 Member Data Documentation

19.52.4.1 extra_global_params

```
pygenn.genn_groups.Group.extra_global_params
```

19.52.4.2 name

pygenn.genn_groups.Group.name

19.52.4.3 vars

pygenn.genn_groups.Group.vars


The documentation for this class was generated from the following file:

• genn_groups.py

19.53 InitSparseConnectivitySnippet::Init Class Reference

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::Init:



Public Member Functions

Init (const Base *snippet, const std::vector< double > ¶ms)

19.53.1 Constructor & Destructor Documentation

19.53.1.1 Init()

The documentation for this class was generated from the following file:

· initSparseConnectivitySnippet.h

19.54 Snippet::Init < SnippetBase > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

- Init (const SnippetBase *snippet, const std::vector< double > ¶ms)
- const SnippetBase * getSnippet () const
- const std::vector< double > & getParams () const
- const std::vector< double > & getDerivedParams () const
- void initDerivedParams (double dt)

19.54.1 Detailed Description

```
template<typename SnippetBase> class Snippet::Init< SnippetBase>
```

Class used to bind together everything required to utilize a snippet

- 1. A pointer to a variable initialisation snippet
- 2. The parameters required to control the variable initialisation snippet

19.54.2 Constructor & Destructor Documentation

19.54.2.1 Init()

19.54.3 Member Function Documentation

19.54.3.1 getDerivedParams()

```
template<typename SnippetBase>
const std::vector<double>& Snippet::Init< SnippetBase >::getDerivedParams ( ) const [inline]
```

19.54.3.2 getParams()


The documentation for this class was generated from the following file:

· snippet.h

19.55 SpineMLSimulator::Input::InterSpikeIntervalBase Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::InterSpikeIntervalBase:



Public Member Functions

virtual void apply (double dt, unsigned long long timestep) override

Protected Member Functions

- InterSpikeIntervalBase (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)
- virtual double getTimeToSpike (double isiMs)=0

Additional Inherited Members

19.55.1 Constructor & Destructor Documentation

19.55.1.1 InterSpikeIntervalBase()

19.55.2 Member Function Documentation

19.55.2.1 apply()

```
void SpineMLSimulator::Input::InterSpikeIntervalBase::apply ( \label{eq:condition} \mbox{double $dt$,} \mbox{unsigned long long $timestep$ ) [override], [virtual]}
```

Implements SpineMLSimulator::Input::Base.

19.55.2.2 getTimeToSpike()

```
\label{lem:continuous} \begin{tabular}{ll} virtual double SpineMLSimulator::Input::InterSpikeIntervalBase::getTimeToSpike ( \\ double $isiMs$ ) [protected], [pure virtual] \end{tabular}
```

Implemented in SpineMLSimulator::Input::PoissonSpikeRate, and SpineMLSimulator::Input::RegularSpikeRate.

The documentation for this class was generated from the following files:


- input.h
- input.cc

19.56 NeuronModels::Izhikevich Class Reference

Izhikevich neuron with fixed parameters [1].

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Izhikevich:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

· virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

• virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

Static Public Member Functions

static const NeuronModels::Izhikevich * getInstance ()

Additional Inherited Members

19.56.1 Detailed Description

Izhikevich neuron with fixed parameters [1].

It is usually described as

$$\begin{array}{lcl} \frac{dV}{dt} & = & 0.04V^2 + 5V + 140 - U + I, \\ \frac{dU}{dt} & = & a(bV - U), \end{array}$$

I is an external input current and the voltage V is reset to parameter c and U incremented by parameter d, whenever V >= 30 mV. This is paired with a particular integration procedure of two 0.5 ms Euler time steps for the V equation followed by one 1 ms time step of the U equation. Because of its popularity we provide this model in this form here event though due to the details of the usual implementation it is strictly speaking inconsistent with the displayed equations.

Variables are:

- ∨ Membrane potential
- U Membrane recovery variable

Parameters are:

- · a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

19.56.2 Member Typedef Documentation

```
19.56.2.1 ParamValues
typedef Snippet::ValueBase< 4 > NeuronModels::Izhikevich::ParamValues
19.56.2.2 PostVarValues
typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PostVarValues
19.56.2.3 PreVarValues
typedef Models::VarInitContainerBase<0> NeuronModels::Izhikevich::PreVarValues
19.56.2.4 VarValues
typedef Models::VarInitContainerBase< 2 > NeuronModels::Izhikevich::VarValues
19.56.3 Member Function Documentation
19.56.3.1 getInstance()
static const NeuronModels::Izhikevich* NeuronModels::Izhikevich::getInstance ( ) [inline],
[static]
19.56.3.2 getParamNames()
virtual StringVec NeuronModels::Izhikevich::getParamNames ( ) const [inline], [override],
[virtual]
Gets names of of (independent) model parameters.
Reimplemented from Snippet::Base.
Reimplemented in NeuronModels::IzhikevichVariable.
19.56.3.3 getSimCode()
```

3.....

virtual std::string NeuronModels::Izhikevich::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.56.3.4 getThresholdConditionCode()

virtual std::string NeuronModels::Izhikevich::getThresholdConditionCode () const [inline],
[override], [virtual]

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.56.3.5 getVars()

virtual VarVec NeuronModels::Izhikevich::getVars () const [inline], [override], [virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

Reimplemented in NeuronModels::IzhikevichVariable.

The documentation for this class was generated from the following file:


neuronModels.h

19.57 NeuronModels::IzhikevichVariable Class Reference

Izhikevich neuron with variable parameters [1].

#include <neuronModels.h>

Inheritance diagram for NeuronModels::IzhikevichVariable:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 6 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- $\hbox{ typedef Models::} VarInitContainerBase < 0 > PostVarValues \\$

Public Member Functions

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

Static Public Member Functions

• static const NeuronModels::IzhikevichVariable * getInstance ()

Additional Inherited Members

19.57.1 Detailed Description

Izhikevich neuron with variable parameters [1].

This is the same model as Izhikevich but parameters are defined as "variables" in order to allow users to provide individual values for each individual neuron instead of fixed values for all neurons across the population.

Accordingly, the model has the Variables:

- ∨ Membrane potential
- U Membrane recovery variable
- · a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

and no parameters.

19.57.2 Member Typedef Documentation

```
19.57.2.1 ParamValues
```

typedef Snippet::ValueBase< 0 > NeuronModels::IzhikevichVariable::ParamValues

19.57.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::IzhikevichVariable::PostVarValues

19.57.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::IzhikevichVariable::PreVarValues

19.57.2.4 VarValues

typedef Models::VarInitContainerBase< 6 > NeuronModels::IzhikevichVariable::VarValues

19.57.3 Member Function Documentation

19.57.3.1 getInstance()

```
static const NeuronModels::IzhikevichVariable* NeuronModels::IzhikevichVariable::getInstance (
) [inline], [static]
```

19.57.3.2 getParamNames()

virtual StringVec NeuronModels::IzhikevichVariable::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::Izhikevich.

19.57.3.3 getVars()

```
virtual VarVec NeuronModels::IzhikevichVariable::getVars ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from NeuronModels::Izhikevich.


The documentation for this class was generated from the following file:

neuronModels.h

19.58 NeuronModels::LIF Class Reference

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::LIF:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

• virtual std::string getResetCode () const override

Gets code that defines the reset action taken after a spike occurred. This can be empty.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

- · virtual DerivedParamVec getDerivedParams () const override
- virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

static const LIF * getInstance ()

Additional Inherited Members

19.58.1 Member Typedef Documentation

19.58.1.1 ParamValues

```
typedef Snippet::ValueBase< 7 > NeuronModels::LIF::ParamValues
```

19.58.1.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PostVarValues
```

19.58.1.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::LIF::PreVarValues
```

19.58.1.4 VarValues

```
typedef Models::VarInitContainerBase< 2 > NeuronModels::LIF::VarValues
```

19.58.2 Member Function Documentation

19.58.2.1 getDerivedParams()

```
virtual DerivedParamVec NeuronModels::LIF::getDerivedParams ( ) const [inline], [override],
[virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

```
19.58.2.2 getInstance()
```

```
static const LIF* NeuronModels::LIF::getInstance ( ) [inline], [static]
```

19.58.2.3 getParamNames()

```
virtual StringVec NeuronModels::LIF::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.58.2.4 getResetCode()

```
virtual std::string NeuronModels::LIF::getResetCode ( ) const [inline], [override], [virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

19.58.2.5 getSimCode()

```
virtual std::string NeuronModels::LIF::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.58.2.6 getThresholdConditionCode()

```
virtual std::string NeuronModels::LIF::getThresholdConditionCode ( ) const [inline], [override],
[virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.58.2.7 getVars()

```
virtual VarVec NeuronModels::LIF::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.58.2.8 SET_NEEDS_AUTO_REFRACTORY()

The documentation for this class was generated from the following file:

• neuronModels.h

19.59 CodeGenerator::MemAlloc Class Reference

```
#include <backendBase.h>
```

Public Member Functions

- size_t getHostBytes () const
- size_t getDeviceBytes () const
- size_t getZeroCopyBytes () const
- size_t getHostMBytes () const
- size_t getDeviceMBytes () const
- size_t getZeroCopyMBytes () const
- MemAlloc & operator+= (const MemAlloc &rhs)

Static Public Member Functions

- static MemAlloc zero ()
- static MemAlloc host (size_t hostBytes)
- static MemAlloc device (size t deviceBytes)
- static MemAlloc zeroCopy (size_t zeroCopyBytes)

19.59.1 Member Function Documentation

The documentation for this class was generated from the following file:


· backendBase.h

19.60 ModelSpec Class Reference

Object used for specifying a neuronal network model.

```
#include <modelSpec.h>
```

Inheritance diagram for ModelSpec:



Public Types

- typedef std::map< std::string, NeuronGroupInternal >::value_type NeuronGroupValueType
- typedef std::map< std::string, SynapseGroupInternal >::value_type SynapseGroupValueType

Public Member Functions

- ModelSpec ()
- ModelSpec (const ModelSpec &)=delete
- ModelSpec & operator= (const ModelSpec &)=delete
- ∼ModelSpec ()

void setName (const std::string &name)

Method to set the neuronal network model name.

void setPrecision (FloatType)

Set numerical precision for floating point.

void setTimePrecision (TimePrecision timePrecision)

Set numerical precision for time.

void setDT (double dt)

Set the integration step size of the model.

void setTiming (bool timingEnabled)

Set whether timers and timing commands are to be included.

void setSeed (unsigned int rngSeed)

Set the random seed (disables automatic seeding if argument not 0).

void setDefaultVarLocation (VarLocation loc)

What is the default location for model state variables?

void setDefaultExtraGlobalParamLocation (VarLocation loc)

What is the default location for model extra global parameters?

void setDefaultSparseConnectivityLocation (VarLocation loc)

What is the default location for sparse synaptic connectivity?

void setDefaultNarrowSparseIndEnabled (bool enabled)

Sets default for whether narrow i.e. less than 32-bit types are used for sparse matrix indices.

void setMergePostsynapticModels (bool merge)

Should compatible postsynaptic models and dendritic delay buffers be merged?

const std::string & getName () const

Gets the name of the neuronal network model.

const std::string & getPrecision () const

Gets the floating point numerical precision.

std::string getTimePrecision () const

Gets the floating point numerical precision used to represent time.

double getDT () const

Gets the model integration step size.

• unsigned int getSeed () const

Get the random seed.

bool isTimingEnabled () const

Are timers and timing commands enabled.

• unsigned int getNumLocalNeurons () const

How many neurons are simulated locally in this model.

unsigned int getNumRemoteNeurons () const

How many neurons are simulated remotely in this model.

unsigned int getNumNeurons () const

How many neurons make up the entire model.

NeuronGroup * findNeuronGroup (const std::string &name)

Find a neuron group by name.

template<typename NeuronModel >

NeuronGroup * addNeuronPopulation (const std::string &name, unsigned int size, const NeuronModel *model, const typename NeuronModel::ParamValues ¶mValues, const typename NeuronModel::Var← Values &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a neuron model managed by the user.

template<typename NeuronModel >

NeuronGroup * addNeuronPopulation (const std::string &name, unsigned int size, const typename Neuron ← Model::ParamValues ¶mValues, const typename NeuronModel::VarValues &varInitialisers, int hostID=0)

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

SynapseGroup * findSynapseGroup (const std::string &name)

Find a synapse group by name.

• template<typename WeightUpdateModel, typename PostsynapticModel > SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const WeightUpdateModel *wum, const typename WeightUpdateModel::ParamValues &weightParamValues, const typename WeightUpdate Model::VarValues &weightVarInitialisers, const typename WeightUpdateModel::PreVarValues &weightPostVarInitialisers, const PostsynapticModel *psm, const typename PostsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticVarInitialisers, const InitSparseConnectivity Snippet::Init &connectivityInitialiser=uninitialisedConnectivity())

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const typename WeightUpdateModel::Param Values &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename Postsynaptic Postsynaptic Postsynaptic Nodel::VarValues &postsynaptic Nodel::VarValues &posts

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE MODEL and IMPLEMENT MODEL macros.

• template < typename WeightUpdateModel , typename PostsynapticModel > SynapseGroup * addSynapsePopulation (const std::string &name, SynapseMatrixType mtype, unsigned int delaySteps, const std::string &src, const std::string &trg, const typename WeightUpdateModel::

ParamValues &weightParamValues, const typename WeightUpdateModel::VarValues &weightVarInitialisers, const typename WeightUpdateModel::PreVarValues &weightPreVarInitialisers, const typename WeightUpdateModel::ParamValues &postsynapticModel::ParamValues &postsynapticParamValues, const typename PostsynapticModel::VarValues &postsynapticVarInitialisers, const InitSparseConnectivitySnippet::Init &connectivityInitialiser=uninitialisedConnectivity())

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

• CurrentSource * findCurrentSource (const std::string &name)

Find a current source by name.

 $\bullet \ \ template {<} typename \ Current Source Model >$

CurrentSource * addCurrentSource (const std::string ¤tSourceName, const CurrentSourceModel *model, const std::string &targetNeuronGroupName, const typename CurrentSourceModel::ParamValues ¶mValues, const typename CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a current source model managed by the user.

• template<typename CurrentSourceModel >

CurrentSource * addCurrentSource (const std::string ¤tSourceName, const std::string &target← NeuronGroupName, const typename CurrentSourceModel::ParamValues ¶mValues, const typename CurrentSourceModel::VarValues &varInitialisers)

Adds a new current source to the model using a singleton current source model created using standard DECLARE← _MODEL and IMPLEMENT_MODEL macros.

Protected Member Functions

void finalize ()

Finalise model.

• std::string scalarExpr (double) const

Get the string literal that should be used to represent a value in the model's floating-point type.

bool zeroCopyInUse () const

Are any variables in any populations in this model using zero-copy memory?

const std::map< std::string, NeuronGroupInternal > & getLocalNeuronGroups () const

Get std::map containing local named NeuronGroup objects in model.

- const std::map < std::string, NeuronGroupInternal > & getRemoteNeuronGroups () const Get std::map containing remote named NeuronGroup objects in model.
- const std::map < std::string, SynapseGroupInternal > & getLocalSynapseGroups () const Get std::map containing local named SynapseGroup objects in model.
- const std::map < std::string, SynapseGroupInternal > & getRemoteSynapseGroups () const
 Get std::map containing remote named SynapseGroup objects in model.
- const std::map < std::string, CurrentSourceInternal > & getLocalCurrentSources () const Get std::map containing local named CurrentSource objects in model.
- const std::map < std::string, CurrentSourceInternal > & getRemoteCurrentSources () const
 Get std::map containing remote named CurrentSource objects in model.

19.60.1 Detailed Description

Object used for specifying a neuronal network model.

19.60.2 Member Typedef Documentation

19.60.2.1 NeuronGroupValueType

typedef std::map<std::string, NeuronGroupInternal>::value_type ModelSpec::NeuronGroupValueType

19.60.2.2 SynapseGroupValueType

typedef std::map<std::string, SynapseGroupInternal>::value_type ModelSpec::SynapseGroupValue← Type

19.60.3 Constructor & Destructor Documentation

19.60.4 Member Function Documentation

19.60.4.1 addCurrentSource() [1/2]

Adds a new current source to the model using a current source model managed by the user.

Template Parameters

ſ

Parameters

currentSourceName	string containing unique name of current source.
model	current source model to use for current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in CurrentSource::VarValues object.

Returns

pointer to newly created CurrentSource

19.60.4.2 addCurrentSource() [2/2]

Adds a new current source to the model using a singleton current source model created using standard DECLAR← E_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

CurrentSourceModel	type of neuron model (derived from CurrentSourceModel::Base).
--------------------	---

currentSourceName	string containing unique name of current source.
targetNeuronGroupName	string name of the target neuron group
paramValues	parameters for model wrapped in CurrentSourceModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in CurrentSourceModel::VarValues object.

Returns

pointer to newly created CurrentSource

19.60.4.3 addNeuronPopulation() [1/2]

Adds a new neuron group to the model using a neuron model managed by the user.

Template Parameters

NeuronModel	type of neuron model (derived from NeuronModels::Base).
-------------	---

Parameters

name	string containing unique name of neuron population.
size	integer specifying how many neurons are in the population.
model	neuron model to use for neuron group.
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.
varInitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
hostID	if using MPI, the ID of the node to simulate this population on.

Returns

pointer to newly created NeuronGroup

19.60.4.4 addNeuronPopulation() [2/2]

Adds a new neuron group to the model using a singleton neuron model created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

name	string containing unique name of neuron population.
size	integer specifying how many neurons are in the population.
paramValues	parameters for model wrapped in NeuronModel::ParamValues object.
varlnitialisers	state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
hostID	if using MPI, the ID of the node to simulate this population on.

Returns

pointer to newly created NeuronGroup

19.60.4.5 addSynapsePopulation() [1/3]

```
{\tt template}{<} {\tt typename WeightUpdateModel , typename PostsynapticModel >}
SynapseGroup* ModelSpec::addSynapsePopulation (
                                           const std::string & name,
                                           SynapseMatrixType mtype,
                                           unsigned int delaySteps,
                                            const std::string & src,
                                           const std::string & trg,
                                            const WeightUpdateModel * wum,
                                            const typename WeightUpdateModel::ParamValues & weightParamValues,
                                            const typename WeightUpdateModel::VarValues & weightVarInitialisers,
                                            const typename WeightUpdateModel::PreVarValues & weightPreVarInitialisers,
                                            const typename WeightUpdateModel::PostVarValues & weightPostVarInitialisers,
                                            const PostsynapticModel * psm,
                                            const typename PostsynapticModel::ParamValues & postsynapticParamValues,
                                            const typename PostsynapticModel::VarValues & postsynapticVarInitialisers,
                                            \verb|const InitSparseConnectivitySnippet::Init & connectivityInitialiser = uninitialised \\ \leftarrow \\ |connectivityInitialiser = |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInitialiser = |connectivityInitialiser | \\ |connectivityInit
Connectivity() ) [inline]
```

Adds a synapse population to the model using weight update and postsynaptic models managed by the user.

Template Parameters

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population
wum	weight update model to use for synapse group.
weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.

weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
psm	postsynaptic model to use for synapse group.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK. Typically wrapped with it's parameters using initConnectivity function

Returns

pointer to newly created SynapseGroup

19.60.4.6 addSynapsePopulation() [2/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

WeightUpdateModel		type of weight update model (derived from WeightUpdateModels::Base).	
	PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).	

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population

weightParamValues	parameters for weight update model wrapped in WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model state variable initialiser snippets and parameters wrapped in WeightUpdateModel::VarValues object.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK. Typically wrapped with it's parameters using initConnectivity function

Returns

pointer to newly created SynapseGroup

19.60.4.7 addSynapsePopulation() [3/3]

Adds a synapse population to the model using singleton weight update and postsynaptic models created using standard DECLARE_MODEL and IMPLEMENT_MODEL macros.

Template Parameters

WeightUpdateModel	type of weight update model (derived from WeightUpdateModels::Base).
PostsynapticModel	type of postsynaptic model (derived from PostsynapticModels::Base).

name	string containing unique name of neuron population.
mtype	how the synaptic matrix associated with this synapse population should be represented.
delaySteps	integer specifying number of timesteps delay this synaptic connection should incur (or NO_DELAY for none)
src	string specifying name of presynaptic (source) population
trg	string specifying name of postsynaptic (target) population

weightParamValues	parameters for weight update model wrapped in
	WeightUpdateModel::ParamValues object.
weightVarInitialisers	weight update model per-synapse state variable initialiser snippets and
	parameters wrapped in WeightUpdateModel::VarValues object.
weightPreVarInitialisers	weight update model presynaptic state variable initialiser snippets and parameters
	wrapped in WeightUpdateModel::VarValues object.
weightPostVarInitialisers	weight update model postsynaptic state variable initialiser snippets and
	parameters wrapped in WeightUpdateModel::VarValues object.
postsynapticParamValues	parameters for postsynaptic model wrapped in PostsynapticModel::ParamValues
	object.
postsynapticVarInitialisers	postsynaptic model state variable initialiser snippets and parameters wrapped in
	NeuronModel::VarValues object.
connectivityInitialiser	sparse connectivity initialisation snippet used to initialise connectivity for
	SynapseMatrixConnectivity::SPARSE or SynapseMatrixConnectivity::BITMASK.
	Typically wrapped with it's parameters using initConnectivity function

Returns

pointer to newly created SynapseGroup

```
19.60.4.8 finalize()
```

```
void ModelSpec::finalize ( ) [protected]
```

Finalise model.

19.60.4.9 findCurrentSource()

Find a current source by name.

This function attempts to find an existing current source.

19.60.4.10 findNeuronGroup()

Find a neuron group by name.

19.60.4.11 findSynapseGroup()

Find a synapse group by name.

19.60.4.12 getDT()

```
double ModelSpec::getDT ( ) const [inline]
```

Gets the model integration step size.

19.60.4.13 getLocalCurrentSources()

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getLocalCurrentSources ( )
const [inline], [protected]
```

Get std::map containing local named CurrentSource objects in model.

19.60.4.14 getLocalNeuronGroups()

```
const std::map<std::string, NeuronGroupInternal>& ModelSpec::getLocalNeuronGroups ( ) const
[inline], [protected]
```

Get std::map containing local named NeuronGroup objects in model.

19.60.4.15 getLocalSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getLocalSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing local named SynapseGroup objects in model.

19.60.4.16 getName()

```
const std::string& ModelSpec::getName ( ) const [inline]
```

Gets the name of the neuronal network model.

19.60.4.17 getNumLocalNeurons()

```
unsigned int ModelSpec::getNumLocalNeurons ( ) const
```

How many neurons are simulated locally in this model.

19.60.4.18 getNumNeurons()

```
unsigned int ModelSpec::getNumNeurons ( ) const [inline]
```

How many neurons make up the entire model.

19.60.4.19 getNumRemoteNeurons()

```
unsigned int ModelSpec::getNumRemoteNeurons ( ) const
```

How many neurons are simulated remotely in this model.

19.60.4.20 getPrecision()

```
const std::string& ModelSpec::getPrecision ( ) const [inline]
```

Gets the floating point numerical precision.

```
19.60.4.21 getRemoteCurrentSources()
```

```
const std::map<std::string, CurrentSourceInternal>& ModelSpec::getRemoteCurrentSources ( )
const [inline], [protected]
```

Get std::map containing remote named CurrentSource objects in model.

19.60.4.22 getRemoteNeuronGroups()

```
const std::map<std::string, NeuronGroupInternal>& ModelSpec::getRemoteNeuronGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named NeuronGroup objects in model.

19.60.4.23 getRemoteSynapseGroups()

```
const std::map<std::string, SynapseGroupInternal>& ModelSpec::getRemoteSynapseGroups ( ) const
[inline], [protected]
```

Get std::map containing remote named SynapseGroup objects in model.

19.60.4.24 getSeed()

```
unsigned int ModelSpec::getSeed ( ) const [inline]
```

Get the random seed.

19.60.4.25 getTimePrecision()

```
std::string ModelSpec::getTimePrecision ( ) const
```

Gets the floating point numerical precision used to represent time.

19.60.4.26 isTimingEnabled()

```
bool ModelSpec::isTimingEnabled ( ) const [inline]
```

Are timers and timing commands enabled.

19.60.4.27 operator=()

19.60.4.28 scalarExpr()

Get the string literal that should be used to represent a value in the model's floating-point type.

19.60.4.29 setDefaultExtraGlobalParamLocation()

What is the default location for model extra global parameters?

Historically, this was just left up to the user to handle

19.60.4.30 setDefaultNarrowSparseIndEnabled()

Sets default for whether narrow i.e. less than 32-bit types are used for sparse matrix indices.

19.60.4.31 setDefaultSparseConnectivityLocation()

```
\begin{tabular}{ll} \beg
```

What is the default location for sparse synaptic connectivity?

Historically, everything was allocated on both the host AND device

19.60.4.32 setDefaultVarLocation()

What is the default location for model state variables?

Historically, everything was allocated on both the host AND device

19.60.4.33 setDT()

Set the integration step size of the model.

19.60.4.34 setMergePostsynapticModels()

Should compatible postsynaptic models and dendritic delay buffers be merged?

This can significantly reduce the cost of updating neuron population but means that per-synapse group inSyn arrays can not be retrieved

19.60.4.35 setName()

Method to set the neuronal network model name.

19.60.4.36 setPrecision()

Set numerical precision for floating point.

This function sets the numerical precision of floating type variables. By default, it is GENN GENN FLOAT.

19.60.4.37 setSeed()

```
void ModelSpec::setSeed (
          unsigned int rngSeed ) [inline]
```

Set the random seed (disables automatic seeding if argument not 0).

19.60.4.38 setTimePrecision()

Set numerical precision for time.

19.60.4.39 setTiming()

```
void ModelSpec::setTiming (
          bool timingEnabled ) [inline]
```

Set whether timers and timing commands are to be included.

19.60.4.40 zeroCopyInUse()

```
bool ModelSpec::zeroCopyInUse ( ) const [protected]
```

Are any variables in any populations in this model using zero-copy memory?


The documentation for this class was generated from the following files:

- · modelSpec.h
- modelSpec.cc

19.61 ModelSpecInternal Class Reference

```
#include <modelSpecInternal.h>
```

Inheritance diagram for ModelSpecInternal:



Additional Inherited Members

The documentation for this class was generated from the following file:

· modelSpecInternal.h

19.62 SpineMLSimulator::NetworkClient Class Reference

```
#include <networkClient.h>
```

Public Types

- enum Mode : char { Mode::Source = 45, Mode::Target = 46 }
- enum DataType: char { DataType::Analogue = 31, DataType::Events = 32, DataType::Impulses = 33 }

Public Member Functions

- NetworkClient ()
- NetworkClient (const std::string &hostname, unsigned int port, unsigned int size, DataType dataType, Mode mode, const std::string &connectionName)
- ∼NetworkClient ()
- bool connect (const std::string &hostname, unsigned int port, unsigned int size, DataType dataType, Mode mode, const std::string &connectionName)
- bool receive (std::vector< double > &buffer)
- bool send (const std::vector< double > &buffer)

19.62.1 Member Enumeration Documentation

19.62.1.1 DataType

```
enum SpineMLSimulator::NetworkClient::DataType : char [strong]
```

Enumerator

Analogue	
Events	
Impulses	

19.62.1.2 Mode

```
enum SpineMLSimulator::NetworkClient::Mode : char [strong]
```

Enumerator

Source	
Target	

19.62.2 Constructor & Destructor Documentation

```
19.62.2.1 NetworkClient() [1/2]
```

```
SpineMLSimulator::NetworkClient::NetworkClient ( )
```

```
19.62.2.2 NetworkClient() [2/2]
SpineMLSimulator::NetworkClient::NetworkClient (
              const std::string & hostname,
              unsigned int port,
              unsigned int size,
              DataType dataType,
              Mode mode,
              const std::string & connectionName )
19.62.2.3 ∼NetworkClient()
{\tt SpineMLSimulator::} {\tt NetworkClient::} {\tt \sim} {\tt NetworkClient} \ \ (\ )
19.62.3 Member Function Documentation
19.62.3.1 connect()
bool SpineMLSimulator::NetworkClient::connect (
              const std::string & hostname,
              unsigned int port,
              unsigned int size,
              DataType dataType,
              Mode mode,
              const std::string & connectionName )
19.62.3.2 receive()
bool SpineMLSimulator::NetworkClient::receive (
              std::vector< double > & buffer )
19.62.3.3 send()
bool SpineMLSimulator::NetworkClient::send (
              const std::vector< double > & buffer )
```


The documentation for this class was generated from the following files:

- · networkClient.h
- · networkClient.cc

19.63 pygenn.genn_groups.NeuronGroup Class Reference

Class representing a group of neurons.

Inheritance diagram for pygenn.genn_groups.NeuronGroup:



Public Member Functions

• def __init__ (self, name)

Init NeuronGroup.

• def current_spikes (self)

Current spikes from GeNN.

def delay_slots (self)

Maximum delay steps needed for this group.

- def size (self)
- def set_neuron (self, model, param_space, var_space)

Set neuron, its parameters and initial variables.

• def add_to (self, model_spec, num_neurons)

Add this NeuronGroup to a model.

• def add_extra_global_param (self, param_name, param_values)

Set extra global parameter.

• def set_extra_global_param (self, param_name, param_values)

Set extra global parameter.

• def load (self, slm, scalar)

Loads neuron group.

• def reinitialise (self, slm, scalar)

Reinitialise neuron group.

Public Attributes

- neuron
- spikes
- · spike_count
- spike_que_ptr
- is_spike_source_array
- type
- pop

19.63.1 Detailed Description

Class representing a group of neurons.

19.63.2 Constructor & Destructor Documentation

Init NeuronGroup.

Parameters

name s	tring name of the group
--------	-------------------------

19.63.3 Member Function Documentation

19.63.3.1 add_extra_global_param()

Set extra global parameter.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.63.3.2 add_to()

Add this NeuronGroup to a model.

Parameters

model_spec	pygenn.genn_model.GeNNModel to add to	
num_neurons	int number of neurons	

19.63.3.3 current_spikes()

```
\label{lem:current_spikes} \mbox{ def pygenn.genn_groups.NeuronGroup.current_spikes (} \\ self \mbox{ )}
```

Current spikes from GeNN.

```
19.63.3.4 delay_slots()
```

```
\label{lem:condition} \mbox{def pygenn\_groups.NeuronGroup.delay\_slots (} \\ self \mbox{)}
```

Maximum delay steps needed for this group.

19.63.3.5 load()

```
def pygenn.genn_groups.NeuronGroup.load ( self, \\ slm, \\ scalar )
```

Loads neuron group.

Parameters

slm	SharedLibraryModel instance for acccessing variables	
scalar	String specifying "scalar" type	

19.63.3.6 reinitialise()

```
def pygenn.genn_groups.NeuronGroup.reinitialise ( self, \\ slm, \\ scalar )
```

Reinitialise neuron group.

Parameters

slm	SharedLibraryModel instance for accessing variables
scalar	String specifying "scalar" type

19.63.3.7 set_extra_global_param()

Set extra global parameter.

param_name	string with the name of the extra global parameter
param values	iterable or a single value

19.63.3.8 set_neuron()

Set neuron, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

19.63.3.9 size()

```
\label{eq:condition} \begin{array}{ll} \operatorname{def} \ \operatorname{pygenn\_groups.NeuronGroup.size} \ \ ( \\ & self \ ) \end{array}
```

19.63.4 Member Data Documentation

19.63.4.1 is_spike_source_array

pygenn.genn_groups.NeuronGroup.is_spike_source_array

19.63.4.2 neuron

pygenn.genn_groups.NeuronGroup.neuron

19.63.4.3 pop

pygenn.genn_groups.NeuronGroup.pop

19.63.4.4 spike_count

 $\verb"pygenn.genn_groups.NeuronGroup.spike_count"$

19.63.4.5 spike_que_ptr

pygenn.genn_groups.NeuronGroup.spike_que_ptr

19.63.4.6 spikes

pygenn.genn_groups.NeuronGroup.spikes

19.63.4.7 type

pygenn.genn_groups.NeuronGroup.type


The documentation for this class was generated from the following file:

· genn_groups.py

19.64 NeuronGroup Class Reference

#include <neuronGroup.h>

Inheritance diagram for NeuronGroup:



Public Member Functions

- NeuronGroup (const NeuronGroup &)=delete
- NeuronGroup ()=delete
- void setSpikeLocation (VarLocation loc)

Set location of this neuron group's output spikes.

void setSpikeEventLocation (VarLocation loc)

Set location of this neuron group's output spike events.

void setSpikeTimeLocation (VarLocation loc)

Set location of this neuron group's output spike times.

void setVarLocation (const std::string &varName, VarLocation loc)

Set variable location of neuron model state variable.

• void setExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of neuron model extra global parameter.

- const std::string & getName () const
- unsigned int getNumNeurons () const

Gets number of neurons in group.

const NeuronModels::Base * getNeuronModel () const

Gets the neuron model used by this group.

- const std::vector< double > & getParams () const
- const std::vector< Models::VarInit > & getVarInitialisers () const
- int getClusterHostID () const
- bool isSpikeTimeRequired () const
- bool isTrueSpikeRequired () const
- bool isSpikeEventRequired () const
- unsigned int getNumDelaySlots () const
- bool isDelayRequired () const
- bool isZeroCopyEnabled () const
- VarLocation getSpikeLocation () const

Get location of this neuron group's output spikes.

VarLocation getSpikeEventLocation () const

Get location of this neuron group's output spike events.

VarLocation getSpikeTimeLocation () const

Get location of this neuron group's output spike times.

VarLocation getVarLocation (const std::string &varName) const

Get location of neuron model state variable by name.

VarLocation getVarLocation (size t index) const

Get location of neuron model state variable by index.

• VarLocation getExtraGlobalParamLocation (const std::string ¶mName) const

Get location of neuron model extra global parameter by name.

VarLocation getExtraGlobalParamLocation (size t index) const

Get location of neuron model extra global parameter by omdex.

bool isSimRNGRequired () const

Does this neuron group require an RNG to simulate?

• bool isInitRNGRequired () const

Does this neuron group require an RNG for it's init code?

bool hasOutputToHost (int targetHostID) const

Does this neuron group have outgoing connections specified host id?

Protected Member Functions

- NeuronGroup (const std::string &name, int numNeurons, const NeuronModels::Base *neuronModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation default
 VarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)
- void checkNumDelaySlots (unsigned int requiredDelay)

Checks delay slots currently provided by the neuron group against a required delay and extends if required.

void updatePreVarQueues (const std::string &code)

Update which presynaptic variables require queues based on piece of code.

void updatePostVarQueues (const std::string &code)

Update which postsynaptic variables require queues based on piece of code.

- void addSpkEventCondition (const std::string &code, const std::string &supportCodeNamespace)
- void addlnSyn (SynapseGroupInternal *synapseGroup)
- void addOutSyn (SynapseGroupInternal *synapseGroup)
- · void initDerivedParams (double dt)
- void mergeIncomingPSM (bool merge)

Merge incoming postsynaptic models.

void injectCurrent (CurrentSourceInternal *source)

add input current source

• const std::vector < SynapseGroupInternal * > & getInSyn () const

Gets pointers to all synapse groups which provide input to this neuron group.

- const std::vector< SynapseGroupInternal * > & getOutSyn () const

Gets pointers to all synapse groups emanating from this neuron group.

const std::vector< CurrentSourceInternal * > & getCurrentSources () const

Gets pointers to all current sources which provide input to this neuron group.

- const std::vector< double > & getDerivedParams () const
- const std::set< std::pair< std::string, std::string > > & getSpikeEventCondition () const
- · bool isParamRequiredBySpikeEventCondition (const std::string &pnamefull) const

Do any of the spike event conditions tested by this neuron require specified parameter?

std::string getCurrentQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables this timestep.

• std::string getPrevQueueOffset (const std::string &devPrefix) const

Get the expression to calculate the queue offset for accessing state of variables in previous timestep.

- bool isVarQueueRequired (const std::string &var) const
- bool isVarQueueRequired (size_t index) const

19.64.1 Constructor & Destructor Documentation

```
19.64.1.1 NeuronGroup() [1/3]
NeuronGroup::NeuronGroup (
             const NeuronGroup & ) [delete]
19.64.1.2 NeuronGroup() [2/3]
NeuronGroup::NeuronGroup ( ) [delete]
19.64.1.3 NeuronGroup() [3/3]
NeuronGroup::NeuronGroup (
             const std::string & name,
             int numNeurons,
             const NeuronModels::Base * neuronModel,
             const std::vector< double > & params,
             const std::vector< Models::VarInit > & varInitialisers,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             int hostID ) [inline], [protected]
19.64.2 Member Function Documentation
19.64.2.1 addlnSyn()
void NeuronGroup::addInSyn (
             SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.64.2.2 addOutSyn()
void NeuronGroup::addOutSyn (
             SynapseGroupInternal * synapseGroup ) [inline], [protected]
19.64.2.3 addSpkEventCondition()
void NeuronGroup::addSpkEventCondition (
             const std::string & code,
             const std::string & supportCodeNamespace ) [protected]
19.64.2.4 checkNumDelaySlots()
void NeuronGroup::checkNumDelaySlots (
             unsigned int requiredDelay ) [protected]
```

Checks delay slots currently provided by the neuron group against a required delay and extends if required.

```
19.64.2.5 getClusterHostID()
int NeuronGroup::getClusterHostID ( ) const [inline]
19.64.2.6 getCurrentQueueOffset()
std::string NeuronGroup::getCurrentQueueOffset (
                               const std::string & devPrefix ) const [protected]
Get the expression to calculate the queue offset for accessing state of variables this timestep.
19.64.2.7 getCurrentSources()
const std::vector<CurrentSourceInternal*>& NeuronGroup::getCurrentSources ( ) const [inline],
 [protected]
Gets pointers to all current sources which provide input to this neuron group.
19.64.2.8 getDerivedParams()
const std::vector<double>& NeuronGroup::getDerivedParams ( ) const [inline], [protected]
19.64.2.9 getExtraGlobalParamLocation() [1/2]
{\tt VarLocation\ NeuronGroup::} {\tt getExtraGlobalParamLocation\ (}
                               const std::string & paramName ) const
Get location of neuron model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.64.2.10 getExtraGlobalParamLocation() [2/2]
VarLocation NeuronGroup::getExtraGlobalParamLocation (
                               size_t index ) const [inline]
Get location of neuron model extra global parameter by omdex.
This is only used by extra global parameters which are pointers
19.64.2.11 getInSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getInSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups which provide input to this neuron group.
19.64.2.12 getMergedInSyn()
\verb|const| std::vector < std::pair < Synapse Group Internal*|, std::vector < Synapse Group Internal*|> > > \& Const | Synapse Group Internal*| > > > & Const | Synapse Group Internal*| > & Const | Synapse Group Internal*|
NeuronGroup::getMergedInSyn ( ) const [inline], [protected]
19.64.2.13 getName()
const std::string& NeuronGroup::getName ( ) const [inline]
```

```
19.64.2.14 getNeuronModel()
const NeuronModels::Base* NeuronGroup::getNeuronModel ( ) const [inline]
Gets the neuron model used by this group.
19.64.2.15 getNumDelaySlots()
unsigned int NeuronGroup::getNumDelaySlots ( ) const [inline]
19.64.2.16 getNumNeurons()
unsigned int NeuronGroup::getNumNeurons ( ) const [inline]
Gets number of neurons in group.
19.64.2.17 getOutSyn()
const std::vector<SynapseGroupInternal*>& NeuronGroup::getOutSyn ( ) const [inline], [protected]
Gets pointers to all synapse groups emanating from this neuron group.
19.64.2.18 getParams()
const std::vector<double>& NeuronGroup::getParams ( ) const [inline]
19.64.2.19 getPrevQueueOffset()
{\tt std::string\ NeuronGroup::getPrevQueueOffset} (
             const std::string & devPrefix ) const [protected]
Get the expression to calculate the queue offset for accessing state of variables in previous timestep.
19.64.2.20 getSpikeEventCondition()
const [inline], [protected]
19.64.2.21 getSpikeEventLocation()
VarLocation NeuronGroup::getSpikeEventLocation ( ) const [inline]
Get location of this neuron group's output spike events.
19.64.2.22 getSpikeLocation()
VarLocation NeuronGroup::getSpikeLocation ( ) const [inline]
```

Get location of this neuron group's output spikes.

```
19.64.2.23 getSpikeTimeLocation()
VarLocation NeuronGroup::getSpikeTimeLocation ( ) const [inline]
Get location of this neuron group's output spike times.
19.64.2.24 getVarInitialisers()
const std::vector<Models::VarInit>& NeuronGroup::getVarInitialisers ( ) const [inline]
19.64.2.25 getVarLocation() [1/2]
VarLocation NeuronGroup::getVarLocation (
             const std::string & varName ) const
Get location of neuron model state variable by name.
19.64.2.26 getVarLocation() [2/2]
VarLocation NeuronGroup::getVarLocation (
              size_t index ) const [inline]
Get location of neuron model state variable by index.
19.64.2.27 hasOutputToHost()
bool NeuronGroup::hasOutputToHost (
              int targetHostID ) const
Does this neuron group have outgoing connections specified host id?
19.64.2.28 initDerivedParams()
void NeuronGroup::initDerivedParams (
             double dt ) [protected]
19.64.2.29 injectCurrent()
void NeuronGroup::injectCurrent (
              CurrentSourceInternal * source ) [protected]
add input current source
19.64.2.30 isDelayRequired()
bool NeuronGroup::isDelayRequired ( ) const [inline]
19.64.2.31 isInitRNGRequired()
bool NeuronGroup::isInitRNGRequired ( ) const
```

Does this neuron group require an RNG for it's init code?

```
19.64.2.32 isParamRequiredBySpikeEventCondition()
bool NeuronGroup::isParamRequiredBySpikeEventCondition (
              const std::string & pnamefull ) const [protected]
Do any of the spike event conditions tested by this neuron require specified parameter?
19.64.2.33 isSimRNGRequired()
bool NeuronGroup::isSimRNGRequired ( ) const
Does this neuron group require an RNG to simulate?
19.64.2.34 isSpikeEventRequired()
bool NeuronGroup::isSpikeEventRequired ( ) const
19.64.2.35 isSpikeTimeRequired()
bool NeuronGroup::isSpikeTimeRequired ( ) const
19.64.2.36 isTrueSpikeRequired()
bool NeuronGroup::isTrueSpikeRequired ( ) const
19.64.2.37 isVarQueueRequired() [1/2]
bool NeuronGroup::isVarQueueRequired (
              const std::string & var ) const [protected]
19.64.2.38 isVarQueueRequired() [2/2]
bool NeuronGroup::isVarQueueRequired (
             size_t index ) const [inline], [protected]
19.64.2.39 isZeroCopyEnabled()
bool NeuronGroup::isZeroCopyEnabled ( ) const
19.64.2.40 mergeIncomingPSM()
void NeuronGroup::mergeIncomingPSM (
             bool merge ) [protected]
```

Merge incoming postsynaptic models.

19.64.2.41 setExtraGlobalParamLocation()

Set location of neuron model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.64.2.42 setSpikeEventLocation()

Set location of this neuron group's output spike events.

This is ignored for simulations on hardware with a single memory space

19.64.2.43 setSpikeLocation()

Set location of this neuron group's output spikes.

This is ignored for simulations on hardware with a single memory space

19.64.2.44 setSpikeTimeLocation()

Set location of this neuron group's output spike times.

This is ignored for simulations on hardware with a single memory space

19.64.2.45 setVarLocation()

Set variable location of neuron model state variable.

This is ignored for simulations on hardware with a single memory space

19.64.2.46 updatePostVarQueues()

Update which postsynaptic variables require queues based on piece of code.

19.64.2.47 updatePreVarQueues()

Update which presynaptic variables require queues based on piece of code.


The documentation for this class was generated from the following files:

- neuronGroup.h
- neuronGroup.cc

19.65 NeuronGroupInternal Class Reference

#include <neuronGroupInternal.h>

Inheritance diagram for NeuronGroupInternal:



Public Member Functions

NeuronGroupInternal (const std::string &name, int numNeurons, const NeuronModels::Base *neuronModel, const std::vector< double > ¶ms, const std::vector< Models::VarInit > &varInitialisers, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, int hostID)

Additional Inherited Members

19.65.1 Constructor & Destructor Documentation

19.65.1.1 NeuronGroupInternal()

The documentation for this class was generated from the following file:


neuronGroupInternal.h

19.66 InitVarSnippet::Normal Class Reference

Initialises variable by sampling from the normal distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Normal:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Normal, 2)
- SET_CODE ("\$(value) = \$(mean) + (\$(gennrand_normal) * \$(sd));")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.66.1 Detailed Description

Initialises variable by sampling from the normal distribution.

This snippet takes 2 parameters:

- mean The mean
- sd The standard distribution

19.66.2 Member Function Documentation

19.66.2.1 DECLARE_SNIPPET()

19.66.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Normal::getParamNames ( ) const [inline], [override], [virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.66.2.3 SET_CODE()

```
InitVarSnippet::Normal::SET_CODE ( )
```

The documentation for this class was generated from the following file:

· initVarSnippet.h

19.67 SpineMLSimulator::ModelProperty::NormalDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::NormalDistribution:

```
SpineMLSimulator::ModelProperty::Base

SpineMLSimulator::ModelProperty::NormalDistribution
```

Public Member Functions

- NormalDistribution (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size)
- void setValue (scalar mean, scalar variance)

19.67.1 Constructor & Destructor Documentation

19.67.1.1 NormalDistribution()

19.67.2 Member Function Documentation

19.67.2.1 setValue()

The documentation for this class was generated from the following files:

- · modelProperty.h
- · modelProperty.cc

19.68 CodeGenerator::CodeStream::OB Struct Reference

An open bracket marker.

```
#include <codeStream.h>
```

Public Member Functions

• OB (unsigned int level)

Public Attributes

const unsigned int Level

19.68.1 Detailed Description

An open bracket marker.

Write to code stream os using:

```
os << OB(16);
```

19.68.2 Constructor & Destructor Documentation

19.68.2.1 OB()

```
CodeGenerator::CodeStream::OB::OB (
          unsigned int level ) [inline]
```

19.68.3 Member Data Documentation

19.68.3.1 Level

```
const unsigned int CodeGenerator::CodeStream::OB::Level
```

The documentation for this struct was generated from the following file:


· codeStream.h

19.69 InitSparseConnectivitySnippet::OneToOne Class Reference

Initialises connectivity to a 'one-to-one' diagonal matrix.

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::OneToOne:



Public Member Functions

- DECLARE_SNIPPET (InitSparseConnectivitySnippet::OneToOne, 0)
- SET_ROW_BUILD_CODE ("\$(addSynapse, \$(id_pre));\ "\$(endRow);\")
- SET_MAX_ROW_LENGTH (1)
- SET_MAX_COL_LENGTH (1)

Additional Inherited Members

19.69.1 Detailed Description

Initialises connectivity to a 'one-to-one' diagonal matrix.

19.69.2 Member Function Documentation

19.69.2.1 DECLARE_SNIPPET()

19.69.2.2 SET_MAX_COL_LENGTH()

19.69.2.3 SET_MAX_ROW_LENGTH()

19.69.2.4 SET_ROW_BUILD_CODE()

The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

19.70 Snippet::Base::ParamVal Struct Reference

Additional input variables, row state variables and other things have a name, a type and an initial value.

```
#include <snippet.h>
```

Public Attributes

- std::string name
- · std::string type
- double value

19.70.1 Detailed Description

Additional input variables, row state variables and other things have a name, a type and an initial value.

19.70.2 Member Data Documentation

19.70.2.1 name

```
std::string Snippet::Base::ParamVal::name
```

19.70.2.2 type

```
std::string Snippet::Base::ParamVal::type
```

19.70.2.3 value

```
double Snippet::Base::ParamVal::value
```

The documentation for this struct was generated from the following file:


· snippet.h

19.71 WeightUpdateModels::PiecewiseSTDP Class Reference

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::PiecewiseSTDP:



Public Member Functions

- DECLARE WEIGHT UPDATE MODEL (PiecewiseSTDP, 10, 2, 0, 0)
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

virtual std::string getLearnPostCode () const override

Gets code to include in the learnSynapsesPost kernel/function.

- virtual DerivedParamVec getDerivedParams () const override
- virtual bool isPreSpikeTimeRequired () const override

Whether presynaptic spike times are needed or not.

virtual bool isPostSpikeTimeRequired () const override


Whether postsynaptic spike times are needed or not.


Additional Inherited Members

19.71.1 Detailed Description

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

The STDP window is defined as a piecewise function:





The STDP curve is applied to the raw synaptic conductance gRaw, which is then filtered through the sugmoidal filter displayed above to obtain the value of g.

Note

The STDP curve implies that unpaired pre- and post-synaptic spikes incur a negative increment in gRaw (and hence in g).

The time of the last spike in each neuron, "sTXX", where XX is the name of a neuron population is (somewhat arbitrarily) initialised to -10.0 ms. If neurons never spike, these spike times are used.

It is the raw synaptic conductance gRaw that is subject to the STDP rule. The resulting synaptic conductance is a sigmoid filter of gRaw. This implies that g is initialised but not gRaw, the synapse will revert to the value that corresponds to gRaw.

An example how to use this synapse correctly is given in map_classol.cc (MBody1 userproject):

```
for (int i= 0; i < model.neuronN[1]*model.neuronN[3]; i++) {
    if (gKCDN[i] < 2.0*SCALAR_MIN) {
        cnt++;
        fprintf(stdout, "Too low conductance value %e detected and set to 2*SCALAR_MIN= %e, at index %d
    \n", gKCDN[i], 2*SCALAR_MIN, i);
        gRCDN[i] = 2.0*SCALAR_MIN; //to avoid log(0)/0 below
    }
    scalar tmp = gKCDN[i] / myKCDN_p[5]*2.0;
    gRawKCDN[i] = 0.5 * log( tmp / (2.0 - tmp)) /myKCDN_p[7] + myKCDN_p[6];
}
cerr << "Total number of low value corrections: " << cnt << endl;</pre>
```

Note

One cannot set values of g fully to 0, as this leads to gRaw= -infinity and this is not support. I.e., 'g' needs to be some nominal value > 0 (but can be extremely small so that it acts like it's 0).

The model has 2 variables:

- \bullet g: conductance of ${\tt scalar}$ type
- gRaw: raw conductance of scalar type

Parameters are (compare to the figure above):

- tLrn: Time scale of learning changes
- tChng: Width of learning window
- tDecay: Time scale of synaptic strength decay
- tPunish10: Time window of suppression in response to 1/0
- tPunish01: Time window of suppression in response to 0/1
- gMax: Maximal conductance achievable
- qMid: Midpoint of sigmoid g filter curve
- gSlope: Slope of sigmoid g filter curve
- tauShift: Shift of learning curve
- gSyn0: Value of syn conductance g decays to

19.71.2 Member Function Documentation

19.71.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.71.2.2 getDerivedParams()

```
virtual DerivedParamVec WeightUpdateModels::PiecewiseSTDP::getDerivedParams ( ) const [inline],
[override], [virtual]
```

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.71.2.3 getLearnPostCode()

```
virtual std::string WeightUpdateModels::PiecewiseSTDP::getLearnPostCode ( ) const [inline],
[override], [virtual]
```

Gets code to include in the learnSynapsesPost kernel/function.

For examples when modelling STDP, this is where the effect of postsynaptic spikes which occur *after* presynaptic spikes are applied.

Reimplemented from WeightUpdateModels::Base.

19.71.2.4 getParamNames()

virtual StringVec WeightUpdateModels::PiecewiseSTDP::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.71.2.5 getSimCode()

virtual std::string WeightUpdateModels::PiecewiseSTDP::getSimCode () const [inline], [override],
[virtual]

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.71.2.6 getVars()

```
virtual VarVec WeightUpdateModels::PiecewiseSTDP::getVars ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.71.2.7 isPostSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPostSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether postsynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

19.71.2.8 isPreSpikeTimeRequired()

```
virtual bool WeightUpdateModels::PiecewiseSTDP::isPreSpikeTimeRequired ( ) const [inline],
[override], [virtual]
```

Whether presynaptic spike times are needed or not.

Reimplemented from WeightUpdateModels::Base.

The documentation for this class was generated from the following file:


• weightUpdateModels.h

19.72 NeuronModels::Poisson Class Reference

Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::Poisson:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

· virtual EGPVec getExtraGlobalParams () const override

Static Public Member Functions

static const NeuronModels::Poisson * getInstance ()

Additional Inherited Members

19.72.1 Detailed Description

Poisson neurons.

Poisson neurons have constant membrane potential (Vrest) unless they are activated randomly to the Vspike value if (t-SpikeTime) > trefract.

It has 2 variables:

- V Membrane potential (mV)
- SpikeTime Time at which the neuron spiked for the last time (ms)

and 4 parameters:

- trefract Refractory period (ms)
- tspike duration of spike (ms)

- Vspike Membrane potential at spike (mV)
- Vrest Membrane potential at rest (mV)

Note

The initial values array for the Poisson type needs two entries for V, and SpikeTime and the parameter array needs four entries for therate, trefract, Vspike and Vrest, in that order.

This model uses a linear approximation for the probability of firing a spike in a given time step of size DT, i.e. the probability of firing is λ times DT: $p = \lambda \Delta t$. This approximation is usually very good, especially for typical, quite small time steps and moderate firing rates. However, it is worth noting that the approximation becomes poor for very high firing rates and large time steps.

19.72.2 Member Typedef Documentation

19.72.2.1 ParamValues

typedef Snippet::ValueBase< 4 > NeuronModels::Poisson::ParamValues

19.72.2.2 PostVarValues

 ${\tt typedef\ Models::} VarInitContainerBase < 0 > \ NeuronModels::Poisson::PostVarValues$

19.72.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::Poisson::PreVarValues

19.72.2.4 VarValues

typedef Models::VarInitContainerBase< 2 > NeuronModels::Poisson::VarValues

19.72.3 Member Function Documentation

19.72.3.1 getExtraGlobalParams()

```
virtual EGPVec NeuronModels::Poisson::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

19.72.3.2 getInstance()

static const NeuronModels::Poisson* NeuronModels::Poisson::getInstance () [inline], [static]

19.72.3.3 getParamNames()

virtual StringVec NeuronModels::Poisson::getParamNames () const [inline], [override], [virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.72.3.4 getSimCode()

```
virtual std::string NeuronModels::Poisson::getSimCode ( ) const [inline], [override], [virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.72.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::Poisson::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.72.3.6 getVars()

```
virtual VarVec NeuronModels::Poisson::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


• neuronModels.h

19.73 NeuronModels::PoissonNew Class Reference

Poisson neurons.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::PoissonNew:



Public Types

- typedef Snippet::ValueBase< 1 > ParamValues
- typedef Models::VarInitContainerBase< 1 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

• virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- virtual DerivedParamVec getDerivedParams () const override
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

• static const NeuronModels::PoissonNew * getInstance ()

Additional Inherited Members

19.73.1 Detailed Description

Poisson neurons.

It has 1 state variable:

- $\label{eq:limits} \textbf{ -} \textbf{ limeStepToSpike - Number of timesteps to next spike}$

and 1 parameter:

• rate - Mean firing rate (Hz)

Note

Internally this samples from the exponential distribution using the C++ 11 < random > library on the CPU and by transforming the uniform distribution, generated using cuRAND, with a natural log on the GPU.

19.73.2 Member Typedef Documentation

19.73.2.1 ParamValues

typedef Snippet::ValueBase< 1 > NeuronModels::PoissonNew::ParamValues

19.73.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PostVarValues

19.73.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::PoissonNew::PreVarValues

19.73.2.4 VarValues

typedef Models::VarInitContainerBase< 1 > NeuronModels::PoissonNew::VarValues

19.73.3 Member Function Documentation

19.73.3.1 getDerivedParams()

virtual DerivedParamVec NeuronModels::PoissonNew::getDerivedParams () const [inline], [override],
[virtual]

Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of model parameter values

Reimplemented from Snippet::Base.

19.73.3.2 getInstance()

static const NeuronModels::PoissonNew* NeuronModels::PoissonNew::getInstance () [inline],
[static]

19.73.3.3 getParamNames()

virtual StringVec NeuronModels::PoissonNew::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.73.3.4 getSimCode()

virtual std::string NeuronModels::PoissonNew::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.73.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::PoissonNew::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.73.3.6 getVars()

```
virtual VarVec NeuronModels::PoissonNew::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.73.3.7 SET_NEEDS_AUTO_REFRACTORY()


The documentation for this class was generated from the following file:

neuronModels.h

19.74 SpineMLSimulator::Input::PoissonSpikeRate Class Reference

```
#include <input.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Input:: Poisson Spike Rate:$



Public Member Functions

PoissonSpikeRate (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)

Protected Member Functions

• virtual double getTimeToSpike (double isiMs)

Additional Inherited Members

19.74.1 Constructor & Destructor Documentation

19.74.1.1 PoissonSpikeRate()

19.74.2 Member Function Documentation

19.74.2.1 getTimeToSpike()

Implements SpineMLSimulator::Input::InterSpikeIntervalBase.

The documentation for this class was generated from the following files:


- input.h
- input.cc

19.75 CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan Class Reference

Postsynaptic parallelism.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan:



Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override
 - Get the number of threads that presynaptic updates should be parallelised across.
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override
- Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

 virtual bool isCompatible (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences) const override

Is this presynaptic update strategy compatible with a given synapse group?

 virtual size_t getSharedMemoryPerThread (const SynapseGroupInternal &sg, const Backend &backend) const override How many neurons does each thread accumulate the outputs of into shared memory.

- virtual void genPreamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override
- virtual void genUpdate (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, size_t idStart, Backend
 Base::SynapseGroupHandler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler,
 BackendBase::SynapseGroupHandler wumProceduralConnectHandler) const override

Generate presynaptic update code.

 virtual void genPostamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size t idStart) const override

19.75.1 Detailed Description

Postsynaptic parallelism.

19.75.2 Member Function Documentation

19.75.2.1 genPostamble()

 $Implements\ Code Generator:: CUDA:: Presynaptic Update Strategy:: Base.$

19.75.2.2 genPreamble()

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.3 genUpdate()

```
{\tt BackendBase::SynapseGroupHandler}\ \textit{wumProceduralConnectHandler}\ )\ {\tt const}\ [{\tt override}], \\ [{\tt virtual}]
```

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.4 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.5 getSharedMemoryPerThread()

How many neurons does each thread accumulate the outputs of into shared memory.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.6 getSynapticMatrixRowStride()

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.75.2.7 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

The documentation for this class was generated from the following files:

- presynapticUpdateStrategy.h
- presynapticUpdateStrategy.cc

19.76 CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask Class Reference

Postsynaptic parallelism.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask:

```
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base

CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask
```

Public Member Functions

virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override

Get the number of threads that presynaptic updates should be parallelised across.

- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override
 - Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.
- virtual bool isCompatible (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences) const override

Is this presynaptic update strategy compatible with a given synapse group?

 virtual size_t getSharedMemoryPerThread (const SynapseGroupInternal &sg, const Backend &backend) const override

How many neurons does each thread accumulate the outputs of into shared memory.

- virtual void genPreamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override
- virtual void genUpdate (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, size_t idStart, Backend← Base::SynapseGroupHandler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler, BackendBase::SynapseGroupHandler wumProceduralConnectHandler) const override

Generate presynaptic update code.

 virtual void genPostamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override

19.76.1 Detailed Description

Postsynaptic parallelism.

19.76.2 Member Function Documentation

19.76.2.1 genPostamble()

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.2 genPreamble()

```
const SynapseGroupInternal & sg,
const Substitutions & popSubs,
const Backend & backend,
size_t idStart ) const [override], [virtual]
```

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.3 genUpdate()

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.4 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.5 getSharedMemoryPerThread()

How many neurons does each thread accumulate the outputs of into shared memory.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.6 getSynapticMatrixRowStride()

```
size_t CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpanBitmask::getSynapticMatrixRow\leftarrow Stride ( const SynapseGroupInternal & sg ) const [override], [virtual]
```

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.76.2.7 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

The documentation for this class was generated from the following files:


- · presynapticUpdateStrategy.h
- · presynapticUpdateStrategy.cc

19.77 CodeGenerator::CUDA::Preferences Struct Reference

Preferences for CUDA backend.

```
#include <backend.h>
```

Inheritance diagram for CodeGenerator::CUDA::Preferences:



Public Member Functions

• Preferences ()

Public Attributes

• bool showPtxInfo = false

Should PTX assembler information be displayed for each CUDA kernel during compilation?

• bool generateLineInfo = false

Should line info be included in resultant executable for debugging/profiling purposes?

• DeviceSelect deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

unsigned int manualDeviceID = 0

If device select method is set to DeviceSelect::MANUAL, id of device to use.

• BlockSizeSelect blockSizeSelectMethod = BlockSizeSelect::OCCUPANCY

How to select CUDA blocksize.

KernelBlockSize manualBlockSizes

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

• std::string userNvccFlags = ""

NVCC compiler options for all GPU code.

19.77.1 Detailed Description

Preferences for CUDA backend.

19.77.2 Constructor & Destructor Documentation

19.77.2.1 **Preferences()**

CodeGenerator::CUDA::Preferences::Preferences () [inline]

19.77.3 Member Data Documentation

19.77.3.1 blockSizeSelectMethod

BlockSizeSelect CodeGenerator::CUDA::Preferences::blockSizeSelectMethod = BlockSizeSelect::OC← CUPANCY

How to select **CUDA** blocksize.

19.77.3.2 deviceSelectMethod

DeviceSelect CodeGenerator::CUDA::Preferences::deviceSelectMethod = DeviceSelect::OPTIMAL

How to select GPU device.

19.77.3.3 generateLineInfo

bool CodeGenerator::CUDA::Preferences::generateLineInfo = false

Should line info be included in resultant executable for debugging/profiling purposes?

19.77.3.4 manualBlockSizes

KernelBlockSize CodeGenerator::CUDA::Preferences::manualBlockSizes

If block size select method is set to BlockSizeSelect::MANUAL, block size to use for each kernel.

19.77.3.5 manualDeviceID

```
unsigned int CodeGenerator::CUDA::Preferences::manualDeviceID = 0
```

If device select method is set to DeviceSelect::MANUAL, id of device to use.

19.77.3.6 showPtxInfo

bool CodeGenerator::CUDA::Preferences::showPtxInfo = false

Should PTX assembler information be displayed for each CUDA kernel during compilation?

19.77.3.7 userNvccFlags

std::string CodeGenerator::CUDA::Preferences::userNvccFlags = ""

NVCC compiler options for all GPU code.


The documentation for this struct was generated from the following file:

· cuda/backend.h

19.78 CodeGenerator::SingleThreadedCPU::Preferences Struct Reference

#include <backend.h>

Inheritance diagram for CodeGenerator::SingleThreadedCPU::Preferences:



Additional Inherited Members

The documentation for this struct was generated from the following file:


• single_threaded_cpu/backend.h

19.79 CodeGenerator::PreferencesBase Struct Reference

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

#include <backendBase.h>

Inheritance diagram for CodeGenerator::PreferencesBase:



Public Attributes

bool optimizeCode = false

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

• bool debugCode = false

Generate code with debug symbols.

- bool enableBitmaskOptimisations = false
- bool automaticCopy = false

If backend/device supports it, copy data automatically when required rather than requiring push and pull.

• std::string userCxxFlagsGNU = ""

C++ compiler options to be used for building all host side code (used for unix based platforms)

std::string userNvccFlagsGNU = ""

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

• plog::Severity logLevel = plog::info

Logging level to use for code generation.

19.79.1 Detailed Description

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

19.79.2 Member Data Documentation

19.79.2.1 automaticCopy

```
bool CodeGenerator::PreferencesBase::automaticCopy = false
```

If backend/device supports it, copy data automatically when required rather than requiring push and pull.

19.79.2.2 debugCode

bool CodeGenerator::PreferencesBase::debugCode = false

Generate code with debug symbols.

19.79.2.3 enableBitmaskOptimisations

```
bool CodeGenerator::PreferencesBase::enableBitmaskOptimisations = false
```

New optimizations made to kernels for simulating synapse groups with BITMASK connectivity Improve performance but break backward compatibility due to word-padding each row

19.79.2.4 logLevel

```
plog::Severity CodeGenerator::PreferencesBase::logLevel = plog::info
```

Logging level to use for code generation.

19.79.2.5 optimizeCode

```
bool CodeGenerator::PreferencesBase::optimizeCode = false
```

Generate speed-optimized code, potentially at the expense of floating-point accuracy.

19.79.2.6 userCxxFlagsGNU

```
std::string CodeGenerator::PreferencesBase::userCxxFlagsGNU = ""
```

C++ compiler options to be used for building all host side code (used for unix based platforms)

19.79.2.7 userNvccFlagsGNU

```
std::string CodeGenerator::PreferencesBase::userNvccFlagsGNU = ""
```

NVCC compiler options they may want to use for all GPU code (used for unix based platforms)

The documentation for this struct was generated from the following file:

· backendBase.h

19.80 CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan Class Reference

Presynaptic parallelism.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan:

```
CodeGenerator::CUDA::PresynapticUpdateStrategy::Base

CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan
```

Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override
 Get the number of threads that presynaptic updates should be parallelised across.
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override
 Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.
- virtual bool isCompatible (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences) const override

Is this presynaptic update strategy compatible with a given synapse group?

virtual size_t getSharedMemoryPerThread (const SynapseGroupInternal &sg, const Backend &backend)
 const override

How many neurons does each thread accumulate the outputs of into shared memory.

- virtual void genPreamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size t idStart) const override
- virtual void genUpdate (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, size_t idStart, Backend Base::SynapseGroupHandler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler, BackendBase::SynapseGroupHandler wumProceduralConnectHandler) const override

Generate presynaptic update code.

 virtual void genPostamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override

19.80.1 Detailed Description

Presynaptic parallelism.

19.80.2 Member Function Documentation

19.80.2.1 genPostamble()

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.80.2.2 genPreamble()

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.80.2.3 genUpdate()

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.80.2.4 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.80.2.5 getSharedMemoryPerThread()

How many neurons does each thread accumulate the outputs of into shared memory.

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.80.2.6 getSynapticMatrixRowStride()

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.80.2.7 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

The documentation for this class was generated from the following files:


- presynapticUpdateStrategy.h
- · presynapticUpdateStrategy.cc

19.81 CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural Class Reference

Presynaptic parallelism with procedural connectivity.

```
#include ynapticUpdateStrategy.h>
```

Inheritance diagram for CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural:



Public Member Functions

- virtual size_t getNumThreads (const SynapseGroupInternal &sg) const override
 - Get the number of threads that presynaptic updates should be parallelised across.
- virtual size_t getSynapticMatrixRowStride (const SynapseGroupInternal &sg) const override
 - Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.
- virtual bool isCompatible (const SynapseGroupInternal &sg, const cudaDeviceProp &deviceProps, const Preferences &preferences) const override

Is this presynaptic update strategy compatible with a given synapse group?

virtual size_t getSharedMemoryPerThread (const SynapseGroupInternal &sg, const Backend &backend)
 const override

How many neurons does each thread accumulate the outputs of into shared memory.

- virtual void genPreamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override
- virtual void genUpdate (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, bool trueSpike, size_t idStart, Backend Base::SynapseGroupHandler wumThreshHandler, BackendBase::SynapseGroupHandler wumSimHandler, BackendBase::SynapseGroupHandler wumProceduralConnectHandler) const override

Generate presynaptic update code.

 virtual void genPostamble (CodeStream &os, const ModelSpecInternal &model, const SynapseGroupInternal &sg, const Substitutions &popSubs, const Backend &backend, size_t idStart) const override

19.81.1 Detailed Description

Presynaptic parallelism with procedural connectivity.

19.81.2 Member Function Documentation

19.81.2.1 genPostamble()

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.81.2.2 genPreamble()

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.81.2.3 genUpdate()

Generate presynaptic update code.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.81.2.4 getNumThreads()

Get the number of threads that presynaptic updates should be parallelised across.

 $Implements\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Base.$

19.81.2.5 getSharedMemoryPerThread()

How many neurons does each thread accumulate the outputs of into shared memory.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.81.2.6 getSynapticMatrixRowStride()

```
\label{lem:size_todeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural::getSynapticMatrix \leftarrow \\ RowStride ( \\ const SynapseGroupInternal & sg ) const [override], [virtual] \\
```

Gets the stride used to access synaptic matrix rows, taking into account sparse data structure, padding etc.

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.

19.81.2.7 isCompatible()

Is this presynaptic update strategy compatible with a given synapse group?

Implements CodeGenerator::CUDA::PresynapticUpdateStrategy::Base.


The documentation for this class was generated from the following files:

- presynapticUpdateStrategy.h
- · presynapticUpdateStrategy.cc

19.82 SpineMLSimulator::Input::RegularSpikeRate Class Reference

```
#include <input.h>
```

 $Inheritance\ diagram\ for\ Spine MLS imulator:: Input:: Regular Spike Rate:$



Public Member Functions

RegularSpikeRate (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, PushCurrentSpikesFunc pushCurrentSpikes)

Protected Member Functions

• virtual double getTimeToSpike (double isiMs) override

Additional Inherited Members

19.82.1 Constructor & Destructor Documentation

19.82.1.1 RegularSpikeRate()

19.82.2 Member Function Documentation

19.82.2.1 getTimeToSpike()

 $Implements\ Spine MLS imulator :: Input :: Inter Spike Interval Base.$

The documentation for this class was generated from the following files:


- input.h
- input.cc

19.83 NeuronModels::RulkovMap Class Reference

Rulkov Map neuron.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::RulkovMap:



Public Types

- typedef Snippet::ValueBase< 4 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual DerivedParamVec getDerivedParams () const override

Static Public Member Functions

• static const NeuronModels::RulkovMap * getInstance ()

Additional Inherited Members

19.83.1 Detailed Description

Rulkov Map neuron.

The RulkovMap type is a map based neuron model based on [5] but in the 1-dimensional map form used in [4]:

$$V(t + \Delta t) = \begin{cases} V_{\text{spike}} \left(\frac{\alpha V_{\text{spike}}}{V_{\text{spike}} - V(t)\beta I_{\text{syn}}} + y \right) & V(t) \leq 0 \\ V_{\text{spike}} \left(\alpha + y \right) & V(t) \leq V_{\text{spike}} \left(\alpha + y \right) & \& V(t - \Delta t) \leq 0 \\ -V_{\text{spike}} & \text{otherwise} \end{cases}$$

Note

The RulkovMap type only works as intended for the single time step size of DT= 0.5.

The RulkovMap type has 2 variables:

- preV the membrane potential at the previous time step

and it has 4 parameters:

- Vspike determines the amplitude of spikes, typically -60mV
- alpha determines the shape of the iteration function, typically α = 3
- y "shift / excitation" parameter, also determines the iteration function, originally, y= -2.468
- beta roughly speaking equivalent to the input resistance, i.e. it regulates the scale of the input into the neuron, typically β = 2.64 M Ω .

Note

The initial values array for the RulkovMap type needs two entries for V and Vpre and the parameter array needs four entries for Vspike, alpha, y and beta, in that order.

19.83.2 Member Typedef Documentation

```
19.83.2.1 ParamValues
typedef Snippet::ValueBase< 4 > NeuronModels::RulkovMap::ParamValues
19.83.2.2 PostVarValues
typedef Models::VarInitContainerBase<0> NeuronModels::RulkovMap::PostVarValues
19.83.2.3 PreVarValues
typedef Models::VarInitContainerBase<0> NeuronModels::RulkovMap::PreVarValues
19.83.2.4 VarValues
typedef Models::VarInitContainerBase< 2 > NeuronModels::RulkovMap::VarValues
19.83.3 Member Function Documentation
19.83.3.1 getDerivedParams()
virtual DerivedParamVec NeuronModels::RulkovMap::getDerivedParams ( ) const [inline], [override],
[virtual]
Gets names of derived model parameters and the function objects to call to Calculate their value from a vector of
model parameter values
Reimplemented from Snippet::Base.
19.83.3.2 getInstance()
static const NeuronModels::RulkovMap* NeuronModels::RulkovMap::getInstance ( ) [inline], [static]
19.83.3.3 getParamNames()
virtual StringVec NeuronModels::RulkovMap::getParamNames ( ) const [inline], [override],
[virtual]
Gets names of of (independent) model parameters.
Reimplemented from Snippet::Base.
```

19.83.3.4 getSimCode()

virtual std::string NeuronModels::RulkovMap::getSimCode () const [inline], [override], [virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN",

i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.83.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::RulkovMap::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.83.3.6 getVars()

```
virtual VarVec NeuronModels::RulkovMap::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.


The documentation for this class was generated from the following file:

neuronModels.h

19.84 SpineMLSimulator::InputValue::ScalarBase Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::ScalarBase:



Protected Member Functions

- ScalarBase (unsigned int numNeurons, const pugi::xml_node &node)
- void applyScalar (double value, std::function< void(unsigned int, double)> applyValueFunc) const

Additional Inherited Members

19.84.1 Constructor & Destructor Documentation

19.84.1.1 ScalarBase()

19.84.2 Member Function Documentation

19.84.2.1 applyScalar()

The documentation for this class was generated from the following files:

- inputValue.h
- · inputValue.cc

19.85 CodeGenerator::CodeStream::Scope Class Reference

```
#include <codeStream.h>
```

Public Member Functions

- Scope (CodeStream &codeStream)
- ~Scope ()

19.85.1 Constructor & Destructor Documentation

```
19.85.1.1 Scope()
```

The documentation for this class was generated from the following files:

- · codeStream.h
- codeStream.cc

19.86 SharedLibraryModel < scalar > Class Template Reference

```
#include <sharedLibraryModel.h>
```

Public Member Functions

- SharedLibraryModel ()
- SharedLibraryModel (const std::string &pathToModel, const std::string &modelName)
- virtual ~SharedLibraryModel ()
- bool open (const std::string &pathToModel, const std::string &modelName)
- void allocateExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- void freeExtraGlobalParam (const std::string &popName, const std::string &varName)

- void pullStateFromDevice (const std::string &popName)
- void pullSpikesFromDevice (const std::string &popName)
- void pullCurrentSpikesFromDevice (const std::string &popName)
- void pullConnectivityFromDevice (const std::string &popName)
- void pullVarFromDevice (const std::string &popName, const std::string &varName)
- void pullExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- void pushStateToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushSpikesToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushCurrentSpikesToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushConnectivityToDevice (const std::string &popName, bool uninitialisedOnly=false)
- void pushVarToDevice (const std::string &popName, const std::string &varName, bool uninitialisedOnly=false)
- void pushExtraGlobalParam (const std::string &popName, const std::string &varName, unsigned int count)
- template<typename T >

T * getArray (const std::string &varName)

• template<typename T >

T * getScalar (const std::string &varName)

- void allocateMem ()
- void freeMem ()
- size t getFreeDeviceMemBytes ()
- · void initialize ()
- void initializeSparse ()
- void stepTime ()
- scalar getTime () const
- unsigned long long getTimestep () const
- void setTime (scalar t)
- void setTimestep (unsigned long long iT)
- double getNeuronUpdateTime () const
- double getInitTime () const
- double getPresynapticUpdateTime () const
- double getPostsynapticUpdateTime () const
- double getSynapseDynamicsTime () const
- · double getInitSparseTime () const
- void * getSymbol (const std::string &symbolName, bool allowMissing=false, void *defaultSymbol=nullptr) const

19.86.1 Constructor & Destructor Documentation

```
19.86.1.3 ∼SharedLibraryModel()
template<typename scalar = float>
virtual SharedLibraryModel < scalar >::~SharedLibraryModel ( ) [inline], [virtual]
19.86.2 Member Function Documentation
19.86.2.1 allocateExtraGlobalParam()
template<typename scalar = float>
void SharedLibraryModel< scalar >::allocateExtraGlobalParam (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.86.2.2 allocateMem()
template<typename scalar = float>
void SharedLibraryModel< scalar >::allocateMem ( ) [inline]
19.86.2.3 freeExtraGlobalParam()
template<typename scalar = float>
void SharedLibraryModel< scalar >::freeExtraGlobalParam (
             const std::string & popName,
             const std::string & varName ) [inline]
19.86.2.4 freeMem()
template<typename scalar = float>
void SharedLibraryModel< scalar >::freeMem ( ) [inline]
19.86.2.5 getArray()
template<typename scalar = float>
{\tt template}{<}{\tt typename}\ {\tt T}\ >
T* SharedLibraryModel< scalar >::getArray (
             const std::string & varName ) [inline]
19.86.2.6 getFreeDeviceMemBytes()
template<typename scalar = float>
\verb|size_t SharedLibraryModel| < \verb|scalar| > ::: getFreeDeviceMemBytes () [inline]|
19.86.2.7 getInitSparseTime()
```

double SharedLibraryModel< scalar >::getInitSparseTime () const [inline]

 ${\tt template}{<}{\tt typename scalar = float}{>}$

```
19.86.2.8 getInitTime()
template<typename scalar = float>
double SharedLibraryModel< scalar >::getInitTime ( ) const [inline]
19.86.2.9 getNeuronUpdateTime()
template<typename scalar = float>
double SharedLibraryModel< scalar >::getNeuronUpdateTime ( ) const [inline]
19.86.2.10 getPostsynapticUpdateTime()
template<typename scalar = float>
double SharedLibraryModel< scalar >::getPostsynapticUpdateTime ( ) const [inline]
19.86.2.11 getPresynapticUpdateTime()
template<typename scalar = float>
double SharedLibraryModel< scalar >::getPresynapticUpdateTime ( ) const [inline]
19.86.2.12 getScalar()
template<typename scalar = float>
{\tt template}{<}{\tt typename}\ {\tt T}\ >
T* SharedLibraryModel< scalar >::getScalar (
             const std::string & varName ) [inline]
19.86.2.13 getSymbol()
template<typename scalar = float>
void* SharedLibraryModel< scalar >::getSymbol (
             const std::string & symbolName,
             bool allowMissing = false,
             void * defaultSymbol = nullptr ) const [inline]
19.86.2.14 getSynapseDynamicsTime()
template<typename scalar = float>
double SharedLibraryModel< scalar >::getSynapseDynamicsTime ( ) const [inline]
19.86.2.15 getTime()
template<typename scalar = float>
scalar SharedLibraryModel< scalar >::getTime ( ) const [inline]
```

```
19.86.2.16 getTimestep()
template<typename scalar = float>
unsigned long long SharedLibraryModel< scalar >::getTimestep ( ) const [inline]
19.86.2.17 initialize()
template<typename scalar = float>
void SharedLibraryModel< scalar >::initialize ( ) [inline]
19.86.2.18 initializeSparse()
template<typename scalar = float>
void SharedLibraryModel< scalar >::initializeSparse ( ) [inline]
19.86.2.19 open()
template<typename scalar = float>
bool SharedLibraryModel< scalar >::open (
             const std::string & pathToModel,
             const std::string & modelName ) [inline]
19.86.2.20 pullConnectivityFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullConnectivityFromDevice (
             const std::string & popName ) [inline]
19.86.2.21 pullCurrentSpikesFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullCurrentSpikesFromDevice (
             const std::string & popName ) [inline]
19.86.2.22 pullExtraGlobalParam()
{\tt template}{<}{\tt typename} \ {\tt scalar} = {\tt float}{>}
void SharedLibraryModel< scalar >::pullExtraGlobalParam (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.86.2.23 pullSpikesFromDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullSpikesFromDevice (
             const std::string & popName ) [inline]
```

```
19.86.2.24 pullStateFromDevice()
```

```
template<typename scalar = float>
void SharedLibraryModel< scalar >::pullStateFromDevice (
             const std::string & popName ) [inline]
19.86.2.25 pullVarFromDevice()
{\tt template}{<}{\tt typename scalar = float}{>}
void SharedLibraryModel< scalar >::pullVarFromDevice (
             const std::string & popName,
             const std::string & varName ) [inline]
19.86.2.26 pushConnectivityToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushConnectivityToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
19.86.2.27 pushCurrentSpikesToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushCurrentSpikesToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
19.86.2.28 pushExtraGlobalParam()
template<typename scalar = float>
\verb|void SharedLibraryModel| < \verb|scalar| >:: pushExtraGlobalParam| (
             const std::string & popName,
             const std::string & varName,
             unsigned int count ) [inline]
19.86.2.29 pushSpikesToDevice()
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushSpikesToDevice (
             const std::string & popName,
             bool uninitialisedOnly = false ) [inline]
```

19.86.2.30 pushStateToDevice()

```
template<typename scalar = float>
void SharedLibraryModel< scalar >::pushStateToDevice (
             const std::string & popName,
             bool \ uninitial is edOnly = false \ ) \quad [inline]
```

19.86.2.31 pushVarToDevice()

void SharedLibraryModel< scalar >::stepTime () [inline]
The documentation for this class was generated from the following file:

· sharedLibraryModel.h

template<typename scalar = float>

19.87 SpineMLSimulator::Simulator Class Reference

```
#include <simulator.h>
```

Public Member Functions

- Simulator (plog::Severity logLevel=plog::warning)
- Simulator (const std::string &experimentXML, const std::string &overrideOutputPath="", plog::Severity log
 Level=plog::warning)
- ∼Simulator ()
- void load (const std::string &experimentXML, const std::string &overrideOutputPath="")

Load model from XML file.

void stepTime ()

Advance simulation by one timestep.

• const LogOutput::AnalogueExternal * getExternalLogger (const std::string &name) const

Get an external logger by name.

• InputValue::External * getExternalInput (const std::string &name) const

Get an external input by name.

• double getDT () const

Get the simulation timestep (in ms)

· double getDurationMs () const

Get duration of simulation read from experiment in ms.

double getInputMs () const

Get the total times accumulated in each stage of the simulation.

- double getSimulateMs () const
- double getLogMs () const
- double getNeuronUpdateTime () const

Timings of individual kernels provided by GeNN.

- double getInitTime () const
- double getPresynapticUpdateTime () const
- double getPostsynapticUpdateTime () const
- double getSynapseDynamicsTime () const
- double getInitSparseTime () const
- unsigned long long calcNumTimesteps () const

Calculate duration of simulation read from experiment in timesteps.

19.87.1 Constructor & Destructor Documentation

```
19.87.1.1 Simulator() [1/2]
SpineMLSimulator::Simulator::Simulator (
              plog::Severity logLevel = plog::warning )
19.87.1.2 Simulator() [2/2]
SpineMLSimulator::Simulator::Simulator (
              const std::string & experimentXML,
              const std::string & overrideOutputPath = "",
              plog::Severity logLevel = plog::warning )
19.87.1.3 \simSimulator()
SpineMLSimulator::Simulator::~Simulator ( )
19.87.2 Member Function Documentation
19.87.2.1 calcNumTimesteps()
unsigned long long SpineMLSimulator::Simulator::calcNumTimesteps ( ) const [inline]
Calculate duration of simulation read from experiment in timesteps.
19.87.2.2 getDT()
double SpineMLSimulator::Simulator::getDT ( ) const [inline]
Get the simulation timestep (in ms)
19.87.2.3 getDurationMs()
```

double SpineMLSimulator::Simulator::getDurationMs () const [inline]

Get duration of simulation read from experiment in ms.

```
19.87.2.4 getExternalInput()
InputValue::External * SpineMLSimulator::Simulator::getExternalInput (
              const std::string & name ) const
Get an external input by name.
19.87.2.5 getExternalLogger()
const LogOutput::AnalogueExternal * SpineMLSimulator::Simulator::getExternalLogger (
              const std::string & name ) const
Get an external logger by name.
19.87.2.6 getInitSparseTime()
double SpineMLSimulator::Simulator::getInitSparseTime ( ) const
19.87.2.7 getInitTime()
double SpineMLSimulator::Simulator::getInitTime ( ) const
19.87.2.8 getInputMs()
double SpineMLSimulator::Simulator::getInputMs ( ) const [inline]
Get the total times accumulated in each stage of the simulation.
19.87.2.9 getLogMs()
double SpineMLSimulator::Simulator::getLogMs ( ) const [inline]
19.87.2.10 getNeuronUpdateTime()
\verb|double SpineMLSimulator::getNeuronUpdateTime () const|\\
Timings of individual kernels provided by GeNN.
19.87.2.11 getPostsynapticUpdateTime()
double SpineMLSimulator::Simulator::getPostsynapticUpdateTime ( ) const
19.87.2.12 getPresynapticUpdateTime()
double SpineMLSimulator::Simulator::getPresynapticUpdateTime ( ) const
```

19.87.2.13 getSimulateMs()

```
double SpineMLSimulator::Simulator::getSimulateMs ( ) const [inline]
```

19.87.2.14 getSynapseDynamicsTime()

```
double SpineMLSimulator::Simulator::getSynapseDynamicsTime ( ) const
```

19.87.2.15 load()

Load model from XML file.

19.87.2.16 stepTime()

```
void SpineMLSimulator::Simulator::stepTime ( )
```

Advance simulation by one timestep.


The documentation for this class was generated from the following files:

- · simulator.h
- · simulator.cc

19.88 SpineMLSimulator::Input::SpikeBase Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::SpikeBase:



Protected Types

typedef void(* PushCurrentSpikesFunc) ()

Protected Member Functions

- SpikeBase (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, Push
 CurrentSpikesFunc pushCurrentSpikes)
- void injectSpike (unsigned int neuronID)
- void uploadSpikes ()

Additional Inherited Members

19.88.1 Member Typedef Documentation

19.88.1.1 PushCurrentSpikesFunc

```
typedef void(* SpineMLSimulator::Input::SpikeBase::PushCurrentSpikesFunc) () [protected]
```

19.88.2 Constructor & Destructor Documentation

19.88.2.1 SpikeBase()

19.88.3 Member Function Documentation

19.88.3.1 injectSpike()

19.88.3.2 uploadSpikes()

```
void SpineMLSimulator::Input::SpikeBase::uploadSpikes ( ) [protected]
```

The documentation for this class was generated from the following files:


- input.h
- · input.cc

19.89 SpikeRecorder < Writer > Class Template Reference

Class to read spikes from neuron groups.

```
#include <spikeRecorder.h>
```

Inheritance diagram for SpikeRecorder < Writer >:



Public Types

- typedef unsigned int &(* GetCurrentSpikeCountFunc) ()
- typedef unsigned int *(* GetCurrentSpikesFunc) ()

Public Member Functions

- template<typename... WriterArgs>
 SpikeRecorder (GetCurrentSpikesFunc getCurrentSpikes, GetCurrentSpikeCountFunc getCurrentSpike←
 Count, WriterArgs &&... writerArgs)
- void record (double t)
- · unsigned int getSum () const

19.89.1 Detailed Description

```
\label{template} \mbox{template} < \mbox{typename Writer} = \mbox{SpikeWriterText} > \\ \mbox{class SpikeRecorder} < \mbox{Writer} > \\
```

Class to read spikes from neuron groups.

19.89.2 Member Typedef Documentation

19.89.2.1 GetCurrentSpikeCountFunc

```
template<typename Writer = SpikeWriterText>
typedef unsigned int&(* SpikeRecorder< Writer >::GetCurrentSpikeCountFunc) ()
```

19.89.2.2 GetCurrentSpikesFunc

```
template<typename Writer = SpikeWriterText>
typedef unsigned int*(* SpikeRecorder< Writer >::GetCurrentSpikesFunc) ()
```

19.89.3 Constructor & Destructor Documentation

19.89.3.1 SpikeRecorder()

19.89.4 Member Function Documentation

19.89.4.1 getSum() template<typename Writer = SpikeWriterText> unsigned int SpikeRecorder< Writer >::getSum () const [inline] 19.89.4.2 record() template<typename Writer = SpikeWriterText> void SpikeRecorder< Writer >::record (

The documentation for this class was generated from the following file:

· spikeRecorder.h


19.90 NeuronModels::SpikeSource Class Reference

double t) [inline]

Empty neuron which allows setting spikes from external sources.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::SpikeSource:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 0 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getThresholdConditionCode () const override
 Gets code which defines the condition for a true spike in the described neuron model.
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

• static const NeuronModels::SpikeSource * getInstance ()

Additional Inherited Members

19.90.1 Detailed Description

Empty neuron which allows setting spikes from external sources.

This model does not contain any update code and can be used to implement the equivalent of a SpikeGenerator Group in Brian or a SpikeSourceArray in PyNN.

19.90.2 Member Typedef Documentation

```
19.90.2.1 ParamValues
```

```
typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSource::ParamValues
```

19.90.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PostVarValues
```

19.90.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSource::PreVarValues
```

19.90.2.4 VarValues

```
typedef Models::VarInitContainerBase< 0 > NeuronModels::SpikeSource::VarValues
```

19.90.3 Member Function Documentation

19.90.3.1 getInstance()

```
static const NeuronModels::SpikeSource* NeuronModels::SpikeSource::getInstance ( ) [inline],
[static]
```

19.90.3.2 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSource::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.90.3.3 SET_NEEDS_AUTO_REFRACTORY()

The documentation for this class was generated from the following file:


· neuronModels.h

19.91 NeuronModels::SpikeSourceArray Class Reference

Spike source array.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::SpikeSourceArray:



Public Types

- typedef Snippet::ValueBase< 0 > ParamValues
- typedef Models::VarInitContainerBase< 2 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

· virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

· virtual std::string getResetCode () const override

Gets code that defines the reset action taken after a spike occurred. This can be empty.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

- · virtual EGPVec getExtraGlobalParams () const override
- SET_NEEDS_AUTO_REFRACTORY (false)

Static Public Member Functions

static const NeuronModels::SpikeSourceArray * getInstance ()

Additional Inherited Members

19.91.1 Detailed Description

Spike source array.

A neuron which reads spike times from a global spikes array It has 2 variables:

- startSpike Index of the next spike in the global array
- endSpike Index of the spike next to the last in the globel array

and 1 global parameter:

• spikeTimes - Array with all spike times

19.91.2 Member Typedef Documentation

19.91.2.1 ParamValues

```
typedef Snippet::ValueBase< 0 > NeuronModels::SpikeSourceArray::ParamValues
```

19.91.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PostVarValues
```

19.91.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::SpikeSourceArray::PreVarValues
```

19.91.2.4 VarValues

```
typedef Models::VarInitContainerBase< 2 > NeuronModels::SpikeSourceArray::VarValues
```

19.91.3 Member Function Documentation

19.91.3.1 getExtraGlobalParams()

```
virtual EGPVec NeuronModels::SpikeSourceArray::getExtraGlobalParams ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of additional per-population parameters for the weight update model.

Reimplemented from Models::Base.

19.91.3.2 getInstance()

```
static const NeuronModels::SpikeSourceArray* NeuronModels::SpikeSourceArray::getInstance ( )
[inline], [static]
```

19.91.3.3 getResetCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getResetCode ( ) const [inline], [override],
[virtual]
```

Gets code that defines the reset action taken after a spike occurred. This can be empty.

Reimplemented from NeuronModels::Base.

19.91.3.4 getSimCode()

virtual std::string NeuronModels::SpikeSourceArray::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

19.91.3.5 getThresholdConditionCode()

```
virtual std::string NeuronModels::SpikeSourceArray::getThresholdConditionCode ( ) const [inline],
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.91.3.6 getVars()

```
virtual VarVec NeuronModels::SpikeSourceArray::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

19.91.3.7 SET_NEEDS_AUTO_REFRACTORY()


The documentation for this class was generated from the following file:

• neuronModels.h

19.92 SpineMLSimulator::Input::SpikeTime Class Reference

```
#include <input.h>
```

Inheritance diagram for SpineMLSimulator::Input::SpikeTime:



Public Member Functions

- SpikeTime (double dt, const pugi::xml_node &node, std::unique_ptr< InputValue::Base > value, unsigned int popSize, unsigned int *spikeQueuePtr, unsigned int *hostSpikeCount, unsigned int *hostSpikes, Push
 CurrentSpikesFunc pushCurrentSpikes)
- · virtual void apply (double dt, unsigned long long timestep) override

Additional Inherited Members

19.92.1 Constructor & Destructor Documentation

19.92.1.1 SpikeTime()

19.92.2 Member Function Documentation

19.92.2.1 apply()

Implements SpineMLSimulator::Input::Base.

The documentation for this class was generated from the following files:

- input.h
- · input.cc

19.93 SpikeWriterText Class Reference

Class to write spikes to text file.

```
#include <spikeRecorder.h>
```

Public Member Functions

SpikeWriterText (const std::string &filename, const std::string &delimiter=" ", bool header=false)

Protected Member Functions

• void recordSpikes (double t, unsigned int spikeCount, const unsigned int *currentSpikes)

19.93.1 Detailed Description

Class to write spikes to text file.

19.93.2 Constructor & Destructor Documentation

19.93.2.1 SpikeWriterText()

```
SpikeWriterText::SpikeWriterText (
    const std::string & filename,
    const std::string & delimiter = " ",
    bool header = false ) [inline]
```

19.93.3 Member Function Documentation

19.93.3.1 recordSpikes()

The documentation for this class was generated from the following file:

• spikeRecorder.h

19.94 SpikeWriterTextCached Class Reference

Class to write spikes to text file, caching in memory before writing.

```
#include <spikeRecorder.h>
```

Public Member Functions

- SpikeWriterTextCached (const std::string &filename, const std::string &delimiter=" ", bool header=false)
- ∼SpikeWriterTextCached ()
- void writeCache ()

Protected Member Functions

• void recordSpikes (double t, unsigned int spikeCount, const unsigned int *currentSpikes)

19.94.1 Detailed Description

Class to write spikes to text file, caching in memory before writing.

19.94.2 Constructor & Destructor Documentation

19.94.2.1 SpikeWriterTextCached()

```
SpikeWriterTextCached::SpikeWriterTextCached (
    const std::string & filename,
    const std::string & delimiter = " ",
    bool header = false ) [inline]
```

19.94.2.2 ∼SpikeWriterTextCached()

```
SpikeWriterTextCached::~SpikeWriterTextCached ( ) [inline]
```

19.94.3 Member Function Documentation

19.94.3.1 recordSpikes()

19.94.3.2 writeCache()

```
void SpikeWriterTextCached::writeCache ( ) [inline]
```

The documentation for this class was generated from the following file:

· spikeRecorder.h

19.95 SpineMLSimulator::StateVar< T > Class Template Reference

```
#include <stateVar.h>
```

Public Member Functions

- bool isAccessible () const
- · void push () const
- void pull () const
- T * get ()
- const T * get () const

19.95.1 Constructor & Destructor Documentation

19.95.1.1 StateVar()

19.95.2 Member Function Documentation

```
19.95.2.1 get() [1/2]
{\tt template}{<}{\tt typename}\ {\tt T}{>}
T* SpineMLSimulator::StateVar< T >::get ( ) [inline]
19.95.2.2 get() [2/2]
template<typename T>
const T* SpineMLSimulator::StateVar< T >::get ( ) const [inline]
19.95.2.3 isAccessible()
{\tt template}{<}{\tt typename}~{\tt T}{>}
bool SpineMLSimulator::StateVar< T >::isAccessible ( ) const [inline]
19.95.2.4 pull()
template<typename T>
void SpineMLSimulator::StateVar< T >::pull () const [inline]
19.95.2.5 push()
template<typename T>
void SpineMLSimulator::StateVar< T >::push ( ) const [inline]
19.95.3 Member Data Documentation
19.95.3.1 m_Direct
{\tt template}{<}{\tt typename}~{\tt T}{>}
Direct SpineMLSimulator::StateVar< T >::m_Direct
19.95.3.2 m_Indirect
template<typename T>
Indirect SpineMLSimulator::StateVar< T >::m_Indirect
The documentation for this class was generated from the following file:
```


stateVar.h

19.96 WeightUpdateModels::StaticGraded Class Reference

Graded-potential, static synapse.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::StaticGraded:



Public Member Functions

- DECLARE_WEIGHT_UPDATE_MODEL (StaticGraded, 2, 1, 0, 0)
- · virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual std::string getEventCode () const override

Gets code run when events (all the instances where event threshold condition is met) are received.

virtual std::string getEventThresholdConditionCode () const override

Gets codes to test for events.

Additional Inherited Members

19.96.1 Detailed Description

Graded-potential, static synapse.

In a graded synapse, the conductance is updated gradually with the rule:

$$gSyn = g * tanh((V - E_{pre})/V_{slope})$$

whenever the membrane potential V is larger than the threshold E_{pre} . The model has 1 variable:

• g: conductance of scalar type

The parameters are:

- Epre: Presynaptic threshold potential
- Vslope: Activation slope of graded release

event code is:

```
\label{local_syn_syn} $$ (addToInSyn, $(g)* tanh(($(V_pre)-($(Epre)))*DT*2/$(Vslope))); $$
```

event threshold condition code is:

```
$(V_pre) > $(Epre)
```

Note

The pre-synaptic variables are referenced with the suffix _pre in synapse related code such as an the event threshold test. Users can also access post-synaptic neuron variables using the suffix _post.

19.96.2 Member Function Documentation

19.96.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.96.2.2 getEventCode()

```
virtual std::string WeightUpdateModels::StaticGraded::getEventCode ( ) const [inline], [override],
[virtual]
```

Gets code run when events (all the instances where event threshold condition is met) are received.

Reimplemented from WeightUpdateModels::Base.

19.96.2.3 getEventThresholdConditionCode()

```
virtual std::string WeightUpdateModels::StaticGraded::getEventThresholdConditionCode ( ) const
[inline], [override], [virtual]
```

Gets codes to test for events.

Reimplemented from WeightUpdateModels::Base.

19.96.2.4 getParamNames()

```
virtual StringVec WeightUpdateModels::StaticGraded::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

19.96.2.5 getVars()

```
virtual VarVec WeightUpdateModels::StaticGraded::getVars ( ) const [inline], [override],
[virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


weightUpdateModels.h

19.97 WeightUpdateModels::StaticPulse Class Reference

Pulse-coupled, static synapse.

```
#include <weightUpdateModels.h>
```

Inheritance diagram for WeightUpdateModels::StaticPulse:



Public Member Functions

- DECLARE_WEIGHT_UPDATE_MODEL (StaticPulse, 0, 1, 0, 0)
- · virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

• virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

Additional Inherited Members

19.97.1 Detailed Description

Pulse-coupled, static synapse.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 1 variable:

• g - conductance of scalar type and no other parameters.

sim code is:

```
"$(addToInSyn, $(g)); \n"
```

19.97.2 Member Function Documentation

19.97.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.97.2.2 getSimCode()

```
virtual std::string WeightUpdateModels::StaticPulse::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.97.2.3 getVars()

virtual VarVec WeightUpdateModels::StaticPulse::getVars () const [inline], [override], [virtual]

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


· weightUpdateModels.h

19.98 WeightUpdateModels::StaticPulseDendriticDelay Class Reference

Pulse-coupled, static synapse with heterogenous dendritic delays.

#include <weightUpdateModels.h>

Inheritance diagram for WeightUpdateModels::StaticPulseDendriticDelay:



Public Member Functions

- DECLARE_WEIGHT_UPDATE_MODEL (StaticPulseDendriticDelay, 0, 2, 0, 0)
- · virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

virtual std::string getSimCode () const override

Gets simulation code run when 'true' spikes are received.

Additional Inherited Members

19.98.1 Detailed Description

Pulse-coupled, static synapse with heterogenous dendritic delays.

No learning rule is applied to the synapse and for each pre-synaptic spikes, the synaptic conductances are simply added to the postsynaptic input variable. The model has 2 variables:

- g conductance of scalar type
- d dendritic delay in timesteps and no other parameters.

sim code is:

" \$(addToInSynDelay, \$(g), \$(d));\n\

19.98.2 Member Function Documentation

19.98.2.1 DECLARE_WEIGHT_UPDATE_MODEL()

19.98.2.2 getSimCode()

```
virtual std::string WeightUpdateModels::StaticPulseDendriticDelay::getSimCode ( ) const [inline],
[override], [virtual]
```

Gets simulation code run when 'true' spikes are received.

Reimplemented from WeightUpdateModels::Base.

19.98.2.3 getVars()

```
virtual VarVec WeightUpdateModels::StaticPulseDendriticDelay::getVars ( ) const [inline],
[override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:

· weightUpdateModels.h

19.99 CodeGenerator::Substitutions Class Reference

```
#include <substitutions.h>
```

Public Member Functions

- Substitutions (const Substitutions *parent=nullptr)
- Substitutions (const std::vector< FunctionTemplate > &functions, const std::string &ftype)
- template<typename T >
 void addVarNameSubstitution (const std::vector< T > &variables, const std::string &sourceSuffix="", const std::string &destPrefix="", const std::string &destSuffix="")
- void addParamNameSubstitution (const std::vector < std::string > ¶mNames, const std::string &source ← Suffix="", const std::string &destPrefix="", const std::string &destSuffix="")
- template<typename T >
 void addVarValueSubstitution (const std::vector< T > &variables, const std::vector< double > &values, const std::string &sourceSuffix="")
- void addParamValueSubstitution (const std::vector< std::string > ¶mNames, const std::vector< double > &values, const std::string &sourceSuffix="")
- void addVarSubstitution (const std::string &source, const std::string &destionation, bool allowOverride=false)
- void addFuncSubstitution (const std::string &source, unsigned int numArguments, const std::string &func
 — Template, bool allowOverride=false)
- bool hasVarSubstitution (const std::string &source) const

- const std::string & getVarSubstitution (const std::string &source) const
- · void apply (std::string &code) const
- void applyCheckUnreplaced (std::string &code, const std::string &context) const
- const std::string operator[] (const std::string &source) const

19.99.1 Constructor & Destructor Documentation

```
19.99.1.1 Substitutions() [1/2]
CodeGenerator::Substitutions::Substitutions (
             const Substitutions * parent = nullptr ) [inline]
19.99.1.2 Substitutions() [2/2]
CodeGenerator::Substitutions::Substitutions (
             const std::vector< FunctionTemplate > & functions,
             const std::string & ftype ) [inline]
19.99.2 Member Function Documentation
19.99.2.1 addFuncSubstitution()
void CodeGenerator::Substitutions::addFuncSubstitution (
             const std::string & source,
             unsigned int numArguments,
             const std::string & funcTemplate,
             bool allowOverride = false ) [inline]
19.99.2.2 addParamNameSubstitution()
void CodeGenerator::Substitutions::addParamNameSubstitution (
             const std::vector< std::string > & paramNames,
             const std::string & sourceSuffix = "",
             const std::string & destPrefix = "",
             const std::string & destSuffix = "" ) [inline]
19.99.2.3 addParamValueSubstitution()
void CodeGenerator::Substitutions::addParamValueSubstitution (
             const std::vector< std::string > & paramNames,
             const std::vector< double > & values,
             const std::string & sourceSuffix = "" ) [inline]
19.99.2.4 addVarNameSubstitution()
template<typename T >
void CodeGenerator::Substitutions::addVarNameSubstitution (
             const std::vector< T > & variables,
```

```
const std::string & sourceSuffix = "",
             const std::string & destPrefix = "",
             const std::string & destSuffix = "" ) [inline]
19.99.2.5 addVarSubstitution()
void CodeGenerator::Substitutions::addVarSubstitution (
             const std::string & source,
             const std::string & destionation,
             bool allowOverride = false ) [inline]
19.99.2.6 addVarValueSubstitution()
template < typename T >
void CodeGenerator::Substitutions::addVarValueSubstitution (
             const std::vector< T > & variables,
             const std::vector< double > & values,
             const std::string & sourceSuffix = "" ) [inline]
19.99.2.7 apply()
void CodeGenerator::Substitutions::apply (
            std::string & code ) const [inline]
19.99.2.8 applyCheckUnreplaced()
void CodeGenerator::Substitutions::applyCheckUnreplaced (
             std::string & code,
             const std::string & context ) const [inline]
19.99.2.9 getVarSubstitution()
const std::string& CodeGenerator::Substitutions::getVarSubstitution (
             const std::string & source ) const [inline]
19.99.2.10 hasVarSubstitution()
bool CodeGenerator::Substitutions::hasVarSubstitution (
             const std::string & source ) const [inline]
19.99.2.11 operator[]()
const std::string CodeGenerator::Substitutions::operator[] (
             const std::string & source ) const [inline]
```


The documentation for this class was generated from the following file:

· substitutions.h

19.100 pygenn.genn_groups.SynapseGroup Class Reference

Class representing synaptic connection between two groups of neurons.

Inheritance diagram for pygenn.genn_groups.SynapseGroup:



Public Member Functions

• def __init__ (self, name)

Init SynapseGroup.

def num synapses (self)

Number of synapses in group.

def weight_update_var_size (self)

Size of each weight update variable.

- def max row length (self)
- def set psm var (self, var name, values)

Set values for a postsynaptic model variable.

def set_pre_var (self, var_name, values)

Set values for a presynaptic variable.

def set_post_var (self, var_name, values)

Set values for a postsynaptic variable.

• def set_weight_update (self, model, param_space, var_space, pre_var_space, post_var_space)

Set weight update model, its parameters and initial variables.

def set_post_syn (self, model, param_space, var_space)

Set postsynaptic model, its parameters and initial variables.

- def get_var_values (self, var_name)
- · def is_connectivity_init_required (self)
- def matrix_type (self)

Type of the projection matrix.

- def matrix_type (self, matrix_type)
- def is_ragged (self)

Tests whether synaptic connectivity uses Ragged format.

def is_bitmask (self)

Tests whether synaptic connectivity uses Bitmask format.

def is_dense (self)

Tests whether synaptic connectivity uses dense format.

• def has_individual_synapse_vars (self)

Tests whether synaptic connectivity has individual weights.

def has_individual_postsynaptic_vars (self)

Tests whether synaptic connectivity has individual postsynaptic model variables.

def set_sparse_connections (self, pre_indices, post_indices)

Set ragged format connections between two groups of neurons.

def get_sparse_pre_inds (self)

Get presynaptic indices of synapse group connections.

```
· def get_sparse_post_inds (self)
```

Get postsynaptic indices of synapse group connections.

def set_connected_populations (self, source, target)

Set two groups of neurons connected by this SynapseGroup.

def add_to (self, model_spec, delay_steps)

Add this SynapseGroup to the a model.

• def add_extra_global_param (self, param_name, param_values)

Set extra global parameter.

def set_extra_global_param (self, param_name, param_values)

Set extra global parameter to weight update model.

def set_psm_extra_global_param (self, param_name, param_values)

Set extra global parameter to postsynaptic model.

• def set_connectivity_extra_global_param (self, param_name, param_values)

Set extra global parameter to connectivity initialisation snippet.

- def load (self, slm, scalar)
- def load_connectivity_init_egps (self, slm, scalar)
- def reinitialise (self, slm, scalar)

Reinitialise synapse group.

Public Attributes

- · connections set
- w_update
- postsyn
- src
- trg
- · psm vars
- · pre_vars
- post_vars
- psm_extra_global_params
- · connectivity_extra_global_params
- · connectivity_initialiser
- synapse_order
- ind
- row_lengths
- pop

19.100.1 Detailed Description

Class representing synaptic connection between two groups of neurons.

19.100.2 Constructor & Destructor Documentation

Init SynapseGroup.

Parameters

name	string name of the group
------	--------------------------

19.100.3 Member Function Documentation

19.100.3.1 add_extra_global_param()

```
def pygenn.genn_groups.SynapseGroup.add_extra_global_param ( self, \\ param_name, \\ param_values )
```

Set extra global parameter.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.100.3.2 add_to()

Add this SynapseGroup to the a model.

Parameters

model_spec	pygenn.genn_model.GeNNModel to add to
delay_steps	number of axonal delay timesteps to simulate for this synapse group

19.100.3.3 get_sparse_post_inds()

Get postsynaptic indices of synapse group connections.

Returns

ndarrays of postsynaptic indices

19.100.3.4 get_sparse_pre_inds()

```
def pygenn.genn_groups.SynapseGroup.get_sparse_pre_inds ( self )
```

Get presynaptic indices of synapse group connections.

Returns

ndarray of presynaptic indices

Tests whether synaptic connectivity has individual postsynaptic model variables.

```
19.100.3.7 has_individual_synapse_vars()
```

self)

```
\label{lem:constraint} $\operatorname{def pygenn.genn\_groups.SynapseGroup.has\_individual\_synapse\_vars} \ ( \\ self \ )
```

Tests whether synaptic connectivity has individual weights.

```
19.100.3.8 is_bitmask()
```

```
\label{lem:constraint}  \mbox{def pygenn.genn\_groups.SynapseGroup.is\_bitmask (} \\ self \mbox{)}
```

Tests whether synaptic connectivity uses Bitmask format.

```
19.100.3.9 is_connectivity_init_required()
```

```
\label{lem:connectivity_init_required} \mbox{def pygenn.genn_groups.SynapseGroup.is\_connectivity\_init\_required (} \\ self \mbox{)}
```

```
19.100.3.10 is_dense()
```

```
\begin{tabular}{ll} $\operatorname{def pygenn.genn\_groups.SynapseGroup.is\_dense} & ( \\ & self ) \end{tabular}
```

Tests whether synaptic connectivity uses dense format.

```
19.100.3.11 is_ragged()
```

Tests whether synaptic connectivity uses Ragged format.

scalar

String specifying "scalar" type

```
19.100.3.12 load()
def pygenn.genn_groups.SynapseGroup.load (
              self,
               slm,
               scalar )
19.100.3.13 load_connectivity_init_egps()
def pygenn.genn_groups.SynapseGroup.load_connectivity_init_egps (
               self,
               slm,
               scalar )
19.100.3.14 matrix_type() [1/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
               self )
Type of the projection matrix.
19.100.3.15 matrix_type() [2/2]
def pygenn.genn_groups.SynapseGroup.matrix_type (
               self,
               matrix_type )
19.100.3.16 max_row_length()
def pygenn.genn_groups.SynapseGroup.max_row_length (
               self )
19.100.3.17 num_synapses()
def pygenn.genn_groups.SynapseGroup.num_synapses (
               self )
Number of synapses in group.
19.100.3.18 reinitialise()
def pygenn.genn_groups.SynapseGroup.reinitialise (
               self,
               slm,
               scalar )
Reinitialise synapse group.
Parameters
          SharedLibraryModel instance for accessing variables
 slm
```

Generated on March 24, 2020 for GeNN by Doxygen

19.100.3.19 set_connected_populations()

```
def pygenn.genn_groups.SynapseGroup.set_connected_populations ( self, \\ source, \\ target \ )
```

Set two groups of neurons connected by this SynapseGroup.

Parameters

source	string name of the presynaptic neuron group
target	string name of the postsynaptic neuron group

19.100.3.20 set_connectivity_extra_global_param()

Set extra global parameter to connectivity initialisation snippet.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.100.3.21 set_extra_global_param()

Set extra global parameter to weight update model.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

19.100.3.22 set_post_syn()

Set postsynaptic model, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables

19.100.3.23 set_post_var()

```
def pygenn.genn_groups.SynapseGroup.set_post_var ( self, \\ var_name, \\ values )
```

Set values for a postsynaptic variable.

Parameters

var_name	string with the name of the presynaptic variable
values	iterable or a single value

19.100.3.24 set_pre_var()

Set values for a presynaptic variable.

Parameters

var_name	string with the name of the presynaptic variable
values	iterable or a single value

19.100.3.25 set_psm_extra_global_param()

Set extra global parameter to postsynaptic model.

Parameters

param_name	string with the name of the extra global parameter
param_values	iterable or a single value

```
19.100.3.26 set_psm_var()
```

Set values for a postsynaptic model variable.

Parameters

var_name	string with the name of the postsynaptic model variable
values	iterable or a single value

19.100.3.27 set_sparse_connections()

```
def pygenn.genn_groups.SynapseGroup.set_sparse_connections ( self, \\ pre\_indices, \\ post\_indices \; )
```

Set ragged format connections between two groups of neurons.

Parameters

pre_indices	ndarray of presynaptic indices
post_indices	ndarray of postsynaptic indices

19.100.3.28 set_weight_update()

Set weight update model, its parameters and initial variables.

Parameters

model	type as string of intance of the model
param_space	dict with model parameters
var_space	dict with model variables
pre_var_space	dict with model presynaptic variables
post_var_space	dict with model postsynaptic variables

19.100.3.29 weight_update_var_size()

```
def pygenn.genn_groups.SynapseGroup.weight_update_var_size (
```

self)

Size of each weight update variable.

19.100.4 Member Data Documentation

19.100.4.1 connections_set

pygenn.genn_groups.SynapseGroup.connections_set

19.100.4.2 connectivity_extra_global_params

 $\verb"pygenn.genn_groups.SynapseGroup.connectivity_extra_global_params"$

19.100.4.3 connectivity_initialiser

 $\verb"pygenn.genn_groups.SynapseGroup.connectivity_initial iser"$

19.100.4.4 ind

pygenn.genn_groups.SynapseGroup.ind

19.100.4.5 pop

pygenn.genn_groups.SynapseGroup.pop

19.100.4.6 post_vars

pygenn.genn_groups.SynapseGroup.post_vars

19.100.4.7 postsyn

 $\verb"pygenn.genn_groups.SynapseGroup.postsyn"$

19.100.4.8 pre_vars

 $\verb"pygenn.genn_groups.SynapseGroup.pre_vars"$

19.100.4.9 psm_extra_global_params

 $\verb"pygenn.genn_groups.SynapseGroup.psm_extra_global_params"$

19.100.4.10 psm_vars

 $\verb"pygenn.genn_groups.SynapseGroup.psm_vars"$

19.100.4.11 row_lengths

pygenn.genn_groups.SynapseGroup.row_lengths

19.100.4.12 src

pygenn.genn_groups.SynapseGroup.src

19.100.4.13 synapse_order

pygenn.genn_groups.SynapseGroup.synapse_order

19.100.4.14 trg

pygenn.genn_groups.SynapseGroup.trg

19.100.4.15 w_update

pygenn.genn_groups.SynapseGroup.w_update


The documentation for this class was generated from the following file:

· genn_groups.py

19.101 SynapseGroup Class Reference

#include <synapseGroup.h>

Inheritance diagram for SynapseGroup:



Public Types

enum SpanType { SpanType::POSTSYNAPTIC, SpanType::PRESYNAPTIC }

Public Member Functions

- SynapseGroup (const SynapseGroup &)=delete
- SynapseGroup ()=delete
- void setWUVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model state variable.

- void setWUPreVarLocation (const std::string &varName, VarLocation loc)
 - Set location of weight update model presynaptic state variable.
- void setWUPostVarLocation (const std::string &varName, VarLocation loc)

Set location of weight update model postsynaptic state variable.

void setWUExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of weight update model extra global parameter.

void setPSVarLocation (const std::string &varName, VarLocation loc)

Set location of postsynaptic model state variable.

void setPSExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of postsynaptic model extra global parameter.

void setSparseConnectivityExtraGlobalParamLocation (const std::string ¶mName, VarLocation loc)

Set location of sparse connectivity initialiser extra global parameter.

void setInSynVarLocation (VarLocation loc)

Set location of variables used to combine input from this synapse group.

void setSparseConnectivityLocation (VarLocation loc)

Set variable mode used for sparse connectivity.

void setDendriticDelayLocation (VarLocation loc)

Set variable mode used for this synapse group's dendritic delay buffers.

void setMaxConnections (unsigned int maxConnections)

Sets the maximum number of target neurons any source neurons can connect to.

void setMaxSourceConnections (unsigned int maxPostConnections)

Sets the maximum number of source neurons any target neuron can connect to.

void setMaxDendriticDelayTimesteps (unsigned int maxDendriticDelay)

Sets the maximum dendritic delay for synapses in this synapse group.

void setSpanType (SpanType spanType)

Set how CUDA implementation is parallelised.

void setNumThreadsPerSpike (unsigned int numThreadsPerSpike)

Set how many threads CUDA implementation uses to process each spike when span type is PRESYNAPTIC.

void setBackPropDelaySteps (unsigned int timesteps)

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

void setNarrowSparseIndEnabled (bool enabled)

Enables or disables using narrow i.e. less than 32-bit types for sparse matrix indices.

- const std::string & getName () const
- SpanType getSpanType () const
- unsigned int getNumThreadsPerSpike () const
- unsigned int getDelaySteps () const
- unsigned int getBackPropDelaySteps () const
- unsigned int getMaxConnections () const
- unsigned int getMaxSourceConnections () const
- unsigned int getMaxDendriticDelayTimesteps () const
- SynapseMatrixType getMatrixType () const
- VarLocation getInSynLocation () const

Get variable mode used for variables used to combine input from this synapse group.

· VarLocation getSparseConnectivityLocation () const

Get variable mode used for sparse connectivity.

VarLocation getDendriticDelayLocation () const

Get variable mode used for this synapse group's dendritic delay buffers.

- int getClusterHostID () const
- bool isTrueSpikeRequired () const

Does synapse group need to handle 'true' spikes.

• bool isSpikeEventRequired () const

Does synapse group need to handle spike-like events.

- const WeightUpdateModels::Base * getWUModel () const
- const std::vector< double > & getWUParams () const
- const std::vector< Models::VarInit > & getWUVarInitialisers () const

- const std::vector< Models::VarInit > & getWUPreVarInitialisers () const
- const std::vector< Models::VarInit > & getWUPostVarInitialisers () const
- const std::vector< double > getWUConstInitVals () const
- const PostsynapticModels::Base * getPSModel () const
- const std::vector< double > & getPSParams () const
- const std::vector< Models::VarInit > & getPSVarInitialisers () const
- const std::vector< double > getPSConstInitVals () const
- const InitSparseConnectivitySnippet::Init & getConnectivityInitialiser () const
- bool isZeroCopyEnabled () const
- VarLocation getWUVarLocation (const std::string &var) const

Get location of weight update model per-synapse state variable by name.

VarLocation getWUVarLocation (size t index) const

Get location of weight update model per-synapse state variable by index.

VarLocation getWUPreVarLocation (const std::string &var) const

Get location of weight update model presynaptic state variable by name.

VarLocation getWUPreVarLocation (size_t index) const

Get location of weight update model presynaptic state variable by index.

VarLocation getWUPostVarLocation (const std::string &var) const

Get location of weight update model postsynaptic state variable by name.

VarLocation getWUPostVarLocation (size_t index) const

Get location of weight update model postsynaptic state variable by index.

• VarLocation getWUExtraGlobalParamLocation (const std::string ¶mName) const

Get location of weight update model extra global parameter by name.

VarLocation getWUExtraGlobalParamLocation (size_t index) const

Get location of weight update model extra global parameter by index.

VarLocation getPSVarLocation (const std::string &var) const

Get location of postsynaptic model state variable.

VarLocation getPSVarLocation (size_t index) const

Get location of postsynaptic model state variable.

VarLocation getPSExtraGlobalParamLocation (const std::string ¶mName) const

Get location of postsynaptic model extra global parameter by name.

VarLocation getPSExtraGlobalParamLocation (size_t index) const

Get location of postsynaptic model extra global parameter by index.

VarLocation getSparseConnectivityExtraGlobalParamLocation (const std::string ¶mName) const

Get location of sparse connectivity initialiser extra global parameter by name.

VarLocation getSparseConnectivityExtraGlobalParamLocation (size_t index) const

Get location of sparse connectivity initialiser extra global parameter by index.

• bool isDendriticDelayRequired () const

Does this synapse group require dendritic delay?

· bool isProceduralConnectivityRNGRequired () const

Does this synapse group require an RNG to generate procedural connectivity?

· bool isPSInitRNGRequired () const

Does this synapse group require an RNG for it's postsynaptic init code?

· bool isWUInitRNGRequired () const

Does this synapse group require an RNG for it's weight update init code?

bool isWUVarInitRequired () const

Is var init code required for any variables in this synapse group's weight update model?

bool isSparseConnectivityInitRequired () const

Is sparse connectivity initialisation code required for this synapse group?

Protected Member Functions

- SynapseGroup (const std::string name, SynapseMatrixType matrixType, unsigned int delaySteps, const WeightUpdateModels::Base *wu, const std::vector< double > &wuParams, const std::vector< Models::~VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &wuPostVarInitialisers, const PostsynapticModels::Base *ps, const std::vector< double > &psParams, const std::vector< Models::VarInit > &psVarInitialisers, NeuronGroupInternal *srcNeuronGroup, NeuronGroupInternal *trgNeuronGroup, const InitSparseConnectivitySnippet::Init &connectivityInitialiser, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, VarLocation defaultSparse
 ConnectivityLocation, bool defaultNarrowSparseIndEnabled)
- NeuronGroupInternal * getSrcNeuronGroup ()
- NeuronGroupInternal * getTrgNeuronGroup ()
- void setEventThresholdReTestRequired (bool req)
- void setPSModelMergeTarget (const std::string &targetName)
- void initDerivedParams (double dt)
- const NeuronGroupInternal * getSrcNeuronGroup () const
- const NeuronGroupInternal * getTrgNeuronGroup () const
- const std::vector< double > & getWUDerivedParams () const
- const std::vector< double > & getPSDerivedParams () const

Does the event threshold needs to be retested in the synapse kernel?

- bool isEventThresholdReTestRequired () const
- const std::string & getPSModelTargetName () const
- bool isPSModelMerged () const
- std::string getPresynapticAxonalDelaySlot (const std::string &devPrefix) const
- std::string getPostsynapticBackPropDelaySlot (const std::string &devPrefix) const
- std::string getDendriticDelayOffset (const std::string &devPrefix, const std::string &offset="") const
- std::string getSparseIndType () const

Get the type to use for sparse connectivity indices for synapse group.

19.101.1 Member Enumeration Documentation

19.101.1.1 SpanType

```
enum SynapseGroup::SpanType [strong]
```

Enumerator

POSTSYNAPTIC PRESYNAPTIC

19.101.2 Constructor & Destructor Documentation

```
19.101.2.1 SynapseGroup() [1/3]
```

```
SynapseGroup::SynapseGroup (

const SynapseGroup & ) [delete]
```

```
19.101.2.2 SynapseGroup() [2/3]
SynapseGroup::SynapseGroup ( ) [delete]
19.101.2.3 SynapseGroup() [3/3]
SynapseGroup::SynapseGroup (
             const std::string name,
             SynapseMatrixType matrixType,
             unsigned int delaySteps,
             const WeightUpdateModels::Base * wu,
             const std::vector< double > & wuParams,
             const std::vector< Models::VarInit > & wuVarInitialisers,
             const std::vector< Models::VarInit > & wuPreVarInitialisers,
             const std::vector< Models::VarInit > & wuPostVarInitialisers,
             const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trgNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation,
             bool defaultNarrowSparseIndEnabled ) [protected]
19.101.3 Member Function Documentation
19.101.3.1 getBackPropDelaySteps()
unsigned int SynapseGroup::getBackPropDelaySteps ( ) const [inline]
19.101.3.2 getClusterHostID()
int SynapseGroup::getClusterHostID ( ) const
19.101.3.3 getConnectivityInitialiser()
const InitSparseConnectivitySnippet::Init& SynapseGroup::getConnectivityInitialiser ( ) const
[inline]
19.101.3.4 getDelaySteps()
unsigned int SynapseGroup::getDelaySteps ( ) const [inline]
19.101.3.5 getDendriticDelayLocation()
VarLocation SynapseGroup::getDendriticDelayLocation () const [inline]
```

Get variable mode used for this synapse group's dendritic delay buffers.

```
19.101.3.6 getDendriticDelayOffset()
std::string SynapseGroup::getDendriticDelayOffset (
             const std::string & devPrefix,
              const std::string & offset = "" ) const [protected]
19.101.3.7 getInSynLocation()
VarLocation SynapseGroup::getInSynLocation ( ) const [inline]
Get variable mode used for variables used to combine input from this synapse group.
19.101.3.8 getMatrixType()
SynapseMatrixType SynapseGroup::getMatrixType ( ) const [inline]
19.101.3.9 getMaxConnections()
unsigned int SynapseGroup::getMaxConnections ( ) const [inline]
19.101.3.10 getMaxDendriticDelayTimesteps()
unsigned int SynapseGroup::getMaxDendriticDelayTimesteps ( ) const [inline]
19.101.3.11 getMaxSourceConnections()
unsigned int SynapseGroup::getMaxSourceConnections ( ) const [inline]
19.101.3.12 getName()
const std::string& SynapseGroup::getName ( ) const [inline]
19.101.3.13 getNumThreadsPerSpike()
unsigned int SynapseGroup::getNumThreadsPerSpike ( ) const [inline]
19.101.3.14 getPostsynapticBackPropDelaySlot()
std::string SynapseGroup::getPostsynapticBackPropDelaySlot (
              const std::string & devPrefix ) const [protected]
Get the expression to calculate the delay slot for accessing Postsynaptic neuron state variables, taking into account
back propagation delay
19.101.3.15 getPresynapticAxonalDelaySlot()
```

std::string SynapseGroup::getPresynapticAxonalDelaySlot (

const std::string & devPrefix) const [protected]

Get the expression to calculate the delay slot for accessing Presynaptic neuron state variables, taking into account axonal delay

```
19.101.3.16 getPSConstInitVals()
const std::vector< double > SynapseGroup::getPSConstInitVals ( ) const
19.101.3.17 getPSDerivedParams()
\verb|const| std::vector<| double>| \& SynapseGroup::getPSDerivedParams () const [inline]|, [protected]| \\
Does the event threshold needs to be retested in the synapse kernel?
19.101.3.18 getPSExtraGlobalParamLocation() [1/2]
VarLocation SynapseGroup::getPSExtraGlobalParamLocation (
              const std::string & paramName ) const
Get location of postsynaptic model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.101.3.19 getPSExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getPSExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of postsynaptic model extra global parameter by index.
This is only used by extra global parameters which are pointers
19.101.3.20 getPSModel()
const PostsynapticModels::Base* SynapseGroup::getPSModel ( ) const [inline]
19.101.3.21 getPSModelTargetName()
const std::string& SynapseGroup::getPSModelTargetName ( ) const [inline], [protected]
19.101.3.22 getPSParams()
const std::vector<double>& SynapseGroup::getPSParams ( ) const [inline]
19.101.3.23 getPSVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getPSVarInitialisers ( ) const [inline]
19.101.3.24 getPSVarLocation() [1/2]
VarLocation SynapseGroup::getPSVarLocation (
              const std::string & var ) const
```

Get location of postsynaptic model state variable.

```
19.101.3.25 getPSVarLocation() [2/2]
VarLocation SynapseGroup::getPSVarLocation (
              size_t index ) const [inline]
Get location of postsynaptic model state variable.
19.101.3.26 getSpanType()
SpanType SynapseGroup::getSpanType ( ) const [inline]
19.101.3.27 getSparseConnectivityExtraGlobalParamLocation() [1/2]
{\tt VarLocation} \  \, {\tt SynapseGroup::} {\tt getSparseConnectivityExtraGlobalParamLocation} \  \, (
              const std::string & paramName ) const
Get location of sparse connectivity initialiser extra global parameter by name.
This is only used by extra global parameters which are pointers
19.101.3.28 getSparseConnectivityExtraGlobalParamLocation() [2/2]
{\tt VarLocation}\ {\tt SynapseGroup::getSparseConnectivityExtraGlobalParamLocation}\ (
              size_t index ) const [inline]
Get location of sparse connectivity initialiser extra global parameter by index.
This is only used by extra global parameters which are pointers
19.101.3.29 getSparseConnectivityLocation()
VarLocation SynapseGroup::getSparseConnectivityLocation ( ) const [inline]
Get variable mode used for sparse connectivity.
19.101.3.30 getSparseIndType()
std::string SynapseGroup::getSparseIndType ( ) const [protected]
Get the type to use for sparse connectivity indices for synapse group.
19.101.3.31 getSrcNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) [inline], [protected]
19.101.3.32 getSrcNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getSrcNeuronGroup ( ) const [inline], [protected]
19.101.3.33 getTrgNeuronGroup() [1/2]
NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) [inline], [protected]
```

```
19.101.3.34 getTrgNeuronGroup() [2/2]
const NeuronGroupInternal* SynapseGroup::getTrgNeuronGroup ( ) const [inline], [protected]
19.101.3.35 getWUConstInitVals()
const std::vector< double > SynapseGroup::getWUConstInitVals ( ) const
19.101.3.36 getWUDerivedParams()
const std::vector<double>& SynapseGroup::getWUDerivedParams ( ) const [inline], [protected]
19.101.3.37 getWUExtraGlobalParamLocation() [1/2]
\label{lem:varLocation} \textbf{VarLocation SynapseGroup::} \textbf{getWUExtraGlobalParamLocation (}
              const std::string & paramName ) const
Get location of weight update model extra global parameter by name.
This is only used by extra global parameters which are pointers
19.101.3.38 getWUExtraGlobalParamLocation() [2/2]
VarLocation SynapseGroup::getWUExtraGlobalParamLocation (
              size_t index ) const [inline]
Get location of weight update model extra global parameter by index.
This is only used by extra global parameters which are pointers
19.101.3.39 getWUModel()
const WeightUpdateModels::Base* SynapseGroup::getWUModel ( ) const [inline]
19.101.3.40 getWUParams()
const std::vector<double>& SynapseGroup::getWUParams ( ) const [inline]
19.101.3.41 getWUPostVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUPostVarInitialisers ( ) const [inline]
19.101.3.42 getWUPostVarLocation() [1/2]
VarLocation SynapseGroup::getWUPostVarLocation (
              const std::string & var ) const
Get location of weight update model postsynaptic state variable by name.
19.101.3.43 getWUPostVarLocation() [2/2]
VarLocation SynapseGroup::getWUPostVarLocation (
              size_t index ) const [inline]
```

Get location of weight update model postsynaptic state variable by index.

Does this synapse group require dendritic delay?

```
19.101.3.44 getWUPreVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUPreVarInitialisers ( ) const [inline]
19.101.3.45 getWUPreVarLocation() [1/2]
VarLocation SynapseGroup::getWUPreVarLocation (
             const std::string & var ) const
Get location of weight update model presynaptic state variable by name.
19.101.3.46 getWUPreVarLocation() [2/2]
VarLocation SynapseGroup::getWUPreVarLocation (
              size_t index ) const [inline]
Get location of weight update model presynaptic state variable by index.
19.101.3.47 getWUVarInitialisers()
const std::vector<Models::VarInit>& SynapseGroup::getWUVarInitialisers ( ) const [inline]
19.101.3.48 getWUVarLocation() [1/2]
VarLocation SynapseGroup::getWUVarLocation (
              const std::string & var ) const
Get location of weight update model per-synapse state variable by name.
19.101.3.49 getWUVarLocation() [2/2]
VarLocation SynapseGroup::getWUVarLocation (
              size_t index ) const [inline]
Get location of weight update model per-synapse state variable by index.
19.101.3.50 initDerivedParams()
void SynapseGroup::initDerivedParams (
              double dt ) [protected]
19.101.3.51 isDendriticDelayRequired()
bool SynapseGroup::isDendriticDelayRequired ( ) const
```

```
19.101.3.52 isEventThresholdReTestRequired()
bool SynapseGroup::isEventThresholdReTestRequired ( ) const [inline], [protected]
This is required when the pre-synaptic neuron population's outgoing synapse groups require different event thresh-
19.101.3.53 isProceduralConnectivityRNGRequired()
bool SynapseGroup::isProceduralConnectivityRNGRequired ( ) const
Does this synapse group require an RNG to generate procedural connectivity?
19.101.3.54 isPSInitRNGRequired()
bool SynapseGroup::isPSInitRNGRequired ( ) const
Does this synapse group require an RNG for it's postsynaptic init code?
19.101.3.55 isPSModelMerged()
bool SynapseGroup::isPSModelMerged ( ) const [inline], [protected]
19.101.3.56 isSparseConnectivityInitRequired()
\verb|bool SynapseGroup::isSparseConnectivityInitRequired () const
Is sparse connectivity initialisation code required for this synapse group?
19.101.3.57 isSpikeEventRequired()
bool SynapseGroup::isSpikeEventRequired ( ) const
Does synapse group need to handle spike-like events.
19.101.3.58 isTrueSpikeRequired()
bool SynapseGroup::isTrueSpikeRequired ( ) const
Does synapse group need to handle 'true' spikes.
19.101.3.59 isWUInitRNGRequired()
bool SynapseGroup::isWUInitRNGRequired ( ) const
Does this synapse group require an RNG for it's weight update init code?
19.101.3.60 isWUVarInitRequired()
bool SynapseGroup::isWUVarInitRequired ( ) const
```

Is var init code required for any variables in this synapse group's weight update model?

19.101.3.61 isZeroCopyEnabled()

```
bool SynapseGroup::isZeroCopyEnabled ( ) const
```

19.101.3.62 setBackPropDelaySteps()

Sets the number of delay steps used to delay postsynaptic spikes travelling back along dendrites to synapses.

19.101.3.63 setDendriticDelayLocation()

Set variable mode used for this synapse group's dendritic delay buffers.

19.101.3.64 setEventThresholdReTestRequired()

```
void SynapseGroup::setEventThresholdReTestRequired ( bool\ req\ ) \quad \hbox{[inline], [protected]}
```

19.101.3.65 setInSynVarLocation()

Set location of variables used to combine input from this synapse group.

This is ignored for simulations on hardware with a single memory space

19.101.3.66 setMaxConnections()

```
void SynapseGroup::setMaxConnections (
          unsigned int maxConnections )
```

Sets the maximum number of target neurons any source neurons can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE to optimise CUDA implementation

19.101.3.67 setMaxDendriticDelayTimesteps()

Sets the maximum dendritic delay for synapses in this synapse group.

19.101.3.68 setMaxSourceConnections()

Sets the maximum number of source neurons any target neuron can connect to.

Use with synaptic matrix types with SynapseMatrixConnectivity::SPARSE and postsynaptic learning to optimise CUDA implementation

19.101.3.69 setNarrowSparseIndEnabled()

```
void SynapseGroup::setNarrowSparseIndEnabled ( bool\ enabled\ )
```

Enables or disables using narrow i.e. less than 32-bit types for sparse matrix indices.

19.101.3.70 setNumThreadsPerSpike()

Set how many threads CUDA implementation uses to process each spike when span type is PRESYNAPTIC.

19.101.3.71 setPSExtraGlobalParamLocation()

Set location of postsynaptic model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.101.3.72 setPSModelMergeTarget()

19.101.3.73 setPSVarLocation()

Set location of postsynaptic model state variable.

This is ignored for simulations on hardware with a single memory space

19.101.3.74 setSpanType()

Set how CUDA implementation is parallelised.

with a thread per target neuron (default) or a thread per source spike

19.101.3.75 setSparseConnectivityExtraGlobalParamLocation()

Set location of sparse connectivity initialiser extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.101.3.76 setSparseConnectivityLocation()

Set variable mode used for sparse connectivity.

This is ignored for simulations on hardware with a single memory space

19.101.3.77 setWUExtraGlobalParamLocation()

Set location of weight update model extra global parameter.

This is ignored for simulations on hardware with a single memory space and only applies to extra global parameters which are pointers.

19.101.3.78 setWUPostVarLocation()

Set location of weight update model postsynaptic state variable.

This is ignored for simulations on hardware with a single memory space

19.101.3.79 setWUPreVarLocation()

Set location of weight update model presynaptic state variable.

This is ignored for simulations on hardware with a single memory space

19.101.3.80 setWUVarLocation()

Set location of weight update model state variable.

This is ignored for simulations on hardware with a single memory space


The documentation for this class was generated from the following files:

- synapseGroup.h
- synapseGroup.cc

19.102 SynapseGroupInternal Class Reference

```
#include <synapseGroupInternal.h>
```

Inheritance diagram for SynapseGroupInternal:



Public Member Functions

SynapseGroupInternal (const std::string name, SynapseMatrixType matrixType, unsigned int delaySteps, const WeightUpdateModels::Base *wu, const std::vector< double > &wuParams, const std::vector< Models::VarInit > &wuParams, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &wuPreVarInitialisers, const std::vector< Models::VarInit > &psVarInitialisers, const std::vector< double > &psParams, const std::vector< Models::VarInit > &psVarInitialisers, NeuronGroup← Internal *srcNeuronGroup, NeuronGroupInternal *trgNeuronGroup, const InitSparseConnectivitySnippet::← Init &connectivityInitialiser, VarLocation defaultVarLocation, VarLocation defaultExtraGlobalParamLocation, VarLocation defaultSparseConnectivityLocation, bool defaultNarrowSparseIndEnabled)

Additional Inherited Members

19.102.1 Constructor & Destructor Documentation

19.102.1.1 SynapseGroupInternal()

```
SynapseGroupInternal::SynapseGroupInternal (
            const std::string name,
             SynapseMatrixType matrixType,
             unsigned int delaySteps,
             const WeightUpdateModels::Base * wu,
             const std::vector< double > & wuParams,
             const std::vector< Models::VarInit > & wuVarInitialisers,
             const std::vector< Models::VarInit > & wuPreVarInitialisers,
             const std::vector< Models::VarInit > & wuPostVarInitialisers,
             const PostsynapticModels::Base * ps,
             const std::vector< double > & psParams,
             const std::vector< Models::VarInit > & psVarInitialisers,
             NeuronGroupInternal * srcNeuronGroup,
             NeuronGroupInternal * trgNeuronGroup,
             const InitSparseConnectivitySnippet::Init & connectivityInitialiser,
             VarLocation defaultVarLocation,
             VarLocation defaultExtraGlobalParamLocation,
             VarLocation defaultSparseConnectivityLocation,
             bool defaultNarrowSparseIndEnabled ) [inline]
```


The documentation for this class was generated from the following file:

• synapseGroupInternal.h

19.103 CodeGenerator::TeeBuf Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeBuf:



Public Member Functions

template<typename... T>
 TeeBuf (T &&... streamBufs)

19.103.1 Constructor & Destructor Documentation

19.103.1.1 TeeBuf()


The documentation for this class was generated from the following file:

• teeStream.h

19.104 CodeGenerator::TeeStream Class Reference

```
#include <teeStream.h>
```

Inheritance diagram for CodeGenerator::TeeStream:



Public Member Functions

template<typename... T>
 TeeStream (T &&... streamBufs)

19.104.1 Constructor & Destructor Documentation

19.104.1.1 TeeStream()

The documentation for this class was generated from the following file:

· teeStream.h

19.105 Timer Class Reference

A generic timer which can give the current elapsed time.

```
#include <timer.h>
```

Public Member Functions

• Timer (const std::string &message, const std::string &filename="")

Create a new Timer with the specified name and optionally a filename to append time to.

• ∼Timer ()

Stop the timer and print current elapsed time to terminal.

• double get () const

Get the elapsed time since this object was created.

19.105.1 Detailed Description

A generic timer which can give the current elapsed time.

19.105.2 Constructor & Destructor Documentation

```
19.105.2.1 Timer()
```

Create a new Timer with the specified name and optionally a filename to append time to.

```
19.105.2.2 \simTimer()
Timer::\simTimer ( ) [inline]
```

Stop the timer and print current elapsed time to terminal.

19.105.3 Member Function Documentation

```
19.105.3.1 get()
double Timer::get ( ) const [inline]
```

Get the elapsed time since this object was created.

The documentation for this class was generated from the following file:

• userproject/include/timer.h

19.106 SpineMLSimulator::Timer Class Reference

```
#include <timer.h>
```

Public Member Functions

- Timer (const std::string &title)
- ∼Timer ()
- · double get () const

19.106.1 Constructor & Destructor Documentation

```
19.106.1.1 Timer()
```

19.106.1.2 \sim Timer()

```
{\tt SpineMLSimulator::Timer::} {\sim} {\tt Timer} \ \ (\ ) \quad [{\tt inline}]
```

19.106.2 Member Function Documentation

```
19.106.2.1 get()
```

```
double SpineMLSimulator::Timer::get ( ) const [inline]
```

The documentation for this class was generated from the following file:

· include/spineml/simulator/timer.h

19.107 TimerAccumulate Class Reference

A timer which adds its elapsed time to an accumulator variable on destruction.

```
#include <timer.h>
```

Public Member Functions

- TimerAccumulate (double &accumulator)
- ∼TimerAccumulate ()

· double get () const

Get the elapsed time since this object was created.

19.107.1 Detailed Description

A timer which adds its elapsed time to an accumulator variable on destruction.

19.107.2 Constructor & Destructor Documentation

19.107.2.1 TimerAccumulate()

19.107.2.2 ~TimerAccumulate()

```
TimerAccumulate::~TimerAccumulate ( ) [inline]
```

19.107.3 Member Function Documentation

```
19.107.3.1 get()
```

```
double TimerAccumulate::get ( ) const [inline]
```

Get the elapsed time since this object was created.

The documentation for this class was generated from the following file:

• userproject/include/timer.h

19.108 SpineMLSimulator::TimerAccumulate Class Reference

```
#include <timer.h>
```

Public Member Functions

- TimerAccumulate (double &accumulator)
- ∼TimerAccumulate ()
- · double get () const

19.108.1 Constructor & Destructor Documentation

19.108.1.1 TimerAccumulate()

19.108.1.2 ∼TimerAccumulate()

```
SpineMLSimulator::TimerAccumulate::~TimerAccumulate ( ) [inline]
```

19.108.2 Member Function Documentation

19.108.2.1 get()

```
double SpineMLSimulator::TimerAccumulate::get ( ) const [inline]
```


The documentation for this class was generated from the following file:

· include/spineml/simulator/timer.h

19.109 SpineMLSimulator::InputValue::TimeVarying Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::TimeVarying:



Public Member Functions

- TimeVarying (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.109.1 Constructor & Destructor Documentation

19.109.1.1 TimeVarying()

19.109.2 Member Function Documentation

19.109.2.1 update()

Implements SpineMLSimulator::InputValue::Base.


The documentation for this class was generated from the following files:

- inputValue.h
- · inputValue.cc

19.110 SpineMLSimulator::InputValue::TimeVaryingArray Class Reference

```
#include <inputValue.h>
```

Inheritance diagram for SpineMLSimulator::InputValue::TimeVaryingArray:



Public Member Functions

- TimeVaryingArray (double dt, unsigned int numNeurons, const pugi::xml_node &node)
- virtual void update (double dt, unsigned long long timestep, std::function< void(unsigned int, double)> applyValueFunc) override

Additional Inherited Members

19.110.1 Constructor & Destructor Documentation

19.110.1.1 TimeVaryingArray()

19.110.2 Member Function Documentation

19.110.2.1 update()

Implements SpineMLSimulator::InputValue::Base.

The documentation for this class was generated from the following files:


- · inputValue.h
- · inputValue.cc

19.111 NeuronModels::TraubMiles Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMiles:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

virtual std::string getThresholdConditionCode () const override

Gets code which defines the condition for a true spike in the described neuron model.

virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

• virtual VarVec getVars () const override

Gets names and types (as strings) of model variables.

Static Public Member Functions

static const NeuronModels::TraubMiles * getInstance ()

Additional Inherited Members

19.111.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

This conductance based model has been taken from [7] and can be described by the equations:

$$C\frac{dV}{dt} = -I_{Na} - I_K - I_{leak} - I_M - I_{i,DC} - I_{i,syn} - I_i,$$

$$I_{Na}(t) = g_{Na}m_i(t)^3 h_i(t)(V_i(t) - E_{Na})$$

$$I_K(t) = g_K n_i(t)^4 (V_i(t) - E_K)$$

$$\frac{dy(t)}{dt} = \alpha_y(V(t))(1 - y(t)) - \beta_y(V(t))y(t),$$

where $y_i = m, h, n$, and

$$\alpha_n = 0.032(-50-V)/(\exp((-50-V)/5)-1)$$

$$\beta_n = 0.5\exp((-55-V)/40)$$

$$\alpha_m = 0.32(-52-V)/(\exp((-52-V)/4)-1)$$

$$\beta_m = 0.28(25+V)/(\exp((25+V)/5)-1)$$

$$\alpha_h = 0.128\exp((-48-V)/18)$$

$$\beta_h = 4/(\exp((-25-V)/5)+1).$$

and typical parameters are C=0.143 nF, $g_{\rm leak}=0.02672~\mu$ S, $E_{\rm leak}=-63.563$ mV, $g_{\rm Na}=7.15~\mu$ S, $E_{\rm Na}=50$ mV, $g_{\rm K}=1.43~\mu$ S, $E_{\rm K}=-95$ mV.

It has 4 variables:

- V membrane potential E
- m probability for Na channel activation m
- · h probability for not Na channel blocking h
- n probability for K channel activation n

and 7 parameters:

- gNa Na conductance in 1/(mOhms * cm[^]2)
- ENa Na equi potential in mV
- gK K conductance in 1/(mOhms * cm²)
- EK K equi potential in mV
- gl Leak conductance in 1/(mOhms * cm²)
- El Leak equi potential in mV
- Cmem Membrane capacity density in muF/cm²

Note

Internally, the ordinary differential equations defining the model are integrated with a linear Euler algorithm and GeNN integrates 25 internal time steps for each neuron for each network time step. I.e., if the network is simulated at DT=0.1 ms, then the neurons are integrated with a linear Euler algorithm with 1DT=0.004 ms. This variant uses IF statements to check for a value at which a singularity would be hit. If so, value calculated by L'Hospital rule is used.

19.111.2 Member Typedef Documentation

19.111.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMiles::ParamValues

19.111.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PostVarValues

19.111.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMiles::PreVarValues

19.111.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMiles::VarValues

19.111.3 Member Function Documentation

19.111.3.1 getInstance()

static const NeuronModels::TraubMiles* NeuronModels::TraubMiles::getInstance () [inline],
[static]

19.111.3.2 getParamNames()

virtual StringVec NeuronModels::TraubMiles::getParamNames () const [inline], [override],

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

Reimplemented in NeuronModels::TraubMilesNStep.

19.111.3.3 getSimCode()

virtual std::string NeuronModels::TraubMiles::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::Base.

 $Reimplemented \ in \ NeuronModels:: TraubMiles NS tep, \ NeuronModels:: TraubMiles Alt, \ and \ NeuronModels:: Traub Miles Fast.$

19.111.3.4 getThresholdConditionCode()

virtual std::string NeuronModels::TraubMiles::getThresholdConditionCode () const [inline],

```
[override], [virtual]
```

Gets code which defines the condition for a true spike in the described neuron model.

This evaluates to a bool (e.g. "V > 20").

Reimplemented from NeuronModels::Base.

19.111.3.5 getVars()

```
virtual VarVec NeuronModels::TraubMiles::getVars ( ) const [inline], [override], [virtual]
```

Gets names and types (as strings) of model variables.

Reimplemented from Models::Base.

The documentation for this class was generated from the following file:


neuronModels.h

19.112 NeuronModels::TraubMilesAlt Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

```
#include <neuronModels.h>
```

Inheritance diagram for NeuronModels::TraubMilesAlt:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

• virtual std::string getSimCode () const override

Gets the code that defines the execution of one timestep of integration of the neuron model.

Static Public Member Functions

static const NeuronModels::TraubMilesAlt * getInstance ()

Additional Inherited Members

19.112.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Using a workaround to avoid singularity: adding the munimum numerical value of the floating point precision used.

19.112.2 Member Typedef Documentation

19.112.2.1 ParamValues

```
typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesAlt::ParamValues
```

19.112.2.2 PostVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PostVarValues
```

19.112.2.3 PreVarValues

```
typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesAlt::PreVarValues
```

19.112.2.4 VarValues

```
typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesAlt::VarValues
```

19.112.3 Member Function Documentation

19.112.3.1 getInstance()

```
static const NeuronModels::TraubMilesAlt* NeuronModels::TraubMilesAlt::getInstance ( ) [inline],
[static]
```

19.112.3.2 getSimCode()

```
virtual std::string NeuronModels::TraubMilesAlt::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


neuronModels.h

19.113 NeuronModels::TraubMilesFast Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesFast:



Public Types

- typedef Snippet::ValueBase< 7 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.

Static Public Member Functions

static const NeuronModels::TraubMilesFast * getInstance ()

Additional Inherited Members

19.113.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations. There are singularities in this model, which can be easily hit in float precision

19.113.2 Member Typedef Documentation

19.113.2.1 ParamValues

typedef Snippet::ValueBase< 7 > NeuronModels::TraubMilesFast::ParamValues

19.113.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PostVarValues

19.113.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesFast::PreVarValues

19.113.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesFast::VarValues

19.113.3 Member Function Documentation

19.113.3.1 getInstance()

static const NeuronModels::TraubMilesFast* NeuronModels::TraubMilesFast::getInstance () [inline],
[static]

19.113.3.2 getSimCode()

virtual std::string NeuronModels::TraubMilesFast::getSimCode () const [inline], [override],
[virtual]

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


neuronModels.h

19.114 NeuronModels::TraubMilesNStep Class Reference

Hodgkin-Huxley neurons with Traub & Miles algorithm.

#include <neuronModels.h>

Inheritance diagram for NeuronModels::TraubMilesNStep:



Public Types

- typedef Snippet::ValueBase< 8 > ParamValues
- typedef Models::VarInitContainerBase< 4 > VarValues
- typedef Models::VarInitContainerBase< 0 > PreVarValues
- typedef Models::VarInitContainerBase< 0 > PostVarValues

Public Member Functions

- virtual std::string getSimCode () const override
 Gets the code that defines the execution of one timestep of integration of the neuron model.
- virtual StringVec getParamNames () const override
 Gets names of of (independent) model parameters.

Static Public Member Functions

• static const NeuronModels::TraubMilesNStep * getInstance ()

Additional Inherited Members

19.114.1 Detailed Description

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Same as standard TraubMiles model but number of inner loops can be set using a parameter

19.114.2 Member Typedef Documentation

19.114.2.1 ParamValues

typedef Snippet::ValueBase< 8 > NeuronModels::TraubMilesNStep::ParamValues

19.114.2.2 PostVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PostVarValues

19.114.2.3 PreVarValues

typedef Models::VarInitContainerBase<0> NeuronModels::TraubMilesNStep::PreVarValues

19.114.2.4 VarValues

typedef Models::VarInitContainerBase< 4 > NeuronModels::TraubMilesNStep::VarValues

19.114.3 Member Function Documentation

19.114.3.1 getInstance()

```
static const NeuronModels::TraubMilesNStep* NeuronModels::TraubMilesNStep::getInstance ( )
[inline], [static]
```

19.114.3.2 getParamNames()

virtual StringVec NeuronModels::TraubMilesNStep::getParamNames () const [inline], [override],
[virtual]

Gets names of of (independent) model parameters.

Reimplemented from NeuronModels::TraubMiles.

19.114.3.3 getSimCode()

```
virtual std::string NeuronModels::TraubMilesNStep::getSimCode ( ) const [inline], [override],
[virtual]
```

Gets the code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

Reimplemented from NeuronModels::TraubMiles.

The documentation for this class was generated from the following file:


neuronModels.h

19.115 InitVarSnippet::Uniform Class Reference

Initialises variable by sampling from the uniform distribution.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uniform:



Public Member Functions

- DECLARE_SNIPPET (InitVarSnippet::Uniform, 2)
- SET_CODE ("const scalar scale = \$(max) \$(min);\ "\$(value)=\$(min)+(\$(gennrand_uniform) *scale);")
- virtual StringVec getParamNames () const override

Gets names of of (independent) model parameters.

Additional Inherited Members

19.115.1 Detailed Description

Initialises variable by sampling from the uniform distribution.

This snippet takes 2 parameters:

- min The minimum value
- max The maximum value

19.115.2 Member Function Documentation

19.115.2.1 DECLARE_SNIPPET()

19.115.2.2 getParamNames()

```
virtual StringVec InitVarSnippet::Uniform::getParamNames ( ) const [inline], [override],
[virtual]
```

Gets names of of (independent) model parameters.

Reimplemented from Snippet::Base.

```
19.115.2.3 SET_CODE()
```

The documentation for this class was generated from the following file:

· initVarSnippet.h

19.116 SpineMLSimulator::ModelProperty::UniformDistribution Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::UniformDistribution:

```
SpineMLSimulator::ModelProperty::Base

SpineMLSimulator::ModelProperty::UniformDistribution
```

Public Member Functions

- UniformDistribution (const pugi::xml_node &node, const StateVar < scalar > &stateVar, unsigned int size)
- void setValue (scalar min, scalar max)

19.116.1 Constructor & Destructor Documentation

19.116.1.1 UniformDistribution()

19.116.2 Member Function Documentation

19.116.2.1 setValue()

The documentation for this class was generated from the following files:


- · modelProperty.h
- · modelProperty.cc

19.117 InitVarSnippet::Uninitialised Class Reference

Used to mark variables as uninitialised - no initialisation code will be run.

```
#include <initVarSnippet.h>
```

Inheritance diagram for InitVarSnippet::Uninitialised:



Public Member Functions

DECLARE_SNIPPET (InitVarSnippet::Uninitialised, 0)

Additional Inherited Members

19.117.1 Detailed Description

Used to mark variables as uninitialised - no initialisation code will be run.

19.117.2 Member Function Documentation

19.117.2.1 DECLARE_SNIPPET()

The documentation for this class was generated from the following file:


· initVarSnippet.h

19.118 InitSparseConnectivitySnippet::Uninitialised Class Reference

Used to mark connectivity as uninitialised - no initialisation code will be run.

```
#include <initSparseConnectivitySnippet.h>
```

Inheritance diagram for InitSparseConnectivitySnippet::Uninitialised:



Public Member Functions

• DECLARE_SNIPPET (InitSparseConnectivitySnippet::Uninitialised, 0)

Additional Inherited Members

19.118.1 Detailed Description

Used to mark connectivity as uninitialised - no initialisation code will be run.

19.118.2 Member Function Documentation

19.118.2.1 DECLARE_SNIPPET()

The documentation for this class was generated from the following file:

• initSparseConnectivitySnippet.h

19.119 Snippet::ValueBase < NumVars > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

- template<typename... T>
 ValueBase (T &&... vals)
- const std::vector< double > & getValues () const

Gets values as a vector of doubles.

• double operator[] (size_t pos) const

19.119.1 Constructor & Destructor Documentation

19.119.1.1 ValueBase()

19.119.2 Member Function Documentation

19.119.2.1 getValues()

```
template<size_t NumVars>
const std::vector<double>& Snippet::ValueBase< NumVars >::getValues ( ) const [inline]
```

Gets values as a vector of doubles.

19.119.2.2 operator[]()

The documentation for this class was generated from the following file:

snippet.h

19.120 Snippet::ValueBase < 0 > Class Template Reference

```
#include <snippet.h>
```

Public Member Functions

- template<typename... T>
 ValueBase (T &&... vals)
- std::vector< double > getValues () const

Gets values as a vector of doubles.

19.120.1 Detailed Description

```
template<> class Snippet::ValueBase< 0 >
```

Template specialisation of ValueBase to avoid compiler warnings in the case when a model requires no parameters or state variables

19.120.2 Constructor & Destructor Documentation

19.120.2.1 ValueBase()

19.120.3 Member Function Documentation

19.120.3.1 getValues()

```
std::vector<double> Snippet::ValueBase< 0 >::getValues ( ) const [inline]
```

Gets values as a vector of doubles.

The documentation for this class was generated from the following file:

· snippet.h

19.121 SpineMLSimulator::ModelProperty::ValueList Class Reference

```
#include <modelProperty.h>
```

Inheritance diagram for SpineMLSimulator::ModelProperty::ValueList:

```
SpineMLSimulator::ModelProperty::Base

SpineMLSimulator::ModelProperty::ValueList
```

Public Member Functions

- ValueList (const pugi::xml_node &node, const filesystem::path &basePath, const std::vector< unsigned int > *remapIndices, const StateVar< scalar > &stateVar, unsigned int size)
- void setValue (const std::vector< scalar > &values, const std::vector< unsigned int > *remapIndices)

19.121.1 Constructor & Destructor Documentation

19.121.1.1 ValueList()

19.121.2 Member Function Documentation

19.121.2.1 setValue()

The documentation for this class was generated from the following files:

- · modelProperty.h
- · modelProperty.cc

19.122 Models::Base::Var Struct Reference

A variable has a name, a type and an access type.

```
#include <models.h>
```

Public Member Functions

- Var (const std::string &n, const std::string &t, VarAccess a)
- · Var (const std::string &n, const std::string &t)
- Var ()

Public Attributes

- std::string name
- · std::string type
- · VarAccess access

19.122.1 Detailed Description

A variable has a name, a type and an access type.

Explicit constructors required as although, through the wonders of C++ aggregate initialization, access would default to VarAccess::READ_WRITE if not specified, this results in a -Wmissing-field-initializers warning on GCC and Clang

19.122.2 Constructor & Destructor Documentation

```
19.122.2.1 Var() [1/3]
Models::Base::Var::Var (
             const std::string & n,
             const std::string & t,
             VarAccess a ) [inline]
19.122.2.2 Var() [2/3]
Models::Base::Var::Var (
             const std::string & n,
             const std::string & t ) [inline]
19.122.2.3 Var() [3/3]
Models::Base::Var::Var ( ) [inline]
19.122.3 Member Data Documentation
19.122.3.1 access
VarAccess Models::Base::Var::access
19.122.3.2 name
std::string Models::Base::Var::name
19.122.3.3 type
std::string Models::Base::Var::type
The documentation for this struct was generated from the following file:
```

· models.h

pygenn.model_preprocessor.Variable Class Reference

Class holding information about GeNN variables.

Inheritance diagram for pygenn.model_preprocessor.Variable:

```
object
pygenn.model_preprocessor.Variable
```

Public Member Functions

- def __init__ (self, variable_name, variable_type, values=None)
 Init Variable.
- def set_values (self, values)

Set Variable's values.

Public Attributes

- name
- type
- view
- needs_allocation
- init_required
- · init_val
- values

19.123.1 Detailed Description

Class holding information about GeNN variables.

19.123.2 Constructor & Destructor Documentation

Init Variable.

Parameters

variable_name	string name of the variable
variable_type	string type of the variable
values	iterable, single value or VarInit instance

19.123.3 Member Function Documentation

Set Variable's values.

Parameters

values iterable, single value or VarInit inst	ance
---	------

19.123.4 Member Data Documentation

19.123.4.1 init_required

pygenn.model_preprocessor.Variable.init_required

19.123.4.2 init_val

 $\verb|pygenn.model_preprocessor.Variable.init_val|\\$

19.123.4.3 name

pygenn.model_preprocessor.Variable.name

19.123.4.4 needs_allocation

pygenn.model_preprocessor.Variable.needs_allocation

19.123.4.5 type

pygenn.model_preprocessor.Variable.type

19.123.4.6 values

pygenn.model_preprocessor.Variable.values

19.123.4.7 view

pygenn.model_preprocessor.Variable.view


The documentation for this class was generated from the following file:

· model_preprocessor.py

19.124 Models::VarInit Class Reference

```
#include <models.h>
```

Inheritance diagram for Models::VarInit:



Public Member Functions

- VarInit (const InitVarSnippet::Base *snippet, const std::vector< double > ¶ms)
- VarInit (double constant)

19.124.1 Constructor & Destructor Documentation

The documentation for this class was generated from the following file:

· models.h

19.125 Models::VarInitContainerBase < NumVars > Class Template Reference

```
#include <models.h>
```

Public Member Functions

- template<typename... T>
 VarInitContainerBase (T &&... initialisers)
- const std::vector < VarInit > & getInitialisers () const

Gets initialisers as a vector of Values.

const VarInit & operator[] (size_t pos) const

19.125.1 Detailed Description

```
template < size_t NumVars > class Models::VarInitContainerBase < NumVars >
```

Wrapper to ensure at compile time that correct number of value initialisers are used when specifying the values of a model's initial state.

19.125.2 Constructor & Destructor Documentation

19.125.2.1 VarInitContainerBase()

19.125.3 Member Function Documentation

19.125.3.1 getInitialisers()

```
template<size_t NumVars>
const std::vector<VarInit>& Models::VarInitContainerBase< NumVars >::getInitialisers ( )
const [inline]
```

Gets initialisers as a vector of Values.

19.125.3.2 operator[]()

The documentation for this class was generated from the following file:

models.h

19.126 Models::VarInitContainerBase < 0 > Class Template Reference

```
#include <models.h>
```

Public Member Functions

- template<typename... T>
 VarInitContainerBase (T &&... initialisers)
- VarInitContainerBase (const Snippet::ValueBase< 0 > &)
- std::vector< VarInit > getInitialisers () const

Gets initialisers as a vector of Values.

19.126.1 Detailed Description

```
template<> class Models::VarInitContainerBase< 0 >
```

Template specialisation of ValueInitBase to avoid compiler warnings in the case when a model requires no variable initialisers

19.126.2 Constructor & Destructor Documentation

The documentation for this class was generated from the following file:

• models.h

20 File Documentation

Gets initialisers as a vector of Values.

- 20.1 00_MainPage.dox File Reference
- 20.2 01_Installation.dox File Reference
- 20.3 02_Quickstart.dox File Reference
- 20.4 03_Examples.dox File Reference
- 20.5 05_SpineML.dox File Reference
- 20.6 06_Brian2GeNN.dox File Reference
- 20.7 07_PyGeNN.dox File Reference
- 20.8 09_ReleaseNotes.dox File Reference

```
20.9 10_UserManual.dox File Reference
```

- 20.10 11_Tutorial.dox File Reference
- 20.11 12_Tutorial.dox File Reference
- 20.12 13_UserGuide.dox File Reference
- 20.13 14_Credits.dox File Reference
- 20.14 __init__.py File Reference

Namespaces

• pygenn

20.15 analogueRecorder.h File Reference

```
#include <fstream>
#include <initializer_list>
#include <string>
#include <vector>
```

Classes

class AnalogueRecorder< T >

20.16 backend.cc File Reference

```
#include "backend.h"
#include <algorithm>
#include <numeric>
#include "gennUtils.h"
#include "logging.h"
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
#include "utils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::CUDA

20.17 backend.cc File Reference

```
#include "backend.h"
#include <random>
#include "gennUtils.h"
```

```
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/codeGenUtils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

• CodeGenerator::SingleThreadedCPU

20.18 backend.h File Reference

```
#include <algorithm>
#include <array>
#include <functional>
#include <map>
#include <string>
#include <unordered_set>
#include <cuda.h>
#include <cuda_runtime.h>
#include "backendExport.h"
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "presynapticUpdateStrategy.h"
```

Classes

struct CodeGenerator::CUDA::Preferences

Preferences for CUDA backend.

· class CodeGenerator::CUDA::Backend

Namespaces

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· CodeGenerator::CUDA

Typedefs

using CodeGenerator::CUDA::KernelBlockSize = std::array < size_t, KernelMax >
 Array of block sizes for each kernel.

Enumerations

enum CodeGenerator::CUDA::DeviceSelect { CodeGenerator::CUDA::DeviceSelect::OPTIMAL, Code
 Generator::CUDA::DeviceSelect::MOST_MEMORY, CodeGenerator::CUDA::DeviceSelect::MANUAL }

Methods for selecting CUDA device.

 enum CodeGenerator::CUDA::BlockSizeSelect { CodeGenerator::CUDA::BlockSizeSelect::OCCUPANCY, CodeGenerator::CUDA::BlockSizeSelect::MANUAL }

Methods for selecting CUDA kernel block size.

enum CodeGenerator::CUDA::Kernel {
 CodeGenerator::CUDA::KernelNeuronUpdate, CodeGenerator::CUDA::KernelPresynapticUpdate, CodeGenerator::CUDA::KernelPresynapticUpdate, CodeGenerator::CUDA::KernelSynapseDynamicsUpdate,
 CodeGenerator::CUDA::KernelInitialize, CodeGenerator::CUDA::KernelInitializeSparse, CodeGenerator::CUDA::KernelPreSynapseReset,
 CodeGenerator::CUDA::KernelMax }

Kernels generated by CUDA backend.

20.19 backend.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include "backendExport.h"
#include "code_generator/backendBase.h"
```

Classes

- struct CodeGenerator::SingleThreadedCPU::Preferences
- · class CodeGenerator::SingleThreadedCPU::Backend

Namespaces

- · filesystem
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

CodeGenerator::SingleThreadedCPU

20.20 backendBase.cc File Reference

```
#include "code_generator/backendBase.h"
#include "gennUtils.h"
#include "logging.h"
```

Macros

#define TYPE(T) {#T, sizeof(T)}

20.20.1 Macro Definition Documentation

20.21 backendBase.h File Reference

```
#include <functional>
#include <map>
#include <string>
#include <unordered_map>
#include <vector>
#include <plog/Severity.h>
#include "codeStream.h"
#include "gennExport.h"
#include "variableMode.h"
```

Classes

· struct CodeGenerator::PreferencesBase

Base class for backend preferences - can be accessed via a global in 'classic' C++ code generator.

- class CodeGenerator::MemAlloc
- · class CodeGenerator::BackendBase

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.22 backendExport.h File Reference

Macros

#define BACKEND_EXPORT

20.22.1 Macro Definition Documentation

20.22.1.1 BACKEND_EXPORT

```
#define BACKEND_EXPORT
```

20.23 binomial.cc File Reference

```
#include "binomial.h"
#include <stdexcept>
#include <cassert>
#include <cmath>
#include <cstdint>
```

Functions

• unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

20.23.1 Function Documentation

20.23.1.1 binomialInverseCDF()

```
unsigned int binomialInverseCDF ( double cdf, unsigned int n, double p )
```

20.24 binomial.h File Reference

```
#include "gennExport.h"
```

Functions

• GENN_EXPORT unsigned int binomialInverseCDF (double cdf, unsigned int n, double p)

20.24.1 Function Documentation

20.24.1.1 binomialInverseCDF()

```
GENN_EXPORT unsigned int binomialInverseCDF ( \label{eq:cdf} \mbox{double } cdf, \\ \mbox{unsigned int } n, \\ \mbox{double } p \mbox{)}
```

20.25 codeGenUtils.cc File Reference

```
#include "code_generator/codeGenUtils.h"
#include <regex>
#include <cstring>
#include "modelSpec.h"
#include "code_generator/substitutions.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Enumerations

• enum MathsFunc

Functions

• void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting strings in the neuron code strings or other templates.

- bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)
 - Tool for substituting variable names in the neuron code strings or other templates using regular expressions.
- bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void CodeGenerator::preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postldx,
 const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

 void CodeGenerator::postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std:: ::string &preldx, const std::string &devPrefix, const std::string &postVarPrefix="", const std::string &postVar← Suffix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &preldx, const std::string &postldx, const std::string &devPrefix, double
 dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="",
 const std::string &postVarSuffix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

20.25.1 Enumeration Type Documentation

20.25.1.1 MathsFunc

enum MathsFunc

20.26 codeGenUtils.h File Reference

```
#include <iomanip>
#include <limits>
#include <string>
#include <sstream>
#include <vector>
#include "models.h"
#include "snippet.h"
#include "variableMode.h"
```

Classes

• struct CodeGenerator::FunctionTemplate

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Tool for substituting strings in the neuron code strings or other templates.

Functions

void CodeGenerator::substitute (std::string &s, const std::string &trg, const std::string &rep)

• bool CodeGenerator::regexVarSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting variable names in the neuron code strings or other templates using regular expressions.

• bool CodeGenerator::regexFuncSubstitute (std::string &s, const std::string &trg, const std::string &rep)

Tool for substituting function names in the neuron code strings or other templates using regular expressions.

void CodeGenerator::functionSubstitute (std::string &code, const std::string &funcName, unsigned int num
 —
 Params, const std::string &replaceFuncTemplate)

This function substitutes function calls in the form:

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr> void CodeGenerator::writePreciseString (std::ostream &os, T value)

This function writes a floating point value to a stream -setting the precision so no digits are lost.

template < class T , typename std::enable_if < std::is_floating_point < T >::value >::type * = nullptr>
std::string CodeGenerator::writePreciseString (T value)

This function writes a floating point value to a string - setting the precision so no digits are lost.

• size t CodeGenerator::ceilDivide (size t numerator, size t denominator)

Divide two integers, rounding up i.e. effectively taking ceil.

• size t CodeGenerator::padSize (size t size, size t blockSize)

Pad an integer to a multiple of another.

• std::string CodeGenerator::ensureFtype (const std::string &oldcode, const std::string &type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

void CodeGenerator::checkUnreplacedVariables (const std::string &code, const std::string &codeName)

This function checks for unknown variable definitions and returns a gennError if any are found.

void CodeGenerator::preNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &offset, const std::string &axonalDelayOffset, const std::string &postIdx,
 const std::string &devPrefix, const std::string &preVarPrefix="", const std::string &preVarSuffix="")

suffix to be used for presynaptic variable accesses - typically combined with prefix to wrap in function call such as __ldg(&XXX)

 void CodeGenerator::postNeuronSubstitutionsInSynapticCode (Substitutions &substitutions, const SynapseGroupInternal &sg, const std::string &offset, const std::string &backPropDelayOffset, const std:: ::string &preldx, const std::string &devPrefix, const std::string &postVarPrefix="", const std::string &postVarPrefix="")

suffix to be used for postsynaptic variable accesses - typically combined with prefix to wrap in function call such as ldq(&XXX)

void CodeGenerator::neuronSubstitutionsInSynapticCode (Substitutions &substitutions, const Synapse
 GroupInternal &sg, const std::string &preldx, const std::string &postldx, const std::string &devPrefix, double
 dt, const std::string &preVarPrefix="", const std::string &postVarPrefix="",
 const std::string &postVarSuffix="")

Function for performing the code and value substitutions necessary to insert neuron related variables, parameters, and extraGlobal parameters into synaptic code.

20.27 codeStream.cc File Reference

```
#include "code_generator/codeStream.h"
#include <algorithm>
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

- GENN EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

20.28 codeStream.h File Reference

```
#include <ostream>
#include <stdexcept>
#include <streambuf>
#include <string>
#include <vector>
#include "logging.h"
#include "gennExport.h"
```

Classes

- class CodeGenerator::CodeStream
- struct CodeGenerator::CodeStream::OB

An open bracket marker.

• struct CodeGenerator::CodeStream::CB

A close bracket marker.

· class CodeGenerator::CodeStream::Scope

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::OB &ob)
- GENN_EXPORT std::ostream & CodeGenerator::operator<< (std::ostream &s, const CodeStream::CB &cb)

20.29 connectors.cc File Reference

```
#include "connectors.h"
#include <algorithm>
#include <fstream>
#include <iostream>
#include <numeric>
#include <random>
#include <tuple>
#include <vector>
#include <cassert>
#include <cstdint>
#include "path.h"
```

```
#include "pugixml/pugixml.hpp"
#include "spineMLLogging.h"
```

20.30 connectors.h File Reference

```
#include <vector>
#include <cstdint>
```

Namespaces

- pugi
- · filesystem
- SpineMLSimulator
- SpineMLSimulator::Connectors

Functions

unsigned int SpineMLSimulator::Connectors::create (const pugi::xml_node &node, double dt, unsigned int numPre, unsigned int numPost, unsigned int **rowLength, unsigned int **ind, uint8_t **delay, const unsigned int *maxRowLength, const filesystem::path &basePath, std::vector< unsigned int > &remapIndices)

20.31 currentSource.cc File Reference

```
#include "currentSource.h"
#include <algorithm>
#include <cmath>
#include "gennUtils.h"
```

20.32 currentSource.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "currentSourceModels.h"
#include "gennExport.h"
#include "variableMode.h"
```

Classes

class CurrentSource

20.33 currentSourceInternal.h File Reference

```
#include "currentSource.h"
```

Classes

class CurrentSourceInternal

20.34 currentSourceModels.cc File Reference

```
#include "currentSourceModels.h"
```

Functions

- IMPLEMENT_MODEL (CurrentSourceModels::DC)
- IMPLEMENT_MODEL (CurrentSourceModels::GaussianNoise)

20.34.1 Function Documentation

20.35 currentSourceModels.h File Reference

```
#include <array>
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "gennExport.h"
#include "models.h"
```

Classes

• class CurrentSourceModels::Base

Base class for all current source models.

• class CurrentSourceModels::DC

DC source.

· class CurrentSourceModels::GaussianNoise

Noisy current source with noise drawn from normal distribution.

Namespaces

CurrentSourceModels

Macros

#define SET_INJECTION_CODE(INJECTION_CODE) virtual std::string getInjectionCode() const override{
 return INJECTION_CODE; }

20.35.1 Macro Definition Documentation

20.35.1.1 SET_INJECTION_CODE

20.36 generateAll.cc File Reference

```
#include "code_generator/generateAll.h"
#include <fstream>
#include <vector>
#include <plog/Log.h>
#include "path.h"
#include "code_generator/codeStream.h"
#include "code_generator/generateInit.h"
#include "code_generator/generateMPI.h"
#include "code_generator/generateNeuronUpdate.h"
#include "code_generator/generateSupportCode.h"
#include "code_generator/generateSynapseUpdate.h"
#include "code_generator/generateRunner.h"
```

20.37 generateAll.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

· filesystem

Functions

• GENN_EXPORT std::vector< std::string > CodeGenerator::generateAll (const ModelSpecInternal &model, const BackendBase &backend, const filesystem::path &outputPath, bool standaloneModules=false)

20.38 generateInit.cc File Reference

```
#include "code_generator/generateInit.h"
#include <string>
```

```
#include "models.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.39 generateInit.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void CodeGenerator::generateInit (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.40 generateMakefile.cc File Reference

```
#include "code_generator/generateMakefile.h"
#include <string>
#include "modelSpec.h"
#include "code_generator/backendBase.h"
```

20.41 generateMakefile.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

void GENN_EXPORT CodeGenerator::generateMakefile (std::ostream &os, const BackendBase &backend, const std::vector< std::string > &moduleNames)

20.42 generateMPI.cc File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include "code_generator/generateMPI.h"
#include <fstream>
#include <cstring>
#include "modelSpecInternal.h"
```

```
#include "code_generator/backendBase.h"
#include "code_generator/codeStream.h"
```

20.42.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

20.43 generateMPI.h File Reference

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

```
#include <string>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void GENN_EXPORT CodeGenerator::generateMPI (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

A function that generates predominantly MPI infrastructure code.

20.43.1 Detailed Description

Contains functions to generate code for running the simulation with MPI. Part of the code generation section.

20.44 generateMSBuild.cc File Reference

```
#include "code_generator/generateMSBuild.h"
#include <string>
#include "code_generator/backendBase.h"
```

20.45 generateMSBuild.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 void GENN_EXPORT CodeGenerator::generateMSBuild (std::ostream &os, const BackendBase &backend, const std::string &projectGUID, const std::vector< std::string > &moduleNames)

20.46 generateNeuronUpdate.cc File Reference

```
#include "code_generator/generateNeuronUpdate.h"
#include <iostream>
#include <string>
#include <plog/Log.h>
#include "models.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.47 generateNeuronUpdate.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateNeuronUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.48 generateRun.h File Reference

```
#include <algorithm>
#include <fstream>
#include <iostream>
#include <string>
#include <cstdlib>
#include "../../include/genn/third_party/CLI11.hpp"
```

Classes

class GenerateRunBase

20.49 generateRunner.cc File Reference

```
#include "code_generator/generateRunner.h"
#include <sstream>
#include <string>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
```

```
#include "code_generator/codeStream.h"
#include "code_generator/teeStream.h"
#include "code_generator/backendBase.h"
```

20.50 generateRunner.h File Reference

```
#include "code_generator/backendBase.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

 MemAlloc CodeGenerator::generateRunner (CodeStream &definitions, CodeStream &definitionsInternal, CodeStream &runner, const ModelSpecInternal &model, const BackendBase &backend, int localHostID)

20.51 generateSupportCode.cc File Reference

```
#include "code_generator/generateSupportCode.h"
#include <string>
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
```

20.52 generateSupportCode.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateSupportCode (CodeStream &os, const ModelSpecInternal &model)

20.53 generateSynapseUpdate.cc File Reference

```
#include "code_generator/generateSynapseUpdate.h"
#include <string>
#include "modelSpecInternal.h"
#include "code_generator/codeStream.h"
#include "code_generator/substitutions.h"
#include "code_generator/backendBase.h"
```

20.54 generateSynapseUpdate.h File Reference

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

Functions

• void CodeGenerator::generateSynapseUpdate (CodeStream &os, const ModelSpecInternal &model, const BackendBase &backend, bool standaloneModules)

20.55 genn_groups.py File Reference

Classes

• class pygenn.genn_groups.Group

Parent class of NeuronGroup, SynapseGroup and CurrentSource.

class pygenn.genn_groups.NeuronGroup

Class representing a group of neurons.

• class pygenn.genn_groups.SynapseGroup

Class representing synaptic connection between two groups of neurons.

• class pygenn.genn_groups.CurrentSource

Class representing a current injection into a group of neurons.

Namespaces

• pygenn.genn_groups

Variables

• pygenn.genn_groups.xrange = range

GeNNGroups This module provides classes which automatize model checks and parameter convesions for GeNN Groups.

20.56 genn_model.py File Reference

Classes

• class pygenn.genn_model.GeNNModel

GeNNModel class This class helps to define, build and run a GeNN model from python.

Namespaces

• pygenn.genn_model

Functions

def pygenn.genn_model.init_var (init_var_snippet, param_space)

This helper function creates a VarInit object to easily initialise a variable using a snippet.

def pygenn.genn_model.init_connectivity (init_sparse_connect_snippet, param_space)

This helper function creates a InitSparseConnectivitySnippet::Init object to easily initialise connectivity using a snippet.

def pygenn_genn_model.create_custom_neuron_class (class_name, param_names=None, var_name_
 types=None, derived_params=None, sim_code=None, threshold_condition_code=None, reset_code=None,
 support_code=None, extra_global_params=None, additional_input_vars=None, is_auto_refractory_
 required=None, custom_body=None)

This helper function creates a custom NeuronModel class.

def pygenn.genn_model.create_custom_postsynaptic_class (class_name, param_names=None, var
 __name_types=None, derived_params=None, decay_code=None, apply_input_code=None, support_
 code=None, custom body=None)

This helper function creates a custom PostsynapticModel class.

def pygenn_genn_model.create_custom_weight_update_class (class_name, param_names=None, var—name_types=None, pre_var_name_types=None, post_var_name_types=None, derived_params=None, sim_code=None, event_code=None, learn_post_code=None, synapse_dynamics_code=None, event_code=None, learn_post_spike_code=None, sim_support_code=None, learn_post_support_code=None, synapse_dynamics_support_code=None, extra_global_params=None, is_pre_spike_time_required=None, custom_body=None)

This helper function creates a custom WeightUpdateModel class.

def pygenn.genn_model.create_custom_current_source_class (class_name, param_names=None, var_
 name_types=None, derived_params=None, injection_code=None, extra_global_params=None, custom_
 body=None)

This helper function creates a custom NeuronModel class.

 def pygenn.genn_model.create_custom_model_class (class_name, base, param_names, var_name_types, derived params, custom body)

This helper function completes a custom model class creation.

def pygenn.genn_model.create_dpf_class (dp_func)

Helper function to create derived parameter function class.

def pygenn.genn_model.create_cmlf_class (cml_func)

Helper function to create function class for calculating sizes of matrices initialised with sparse connectivity initialisation snippet.

def pygenn.genn_model.create_custom_init_var_snippet_class (class_name, param_names=None, derived_params=None, var_init_code=None, custom_body=None)

This helper function creates a custom InitVarSnippet class.

def pygenn.genn_model.create_custom_sparse_connect_init_snippet_class (class_name, param_
 names=None, derived_params=None, row_build_code=None, row_build_state_vars=None, calc_max_
 row_len_func=None, calc_max_col_len_func=None, extra_global_params=None, custom_body=None)

This helper function creates a custom InitSparseConnectivitySnippet class.

Variables

- pygenn.genn_model.backend_modules = OrderedDict()
- pygenn.genn_model.m = import_module(".genn_wrapper." + b + "Backend", "pygenn")

20.57 gennExport.h File Reference

Macros

• #define GENN EXPORT

20.57.1 Macro Definition Documentation

20.57.1.1 GENN_EXPORT

```
#define GENN_EXPORT
```

20.58 gennUtils.cc File Reference

```
#include "gennUtils.h"
#include <algorithm>
```

Namespaces

• Utils

Functions

• GENN_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

GENN_EXPORT bool Utils::isRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

• GENN_EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

20.59 gennUtils.h File Reference

```
#include <string>
#include <vector>
#include "gennExport.h"
#include "models.h"
```

Namespaces

Utils

Functions

• GENN_EXPORT bool Utils::isRNGRequired (const std::string &code)

Does the code string contain any functions requiring random number generator.

• GENN_EXPORT bool Utils::isRNGRequired (const std::vector< Models::VarInit > &varInitialisers)

Does the model with the vectors of variable initialisers and modes require an RNG for the specified init location i.e. host or device.

• GENN_EXPORT bool Utils::isTypePointer (const std::string &type)

Function to determine whether a string containing a type is a pointer.

GENN_EXPORT std::string Utils::getUnderlyingType (const std::string &type)

Assuming type is a string containing a pointer type, function to return the underlying type.

20.60 initSparseConnectivitySnippet.cc File Reference

```
#include "initSparseConnectivitySnippet.h"
```

Functions

- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::Uninitialised)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::OneToOne)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::FixedProbability)
- IMPLEMENT_SNIPPET (InitSparseConnectivitySnippet::FixedProbabilityNoAutapse)

20.60.1 Function Documentation

20.61 initSparseConnectivitySnippet.h File Reference

```
#include <functional>
#include <vector>
#include <cassert>
#include <cmath>
#include "binomial.h"
#include "snippet.h"
```

Classes

- class InitSparseConnectivitySnippet::Base
- · class InitSparseConnectivitySnippet::Init
- · class InitSparseConnectivitySnippet::Uninitialised

Used to mark connectivity as uninitialised - no initialisation code will be run.

class InitSparseConnectivitySnippet::OneToOne

Initialises connectivity to a 'one-to-one' diagonal matrix.

- class InitSparseConnectivitySnippet::FixedProbabilityBase
- class InitSparseConnectivitySnippet::FixedProbability
- class InitSparseConnectivitySnippet::FixedProbabilityNoAutapse

Namespaces

InitSparseConnectivitySnippet

Base class for all sparse connectivity initialisation snippets.

Macros

- #define SET_ROW_BUILD_CODE(CODE) virtual std::string getRowBuildCode() const override{ return CO←DE: }
- #define SET_ROW_BUILD_STATE_VARS(...) virtual ParamValVec getRowBuildStateVars() const override{
 return VA ARGS ;}
- #define SET_CALC_MAX_ROW_LENGTH_FUNC(FUNC) virtual CalcMaxLengthFunc getCalcMaxRow
 LengthFunc() const override{ return FUNC; }
- #define SET_CALC_MAX_COL_LENGTH_FUNC(FUNC) virtual CalcMaxLengthFunc getCalcMaxCol← LengthFunc() const override{ return FUNC; }
- #define SET_MAX_ROW_LENGTH(MAX_ROW_LENGTH) virtual CalcMaxLengthFunc getCalcMaxRow
 LengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return M←
 AX ROW LENGTH; }; }
- #define SET_MAX_COL_LENGTH(MAX_COL_LENGTH) virtual CalcMaxLengthFunc getCalcMaxCol LengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return MAX_COL_LENGTH; }; }
- #define SET_EXTRA_GLOBAL_PARAMS(...) virtual EGPVec getExtraGlobalParams() const override{ return __VA_ARGS__; }

20.61.1 Macro Definition Documentation

```
20.61.1.1 SET_CALC_MAX_COL_LENGTH_FUNC
```

20.61.1.2 SET_CALC_MAX_ROW_LENGTH_FUNC

```
\label{eq:func} \begin{tabular}{ll} \#define & SET\_CALC\_MAX\_ROW\_LENGTH\_FUNC ( \\ & FUNC \end{tabular} \begin{tabular}{ll} FUNC \end{tabular} \begin{tabular}{ll} FUNC & GetCalcMaxRowLengthFunc () & Const override \end{tabular} \begin{tabular}{ll} FUNC; \end{tabular} \begin{tabular}{ll} FUNC & GetCalcMaxRowLengthFunc () & Const override \end{tabular} \begin{tabular}{ll} FUNC; \end{tabular}
```

20.61.1.3 SET_EXTRA_GLOBAL_PARAMS

20.61.1.4 SET_MAX_COL_LENGTH #define SET_MAX_COL_LENGTH(MAX_COL_LENGTH) virtual CalcMaxLengthFunc getCalcMaxColLengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return MAX_COL_LENGTH; }; 20.61.1.5 SET_MAX_ROW_LENGTH #define SET_MAX_ROW_LENGTH(MAX_ROW_LENGTH) virtual CalcMaxLengthFunc getCalcMaxRowLengthFunc() const override{ return [](unsigned int, unsigned int, const std::vector<double> &){ return MAX_ROW_LENGTH; }; 20.61.1.6 SET_ROW_BUILD_CODE #define SET_ROW_BUILD_CODE(CODE) virtual std::string getRowBuildCode() const override{ return CODE; } 20.61.1.7 SET_ROW_BUILD_STATE_VARS #define SET_ROW_BUILD_STATE_VARS(...) virtual ParamValVec getRowBuildStateVars() const override{ return __VA_A↔ RGS__; } 20.62 initVarSnippet.cc File Reference #include "initVarSnippet.h" **Functions** • IMPLEMENT_SNIPPET (InitVarSnippet::Uninitialised) IMPLEMENT_SNIPPET (InitVarSnippet::Constant) IMPLEMENT SNIPPET (InitVarSnippet::Uniform) • IMPLEMENT_SNIPPET (InitVarSnippet::Normal) IMPLEMENT_SNIPPET (InitVarSnippet::Exponential) IMPLEMENT_SNIPPET (InitVarSnippet::Gamma) 20.62.1 Function Documentation **20.62.1.1 IMPLEMENT_SNIPPET()** [1/6] IMPLEMENT_SNIPPET (InitVarSnippet::Uninitialised)

InitVarSnippet::Constant)

20.62.1.2 IMPLEMENT_SNIPPET() [2/6]

IMPLEMENT_SNIPPET (

Classes

- class InitVarSnippet::Base
- class InitVarSnippet::Uninitialised

Used to mark variables as uninitialised - no initialisation code will be run.

• class InitVarSnippet::Constant

Initialises variable to a constant value.

class InitVarSnippet::Uniform

Initialises variable by sampling from the uniform distribution.

· class InitVarSnippet::Normal

Initialises variable by sampling from the normal distribution.

class InitVarSnippet::Exponential

Initialises variable by sampling from the exponential distribution.

· class InitVarSnippet::Gamma

Initialises variable by sampling from the exponential distribution.

Namespaces

InitVarSnippet

Base class for all value initialisation snippets.

Macros

#define SET_CODE(CODE) virtual std::string getCode() const override{ return CODE; }

20.63.1 Macro Definition Documentation

20.64 input.cc File Reference

```
#include "input.h"
#include <limits>
#include <iostream>
#include <cmath>
#include "pugixml/pugixml.hpp"
#include "spineMLLogging.h"
#include "inputValue.h"
#include "modelProperty.h"
```

20.65 input.h File Reference

```
#include <functional>
#include <map>
#include <memory>
#include <random>
```

Classes

- · class SpineMLSimulator::Input::Base
- · class SpineMLSimulator::Input::SpikeBase
- class SpineMLSimulator::Input::InterSpikeIntervalBase
- class SpineMLSimulator::Input::RegularSpikeRate
- class SpineMLSimulator::Input::PoissonSpikeRate
- class SpineMLSimulator::Input::SpikeTime
- class SpineMLSimulator::Input::Analogue

Namespaces

- pugi
- SpineMLSimulator
- SpineMLSimulator::InputValue
- SpineMLSimulator::ModelProperty
- SpineMLSimulator::Input

20.66 inputValue.cc File Reference

```
#include "inputValue.h"
#include <iostream>
#include <sstream>
#include <cassert>
#include <cmath>
```

```
#include <cstring>
#include "pugixml/pugixml.hpp"
#include "spineMLLogging.h"
#include "spineMLUtils.h"
```

20.67 inputValue.h File Reference

```
#include <functional>
#include <map>
#include <memory>
#include <string>
#include <vector>
#include "networkClient.h"
```

Classes

- · class SpineMLSimulator::InputValue::Base
- class SpineMLSimulator::InputValue::ScalarBase
- class SpineMLSimulator::InputValue::Constant
- class SpineMLSimulator::InputValue::ConstantArray
- class SpineMLSimulator::InputValue::TimeVarying
- · class SpineMLSimulator::InputValue::TimeVaryingArray
- class SpineMLSimulator::InputValue::External
- class SpineMLSimulator::InputValue::ExternalNetwork

Namespaces

- pugi
- SpineMLSimulator
- SpineMLSimulator::InputValue

Functions

 std::unique_ptr< Base > SpineMLSimulator::InputValue::create (double dt, unsigned int numNeurons, const pugi::xml_node &node, std::map< std::string, InputValue::External *> &externalInputs)

20.68 logging.cc File Reference

```
#include "logging.h"
```

20.69 logging.h File Reference

```
#include <plog/Log.h>
#include <plog/Severity.h>
#include "gennExport.h"
```

Namespaces

- plog
- Logging

Macros

- #define LOGV_GENN LOGV_(Logging::CHANNEL_GENN)
- #define LOGD GENN LOGD (Logging::CHANNEL GENN)
- #define LOGI_GENN LOGI_(Logging::CHANNEL_GENN)
- #define LOGW_GENN LOGW_(Logging::CHANNEL_GENN)
- #define LOGE_GENN LOGE_(Logging::CHANNEL_GENN)
- #define LOGF_GENN LOGF_(Logging::CHANNEL_GENN)
- #define LOGV_CODE_GEN LOGV_(Logging::CHANNEL_CODE_GEN)
- #define LOGD_CODE_GEN LOGD_(Logging::CHANNEL_CODE_GEN)
- #define LOGI_CODE_GEN LOGI_(Logging::CHANNEL_CODE_GEN)
- #define LOGW_CODE_GEN LOGW_(Logging::CHANNEL_CODE_GEN)
- #define LOGE_CODE_GEN LOGE_(Logging::CHANNEL_CODE_GEN)
- #define LOGF_CODE_GEN LOGF_(Logging::CHANNEL_CODE_GEN)
- #define LOGV_BACKEND LOGV_(Logging::CHANNEL_BACKEND)
- #define LOGD_BACKEND LOGD_(Logging::CHANNEL_BACKEND)
- #define LOGI_BACKEND LOGI_(Logging::CHANNEL_BACKEND)
- #define LOGW_BACKEND LOGW_(Logging::CHANNEL_BACKEND)
- #define LOGE_BACKEND LOGE_(Logging::CHANNEL_BACKEND)
- #define LOGF_BACKEND LOGF_(Logging::CHANNEL_BACKEND)

Enumerations

enum Logging::Channel { Logging::CHANNEL_GENN = 0, Logging::CHANNEL_CODE_GEN = 1, Logging
 ::CHANNEL_BACKEND = 2, Logging::CHANNEL_MAX }

Functions

GENN_EXPORT void Logging::init (plog::Severity gennLevel, plog::Severity codeGeneratorLevel, plog::I←
 Appender *gennAppender, plog::IAppender *codeGeneratorAppender)

20.69.1 Macro Definition Documentation

```
20.69.1.1 LOGD_BACKEND
#define LOGD_BACKEND LOGD_(Logging::CHANNEL_BACKEND)

20.69.1.2 LOGD_CODE_GEN
#define LOGD_CODE_GEN LOGD_(Logging::CHANNEL_CODE_GEN)

20.69.1.3 LOGD_GENN
```

#define LOGD_GENN LOGD_(Logging::CHANNEL_GENN)

```
20.69.1.4 LOGE_BACKEND
#define LOGE_BACKEND LOGE_(Logging::CHANNEL_BACKEND)
20.69.1.5 LOGE_CODE_GEN
#define LOGE_CODE_GEN LOGE_(Logging::CHANNEL_CODE_GEN)
20.69.1.6 LOGE_GENN
#define LOGE_GENN LOGE_(Logging::CHANNEL_GENN)
20.69.1.7 LOGF_BACKEND
#define LOGF_BACKEND LOGF_(Logging::CHANNEL_BACKEND)
20.69.1.8 LOGF_CODE_GEN
#define LOGF_CODE_GEN LOGF_(Logging::CHANNEL_CODE_GEN)
20.69.1.9 LOGF_GENN
#define LOGF_GENN LOGF_(Logging::CHANNEL_GENN)
20.69.1.10 LOGI_BACKEND
#define LOGI_BACKEND LOGI_(Logging::CHANNEL_BACKEND)
20.69.1.11 LOGI_CODE_GEN
#define LOGI_CODE_GEN LOGI_(Logging::CHANNEL_CODE_GEN)
20.69.1.12 LOGI_GENN
#define LOGI_GENN LOGI_(Logging::CHANNEL_GENN)
20.69.1.13 LOGV_BACKEND
#define LOGV_BACKEND LOGV_(Logging::CHANNEL_BACKEND)
20.69.1.14 LOGV_CODE_GEN
#define LOGV_CODE_GEN LOGV_(Logging::CHANNEL_CODE_GEN)
```

```
20.69.1.15 LOGV_GENN

#define LOGV_GENN LOGV_(Logging::CHANNEL_GENN)

20.69.1.16 LOGW_BACKEND

#define LOGW_BACKEND LOGW_(Logging::CHANNEL_BACKEND)

20.69.1.17 LOGW_CODE_GEN

#define LOGW_CODE_GEN LOGW_(Logging::CHANNEL_CODE_GEN)

20.69.1.18 LOGW_GENN

#define LOGW_GENN LOGW_(Logging::CHANNEL_GENN)
```

20.70 logOutput.cc File Reference

```
#include "logOutput.h"
#include <algorithm>
#include <limits>
#include <iostream>
#include <cassert>
#include <cmath>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include "spineMLLogging.h"
#include "spineMLUtils.h"
```

20.71 logOutput.h File Reference

```
#include <fstream>
#include <set>
#include <string>
#include <vector>
#include "modelProperty.h"
#include "networkClient.h"
```

Classes

- · class SpineMLSimulator::LogOutput::Base
- class SpineMLSimulator::LogOutput::AnalogueBase
- class SpineMLSimulator::LogOutput::AnalogueFile
- class SpineMLSimulator::LogOutput::AnalogueExternal
- class SpineMLSimulator::LogOutput::AnalogueNetwork
- · class SpineMLSimulator::LogOutput::Event

Namespaces

pugi

- · filesystem
- SpineMLSimulator
- SpineMLSimulator::LogOutput

20.72 logWriter.h File Reference

20.73 model_preprocessor.py File Reference

Classes

• class pygenn.model preprocessor.Variable

Class holding information about GeNN variables.

· class pygenn.model_preprocessor.ExtraGlobalVariable

Class holding information about GeNN extra global pointer variable.

Namespaces

· pygenn.model_preprocessor

Functions

• def pygenn.model_preprocessor.prepare_model (model, param_space, var_space, pre_var_space=None, post_var_space=None, model_family=None)

Prepare a model by checking its validity and extracting information about variables and parameters.

• def pygenn.model_preprocessor.prepare_snippet (snippet, param_space, snippet_family)

Prepare a snippet by checking its validity and extracting information about parameters.

• def pygenn.model_preprocessor.is_model_valid (model, model_family)

Check whether the model is valid, i.e is native or derived from model_family.Custom.

• def pygenn.model preprocessor.param space to vals (model, param space)

Convert a param_space dict to ParamValues.

• def pygenn.model_preprocessor.param_space_to_val_vec (model, param_space)

Convert a param_space dict to a std::vector<double>

• def pygenn.model_preprocessor.var_space_to_vals (model, var_space)

Convert a var_space dict to VarValues.

• def pygenn.model_preprocessor.pre_var_space_to_vals (model, var_space)

Convert a var_space dict to PreVarValues.

def pygenn.model_preprocessor.post_var_space_to_vals (model, var_space)

Convert a var_space dict to PostVarValues.

Variables

- pygenn.model_preprocessor.GeNNType = namedtuple("GeNNType", ["np_dtype", "assign_ext_ptr_array", "assign_ext_ptr_single"])
- dictionary pygenn.model_preprocessor.genn_types

20.74 modelProperty.cc File Reference

```
#include "modelProperty.h"
#include <algorithm>
#include <fstream>
#include <iostream>
#include <cassert>
#include <cstring>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include "spineMLLogging.h"
```

20.75 modelProperty.h File Reference

```
#include <memory>
#include <random>
#include <vector>
#include "stateVar.h"
```

Classes

- · class SpineMLSimulator::ModelProperty::Base
- · class SpineMLSimulator::ModelProperty::Fixed
- class SpineMLSimulator::ModelProperty::ValueList
- · class SpineMLSimulator::ModelProperty::UniformDistribution
- class SpineMLSimulator::ModelProperty::NormalDistribution
- class SpineMLSimulator::ModelProperty::ExponentialDistribution

Namespaces

- pugi
- filesystem
- SpineMLSimulator
- · SpineMLSimulator::ModelProperty

Typedefs

typedef float SpineMLSimulator::scalar

Functions

• std::unique_ptr< Base > SpineMLSimulator::ModelProperty::create (const pugi::xml_node &node, const StateVar< scalar > &stateVar, unsigned int size, bool skipGeNNInitialised, const filesystem::path &basePath, const std::string &valueNamespace, const std::vector< unsigned int > *remapIndices)

20.76 models.h File Reference

```
#include <string>
#include <vector>
#include "snippet.h"
#include "initVarSnippet.h"
```

Classes

- · class Models::VarInit
- class Models::VarInitContainerBase< NumVars >
- class Models::VarInitContainerBase< 0 >
- class Models::Base

Base class for all models - in addition to the parameters snippets have, models can have state variables.

struct Models::Base::Var

A variable has a name, a type and an access type.

Namespaces

· Models

Macros

- #define DECLARE MODEL(TYPE, NUM PARAMS, NUM VARS)
- #define IMPLEMENT_MODEL(TYPE) IMPLEMENT_SNIPPET(TYPE)
- #define SET_VARS(...) virtual VarVec getVars() const override{ return __VA_ARGS__; }
- #define SET_EXTRA_GLOBAL_PARAMS(...) virtual EGPVec getExtraGlobalParams() const override{ return __VA_ARGS__;}

Enumerations

enum VarAccess { VarAccess::READ_WRITE = 0, VarAccess::READ_ONLY }

How is this variable accessed by model?

20.76.1 Macro Definition Documentation

20.76.1.1 DECLARE_MODEL

Value:

20.76.1.2 IMPLEMENT_MODEL

20.76.1.3 SET_EXTRA_GLOBAL_PARAMS

20.76.2 Enumeration Type Documentation

20.76.2.1 VarAccess

```
enum VarAccess [strong]
```

How is this variable accessed by model?

Enumerator

READ_WRITE	
READ_ONLY	This variable is both read and written by the model.

20.77 modelSpec.cc File Reference

```
#include <algorithm>
#include <numeric>
#include <typeinfo>
#include <cstdio>
#include <cmath>
#include <cassert>
#include "modelSpec.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/substitutions.h"
```

20.78 modelSpec.h File Reference

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections.

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronGroupInternal.h"
#include "synapseGroupInternal.h"
#include "currentSourceInternal.h"
```

Classes

class ModelSpec

Object used for specifying a neuronal network model.

Macros

• #define NO DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

Typedefs

typedef ModelSpec NNmodel

Enumerations

enum FloatType { , GENN_LONG_DOUBLE }

Floating point precision to use for models.

enum TimePrecision { TimePrecision::DEFAULT, TimePrecision::FLOAT, TimePrecision::DUBLE }

Precision to use for variables which store time.

Functions

• template<typename S >

Models::VarInit initVar (const typename S::ParamValues ¶ms)

Initialise a variable using an initialisation snippet.

• template<typename S >

 $std::enable_if < std::is_same < typename S::ParamValues, Snippet::ValueBase < 0 > >::value, Models:: \leftarrow VarInit >::type initVar ()$

Initialise a variable using an initialisation snippet with no parameters.

• Models::VarInit uninitialisedVar ()

Mark a variable as uninitialised.

• template<typename S >

InitSparseConnectivitySnippet::Init initConnectivity (const typename S::ParamValues ¶ms)

Initialise connectivity using a sparse connectivity snippet.

• template<typename S >

std::enable_if< std::is_same< typename S::ParamValues, Snippet::ValueBase< 0 > >::value, InitSparse ConnectivitySnippet::Init >::type initConnectivity ()

Initialise connectivity using a sparse connectivity snippet with no parameters.

InitSparseConnectivitySnippet::Init uninitialisedConnectivity ()

Mark a synapse group's sparse connectivity as uninitialised.

20.78.1 Detailed Description

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of ModelSpec for defining a neuronal network model. Part of the code generation and generated code sections.

20.78.2 Macro Definition Documentation

20.78.2.1 NO_DELAY

```
#define NO_DELAY 0
```

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

20.78.3 Typedef Documentation

20.78.3.1 NNmodel

```
typedef ModelSpec NNmodel
```

20.78.4 Enumeration Type Documentation

20.78.4.1 FloatType

```
enum FloatType
```

Floating point precision to use for models.

Enumerator

```
GENN_LONG_DOUBLE
```

20.78.4.2 TimePrecision

```
enum TimePrecision [strong]
```

Precision to use for variables which store time.

Enumerator

DEFAULT	Time uses default model precision.
FLOAT	Time uses single precision - not suitable for long simulations.
DOUBLE	Time uses double precision - may reduce performance.

20.78.5 Function Documentation

20.78.5.1 initConnectivity() [1/2]

Initialise connectivity using a sparse connectivity snippet.

Template Parameters

S type of sparse connectivitiy initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

Parameters

params parameters for snippet wrapped in S::ParamValues object.

Returns

InitSparseConnectivitySnippet::Init object for passing to ModelSpec::addSynapsePopulation

```
20.78.5.2 initConnectivity() [2/2]

template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Init
SparseConnectivitySnippet::Init>::type initConnectivity ( ) [inline]
```

Initialise connectivity using a sparse connectivity snippet with no parameters.

Template Parameters

S | type of sparse connectivity initialisation snippet (derived from InitSparseConnectivitySnippet::Base).

Returns

InitSparseConnectivitySnippet::Init object for passing to ModelSpec::addSynapsePopulation

Initialise a variable using an initialisation snippet.

Template Parameters

S | type of variable initialisation snippet (derived from InitVarSnippet::Base).

Parameters

params parameters for snippet wrapped in S::ParamValues object.

Returns

Models::VarInit object for use within model's VarValues

```
20.78.5.4 initVar() [2/2]

template<typename S >
std::enable_if<std::is_same<typename S::ParamValues, Snippet::ValueBase<0> >::value, Models←
::VarInit>::type initVar ( ) [inline]
```

Initialise a variable using an initialisation snippet with no parameters.

Template Parameters

type of variable initialisation snippet (derived from InitVarSnippet::Base).

Returns

Models::VarInit object for use within model's VarValues

20.78.5.5 uninitialisedConnectivity()

```
InitSparseConnectivitySnippet::Init uninitialisedConnectivity ( ) [inline]
```

Mark a synapse group's sparse connectivity as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the connectivity from host to device during initializeSparse function (and, if necessary generate any additional data structures it requires)

20.78.5.6 uninitialisedVar()

```
Models::VarInit uninitialisedVar ( ) [inline]
```

Mark a variable as uninitialised.

This means that the backend will not generate any automatic initialization code, but will instead copy the variable from host to device during initializeSparse function

20.79 modelSpecInternal.h File Reference

```
#include "modelSpec.h"
```

Classes

class ModelSpecInternal

20.80 networkClient.cc File Reference

```
#include "networkClient.h"
#include <stdexcept>
#include <cstring>
#include "spineMLLogging.h"
```

20.81 networkClient.h File Reference

```
#include <iostream>
#include <string>
#include <vector>
#include <arpa/inet.h>
#include <netinet/in.h>
#include <netinet/tcp.h>
#include <sys/socket.h>
#include <sys/types.h>
```

```
#include <unistd.h>
#include "spineMLLogging.h"
```

Classes

· class SpineMLSimulator::NetworkClient

Namespaces

SpineMLSimulator

20.82 neuronGroup.cc File Reference

```
#include "neuronGroup.h"
#include <algorithm>
#include <cmath>
#include "currentSourceInternal.h"
#include "logging.h"
#include "neuronGroupInternal.h"
#include "synapseGroupInternal.h"
#include "gennUtils.h"
```

20.83 neuronGroup.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "neuronModels.h"
#include "variableMode.h"
```

Classes

• class NeuronGroup

20.84 neuronGroupInternal.h File Reference

```
#include "neuronGroup.h"
```

Classes

• class NeuronGroupInternal

20.85 neuronModels.cc File Reference

```
#include "neuronModels.h"
```

Functions

- IMPLEMENT_MODEL (NeuronModels::RulkovMap)
- IMPLEMENT MODEL (NeuronModels::Izhikevich)
- IMPLEMENT MODEL (NeuronModels::IzhikevichVariable)
- IMPLEMENT_MODEL (NeuronModels::LIF)
- IMPLEMENT_MODEL (NeuronModels::SpikeSource)
- IMPLEMENT_MODEL (NeuronModels::SpikeSourceArray)
- IMPLEMENT_MODEL (NeuronModels::Poisson)
- IMPLEMENT_MODEL (NeuronModels::PoissonNew)
- IMPLEMENT_MODEL (NeuronModels::TraubMiles)
- IMPLEMENT_MODEL (NeuronModels::TraubMilesFast)
- IMPLEMENT_MODEL (NeuronModels::TraubMilesAlt)
- IMPLEMENT_MODEL (NeuronModels::TraubMilesNStep)

20.85.1 Function Documentation

```
20.85.1.1 IMPLEMENT_MODEL() [1/12]
IMPLEMENT_MODEL (
             NeuronModels::RulkovMap )
20.85.1.2 IMPLEMENT_MODEL() [2/12]
IMPLEMENT_MODEL (
            NeuronModels::Izhikevich )
20.85.1.3 IMPLEMENT_MODEL() [3/12]
IMPLEMENT_MODEL (
             NeuronModels::IzhikevichVariable )
20.85.1.4 IMPLEMENT_MODEL() [4/12]
IMPLEMENT_MODEL (
            NeuronModels::LIF )
20.85.1.5 IMPLEMENT_MODEL() [5/12]
IMPLEMENT_MODEL (
            NeuronModels::SpikeSource )
20.85.1.6 IMPLEMENT_MODEL() [6/12]
IMPLEMENT_MODEL (
             NeuronModels::SpikeSourceArray )
```

20.85.1.7 IMPLEMENT_MODEL() [7/12]

IMPLEMENT_MODEL (

```
NeuronModels::Poisson )
20.85.1.8 IMPLEMENT_MODEL() [8/12]
IMPLEMENT_MODEL (
            NeuronModels::PoissonNew )
20.85.1.9 IMPLEMENT_MODEL() [9/12]
IMPLEMENT_MODEL (
             NeuronModels::TraubMiles )
20.85.1.10 IMPLEMENT_MODEL() [10/12]
IMPLEMENT_MODEL (
             NeuronModels::TraubMilesFast )
20.85.1.11 IMPLEMENT_MODEL() [11/12]
IMPLEMENT_MODEL (
             NeuronModels::TraubMilesAlt )
20.85.1.12 IMPLEMENT_MODEL() [12/12]
IMPLEMENT_MODEL (
             NeuronModels::TraubMilesNStep )
20.86 neuronModels.h File Reference
#include <array>
#include <functional>
#include <string>
#include <tuple>
#include <vector>
#include <cmath>
#include "models.h"
Classes
   • class NeuronModels::Base
        Base class for all neuron models.
   • class NeuronModels::RulkovMap
        Rulkov Map neuron.

    class NeuronModels::Izhikevich

        Izhikevich neuron with fixed parameters [1].

    class NeuronModels::IzhikevichVariable
```

Izhikevich neuron with variable parameters [1].

- class NeuronModels::LIF
- · class NeuronModels::SpikeSource

Empty neuron which allows setting spikes from external sources.

· class NeuronModels::SpikeSourceArray

Spike source array.

class NeuronModels::Poisson

Poisson neurons.

· class NeuronModels::PoissonNew

Poisson neurons.

class NeuronModels::TraubMiles

Hodgkin-Huxley neurons with Traub & Miles algorithm.

class NeuronModels::TraubMilesFast

Hodgkin-Huxley neurons with Traub & Miles algorithm: Original fast implementation, using 25 inner iterations.

· class NeuronModels::TraubMilesAlt

Hodgkin-Huxley neurons with Traub & Miles algorithm.

class NeuronModels::TraubMilesNStep

Hodgkin-Huxley neurons with Traub & Miles algorithm.

Namespaces

NeuronModels

Macros

- #define SET_SIM_CODE(SIM_CODE) virtual std::string getSimCode() const override{ return SIM_CODE; }
- #define SET_THRESHOLD_CONDITION_CODE(THRESHOLD_CONDITION_CODE) virtual std::string getThresholdConditionCode() const override{ return THRESHOLD_CONDITION_CODE; }
- #define SET_RESET_CODE(RESET_CODE) virtual std::string getResetCode() const override{ return RE
 SET_CODE; }
- #define SET_SUPPORT_CODE(SUPPORT_CODE) virtual std::string getSupportCode() const override{ return SUPPORT_CODE; }
- #define SET_ADDITIONAL_INPUT_VARS(...) virtual ParamValVec getAdditionalInputVars() const override{
 return VA ARGS ;}

20.86.1 Macro Definition Documentation

20.86.1.1 SET_ADDITIONAL_INPUT_VARS

20.86.1.2 SET_NEEDS_AUTO_REFRACTORY

20.86.1.3 SET_RESET_CODE

```
#define SET_RESET_CODE ( RESET\_CODE \ ) \ virtual \ std::string \ getResetCode() \ const \ override \{ \ return \ RESET\_CO \leftrightarrow DE; \ \}
```

20.86.1.4 SET_SIM_CODE

20.86.1.5 SET_SUPPORT_CODE

20.86.1.6 SET_THRESHOLD_CONDITION_CODE

20.87 optimiser.cc File Reference

```
#include "optimiser.h"
#include <algorithm>
#include <iostream>
#include <map>
#include <cudenties
#include <cstdlib>
#include <cudenties
#include <cudenties
#include <cudenties
#include <cudenties
#include <ploy/Log.h>
#include "path.h"
#include "logging.h"
#include "modelSpecInternal.h"
#include "code_generator/generateAll.h"
#include "utils.h"
```

Namespaces

- CodeGenerator
 - Helper class for generating code automatically inserts brackets, indents etc.
- CodeGenerator::CUDA
- CodeGenerator::CUDA::Optimiser

Functions

 BACKEND_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::IAppender *backend← Appender, int localHostID, const Preferences &preferences)

20.88 optimiser.cc File Reference

```
#include "optimiser.h"
#include "modelSpecInternal.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::SingleThreadedCPU
- CodeGenerator::SingleThreadedCPU::Optimiser

Functions

 BACKEND_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::I
 Appender *backendAppender, int localHostID, const Preferences &preferences)

20.89 optimiser.h File Reference

```
#include "backendExport.h"
#include "backend.h"
```

Namespaces

- plog
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- · CodeGenerator::CUDA
- · CodeGenerator::CUDA::Optimiser

Functions

• BACKEND_EXPORT Backend CodeGenerator::CUDA::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::IAppender *backend← Appender, int localHostID, const Preferences &preferences)

20.90 optimiser.h File Reference

```
#include <plog/Severity.h>
#include "backendExport.h"
#include "backend.h"
```

Namespaces

- plog
- CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::SingleThreadedCPU
- CodeGenerator::SingleThreadedCPU::Optimiser

Functions

 BACKEND_EXPORT Backend CodeGenerator::SingleThreadedCPU::Optimiser::createBackend (const ModelSpecInternal &model, const filesystem::path &outputPath, plog::Severity backendLevel, plog::I
 Appender *backendAppender, int localHostID, const Preferences &preferences)

20.91 postsynapticModels.cc File Reference

```
#include "postsynapticModels.h"
```

Functions

- IMPLEMENT MODEL (PostsynapticModels::ExpCurr)
- IMPLEMENT_MODEL (PostsynapticModels::ExpCond)
- IMPLEMENT_MODEL (PostsynapticModels::DeltaCurr)

20.91.1 Function Documentation

20.92 postsynapticModels.h File Reference

```
#include <cmath>
#include "models.h"
```

Classes

• class PostsynapticModels::Base

Base class for all postsynaptic models.

· class PostsynapticModels::ExpCurr

Exponential decay with synaptic input treated as a current value.

· class PostsynapticModels::ExpCond

Exponential decay with synaptic input treated as a conductance value.

· class PostsynapticModels::DeltaCurr

Simple delta current synapse.

Namespaces

PostsynapticModels

Macros

- #define SET_DECAY_CODE(DECAY_CODE) virtual std::string getDecayCode() const override{ return DE
 CAY_CODE; }
- #define SET_CURRENT_CONVERTER_CODE(CURRENT_CONVERTER_CODE) virtual std::string get
 ApplyInputCode() const override{ return "\$(Isyn) += " CURRENT_CONVERTER_CODE ";"; }
- #define SET_APPLY_INPUT_CODE(APPLY_INPUT_CODE) virtual std::string getApplyInputCode() const override{ return APPLY_INPUT_CODE; }
- #define SET_SUPPORT_CODE(SUPPORT_CODE) virtual std::string getSupportCode() const override{ return SUPPORT_CODE;}

20.92.1 Macro Definition Documentation

20.92.1.1 SET_APPLY_INPUT_CODE

20.92.1.2 SET_CURRENT_CONVERTER_CODE

20.92.1.3 SET_DECAY_CODE

```
#define SET_DECAY_CODE ( {\it DECAY\_CODE}~)~ {\it virtual std::string getDecayCode()}~ {\it const override} \{~ {\it return DECAY\_CO} \leftarrow {\it DE;}~ \}
```

20.92.1.4 SET_SUPPORT_CODE

```
 \begin{tabular}{ll} \#define SET\_SUPPORT\_CODE ( & & SUPPORT\_CODE ) & virtual std::string getSupportCode() & const override { return SUPP} $$ ORT\_CODE; $$ \}
```

20.93 presynapticUpdateStrategy.cc File Reference

```
#include "presynapticUpdateStrategy.h"
#include <numeric>
#include <cuda_runtime.h>
#include "gennUtils.h"
#include "modelSpecInternal.h"
#include "code_generator/codeGenUtils.h"
#include "code_generator/codeStream.h"
```

```
#include "code_generator/substitutions.h"
#include "backend.h"
#include "utils.h"
```

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- CodeGenerator::CUDA::PresynapticUpdateStrategy

20.94 presynapticUpdateStrategy.h File Reference

```
#include "code_generator/backendBase.h"
```

Classes

- class CodeGenerator::CUDA::PresynapticUpdateStrategy::Base
- class CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpan

Presynaptic parallelism.

• class CodeGenerator::CUDA::PresynapticUpdateStrategy::PostSpan

Postsynaptic parallelism.

 $\bullet \ \ class\ Code Generator :: CUDA :: Presynaptic Update Strategy :: Post Span Bitmask$

Postsynaptic parallelism.

• class CodeGenerator::CUDA::PresynapticUpdateStrategy::PreSpanProcedural

Presynaptic parallelism with procedural connectivity.

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

- CodeGenerator::CUDA
- · CodeGenerator::CUDA::PresynapticUpdateStrategy

20.95 sharedLibraryModel.h File Reference

```
#include <algorithm>
#include <array>
#include <iostream>
#include <string>
#include <vector>
#include <utility>
#include <utility>
#include <bitset>
#include <dlfcn.h>
```

Classes

class SharedLibraryModel< scalar >

20.96 simulator.cc File Reference

```
#include "simulator.h"
#include <functional>
#include <iostream>
#include <map>
#include <memory>
#include <random>
#include <set>
#include <string>
#include <cassert>
#include <cmath>
#include <cstdlib>
#include <dlfcn.h>
#include "path.h"
#include "pugixml/pugixml.hpp"
#include <plog/Log.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "spineMLLogging.h"
#include "spineMLUtils.h"
#include "connectors.h"
#include "input.h"
#include "inputValue.h"
#include "logOutput.h"
#include "modelProperty.h"
#include "stateVar.h"
#include "timer.h"
```

Namespaces

SpineMLSimulator

20.97 simulator.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <tuple>
#include <plog/Severity.h>
#include <plog/Appenders/ConsoleAppender.h>
#include "input.h"
#include "inputValue.h"
#include "logOutput.h"
#include "modelProperty.h"
```

Classes

· class SpineMLSimulator::Simulator

Namespaces

SpineMLSimulator

20.98 snippet.h File Reference

```
#include <algorithm>
#include <functional>
#include <string>
#include <vector>
#include <cassert>
#include "gennExport.h"
```

Classes

- class Snippet::ValueBase< NumVars >
- class Snippet::ValueBase< 0 >
- · class Snippet::Base

Base class for all code snippets.

struct Snippet::Base::EGP

An extra global parameter has a name and a type.

• struct Snippet::Base::ParamVal

Additional input variables, row state variables and other things have a name, a type and an initial value.

• struct Snippet::Base::DerivedParam

A derived parameter has a name and a function for obtaining its value.

class Snippet::Init< SnippetBase >

Namespaces

Snippet

Macros

- #define DECLARE_SNIPPET(TYPE, NUM_PARAMS)
- #define IMPLEMENT_SNIPPET(TYPE) TYPE *TYPE::s_Instance = NULL
- #define SET_PARAM_NAMES(...) virtual StringVec getParamNames() const override{ return __VA_ARGS←
 __;}
- #define SET_DERIVED_PARAMS(...) virtual DerivedParamVec getDerivedParams() const override{ return __VA_ARGS__;}

20.98.1 Macro Definition Documentation

20.98.1.1 DECLARE_SNIPPET

Value:

```
private:
    GENN_EXPORT static TYPE *s_Instance;
public:
    static const TYPE *getInstance()
    {
        if (s_Instance == NULL)
        {
            s_Instance = new TYPE;
        }
}
```

```
return s_Instance;
}
typedef Snippet::ValueBase<NUM_PARAMS> ParamValues
```

20.98.1.2 IMPLEMENT_SNIPPET

20.98.1.3 SET_DERIVED_PARAMS

```
#define SET_DERIVED_PARAMS( ... ) virtual DerivedParamVec getDerivedParams() const override{ return \__VA\_A \leftarrow RGS\__; }
```

20.98.1.4 SET_PARAM_NAMES

20.99 spikeRecorder.h File Reference

```
#include <algorithm>
#include <fstream>
#include <iterator>
#include <list>
#include <tuple>
#include <vector>
```

Classes

· class SpikeWriterText

Class to write spikes to text file.

· class SpikeWriterTextCached

Class to write spikes to text file, caching in memory before writing.

class SpikeRecorder
 Writer >

Class to read spikes from neuron groups.

20.100 stateVar.h File Reference

```
#include <functional>
#include "spineMLLogging.h"
```

Classes

class SpineMLSimulator::StateVar< T >

Namespaces

SpineMLSimulator

20.101 substitutions.h File Reference

```
#include <map>
#include <stdexcept>
#include <string>
#include <cassert>
#include "logging.h"
#include "codeGenUtils.h"
```

Classes

class CodeGenerator::Substitutions

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.102 synapseGroup.cc File Reference

```
#include "synapseGroup.h"
#include <algorithm>
#include <cmath>
#include <iostream>
#include "neuronGroupInternal.h"
#include "gennUtils.h"
```

20.103 synapseGroup.h File Reference

```
#include <map>
#include <set>
#include <string>
#include <vector>
#include "gennExport.h"
#include "initSparseConnectivitySnippet.h"
#include "postsynapticModels.h"
#include "weightUpdateModels.h"
#include "synapseMatrixType.h"
#include "variableMode.h"
```

Classes

· class SynapseGroup

20.104 synapseGroupInternal.h File Reference

```
#include "synapseGroup.h"
```

Classes

· class SynapseGroupInternal

20.105 synapseMatrixType.h File Reference

Enumerations

- enum SynapseMatrixConnectivity:: unsigned int { SynapseMatrixConnectivity::DENSE = (1 << 0), SynapseMatrixConnectivity::BITMASK = (1 << 1), SynapseMatrixConnectivity::SPARSE = (1 << 2), SynapseMatrixConnectivity::PROCEDURAL = (1 << 3) }
 - < Flags defining differnet types of synaptic matrix connectivity
- enum SynapseMatrixWeight: unsigned int { SynapseMatrixWeight::GLOBAL = (1 << 5), SynapseMatrix
 Weight::INDIVIDUAL = (1 << 6), SynapseMatrixWeight::PROCEDURAL = (1 << 7), SynapseMatrix
 Weight::INDIVIDUAL_PSM = (1 << 8) }

SynapseMatrixType::BITMASK_GLOBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(Synapse MatrixConnectivity::BITMASK) | static_cast<unsigned int>(SynapseMatrixWeight::GLOBAL) | static cast<unsigned int>(SynapseMatrixType::SPARSE_GL OBALG = static_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE_GLOBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(SynapseMatrixTonnectivity::SPARSE) | static_cast<unsigned int>(Synapse MatrixWeight::INDIVIDUAL_PSM), Synapse MatrixWeight::INDIVIDUAL_PSM), Synapse MatrixTonnectivity::SPARSE_INDIVIDUALG = static_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE) | static_cast<unsigned int>(SynapseMatrixConnectivity::SPARSE

SynapseMatrixType::PROCEDURAL_GLOBALG = static_cast<unsigned int>(SynapseMatrixConnectivity ::PROCEDURAL) | static_cast<unsigned int>(SynapseMatrixWeight::GLOBAL), SynapseMatrixType::P ROCEDURAL_GLOBALG_INDIVIDUAL_PSM = static_cast<unsigned int>(SynapseMatrixConnectivity ::PROCEDURAL) | static_cast<unsigned int>(SynapseMatrixWeight::GLOBAL) | static_cast<unsigned int>(SynapseMatrixType::PROCEDURAL_PROCEDURAL LG = static_cast<unsigned int>(SynapseMatrixConnectivity::PROCEDURAL) | static_cast<unsigned int>(SynapseMatrixWeight::INDIV | static_cast<unsigned int>(SynapseMatrixWeight::INDIV | static_cast<unsigned int>(SynapseMatrixWeight::INDIV | IDUAL_PSM) }

Functions

- bool operator& (SynapseMatrixType type, SynapseMatrixConnectivity connType)
- bool operator& (SynapseMatrixType type, SynapseMatrixWeight weightType)
- SynapseMatrixType operator (SynapseMatrixWeight weightType, SynapseMatrixConnectivity connType)

20.105.1 Enumeration Type Documentation

20.105.1.1 SynapseMatrixConnectivity

```
enum SynapseMatrixConnectivity : unsigned int [strong]
```

< Flags defining differnet types of synaptic matrix connectivity

Enumerator

DENSE	
BITMASK	
SPARSE	
PROCEDURAL	

20.105.1.2 SynapseMatrixType

enum SynapseMatrixType : unsigned int [strong]

Enumerator

DENSE_GLOBALG	
DENSE_GLOBALG_INDIVIDUAL_PSM	
DENSE_INDIVIDUALG	
BITMASK_GLOBALG	
BITMASK_GLOBALG_INDIVIDUAL_PSM	
SPARSE_GLOBALG	
SPARSE_GLOBALG_INDIVIDUAL_PSM	
SPARSE_INDIVIDUALG	
PROCEDURAL_GLOBALG	
PROCEDURAL_GLOBALG_INDIVIDUAL_PSM	
PROCEDURAL_PROCEDURALG	

20.105.1.3 SynapseMatrixWeight

enum SynapseMatrixWeight : unsigned int [strong]

Enumerator

GLOBAL	
INDIVIDUAL	
PROCEDURAL	
INDIVIDUAL_PSM	

20.105.2 Function Documentation

```
20.105.2.1 operator&() [1/2]
bool operator & (
             SynapseMatrixType type,
             SynapseMatrixConnectivity connType ) [inline]
20.105.2.2 operator&() [2/2]
bool operator & (
             SynapseMatrixType type,
             SynapseMatrixWeight weightType ) [inline]
20.105.2.3 operator " | ()
SynapseMatrixType operator| (
             SynapseMatrixWeight weightType,
             SynapseMatrixConnectivity connType ) [inline]
20.106 teeStream.h File Reference
```

```
#include <ostream>
#include <streambuf>
#include <vector>
```

Classes

- · class CodeGenerator::TeeBuf
- · class CodeGenerator::TeeStream

Namespaces

CodeGenerator

Helper class for generating code - automatically inserts brackets, indents etc.

20.107 timer.h File Reference

```
#include <chrono>
#include <iostream>
#include <string>
#include "spineMLLogging.h"
```

Classes

- · class SpineMLSimulator::Timer
- · class SpineMLSimulator::TimerAccumulate

Namespaces

SpineMLSimulator

20.108 timer.h File Reference

```
#include <chrono>
#include <fstream>
#include <iostream>
#include <string>
```

Classes

class Timer

A generic timer which can give the current elapsed time.

· class TimerAccumulate

A timer which adds its elapsed time to an accumulator variable on destruction.

20.109 utils.h File Reference

```
#include <iostream>
#include "logging.h"
```

Macros

- #define CHECK_CU_ERRORS(call) call
- #define CHECK_CUDA_ERRORS(call)

20.109.1 Macro Definition Documentation

20.109.1.1 CHECK_CU_ERRORS

```
\begin{tabular}{ll} \# define CHECK\_CU\_ERRORS ( \\ & call \end{tabular} ) call \\ \end{tabular}
```

20.109.1.2 CHECK_CUDA_ERRORS

```
\begin{tabular}{ll} \# define \ CHECK\_CUDA\_ERRORS ( \\ call \ ) \end{tabular}
```

Value:

```
{
    cudaError_t error = call;
    if (error != cudaSuccess) {
        LOGE_BACKEND << __FILE__ << ": " << __LINE__ << ": cuda runtime error " << error << ": " << cudaGetErrorString(error); \
        exit(EXIT_FAILURE);
    }
}</pre>
```

20.110 variableMode.h File Reference

```
#include <cstdint>
```

Enumerations

```
    enum VarLocation : uint8_t {
        VarLocation::HOST = (1 << 0), VarLocation::DEVICE = (1 << 1), VarLocation::ZERO_COPY = (1 << 2),
        VarLocation::HOST_DEVICE = HOST | DEVICE,
        VarLocation::HOST_DEVICE_ZERO_COPY = HOST | DEVICE | ZERO_COPY }</li>
```

< Flags defining which memory space variables should be allocated in

Functions

bool operator& (VarLocation locA, VarLocation locB)

20.110.1 Enumeration Type Documentation

20.110.1.1 VarLocation

```
enum VarLocation : uint8_t [strong]
```

< Flags defining which memory space variables should be allocated in

Enumerator

HOST	
DEVICE	
ZERO_COPY	
HOST_DEVICE	
HOST_DEVICE_ZERO_COPY	

20.110.2 Function Documentation

20.110.2.1 operator&()

20.111 weightUpdateModels.cc File Reference

```
#include "weightUpdateModels.h"
```

Functions

IMPLEMENT_MODEL (WeightUpdateModels::StaticPulse)

- IMPLEMENT_MODEL (WeightUpdateModels::StaticPulseDendriticDelay)
- IMPLEMENT_MODEL (WeightUpdateModels::StaticGraded)
- IMPLEMENT_MODEL (WeightUpdateModels::PiecewiseSTDP)

20.111.1 Function Documentation

20.112 weightUpdateModels.h File Reference

```
#include "models.h"
```

Classes

· class WeightUpdateModels::Base

Base class for all weight update models.

class WeightUpdateModels::StaticPulse

Pulse-coupled, static synapse.

class WeightUpdateModels::StaticPulseDendriticDelay

Pulse-coupled, static synapse with heterogenous dendritic delays.

class WeightUpdateModels::StaticGraded

Graded-potential, static synapse.

• class WeightUpdateModels::PiecewiseSTDP

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse.

Namespaces

WeightUpdateModels

Macros

- #define DECLARE_WEIGHT_UPDATE_MODEL(TYPE, NUM_PARAMS, NUM_VARS, NUM_PRE_VARS, NUM_POST_VARS)
- #define SET_SIM_CODE(SIM_CODE) virtual std::string getSimCode() const override{ return SIM_CODE; }
- #define SET_EVENT_CODE(EVENT_CODE) virtual std::string getEventCode() const override{ return EV← ENT_CODE; }
- #define SET_LEARN_POST_CODE(LEARN_POST_CODE) virtual std::string getLearnPostCode() const override{ return LEARN POST CODE; }
- #define SET_SYNAPSE_DYNAMICS_CODE(SYNAPSE_DYNAMICS_CODE) virtual std::string get
 SynapseDynamicsCode() const override{ return SYNAPSE_DYNAMICS_CODE; }
- #define SET_EVENT_THRESHOLD_CONDITION_CODE(EVENT_THRESHOLD_CONDITION_CODE) virtual std::string getEventThresholdConditionCode() const override{ return EVENT_THRESHOLD_CONDITI
 ON CODE;}
- #define SET_SIM_SUPPORT_CODE(SIM_SUPPORT_CODE) virtual std::string getSimSupportCode() const override{ return SIM_SUPPORT_CODE; }
- #define SET_LEARN_POST_SUPPORT_CODE(LEARN_POST_SUPPORT_CODE) virtual std::string get
 LearnPostSupportCode() const override{ return LEARN_POST_SUPPORT_CODE; }
- #define SET_SYNAPSE_DYNAMICS_SUPPORT_CODE(SYNAPSE_DYNAMICS_SUPPORT_CODE) virtual std::string getSynapseDynamicsSuppportCode() const override{ return SYNAPSE_DYNAMICS_SUPPORT_CODE;}
- #define SET_PRE_SPIKE_CODE(PRE_SPIKE_CODE) virtual std::string getPreSpikeCode() const override{
 return PRE_SPIKE_CODE;}
- #define SET_POST_SPIKE_CODE(POST_SPIKE_CODE) virtual std::string getPostSpikeCode() const override{ return POST_SPIKE_CODE; }
- #define SET_PRE_VARS(...) virtual VarVec getPreVars() const override{ return __VA_ARGS__; }
- #define SET_POST_VARS(...) virtual VarVec getPostVars() const override{ return __VA_ARGS__; }
- #define SET_NEEDS_PRE_SPIKE_TIME(PRE_SPIKE_TIME_REQUIRED) virtual bool isPreSpikeTime
 Required() const override{ return PRE_SPIKE_TIME_REQUIRED; }

20.112.1 Macro Definition Documentation

20.112.1.1 DECLARE WEIGHT UPDATE MODEL

Value:

20.112.1.2 SET_EVENT_CODE

```
#define SET_EVENT_CODE(  {\it EVENT\_CODE} \ ) \ \ {\it virtual std::string getEventCode()} \ \ {\it const override} \{ \ \ {\it return EVENT\_CO} \hookrightarrow {\it DE;} \ \}
```

20.112.1.3 SET_EVENT_THRESHOLD_CONDITION_CODE

20.112.1.4 SET_LEARN_POST_CODE

20.112.1.5 SET_LEARN_POST_SUPPORT_CODE

20.112.1.6 SET_NEEDS_POST_SPIKE_TIME

20.112.1.7 SET_NEEDS_PRE_SPIKE_TIME

20.112.1.8 SET_POST_SPIKE_CODE

20.112.1.9 SET_POST_VARS

20.112.1.10 SET_PRE_SPIKE_CODE

```
#define SET_PRE_SPIKE_CODE (  PRE\_SPIKE\_CODE \ ) \ \ virtual \ \ std::string \ getPreSpikeCode() \ \ const \ \ override \{ \ return \ P \leftarrow RE\_SPIKE\_CODE; \}
```

20.112.1.11 SET_PRE_VARS

20.112.1.12 SET_SIM_CODE

20.112.1.13 SET_SIM_SUPPORT_CODE

20.112.1.14 SET_SYNAPSE_DYNAMICS_CODE

20.112.1.15 SET_SYNAPSE_DYNAMICS_SUPPORT_CODE

```
#define SET_SYNAPSE_DYNAMICS_SUPPORT_CODE(

SYNAPSE_DYNAMICS_SUPPORT_CODE) virtual std::string getSynapseDynamicsSuppport

Code() const override{ return SYNAPSE_DYNAMICS_SUPPORT_CODE; }
```

428 REFERENCES

References

[1] Eugene M Izhikevich. Simple model of spiking neurons. *IEEE Transactions on neural networks*, 14(6):1569–1572, 2003. 7, 8, 9, 64, 83, 222, 223, 225, 226, 408, 409

- [2] Abigail Morrison, Markus Diesmann, and Wulfram Gerstner. Phenomenological models of synaptic plasticity based on spike timing. *Biological Cybernetics*, 98:459–478, 2008. 34
- [3] T. Nowotny. Parallel implementation of a spiking neuronal network model of unsupervised olfactory learning on NVidia CUDA. In P. Sobrevilla, editor, *IEEE World Congress on Computational Intelligence*, pages 3238–3245, Barcelona, 2010. IEEE. 34
- [4] Thomas Nowotny, Ramón Huerta, Henry DI Abarbanel, and Mikhail I Rabinovich. Self-organization in the olfactory system: one shot odor recognition in insects. *Biological cybernetics*, 93(6):436–446, 2005. 11, 289
- [5] Nikolai F Rulkov. Modeling of spiking-bursting neural behavior using two-dimensional map. *Physical Review E*, 65(4):041922, 2002. 289
- [6] Marcel Stimberg, Dan F. M. Goodman, and Thomas Nowotny. Brian2genn: a system for accelerating a large variety of spiking neural networks with graphics hardware. *bioRxiv*, 2018. 14
- [7] R. D. Traub and R. Miles. Neural Networks of the Hippocampus. Cambridge University Press, New York, 1991. 11, 12, 351

Index

init	pygenn::genn_groups::CurrentSource, 175
pygenn::genn_groups::CurrentSource, 175	pygenn::genn_groups::NeuronGroup, 248
pygenn::genn_groups::Group, 218	pygenn::genn_groups::SynapseGroup, 322
pygenn::genn_groups::NeuronGroup, 247	add_neuron_population
pygenn::genn_groups::SynapseGroup, 321	pygenn::genn_model::GeNNModel, 210
pygenn::genn_model::GeNNModel, 209	add_synapse_population
pygenn::model_preprocessor::ExtraGlobal←	pygenn::genn_model::GeNNModel, 211
Variable, 196	add to
pygenn::model_preprocessor::Variable, 366	pygenn::genn_groups::CurrentSource, 176
initpy, 371	pygenn::genn_groups::NeuronGroup, 248
\sim BackendBase	pygenn::genn_groups::SynapseGroup, 322
CodeGenerator::BackendBase, 137	addCurrentSource
\sim Base	ModelSpec, 234, 235
Snippet::Base, 156	addFuncSubstitution
SpineMLSimulator::Input::Base, 164	CodeGenerator::Substitutions, 318
SpineMLSimulator::InputValue::Base, 166	addInSyn
SpineMLSimulator::LogOutput::Base, 167	•
SpineMLSimulator::ModelProperty::Base, 168	NeuronGroup, 253
~ModelSpec	addNeuronPopulation
ModelSpec, 234	ModelSpec, 236
~NetworkClient	addOutSyn
SpineMLSimulator::NetworkClient, 246	NeuronGroup, 253
~Scope	addParamNameSubstitution
CodeGenerator::CodeStream::Scope, 292	CodeGenerator::Substitutions, 318
~SharedLibraryModel	addParamValueSubstitution
SharedLibraryModel, 293	CodeGenerator::Substitutions, 318
~Simulator	addPresynapticUpdateStrategy
SpineMLSimulator::Simulator, 299	CodeGenerator::CUDA::Backend, 110
~SpikeWriterTextCached	addSpkEventCondition
SpikeWriterTextCached, 311	NeuronGroup, 253
~Timer	addSynapsePopulation
SpineMLSimulator::Timer, 346	ModelSpec, 237-239
Timer, 345	addType
~TimerAccumulate	CodeGenerator::BackendBase, 137
SpineMLSimulator::TimerAccumulate, 347	addVarNameSubstitution
TimerAccumulate, 347	CodeGenerator::Substitutions, 318
00_MainPage.dox, 370	addVarSubstitution
01_Installation.dox, 370	CodeGenerator::Substitutions, 319
02 Quickstart.dox, 370	addVarValueSubstitution
03_Examples.dox, 370	CodeGenerator::Substitutions, 319
05 SpineML.dox, 370	allocateExtraGlobalParam
06_Brian2GeNN.dox, 370	SharedLibraryModel, 294
07 PyGeNN.dox, 370	allocateMem
09 ReleaseNotes.dox, 370	SharedLibraryModel, 294
-	Analogue
10_UserManual.dox, 371	SpineMLSimulator::Input::Analogue, 101
11_Tutorial.dox, 371	AnalogueBase
12_Tutorial.dox, 371	SpineMLSimulator::LogOutput::AnalogueBase,
13_UserGuide.dox, 371	102
14_Credits.dox, 371	
	AnalogueExternal
access Madalau Panau Vari 2005	SpineMLSimulator::LogOutput::AnalogueExterna
Models::Base::Var, 365	103
add_current_source	AnalogueFile
pygenn::genn_model::GeNNModel, 210	SpineMLSimulator::LogOutput::AnalogueFile, 104
add_extra_global_param	AnalogueNetwork

430 INDEX

SpineMLSimulator::LogOutput::AnalogueNetwork,	GenerateRunBase, 206
AnalogueRecorder	CHECK_CU_ERRORS
	utils.h, 422
AnalogueRecorder, 106	CHECK CUDA ERRORS
record, 107	utils.h, 422
AnalogueRecorder< T >, 106	CalcMaxLengthFunc
analogueRecorder.h, 371	
apply	InitSparseConnectivitySnippet::Base, 150
CodeGenerator::Substitutions, 319	calcNumTimesteps
SpineMLSimulator::Input::Analogue, 101	SpineMLSimulator::Simulator, 299
SpineMLSimulator::Input::Base, 165	CB
SpineMLSimulator::Input::InterSpikeIntervalBase,	CodeGenerator::CodeStream::CB, 169
222	ceilDivide
SpineMLSimulator::Input::SpikeTime, 309	CodeGenerator, 72
applyCheckUnreplaced	Channel
CodeGenerator::Substitutions, 319	Logging, 82
applyScalar	checkNumDelaySlots
• • •	NeuronGroup, 253
SpineMLSimulator::InputValue::ScalarBase, 292	checkUnreplacedVariables
automaticCopy	CodeGenerator, 72
CodeGenerator::PreferencesBase, 282	codeGenUtils.cc, 375
DACKEND EVPORT	•
BACKEND_EXPORT	MathsFunc, 376
backendExport.h, 374	codeGenUtils.h, 376
Backend	CodeGenerator, 71
CodeGenerator::CUDA::Backend, 109	ceilDivide, 72
CodeGenerator::SingleThreadedCPU::Backend,	checkUnreplacedVariables, 72
123	ensureFtype, 73
backend.cc, 371	functionSubstitute, 73
backend.h, 372, 373	generateAll, 73
backend_log_level	generateInit, 73
pygenn::genn_model::GeNNModel, 217	generateMPI, 73
backend_modules	generateMSBuild, 74
pygenn::genn_model, 92	generateMakefile, 73
BackendBase	generateNeuronUpdate, 74
	- ·
CodeGenerator::BackendBase, 137	generateRunner, 74
backendBase.cc, 373	generateSupportCode, 74
TYPE, 373	generateSynapseUpdate, 74
backendBase.h, 374	neuronSubstitutionsInSynapticCode, 74
backendExport.h, 374	operator<<, 75
BACKEND_EXPORT, 374	padSize, 75
Base	postNeuronSubstitutionsInSynapticCode, 76
SpineMLSimulator::Input::Base, 164	preNeuronSubstitutionsInSynapticCode, 76
SpineMLSimulator::InputValue::Base, 166	regexFuncSubstitute, 77
SpineMLSimulator::LogOutput::Base, 167	regexVarSubstitute, 77
SpineMLSimulator::ModelProperty::Base, 168	substitute, 77
binomial.cc, 374	writePreciseString, 77
binomialInverseCDF, 375	CodeGenerator::BackendBase, 133
binomial.h, 375	~BackendBase, 137
binomialInverseCDF, 375	•
	addType, 137
binomialInverseCDF	BackendBase, 137
binomial.cc, 375	genAllocateMemPreamble, 137
binomial.h, 375	genArray, 137
BlockSizeSelect	genCurrentSpikeLikeEventPull, 138
CodeGenerator::CUDA, 78	genCurrentSpikeLikeEventPush, 138
blockSizeSelectMethod	genCurrentTrueSpikePull, 138
CodeGenerator::CUDA::Preferences, 280	genCurrentTrueSpikePush, 138
build	genCurrentVariablePull, 138
pygenn::genn_model::GeNNModel, 212	genCurrentVariablePush, 139
buildAndRun	genCurrentVariablePushPull, 139

INDEX 431

genDefinitionsInternalPreamble, 139	genCurrentVariablePush, 111
genDefinitionsPreamble, 139	genDefinitionsInternalPreamble, 111
genExtraGlobalParamAllocation, 139	genDefinitionsPreamble, 111
genExtraGlobalParamDefinition, 140	genExtraGlobalParamAllocation, 112
genExtraGlobalParamImplementation, 140	genExtraGlobalParamDefinition, 112
genExtraGlobalParamPull, 140	genExtraGlobalParamImplementation, 112
genExtraGlobalParamPush, 140	genExtraGlobalParamPull, 112
genGlobalRNG, 140	genExtraGlobalParamPush, 112
genInit, 141	genGlobalRNG, 113
genMSBuildCompileModule, 141	genInit, 113
genMSBuildConfigProperties, 142	genMSBuildCompileModule, 114
genMSBuildImportProps, 142	genMSBuildConfigProperties, 114
genMSBuildImportTarget, 142	genMSBuildImportProps, 114
genMSBuildItemDefinitions, 142	genMSBuildImportTarget, 114
genMakefileCompileRule, 141	genMSBuildItemDefinitions, 114
genMakefileLinkRule, 141	genMakefileCompileRule, 113
genMakefilePreamble, 141	genMakefileLinkRule, 113
genNeuronUpdate, 142	genMakefilePreamble, 113
genPopVariableInit, 143	genNeuronUpdate, 114
genPopulationRNG, 143	genPopVariableInit, 115
genReturnFreeDeviceMemoryBytes, 143	genPopulationRNG, 115
genRunnerPreamble, 143	genReturnFreeDeviceMemoryBytes, 115
genScalar, 143	genRunnerPreamble, 115
genStepTimeFinalisePreamble, 144	genStepTimeFinalisePreamble, 116
genSynapseUpdate, 144	genSynapseUpdate, 116
genSynapseVariableRowlnit, 145	genSynapseVariableRowInit, 117
genTimer, 145	genTimer, 117
genVariableAllocation, 145	genVariableAllocation, 117
genVariableDefinition, 145	genVariableDefinition, 117
genVariableFree, 146	genVariableFree, 117
genVariableImplementation, 146	genVariableImplementation, 118
genVariableInit, 146	genVariableInit, 118
genVariablePull, 146	genVariablePull, 118
genVariablePush, 146	genVariablePush, 118
genVariablePushPull, 147	getChosenCUDADevice, 118
getDeviceMemoryBytes, 147	getChosenDeviceID, 119
getLocalHostID, 147	getDeviceMemoryBytes, 119
getSize, 147	getFloatAtomicAdd, 119
getSynapticMatrixRowStride, 147	getKernelBlockSize, 119
getVarPrefix, 147	getNVCCFlags, 119
GroupHandler, 136	getNumInitialisationRNGStreams, 119
Handler, 136	getNumPostsynapticUpdateThreads, 119
isAutomaticCopyEnabled, 147	getNumPresynapticUpdateThreads, 119
isGlobalRNGRequired, 148	getNumSynapseDynamicsThreads, 119
isPostsynapticRemapRequired, 148	getRuntimeVersion, 120
isSynRemapRequired, 148	getSynapticMatrixRowStride, 120
NeuronGroupHandler, 136	getVarPrefix, 120
NeuronGroupSimHandler, 136	isAutomaticCopyEnabled, 120
SynapseGroupHandler, 137	isGlobalRNGRequired, 120
CodeGenerator::CUDA::Backend, 107	isPostsynapticRemapRequired, 120
addPresynapticUpdateStrategy, 110	isSynRemapRequired, 120
Backend, 109	KernelNames, 121
genAllocateMemPreamble, 110	CodeGenerator::CUDA::Optimiser, 79
genCurrentSpikeLikeEventPull, 110	createBackend, 79
genCurrentSpikeLikeEventPush, 110	CodeGenerator::CUDA::Preferences, 279
genCurrentTrueSpikePull, 110	blockSizeSelectMethod, 280
genCurrentTrueSpikePush, 111	deviceSelectMethod, 280
•	
genCurrentVariablePull, 111	generateLineInfo, 280

432 INDEX

IDI 10' 000	•
manualBlockSizes, 280	operator<<, 171
manualDeviceID, 280	setSink, 171
Preferences, 280	CodeGenerator::CodeStream::CB, 169
showPtxInfo, 280	CB, 169
userNvccFlags, 280	Level, 170
CodeGenerator::CUDA::PresynapticUpdateStrategy, 79	CodeGenerator::CodeStream::OB, 261
CodeGenerator::CUDA::PresynapticUpdateStrategy::	Level, 262
Base, 158	OB, 261
genPostamble, 159	CodeGenerator::CodeStream::Scope, 292
genPreamble, 159	~Scope, 292
genUpdate, 159	Scope, 292
getNumThreads, 159	CodeGenerator::FunctionTemplate, 202
getSharedMemoryPerThread, 160	doublePrecisionTemplate, 202
getSynapticMatrixRowStride, 160	genericName, 203
isCompatible, 160	numArguments, 203
CodeGenerator::CUDA::PresynapticUpdateStrategy::	operator=, 202
PostSpan, 274	singlePrecisionTemplate, 203
genPostamble, 275	CodeGenerator::MemAlloc, 230
genPreamble, 275	device, 230
genUpdate, 275	getDeviceBytes, 230
getNumThreads, 276	getDeviceMBytes, 230
getSharedMemoryPerThread, 276	getHostBytes, 230
getSynapticMatrixRowStride, 276	getHostMBytes, 230
isCompatible, 276	getZeroCopyBytes, 230
CodeGenerator::CUDA::PresynapticUpdateStrategy::	getZeroCopyMBytes, 230
PostSpanBitmask, 276	host, 231
genPostamble, 277	operator+=, 231
genPreamble, 277	zero, 231
genUpdate, 278	zeroCopy, 231
getNumThreads, 278	CodeGenerator::PreferencesBase, 281
getSharedMemoryPerThread, 278	automaticCopy, 282
	1 2 7
getSynapticMatrixRowStride, 278	debugCode, 282
getSynapticMatrixRowStride, 278 isCompatible, 278	debugCode, 282 enableBitmaskOptimisations, 282
isCompatible, 278	enableBitmaskOptimisations, 282
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::←	enableBitmaskOptimisations, 282 logLevel, 282
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentSpikeLikeEventPush, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikePull, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpanProcedural, 285	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePull, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpanProcedural, 285 genPostamble, 286	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePush, 124 genCurrentVariablePull, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeVull, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 124
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getSharedMemoryPerThread, 286	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy::← PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamDefinition, 126
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 126 genExtraGlobalParamImplementation, 126
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentTrueSpikePush, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 126 genExtraGlobalParamImplementation, 126 genExtraGlobalParamImplementation, 126 genExtraGlobalParamPull, 126
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77 BlockSizeSelect, 78	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamImplementation, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPull, 126
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77 BlockSizeSelect, 78 DeviceSelect, 78	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePull, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamImplementation, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPush, 126 genExtraGlobalParamPush, 126 genGlobalRNG, 126
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genPreamble, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77 BlockSizeSelect, 78 DeviceSelect, 78 Kernel, 79	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePush, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamImplementation, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPush, 126 genGlobalRNG, 126 genInit, 127
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 getSynapticMatrixRowStride, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genUpdate, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77 BlockSizeSelect, 78 Kernel, 79 KernelBlockSize, 78	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePush, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamDefinition, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPull, 126 genExtraGlobalRNG, 126 genInit, 127 genMSBuildCompileModule, 127
isCompatible, 278 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpan, 283 genPostamble, 283 genPreamble, 283 genUpdate, 284 getNumThreads, 284 getSharedMemoryPerThread, 284 isCompatible, 285 CodeGenerator::CUDA::PresynapticUpdateStrategy:: PreSpanProcedural, 285 genPostamble, 286 genPreamble, 286 genPreamble, 286 getNumThreads, 286 getNumThreads, 286 getSharedMemoryPerThread, 286 getSharedMemoryPerThread, 286 getSynapticMatrixRowStride, 287 isCompatible, 287 CodeGenerator::CUDA, 77 BlockSizeSelect, 78 DeviceSelect, 78 Kernel, 79	enableBitmaskOptimisations, 282 logLevel, 282 optimizeCode, 282 userCxxFlagsGNU, 282 userNvccFlagsGNU, 282 CodeGenerator::SingleThreadedCPU::Backend, 121 Backend, 123 genAllocateMemPreamble, 124 genCurrentSpikeLikeEventPull, 124 genCurrentTrueSpikeLikeEventPush, 124 genCurrentTrueSpikePush, 124 genCurrentVariablePull, 124 genCurrentVariablePull, 125 genDefinitionsInternalPreamble, 125 genDefinitionsPreamble, 125 genExtraGlobalParamAllocation, 125 genExtraGlobalParamImplementation, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPull, 126 genExtraGlobalParamPush, 126 genGlobalRNG, 126 genInit, 127

genMSBuildImportTarget, 128	pygenn::genn_groups::SynapseGroup, 328
genMSBuildItemDefinitions, 128	connectivity_initialiser
genMakefileCompileRule, 127	pygenn::genn_groups::SynapseGroup, 328
genMakefileLinkRule, 127	connectors.cc, 378
genMakefilePreamble, 127	connectors.h, 379
genNeuronUpdate, 128	Constant
genPopVariableInit, 129	SpineMLSimulator::InputValue::Constant, 173
genPopulationRNG, 128	ConstantArray
genReturnFreeDeviceMemoryBytes, 129	SpineMLSimulator::InputValue::ConstantArray, 174
genRunnerPreamble, 129	create
genStepTimeFinalisePreamble, 129	SpineMLSimulator::Connectors, 97
genSynapseUpdate, 129	SpineMLSimulator::InputValue, 98
genSynapseVariableRowInit, 130	SpineMLSimulator::ModelProperty, 99
genTimer, 130	create_cmlf_class
genVariableAllocation, 131	pygenn::genn_model, 85
genVariableDefinition, 131	create_custom_current_source_class
genVariableFree, 131	pygenn::genn_model, 86
genVariableImplementation, 131	create_custom_init_var_snippet_class
genVariableInit, 131	pygenn::genn_model, 86
genVariablePull, 132	create_custom_model_class
genVariablePush, 132	pygenn::genn_model, 87
getDeviceMemoryBytes, 132	create_custom_neuron_class
getSynapticMatrixRowStride, 132	pygenn::genn_model, 87
getVarPrefix, 132	create_custom_postsynaptic_class
isAutomaticCopyEnabled, 133	pygenn::genn_model, 88
isGlobalRNGRequired, 133	create_custom_sparse_connect_init_snippet_class
isPostsynapticRemapRequired, 133	pygenn::genn_model, 89
isSynRemapRequired, 133	create_custom_weight_update_class
CodeGenerator::SingleThreadedCPU::Optimiser, 80	pygenn::genn_model, 90
createBackend, 80	create_dpf_class
CodeGenerator::SingleThreadedCPU::Preferences, 281	pygenn::genn_model, 91
CodeGenerator::SingleThreadedCPU, 80	createBackend
CodeGenerator::Substitutions, 317	CodeGenerator::CUDA::Optimiser, 79
addFuncSubstitution, 318	CodeGenerator::SingleThreadedCPU::Optimiser,
addParamNameSubstitution, 318	80
addParamValueSubstitution, 318	current_source_model
addVarNameSubstitution, 318	pygenn::genn_groups::CurrentSource, 177
addVarSubstitution, 319	current_sources
addVarValueSubstitution, 319	pygenn::genn_model::GeNNModel, 217
apply, 319	current_spikes
applyCheckUnreplaced, 319	pygenn::genn_groups::NeuronGroup, 248
getVarSubstitution, 319	CurrentSource, 178
hasVarSubstitution, 319	CurrentSource, 178, 179
operator[], 319	getCurrentSourceModel, 179
Substitutions, 318	getDerivedParams, 179
CodeGenerator::TeeBuf, 343	getExtraGlobalParamLocation, 179
TeeBuf, 344	getName, 179
CodeGenerator::TeeStream, 344	getParams, 179
TeeStream, 344	getVarInitialisers, 180
CodeStream	getVarLocation, 180
CodeGenerator::CodeStream, 170, 171	initDerivedParams, 180
codeStream.cc, 377	isInitRNGRequired, 180
codeStream.h, 378	isSimRNGRequired, 180
connect	setExtraGlobalParamLocation, 180
SpineMLSimulator::NetworkClient, 246	setVarLocation, 180
connections_set	currentSource.cc, 379
pygenn::genn_groups::SynapseGroup, 328	currentSource.h, 379
connectivity_extra_global_params	CurrentSourceInternal, 181
/— — — — · · · ·	,

Current Course Internal 101	Davis and Davis and Vala
CurrentSourceInternal, 181	DerivedParamVec
currentSourceInternal.h, 379 CurrentSourceModels, 80	Snippet::Base, 156 device
currentSourceModels.cc, 380	
IMPLEMENT_MODEL, 380	CodeGenerator::MemAlloc, 230 DeviceSelect
currentSourceModels.h, 380	CodeGenerator::CUDA, 78
SET_INJECTION_CODE, 381	deviceSelectMethod
CurrentSourceModels::Base, 148	
getInjectionCode, 149	CodeGenerator::CUDA::Preferences, 280 doublePrecisionTemplate
CurrentSourceModels::DC, 181	CodeGenerator::FunctionTemplate, 202
getInstance, 183	dT
getParamNames, 183	pygenn::genn model::GeNNModel, 212, 213, 217
ParamValues, 182	pygeriiigeriii_modeiderviviodei, 212, 213, 217
PostVarValues, 182	EGPVec
PreVarValues, 182	Snippet::Base, 156
SET_INJECTION_CODE, 183	enableBitmaskOptimisations
VarValues, 183	CodeGenerator::PreferencesBase, 282
CurrentSourceModels::GaussianNoise, 204	end
getInstance, 205	pygenn::genn_model::GeNNModel, 213
getParamNames, 206	ensureFtype
ParamValues, 205	CodeGenerator, 73
PostVarValues, 205	Event
PreVarValues, 205	SpineMLSimulator::LogOutput::Event, 186
SET_INJECTION_CODE, 206	Exponential Distribution
VarValues, 205	SpineMLSimulator::ModelProperty::Exponential ←
DECLARE MORE	Distribution, 192
DECLARE_MODEL	External
models.h, 400	SpineMLSimulator::InputValue::External, 193
DECLARE_SNIPPET	ExternalNetwork
InitSparseConnectivitySnippet::FixedProbability,	SpineMLSimulator::InputValue::ExternalNetwork,
199	195
InitSparseConnectivitySnippet::FixedProbability NoAutopage 201	extra_global_params
NoAutapse, 201 InitSparseConnectivitySnippet::OneToOne, 262	pygenn::genn_groups::Group, 219
InitSparseConnectivitySnippet::Uninitialised, 361	
InitVarSnippet::Constant, 172	filesystem, 81
InitVarSnippet::Exponential, 192	finalize
InitVarSnippet::Gamma, 204	ModelSpec, 240
InitVarSnippet::Normal, 260	findCurrentSource
InitVarSnippet::Uniform, 359	ModelSpec, 240
InitVarSnippet::Uninitialised, 361	findNeuronGroup
snippet.h, 416	ModelSpec, 240
DECLARE_WEIGHT_UPDATE_MODEL	findSynapseGroup
weightUpdateModels.h, 425	ModelSpec, 240
WeightUpdateModels::PiecewiseSTDP, 266	Fixed
WeightUpdateModels::StaticGraded, 314	SpineMLSimulator::ModelProperty::Fixed, 197,
WeightUpdateModels::StaticPulse, 315	198
WeightUpdateModels::StaticPulseDendriticDelay,	FloatType
317	modelSpec.h, 403
DataType	free_device_mem_bytes
SpineMLSimulator::NetworkClient, 245	pygenn::genn_model::GeNNModel, 213
debugCode	freeExtraGlobalParam
CodeGenerator::PreferencesBase, 282	SharedLibraryModel, 294
default_sparse_connectivity_location	freeMem
pygenn::genn_model::GeNNModel, 212	SharedLibraryModel, 294
default_var_location	func
pygenn::genn_model::GeNNModel, 212, 217	Snippet::Base::DerivedParam, 185
delay_slots	functionSubstitute
pygenn::genn_groups::NeuronGroup, 248	CodeGenerator, 73

GENN_EXPORT gennExport.h, 388	genExtraGlobalParamDefinition CodeGenerator::BackendBase, 140
GeNNType	CodeGenerator::CUDA::Backend, 112
pygenn::model_preprocessor, 96	CodeGenerator::SingleThreadedCPU::Backend,
genAllocateMemPreamble	126
CodeGenerator::BackendBase, 137	genExtraGlobalParamImplementation
CodeGenerator::CUDA::Backend, 110	CodeGenerator::BackendBase, 140
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA::Backend, 112
124	CodeGenerator::SingleThreadedCPU::Backend,
genArray	126
CodeGenerator::BackendBase, 137	genExtraGlobalParamPull
genCurrentSpikeLikeEventPull	CodeGenerator::BackendBase, 140
CodeGenerator::BackendBase, 138	CodeGenerator::CUDA::Backend, 112
CodeGenerator::CUDA::Backend, 110	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	126
124	genExtraGlobalParamPush
genCurrentSpikeLikeEventPush	CodeGenerator::BackendBase, 140
CodeGenerator::BackendBase, 138	CodeGenerator::CUDA::Backend, 112
CodeGenerator::CUDA::Backend, 110	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	126
124	genGlobalRNG
genCurrentTrueSpikePull	CodeGenerator::BackendBase, 140
CodeGenerator::BackendBase, 138	CodeGenerator::CUDA::Backend, 113
CodeGenerator::CUDA::Backend, 110	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	126
124	genInit
genCurrentTrueSpikePush CodeGenerator::BackendBase, 138	CodeGenerator::BackendBase, 141 CodeGenerator::CUDA::Backend, 113
CodeGenerator::CUDA::Backend, 111	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	127
124	genMSBuildCompileModule
genCurrentVariablePull	CodeGenerator::BackendBase, 141
CodeGenerator::BackendBase, 138	CodeGenerator::CUDA::Backend, 114
CodeGenerator::CUDA::Backend, 111	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	127
124	genMSBuildConfigProperties
genCurrentVariablePush	CodeGenerator::BackendBase, 142
CodeGenerator::BackendBase, 139	CodeGenerator::CUDA::Backend, 114
CodeGenerator::CUDA::Backend, 111	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::SingleThreadedCPU::Backend,	127
125	genMSBuildImportProps
genCurrentVariablePushPull	CodeGenerator::BackendBase, 142
CodeGenerator::BackendBase, 139	CodeGenerator::CUDA::Backend, 114
genDefinitionsInternalPreamble	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 139	128
CodeGenerator::CUDA::Backend, 111	genMSBuildImportTarget
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 142
125	CodeGenerator::CUDA::Backend, 114
genDefinitionsPreamble	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 139	128
CodeGenerator::CUDA::Backend, 111	genMSBuildItemDefinitions
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 142
125	CodeGenerator::CUDA::Backend, 114
genExtraGlobalParamAllocation	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::BackendBase, 139	128
CodeGenerator::CUDA::Backend, 112	genMakefileCompileRule
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::BackendBase, 141
125	CodeGenerator::CUDA::Backend, 113

CodeGenerator::SingleThreadedCPU::Backend,	129
127	genScalar
genMakefileLinkRule	CodeGenerator::BackendBase, 143
CodeGenerator::BackendBase, 141	genStepTimeFinalisePreamble
CodeGenerator::CUDA::Backend, 113	CodeGenerator::BackendBase, 144
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA::Backend, 116
127	CodeGenerator::SingleThreadedCPU::Backend,
genMakefilePreamble	129
CodeGenerator::BackendBase, 141	genSynapseUpdate
CodeGenerator::CUDA::Backend, 113	CodeGenerator::BackendBase, 144
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA::Backend, 116
127	CodeGenerator::SingleThreadedCPU::Backend,
genNeuronUpdate	129
CodeGenerator::BackendBase, 142	genSynapseVariableRowInit
CodeGenerator::CUDA::Backend, 114	CodeGenerator::BackendBase, 145
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA::Backend, 117
128	CodeGenerator::SingleThreadedCPU::Backend,
genPopVariableInit	130
CodeGenerator::BackendBase, 143	genTimer
CodeGenerator::CUDA::Backend, 115	CodeGenerator::BackendBase, 145
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::CUDA::Backend, 117
129	CodeGenerator::SingleThreadedCPU::Backend,
genPopulationRNG	130
CodeGenerator::BackendBase, 143	genUpdate
CodeGenerator::CUDA::Backend, 115	CodeGenerator::CUDA::PresynapticUpdate
CodeGenerator::SingleThreadedCPU::Backend,	Strategy::Base, 159
128	CodeGenerator::CUDA::PresynapticUpdate ←
genPostamble	Strategy::PostSpan, 275
CodeGenerator::CUDA::PresynapticUpdate ←	CodeGenerator::CUDA::PresynapticUpdate ←
Strategy::Base, 159	Strategy::PostSpanBitmask, 278
CodeGenerator::CUDA::PresynapticUpdate ←	CodeGenerator::CUDA::PresynapticUpdate Otrata vivi Pir Oraci 0004
Strategy::PostSpan, 275	Strategy::PreSpan, 284
CodeGenerator::CUDA::PresynapticUpdate Ctrate and Pitmon 0.777	CodeGenerator::CUDA::PresynapticUpdate Ctrategray Presponding 200
Strategy::PostSpanBitmask, 277	Strategy::PreSpanProcedural, 286 genVariableAllocation
CodeGenerator::CUDA::PresynapticUpdate Strategy::PreSpan, 283	CodeGenerator::BackendBase, 145
CodeGenerator::CUDA::PresynapticUpdate←	CodeGenerator::CUDA::Backend, 117
Strategy::PreSpanProcedural, 286	CodeGenerator::SingleThreadedCPU::Backend,
genPreamble	131
CodeGenerator::CUDA::PresynapticUpdate←	genVariableDefinition
Strategy::Base, 159	CodeGenerator::BackendBase, 145
CodeGenerator::CUDA::PresynapticUpdate←	CodeGenerator::CUDA::Backend, 117
Strategy::PostSpan, 275	CodeGenerator::SingleThreadedCPU::Backend,
CodeGenerator::CUDA::PresynapticUpdate ←	131
Strategy::PostSpanBitmask, 277	genVariableFree
CodeGenerator::CUDA::PresynapticUpdate ←	CodeGenerator::BackendBase, 146
Strategy::PreSpan, 283	CodeGenerator::CUDA::Backend, 117
CodeGenerator::CUDA::PresynapticUpdate ←	CodeGenerator::SingleThreadedCPU::Backend,
Strategy::PreSpanProcedural, 286	131
genReturnFreeDeviceMemoryBytes	genVariableImplementation
CodeGenerator::BackendBase, 143	CodeGenerator::BackendBase, 146
CodeGenerator::CUDA::Backend, 115	CodeGenerator::CUDA::Backend, 118
CodeGenerator::SingleThreadedCPU::Backend,	CodeGenerator::SingleThreadedCPU::Backend,
129	131
genRunnerPreamble	genVariableInit
CodeGenerator::BackendBase, 143	CodeGenerator::BackendBase, 146
CodeGenerator::CUDA::Backend, 115	CodeGenerator::CUDA::Backend, 118
Code Generator :: Single Threaded CPU :: Backend,	${\tt CodeGenerator::SingleThreadedCPU::Backend,}$

131	generateSynapseUpdate
genVariablePull	CodeGenerator, 74
CodeGenerator::BackendBase, 146	generateSynapseUpdate.cc, 385
CodeGenerator::CUDA::Backend, 118	generateSynapseUpdate.h, 386
CodeGenerator::SingleThreadedCPU::Backend,	genericName
132	CodeGenerator::FunctionTemplate, 203
genVariablePush	genn_groups.py, 386
CodeGenerator::BackendBase, 146	genn_model.py, 386
CodeGenerator::CUDA::Backend, 118	genn_types
CodeGenerator::SingleThreadedCPU::Backend,	pygenn::model_preprocessor, 96
132	gennExport.h, 387
genVariablePushPull	GENN_EXPORT, 388
CodeGenerator::BackendBase, 147	gennUtils.cc, 388
generateAll	gennUtils.h, 388
CodeGenerator, 73	-
	get
generateAll.cc, 381	SpineMLSimulator::StateVar, 312
generateAll.h, 381	SpineMLSimulator::Timer, 346
generateInit	SpineMLSimulator::TimerAccumulate, 348
CodeGenerator, 73	Timer, 345
generatelnit.cc, 381	TimerAccumulate, 347
generatelini.h, 382	get_sparse_post_inds
generateLineInfo	pygenn::genn_groups::SynapseGroup, 322
CodeGenerator::CUDA::Preferences, 280	get_sparse_pre_inds
generateMPI.cc, 382	pygenn::genn_groups::SynapseGroup, 322
generateMPI.h, 383	get_var_values
generateMPI	pygenn::genn_groups::SynapseGroup, 323
CodeGenerator, 73	getAdditionalInputVars
generateMSBuild	NeuronModels::Base, 154
CodeGenerator, 74	getApp
generateMSBuild.cc, 383	GenerateRunBase, 207
generateMSBuild.h, 383	getApplyInputCode
generateMakefile	PostsynapticModels::Base, 158
CodeGenerator, 73	PostsynapticModels::DeltaCurr, 184
generateMakefile.cc, 382	PostsynapticModels::ExpCond, 188
generateMakefile.h, 382	PostsynapticModels::ExpCurr, 190
generateNeuronUpdate	getArray
CodeGenerator, 74	SharedLibraryModel, 294
generateNeuronUpdate.cc, 384	getBackPropDelaySteps
generateNeuronUpdate.h, 384	SynapseGroup, 333
generateRun.h, 384	getBuffer
GenerateRunBase, 206	SpineMLSimulator::InputValue::External, 194
buildAndRun, 206	getBufferBegin
GenerateRunBase, 206	SpineMLSimulator::InputValue::External, 194
getApp, 207	getBufferEnd
getExitCode, 207	SpineMLSimulator::InputValue::External, 194
getExperimentName, 207	getCalcMaxColLengthFunc
getOutDir, 207	InitSparseConnectivitySnippet::Base, 150
parseCommandLine, 207	getCalcMaxRowLengthFunc
runTools, 207	InitSparseConnectivitySnippet::Base, 150
writeSizes, 207	getChosenCUDADevice
generateRunner	CodeGenerator::CUDA::Backend, 118
CodeGenerator, 74	getChosenDeviceID
generateRunner.cc, 384	CodeGenerator::CUDA::Backend, 119
generateRunner.h, 385	getClusterHostID
generateSupportCode	NeuronGroup, 253
CodeGenerator, 74	SynapseGroup, 333
generateSupportCode.cc, 385	getCode
generateSupportCode.h, 385	InitVarSnippet::Base, 151

and Commontivity Initialians	Canavata Dun Daga 2007
getConnectivityInitialiser	GenerateRunBase, 207
SynapseGroup, 333	getExperimentName
getCurrentQueueOffset	GenerateRunBase, 207
NeuronGroup, 254	getExternalInput
getCurrentSourceModel	SpineMLSimulator::Simulator, 300
CurrentSource, 179	getExternalLogger
getCurrentSources	SpineMLSimulator::Simulator, 300
NeuronGroup, 254	getExtraGlobalParamIndex
GetCurrentSpikeCountFunc	InitSparseConnectivitySnippet::Base, 150
SpikeRecorder, 303	Models::Base, 152
GetCurrentSpikesFunc	getExtraGlobalParamLocation
SpikeRecorder, 303	CurrentSource, 179
getDecayCode	NeuronGroup, 254
PostsynapticModels::Base, 158	getExtraGlobalParams
PostsynapticModels::ExpCond, 188	InitSparseConnectivitySnippet::Base, 150
PostsynapticModels::ExpCurr, 190	Models::Base, 152
getDelaySteps	NeuronModels::Poisson, 269
SynapseGroup, 333	NeuronModels::SpikeSourceArray, 307
getDendriticDelayLocation	getFloatAtomicAdd
SynapseGroup, 333	CodeGenerator::CUDA::Backend, 119
getDendriticDelayOffset	getFreeDeviceMemBytes
SynapseGroup, 334	SharedLibraryModel, 294
getDerivedParams	getHostBytes
CurrentSource, 179	CodeGenerator::MemAlloc, 230
InitSparseConnectivitySnippet::FixedProbability←	getHostMBytes
Base, 200	CodeGenerator::MemAlloc, 230
NeuronGroup, 254	getHostStateVar
NeuronModels::LIF, 228	SpineMLSimulator::ModelProperty::Base, 168
NeuronModels::PoissonNew, 272	getInSyn
NeuronModels::RulkovMap, 290	NeuronGroup, 254
PostsynapticModels::ExpCond, 188	getInSynLocation
PostsynapticModels::ExpCurr, 190	SynapseGroup, 334
Snippet::Base, 156	getIndices
Snippet::Init, 220	SpineMLSimulator::LogOutput::AnalogueBase,
WeightUpdateModels::PiecewiseSTDP, 266	102
getDeviceBytes	getInitSparseTime
CodeGenerator::MemAlloc, 230	SharedLibraryModel, 294
getDeviceMBytes	SpineMLSimulator::Simulator, 300
CodeGenerator::MemAlloc, 230	getInitTime
getDeviceMemoryBytes	SharedLibraryModel, 295
CodeGenerator::BackendBase, 147	SpineMLSimulator::Simulator, 300
CodeGenerator::CUDA::Backend, 119	getInitialisers
CodeGenerator::SingleThreadedCPU::Backend,	Models::VarInitContainerBase, 369
132	Models::VarInitContainerBase< 0 >, 370
	getInjectionCode
getDT ModelSpec, 240	CurrentSourceModels::Base, 149
SpineMLSimulator::Simulator, 299	
•	getInputMs
getDurationMs	SpineMLSimulator::Simulator, 300
SpineMLSimulator::Simulator, 299	getInstance
getEndTimestep	CurrentSourceModels::DC, 183
SpineMLSimulator::LogOutput::Base, 167	CurrentSourceModels::GaussianNoise, 205
getEventCode	NeuronModels::Izhikevich, 224
WeightUpdateModels::Base, 161	NeuronModels::IzhikevichVariable, 226
WeightUpdateModels::StaticGraded, 314	NeuronModels::LIF, 228
getEventThresholdConditionCode	NeuronModels::Poisson, 269
WeightUpdateModels::Base, 162	NeuronModels::PoissonNew, 272
WeightUpdateModels::StaticGraded, 314	NeuronModels::RulkovMap, 290
getExitCode	NeuronModels::SpikeSource, 305

NeuronModels::SpikeSourceArray, 307	getNumNeurons
NeuronModels::TraubMiles, 352	ModelSpec, 241
NeuronModels::TraubMilesAlt, 354	NeuronGroup, 255
NeuronModels::TraubMilesFast, 356	SpineMLSimulator::InputValue::Base, 166
NeuronModels::TraubMilesNStep, 358	getNumPostsynapticUpdateThreads
PostsynapticModels::DeltaCurr, 185	CodeGenerator::CUDA::Backend, 119
PostsynapticModels::ExpCond, 189	getNumPresynapticUpdateThreads
PostsynapticModels::ExpCurr, 191	CodeGenerator::CUDA::Backend, 119
getKernelBlockSize	getNumRemoteNeurons
CodeGenerator::CUDA::Backend, 119	ModelSpec, 241
getLearnPostCode	getNumSynapseDynamicsThreads
WeightUpdateModels::Base, 162	CodeGenerator::CUDA::Backend, 119
WeightUpdateModels::PiecewiseSTDP, 266	getNumThreads
getLearnPostSupportCode	CodeGenerator::CUDA::PresynapticUpdate←
WeightUpdateModels::Base, 162	Strategy::Base, 159
getLocalCurrentSources	CodeGenerator::CUDA::PresynapticUpdate←
ModelSpec, 241	Strategy::PostSpan, 276
getLocalHostID	CodeGenerator::CUDA::PresynapticUpdate ←
CodeGenerator::BackendBase, 147	Strategy::PostSpanBitmask, 278
getLocalNeuronGroups	CodeGenerator::CUDA::PresynapticUpdate ←
ModelSpec, 241	Strategy::PreSpan, 284
getLocalSynapseGroups	CodeGenerator::CUDA::PresynapticUpdate ←
ModelSpec, 241	Strategy::PreSpanProcedural, 286
getLogMs	getNumThreadsPerSpike
SpineMLSimulator::Simulator, 300	SynapseGroup, 334
getMatrixType	getOutDir
SynapseGroup, 334	GenerateRunBase, 207
getMaxConnections	getOutSyn
SynapseGroup, 334	NeuronGroup, 255
getMaxDendriticDelayTimesteps	getPSConstInitVals
SynapseGroup, 334	SynapseGroup, 335
getMaxSourceConnections	getPSDerivedParams
SynapseGroup, 334	SynapseGroup, 335
getMergedInSyn	getPSExtraGlobalParamLocation
NeuronGroup, 254	SynapseGroup, 335
getModelPropertySize	getPSModel
SpineMLSimulator::LogOutput::AnalogueBase,	SynapseGroup, 335
102	getPSModelTargetName
getNVCCFlags	SynapseGroup, 335
CodeGenerator::CUDA::Backend, 119	getPSParams
getName	SynapseGroup, 335
CurrentSource, 179	getPSVarInitialisers
ModelSpec, 241	SynapseGroup, 335
NeuronGroup, 254	getPSVarLocation
SynapseGroup, 334	SynapseGroup, 335
getNamedVecIndex	getParamNames
Snippet::Base, 156	CurrentSourceModels::DC, 183
getNeuronModel	CurrentSourceModels::GaussianNoise, 206
NeuronGroup, 254	InitSparseConnectivitySnippet::FixedProbability←
getNeuronUpdateTime	Base, 200
SharedLibraryModel, 295	InitVarSnippet::Constant, 172
SpineMLSimulator::Simulator, 300	InitVarSnippet::Exponential, 192
getNumDelaySlots	InitVarSnippet::Gamma, 204
NeuronGroup, 255	InitVarSnippet::Normal, 260
getNumInitialisationRNGStreams	InitVarSnippet::Uniform, 359
CodeGenerator::CUDA::Backend, 119	NeuronModels::Izhikevich, 224
getNumLocalNeurons	NeuronModels::IzhikevichVariable, 227
ModelSpec, 241	NeuronModels::LIF, 229

NeuronModels::Poisson, 269	getScalar
NeuronModels::PoissonNew, 272	SharedLibraryModel, 295
NeuronModels::RulkovMap, 290	getSeed
NeuronModels::TraubMiles, 352	ModelSpec, 242
NeuronModels::TraubMilesNStep, 358	getSharedMemoryPerThread
PostsynapticModels::ExpCond, 189	$Code Generator :: CUDA :: Presynaptic Update \leftarrow$
PostsynapticModels::ExpCurr, 191	Strategy::Base, 160
Snippet::Base, 157	CodeGenerator::CUDA::PresynapticUpdate ←
WeightUpdateModels::PiecewiseSTDP, 266	Strategy::PostSpan, 276
WeightUpdateModels::StaticGraded, 314	CodeGenerator::CUDA::PresynapticUpdate ←
getParams	Strategy::PostSpanBitmask, 278
CurrentSource, 179	CodeGenerator::CUDA::PresynapticUpdate←
NeuronGroup, 255	Strategy::PreSpan, 284
Snippet::Init, 220	CodeGenerator::CUDA::PresynapticUpdate ←
getPostSpikeCode	Strategy::PreSpanProcedural, 286
WeightUpdateModels::Base, 162	getSimCode
getPostVarIndex	NeuronModels::Base, 154
WeightUpdateModels::Base, 162	NeuronModels::Izhikevich, 224
getPostVars	NeuronModels::LIF, 229
WeightUpdateModels::Base, 162	NeuronModels::Poisson, 270
getPostsynapticBackPropDelaySlot	NeuronModels::PoissonNew, 272
SynapseGroup, 334	NeuronModels::RulkovMap, 290
getPostsynapticUpdateTime	NeuronModels::SpikeSourceArray, 308
SharedLibraryModel, 295	NeuronModels::TraubMiles, 352
SpineMLSimulator::Simulator, 300	NeuronModels::TraubMilesAlt, 354
getPreSpikeCode	NeuronModels::TraubMilesFast, 356
WeightUpdateModels::Base, 162	NeuronModels::TraubMilesNStep, 358
getPreVarIndex	WeightUpdateModels::Base, 163
WeightUpdateModels::Base, 163	WeightUpdateModels::PiecewiseSTDP, 267
getPreVars	WeightUpdateModels::StaticPulse, 315
WeightUpdateModels::Base, 163	WeightUpdateModels::StaticPulseDendriticDelay
getPrecision	317
ModelSpec, 241	getSimSupportCode
getPresynapticAxonalDelaySlot	WeightUpdateModels::Base, 163
SynapseGroup, 334	getSimulateMs
getPresynapticUpdateTime	SpineMLSimulator::Simulator, 300
SharedLibraryModel, 295	getSize
SpineMLSimulator::Simulator, 300	CodeGenerator::BackendBase, 147
getPrevQueueOffset	SpineMLSimulator::InputValue::External, 194
NeuronGroup, 255	SpineMLSimulator::ModelProperty::Base, 169
getRemoteCurrentSources	getSnippet
ModelSpec, 242	Snippet::Init, 221
getRemoteNeuronGroups	getSpanType
ModelSpec, 242	SynapseGroup, 336
getRemoteSynapseGroups	getSparseConnectivityExtraGlobalParamLocation
ModelSpec, 242	SynapseGroup, 336
getResetCode	getSparseConnectivityLocation
NeuronModels::Base, 154	SynapseGroup, 336
NeuronModels::LIF, 229	getSparseIndType SynapseGroup, 336
NeuronModels::SpikeSourceArray, 307	
getRowBuildCode	getSpikeEventCondition
InitSparseConnectivitySnippet::Base, 150	NeuronGroup, 255
InitSparseConnectivitySnippet::FixedProbability←	getSpikeEventLocation
Base, 200	NeuronGroup, 255
getRowBuildStateVars	getSpikeLocation
InitSparseConnectivitySnippet::Base, 150	NeuronGroup, 255
getRuntimeVersion	getSpikeTimeLocation
CodeGenerator::CUDA::Backend, 120	NeuronGroup, 255

getSrcNeuronGroup	getTimestep
SynapseGroup, 336	SharedLibraryModel, 295
getStateVarBegin	getTrgNeuronGroup
SpineMLSimulator::LogOutput::AnalogueBase,	SynapseGroup, 336
102	getUnderlyingType
getStateVarEnd	Utils, 99
SpineMLSimulator::LogOutput::AnalogueBase,	getValues
102	Snippet::ValueBase, 362
getSum	Snippet::ValueBase< 0 >, 363
SpikeRecorder, 304	getVarIndex
getSupportCode	Models::Base, 152
NeuronModels::Base, 154	getVarInitialisers
PostsynapticModels::Base, 158	CurrentSource, 180
getSymbol	NeuronGroup, 256
SharedLibraryModel, 295	getVarLocation
getSynapseDynamicsCode	CurrentSource, 180
WeightUpdateModels::Base, 163	NeuronGroup, 256
getSynapseDynamicsSuppportCode	getVarPrefix
WeightUpdateModels::Base, 163	CodeGenerator::BackendBase, 147
getSynapseDynamicsTime	CodeGenerator::CUDA::Backend, 120
SharedLibraryModel, 295	CodeGenerator::SingleThreadedCPU::Backend,
SpineMLSimulator::Simulator, 301	132
getSynapticMatrixRowStride	getVarSubstitution
CodeGenerator::BackendBase, 147	CodeGenerator::Substitutions, 319
CodeGenerator::CUDA::Backend, 120	getVars
CodeGenerator::CUDA::PresynapticUpdate←	Models::Base, 152
Strategy::Base, 160	NeuronModels::Izhikevich, 225
CodeGenerator::CUDA::PresynapticUpdate ←	NeuronModels::IzhikevichVariable, 227
Strategy::PostSpan, 276	NeuronModels::LIF, 229
CodeGenerator::CUDA::PresynapticUpdate←	NeuronModels::Poisson, 270
Strategy::PostSpanBitmask, 278	NeuronModels::PoissonNew, 273
CodeGenerator::CUDA::PresynapticUpdate ←	NeuronModels::RulkovMap, 291
Strategy::PreSpan, 284	NeuronModels::SpikeSourceArray, 308
CodeGenerator::CUDA::PresynapticUpdate ←	NeuronModels::TraubMiles, 353
Strategy::PreSpanProcedural, 287	WeightUpdateModels::PiecewiseSTDP, 267
CodeGenerator::SingleThreadedCPU::Backend,	WeightUpdateModels::StaticGraded, 314
132	WeightUpdateModels::StaticPulse, 316
getTargetIndices	WeightUpdateModels::StaticPulseDendriticDelay,
SpineMLSimulator::InputValue::Base, 166	317
getThresholdConditionCode	getWUConstInitVals
NeuronModels::Base, 154	SynapseGroup, 337
NeuronModels::Izhikevich, 224	getWUDerivedParams
NeuronModels::LIF, 229	SynapseGroup, 337
NeuronModels::Poisson, 270	getWUExtraGlobalParamLocation
NeuronModels::PoissonNew, 272	SynapseGroup, 337
NeuronModels::RulkovMap, 291	getWUModel
NeuronModels::SpikeSource, 305	SynapseGroup, 337
NeuronModels::SpikeSourceArray, 308	getWUParams
NeuronModels::TraubMiles, 352	SynapseGroup, 337
getTime	getWUPostVarInitialisers
SharedLibraryModel, 295	SynapseGroup, 337
getTimePrecision	getWUPostVarLocation
ModelSpec, 242	SynapseGroup, 337
getTimeToSpike	getWUPreVarInitialisers
SpineMLSimulator::Input::InterSpikeIntervalBase,	SynapseGroup, 338
222	getWUPreVarLocation
SpineMLSimulator::Input::PoissonSpikeRate, 274	SynapseGroup, 338
SpineMLSimulator::Input::RegularSpikeRate, 288	getWUVarInitialisers

SynapseGroup, 338	InitSparseConnectivitySnippet, 81
getWUVarLocation	initSparseConnectivitySnippet.cc, 389
SynapseGroup, 338	IMPLEMENT_SNIPPET, 389
getZeroCopyBytes	initSparseConnectivitySnippet.h, 389
CodeGenerator::MemAlloc, 230	SET_CALC_MAX_COL_LENGTH_FUNC, 390
getZeroCopyMBytes	SET_CALC_MAX_ROW_LENGTH_FUNC, 390
CodeGenerator::MemAlloc, 230	SET EXTRA GLOBAL PARAMS, 390
GroupHandler	SET_MAX_COL_LENGTH, 390
CodeGenerator::BackendBase, 136	SET_MAX_ROW_LENGTH, 391
	SET_ROW_BUILD_CODE, 391
Handler	
CodeGenerator::BackendBase, 136	SET_ROW_BUILD_STATE_VARS, 391
has_individual_postsynaptic_vars	InitSparseConnectivitySnippet::Base, 149
pygenn::genn_groups::SynapseGroup, 323	CalcMaxLengthFunc, 150
has_individual_synapse_vars	getCalcMaxColLengthFunc, 150
pygenn::genn_groups::SynapseGroup, 323	getCalcMaxRowLengthFunc, 150
	getExtraGlobalParamIndex, 150
hasOutputToHost	getExtraGlobalParams, 150
NeuronGroup, 256	getRowBuildCode, 150
hasVarSubstitution	getRowBuildStateVars, 150
CodeGenerator::Substitutions, 319	InitSparseConnectivitySnippet::FixedProbability, 198
host	DECLARE SNIPPET, 199
CodeGenerator::MemAlloc, 231	SET ROW BUILD CODE, 199
	InitSparseConnectivitySnippet::FixedProbabilityBase,
IMPLEMENT_MODEL	199
currentSourceModels.cc, 380	getDerivedParams, 200
models.h, 400	-
neuronModels.cc, 407, 408	getParamNames, 200
postsynapticModels.cc, 412	getRowBuildCode, 200
weightUpdateModels.cc, 424	SET_CALC_MAX_COL_LENGTH_FUNC, 200
IMPLEMENT_SNIPPET	SET_CALC_MAX_ROW_LENGTH_FUNC, 200
initSparseConnectivitySnippet.cc, 389	SET_ROW_BUILD_STATE_VARS, 201
initVarSnippet.cc, 391, 392	$In it Sparse Connectivity Snippet :: Fixed Probability No \hookleftarrow$
snippet.h, 417	Autapse, 201
ind	DECLARE_SNIPPET, 201
pygenn::genn_groups::SynapseGroup, 328	SET_ROW_BUILD_CODE, 202
Init	InitSparseConnectivitySnippet::Init, 219
InitSparseConnectivitySnippet::Init, 219	Init, 219
Snippet::Init, 220	InitSparseConnectivitySnippet::OneToOne, 262
	DECLARE SNIPPET, 262
init	SET_MAX_COL_LENGTH, 263
Logging, 82	SET_MAX_ROW_LENGTH, 263
init_connectivity	SET_ROW_BUILD_CODE, 263
pygenn::genn_model, 91	InitSparseConnectivitySnippet::Uninitialised, 361
init_required	DECLARE SNIPPET, 361
pygenn::model_preprocessor::Variable, 367	- · · · · · · · · · · · · · · · · · · ·
init_sparse_time	initVar
pygenn::genn_model::GeNNModel, 213	modelSpec.h, 404
init_time	InitVarSnippet, 81
pygenn::genn_model::GeNNModel, 213	initVarSnippet.cc, 391
init_val	IMPLEMENT_SNIPPET, 391, 392
pygenn::model_preprocessor::Variable, 367	initVarSnippet.h, 392
init_var	SET_CODE, 393
pygenn::genn_model, 91	InitVarSnippet::Base, 151
initConnectivity	getCode, 151
modelSpec.h, 403, 404	InitVarSnippet::Constant, 171
initDerivedParams	DECLARE_SNIPPET, 172
CurrentSource, 180	getParamNames, 172
NeuronGroup, 256	SET CODE, 172
Snippet::Init, 221	InitVarSnippet::Exponential, 191
• •	·····
SynapseGroup, 338	DECLARE_SNIPPET, 192

getParamNames, 192	CodeGenerator::CUDA::PresynapticUpdate←
SET_CODE, 192	Strategy::PostSpan, 276
InitVarSnippet::Gamma, 203	CodeGenerator::CUDA::PresynapticUpdate↔
DECLARE_SNIPPET, 204	Strategy::PostSpanBitmask, 278
getParamNames, 204	CodeGenerator::CUDA::PresynapticUpdate ←
SET_CODE, 204	Strategy::PreSpan, 285
InitVarSnippet::Normal, 259	CodeGenerator::CUDA::PresynapticUpdate↔
DECLARE_SNIPPET, 260	Strategy::PreSpanProcedural, 287
getParamNames, 260	isDelayRequired
SET_CODE, 260	NeuronGroup, 256
InitVarSnippet::Uniform, 358	isDendriticDelayRequired
DECLARE_SNIPPET, 359	SynapseGroup, 338
getParamNames, 359	isEventThresholdReTestRequired
SET_CODE, 359	SynapseGroup, 338
InitVarSnippet::Uninitialised, 360	isGlobalRNGRequired
DECLARE_SNIPPET, 361	CodeGenerator::BackendBase, 148
initialize	CodeGenerator::CUDA::Backend, 120
SharedLibraryModel, 296	CodeGenerator::SingleThreadedCPU::Backend,
initializeSparse	133
SharedLibraryModel, 296	isInitRNGRequired
injectCurrent	CurrentSource, 180
NeuronGroup, 256	NeuronGroup, 256
injectSpike	isPSInitRNGRequired SynapseGroup, 339
SpineMLSimulator::Input::SpikeBase, 302	isPSModelMerged
input.cc, 393	SynapseGroup, 339
input.h, 393	isParamRequiredBySpikeEventCondition
inputValue.cc, 393 inputValue.h, 394	NeuronGroup, 257
InterSpikeIntervalBase	isPostSpikeTimeRequired
SpineMLSimulator::Input::InterSpikeIntervalBase,	WeightUpdateModels::Base, 163
	- ·
221	WeightUpdateModels::PiecewiseSTDP, 267
221 is_bitmask	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired
<pre>221 is_bitmask pygenn::genn_groups::SynapseGroup, 323</pre>	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148
<pre>221 is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required</pre>	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend,
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197 is_spike_source_array	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197 is_spike_source_array pygenn::genn_groups::NeuronGroup, 250	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197 is_spike_source_array pygenn::genn_groups::NeuronGroup, 250 isAccessible	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197 is_spike_source_array pygenn::genn_groups::NeuronGroup, 250 isAccessible SpineMLSimulator::StateVar, 312	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired NeuronGroup, 257
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal←	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired NeuronGroup, 257 isSpikeTimeRequired NeuronGroup, 257 isSynRemapRequired
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired NeuronGroup, 257 isSynRemapRequired CodeGenerator::BackendBase, 148
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal Variable, 197 is_spike_source_array pygenn::genn_groups::NeuronGroup, 250 isAccessible SpineMLSimulator::StateVar, 312 isAutoRefractoryRequired NeuronModels::Base, 155 isAutomaticCopyEnabled CodeGenerator::BackendBase, 147 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isCompatible	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired NeuronGroup, 257 isSynRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120
is_bitmask pygenn::genn_groups::SynapseGroup, 323 is_connectivity_init_required pygenn::genn_groups::SynapseGroup, 323 is_dense pygenn::genn_groups::SynapseGroup, 323 is_model_valid pygenn::model_preprocessor, 93 is_ragged pygenn::genn_groups::SynapseGroup, 323 is_scalar pygenn::model_preprocessor::ExtraGlobal	WeightUpdateModels::PiecewiseSTDP, 267 isPostsynapticRemapRequired CodeGenerator::BackendBase, 148 CodeGenerator::CUDA::Backend, 120 CodeGenerator::SingleThreadedCPU::Backend, 133 isPreSpikeTimeRequired WeightUpdateModels::Base, 164 WeightUpdateModels::PiecewiseSTDP, 267 isProceduralConnectivityRNGRequired SynapseGroup, 339 isRNGRequired Utils, 100 isSimRNGRequired CurrentSource, 180 NeuronGroup, 257 isSparseConnectivityInitRequired SynapseGroup, 339 isSpikeEventRequired NeuronGroup, 257 SynapseGroup, 339 isSpikeTimeRequired NeuronGroup, 257 isSynRemapRequired CodeGenerator::BackendBase, 148

isTimingEnabled	logging.h, 397
ModelSpec, 242	Level
isTrueSpikeRequired	CodeGenerator::CodeStream::CB, 170
NeuronGroup, 257	CodeGenerator::CodeStream::OB, 262
SynapseGroup, 339	load
isTypePointer	pygenn::genn_groups::CurrentSource, 176
Utils, 100	pygenn::genn_groups::NeuronGroup, 249
isVarQueueRequired	pygenn::genn_groups::SynapseGroup, 323
NeuronGroup, 257	pygenn::genn_model::GeNNModel, 213
isWUInitRNGRequired	SpineMLSimulator::Simulator, 301
SynapseGroup, 339	load_connectivity_init_egps
isWUVarInitRequired	pygenn::genn_groups::SynapseGroup, 324
SynapseGroup, 339	logLevel
isZeroCopyEnabled	CodeGenerator::PreferencesBase, 282
NeuronGroup, 257	
•	logOutput b. 397
SynapseGroup, 339	logOutput.h, 397
Kernel	logWriter.h, 398
	Logging, 82
CodeGenerator::CUDA, 79	Channel, 82
KernelBlockSize	init, 82
CodeGenerator::CUDA, 78	logging.cc, 394
KernelNames	logging.h, 394
CodeGenerator::CUDA::Backend, 121	LOGD_BACKEND, 395
	LOGD_CODE_GEN, 395
LOGD_BACKEND	LOGD_GENN, 395
logging.h, 395	LOGE_BACKEND, 395
LOGD_CODE_GEN	LOGE_CODE_GEN, 396
logging.h, 395	LOGE GENN, 396
LOGD_GENN	LOGF_BACKEND, 396
logging.h, 395	LOGF_CODE_GEN, 396
LOGE_BACKEND	LOGF_GENN, 396
logging.h, 395	LOGI_BACKEND, 396
LOGE_CODE_GEN	LOGI_CODE_GEN, 396
logging.h, 396	LOGI_GENN, 396
LOGE GENN	
logging.h, 396	LOGV_BACKEND, 396
LOGF_BACKEND	LOGV_CODE_GEN, 396
logging.h, 396	LOGV_GENN, 396
LOGF_CODE_GEN	LOGW_BACKEND, 397
logging.h, 396	LOGW_CODE_GEN, 397
LOGF GENN	LOGW_GENN, 397
-	
logging.h, 396	m
LOGI_BACKEND	pygenn::genn_model, 92
logging.h, 396	m_Direct
LOGI_CODE_GEN	SpineMLSimulator::StateVar, 312
logging.h, 396	m_Indirect
LOGI_GENN	SpineMLSimulator::StateVar, 312
logging.h, 396	manualBlockSizes
LOGV_BACKEND	CodeGenerator::CUDA::Preferences, 280
logging.h, 396	manualDeviceID
LOGV_CODE_GEN	CodeGenerator::CUDA::Preferences, 280
logging.h, 396	MathsFunc
LOGV_GENN	codeGenUtils.cc, 376
logging.h, 396	matrix_type
LOGW_BACKEND	pygenn::genn_groups::SynapseGroup, 324
logging.h, 397	max_row_length
LOGW_CODE_GEN	pygenn::genn_groups::SynapseGroup, 324
logging.h, 397	mergeIncomingPSM
LOGW GENN	NeuronGroup, 257
	110010110100p, <u>L</u> 01

Mode	ModelSpecInternal, 244
SpineMLSimulator::NetworkClient, 245	modelSpecInternal.h, 405
model_name	Models, 82
pygenn::genn_model::GeNNModel, 213, 217	models.h, 399
model preprocessor.py, 398	DECLARE_MODEL, 400
modelProperty.cc, 399	IMPLEMENT_MODEL, 400
modelProperty.h, 399	SET_EXTRA_GLOBAL_PARAMS, 400
ModelSpec, 231	SET VARS, 401
~ModelSpec, 234	VarAccess, 401
addCurrentSource, 234, 235	Models::Base, 151
addNeuronPopulation, 236	getExtraGlobalParamIndex, 152
addSynapsePopulation, 237–239	getExtraGlobalParams, 152
finalize, 240	getVarIndex, 152
findCurrentSource, 240	getVars, 152
findNeuronGroup, 240	VarVec, 152
findSynapseGroup, 240	Models::Base::Var, 364
getDT, 240	access, 365
getLocalCurrentSources, 241	name, 365
getLocalNeuronGroups, 241	type, 365
getLocalSynapseGroups, 241	Var, 365
getName, 241	Models::VarInit, 368
getNumLocalNeurons, 241	VarInit, 368
getNumNeurons, 241	Models::VarInitContainerBase
getNumRemoteNeurons, 241	getInitialisers, 369
getPrecision, 241	operator[], 369
getRemoteCurrentSources, 242	VarInitContainerBase, 369
getRemoteNeuronGroups, 242	Models::VarInitContainerBase< 0 >, 369
getRemoteSynapseGroups, 242	getInitialisers, 370
getSeed, 242	VarInitContainerBase, 370
getTimePrecision, 242	Models::VarInitContainerBase< NumVars >, 368
isTimingEnabled, 242	
ModelSpec, 234	NNmodel
NeuronGroupValueType, 234	modelSpec.h, 403
operator=, 242	NO_DELAY
scalarExpr, 242	modelSpec.h, 402
setDefaultExtraGlobalParamLocation, 242	name
•	Models::Base::Var, 365
setDefaultNarrowSparseIndEnabled, 243	pygenn::genn_groups::Group, 219
setDefaultSparseConnectivityLocation, 243	pygenn::model_preprocessor::ExtraGlobal ←
setDefaultVarLocation, 243 setDT, 243	Variable, 197
•	pygenn::model_preprocessor::Variable, 367
setMergePostsynapticModels, 243	Snippet::Base::DerivedParam, 185
setName, 243	Snippet::Base::EGP, 186
setPrecision, 243	Snippet::Base::ParamVal, 263
setSeed, 244	needs_allocation
setTimePrecision, 244	pygenn::model_preprocessor::Variable, 367
setTiming, 244	NetworkClient
SynapseGroupValueType, 234	SpineMLSimulator::NetworkClient, 245
zeroCopyInUse, 244	networkClient.cc, 405
modelSpec.cc, 401	networkClient.h, 405
modelSpec.h, 401	neuron
FloatType, 403	pygenn::genn_groups::NeuronGroup, 250
initConnectivity, 403, 404	neuron_populations
initVar, 404	pygenn::genn_model::GeNNModel, 217
NNmodel, 403	neuron_update_time
NO_DELAY, 402	
	pygenn::genn_model::GeNNModel, 214
TimePrecision, 403	NeuronGroup, 251
TimePrecision, 403 uninitialisedConnectivity, 405 uninitialisedVar, 405	

addSpkEventCondition, 253	SET_ADDITIONAL_INPUT_VARS, 409
checkNumDelaySlots, 253	SET_NEEDS_AUTO_REFRACTORY, 409
getClusterHostID, 253	SET_RESET_CODE, 409
getCurrentQueueOffset, 254	SET SIM CODE, 410
getCurrentSources, 254	SET_SUPPORT_CODE, 410
getDerivedParams, 254	SET_THRESHOLD_CONDITION_CODE, 410
getExtraGlobalParamLocation, 254	NeuronModels::Base, 153
getInSyn, 254	getAdditionalInputVars, 154
getMergedInSyn, 254	getResetCode, 154
getName, 254	getSimCode, 154
getNeuronModel, 254	getSupportCode, 154
getNumDelaySlots, 255	getThresholdConditionCode, 154
getNumNeurons, 255	isAutoRefractoryRequired, 155
getOutSyn, 255	NeuronModels::Izhikevich, 222
getParams, 255	getInstance, 224
getPrevQueueOffset, 255	getParamNames, 224
getSpikeEventCondition, 255	getSimCode, 224
getSpikeEventLocation, 255	getThresholdConditionCode, 224
getSpikeLocation, 255	getVars, 225
getSpikeTimeLocation, 255	ParamValues, 224
getVarInitialisers, 256	PostVarValues, 224
getVarLocation, 256	PreVarValues, 224
hasOutputToHost, 256	VarValues, 224
initDerivedParams, 256	NeuronModels::IzhikevichVariable, 225
injectCurrent, 256	getInstance, 226
isDelayRequired, 256	getParamNames, 227
isInitRNGRequired, 256	getVars, 227
isParamRequiredBySpikeEventCondition, 257	ParamValues, 226
isSimRNGRequired, 257	PostVarValues, 226
isSpikeEventRequired, 257	PreVarValues, 226
isSpikeTimeRequired, 257	VarValues, 226
isTrueSpikeRequired, 257	NeuronModels::LIF, 227
isVarQueueRequired, 257	getDerivedParams, 228
isZeroCopyEnabled, 257	getInstance, 228
mergeIncomingPSM, 257	getParamNames, 229
NeuronGroup, 253	getResetCode, 229
setExtraGlobalParamLocation, 257	getSimCode, 229
setSpikeEventLocation, 258	getThresholdConditionCode, 229
setSpikeLocation, 258	getVars, 229
setSpikeTimeLocation, 258	ParamValues, 228
setVarLocation, 258	PostVarValues, 228
updatePostVarQueues, 258	PreVarValues, 228
updatePreVarQueues, 258	SET_NEEDS_AUTO_REFRACTORY, 229
neuronGroup.cc, 406	
•	VarValues, 228
neuronGroup.h, 406	NeuronModels::Poisson, 267
NeuronGroupHandler	getExtraGlobalParams, 269
CodeGenerator::BackendBase, 136	getInstance, 269
NeuronGroupInternal, 259	getParamNames, 269
NeuronGroupInternal, 259	getSimCode, 270
neuronGroupInternal.h, 406	getThresholdConditionCode, 270
NeuronGroupSimHandler	getVars, 270
CodeGenerator::BackendBase, 136	ParamValues, 269
NeuronGroupValueType	PostVarValues, 269
ModelSpec, 234	PreVarValues, 269
NeuronModels, 83	VarValues, 269
neuronModels.cc, 406	NeuronModels::PoissonNew, 270
IMPLEMENT_MODEL, 407, 408	getDerivedParams, 272
neuronModels.h, 408	getInstance, 272

getParamNames, 272	getInstance, 356
getSimCode, 272	getSimCode, 356
getThresholdConditionCode, 272	ParamValues, 355
getVars, 273	PostVarValues, 355
ParamValues, 271	PreVarValues, 356
PostVarValues, 271	VarValues, 356
PreVarValues, 272	NeuronModels::TraubMilesNStep, 356
SET_NEEDS_AUTO_REFRACTORY, 273	getInstance, 358
VarValues, 272	getParamNames, 358
NeuronModels::RulkovMap, 288	getSimCode, 358
getDerivedParams, 290	ParamValues, 357
_	PostVarValues, 357
getInstance, 290	PreVarValues, 357
getParamNames, 290	VarValues, 358
getSimCode, 290	
getThresholdConditionCode, 291	neuronSubstitutionsInSynapticCode
getVars, 291	CodeGenerator, 74
ParamValues, 290	NormalDistribution
PostVarValues, 290	SpineMLSimulator::ModelProperty::Normal
PreVarValues, 290	Distribution, 261
VarValues, 290	num_synapses
NeuronModels::SpikeSource, 304	pygenn::genn_groups::SynapseGroup, 324
getInstance, 305	numArguments
getThresholdConditionCode, 305	CodeGenerator::FunctionTemplate, 203
ParamValues, 305	
PostVarValues, 305	OB
PreVarValues, 305	CodeGenerator::CodeStream::OB, 261
SET_NEEDS_AUTO_REFRACTORY, 305	open
VarValues, 305	SharedLibraryModel, 296
	operator<<
NeuronModels::SpikeSourceArray, 306	CodeGenerator, 75
getExtraGlobalParams, 307	CodeGenerator::CodeStream, 171
getInstance, 307	operator+=
getResetCode, 307	CodeGenerator::MemAlloc, 231
getSimCode, 308	operator=
getThresholdConditionCode, 308	CodeGenerator::FunctionTemplate, 202
getVars, 308	ModelSpec, 242
ParamValues, 307	operator&
PostVarValues, 307	synapseMatrixType.h, 420, 421
PreVarValues, 307	variableMode.h, 423
SET_NEEDS_AUTO_REFRACTORY, 308	
VarValues, 307	operator[]
NeuronModels::TraubMiles, 350	CodeGenerator::Substitutions, 319
getInstance, 352	Models::VarInitContainerBase, 369
getParamNames, 352	Snippet::ValueBase, 362
getSimCode, 352	operator
getThresholdConditionCode, 352	synapseMatrixType.h, 421
•	optimiser.cc, 410, 411
getVars, 353	optimiser.h, 411
ParamValues, 351	optimizeCode
PostVarValues, 352	CodeGenerator::PreferencesBase, 282
PreVarValues, 352	
VarValues, 352	padSize
NeuronModels::TraubMilesAlt, 353	CodeGenerator, 75
getInstance, 354	param_space_to_val_vec
getSimCode, 354	pygenn::model_preprocessor, 93
ParamValues, 354	param_space_to_vals
PostVarValues, 354	pygenn::model_preprocessor, 93
PreVarValues, 354	ParamValVec
VarValues, 354	Snippet::Base, 156
NeuronModels::TraubMilesFast, 355	ParamValues

CurrentSourceModels::DC, 182	SET_APPLY_INPUT_CODE, 413
CurrentSourceModels::GaussianNoise, 205	SET_CURRENT_CONVERTER_CODE, 413
NeuronModels::Izhikevich, 224	SET_DECAY_CODE, 413
NeuronModels::IzhikevichVariable, 226	SET SUPPORT CODE, 413
NeuronModels::LIF, 228	PostsynapticModels::Base, 157
NeuronModels::Poisson, 269	getApplyInputCode, 158
NeuronModels::PoissonNew, 271	getDecayCode, 158
NeuronModels::RulkovMap, 290	getSupportCode, 158
NeuronModels::SpikeSource, 305	PostsynapticModels::DeltaCurr, 183
NeuronModels::SpikeSourceArray, 307	getApplyInputCode, 184
NeuronModels::TraubMiles, 351	getInstance, 185
NeuronModels::TraubMilesAlt, 354	ParamValues, 184
NeuronModels::TraubMilesFast, 355	PostVarValues, 184
NeuronModels::TraubMilesNStep, 357	PreVarValues, 184
PostsynapticModels::DeltaCurr, 184	VarValues, 184
PostsynapticModels::ExpCond, 188	PostsynapticModels::ExpCond, 187
PostsynapticModels::ExpCurr, 190	getApplyInputCode, 188
parseCommandLine	getDecayCode, 188
GenerateRunBase, 207	getDerivedParams, 188
plog, 83	getInstance, 189
• •	
PoissonSpikeRate	getParamNames, 189
SpineMLSimulator::Input::PoissonSpikeRate, 274	ParamValues, 188
pop	PostVarValues, 188
pygenn::genn_groups::CurrentSource, 177	PreVarValues, 188
pygenn::genn_groups::NeuronGroup, 250	VarValues, 188
pygenn::genn_groups::SynapseGroup, 328	PostsynapticModels::ExpCurr, 189
post_var_space_to_vals	getApplyInputCode, 190
pygenn::model_preprocessor, 94	getDecayCode, 190
post_vars	getDerivedParams, 190
pygenn::genn_groups::SynapseGroup, 328	getInstance, 191
postNeuronSubstitutionsInSynapticCode	getParamNames, 191
CodeGenerator, 76	ParamValues, 190
PostVarValues	PostVarValues, 190
CurrentSourceModels::DC, 182	PreVarValues, 190
CurrentSourceModels::GaussianNoise, 205	VarValues, 190
NeuronModels::Izhikevich, 224	•
	pre_var_space_to_vals
NeuronModels::IzhikevichVariable, 226	pygenn::model_preprocessor, 94
NeuronModels::LIF, 228	pre_vars
NeuronModels::Poisson, 269	pygenn::genn_groups::SynapseGroup, 328
NeuronModels::PoissonNew, 271	preNeuronSubstitutionsInSynapticCode
NeuronModels::RulkovMap, 290	CodeGenerator, 76
NeuronModels::SpikeSource, 305	PreVarValues
NeuronModels::SpikeSourceArray, 307	CurrentSourceModels::DC, 182
NeuronModels::TraubMiles, 352	CurrentSourceModels::GaussianNoise, 205
NeuronModels::TraubMilesAlt, 354	NeuronModels::Izhikevich, 224
NeuronModels::TraubMilesFast, 355	NeuronModels::IzhikevichVariable, 226
NeuronModels::TraubMilesNStep, 357	NeuronModels::LIF, 228
PostsynapticModels::DeltaCurr, 184	NeuronModels::Poisson, 269
PostsynapticModels::ExpCond, 188	NeuronModels::PoissonNew, 272
PostsynapticModels::ExpCurr, 190	NeuronModels::RulkovMap, 290
	• •
postsyn	NeuronModels::SpikeSource, 305
pygenn::genn_groups::SynapseGroup, 328	NeuronModels::SpikeSourceArray, 307
postsynaptic_update_time	NeuronModels::TraubMiles, 352
pygenn::genn_model::GeNNModel, 214	NeuronModels::TraubMilesAlt, 354
PostsynapticModels, 83	NeuronModels::TraubMilesFast, 356
postsynapticModels.cc, 412	NeuronModels::TraubMilesNStep, 357
IMPLEMENT_MODEL, 412	PostsynapticModels::DeltaCurr, 184
postsynapticModels.h, 412	PostsynapticModels::ExpCond, 188

PostsynapticModels::ExpCurr, 190	SharedLibraryModel, 297
Preferences	PushCurrentSpikesFunc
CodeGenerator::CUDA::Preferences, 280	SpineMLSimulator::Input::SpikeBase, 302
prepare_model	pushCurrentSpikesToDevice
pygenn::model_preprocessor, 94	SharedLibraryModel, 297
prepare_snippet	pushExtraGlobalParam
pygenn::model_preprocessor, 95	SharedLibraryModel, 297
presynaptic_update_time	pushSpikesToDevice
pygenn::genn_model::GeNNModel, 214	SharedLibraryModel, 297
presynapticUpdateStrategy.cc, 413	pushStateToDevice
presynapticUpdateStrategy.h, 414	SharedLibraryModel, 297
psm_extra_global_params	pushToDevice
pygenn::genn_groups::SynapseGroup, 328	SpineMLSimulator::ModelProperty::Base, 169
psm_vars	pushVarToDevice
pygenn::genn_groups::SynapseGroup, 328	SharedLibraryModel, 297
pugi, 84	pygenn, 84
pull	pygenn.genn_groups, 84
SpineMLSimulator::StateVar, 312	pygenn.genn_groups.CurrentSource, 174
pull_connectivity_from_device	pygenn.genn_groups.Group, 218
pygenn::genn_model::GeNNModel, 214	pygenn.genn_groups.NeuronGroup, 246
pull_current_spikes_from_device	pygenn.genn_groups.SynapseGroup, 320
pygenn::genn_model::GeNNModel, 214	pygenn.genn_model, 84
pull_spikes_from_device	pygenn.genn_model.GeNNModel, 207
pygenn::genn_model::GeNNModel, 214	pygenn.model_preprocessor, 92
pull_state_from_device	pygenn.model_preprocessor.ExtraGlobalVariable, 195
pygenn::genn_model::GeNNModel, 214	pygenn.model_preprocessor.Variable, 365
pull_var_from_device	pygenn::genn_groups
pygenn::genn_model::GeNNModel, 214	xrange, 84
pullConnectivityFromDevice	pygenn::genn_groups::CurrentSource
SharedLibraryModel, 296	init, 175
pullCurrentSpikesFromDevice	add_extra_global_param, 175
SharedLibraryModel, 296	add_to, 176
pullExtraGlobalParam	current_source_model, 177
SharedLibraryModel, 296	load, 176
pullFromDevice	pop, 177
SpineMLSimulator::ModelProperty::Base, 169	reinitialise, 176
pullModelPropertyFromDevice	set_current_source_model, 176
SpineMLSimulator::LogOutput::AnalogueBase,	set_extra_global_param, 177
103	size, 177
pullSpikesFromDevice	target_pop, 177
SharedLibraryModel, 296	pygenn::genn_groups::Group
pullStateFromDevice	init, 218
SharedLibraryModel, 296	extra_global_params, 219
pullVarFromDevice	name, 219
SharedLibraryModel, 297	set_var, 218
push	vars, 219
SpineMLSimulator::StateVar, 312	pygenn::genn_groups::NeuronGroup
push_connectivity_to_device	init, 247
pygenn::genn_model::GeNNModel, 215	add_extra_global_param, 248
push_current_spikes_to_device	add_to, 248
pygenn::genn_model::GeNNModel, 215	current_spikes, 248
push_spikes_to_device	delay_slots, 248
pygenn::genn_model::GeNNModel, 215	is_spike_source_array, 250
push_state_to_device	load, 249
pygenn::genn_model::GeNNModel, 215	neuron, 250
push_var_to_device	pop, 250
pygenn::genn_model::GeNNModel, 215	reinitialise, 249
pushConnectivityToDevice	set_extra_global_param, 249
p	ooi_oniia_giobai_paiaiii, = iv

set_neuron, 249	create_custom_postsynaptic_class, 88
size, 250	create_custom_sparse_connect_init_snippet_<
spike_count, 250	class, 89
spike_que_ptr, 250	create_custom_weight_update_class, 90
spikes, 250	create_dpf_class, 91
type, 250	init_connectivity, 91
pygenn::genn_groups::SynapseGroup	init_var, 91
init, 321	m, 92
add_extra_global_param, 322	pygenn::genn_model::GeNNModel
add_to, 322	init, 209
connections_set, 328	add_current_source, 210
connectivity_extra_global_params, 328	add_neuron_population, 210
connectivity_initialiser, 328	add_synapse_population, 211
get_sparse_post_inds, 322	backend_log_level, 217
get_sparse_pre_inds, 322	build, 212
get_var_values, 323	current_sources, 217
has_individual_postsynaptic_vars, 323	default_sparse_connectivity_location, 212
has_individual_synapse_vars, 323	default_var_location, 212, 217
ind, 328	dT, 212, 213, 217
is_bitmask, 323	end, 213
is_connectivity_init_required, 323	free_device_mem_bytes, 213
is dense, 323	init_sparse_time, 213
is_ragged, 323	init_time, 213
load, 323	load, 213
load_connectivity_init_egps, 324	model_name, 213, 217
matrix_type, 324	neuron_populations, 217
max_row_length, 324	neuron_update_time, 214
num_synapses, 324	postsynaptic_update_time, 214
pop, 328	presynaptic_update_time, 214
post_vars, 328	pull_connectivity_from_device, 214
postsyn, 328	pull_current_spikes_from_device, 214
pre_vars, 328	pull_spikes_from_device, 214
psm_extra_global_params, 328	pull_state_from_device, 214
psm_vars, 328	pull_var_from_device, 214
reinitialise, 324	push_connectivity_to_device, 215
row lengths, 329	push_current_spikes_to_device, 215
set connected populations, 325	push_spikes_to_device, 215
set_connectivity_extra_global_param, 325	push state to device, 215
set extra global param, 325	push_var_to_device, 215
set_post_syn, 325	reinitialise, 215
set_post_var, 326	step_time, 215
— —	• —
set_pre_var, 326	synapse_dynamics_time, 216
set_psm_extra_global_param, 326	synapse_populations, 217
set_psm_var, 326	t, 216
set_sparse_connections, 327	timestep, 216
set_weight_update, 327	timing_enabled, 216
src, 329	use_backend, 216, 217
synapse_order, 329	pygenn::model_preprocessor
trg, 329	GeNNType, 96
w_update, 329	genn_types, 96
weight_update_var_size, 327	is_model_valid, 93
pygenn::genn_model	param_space_to_val_vec, 93
backend_modules, 92	param_space_to_vals, 93
create_cmlf_class, 85	post_var_space_to_vals, 94
create_custom_current_source_class, 86	pre_var_space_to_vals, 94
create_custom_init_var_snippet_class, 86	prepare_model, 94
create_custom_model_class, 87	prepare_snippet, 95
create_custom_neuron_class, 87	var_space_to_vals, 95

pygenn::model_preprocessor::ExtraGlobalVariableinit, 196	InitSparseConnectivitySnippet::FixedProbability Base, 200
is_scalar, 197	SET_CALC_MAX_ROW_LENGTH_FUNC
name, 197	initSparseConnectivitySnippet.h, 390
set values, 196	InitSparseConnectivitySnippet::FixedProbability
type, 197	
values, 197	Base, 200
	SET_CODE
view, 197	initVarSnippet.h, 393
pygenn::model_preprocessor::Variable	InitVarSnippet::Constant, 172
init, 366	InitVarSnippet::Exponential, 192
init_required, 367	InitVarSnippet::Gamma, 204
init_val, 367	InitVarSnippet::Normal, 260
name, 367	InitVarSnippet::Uniform, 359
needs_allocation, 367	SET_CURRENT_CONVERTER_CODE
set_values, 366	postsynapticModels.h, 413
type, 367	SET_DECAY_CODE
values, 367	postsynapticModels.h, 413
view, 367	SET_DERIVED_PARAMS
	snippet.h, 417
receive	SET_EVENT_CODE
SpineMLSimulator::NetworkClient, 246	weightUpdateModels.h, 425
record	SET_EVENT_THRESHOLD_CONDITION_CODE
AnalogueRecorder, 107	weightUpdateModels.h, 426
SpikeRecorder, 304	SET_EXTRA_GLOBAL_PARAMS
SpineMLSimulator::LogOutput::AnalogueExternal,	initSparseConnectivitySnippet.h, 390
104	models.h, 400
SpineMLSimulator::LogOutput::AnalogueFile, 105	SET_INJECTION_CODE
SpineMLSimulator::LogOutput::Base, 167	currentSourceModels.h, 381
SpineMLSimulator::LogOutput::Event, 187	CurrentSourceModels::DC, 183
recordInternal	CurrentSourceModels::GaussianNoise, 206
SpineMLSimulator::LogOutput::AnalogueExternal,	
104	SET_LEARN_POST_CODE
SpineMLSimulator::LogOutput::AnalogueNetwork,	weightUpdateModels.h, 426
106	SET_LEARN_POST_SUPPORT_CODE
recordSpikes	weightUpdateModels.h, 426
SpikeWriterText, 310	SET_MAX_COL_LENGTH
SpikeWriterTextCached, 311	initSparseConnectivitySnippet.h, 390
regexFuncSubstitute	InitSparseConnectivitySnippet::OneToOne, 263
CodeGenerator, 77	SET_MAX_ROW_LENGTH
regexVarSubstitute	initSparseConnectivitySnippet.h, 391
CodeGenerator, 77	InitSparseConnectivitySnippet::OneToOne, 263
RegularSpikeRate	SET_NEEDS_AUTO_REFRACTORY
SpineMLSimulator::Input::RegularSpikeRate, 288	neuronModels.h, 409
reinitialise	NeuronModels::LIF, 229
pygenn::genn_groups::CurrentSource, 176	NeuronModels::PoissonNew, 273
pygenn::genn_groups::NeuronGroup, 249	NeuronModels::SpikeSource, 305
pygenn::genn_groups::SynapseGroup, 324	NeuronModels::SpikeSourceArray, 308
pygenn::genn_model::GeNNModel, 215	SET_NEEDS_POST_SPIKE_TIME
row_lengths	weightUpdateModels.h, 426
pygenn::genn_groups::SynapseGroup, 329	SET_NEEDS_PRE_SPIKE_TIME
runTools	weightUpdateModels.h, 426
	SET PARAM NAMES
GenerateRunBase, 207	snippet.h, 417
SET_ADDITIONAL_INPUT_VARS	SET_POST_SPIKE_CODE
neuronModels.h, 409	weightUpdateModels.h, 426
SET_APPLY_INPUT_CODE	SET_POST_VARS
	weightUpdateModels.h, 426
postsynapticModels.h, 413	- ·
SET_CALC_MAX_COL_LENGTH_FUNC	SET_PRE_SPIKE_CODE
initSparseConnectivitySnippet.h, 390	weightUpdateModels.h, 426

SET_PRE_VARS	pygenn::genn_groups::SynapseGroup, 326
weightUpdateModels.h, 427	set_psm_extra_global_param
SET_RESET_CODE	pygenn::genn_groups::SynapseGroup, 326
neuronModels.h, 409	set_psm_var
SET_ROW_BUILD_CODE	pygenn::genn_groups::SynapseGroup, 326
initSparseConnectivitySnippet.h, 391	set_sparse_connections
InitSparseConnectivitySnippet::FixedProbability,	pygenn::genn_groups::SynapseGroup, 327
199	set_values
$In it Sparse Connectivity Snippet :: Fixed Probability \leftarrow$	pygenn::model_preprocessor::ExtraGlobal
NoAutapse, 202	Variable, 196
InitSparseConnectivitySnippet::OneToOne, 263	pygenn::model_preprocessor::Variable, 366
SET_ROW_BUILD_STATE_VARS	set_var
initSparseConnectivitySnippet.h, 391	pygenn::genn_groups::Group, 218
$In it Sparse Connectivity Snippet :: Fixed Probability {\it } {\it } \\$	set_weight_update
Base, 201	pygenn::genn_groups::SynapseGroup, 327
SET_SIM_CODE	setBackPropDelaySteps
neuronModels.h, 410	SynapseGroup, 340
weightUpdateModels.h, 427	setDefaultExtraGlobalParamLocation
SET_SIM_SUPPORT_CODE	ModelSpec, 242
weightUpdateModels.h, 427	setDefaultNarrowSparseIndEnabled
SET_SUPPORT_CODE	ModelSpec, 243
neuronModels.h, 410	setDefaultSparseConnectivityLocation
postsynapticModels.h, 413	ModelSpec, 243
SET_SYNAPSE_DYNAMICS_CODE	setDefaultVarLocation
weightUpdateModels.h, 427	ModelSpec, 243
SET_SYNAPSE_DYNAMICS_SUPPORT_CODE	setDendriticDelayLocation
weightUpdateModels.h, 427	SynapseGroup, 340
SET_THRESHOLD_CONDITION_CODE	setDT
neuronModels.h, 410	ModelSpec, 243
SET_VARS	setEventThresholdReTestRequired
models.h, 401	SynapseGroup, 340
scalar	setExtraGlobalParamLocation
SpineMLSimulator, 97	CurrentSource, 180
ScalarBase	NeuronGroup, 257
SpineMLSimulator::InputValue::ScalarBase, 291	setInSynVarLocation
scalarExpr	SynapseGroup, 340
ModelSpec, 242	setMaxConnections
Scope	SynapseGroup, 340
CodeGenerator::CodeStream::Scope, 292	setMaxDendriticDelayTimesteps
send	SynapseGroup, 340
SpineMLSimulator::NetworkClient, 246	setMaxSourceConnections
set_connected_populations	SynapseGroup, 340
pygenn::genn_groups::SynapseGroup, 325	setMergePostsynapticModels
set_connectivity_extra_global_param	ModelSpec, 243
pygenn::genn_groups::SynapseGroup, 325	setName
set_current_source_model	ModelSpec, 243
pygenn::genn_groups::CurrentSource, 176	setNarrowSparseIndEnabled
set_extra_global_param	SynapseGroup, 340
pygenn::genn_groups::CurrentSource, 177	setNumThreadsPerSpike
pygenn::genn_groups::NeuronGroup, 249	SynapseGroup, 341
pygenn::genn_groups::SynapseGroup, 325	setPSExtraGlobalParamLocation
set_neuron	SynapseGroup, 341
pygenn::genn_groups::NeuronGroup, 249	setPSModelMergeTarget
set_post_syn	SynapseGroup, 341
pygenn::genn_groups::SynapseGroup, 325	setPSVarLocation
set_post_var	SynapseGroup, 341
pygenn::genn_groups::SynapseGroup, 326	setPrecision
set pre var	ModelSpec. 243

setSeed	getSymbol, 295
ModelSpec, 244	getSynapseDynamicsTime, 295
setSink	getTime, 295
CodeGenerator::CodeStream, 171	getTime, 233 getTimestep, 295
setSpanType	initialize, 296
SynapseGroup, 341	initializeSparse, 296
• •	open, 296
setSparseConnectivityExtraGlobalParamLocation	•
SynapseGroup, 341	pullConnectivityFromDevice, 296
setSparseConnectivityLocation	pullCurrentSpikesFromDevice, 296
SynapseGroup, 341	pullExtraGlobalParam, 296
setSpikeEventLocation	pullSpikesFromDevice, 296
NeuronGroup, 258	pullStateFromDevice, 296
setSpikeLocation	pullVarFromDevice, 297
NeuronGroup, 258	pushConnectivityToDevice, 297
setSpikeTimeLocation	pushCurrentSpikesToDevice, 297
NeuronGroup, 258	pushExtraGlobalParam, 297
setTime	pushSpikesToDevice, 297
SharedLibraryModel, 298	pushStateToDevice, 297
setTimePrecision	pushVarToDevice, 297
ModelSpec, 244	setTime, 298
setTimestep	setTimestep, 298
SharedLibraryModel, 298	SharedLibraryModel, 293
setTiming	stepTime, 298
ModelSpec, 244	SharedLibraryModel< scalar >, 292
setValue	sharedLibraryModel.h, 414
SpineMLSimulator::ModelProperty::Exponential←	shouldApply
Distribution, 193	SpineMLSimulator::Input::Base, 165
SpineMLSimulator::ModelProperty::Fixed, 198	shouldRecord
SpineMLSimulator::ModelProperty::Normal →	SpineMLSimulator::LogOutput::Base, 167
Distribution, 261	showPtxInfo
SpineMLSimulator::ModelProperty::Uniform←	CodeGenerator::CUDA::Preferences, 280
Distribution, 360	Simulator
SpineMLSimulator::ModelProperty::ValueList, 364	
setVarLocation	SpineMLSimulator::Simulator, 299
	simulator.cc, 415
CurrentSource, 180	simulator.h, 415
NeuronGroup, 258	singlePrecisionTemplate
setWUExtraGlobalParamLocation	CodeGenerator::FunctionTemplate, 203
SynapseGroup, 342	size
setWUPostVarLocation	pygenn::genn_groups::CurrentSource, 177
SynapseGroup, 342	pygenn::genn_groups::NeuronGroup, 250
setWUPreVarLocation	Snippet, 96
SynapseGroup, 342	snippet.h, 416
setWUVarLocation	DECLARE_SNIPPET, 416
SynapseGroup, 342	IMPLEMENT_SNIPPET, 417
SharedLibraryModel	SET_DERIVED_PARAMS, 417
~SharedLibraryModel, 293	SET_PARAM_NAMES, 417
allocateExtraGlobalParam, 294	Snippet::Base, 155
allocateMem, 294	\sim Base, 156
freeExtraGlobalParam, 294	DerivedParamVec, 156
freeMem, 294	EGPVec, 156
getArray, 294	getDerivedParams, 156
getFreeDeviceMemBytes, 294	getNamedVecIndex, 156
- · · · · · · · · · · · · · · · · · · ·	getParamNames, 157
getInitSparseTime, 294	-
getInitTime, 295	ParamValVec, 156
getNeuronUpdateTime, 295	StringVec, 156
getPostsynapticUpdateTime, 295	Snippet::Base::DerivedParam, 185
getPresynapticUpdateTime, 295	func, 185
getScalar, 295	name, 185

Snippet::Base::EGP, 185	SpineMLSimulator::Input::Base, 164
name, 186	\sim Base, 164
type, 186	apply, 165
Snippet::Base::ParamVal, 263	Base, 164
name, 263	shouldApply, 165
type, 263	updateValues, 165
value, 263	SpineMLSimulator::Input::InterSpikeIntervalBase, 221
Snippet::Init	apply, 222
getDerivedParams, 220	getTimeToSpike, 222
getParams, 220	InterSpikeIntervalBase, 221
getSnippet, 221	SpineMLSimulator::Input::PoissonSpikeRate, 273
Init, 220	getTimeToSpike, 274
initDerivedParams, 221	PoissonSpikeRate, 274
Snippet::Init< SnippetBase >, 220	SpineMLSimulator::Input::RegularSpikeRate, 287
Snippet::ValueBase	getTimeToSpike, 288
getValues, 362	RegularSpikeRate, 288
operator[], 362	SpineMLSimulator::Input::SpikeBase, 301
ValueBase, 362	injectSpike, 302
Snippet::ValueBase< 0 >, 363	PushCurrentSpikesFunc, 302
getValues, 363	SpikeBase, 302
ValueBase, 363	uploadSpikes, 302
	•
Snippet::ValueBase < NumVars >, 362	SpineMLSimulator::Input::SpikeTime, 308
SpanType	apply, 309
SynapseGroup, 332	SpikeTime, 309
spike_count	SpineMLSimulator::InputValue, 98
pygenn::genn_groups::NeuronGroup, 250	create, 98
spike_que_ptr	SpineMLSimulator::InputValue::Base, 165
pygenn::genn_groups::NeuronGroup, 250	∼Base, 166
SpikeBase	Base, 166
SpineMLSimulator::Input::SpikeBase, 302	getNumNeurons, 166
SpikeRecorder	getTargetIndices, 166
GetCurrentSpikeCountFunc, 303	update, 166
GetCurrentSpikesFunc, 303	SpineMLSimulator::InputValue::Constant, 172
getSum, 304	Constant, 173
record, 304	update, 173
SpikeRecorder, 303	SpineMLSimulator::InputValue::ConstantArray, 173
SpikeRecorder< Writer >, 302	ConstantArray, 174
spikeRecorder.h, 417	update, 174
SpikeTime	SpineMLSimulator::InputValue::External, 193
SpineMLSimulator::Input::SpikeTime, 309	External, 193
SpikeWriterText, 309	getBuffer, 194
recordSpikes, 310	getBufferBegin, 194
SpikeWriterText, 310	getBufferEnd, 194
SpikeWriterTextCached, 310	getSize, 194
~SpikeWriterTextCached, 311	update, 194
recordSpikes, 311	updateInternal, 194
SpikeWriterTextCached, 310	SpineMLSimulator::InputValue::ExternalNetwork, 194
writeCache, 311	ExternalNetwork, 195
spikes	updateInternal, 195
pygenn::genn_groups::NeuronGroup, 250	SpineMLSimulator::InputValue::ScalarBase, 291
SpineMLSimulator, 97	applyScalar, 292
scalar, 97	ScalarBase, 291
SpineMLSimulator::Connectors, 97	SpineMLSimulator::InputValue::TimeVarying, 348
create, 97	TimeVarying, 348
SpineMLSimulator::Input, 98	update, 348
SpineMLSimulator::Input::Analogue, 100	SpineMLSimulator::InputValue::TimeVaryingArray, 349
Analogue, 101	TimeVaryingArray, 349
apply, 101	update, 349
11.77	1,

SpineMLSimulator::LogOutput, 98 SpineMLSimulator::LogOutput::AnalogueBase, 101 AnalogueBase, 102	Mode, 245 NetworkClient, 245 receive, 246
getIndices, 102	send, 246
getModelPropertySize, 102	SpineMLSimulator::Simulator, 298
getStateVarBegin, 102	\sim Simulator, 299
getStateVarEnd, 102	calcNumTimesteps, 299
pullModelPropertyFromDevice, 103	getDT, 299
SpineMLSimulator::LogOutput::AnalogueExternal, 103	getDurationMs, 299
AnalogueExternal, 103	getExternalInput, 300
record, 104	getExternalLogger, 300
recordInternal, 104	getInitSparseTime, 300
SpineMLSimulator::LogOutput::AnalogueFile, 104	getInitTime, 300
AnalogueFile, 104	getInputMs, 300
record, 105	getLogMs, 300
SpineMLSimulator::LogOutput::AnalogueNetwork, 105	getNeuronUpdateTime, 300
AnalogueNetwork, 105	getPostsynapticUpdateTime, 300
recordInternal, 106	getPresynapticUpdateTime, 300
SpineMLSimulator::LogOutput::Base, 166	getSimulateMs, 300
~Base, 167	getSynapseDynamicsTime, 301
Base, 167	load, 301
getEndTimestep, 167	Simulator, 299
record, 167	stepTime, 301
shouldRecord, 167	SpineMLSimulator::StateVar
SpineMLSimulator::LogOutput::Event, 186	get, 312
Event, 186	isAccessible, 312
record, 187	m_Direct, 312
SpineMLSimulator::ModelProperty, 99	m_Indirect, 312
create, 99	pull, 312
SpineMLSimulator::ModelProperty::Base, 168	push, 312
~Base, 168	StateVar, 311
Base, 168	SpineMLSimulator::StateVar< T >, 311
getHostStateVar, 168	SpineMLSimulator::Timer, 346
getSize, 169	\sim Timer, 346
pullFromDevice, 169	get, 346
pushToDevice, 169	Timer, 346
$Spine MLS imulator :: Model Property :: Exponential {\leftarrow}$	SpineMLSimulator::TimerAccumulate, 347
Distribution, 192	\sim TimerAccumulate, 347
ExponentialDistribution, 192	get, 348
setValue, 193	TimerAccumulate, 347
SpineMLSimulator::ModelProperty::Fixed, 197	src
Fixed, 197, 198	pygenn::genn_groups::SynapseGroup, 329
setValue, 198	StateVar
SpineMLSimulator::ModelProperty::NormalDistribution,	SpineMLSimulator::StateVar, 311
260	stateVar.h, 417
NormalDistribution, 261	step_time
setValue, 261	pygenn::genn_model::GeNNModel, 215
SpineMLSimulator::ModelProperty::UniformDistribution,	stepTime
359	SharedLibraryModel, 298
setValue, 360	SpineMLSimulator::Simulator, 301
UniformDistribution, 360	StringVec
SpineMLSimulator::ModelProperty::ValueList, 363	Snippet::Base, 156
setValue, 364	substitute
ValueList, 364	CodeGenerator, 77
SpineMLSimulator::NetworkClient, 245	Substitutions
~NetworkClient, 246	CodeGenerator::Substitutions, 318
connect, 246	substitutions.h, 418
DataType, 245	synapse_dynamics_time

pygenn::genn_model::GeNNModel, 216	isZeroCopyEnabled, 339
synapse_order	setBackPropDelaySteps, 340
pygenn::genn_groups::SynapseGroup, 329	setDendriticDelayLocation, 340
synapse_populations	setEventThresholdReTestRequired, 340
pygenn::genn_model::GeNNModel, 217	setInSynVarLocation, 340
SynapseGroup, 329	setMaxConnections, 340
getBackPropDelaySteps, 333	setMaxDendriticDelayTimesteps, 340
getClusterHostID, 333	setMaxSourceConnections, 340
getConnectivityInitialiser, 333	setNarrowSparseIndEnabled, 340
getDelaySteps, 333	setNumThreadsPerSpike, 341
getDendriticDelayLocation, 333	setPSExtraGlobalParamLocation, 341
getDendriticDelayOffset, 334	setPSModelMergeTarget, 341
getInSynLocation, 334	setPSVarLocation, 341
getMatrixType, 334	setSpanType, 341
getMaxConnections, 334	setSparseConnectivityExtraGlobalParamLocation
getMaxDendriticDelayTimesteps, 334	341
getMaxSourceConnections, 334	setSparseConnectivityLocation, 341
getName, 334	setWUExtraGlobalParamLocation, 342
getNumThreadsPerSpike, 334	setWUPostVarLocation, 342
	setWUPreVarLocation, 342
getPSConstInitVals, 335	setWUVarLocation, 342
getPSDerivedParams, 335	SpanType, 332
getPSExtraGlobalParamLocation, 335	SynapseGroup, 332, 333
getPSModel, 335	synapseGroup.cc, 418
getPSModelTargetName, 335	synapseGroup.h, 418
getPSParams, 335	
getPSVarInitialisers, 335	SynapseGroupHandler
getPSVarLocation, 335	CodeGenerator::BackendBase, 137
getPostsynapticBackPropDelaySlot, 334	SynapseGroupInternal, 342
getPresynapticAxonalDelaySlot, 334	SynapseGroupInternal, 343
getSpanType, 336	synapseGroupInternal.h, 419
getSparseConnectivityExtraGlobalParamLocation,	SynapseGroupValueType
336	ModelSpec, 234
getSparseConnectivityLocation, 336	SynapseMatrixConnectivity
getSparseIndType, 336	synapseMatrixType.h, 420
getSrcNeuronGroup, 336	SynapseMatrixType
getTrgNeuronGroup, 336	synapseMatrixType.h, 420
getWUConstInitVals, 337	synapseMatrixType.h, 419
getWUDerivedParams, 337	operator&, 420, 421
getWUExtraGlobalParamLocation, 337	operator , 421
getWUModel, 337	SynapseMatrixConnectivity, 420
getWUParams, 337	SynapseMatrixType, 420
getWUPostVarInitialisers, 337	SynapseMatrixWeight, 420
-	SynapseMatrixWeight
getWUPostVarLocation, 337	synapseMatrixType.h, 420
getWUPreVarInitialisers, 338	
getWUPreVarLocation, 338	t
getWUVarInitialisers, 338	pygenn::genn_model::GeNNModel, 216
getWUVarLocation, 338	TYPE
initDerivedParams, 338	backendBase.cc, 373
isDendriticDelayRequired, 338	target_pop
isEventThresholdReTestRequired, 338	pygenn::genn_groups::CurrentSource, 177
isPSInitRNGRequired, 339	TeeBuf
isPSModelMerged, 339	CodeGenerator::TeeBuf, 344
isProceduralConnectivityRNGRequired, 339	TeeStream
isSparseConnectivityInitRequired, 339	CodeGenerator::TeeStream, 344
isSpikeEventRequired, 339	teeStream.h, 421
isTrueSpikeRequired, 339	TimePrecision
isWUInitRNGRequired, 339	modelSpec.h, 403
isWUVarInitRequired, 339	TimeVarying

SpineMLSimulator::InputValue::TimeVarying, 348	userCxxFlagsGNU
TimeVaryingArray	CodeGenerator::PreferencesBase, 282
SpineMLSimulator::InputValue::TimeVaryingArray,	userNvccFlags
349	CodeGenerator::CUDA::Preferences, 280
Timer, 345	userNvccFlagsGNU
∼Timer, 345	CodeGenerator::PreferencesBase, 282
get, 345	Utils, 99
SpineMLSimulator::Timer, 346	getUnderlyingType, 99
Timer, 345	isRNGRequired, 100
timer.h, 421, 422	isTypePointer, 100
TimerAccumulate, 346	utils.h, 422
\sim TimerAccumulate, 347	CHECK_CU_ERRORS, 422
get, 347	CHECK_CUDA_ERRORS, 422
SpineMLSimulator::TimerAccumulate, 347	
TimerAccumulate, 347	value
timestep	Snippet::Base::ParamVal, 263
pygenn::genn_model::GeNNModel, 216	ValueBase
timing_enabled	Snippet::ValueBase, 362
pygenn::genn_model::GeNNModel, 216	Snippet::ValueBase< 0 >, 363
trg	ValueList
pygenn::genn_groups::SynapseGroup, 329	SpineMLSimulator::ModelProperty::ValueList, 364
type	values
Models::Base::Var, 365	pygenn::model_preprocessor::ExtraGlobal←
pygenn::genn_groups::NeuronGroup, 250	Variable, 197
pygenn::model_preprocessor::ExtraGlobal←	pygenn::model_preprocessor::Variable, 367
Variable, 197	Var
pygenn::model_preprocessor::Variable, 367	Models::Base::Var, 365
Snippet::Base::EGP, 186	var_space_to_vals
Snippet::Base::ParamVal, 263	pygenn::model_preprocessor, 95 VarAccess
UniformDistribution	models.h, 401
SpineMLSimulator::ModelProperty::Uniform←	VarInit
Distribution, 360	Models::VarInit, 368
uninitialisedConnectivity	VarInitContainerBase
modelSpec.h, 405	Models::VarInitContainerBase, 369
uninitialisedVar	Models::VarInitContainerBase< 0 >, 370
modelSpec.h, 405	VarLocation
update	variableMode.h, 423
SpineMLSimulator::InputValue::Base, 166	VarValues
SpineMLSimulator::InputValue::Constant, 173	CurrentSourceModels::DC, 183
SpineMLSimulator::InputValue::ConstantArray, 174	CurrentSourceModels::GaussianNoise, 205
SpineMLSimulator::InputValue::External, 194	NeuronModels::Izhikevich, 224
SpineMLSimulator::InputValue::TimeVarying, 348	NeuronModels::IzhikevichVariable, 226
SpineMLSimulator::InputValue::TimeVaryingArray,	NeuronModels::LIF, 228
349	NeuronModels::Poisson, 269
updateInternal	NeuronModels::PoissonNew, 272
SpineMLSimulator::InputValue::External, 194	NeuronModels::RulkovMap, 290
SpineMLSimulator::InputValue::ExternalNetwork,	NeuronModels::SpikeSource, 305
195	NeuronModels::SpikeSourceArray, 307
updatePostVarQueues	NeuronModels::TraubMiles, 352
NeuronGroup, 258	NeuronModels::TraubMilesAlt, 354
updatePreVarQueues	NeuronModels::TraubMilesFast, 356
NeuronGroup, 258	NeuronModels::TraubMilesNStep, 358
updateValues	PostsynapticModels::DeltaCurr, 184
SpineMLSimulator::Input::Base, 165	PostsynapticModels::ExpCond, 188
uploadSpikes	PostsynapticModels::ExpCurr, 190
SpineMLSimulator::Input::SpikeBase, 302	VarVec
use_backend	Models::Base, 152
pygenn::genn_model::GeNNModel, 216, 217	variableMode.h, 423

operator&, 423	isPreSpikeTimeRequired, 267
VarLocation, 423	WeightUpdateModels::StaticGraded, 312
vars	DECLARE_WEIGHT_UPDATE_MODEL, 314
pygenn::genn_groups::Group, 219	getEventCode, 314
view	getEventThresholdConditionCode, 314
pygenn::model_preprocessor::ExtraGlobal←	getParamNames, 314
Variable, 197	getVars, 314
pygenn::model_preprocessor::Variable, 367	WeightUpdateModels::StaticPulse, 314
1,79	DECLARE_WEIGHT_UPDATE_MODEL, 315
w_update	getSimCode, 315
pygenn::genn_groups::SynapseGroup, 329	getVars, 316
weight update var size	WeightUpdateModels::StaticPulseDendriticDelay, 316
pygenn::genn_groups::SynapseGroup, 327	DECLARE_WEIGHT_UPDATE_MODEL, 317
WeightUpdateModels, 100	
weightUpdateModels.cc, 423	getSimCode, 317
IMPLEMENT_MODEL, 424	getVars, 317
weightUpdateModels.h, 424	writeCache
DECLARE_WEIGHT_UPDATE_MODEL, 425	SpikeWriterTextCached, 311
	writePreciseString
SET_EVENT_CODE, 425	CodeGenerator, 77
SET_EVENT_THRESHOLD_CONDITION_CODE,	writeSizes
426	GenerateRunBase, 207
SET_LEARN_POST_CODE, 426	
SET_LEARN_POST_SUPPORT_CODE, 426	xrange
SET_NEEDS_POST_SPIKE_TIME, 426	pygenn::genn_groups, 84
SET_NEEDS_PRE_SPIKE_TIME, 426	
SET_POST_SPIKE_CODE, 426	zero
SET_POST_VARS, 426	CodeGenerator::MemAlloc, 231
SET_PRE_SPIKE_CODE, 426	zeroCopy
SET_PRE_VARS, 427	CodeGenerator::MemAlloc, 231
SET_SIM_CODE, 427	zeroCopyInUse
SET_SIM_SUPPORT_CODE, 427	ModelSpec, 244
SET_SYNAPSE_DYNAMICS_CODE, 427	•
SET_SYNAPSE_DYNAMICS_SUPPORT_CODE,	
427	
WeightUpdateModels::Base, 160	
getEventCode, 161	
getEventThresholdConditionCode, 162	
getLearnPostCode, 162	
-	
getLearnPostSupportCode, 162	
getPostSpikeCode, 162	
getPostVarIndex, 162	
getPostVars, 162	
getPreSpikeCode, 162	
getPreVarIndex, 163	
getPreVars, 163	
getSimCode, 163	
getSimSupportCode, 163	
getSynapseDynamicsCode, 163	
getSynapseDynamicsSuppportCode, 163	
isPostSpikeTimeRequired, 163	
isPreSpikeTimeRequired, 164	
WeightUpdateModels::PiecewiseSTDP, 264	
DECLARE_WEIGHT_UPDATE_MODEL, 266	
getDerivedParams, 266	
getLearnPostCode, 266	
getParamNames, 266	
getSimCode, 267	
getVars, 267	
isPostSpikeTimeRequired, 267	
ioi ootopiike rimertequirea, 207	