GeNN

2.1

Generated by Doxygen 1.8.9.1

Fri Jun 12 2015 23:25:43

ii CONTENTS

Contents

1	Mair	n Page	2
2	Inst	allation	2
	2.1	Downloading a release	2
	2.2	Obtaining a Git snapshot	2
	2.3	Installing GeNN	3
	2.4	Testing Your Installation	4
3	Quid	ekstart	4
	3.1	Running an Example Model in Unix	4
	3.2	Running an Example Model in Windows	4
	3.3	How to use GeNN for New Projects	5
	3.4	Defining a New Model in GeNN	6
4	Exa	mples	8
	4.1	Single compartment Izhikevich neuron(s)	8
	4.2	Izhikevich neurons driven by Poisson input spike trains:	8
	4.3	Pulse-coupled Izhikevich network	9
	4.4	Izhikevich network with delayed synapses	10
	4.5	Insect olfaction model	10
	4.6	Insect olfaction model with user-defined neuron and synapse models	11
	4.7	Insect Olfaction Model using INDIVIDUALID connectivity scheme	11
	4.8	Insect Olfaction Model using INDIVIDUALID connectivity scheme	12
	4.9	Voltage clamp simulation to estimate Hodgkin-Huxley parameters	12
5	Rele	ease Notes for GeNN v2.0	13
6	Use	r Manual	15
	6.1	Contents	16
	6.2	Introduction	16
	6.3	Defining a network model	16
		6.3.1 Defining neuron populations	17
		6.3.2 Defining synapse populations	17
	6.4	Neuron models	18
		6.4.1 MAPNEURON (Map Neurons)	18
		6.4.2 POISSONNEURON (Poisson Neurons)	19
		6.4.3 TRAUBMILES_FAST (Hodgkin-Huxley neurons with Traub & Miles algorithm)	20
		6.4.4 IZHIKEVICH (Izhikevich neurons with fixed parameters)	21
		6.4.5 IZHIKEVICH_V (Izhikevich neurons with variable parameters)	21
		6.4.6 SPIKESOURCE (empty neuron which allows setting spikes from external sources)	22

		6.4.7	Defining your own neuron type	22
		6.4.8	Explicit current input to neurons (will be removed in future versions)	23
	6.5	Synaps	se models	23
		6.5.1	Built-in Models	24
		6.5.2	NSYNAPSE (No Learning)	24
		6.5.3	NGRADSYNAPSE (Graded Synapse)	25
		6.5.4	LEARN1SYNAPSE (Learning Synapse with a Primitive Role)	25
		6.5.5	LEARN1SYNAPSE (Learning Synapse with a Primitive Role)	26
		6.5.6	Conductance definition methods	26
		6.5.7	Connectivity types	26
		6.5.8	Postsynaptic integration methods	27
7	Tuto	rial 1		27
	7.1	The Mo	odel Definition	27
	7.2	User C	ode	29
	7.3	Makefi	e	30
	7.4	Making	and Running the Simulation	31
	7.5	Adding	External Input	31
8	Tuto	rial 2		32
	8.1	Adding	Synaptic connections	33
	8.2	Definin	g the Detailed Synaptic Connections	34
	8.3	Setting	Heterogeneous Initial Conditions	35
9	Sugg	_	s for users	36
	9.1	Creatir	ng and simulating a network model	36
	9.2	Floatin	g point precision	38
	9.3	Workin	g with variables in GeNN	38
		9.3.1	Model variables	38
		9.3.2	Built-in Variables in GeNN	39
	9.4	Debug	ging suggestions	40
		9.4.1		40
10	Cred	lits		40
11	Hiera	archical	Index	40
	11.1	Class I	Hierarchy	40
12	Clas	s Index		42
	12.1	Class I	ist	42
13	File	Index		43
	13.1	File Lis	at	43

iv CONTENTS

14	Class	s Documentation	48
	14.1	classIzh Class Reference	48
		14.1.1 Constructor & Destructor Documentation	49
		14.1.2 Member Function Documentation	49
		14.1.3 Member Data Documentation	50
	14.2	classol Class Reference	51
		14.2.1 Detailed Description	53
		14.2.2 Constructor & Destructor Documentation	54
		14.2.3 Member Function Documentation	54
		14.2.4 Member Data Documentation	59
	14.3	CodeHelper Class Reference	59
		14.3.1 Constructor & Destructor Documentation	60
		14.3.2 Member Function Documentation	60
		14.3.3 Member Data Documentation	60
	14.4	CStopWatch Class Reference	60
		14.4.1 Constructor & Destructor Documentation	61
		14.4.2 Member Function Documentation	61
	14.5	dpclass Class Reference	61
		14.5.1 Constructor & Destructor Documentation	61
		14.5.2 Member Function Documentation	61
	14.6	errTupel Struct Reference	62
		14.6.1 Member Data Documentation	62
	14.7	expDecayDp Class Reference	62
		14.7.1 Detailed Description	62
		14.7.2 Member Function Documentation	62
	14.8	inputSpec Struct Reference	63
		14.8.1 Member Data Documentation	63
	14.9	neuronModel Struct Reference	63
		14.9.1 Detailed Description	64
		14.9.2 Member Data Documentation	64
	14.10	Oneuronpop Class Reference	65
		14.10.1 Constructor & Destructor Documentation	66
		14.10.2 Member Function Documentation	66
		14.10.3 Member Data Documentation	66
	14.11	NNmodel Class Reference	67
		14.11.1 Detailed Description	70
		14.11.2 Constructor & Destructor Documentation	70
		14.11.3 Member Function Documentation	70
		14.11.4 Member Data Documentation	76
	14.12	2Parameter Struct Reference	80

14.12.1 Member Data Documentation	80
14.13postSynModel Struct Reference	81
14.13.1 Detailed Description	81
14.13.2 Member Data Documentation	81
14.14postVarsInPostLearn Class Reference	82
14.14.1 Constructor & Destructor Documentation	82
14.14.2 Member Function Documentation	82
14.14.3 Member Data Documentation	82
14.15postVarsInPostLearn_sparse Class Reference	82
14.15.1 Constructor & Destructor Documentation	83
14.15.2 Member Function Documentation	83
14.15.3 Member Data Documentation	83
14.16postVarsInSimCode Class Reference	83
14.16.1 Constructor & Destructor Documentation	84
14.16.2 Member Function Documentation	84
14.16.3 Member Data Documentation	84
14.17postVarsInSimCode_sparse Class Reference	84
14.17.1 Constructor & Destructor Documentation	84
14.17.2 Member Function Documentation	84
14.17.3 Member Data Documentation	84
14.18postVarsInSynapseDynamics Class Reference	85
14.18.1 Constructor & Destructor Documentation	85
14.18.2 Member Function Documentation	85
14.18.3 Member Data Documentation	85
14.19postVarsInSynapseDynamics_sparse Class Reference	85
14.19.1 Constructor & Destructor Documentation	86
14.19.2 Member Function Documentation	86
14.19.3 Member Data Documentation	86
14.20 pre VarsIn PostLearn Class Reference	86
14.20.1 Constructor & Destructor Documentation	87
14.20.2 Member Function Documentation	87
14.20.3 Member Data Documentation	87
14.21 preVarsInPostLearn_sparse Class Reference	87
14.21.1 Constructor & Destructor Documentation	87
14.21.2 Member Function Documentation	87
14.21.3 Member Data Documentation	87
14.22preVarsInSimCode Class Reference	88
14.22.1 Constructor & Destructor Documentation	88
14.22.2 Member Function Documentation	88
14.22.3 Member Data Documentation	88

vi CONTENTS

14.23preVarsInSimCode_sparse Class Reference	88
14.23.1 Constructor & Destructor Documentation	89
14.23.2 Member Function Documentation	89
14.23.3 Member Data Documentation	89
14.24preVarsInSynapseDynamics Class Reference	89
14.24.1 Constructor & Destructor Documentation	90
14.24.2 Member Function Documentation	90
14.24.3 Member Data Documentation	90
14.25preVarsInSynapseDynamics_sparse Class Reference	90
14.25.1 Constructor & Destructor Documentation	90
14.25.2 Member Function Documentation	90
14.25.3 Member Data Documentation	90
14.26pwSTDP Class Reference	91
14.26.1 Detailed Description	91
14.26.2 Member Function Documentation	91
14.27pwSTDP_userdef Class Reference	92
14.27.1 Detailed Description	92
14.27.2 Member Function Documentation	92
14.28randomGauss Class Reference	93
14.28.1 Detailed Description	93
14.28.2 Constructor & Destructor Documentation	93
14.28.3 Member Function Documentation	93
14.29randomGen Class Reference	94
14.29.1 Detailed Description	94
14.29.2 Constructor & Destructor Documentation	94
14.29.3 Member Function Documentation	94
14.30rulkovdp Class Reference	95
14.30.1 Detailed Description	95
14.30.2 Member Function Documentation	95
14.31Schmuker2014_classifier Class Reference	95
14.31.1 Detailed Description	97
14.31.2 Member Enumeration Documentation	98
14.31.3 Constructor & Destructor Documentation	98
14.31.4 Member Function Documentation	98
14.31.5 Member Data Documentation	00
14.32stdRG Class Reference	01
14.32.1 Constructor & Destructor Documentation	01
14.32.2 Member Function Documentation	
14.33stopWatch Struct Reference	
14.33.1 Member Data Documentation	02

CONTENTS vii

	14.34SynDelay Class Reference	102
	14.34.1 Constructor & Destructor Documentation	102
	14.34.2 Member Function Documentation	102
	14.35weightUpdateModel Class Reference	103
	14.35.1 Detailed Description	104
	14.35.2 Constructor & Destructor Documentation	104
	14.35.3 Member Data Documentation	104
45	File Documentation	105
13	15.1 00_MainPage.dox File Reference	
	15.2 01_Installation.dox File Reference	
	15.3 02_Quickstart.dox File Reference	
	15.4 03_Examples.dox File Reference	
	15.5 09_ReleaseNotes_v2.dox File Reference	
	15.6 10 UserManual.dox File Reference	
	15.7 11 Tutorial.dox File Reference	
	15.8 12_Tutorial.dox File Reference	
	15.9 13_UserGuide.dox File Reference	
	15.1014_Credits.dox File Reference	
	15.11 classol_sim.cu File Reference	
	15.11.1 Function Documentation	
	15.12classol_sim.cu File Reference	
	15.12.1 Function Documentation	
	15.13classol_sim.cu File Reference	
	15.13.1 Function Documentation	
	15.14classol_sim.cu File Reference	
	15.14.1 Function Documentation	
	15.15classol_sim.h File Reference	
	15.15.1 Macro Definition Documentation	107
	15.15.2 Variable Documentation	107
	15.16classol_sim.h File Reference	108
	15.16.1 Macro Definition Documentation	108
	15.16.2 Variable Documentation	108
	15.17classol_sim.h File Reference	109
	15.17.1 Macro Definition Documentation	109
	15.17.2 Variable Documentation	110
	15.18classol_sim.h File Reference	110
	15.18.1 Macro Definition Documentation	
	15.18.2 Variable Documentation	111
	15.19CodeHelper.cc File Reference	111

VIII CONTENTS

15.19.1 Macro Definition Documentation	111
15.20ensureFtype.h File Reference	112
15.20.1 Function Documentation	112
15.20.2 Variable Documentation	112
15.21 experiment.cu File Reference	112
15.21.1 Macro Definition Documentation	113
15.21.2 Typedef Documentation	113
15.21.3 Function Documentation	113
15.21.4 Variable Documentation	113
15.22 experiment.h File Reference	114
15.22.1 Macro Definition Documentation	114
15.22.2 Typedef Documentation	115
15.22.3 Variable Documentation	115
15.23extra_neurons.h File Reference	115
15.23.1 Function Documentation	116
15.23.2 Variable Documentation	116
15.24extra_postsynapses.h File Reference	117
15.24.1 Function Documentation	117
15.24.2 Variable Documentation	117
15.25extra_postsynapses.h File Reference	118
15.25.1 Function Documentation	118
15.25.2 Variable Documentation	118
15.26extra_weightupdates.h File Reference	119
15.27GA.cc File Reference	119
15.27.1 Function Documentation	119
15.28 gauss.cc File Reference	119
15.28.1 Detailed Description	119
15.28.2 Macro Definition Documentation	120
15.29 gauss.h File Reference	120
15.29.1 Detailed Description	120
15.29.2 Macro Definition Documentation	120
15.30gen_input_structured.cc File Reference	120
15.30.1 Function Documentation	121
15.30.2 Variable Documentation	121
15.31gen_kcdn_syns.cc File Reference	121
15.31.1 Detailed Description	121
15.31.2 Function Documentation	121
15.31.3 Variable Documentation	
15.32gen_kcdn_syns_fixto10K.cc File Reference	121
15.32.1 Function Documentation	122

15.32.2 Variable Documentation
15.33gen_pnkc_syns.cc File Reference
15.33.1 Detailed Description
15.33.2 Function Documentation
15.33.3 Variable Documentation
15.34gen_pnkc_syns_indivID.cc File Reference
15.34.1 Detailed Description
15.34.2 Function Documentation
15.34.3 Variable Documentation
15.35gen_pnlhi_syns.cc File Reference
15.35.1 Detailed Description
15.35.2 Function Documentation
15.36gen_syns_sparse.cc File Reference
15.36.1 Detailed Description
15.36.2 Function Documentation
15.36.3 Variable Documentation
15.37gen_syns_sparse_izhModel.cc File Reference
15.37.1 Detailed Description
15.37.2 Function Documentation
15.37.3 Variable Documentation
15.38generate_run.cc File Reference
15.38.1 Function Documentation
15.39generate_run.cc File Reference
15.39.1 Macro Definition Documentation
15.39.2 Function Documentation
15.40generate_run.cc File Reference
15.40.1 Macro Definition Documentation
15.40.2 Function Documentation
15.41 generate_run.cc File Reference
15.41.1 Macro Definition Documentation
15.41.2 Function Documentation
15.42generate_run.cc File Reference
15.42.1 Macro Definition Documentation
15.42.2 Function Documentation
15.43generate_run.cc File Reference
15.43.1 Macro Definition Documentation
15.43.2 Function Documentation
15.44generate_run.cc File Reference
15.44.1 Function Documentation
15.45generate_run.cc File Reference

X CONTENTS

15.45.1 Function Documentation
15.46generateALL.cc File Reference
15.46.1 Detailed Description
15.46.2 Function Documentation
15.47generateCPU.cc File Reference
15.47.1 Detailed Description
15.47.2 Function Documentation
15.48generateKernels.cc File Reference
15.48.1 Detailed Description
15.48.2 Function Documentation
15.48.3 Variable Documentation
15.49generateRunner.cc File Reference
15.49.1 Detailed Description
15.49.2 Function Documentation
15.50GeNNHelperKrnls.cu File Reference
15.50.1 Macro Definition Documentation
15.50.2 Function Documentation
15.51 global.h File Reference
15.51.1 Detailed Description
15.51.2 Macro Definition Documentation
15.51.3 Variable Documentation
15.52helper.h File Reference
15.52.1 Function Documentation
15.52.2 Variable Documentation
15.53HHVClamp.cc File Reference
15.53.1 Detailed Description
15.53.2 Macro Definition Documentation
15.53.3 Function Documentation
15.53.4 Variable Documentation
15.54HHVClampParameters.h File Reference
15.54.1 Macro Definition Documentation
15.55hr_time.cpp File Reference
15.55.1 Detailed Description
15.55.2 Macro Definition Documentation
15.56hr_time.h File Reference
15.56.1 Detailed Description
15.57lzh_sim_sparse.cu File Reference
15.57.1 Function Documentation
15.58lzh_sparse.cc File Reference
15.58.1 Macro Definition Documentation

CONTENTS xi

15.58.2 Function Documentation
15.58.3 Variable Documentation
15.59Izh_sparse_model.cc File Reference
15.59.1 Macro Definition Documentation
15.59.2 Variable Documentation
15.60 lzh_sparse_model.h File Reference
15.61 lzh_sparse_sim.h File Reference
15.61.1 Macro Definition Documentation
15.61.2 Variable Documentation
15.62map_classol.cc File Reference
15.62.1 Macro Definition Documentation
15.63map_classol.cc File Reference
15.63.1 Macro Definition Documentation
15.64map_classol.cc File Reference
15.64.1 Macro Definition Documentation
15.65map_classol.cc File Reference
15.65.1 Macro Definition Documentation
15.66map_classol.h File Reference
15.67map_classol.h File Reference
15.68map_classol.h File Reference
15.69map_classol.h File Reference
15.70MBody1.cc File Reference
15.70.1 Macro Definition Documentation
15.70.2 Function Documentation
15.70.3 Variable Documentation
15.71 MBody1.cc File Reference
15.71.1 Macro Definition Documentation
15.71.2 Function Documentation
15.71.3 Variable Documentation
15.72MBody_delayedSyn.cc File Reference
15.72.1 Detailed Description
15.72.2 Macro Definition Documentation
15.72.3 Function Documentation
15.72.4 Variable Documentation
15.73MBody_individualID.cc File Reference
15.73.1 Detailed Description
15.73.2 Macro Definition Documentation
15.73.3 Function Documentation
15.73.4 Variable Documentation
15.74MBody_userdef.cc File Reference

xii CONTENTS

15.74.1 Detailed Description
15.74.2 Macro Definition Documentation
15.74.3 Function Documentation
15.74.4 Variable Documentation
15.75Model_Schmuker_2014_classifier.cc File Reference
15.75.1 Macro Definition Documentation
15.75.2 Function Documentation
15.76modelSpec.cc File Reference
15.76.1 Macro Definition Documentation
15.76.2 Function Documentation
15.77modelSpec.h File Reference
15.77.1 Detailed Description
15.77.2 Macro Definition Documentation
15.77.3 Function Documentation
15.77.4 Variable Documentation
15.78OneComp.cc File Reference
15.78.1 Macro Definition Documentation
15.78.2 Function Documentation
15.78.3 Variable Documentation
15.79OneComp_model.cc File Reference
15.79.1 Macro Definition Documentation
15.80OneComp_model.h File Reference
15.81OneComp_sim.cu File Reference
15.81.1 Function Documentation
15.82OneComp_sim.h File Reference
15.82.1 Macro Definition Documentation
15.82.2 Variable Documentation
15.83PoissonIzh-model.cc File Reference
15.83.1 Macro Definition Documentation
15.84PoissonIzh-model.h File Reference
15.85PoissonIzh.cc File Reference
15.85.1 Macro Definition Documentation
15.85.2 Function Documentation
15.85.3 Variable Documentation
15.86PoissonIzh_sim.cu File Reference
15.86.1 Function Documentation
15.87PoissonIzh_sim.h File Reference
15.87.1 Macro Definition Documentation
15.87.2 Variable Documentation
15.88postVarsInPostLearn.cc File Reference

CONTENTS xiii

15.88.1 Macro Definition Documentation
15.88.2 Function Documentation
15.88.3 Variable Documentation
15.89postVarsInPostLearn_sparse.cc File Reference
15.89.1 Macro Definition Documentation
15.89.2 Function Documentation
15.89.3 Variable Documentation
15.90postVarsInSimCode.cc File Reference
15.90.1 Macro Definition Documentation
15.90.2 Function Documentation
15.90.3 Variable Documentation
15.91 postVarsInSimCode_sparse.cc File Reference
15.91.1 Macro Definition Documentation
15.91.2 Function Documentation
15.91.3 Variable Documentation
15.92postVarsInSynapseDynamics.cc File Reference
15.92.1 Macro Definition Documentation
15.92.2 Function Documentation
15.92.3 Variable Documentation
15.93postVarsInSynapseDynamics_sparse.cc File Reference
15.93.1 Macro Definition Documentation
15.93.2 Function Documentation
15.93.3 Variable Documentation
15.94preVarsInPostLearn.cc File Reference
15.94.1 Macro Definition Documentation
15.94.2 Function Documentation
15.94.3 Variable Documentation
15.95preVarsInPostLearn_sparse.cc File Reference
15.95.1 Macro Definition Documentation
15.95.2 Function Documentation
15.95.3 Variable Documentation
15.96preVarsInSimCode.cc File Reference
15.96.1 Macro Definition Documentation
15.96.2 Function Documentation
15.96.3 Variable Documentation
15.97preVarsInSimCode_sparse.cc File Reference
15.97.1 Macro Definition Documentation
15.97.2 Function Documentation
15.97.3 Variable Documentation
15.98preVarsInSynapseDynamics.cc File Reference

xiv CONTENTS

15.98.1 Macro Definition Documentation
15.98.2 Function Documentation
15.98.3 Variable Documentation
15.99preVarsInSynapseDynamics_sparse.cc File Reference
15.99.1 Macro Definition Documentation
15.99.2 Function Documentation
15.99.3 Variable Documentation
15.10@andomGen.cc File Reference
15.100. Detailed Description
15.100.2Macro Definition Documentation
15.10 flandom Gen.h File Reference
15.101. Detailed Description
15.101.2Macro Definition Documentation
15.10 2 chmuker2014_classifier.cu File Reference
15.102. Macro Definition Documentation
15.10 \$ chmuker2014_classifier.h File Reference
15.103. Detailed Description
15.10 4 impleBit.h File Reference
15.104. Detailed Description
15.104.2Macro Definition Documentation
15.10 s izes.h File Reference
15.105. Macro Definition Documentation
15.106 parse Utils.cc File Reference
15.106. Macro Definition Documentation
15.106. Function Documentation
15.10 stringutils.h File Reference
15.107. Macro Definition Documentation
15.107. Function Documentation
15.107.3/ariable Documentation
15.10 S ynDelay.cc File Reference
15.108. Macro Definition Documentation
15.108. Function Documentation
15.108.3/ariable Documentation
15.10 % ynDelaySim.cu File Reference
15.109. Macro Definition Documentation
15.109. Function Documentation
15.11 % ynDelaySim.h File Reference
15.110.1 Macro Definition Documentation
15.111estHelper.h File Reference
15.111. Function Documentation

CONTENTS xv

15.11 2est Helper.h File Reference
15.112. Function Documentation
15.11&estPostVarsInPostLearn.cu File Reference
15.113. Macro Definition Documentation
15.113. Function Documentation
15.11#estPostVarsInPostLearn.h File Reference
15.114. Macro Definition Documentation
15.11 5 estPostVarsInPostLearn_sparse.cu File Reference
15.115. Macro Definition Documentation
15.115. Function Documentation
15.11 cestPostVarsInPostLearn_sparse.h File Reference
15.116. Macro Definition Documentation
15.11 TestPostVarsInSimCode.cu File Reference
15.117. Macro Definition Documentation
15.117. Function Documentation
15.11&estPostVarsInSimCode.h File Reference
15.118. Macro Definition Documentation
15.11 9 estPostVarsInSimCode_sparse.cu File Reference
15.119. Macro Definition Documentation
15.119. Function Documentation
15.12@estPostVarsInSimCode_sparse.h File Reference
15.120. Macro Definition Documentation
15.12 testPostVarsInSynapseDynamics.cu File Reference
15.121. Macro Definition Documentation
15.121. Function Documentation
15.12 2est Post Vars In Synapse Dynamics. h File Reference
15.122. Macro Definition Documentation
15.12 SestPostVarsInSynapseDynamics_sparse.cu File Reference
15.123. Macro Definition Documentation
15.123. Function Documentation
15.12 testPostVarsInSynapseDynamics_sparse.h File Reference
15.124. Macro Definition Documentation
15.125estPreVarsInPostLearn.cu File Reference
15.125. Macro Definition Documentation
15.125. Function Documentation
15.12 testPreVarsInPostLearn.h File Reference
15.126. Macro Definition Documentation
15.12 TestPreVarsInPostLearn_sparse.cu File Reference
15.127. Macro Definition Documentation
15.127. Function Documentation

Ind	ex	223
Bib	liography	221
	15.140.2/ariable Documentation	220
	15.140. Macro Definition Documentation	
	15.14\(\mathbb{O}\)ClampGA.h File Reference	
	15.139. Function Documentation	
	15.139. Detailed Description	219
	15.139/ClampGA.cu File Reference	219
	15.138.4/ariable Documentation	219
	15.138. Function Documentation	218
	15.138.2Macro Definition Documentation	218
	15.138. Detailed Description	218
	15.138tils.h File Reference	216
	15.137. Function Documentation	216
	15.137.2Macro Definition Documentation	216
	15.137. Detailed Description	216
	15.13% String.h File Reference	215
	15.136. Macro Definition Documentation	
	15.13@estPreVarsInSynapseDynamics_sparse.h File Reference	215
	15.135. Function Documentation	215
	15.135. Macro Definition Documentation	215
	15.13festPreVarsInSynapseDynamics_sparse.cu File Reference	215
	15.134. Macro Definition Documentation	
	15.13 testPreVarsInSynapseDynamics.h File Reference	214
	15.133. Function Documentation	214
	15.133. Macro Definition Documentation	
	15.138estPreVarsInSynapseDynamics.cu File Reference	
	15.132. Macro Definition Documentation	
	15.132estPreVarsInSimCode_sparse.h File Reference	
	15.131. Function Documentation	
	15.131. Macro Definition Documentation	
	15.131estPreVarsInSimCode_sparse.cu File Reference	
	15.130. Macro Definition Documentation	
	15.13@estPreVarsInSimCode.h File Reference	
	15.129. Function Documentation	
	15.129. Macro Definition Documentation	
	15.12\text{\text{\text{8}}stPreVarsInSimCode.cu File Reference	
	15.128. Macro Definition Documentation	
	15.12&stPreVarsInPostLearn_sparse.h File Reference	211

1 Main Page

GeNN is a software package to enable neuronal network simulations on NVIDIA GPUs by code generation. Models are defined in a simple C-style API and the code for running them on either GPU or CPU hardware is generated by GeNN. GeNN can also be used through external interfaces. Currently there are prototype interfaces for Spine Creator and SpineML and for Brian2.

GeNN is currently developed and maintained by

```
James Turner (contact James)
Dr. Esin Yavuz (contact Esin)
Prof. Thomas Nowotny (contact Thomas)
```

The development of GeNN is partially supported by the EPSRC (grant number EP/J019690/1 - Green Brain Project).

Note

This documentation is under construction. If you cannot find what you are looking for, please contact the project developers.

Next

2 Installation

You can download GeNN either as a zip file of a stable release or a snapshot of the most recent stable version or the unstable development version using the Git version control system.

2.1 Downloading a release

Point your browser to https://github.com/genn-team/genn/releases and download a release from the list by clicking the relevant source code button. Note that GeNN is only distributed in the form of source code due to its code generation design. Binary distributions would not make sense in this framework and are not provided. After downloading continue to install GeNN as described in the Installing GeNN section below.

2.2 Obtaining a Git snapshot

If it is not yet installed on your system, download and install Git (http://git-scm.com/). Then clone the GeNN repository from Github

```
git clone https://github.com/genn-team/genn.git
```

The github url of GeNN in the command above can be copied from the HTTPS clone URL displayed on the GeNN Github page (https://github.com/genn-team/genn).

This will clone the entire repository, including all open branches. By default git will check out the master branch which contains the source version upon which the latest release is based. If you want the most recent (but unstable) development version (which may or may not be fully functional at any given time), checkout the development branch

```
git checkout development
```

There are other branches in the repository that are used for specific development purposes and are opened and closed without warning.

As an alternative to using git you can also download the full content of GeNN sources clicking on the "Download ZIP" button on the bottom right of the GeNN Github page (https://github.com/genn-team/genn).

2.3 Installing GeNN 3

2.3 Installing GeNN

Installing GeNN comprises a few simple steps to create the GeNN development environment.

- (i) If you have downloaded a zip file, unpack GeNN.zip in a convenient location. Otherwise enter the directory where you downloaded the Git repository.
- (ii) Define the environment variable "GENN_PATH" to point to the main GeNN directory, e.g. if you extracted/downloaded GeNN to /usr/local/GeNN, then you can add "export GENN_PATH=/usr/local/GeNN" to your login script (e.g. .profile or .bashrc. If you are using WINDOWS, the path should be a windows path as it will be interpreted by the Visual C++ compiler cl, and enciront variables are best set using setx in a Windows cmd window. To do so, open a Windows cmd window byt typing cmd in the search field of the start menu, followed by the enter key. In the cmd window type

```
setx GENN_PATH "C:\Users\me\GeNN"
```

where C:\Users\me\GeNN is the path to your GeNN directory.

(iii) Add \$GENN PATH/lib/bin to your PATH variable, e.g.

```
export PATH=$PATH:$GENN_PATH/lib/bin
```

in your login script, or in windows,

```
setx PATH=%PATH%;%GENN_PATH%/lib/bin
```

- (iv) If you haven't installed CUDA on your machine, obtain a fresh installation of the NVIDIA CUDA toolkit from https://developer.nvidia.com/cuda-downloads
- (v) Set the CUDA_PATH variable if it is not already set by the system, by putting

```
export CUDA_PATH=/usr/local/cuda
```

in your login script (or, if CUDA is installed in a non-standard location, the appropriate path to the main CUDA directory). For most people, this will be done by the CUDA install script and the default value of /usr/local/cuda is fine. In Windows, use setx to set this variable,

```
setx CUDA_PATH
```

This normally completes the installation.

Depending on the needs of your own projects, e.g., depencies on other libraries or non-standard installation paths of libraries used by GeNN, you may want to modify Makefile examples under $GENN_PATH/userproject/xxx \leftarrow project$ and $GENN_PATH/userproject/xxx project/model$ to add extra linker-, include- and compiler-flags on a per-project basis, or modify global default flags in $GENN_PATH/lib/include/makefile \leftarrow common.mk$.

For all makefiles there are separate makefiles for Unix-style operating systems (GNUmakefile) such as Linux or MacOS and for Windows (WINmakefile).

If you are using GeNN in Windows, you can use make.bat to build examples which will attempt to setup your development environment by executing vcvarsall.bat which is part of every Visual Studio distribution. For this to work properly, GeNN must be able to locate the Visual Studio install directory, which should be contained in the VS_PATH environment variable. You can set this variable by hand if it is not already set by the Visual C++ installer by typing

```
setx VS_PATH "C:\Program Files (x86)\Microsoft Visual Studio 10.0"
```

Note

- The exact path and name of Visual C++ installations will vary between systems.
- Double quotation marks like in the above example are necessary whenever a path contains spaces.

GeNN also has experimental CYGWIN support. However, with the introduction of native Windows support in GeNN 1.1.3, this is not being developed further and should be considered as deprecated.

2.4 Testing Your Installation

To test your installation, follow the example in the Quickstart section.

Top | Next

3 Quickstart

GeNN is based on the idea of code generation for the involved GPU or CPU simulation code for neuronal network models but leaves a lot of freedom how to use the generated code in the final application. To facilitate the use of GeNN on the background of this philosophy, it comes with a number of complete examples containing both the model description code that is used by GeNN for code generation and the "user side code" to run the generated model and safe the results. Running these complete examples should be achievable in a few minutes. The necessary steps are described below.

3.1 Running an Example Model in Unix

In order to get a quick start and run a provided model, open a shell, navigate to GeNN/tools and type

make

This will compile additional tools for creating and running example projects. For a first complete test, the system is best used with a full driver program such as in the Insect olfaction model example:

```
tools/generate_run <0(CPU)/1(GPU)> <#AL> <#KC> <#LH> <#DN> <gscale> <OUTNAME> <MODEL> <DEBUG> <FTYPE> <REUSE>.
```

To compile $generate_run.cc$, navigate to the $userproject/MBody1_project$ directory and type

make all

This will generate an executable that you can invoke with, e.g.,

```
./generate_run 1 100 1000 20 100 0.0025 test1 MBody1 0 FLOAT 0
```

which would generate and simulate a model of the locust olfactory system with 100 projection neurons, 1000 Kenyon cells, 20 lateral horn interneurons and 100 output neurons n the mushroom body lobes.

The tool generate_run will generate connectivity matrices for the model $\mathtt{MBody1}$ and store them into files, compile and run the model on the GPU using these files as inputs and output the resulting spiking activity. To fix the GPU used, replace the first argument 1 with the device number of the desired GPU plus 2, e.g., 2 for GPU 0. All input and output files will be prefixed with $\mathtt{test1}$ and will be created in a sub-directory with the name $\mathtt{test1}_\mathtt{output}$. The third to last parameter 0 will switch the debugging mode off, 1 would switch it on. More about debugging in the debugging section . The parameter \mathtt{FLOAT} will run the model in float (single precision floating point), using $\mathtt{DOU} \leftarrow \mathtt{BLE}$ would use double precision. The last parameter regulates whether previously generated files for connectivity and input should be reused (1) or files should be generated anew (0).

The MBody1 example is already a highly integrated example that showcases many of the features of GeNN and how to program the user-side code for a GeNN application. More details in the User Manual

3.2 Running an Example Model in Windows

All interaction with GeNN programs are command-line based and hence are executed within a cmd window. Open a cmd window and navigate to the userprojects\tools directory.

cd %GENN_PATH%\userprojects\tools

Then type

make.bat all

to compile a number of tools that are used by the example projects to generate connectivity and inputs to model networks.

The navigate to the MBody1_project directory.

```
cd ..\MBody1_project
```

By typing

make.bat all

you can compile the <code>generate_run</code> engine that allows to run a Insect olfaction model model of the insect mush-room body:

```
tools/generate_run <0(CPU)/1(GPU)> <#AL> <#KC> <#LH> <#DN> <gscale> <OUTNAME> <MODEL> <DEBUG> <FTYPE>
```

To invoke generate_run.exe type, e.g.,

```
generate_run.exe 1 100 1000 20 100 0.0025 test1 MBody1 0 FLOAT 0
```

which would generate and simulate a model of the locust olfactory system with 100 projection neurons, 1000 Kenyon cells, 20 lateral horn interneurons and 100 output neurons n the mushroom body lobes.

The tool <code>generate_run.exe</code> will generate connectivity matrices for the model <code>MBody1</code> and store them into files, compile and run the model on an automatically chosen GPU using these files as inputs and output the resulting spiking activity. To fix the GPU used, replace the first argument 1 with the device number of the desired GPU plus 2, e.g., 2 for GPU 0. All input and output files will be prefixed with <code>test1</code> and will be created in a sub-directory with the name <code>test1_output</code>. The last parameter 0 will switch the debugging mode off, 1 would switch it on. More about debugging in the <code>debugging section</code>.

The MBody1 example is already a highly integrated example that showcases many of the features of GeNN and how to program the user-side code for a GeNN application. More details in the User Manual

3.3 How to use GeNN for New Projects

Creating and running projects in GeNN involves a few steps ranging from defining the fundamentals of the model, inputs to the model, details of the model like specific connectivity matrices or initial values, running the model and analyzing or saving the data.

The most common way to use GeNN is to create or modify a program such as userproject/MBody1_\Limits project/generate_run.cc that wraps around other programs that are used for each of the necessary steps listed above. In more detail, what generate_run and similar programs do is:

- 1. To use other tools (programs) to generate connectivity matrices and store them into files.
- 2. To build the source code of a model simulation using GeNN. In the example of the MBody1_project this entails writing neuron numbers into userproject/include/sizes.h, and executing

```
buildmodel.sh MBody1 [DEBUG OFF/ON]
```

The buildmodel.sh script compiles the installed GeNN code generator in conjunction with the user-provided model description (see below), in this example model/MBody1.cc. It then executes the GeNN code generator to generate the complete model simulation code for the MBody1 model.

3. To compile the generated model code, that can be found in model/MBody1_CODE/ by invoking make clean && make in the model directory. It is at this stage that GeNN generated model simulation code is combined with user-side run-time code, in this example classol_sim.cu (classify-olfaction-simulation) which uses the map_classol (map-neuron-based-classifier-olfaction) class.

4. To finally run the resulting stand-alone simulator executable, in the MBody1 example classol_sim in the model directory.

The generate_run tool is only a suggested usage scenario of GeNN. Alternatively, users can manually execute the four steps above or integrate GeNN with development environments of their own choice.

Note

The usage scenario described was made explicit for Unix environments. In Windows the setup is essentially the same except for the usual operating system dependent syntax differences, e.g. the build script is named buildmodel.bat, compilation of the generated model simulator would be make.bat clean && make.bat all, or, nmake f WINmakefile clean && nmake f WINmakefile all, and the resulting executable would be named classol_sim.exe.

GeNN comes with several example projects which showcase how to use its features. The MBody1 example discussed above is one of the many provided examples that are described in more detail in Example projects.

3.4 Defining a New Model in GeNN

According to the work flow outlined above, there are several steps to be completed to define a neuronal network model.

1. The neuronal network of interest is defined in a model definition file, e.g. Example1.cc.

Note

GeNN follows a convention in which C/C++ files end with .cc and the model definition file will only be recognized by the <code>buildmodel.sh</code> or <code>buildmodel.bat</code> scripts if it follows this convention and ends on .cc.

- 2. Within the the model definition file Example1.cc, the following tasks need to be completed:
 - a) The time step DT needs to be defined, e.g.

```
#define DT 0.1
```

Note

All provided examples and pre-defined model elements in GeNN work with units of mV, ms, nF and muS. However, the choice of units is entirely left to the user if custom model elements are used.

b) The GeNN files modelSpec.h and modelSpec.cc need to be included,

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

c) The values for initial variables and parameters for neuron and synapse populations need to be defined, e.g.

would define the (homogeneous) parameters for a population of Poisson neurons.

Note

The number of required parameters and their meaning is defined by the neuron or synapse type. Refer to the User Manual for details.

We recommend, however, to use comments like in the above example to achieve maximal clarity of each parameter's meaning.

If heterogeneous parameter values are needed for any particular population of neurons (synapses), a new neuron (synapse) type needs to be defined in which these parameters are defined as "variables" rather than parameters. See the User Manual for how to define new neuron (synapse) types.

d) the actual network needs to be defined in the form of a function modelDefinition, i.e.

```
void modelDefinition(NNmodel &model);
```

Note

The name modelDefinition and its parameter of type NNmodel& are fixed and cannot be changed if GeNN is to recognize it as a model definition.

 ${\tt MBody1.cc}$ shows a typical example of a model definition function. In its core it contains calls to ${\tt model.} \leftarrow {\tt addNeuronPopulation}$ and ${\tt model.addSynapsePopulation}$ to build up the network. For a full range of options for defining a network, refer to the User Manual.

- The programmer defines her own "user-side" modeling code similar to the code in userproject/M

 Body1_project/model/map_classol.* and userproject/MBody1_project/model/classol

 _sim.*. In this code,
 - a) she defines the connectivity matrices between neuron groups. (In the MBody1 example those are read from files). Refer to the User Manual for the required format of connectivity matrices for dense or sparse connectivities.
 - b) she defines input patterns (e.g. for Poisson neurons like in the MBody1 example) or individual initial values for neuron and/or synapse variables.

Note

The initial values given in the modelDefinition are automatically applied homogeneously to every individual neuron or synapse in each of the neuron or synapse groups.

c) she uses stepTimeGPU(...); to run one time step on the GPU or stepTimeCPU(...); to run one on the CPU. (both GPU and CPU versions are always compiled).

Note

However, mixing CPU and GPU execution does not make too much sense. Among other things, The CPU version uses the same host side memory where to results from the GPU version are copied, which would lead to collisions between what is calculated on the CPU and on the GPU (see next point). However, in certain circumstances, expert users may want to split the calculation and calculate parts (e.g. neurons) on the GPU and parts (e.g. synapses) on the CPU. In such cases the fundamental kernel and function calls contained in stepTimeXXX need to be used and appropriate copies of the data from the CPU to the GPU and vice versa need to be performed.

- d) she uses functions like copyStateFromDevice() etc to transfer the results from GPU calculations to the main memory of the host computer for further processing.
- e) she analyzes the results. In the most simple case this could just be writing the relevant data to output files.

Previous | Top | Next

4 Examples

GeNN comes with a number of complete examples. At the moment, there are seven such example projects provided with GeNN.

4.1 Single compartment Izhikevich neuron(s)

This is a minimal example, with only one neuron population (with more or less neurons depending on the command line, but without any synapses). The neurons are Izhikevich neurons [1] with homogeneous parameters across the neuron population. The model can be used by navigating to the userproject/OneComp_project directory and entering a command line

```
./generate_run <CPU/GPU> <n> <OUTNAME> <MODEL> <DEBUG> <FTYPE> <REUSE>.
```

All parameters are mandatory and signify:

- CPU/GPU: Choose whether to run the simulation on CPU (0) or GPU (1).
- n: Number of neurons
- · OUTNAME: The base name of the output location and output files
- MODEL: The name of the model to execute, as provided this would be OneComp
- DEBUG: Whether to start in debug mode (1) or normally (0)
- FTYPE: Floating point type FLOAT or DOUBLE
- REUSE: whether to re-use input files

This would create n tonically spiking Izhikevich neuron(s) with no connectivity, receiving a constant, identical 4 nA input current.

For example, navigate to the userproject/OneComp_project directory and type

```
make all
./generate_run 1 1 Outdir OneComp_sim OneComp 0 FLOAT 0
```

to model a single neuron which output will be saved in the Outdir_output directory.

4.2 Izhikevich neurons driven by Poisson input spike trains:

In this example project there is again a pool of non-connected Izhikevich model neurons [1] that are connected to a pool of Poisson input neurons with a fixed probability.

The model can be compiled by navigating to the userproject \PoissonIzh_project directory and typing

```
make all
```

Subsequently it can be invoked using the following command line

```
./generate_run <CPU/GPU> <nPOISSON> <nIZHIKEVICH> <PCONN> <GSCALE> <OUTNAME> <MODEL> <DEBUG OFF/ON> < FTYPE> <REUSE>
```

All parameters are mandatory and signify:

- CPU/GPU: Choose whether to run the simulation on CPU (0) or GPU (1).
- \nPOISSON: Number of Poisson input neurons
- \nIZHIKEVICH: Number of Izhikevich neurons
- PCONN: Probability of connections
- OUTNAME: The base name of the output location and output files
- MODEL: The name of the model to execute, as provided this would be PoissonIzh
- DEBUG: Whether to start in debug mode (1) or normally (0)
- FTYPE: Floating point type FLOAT or DOUBLE
- · REUSE: whether to re-use input files

For example, navigate to the userproject/PoissonIzh_project directory and type

```
./generate run 1 100 10 0.5 2 Outdir PoissonIzh 0 DOUBLE 0
```

This will generate a network of 100 Poisson neurons connected to 10 Izhikevich neurons with a probability of 0.5. The same example network can be used with sparse connectivity (i.e. sparse matrix representations for the connectivity within GeNN) by using the keyword SPARSE in the addSynapsePopulation instead of DENSE in PoissonIzh.cc, uncommenting the lines following the comment //SPARSE CONNECTIVITY in the file Poisson ← Izh_sim.cu and commenting the lines following //DENSE CONNECTIVITY. In this example the model would be simulated with double precision variables and input files and connectivity would not be reused from earlier runs.

4.3 Pulse-coupled Izhikevich network

This example model is inspired by simple thalamo-cortical network of Izhikevich [1] with an excitatory and an inhibitory population of spiking neurons that are randomly connected.

The model can be built by navigating to the userproject/Izh_Sparse_project directory and typing

make all

It can then be used as

```
./generate_run <CPU/GPU> <nN> <nCONN> <GSCALE> <OUTNAME> <MODEL> <DEBUG OFF/ON> <FTYPE> <REUSE>
```

All parameters are mandatory and signify:

- CPU/GPU: Choose whether to run the simulation on CPU (0) or GPU (1).
- \nN: Number of neurons
- \nCONN: Number of connections per neuron
- · 'GSCALE': General scaling of synaptic conductances
- · OUTNAME: The base name of the output location and output files
- \bullet MODEL: The name of the model to execute, as provided this would be ${\tt Izh_sparse}$
- DEBUG: Whether to start in debug mode (1) or normally (0)
- FTYPE: Floating point type FLOAT or DOUBLE

REUSE: whether to re-use input files

The model creates a pulse-coupled network [1] with 80% excitatory 20% inhibitory neurons, each connecting to nCONN neurons using the sparse matrix connectivity methods of GeNN.

For example, typing

```
./generate_run 1 10000 1000 1 Outdir Izh_sparse 0 FLOAT 0
```

generates a random network of 8000 excitatory and 2000 inhibitory neurons which each have 1000 outgoing synapses to randomly chosen post-synaptic target neurons. The synapses are of a simple pulse-coupling type. The results of the simulation are saved in the directory Outdir_output, debugging is switched off, and the connectivity is generated afresh (rather than being read from existing files).

Note

If connectivity were to be read from files, the connectivity files would have to be in the inputfiles subdirectory and be named according to the names of the synapse populations involved, e.g., glzh_sparse _ee (<variable name>=g <model name>=lzh_sparse <synapse population>=_ee). These name conventions are not part of the core GeNN definitions and it is the privilege (or burden) of the user to find their own in their own versions of generate_run.

4.4 Izhikevich network with delayed synapses

This example project demonstrates the feature of synaptic delays in GeNN. It creates a network of three Izhikevich neuron groups, connected all-to-all with short, medium and long delay synapse groups. Synaptic weights are chosen such that neurons in the output group only spike if they are simultaneously excited by the input neurons, via synapses with long delay, and the interneurons, via synapses with shorter delay.

To run this example project, navigate to userproject/SynDelay_project and type, e.g.,

```
buildmodel SynDelay
make clean && make
./bin/release/syn_delay 1 output
```

4.5 Insect olfaction model

This project implements the insect olfaction model by Nowotny et al. [2] that demonstrates self-organized clustering of odours in a simulation of the insect antennal lobe and mushroom body. As provided the model works with conductance based Hodgkin-Huxley neurons [4] and several different synapse types, conductance based (but pulse-coupled) excitatory synapses, graded inhibitory synapses and synapses with a simplified STDP rule.

To explore the model navigate to userproject/MBody1_project/ and type

```
make all
./generate_run
```

This will show you the command line parameters that are needed,

```
generate_run <CPU/GPU> <nAL> <nKC> <nLHI> <nDN> <GSCALE> <OUTNAME> <MODEL> <DEBUG> <FTYPE> <REUSE>
```

All parameters are mandatory and signify:

- CPU/GPU: Choose whether to run the simulation on CPU (0) or GPU (1).
- nAL: Number of neurons in the antennal lobe (AL), the input neurons to this model
- nKC: Number of Kenyon cells (KC) in the "hidden layer"
- nLH: Number of lateral horn interneurons, implementing gain control
- nDN: Number of decision neurons (DN) in the output layer
- GSCALE: A general rescaling factor for snaptic strength
- · OUTNAME: The base name of the output location and output files
- MODEL: The name of the model to execute, as provided this would be MBody1
- DEBUG: Whether to start in debug mode (1) or normally (0)
- FTYPE: Floating point type FLOAT or DOUBLE
- · REUSE: whether to re-use input files

The tool generate_run will generate connectivity files for the model MBody1, compile this model for the CPU and GPU and execute it. The command line parameters are the numbers of neurons in the different neuropils of the model and an overall synaptic strength scaling factor. A typical call would be, e.g.,

```
./generate_run 1 100 1000 20 100 0.0025 test1 MBody1 0 FLOAT 0
```

which would generate a model, and run it on the GPU (first parameter), with 100 antennal lobe neurons, 1000 mushroom body Kenyon cells, 20 lateral horn interneurons and 100 mushroom body output neurons. All output files will be prefixed with test1 and stored in test1_output. The model that is run is defined in $model/\leftarrow MBody1.cc$, debugging is switched off, the model would be simulated using float (single precision floating point) variables and parameters and the connectivity and input would be generated afresh for this run.

As provided, the model outputs a file test1.out.st that contains the spiking activity observed in the simulation, There are two columns in this ASCII file, the first one containing the time of a spike and the second one the ID of the neuron that spiked. Users of matlab can use the scripts in the matlab directory to plot the results of a simulation. For more about the model itself and the scientific insights gained from it see [2].

4.6 Insect olfaction model with user-defined neuron and synapse models

This examples recapitulates the exact same model as Insect olfaction model above but with user-defined model types for neurons and synapses. It is run the same way as Insect olfaction model, e.g.

```
./generate_run 1 100 1000 20 100 0.0025 test1 MBody_userdef 0 FLOAT 0
```

But the way user-defined types are used should be very instructive to advanced users wishing to do the same with their models.

4.7 Insect Olfaction Model using INDIVIDUALID connectivity scheme

This example is very similar to the Insect olfaction model example. The only difference is that PN to KC connections are defined with the INDIVIDUALID mechanism.

It is run the same way as Insect olfaction model, e.g.

```
./generate_run 1 100 1000 20 100 0.0025 test1 MBody_individualID 0 FLOAT 0
```

4.8 Insect Olfaction Model using INDIVIDUALID connectivity scheme

A variation of the Insect olfaction model example using synaptic delays. In this example, the Kenyon Cell-Decision Neuron synapses are delayed by (5 * DT) ms, and the Decision Neuron-Decision Neuron synapses are delayed by (3 * DT) ms. The example is intended to test the operation of synapses which have a combination of delayed spike propagation and STDP (plasticity).

It is run the same way as Insect olfaction model, e.g.

```
./generate_run 1 100 1000 20 100 0.0025 test1 MBody_delayedSyn 0 FLOAT 0
```

4.9 Voltage clamp simulation to estimate Hodgkin-Huxley parameters

This example simulates a population of Hodgkin-Huxley neuron models on the GPU and evolves them with a simple guided random search (simple GA) to mimic the dynamics of a separate Hodgkin-Huxley neuron that is simulated on the CPU. The parameters of the CPU simulated "true cell" are drifting according to a user-chosen protocol : Either one of the parameters gNa, ENa, gKd, EKd, gleak, Eleak, Cmem are modified by a sinusoidal addition (voltage parameters) or factor (conductance or capacitance) - protocol 0-6. For protocol 7 all 7 parameters undergo a random walk concurrently.

The syntax of the generate_run program is

The parameters are

- GPU/CPU: Whether to use the GPU (1) or CPU (0) for the model neuron population
- protocol: Which changes to apply during the run to the parameters of the "true cell"
- nPop: Number of neurons in the tracking population
- totalT: Time in ms how long to run the simulation
- · outdir: The directory in which to save results
- debug mode: whether to start in debugging mode (1) or not (0) GPU choice: explicit choice of the GPU to be used.

An example invocation is:

```
./generate_run 1 2 5000 1000 test1 0 0
```

This will simulate nPop= 5000 Hodgkin-Huxley neurons on the GPU which will for 1000 ms be matched to a Hodgkin-Huxley neuron where the parameter gKd is sinusoidally modulated. The output files will be written into a directory of the name test1_output, which will be created if it does not yet exist.

```
Previous | Top | Next
```

5 Release Notes for GeNN v2.0

Version 2.0 of GeNN comes with a lot of improvements and added features, some of which have necessitated some changes to the structure of parameter arrays among others.

User Side Changes

- 1. Users are now required to call initGeNN () in the model definition function before adding any populations to the neuronal network model.
- 2. glbscnt is now call glbSpkCnt for consistency with glbSpkEvntCnt.
- 3. There is no longer a privileged parameter Epre. Spike type events are now defined by a code string spk \leftarrow EvntThreshold, the same way proper spikes are. The only difference is that Spike type events are specific to a synapse type rather than a neuron type.
- 4. The function setSynapseG has been deprecated. In a GLOBALG scenario, the variables of a synapse group are set to the initial values provided in the modeldefinition function.
- 5. Due to the split of synaptic models into weightUpdateModel and postSynModel, the parameter arrays used during model definition need to be carefully split as well so that each side gets the right parameters. For example, previously

"'C++ float myPNKC_p[3]= { 0.0, // 0 - Erev: Reversal potential -20.0, // 1 - Epre: Presynaptic threshold potential 1.0 // 2 - tau_S: decay time constant for S [ms] }; "would define the parameter array of three parameters, Erev, Epre, and tau_S for a synapse of typeNSYNAPS \leftarrow E. This now needs to be "split" into "C++ float *myPNKC_p= NULL; float postExpPNK \leftarrow C[2]={ 1.0, // 0 - tau_S: decay time constant for S [ms] 0.0 // 1 - Erev: Reversal potential }; "i.e. parameters Erev and tau_S are moved to the post-synaptic model and its parameter array of two parameters. Epreis discontinued as a parameter for NSYNAPSE. As a consequence the weightupdate model of NSYNAPSE has no parameters and one can pass NULL for the parameter array in addSynapse Population'.

The correct parameter lists for all defined neuron and synapse model types are listed in the User Manual.

Note:* If the parameters are not redefined appropriately this will lead to uncontrolled behaviour of models and likely to sgementation faults and crashes.

- 1. Advanced users can now define variables as type scalar when introducing new neuron or synapse types. This will at the code generation stage be translated to the model's floating point type (ftype), float or double. This works for defining variables as well as in all code snippets. Users can also use the expressions SCALAR_MAX and SCALAR_MIN for FLT_MIN, FLT_MAX, DBL_MIN and DBL_MAX, respectively. Corresponding definitions of scalar, SCALAR_MIN and SCALAR_MAX are also available for user-side code whenever the code-generated file runner.cc has been included.
- 2. The example projects have been re-organized so that wrapper scripts of the <code>generate_run</code> type are now all located together with the models they run instead of in a common <code>tools</code> directory. Generally the structure now is that each example project contains the wrapper script <code>generate_run</code> and a <code>model</code> subdirectory which contains the model description file and the user side code complete with Makefiles for Unix and Windows operating systems. The generated code will be deposited in the <code>model subdirectory</code> in its <code>own modelname_CODE</code> folder. Simulation results will always be deposited in a new sub-folder of the main project directory.
- 3. The addSynapsePopulation (...) function has now more mandatory parameters relating to the introduction of separate weightupdate models (pre-synaptic models) and postynaptic models. The correct syntax for the addSynapsePopulation (...) can be found with detailed explanations in teh User Manual.
- 4. We have introduced a simple performance profiling method that users can employ to get an overview over the differential use of time by different kernels. To enable the timers in GeNN generated code, one needs to declare "'C++ networkmodel.setTiming(TRUE); "This will make available and

operate GPU-side cudeEvent based timers whose cumulative value can be found in the double precision variables neuron_tme, synapse_tmeandlearning_tme. They measure the accumulated time that has been spent calculating the neuron kernel, synapse kernel and learning kernel, respectively. CP \leftarrow U-side timers for the simulation functions are also available and their cumulative values can be obtained through "C++ float x= sdkGetTimerValue(&neuron \leftarrow _timer); float y= sdkGetTimerValue(&synapse_timer); float z= sdkGetTimerValue(&learning_timer); "The Insect olfaction model example shows how these can be used in the user-side code. To enable timing profiling in this example, simply enable it for GeNN: "C++ model.setTiming(TRUE); "inMBody1.cc<tt>'smodel \leftarrow Definitionfunction and define the macroTIMINGinclassol_sim.h<tt> "C++ #define TIMING "This will have the effect that timing information is output intoOUTNA \leftarrow ME_output/OUTNAME.timingprofile'.

Developer Side Changes

- 1. allocateSparseArrays () has been changed to take the number of connections, connN, as an argument rather than expecting it to have been set in the Connetion struct before the function is called as was the arrangement previously.
- 2. For the case of sparse connectivity, there is now a reverse mapping implemented with revers index arrays and a remap array that points to the original positions of variable values in teh forward array. By this mechanism, revers lookups from post to pre synaptic indices are possible but value changes in the sparse array values do only need to be done once.
- 3. SpkEvnt code is no longer generated whenever it is not actually used. That is also true on a somewhat finer granularity where variable queues for synapse delays are only maintained if the corresponding variables are used in synaptic code. True spikes on the other hand are always detected in case the user is interested in them.

Previous | Top | Next

/*!

This release includes some new features and several bug fixes on GeNN v2.0.

User Side Changes

- 1. Block size debugging flag and the asGoodAsZero variables are moved into include/global.h.
- 2. NGRADSYNAPSES dynamics have changed (See Bug fix #4) and this change is applied to the example projects. If you are using this synapse model, you may want to consider changing model parameters.
- 3. The delay slots are now such that NO_DELAY is 0 delay slots (previously 1) and 1 means an actual delay of 1 time step.
- 4. The convenience function convertProbabilityToRandomNumberThreshold(float *, uint64_t *, int) was changed so that it actually converts firing probability/timestep into a threshold value for the GeNN random number generator (as its name always suggested). The previous functionality of converting a *rate* in kHz into a firing threshold number for the GeNN random number generator is now provided with the name convertRateToRandomNumberThreshold(float *, uint64 t *, int)
- 5. Every model definition function modelDefinition() now needs to end with calling NNmodel←::finalize() for the defined network model. This will lock down the model and prevent any further changes to it by the supported methods. It also triggers necessary analysis of the model structure that should only be performed once. If the finalize() function is not called, GeNN will issue an error and exit before code generation.

6 User Manual 15

6. To be more consistent in function naming the pull<SYNAPSENAME>FromDevice and push<S← YNAPSENAME>ToDevice have been renamed to pull<SYNAPSENAME>StateFromDevice and push<SYNAPSENAME>StateToDevice. The old versions are still supported through macro definitions to make the transition easier.

- 7. New convenience macros are now provided to access the current spike numbers and identities of neurons that spiked. These are called spikeCount_XX and spike_XX where "XX" is the name of the neuron group. They access the values for the current time step even if there are synaptic delays and spikes are stored in circular queues.
- 8. There is now a pre-defined neuron type "SPIKECOURCE" which is empty and can be used to define PyNN style spike source arrays.
- 9. The macros FLOAT and DOUBLE were replaced with GENN_FLOAT and GENN_DOUBLE due to name clashes with typedefs in Windows that define FLOAT and DOUBLE.

Developer Side Changes

1. We introduced a file definitions.h, which is generated and filled with useful macros such as spkQuePtrShift which tells users where in the circular spike queue their spikes start.

Improvements

- 1. Improved debugging information for block size optimisation and device choice.
- 2. Changed the device selection logic so that device occupancy has larger priority than device capability version.
- 3. A new HH model called TRAUBMILES_PSTEP where we can set the number of inner loops as a parameter is introduced. It uses the TRAUBMILES_SAFE method.
- 4. An alternative method is added for the insect olfaction model in order to fix the number of connections to a maximum of 10K in order to avoid negative conductance tails.
- 5. We introduced a #define for an "int" function that translates floating points to integers.

Bug fixes:

- 1. AtomicAdd replacement for old GPUs were used by mistake if the model runs in double precision.
- 2. Timing of individual kernels is fixed and improved.
- More careful setting of maximum number of connections in sparse connectivity, covering mixed dense/sparse network scenarios.
- 4. NGRADSYNAPSES was not scaling correctly with varying time step.
- 5. Fixed a bug where learning kernel with sparse connectivity was going out of array.
- 6. Fixed synapse kernel name substitutions where the "dd_" prefix was omitted by mistake.

Previous | Top | Next

6 User Manual

6.1 Contents

Introduction
Defining a network model
Neuron models
Synapse models

6.2 Introduction

GeNN is a software library for facilitating the simulation of neuronal network models on NVIDIA CUDA enabled GPU hardware. It was designed with computational neuroscience models in mind rather than artificial neural networks. The main philosophy of GeNN is two-fold:

- 1. GeNN relies heavily on code generation to make it very flexible and to allow adjusting simulation code to the model of interest and the GPU hardware that is detected at compile time.
- 2. GeNN is lightweight in that it provides code for running models of neuronal networks on GPU hardware but it leaves it to the user to write a final simulation engine. It so allows maximal flexibility to the user who can use any of the provided code but can fully choose, inspect, extend or otherwise modify the generated code. She can also introduce her own optimisations and in particular control the data flow from and to the GPU in any desired granularity.

This manual gives an overview of how to use GeNN for a novice user and tries to lead the user to more expert use later on. With this we jump right in.

Previous | Top | Next

6.3 Defining a network model

A network model is defined by the user by providing the function

```
void modelDefinition(NNmodel &model)
```

in a separate file with name name.cc, where name is the name of the model network under consideration. In this function, the following tasks must be completed:

1. The name of the model must be defined:

```
model.setName("MvModel");
```

- 2. Neuron populations (at least one) must be added (see <u>Defining neuron populations</u>). The user may add as many neuron populations as she wishes. If resources run out, there will not be a warning but GeNN will fail. However, before this breaking point is reached, GeNN will make all necessary efforts in terms of block size optimisation to accommodate the defined models. All populations must have a unique name.
- 3. Synapse populations (zero or more) can be added (see Defining synapse populations). Again, the number of synaptic connection populations is unlimited other than by resources.

Note

GeNN uses the convention where C/C++ files end in .cc. If this is not adhered to the build script buildmodel.sh will not recognise the model definition file.

6.3.1 Defining neuron populations

Neuron populations are added using the function

```
model.addNeuronPopulation(name, n, TYPE, para, ini);
```

where the arguments are:

- const char* name: Unique name of the neuron population
- int n: number of neurons in the population
- int TYPE: Type of the neurons, refers to either a standard type (see Neuron models) or user-defined type; this is an integer that indicates the position in the list of all neuron models where the model in question is stored.
- double *para: Parameters of this neuron type
- double *ini: Initial values for variables of this neuron type

The user may add as many neuron populations as the model necessitates. They must all have unique names. The possible values for the arguments, predefined models and their parameters and initial values are detailed Neuron models below.

6.3.2 Defining synapse populations

Synapse populations are added with the command

where the arguments are

- const char* name: The name of the synapse population
- int sType: The type of synapse to be added. See Built-in Models below for the available predefined synapse types.
- int sConn: The type of synaptic connectivity. the options currently are "ALLTOALL", "DENSE", "SPARSE" (see Connectivity types)
- int gType: The way how the synaptic conductivity g will be defined. Options are "INDIVIDUALG", "G
 LOBALG", "INDIVIDUALID". For their meaning, see LEARN1SYNAPSE (Learning Synapse with a Primitive Role) below.
- int delay: Synaptic delay (in multiples of the simulation time step DT).
- int postSyn: Postsynaptic integration method. See Postsynaptic integration methods for predefined types.
- char* preName: Name of the (existing!) pre-synaptic neuron population.
- char* postName: Name of the (existing!) post-synaptic neuron population.
- double *sIni: A C-array of doubles containing initial values for the (pre-) synaptic variables.
- double *sParam: A C-array of double precision that contains parameter values (common to all synapses
 of the population) which will be used for the defined synapses. The array must contain the right number of
 parameters in the right order for the chosen synapse type. If too few, segmentation faults will occur, if too
 many, excess will be ignored. For pre-defined synapse types the required parameters and their meaning are
 listed in NSYNAPSE (No Learning) below.

 double * psIni: A C-array of double precision numbers containing initial values for the post-synaptic model variables

 double * psPara: A C-array of double precision numbers containing parameters fo the post-snaptic model.

Note

If the synapse conductance definition type is "GLOBALG" then the global value of the synapse conductances is taken from the initial value provided in sINI. (The function setSynapseG() from earlier versions of GeNN has been deprecated).

Synaptic updates can occur per "true" spike (i.e at one point per spike, e.g. after a threshold was crossed) or for all "spike type events" (e.g. all points above a given threshold). This is defined within each given synapse type.

Previous | Top | Next

6.4 Neuron models

There is a number of predefined models which can be chosen in the addNeuronGroup(...) function by their unique cardinal number, starting from 0. For convenience, C variables with readable names are predefined

- 0: MAPNEURON
- 1: POISSONNEURON
- 2: TRAUBMILES_FAST
- 3: TRAUBMILES ALTERNATIVE
- 4: TRAUBMILES_SAFE
- 5: TRAUBMILES PSTEP
- 6: IZHIKEVICH
- 7: IZHIKEVICH V
- 8: SPIKESOURCE

Note

Ist is best practice to not depend on the unique cardinal numbers but use predefined names. While it is not intended that the numbers will change the unique names are guaranteed to work in all future versions of GeNN.

6.4.1 MAPNEURON (Map Neurons)

The MAPNEURON type is a map based neuron model based on [3] but in the 1-dimensional map form used in [2]:

$$V(t + \Delta t) = \begin{cases} V_{\text{spike}} \left(\frac{\alpha V_{\text{spike}}}{V_{\text{spike}} - V(t)\beta I_{\text{syn}}} + y \right) & V(t) \leq 0 \\ V_{\text{spike}} \left(\alpha + y \right) & V(t) \leq V_{\text{spike}} \left(\alpha + y \right) \& V(t - \Delta t) \leq 0 \\ -V_{\text{spike}} & \text{otherwise} \end{cases}$$

6.4 Neuron models 19

Note

The MAPNEURON type only works as intended for the single time step size of DT= 0.5.

The MAPNEURON type has 2 variables:

- V the membrane potential
- preV the membrane potential at the previous time step

and it has 4 parameters:

- Vspike determines the amplitude of spikes, typically -60mV
- alpha determines the shape of the iteration function, typically α = 3
- y "shift / excitation" parameter, also determines the iteration function, originally, y = -2.468
- beta roughly speaking equivalent to the input resistance, i.e. it regulates the scale of the input into the neuron, typically β = 2.64 $M\Omega$.

Note

The initial values array for the MAPNEURON type needs two entries for V and Vpre and the parameter array needs four entries for Vspike, alpha, y and beta, in that order.

6.4.2 POISSONNEURON (Poisson Neurons)

Poisson neurons have constant membrane potential (Vrest) unless they are activated randomly to the Vspike value if (t-SpikeTime) > trefract.

It has 3 variables:

- V Membrane potential
- Seed Seed for random number generation
- SpikeTime Time at which the neuron spiked for the last time

and 4 parameters:

- therate Firing rate
- trefract Refractory period
- Vspike Membrane potential at spike (mV)
- Vrest Membrane potential at rest (mV)

Note

The initial values array for the POISSONNEURON type needs three entries for V, Seed and SpikeTime and the parameter array needs four entries for therate, trefract, Vspike and Vrest, in that order. Internally, GeNN uses a linear approximation for the probability of firing a spike in a given time step of size DT, i.e. the probability of firing is therate times DT: $p=\lambda \Delta t$. This approximation is usually very good, especially for typical, quite small time steps and moderate firing rates. However, it is worth noting that the approximation becomes poor for very high firing rates and large time steps. An unrelated problem may occur with very low firing rates and small time steps. In that case it can occur that the firing probability is so small that the granularity of the 64 bit integer based random number generator begins to show. The effect manifests itself in that small changes in the firing rate do not seem to have an effect on the behaviour of the Poisson neurons because the numbers are so small that only if the random number is identical 0 a spike will be triggered.

6.4.3 TRAUBMILES_FAST (Hodgkin-Huxley neurons with Traub & Miles algorithm)

This conductance based model has been taken from [4] and can be described by the equations:

$$C \frac{dV}{dt} = -I_{\text{Na}} - I_K - I_{\text{leak}} - I_M - I_{i,DC} - I_{i,\text{syn}} - I_i,$$

$$I_{\text{Na}}(t) = g_{\text{Na}} m_i(t)^3 h_i(t) (V_i(t) - E_{\text{Na}})$$

$$I_{\text{K}}(t) = g_{\text{K}} n_i(t)^4 (V_i(t) - E_{\text{K}})$$

$$\frac{dy(t)}{dt} = \alpha_y(V(t)) (1 - y(t)) - \beta_y(V(t)) y(t),$$

where $y_i = m, h, n$, and

$$\alpha_n = 0.032(-50 - V)/(\exp((-50 - V)/5) - 1)$$

$$\beta_n = 0.5 \exp((-55 - V)/40)$$

$$\alpha_m = 0.32(-52 - V)/(\exp((-52 - V)/4) - 1)$$

$$\beta_m = 0.28(25 + V)/(\exp((25 + V)/5) - 1)$$

$$\alpha_h = 0.128 \exp((-48 - V)/18)$$

$$\beta_h = 4/(\exp((-25 - V)/5) + 1).$$

and typical parameters are C=0.143 nF, $g_{\rm leak}=0.02672~\mu$ S, $E_{\rm leak}=-63.563$ mV, $g_{\rm Na}=7.15~\mu$ S, $E_{\rm Na}=50$ mV, $g_{\rm K}=1.43~\mu$ S, $E_{\rm K}=-95$ mV.

It has 4 variables:

- V membrane potential E
- · m probability for Na channel activation m
- · h probability for not Na channel blocking h
- · n probability for K channel activation n

and 7 parameters:

- gNa Na conductance in 1/(mOhms * cm²)
- ENa Na equi potential in mV
- gK K conductance in 1/(mOhms * cm²)
- EK K equi potential in mV
- gl Leak conductance in 1/(mOhms * cm²)
- El Leak equi potential in mV
- Cmem Membrane capacity density in muF/cm 2

Note

Internally, the ordinary differential equations defining the model are integrated with a linear Euler algorithm and GeNN integrates 25 internal time steps for each neuron for each network time step. I.e., if the network is simulated at DT=0.1 ms, then the neurons are integrated with a linear Euler algorithm with 1DT=0.004 ms.

Other variants of the same model are TRAUBMILES_ALTERNATIVE, TRAUBMILES_SAFE and TRAUBMILES_ \leftarrow PSTEP. The former two are addressing the problem of singularities in the original Traub & Miles model [4]. At V= -52 mV, -25 mV, and -50 mV, the equations for α have denominators with value 0. Mathematically this is not a problem because the nominator is 0 as well and the left and right limits towards these singular points coincide. Numerically,

6.4 Neuron models 21

however this does lead to nan (not-a-number) results through division by 0. The TRAUBMILES_ALTERNATIVE model adds SCALAR_MIN to the denominators at all times which typically is completely effect-free because it is truncated from teh mantissa, except when the denominator is very close to 0, in which case it avoids the singular value.

TRAUBMILES_SAFE takes a much more direct approach in which at the singular points, the correct value calculated offline with l'Hopital's rule in substituted. This is implemented with "if" statements.

Finally, the TRAUBMILES_PSTEP model allows users to control the number of internal loops, or sub-timesteps, that are used. This is enabled by making the number of time steps an explicit parameter of the model.

6.4.4 IZHIKEVICH (Izhikevich neurons with fixed parameters)

This is the Izhikevich model with fixed parameters [1]. It is usually described as

$$\begin{array}{lcl} \frac{dV}{dt} & = & 0.04V^2 + 5V + 140 - U + I, \\ \frac{dU}{dt} & = & a(bV-U), \end{array}$$

I is an external input current and the voltage V is reset to parameter c and U incremented by parameter d, whenever V >= 30 mV. This is paired with a particular integration procedure of two 0.5 ms Euler time steps for the V equation followed by one 1 ms time step of the U equation. Because of its popularity we provide this model in this form here event though due to the details of the usual implementation it is strictly speaking inconsistent with the displayed equations.

Variables are:

- V Membrane potential
- U Membrane recovery variable

Parameters are:

- · a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

6.4.5 IZHIKEVICH_V (Izhikevich neurons with variable parameters)

This is the same model as IZHIKEVICH (Izhikevich neurons with fixed parameters) IZHIKEVICH but parameters are defined as "variables" in order to allow users to provide individual values for each individual neuron instead of fixed values for all neurons across the population.

Accordingly, the model has the Variables:

- $\ensuremath{\,\vee\,}$ Membrane potential
- U Membrane recovery variable
- a time scale of U
- b sensitivity of U
- c after-spike reset value of V
- d after-spike reset value of U

and no parameters.

6.4.6 SPIKESOURCE (empty neuron which allows setting spikes from external sources)

This model does not contain any update code and can be used to implement the equivalent of a SpikeGenerator
Group in Brian or a SpikeSourceArray in PyNN.

6.4.7 Defining your own neuron type

In order to define a new neuron type for use in a GeNN application, it is necessary to populate an object of class neuronModel and append it to the global vector nModels. This can be done conveniently within the model Oefinition Definition fundtion just before the model is needed. The neuronModel class has several data members that make up the full description of the neuron model:

simCode of type string: This needs to be assigned a C++ (stl) string that contains the code for executing
the integration of the model for one time step. Within this code string, variables need to be referred to by,
where NAME is the name of the variable as defined in the vector varNames. The code may refer to the
predefined primitives DT for the time step size and for the total incoming synaptic current. It can also refer to
a unique ID (within the population) using.

```
Example:
```

```
neuronModel model; model.simCode=String("$(V)+= (-$(a)$(V)+$(Isyn))*DT;"); would implement a leaky itegrator \frac{dV}{dt}=-aV+I_{\mathrm{syn}}.
```

varNames of type vector<string>: This vector needs to be filled with the names of variables that
make up the neuron state. The variables defined here as NAME can then be used in the syntax in the code
string.

Example:

```
model.varNames.push_back(String("V"));
```

would add the variable V as needed by the code string in the example above.

varTypes of type vector<string>: This vector needs to be filled with the variable type (e.g. "float",
"double", etc) for the variables defined in varNames. Types and variables are matched to each other by
position in the respective vectors, i.e. the 0th entry of varNames will have the type stored in the 0th entry of
varTypes and so on.

Example:

```
model.varTypes.push_back(String("float"));
```

would designate the variable V to be of type float.

Note

pNames of type vector<string>: This vector will contain the names of parameters relevant to the
model. If defined as NAME here, they can then be referenced as in the code string. The length of this vector
determines the expected number of parameters in the initialisation of the neuron model. Parameters are
assumed to be always of type double.

```
model.pNames.push_back(String("a"));
```

stores the parameter a needed in the code example above.

dpNames of type vector<string>: Names of "dependent parameters". Dependent parameters are a
mechanism for enhanced efficiency when running neuron models. If parameters with model-side meaning,
such as time constants or conductances always appear in a certain combination in the model, then it is more
efficient to pre-compute this combination and define it as a dependent parameter. This vector contains the
names of such dependent parameters.

thresholdConditionCode of type vector<string> (if applicable): Condition for true spike detection.

For example, if in the example above the original model had been $\frac{dV}{dt} = -g/C\,V + I_{\rm syn}$. Then one could define the code string and parameters as

```
model.simCode=String("$(V)+= (-$(a)$(V)+$(Isyn))*DT;");
model.varNames.push_back(String("V"));
model.varTypes.push_back(String("float"));
model.pNames.push_back(String("g"));
model.pNames.push_back(String("C"));
model.dpNames.push_back(String("C"));
```

dps of type dpclass*: The dependent parameter class, i.e. an implementation of dpclass which would return the value for dependent parameters when queried for them. E.g. in the example above it would return a when queried for dependent parameter 0 through dpclass::calculateDerivedParameter(). Examples how this is done can be found in the pre-defined classes, e.g. expDecayDp, pwSTDP, rulkovdp etc.

Once the completed neuronModel object is appended to the nModels vector,

```
nModels.push_back(model);
```

it can be used in network descriptions by referring to its cardinal number in the nModels vector. I.e., if the model is added as the 4th entry, it would be model "3" (counting starts at 0 in usual C convention). The information of the cardinal number of a new model can be obtained by referring to nModels.size() right before appending the new model, i.e. a typical use case would be.

```
int myModel= nModels.size();
nModels.push_back(model);
```

. Then one can use the model as

```
\verb|networkModel.addNeuronPopulation(..., myModel, ...);|\\
```

6.4.8 Explicit current input to neurons (will be removed in future versions)

The user can decide whether a neuron group receives external input current or not in addition to the synaptic input that it receives from the network. External input to a neuron group is activated by calling activateDirect Input function. It receives two arguments: The first argument is the name of the neuron group to receive input current. The second parameter defines the type of input. Current options are:

- 0: NOINP: Neuron group receives no input. This is the value by default when the explicit input is not activated.
- 1: CONSTINP: All the neurons receive a constant input value. This value may also be defined as a variable, i.e. be time-dependent.
- 2: MATINP: The input is read from a file containing the input matrix.
- 3: INPRULE: The input is defined as a rule. It differs from CONSTINP in the way that the input is injected: CONSTINP creates a value which is modified in real time, hence complex instructions are limited. INPRULE creates an input array which will be copied into the device memory.

6.5 Synapse models

A synapse model is a weightUpdateModel object which consists of variables, parameters, and string objects which will be substituted in the code. The three strings that will be substituted in the code for synapse update are:

• simCode: Simulation code that is used when a true spike is detected. The update is performed only once, one time step after threshold condition detection, which is defined by thresholdConditionCode in the neuron model of the corresponding presynaptic neuron population.

Typically, spikes lead to update of synaptic variables that then lead to the activation of input into the post-synaptic neuron. Most of the ime these inputs add linearly at the post-synaptic neuron. This is assumed in GeNN and the term to be added to the activation of the post-synaptic neuron should be provided as the value of the by the \$(addtoinsyn) snippet. For example

```
"\(addtoinsyn) = \(inc);"
```

where "inc" is a parameter of the weightupdate model, would define a constant increment of the synaptic input of a post-synaptic neuron for each pre-synaptic spike.

When a spike is detected in the presynaptic neuron population, the simCode is executed. Within the code snippet the \$(addtoinSyn) update just discussed should be be followed by the \$(updatelinsyn) keyword to indicate that the summation of synaptic inputs can now occur. This can then be followed by updates on the internal synapse variables that may have contributed to addtoinSyn. For an example, see NSYNAPSE (No Learning) for a simple synapse update model and LEARN1SYNAPSE (Learning Synapse with a Primitive Role) for a more complicated model that uses STDP.

- simCodeEvnt: Simulation code that is used for spike like events, where updates are done for all instances in which the event condition defined by evntThreshold is met. evntThreshold is also be provided as a code string. For an example, see NGRADSYNAPSE (Graded Synapse).
- simLearnPost: Simulation code which is used in the learnSynapsesPost kernel/function, which performs updates to synapses that are triggered by post-synaptic spikes. This is rather unusual other than in learning rules like e.g. STDP. For an example that uses simLearnPost, see LEARN1SYNAPSE (Learning Synapse with a Primitive Role).
- synapseDynamics: Simulation code that applies for every time step, i.e.is unlike the others not gated with a condition. This can be used where synapses have internal variables and dynamics that are described in continuous time, e.g. by ODEs. Usng this mechnanism is typically computationally veruy costly because of the large number of synapses in a typical network.

All code snippets can be used to manipulate any synapse variable and so implement both synaptic dynamics and learning processes.

6.5.1 Built-in Models

Currently 3 predefined synapse models are available:

- NSYNAPSE
- NGRADSYNAPSE
- LEARN1SYNAPSE

These are defined in lib.include/utils.h. The MBody_userdef example also includes a modified version of these models as user-defined models.

6.5.2 NSYNAPSE (No Learning)

If this model is selected, no learning rule is applied to the synapse and for each pre-synaptic spikes the synaptic conductances are simply added to the postsynaptic input variable. The model has 1 variable:

• g - conductance of scalar type

6.5 Synapse models 25

and no other parameters.

simCode is:

```
" $(addtoinSyn) = $(g);\n\
$(updatelinsyn);\n"
```

6.5.3 NGRADSYNAPSE (Graded Synapse)

In a graded synapse, the conductance is updated gradually with the rule:

$$gSyn = g * tanh((V - E_{pre})/V_{slope})$$

whenever the membrane potential V is larger than the threshold E_{pre} . The model has 1 variable:

• g: conductance of scalar type

The parameters are:

- Epre: Presynaptic threshold potential
- Vslope: Activation slope of graded release

simCodeEvnt is:

" \$(V_pre) > \$(Epre)"

```
" $ (addtoinSyn) = $ (g) * tanh(($(V_pre)-($(Epre)))*DT*2/$(Vslope));\n\
    $(updatelinsyn);\n"
evntThreshold is:
```

Note

The pre-synaptic variables are referenced with the suffix $_pre$ in synapse related code such as an $evnt \leftarrow Threshold$. Users can also access post-synaptic neuron variables using the suffix $_post$.

6.5.4 LEARN1SYNAPSE (Learning Synapse with a Primitive Role)

This is a simple STDP rule including a time delay for the finite transmission speed of the synapse, defined as a piecewise function.

The model has 2 variables:

- g: conductance of scalar type
- gRaw: raw conductance of scalar type

Parameters are:

- Epre: Presynaptic threshold potential
- ${\tt tLrn} \colon$ Time scale of learning changes
- tChng: Width of learning window
- tDecay: Time scale of synaptic strength decay
- tPunish10: Time window of suppression in response to 1/0

tPunish01: Time window of suppression in response to 0/1

• qMax: Maximal conductance achievable

• gMid: Midpoint of sigmoid g filter curve

• gSlope: Slope of sigmoid g filter curve

• tauShift: Shift of learning curve

gSyn0: Value of syn conductance g decays to

For more details about these built-in synapse models, see [2].

6.5.5 LEARN1SYNAPSE (Learning Synapse with a Primitive Role)

If users want to define their own models, they can add a new weightUpdateModel that includes the variables, parameters, and update codes as desired, and then push this object in the weightUpdateModels vector. The model can be used by referring to its index in the weightUpdateModels vector when adding a new population by with a call to addSynapsePopulation.

6.5.6 Conductance definition methods

The available options work as follows:

- INDIVIDUALG: When this option is chosen in the addSynapsePopulation command, GeNN reserves an array of size n_pre x n_post float for individual conductance values for each combination of pre and postsynaptic neuron. The actual values of the conductances are passed at runtime from the user side code, using the pushXXXXXToDevice function, where XXXX is the name of the synapse population.
- GLOBALG: When this option is chosen, the value of the variables of the synapse model (including its conductance) is taken to be the initial value provided for the synapse model's variables. This option can only be sensibly combined with connectivity type ALLTOALL.
- INDIVIDUALID: When this option is chosen, GeNN expects to use the same maximal conductance for all existing synaptic connections but which synapses exist will be defined at runtime from the user side code, provided as a binary array (see Insect olfaction model).

6.5.7 Connectivity types

If INDIVIDUALG is used with ALLTOALL or DENSE connectivity (these are equivalent in this case), synapse variables are stored in an array of size npre * npost .

If the connectivity is of SPARSE type, connectivity indices are stored in a struct named SparseProjection in order to minimize the memory equirements. The struct SparseProjection contains the following members: 1: unsigned int connN: number of connections in the population. This value is needed for allocation of arrays. The indices that correspond to these values are defined in a pre-to-post basis by the following arrays: 2: unsigned int ind, of size connN: Indices of corresponding postsynaptic neurons concatenated for each presynaptic neuron. 3: unsigned int *indlnG, of size model.neuronN[model.synapseSource[synInd]]+1: This array defines from which index in the synapse variable array the indices in ind would correspond to the presynaptic neuron that corresponds to the index of the indlnG array, with the number of connections being the size of ind. More specifically, indlng[n+1]-indlng[n] would give the number of postsynaptic connections for neuron n.

For example, consider a network of two presynaptic neurons connected to three postsynaptic neurons: 0th presynaptic neuron connected to 1st and 2nd postsynaptic neurons, the 1st presynaptic neuron connected to 0th and 2nd neurons. The struct SparseProjection should have these members, with indexing from 0:

```
ConnN = 4
ind= [1 2 0 2]
indIng= [0 2 4]
```

7 Tutorial 1 27

A synapse variable of a sparsely connected synapse will be kept in an array using this conductance for indexing. For example, a variable called g will be kept in an array such as: $g = [g_pre0-post1 g_pre0-post2 g_pre1-post0 g_pre1-post2]$ If there are no connections for a presynaptic neuron, then g[indlng[n]]=g[indlng[n]+1].

See tools/gen_syns_sparse_lzhModel used in lzh_sparse project to see a working example.

6.5.8 Postsynaptic integration methods

The postSynModel defines how synaptic activation translates into an input current (or other input term for models that are not current based). It also can contain equations defining dynamics that are applied to the (summed) synaptic activation, e.g. an exponential decay over time.

A postSynModel object consists of variables, parameters, derived parameters and two strings that define the code for current generation and continuous dynamics.

- string postSynDecay: This code defines the continuous time dynamics of the summed presynaptic inputs at the postsynaptic neuron. This usually consists of some kind of decay function.
- string postSyntoCurrent: This code defines how the synaptic inputs lead to an input input current (lsyn) to the postsynaptic neuron.

There are currently 2 built-in postsynaptic integration methods:

EXPDECAY: Exponential decay. Decay time constant and reversal potential parameters are needed for this post-synaptic mechanism.

This model has no variables and two parameters:

- tau: Decay time constant
- E : Reversal potential

tau is used by the derived parameter expdecay which returns expf(-dt/tau).

IZHIKEVICH PS: Empty postsynaptic rule to be used with Izhikevich neurons.

Previous | Top | Next

7 Tutorial 1

In this tutorial we will go through step by step instructions how to create and run a GeNN simulation starting from scratch. Normally, we recommend users to use one of the example projects as a starting point but it can be very instructive to go through the necessary steps one by one once to appreciate what parts make a GeNN simulation.

7.1 The Model Definition

In this tutorial we will use a pre-defined neuron model type (TRAUBMILES) and create a simulation of ten Hodgkin-Huxley neurons [4] without any synaptic connections. We will run this simulation on a GPU and save the results to stdout.

The first step is to write a model definition function in a model definition file. Create a new empty file $tenHH \leftarrow Model.cc$ with your favourite editor, e.g.

>> emacs tenHHModel.cc &

Note

The ">>" in the example code snippets refers to a shell prompt in a unix shell, do not enter them as part of your shell commands.

The model definition file contains the definition of the network model we want to simulate. First, we need to define the simulation step size DT and include the GeNN model specification codes modelSpec.h and modelSpec.cc<tt>. Then the model definition takes the form of a function namedmodelDefinitionthat takes one argument, passed by reference, of typeNNmodel. Type in yourtenHHModel.cc' file:

```
// Model definintion file tenHHModel.cc
#define DT 0.1
#include "modelSpec.h"
#include "modelSpec.cc"

void modelDefinition(NNmodel &model)
{
    // definition of tenHHModel
}
```

With this we have fixed the integration time step to 0.1 in the usual time units. The typical units in GeNN are ms, mV, nF, and \form#10S. Therefore, this defines DT= 0.1 ms. Now we need to fill the actual model definition.

Two standard elements to the 'modelDefinition function are initialising GeNN and setting the name of the model:

```
initGeNN();
model.setName("tenHHModel");
```

Note

The name of the model given in the setName method does not need to match the file name of the model definition file. However, we strongly recommend it and if conflicting, the file name of the model definition file will prevail.

Making the actual model definition makes use of the addNeuronPopulation and 'addSynapse \leftarrow Populationmember functions of the NNmodel object. The arguments to a call toaddNeuronPopulations are

- string name: the name of the population
- \bullet int $\,$ N: The number of neurons in the population
- int type: The type of neurons in the population
- double *p: An array of parameter values for teh neurons in the population
- double *ini: An array of initial values for neuron variables

We first create the parameter and initial variable arrays,

```
// definition of tenHHModel
double p[7] = {
  7.15,
                   // 0 - gNa: Na conductance in muS
                   // 1 - ENa: Na equi potential in mV \,
  50.0.
  1.43,
                  // 2 - gK: K conductance in muS
                  // 3 - EK: K equi potential in mV
  0.02672,
                  // 4 - gl: leak conductance in muS
                  // 5 - El: leak equi potential in mV
// 6 - Cmem: membr. capacity density in nF
  -63.563,
  0.143
double ini[4]= {
                // 0 - membrane potential V
  -60.0,
  0.0529324,
                  // 1 - prob. for Na channel activation m
                  // 2 - prob. for not Na channel blocking h
  0.3176767,
                   ^{\prime\prime} // 3 - prob. for K channel activation n
  0.5961207
```

7.2 User Code 29

Note

The comments are obviously only for clarity, they can in principle be omitted. To avoid any confusion about the meaning of parameters and variables, however, we recommend strongly to always include comments of this type.

Having defined the parameter values and initial values we can now create the neuron population,

```
model.addNeuronPopulation("Pop1", 10, TRAUBMILES, p, ini);
```

Note

TRAUBMILES is a variable defined in the GeNN model specification that contains the index number of the pre-defined Traub & Miles model [4].

The model definition then needs to end on calling

```
model.finalize();
```

This completes the model definition in this example. The complete tenHHModel.cc file now should look like this:

```
// Model definintion file tenHHModel.cc
#define DT 0.1
#include "modelSpec.h"
#include "modelSpec.cc"
void modelDefinition(NNmodel &model)
  // definition of tenHHModel
  initGeNN();
  model.setName("tenHHModel");
  double p[7] = {
                    // 0 - gNa: Na conductance in muS // 1 - ENa: Na equi potential in mV \,
    7.15,
    50.0.
                    // 2 - gK: K conductance in muS \,
    1.43,
                   // 3 - EK: K equi potential in mV
   -95.0,
    0.02672,
                   // 4 - gl: leak conductance in muS
    -63.563,
                   // 5 - El: leak equi potential in mV
                    // 6 - Cmem: membr. capacity density in nF
    0.143
  };
  double ini[4]= {
                   // 0 - membrane potential V
    -60.0,
    0.0529324,
                   // 1 - prob. for Na channel activation m
    0.3176767,
                   // 2 - prob. for not Na channel blocking h
                   // 3 - prob. for K channel activation n
    0.5961207
  };
 model.addNeuronPopulation("Pop1", 10, TRAUBMILES, p, ini);
 model.finalize();
```

This model definition suffices to generate code for simulating the ten Hodgkin-Huxley neurons on the a GPU or CPU. The second part of a GeNN simulation is the user code that sets up the simulation, does the data handling for input and output and generally defines the numerical experiment to be run.

7.2 User Code

For the purposes of this tutorial we will initially simply run the model for one simulated second and record the final neuron variables into a file. GeNN provides the code for simulating the model in a function called $stepTimeC \leftarrow PU()$ (execution on CPU only) or stepTimeGPU() (execution on a GPU). To make use of this code we need to define a minimal C/C++ main function. Open a new empty file tenHHSimulation.cc in an editor and type

```
// tenHHModel simulation code
#include "tenHHModel.cc"
#include "tenHHModel_CODE/runner.cc"
```

```
int main()
{
  allocateMem();
  initialize();
  return 0;
```

This boiler plate code includes the relevant model definition file we completed earlier and the entry point to the generated code runner.cc in the subdirectory tenHHModel CODE where GeNN deposits all generated code.

Calling allocateMem() allocates the memory structures for all neuron variables and initialize() sets the initial values and copies values to the GPU.

Now we can use the generated code to execute the integration of the neuron equations provided by GeNN. To do so, we add after initialize();

```
stepTimeGPU(1000.0);
```

and we need to copy the result, and output it to stdout,

```
pullPop1fromDevice();
for (int i= 0; i < 10; i++) {
   cout << VPop1[i] << " ";
   cout << mPop1[i] << " ";
   cout << hPop1[i] << " ";
   cout << nPop1[i] << endl;
}</pre>
```

pullPop1fromDevice() copies all relevant state variables of the Pop1 neuron group from the GPU to the CPU main memory. Then we can output the results to stdout by looping through all 10 neurons and outputting the state variables VPop1, mPop1, hPop1, nPop1.

Note

The naming convention for variables in GeNN is the variable name defined by the neuron type, here TRAU← BMILES defining V, m, h, and n, followed by the population name, here Pop1.

This completes the user code. The complete tenHHSimulation.cu file shoul now look like

```
// tenHHModel simulation code
#include "tenHHModel.cc"
#include "tenHHModel_CODE/runner.cc"
int main()
{
   allocateMem();
   initialize();
   stepTimeGPU(1000.0);
   pullPoplfromDevice();
   for (int i= 0; i < 10; i++) {
      cout << VPopl[i] << " ";
      cout << MPopl[i] << " ";
      cout << hPopl[i] << " ";
      cout << nPopl[i] << " ";
      cout << nPopl[i] << moderate of the cout;
}
return 0;
}</pre>
```

7.3 Makefile

A GeNN simulation is built with a simple Makefile. On Unix systems we typically name it GNUmakefile. Create this file and enter

```
EXECUTABLE :=tenHHSimulation

SOURCES :=tenHHSimulation.cu

include $(GENN_PATH)/userproject/include/makefile_common_gnu.mk
```

This defines that the final executable of this simulation is named tenHHSimulation and the simulation code is given in the file tenHHSimulation.cu that we completed above.

Now we are ready to compile and run the simulation

7.4 Making and Running the Simulation

To build the model and generate the GeNN code, type in a terminal where you are in the directory containing your tenHHModel.cc file,

```
>> buildmodel.sh tenHHModel
```

If your environment variables GENN_PATH and CUDA_PATH are correctly configured, you should see some compile output ending in Model build complete Now type

make

This should compile your tenHHSimulation executable and you can execute it with

```
./tenHHSimulation
```

The output you obtain should look like

```
-63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243 -63.7838 0.0350042 0.336314 0.563243
```

This completes this tutorial. You have created a GeNN model and simulated it successfully!

7.5 Adding External Input

In the example we have created so far, the neurons are not connected and do not receive input. As the TRAUB MILES model is silent in such conditions, the ten neurons simply will simply rest at their resting potential. To make things more interesting, let us add a constant input to all neurons, add to the end of the modelDefinition function

```
model.activateDirectInput("Pop1", CONSTINP);
model.setConstInp("Pop1", 0.1);
```

This will add a constant input of 0.1 nA to all ten neurons. When run with this addition you should observe the output

```
-63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695 -63.1468 0.0211871 0.987233 0.0423695
```

This is still not particularly interesting as we are just observing the final value of the membrane potentials. To see what is going on in the meantime, we need to copy intermediate values from the device and best save them into a file. This can be done in many ways but one sensible way of doing this is to replace the line

```
stepTimeGPU(1000.0);
```


in tenHHSimulation.cu to something like this:

```
ofstream os("tenHH_output.V.dat");
double t= 0.0;
for (int i= 0; i < 5000; i++) {
    stepTimeGPU(0.2);
    pullPoplfromDevice();
    os << t << " ";
    for (int j= 0; j < 10; j++) {
        os << VPopl[j] << " ";
    }
    os << endl;
    t+= 0.2;
}
os.close();</pre>
```

After building, making and executing,

```
builmodel.sh tenHHModel
make clean all
./tenHHSimulation
```

there should be a file $tenHH_output.V.dat$ in the same directory. If you plot column one (time) against column two (voltage of neuron 0), you should observe dynamics like this:



The completed files from this tutorial can be found in userproject/tenHH_project.

8 Tutorial 2

In this tutorial we will learn to add synapsePopulations to connect neurons in neuron groups to each other with synatic models. As an example we will connect the ten Hodgkin-Huxley neurons from tutorial 1 in a ring of excitatory synapses.

First, copy the files from Tutorial 1 into a new directory and rename them to new names, e.g.

```
>> cp -r tenHH_project tenHHRing_project
>> cd tenHHRing_project
>> mv tenHHModel.cc tenHHRingModel.cc
>> mv tenHHSimulation.cu tenHHRingSimulation.cu
```

Now, we need to add a synapse group to the model that allows to connect neurons from the Pop1 group to connect to other neurons of this group. Open tenHHRingModel.cc, change the model name inside,

```
model.setName("tenHHRing");
```

8.1 Adding Synaptic connections

Now we need additional initial values and parameters for the synapse and post-synaptic models. We will use the standard NSYNAPSE weightupdate model and EXPDECAY post-synaptic model. They need intial variables and parameters as follows:

If an array is not needed we set it to the NULL pointer. Here there are for example no synaptic parameters and no initial values for the post-synaptic mechanism. We can then add a synapse population at the end of the model \leftarrow Definition(...) function,

The addSynapsePopulation parameters are

- const char *name: The name of the synapse population, here "Pop1self"
- int sType: The type of synapse to be added, we here use the predefined typse NSYNAPSE. See Built-in Models for all available predefined synapse types.
- int sConn: The type of synaptic connectivity, here DENSE which means we will provide a full connectivity
 mtrix later.
- int gType: The way how the synaptic conductivity g will be defined. With GLOBALG we indicate that all conductance are of the same conductance value, which will be the value given in sPara.
- int delay: NO_DELAY means that there will be no delays for synaptic signal propagation.
- int postSyn: Postsynaptic integration method, we are here using the standard model of an exponential decay of synaptic excitation.
- char *preName: Name of the pre-synaptic neuron population, here the Pop1 population.
- char *postName: Name of the post-synaptic neuron population, here also Pop1.
- double *sIni: A C-array of doubles containing initial values for the synaptic variables.
- double *sParam: A C-array of double precision that contains parameter values (common to all synapses
 of the population)
- double *psIni: A C-array of double precision numbers containing initial values for the post-synaptic model variables
- double *psPara: A C-array of double precision numbers containing parameters fo the post-snaptic model.

Adding the addSynapsePopulation command to the model definition informs GeNN that there will be synapses between the named neuron populations, here between population Pop1 and itself. The detailed connectivity as defined by the variables g, we have still to define in the setup of our simulation. As always, the modelDefinition function ends on

```
model.finalize();
```

At this point our model definition file tenHHRingModel.cc should look like this

```
// Model definintion file tenHHModel.cc
#define DT 0.1
#include "modelSpec.h"
#include "modelSpec.cc"
void modelDefinition(NNmodel &model)
  // definition of tenHHModel
  initGeNN();
  model.setName("tenHHRingModel");
  double p[7] = {
                      // 0 - gNa: Na conductance in muS
    7.15,
                     // 1 - ENa: Na equi potential in mV
    1.43,
                     // 2 - gK: K conductance in muS
                   // 3 - EK: K equi potential in mV
// 4 - gl: leak conductance in muS
   -95.0,
    0.02672.
                     // 5 - El: leak equi potential in mV
    -63.563,
                     // 6 - Cmem: membr. capacity density in nF
    0.143
  double ini[4]= {
                   // 0 - membrane potential V
// 1 - prob. for Na channel activation m
// 2 - prob. for not Na channel blocking h
    -60.0,
0.0529324,
    0.3176767,
                    // 3 - prob. for K channel activation n
    0.5961207
  model.addNeuronPopulation("Pop1", 10, TRAUBMILES, p, ini);
model.activateDirectInput("Pop1", CONSTINP);
model.setConstInp("Pop1", 0.1);
  double s_ini[1] = {
    0.0
               // 0 - g: the synaptic conductance value
  double *s_p= NULL;
  double *ps_ini= NULL;
  // 1 - Erev: Reversal potential
  model.addSynapsePopulation("Pop1self", NSYNAPSE,
      DENSE, INDIVIDUALG, NO_DELAY, EXPDECAY, "Pop1", "Pop1", s_ini, s_p, ps_ini,
       ps_p);
  model.finalize();
```

8.2 Defining the Detailed Synaptic Connections

Open the tenHHRingSimulation.cu file and update the file names of includes:

```
// tenHHRingModel simulation code
#include "tenHHRingModel.cc"
#include "tenHHRingModel_CODE/runner.cc"
```

Now we need to add code to generate the desired ring connectivity.

```
allocateMem();
initialize();
// define the connectivity
int pre, post;
for (int i= 0; i < 10; i++) {
   pre= i;
   post= (i+1)%10;
   gPoplself[pre*10+post]= 0.01;
}
pushPoplselftoDevice();</pre>
```

After memory allocation and initialization gPop1self will contain only zeros. We then assign in the loop a non-zero conductivity of 0.01 μ S to all synapses from neuron i to i+1 (and 9 to 0 to close the ring).

After adjusting the GNUmakefile to read

```
EXECUTABLE :=tenHHRingSimulation
SOURCES :=tenHHRingSimulation.cu
include $(GENN_PATH)/userproject/include/makefile_common_gnu.mk
```

we can build the model

```
>> buildmodel.sh tenHHRingModel
```

and make it

```
>> make clean all
```

After this there should be an exectable tenHHRingSimulation, which can be executed,

```
>> ./tenHHRingSimulation
```

which should again result in

```
-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886


-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886

-64.9054 0.0147837 0.981337 0.030886
```

If we plot the content of columns one and two of tenHHexample.V.dat it looks very similar as in Tutorial 1



This is because the inhibitory synapses we created were all triggered at the same time so that they act during a post-synaptic spike which makes their effect all but invisible.

8.3 Setting Heterogeneous Initial Conditions

If we define different initial conditions for each of the ten neurons, i.e. add after initialize(),

```
// set initial variables
for (int i= 0; i < 10; i++) {
   VPopl[i] = -60.0+i;
}
pushPopltoDevice();</pre>
```

then we observe different final values for each neuron,

```
-57.3412 0.06223 0.981374 0.104417

-53.3189 0.442962 0.0664687 0.764513

-73.1413 0.00253709 0.927251 0.0277236

-67.1179 0.00927304 0.986692 0.0206106

-63.5878 0.01938 0.991071 0.0387962

-62.2114 0.0255295 0.990933 0.0504799


-61.404 0.0298902 0.990949 0.0586459

-60.6691 0.034405 0.990225 0.0668015

-59.8977 0.0397467 0.988701 0.0758159

-58.9727 0.0470178 0.98615 0.0866963
```

and zooming in on the first 200 ms, the voltage of the first neuron now looks like this



The complete codes for this tutorial are in userproject\tenHHRing_project.

9 Suggestions for users

GeNN generates code according to the network model defined by the user, but lets users use generated code the way they want. Here we explain in some more detail how to setup GeNN and how to use generated functions. We recommend users to also have a look at the Examples, and to follow the tutorials Tutorial 1 and Tutorial 2.

9.1 Creating and simulating a network model

The user is first expected to create an object of class NNmodel by creating the function modelDefinition() which includes calls to following methods in correct order:

- initGeNN();
- NNmodel::setName();

Then add neuron populations by:

NNmodel::addNeuronPopulation();

for each neuron population. Add synapse populations by:

NNmodel::addSynapsePopulation();

for each synapse population.

The modelDefinition() needs to end with calling NNmodel::finalize().

Other optional functions are explained in NNmodel class reference. At the end the function should look like this:

```
void modelDefinition(NNModel &model) {
  initGeNN();
  model.setName("YourModelName");
  model.addNeuronPopulation(...);
  ...
  model.addSynapsePopulation(...);
  ...
  model.finalize();
}
```

modelSpec.h and modelSpec.cc should be included in the file where this function is defined.

This function will be called by generateALL.cc to create corresponding CPU and GPU simulation codes under the <YourModelName>_CODE directory.

These functions can then be used in a .cu file which runs the simulation. This file should include <YourModel ← Name>_CODE/runner.cc. Generated code differ from one model to the other, but core functions are the same and they should be called in correct order. First, the following variables should be defined and initialized:

- NNmodel model // initialized by calling modelDefinition(model)
- · Array containing current input (if any)

The following are declared by GeNN but should be initialized by the user:

- · Poisson neuron offset and rates (if any)
- · Connectivity matrices (if sparse)
- Neuron and synapse variables (if not initialising to the homogeneous initial value provided during model
 — Definition)

Core functions generated by GeNN to be included in the user code include:

- · allocateMem()
- deviceMemAllocate()
- · initialize()
- initializeAllSparseArrays()
- convertProbabilityToRandomNumberThreshold()
- $\bullet \ convertRateToRandomNumberThreshold()\\$
- copyStateToDevice()
- push<neuron or synapse name>StatetoDevice()
- pull<neuron or synapse name>StatefromDevice()
- · copyStateFromDevice()
- · copySpikeNFromDevice()
- · copySpikesFromDevice()
- stepTimeCPU() //arguments depend on model
- stepTimeGPU() //arguments depend on model

- · freeMem()
- · freeDeviceMem()

Copying elements from GPU to host memory is very costly in terms of performance and should only be done when needed.

9.2 Floating point precision

Double precision floating point numbers are supported by devices with compute capability 1.3 or higher. If you have an older GPU, you need to use single precision floating point in your models and simulation.

GPUs are designed to work better with single precision while double precision is the standard for CPUs. This difference should be kept in mind while comparing performance.

While setting up the network for GeNN, double precision floating point numbers are used as this part is done on the CPU. For the simulation, GeNN lets users choose between single or double precision. Overall, new variables in the generated code are defined with the precision specified by NNmodel::setPrecision(unsigned int), providing GENN_FLOAT or GENN_DOUBLE as argument. GENN_FLOAT is the default value. The keyword scalar can be used in the user-defined model codes for a variable that could either be single or double precision. This keyword is detected at code generation and substituted with "float" or "double" according to the precision set by NNmodel ::setPrecision(unsigned int).

There may be ambiguities in arithmetic operations using explicit numbers. Standard C compilers presume that any number defined as "X" is an integer and any number defined as "X.Y" is a double. Make sure to use the same precision in your operations in order to avoid performance loss.

9.3 Working with variables in GeNN

9.3.1 Model variables

User-defined model variables originate from core units such as neuronModel, weightUpdateModel or postSynModel objects. The name of a variable is defined when the model type is introduced, i.e. with a statement such as

```
neuronModel model;
model.varNames.push_back(String"x"));
model.varTypes.push_back(String("double"));
...
int myModel= nModels.size();
nModels.push_back(model);
```

This declares that whenever the defined model type of cardinal number myModel is used, there will be a variable of core name x. varType can be of scalar type (see Floating point precision). The full GeNN name of this variable is obtained by directly concatenating the core name with the name of the neuron population in which the model type has been used, i.e. after a definition

```
networkModel.addNeuronPopulation("EN", n, myModel, ...);
```

there will be a variable $x \in N$ of type double* available in the global namespace of the simulation program. GeNN will pre-allocate this C array to the correct size of elements corresponding to the size of the neuron population, n in the example above. GeNN will also free these variables when the provided function freeMem() is called. Users can otherwise manipulate these variable arrays as they wish. For convenience, GeNN provides functions pullxxstatefromDevice() and pushxxstatefoDevice() to copy the variables associated to a neuron population XX from the device into host memory and vice versa. E.g.

```
pullENStatefromDevice();
```

would copy the C array xEN from device memory into host memory (and any other variables that the neuron type of the population EN may have).

The user can also directly use CUDA memory copy commands independent of the provided convenience functions. The relevant device pointers for all variables that exist in host memory have the same name as the host variable but are prefixed with d_{-} . For example, the copy command that would be contained in $pullenstatefrom \rightarrow Device()$ will look like

```
unsigned int size;
size = sizeof(double) * nEN;
cudaMemcpy(xEN, d_xEN, size, cudaMemcpyDeviceToHost);
```

where nEN is an integer containing the population size of the EN neuron population.

The same convention as for neuron variables applies for the variables of synapse populations, both for those originating from weightupdate models and from post-synaptic models, e.g. the variables in type ${\tt NSYNAPSE}$ contain the variable ${\tt q}$ of type float. Then, after

```
\verb|networkModel.addSynapsePopulation("ENIN", NSYNAPSE, ...);|\\
```

there will be a global variable of type float* with the name gENIN that is pre-allocated to the right size. There will also be a matching device pointer with the name d_gENIN.

Note

The content of <code>genin</code> needs to be interpreted differently for DENSE connectivity and sparse matrix based SPARSE connectivity representations. For DENSE connectivity <code>genin</code> would contain "n_pre" times "n_post" elements, ordered along the pre-synaptic neurons as the major dimension, i.e. the value of <code>genin</code> for the ith pre-synaptic neuron and the jth post-synaptic neuron would be <code>genin</code> [$i*n_post+j$]. The arrangement of values in the SPARSE representation is explained in section Connectivity types

Be aware that the above naming conventions do assume that variables from the weightupdate models and the postSynModels that are used together in a synapse population are unique. If both the weightupdate model and the postSynModel have a variable of the same name, the behaviour is undefined.

9.3.2 Built-in Variables in GeNN

Since GeNN 2.0, there are no more explicitly hard-coded synapse and neuron variables. Users are free to name the variable of their models as they want. However, there are some reserved variables that are used for intermediary calculations and communication between different parts of the generated code. They can be used in the user defined code but no other variables should be defined with these names.

- DT: Time step (typically in ms) for simulation; Neuron integration can be done in multiple sub-steps inside
 the neuron model for numerical stability (see Traub-Miles and Izhikevich neuron model variations in Neuron
 models).
- addtoinSyn: This variable is used by weightUpdateModel for updating synaptic input. The way it is
 modified is defined in weightUpdateModel.simCode or weightUpdateModel.simCodeEvnt, therefore if a user
 defines her own model she should update this variable to contain the input to the post-synaptic model.
- updatelinsyn: At the end of the synaptic update by addtoinSyn, final values are copied back to the
 d_inSyn<synapsePopulation> variables which will be used in the next step of the neuron update to provide
 the input to the postsynaptic neurons. This keyword designated where the changes to addtoinSyn have
 been completed and it is safe to update the summed synaptic input and write back to d_inSyn<synapse
 Population> in device memory.
- inSyn: This is an intermediary synapse variable which contains the summed input into a postsynaptic neuron (originating from the addtoinSyn variables of the incoming synapses).
- Isyn: This is a local variable which contains the (summed) input current to a neuron. It is typically the sum of any explicit current input and all synaptic inputs. The way its value is calculated during the update of the postsynaptic neuron is defined by the code provided in the postSynModel. For example, the standard EXP \leftarrow DECAY postsynaptic model defines ps.postSyntoCurrent= String("\$(inSyn)*(\$(E)-\$(V))"); which implements a conductance based synapse in which the postsynaptic current is given by $I_{\rm syn} = g * s * (V_{\rm rev} V_{\rm post})$.

Note

The addtoinSyn variables from all incoming synapses are automatically summed and added to the current value of inSyn.

The value resulting from the postSyntoCurrent code is assigned to Isyn and can then be used in neuron simCode like so:

```
(V) += (-(V) + (Isyn)) *DT
```

• sT: As a neuron variable, this is the last spike time in a neuron and is automatically generated for pre and postsynaptic neuron groups of a synapse group i that follows a spike based learning rule (indicated by usesPostLearning[i]= TRUE for the ith synapse population).

In addition to these variables, neuron variables can be referred to in the synapse models by calling \$(<neuron \cup VarName>_pre) for the presynaptic neuron population, and \$(<neuronVarName>_post) for the postsynaptic population. For example, \$(sT pre), \$(sT post), \$(V pre), etc.

9.4 Debugging suggestions

In Linux, users can use cuda-gdb to debug on the GPU. Example projects in userproject and lib/bin/buildmodel.sh come with a flag to enable debugging. If you are using a project with debugging, the code will be compiled with -g -G flags. In CPU mode the executable will be run in gdb, and in GPU mode it will be run in cuda-gdb in tui mode.

Note

Do not forget to switch debugging flags -g and -G off after debugging is complete as they negatively affect performance.

9.4.1

Previous | Top | Next

10 Credits

GeNN was created by Thomas Nowotny.

Addition of Izhikevich model, debugging modes and sparse connectivity by Esin Yavuz.

Block size optimisations and delayed synapses by James Turner.

Automatic brackets and dense to sparse network conversion by Alan Diamond.

User-defined synaptic and postsynaptic methods by Alex Cope and Esin Yavuz.

Example projects were provided by Alan Diamond, James Turner, Esin Yavuz and Thomas Nowotny.

Previous | Top

11 Hierarchical Index

11.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

classIzh	48
classol	51
CodeHelper	59
CStopWatch	60
dpclass	61
expDecayDp	62
pwSTDP	9 1
pwSTDP_userdef	92
rulkovdp	95
errTupel	62
inputSpec	63
neuronModel	63
neuronpop	65
NNmodel	67
Parameter	80
postSynModel	8 1
postVarsInPostLearn	82
postVarsInPostLearn_sparse	82
postVarsInSimCode	83
postVarsInSimCode_sparse	84
postVarsInSynapseDynamics	85
postVarsInSynapseDynamics_sparse	85
preVarsInPostLearn	86
preVarsInPostLearn_sparse	87
preVarsInSimCode	88
preVarsInSimCode_sparse	88
preVarsInSynapseDynamics	89
preVarsInSynapseDynamics_sparse	90
randomGauss	93
randomGen	94
Schmuker2014_classifier	95
stdRG	101

:	stopWatch	102
;	SynDelay	102
,	weightUpdateModel	103
12	Class Index	
12.1	1 Class List	
Her	e are the classes, structs, unions and interfaces with brief descriptions:	
	classizh	48
	classol	
	This class cpontains the methods for running the MBody1 example model	51
(CodeHelper	59
	CStopWatch	60
•	dpclass	61
•	errTupel	62
•	expDecayDp Class defining the dependent parameter for exponential decay	62
i	inputSpec	63
ı	neuronModel Class (struct) for specifying a neuron model	63
ı	neuronpop	65
ı	NNmodel Structure to hold the information that defines synapse dynamics (a model of how synapse variables change over time, independent of or in addition to changes when spikes occur)	67
ı	Parameter	80
ı	postSynModel Structure to hold the information that defines a post-synaptic model (a model of how synapses affect post-synaptic neuron variables, classically in the form of a synaptic current). It also allows to define an equation for the dynamics that can be applied to the summed synaptic	
	input variable "insyn"	81
	postVarsInPostLearn	82
	postVarsInPostLearn_sparse	82
ı	postVarsInSimCode	83
	postVarsInSimCode_sparse	84
	postVarsInSynapseDynamics	85
	postVarsInSynapseDynamics_sparse	85
	preVarsInPostLearn	86

13 File Index 43

	preVarsInPostLearn_sparse	87
	preVarsInSimCode	88
	preVarsInSimCode_sparse	88
	preVarsInSynapseDynamics	89
	preVarsInSynapseDynamics_sparse	90
	pwSTDP TODO This class definition may be code-generated in a future release	91
	pwSTDP_userdef TODO This class definition may be code-generated in a future release	92
	randomGauss Class random Gauss encapsulates the methods for generating random neumbers with Gaussian distribution	93
	randomGen Class randomGen which implements the ISAAC random number generator for uniformely distributed random numbers	94
	rulkovdp Class defining the dependent parameters of teh Rulkov map neuron	95
	Schmuker2014_classifier This class cpontains the methods for running the Schmuker_2014_classifier example model	95
	stdRG	101
	stopWatch	102
	SynDelay	102
	weightUpdateModel Structure to hold the information that defines a weightupdate model (a model of how spikes affect synaptic (and/or) (mostly) post-synaptic neuron variables. It also allows to define changes in response to post-synaptic spikes/spike-like events	103
13	File Index	
13.	1 File List	
He	re is a list of all files with brief descriptions:	
	MBody1_project/model/classol_sim.cu	105
	MBody_delayedSyn_project/model/classol_sim.cu	106
	MBody_individualID_project/model/classol_sim.cu	106
	MBody_userdef_project/model/classol_sim.cu	106
	MBody1_project/model/classol_sim.h	107
	MBody_delayedSyn_project/model/classol_sim.h	108
	MBody_individualID_project/model/classol_sim.h	109

MBody_userdef_project/model/classol_sim.h	110
CodeHelper.cc	111
ensureFtype.h	112
experiment.cu	112
experiment.h	114
extra_neurons.h	115
lib/include/extra_postsynapses.h	117
SpineML_to_GeNN/extra_postsynapses.h	118
extra_weightupdates.h	119
GA.cc	119
gauss.cc Contains the implementation of the Gaussian random number generator class randomGauss	119
gauss.h Random number generator for Gaussian random variable with mean 0 and standard deviation 1	120
gen_input_structured.cc	120
gen_kcdn_syns.cc This file is part of a tool chain for running the classol/MBody1 example model	121
gen_kcdn_syns_fixto10K.cc	121
gen_pnkc_syns.cc This file is part of a tool chain for running the classol/MBody1 example model	122
gen_pnkc_syns_indivID.cc This file is part of a tool chain for running the classol/MBody1 example model	123
gen_pnlhi_syns.cc This file is part of a tool chain for running the classol/MBody1 example model	123
gen_syns_sparse.cc This file generates the arrays needed for sparse connectivity. The connectivity is saved to a file for each variable and can then be read to fill the struct of connectivity	124
gen_syns_sparse_izhModel.cc This file is part of a tool chain for running the Izhikevich network model	125
HHVclampGA_project/generate_run.cc	127
lzh_sparse_project/generate_run.cc	127
MBody1_project/generate_run.cc	128
MBody_delayedSyn_project/generate_run.cc	129
MBody_individualID_project/generate_run.cc	130
MBody_userdef_project/generate_run.cc	131
OneComp_project/generate_run.cc	132

13.1 File List 45

PoissonIzh_project/generate_run.cc	132
generateALL.cc Main file combining the code for code generation. Part of the code generation section	133
generateCPU.cc Functions for generating code that will run the neuron and synapse simulations on the CPU. Part of the code generation section	134
generateKernels.cc Contains functions that generate code for CUDA kernels. Part of the code generation section	135
generateRunner.cc Contains functions to generate code for running the simulation on the GPU, and for I/O convenience functions between GPU and CPU space. Part of the code generation section	137
GeNNHelperKrnls.cu	137
global.h Global header file containing a few global variables. Part of the code generation section	138
helper.h	140
HHVClamp.cc This file contains the model definition of HHVClamp model. It is used in both the GeNN code generation and the user side simulation code. The HHVClamp model implements a population of unconnected Hodgkin-Huxley neurons that evolve to mimick a model run on the CPU, using	140
genetic algorithm techniques	142 143
HHVClampParameters.h	143
hr_time.cpp This file contains the implementation of the CStopWatch class that provides a simple timing tool based on the system clock	143
hr_time.h This header file contains the definition of the CStopWatch class that implements a simple timing tool using the system clock	144
lzh_sim_sparse.cu	144
lzh_sparse.cc	144
lzh_sparse_model.cc	146
lzh_sparse_model.h	146
lzh_sparse_sim.h	147
MBody1_project/model/map_classol.cc	147
MBody_delayedSyn_project/model/map_classol.cc	148
MBody_individualID_project/model/map_classol.cc	148
MBody_userdef_project/model/map_classol.cc	148
MBody1_project/model/map_classol.h	149
MBody_delayedSyn_project/model/map_classol.h	149
MBody_individualID_project/model/map_classol.h	149

MBody_userdef_project/model/map_classol.h	149
HHVclampGA_project/model/MBody1.cc	149
MBody1_project/model/MBody1.cc	152
MBody_delayedSyn.cc This file contains the model definition of the mushroom body "MBody_delayedSyn" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim)	156
MBody_individualID.cc This file contains the model definition of the mushroom body "MBody_incividualID" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim). It uses INDIVIDUALID for the connections from AL to MB allowing quite large numbers of PN and KC	160
MBody_userdef.cc This file contains the model definition of the mushroom body model. tis used in the GeNN code generation and the user side simulation code (class classol, file classol_sim)	164
Model_Schmuker_2014_classifier.cc	168
modelSpec.cc	169
modelSpec.h Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of NNmodel for defining a neuronal network model. Part of the code generation and generated code sections	169
OneComp.cc	175
OneComp_model.cc	176
OneComp_model.h	176
OneComp_sim.cu	176
OneComp_sim.h	177
Poissonlzh-model.cc	177
Poissonlzh-model.h	178
Poissonlzh.cc	178
PoissonIzh_sim.cu	180
PoissonIzh_sim.h	180
postVarsInPostLearn.cc	181
postVarsInPostLearn_sparse.cc	182
postVarsInSimCode.cc	184
postVarsInSimCode_sparse.cc	185
postVarsInSynapseDynamics.cc	186
postVarsInSynapseDynamics_sparse.cc	187

13.1 File List 47

preVarsInPostLearn.cc	188
preVarsInPostLearn_sparse.cc	189
preVarsInSimCode.cc	190
preVarsInSimCode_sparse.cc	191
preVarsInSynapseDynamics.cc	192
preVarsInSynapseDynamics_sparse.cc	193
randomGen.cc Contains the implementation of the ISAAC random number generator class for uniformly distributed random numbers and for a standard random number generator based on the C function rand()	194
randomGen.h Header file containing the class definition for a uniform random generator based on the ISAAC random number generator	195
Schmuker2014_classifier.cu	195
Schmuker2014_classifier.h Header file containing the class definition for the Schmuker2014 classifier, which contains the methods for setting up, initialising, simulating and saving results of a multivariate classifier imspired by the insect olfactory system. See "A neuromorphic network for generic multivariate data classification, Michael Schmuker, Thomas Pfeilc, and Martin Paul Nawrota, 2014"	196
simpleBit.h Contains three macros that allow simple bit manipulations on an (presumably unsigned) 32 bit integer	196
sizes.h	197
sparseUtils.cc	197
stringutils.h	198
SynDelay.cc	200
SynDelaySim.cu	202
SynDelaySim.h	203
postsynapticVariables/testHelper.h	203
presynapticVariables/testHelper.h	203
testPostVarsInPostLearn.cu	204
testPostVarsInPostLearn.h	204
testPostVarsInPostLearn_sparse.cu	205
testPostVarsInPostLearn_sparse.h	205
testPostVarsInSimCode.cu	206
testPostVarsInSimCode.h	206
testPostVarsInSimCode_sparse.cu	207

testPostVarsInSimCode_sparse.h	207
testPostVarsInSynapseDynamics.cu	208
testPostVarsInSynapseDynamics.h	208
testPostVarsInSynapseDynamics_sparse.cu	209
testPostVarsInSynapseDynamics_sparse.h	209
testPreVarsInPostLearn.cu	210
testPreVarsInPostLearn.h	210
testPreVarsInPostLearn_sparse.cu	211
testPreVarsInPostLearn_sparse.h	211
testPreVarsInSimCode.cu	212
testPreVarsInSimCode.h	212
testPreVarsInSimCode_sparse.cu	213
testPreVarsInSimCode_sparse.h	213
testPreVarsInSynapseDynamics.cu	214
testPreVarsInSynapseDynamics.h	214
testPreVarsInSynapseDynamics_sparse.cu	215
testPreVarsInSynapseDynamics_sparse.h	215
toString.h Contains a template function for string conversion from const char∗ to C++ string	215
utils.h This file contains standard utility functions provide within the NVIDIA CUDA software development toolkit (SDK). The remainder of the file contains a function that defines the standard neuron models	216
VClampGA.cu Main entry point for the GeNN project demonstrating realtime fitting of a neuron with a GA running mostly on the GPU	219
VClampGA.h	220

14 Class Documentation

14.1 classIzh Class Reference

#include <Izh_sparse_model.h>

Public Member Functions

- classIzh ()
- \sim classIzh ()
- void init (unsigned int)

 void allocate_device_mem_patterns () void allocate_device_mem_input () void copy_device_mem_input () • void read_sparsesyns_par (int, struct SparseProjection, FILE *, FILE *, FILE *, scalar *) void gen_alltoall_syns (scalar *, unsigned int, unsigned int, scalar) void free_device_mem () void write_input_to_file (FILE *) void read_input_values (FILE *) · void create_input_values () • void run (double, unsigned int) void getSpikesFromGPU () Method for copying all spikes of the last time step from the GPU. void getSpikeNumbersFromGPU () Method for copying the number of spikes in all neuron populations that have occurred during the last time step. void output_state (FILE *, unsigned int) void output_spikes (FILE *, unsigned int) void output_params (FILE *, FILE *) • void sum_spikes () void setInput (unsigned int) void randomizeVar (scalar *, scalar, unsigned int) void randomizeVarSq (scalar *, scalar, unsigned int) · void initializeAllVars (unsigned int) **Public Attributes** NNmodel model scalar * input1 scalar * input2 scalar * d_input1 • scalar * d_input2 • unsigned int sumPExc · unsigned int sumPInh 14.1.1 Constructor & Destructor Documentation 14.1.1.1 classlzh::classlzh() 14.1.1.2 classlzh:: ∼classlzh () 14.1.2 Member Function Documentation

```
14.1.2.2 void classlzh::allocate_device_mem_patterns()

14.1.2.3 void classlzh::copy_device_mem_input()

14.1.2.4 void classlzh::create_input_values()

14.1.2.5 void classlzh::free_device_mem()

14.1.2.6 void classlzh::gen_alltoall_syns( scalar * g, unsigned int nPre, unsigned int nPost, scalar gscale)
```

14.1.2.1 void classlzh::allocate_device_mem_input ()

Parameters

gscale Generate random conductivity values for an all to all network

```
14.1.2.7 void classlzh::getSpikeNumbersFromGPU ( )
```

Method for copying the number of spikes in all neuron populations that have occurred during the last time step.

This method is a simple wrapper for the convenience function copySpikeNFromDevice() provided by GeNN.

```
14.1.2.8 void classlzh::getSpikesFromGPU ( )
```

Method for copying all spikes of the last time step from the GPU.

This is a simple wrapper for the convenience function copySpikesFromDevice() which is provided by GeNN.

```
14.1.2.9 void classIzh::init ( unsigned int which )
```

```
14.1.2.10 void classIzh::initializeAllVars ( unsigned int which )
```

```
14.1.2.11 void classlzh::output_params ( FILE * f, FILE * f2 )
```

```
14.1.2.12 void classIzh::output_spikes ( FILE * f, unsigned int which )
```

```
14.1.2.13 void classIzh::output_state ( FILE * f, unsigned int which )
```

14.1.2.14 void classlzh::randomizeVar (scalar * Var, scalar strength, unsigned int neuronGrp)

14.1.2.15 void classlzh::randomizeVarSq (scalar * Var, scalar strength, unsigned int neuronGrp)

```
14.1.2.16 void classlzh::read_input_values ( FILE * )
```

14.1.2.17 void class|zh::read_sparsesyns_par (int synlnd, struct SparseProjection C, FILE * f_ind, FILE * f_indlnG, FILE * f_g, scalar * g)

Parameters

g | File handle for a file containing sparse conductivity values

```
14.1.2.18 void classIzh::run ( double runtime, unsigned int which )
```

```
14.1.2.19 void classIzh::setInput ( unsigned int which )
```

```
14.1.2.20 void classlzh::sum_spikes ( )
```

14.1.2.21 void classlzh::write_input_to_file (FILE * f)

14.1.3 Member Data Documentation

```
14.1.3.1 scalar* classlzh::d_input1
```

14.1.3.2 scalar * classlzh::d_input2

14.1.3.3 scalar* classlzh::input1

14.1.3.4 scalar * classlzh::input2

14.1.3.5 NNmodel classlzh::model

14.1.3.6 unsigned int classIzh::sumPExc

14.1.3.7 unsigned int classIzh::sumPInh

The documentation for this class was generated from the following files:

- Izh_sparse_model.h
- · Izh sparse model.cc

14.2 classol Class Reference

This class coontains the methods for running the MBody1 example model.

```
#include <map_classol.h>
```

Public Member Functions

- · classol ()
- ∼classol ()
- · void init (unsigned int)

Method for initialising variables.

• void allocate_device_mem_patterns ()

Method for allocating memory on the GPU device to hold the input patterns.

void free_device_mem ()

Methods for unallocating the memory for input patterns on the GPU device.

void read_pnkcsyns (FILE *)

Method for reading the connectivity between PNs and KCs from a file.

- void read_sparsesyns_par (int, struct SparseProjection, scalar *, FILE *, FILE *, FILE *)
- void write_pnkcsyns (FILE *)

Method for writing the conenctivity between PNs and KCs back into file.

void read_pnlhisyns (FILE *)

Method for reading the connectivity between PNs and LHIs from a file.

• void write_pnlhisyns (FILE *)

Method for writing the connectivity between PNs and LHIs to a file.

void read_kcdnsyns (FILE *)

Method for reading the connectivity between KCs and DNs (detector neurons) from a file.

• void write_kcdnsyns (FILE *)

Method to write the connectivity between KCs and DNs (detector neurons) to a file.

void read_input_patterns (FILE *)

Method for reading the input patterns from a file.

void generate_baserates ()

Method for calculating the baseline rates of the Poisson input neurons.

void runGPU (scalar)

Method for simulating the model for a given period of time on the GPU.

void runCPU (scalar)

Method for simulating the model for a given period of time on the CPU.

void output_state (FILE *, unsigned int)

Method for copying from device and writing out to file of the entire state of the model.

void getSpikesFromGPU ()

Method for copying all spikes of the last time step from the GPU.

void getSpikeNumbersFromGPU ()

Method for copying the number of spikes in all neuron populations that have occurred during the last time step.

void output_spikes (FILE *, unsigned int)

Method for writing the spikes occurred in the last time step to a file.

```
· void sum_spikes ()
      Method for summing up spike numbers.

    void get kcdnsyns ()

     Method for copying the synaptic conductances of the learning synapses between KCs and DNs (detector neurons)
     back to the CPU memory.
· classol ()

    ∼classol ()

    void init (unsigned int)

· void allocate device mem patterns ()
• void free device mem ()

    void read_pnkcsyns (FILE *)

    void read_sparsesyns_par (int, struct SparseProjection, scalar *, FILE *, FILE *, FILE *)

    void write_pnkcsyns (FILE *)

• void read_pnlhisyns (FILE *)

    void write pnlhisyns (FILE *)

    void read_kcdnsyns (FILE *)

    void write_kcdnsyns (FILE *)

    void read_input_patterns (FILE *)

· void generate baserates ()
· void run (scalar, unsigned int)
      Method for simulating the model for a given period of time.

    void output_state (FILE *, unsigned int)

    void getSpikesFromGPU ()

    void getSpikeNumbersFromGPU ()

    void output spikes (FILE *, unsigned int)

    void sum_spikes ()

void get_kcdnsyns ()
· classol ()

    ∼classol ()

    void init (unsigned int)

    void allocate device mem patterns ()

void free_device_mem ()

    void read_pnkcsyns (FILE *)

• void read_sparsesyns_par (int, struct SparseProjection, scalar *, FILE *, FILE *, FILE *)

    void write pnkcsyns (FILE *)

    void read pnlhisyns (FILE *)

    void write pnlhisyns (FILE *)

    void read_kcdnsyns (FILE *)

• void write_kcdnsyns (FILE *)

    void read input patterns (FILE *)

• void generate_baserates ()
· void run (scalar, unsigned int)

    void output state (FILE *, unsigned int)

    void getSpikesFromGPU ()

    void getSpikeNumbersFromGPU ()

    void output spikes (FILE *, unsigned int)

void sum_spikes ()
void get_kcdnsyns ()

    classol ()

    ∼classol ()

    void init (unsigned int)

    void allocate_device_mem_patterns ()

• void free device mem ()

    void read_pnkcsyns (FILE *)
```

```
template < class DATATYPE >
  void read_sparsesyns_par (DATATYPE *, int, struct SparseProjection, FILE *, FILE *, FILE *)

    void write_pnkcsyns (FILE *)

    void read pnlhisyns (FILE *)

    void write pnlhisyns (FILE *)

    void read_kcdnsyns (FILE *)

    void write_kcdnsyns (FILE *)

    void read_input_patterns (FILE *)

· void generate baserates ()

    void runGPU (scalar)

· void runCPU (scalar)

    void output_state (FILE *, unsigned int)

    void getSpikesFromGPU ()

    void getSpikeNumbersFromGPU ()

    void output_spikes (FILE *, unsigned int)

• void sum_spikes ()
void get_kcdnsyns ()
· classol ()

    ∼classol ()

    void init (unsigned int)

    void allocate_device_mem_input ()

void free_device_mem ()

    void read_PNIzh1syns (scalar *, FILE *)

• void read_sparsesyns_par (int, struct SparseProjection, FILE *, FILE *, FILE *, double *)

    void generate_baserates ()

• void run (float, unsigned int)

    void output_state (FILE *, unsigned int)

    void getSpikesFromGPU ()

    void getSpikeNumbersFromGPU ()

    void output_spikes (FILE *, unsigned int)

void sum_spikes ()
```

Public Attributes

- NNmodel model
- · unsigned int offset
- uint64_t * theRates
- scalar * p_pattern
- uint64_t * pattern
- uint64_t * baserates
- uint64_t * d_pattern
- uint64_t * d_baserates
- unsigned int sumPN
- · unsigned int sumKC
- unsigned int sumLHI
- unsigned int sumDN
- unsigned int size_g
- unsigned int sumlzh1

14.2.1 Detailed Description

This class coontains the methods for running the MBody1 example model.

This class cpontains the methods for running the MBody_delayedSyn example model.

```
14.2.2 Constructor & Destructor Documentation
14.2.2.1 classol::classol()
14.2.2.2 classol:: ∼ classol ( )
14.2.2.3 classol::classol()
14.2.2.4 classol:: ∼classol ( )
14.2.2.5 classol::classol()
14.2.2.6 classol:: ∼ classol ( )
14.2.2.7 classol::classol()
14.2.2.8 classol:: ∼classol ( )
14.2.2.9 classol::classol()
14.2.2.10 classol:: ∼ classol ( )
14.2.3 Member Function Documentation
14.2.3.1 void classol::allocate_device_mem_input()
14.2.3.2 void classol::allocate_device_mem_patterns ( )
Method for allocating memory on the GPU device to hold the input patterns.
14.2.3.3 void classol::allocate_device_mem_patterns ( )
14.2.3.4 void classol::allocate_device_mem_patterns ( )
14.2.3.5 void classol::allocate_device_mem_patterns ( )
14.2.3.6 void classol::free_device_mem ( )
14.2.3.7 void classol::free_device_mem ( )
14.2.3.8 void classol::free_device_mem ( )
14.2.3.9 void classol::free_device_mem ( )
Methods for unallocating the memory for input patterns on the GPU device.
14.2.3.10 void classol::free_device_mem ( )
14.2.3.11 void classol::generate_baserates ( )
14.2.3.12 void classol::generate_baserates ( )
14.2.3.13 void classol::generate_baserates ( )
Method for calculating the baseline rates of the Poisson input neurons.
14.2.3.14 void classol::generate_baserates ( )
14.2.3.15 void classol::generate_baserates ( )
14.2.3.16 void classol::get_kcdnsyns()
```

```
    14.2.3.17 void classol::get_kcdnsyns ( )
    14.2.3.18 void classol::get_kcdnsyns ( )
    Method for copying the synaptic conductances of the learning synapses between KCs and DNs (detector neurons) back to the CPU memory.
```

```
14.2.3.19 void classol::get_kcdnsyns()

14.2.3.20 void classol::getSpikeNumbersFromGPU()

14.2.3.21 void classol::getSpikeNumbersFromGPU()

14.2.3.22 void classol::getSpikeNumbersFromGPU()

14.2.3.23 void classol::getSpikeNumbersFromGPU()
```

Method for copying the number of spikes in all neuron populations that have occurred during the last time step.

This method is a simple wrapper for the convenience function copySpikeNFromDevice() provided by GeNN.

```
14.2.3.24 void classol::getSpikeNumbersFromGPU ( )

14.2.3.25 void classol::getSpikesFromGPU ( )

14.2.3.26 void classol::getSpikesFromGPU ( )

14.2.3.27 void classol::getSpikesFromGPU ( )

14.2.3.28 void classol::getSpikesFromGPU ( )
```

Method for copying all spikes of the last time step from the GPU.

This is a simple wrapper for the convenience function copySpikesFromDevice() which is provided by GeNN.

```
14.2.3.29 void classol::getSpikesFromGPU ( )

14.2.3.30 void classol::init ( unsigned int )

14.2.3.31 void classol::init ( unsigned int which )
```

Method for initialising variables.

Parameters

which Flag defining whether GPU or CPU only version is run

```
14.2.3.32 void classol::init ( unsigned int )

14.2.3.33 void classol::init ( unsigned int )

14.2.3.34 void classol::init ( unsigned int )

14.2.3.35 void classol::output_spikes ( FILE * , unsigned int )

14.2.3.36 void classol::output_spikes ( FILE * , unsigned int )

14.2.3.37 void classol::output_spikes ( FILE * , unsigned int )

14.2.3.38 void classol::output_spikes ( FILE * f, unsigned int which )
```

Method for writing the spikes occurred in the last time step to a file.

Parameters

f	File handle for a file to write spike times to
which	Flag determining whether using GPU or CPU only

```
14.2.3.39 void classol::output_spikes ( FILE * , unsigned int )

14.2.3.40 void classol::output_state ( FILE * , unsigned int )

14.2.3.41 void classol::output_state ( FILE * , unsigned int )

14.2.3.42 void classol::output_state ( FILE * , unsigned int )

14.2.3.43 void classol::output_state ( FILE * f, unsigned int which )
```

Method for copying from device and writing out to file of the entire state of the model.

Parameters

f	File handle for a file to write the model state to
which	Flag determining whether using GPU or CPU only

```
14.2.3.44 void classol::output_state ( FILE * , unsigned int )14.2.3.45 void classol::read_input_patterns ( FILE * f )
```

Method for reading the input patterns from a file.

Parameters

f	File handle for a file containing input patterns

```
14.2.3.46 void classol::read_input_patterns ( FILE * )

14.2.3.47 void classol::read_input_patterns ( FILE * )

14.2.3.48 void classol::read_input_patterns ( FILE * )

14.2.3.49 void classol::read_kcdnsyns ( FILE * f )
```

Method for reading the connectivity between KCs and DNs (detector neurons) from a file.

Parameters

f File handle for a file containing KC to DN (detector neuron) conductivity values

```
14.2.3.50 void classol::read_kcdnsyns ( FILE * )

14.2.3.51 void classol::read_kcdnsyns ( FILE * )

14.2.3.52 void classol::read_kcdnsyns ( FILE * )

14.2.3.53 void classol::read_PNlzh1syns ( scalar * gp, FILE * f )

14.2.3.54 void classol::read_pnkcsyns ( FILE * )

14.2.3.55 void classol::read_pnkcsyns ( FILE * f )
```

Method for reading the connectivity between PNs and KCs from a file.

Parameters

```
File handle for a file containing PN to KC conductivity values
14.2.3.56 void classol::read_pnkcsyns ( FILE * )
14.2.3.57 void classol::read_pnkcsyns ( FILE * )
14.2.3.58 void classol::read_pnlhisyns ( FILE * f )
Method for reading the connectivity between PNs and LHIs from a file.
Parameters
                       File handle for a file containing PN to LHI conductivity values
14.2.3.59 void classol::read_pnlhisyns ( FILE * )
14.2.3.60 void classol::read_pnlhisyns ( FILE * )
14.2.3.61 void classol::read_pnlhisyns ( FILE * )
14.2.3.62 void classol::read_sparsesyns_par ( int synInd, struct SparseProjection C, FILE * f_ind, FILE * f_indInG, FILE * f_g,
          double *g)
Parameters
                       File handle for a file containing sparse conductivity values
14.2.3.63 void classol::read_sparsesyns_par ( int synInd, struct SparseProjection C, scalar * g, FILE * f_ind, FILE *
          f_indInG, FILE * f_g )
Parameters
                       File handle for a file containing sparse connectivity values
14.2.3.64 void classol::read_sparsesyns_par ( int , struct SparseProjection , scalar * , FILE * , FILE * , FILE * )
14.2.3.65 void classol::read_sparsesyns_par ( int , struct SparseProjection , scalar * , FILE * , FILE * , FILE * )
14.2.3.66 template < class DATATYPE > void classol::read_sparsesyns_par ( DATATYPE * wuvar, int synInd, struct
          SparseProjection C, FILE *f_ind, FILE *f_indInG, FILE *f_g)
Parameters
                       File handle for a file containing sparse conductivity values
14.2.3.67 void classol::run ( float runtime, unsigned int which )
14.2.3.68 void classol::run ( scalar runtime, unsigned int which )
Method for simulating the model for a given period of time.
Parameters
                       Duration of time to run the model for
            runtime
```

which | Flag determining whether to run on GPU or CPU only

```
14.2.3.69 void classol::run ( scalar , unsigned int )
```

14.2.3.70 void classol::runCPU (scalar runtime)

Method for simulating the model for a given period of time on the CPU.

Method for simulating the model for a given period of time on th CPU.

Parameters

runtime Duration of time to run the model for

```
14.2.3.71 void classol::runCPU ( scalar )
```

14.2.3.72 void classol::runGPU (scalar runtime)

Method for simulating the model for a given period of time on the GPU.

Method for simulating the model for a given period of time on th GPU.

Parameters

runtime Duration of time to run the model for

```
14.2.3.73 void classol::runGPU ( scalar )
```

14.2.3.74 void classol::sum_spikes ()

14.2.3.75 void classol::sum_spikes ()

14.2.3.76 void classol::sum_spikes ()

14.2.3.77 void classol::sum_spikes ()

Method for summing up spike numbers.

14.2.3.78 void classol::sum_spikes ()

14.2.3.79 void classol::write_kcdnsyns (FILE * f)

Method to write the connectivity between KCs and DNs (detector neurons) to a file.

Parameters

f | File handle for a file to write KC to DN (detectore neuron) conductivity values to

```
14.2.3.80 void classol::write_kcdnsyns ( FILE * )
```

14.2.3.81 void classol::write_kcdnsyns (FILE *)

14.2.3.82 void classol::write_kcdnsyns (FILE *)

14.2.3.83 void classol::write_pnkcsyns (FILE *)

14.2.3.84 void classol::write_pnkcsyns (FILE *)

14.2.3.85 void classol::write_pnkcsyns (FILE * f)

Method for writing the conenctivity between PNs and KCs back into file.

Parameters

```
f | File handle for a file to write PN to KC conductivity values to

14.2.3.86 void classol::write_pnkcsyns ( FILE * )

14.2.3.87 void classol::write_pnlhisyns ( FILE * )
```

14.2.3.88 void classol::write_pnlhisyns (FILE * f)

Method for writing the connectivity between PNs and LHIs to a file.

Parameters

f | File handle for a file to write PN to LHI conductivity values to

```
14.2.3.89 void classol::write_pnlhisyns ( FILE * )
14.2.3.90 void classol::write_pnlhisyns ( FILE * )
14.2.4 Member Data Documentation
14.2.4.1 uint64_t * classol::baserates
14.2.4.2 uint64_t * classol::d_baserates
14.2.4.3 uint64_t * classol::d_pattern
14.2.4.4 NNmodel classol::model
14.2.4.5 unsigned int classol::offset
14.2.4.6 scalar * classol::p_pattern
14.2.4.7 uint64_t * classol::pattern
14.2.4.8 unsigned int classol::size_g
14.2.4.9 unsigned int classol::sumDN
14.2.4.10 unsigned int classol::sumlzh1
14.2.4.11 unsigned int classol::sumKC
14.2.4.12 unsigned int classol::sumLHI
14.2.4.13 unsigned int classol::sumPN
14.2.4.14 uint64_t * classol::theRates
```

The documentation for this class was generated from the following files:

- MBody1_project/model/map_classol.h
- · PoissonIzh-model.h
- MBody1_project/model/map_classol.cc
- · PoissonIzh-model.cc

14.3 CodeHelper Class Reference

Public Member Functions

- CodeHelper ()
- void setVerbose (bool isVerbose)
- string openBrace (unsigned int level)
- string closeBrace (unsigned int level)
- string endl ()

Public Attributes

- vector< unsigned int > braces
- · bool verbose

```
14.3.1 Constructor & Destructor Documentation
```

```
14.3.1.1 CodeHelper::CodeHelper( ) [inline]
```

14.3.2 Member Function Documentation

```
14.3.2.1 string CodeHelper::closeBrace (unsigned int level) [inline]
```

14.3.2.2 string CodeHelper::endl() [inline]

14.3.2.3 string CodeHelper::openBrace (unsigned int level) [inline]

14.3.2.4 void CodeHelper::setVerbose (bool isVerbose) [inline]

14.3.3 Member Data Documentation

14.3.3.1 vector < unsigned int > CodeHelper::braces

14.3.3.2 bool CodeHelper::verbose

The documentation for this class was generated from the following file:

· CodeHelper.cc

14.4 CStopWatch Class Reference

```
#include <hr_time.h>
```

Public Member Functions

- CStopWatch ()
- void startTimer ()

This method starts the timer.

• void stopTimer ()

This method stops the timer.

• double getElapsedTime ()

This method returns the time elapsed between start and stop of the timer in seconds.

```
14.4.1 Constructor & Destructor Documentation
```

```
14.4.1.1 CStopWatch::CStopWatch() [inline]
```

14.4.2 Member Function Documentation

```
14.4.2.1 double CStopWatch::getElapsedTime ( )
```

This method returns the time elapsed between start and stop of the timer in seconds.

```
14.4.2.2 void CStopWatch::startTimer ( )
```

This method starts the timer.

```
14.4.2.3 void CStopWatch::stopTimer ( )
```

This method stops the timer.


The documentation for this class was generated from the following files:

- hr_time.h
- · hr time.cpp

14.5 dpclass Class Reference

```
#include <modelSpec.h>
```

Inheritance diagram for dpclass:



Public Member Functions

- dpclass ()
- virtual double calculateDerivedParameter (int index, vector< double > pars, double dt=1.0)

14.5.1 Constructor & Destructor Documentation

```
14.5.1.1 dpclass::dpclass() [inline]
```

14.5.2 Member Function Documentation

```
14.5.2.1 virtual double dpclass::calculateDerivedParameter ( int index, vector< double > pars, double dt = 1.0 ) [inline], [virtual]
```

Reimplemented in expDecayDp, rulkovdp, pwSTDP_userdef, and pwSTDP.

The documentation for this class was generated from the following file:

· modelSpec.h

14.6 errTupel Struct Reference

Public Attributes

- · unsigned int id
- · double err
- 14.6.1 Member Data Documentation
- 14.6.1.1 double errTupel::err
- 14.6.1.2 unsigned int errTupel::id

The documentation for this struct was generated from the following file:


• GA.cc

14.7 expDecayDp Class Reference

Class defining the dependent parameter for exponential decay.

```
#include <utils.h>
```

Inheritance diagram for expDecayDp:



Public Member Functions

- double calculateDerivedParameter (int index, vector< double > pars, double dt=1.0)
- double expDecay (vector< double > pars, double dt)
- 14.7.1 Detailed Description

Class defining the dependent parameter for exponential decay.

14.7.2 Member Function Documentation

```
14.7.2.1 double expDecayDp::calculateDerivedParameter ( int index, vector< double > pars, double dt = 1.0 )
[inline], [virtual]
```

Reimplemented from dpclass.

```
14.7.2.2 double expDecayDp::expDecay ( vector < double > pars, double dt ) [inline]
```

The documentation for this class was generated from the following file:

· utils.h

14.8 inputSpec Struct Reference

```
#include <helper.h>
```

Public Attributes

- double t
- double baseV
- int N
- vector< double > st
- vector< double > V
- 14.8.1 Member Data Documentation
- 14.8.1.1 double inputSpec::baseV
- 14.8.1.2 int inputSpec::N
- 14.8.1.3 vector<double> inputSpec::st
- 14.8.1.4 double inputSpec::t
- 14.8.1.5 vector<double> inputSpec::V

The documentation for this struct was generated from the following file:

· helper.h

14.9 neuronModel Struct Reference

class (struct) for specifying a neuron model.

```
#include <modelSpec.h>
```

Public Attributes

string simCode

Code that defines the execution of one timestep of integration of the neuron model.

· string thresholdConditionCode

Code evaluating to a bool (e.g. "V > 20") that defines the condition for a true spike in the described neuron model.

string resetCode

Code that defines the reset action taken after a spike occurred. This can be empty.

vector< string > varNames

Names of the variables in the neuron model.

vector< string > tmpVarNames

never used

vector< string > varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

vector< string > tmpVarTypes

never used

vector< string > pNames

Names of (independent) parameters of the model.

vector< string > dpNames

Names of dependent parameters of the model.

vector< string > extraGlobalNeuronKernelParameters

Additional parameter in the neuron kernel; it is translated to a population specific name but otherwise assumed to be one parameter per population rather than per neuron.

vector< string > extraGlobalNeuronKernelParameterTypes

Additional parameters in the neuron kernel; they are translated to a population specific name but otherwise assumed to be one parameter per population rather than per neuron.

· dpclass * dps

Derived parameters.

· bool needPreSt

Whether presynaptic spike times are needed or not.

· bool needPostSt

Whether postsynaptic spike times are needed or not.

14.9.1 Detailed Description

class (struct) for specifying a neuron model.

14.9.2 Member Data Documentation

14.9.2.1 vector<string> neuronModel::dpNames

Names of dependent parameters of the model.

The dependent parameters are functions of independent parameters that enter into the neuron model. To avoid unecessary computational overhead, these parameters are calculated at compile time and inserted as explicit values into the generated code. See method NNmodel::initDerivedNeuronPara for how this is done.

14.9.2.2 dpclass* neuronModel::dps

Derived parameters.

 $14.9.2.3 \quad vector {<} string {>} \ neuron Model :: extra Global Neuron Kernel Parameters$

Additional parameter in the neuron kernel; it is translated to a population specific name but otherwise assumed to be one parameter per population rather than per neuron.

14.9.2.4 vector<string> neuronModel::extraGlobalNeuronKernelParameterTypes

Additional parameters in the neuron kernel; they are translated to a population specific name but otherwise assumed to be one parameter per population rather than per neuron.

14.9.2.5 bool neuronModel::needPostSt

Whether postsynaptic spike times are needed or not.

14.9.2.6 bool neuronModel::needPreSt

Whether presynaptic spike times are needed or not.

14.9.2.7 vector<string> neuronModel::pNames

Names of (independent) parameters of the model.

14.9.2.8 string neuronModel::resetCode

Code that defines the reset action taken after a spike occurred. This can be empty.

14.9.2.9 string neuronModel::simCode

Code that defines the execution of one timestep of integration of the neuron model.

The code will refer to for the value of the variable with name "NN". It needs to refer to the predefined variable "ISYN", i.e. contain, if it is to receive input.

14.9.2.10 string neuronModel::thresholdConditionCode

Code evaluating to a bool (e.g. "V > 20") that defines the condition for a true spike in the described neuron model.

```
14.9.2.11 vector<string> neuronModel::tmpVarNames
```

never used

14.9.2.12 vector<string> neuronModel::tmpVarTypes

never used

14.9.2.13 vector<string> neuronModel::varNames

Names of the variables in the neuron model.

14.9.2.14 vector<string> neuronModel::varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

The documentation for this struct was generated from the following file:

· modelSpec.h

14.10 neuronpop Class Reference

```
#include <OneComp_model.h>
```

Public Member Functions

- neuronpop ()
- ∼neuronpop ()
- void init (unsigned int)
- void allocate_device_mem_patterns ()
- void allocate_device_mem_input ()
- void copy_device_mem_input ()
- void write_input_to_file (FILE *)
- void read_input_values (FILE *)
- void create_input_values (float t)
- void run (float, unsigned int)
- void getSpikesFromGPU ()

Method for copying all spikes of the last time step from the GPU.

• void getSpikeNumbersFromGPU ()

Method for copying the number of spikes in all neuron populations that have occurred during the last time step.

- void output_state (FILE *, unsigned int)
- void output_spikes (FILE *, unsigned int)
- void sum_spikes ()

Public Attributes

```
    NNmodel model

    float * input1
    float * d_input1
    • unsigned int sumIzh1
14.10.1 Constructor & Destructor Documentation
14.10.1.1 neuronpop::neuronpop ( )
14.10.1.2 neuronpop::∼neuronpop ( )
14.10.2 Member Function Documentation
14.10.2.1 void neuronpop::allocate_device_mem_input ( )
14.10.2.2 void neuronpop::allocate_device_mem_patterns ( )
14.10.2.3 void neuronpop::copy_device_mem_input ( )
14.10.2.4 void neuronpop::create_input_values ( float t )
14.10.2.5 void neuronpop::getSpikeNumbersFromGPU ( )
Method for copying the number of spikes in all neuron populations that have occurred during the last time step.
This method is a simple wrapper for the convenience function copySpikeNFromDevice() provided by GeNN.
14.10.2.6 void neuronpop::getSpikesFromGPU ( )
Method for copying all spikes of the last time step from the GPU.
This is a simple wrapper for the convenience function copySpikesFromDevice() which is provided by GeNN.
14.10.2.7 void neuronpop::init ( unsigned int which )
14.10.2.8 void neuronpop::output_spikes (FILE * f, unsigned int which )
14.10.2.9 void neuronpop::output_state ( FILE * f, unsigned int which )
14.10.2.10 void neuronpop::read_input_values ( FILE * f )
14.10.2.11 void neuronpop::run ( float runtime, unsigned int which )
14.10.2.12 void neuronpop::sum_spikes ( )
14.10.2.13 void neuronpop::write_input_to_file ( FILE * f )
14.10.3 Member Data Documentation
14.10.3.1 float* neuronpop::d_input1
14.10.3.2 float* neuronpop::input1
```

The documentation for this class was generated from the following files:

· OneComp_model.h

14.10.3.3 NNmodel neuronpop::model

14.10.3.4 unsigned int neuronpop::sumlzh1

• OneComp_model.cc

14.11 NNmodel Class Reference

Structure to hold the information that defines synapse dynamics (a model of how synapse variables change over time, independent of or in addition to changes when spikes occur).

```
#include <modelSpec.h>
```

Public Member Functions

- NNmodel ()
- ∼NNmodel ()
- void setName (const string)

Method to set the neuronal network model name.

void setPrecision (unsigned int)

Set numerical precision for floating point.

void setTiming (bool)

Set whether timers and timing commands are to be included.

void setSeed (unsigned int)

Set the random seed (disables automatic seeding if argument not 0).

- void checkSizes (unsigned int *, unsigned int *, unsigned int *)
- void setGPUDevice (int)

Method to choose the GPU to be used for the model. If "AUTODEVICE' (-1), GeNN will choose the device based on a heuristic rule.

void addNeuronPopulation (const char *, unsigned int, unsigned int, double *, double *)

Method for adding a neuron population to a neuronal network model, using C style character array for the name of the population.

void addNeuronPopulation (const string, unsigned int, unsigned int, double *, double *)

Method for adding a neuron population to a neuronal network model, using C++ string for the name of the population.

void addNeuronPopulation (const string, unsigned int, unsigned int, vector< double >, vector< double >)

Method for adding a neuron population to a neuronal network model, using C++ string for the name of the population.

void activateDirectInput (const string, unsigned int)

Method for activating explicit current input.

void setConstInp (const string, double)

Method for setting the global input value for a neuron population if CONSTINP.

void setNeuronClusterIndex (const string neuronGroup, int hostID, int deviceID)

Function for setting which host and which device a neuron group will be simulated on.

• void addSynapsePopulation (const string name, unsigned int syntype, unsigned int conntype, unsigned int gtype, const string src, const string trg, double *p)

Overload of method for backwards compatibility.

• void addSynapsePopulation (const char *, unsigned int, u

Method for adding a synapse population to a neuronal network model, using C style character array for the name of the population.

• void addSynapsePopulation (const string, unsigned int, u

Overloaded version without initial variables for synapses.

• void addSynapsePopulation (const string, unsigned int, u

Method for adding a synapse population to a neuronal network model, using C++ string for the name of the population.

• void addSynapsePopulation (const string, unsigned int, u

Method for adding a synapse population to a neuronal network model, using C++ string for the name of the population.

void setSynapseG (const string, double)

Method for setting the conductance (g) value for a synapse population with "GLOBALG" charactertistic.

void setMaxConn (const string, unsigned int)

This function defines the maximum number of connections for a neuron in the population.

• void setSynapseClusterIndex (const string synapseGroup, int hostID, int deviceID)

Function for setting which host and which device a synapse group will be simulated on.

- void initLearnGrps ()
- · void finalize ()

Public Attributes

· string name

Name of the neuronal newtwork model.

string ftype

Type of floating point variables (float, double, ...; default: float)

string RNtype

Underlying type for random number generation (default: long)

int final

Flag for whether the model has been finalized.

· unsigned int needSt

Whether last spike times are needed at all in this network model (related to STDP)

unsigned int needSynapseDelay

Whether delayed synapse conductance is required in the network.

- · int chooseGPUDevice
- bool timing
- unsigned int seed
- unsigned int neuronGrpN

Number of neuron groups.

vector< string > neuronName

Names of neuron groups.

vector< unsigned int > neuronN

Number of neurons in group.

vector< unsigned int > sumNeuronN

Summed neuron numbers.

 $\bullet \ \ \text{vector}{<} \ \text{unsigned int} > \text{padSumNeuronN} \\$

Padded summed neuron numbers.

- vector< unsigned int > neuronPostSyn
- vector< unsigned int > neuronType

Postsynaptic methods to the neuron.

vector< vector< double >> neuronPara

Parameters of neurons.

vector< vector< double >> dnp

Derived neuron parameters.

vector< vector< double >> neuronIni

Initial values of neurons.

vector< vector< unsigned int >> inSyn

The ids of the incoming synapse groups.

vector< vector< unsigned int > > outSyn

The ids of the outgoing synapse groups.

vector< unsigned int > receivesInputCurrent

flags whether neurons of a population receive explicit input currents

vector< bool > neuronNeedSt

Whether last spike time needs to be saved for a group.

vector< bool > neuronNeedTrueSpk

Whether spike-like events from a group are required.

vector< bool > neuronNeedSpkEvnt

Whether spike-like events from a group are required.

vector< vector< bool >> neuronVarNeedQueue

Whether a neuron variable needs queueing for syn code.

vector< string > neuronSpkEvntCondition

Will contain the spike event condition code when spike events are used.

vector< unsigned int > neuronDelaySlots

The number of slots needed in the synapse delay queues of a neuron group.

vector< int > neuronHostID

The ID of the cluster node which the neuron groups are computed on.

vector< int > neuronDeviceID

The ID of the CUDA device which the neuron groups are computed on.

unsigned int synapseGrpN

Number of synapse groups.

vector< string > synapseName

Names of synapse groups.

vector< unsigned int > maxConn

Padded summed maximum number of connections for a neuron in the neuron groups.

- vector< unsigned int > padSumSynapseKrnl
- vector< unsigned int > synapseType

Types of synapses.

vector< unsigned int > synapseConnType

Connectivity type of synapses.

vector< unsigned int > synapseGType

Type of specification method for synaptic conductance.

vector< unsigned int > synapseSource

Presynaptic neuron groups.

vector< unsigned int > synapseTarget

Postsynaptic neuron groups.

vector< unsigned int > synapseInSynNo

IDs of the target neurons' incoming synapse variables for each synapse group.

vector< unsigned int > synapseOutSynNo

The target neurons' outgoing synapse for each synapse group.

 $\bullet \ \ \mathsf{vector} {<} \ \mathsf{bool} {>} \ \mathsf{synapseUsesTrueSpikes} \\$

Defines if synapse update is done after detection of real spikes (only one point after threshold)

vector< bool > synapseUsesSpikeEvents

Defines if synapse update is done after detection of spike events (every point above threshold)

vector< bool > synapseUsesPostLearning

Defines if anything is done in case of postsynaptic neuron spiking before presynaptic neuron (punishment in STDP etc.)

vector< vector< string >> synapseSpkEvntVars

Defines variable names that are needed in the SpkEvnt condition and that are pre-fetched for that purpose into shared memory.

vector< vector< double >> synapsePara

parameters of synapses

vector< vector< double >> synapselni

Initial values of synapse variables.

• vector< vector< double >> dsp w

Derived synapse parameters (weightUpdateModel only)

vector< unsigned int > postSynapseType

Types of post-synaptic model.

vector< vector< double > > postSynapsePara

parameters of postsynapses

vector< vector< double >> postSynIni

Initial values of postsynaptic variables.

vector< vector< double > > dpsp

Derived postsynapse parameters.

vector< double > globalInp

Global explicit input if CONSTINP is chosen.

• unsigned int IrnGroups

Number of synapse groups with learning.

vector< unsigned int > padSumLearnN

Padded summed neuron numbers of learn group source populations.

vector< unsigned int > lrnSynGrp

Enumeration of the IDs of synapse groups that learn.

vector< unsigned int > synapseDelay

Global synaptic conductance delay for the group (in time steps)

vector< int > synapseHostID

The ID of the cluster node which the synapse groups are computed on.

vector< int > synapseDeviceID

The ID of the CUDA device which the synapse groups are computed on.

14.11.1 Detailed Description

Structure to hold the information that defines synapse dynamics (a model of how synapse variables change over time, independent of or in addition to changes when spikes occur).

14.11.2 Constructor & Destructor Documentation

```
14.11.2.1 NNmodel::NNmodel ( )
```

14.11.2.2 NNmodel::~NNmodel ()

14.11.3 Member Function Documentation

14.11.3.1 void NNmodel::activateDirectInput (const string name, unsigned int type)

Method for activating explicit current input.

This function defines the type of the explicit input to the neuron model. Current options are common constant input to all neurons, input from a file and input defines as a rule.

Parameters

name	Name of the neuron population
type	Type of input: 1 if common input, 2 if custom input from file, 3 if custom input as a rule

14.11.3.2 void NNmodel::addNeuronPopulation (const char * name, unsigned int nNo, unsigned int type, double * p, double * ini)

Method for adding a neuron population to a neuronal network model, using C style character array for the name of the population.

Parameters

name	Name of the neuron population
nNo	Number of neurons in the population
type	Type of the neurons, refers to either a standard type or user-defined type
р	Parameters of this neuron type
ini	Initial values for variables of this neuron type

14.11.3.3 void NNmodel::addNeuronPopulation (const string *name*, unsigned int *nNo*, unsigned int *type*, double * *p*, double * *ini*)

Method for adding a neuron population to a neuronal network model, using C++ string for the name of the population.

Parameters

name	The name of the neuron population
nNo	Number of neurons in the population
type	Type of the neurons, refers to either a standard type or user-defined type
р	Parameters of this neuron type
ini	Initial values for variables of this neuron type

14.11.3.4 void NNmodel::addNeuronPopulation (const string *name*, unsigned int *nNo*, unsigned int *type*, vector< double > p, vector< double > ini)

Method for adding a neuron population to a neuronal network model, using C++ string for the name of the population.

This function adds a neuron population to a neuronal network models, assigning the name, the number of neurons in the group, the neuron type, parameters and initial values. The latter two defined as STL vectors of double.

Parameters

name	The name of the neuron population
nNo	Number of neurons in the population
type	Type of the neurons, refers to either a standard type or user-defined type
р	Parameters of this neuron type
ini	Initial values for variables of this neuron type

14.11.3.5 void NNmodel::addSynapsePopulation (const string *name*, unsigned int *syntype*, unsigned int *conntype*, unsigned int *gtype*, const string *src*, const string *target*, double * *params*)

Overload of method for backwards compatibility.

name	The name of the synapse population
syntype	The type of synapse to be added (i.e. learning mode)
conntype	The type of synaptic connectivity
gtype	The way how the synaptic conductivity g will be defined
src	Name of the (existing!) pre-synaptic neuron population
target	Name of the (existing!) post-synaptic neuron population
params	A C-type array of doubles that contains synapse parameter values (common to all synapses
	of the population) which will be used for the defined synapses. The array must contain the
	right number of parameters in the right order for the chosen synapse type. If too few, seg-
	mentation faults will occur, if too many, excess will be ignored.

14.11.3.6 void NNmodel::addSynapsePopulation (const char * name, unsigned int syntype, unsigned int conntype, unsigned int gtype, unsigned int delaySteps, unsigned int postsyn, const char * src, const char * trg, double * p, double * PSVini, double * ps)

Method for adding a synapse population to a neuronal network model, using C style character array for the name of the population.

Parameters

name	The name of the synapse population
syntype	The type of synapse to be added (i.e. learning mode)
conntype	The type of synaptic connectivity
gtype	The way how the synaptic conductivity g will be defined
delaySteps	Number of delay slots
postsyn	Postsynaptic integration method
src	Name of the (existing!) pre-synaptic neuron population
trg	Name of the (existing!) post-synaptic neuron population
р	A C-type array of doubles that contains synapse parameter values (common to all synapses
	of the population) which will be used for the defined synapses. The array must contain the
	right number of parameters in the right order for the chosen synapse type. If too few, seg-
	mentation faults will occur, if too many, excess will be ignored.
PSVini	A C-type array of doubles that contains the initial values for postsynaptic mechanism variables
	(common to all synapses of the population) which will be used for the defined synapses. The
	array must contain the right number of parameters in the right order for the chosen synapse
	type. If too few, segmentation faults will occur, if too many, excess will be ignored.
ps	A C-type array of doubles that contains postsynaptic mechanism parameter values (common
	to all synapses of the population) which will be used for the defined synapses. The array
	must contain the right number of parameters in the right order for the chosen synapse type.
	If too few, segmentation faults will occur, if too many, excess will be ignored.

14.11.3.7 void NNmodel::addSynapsePopulation (const string *name*, unsigned int *syntype*, unsigned int *conntype*, unsigned int *gtype*, unsigned int *delaySteps*, unsigned int *postsyn*, const string *src*, const string *trg*, double * *p*, double * *PSVini*, double * *ps*)

Overloaded version without initial variables for synapses.

Overloaded old version.

name	The name of the synapse population
syntype	The type of synapse to be added (i.e. learning mode)
conntype	The type of synaptic connectivity
gtype	The way how the synaptic conductivity g will be defined
delaySteps	Number of delay slots
postsyn	Postsynaptic integration method
src	Name of the (existing!) pre-synaptic neuron population
trg	Name of the (existing!) post-synaptic neuron population
р	A C-type array of doubles that contains synapse parameter values (common to all synapses
	of the population) which will be used for the defined synapses. The array must contain the
	right number of parameters in the right order for the chosen synapse type. If too few, seg-
	mentation faults will occur, if too many, excess will be ignored.
PSVini	A C-type array of doubles that contains the initial values for postsynaptic mechanism variables
	(common to all synapses of the population) which will be used for the defined synapses. The
	array must contain the right number of parameters in the right order for the chosen synapse
	type. If too few, segmentation faults will occur, if too many, excess will be ignored.
ps	A C-type array of doubles that contains postsynaptic mechanism parameter values (common
	to all synapses of the population) which will be used for the defined synapses. The array
	must contain the right number of parameters in the right order for the chosen synapse type.
	If too few, segmentation faults will occur, if too many, excess will be ignored.

14.11.3.8 void NNmodel::addSynapsePopulation (const string *name*, unsigned int *syntype*, unsigned int *conntype*, unsigned int *gtype*, unsigned int *delaySteps*, unsigned int *postsyn*, const string *src*, const string *trg*, double * *synini*, double * *ps*)

Method for adding a synapse population to a neuronal network model, using C++ string for the name of the population.

This function adds a synapse population to a neuronal network model, assigning the name, the synapse type, the connectivity type, the type of conductance specification, the source and destination neuron populations, and the synaptic parameters.

Parameters

The contract of the contract o
The name of the synapse population
The type of synapse to be added (i.e. learning mode)
The type of synaptic connectivity
The way how the synaptic conductivity g will be defined
Number of delay slots
Postsynaptic integration method
Name of the (existing!) pre-synaptic neuron population
Name of the (existing!) post-synaptic neuron population
A C-type array of doubles that contains the initial values for synapse variables (common to
all synapses of the population) which will be used for the defined synapses. The array must
contain the right number of parameters in the right order for the chosen synapse type. If too
few, segmentation faults will occur, if too many, excess will be ignored.
A C-type array of doubles that contains synapse parameter values (common to all synapses
of the population) which will be used for the defined synapses. The array must contain the
right number of parameters in the right order for the chosen synapse type. If too few, seg-
mentation faults will occur, if too many, excess will be ignored.
A C-type array of doubles that contains the initial values for postsynaptic mechanism variables
(common to all synapses of the population) which will be used for the defined synapses. The
array must contain the right number of parameters in the right order for the chosen synapse
type. If too few, segmentation faults will occur, if too many, excess will be ignored.
A C-type array of doubles that contains postsynaptic mechanism parameter values (common
to all synapses of the population) which will be used for the defined synapses. The array
must contain the right number of parameters in the right order for the chosen synapse type.
If too few, segmentation faults will occur, if too many, excess will be ignored.

14.11.3.9 void NNmodel::addSynapsePopulation (const string *name*, unsigned int *syntype*, unsigned int *conntype*, unsigned int *gtype*, unsigned int *delaySteps*, unsigned int *postsyn*, const string *src*, const string *trg*, vector< double > synini, vector< double > p, vector< double > PSVini, vector< double > ps)

Method for adding a synapse population to a neuronal network model, using C++ string for the name of the population.

This function adds a synapse population to a neuronal network model, assigning the name, the synapse type, the connectivity type, the type of conductance specification, the source and destination neuron populations, and the synaptic parameters.

name	The name of the synapse population
syntype	The type of synapse to be added (i.e. learning mode)
conntype	The type of synaptic connectivity
gtype	The way how the synaptic conductivity g will be defined
delaySteps	Number of delay slots

postsyn	Postsynaptic integration method
src	Name of the (existing!) pre-synaptic neuron population
trg	Name of the (existing!) post-synaptic neuron population
synini	A C-type array of doubles that contains the initial values for synapse variables (common to
	all synapses of the population) which will be used for the defined synapses. The array must
	contain the right number of parameters in the right order for the chosen synapse type. If too
	few, segmentation faults will occur, if too many, excess will be ignored.
р	A C-type array of doubles that contains synapse parameter values (common to all synapses
	of the population) which will be used for the defined synapses. The array must contain the
	right number of parameters in the right order for the chosen synapse type. If too few, seg-
	mentation faults will occur, if too many, excess will be ignored.
PSVini	A C-type array of doubles that contains the initial values for postsynaptic mechanism variables
	(common to all synapses of the population) which will be used for the defined synapses. The
	array must contain the right number of parameters in the right order for the chosen synapse
	type. If too few, segmentation faults will occur, if too many, excess will be ignored.
ps	A C-type array of doubles that contains postsynaptic mechanism parameter values (common
	to all synapses of the population) which will be used for the defined synapses. The array
	must contain the right number of parameters in the right order for the chosen synapse type.
	If too few, segmentation faults will occur, if too many, excess will be ignored.

14.11.3.10 void NNmodel::checkSizes (unsigned int * , unsigned int * , unsigned int *)

14.11.3.11 void NNmodel::finalize ()

14.11.3.12 void NNmodel::initLearnGrps ()

14.11.3.13 void NNmodel::setConstInp (const string sName, double globalInp0)

Method for setting the global input value for a neuron population if CONSTINP.

This function sets a global input value to the specified neuron group.

14.11.3.14 void NNmodel::setGPUDevice (int device)

Method to choose the GPU to be used for the model. If "AUTODEVICE' (-1), GeNN will choose the device based on a heuristic rule.

This function defines the way how the GPU is chosen. If "AUTODEVICE" (-1) is given as the argument, GeNN will use internal heuristics to choose the device. Otherwise the argument is the device number and the indicated device will be used.

14.11.3.15 void NNmodel::setMaxConn (const string sname, unsigned int maxConnP)

This function defines the maximum number of connections for a neuron in the population.

14.11.3.16 void NNmodel::setName (const string inname)

Method to set the neuronal network model name.

14.11.3.17 void NNmodel::setNeuronClusterIndex (const string neuronGroup, int hostID, int deviceID)

Function for setting which host and which device a neuron group will be simulated on.

This function is for setting which host and which device a neuron group will be simulated on.

neuronGroup	Name of the neuron population
hostID	ID of the host
deviceID	ID of the device

14.11.3.18 void NNmodel::setPrecision (unsigned int floattype)

Set numerical precision for floating point.

This function sets the numerical precision of floating type variables. By default, it is GENN GENN FLOAT.

14.11.3.19 void NNmodel::setSeed (unsigned int inseed)

Set the random seed (disables automatic seeding if argument not 0).

This function sets the random seed. If the passed argument is > 0, automatic seeding is disabled. If the argument is 0, the underlying seed is obtained from the time() function.

Parameters

inseed	the new seed

14.11.3.20 void NNmodel::setSynapseClusterIndex (const string synapseGroup, int hostID, int deviceID)

Function for setting which host and which device a synapse group will be simulated on.

This function is for setting which host and which device a synapse group will be simulated on.

Parameters

synapseGroup	Name of the synapse population
hostID	ID of the host
deviceID	ID of the device

14.11.3.21 void NNmodel::setSynapseG (const string *sName*, double *g*)

Method for setting the conductance (g) value for a synapse population with "GLOBALG" charactertistic.

This functions sets the global value of the maximal synaptic conductance for a synapse population that was idfentified as conductance specification method "GLOBALG".

14.11.3.22 void NNmodel::setTiming (bool theTiming)

Set whether timers and timing commands are to be included.

This function sets a flag to determine whether timers and timing commands are to be included in generated code.

14.11.4 Member Data Documentation

14.11.4.1 int NNmodel::chooseGPUDevice

14.11.4.2 vector<vector<double> > NNmodel::dnp

Derived neuron parameters.

 $14.11.4.3 \quad \text{vector}{<}\text{vector}{<}\text{double}{>}> \text{NNmodel}{::}\text{dpsp}$

Derived postsynapse parameters.

14.11.4.4 $vector < vector < double > NNmodel::dsp_w$

Derived synapse parameters (weightUpdateModel only)

14.11.4.5 int NNmodel::final

Flag for whether the model has been finalized.

14.11.4.6 string NNmodel::ftype

Type of floating point variables (float, double, ...; default: float)

14.11.4.7 vector<double> NNmodel::globalInp

Global explicit input if CONSTINP is chosen.

14.11.4.8 vector<vector<unsigned int>> NNmodel::inSyn

The ids of the incoming synapse groups.

14.11.4.9 unsigned int NNmodel::IrnGroups

Number of synapse groups with learning.

14.11.4.10 vector<unsigned int> NNmodel::IrnSynGrp

Enumeration of the IDs of synapse groups that learn.

14.11.4.11 vector<unsigned int> NNmodel::maxConn

Padded summed maximum number of connections for a neuron in the neuron groups.

14.11.4.12 string NNmodel::name

Name of the neuronal newtwork model.

14.11.4.13 unsigned int NNmodel::needSt

Whether last spike times are needed at all in this network model (related to STDP)

14.11.4.14 unsigned int NNmodel::needSynapseDelay

Whether delayed synapse conductance is required in the network.

14.11.4.15 vector<unsigned int> NNmodel::neuronDelaySlots

The number of slots needed in the synapse delay queues of a neuron group.

14.11.4.16 vector<int> NNmodel::neuronDeviceID

The ID of the CUDA device which the neuron groups are computed on.

14.11.4.17 unsigned int NNmodel::neuronGrpN

Number of neuron groups.

14.11.4.18 vector<int> NNmodel::neuronHostID

The ID of the cluster node which the neuron groups are computed on.

14.11.4.19 vector<vector<double>> NNmodel::neuronIni

Initial values of neurons.

14.11.4.20 vector<unsigned int> NNmodel::neuronN

Number of neurons in group.

14.11.4.21 vector < string > NNmodel::neuronName

Names of neuron groups.

14.11.4.22 vector
bool> NNmodel::neuronNeedSpkEvnt

Whether spike-like events from a group are required.

14.11.4.23 vector
bool> NNmodel::neuronNeedSt

Whether last spike time needs to be saved for a group.

14.11.4.24 vector
bool> NNmodel::neuronNeedTrueSpk

Whether spike-like events from a group are required.

 $14.11.4.25 \quad vector {<} vector {<} double {>} > NNmodel::neuronPara$

Parameters of neurons.

14.11.4.26 vector<unsigned int> NNmodel::neuronPostSyn

14.11.4.27 vector < string > NNmodel::neuronSpkEvntCondition

Will contain the spike event condition code when spike events are used.

14.11.4.28 vector<unsigned int> NNmodel::neuronType

Postsynaptic methods to the neuron.

Types of neurons

 $14.11.4.29 \quad vector{<}vector{<}bool{>} > NNmodel::neuronVarNeedQueue$

Whether a neuron variable needs queueing for syn code.

14.11.4.30 vector<vector<unsigned int>> NNmodel::outSyn

The ids of the outgoing synapse groups.

14.11.4.31 vector<unsigned int> NNmodel::padSumLearnN

Padded summed neuron numbers of learn group source populations.

 $14.11.4.32 \quad vector {<} unsigned \ int {>} \ NNmodel::padSumNeuronN$

Padded summed neuron numbers.

14.11.4.33 vector<unsigned int> NNmodel::padSumSynapseKrnl

14.11.4.34 vector<vector<double> > NNmodel::postSynapsePara

parameters of postsynapses

 $14.11.4.35 \quad \text{vector}{<} \text{unsigned int}{>} \, \text{NNmodel::postSynapseType}$

Types of post-synaptic model.

14.11.4.36 vector<vector<double>> NNmodel::postSynIni

Initial values of postsynaptic variables.

14.11.4.37 vector < unsigned int > NNmodel::receivesInputCurrent

flags whether neurons of a population receive explicit input currents

14.11.4.38 string NNmodel::RNtype

Underlying type for random number generation (default: long)

14.11.4.39 unsigned int NNmodel::seed

14.11.4.40 vector < unsigned int > NNmodel::sumNeuronN

Summed neuron numbers.

14.11.4.41 vector<unsigned int> NNmodel::synapseConnType

Connectivity type of synapses.

14.11.4.42 vector<unsigned int> NNmodel::synapseDelay

Global synaptic conductance delay for the group (in time steps)

14.11.4.43 vector<int> NNmodel::synapseDeviceID

The ID of the CUDA device which the synapse groups are computed on.

14.11.4.44 unsigned int NNmodel::synapseGrpN

Number of synapse groups.

14.11.4.45 vector<unsigned int> NNmodel::synapseGType

Type of specification method for synaptic conductance.

14.11.4.46 vector<int> NNmodel::synapseHostID

The ID of the cluster node which the synapse groups are computed on.

 $14.11.4.47 \quad vector < vector < double >> NNmodel::synapselni$

Initial values of synapse variables.

14.11.4.48 vector<unsigned int> NNmodel::synapselnSynNo

IDs of the target neurons' incoming synapse variables for each synapse group.

14.11.4.49 vector < string > NNmodel::synapseName

Names of synapse groups.

14.11.4.50 vector<unsigned int> NNmodel::synapseOutSynNo

The target neurons' outgoing synapse for each synapse group.

14.11.4.51 vector<vector<double>> NNmodel::synapsePara

parameters of synapses

14.11.4.52 vector<unsigned int> NNmodel::synapseSource

Presynaptic neuron groups.

14.11.4.53 vector<vector<string>> NNmodel::synapseSpkEvntVars

Defines variable names that are needed in the SpkEvnt condition and that are pre-fetched for that purpose into shared memory.

14.11.4.54 vector<unsigned int> NNmodel::synapseTarget

Postsynaptic neuron groups.

14.11.4.55 vector<unsigned int> NNmodel::synapseType

Types of synapses.

14.11.4.56 vector < bool > NNmodel::synapseUsesPostLearning

Defines if anything is done in case of postsynaptic neuron spiking before presynaptic neuron (punishment in STDP etc.)

14.11.4.57 vector
bool> NNmodel::synapseUsesSpikeEvents

Defines if synapse update is done after detection of spike events (every point above threshold)

14.11.4.58 vector
bool> NNmodel::synapseUsesTrueSpikes

Defines if synapse update is done after detection of real spikes (only one point after threshold)

14.11.4.59 bool NNmodel::timing

The documentation for this class was generated from the following files:

- modelSpec.h
- · modelSpec.cc

14.12 Parameter Struct Reference

Public Attributes

- string name
- · string value

14.12.1 Member Data Documentation

14.12.1.1 string Parameter::name

14.12.1.2 string Parameter::value

The documentation for this struct was generated from the following file:

· experiment.cu

14.13 postSynModel Struct Reference

Structure to hold the information that defines a post-synaptic model (a model of how synapses affect post-synaptic neuron variables, classically in the form of a synaptic current). It also allows to define an equation for the dynamics that can be applied to the summed synaptic input variable "insyn".

#include <modelSpec.h>

Public Attributes

string postSyntoCurrent

Code that defines how postsynaptic update is translated to current.

string postSynDecay

Code that defines how postsynaptic current decays.

vector< string > varNames

Names of the variables in the postsynaptic model.

vector< string > varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

vector< string > pNames

Names of (independent) parameters of the model.

vector< string > dpNames

Names of dependent parameters of the model.

· dpclass * dps

Derived parameters.

14.13.1 Detailed Description

Structure to hold the information that defines a post-synaptic model (a model of how synapses affect post-synaptic neuron variables, classically in the form of a synaptic current). It also allows to define an equation for the dynamics that can be applied to the summed synaptic input variable "insyn".

14.13.2 Member Data Documentation

14.13.2.1 vector<string> postSynModel::dpNames

Names of dependent parameters of the model.

14.13.2.2 dpclass* postSynModel::dps

Derived parameters.

14.13.2.3 vector<string> postSynModel::pNames

Names of (independent) parameters of the model.

14.13.2.4 string postSynModel::postSynDecay

Code that defines how postsynaptic current decays.

14.13.2.5 string postSynModel::postSyntoCurrent

Code that defines how postsynaptic update is translated to current.

14.13.2.6 vector<string> postSynModel::varNames

Names of the variables in the postsynaptic model.

14.13.2.7 vector<string> postSynModel::varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

The documentation for this struct was generated from the following file:

modelSpec.h

14.14 postVarsInPostLearn Class Reference

```
#include <testPostVarsInPostLearn.h>
```

Public Member Functions

- postVarsInPostLearn ()
- ~postVarsInPostLearn ()
- void init_synapses ()
- void init_neurons ()
- void run (float, int)

Public Attributes

float ** theW

14.14.1 Constructor & Destructor Documentation

```
14.14.1.1 postVarsInPostLearn::postVarsInPostLearn()
```

- 14.14.1.2 postVarsInPostLearn::~postVarsInPostLearn()
- 14.14.2 Member Function Documentation
- 14.14.2.1 void postVarsInPostLearn::init_neurons ()
- 14.14.2.2 void postVarsInPostLearn::init_synapses ()
- 14.14.2.3 void postVarsInPostLearn::run (float t, int which)
- 14.14.3 Member Data Documentation
- 14.14.3.1 float** postVarsInPostLearn::theW

The documentation for this class was generated from the following files:

- testPostVarsInPostLearn.h
- testPostVarsInPostLearn.cu

14.15 postVarsInPostLearn_sparse Class Reference

```
#include <testPostVarsInPostLearn_sparse.h>
```

Public Member Functions

- postVarsInPostLearn_sparse ()
- ~postVarsInPostLearn_sparse ()
- void init_synapses ()
- void init_neurons ()
- void run (float, int)

Public Attributes

float ** theW

```
14.15.1 Constructor & Destructor Documentation
14.15.1.1 postVarsInPostLearn_sparse::postVarsInPostLearn_sparse ( )
14.15.1.2 postVarsInPostLearn_sparse::~postVarsInPostLearn_sparse( )
14.15.2 Member Function Documentation
14.15.2.1 void postVarsInPostLearn_sparse::init_neurons()
14.15.2.2 void postVarsInPostLearn_sparse::init_synapses ( )
14.15.2.3 void postVarsInPostLearn_sparse::run ( float t, int which )
14.15.3 Member Data Documentation
14.15.3.1 float** postVarsInPostLearn_sparse::theW
The documentation for this class was generated from the following files:

    testPostVarsInPostLearn_sparse.h

    • testPostVarsInPostLearn_sparse.cu
14.16 postVarsInSimCode Class Reference
#include <testPostVarsInSimCode.h>
Public Member Functions

    postVarsInSimCode ()

    ~postVarsInSimCode ()

    • void init synapses ()
    · void init_neurons ()
    • void run (float, int)
Public Attributes
    float ** theW
14.16.1 Constructor & Destructor Documentation
14.16.1.1 postVarsInSimCode::postVarsInSimCode ( )
14.16.1.2 postVarsInSimCode::~postVarsInSimCode( )
14.16.2 Member Function Documentation
14.16.2.1 void postVarsInSimCode::init_neurons ( )
14.16.2.2 void postVarsInSimCode::init_synapses ( )
```

14.16.3 Member Data Documentation

14.16.2.3 void postVarsInSimCode::run (float t, int which)

14.16.3.1 float** postVarsInSimCode::theW

The documentation for this class was generated from the following files:

- · testPostVarsInSimCode.h
- testPostVarsInSimCode.cu

14.17 postVarsInSimCode_sparse Class Reference

```
#include <testPostVarsInSimCode_sparse.h>
```

Public Member Functions

- postVarsInSimCode_sparse ()
- ~postVarsInSimCode_sparse ()
- void init_synapses ()
- void init neurons ()
- · void run (float, int)

Public Attributes

float ** theW

14.17.1 Constructor & Destructor Documentation

```
14.17.1.1 postVarsInSimCode_sparse::postVarsInSimCode_sparse( )
```

- 14.17.1.2 postVarsInSimCode_sparse::~postVarsInSimCode_sparse()
- 14.17.2 Member Function Documentation
- 14.17.2.1 void postVarsInSimCode_sparse::init_neurons ()
- 14.17.2.2 void postVarsInSimCode_sparse::init_synapses ()
- 14.17.2.3 void postVarsInSimCode_sparse::run (float t, int which)
- 14.17.3 Member Data Documentation
- 14.17.3.1 float** postVarsInSimCode_sparse::theW

The documentation for this class was generated from the following files:

- testPostVarsInSimCode_sparse.h
- testPostVarsInSimCode_sparse.cu

14.18 postVarsInSynapseDynamics Class Reference

#include <testPostVarsInSynapseDynamics.h>

Public Member Functions

- postVarsInSynapseDynamics ()
- ∼postVarsInSynapseDynamics ()
- void init_synapses ()
- void init_neurons ()
- · void run (float, int)

Public Attributes

float ** theW

14.18.1 Constructor & Destructor Documentation

```
14.18.1.1 postVarsInSynapseDynamics::postVarsInSynapseDynamics ( )
```

```
14.18.1.2 postVarsInSynapseDynamics::~postVarsInSynapseDynamics()
```

14.18.2 Member Function Documentation

```
14.18.2.1 void postVarsInSynapseDynamics::init_neurons ( )
```

14.18.2.2 void postVarsInSynapseDynamics::init_synapses ()

14.18.2.3 void postVarsInSynapseDynamics::run (float t, int which)

14.18.3 Member Data Documentation

14.18.3.1 float** postVarsInSynapseDynamics::theW

The documentation for this class was generated from the following files:

- testPostVarsInSynapseDynamics.h
- testPostVarsInSynapseDynamics.cu

14.19 postVarsInSynapseDynamics sparse Class Reference

```
#include <testPostVarsInSynapseDynamics_sparse.h>
```

Public Member Functions

- postVarsInSynapseDynamics_sparse ()
- ~postVarsInSynapseDynamics_sparse ()
- · void init_synapses ()
- void init_neurons ()
- · void run (float, int)

Public Attributes

float ** theW

```
14.19.1 Constructor & Destructor Documentation
14.19.1.1 postVarsInSynapseDynamics_sparse::postVarsInSynapseDynamics_sparse ( )
14.19.1.2 postVarsInSynapseDynamics_sparse::~postVarsInSynapseDynamics_sparse ( )
14.19.2 Member Function Documentation
14.19.2.1 void postVarsInSynapseDynamics_sparse::init_neurons ( )
14.19.2.2 void postVarsInSynapseDynamics_sparse::init_synapses ( )
14.19.2.3 void postVarsInSynapseDynamics_sparse::run ( float t, int which )
14.19.3 Member Data Documentation
14.19.3.1 float** postVarsInSynapseDynamics_sparse::theW
The documentation for this class was generated from the following files:
    testPostVarsInSynapseDynamics_sparse.h
    • testPostVarsInSynapseDynamics_sparse.cu
14.20 preVarsInPostLearn Class Reference
#include <testPreVarsInPostLearn.h>
Public Member Functions

    preVarsInPostLearn ()

    ~preVarsInPostLearn ()

    • void init synapses ()
    · void init_neurons ()
    • void run (float, int)
Public Attributes
    float ** theW
14.20.1 Constructor & Destructor Documentation
14.20.1.1 preVarsInPostLearn::preVarsInPostLearn()
14.20.1.2 preVarsInPostLearn::~preVarsInPostLearn()
14.20.2 Member Function Documentation
14.20.2.1 void preVarsInPostLearn::init_neurons ( )
14.20.2.2 void preVarsInPostLearn::init_synapses ( )
14.20.2.3 void preVarsInPostLearn::run ( float t, int which )
```

14.20.3 Member Data Documentation

```
14.20.3.1 float** preVarsInPostLearn::theW
```

The documentation for this class was generated from the following files:

- · testPreVarsInPostLearn.h
- testPreVarsInPostLearn.cu

14.21 preVarsInPostLearn_sparse Class Reference

```
#include <testPreVarsInPostLearn_sparse.h>
```

Public Member Functions

- preVarsInPostLearn_sparse ()
- ∼preVarsInPostLearn_sparse ()
- void init_synapses ()
- void init neurons ()
- · void run (float, int)

Public Attributes

float ** theW

14.21.1 Constructor & Destructor Documentation

```
14.21.1.1 preVarsInPostLearn_sparse::preVarsInPostLearn_sparse ( )
```

- 14.21.1.2 preVarsInPostLearn_sparse::~preVarsInPostLearn_sparse()
- 14.21.2 Member Function Documentation
- 14.21.2.1 void preVarsInPostLearn_sparse::init_neurons ()
- 14.21.2.2 void preVarsInPostLearn_sparse::init_synapses ()
- 14.21.2.3 void preVarsInPostLearn_sparse::run (float t, int which)
- 14.21.3 Member Data Documentation
- 14.21.3.1 float** preVarsInPostLearn_sparse::theW

The documentation for this class was generated from the following files:

- testPreVarsInPostLearn sparse.h
- · testPreVarsInPostLearn_sparse.cu

14.22 preVarsInSimCode Class Reference

#include <testPreVarsInSimCode.h>

Public Member Functions

- preVarsInSimCode ()
- ∼preVarsInSimCode ()
- void init_synapses ()
- void init_neurons ()
- · void run (float, int)

Public Attributes

float ** theW

```
14.22.1 Constructor & Destructor Documentation
```

```
14.22.1.1 preVarsInSimCode::preVarsInSimCode()
```

- 14.22.1.2 preVarsInSimCode::~preVarsInSimCode()
- 14.22.2 Member Function Documentation
- 14.22.2.1 void preVarsInSimCode::init_neurons ()
- 14.22.2.2 void preVarsInSimCode::init_synapses ()
- 14.22.2.3 void preVarsInSimCode::run (float t, int which)
- 14.22.3 Member Data Documentation
- 14.22.3.1 float** preVarsInSimCode::theW

The documentation for this class was generated from the following files:

- testPreVarsInSimCode.h
- testPreVarsInSimCode.cu

14.23 preVarsInSimCode_sparse Class Reference

```
#include <testPreVarsInSimCode_sparse.h>
```

Public Member Functions

- preVarsInSimCode_sparse ()
- \sim preVarsInSimCode_sparse ()
- void init_synapses ()
- void init_neurons ()
- void run (float, int)

Public Attributes

float ** theW

```
14.23.1 Constructor & Destructor Documentation
14.23.1.1 preVarsInSimCode_sparse::preVarsInSimCode_sparse( )
14.23.1.2 preVarsInSimCode_sparse::~preVarsInSimCode_sparse( )
14.23.2 Member Function Documentation
14.23.2.1 void preVarsInSimCode_sparse::init_neurons()
14.23.2.2 void preVarsInSimCode_sparse::init_synapses ( )
14.23.2.3 void preVarsInSimCode_sparse::run ( float t, int which )
14.23.3 Member Data Documentation
14.23.3.1 float** preVarsInSimCode_sparse::theW
The documentation for this class was generated from the following files:

    testPreVarsInSimCode_sparse.h

    • testPreVarsInSimCode_sparse.cu
14.24 preVarsInSynapseDynamics Class Reference
#include <testPreVarsInSynapseDynamics.h>
Public Member Functions

    preVarsInSynapseDynamics ()

    ∼preVarsInSynapseDynamics ()

    • void init synapses ()
    • void init_neurons ()
    • void run (float, int)
Public Attributes
    float ** theW
14.24.1 Constructor & Destructor Documentation
14.24.1.1 preVarsInSynapseDynamics::preVarsInSynapseDynamics ( )
14.24.1.2 preVarsInSynapseDynamics::~preVarsInSynapseDynamics()
14.24.2 Member Function Documentation
14.24.2.1 void preVarsInSynapseDynamics::init_neurons ( )
14.24.2.2 void preVarsInSynapseDynamics::init_synapses ( )
14.24.2.3 void preVarsInSynapseDynamics::run ( float t, int which )
```

14.24.3 Member Data Documentation

14.24.3.1 float** preVarsInSynapseDynamics::theW

The documentation for this class was generated from the following files:

- testPreVarsInSynapseDynamics.h
- testPreVarsInSynapseDynamics.cu

14.25 preVarsInSynapseDynamics_sparse Class Reference

```
#include <testPreVarsInSynapseDynamics_sparse.h>
```

Public Member Functions

- preVarsInSynapseDynamics_sparse ()
- ~preVarsInSynapseDynamics_sparse ()
- void init_synapses ()
- void init_neurons ()
- · void run (float, int)

Public Attributes

float ** theW

```
14.25.1 Constructor & Destructor Documentation
```

```
14.25.1.1 preVarsInSynapseDynamics_sparse::preVarsInSynapseDynamics_sparse( )
```

- 14.25.1.2 preVarsInSynapseDynamics_sparse::~preVarsInSynapseDynamics_sparse ()
- 14.25.2 Member Function Documentation
- 14.25.2.1 void preVarsInSynapseDynamics_sparse::init_neurons ()
- 14.25.2.2 void preVarsInSynapseDynamics_sparse::init_synapses ()
- 14.25.2.3 void preVarsInSynapseDynamics_sparse::run (float t, int which)
- 14.25.3 Member Data Documentation
- $14.25.3.1 \quad float**preVarsInSynapseDynamics_sparse::theW$

The documentation for this class was generated from the following files:

- testPreVarsInSynapseDynamics_sparse.h
- testPreVarsInSynapseDynamics_sparse.cu

14.26 pwSTDP Class Reference

TODO This class definition may be code-generated in a future release.

```
#include <utils.h>
```

Inheritance diagram for pwSTDP:



Public Member Functions

- double calculateDerivedParameter (int index, vector< double > pars, double dt)
- double lim0 (vector< double > pars, double dt)
- double lim1 (vector< double > pars, double dt)
- double slope0 (vector< double > pars, double dt)
- double slope1 (vector< double > pars, double dt)
- double off0 (vector< double > pars, double dt)
- double off1 (vector< double > pars, double dt)
- double off2 (vector< double > pars, double dt)

14.26.1 Detailed Description

TODO This class definition may be code-generated in a future release.

This class defines derived parameters for the learn1synapse standard weightupdate model

14.26.2 Member Function Documentation

```
14.26.2.1 double pwSTDP::calculateDerivedParameter ( int index, vector< double > pars, double dt ) [inline], [virtual]
```

Reimplemented from dpclass.

```
14.26.2.2 double pwSTDP::lim0 ( vector < double > pars, double dt ) [inline]
14.26.2.3 double pwSTDP::lim1 ( vector < double > pars, double dt ) [inline]
14.26.2.4 double pwSTDP::off0 ( vector < double > pars, double dt ) [inline]
14.26.2.5 double pwSTDP::off1 ( vector < double > pars, double dt ) [inline]
14.26.2.6 double pwSTDP::off2 ( vector < double > pars, double dt ) [inline]
14.26.2.7 double pwSTDP::slope0 ( vector < double > pars, double dt ) [inline]
14.26.2.8 double pwSTDP::slope1 ( vector < double > pars, double dt ) [inline]
```


The documentation for this class was generated from the following file:

utils.h

14.27 pwSTDP_userdef Class Reference

TODO This class definition may be code-generated in a future release.

Inheritance diagram for pwSTDP_userdef:



Public Member Functions

- double calculateDerivedParameter (int index, vector< double > pars, double dt=DT)
- double lim0 (vector< double > pars, double dt)
- double lim1 (vector< double > pars, double dt)
- double slope0 (vector< double > pars, double dt)
- double slope1 (vector< double > pars, double dt)
- double off0 (vector< double > pars, double dt)
- double off1 (vector< double > pars, double dt)
- double off2 (vector< double > pars, double dt)

14.27.1 Detailed Description

TODO This class definition may be code-generated in a future release.

14.27.2 Member Function Documentation

```
14.27.2.1 double pwSTDP_userdef::calculateDerivedParameter ( int index, vector < double > pars, double dt = DT )
[inline], [virtual]
```

Reimplemented from dpclass.

```
14.27.2.2 double pwSTDP_userdef::lim0 ( vector < double > pars, double dt ) [inline]
14.27.2.3 double pwSTDP_userdef::lim1 ( vector < double > pars, double dt ) [inline]
14.27.2.4 double pwSTDP_userdef::off0 ( vector < double > pars, double dt ) [inline]
14.27.2.5 double pwSTDP_userdef::off1 ( vector < double > pars, double dt ) [inline]
14.27.2.6 double pwSTDP_userdef::off2 ( vector < double > pars, double dt ) [inline]
14.27.2.7 double pwSTDP_userdef::slope0 ( vector < double > pars, double dt ) [inline]
14.27.2.8 double pwSTDP_userdef::slope1 ( vector < double > pars, double dt ) [inline]
```

The documentation for this class was generated from the following file:

• MBody_userdef.cc

14.28 randomGauss Class Reference

Class random Gauss encapsulates the methods for generating random neumbers with Gaussian distribution.

```
#include <gauss.h>
```

Public Member Functions

randomGauss ()

Constructor for the Gaussian random number generator class without giving explicit seeds.

• randomGauss (unsigned long, unsigned long, unsigned long)

Constructor for the Gaussian random number generator class when seeds are provided explicitly.

- ∼randomGauss ()
- double n ()

Method for obtaining a random number with Gaussian distribution.

void srand (unsigned long, unsigned long, unsigned long)

Function for seeding with fixed seeds.

14.28.1 Detailed Description

Class random Gauss encapsulates the methods for generating random neumbers with Gaussian distribution.

A random number from a Gaussian distribution of mean 0 and standard deviation 1 is obtained by calling the method randomGauss::n().

14.28.2 Constructor & Destructor Documentation

```
14.28.2.1 randomGauss::randomGauss() [explicit]
```

Constructor for the Gaussian random number generator class without giving explicit seeds.

The seeds for random number generation are generated from the internal clock of the computer during execution.

```
14.28.2.2 randomGauss::randomGauss ( unsigned long seed1, unsigned long seed2, unsigned long seed3 )
```

Constructor for the Gaussian random number generator class when seeds are provided explicitly.

The seeds are three arbitrary unsigned long integers.

```
14.28.2.3 randomGauss::∼randomGauss ( ) [inline]14.28.3 Member Function Documentation
```

Method for obtaining a random number with Gaussian distribution.

Function for generating a pseudo random number from a Gaussian distribution.

14.28.3.2 void randomGauss::srand (unsigned long seed1, unsigned long seed2, unsigned long seed3)

Function for seeding with fixed seeds.

14.28.3.1 double randomGauss::n()

The documentation for this class was generated from the following files:

- · gauss.h
- gauss.cc

14.29 randomGen Class Reference

Class randomGen which implements the ISAAC random number generator for uniformely distributed random numbers.

```
#include <randomGen.h>
```

Public Member Functions

· randomGen ()

Constructor for the ISAAC random number generator class without giving explicit seeds.

• randomGen (unsigned long, unsigned long, unsigned long)

Constructor for the Gaussian random number generator class when seeds are provided explicitly.

- ∼randomGen ()
- double n ()

Method to obtain a random number from a uniform ditribution on [0,1].

void srand (unsigned long, unsigned long, unsigned long)

Function for seeding with fixed seeds.

14.29.1 Detailed Description

Class randomGen which implements the ISAAC random number generator for uniformely distributed random numbers

The random number generator initializes with system timea or explicit seeds and returns a random number according to a uniform distribution on [0,1]; making use of the ISAAC random number generator; C++ Implementation by Quinn Tyler Jackson of the RG invented by Bob Jenkins Jr.

14.29.2 Constructor & Destructor Documentation

```
14.29.2.1 randomGen::randomGen() [explicit]
```

Constructor for the ISAAC random number generator class without giving explicit seeds.

The seeds for random number generation are generated from the internal clock of the computer during execution.

```
14.29.2.2 randomGen::randomGen ( unsigned long seed1, unsigned long seed2, unsigned long seed3)
```

Constructor for the Gaussian random number generator class when seeds are provided explicitly.

The seeds are three arbitrary unsigned long integers.

```
14.29.2.3 randomGen::∼randomGen() [inline]14.29.3 Member Function Documentation14.29.3.1 double randomGen::n()
```

Method to obtain a random number from a uniform ditribution on [0,1].

Function for generating a pseudo random number from a uniform distribution on the interval [0,1].

```
14.29.3.2 void randomGen::srand ( unsigned long seed1, unsigned long seed2, unsigned long seed3 )
```

Function for seeding with fixed seeds.

The documentation for this class was generated from the following files:

- · randomGen.h
- · randomGen.cc

14.30 rulkovdp Class Reference

Class defining the dependent parameters of teh Rulkov map neuron.

```
#include <utils.h>
```

Inheritance diagram for rulkovdp:



Public Member Functions

- double calculateDerivedParameter (int index, vector< double > pars, double dt=1.0)
- double ip0 (vector< double > pars)
- double ip1 (vector< double > pars)
- double ip2 (vector< double > pars)

14.30.1 Detailed Description

Class defining the dependent parameters of teh Rulkov map neuron.

14.30.2 Member Function Documentation

```
14.30.2.1 double rulkovdp::calculateDerivedParameter ( int index, vector < double > pars, double dt = 1.0 ) [inline], [virtual]
```

Reimplemented from dpclass.

```
14.30.2.2 double rulkovdp::ip0 ( vector < double > pars ) [inline]
14.30.2.3 double rulkovdp::ip1 ( vector < double > pars ) [inline]
14.30.2.4 double rulkovdp::ip2 ( vector < double > pars ) [inline]
```

The documentation for this class was generated from the following file:

· utils.h

14.31 Schmuker2014_classifier Class Reference

This class cpontains the methods for running the Schmuker_2014_classifier example model.

```
#include <Schmuker2014_classifier.h>
```

Public Types

enum data_type { data_type_int, data_type_uint, data_type_float, data_type_double }

Public Member Functions

- Schmuker2014_classifier ()
- ∼Schmuker2014 classifier ()
- · void allocateHostAndDeviceMemory ()
- void populateDeviceMemory ()
- void update_input_data_on_device ()
- void clearDownDevice ()

- · void run (float runtime, string filename_rasterPlot, bool usePlasticity)
- void getSpikesFromGPU ()
- void getSpikeNumbersFromGPU ()
- void outputSpikes (FILE *, string delim)
- void initialiseWeights_SPARSE_RN_PN ()
- · void initialiseWeights WTA PN PN ()
- void initialiseWeights_DENSE_PN_AN ()
- void initialiseWeights_WTA_AN_AN ()
- void createWTAConnectivity (float *synapse, UINT populationSize, UINT clusterSize, float synapseWeight, float probability)
- bool randomEventOccurred (float probability)
- void updateWeights_PN_AN_on_device ()
- · void generate or load inputrates dataset (unsigned int recordingIdx)
- void generate_inputrates_dataset (unsigned int recordingldx)
- FILE * openRecordingFile (UINT recordingIndex)
- void applyLearningRuleSynapses (float *synapsesPNAN)
- void initialiseInputData ()
- void load_VR_data ()
- void setCorrectClass (UINT recordingIdx)
- UINT getClassCluster (UINT anldx)
- · void loadClassLabels ()
- void addInputRate (float *samplePoint, UINT timeStep)
- uint64_t convertToRateCode (float inputRateHz)
- float calculateVrResponse (float *samplePoint, float *vrPoint)
- void setMaxMinSampleDistances ()
- void findMaxMinSampleDistances (float *samples, UINT startAt, UINT totalSamples)
- float getSampleDistance (UINT max0_min1)
- float getManhattanDistance (float *pointA, float *pointB, UINT numElements)
- float getRand0to1 ()
- UINT calculateOverallWinner ()
- UINT calculateWinner (unsigned int *clusterSpikeCount)
- UINT calculateCurrentWindowWinner ()
- · void updateIndividualSpikeCountPN ()
- · void resetIndividualSpikeCountPN ()
- void updateClusterSpikeCountAN ()
- void resetClusterSpikeCountAN ()
- void resetOverallWinner ()
- void updateWeights_PN_AN ()
- UINT getClusterIndex (UINT neuronIndex, UINT clusterSize)
- void generateSimulatedTimeSeriesData ()
- string getRecordingFilename (UINT recordingIdx)
- bool loadArrayFromTextFile (string path, void *array, string delim, UINT arrayLen, data_type dataType)
- void checkContents (string title, void *array, UINT howMany, UINT displayPerLine, data_type dataType, UINT decimalPoints)
- void checkContents (string title, void *array, UINT howMany, UINT displayPerLine, data_type dataType, UINT decimalPoints, string delim)
- void printSeparator ()
- · void resetDevice ()
- void startLog ()

Public Attributes

- double d_maxRandomNumber
- · float t
- NNmodel model
- uint64 t * inputRates
- · unsigned int inputRatesSize
- float * vrData
- unsigned int * classLabel
- unsigned int * individualSpikeCountPN
- unsigned int * overallWinnerSpikeCountAN
- unsigned int * clusterSpikeCountAN
- float * plasticWeights
- uint64_t * d_inputRates
- unsigned int countRN
- unsigned int countPN
- · unsigned int countAN
- unsigned int countPNAN
- float * sampleDistance
- · string recordingsDir
- · string cacheDir
- · string outputDir
- · string datasetName
- · string uniqueRunId
- UINT correctClass
- · int winningClass
- FILE * log
- UINT param_SPIKING_ACTIVITY_THRESHOLD_HZ
- UINT param_MAX_FIRING_RATE_HZ
- UINT param_MIN_FIRING_RATE_HZ
- · float param GLOBAL WEIGHT SCALING
- float param WEIGHT RN PN
- float param_CONNECTIVITY_RN_PN
- float param_WEIGHT_WTA_PN_PN
- float param_WEIGHT_WTA_AN_AN
- float param_CONNECTIVITY_PN_PN
- float param_CONNECTIVITY_AN_AN
- float param_CONNECTIVITY_PN_AN
- float param_MIN_WEIGHT_PN_AN
- · float param MAX WEIGHT PN AN
- float param_WEIGHT_DELTA_PN_AN
- float param_PLASTICITY_INTERVAL_MS
- bool clearedDownDevice

Static Public Attributes

• static const unsigned int timestepsPerRecording = RECORDING_TIME_MS / DT

14.31.1 Detailed Description

This class cpontains the methods for running the Schmuker_2014_classifier example model.

```
14.31.2 Member Enumeration Documentation
 14.31.2.1 enum Schmuker2014_classifier::data_type
Enumerator
     data_type_int
     data_type_uint
     data_type_float
      data_type_double
 14.31.3 Constructor & Destructor Documentation
 14.31.3.1 Schmuker2014_classifier::Schmuker2014_classifier( )
 14.31.3.2 Schmuker2014_classifier:: ~Schmuker2014_classifier ( )
 14.31.4 Member Function Documentation
 14.31.4.1 void Schmuker2014 classifier::addInputRate ( float * samplePoint, UINT timeStep )
 14.31.4.2 void Schmuker2014_classifier::allocateHostAndDeviceMemory ( )
 14.31.4.3 void Schmuker2014_classifier::applyLearningRuleSynapses ( float * synapsesPNAN )
 14.31.4.4 UINT Schmuker2014_classifier::calculateCurrentWindowWinner()
 14.31.4.5 UINT Schmuker2014_classifier::calculateOverallWinner( )
 14.31.4.6 float Schmuker2014 classifier::calculateVrResponse ( float * samplePoint, float * vrPoint )
 14.31.4.7 UINT Schmuker2014_classifier::calculateWinner ( unsigned int * clusterSpikeCount )
 14.31.4.8 void Schmuker2014_classifier::checkContents ( string title, void * array, UINT howMany, UINT displayPerLine,
           data_type dataType, UINT decimalPoints )
 14.31.4.9 void Schmuker2014_classifier::checkContents ( string title, void * array, UINT howMany, UINT displayPerLine,
           data_type dataType, UINT decimalPoints, string delim )
 14.31.4.10 void Schmuker2014_classifier::clearDownDevice ( )
 14.31.4.11 uint64_t Schmuker2014_classifier::convertToRateCode ( float inputRateHz )
 14.31.4.12 void Schmuker2014_classifier::createWTAConnectivity ( float * synapse, UINT populationSize, UINT clusterSize,
            float synapseWeight, float probability )
 14.31.4.13 void Schmuker2014_classifier::findMaxMinSampleDistances ( float * samples, UINT startAt, UINT totalSamples )
 14.31.4.14 void Schmuker2014_classifier::generate_inputrates_dataset ( unsigned int recordingldx )
 14.31.4.15 void Schmuker2014_classifier::generate_or_load_inputrates_dataset ( unsigned int recordingldx )
 14.31.4.16 void Schmuker2014_classifier::generateSimulatedTimeSeriesData ( )
 14.31.4.17 UINT Schmuker2014_classifier::getClassCluster ( UINT anldx )
 14.31.4.18 UINT Schmuker2014_classifier::getClusterIndex ( UINT neuronIndex, UINT clusterSize )
 14.31.4.19 float Schmuker2014_classifier::getManhattanDistance (float * pointA, float * pointB, UINT numElements)
```

```
14.31.4.20
           float Schmuker2014_classifier::getRand0to1 ( )
14.31.4.21
           string Schmuker2014_classifier::getRecordingFilename ( UINT recordingIdx )
14.31.4.22
           float Schmuker2014_classifier::getSampleDistance ( UINT max0_min1 )
14.31.4.23
           void Schmuker2014_classifier::getSpikeNumbersFromGPU ( )
14.31.4.24
           void Schmuker2014_classifier::getSpikesFromGPU ( )
14.31.4.25 void Schmuker2014_classifier::initialiseInputData ( )
14.31.4.26 void Schmuker2014_classifier::initialiseWeights_DENSE_PN_AN ( )
14.31.4.27 void Schmuker2014_classifier::initialiseWeights_SPARSE_RN_PN ( )
14.31.4.28 void Schmuker2014_classifier::initialiseWeights_WTA_AN_AN ( )
14.31.4.29 void Schmuker2014_classifier::initialiseWeights_WTA_PN_PN()
14.31.4.30 void Schmuker2014_classifier::load_VR_data( )
           bool Schmuker2014_classifier::loadArrayFromTextFile ( string path, void * array, string delim, UINT arrayLen,
14.31.4.31
           data_type dataType )
14.31.4.32 void Schmuker2014_classifier::loadClassLabels ( )
14.31.4.33 FILE * Schmuker2014_classifier::openRecordingFile ( UINT recordingIndex )
14.31.4.34 void Schmuker2014_classifier::outputSpikes (FILE * f, string delim )
14.31.4.35 void Schmuker2014_classifier::populateDeviceMemory ( )
14.31.4.36 void Schmuker2014_classifier::printSeparator()
14.31.4.37 bool Schmuker2014_classifier::randomEventOccurred ( float probability )
14.31.4.38 void Schmuker2014_classifier::resetClusterSpikeCountAN ( )
14.31.4.39 void Schmuker2014_classifier::resetDevice ( )
14.31.4.40 void Schmuker2014_classifier::resetIndividualSpikeCountPN()
14.31.4.41 void Schmuker2014_classifier::resetOverallWinner()
14.31.4.42 void Schmuker2014_classifier::run ( float runtime, string filename_rasterPlot, bool usePlasticity )
14.31.4.43 void Schmuker2014_classifier::setCorrectClass ( UINT recordingldx )
14.31.4.44 void Schmuker2014_classifier::setMaxMinSampleDistances ( )
14.31.4.45 void Schmuker2014_classifier::startLog ( )
14.31.4.46 void Schmuker2014_classifier::update_input_data_on_device ( )
14.31.4.47 void Schmuker2014_classifier::updateClusterSpikeCountAN ( )
14.31.4.48 void Schmuker2014_classifier::updateIndividualSpikeCountPN ( )
14.31.4.49 void Schmuker2014_classifier::updateWeights_PN_AN ( )
14.31.4.50 void Schmuker2014_classifier::updateWeights_PN_AN_on_device ( )
```

14.31.5	Member	Data	Documentation
---------	--------	------	---------------

14.31.5.1	string Schmuker2014_classifier::cacheDir
14.31.5.2	unsigned int* Schmuker2014_classifier::classLabel
14.31.5.3	bool Schmuker2014_classifier::clearedDownDevice
14.31.5.4	unsigned int* Schmuker2014_classifier::clusterSpikeCountAN
14.31.5.5	UINT Schmuker2014_classifier::correctClass
14.31.5.6	unsigned int Schmuker2014_classifier::countAN
14.31.5.7	unsigned int Schmuker2014_classifier::countPN
14.31.5.8	unsigned int Schmuker2014_classifier::countPNAN
14.31.5.9	unsigned int Schmuker2014_classifier::countRN
14.31.5.10	uint64_t* Schmuker2014_classifier::d_inputRates
14.31.5.11	double Schmuker2014_classifier::d_maxRandomNumber
14.31.5.12	string Schmuker2014_classifier::datasetName
14.31.5.13	unsigned int* Schmuker2014_classifier::individualSpikeCountPN
14.31.5.14	uint64_t* Schmuker2014_classifier::inputRates
14.31.5.15	unsigned int Schmuker2014_classifier::inputRatesSize
14.31.5.16	FILE* Schmuker2014_classifier::log
14.31.5.17	NNmodel Schmuker2014_classifier::model
14.31.5.18	string Schmuker2014_classifier::outputDir
14.31.5.19	unsigned int* Schmuker2014_classifier::overallWinnerSpikeCountAN
14.31.5.20	float Schmuker2014_classifier::param_CONNECTIVITY_AN_AN
14.31.5.21	float Schmuker2014_classifier::param_CONNECTIVITY_PN_AN
14.31.5.22	float Schmuker2014_classifier::param_CONNECTIVITY_PN_PN
14.31.5.23	float Schmuker2014_classifier::param_CONNECTIVITY_RN_PN
14.31.5.24	float Schmuker2014_classifier::param_GLOBAL_WEIGHT_SCALING
14.31.5.25	UINT Schmuker2014_classifier::param_MAX_FIRING_RATE_HZ
14.31.5.26	float Schmuker2014_classifier::param_MAX_WEIGHT_PN_AN
14.31.5.27	UINT Schmuker2014_classifier::param_MIN_FIRING_RATE_HZ
14.31.5.28	float Schmuker2014_classifier::param_MIN_WEIGHT_PN_AN
14.31.5.29	float Schmuker2014_classifier::param_PLASTICITY_INTERVAL_MS
14.31.5.30	UINT Schmuker2014_classifier::param_SPIKING_ACTIVITY_THRESHOLD_HZ

```
14.31.5.31 float Schmuker2014_classifier::param_WEIGHT_DELTA_PN_AN

14.31.5.32 float Schmuker2014_classifier::param_WEIGHT_RN_PN

14.31.5.33 float Schmuker2014_classifier::param_WEIGHT_WTA_AN_AN

14.31.5.34 float Schmuker2014_classifier::param_WEIGHT_WTA_PN_PN

14.31.5.35 float* Schmuker2014_classifier::plasticWeights

14.31.5.36 string Schmuker2014_classifier::recordingsDir

14.31.5.37 float* Schmuker2014_classifier::sampleDistance

14.31.5.38 float Schmuker2014_classifier::timestepsPerRecording = RECORDING_TIME_MS / DT [static]

14.31.5.40 string Schmuker2014_classifier::uniqueRunld

14.31.5.41 float* Schmuker2014_classifier::vrData

14.31.5.42 int Schmuker2014_classifier::winningClass
```

The documentation for this class was generated from the following files:

- Schmuker2014_classifier.h
- Schmuker2014_classifier.cu

14.32 stdRG Class Reference

```
#include <randomGen.h>
```

Public Member Functions

• stdRG ()

Constructor of the standard random number generator class without explicit seed.

stdRG (unsigned int)

Constructor of the standard random number generator class with explicit seed.

- \sim stdRG ()
- double n ()

Method to generate a uniform random number.

unsigned long nlong ()

14.32.1 Constructor & Destructor Documentation

```
14.32.1.1 stdRG::stdRG( ) [explicit]
```

Constructor of the standard random number generator class without explicit seed.

The seed is taken from teh internal clock of the computer.

```
14.32.1.2 stdRG::stdRG ( unsigned int seed )
```

Constructor of the standard random number generator class with explicit seed.

The seed is an arbitrary unsigned int

```
14.32.1.3 stdRG::~stdRG() [inline]
14.32.2 Member Function Documentation
14.32.2.1 double stdRG::n ( )
Method to generate a uniform random number.
The moethod is a wrapper for the C function rand() and returns a pseudo random number in the interval [0,1[
14.32.2.2 unsigned long stdRG::nlong ( )
The documentation for this class was generated from the following files:
    · randomGen.h
    · randomGen.cc
14.33 stopWatch Struct Reference
#include <hr_time.h>
Public Attributes
    · timeval start

    timeval stop

14.33.1 Member Data Documentation
14.33.1.1 timeval stopWatch::start
14.33.1.2 timeval stopWatch::stop
The documentation for this struct was generated from the following file:
    • hr_time.h
14.34 SynDelay Class Reference
#include <SynDelaySim.h>
Public Member Functions
    • SynDelay (bool usingGPU)

    ∼SynDelay ()

    void run (float t)

14.34.1 Constructor & Destructor Documentation
14.34.1.1 SynDelay::SynDelay (bool usingGPU)
```

14.34.1.2 SynDelay::∼SynDelay ()

14.34.2 Member Function Documentation

14.34.2.1 void SynDelay::run (float t)

The documentation for this class was generated from the following files:

- · SynDelaySim.h
- · SynDelaySim.cu

14.35 weightUpdateModel Class Reference

Structure to hold the information that defines a weightupdate model (a model of how spikes affect synaptic (and/or) (mostly) post-synaptic neuron variables. It also allows to define changes in response to post-synaptic spikes/spike-like events.

```
#include <modelSpec.h>
```

Public Member Functions

weightUpdateModel ()

Public Attributes

string simCode

Simulation code that is used for true spikes (only one time step after spike detection)

string simCodeEvnt

Simulation code that is used for spike events (all the instances where event threshold condition is met)

string simLearnPost

Simulation code which is used in the learnSynapsesPost kernel/function, where postsynaptic neuron spikes before the presynaptic neuron in the STDP window.

· string evntThreshold

Simulation code for spike event detection.

string synapseDynamics

Simulation code for synapse dynamics independent of spike detection.

vector< string > varNames

Names of the variables in the postsynaptic model.

vector< string > varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

vector< string > pNames

Names of (independent) parameters of the model.

vector< string > dpNames

Names of dependent parameters of the model.

vector< string > extraGlobalSynapseKernelParameters

Additional parameter in the neuron kernel; it is translated to a population specific name but otherwise assumed to be one parameter per population rather than per synapse.

 $\bullet \ \ vector < string > extra Global Synapse Kernel Parameter Types \\$

Additional parameters in the neuron kernel; they are translated to a population specific name but otherwise assumed to be one parameter per population rather than per synapse.

- · dpclass * dps
- · bool needPreSt

Whether presynaptic spike times are needed or not.

bool needPostSt

Whether postsynaptic spike times are needed or not.

14.35.1 Detailed Description

Structure to hold the information that defines a weightupdate model (a model of how spikes affect synaptic (and/or) (mostly) post-synaptic neuron variables. It also allows to define changes in response to post-synaptic spikes/spike-like events.

14.35.2 Constructor & Destructor Documentation

14.35.2.1 weightUpdateModel::weightUpdateModel() [inline]

14.35.3 Member Data Documentation

14.35.3.1 vector<string> weightUpdateModel::dpNames

Names of dependent parameters of the model.

14.35.3.2 dpclass* weightUpdateModel::dps

14.35.3.3 string weightUpdateModel::evntThreshold

Simulation code for spike event detection.

14.35.3.4 vector<string> weightUpdateModel::extraGlobalSynapseKernelParameters

Additional parameter in the neuron kernel; it is translated to a population specific name but otherwise assumed to be one parameter per population rather than per synapse.

14.35.3.5 vector<string> weightUpdateModel::extraGlobalSynapseKernelParameterTypes

Additional parameters in the neuron kernel; they are translated to a population specific name but otherwise assumed to be one parameter per population rather than per synapse.

14.35.3.6 bool weightUpdateModel::needPostSt

Whether postsynaptic spike times are needed or not.

14.35.3.7 bool weightUpdateModel::needPreSt

Whether presynaptic spike times are needed or not.

14.35.3.8 vector<string> weightUpdateModel::pNames

Names of (independent) parameters of the model.

14.35.3.9 string weightUpdateModel::simCode

Simulation code that is used for true spikes (only one time step after spike detection)

14.35.3.10 string weightUpdateModel::simCodeEvnt

Simulation code that is used for spike events (all the instances where event threshold condition is met)

14.35.3.11 string weightUpdateModel::simLearnPost

Simulation code which is used in the learnSynapsesPost kernel/function, where postsynaptic neuron spikes before the presynaptic neuron in the STDP window.

14.35.3.12 string weightUpdateModel::synapseDynamics

Simulation code for synapse dynamics independent of spike detection.

15 File Documentation 105

14.35.3.13 vector < string > weightUpdateModel::varNames

Names of the variables in the postsynaptic model.

14.35.3.14 vector < string > weightUpdateModel::varTypes

Types of the variable named above, e.g. "float". Names and types are matched by their order of occurrence in the vector.

The documentation for this class was generated from the following file:

· modelSpec.h

15 File Documentation

- 15.1 00 MainPage.dox File Reference
- 15.2 01_Installation.dox File Reference
- 15.3 02_Quickstart.dox File Reference
- 15.4 03_Examples.dox File Reference
- 15.5 09_ReleaseNotes_v2.dox File Reference
- 15.6 10_UserManual.dox File Reference
- 15.7 11_Tutorial.dox File Reference
- 15.8 12_Tutorial.dox File Reference
- 15.9 13_UserGuide.dox File Reference
- 15.10 14 Credits.dox File Reference
- 15.11 classol_sim.cu File Reference

```
#include "classol_sim.h"
```

Functions

• int main (int argc, char *argv[])

This function is the entry point for running the simulation of the MBody1 model network.

15.11.1 Function Documentation

15.11.1.1 int main (int argc, char * argv[])

This function is the entry point for running the simulation of the MBody1 model network.

15.12 classol_sim.cu File Reference

```
#include "classol_sim.h"
```

Functions

• int main (int argc, char *argv[])

This function is the entry point for running the simulation of the MBody_delayedSyn model network.

15.12.1 Function Documentation

```
15.12.1.1 int main ( int argc, char * argv[])
```

This function is the entry point for running the simulation of the MBody_delayedSyn model network.

15.13 classol_sim.cu File Reference

```
#include "classol_sim.h"
```

Functions

• int main (int argc, char *argv[])

This function is the entry point for running the simulation of the MBody1 model network.

15.13.1 Function Documentation

```
15.13.1.1 int main ( int argc, char * argv[])
```

This function is the entry point for running the simulation of the MBody1 model network.

15.14 classol sim.cu File Reference

```
#include "classol sim.h"
```

Functions

• int main (int argc, char *argv[])

This function is the entry point for running the simulation of the MBody1 model network.

15.14.1 Function Documentation

```
15.14.1.1 int main ( int argc, char * argv[])
```

This function is the entry point for running the simulation of the MBody1 model network.

15.15 classol_sim.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "MBody1.cc"
#include "map_classol.cc"
```

Macros

- #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X= (Y >> 16);
- #define DBG_SIZE 10000
- #define PATTERNNO 100
- #define T_REPORT_TME 10000.0
- #define SYN_OUT_TME 20000.0
- #define PAT_TIME 100.0
- #define PATFTIME 1.5
- #define TOTAL TME 500.0

Variables

- scalar t = 0.0f
- unsigned int iT = 0
- scalar InputBaseRate = 2e-04
- int patSetTime
- int patFireTime
- · CStopWatch timer

15.15.1 Macro Definition Documentation

- 15.15.1.1 #define DBG_SIZE 10000
- 15.15.1.2 #define MYRAND(Y, X) Y = Y * 1103515245 + 12345; <math>X = (Y >> 16);
- 15.15.1.3 #define PAT_TIME 100.0
- 15.15.1.4 #define PATFTIME 1.5
- 15.15.1.5 #define PATTERNNO 100
- 15.15.1.6 #define SYN_OUT_TME 20000.0
- 15.15.1.7 #define T_REPORT_TME 10000.0
- 15.15.1.8 #define TOTAL_TME 500.0
- 15.15.2 Variable Documentation
- 15.15.2.1 scalar InputBaseRate = 2e-04
- 15.15.2.2 unsigned int iT = 0
- 15.15.2.3 int patFireTime

```
15.15.2.4 int patSetTime
```

15.15.2.5 scalar t = 0.0f

15.15.2.6 CStopWatch timer

15.16 classol_sim.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "MBody_delayedSyn.cc"
#include "map_classol.cc"
```

Macros

- #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X = (Y >> 16);
- #define DBG_SIZE 10000
- #define PATTERNNO 100
- #define T_REPORT_TME 10000.0
- #define SYN_OUT_TME 20000.0
- #define PAT_TIME 100.0
- #define PATFTIME 1.5
- #define TOTAL_TME 5000.0

Variables

- scalar t = 0.0f
- unsigned int iT = 0
- scalar InputBaseRate = 2e-04
- int patSetTime
- · int patFireTime
- · CStopWatch timer

15.16.1 Macro Definition Documentation

```
15.16.1.1 #define DBG_SIZE 10000
```

- 15.16.1.2 #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X= (Y >> 16);
- 15.16.1.3 #define PAT_TIME 100.0
- 15.16.1.4 #define PATFTIME 1.5
- 15.16.1.5 #define PATTERNNO 100
- 15.16.1.6 #define SYN_OUT_TME 20000.0
- 15.16.1.7 #define T_REPORT_TME 10000.0
- 15.16.1.8 #define TOTAL_TME 5000.0
- 15.16.2 Variable Documentation

```
15.16.2.1 scalar InputBaseRate = 2e-04
15.16.2.2 unsigned int iT = 0
15.16.2.3 int patFireTime
15.16.2.4 int patSetTime
15.16.2.5 scalar t = 0.0f
15.16.2.6 CStopWatch timer
15.17 classol_sim.h File Reference
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "MBody_individualID.cc"
#include "map_classol.cc"
Macros
    • #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X= (Y >> 16);
    • #define DBG_SIZE 10000
    • #define PATTERNNO 100
    • #define T_REPORT_TME 10000.0
    • #define SYN OUT TME 20000.0
    • #define PAT_TIME 100.0
    • #define PATFTIME 1.5

    #define TOTAL_TME 5000.0

Variables

    scalar t = 0.0f

    • unsigned int iT = 0
    • scalar InputBaseRate = 2e-04

    int patSetTime

    int patFireTime

    CStopWatch timer

15.17.1 Macro Definition Documentation
15.17.1.1 #define DBG_SIZE 10000
15.17.1.2 #define MYRAND( Y, X) Y = Y * 1103515245 + 12345; X= (<math>Y >> 16);
15.17.1.3 #define PAT_TIME 100.0
15.17.1.4 #define PATFTIME 1.5
```

15.17.1.5 #define PATTERNNO 100

15.17.1.6 #define SYN_OUT_TME 20000.0

```
15.17.1.7 #define T_REPORT_TME 10000.0
15.17.1.8 #define TOTAL_TME 5000.0
15.17.2 Variable Documentation
15.17.2.1 scalar InputBaseRate = 2e-04
15.17.2.2 unsigned int iT = 0
15.17.2.3 int patFireTime
15.17.2.4 int patSetTime
15.17.2.5 scalar t = 0.0f
15.17.2.6 CStopWatch timer
15.18 classol_sim.h File Reference
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include <cfloat>
#include "MBody userdef.cc"
#include "map_classol.cc"
Macros
    • #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X = (Y >> 16);
    • #define DBG SIZE 10000

    #define PATTERNNO 100

    • #define T_REPORT_TME 10000.0
    • #define SYN OUT TME 20000.0

    #define PAT_TIME 100.0

    • #define PATFTIME 1.5

    #define TOTAL_TME 5000.0

Variables
    • scalar t = 0.0f
    • unsigned int iT = 0
    • scalar InputBaseRate = 2e-04

    int patSetTime

    int patFireTime

    · CStopWatch timer
15.18.1 Macro Definition Documentation
15.18.1.1 #define DBG_SIZE 10000
15.18.1.2 #define MYRAND( Y, X) Y = Y * 1103515245 + 12345; <math>X = (Y >> 16);
```

15.18.1.3 #define PAT_TIME 100.0

```
15.18.1.4 #define PATFTIME 1.5

15.18.1.5 #define PATTERNNO 100

15.18.1.6 #define SYN_OUT_TME 20000.0

15.18.1.7 #define T_REPORT_TME 10000.0

15.18.1.8 #define TOTAL_TME 5000.0

15.18.2 Variable Documentation

15.18.2.1 scalar InputBaseRate = 2e-04

15.18.2.2 unsigned int iT = 0

15.18.2.3 int patFireTime

15.18.2.4 int patSetTime

15.18.2.5 scalar t = 0.0f
```

15.19 CodeHelper.cc File Reference

```
#include <iostream>
#include <cstring>
#include <string>
#include <sstream>
#include <vector>
```

15.18.2.6 CStopWatch timer

Classes

• class CodeHelper

Macros

- #define __CODE_HELPER_CC
- #define SAVEP(X) "(" << X << ")"
- #define OB(X) hlp.openBrace(X)
- #define CB(X) hlp.closeBrace(X)
- #define ENDL hlp.endl()

15.19.1 Macro Definition Documentation

- 15.19.1.1 #define __CODE_HELPER_CC
- 15.19.1.2 #define CB(X) hlp.closeBrace(X)
- 15.19.1.3 #define ENDL hlp.endl()
- 15.19.1.4 #define OB(X) hlp.openBrace(X)
- 15.19.1.5 #define SAVEP($\it X$) "(" << X << ")"

15.20 ensureFtype.h File Reference

```
#include <string>
```

Functions

- · void doFinal (string &code, unsigned int i, string type, unsigned int &state)
- string ensureFtype (string oldcode, string type)

Variables

```
• string digits = string("0123456789")
```

Function for converting code to contain only explicit single precision (float) constants.

```
• string op = string("+-*/(<>= ,;")+string("\n")+string("\t")
```

15.20.1 Function Documentation

```
15.20.1.1 void doFinal ( string & code, unsigned int i, string type, unsigned int & state )
```

```
15.20.1.2 string ensureFtype ( string oldcode, string type )
```

15.20.2 Variable Documentation

```
15.20.2.1 string digits = string("0123456789")
```

Function for converting code to contain only explicit single precision (float) constants.

```
15.20.2.2 string op = string("+-*/(<>=,;")+string("\n")+string("\t")
```

15.21 experiment.cu File Reference

```
#include "experiment.h"
#include <time.h>
#include <algorithm>
#include <sys/types.h>
#include <sys/stat.h>
```

Classes

struct Parameter

Macros

- #define RAND(Y, X) Y = Y * 1103515245 +12345;X= (unsigned int)(Y >> 16) & 32767
- #define S_ISDIR(mode) (((mode) & S_IFMT) == S_IFDIR)

Typedefs

typedef struct Parameter Parameter

Functions

- bool directoryExists (string const &path)
- bool createDirectory (string path)
- float getAverage (vector< float > &v)
- float getStdDev (vector< float > &v, float avg)
- bool printTextFile (string path)
- string getUniqueRunId ()
- void outputRunParameters ()
- bool applyInputToClassifier (UINT recordingIdx, bool usePlasticity)
- bool vectorContains (vector< int > &vec, int lookingFor)
- void setDefaultParamValues ()
- int main (int argc, char *argv[])

Variables

• Schmuker2014_classifier classifier

```
15.21.1 Macro Definition Documentation
15.21.1.1 #define RAND( Y, X) Y = Y * 1103515245 +12345;X= (unsigned int)(Y >> 16) & 32767
15.21.1.2 #define S_ISDIR( mode ) (((mode) & S_IFMT) == S_IFDIR)
15.21.2 Typedef Documentation
15.21.2.1 typedef struct Parameter Parameter
15.21.3 Function Documentation
15.21.3.1 bool applyInputToClassifier ( UINT recordingIdx, bool usePlasticity )
15.21.3.2 bool createDirectory ( string path )
15.21.3.3 bool directoryExists ( string const & path )
15.21.3.4 float getAverage (vector < float > & v)
15.21.3.5 float getStdDev (vector < float > & v, float avg)
15.21.3.6 string getUniqueRunld ( )
15.21.3.7 int main ( int argc, char * argv[] )
15.21.3.8 void outputRunParameters ( )
15.21.3.9 bool printTextFile ( string path )
15.21.3.10 void setDefaultParamValues ( )
15.21.3.11 bool vectorContains ( vector < int > & vec, int lookingFor )
15.21.4 Variable Documentation
```

15.21.4.1 Schmuker2014_classifier classifier

15.22 experiment.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include "Schmuker2014_classifier.cu"
```

Macros

- #define divi "/"
- #define D_MAX_RANDOM_NUM 32767
- #define RECORDINGS DIR "recordings iris data"
- #define CACHE_DIR "cached_iris_data"
- #define OUTPUT DIR "output iris"
- #define VR DATA FILENAME "VR-recordings-iris.data"
- #define DATASET_NAME "Iris"
- #define TOTAL_RECORDINGS 150
- #define N FOLDING 5
- #define RECORDING_TIME_MS 1000
- #define REPEAT_LEARNING_SET 2
- #define SPIKING ACTIVITY THRESHOLD HZ 5
- #define FLAG_RUN_ON_CPU 1
- #define MAX_FIRING_RATE_HZ 70
- #define MIN FIRING RATE HZ 20
- #define GLOBAL WEIGHT SCALING 1.0
- #define WEIGHT_RN_PN 0.5
- #define CONNECTIVITY RN PN 0.5
- #define WEIGHT_WTA_PN_PN 0.01
- #define WEIGHT WTA AN AN 0.01
- #define CONNECTIVITY PN PN 0.5
- #define CONNECTIVITY_AN_AN 0.5
- #define CONNECTIVITY_PN_AN 0.5
- #define MIN WEIGHT PN AN 0.1
- #define MAX WEIGHT PN AN 0.4
- #define WEIGHT_DELTA_PN_AN 0.04
- #define PLASTICITY INTERVAL MS 330

Typedefs

typedef unsigned int UINT

Variables

· CStopWatch timer

15.22.1 Macro Definition Documentation

15.22.1.1 #define CACHE_DIR "cached_iris_data"

15.22.1.2 #define CONNECTIVITY_AN_AN 0.5

15.22.1.3 #define CONNECTIVITY_PN_AN 0.5

15.22.1.4 #define CONNECTIVITY_PN_PN 0.5 15.22.1.5 #define CONNECTIVITY_RN_PN 0.5 15.22.1.6 #define D_MAX_RANDOM_NUM 32767 15.22.1.7 #define DATASET_NAME "Iris" 15.22.1.8 #define divi "/" 15.22.1.9 #define FLAG_RUN_ON_CPU 1 15.22.1.10 #define GLOBAL_WEIGHT_SCALING 1.0 15.22.1.11 #define MAX_FIRING_RATE_HZ 70 15.22.1.12 #define MAX_WEIGHT_PN_AN 0.4 15.22.1.13 #define MIN_FIRING_RATE_HZ 20 15.22.1.14 #define MIN_WEIGHT_PN_AN 0.1 15.22.1.15 #define N_FOLDING 5 15.22.1.16 #define OUTPUT_DIR "output_iris" 15.22.1.17 #define PLASTICITY_INTERVAL_MS 330 15.22.1.18 #define RECORDING_TIME_MS 1000 15.22.1.19 #define RECORDINGS_DIR "recordings_iris_data" 15.22.1.20 #define REPEAT_LEARNING_SET 2 15.22.1.21 #define SPIKING_ACTIVITY_THRESHOLD_HZ 5 15.22.1.22 #define TOTAL_RECORDINGS 150 15.22.1.23 #define VR_DATA_FILENAME "VR-recordings-iris.data" 15.22.1.24 #define WEIGHT_DELTA_PN_AN 0.04 15.22.1.25 #define WEIGHT_RN_PN 0.5 15.22.1.26 #define WEIGHT_WTA_AN_AN 0.01 15.22.1.27 #define WEIGHT_WTA_PN_PN 0.01 15.22.2 Typedef Documentation 15.22.2.1 typedef unsigned int UINT 15.22.3 Variable Documentation 15.22.3.1 CStopWatch timer

Functions

- n varNames clear ()
- n varNames push_back (tS("V"))

15.23 extra_neurons.h File Reference

```
n varTypes push_back (tS("float"))
```

- n varNames push_back (tS("V_NB"))
- n varNames push_back (tS("tSpike_NB"))
- n varNames push_back (tS("__regime_val"))
- n varTypes push_back (tS("int"))
- n pNames push_back (tS("VReset_NB"))
- n pNames push_back (tS("VThresh_NB"))
- n pNames push_back (tS("tRefrac_NB"))
- n pNames push_back (tS("VRest_NB"))
- n pNames push_back (tS("TAUm_NB"))
- n pNames push_back (tS("Cm_NB"))
- nModels push_back (n)
- n varNames push_back (tS("count_t_NB"))
- n pNames push_back (tS("max_t_NB"))

Variables

· n simCode

```
15.23.1 Function Documentation
15.23.1.1 ps dpNames clear ( )
15.23.1.2 n varNames push_back ( tS("V") )
15.23.1.3 ps varTypes push_back ( tS("float") )
15.23.1.4 n varNames push_back ( tS("V_NB") )
15.23.1.5 n varNames push_back ( tS("tSpike_NB") )
15.23.1.6 n varNames push_back ( tS("__regime_val") )
15.23.1.7 n varTypes push_back ( tS("int") )
15.23.1.8 n pNames push_back ( tS("VReset_NB") )
15.23.1.9 n pNames push_back ( tS("VThresh_NB") )
15.23.1.10 n pNames push_back ( tS("tRefrac_NB") )
15.23.1.11 n pNames push_back ( tS("VRest_NB") )
15.23.1.12 n pNames push_back ( tS("TAUm_NB") )
15.23.1.13 n pNames push_back ( tS("Cm_NB") )
15.23.1.14 nModels push_back ( n )
15.23.1.15 n varNames push_back ( tS("count_t_NB") )
15.23.1.16 n pNames push_back ( tS("max_t_NB") )
15.23.2 Variable Documentation
```

Initial value:

15.23.2.1 n simCode

15.24 extra_postsynapses.h File Reference

Functions

- ps varNames clear ()
- ps varNames push_back (tS("g_PS"))
- ps varTypes push_back (tS("float"))
- ps pNames push_back (tS("tau_syn_PS"))
- ps pNames push_back (tS("E_PS"))
- postSynModels push_back (ps)

Variables

- ps postSyntoCurrent
- ps postSynDecay

15.24.1 Function Documentation

```
15.24.1.1 ps varNames clear ( )
```

- 15.24.1.2 ps varNames push_back (tS("g_PS"))
- 15.24.1.3 ps varTypes push_back (tS("float"))
- 15.24.1.4 ps pNames push_back (tS("tau_syn_PS"))
- 15.24.1.5 ps pNames push_back (tS("E_PS"))
- 15.24.1.6 postSynModels push_back (ps)
- 15.24.2 Variable Documentation
- 15.24.2.1 ps postSynDecay

Initial value:

15.24.2.2 ps postSyntoCurrent

Initial value:

15.25 extra_postsynapses.h File Reference

Functions

- ps varNames clear ()
- postSynModels push_back (ps)
- ps varNames push_back (tS("g_PS"))
- ps varTypes push_back (tS("float"))
- ps pNames push_back (tS("tau_syn_PS"))
- ps pNames push_back (tS("E_PS"))

Variables

- postSynModel ps
- ps postSyntoCurrent
- ps postSynDecay

```
15.25.1 Function Documentation
```

```
15.25.1.1 ps varNames clear ( )
```

- 15.25.1.2 postSynModels push_back (ps)
- 15.25.1.3 ps varNames push_back (tS("g_PS"))
- 15.25.1.4 ps varTypes push_back (tS("float"))
- 15.25.1.5 ps pNames push_back (tS("tau_syn_PS"))
- 15.25.1.6 ps pNames push_back (tS("E_PS"))
- 15.25.2 Variable Documentation
- 15.25.2.1 ps postSynDecay

Initial value:

```
= tS(" \setminus $(inSyn) = 0; \setminus ")
```

15.25.2.2 ps postSyntoCurrent

Initial value:

15.25.2.3 postSynModel ps

15.26 extra_weightupdates.h File Reference

15.27 GA.cc File Reference

```
#include <algorithm>
```

Classes

struct errTupel

Functions

- int compareErrTupel (const void *x, const void *y)
- void procreatePop (FILE *osb)

15.27.1 Function Documentation

```
15.27.1.1 int compare Err Tupel ( const void *x, const void *y)
```

```
15.27.1.2 void procreatePop ( FILE * osb )
```

15.28 gauss.cc File Reference

Contains the implementation of the Gaussian random number generator class randomGauss.

```
#include "gauss.h"
```

Macros

• #define GAUSS_CC

macro for avoiding multiple inclusion during compilation

15.28.1 Detailed Description

Contains the implementation of the Gaussian random number generator class randomGauss.

15.28.2 Macro Definition Documentation

15.28.2.1 #define GAUSS_CC

macro for avoiding multiple inclusion during compilation

15.29 gauss.h File Reference

Random number generator for Gaussian random variable with mean 0 and standard deviation 1.

```
#include <cmath>
#include "randomGen.h"
#include "randomGen.cc"
#include "gauss.cc"
```

Classes

· class randomGauss

Class random Gauss encapsulates the methods for generating random neumbers with Gaussian distribution.

Macros

• #define GAUSS H

macro for avoiding multiple inclusion during compilation

15.29.1 Detailed Description

Random number generator for Gaussian random variable with mean 0 and standard deviation 1.

This random number generator is based on the ratio of uniforms method by A.J. Kinderman and J.F. Monahan and improved with quadratic boundind curves by J.L. Leva. Taken from Algorithm 712 ACM Trans. Math. Softw. 18 p. 454. (the necessary uniform random variables are obtained from the ISAAC random number generator; C++ Implementation by Quinn Tyler Jackson of the RG invented by Bob Jenkins Jr.).

15.29.2 Macro Definition Documentation

```
15.29.2.1 #define GAUSS H
```

macro for avoiding multiple inclusion during compilation

15.30 gen_input_structured.cc File Reference

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
#include "randomGen.h"
#include "randomGen.cc"
```

Functions

• int main (int argc, char *argv[])

Variables

randomGen R

```
15.30.1 Function Documentation
15.30.1.1 int main (int argc, char * argv[])
15.30.2 Variable Documentation
15.30.2.1 randomGen R
15.31 gen_kcdn_syns.cc File Reference
```

This file is part of a tool chain for running the classol/MBody1 example model.

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
#include "randomGen.h"
#include "gauss.h"
#include "randomGen.cc"
```

Functions

• int main (int argc, char *argv[])

Variables

- randomGen R
- · randomGauss RG

15.31.1 Detailed Description

This file is part of a tool chain for running the classol/MBody1 example model.

This file compiles to a tool to generate appropriate connectivity patterns between KCs and DNs (detector neurons) in the model. The connectivity is saved to file and can then be read by the classol method for reading this connectivity.

```
15.31.2 Function Documentation
15.31.2.1 int main ( int argc, char * argv[] )
15.31.3 Variable Documentation
15.31.3.1 randomGen R
15.31.3.2 randomGauss RG
15.32 gen_kcdn_syns_fixto10K.cc File Reference
#include <iostream>
```

```
#include <fstream>
#include <stdlib.h>
#include "randomGen.h"
#include "gauss.h"
#include "randomGen.cc"
```

Functions

• int main (int argc, char *argv[])

Variables

- · randomGen R
- randomGen R2
- · randomGauss RG

```
15.32.1 Function Documentation
```

```
15.32.1.1 int main ( int argc, char * argv[])
```

15.32.2 Variable Documentation

15.32.2.1 randomGen R

15.32.2.2 randomGen R2

15.32.2.3 randomGauss RG

15.33 gen_pnkc_syns.cc File Reference

This file is part of a tool chain for running the classol/MBody1 example model.

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
#include "randomGen.h"
#include "gauss.h"
#include "randomGen.cc"
```

Functions

• int main (int argc, char *argv[])

Variables

- randomGen R
- · randomGauss RG

15.33.1 Detailed Description

This file is part of a tool chain for running the classol/MBody1 example model.

This file compiles to a tool to generate appropriate connectivity patterns between PNs and KCs in the model. The connectivity is saved to file and can then be read by the classol method for reading this connectivity.

```
15.33.2 Function Documentation

15.33.2.1 int main ( int argc, char * argv[] )

15.33.3 Variable Documentation

15.33.3.1 randomGen R

15.33.3.2 randomGauss RG
```

15.34 gen_pnkc_syns_indivID.cc File Reference

This file is part of a tool chain for running the classol/MBody1 example model.

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
#include <cstdint>
#include "randomGen.h"
#include "gauss.h"
#include "simpleBit.h"
#include "randomGen.cc"
```

Functions

• int main (int argc, char *argv[])

Variables

- · randomGen R
- randomGauss RG

15.34.1 Detailed Description

This file is part of a tool chain for running the classol/MBody1 example model.

This file compiles to a tool to generate appropriate connectivity patterns between PNs and KCs in the model. In contrast to the gen_pnkc_syns.cc tool, here the output is in a format that is suited for the "INDIVIDUALID" method for specifying connectivity. The connectivity is saved to file and can then be read by the classol method for reading this connectivity.

```
15.34.2 Function Documentation
15.34.2.1 int main (int argc, char * argv[])
15.34.3 Variable Documentation
15.34.3.1 randomGen R
15.34.3.2 randomGauss RG
```

15.35 gen_pnlhi_syns.cc File Reference

This file is part of a tool chain for running the classol/MBody1 example model.

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
```

Functions

• int main (int argc, char *argv[])

15.35.1 Detailed Description

This file is part of a tool chain for running the classol/MBody1 example model.

This file compiles to a tool to generate appropriate connectivity patterns between PNs and LHIs (lateral horn interneurons) in the model. The connectivity is saved to file and can then be read by the classol method for reading this connectivity.

15.35.2 Function Documentation

```
15.35.2.1 int main ( int argc, char * argv[])
```

15.36 gen_syns_sparse.cc File Reference

This file generates the arrays needed for sparse connectivity. The connectivity is saved to a file for each variable and can then be read to fill the struct of connectivity.

```
#include <iostream>
#include <fstream>
#include <string.h>
#include "randomGen.h"
#include "gauss.h"
#include <vector>
```

Functions

int main (int argc, char *argv[])

Variables

- randomGen R
- · randomGauss RG

15.36.1 Detailed Description

This file generates the arrays needed for sparse connectivity. The connectivity is saved to a file for each variable and can then be read to fill the struct of connectivity.

```
15.36.2 Function Documentation
```

```
15.36.2.1 int main ( int argc, char * argv[])
```

15.36.3 Variable Documentation

```
15.36.3.1 randomGen R15.36.3.2 randomGauss RG15.37 gen_syns_sparse_izhModel.cc File Reference
```

This file is part of a tool chain for running the Izhikevich network model.

```
#include <iostream>
#include <fstream>
#include <stdlib.h>
#include <string.h>
#include <vector>
#include "randomGen.h"
#include "randomGen.cc"
```

Functions

- int printVector (vector< unsigned int > &)
- int printVector (vector< double > &)
- int main (int argc, char *argv[])

Variables

- · randomGen R
- · randomGen Rind
- · double gsyn
- double * garray
- unsigned int * ind
- double * garray_ee
- std::vector< double > g_ee
- std::vector< unsigned int > indlnG_ee
- std::vector< unsigned int > ind_ee
- double * garray_ei
- std::vector< double > g_ei
- std::vector< unsigned int > indlnG_ei
- std::vector< unsigned int > ind ei
- double * garray_ie
- std::vector< double > g_ie
- std::vector< unsigned int > indlnG_ie
- std::vector< unsigned int > ind_ie
- double * garray_ii
- std::vector< double > g_ii
- std::vector< unsigned int > indlnG_ii
- std::vector< unsigned int > ind_ii

15.37.1 Detailed Description

This file is part of a tool chain for running the Izhikevich network model.

15.37.2 Function Documentation

```
15.37.2.1 int main ( int argc, char * argv[] )
15.37.2.2 int printVector ( vector< unsigned int > \& v )
15.37.2.3 int printVector ( vector< double > \& v )
15.37.3 Variable Documentation
```

```
15.37.3.1 std::vector<double> g_ee
15.37.3.2 std::vector<double> g_ei
15.37.3.3 std::vector<double> g_ie
15.37.3.4 std::vector<double> g_ii
15.37.3.5 double* garray
15.37.3.6 double* garray_ee
15.37.3.7 double* garray_ei
15.37.3.8 double* garray_ie
15.37.3.9 double* garray_ii
15.37.3.10 double gsyn
15.37.3.11 unsigned int* ind
15.37.3.12 std::vector<unsigned int> ind_ee
15.37.3.13 std::vector<unsigned int> ind_ei
15.37.3.14 std::vector<unsigned int> ind_ie
15.37.3.15 std::vector<unsigned int> ind_ii
15.37.3.16 std::vector<unsigned int> indlnG_ee
15.37.3.17 std::vector<unsigned int> indlnG_ei
15.37.3.18 std::vector<unsigned int> indlnG_ie
15.37.3.19 std::vector<unsigned int> indlnG_ii
15.37.3.20 randomGen R
```

15.37.3.21 randomGen Rind

15.38 generate_run.cc File Reference

```
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include "toString.h"
#include <sys/stat.h>
```

Functions

```
    int main (int argc, char *argv[])
    Main entry point for generate_run.
```

15.38.1 Function Documentation

```
15.38.1.1 int main ( int argc, char * argv[])
```

Main entry point for generate_run.

15.39 generate_run.cc File Reference

```
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <locale>
#include <sys/stat.h>
```

Macros

#define tS(X) toString(X)

Macro providing the abbreviated syntax tS() instead of toString().

Functions

```
    template < typename T >
    std::string toString (T t)
```

Template function for string conversion.

- string to Upper (string s)
- string toLower (string s)
- unsigned int openFileGetMax (unsigned int *array, unsigned int size, string name)
- int main (int argc, char *argv[])

Main entry point for generate_run.

```
15.39.1 Macro Definition Documentation
15.39.1.1 #define tS( X ) toString(X)
Macro providing the abbreviated syntax tS() instead of toString().
15.39.2 Function Documentation
15.39.2.1 int main ( int argc, char * argv[])
Main entry point for generate_run.
15.39.2.2 unsigned int openFileGetMax ( unsigned int * array, unsigned int size, string name )
15.39.2.3 string to Lower ( string s )
15.39.2.4 template < typename T > std::string to String ( T t )
Template function for string conversion.
15.39.2.5 string to Upper ( string s )
15.40 generate_run.cc File Reference
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <cfloat>
#include <locale>
#include <sys/stat.h>
Macros

    #define tS(X) toString(X)

         Macro providing the abbreviated syntax tS() instead of toString().
Functions
    • template<typename T >
      std::string toString (T t)
         template function for string conversion from const char* to C++ string

    string toUpper (string s)

    • string toLower (string s)
    • int main (int argc, char *argv[])
         Main entry point for generate_run.
15.40.1 Macro Definition Documentation
15.40.1.1 #define tS( X ) toString(X)
Macro providing the abbreviated syntax tS() instead of toString().
```

```
15.40.2 Function Documentation
15.40.2.1 int main ( int argc, char * argv[])
Main entry point for generate_run.
15.40.2.2 string to Lower ( string s )
15.40.2.3 template < typename T > std::string to String ( T t )
template function for string conversion from const char* to C++ string
15.40.2.4 string to Upper ( string s )
15.41 generate run.cc File Reference
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <cfloat>
#include <locale>
#include <sys/stat.h>
Macros

    #define tS(X) toString(X)

         Macro providing the abbreviated syntax tS() instead of toString().
Functions
    \bullet \ \ template\!<\!typename\ T>
      std::string toString (T t)
         template function for string conversion from const char* to C++ string

    string toUpper (string s)

    • string toLower (string s)
    • int main (int argc, char *argv[])
          Main entry point for generate_run.
15.41.1 Macro Definition Documentation
15.41.1.1 #define tS( X ) toString(X)
Macro providing the abbreviated syntax tS() instead of toString().
15.41.2 Function Documentation
15.41.2.1 int main ( int argc, char * argv[])
Main entry point for generate_run.
```

```
15.41.2.2 string toLower ( string s )
15.41.2.3 template < typename T > std::string to String ( T t )
template function for string conversion from const char* to C++ string
15.41.2.4 string to Upper ( string s )
15.42 generate_run.cc File Reference
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <cfloat>
#include <locale>
#include <sys/stat.h>
Macros

    #define tS(X) toString(X)

         Macro providing the abbreviated syntax tS() instead of toString().
Functions
    • template<typename T >
      std::string toString (T t)
         template function for string conversion from const char* to C++ string
    • string toUpper (string s)
    • string toLower (string s)
    • int main (int argc, char *argv[])
         Main entry point for generate_run.
15.42.1 Macro Definition Documentation
15.42.1.1 #define tS( X ) toString(X)
Macro providing the abbreviated syntax tS() instead of toString().
15.42.2 Function Documentation
15.42.2.1 int main ( int argc, char * argv[])
Main entry point for generate_run.
15.42.2.2 string toLower ( string s )
15.42.2.3 template < typename T > std::string to String ( T t )
template function for string conversion from const char* to C++ string
```

```
15.42.2.4 string to Upper (string s)
```

15.43 generate_run.cc File Reference

```
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <cfloat>
#include <locale>
#include <sys/stat.h>
```

Macros

#define tS(X) toString(X)

Macro providing the abbreviated syntax tS() instead of toString().

Functions

```
template<typename T > std::string toString (T t)
```

Template function for string conversion.

- string to Upper (string s)
- string toLower (string s)
- int main (int argc, char *argv[])

Main entry point for generate_run.

15.43.1 Macro Definition Documentation

```
15.43.1.1 #define tS( X ) toString(X)
```

Macro providing the abbreviated syntax tS() instead of toString().

```
15.43.2 Function Documentation
```

```
15.43.2.1 int main ( int argc, char * argv[])
```

Main entry point for generate_run.

```
15.43.2.2 string to Lower ( string s )
```

15.43.2.3 template<typename T > std::string toString (T t)

Template function for string conversion.

15.43.2.4 string to Upper (string s)

15.44 generate_run.cc File Reference

```
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <sys/stat.h>
```

Functions

```
template<typename T > std::string toString (T t)
```

Template function for string conversion.

• int main (int argc, char *argv[])

Main entry point for generate_run.

15.44.1 Function Documentation

```
15.44.1.1 int main ( int argc, char * argv[])
```

Main entry point for generate_run.

```
15.44.1.2 template<typename T > std::string toString ( T t )
```

Template function for string conversion.

15.45 generate_run.cc File Reference

```
#include <iostream>
#include <fstream>
#include <string>
#include <sstream>
#include <cstdlib>
#include <cmath>
#include <sys/stat.h>
```

Functions

```
    template<typename T >
    std::string toString (T t)
```

Template function for string conversion.

• int main (int argc, char *argv[])

Main entry point for generate_run.

15.45.1 Function Documentation

```
15.45.1.1 int main ( int argc, char * argv[])
```

Main entry point for generate_run.

```
15.45.1.2 template < typename T > std::string toString ( T t )
```

Template function for string conversion.

15.46 generateALL.cc File Reference

Main file combining the code for code generation. Part of the code generation section.

```
#include "global.h"
#include "modelSpec.h"
#include "modelSpec.cc"
#include "generateKernels.cc"
#include "generateRunner.cc"
#include "generateCPU.cc"
#include <sys/stat.h>
```

Functions

void generate model runner (NNmodel &model, string path)

This function will call the necessary sub-functions to generate the code for simulating a model.

int chooseDevice (ostream &mos, NNmodel *&model, string path)

Helper function that prepares data structures and detects the hardware properties to enable the code generation code that follows.

int main (int argc, char *argv[])

Main entry point for the generateALL executable that generates the code for GPU and CPU.

15.46.1 Detailed Description

Main file combining the code for code generation. Part of the code generation section.

The file includes separate files for generating kernels (generateKernels.cc), generating the CPU side code for running simulations on either the CPU or GPU (generateRunner.cc) and for CPU-only simulation code (generateCP← U.cc).

15.46.2 Function Documentation

```
15.46.2.1 int chooseDevice (ostream & mos, NNmodel *& model, string path)
```

Helper function that prepares data structures and detects the hardware properties to enable the code generation code that follows.

The main tasks in this function are the detection and characterization of the GPU device present (if any), choosing which GPU device to use, finding and appropriate block size, taking note of the major and minor version of the $C \leftarrow UDA$ enabled device chosen for use, and populating the list of standard neuron models. The chosen device number is returned.

Parameters

mos	output stream for messages
model	the nn model we are generating code for
path	path the generated code will be deposited

15.46.2.2 void generate_model_runner (NNmodel & model, string path)

This function will call the necessary sub-functions to generate the code for simulating a model.

Parameters

model	Model description
path	Path where the generated code will be deposited

15.46.2.3 int main (int argc, char * argv[])

Main entry point for the generateALL executable that generates the code for GPU and CPU.

The main function is the entry point for the code generation engine. It prepares the system and then invokes generate_model_runner to inititate the different parts of actual code generation.

Parameters

argc	number of arguments; expected to be 2
argv	Arguments; expected to contain the target directory for code generation.

15.47 generateCPU.cc File Reference

Functions for generating code that will run the neuron and synapse simulations on the CPU. Part of the code generation section.

```
#include <string>
#include "CodeHelper.cc"
#include <cfloat>
```

Functions

- void genNeuronFunction (NNmodel &model, string &path, ostream &mos)
 - Function that generates the code of the function the will simulate all neurons on the CPU.
- void generate_process_presynaptic_events_code_CPU (ostream &os, NNmodel &model, unsigned int src, unsigned int trg, int i, string &localID, unsigned int inSynNo, string postfix)

Function for generating the CUDA synapse kernel code that handles presynaptic spikes or spike type events.

• void genSynapseFunction (NNmodel &model, string &path, ostream &mos)

Function that generates code that will simulate all synapses of the model on the CPU.

15.47.1 Detailed Description

Functions for generating code that will run the neuron and synapse simulations on the CPU. Part of the code generation section.

15.47.2 Function Documentation

15.47.2.1 void generate_process_presynaptic_events_code_CPU (ostream & os, NNmodel & model, unsigned int src, unsigned int trg, int i, string & localID, unsigned int inSynNo, string postfix)

Function for generating the CUDA synapse kernel code that handles presynaptic spikes or spike type events.

Parameters

os	output stream for code

model	the neuronal network model to generate code for
src	the number of the src neuron population
trg	the number of the target neuron population
i	the index of the synapse group being processed
localID	the variable name of the local ID of the thread within the synapse group
inSynNo	the ID number of the current synapse population as the incoming population to the target
	neuron population
postfix	whether to generate code for true spikes or spike type events

15.47.2.2 void genNeuronFunction (NNmodel & model, string & path, ostream & mos)

Function that generates the code of the function the will simulate all neurons on the CPU.

Parameters

model	Model description
path	output stream for code
mos	output stream for messages

15.47.2.3 void genSynapseFunction (NNmodel & model, string & path, ostream & mos)

Function that generates code that will simulate all synapses of the model on the CPU.

Parameters

model	Model description
path	Path for code generation
mos	output stream for messages

15.48 generateKernels.cc File Reference

Contains functions that generate code for CUDA kernels. Part of the code generation section.

```
#include <string>
#include "CodeHelper.cc"
#include "global.h"
```

Functions

• void genNeuronKernel (NNmodel &model, string &path, ostream &mos)

Function for generating the CUDA kernel that simulates all neurons in the model.

• void generate_process_presynaptic_events_code (ostream &os, NNmodel &model, unsigned int src, unsigned int trg, int i, string &localID, unsigned int inSynNo, string postfix)

Function for generating the CUDA synapse kernel code that handles presynaptic spikes or spike type events.

• void genSynapseKernel (NNmodel &model, string &path, ostream &mos)

Function for generating a CUDA kernel for simulating all synapses.

- short * isGrpVarNeeded
- CodeHelper hlp

15.48.1 Detailed Description

Contains functions that generate code for CUDA kernels. Part of the code generation section.

15.48.2 Function Documentation

15.48.2.1 void generate_process_presynaptic_events_code (ostream & os, NNmodel & model, unsigned int src, unsigned int trg, int i, string & localID, unsigned int inSynNo, string postfix)

Function for generating the CUDA synapse kernel code that handles presynaptic spikes or spike type events.

Parameters

os	output stream for code
model	the neuronal network model to generate code for
src	the number of the src neuron population
trg	the number of the target neuron population
i	the index of the synapse group being processed
localID	the variable name of the local ID of the thread within the synapse group
inSynNo	the ID number of the current synapse population as the incoming population to the target
	neuron population
postfix	whether to generate code for true spikes or spike type events

15.48.2.2 void genNeuronKernel (NNmodel & model, string & path, ostream & mos)

Function for generating the CUDA kernel that simulates all neurons in the model.

The code generated upon execution of this function is for defining GPU side global variables that will hold model state in the GPU global memory and for the actual kernel function for simulating the neurons for one time step. Binary flag for the sparse synapses to use atomic operations when the number of connections is bigger than the block size, and shared variables otherwise

Parameters

model	Model description
path	path for code output
mos	output stream for messages

15.48.2.3 void genSynapseKernel (NNmodel & model, string & path, ostream & mos)

Function for generating a CUDA kernel for simulating all synapses.

This functions generates code for global variables on the GPU side that are synapse-related and the actual CUDA kernel for simulating one time step of the synapses. < "id" if first synapse group, else "lid". lid =(thread index- last thread of the last synapse group)

Parameters

model	Model description
path	Path for code output
mos	output stream for messages

15.48.3 Variable Documentation

15.48.3.1 CodeHelper hlp

15.48.3.2 short* isGrpVarNeeded

15.49 generateRunner.cc File Reference

Contains functions to generate code for running the simulation on the GPU, and for I/O convenience functions between GPU and CPU space. Part of the code generation section.

#include <cfloat>

Functions

void genRunner (NNmodel &model, string path, ostream &mos)

A function that generates predominantly host-side code.

• void genRunnerGPU (NNmodel &model, string &path, ostream &mos)

A function to generate the code that simulates the model on the GPU.

15.49.1 Detailed Description

Contains functions to generate code for running the simulation on the GPU, and for I/O convenience functions between GPU and CPU space. Part of the code generation section.

15.49.2 Function Documentation

15.49.2.1 void genRunner (NNmodel & model, string path, ostream & mos)

A function that generates predominantly host-side code.

In this function host-side functions and other code are generated, including: Global host variables, "allocatedMem()" function for allocating memories, "freeMem" function for freeing the allocated memories, "initialize" for initializing host variables, "gFunc" and "initGRaw()" for use with plastic synapses if such synapses exist in the model. Method for cleaning up and resetting device while quitting GeNN

Parameters

model	Model description
path	path for code generation
mos	output stream for messages

15.49.2.2 void genRunnerGPU (NNmodel & model, string & path, ostream & mos)

A function to generate the code that simulates the model on the GPU.

The function generates functions that will spawn kernel grids onto the GPU (but not the actual kernel code which is generated in "genNeuronKernel()" and "genSynpaseKernel()"). Generated functions include "copyGToDevice()", "copyGFromDevice()", "copyStateToDevice()", "copyStateFromDevice()", "copySpikesFromDevice()", "copySpikesFromDevice()", "copySpikesFromDevice()". The last mentioned function is the function that will initialize the execution on the GPU in the generated simulation engine. All other generated functions are "convenience functions" to handle data transfer from and to the GPU.

Parameters

model	Model description
path	path for code generation
mos	output stream for messages

15.50 GeNNHelperKrnls.cu File Reference

#include <curand_kernel.h>

Macros

#define BlkSz 256

Functions

```
• __global__ void setup_kernel (curandState *state, unsigned long seed, int sizeofResult)
```

```
    template < class T >
        __global__ void generate_random_gpulnput_xorwow (curandState *state, T *result, int sizeofResult, T Rstrength, T Rshift)
```

void xorwow_setup (curandState *devStates, long int sampleSize)

```
15.50.1 Macro Definition Documentation
```

```
15.50.1.1 #define BlkSz 256
```

15.50.2 Function Documentation

```
15.50.2.1 template < class T > __global__ void generate_random_gpulnput_xorwow ( curandState * state, T * result, int sizeofResult, T Rstrength, T Rshift )
```

```
15.50.2.2 __global__ void setup_kernel ( curandState * state, unsigned long seed, int sizeofResult )
```

```
15.50.2.3 void xorwow_setup ( curandState * devStates, long int sampleSize )
```

15.51 global.h File Reference

Global header file containing a few global variables. Part of the code generation section.

```
#include <iostream>
#include <cstring>
#include <string>
#include <sstream>
#include <vector>
#include <cmath>
#include <cuda_runtime.h>
#include "toString.h"
#include <stdint.h>
```

Macros

 #define _GLOBAL_H_ macro for avoiding multiple inclusion during compilation

- int neuronBlkSz
- int synapseBlkSz
- int learnBlkSz
- cudaDeviceProp * deviceProp
- int theDev
- · int hostCount

Global variable containing the number of hosts within the local compute cluster.

· int deviceCount

Global variable containing the number of CUDA devices found on this host.

• int optimiseBlockSize = 1

Flag for signalling whether or not block size optimisation should be performed.

• int UIntSz = sizeof(unsigned int) * 8

size of the unsigned int variable type on the local architecture

• int logUIntSz = (int) (logf((float) UIntSz) / logf(2.0f) + 1e-5f)

logarithm of the size of the unsigned int variable type on the local architecture

• double asGoodAsZero = 1e-19

Global variable that is used when detecting close to zero values, for example when setting sparse connectivity from a dense matrix.

15.51.1 Detailed Description

Global header file containing a few global variables. Part of the code generation section.

This global header file also takes care of including some generally used cuda support header files.

15.51.2 Macro Definition Documentation

15.51.2.1 #define _GLOBAL_H_

macro for avoiding multiple inclusion during compilation

15.51.3 Variable Documentation

15.51.3.1 double asGoodAsZero = 1e-19

Global variable that is used when detecting close to zero values, for example when setting sparse connectivity from a dense matrix.

15.51.3.2 int deviceCount

Global variable containing the number of CUDA devices found on this host.

15.51.3.3 cudaDeviceProp* deviceProp

15.51.3.4 int hostCount

Global variable containing the number of hosts within the local compute cluster.

15.51.3.5 int learnBlkSz

15.51.3.6 int logUIntSz = (int) (logf((float) UIntSz) / logf(2.0f) + 1e-5f)

logarithm of the size of the unsigned int variable type on the local architecture

15.51.3.7 int neuronBlkSz

15.51.3.8 int optimiseBlockSize = 1

Flag for signalling whether or not block size optimisation should be performed.

```
15.51.3.9 int synapseBlkSz
15.51.3.10 int theDev
15.51.3.11 int UIntSz = sizeof(unsigned int) * 8
size of the unsigned int variable type on the local architecture
```

15.52 helper.h File Reference

```
#include <vector>
```

Classes

struct inputSpec

Functions

- ostream & operator<< (ostream &os, inputSpec &I)
- void write_para ()
- void single_var_init_fullrange (int n)
- void single_var_reinit (int n, double fac)
- void copy_var (int src, int trg)
- void var_init_fullrange ()
- · void var_reinit (double fac)
- void truevar_init ()
- void initexpHH ()
- void truevar_initexpHH ()
- void runexpHH (float t)
- void initl (inputSpec &I)

- double sigGNa = 0.1
- double sigENa = 10.0
- double sigGK = 0.1
- double sigEK = 10.0
- double sigGI = 0.1
- double sigEl = 10.0
- double sigC = 0.1
- const double limit [7][2]
- double Vexp
- double mexp
- double hexp
- double nexp
- double gNaexp
- double ENaexp
- double gKexp
- double EKexp
- double glexp
- double Elexp
- double Cexp

```
15.52.1 Function Documentation
15.52.1.1 void copy_var ( int src, int trg )
15.52.1.2 void initexpHH ( )
15.52.1.3 void initl (inputSpec & I)
15.52.1.4 ostream& operator << ( ostream & os, inputSpec & I )
15.52.1.5 void runexpHH ( float t )
15.52.1.6 void single_var_init_fullrange ( int n )
15.52.1.7 void single_var_reinit ( int n, double fac )
15.52.1.8 void truevar_init ( )
15.52.1.9 void truevar_initexpHH ( )
15.52.1.10 void var_init_fullrange ( )
15.52.1.11 void var_reinit ( double fac )
15.52.1.12 void write_para ( )
15.52.2 Variable Documentation
15.52.2.1 double Cexp
15.52.2.2 double EKexp
15.52.2.3 double Elexp
15.52.2.4 double ENaexp
15.52.2.5 double gKexp
15.52.2.6 double glexp
15.52.2.7 double gNaexp
15.52.2.8 double hexp
15.52.2.9 const double limit[7][2]
Initial value:
= {{1.0, 200.0},
                               {0.0, 100.0},
{1.0, 100.0},
                                \{-100.0, -20.0\},\
                               {1.0, 50.0},
{-100.0, -20.0},
{1e-1, 10.0}}
15.52.2.10 double mexp
15.52.2.11 double nexp
15.52.2.12 double sigC = 0.1
15.52.2.13 double sigEK = 10.0
```

```
15.52.2.14 double sigEl = 10.0

15.52.2.15 double sigENa = 10.0

15.52.2.16 double sigGK = 0.1

15.52.2.17 double sigGl = 0.1

15.52.2.18 double sigGNa = 0.1

15.52.2.19 double Vexp
```

15.53 HHVClamp.cc File Reference

This file contains the model definition of HHVClamp model. It is used in both the GeNN code generation and the user side simulation code. The HHVClamp model implements a population of unconnected Hodgkin-Huxley neurons that evolve to mimick a model run on the CPU, using genetic algorithm techniques.

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "HHVClampParameters.h"
```

Macros

#define DT 0.25

This defines the global time step at which the simulation will run.

Functions

• void modelDefinition (NNmodel &model)

This function defines the HH model with variable parameters.

Variables

- double myHH_ini [11]double * myHH_p = NULL
- 15.53.1 Detailed Description

This file contains the model definition of HHVClamp model. It is used in both the GeNN code generation and the user side simulation code. The HHVClamp model implements a population of unconnected Hodgkin-Huxley neurons that evolve to mimick a model run on the CPU, using genetic algorithm techniques.

```
15.53.2 Macro Definition Documentation
```

15.53.2.1 #define DT 0.25

This defines the global time step at which the simulation will run.

15.53.3 Function Documentation

15.53.3.1 void modelDefinition (NNmodel & model)

This function defines the HH model with variable parameters.

```
15.53.4 Variable Documentation
```

15.53.4.1 double myHH_ini[11]

Initial value:

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207,
    120.0,
    55.0,
    36.0,
    -72.0,
    0.3,
    -50.0,
    1.0
```

15.53.4.2 double * myHH_p = NULL

15.54 HHVClampParameters.h File Reference

Macros

- #define NPOP 5000
- #define TOTALT 1000
- #define fixGPU 0

15.54.1 Macro Definition Documentation

```
15.54.1.1 #define fixGPU 0
```

15.54.1.2 #define NPOP 5000

15.54.1.3 #define TOTALT 1000

15.55 hr_time.cpp File Reference

This file contains the implementation of the CStopWatch class that provides a simple timing tool based on the system clock.

```
#include <cstdio>
#include "hr_time.h"
```

Macros

#define HR_TIMER

15.55.1 Detailed Description

This file contains the implementation of the CStopWatch class that provides a simple timing tool based on the system clock.

15.55.2 Macro Definition Documentation

15.55.2.1 #define HR_TIMER

15.56 hr_time.h File Reference

This header file contains the definition of the CStopWatch class that implements a simple timing tool using the system clock.

```
#include <sys/time.h>
```

Classes

- struct stopWatch
- · class CStopWatch

15.56.1 Detailed Description

This header file contains the definition of the CStopWatch class that implements a simple timing tool using the system clock.

15.57 Izh_sim_sparse.cu File Reference

```
#include <iostream>
#include <fstream>
#include "Izh_sparse_sim.h"
#include "../GeNNHelperKrnls.cu"
```

Functions

• int main (int argc, char *argv[])

15.57.1 Function Documentation

```
15.57.1.1 int main ( int argc, char * argv[])
```

15.58 Izh_sparse.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include <vector>
#include "sizes.h"
```

Macros

• #define DT 1.0

Functions

• void modelDefinition (NNmodel &model)

```
• std::vector< unsigned int > neuronPSize
    • std::vector< unsigned int > neuronVSize
    • std::vector< unsigned int > synapsePSize
    • scalar meanInpExc = 5.0
    • scalar meanInpInh = 2.0
    • double * exclzh_p = NULL
    double * inhlzh_p = NULL
    • double IzhExc_ini [6]
    • double lzhlnh_ini [6]
    double * SynIzh_p = NULL
    double * postExpP = NULL
    double * postSynV = NULL
    • double Synlzh_ini [1]
15.58.1 Macro Definition Documentation
15.58.1.1 #define DT 1.0
15.58.2 Function Documentation
15.58.2.1 void modelDefinition ( NNmodel & model )
15.58.3 Variable Documentation
15.58.3.1 double* exclzh_p = NULL
15.58.3.2 double* inhlzh_p = NULL
15.58.3.3 double lzhExc_ini[6]
Initial value:
= {
        -65.0,
        0.0,
        0.02,
        -65.0,
         8.0
15.58.3.4 double lzhlnh_ini[6]
Initial value:
= {
         0.02,
        0.25,
        -65.0,
         2.0
```

```
15.58.3.5 scalar meanInpExc = 5.0
15.58.3.6 scalar meaninpinh = 2.0
15.58.3.7 std::vector<unsigned int> neuronPSize
15.58.3.8 std::vector<unsigned int> neuronVSize
15.58.3.9 double* postExpP = NULL
15.58.3.10 double* postSynV = NULL
15.58.3.11 std::vector<unsigned int> synapsePSize
15.58.3.12 double Synlzh_ini[1]
Initial value:
   0.0
15.58.3.13 double * SynIzh_p = NULL
15.59 Izh_sparse_model.cc File Reference
#include "Izh_sparse_CODE/runner.cc"
#include "../../lib/include/numlib/randomGen.h"
#include "../../lib/include/numlib/gauss.h"
#include "Izh_sparse_model.h"
Macros
    • #define _IZH_SPARSE_MODEL_CC_
Variables
   · randomGauss RG
    · randomGen R
15.59.1 Macro Definition Documentation
15.59.1.1 #define _IZH_SPARSE_MODEL_CC_
15.59.2 Variable Documentation
15.59.2.1 randomGen R
15.59.2.2 randomGauss RG
15.60 Izh sparse model.h File Reference
Classes
```

class classIzh

15.61 Izh_sparse_sim.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "Izh_sparse.cc"
#include "Izh_sparse_model.cc"
```

Macros

- #define DBG_SIZE 5000
- #define T_REPORT_TME 5000.0
- #define TOTAL_TME 5000.0

Variables

- float t = 0.0f
- unsigned int iT = 0
- · CStopWatch timer
- 15.61.1 Macro Definition Documentation
- 15.61.1.1 #define DBG_SIZE 5000
- 15.61.1.2 #define T_REPORT_TME 5000.0
- 15.61.1.3 #define TOTAL_TME 5000.0
- 15.61.2 Variable Documentation
- 15.61.2.1 unsigned int iT = 0
- 15.61.2.2 float t = 0.0f
- 15.61.2.3 CStopWatch timer

15.62 map_classol.cc File Reference

```
#include "map_classol.h"
#include "MBody1_CODE/runner.cc"
```

Macros

 #define _MAP_CLASSOL_CC_ macro for avoiding multiple inclusion during compilation

15.62.1 Macro Definition Documentation

15.62.1.1 #define _MAP_CLASSOL_CC_

macro for avoiding multiple inclusion during compilation

15.63 map_classol.cc File Reference

```
#include "map_classol.h"
#include "MBody_delayedSyn_CODE/runner.cc"
```

Macros

• #define _MAP_CLASSOL_CC_

macro for avoiding multiple inclusion during compilation

15.63.1 Macro Definition Documentation

```
15.63.1.1 #define _MAP_CLASSOL_CC_
```

macro for avoiding multiple inclusion during compilation

15.64 map_classol.cc File Reference

```
#include "map_classol.h"
#include "MBody_individualID_CODE/runner.cc"
```

Macros

 #define _MAP_CLASSOL_CC_ macro for avoiding multiple inclusion during compilation

15.64.1 Macro Definition Documentation

```
15.64.1.1 #define _MAP_CLASSOL_CC_
```

macro for avoiding multiple inclusion during compilation

15.65 map_classol.cc File Reference

```
#include "MBody_userdef_CODE/runner.cc"
#include "sparseUtils.cc"
#include "map_classol.h"
```

Macros

 #define _MAP_CLASSOL_CC_ macro for avoiding multiple inclusion during compilation

15.65.1 Macro Definition Documentation

15.65.1.1 #define _MAP_CLASSOL_CC_

macro for avoiding multiple inclusion during compilation

15.66 map_classol.h File Reference

Classes

· class classol

This class coontains the methods for running the MBody1 example model.

15.67 map_classol.h File Reference

Classes

· class classol

This class coontains the methods for running the MBody1 example model.

15.68 map_classol.h File Reference

Classes

· class classol

This class cpontains the methods for running the MBody1 example model.

15.69 map_classol.h File Reference

Classes

· class classol

This class coontains the methods for running the MBody1 example model.

15.70 MBody1.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "../../userproject/include/sizes.h"
```

Macros

• #define DT 0.1

This defines the global time step at which the simulation will run.

Functions

· void modelDefinition (NNmodel &model)

This function defines the MBody1 model, and it is a good example of how networks should be defined.

- double myPOI_p [4]
- double myPOI_ini [4]
- double stdTM_p [7]
- double stdTM_ini [4]

```
    double myPNKC_p [3]
```

- double postExpPNKC [2]
- double myPNLHI_p [3]
- double postExpPNLHI [2]
- double myLHIKC_p [4]
- double gLHIKC = 0.006
- double postExpLHIKC [2]
- double myKCDN_p [13]
- double postExpKCDN [2]
- double myDNDN_p [4]
- double gDNDN = 0.01
- double postExpDNDN [2]
- double * postSynV = NULL

15.70.1 Macro Definition Documentation

```
15.70.1.1 #define DT 0.1
```

This defines the global time step at which the simulation will run.

```
15.70.2 Function Documentation
```

```
15.70.2.1 void modelDefinition ( NNmodel & model )
```

This function defines the MBody1 model, and it is a good example of how networks should be defined.

```
15.70.3 Variable Documentation
```

```
15.70.3.1 double gDNDN = 0.01
```

15.70.3.2 double gLHIKC = 0.006

15.70.3.3 double myDNDN_p[4]

Initial value:

```
= {
  -92.0,
  -30.0,
  8.0,
  50.0
}
```

15.70.3.4 double myKCDN_p[13]

```
= {
    0.0,
    -20.0,
    5.0,
    25.0,
    100.0,
    50000.0,
    100000.0,
    0.03,
    33.33,
    10.0,
    0.00006
```

15.70.3.5 double myLHIKC_p[4]

```
Initial value:
```

```
= {
    -92.0,
    -40.0,
    3.0,
    50.0
```

15.70.3.6 double myPNKC_p[3]

Initial value:

```
= {
    0.0,
    -20.0,
    1.0
```

15.70.3.7 double myPNLHI_p[3]

Initial value:

```
= {
    0.0,
    -20.0,
    1.0
```

15.70.3.8 double myPOI_ini[4]

Initial value:

```
= {
-60.0,
0,
-10.0,
```

15.70.3.9 double myPOI_p[4]

Initial value:

```
= {
    0.1,
    2.5,
    20.0,
    -60.0
```

15.70.3.10 double postExpDNDN[2]

Initial value:

```
= {
8.0,
-92.0
```

15.70.3.11 double postExpKCDN[2]

```
= {
    5.0,
    0.0
}
```

15.70.3.12 double postExpLHIKC[2]

Initial value:

```
={
3.0,
-92.0
```

15.70.3.13 double postExpPNKC[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.70.3.14 double postExpPNLHI[2]

Initial value:

```
= {
1.0,
0.0
```

15.70.3.15 double* postSynV = NULL

15.70.3.16 double stdTM_ini[4]

Initial value:

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207
```

15.70.3.17 double stdTM_p[7]

Initial value:

```
= {
    7.15,
    50.0,
    1.43,
    -95.0,
    0.02672,
    -63.563,
    0.143
```

15.71 MBody1.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "sizes.h"
```

Macros

#define DT 0.1

This defines the global time step at which the simulation will run.

Functions

· void modelDefinition (NNmodel &model)

This function defines the MBody1 model, and it is a good example of how networks should be defined.

Variables

- double myPOI p [4]
- double myPOI_ini [3]
- double stdTM_p [7]
- double stdTM_ini [4]
- double * myPNKC_p = NULL
- double myPNKC_ini [1]
- double postExpPNKC [2]
- double * myPNLHI_p = NULL
- double myPNLHI_ini [1]
- double postExpPNLHI [2]
- double myLHIKC_p [2]
- double myLHIKC_ini [1]
- double postExpLHIKC [2]
- double myKCDN_p [10]
- double myKCDN_ini [2]
- double postExpKCDN [2]
- double myDNDN_p [2]
- double myDNDN_ini [1]
- double postExpDNDN [2]
- double * postSynV = NULL

15.71.1 Macro Definition Documentation

15.71.1.1 #define DT 0.1

This defines the global time step at which the simulation will run.

15.71.2 Function Documentation

```
15.71.2.1 void modelDefinition ( NNmodel & model )
```

This function defines the MBody1 model, and it is a good example of how networks should be defined.

15.71.3 Variable Documentation

15.71.3.1 double myDNDN_ini[1]

```
={
    5.0/_NLB
```

```
15.71.3.2 double myDNDN_p[2]
```

```
Initial value:
```

```
= {
    -30.0,
    50.0
}
```

15.71.3.3 double myKCDN_ini[2]

Initial value:

```
={
    0.01,
    0.01,
}
```

15.71.3.4 double myKCDN_p[10]

Initial value:

```
= {
    50.0,
    50.0,
    50000.0,
    100000.0,
    200.0,
    0.015,
    0.0075,
    33.33,
    10.0,
    0.00006
```

15.71.3.5 double myLHIKC_ini[1]

Initial value:

```
= {
    1.0/_NLHI
```

15.71.3.6 double myLHIKC_p[2]

Initial value:

```
= {
    -40.0,
    50.0
}
```

15.71.3.7 double myPNKC_ini[1]

Initial value:

```
= {
 0.01
}
```

15.71.3.8 double* myPNKC_p = NULL

15.71.3.9 double myPNLHI_ini[1]

```
= {
 0.0
```

```
15.71.3.10 double* myPNLHI_p = NULL
```

15.71.3.11 double myPOI_ini[3]

Initial value:

```
= {
-60.0,
0,
-10.0
```

15.71.3.12 double myPOI_p[4]

Initial value:

```
= {
    0.1,
    2.5,
    20.0,
    -60.0
```

15.71.3.13 double postExpDNDN[2]

Initial value:

```
={
2.5,
-92.0
}
```

15.71.3.14 double postExpKCDN[2]

Initial value:

```
= {
5.0,
0.0
```

15.71.3.15 double postExpLHIKC[2]

Initial value:

```
={
1.5,
-92.0
```

15.71.3.16 double postExpPNKC[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.71.3.17 double postExpPNLHI[2]

```
= {
1.0,
0.0
```

```
15.71.3.18 double* postSynV = NULL
```

15.71.3.19 double stdTM_ini[4]

Initial value:

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207
}
```

15.71.3.20 double stdTM_p[7]

Initial value:

```
= {
    7.15,
    50.0,
    1.43,
    -95.0,
    0.02672,
    -63.563,
    0.143
```

15.72 MBody_delayedSyn.cc File Reference

This file contains the model definition of the mushroom body "MBody_delayedSyn" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim).

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "sizes.h"
```

Macros

• #define DT 0.1

This defines the global time step at which the simulation will run.

Functions

· void modelDefinition (NNmodel &model)

This function defines the MBody_delayedSyn model, and it is a good example of how networks should be defined.

- double myPOI_p [4]
- double myPOI_ini [3]
- double stdTM_p [7]
- double stdTM_ini [4]
- double * myPNKC_p = NULL
- double myPNKC_ini [1]
- double postExpPNKC [2]
- double * myPNLHI_p = NULL
- double myPNLHI_ini [1]
- double postExpPNLHI [2]

- double myLHIKC_p [2]
- double myLHIKC_ini [1]
- double postExpLHIKC [2]
- double myKCDN_p [10]
- double myKCDN_ini [2]
- double postExpKCDN [2]
- double myDNDN_p [2]
- double myDNDN_ini [1]
- double postExpDNDN [2]
- double * postSynV = NULL

15.72.1 Detailed Description

This file contains the model definition of the mushroom body "MBody_delayedSyn" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim).

15.72.2 Macro Definition Documentation

15.72.2.1 #define DT 0.1

This defines the global time step at which the simulation will run.

15.72.3 Function Documentation

```
15.72.3.1 void modelDefinition ( NNmodel & model )
```

This function defines the MBody_delayedSyn model, and it is a good example of how networks should be defined.

15.72.4 Variable Documentation

15.72.4.1 double myDNDN_ini[1]

Initial value:

```
={
    5.0/_NLB
}
```

15.72.4.2 double myDNDN_p[2]

Initial value:

```
= {
    -30.0,
    50.0
```

15.72.4.3 double myKCDN_ini[2]

```
={
0.01,
0.01,
```

15.72.4.4 double myKCDN_p[10]

```
Initial value:
```

```
= {
    50.0,
    50.00,
    50000.0,
    100000.0,
    200.0,
    0.0015,
    0.0075,
    33.33,
    10.0,
    0.00006
```

15.72.4.5 double myLHIKC_ini[1]

Initial value:

```
= {
    1.0/_NLHI
}
```

15.72.4.6 double myLHIKC_p[2]

Initial value:

```
= {
    -40.0,
    50.0
}
```

15.72.4.7 double myPNKC_ini[1]

Initial value:

```
= {
 0.01
```

15.72.4.8 double* myPNKC_p = NULL

15.72.4.9 double myPNLHI_ini[1]

Initial value:

```
= {
 0.0
}
```

15.72.4.10 double* myPNLHI_p = NULL

15.72.4.11 double myPOI_ini[3]

```
= {
-60.0,
0,
-10.0
```

15.72.4.12 double myPOI_p[4]

```
Initial value:
```

```
= {
    0.1,
    2.5,
    20.0,
    -60.0
}
```

15.72.4.13 double postExpDNDN[2]

Initial value:

```
={
2.5,
-92.0
```

15.72.4.14 double postExpKCDN[2]

Initial value:

```
={
5.0,
0.0
```

15.72.4.15 double postExpLHIKC[2]

Initial value:

```
= {
1.5,
-92.0
```

15.72.4.16 double postExpPNKC[2]

Initial value:

```
={
1.0,
0.0
}
```

15.72.4.17 double postExpPNLHI[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.72.4.18 double* postSynV = NULL

15.72.4.19 double stdTM_ini[4]

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207
```

15.72.4.20 double stdTM_p[7]

Initial value:

```
= {
    7.15,
    50.0,
    1.43,
    -95.0,
    0.02672,
    -63.563,
    0.143
}
```

15.73 MBody_individualID.cc File Reference

This file contains the model definition of the mushroom body "MBody_incividualID" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim). It uses INDIVIDUALID for the connections from AL to MB allowing quite large numbers of PN and KC.

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "sizes.h"
```

Macros

• #define DT 0.1

This defines the global time step at which the simulation will run.

Functions

· void modelDefinition (NNmodel &model)

This function defines the MBody1 model, and it is a good example of how networks should be defined.

- double myPOI_p [4]
- double myPOI_ini [3]
- double stdTM_p [7]
- double stdTM_ini [4]
- double * myPNKC_p = NULL
- double myPNKC ini [1]
- double postExpPNKC [2]
- double * myPNLHI_p = NULL
- double myPNLHI ini [1]
- double postExpPNLHI [2]
- double myLHIKC_p [2]
- double myLHIKC_ini [1]
- double postExpLHIKC [2]
- double myKCDN_p [11]
- double myKCDN_ini [2]
- double postExpKCDN [2]
- double myDNDN p [2]
- double myDNDN_ini [1]
- double postExpDNDN [2]
- double * postSynV = NULL

15.73.1 Detailed Description

This file contains the model definition of the mushroom body "MBody_incividualID" model. It is used in both the GeNN code generation and the user side simulation code (class classol, file classol_sim). It uses INDIVIDUALID for the connections from AL to MB allowing quite large numbers of PN and KC.

15.73.2 Macro Definition Documentation

```
15.73.2.1 #define DT 0.1
```

This defines the global time step at which the simulation will run.

15.73.3 Function Documentation

```
15.73.3.1 void modelDefinition ( NNmodel & model )
```

This function defines the MBody1 model, and it is a good example of how networks should be defined.

15.73.4 Variable Documentation

```
15.73.4.1 double myDNDN_ini[1]
```

Initial value:

```
={
    5.0/_NLB
}
```

15.73.4.2 double myDNDN_p[2]

Initial value:

```
= {
-30.0,
50.0
```

15.73.4.3 double myKCDN_ini[2]

Initial value:

```
= {
    0.01,
    0.01,
```

15.73.4.4 double myKCDN_p[11]

```
= {
    50.0,
    50.0,
50000.0,
100000.0,
200.0,
0.015,
0.0075,
33.33,
10.0,
0.00006
```

```
15.73.4.5 double myLHIKC_ini[1]
```

Initial value:

```
= {
    1.0/_NLHI
}
```

15.73.4.6 double myLHIKC_p[2]

Initial value:

```
= {
    -40.0,
    50.0
}
```

15.73.4.7 double myPNKC_ini[1]

Initial value:

```
= {
   gPNKC_GLOBAL
}
```

15.73.4.8 double* myPNKC_p = NULL

15.73.4.9 double myPNLHI_ini[1]

Initial value:

```
= {
 0.0
```

15.73.4.10 double* myPNLHI_p = NULL

15.73.4.11 double myPOI_ini[3]

Initial value:

```
= {
-60.0,
0,
-10.0
}
```

15.73.4.12 double myPOI_p[4]

Initial value:

```
= {
    0.1,
    2.5,
    20.0,
    -60.0
```

15.73.4.13 double postExpDNDN[2]

```
= {
2.5,
-92.0
```

```
15.73.4.14 double postExpKCDN[2]
```

Initial value:

```
= {
    5.0,
    0.0
```

15.73.4.15 double postExpLHIKC[2]

Initial value:

```
={
1.5,
-92.0
```

15.73.4.16 double postExpPNKC[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.73.4.17 double postExpPNLHI[2]

Initial value:

```
= {
1.0,
0.0
```

15.73.4.18 double* postSynV = NULL

15.73.4.19 double stdTM_ini[4]

Initial value:

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207
```

15.73.4.20 double stdTM_p[7]

```
= {
    7.15,
    50.0,
    1.43,
    -95.0,
    0.02672,
    -63.563,
    0.143
```

15.74 MBody_userdef.cc File Reference

This file contains the model definition of the mushroom body model. tis used in the GeNN code generation and the user side simulation code (class classol, file classol_sim).

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "sizes.h"
```

Classes

· class pwSTDP_userdef

TODO This class definition may be code-generated in a future release.

Macros

• #define DT 0.1

This defines the global time step at which the simulation will run.

#define TIMING

Functions

· void modelDefinition (NNmodel &model)

This function defines the MBody1 model with user defined synapses.

- double myPOI_p [4]
- double myPOI_ini [3]
- double stdTM_p [7]
- double stdTM_ini [4]
- double * myPNKC_p = NULL
- double myPNKC_ini [1]
- double postExpPNKC [2]
- double * myPNLHI_p = NULL
- double myPNLHI_ini [1]
- double postExpPNLHI [2]
- double myLHIKC_p [2]
- double myLHIKC_ini [1]
- double postExpLHIKC [2]
- double myKCDN_p [11]
- double myKCDN_ini [2]
- double postExpKCDN [2]
- double myDNDN_p [2]
- double myDNDN_ini [1]
- double postExpDNDN [2]
- double * postSynV = NULL
- double postSynV EXPDECAY EVAR [1]
- scalar * gpPNKC = new scalar[_NAL*_NMB]
- scalar * gpKCDN = new scalar[_NMB*_NLB]

15.74.1 Detailed Description

This file contains the model definition of the mushroom body model. tis used in the GeNN code generation and the user side simulation code (class classol, file classol_sim).

15.74.2 Macro Definition Documentation

```
15.74.2.1 #define DT 0.1
```

This defines the global time step at which the simulation will run.

```
15.74.2.2 #define TIMING
```

15.74.3 Function Documentation

```
15.74.3.1 void modelDefinition ( NNmodel & model )
```

This function defines the MBody1 model with user defined synapses.

```
15.74.4 Variable Documentation
```

```
15.74.4.1 scalar* gpKCDN = new scalar[_NMB*_NLB]
```

15.74.4.3 double myDNDN_ini[1]

Initial value:

```
={
5.0/_NLB
```

15.74.4.4 double myDNDN_p[2]

Initial value:

```
= {
 -30.0,
 50.0
```

15.74.4.5 double myKCDN_ini[2]

Initial value:

```
={
    0.01,
    0.01,
```

15.74.4.6 double myKCDN_p[11]

```
= {
    -20.0,
    50.0,
    50.0,
    50000.0,
```

```
200.0,
0.015,
0.0075,
33.33,
10.0,
0.00006
```

15.74.4.7 double myLHIKC_ini[1]

Initial value:

```
= {
    1.0/_NLHI
}
```

15.74.4.8 double myLHIKC_p[2]

Initial value:

```
= {
    -40.0,
    50.0
}
```

15.74.4.9 double myPNKC_ini[1]

Initial value:

```
= {
 0.01
}
```

15.74.4.10 double* myPNKC_p = NULL

15.74.4.11 double myPNLHI_ini[1]

Initial value:

```
= {
```

15.74.4.12 double* myPNLHI_p = NULL

15.74.4.13 double myPOI_ini[3]

Initial value:

```
= {
-60.0,
0,
-10.0
```

15.74.4.14 double myPOI_p[4]

```
= {
    0.1,
    2.5,
    20.0,
    -60.0
```

```
15.74.4.15 double postExpDNDN[2]
```

```
Initial value:
```

```
= {
2.5,
-92.0
```

15.74.4.16 double postExpKCDN[2]

Initial value:

```
= {
    5.0,
    0.0
}
```

15.74.4.17 double postExpLHIKC[2]

Initial value:

```
={
1.5,
-92.0
}
```

15.74.4.18 double postExpPNKC[2]

Initial value:

```
={
1.0,
0.0
```

15.74.4.19 double postExpPNLHI[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.74.4.20 double* postSynV = NULL

15.74.4.21 double postSynV_EXPDECAY_EVAR[1]

Initial value:

```
= {
0
}
```

15.74.4.22 double stdTM_ini[4]

```
= {
    -60.0,
    0.0529324,
    0.3176767,
    0.5961207
```

15.74.4.23 double stdTM_p[7]

Initial value:

```
= {
    7.15,
    50.0,
    1.43,
    -95.0,
    0.02672,
    -63.563,
    0.143
```

15.75 Model_Schmuker_2014_classifier.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

- #define DT 0.5
- #define NUM VR 10
- #define NUM_FEATURES 4
- #define NUM_CLASSES 3
- #define NETWORK SCALE 10
- #define CLUST_SIZE_AN (NETWORK_SCALE * 6)
- #define CLUST_SIZE_PN (NETWORK_SCALE * 6)
- #define CLUST_SIZE_RN (NETWORK_SCALE * 6)
- #define SYNAPSE_TAU_RNPN 1.0
- #define SYNAPSE_TAU_PNPN 5.5
- #define SYNAPSE_TAU_PNAN 1.0
- #define SYNAPSE_TAU_ANAN 8.0

Functions

void modelDefinition (NNmodel &model)

15.75.1 Macro Definition Documentation

- 15.75.1.1 #define CLUST_SIZE_AN (NETWORK_SCALE * 6)
- 15.75.1.2 #define CLUST_SIZE_PN (NETWORK_SCALE * 6)
- 15.75.1.3 #define CLUST_SIZE_RN (NETWORK_SCALE * 6)
- 15.75.1.4 #define DT 0.5
- 15.75.1.5 #define NETWORK_SCALE 10
- 15.75.1.6 #define NUM_CLASSES 3
- 15.75.1.7 #define NUM_FEATURES 4
- 15.75.1.8 #define NUM_VR 10
- 15.75.1.9 #define SYNAPSE_TAU_ANAN 8.0

```
15.75.1.10 #define SYNAPSE_TAU_PNAN 1.0

15.75.1.11 #define SYNAPSE_TAU_PNPN 5.5

15.75.1.12 #define SYNAPSE_TAU_RNPN 1.0

15.75.2 Function Documentation

15.75.2.1 void modelDefinition ( NNmodel & model )

15.76 modelSpec.cc File Reference

#include "utils.h"
```

Macros

 #define _MODELSPEC_CC_ macro for avoiding multiple inclusion during compilation

Functions

· void initGeNN ()

Method for GeNN initialisation (by preparing standard models)

15.76.1 Macro Definition Documentation

```
15.76.1.1 #define _MODELSPEC_CC_
```

macro for avoiding multiple inclusion during compilation

15.76.2 Function Documentation

```
15.76.2.1 void initGeNN ( )
```

Method for GeNN initialisation (by preparing standard models)

15.77 modelSpec.h File Reference

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of NNmodel for defining a neuronal network model. Part of the code generation and generated code sections.

```
#include <vector>
#include "global.h"
```

Classes

- · class dpclass
- struct neuronModel

class (struct) for specifying a neuron model.

struct postSynModel

Structure to hold the information that defines a post-synaptic model (a model of how synapses affect post-synaptic neuron variables, classically in the form of a synaptic current). It also allows to define an equation for the dynamics that can be applied to the summed synaptic input variable "insyn".

class weightUpdateModel

Structure to hold the information that defines a weightupdate model (a model of how spikes affect synaptic (and/or) (mostly) post-synaptic neuron variables. It also allows to define changes in response to post-synaptic spikes/spike-like events.

class NNmodel

Structure to hold the information that defines synapse dynamics (a model of how synapse variables change over time, independent of or in addition to changes when spikes occur).

Macros

• #define _MODELSPEC_H_

macro for avoiding multiple inclusion during compilation

- #define MAXNRN 7
- #define SYNTYPENO 4
- #define NOINP 0

Macro attaching the name NOINP (no input) to 0.

#define CONSTINP 1

Macro attaching the name CONSTINP (constant input) to 1.

#define MATINP 2

Macro attaching the name MATINP (explicit input defined as a matrix) to 2.

• #define INPRULE 3

Macro attaching the name INPRULE (explicit dynamic input defined as a rule) to 3.

• #define RANDNINP 4

Macro attaching the name RANDNINP (Random input with Gaussian distribution, calculated real time on the device by the generated code) to 4 (TODO, not implemented yet)

• #define ALLTOALL 0

Macro attaching the label "ALLTOALL" to connectivity type 0.

#define DENSE 1

Macro attaching the label "DENSE" to connectivity type 1.

• #define SPARSE 2

Macro attaching the label "SPARSE" to connectivity type 2.

#define INDIVIDUALG 0

Macro attaching the label "INDIVIDUALG" to method 0 for the definition of synaptic conductances.

• #define GLOBALG 1

Macro attaching the label "GLOBALG" to method 1 for the definition of synaptic conductances.

• #define INDIVIDUALID 2

Macro attaching the label "INDIVIDUALID" to method 2 for the definition of synaptic conductances.

• #define NO DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

• #define NOLEARNING 0

Macro attaching the label "NOLEARNING" to flag 0.

• #define LEARNING 1

Macro attaching the label "LEARNING" to flag 1.

#define EXITSYN 0

Macro attaching the label "EXITSYN" to flag 0 (excitatory synapse)

#define INHIBSYN 1

Macro attaching the label "INHIBSYN" to flag 1 (inhibitory synapse)

• #define TRUE 1

Macro attaching the label "TRUE" to value 1.

#define FALSE 0

Macro attaching the label "FALSE" to value 0.

#define CPU 0

Macro attaching the label "CPU" to flag 0.

#define GPU 1

Macro attaching the label "GPU" to flag 1.

#define GENN FLOAT 0

Macro attaching the label "GENN_FLOAT" to flag 0. Used by NNModel::setPrecision()

• #define GENN DOUBLE 1

Macro attaching the label "GENN_DOUBLE" to flag 1. Used by NNModel::setPrecision()

#define AUTODEVICE -1

Macro attaching the label AUTODEVICE to flag -1. Used by setGPUDevice.

#define SPK_THRESH_STDP 0.0f

Macro defining the spiking threshold for the purposes of STDP.

#define MAXPOSTSYN 2

Functions

void initGeNN ()

Method for GeNN initialisation (by preparing standard models)

Variables

- unsigned int GeNNReady = 0
- unsigned int MAPNEURON

variable attaching the name "MAPNEURON"

unsigned int POISSONNEURON

variable attaching the name "POISSONNEURON"

unsigned int TRAUBMILES_FAST

variable attaching the name "TRAUBMILES_FAST"

unsigned int TRAUBMILES_ALTERNATIVE

variable attaching the name "TRAUBMILES_ALTERNATIVE"

unsigned int TRAUBMILES_SAFE

variable attaching the name "TRAUBMILES_SAFE"

unsigned int TRAUBMILES

variable attaching the name "TRAUBMILES"

unsigned int TRAUBMILES_PSTEP

variable attaching the name "TRAUBMILES_PSTEP"

unsigned int IZHIKEVICH

variable attaching the name "IZHIKEVICH"

unsigned int IZHIKEVICH_V

variable attaching the name "IZHIKEVICH_V"

• unsigned int SPIKESOURCE

variable attaching the name "SPIKESOURCE"

• unsigned int NSYNAPSE

Variable attaching the name NSYNAPSE to predefined synapse type 0, which is a non-learning synapse.

unsigned int NGRADSYNAPSE

Variable attaching the name NGRADSYNAPSE to predefined synapse type 1 which is a graded synapse wrt the presynaptic voltage.

• unsigned int LEARN1SYNAPSE

Variable attaching the name LEARN1SYNAPSE to the predefined synapse type 2 which is a learning using spike timing; uses a primitive STDP rule for learning.

- unsigned int EXPDECAY
- unsigned int IZHIKEVICH_PS

15.77.1 Detailed Description

Header file that contains the class (struct) definition of neuronModel for defining a neuron model and the class definition of NNmodel for defining a neuronal network model. Part of the code generation and generated code sections.

15.77.2 Macro Definition Documentation

15.77.2.1 #define _MODELSPEC_H_

macro for avoiding multiple inclusion during compilation

15.77.2.2 #define ALLTOALL 0

Macro attaching the label "ALLTOALL" to connectivity type 0.

15.77.2.3 #define AUTODEVICE -1

Macro attaching the label AUTODEVICE to flag -1. Used by setGPUDevice.

15.77.2.4 #define CONSTINP 1

Macro attaching the name CONSTINP (constant input) to 1.

15.77.2.5 #define CPU 0

Macro attaching the label "CPU" to flag 0.

15.77.2.6 #define DENSE 1

Macro attaching the label "DENSE" to connectivity type 1.

15.77.2.7 #define EXITSYN 0

Macro attaching the label "EXITSYN" to flag 0 (excitatory synapse)

15.77.2.8 #define FALSE 0

Macro attaching the label "FALSE" to value 0.

15.77.2.9 #define GENN_DOUBLE 1

Macro attaching the label "GENN_DOUBLE" to flag 1. Used by NNModel::setPrecision()

15.77.2.10 #define GENN_FLOAT 0

Macro attaching the label "GENN_FLOAT" to flag 0. Used by NNModel::setPrecision()

15.77.2.11 #define GLOBALG 1

Macro attaching the label "GLOBALG" to method 1 for the definition of synaptic conductances.

15.77.2.12 #define GPU 1

Macro attaching the label "GPU" to flag 1.

15.77.2.13 #define INDIVIDUALG 0

Macro attaching the label "INDIVIDUALG" to method 0 for the definition of synaptic conductances.

15.77.2.14 #define INDIVIDUALID 2

Macro attaching the label "INDIVIDUALID" to method 2 for the definition of synaptic conductances.

15.77.2.15 #define INHIBSYN 1

Macro attaching the label "INHIBSYN" to flag 1 (inhibitory synapse)

15.77.2.16 #define INPRULE 3

Macro attaching the name INPRULE (explicit dynamic input defined as a rule) to 3.

15.77.2.17 #define LEARNING 1

Macro attaching the label "LEARNING" to flag 1.

15.77.2.18 #define MATINP 2

Macro attaching the name MATINP (explicit input defined as a matrix) to 2.

15.77.2.19 #define MAXNRN 7

15.77.2.20 #define MAXPOSTSYN 2

15.77.2.21 #define NO_DELAY 0

Macro used to indicate no synapse delay for the group (only one queue slot will be generated)

15.77.2.22 #define NOINP 0

Macro attaching the name NOINP (no input) to 0.

15.77.2.23 #define NOLEARNING 0

Macro attaching the label "NOLEARNING" to flag 0.

15.77.2.24 #define RANDNINP 4

Macro attaching the name RANDNINP (Random input with Gaussian distribution, calculated real time on the device by the generated code) to 4 (TODO, not implemented yet)

15.77.2.25 #define SPARSE 2

Macro attaching the label "SPARSE" to connectivity type 2.

15.77.2.26 #define SPK_THRESH_STDP 0.0f

Macro defining the spiking threshold for the purposes of STDP.

15.77.2.27 #define SYNTYPENO 4

15.77.2.28 #define TRUE 1

Macro attaching the label "TRUE" to value 1.

15.77.3 Function Documentation

15.77.3.1 void initGeNN ()

Method for GeNN initialisation (by preparing standard models)

15.77.4 Variable Documentation

15.77.4.1 unsigned int EXPDECAY

15.77.4.2 unsigned int GeNNReady = 0

15.77.4.3 unsigned int IZHIKEVICH

variable attaching the name "IZHIKEVICH"

15.77.4.4 unsigned int IZHIKEVICH_PS

15.77.4.5 unsigned int IZHIKEVICH_V

variable attaching the name "IZHIKEVICH V"

15.77.4.6 unsigned int LEARN1SYNAPSE

Variable attaching the name LEARN1SYNAPSE to the predefined synapse type 2 which is a learning using spike timing; uses a primitive STDP rule for learning.

15.77.4.7 unsigned int MAPNEURON

variable attaching the name "MAPNEURON"

15.77.4.8 unsigned int NGRADSYNAPSE

Variable attaching the name NGRADSYNAPSE to predefined synapse type 1 which is a graded synapse wrt the presynaptic voltage.

15.77.4.9 unsigned int NSYNAPSE

Variable attaching the name NSYNAPSE to predefined synapse type 0, which is a non-learning synapse.

15.77.4.10 unsigned int POISSONNEURON

variable attaching the name "POISSONNEURON"

15.77.4.11 unsigned int SPIKESOURCE

variable attaching the name "SPIKESOURCE"

15.77.4.12 unsigned int TRAUBMILES

variable attaching the name "TRAUBMILES"

15.77.4.13 unsigned int TRAUBMILES_ALTERNATIVE

variable attaching the name "TRAUBMILES_ALTERNATIVE"

15.77.4.14 unsigned int TRAUBMILES_FAST

variable attaching the name "TRAUBMILES_FAST"

15.77.4.15 unsigned int TRAUBMILES_PSTEP

variable attaching the name "TRAUBMILES_PSTEP"

15.77.4.16 unsigned int TRAUBMILES_SAFE

variable attaching the name "TRAUBMILES_SAFE"

15.78 OneComp.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "../../userproject/include/sizes.h"
```

Macros

#define DT 1.0

Functions

• void modelDefinition (NNmodel &model)

Variables

```
• double exlzh_p [4]
```

- double exlzh_ini [2]
- double mySyn_p [3]
- double postExp [2]
- double * postSynV = NULL
- float inplzh1 = 4.0

15.78.1 Macro Definition Documentation

```
15.78.1.1 #define DT 1.0
```

15.78.2 Function Documentation

15.78.2.1 void modelDefinition (NNmodel & model)

15.78.3 Variable Documentation

15.78.3.1 double exlzh_ini[2]

Initial value:

```
={
-65,
-20
}
```

15.78.3.2 double exlzh_p[4]

```
={
0.02,
0.2,
-65,
6
```

```
15.78.3.3 float inplzh1 = 4.0
15.78.3.4 double mySyn_p[3]
Initial value:
= {
0.0,
-20.0,
 1.0
15.78.3.5 double postExp[2]
Initial value:
={
1.0,
0.0
15.78.3.6 double* postSynV = NULL
15.79 OneComp_model.cc File Reference
#include "OneComp_CODE/runner.cc"
Macros
   • #define _ONECOMP_MODEL_CC_
15.79.1 Macro Definition Documentation
15.79.1.1 #define _ONECOMP_MODEL_CC_
15.80 OneComp_model.h File Reference
#include "OneComp.cc"
Classes

    class neuronpop

15.81 OneComp_sim.cu File Reference
#include "OneComp_sim.h"
Functions
```

int main (int argc, char *argv[])

```
15.81.1 Function Documentation
```

```
15.81.1.1 int main ( int argc, char * argv[])
```

15.82 OneComp_sim.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "OneComp_model.h"
#include "OneComp_model.cc"
```

Macros

- #define DBG_SIZE 10000
- #define T_REPORT_TME 100.0
- #define TOTAL TME 5000

Variables

- float t = 0.0f
- unsigned int iT = 0
- CStopWatch timer

15.82.1 Macro Definition Documentation

```
15.82.1.1 #define DBG_SIZE 10000
```

- 15.82.1.2 #define T_REPORT_TME 100.0
- 15.82.1.3 #define TOTAL_TME 5000
- 15.82.2 Variable Documentation
- 15.82.2.1 unsigned int iT = 0
- 15.82.2.2 float t = 0.0f
- 15.82.2.3 CStopWatch timer

15.83 PoissonIzh-model.cc File Reference

```
#include "PoissonIzh-model.h"
#include "PoissonIzh_CODE/runner.cc"
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define _POISSONIZHMODEL_CC_

15.83.1 Macro Definition Documentation

15.83.1.1 #define POISSONIZHMODEL_CC_

15.84 PoissonIzh-model.h File Reference

Classes

· class classol

This class coontains the methods for running the MBody1 example model.

15.85 PoissonIzh.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
#include "../../userproject/include/sizes.h"
```

Macros

- #define DT 1.0
- #define _FTYPE GENN_FLOAT
- #define scalar float
- #define SCALAR MIN (float)FLT MIN
- #define SCALAR_MAX (float)FLT_MAX

Functions

· void modelDefinition (NNmodel &model)

Variables

- double myPOI_p [4]
- double myPOI_ini [4]
- double exlzh_p [4]
- double exlzh_ini [2]
- double mySyn_p [3]
- double mySyn_ini [1]
- double postExp [2]
- double * postSynV = NULL

15.85.1 Macro Definition Documentation

- 15.85.1.1 #define _FTYPE GENN_FLOAT
- 15.85.1.2 #define DT 1.0
- 15.85.1.3 #define scalar float
- 15.85.1.4 #define SCALAR_MAX (float)FLT_MAX
- 15.85.1.5 #define SCALAR_MIN (float)FLT_MIN
- 15.85.2 Function Documentation

```
15.85.2.1 void modelDefinition ( NNmodel & model )
15.85.3 Variable Documentation
15.85.3.1 double exlzh_ini[2]
Initial value:
         -65,
-20
15.85.3.2 double exlzh_p[4]
Initial value:
= {
         0.02,
         -65,
15.85.3.3 double myPOI_ini[4]
Initial value:
= {
-60.0,
 0,
-10.0
15.85.3.4 double myPOI_p[4]
Initial value:
= {
 1,
2.5,
20.0,
  -60.0
15.85.3.5 double mySyn_ini[1]
Initial value:
= {
0.0
}
15.85.3.6 double mySyn_p[3]
Initial value:
= {
    0.0,
    -20.0,
    1.0
```

15.85.3.7 double postExp[2]

Initial value:

```
= {
1.0,
0.0
```

15.85.3.8 double* postSynV = NULL

15.86 PoissonIzh_sim.cu File Reference

```
#include "PoissonIzh_sim.h"
```

Functions

• int main (int argc, char *argv[])

15.86.1 Function Documentation

```
15.86.1.1 int main ( int argc, char * argv[])
```

15.87 PoissonIzh_sim.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "PoissonIzh.cc"
#include "PoissonIzh-model.h"
#include "PoissonIzh-model.cc"
```

Macros

- #define MYRAND(Y, X) Y = Y * 1103515245 +12345; X= (Y >> 16);
- #define INJECTCURRENT 0
- #define DBG_SIZE 1000
- #define PATTERNNO 100
- #define T_REPORT_TME 1000.0
- #define SYN_OUT_TME 2000.0
- #define TOTAL_TME 5000

Variables

- float t = 0.0f
- unsigned int iT = 0
- scalar InputBaseRate = 2e-02
- CStopWatch timer

```
15.87.1 Macro Definition Documentation
15.87.1.1 #define DBG_SIZE 1000
15.87.1.2 #define INJECTCURRENT 0
15.87.1.3 #define MYRAND( Y, X) Y = Y * 1103515245 +12345; X= (Y >> 16);
15.87.1.4 #define PATTERNNO 100
15.87.1.5 #define SYN_OUT_TME 2000.0
15.87.1.6 #define T_REPORT_TME 1000.0
15.87.1.7 #define TOTAL_TME 5000
15.87.2 Variable Documentation
15.87.2.1 scalar InputBaseRate = 2e-02
15.87.2.2 unsigned int iT = 0
15.87.2.3 float t = 0.0f
15.87.2.4 CStopWatch timer
15.88 postVarsInPostLearn.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

• void modelDefinition (NNmodel &model)

Variables

```
double neuron_p [1]
double neuron_p2 [1]
double neuron_ini [2]
double * synapses_p = NULL
double synapses_ini [1]
double * postSyn_p = NULL
double * postSyn_ini = NULL
```

15.88.1 Macro Definition Documentation

15.88.1.1 #define DT 1.0f

15.88.2 Function Documentation

```
15.88.2.1 void modelDefinition ( NNmodel & model )
15.88.3 Variable Documentation
15.88.3.1 double neuron_ini[2]
Initial value:
= {
0.0,
   0.0
15.88.3.2 double neuron_p[1]
Initial value:
   1.0
15.88.3.3 double neuron_p2[1]
Initial value:
    2.0
15.88.3.4 double* postSyn_ini = NULL
15.88.3.5 double* postSyn_p = NULL
15.88.3.6 double synapses_ini[1]
Initial value:
= { 0.0
15.88.3.7 double* synapses_p = NULL
15.89 postVarsInPostLearn_sparse.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
Macros
   • #define DT 1.0f
```

Functions

• void modelDefinition (NNmodel &model)

```
Variables
```

```
• double neuron_p [1]
    • double neuron_p2 [1]
    • double neuron_ini [2]
    • double * synapses_p = NULL
    • double synapses_ini [1]
    • double * postSyn_p = NULL
    double * postSyn_ini = NULL
15.89.1 Macro Definition Documentation
15.89.1.1 #define DT 1.0f
15.89.2 Function Documentation
15.89.2.1 void modelDefinition ( NNmodel & model )
15.89.3 Variable Documentation
15.89.3.1 double neuron_ini[2]
Initial value:
15.89.3.2 double neuron_p[1]
Initial value:
    1.0
15.89.3.3 double neuron_p2[1]
Initial value:
    2.0
15.89.3.4 double* postSyn_ini = NULL
15.89.3.5 double* postSyn_p = NULL
15.89.3.6 double synapses_ini[1]
Initial value:
    0.0
```

```
15.89.3.7 double* synapses_p = NULL
```

15.90 postVarsInSimCode.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

· void modelDefinition (NNmodel &model)

Variables

```
• double * neuron_p = NULL
```

- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn_p = NULL
- double * postSyn_ini = NULL

15.90.1 Macro Definition Documentation

```
15.90.1.1 #define DT 1.0f
```

15.90.2 Function Documentation

15.90.2.1 void modelDefinition (NNmodel & model)

15.90.3 Variable Documentation

15.90.3.1 double neuron_ini[2]

Initial value:

15.90.3.2 double* neuron_p = NULL

15.90.3.3 double* postSyn_ini = NULL

15.90.3.4 double* postSyn_p = NULL

15.90.3.5 double synapses_ini[1]

```
= {
```

```
15.90.3.6 double* synapses_p = NULL
```

15.91 postVarsInSimCode_sparse.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

· void modelDefinition (NNmodel &model)

Variables

```
• double * neuron p = NULL
```

- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn p = NULL
- double * postSyn_ini = NULL

15.91.1 Macro Definition Documentation

```
15.91.1.1 #define DT 1.0f
```

15.91.2 Function Documentation

15.91.2.1 void modelDefinition (NNmodel & model)

15.91.3 Variable Documentation

15.91.3.1 double neuron_ini[2]

Initial value:

15.91.3.2 double* neuron_p = NULL

15.91.3.3 double* postSyn_ini = NULL

15.91.3.4 double* postSyn_p = NULL

15.91.3.5 double synapses_ini[1]

```
= {
```

```
15.91.3.6 double* synapses_p = NULL
```

15.92 postVarsInSynapseDynamics.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

· void modelDefinition (NNmodel &model)

Variables

```
• double * neuron p = NULL
```

- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn p = NULL
- double * postSyn_ini = NULL

15.92.1 Macro Definition Documentation

```
15.92.1.1 #define DT 1.0f
```

15.92.2 Function Documentation

15.92.2.1 void modelDefinition (NNmodel & model)

15.92.3 Variable Documentation

15.92.3.1 double neuron_ini[2]

Initial value:

15.92.3.2 double* neuron_p = NULL

15.92.3.3 double* postSyn_ini = NULL

15.92.3.4 double* postSyn_p = NULL

15.92.3.5 double synapses_ini[1]

```
= {
```

```
15.92.3.6 double* synapses_p = NULL
```

15.93 postVarsInSynapseDynamics_sparse.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

· void modelDefinition (NNmodel &model)

Variables

```
• double * neuron p = NULL
```

- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn p = NULL
- double * postSyn_ini = NULL

15.93.1 Macro Definition Documentation

```
15.93.1.1 #define DT 1.0f
```

15.93.2 Function Documentation

15.93.2.1 void modelDefinition (NNmodel & model)

15.93.3 Variable Documentation

15.93.3.1 double neuron_ini[2]

Initial value:

15.93.3.2 double* neuron_p = NULL

15.93.3.3 double* postSyn_ini = NULL

15.93.3.4 double* postSyn_p = NULL

15.93.3.5 double synapses_ini[1]

```
= {
```

```
15.93.3.6 double* synapses_p = NULL
```

15.94 preVarsInPostLearn.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

• void modelDefinition (NNmodel &model)

Variables

```
• double neuron_p [1]
```

- double neuron_p2 [1]
- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn_p = NULL
- double * postSyn_ini = NULL

15.94.1 Macro Definition Documentation

```
15.94.1.1 #define DT 1.0f
```

15.94.2 Function Documentation

15.94.2.1 void modelDefinition (NNmodel & model)

15.94.3 Variable Documentation

15.94.3.1 double neuron_ini[2]

Initial value:

15.94.3.2 double neuron_p[1]

```
={
1.0
```

```
15.94.3.3 double neuron_p2[1]
```

Initial value:

Initial value:

```
= {
 0.0
}
```

15.94.3.7 double* synapses_p = NULL

15.95 preVarsInPostLearn_sparse.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

· void modelDefinition (NNmodel &model)

Variables

```
double neuron_p [1]double neuron_p2 [1]
```

• double neuron_ini [2]

double * synapses_p = NULL

• double synapses_ini [1]

double * postSyn_p = NULL

double * postSyn_ini = NULL

15.95.1 Macro Definition Documentation

```
15.95.1.1 #define DT 1.0f
```

15.95.2 Function Documentation

15.95.2.1 void modelDefinition (NNmodel & model)

15.95.3 Variable Documentation

```
15.95.3.1 double neuron_ini[2]
```

Initial value:

15.95.3.2 double neuron_p[1]

Initial value:

```
= {
1.0
}
```

15.95.3.3 double neuron_p2[1]

Initial value:

```
= {
2.0
}
```

15.95.3.4 double* postSyn_ini = NULL

15.95.3.5 double* postSyn_p = NULL

15.95.3.6 double synapses_ini[1]

Initial value:

15.95.3.7 double* synapses_p = NULL

15.96 preVarsInSimCode.cc File Reference

```
#include "modelSpec.h"
#include "modelSpec.cc"
```

Macros

• #define DT 1.0f

Functions

• void modelDefinition (NNmodel &model)

Variables

```
• double * neuron_p = NULL
```

- double neuron_ini [2]
- double * synapses_p = NULL
- double synapses_ini [1]
- double * postSyn_p = NULL
- double * postSyn_ini = NULL

```
15.96.1 Macro Definition Documentation
15.96.1.1 #define DT 1.0f
15.96.2 Function Documentation
15.96.2.1 void modelDefinition ( NNmodel & model )
15.96.3 Variable Documentation
15.96.3.1 double neuron_ini[2]
Initial value:
   0.0,
    0.0
15.96.3.2 double* neuron_p = NULL
15.96.3.3 double* postSyn_ini = NULL
15.96.3.4 double* postSyn_p = NULL
15.96.3.5 double synapses_ini[1]
Initial value:
   0.0
15.96.3.6 double* synapses_p = NULL
15.97 preVarsInSimCode_sparse.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
Macros
    • #define DT 1.0f
Functions
    · void modelDefinition (NNmodel &model)
Variables
    • double * neuron_p = NULL
    • double neuron_ini [2]
    • double * synapses_p = NULL
    • double synapses_ini [1]
    double * postSyn_p = NULL
    double * postSyn_ini = NULL
```

```
15.97.1 Macro Definition Documentation
15.97.1.1 #define DT 1.0f
15.97.2 Function Documentation
15.97.2.1 void modelDefinition ( NNmodel & model )
15.97.3 Variable Documentation
15.97.3.1 double neuron_ini[2]
Initial value:
   0.0,
    0.0
15.97.3.2 double* neuron_p = NULL
15.97.3.3 double* postSyn_ini = NULL
15.97.3.4 double* postSyn_p = NULL
15.97.3.5 double synapses_ini[1]
Initial value:
   0.0
15.97.3.6 double* synapses_p = NULL
15.98 preVarsInSynapseDynamics.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
Macros
    • #define DT 1.0f
Functions
    · void modelDefinition (NNmodel &model)
Variables
    • double * neuron_p = NULL
    • double neuron_ini [2]
    • double * synapses_p = NULL
    • double synapses_ini [1]
```

double * postSyn_p = NULLdouble * postSyn_ini = NULL

```
15.98.1 Macro Definition Documentation
15.98.1.1 #define DT 1.0f
15.98.2 Function Documentation
15.98.2.1 void modelDefinition ( NNmodel & model )
15.98.3 Variable Documentation
15.98.3.1 double neuron_ini[2]
Initial value:
   0.0,
    0.0
15.98.3.2 double* neuron_p = NULL
15.98.3.3 double* postSyn_ini = NULL
15.98.3.4 double* postSyn_p = NULL
15.98.3.5 double synapses_ini[1]
Initial value:
   0.0
15.98.3.6 double* synapses_p = NULL
15.99 preVarsInSynapseDynamics_sparse.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
Macros
    • #define DT 1.0f
Functions
    · void modelDefinition (NNmodel &model)
Variables
    • double * neuron_p = NULL
    • double neuron_ini [2]
    • double * synapses_p = NULL
    • double synapses_ini [1]
    double * postSyn_p = NULL
```

double * postSyn_ini = NULL

```
15.99.1 Macro Definition Documentation
15.99.1.1 #define DT 1.0f
15.99.2 Function Documentation
15.99.2.1 void modelDefinition ( NNmodel & model )
```

15.99.3 Variable Documentation

15.99.3.1 double neuron_ini[2]

Initial value:

15.99.3.5 double synapses_ini[1]

Initial value:

```
= {
 0.0
```

15.99.3.6 double* synapses_p = NULL

15.100 randomGen.cc File Reference

Contains the implementation of the ISAAC random number generator class for uniformly distributed random numbers and for a standard random number generator based on the C function rand().

```
#include "randomGen.h"
```

Macros

• #define RANDOMGEN_CC

macro for avoiding multiple inclusion during compilation

15.100.1 Detailed Description

Contains the implementation of the ISAAC random number generator class for uniformly distributed random numbers and for a standard random number generator based on the C function rand().

15.100.2 Macro Definition Documentation

15.100.2.1 #define RANDOMGEN_CC

macro for avoiding multiple inclusion during compilation

15.101 randomGen.h File Reference

header file containing the class definition for a uniform random generator based on the ISAAC random number generator

```
#include <time.h>
#include <limits.h>
#include <stdlib.h>
#include "isaac.hpp"
#include <assert.h>
```

Classes

· class randomGen

Class randomGen which implements the ISAAC random number generator for uniformely distributed random numbers.

· class stdRG

Macros

• #define RANDOMGEN_H

macro for avoiding multiple inclusion during compilation

15.101.1 Detailed Description

header file containing the class definition for a uniform random generator based on the ISAAC random number generator

15.101.2 Macro Definition Documentation

15.101.2.1 #define RANDOMGEN_H

macro for avoiding multiple inclusion during compilation

15.102 Schmuker2014_classifier.cu File Reference

```
#include <stdio.h>
#include <iostream>
#include <string>
#include <sstream>
#include <fstream>
#include <stdlib.h>
#include <time.h>
#include "Schmuker2014_classifier.h"
#include "Schmuker_2014_classifier_CODE/runner.cc"
#include "sparseUtils.cc"
```

Macros

• #define _SCHMUKER2014_CLASSIFIER_

macro for avoiding multiple inclusion during compilation

15.102.1 Macro Definition Documentation

```
15.102.1.1 #define _SCHMUKER2014_CLASSIFIER_
```

macro for avoiding multiple inclusion during compilation

15.103 Schmuker2014_classifier.h File Reference

Header file containing the class definition for the Schmuker2014 classifier, which contains the methods for setting up, initialising, simulating and saving results of a multivariate classifier imspired by the insect olfactory system. See "A neuromorphic network for generic multivariate data classification, Michael Schmuker, Thomas Pfeilc, and Martin Paul Nawrota, 2014".

```
#include "Model_Schmuker_2014_classifier.cc"
```

Classes

· class Schmuker2014 classifier

This class cpontains the methods for running the Schmuker_2014_classifier example model.

15.103.1 Detailed Description

Header file containing the class definition for the Schmuker2014 classifier, which contains the methods for setting up, initialising, simulating and saving results of a multivariate classifier imspired by the insect olfactory system. See "A neuromorphic network for generic multivariate data classification, Michael Schmuker, Thomas Pfeilc, and Martin Paul Nawrota, 2014".

15.104 simpleBit.h File Reference

Contains three macros that allow simple bit manipulations on an (presumably unsigned) 32 bit integer.

```
#include <cassert>
#include <cmath>
```

Macros

• #define SIMPLEBIT H

macro for avoiding multiple inclusion during compilation

#define B(x, i) ((x) & (0x80000000 >> (i)))

Extract the bit at the specified position i from x.

• #define setB(x, i) $x = ((x) \mid (0x800000000 >> (i)))$

Set the bit at the specified position i in x to 1.

• #define delB(x, i) x= ((x) & (\sim (0x80000000 >> (i))))

Set the bit at the specified position i in x to 0.

15.104.1 Detailed Description

Contains three macros that allow simple bit manipulations on an (presumably unsigned) 32 bit integer.

```
15.104.2 Macro Definition Documentation
15.104.2.1 #define B( x, i) ((x) & (0x800000000 >> (i)))
Extract the bit at the specified position i from x.
15.104.2.2 #define delB( x, i) x= ((x) & (\sim(0x800000000 >> (i))))
Set the bit at the specified position i in x to 0.
15.104.2.3 #define setB( x, i) x = ((x) | (0x800000000 >> (i)))
Set the bit at the specified position i in x to 1.
15.104.2.4 #define SIMPLEBIT H
macro for avoiding multiple inclusion during compilation
15.105 sizes.h File Reference
Macros
```

#define _NC1 1

15.105.1 Macro Definition Documentation

15.105.1.1 #define NC1 1

15.106 sparseUtils.cc File Reference

```
#include <cstdio>
#include <cmath>
```

Macros

• #define sparse utils cc

Functions

- template < class DATATYPE > unsigned int countEntriesAbove (DATATYPE *Array, int sz, double includeAbove)
- template < class DATATYPE > DATATYPE getG (DATATYPE *wuvar, SparseProjection *sparseStruct, int x, int y)
- template < class DATATYPE > float getSparseVar (DATATYPE *wuvar, SparseProjection *sparseStruct, int x, int y)
- template < class DATATYPE > void setSparseConnectivityFromDense (DATATYPE *wuvar, int preN, int postN, DATATYPE *tmp_gRNPN, SparseProjection *sparseStruct)
- template < class DATATYPE > void createSparseConnectivityFromDense (DATATYPE *wuvar, int preN, int postN, DATATYPE *tmp_gR ← NPN, SparseProjection *sparseStruct, bool runTest)
- void createPosttoPreArray (unsigned int preN, unsigned int postN, SparseProjection *sparseStruct)
- void strsearch (string &s, const string trg)

!!!!find var to check if a string is used in a code (atm it is used to create post-to-pre arrays)

```
15.106.1 Macro Definition Documentation

15.106.1.1 #define sparse_utils_cc

15.106.2.1 template < class DATATYPE > unsigned int countEntriesAbove ( DATATYPE * Array, int sz, double includeAbove )

15.106.2.2 void createPosttoPreArray ( unsigned int preN, unsigned int postN, SparseProjection * sparseStruct )

15.106.2.3 template < class DATATYPE > void createSparseConnectivityFromDense ( DATATYPE * wuvar, int preN, int postN, DATATYPE * tmp_gRNPN, SparseProjection * sparseStruct, bool runTest )

15.106.2.4 template < class DATATYPE > DATATYPE getG ( DATATYPE * wuvar, SparseProjection * sparseStruct, int x, int y )

15.106.2.5 template < class DATATYPE > float getSparseVar ( DATATYPE * wuvar, SparseProjection * sparseStruct, int x, int y )

15.106.2.6 template < class DATATYPE > void setSparseConnectivityFromDense ( DATATYPE * wuvar, int preN, int postN, DATATYPE * tmp_gRNPN, SparseProjection * sparseStruct )
```

15.107 stringutils.h File Reference

```
#include <string>
```

Macros

• #define __mathFN 56

Functions

void substitute (string &s, const string trg, const string rep)

Tool for substituting strings in the neuron code strings or other templates.

void name_substitutions (string &code, string prefix, vector < string > &names, string postfix=string(""))

This function performs a list of name substitutions for variables in code snippets.

!!!!find var to check if a string is used in a code (atm it is used to create post-to-pre arrays)

void value_substitutions (string &code, vector< string > &names, vector< double > &values)

This function performs a list of value substitutions for parameters in code snippets.

void extended_name_substitutions (string &code, string prefix, vector< string > &names, string ext, string postfix=string(""))

This function performs a list of name substitutions for variables in code snippets where the variables have a prefix/postfix in their names.

void extended_value_substitutions (string &code, vector< string > &names, string ext, vector< double > &values)

This function performs a list of value substitutions for parameters in code snippets where the parameters have a prefix/postfix in their names.

• void ensureMathFunctionFtype (string &code, string type)

This function converts code to contain only explicit single precision (float) function calls (C99 standard)

void doFinal (string &code, unsigned int i, string type, unsigned int &state)

This function is part of the parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

• string ensureFtype (string oldcode, string type)

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

Variables

```
    string digits = string("0123456789")
    string op = string("+-*/(<>= ,;")+string("\n")+string("\t")
    const char * __dnames [__mathFN]
```

15.107.1 Macro Definition Documentation

const char * fnames [mathFN]

```
15.107.1.1 #define __mathFN 56
```

15.107.2 Function Documentation

15.107.2.1 void doFinal (string & code, unsigned int i, string type, unsigned int & state)

This function is part of the parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

```
15.107.2.2 string ensureFtype ( string oldcode, string type )
```

This function implements a parser that converts any floating point constant in a code snippet to a floating point constant with an explicit precision (by appending "f" or removing it).

```
15.107.2.3 void ensureMathFunctionFtype ( string & code, string type )
```

This function converts code to contain only explicit single precision (float) function calls (C99 standard)

```
15.107.2.4 void extended_name_substitutions ( string & code, string prefix, vector < string > & names, string ext, string postfix = string(""))
```

This function performs a list of name substitutions for variables in code snippets where the variables have a pre-fix/postfix in their names.

```
15.107.2.5 void extended_value_substitutions ( string & code, vector < string > & names, string ext, vector < double > & values)
```

This function performs a list of value substitutions for parameters in code snippets where the parameters have a prefix/postfix in their names.

```
15.107.2.6 void name_substitutions ( string & code, string prefix, vector < string > & names, string postfix = string ("")
)
```

This function performs a list of name substitutions for variables in code snippets.

```
15.107.2.7 void substitute ( string & s, const string trg, const string rep )
```

Tool for substituting strings in the neuron code strings or other templates.

```
15.107.2.8 void value_substitutions ( string & code, vector < string > & names, vector < double > & values )
```

This function performs a list of value substitutions for parameters in code snippets.

```
15.107.3 Variable Documentation
15.107.3.1 const char* __dnames[__mathFN]
15.107.3.2 const char* __fnames[__mathFN]
15.107.3.3 string digits = string("0123456789")
15.107.3.4 string op = string("+-*/(<>= ;;")+string("\n")+string("\t")
15.108 SynDelay.cc File Reference
#include "modelSpec.h"
#include "modelSpec.cc"
Macros
    • #define DT 1.0f
Functions
    · void modelDefinition (NNmodel &model)
Variables
    double input_p [4]
    • double input_ini [2]
    • double postExpInp [2]
    double inter_p [4]
    • double inter_ini [2]
    • double postExpInt [2]
    double output_p [4]
    • double output_ini [2]

    double postExpOut [2]

    • double * synapses_p = NULL
    • double inputInter_ini [1]

    double inputOutput_ini [1]

    • double interOutput ini [1]

    double * postSynV = NULL

    • double constlnput = 4.0
15.108.1 Macro Definition Documentation
15.108.1.1 #define DT 1.0f
15.108.2 Function Documentation
15.108.2.1 void modelDefinition ( NNmodel & model )
15.108.3 Variable Documentation
```

15.108.3.1 double constliput = 4.0

```
15.108.3.2 double input_ini[2]
```

```
Initial value:
```

```
= {
 -65,
 -20
```

15.108.3.3 double input_p[4]

Initial value:

```
= {
    0.02,
    0.2,
    -65,
    6
```

15.108.3.4 double inputInter_ini[1]

Initial value:

```
= {
 0.06
}
```

15.108.3.5 double inputOutput_ini[1]

Initial value:

```
= {
 0.03
}
```

15.108.3.6 double inter_ini[2]

Initial value:

```
= {
 -65,
 -20
```

15.108.3.7 double inter_p[4]

Initial value:

```
= {
    0.02,
    0.2,
    -65,
    6
```

15.108.3.8 double interOutput_ini[1]

```
= {
 0.03
}
```

```
15.108.3.9 double output_ini[2]
```

```
Initial value:
```

```
= {
 -65,
 -20
```

15.108.3.10 double output_p[4]

Initial value:

```
= {
    0.02,
    0.2,
    -65,
    6
```

15.108.3.11 double postExpInp[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.108.3.12 double postExpInt[2]

Initial value:

```
= {
    1.0,
    0.0
}
```

15.108.3.13 double postExpOut[2]

Initial value:

```
= {
1.0,
0.0
}
```

15.108.3.14 double* postSynV = NULL

15.108.3.15 double* synapses_p = NULL

15.109 SynDelaySim.cu File Reference

```
#include <cstdlib>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "SynDelaySim.h"
#include "SynDelay_CODE/definitions.h"
#include "SynDelay_CODE/runner.cc"
```

Macros

• #define SYNDELAYSIM_CU

Functions

```
• int main (int argc, char *argv[])
```

```
15.109.1 Macro Definition Documentation
```

```
15.109.1.1 #define SYNDELAYSIM_CU
```

15.109.2 Function Documentation

15.109.2.1 int main (int argc, char * argv[])

15.110 SynDelaySim.h File Reference

Classes

class SynDelay

Macros

- #define DT 1.0f
- #define TOTAL_TIME 5000.0f
- #define REPORT_TIME 1000.0f

```
15.110.1 Macro Definition Documentation
```

```
15.110.1.1 #define DT 1.0f
```

15.110.1.2 #define REPORT_TIME 1000.0f

15.110.1.3 #define TOTAL_TIME 5000.0f

15.111 testHelper.h File Reference

Functions

```
template < class T >
T absDiff (T *x0, T *x1, int n)
```

15.111.1 Function Documentation

```
15.111.1.1 template < class T > T absDiff ( T * x0, T * x1, int n )
```

15.112 testHelper.h File Reference

Functions

```
    template < class T >
        T absDiff (T *x0, T *x1, int n)
```

```
15.112.1 Function Documentation
15.112.1.1 template < class T > T absDiff ( T * x0, T * x1, int n )
15.113 testPostVarsInPostLearn.cu File Reference
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInPostLearn.h"
#include "postVarsInPostLearn_CODE/definitions.h"
#include "postVarsInPostLearn_CODE/runner.cc"
Macros

    #define TESTPREVARSINSIMCODE CU

Functions
   • int main (int argc, char *argv[])
15.113.1 Macro Definition Documentation
15.113.1.1 #define TESTPREVARSINSIMCODE_CU
15.113.2 Function Documentation
15.113.2.1 int main ( int argc, char * argv[])
15.114 testPostVarsInPostLearn.h File Reference
Classes

    class postVarsInPostLearn

Macros
   • #define DT 0.1f
   • #define TOTAL_TIME 20.0f
   • #define REPORT_TIME 1.0f
15.114.1 Macro Definition Documentation
15.114.1.1 #define DT 0.1f
15.114.1.2 #define REPORT_TIME 1.0f
15.114.1.3 #define TOTAL_TIME 20.0f
```

15.115 testPostVarsInPostLearn_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInPostLearn_sparse.h"
#include "postVarsInPostLearn_sparse_CODE/definitions.h"
#include "postVarsInPostLearn_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINPOSTLEARN SPARSE CU

Functions

int main (int argc, char *argv[])

```
15.115.1 Macro Definition Documentation
```

15.115.1.1 #define TESTPREVARSINPOSTLEARN_SPARSE_CU

15.115.2 Function Documentation

15.115.2.1 int main (int argc, char * argv[])

15.116 testPostVarsInPostLearn_sparse.h File Reference

Classes

• class postVarsInPostLearn_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

```
15.116.1 Macro Definition Documentation
```

15.116.1.1 #define DT 0.1f

15.116.1.2 #define REPORT_TIME 1.0f

15.116.1.3 #define TOTAL_TIME 20.0f

15.117 testPostVarsInSimCode.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInSimCode.h"
#include "postVarsInSimCode_CODE/definitions.h"
#include "postVarsInSimCode_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSIMCODE CU

Functions

• int main (int argc, char *argv[])

```
15.117.1 Macro Definition Documentation
```

15.117.1.1 #define TESTPREVARSINSIMCODE_CU

15.117.2 Function Documentation

15.117.2.1 int main (int argc, char * argv[])

15.118 testPostVarsInSimCode.h File Reference

Classes

• class postVarsInSimCode

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f
- 15.118.1 Macro Definition Documentation
- 15.118.1.1 #define DT 0.1f
- 15.118.1.2 #define REPORT_TIME 1.0f
- 15.118.1.3 #define TOTAL_TIME 20.0f

15.119 testPostVarsInSimCode_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInSimCode_sparse.h"
#include "postVarsInSimCode_sparse_CODE/definitions.h"
#include "postVarsInSimCode_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSIMCODE CU

Functions

int main (int argc, char *argv[])

```
15.119.1 Macro Definition Documentation
```

15.119.1.1 #define TESTPREVARSINSIMCODE_CU

15.119.2 Function Documentation

15.119.2.1 int main (int argc, char * argv[])

15.120 testPostVarsInSimCode_sparse.h File Reference

Classes

• class postVarsInSimCode_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

```
15.120.1 Macro Definition Documentation
```

15.120.1.1 #define DT 0.1f

15.120.1.2 #define REPORT_TIME 1.0f

15.120.1.3 #define TOTAL_TIME 20.0f

15.121 testPostVarsInSynapseDynamics.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInSynapseDynamics.h"
#include "postVarsInSynapseDynamics_CODE/definitions.h"
#include "postVarsInSynapseDynamics_CODE/runner.cc"
```

Macros

#define TESTPREVARSINSYNAPSEDYNAMICS CU

Functions

• int main (int argc, char *argv[])

```
15.121.1 Macro Definition Documentation
```

15.121.1.1 #define TESTPREVARSINSYNAPSEDYNAMICS_CU

15.121.2 Function Documentation

15.121.2.1 int main (int *argc*, char * *argv[*])

15.122 testPostVarsInSynapseDynamics.h File Reference

Classes

• class postVarsInSynapseDynamics

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f
- 15.122.1 Macro Definition Documentation
- 15.122.1.1 #define DT 0.1f
- 15.122.1.2 #define REPORT_TIME 1.0f
- 15.122.1.3 #define TOTAL_TIME 20.0f

15.123 testPostVarsInSynapseDynamics_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPostVarsInSynapseDynamics_sparse.h"
#include "postVarsInSynapseDynamics_sparse_CODE/definitions.h"
#include "postVarsInSynapseDynamics_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSYNAPSEDYNAMICS SPARSE CU

Functions

```
    int main (int argc, char *argv[])
```

```
15.123.1 Macro Definition Documentation
```

15.123.1.1 #define TESTPREVARSINSYNAPSEDYNAMICS_SPARSE_CU

15.123.2 Function Documentation

15.123.2.1 int main (int argc, char * argv[])

15.124 testPostVarsInSynapseDynamics_sparse.h File Reference

Classes

• class postVarsInSynapseDynamics_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

15.124.1 Macro Definition Documentation

15.124.1.1 #define DT 0.1f

15.124.1.2 #define REPORT_TIME 1.0f

15.124.1.3 #define TOTAL_TIME 20.0f

15.125 testPreVarsInPostLearn.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInPostLearn.h"
#include "preVarsInPostLearn_CODE/definitions.h"
#include "preVarsInPostLearn_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSIMCODE CU

Functions

• int main (int argc, char *argv[])

```
15.125.1 Macro Definition Documentation
```

15.125.1.1 #define TESTPREVARSINSIMCODE_CU

15.125.2 Function Documentation

15.125.2.1 int main (int *argc*, char * *argv*[])

15.126 testPreVarsInPostLearn.h File Reference

Classes

• class preVarsInPostLearn

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f
- 15.126.1 Macro Definition Documentation
- 15.126.1.1 #define DT 0.1f
- 15.126.1.2 #define REPORT_TIME 1.0f
- 15.126.1.3 #define TOTAL_TIME 20.0f

15.127 testPreVarsInPostLearn_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInPostLearn_sparse.h"
#include "preVarsInPostLearn_sparse_CODE/definitions.h"
#include "preVarsInPostLearn_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINPOSTLEARN SPARSE CU

Functions

int main (int argc, char *argv[])

```
15.127.1 Macro Definition Documentation
```

15.127.1.1 #define TESTPREVARSINPOSTLEARN_SPARSE_CU

15.127.2 Function Documentation

15.127.2.1 int main (int argc, char * argv[])

15.128 testPreVarsInPostLearn_sparse.h File Reference

Classes

• class preVarsInPostLearn_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

```
15.128.1 Macro Definition Documentation
```

15.128.1.1 #define DT 0.1f

15.128.1.2 #define REPORT_TIME 1.0f

15.128.1.3 #define TOTAL_TIME 20.0f

15.129 testPreVarsInSimCode.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInSimCode.h"
#include "preVarsInSimCode_CODE/definitions.h"
#include "preVarsInSimCode_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSIMCODE CU

Functions

• int main (int argc, char *argv[])

```
15.129.1 Macro Definition Documentation
```

15.129.1.1 #define TESTPREVARSINSIMCODE_CU

15.129.2 Function Documentation

15.129.2.1 int main (int *argc*, char * *argv*[])

15.130 testPreVarsInSimCode.h File Reference

Classes

• class preVarsInSimCode

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

```
15.130.1 Macro Definition Documentation
```

15.130.1.1 #define DT 0.1f

15.130.1.2 #define REPORT_TIME 1.0f

15.130.1.3 #define TOTAL_TIME 20.0f

15.131 testPreVarsInSimCode_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInSimCode_sparse.h"
#include "preVarsInSimCode_sparse_CODE/definitions.h"
#include "preVarsInSimCode_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSIMCODE CU

Functions

int main (int argc, char *argv[])

```
15.131.1 Macro Definition Documentation
```

15.131.1.1 #define TESTPREVARSINSIMCODE_CU

15.131.2 Function Documentation

15.131.2.1 int main (int *argc*, char * *argv*[])

15.132 testPreVarsInSimCode_sparse.h File Reference

Classes

• class preVarsInSimCode_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

```
15.132.1 Macro Definition Documentation
```

15.132.1.1 #define DT 0.1f

15.132.1.2 #define REPORT_TIME 1.0f

15.132.1.3 #define TOTAL_TIME 20.0f

15.133 testPreVarsInSynapseDynamics.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInSynapseDynamics.h"
#include "preVarsInSynapseDynamics_CODE/definitions.h"
#include "preVarsInSynapseDynamics_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSYNAPSEDYNAMICS CU

Functions

• int main (int argc, char *argv[])

```
15.133.1 Macro Definition Documentation
```

15.133.1.1 #define TESTPREVARSINSYNAPSEDYNAMICS_CU

15.133.2 Function Documentation

15.133.2.1 int main (int *argc*, char * *argv*[])

15.134 testPreVarsInSynapseDynamics.h File Reference

Classes

• class preVarsInSynapseDynamics

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f
- 15.134.1 Macro Definition Documentation
- 15.134.1.1 #define DT 0.1f
- 15.134.1.2 #define REPORT_TIME 1.0f
- 15.134.1.3 #define TOTAL_TIME 20.0f

15.135 testPreVarsInSynapseDynamics_sparse.cu File Reference

```
#include <cstdlib>
#include <cfloat>
#include <iostream>
#include <fstream>
#include "hr_time.cpp"
#include "utils.h"
#include "testHelper.h"
#include "testPreVarsInSynapseDynamics_sparse.h"
#include "preVarsInSynapseDynamics_sparse_CODE/definitions.h"
#include "preVarsInSynapseDynamics_sparse_CODE/runner.cc"
```

Macros

• #define TESTPREVARSINSYNAPSEDYNAMICS_SPARSE_CU

Functions

```
• int main (int argc, char *argv[])
```

```
15.135.1 Macro Definition Documentation
```

15.135.1.1 #define TESTPREVARSINSYNAPSEDYNAMICS_SPARSE_CU

15.135.2 Function Documentation

15.135.2.1 int main (int argc, char * argv[])

15.136 testPreVarsInSynapseDynamics_sparse.h File Reference

Classes

• class preVarsInSynapseDynamics_sparse

Macros

- #define DT 0.1f
- #define TOTAL_TIME 20.0f
- #define REPORT_TIME 1.0f

15.136.1 Macro Definition Documentation

15.136.1.1 #define DT 0.1f

15.136.1.2 #define REPORT TIME 1.0f

15.136.1.3 #define TOTAL_TIME 20.0f

15.137 toString.h File Reference

Contains a template function for string conversion from const char* to C++ string.

```
#include <string>
#include <sstream>
```

Macros

#define _TOSTRING_H_
macro for avoiding multiple inclusion during compilation

#define tS(X) toString(X)

Macro providing the abbreviated syntax tS() instead of toString().

Functions

```
    template < class T >
        std::string toString (T t)
        template function for string conversion from const char* to C++ string
    template <>
        std::string toString (float t)
```

15.137.1 Detailed Description

std::string toString (double t)

template<>

Contains a template function for string conversion from const char* to C++ string.

```
15.137.2 Macro Definition Documentation
15.137.2.1 #define _TOSTRING_H_
macro for avoiding multiple inclusion during compilation
15.137.2.2 #define tS( X ) toString(X)
Macro providing the abbreviated syntax tS() instead of toString().
15.137.3 Function Documentation
```

```
15.137.3.1 template < class T > std::string toString ( T t ) template function for string conversion from const char* to C++ string 15.137.3.2 template <> std::string toString ( float t ) 15.137.3.3 template <> std::string toString ( double t ) 15.138 utils.h File Reference
```

This file contains standard utility functions provide within the NVIDIA CUDA software development toolkit (SDK). The remainder of the file contains a function that defines the standard neuron models.

```
#include <cstdlib>
#include <iostream>
#include <string>
#include <vector>
#include <map>
#include <memory>
#include <fstream>
#include <cmath>
#include <cuda_runtime.h>
#include "modelSpec.h"
#include "toString.h"
#include "stringutils.h"
#include "extra_neurons.h"
#include "extra_postsynapses.h"
#include "extra_weightupdates.h"
#include "numlib/simpleBit.h"
```

Classes

· class rulkovdp

Class defining the dependent parameters of teh Rulkov map neuron.

class expDecayDp

Class defining the dependent parameter for exponential decay.

class pwSTDP

TODO This class definition may be code-generated in a future release.

Macros

• #define _UTILS_H_

macro for avoiding multiple inclusion during compilation

• #define CHECK_CUDA_ERRORS(call)

Macro for wrapping cuda runtime function calls and catching any errors that may be thrown.

Functions

void gennError (string error)

Function called upon the detection of an error. Outputs an error message and then exits.

void gennError (const char *error)

Function called upon the detection of an error. Outputs an error message and then exits.

• void writeHeader (ostream &os)

Function to write the comment header denoting file authorship and contact details into the generated code.

unsigned int theSize (string type)

Tool for determining the size of variable types on the current architecture.

• void prepareStandardModels ()

Function that defines standard neuron models.

void preparePostSynModels ()

Function that prepares the standard post-synaptic models, including their variables, parameters, dependent parameters and code strings.

void prepareWeightUpdateModels ()

Function that prepares the standard (pre) synaptic models, including their variables, parameters, dependent parameters and code strings.

Variables

vector< neuronModel > nModels

Global C++ vector containing all neuron model descriptions.

vector< postSynModel > postSynModels

Global C++ vector containing all post-synaptic update model descriptions.

vector< weightUpdateModel > weightUpdateModels

Global C++ vector containing all weightupdate model descriptions.

15.138.1 Detailed Description

This file contains standard utility functions provide within the NVIDIA CUDA software development toolkit (SDK). The remainder of the file contains a function that defines the standard neuron models.

15.138.2 Macro Definition Documentation

```
15.138.2.1 #define _UTILS_H_
```

macro for avoiding multiple inclusion during compilation

```
15.138.2.2 #define CHECK_CUDA_ERRORS( call )
```

Value:

Macro for wrapping cuda runtime function calls and catching any errors that may be thrown.

15.138.3 Function Documentation

```
15.138.3.1 void gennError ( string error )
```

Function called upon the detection of an error. Outputs an error message and then exits.

```
15.138.3.2 void gennError ( const char * error )
```

Function called upon the detection of an error. Outputs an error message and then exits.

```
15.138.3.3 void preparePostSynModels ( )
```

Function that prepares the standard post-synaptic models, including their variables, parameters, dependent parameters and code strings.

```
15.138.3.4 void prepareStandardModels ( )
```

Function that defines standard neuron models.

The neuron models are defined and added to the C++ vector nModels that is holding all neuron model descriptions. User defined neuron models can be appended to this vector later in (a) separate function(s).

```
15.138.3.5 void prepareWeightUpdateModels ( )
```

Function that prepares the standard (pre) synaptic models, including their variables, parameters, dependent parameters and code strings.

```
15.138.3.6 unsigned int the Size ( string type )
```

Tool for determining the size of variable types on the current architecture.

```
15.138.3.7 void writeHeader (ostream & os)
```

Function to write the comment header denoting file authorship and contact details into the generated code.

15.138.4 Variable Documentation

15.138.4.1 vector<neuronModel> nModels

Global C++ vector containing all neuron model descriptions.

15.138.4.2 vector<postSynModel> postSynModels

Global C++ vector containing all post-synaptic update model descriptions.

15.138.4.3 vector<weightUpdateModel> weightUpdateModels

Global C++ vector containing all weightupdate model descriptions.

15.139 VClampGA.cu File Reference

Main entry point for the GeNN project demonstrating realtime fitting of a neuron with a GA running mostly on the GPU.

```
#include "VClampGA.h"
```

Functions

• int main (int argc, char *argv[])

This function is the entry point for running the project.

15.139.1 Detailed Description

Main entry point for the GeNN project demonstrating realtime fitting of a neuron with a GA running mostly on the GPU.

15.139.2 Function Documentation

15.139.2.1 int main (int argc, char * argv[])

This function is the entry point for running the project.

15.140 VClampGA.h File Reference

```
#include <cassert>
#include "hr_time.cpp"
#include "utils.h"
#include <cuda_runtime.h>
#include "HHVClamp.cc"
#include "HHVClamp_CODE/runner.cc"
#include "../../../lib/include/numlib/randomGen.h"
#include "../../../lib/include/numlib/gauss.h"
#include "helper.h"
#include "GA.cc"
```

Macros

• #define RAND(Y, X) Y = Y * 1103515245 +12345;X= (unsigned int)(Y >> 16) & 32767

Variables

- randomGen R
- randomGauss RG
- double t = 0.0f
- unsigned int iT = 0
- · CStopWatch timer
- 15.140.1 Macro Definition Documentation
- 15.140.1.1 #define RAND(Y, X) Y = Y * 1103515245 +12345;X= (unsigned int)(Y >> 16) & 32767
- 15.140.2 Variable Documentation
- 15.140.2.1 unsigned int iT = 0
- 15.140.2.2 randomGen R
- 15.140.2.3 randomGauss RG
- 15.140.2.4 double t = 0.0f
- 15.140.2.5 CStopWatch timer

REFERENCES 221

References

[1] Eugene M Izhikevich. Simple model of spiking neurons. *IEEE Transactions on neural networks*, 14(6):1569–1572, 2003. 8, 9, 10, 21

- [2] Thomas Nowotny, Ramón Huerta, Henry DI Abarbanel, and Mikhail I Rabinovich. Self-organization in the olfactory system: one shot odor recognition in insects. *Biological cybernetics*, 93(6):436–446, 2005. 10, 11, 18, 26
- [3] Nikolai F Rulkov. Modeling of spiking-bursting neural behavior using two-dimensional map. *Physical Review E*, 65(4):041922, 2002. 18
- [4] R. D. Traub and R. Miles. *Neural Networks of the Hippocampus*. Cambridge University Press, New York, 1991. 10, 20, 27, 29

Index

_FTYPE	postVarsInSimCode, 84
PoissonIzh.cc, 178	~postVarsInSimCode_sparse
_GLOBAL_H_	postVarsInSimCode_sparse, 84
global.h, 139	~postVarsInSynapseDynamics
_IZH_SPARSE_MODEL_CC_	postVarsInSynapseDynamics, 85
Izh_sparse_model.cc, 146	~postVarsInSynapseDynamics_sparse
_MAP_CLASSOL_CC_	postVarsInSynapseDynamics_sparse, 86
MBody1_project/model/map_classol.cc, 147	~preVarsInPostLearn
MBody_delayedSyn_project/model/map_classol.	preVarsInPostLearn, 87
cc, 148	~preVarsInPostLearn_sparse
MBody_individualID_project/model/map_classol.←	preVarsInPostLearn sparse, 87
cc, 148	~preVarsInSimCode
MBody_userdef_project/model/map_classol.cc,	preVarsInSimCode, 88
148	~preVarsInSimCode_sparse
_MODELSPEC_CC_	preVarsInSimCode_sparse, 89
modelSpec.cc, 169	~preVarsInSynapseDynamics
_MODELSPEC_H_	preVarsInSynapseDynamics, 90
modelSpec.h, 172	~preVarsInSynapseDynamics_sparse
NC1	preVarsInSynapseDynamics_sparse, 90
sizes.h, 197	~randomGauss
_ONECOMP_MODEL_CC_	randomGauss, 93
OneComp_model.cc, 176	~randomGen
_POISSONIZHMODEL_CC_	randomGen, 94
PoissonIzh-model.cc, 178	~stdRG
_SCHMUKER2014_CLASSIFIER_	stdRG, 101
Schmuker2014_classifier.cu, 196	00_MainPage.dox, 105
_TOSTRING_H_	01_Installation.dox, 105
toString.h, 216	02_Quickstart.dox, 105
_UTILS_H_	03_Examples.dox, 105
utils.h, 218	09_ReleaseNotes_v2.dox, 105
CODE_HELPER_CC	10_UserManual.dox, 105
CodeHelper.cc, 111	11_Tutorial.dox, 105
dnames	12_Tutorial.dox, 105
stringutils.h, 200	13_UserGuide.dox, 105
fnames	14_Credits.dox, 105
stringutils.h, 200	
mathFN	ALLTOALL
stringutils.h, 199	modelSpec.h, 172
\sim NNmodel	AUTODEVICE
NNmodel, 70	modelSpec.h, 172
~Schmuker2014_classifier	absDiff
Schmuker2014_classifier, 98	postsynapticVariables/testHelper.h, 203
\sim SynDelay	presynapticVariables/testHelper.h, 204
SynDelay, 102	activateDirectInput
\sim classIzh	NNmodel, 70
classIzh, 49	addInputRate
\sim classol	Schmuker2014_classifier, 98
classol, 54	addNeuronPopulation
\sim neuronpop	NNmodel, 70, 71
neuronpop, 66	addSynapsePopulation
~postVarsInPostLearn	NNmodel, 71, 73, 74
postVarsInPostLearn, 82	allocate_device_mem_input
~postVarsInPostLearn_sparse	classIzh, 49
postVarsInPostLearn_sparse, 83	classol, 54
~postVarsInSimCode	neuronpop, 66

allocate_device_mem_patterns	expDecayDp, 62
classIzh, 49	pwSTDP, 91
classol, 54	pwSTDP_userdef, 92
neuronpop, 66	rulkovdp, 95
allocateHostAndDeviceMemory	calculateOverallWinner
Schmuker2014_classifier, 98	Schmuker2014_classifier, 98
applyInputToClassifier	calculateVrResponse
experiment.cu, 113	Schmuker2014_classifier, 98
applyLearningRuleSynapses	calculateWinner
Schmuker2014_classifier, 98	Schmuker2014_classifier, 98
asGoodAsZero	Cexp
global.h, 139	helper.h, 141
D	checkContents
B simple Bit h 107	Schmuker2014_classifier, 98
simpleBit.h, 197 baseV	checkSizes
	NNmodel, 75
inputSpec, 63	chooseDevice
baserates	generateALL.cc, 133
classol, 59	chooseGPUDevice
BlkSz	NNmodel, 76
GeNNHelperKrnls.cu, 138	classIzh, 48
braces	∼classlzh, 49
CodeHelper, 60	allocate_device_mem_input, 49
CACHE DID	allocate_device_mem_patterns, 49
CACHE_DIR	classIzh, 49
experiment.h, 114	copy_device_mem_input, 49
CB Codel Johnson 111	create_input_values, 49
CodeHelper.cc, 111 CHECK CUDA ERRORS	d_input1, 50
	d_input2, 50
utils.h, 218	free_device_mem, 49
CLUST_SIZE_AN	gen_alltoall_syns, 49
Model_Schmuker_2014_classifier.cc, 168	getSpikeNumbersFromGPU, 50
CLUST_SIZE_PN	getSpikesFromGPU, 50
Model_Schmuker_2014_classifier.cc, 168	init, 50
CLUST_SIZE_RN	initializeAllVars, 50
Model_Schmuker_2014_classifier.cc, 168	input1, 50
CONNECTIVITY_AN_AN	input2, 50
experiment.h, 114	model, 50
CONNECTIVITY_PN_AN	output_params, 50
experiment.h, 114	output_spikes, 50
CONNECTIVITY_PN_PN	output_state, 50
experiment.h, 114	randomizeVar, 50
CONNECTIVITY_RN_PN	randomizeVarSq, 50
experiment.h, 115	read_input_values, 50
CONSTINP	read_sparsesyns_par, 50
modelSpec.h, 172	_ , _ , _ ,
CPU	run, 50
modelSpec.h, 172	setInput, 50
CStopWatch, 60	sum_spikes, 50
CStopWatch, 61	sumPExc, 50
getElapsedTime, 61	sumPlnh, 50
startTimer, 61	write_input_to_file, 50
stopTimer, 61	classLabel
cacheDir	Schmuker2014_classifier, 100
Schmuker2014_classifier, 100	classifier
calculateCurrentWindowWinner	experiment.cu, 113
Schmuker2014_classifier, 98	classol, 51
calculateDerivedParameter	∼classol, 54
dpclass, 61	allocate_device_mem_input, 54

	allocate_device_mem_patterns, 54	verbose, 60
	baserates, 59	CodeHelper.cc, 111
	classol, 54	CODE_HELPER_CC, 111
		CB, 111
	d_baserates, 59	
	d_pattern, 59	ENDL, 111
	free_device_mem, 54	OB, 111
	generate_baserates, 54	SAVEP, 111
	get_kcdnsyns, 54, 55	compareErrTupel
	getSpikeNumbersFromGPU, 55	GA.cc, 119
	getSpikesFromGPU, 55	constInput
	init, 55	SynDelay.cc, 200
	model, 59	convertToRateCode
	offset, 59	Schmuker2014_classifier, 98
	output_spikes, 55, 56	copy_device_mem_input
	output_state, 56	classIzh, 49
	p_pattern, 59	neuronpop, 66
	pattern, 59	copy_var
	read_PNIzh1syns, 56	helper.h, 141
	read_input_patterns, 56	correctClass
	read_kcdnsyns, 56	Schmuker2014_classifier, 100
	read_pnkcsyns, 56, 57	countAN
		Schmuker2014_classifier, 100
	read_pnlhisyns, 57	countEntriesAbove
	read_sparsesyns_par, 57	sparseUtils.cc, 198
	run, 57, 58	countPN
	runCPU, 58	Schmuker2014_classifier, 100
	runGPU, 58	countPNAN
	size_g, 59	
	sum_spikes, 58	Schmuker2014_classifier, 100
	sumDN, 59	countRN
	sumlzh1, 59	Schmuker2014_classifier, 100
	sumKC, 59	create_input_values
	sumLHI, 59	classIzh, 49
	sumPN, 59	neuronpop, 66
	theRates, 59	createDirectory
	write_kcdnsyns, 58	experiment.cu, 113
	write_pnkcsyns, 58, 59	createPosttoPreArray
	write_pnlhisyns, 59	sparseUtils.cc, 198
class	sol_sim.cu, 105, 106	create Sparse Connectivity From Dense
	sol_sim.h, 107–110	sparseUtils.cc, 198
clear		createWTAConnectivity
Cicai		Schmuker2014_classifier, 98
	extra_neurons.h, 116	
	lib/include/extra_postsynapses.h, 117	D_MAX_RANDOM_NUM
	SpineML_to_GeNN/extra_postsynapses.h, 118	experiment.h, 115
clear	DownDevice	d_baserates
	Schmuker2014_classifier, 98	classol, 59
clear	redDownDevice	d_input1
	Schmuker2014_classifier, 100	classIzh, 50
close	eBrace	neuronpop, 66
	CodeHelper, 60	d_input2
clust	erSpikeCountAN	classIzh, 50
	Schmuker2014_classifier, 100	d_inputRates
Code	eHelper, 59	Schmuker2014_classifier, 100
	braces, 60	d maxRandomNumber
	closeBrace, 60	Schmuker2014_classifier, 100
	CodeHelper, 60	d pattern
	endl, 60	classol, 59
	openBrace, 60	DATASET_NAME
	setVerbose, 60	experiment.h, 115
	55 5. 5555, 55	CAPCINIONIUM, I IV

DBG	_SIZE	Schmuker2014_classifier, 98
	Izh_sparse_sim.h, 147	datasetName
	MBody1_project/model/classol_sim.h, 107	Schmuker2014_classifier, 100
	MBody_delayedSyn_project/model/classol_sim.h,	delB
	108	simpleBit.h, 197
	MBody_individualID_project/model/classol_sim.h,	deviceCount
	109	global.h, 139
	MBody_userdef_project/model/classol_sim.h, 110	deviceProp
	OneComp_sim.h, 177	global.h, 139
	PoissonIzh sim.h, 181	digits
DEN	_	ensureFtype.h, 112
	modelSpec.h, 172	stringutils.h, 200
DT	modelepodin, 172	directoryExists
	HHVClamp.cc, 142	experiment.cu, 113
	HHVclampGA_project/model/MBody1.cc, 150	divi
		experiment.h, 115
	Izh_sparse.cc, 145	dnp
	MBody1_project/model/MBody1.cc, 153	NNmodel, 76
	MBody_delayedSyn.cc, 157	doFinal
	MBody_individualID.cc, 161	
	MBody_userdef.cc, 165	ensureFtype.h, 112
	Model_Schmuker_2014_classifier.cc, 168	stringutils.h, 199
	OneComp.cc, 175	dpNames
	PoissonIzh.cc, 178	neuronModel, 64
	postVarsInPostLearn.cc, 181	postSynModel, 81
	postVarsInPostLearn_sparse.cc, 183	weightUpdateModel, 104
	postVarsInSimCode.cc, 184	dpclass, 61
	postVarsInSimCode_sparse.cc, 185	calculateDerivedParameter, 61
	postVarsInSynapseDynamics.cc, 186	dpclass, 61
	postVarsInSynapseDynamics_sparse.cc, 187	dps
	preVarsInPostLearn.cc, 188	neuronModel, 64
	preVarsInPostLearn_sparse.cc, 189	postSynModel, 81
	preVarsInSimCode.cc, 191	weightUpdateModel, 104
	preVarsInSimCode_soc, 191 preVarsInSimCode_sparse.cc, 192	dpsp
	preVarsInSinCode_sparse.cc, 192 preVarsInSynapseDynamics.cc, 193	NNmodel, 76
		dsp_w
	preVarsInSynapseDynamics_sparse.cc, 194	NNmodel, 76
	SynDelay.cc, 200	
	SynDelaySim.h, 203	EKexp
	testPostVarsInPostLearn.h, 204	helper.h, 141
	testPostVarsInPostLearn_sparse.h, 205	ENDL
	testPostVarsInSimCode.h, 206	CodeHelper.cc, 111
	testPostVarsInSimCode_sparse.h, 207	ENaexp
	testPostVarsInSynapseDynamics.h, 208	helper.h, 141
	testPostVarsInSynapseDynamics_sparse.h, 209	EXITSYN
	testPreVarsInPostLearn.h, 210	modelSpec.h, 172
	testPreVarsInPostLearn_sparse.h, 211	EXPDECAY
	testPreVarsInSimCode.h, 212	modelSpec.h, 174
	testPreVarsInSimCode_sparse.h, 213	Elexp
	testPreVarsInSynapseDynamics.h, 214	helper.h, 141
	testPreVarsInSynapseDynamics_sparse.h, 215	endl
	_type	CodeHelper, 60
	Schmuker2014_classifier, 98	ensureFtype
	_type_double	ensureFtype.h, 112
	Schmuker2014_classifier, 98	stringutils.h, 199
	_type_float	ensureFtype.h, 112
	Schmuker2014_classifier, 98	digits, 112
	_type_int	doFinal, 112
	Schmuker2014_classifier, 98	ensureFtype, 112
uata_	_type_uint	op, 112

ensureMathFunctionFtype	REPEAT_LEARNING_SET, 115
stringutils.h, 199	SPIKING_ACTIVITY_THRESHOLD_HZ, 115
err	TOTAL_RECORDINGS, 115
errTupel, 62	timer, 115
errTupel, 62	UINT, 115
err, 62	VR_DATA_FILENAME, 115
id, 62	WEIGHT_DELTA_PN_AN, 115
evntThreshold	WEIGHT_RN_PN, 115
weightUpdateModel, 104	WEIGHT_WTA_AN_AN, 115
exlzh_ini	WEIGHT_WTA_PN_PN, 115
OneComp.cc, 175	extended_name_substitutions stringutils.h, 199
PoissonIzh.cc, 179	extended_value_substitutions
exizh_p	stringutils.h, 199
OneComp.cc, 175	extra_neurons.h, 115
PoissonIzh.cc, 179	clear, 116
exclzh_p	push_back, 116
Izh_sparse.cc, 145	simCode, 116
expDecay expDecayDp, 62	extra_postsynapses.h, 117, 118
expDecayDp, 62	extra_weightupdates.h, 119
calculateDerivedParameter, 62	extraGlobalNeuronKernelParameterTypes
expDecay, 62	neuronModel, 64
experiment.cu, 112	extraGlobalNeuronKernelParameters
applyInputToClassifier, 113	neuronModel, 64
classifier, 113	extraGlobalSynapseKernelParameterTypes
createDirectory, 113	weightUpdateModel, 104
directoryExists, 113	extraGlobalSynapseKernelParameters
getAverage, 113	weightUpdateModel, 104
getStdDev, 113	
getUniqueRunId, 113	FALSE
main, 113	modelSpec.h, 172
outputRunParameters, 113	FLAG_RUN_ON_CPU
Parameter, 113	experiment.h, 115 final
printTextFile, 113	
RAND, 113	NNmodel, 77 finalize
S_ISDIR, 113	NNmodel, 75
setDefaultParamValues, 113	findMaxMinSampleDistances
vectorContains, 113	Schmuker2014 classifier, 98
experiment.h, 114	fixGPU
CACHE_DIR, 114	HHVClampParameters.h, 143
CONNECTIVITY_AN_AN, 114	free_device_mem
CONNECTIVITY_PN_AN, 114	classIzh, 49
CONNECTIVITY_PN_PN, 114	classol, 54
CONNECTIVITY_RN_PN, 115	ftype
D_MAX_RANDOM_NUM, 115	NNmodel, 77
DATASET_NAME, 115	
divi, 115	g_ee
FLAG_RUN_ON_CPU, 115	gen_syns_sparse_izhModel.cc, 126
GLOBAL_WEIGHT_SCALING, 115	g_ei
MAX_FIRING_RATE_HZ, 115	gen_syns_sparse_izhModel.cc, 126
MAX_WEIGHT_PN_AN, 115	g_ie
MIN_FIRING_RATE_HZ, 115	gen_syns_sparse_izhModel.cc, 126
MIN_WEIGHT_PN_AN, 115	g_ii
N_FOLDING, 115	gen_syns_sparse_izhModel.cc, 126
OUTPUT_DIR, 115	GA.cc, 119
PLASTICITY_INTERVAL_MS, 115	compareErrTupel, 119
RECORDING_TIME_MS, 115 RECORDINGS_DIR, 115	procreatePop, 119 GAUSS CC
NECONDINGS_DIN, 115	GAUSS_UU

gauss.cc, 120	R, 123
GAUSS_H	RG, 123
gauss.h, 120	gen_pnkc_syns_indivID.cc, 123
gDNDN	main, 123
HHVclampGA_project/model/MBody1.cc, 150	R, 123
GENN_DOUBLE	RG, 123
modelSpec.h, 172	gen_pnlhi_syns.cc, 123
GENN_FLOAT	main, 124
modelSpec.h, 172	gen_syns_sparse.cc, 124
gKexp	main, 124
helper.h, 141	R, 124
gLHIKC	RG, 125
HHVclampGA_project/model/MBody1.cc, 150	gen_syns_sparse_izhModel.cc, 125
GLOBAL_WEIGHT_SCALING	g ee, 126
experiment.h, 115	g_ei, 126
GLOBALG	g_ie, 126
modelSpec.h, 172	g_ii, 126
gNaexp	garray, 126
helper.h, 141	garray_ee, 126
GPU	garray_ei, 126
modelSpec.h, 172	garray_ie, 126
garray	garray_ii, 126
gen_syns_sparse_izhModel.cc, 126	gsyn, 126
garray ee	ind, 126
gen_syns_sparse_izhModel.cc, 126	ind_ee, 126
garray ei	ind_ei, 126
gen_syns_sparse_izhModel.cc, 126	ind_ie, 126
garray ie	ind_ie, 126
gen_syns_sparse_izhModel.cc, 126	
	indlnG_ee, 126
garray_ii	indlnG_ei, 126
gen_syns_sparse_izhModel.cc, 126	indlnG_ie, 126
gauss.cc, 119	indlnG_ii, 126
GAUSS_CC, 120	main, 126
gauss.h, 120	printVector, 126
GAUSS_H, 120	R, 126
GeNNHelperKrnls.cu, 137	Rind, 126
BlkSz, 138	genNeuronFunction
generate_random_gpuInput_xorwow, 138	generateCPU.cc, 135
setup_kernel, 138	genNeuronKernel
xorwow_setup, 138	generateKernels.cc, 136
GeNNReady	genRunner
modelSpec.h, 174	generateRunner.cc, 137
gen_alltoall_syns	genRunnerGPU
classIzh, 49	generateRunner.cc, 137
gen_input_structured.cc, 120	genSynapseFunction
main, 121	generateCPU.cc, 135
R, 121	genSynapseKernel
gen_kcdn_syns.cc, 121	generateKernels.cc, 136
main, 121	generate_baserates
R, 121	classol, 54
RG, 121	generate_inputrates_dataset
gen_kcdn_syns_fixto10K.cc, 121	Schmuker2014_classifier, 98
main, 122	generate_model_runner
R, 122	generateALL.cc, 133
R2, 122	generate_or_load_inputrates_dataset
RG, 122	Schmuker2014_classifier, 98
gen_pnkc_syns.cc, 122	generate_process_presynaptic_events_code
main, 123	generateKernels.cc, 136

generate_process_presynaptic_events_code_CPU	Schmuker2014_classifier, 99
generateCPU.cc, 134	getStdDev
generate_random_gpuInput_xorwow	experiment.cu, 113
GeNNHelperKrnls.cu, 138	getUniqueRunId
generate_run.cc, 127–132	experiment.cu, 113
generateALL.cc, 133	glexp
chooseDevice, 133	helper.h, 141
generate_model_runner, 133	global.h, 138
main, 134	_GLOBAL_H_, 139
generateCPU.cc, 134	asGoodAsZero, 139
genNeuronFunction, 135	deviceCount, 139
genSynapseFunction, 135	deviceProp, 139
generate_process_presynaptic_events_code_C↔	hostCount, 139
PU, 134	learnBlkSz, 139
generateKernels.cc, 135	logUIntSz, 139
genNeuronKernel, 136	neuronBlkSz, 139
genSynapseKernel, 136	optimiseBlockSize, 139
generate process presynaptic events code, 136	synapseBlkSz, 139
hlp, 136	theDev, 140
isGrpVarNeeded, 136	UIntSz, 140
generateRunner.cc, 137	globalinp
genRunner, 137	NNmodel, 77
<u> </u>	gpKCDN
genRunnerGPU, 137	MBody userdef.cc, 165
generateSimulatedTimeSeriesData	gpPNKC
Schmuker2014_classifier, 98	MBody_userdef.cc, 165
gennError	gsyn
utils.h, 218	gen_syns_sparse_izhModel.cc, 126
get_kcdnsyns	3,, -
classol, 54, 55	HHVClamp.cc, 142
getAverage	DT, 142
experiment.cu, 113	modelDefinition, 142
getClassCluster	myHH_ini, 143
Schmuker2014_classifier, 98	myHH_p, 143
getClusterIndex	HHVClampParameters.h, 143
Schmuker2014_classifier, 98	fixGPU, 143
getElapsedTime	NPOP, 143
CStopWatch, 61	TOTALT, 143
getG	HHVclampGA_project/generate_run.cc
sparseUtils.cc, 198	main, 127
getManhattanDistance	HHVclampGA_project/model/MBody1.cc
Schmuker2014_classifier, 98	DT, 150
getRand0to1	gDNDN, 150
Schmuker2014_classifier, 98	gLHIKC, 150
getRecordingFilename	modelDefinition, 150
Schmuker2014_classifier, 99	myDNDN_p, 150
getSampleDistance	myKCDN_p, 150
Schmuker2014_classifier, 99	myLHIKC_p, 150
getSparseVar	myPNKC_p, 151
sparseUtils.cc, 198	myPNLHI_p, 151
getSpikeNumbersFromGPU	myPOI_ini, 151
classIzh, 50	myPOI_p, 151
classol, 55	postExpDNDN, 151
neuronpop, 66	postExpKCDN, 151
Schmuker2014_classifier, 99	postExpLHIKC, 151
getSpikesFromGPU	postExpPNKC, 152
classIzh, 50	postExpPNLHI, 152
classol, 55	postSynV, 152
neuronpop, 66	stdTM_ini, 152

stdTM_p, 152	MBody_delayedSyn_project/model/classol_sim.h,
HR_TIMER	109
hr_time.cpp, 143	MBody_individualID_project/model/classol_sim.h,
helper.h, 140	110
Cexp, 141	MBody_userdef_project/model/classol_sim.h, 111
copy_var, 141	OneComp_sim.h, 177
EKexp, 141	PoissonIzh_sim.h, 181
ENaexp, 141	VClampGA.h, 220
Elexp, 141	IZHIKEVICH
gKexp, 141	modelSpec.h, 174
gNaexp, 141	IZHIKEVICH PS
glexp, 141	modelSpec.h, 174
hexp, 141	IZHIKEVICH V
initl, 141	modelSpec.h, 174
initexpHH, 141	id
limit, 141	errTupel, 62
	•
mexp, 141	inSyn
nexp, 141	NNmodel, 77
operator<<, 141	ind
runexpHH, 141	gen_syns_sparse_izhModel.cc, 126
sigC, 141	ind_ee
sigEK, 141	gen_syns_sparse_izhModel.cc, 126
sigENa, 142	ind_ei
sigEl, 141	gen_syns_sparse_izhModel.cc, 126
sigGK, 142	ind_ie
sigGNa, 142	gen_syns_sparse_izhModel.cc, 126
sigGl, 142	ind_ii
single_var_init_fullrange, 141	gen_syns_sparse_izhModel.cc, 126
single_var_reinit, 141	indInG_ee
truevar_init, 141	gen_syns_sparse_izhModel.cc, 126
truevar_initexpHH, 141	indInG_ei
var_init_fullrange, 141	gen_syns_sparse_izhModel.cc, 126
var_reinit, 141	indlnG_ie
Vexp, 142	gen_syns_sparse_izhModel.cc, 126
write para, 141	indInG_ii
hexp	gen_syns_sparse_izhModel.cc, 126
helper.h, 141	individualSpikeCountPN
hlp	Schmuker2014 classifier, 100
generateKernels.cc, 136	inhlzh p
hostCount	Izh sparse.cc, 145
global.h, 139	init
hr_time.cpp, 143	classIzh, 50
HR TIMER, 143	classol, 55
hr_time.h, 144	neuronpop, 66
u	init neurons
INDIVIDUALG	postVarsInPostLearn, 82
	postVarsInPostLearn sparse, 83
modelSpec.h, 172	
INDIVIDUALID	postVarsInSimCode, 84
modelSpec.h, 172	postVarsInSimCode_sparse, 84
INHIBSYN	postVarsInSynapseDynamics, 85
modelSpec.h, 173	postVarsInSynapseDynamics_sparse, 86
INJECTCURRENT	preVarsInPostLearn, 87
PoissonIzh_sim.h, 181	preVarsInPostLearn_sparse, 87
INPRULE	preVarsInSimCode, 88
modelSpec.h, 173	preVarsInSimCode_sparse, 89
iT	preVarsInSynapseDynamics, 90
Izh_sparse_sim.h, 147	preVarsInSynapseDynamics_sparse, 90
MBodv1 project/model/classol sim.h. 107	init synapses

nostVaraInDostLoarn 92	inputPatasCiza
postVarsInPostLearn, 82	inputRatesSize
postVarsInPostLearn_sparse, 83	Schmuker2014_classifier, 100
postVarsInSimCode, 84	inputSpec, 63
postVarsInSimCode_sparse, 84	baseV, 63
postVarsInSynapseDynamics, 85	N, 63
postVarsInSynapseDynamics_sparse, 86	st, 63
preVarsInPostLearn, 87	t, 63
preVarsInPostLearn_sparse, 87	V, 63
preVarsInSimCode, 88	inter_ini
preVarsInSimCode sparse, 89	SynDelay.cc, 201
preVarsInSynapseDynamics, 90	inter p
preVarsInSynapseDynamics_sparse, 90	SynDelay.cc, 201
initGeNN	interOutput_ini
modelSpec.cc, 169	SynDelay.cc, 201
•	-
modelSpec.h, 173	ip0
initl	rulkovdp, 95
helper.h, 141	ip1
initLearnGrps	rulkovdp, <mark>95</mark>
NNmodel, 75	ip2
initexpHH	rulkovdp, 95
helper.h, 141	isGrpVarNeeded
initialiseInputData	generateKernels.cc, 136
Schmuker2014_classifier, 99	lzh_sim_sparse.cu, 144
initialiseWeights_DENSE_PN_AN	main, 144
Schmuker2014_classifier, 99	Izh_sparse.cc, 144
initialiseWeights SPARSE RN PN	DT, 145
· – –	
Schmuker2014_classifier, 99	exclzh_p, 145
initialiseWeights_WTA_AN_AN	inhlzh_p, 145
Schmuker2014_classifier, 99	IzhExc_ini, 145
initialiseWeights_WTA_PN_PN	IzhInh_ini, 145
Schmuker2014_classifier, 99	meanInpExc, 145
initializeAllVars	meanInpInh, 146
classIzh, 50	modelDefinition, 145
inplzh1	neuronPSize, 146
OneComp.cc, 175	neuronVSize, 146
input1	postExpP, 146
classIzh, 50	postSynV, 146
neuronpop, 66	SynIzh ini, 146
input2	SynIzh_p, 146
classIzh, 50	synapsePSize, 146
	Izh_sparse_model.cc, 146
input_ini	_ · _
SynDelay.cc, 200	_IZH_SPARSE_MODEL_CC_, 146
input_p	R, 146
SynDelay.cc, 201	RG, 146
InputBaseRate	Izh_sparse_model.h, 146
MBody1_project/model/classol_sim.h, 107	lzh_sparse_project/generate_run.cc
MBody_delayedSyn_project/model/classol_sim.h,	main, 128
108	openFileGetMax, 128
MBody_individualID_project/model/classol_sim.h,	tS, 128
110	toLower, 128
MBody_userdef_project/model/classol_sim.h, 111	toString, 128
PoissonIzh_sim.h, 181	toUpper, 128
inputInter_ini	Izh_sparse_sim.h, 147
SynDelay.cc, 201	DBG_SIZE, 147
inputOutput_ini	iT, 147
SynDelay.cc, 201	t, 147
inputRates	T_REPORT_TME, 147
Schmuker2014_classifier, 100	TOTAL_TME, 147

timer, 147	MBody1_project/model/MBody1.cc
IzhExc_ini	DT, 153
Izh_sparse.cc, 145	modelDefinition, 153
lzhlnh_ini	myDNDN_ini, 153
Izh_sparse.cc, 145	myDNDN_p, 153
	myKCDN_ini, 154
LEARN1SYNAPSE	myKCDN_p, 154
modelSpec.h, 174	myLHIKC_ini, 154
LEARNING	myLHIKC_p, 154
modelSpec.h, 173	myPNKC_ini, 154
learnBlkSz	myPNKC_p, 154
global.h, 139	myPNLHI_ini, 154
lib/include/extra_postsynapses.h	myPNLHI_p, 154
clear, 117	myPOI_ini, 155
postSynDecay, 117	myPOI_p, 155
postSyntoCurrent, 117	postExpDNDN, 155
push_back, 117	postExpKCDN, 155
lim0	postExpLHIKC, 155
pwSTDP, 91	postExpPNKC, 155
pwSTDP_userdef, 92	postExpPNLHI, 155
lim1	·
pwSTDP, 91	postSynV, 155
pwSTDP_userdef, 92	stdTM_ini, 156
limit	stdTM_p, 156
helper.h, 141	MBody1_project/model/classol_sim.cu
load_VR_data	main, 105
Schmuker2014_classifier, 99	MBody1_project/model/classol_sim.h
loadArrayFromTextFile	DBG_SIZE, 107
Schmuker2014_classifier, 99	iT, 107
loadClassLabels	InputBaseRate, 107
Schmuker2014_classifier, 99	MYRAND, 107
log	PAT_TIME, 107
Schmuker2014_classifier, 100	PATFTIME, 107
logUIntSz	PATTERNNO, 107
global.h, 139	patFireTime, 107
IrnGroups	patSetTime, 107
NNmodel, 77	SYN_OUT_TME, 107
IrnSynGrp	t, 108
NNmodel, 77	T_REPORT_TME, 107
Talandadi, 77	TOTAL_TME, 107
MAPNEURON	timer, 108
modelSpec.h, 174	MBody1_project/model/map_classol.cc
MATINP	_MAP_CLASSOL_CC_, 147
modelSpec.h, 173	MBody_delayedSyn.cc, 156
MAX_FIRING_RATE_HZ	DT, 157
experiment.h, 115	modelDefinition, 157
MAX_WEIGHT_PN_AN	myDNDN_ini, 157
experiment.h, 115	myDNDN p, 157
MAXNRN	myKCDN_ini, 157
modelSpec.h, 173	myKCDN_p, 157
MAXPOSTSYN	myLHIKC_ini, 158
modelSpec.h, 173	myLHIKC_p, 158
MBody1.cc, 149, 152	myPNKC_ini, 158
MBody1_project/generate_run.cc	myPNKC_p, 158
main, 129	myPNLHI_ini, 158
tS, 128	myPNLHI_p, 158
toLower, 129	myPOI_ini, 158
toString, 129	myPOI_p, 158
toUpper, 129	postExpDNDN, 159
to oppor, 120	poolExportors, 100

month well CDN 450	tal away 100
postExpKCDN, 159	toLower, 130
postExpLHIKC, 159	toString, 130
postExpPNKC, 159	toUpper, 130
postExpPNLHI, 159	MBody_individualID_project/model/classol_sim.cu
postSynV, 159	main, 106
stdTM_ini, 159	MBody_individualID_project/model/classol_sim.h
stdTM_p, 159	DBG_SIZE, 109
MBody_delayedSyn_project/generate_run.cc	iT, 110
main, 129	InputBaseRate, 110
tS, 129	MYRAND, 109
toLower, 129	PAT_TIME, 109
toString, 130	PATFTIME, 109
toUpper, 130	PATTERNNO, 109
MBody_delayedSyn_project/model/classol_sim.cu	patFireTime, 110
main, 106	patSetTime, 110
MBody_delayedSyn_project/model/classol_sim.h	SYN_OUT_TME, 109
DBG_SIZE, 108	t, 110
iT, 109	T_REPORT_TME, 109
	TOTAL TME, 110
InputBaseRate, 108	<i>_ ,</i>
MYRAND, 108	timer, 110
PAT_TIME, 108	MBody_individualID_project/model/map_classol.cc
PATFTIME, 108	_MAP_CLASSOL_CC_, 148
PATTERNNO, 108	MBody_userdef.cc, 164
patFireTime, 109	DT, 165
patSetTime, 109	gpKCDN, 165
SYN_OUT_TME, 108	gpPNKC, 165
t, 109	modelDefinition, 165
T_REPORT_TME, 108	myDNDN_ini, 165
TOTAL_TME, 108	myDNDN_p, 165
timer, 109	myKCDN_ini, 165
MBody_delayedSyn_project/model/map_classol.cc	myKCDN_p, 165
_MAP_CLASSOL_CC_, 148	myLHIKC_ini, 166
MBody_individualID.cc, 160	myLHIKC_p, 166
DT, 161	myPNKC_ini, 166
modelDefinition, 161	myPNKC_p, 166
myDNDN ini, 161	myPNLHI_ini, 166
myDNDN_p, 161	myPNLHI_p, 166
myKCDN_ini, 161	myPOI_ini, 166
myKCDN_p, 161	myPOI_p, 166
-	
myLHIKC_ini, 161	postExpDNDN, 166
myLHIKC_p, 162	postExpKCDN, 167
myPNKC_ini, 162	postExpLHIKC, 167
myPNKC_p, 162	postExpPNKC, 167
myPNLHI_ini, 162	postExpPNLHI, 167
myPNLHI_p, 162	postSynV, 167
myPOI_ini, 162	postSynV_EXPDECAY_EVAR, 167
myPOI_p, 162	stdTM_ini, 167
postExpDNDN, 162	stdTM_p, 167
postExpKCDN, 162	TIMING, 165
postExpLHIKC, 163	MBody_userdef_project/generate_run.cc
postExpPNKC, 163	main, 131
postExpPNLHI, 163	tS, 131
postSynV, 163	toLower, 131
stdTM_ini, 163	toString, 131
stdTM_p, 163	toUpper, 131
MBody_individualID_project/generate_run.cc	MBody_userdef_project/model/classol_sim.cu
main, 130	main, 106
tS, 130	MBody_userdef_project/model/classol_sim.h

	DBG_SIZE, 110	testPostVarsInPostLearn_sparse.cu, 205
	iT, 111	testPostVarsInSimCode.cu, 206
	InputBaseRate, 111	testPostVarsInSimCode_sparse.cu, 207
	MYRAND, 110	testPostVarsInSynapseDynamics.cu, 208
	PAT_TIME, 110	testPostVarsInSynapseDynamics_sparse.cu, 209
	PATFTIME, 110	testPreVarsInPostLearn.cu, 210
	PATTERNNO, 111	testPreVarsInPostLearn_sparse.cu, 211
	patFireTime, 111	testPreVarsInSimCode.cu, 212
	patSetTime, 111	testPreVarsInSimCode sparse.cu, 213
	SYN_OUT_TME, 111	testPreVarsInSynapseDynamics.cu, 214
	t, 111	testPreVarsInSynapseDynamics_sparse.cu, 215
	T REPORT TME, 111	VClampGA.cu, 219
	TOTAL_TME, 111	map_classol.cc, 147, 148
	timer, 111	map_classol.h, 149
MRo	ody_userdef_project/model/map_classol.cc	maxConn
IVIDO	_MAP_CLASSOL_CC_, 148	NNmodel, 77
IVIIIN	_FIRING_RATE_HZ	meanInpExc
	experiment.h, 115	lzh_sparse.cc, 145
IVIIIN _.	_WEIGHT_PN_AN	meanInpInh
	experiment.h, 115	Izh_sparse.cc, 146
MYF	RAND	mexp
	MBody1_project/model/classol_sim.h, 107	helper.h, 141
	MBody_delayedSyn_project/model/classol_sim.h,	model
	108	classIzh, 50
	MBody_individualID_project/model/classol_sim.h,	classol, 59
	109	neuronpop, 66
	MBody_userdef_project/model/classol_sim.h, 110	Schmuker2014_classifier, 100
	PoissonIzh_sim.h, 181	Model_Schmuker_2014_classifier.cc, 168
mair		CLUST_SIZE_AN, 168
	experiment.cu, 113	CLUST_SIZE_PN, 168
	gen_input_structured.cc, 121	CLUST_SIZE_RN, 168
	gen_kcdn_syns.cc, 121	DT, 168
	gen_kcdn_syns_fixto10K.cc, 122	modelDefinition, 169
	gen_pnkc_syns.cc, 123	NETWORK_SCALE, 168
	gen_pnkc_syns_indivID.cc, 123	NUM_CLASSES, 168
	gen_pnlhi_syns.cc, 124	NUM_FEATURES, 168
	gen_syns_sparse.cc, 124	NUM_VR, 168
	gen_syns_sparse_izhModel.cc, 126	SYNAPSE_TAU_ANAN, 168
	generateALL.cc, 134	SYNAPSE_TAU_PNAN, 168
	HHVclampGA_project/generate_run.cc, 127	SYNAPSE_TAU_PNPN, 169
	Izh_sim_sparse.cu, 144	SYNAPSE_TAU_RNPN, 169
	Izh_sparse_project/generate_run.cc, 128	modelDefinition
	MBody1_project/generate_run.cc, 129	HHVClamp.cc, 142
	MBody1_project/model/classol_sim.cu, 105	HHVclampGA_project/model/MBody1.cc, 150
	MBody_delayedSyn_project/generate_run.cc, 129	lzh_sparse.cc, 145
	MBody_delayedSyn_project/model/classol_sim.cu,	MBody1_project/model/MBody1.cc, 153
	106	MBody_delayedSyn.cc, 157
	MBody_individualID_project/generate_run.cc, 130	MBody_individualID.cc, 161
	MBody_individualID_project/model/classol_sim.cu,	MBody_userdef.cc, 165
	106	Model_Schmuker_2014_classifier.cc, 169
	MBody_userdef_project/generate_run.cc, 131	OneComp.cc, 175
	MBody_userdef_project/model/classol_sim.cu, 106	PoissonIzh.cc, 178
	OneComp_project/generate_run.cc, 132	postVarsInPostLearn.cc, 181
	OneComp_sim.cu, 177	postVarsInPostLearn_sparse.cc, 183
	PoissonIzh_project/generate_run.cc, 132	postVarsInSimCode.cc, 184
	PoissonIzh_sim.cu, 180	postVarsInSimCode_sparse.cc, 185
	SynDelaySim.cu, 203	postVarsInSynapseDynamics.cc, 186
	testPostVarsInPostLearn.cu, 204	postVarsInSynapseDynamics_sparse.cc, 187

preVarsInPostLearn.cc, 188	MBody_delayedSyn.cc, 157
preVarsInPostLearn_sparse.cc, 189	MBody_individualID.cc, 161
preVarsInSimCode.cc, 191	MBody_userdef.cc, 165
preVarsInSimCode_sparse.cc, 192	myDNDN_p
preVarsInSynapseDynamics.cc, 193	HHVclampGA_project/model/MBody1.cc, 150
preVarsInSynapseDynamics_sparse.cc, 194	MBody1_project/model/MBody1.cc, 153
SynDelay.cc, 200	MBody_delayedSyn.cc, 157
modelSpec.cc, 169	MBody_individualID.cc, 161
_MODELSPEC_CC_, 169	MBody userdef.cc, 165
initGeNN, 169	myHH_ini
modelSpec.h, 169	HHVClamp.cc, 143
_MODELSPEC_H_, 172	•
ALLTOALL, 172	myHH_p
	HHVClamp.cc, 143
AUTODEVICE, 172	myKCDN_ini MPady1_project/model/MPady1_co_154
CONSTINP, 172 CPU, 172	MBody1_project/model/MBody1.cc, 154
	MBody_delayedSyn.cc, 157
DENSE, 172	MBody_individualID.cc, 161
EXITSYN, 172	MBody_userdef.cc, 165
EXPDECAY, 174	myKCDN_p
FALSE, 172	HHVclampGA_project/model/MBody1.cc, 150
GENN_DOUBLE, 172	MBody1_project/model/MBody1.cc, 154
GENN_FLOAT, 172	MBody_delayedSyn.cc, 157
GLOBALG, 172	MBody_individualID.cc, 161
GPU, 172	MBody_userdef.cc, 165
GeNNReady, 174	myLHIKC_ini
INDIVIDUALG, 172	MBody1_project/model/MBody1.cc, 154
INDIVIDUALID, 172	MBody_delayedSyn.cc, 158
INHIBSYN, 173	MBody_individualID.cc, 161
INPRULE, 173	MBody_userdef.cc, 166
IZHIKEVICH, 174	myLHIKC_p
IZHIKEVICH_PS, 174	HHVclampGA_project/model/MBody1.cc, 150
IZHIKEVICH_V, 174	MBody1_project/model/MBody1.cc, 154
initGeNN, 173	MBody_delayedSyn.cc, 158
LEARN1SYNAPSE, 174	MBody_individualID.cc, 162
LEARNING, 173	MBody_userdef.cc, 166
MAPNEURON, 174	myPNKC_ini
MATINP, 173	MBody1_project/model/MBody1.cc, 154
MAXNRN, 173	MBody_delayedSyn.cc, 158
MAXPOSTSYN, 173	MBody_individualID.cc, 162
NGRADSYNAPSE, 174	MBody_userdef.cc, 166
NO_DELAY, 173	myPNKC_p
NOINP, 173	HHVclampGA_project/model/MBody1.cc, 151
NOLEARNING, 173	MBody1_project/model/MBody1.cc, 154
NSYNAPSE, 174	MBody_delayedSyn.cc, 158
POISSONNEURON, 174	MBody_individualID.cc, 162
RANDNINP, 173	MBody_userdef.cc, 166
SPARSE, 173	myPNLHI_ini
SPIKESOURCE, 174	MBody1_project/model/MBody1.cc, 154
SPK_THRESH_STDP, 173	MBody_delayedSyn.cc, 158
SYNTYPENO, 173	MBody_individualID.cc, 162
TRAUBMILES, 174	MBody_userdef.cc, 166
TRAUBMILES_ALTERNATIVE, 174	myPNLHI_p
TRAUBMILES_FAST, 174	HHVclampGA_project/model/MBody1.cc, 151
TRAUBMILES_PSTEP, 174	MBody1_project/model/MBody1.cc, 154
TRAUBMILES_SAFE, 174	MBody_delayedSyn.cc, 158
TRUE, 173	MBody_individualID.cc, 162
myDNDN_ini	MBody_userdef.cc, 166
MBody1_project/model/MBody1.cc, 153	myPOI_ini

HHVclampGA project/model/MBody1.cc, 151	neuronHostID, 77
MBody1_project/model/MBody1.cc, 155	neuronIni, 77
MBody_delayedSyn.cc, 158	neuronN, 78
MBody_individualID.cc, 162	neuronName, 78
MBody userdef.cc, 166	
· · · · · · · · · · · · · · · · · · ·	neuronNeedSpkEvnt, 78
PoissonIzh.cc, 179	neuronNeedSt, 78
myPOI_p	neuronNeedTrueSpk, 78
HHVclampGA_project/model/MBody1.cc, 151	neuronPara, 78
MBody1_project/model/MBody1.cc, 155	neuronPostSyn, 78
MBody_delayedSyn.cc, 158	neuronSpkEvntCondition, 78
MBody_individualID.cc, 162	neuronType, 78
MBody_userdef.cc, 166	neuronVarNeedQueue, 78
PoissonIzh.cc, 179	outSyn, 78
mySyn_ini	padSumLearnN, 78
PoissonIzh.cc, 179	padSumNeuronN, 78
mySyn_p	padSumSynapseKrnl, 78
OneComp.cc, 176	postSynIni, 79
PoissonIzh.cc, 179	•
1 0.000 m2 m2 m 0 0, 17 0	postSynapsePara, 78
N	postSynapseType, 78
inputSpec, 63	RNtype, 79
n	receivesInputCurrent, 79
randomGauss, 93	seed, 79
randomGen, 94	setConstInp, 75
	setGPUDevice, 75
stdRG, 102	setMaxConn, 75
N_FOLDING	setName, 75
experiment.h, 115	setNeuronClusterIndex, 75
NETWORK_SCALE	setPrecision, 76
Model_Schmuker_2014_classifier.cc, 168	setSeed, 76
NGRADSYNAPSE	
modelSpec.h, 174	setSynapseClusterIndex, 76
nModels	setSynapseG, 76
utils.h, 219	setTiming, 76
NNmodel, 67	sumNeuronN, 79
\sim NNmodel, 70	synapseConnType, 79
activateDirectInput, 70	synapseDelay, 79
addNeuronPopulation, 70, 71	synapseDeviceID, 79
addSynapsePopulation, 71, 73, 74	synapseGType, 79
checkSizes, 75	synapseGrpN, 79
chooseGPUDevice, 76	synapseHostID, 79
	synapselnSynNo, 79
dnp, 76	synapselni, 79
dpsp, 76	synapseName, 79
dsp_w, 76	synapseOutSynNo, 79
final, 77	- · ·
finalize, 75	synapsePara, 79
ftype, 77	synapseSource, 80
globalInp, 77	synapseSpkEvntVars, 80
inSyn, 77	synapseTarget, 80
initLearnGrps, 75	synapseType, 80
IrnGroups, 77	synapseUsesPostLearning, 80
IrnSynGrp, 77	synapseUsesSpikeEvents, 80
maxConn, 77	synapseUsesTrueSpikes, 80
NNmodel, 70	timing, 80
name, 77	NO DELAY
needSt, 77	modelSpec.h, 173
needSynapseDelay, 77	NOINP
neuronDelaySlots, 77	modelSpec.h, 173
neuronDeviceID, 77	NOLEARNING
neuronGrpN, 77	modelSpec.h, 173

NPOP	neuronDelaySlots
HHVClampParameters.h, 143	NNmodel, 77
NSYNAPSE	neuronDeviceID
modelSpec.h, 174	NNmodel, 77
NUM_CLASSES	neuronGrpN
Model_Schmuker_2014_classifier.cc, 168	NNmodel, 77
NUM_FEATURES	neuronHostID
Model_Schmuker_2014_classifier.cc, 168	NNmodel, 77
NUM_VR	neuronIni
Model_Schmuker_2014_classifier.cc, 168	NNmodel, 77
name	neuronModel, 63
NNmodel, 77	dpNames, 64
Parameter, 80	dps, 64
name_substitutions	extraGlobalNeuronKernelParameterTypes, 64
stringutils.h, 199	extraGlobalNeuronKernelParameters, 64
needPostSt	needPostSt, 64
neuronModel, 64	needPreSt, 64
weightUpdateModel, 104	pNames, 64
needPreSt	resetCode, 64
neuronModel, 64	simCode, 64
weightUpdateModel, 104	thresholdConditionCode, 65
needSt	tmpVarNames, 65
NNmodel, 77	tmpVarTypes, 65
needSynapseDelay	varNames, 65
NNmodel, 77	varTypes, 65
neuron_ini	neuronN
postVarsInPostLearn.cc, 182	NNmodel, 78
postVarsInPostLearn_sparse.cc, 183	neuronName
postVarsInSimCode.cc, 184	NNmodel, 78
postVarsInSimCode_sparse.cc, 185	neuronNeedSpkEvnt
postVarsInSynapseDynamics.cc, 186	NNmodel, 78
postVarsInSynapseDynamics_sparse.cc, 187	neuronNeedSt
preVarsInPostLearn.cc, 188	NNmodel, 78
preVarsInPostLearn_sparse.cc, 189	neuronNeedTrueSpk
preVarsInSimCode.cc, 191	NNmodel, 78
preVarsInSimCode_sparse.cc, 192	neuronPSize
preVarsInSynapseDynamics.cc, 193	Izh_sparse.cc, 146
preVarsInSynapseDynamics_sparse.cc, 194	neuronPara
neuron_p	NNmodel, 78
postVarsInPostLearn.cc, 182	neuronPostSyn
postVarsInPostLearn_sparse.cc, 183	NNmodel, 78
postVarsInSimCode.cc, 184	neuronSpkEvntCondition
postVarsInSimCode_sparse.cc, 185	NNmodel, 78
postVarsInSynapseDynamics.cc, 186	neuronType
postVarsInSynapseDynamics_sparse.cc, 187	NNmodel, 78
preVarsInPostLearn.cc, 188	neuronVSize
preVarsInPostLearn_sparse.cc, 190	Izh_sparse.cc, 146
preVarsInSimCode.cc, 191	neuronVarNeedQueue
preVarsInSimCode_sparse.cc, 192	NNmodel, 78
preVarsInSynapseDynamics.cc, 193	neuronpop, 65
preVarsInSynapseDynamics_sparse.cc, 194	\sim neuronpop, 66
neuron_p2	allocate_device_mem_input, 66
postVarsInPostLearn.cc, 182	allocate_device_mem_patterns, 66
postVarsInPostLearn_sparse.cc, 183	copy_device_mem_input, 66
preVarsInPostLearn.cc, 188	create_input_values, 66
preVarsInPostLearn_sparse.cc, 190	d_input1, 66
neuronBlkSz	getSpikeNumbersFromGPU, 66
global.h, 139	getSpikesFromGPU, 66

init, 66	CodeHelper, 60
input1, 66	openFileGetMax
model, 66	Izh_sparse_project/generate_run.cc, 128
neuronpop, 66	openRecordingFile
output_spikes, 66	Schmuker2014_classifier, 99
output_state, 66	operator<<
read_input_values, 66	helper.h, 141
run, 66	optimiseBlockSize
sum_spikes, 66	global.h, 139
sumlzh1, 66	outSyn
write_input_to_file, 66	NNmodel, 78
nexp	output_ini
helper.h, 141	SynDelay.cc, 201
nlong	output_p
stdRG, 102	SynDelay.cc, 202
	output_params
OB	classIzh, 50
CodeHelper.cc, 111	output_spikes
OUTPUT_DIR	classIzh, 50
experiment.h, 115	classol, 55, 56
off0	neuronpop, 66
pwSTDP, 91	output_state
pwSTDP_userdef, 92	classIzh, 50
off1	classol, 56
pwSTDP, 91	neuronpop, 66
pwSTDP_userdef, 92	outputDir
off2	Schmuker2014_classifier, 100
pwSTDP, 91	outputRunParameters
pwSTDP_userdef, 92	experiment.cu, 113
offset	outputSpikes
classol, 59	Schmuker2014_classifier, 99
OneComp.cc, 175	overallWinnerSpikeCountAN
DT, 175	Schmuker2014_classifier, 100
exlzh_ini, 175	_ ,
exlzh_p, 175	p_pattern
inplzh1, 175	classol, 59
modelDefinition, 175	PAT_TIME
mySyn_p, 176	MBody1_project/model/classol_sim.h, 107
postExp, 176	MBody_delayedSyn_project/model/classol_sim.h,
postSynV, 176	108
OneComp_model.cc, 176	MBody_individualID_project/model/classol_sim.h,
_ONECOMP_MODEL_CC_, 176	109
OneComp_model.h, 176	MBody_userdef_project/model/classol_sim.h, 110
OneComp_project/generate_run.cc	PATFTIME
main, 132	MBody1_project/model/classol_sim.h, 107
toString, 132	MBody_delayedSyn_project/model/classol_sim.h,
OneComp_sim.cu, 176	108
main, 177	MBody_individualID_project/model/classol_sim.h,
OneComp_sim.h, 177	109
DBG_SIZE, 177	MBody_userdef_project/model/classol_sim.h, 110
iT, 177	PATTERNNO
t, 177	MBody1_project/model/classol_sim.h, 107
T_REPORT_TME, 177	MBody_delayedSyn_project/model/classol_sim.h,
TOTAL_TME, 177	108
timer, 177	MBody_individualID_project/model/classol_sim.h,
ор	109
ensureFtype.h, 112	MBody_userdef_project/model/classol_sim.h, 111
stringutils.h, 200	PoissonIzh_sim.h, 181
openBrace	PLASTICITY_INTERVAL_MS

experiment.h, 115	MBody_individualID_project/model/classol_sim.h,
pNames	110
neuronModel, 64	MBody_userdef_project/model/classol_sim.h, 111
postSynModel, 81	pattern
weightUpdateModel, 104	classol, 59
POISSONNEURON	plasticWeights
modelSpec.h, 174	Schmuker2014_classifier, 101
padSumLearnN	PoissonIzh-model.cc, 177
NNmodel, 78	_POISSONIZHMODEL_CC_, 178
padSumNeuronN	PoissonIzh-model.h, 178
NNmodel, 78	PoissonIzh.cc, 178
padSumSynapseKrnl	FTYPE, 178
NNmodel, 78	DT, 178
param_CONNECTIVITY_AN_AN	exlzh_ini, 179
Schmuker2014_classifier, 100	exizh_p, 179
param_CONNECTIVITY_PN_AN	modelDefinition, 178
Schmuker2014_classifier, 100	myPOI_ini, 179
param_CONNECTIVITY_PN_PN	myPOI_p, 179
Schmuker2014 classifier, 100	mySyn ini, 179
param_CONNECTIVITY_RN_PN	mySyn_p, 179
Schmuker2014_classifier, 100	postExp, 179
param_GLOBAL_WEIGHT_SCALING	postSynV, 180
Schmuker2014_classifier, 100	SCALAR_MAX, 178
param_MAX_FIRING_RATE_HZ	SCALAR MIN, 178
Schmuker2014_classifier, 100	scalar, 178
param_MAX_WEIGHT_PN_AN	PoissonIzh_project/generate_run.cc
Schmuker2014_classifier, 100	main, 132
param_MIN_FIRING_RATE_HZ	toString, 132
Schmuker2014_classifier, 100	PoissonIzh_sim.cu, 180
param_MIN_WEIGHT_PN_AN	main, 180
Schmuker2014_classifier, 100	PoissonIzh_sim.h, 180
param_PLASTICITY_INTERVAL_MS	DBG_SIZE, 181
Schmuker2014_classifier, 100	INJECTCURRENT, 181
param_SPIKING_ACTIVITY_THRESHOLD_HZ	iT, 181
Schmuker2014 classifier, 100	InputBaseRate, 181
param_WEIGHT_DELTA_PN_AN	MYRAND, 181
Schmuker2014_classifier, 100	PATTERNNO, 181
param_WEIGHT_RN_PN	SYN OUT TME, 181
Schmuker2014_classifier, 101	t, 181
param_WEIGHT_WTA_AN_AN	T_REPORT_TME, 181
Schmuker2014_classifier, 101	TOTAL_TME, 181
param_WEIGHT_WTA_PN_PN	timer, 181
Schmuker2014_classifier, 101	populateDeviceMemory
Parameter, 80	Schmuker2014_classifier, 99
experiment.cu, 113	postExp
name, 80	OneComp.cc, 176
value, 80	PoissonIzh.cc, 179
patFireTime	postExpDNDN
MBody1_project/model/classol_sim.h, 107	HHVclampGA_project/model/MBody1.cc, 151
MBody_delayedSyn_project/model/classol_sim.h,	MBody1_project/model/MBody1.cc, 155
109	MBody_delayedSyn.cc, 159
MBody_individualID_project/model/classol_sim.h,	MBody_individualID.cc, 162
110	MBody_userdef.cc, 166
MBody_userdef_project/model/classol_sim.h, 111	postExpInp
patSetTime	SynDelay.cc, 202
MBody1_project/model/classol_sim.h, 107	postExpInt
$MBody_delayedSyn_project/model/classol_sim.h,$	SynDelay.cc, 202
109	postExpKCDN

HHVclampGA_project/model/MBody1.cc, 151	NNmodel, 79
MBody1_project/model/MBody1.cc, 155	postSynModel, 81
MBody_delayedSyn.cc, 159	dpNames, 81
MBody_individualID.cc, 162	dps, 81
MBody_userdef.cc, 167	pNames, 81
postExpLHIKC	postSynDecay, 81
HHVclampGA_project/model/MBody1.cc, 151	postSyntoCurrent, 81
MBody1_project/model/MBody1.cc, 155	varNames, 81
MBody_delayedSyn.cc, 159	varTypes, 81
MBody_individualID.cc, 163	postSynModels
MBody_userdef.cc, 167	utils.h, 219
postExpOut	postSynV
SynDelay.cc, 202	HHVclampGA_project/model/MBody1.cc, 152
postExpP	Izh_sparse.cc, 146
Izh_sparse.cc, 146	MBody1_project/model/MBody1.cc, 155
postExpPNKC	MBody_delayedSyn.cc, 159
HHVclampGA_project/model/MBody1.cc, 152	MBody_individualID.cc, 163
MBody1_project/model/MBody1.cc, 155	MBody_userdef.cc, 167
MBody_delayedSyn.cc, 159	OneComp.cc, 176
	PoissonIzh.cc, 180
MBody_individualID.cc, 163	
MBody_userdef.cc, 167	SynDelay.cc, 202
postExpPNLHI	postSynV_EXPDECAY_EVAR
HHVclampGA_project/model/MBody1.cc, 152	MBody_userdef.cc, 167
MBody1_project/model/MBody1.cc, 155	postSynapsePara
MBody_delayedSyn.cc, 159	NNmodel, 78
MBody_individualID.cc, 163	postSynapseType
MBody_userdef.cc, 167	NNmodel, 78
postSyn_ini	postSyntoCurrent
postVarsInPostLearn.cc, 182	lib/include/extra_postsynapses.h, 117
postVarsInPostLearn_sparse.cc, 183	postSynModel, 81
postVarsInSimCode.cc, 184	SpineML_to_GeNN/extra_postsynapses.h, 118
postVarsInSimCode_sparse.cc, 185	postVarsInPostLearn, 82
postVarsInSynapseDynamics.cc, 186	~postVarsInPostLearn, 82
postVarsInSynapseDynamics_sparse.cc, 187	init_neurons, 82
preVarsInPostLearn.cc, 189	init_synapses, 82
preVarsInPostLearn_sparse.cc, 190	postVarsInPostLearn, 82
preVarsInSimCode.cc, 191	run, 82
preVarsInSimCode_sparse.cc, 192	theW, 82
preVarsInSynapseDynamics.cc, 193	postVarsInPostLearn.cc, 181
preVarsInSynapseDynamics_sparse.cc, 194	DT, 181
postSyn_p	modelDefinition, 181
postVarsInPostLearn.cc, 182	neuron_ini, 182
postVarsInPostLearn_sparse.cc, 183	neuron p, 182
postVarsInSimCode.cc, 184	_ , ·
•	neuron_p2, 182
postVarsInSimCode_sparse.cc, 185	postSyn_ini, 182
postVarsInSynapseDynamics.cc, 186	postSyn_p, 182
postVarsInSynapseDynamics_sparse.cc, 187	synapses_ini, 182
preVarsInPostLearn.cc, 189	synapses_p, 182
preVarsInPostLearn_sparse.cc, 190	postVarsInPostLearn_sparse, 82
preVarsInSimCode.cc, 191	~postVarsInPostLearn_sparse, 83
preVarsInSimCode_sparse.cc, 192	init_neurons, 83
preVarsInSynapseDynamics.cc, 193	init_synapses, 83
preVarsInSynapseDynamics_sparse.cc, 194	postVarsInPostLearn_sparse, 83
postSynDecay	run, 83
lib/include/extra_postsynapses.h, 117	theW, 83
postSynModel, 81	postVarsInPostLearn_sparse.cc, 182
SpineML_to_GeNN/extra_postsynapses.h, 118	DT, 183
postSynIni	modelDefinition, 183

neuron_ini, 183	init_synapses, 86
neuron_p, 183	postVarsInSynapseDynamics_sparse, 86
neuron_p2, 183	run, 86
postSyn_ini, 183	theW, 86
postSyn_p, 183	postVarsInSynapseDynamics_sparse.cc, 187
synapses_ini, 183	DT, 187
synapses_p, 183	modelDefinition, 187
postVarsInSimCode, 83	neuron_ini, 187
~postVarsInSimCode, 84	neuron_p, 187
init neurons, 84	postSyn_ini, 187
init synapses, 84	postSyn_p, 187
postVarsInSimCode, 84	synapses_ini, 187
run, 84	synapses_p, 187
theW, 84	postsynapticVariables/testHelper.h
postVarsInSimCode.cc, 184	absDiff, 203
DT, 184	preVarsInPostLearn, 86
modelDefinition, 184	~preVarsInPostLearn, 87
neuron_ini, 184	init_neurons, 87
	init_synapses, 87
neuron_p, 184	
postSyn_ini, 184	preVarsInPostLearn, 87
postSyn_p, 184	run, 87
synapses_ini, 184	theW, 87
synapses_p, 184	preVarsInPostLearn.cc, 188
postVarsInSimCode_sparse, 84	DT, 188
~postVarsInSimCode_sparse, 84	modelDefinition, 188
init_neurons, 84	neuron_ini, 188
init_synapses, 84	neuron_p, 188
postVarsInSimCode_sparse, 84	neuron_p2, 188
run, 84	postSyn_ini, 189
theW, 84	postSyn_p, 189
postVarsInSimCode_sparse.cc, 185	synapses_ini, 189
DT, 185	synapses_p, 189
modelDefinition, 185	preVarsInPostLearn_sparse, 87
neuron_ini, 185	\sim preVarsInPostLearn_sparse, 87
neuron_p, 185	init_neurons, 87
postSyn_ini, 185	init_synapses, 87
postSyn_p, 185	preVarsInPostLearn_sparse, 87
synapses_ini, 185	run, 87
synapses_p, 185	theW, 87
postVarsInSynapseDynamics, 85	preVarsInPostLearn_sparse.cc, 189
~postVarsInSynapseDynamics, 85	DT, 189
init_neurons, 85	modelDefinition, 189
init_synapses, 85	neuron_ini, 189
postVarsInSynapseDynamics, 85	neuron_p, 190
run, 85	neuron_p2, 190
theW, 85	postSyn_ini, 190
postVarsInSynapseDynamics.cc, 186	postSyn_p, 190
DT, 186	synapses_ini, 190
modelDefinition, 186	synapses_p, 190
	preVarsInSimCode, 88
neuron_ini, 186 neuron_p, 186	~preVarsInSimCode, 88
_ .	•
postSyn_ini, 186	init_neurons, 88
postSyn_p, 186	init_synapses, 88
synapses_ini, 186	preVarsInSimCode, 88
synapses_p, 186	run, 88
postVarsInSynapseDynamics_sparse, 85	theW, 88
~postVarsInSynapseDynamics_sparse, 86	preVarsInSimCode.cc, 190
init_neurons, 86	DT, 191

modelDefinition 101	utilo b. 219
modelDefinition, 191	utils.h, 218
neuron_ini, 191	prepareWeightUpdateModels
neuron_p, 191	utils.h, 218
postSyn_ini, 191	presynapticVariables/testHelper.h
postSyn_p, 191	absDiff, 204
synapses_ini, 191	printSeparator
synapses_p, 191	Schmuker2014_classifier, 99
preVarsInSimCode_sparse, 88	printTextFile
\sim preVarsInSimCode_sparse, 89	experiment.cu, 113
init_neurons, 89	printVector
init_synapses, 89	gen_syns_sparse_izhModel.cc, 126
preVarsInSimCode_sparse, 89	procreatePop
run, 89	GA.cc, 119
theW, 89	ps
preVarsInSimCode_sparse.cc, 191	SpineML_to_GeNN/extra_postsynapses.h, 119
DT, 192	push_back
	extra_neurons.h, 116
modelDefinition, 192	lib/include/extra postsynapses.h, 117
neuron_ini, 192	SpineML to GeNN/extra postsynapses.h, 118
neuron_p, 192	pwSTDP, 91
postSyn_ini, 192	•
postSyn_p, 192	calculateDerivedParameter, 91
synapses_ini, 192	lim0, 91
synapses_p, 192	lim1, 91
preVarsInSynapseDynamics, 89	off0, 91
~preVarsInSynapseDynamics, 90	off1, 91
init_neurons, 90	off2, 91
init_synapses, 90	slope0, 91
preVarsInSynapseDynamics, 90	slope1, 91
run, 90	pwSTDP_userdef, 92
theW, 90	calculateDerivedParameter, 92
	lim0, 92
preVarsInSynapseDynamics.cc, 192	lim1, 92
DT, 193	off0, 92
modelDefinition, 193	off1, 92
neuron_ini, 193	off2, 92
neuron_p, 193	slope0, 92
postSyn_ini, 193	slope1, 92
postSyn_p, 193	310pe 1, 32
synapses_ini, 193	R
synapses_p, 193	gen_input_structured.cc, 121
preVarsInSynapseDynamics_sparse, 90	gen_kcdn_syns.cc, 121
~preVarsInSynapseDynamics_sparse, 90	gen_kcdn_syns_fixto10K.cc, 122
init_neurons, 90	gen_pnkc_syns.cc, 123
init_synapses, 90	gen_pnkc_syns_indivID.cc, 123
preVarsInSynapseDynamics_sparse, 90	
run, 90	gen_syns_sparse.cc, 124
theW, 90	gen_syns_sparse_izhModel.cc, 126
	lzh_sparse_model.cc, 146
preVarsInSynapseDynamics_sparse.cc, 193	VClampGA.h, 220
DT, 194	R2
modelDefinition, 194	gen_kcdn_syns_fixto10K.cc, 122
neuron_ini, 194	RAND
neuron_p, 194	experiment.cu, 113
postSyn_ini, 194	VClampGA.h, 220
postSyn_p, 194	RANDNINP
synapses_ini, 194	modelSpec.h, 173
synapses_p, 194	RANDOMGEN_CC
preparePostSynModels	randomGen.cc, 194
utils.h, 218	RANDOMGEN H
prepareStandardModels	randomGen.h, 195
• •	•

RECORDING_TIME_MS	classol, 56
experiment.h, 115	read_pnkcsyns
RECORDINGS_DIR	classol, 56, 57
experiment.h, 115	read_pnlhisyns
REPEAT_LEARNING_SET	classol, 57
experiment.h, 115	read_sparsesyns_par
REPORT_TIME	classIzh, 50
SynDelaySim.h, 203	classol, 57
testPostVarsInPostLearn.h, 204	receivesInputCurrent
testPostVarsInPostLearn sparse.h, 205	NNmodel, 79
testPostVarsInSimCode.h, 206	recordingsDir
testPostVarsInSimCode sparse.h, 207	Schmuker2014_classifier, 101
testPostVarsInSynapseDynamics.h, 208	resetClusterSpikeCountAN
testPostVarsInSynapseDynamics_sparse.h, 209	Schmuker2014_classifier, 99
testPreVarsInPostLearn.h, 210	resetCode
testPreVarsInPostLearn_sparse.h, 211	neuronModel, 64
testPreVarsInSimCode.h, 212	resetDevice
testPreVarsInSimCode sparse.h, 213	Schmuker2014_classifier, 99
testPreVarsInSynapseDynamics.h, 214	resetIndividualSpikeCountPN
testPreVarsInSynapseDynamics_sparse.h, 215	Schmuker2014_classifier, 99
RG	resetOverallWinner
gen_kcdn_syns.cc, 121	Schmuker2014_classifier, 99
gen_kcdn_syns_fixto10K.cc, 122	Rind
gen_pnkc_syns.cc, 123	gen_syns_sparse_izhModel.cc, 126
gen_pnkc_syns_indivID.cc, 123	rulkovdp, 95
gen_syns_sparse.cc, 125	calculateDerivedParameter, 95
lzh_sparse_model.cc, 146	ip0, 95
VClampGA.h, 220	ip1, 95
RNtype	ip2, 95
NNmodel, 79	run
randomEventOccurred	classIzh, 50
Schmuker2014_classifier, 99	classol, 57, 58
randomGauss, 93	neuronpop, 66
~randomGauss, 93	postVarsInPostLearn, 82
n, 93	postVarsInPostLearn_sparse, 83
randomGauss, 93	postVarsInSimCode, 84
srand, 93	postVarsInSimCode_sparse, 84
randomGen, 94	postVarsInSynapseDynamics, 85
∼randomGen, 94	postVarsInSynapseDynamics_sparse, 86
n, 94	preVarsInPostLearn, 87
randomGen, 94	preVarsInPostLearn_sparse, 87
srand, 94	preVarsInSimCode, 88
randomGen.cc, 194	preVarsInSimCode_sparse, 89
RANDOMGEN_CC, 194	preVarsInSynapseDynamics, 90
randomGen.h, 195	preVarsInSynapseDynamics_sparse, 90
RANDOMGEN H, 195	Schmuker2014_classifier, 99
randomizeVar	SynDelay, 102
classIzh, 50	runCPU
randomizeVarSq	classol, 58
classIzh, 50	runGPU
read_PNIzh1syns	classol, 58
classol, 56	runexpHH
	helper.h, 141
read_input_patterns classol, 56	e ienip
	S_ISDIR
read_input_values	experiment.cu, 113 SAVEP
classIzh, 50	
neuronpop, 66 read_kcdnsyns	CodeHelper.cc, 111 SCALAR MAX
reau noullaylla	OUALAI I_IVIAA

PoissonIzh.cc, 178	createWTAConnectivity, 98
SCALAR MIN	d_inputRates, 100
PoissonIzh.cc, 178	d_maxRandomNumber, 100
SIMPLEBIT H	data_type, 98
-	data_type, 98 data_type_double, 98
simpleBit.h, 197 SPARSE	data_type_double, 98 data_type_float, 98
modelSpec.h, 173	data_type_int, 98
SPIKESOURCE	data_type_uint, 98
modelSpec.h, 174	datasetName, 100
SPIKING_ACTIVITY_THRESHOLD_HZ	findMaxMinSampleDistances, 98
experiment.h, 115	generate_inputrates_dataset, 98
SPK_THRESH_STDP	generate_or_load_inputrates_dataset, 98
modelSpec.h, 173	generateSimulatedTimeSeriesData, 98
SYN_OUT_TME	getClassCluster, 98
MBody1_project/model/classol_sim.h, 107	getClusterIndex, 98
MBody_delayedSyn_project/model/classol_sim.h,	getManhattanDistance, 98
108	getRand0to1, 98
MBody_individualID_project/model/classol_sim.h,	getRecordingFilename, 99
109	getSampleDistance, 99
MBody_userdef_project/model/classol_sim.h, 111	getSpikeNumbersFromGPU, 99
PoissonIzh_sim.h, 181	getSpikesFromGPU, 99
SYNAPSE_TAU_ANAN	individualSpikeCountPN, 100
Model_Schmuker_2014_classifier.cc, 168	initialiseInputData, 99
SYNAPSE_TAU_PNAN	initialiseWeights_DENSE_PN_AN, 99
Model_Schmuker_2014_classifier.cc, 168	initialiseWeights_SPARSE_RN_PN, 99
SYNAPSE_TAU_PNPN	initialiseWeights_WTA_AN_AN, 99
Model_Schmuker_2014_classifier.cc, 169	initialiseWeights_WTA_PN_PN, 99
SYNAPSE_TAU_RNPN	inputRates, 100
Model_Schmuker_2014_classifier.cc, 169	inputRatesSize, 100
SYNDELAYSIM_CU	load_VR_data, 99
SynDelaySim.cu, 203	loadArrayFromTextFile, 99
SYNTYPENO	loadClassLabels, 99
modelSpec.h, 173	log, 100
sampleDistance	model, 100
Schmuker2014_classifier, 101	openRecordingFile, 99
scalar	outputDir, 100
PoissonIzh.cc, 178	outputSpikes, 99
Schmuker2014_classifier, 95	overallWinnerSpikeCountAN, 100
~Schmuker2014_classifier, 98	param_CONNECTIVITY_AN_AN, 100
addInputRate, 98	param CONNECTIVITY PN AN, 100
allocateHostAndDeviceMemory, 98	param_CONNECTIVITY_PN_PN, 100
applyLearningRuleSynapses, 98	param_CONNECTIVITY_RN_PN, 100
cacheDir, 100	param GLOBAL WEIGHT SCALING, 100
calculateCurrentWindowWinner, 98	param_MAX_FIRING_RATE_HZ, 100
calculateOverallWinner, 98	param_MAX_WEIGHT_PN_AN, 100
calculateVrResponse, 98	param MIN FIRING RATE HZ, 100
calculateWinner, 98	param_MIN_WEIGHT_PN_AN, 100
checkContents, 98	param_PLASTICITY_INTERVAL_MS, 100
classLabel, 100	param SPIKING ACTIVITY THRESHOLD HZ,
clearDownDevice, 98	100
clearedDownDevice, 100	param_WEIGHT_DELTA_PN_AN, 100
clusterSpikeCountAN, 100	param_WEIGHT_RN_PN, 101
convertToRateCode, 98	param_WEIGHT_WTA_AN_AN, 101
correctClass, 100	param_WEIGHT_WTA_PN_PN, 101
countAN, 100	plasticWeights, 101
countPN, 100	populateDeviceMemory, 99
countPNAN, 100	printSeparator, 99
	randomEventOccurred, 99
countRN, 100	randomeveniloccurred, 33

recordingsDir, 101	setVerbose
resetClusterSpikeCountAN, 99	CodeHelper, 60
resetDevice, 99	setup_kernel
resetIndividualSpikeCountPN, 99	GeNNHelperKrnls.cu, 138
resetOverallWinner, 99	sigC
run, 99	helper.h, 141
sampleDistance, 101	sigEK
Schmuker2014_classifier, 98	helper.h, 141
setCorrectClass, 99	sigENa
setMaxMinSampleDistances, 99	helper.h, 142
startLog, 99	sigEl
t, 101	helper.h, 141
timestepsPerRecording, 101	sigGK
uniqueRunId, 101	helper.h, 142
update_input_data_on_device, 99	sigGNa
updateClusterSpikeCountAN, 99	helper.h, 142
updateIndividualSpikeCountPN, 99	sigGl
updateWeights_PN_AN, 99	helper.h, 142
updateWeights_PN_AN_on_device, 99	simCode
vrData, 101	extra_neurons.h, 116
winningClass, 101	neuronModel, 64
Schmuker2014_classifier.cu, 195	weightUpdateModel, 104
_SCHMUKER2014_CLASSIFIER_, 196	simCodeEvnt
Schmuker2014_classifier.h, 196	weightUpdateModel, 104
seed	simLearnPost
NNmodel, 79	weightUpdateModel, 104
setB	simpleBit.h, 196
simpleBit.h, 197	B, 197
setConstInp	delB, 197
NNmodel, 75	SIMPLEBIT_H, 197
setCorrectClass	setB, 197
Schmuker2014_classifier, 99	single_var_init_fullrange
setDefaultParamValues	helper.h, 141
experiment.cu, 113	single_var_reinit
setGPUDevice	helper.h, 141
NNmodel, 75	size_g
setInput	classol, 59
classIzh, 50	sizes.h, 197
setMaxConn	_NC1, 197
NNmodel, 75	slope0
setMaxMinSampleDistances	pwSTDP, 91
Schmuker2014_classifier, 99	pwSTDP_userdef, 92
setName	slope1
NNmodel, 75	pwSTDP, 91
setNeuronClusterIndex	pwSTDP_userdef, 92
NNmodel, 75	sparse_utils_cc
setPrecision	sparseUtils.cc, 198
NNmodel, 76	sparseUtils.cc, 197
setSeed	countEntriesAbove, 198
NNmodel, 76	createPosttoPreArray, 198
setSparseConnectivityFromDense	createSparseConnectivityFromDense, 198
sparseUtils.cc, 198	getG, 198
setSynapseClusterIndex	getSparseVar, 198
NNmodel, 76	setSparseConnectivityFromDense, 198
setSynapseG	sparse_utils_cc, 198
NNmodel, 76	strsearch, 198
setTiming	SpineML_to_GeNN/extra_postsynapses.h
NNmodel, 76	clear, 118
, -	, -

	postSynDecay, 118	classIzh, 50
	postSyntoCurrent, 118	classol, 58
	ps, 119	neuronpop, 66
	push_back, 118	sumDN
sranc		classol, 59
	randomGauss, 93	sumlzh1
	randomGen, 94	classol, 59
st		neuronpop, 66
	inputSpec, 63	sumKC
start		classol, 59
	stopWatch, 102	sumLHI
startl	-	classol, 59
	Schmuker2014_classifier, 99	sumNeuronN
	Timer	NNmodel, 79
	CStopWatch, 61	sumPExc
	G, 101	classIzh, 50
	~stdRG, 101	sumPlnh
	n, 102	classIzh, 50
	nlong, 102	sumPN
	stdRG, 101	classol, 59
stdTN		SynDelay, 102
	HHVclampGA_project/model/MBody1.cc, 152	∼SynDelay, 102
	MBody1_project/model/MBody1.cc, 156	run, 102
	MBody_delayedSyn.cc, 159	SynDelay, 102
	MBody_individualID.cc, 163	SynDelay.cc, 200
	MBody_userdef.cc, 167	constlnput, 200
stdTN	-	DT, 200
	HHVclampGA_project/model/MBody1.cc, 152 MBody1_project/model/MBody1.cc, 156	input_ini, 200
	MBody_delayedSyn.cc, 159	input_p, 201 inputInter_ini, 201
	MBody_individualID.cc, 163 MBody_userdef.cc, 167	inputOutput_ini, 201 inter_ini, 201
	wibody_userder.cc, 107	inter_nii, 201
stop	stopWatch, 102	inter_p, 201
stop7	·	modelDefinition, 200
	CStopWatch, 61	output_ini, 201
	Watch, 102	output_p, 202
•	start, 102	postExpInp, 202
	stop, 102	postExplint, 202
	gutils.h, 198	postExpOut, 202
Sumg	dnames, 200	postSynV, 202
	fnames, 200	synapses_p, 202
	mathFN, 199	SynDelaySim.cu, 202
	digits, 200	main, 203
	doFinal, 199	SYNDELAYSIM CU, 203
	ensureFtype, 199	SynDelaySim.h, 203
	ensureMathFunctionFtype, 199	DT, 203
	extended_name_substitutions, 199	REPORT TIME, 203
	extended_value_substitutions, 199	TOTAL_TIME, 203
	name_substitutions, 199	SynIzh_ini
	op, 200	lzh_sparse.cc, 146
	substitute, 199	SynIzh_p
	value_substitutions, 199	Izh_sparse.cc, 146
strse		synapseBlkSz
	sparseUtils.cc, 198	global.h, 139
subst	•	synapseConnType
	stringutils.h, 199	NNmodel, 79
	spikes	synapseDelay
Juii_	_abaa	5,ap5525iay

NNmadel 70	nra/aralnDaatl aarn anaraa aa 100
NNmodel, 79	preVarsInPostLearn_sparse.cc, 190
synapseDeviceID	preVarsInSimCode.cc, 191
NNmodel, 79	preVarsInSimCode_sparse.cc, 192
synapseDynamics	preVarsInSynapseDynamics.cc, 193
weightUpdateModel, 104	preVarsInSynapseDynamics_sparse.cc, 194
synapseGType	SynDelay.cc, 202
NNmodel, 79	t
synapseGrpN	inputSpec, 63
NNmodel, 79	·
synapseHostID	Izh_sparse_sim.h, 147
NNmodel, 79	MBody1_project/model/classol_sim.h, 108
synapseInSynNo	MBody_delayedSyn_project/model/classol_sim.h,
NNmodel, 79	109
synapselni	MBody_individualID_project/model/classol_sim.h,
NNmodel, 79	110
synapseName	MBody_userdef_project/model/classol_sim.h, 111
NNmodel, 79	OneComp_sim.h, 177
synapseOutSynNo	PoissonIzh_sim.h, 181
NNmodel, 79	Schmuker2014_classifier, 101
synapsePSize	VClampGA.h, 220
Izh_sparse.cc, 146	T_REPORT_TME
synapsePara	Izh_sparse_sim.h, 147
NNmodel, 79	MBody1_project/model/classol_sim.h, 107
synapseSource	MBody_delayedSyn_project/model/classol_sim.h,
NNmodel, 80	108
synapseSpkEvntVars	MBody_individualID_project/model/classol_sim.h,
NNmodel, 80	109
synapseTarget	MBody_userdef_project/model/classol_sim.h, 111
NNmodel, 80	OneComp_sim.h, 177
synapseType	PoissonIzh_sim.h, 181
NNmodel, 80	TESTPREVARSINPOSTLEARN_SPARSE_CU
synapseUsesPostLearning	testPostVarsInPostLearn_sparse.cu, 205
NNmodel, 80	testPreVarsInPostLearn_sparse.cu, 211
synapseUsesSpikeEvents	TESTPREVARSINSIMCODE_CU
NNmodel, 80	testPostVarsInPostLearn.cu, 204
synapseUsesTrueSpikes	testPostVarsInSimCode.cu, 206
	testPostVarsInSimCode_sparse.cu, 207
NNmodel, 80	testPreVarsInPostLearn.cu, 210
synapses_ini	testPreVarsInSimCode.cu, 212
postVarsInPostLearn.cc, 182	testPreVarsInSimCode_sparse.cu, 213
postVarsInPostLearn_sparse.cc, 183	TESTPREVARSINSYNAPSEDYNAMICS_CU
postVarsInSimCode.cc, 184	testPostVarsInSynapseDynamics.cu, 208
postVarsInSimCode_sparse.cc, 185	testPreVarsInSynapseDynamics.cu, 214
postVarsInSynapseDynamics.cc, 186	TESTPREVARSINSYNAPSEDYNAMICS_SPARSE_
postVarsInSynapseDynamics_sparse.cc, 187	CU
preVarsInPostLearn.cc, 189	testPostVarsInSynapseDynamics_sparse.cu, 209
preVarsInPostLearn_sparse.cc, 190	testPreVarsInSynapseDynamics_sparse.cu, 215
preVarsInSimCode.cc, 191	TIMING
preVarsInSimCode_sparse.cc, 192	MBody_userdef.cc, 165
preVarsInSynapseDynamics.cc, 193	TOTAL_RECORDINGS
preVarsInSynapseDynamics_sparse.cc, 194	experiment.h, 115
synapses_p	TOTAL_TIME
postVarsInPostLearn.cc, 182	SynDelaySim.h, 203
postVarsInPostLearn_sparse.cc, 183	testPostVarsInPostLearn.h, 204
postVarsInSimCode.cc, 184	testPostVarsInPostLearn_sparse.h, 205
postVarsInSimCode_sparse.cc, 185	testPostVarsInSimCode.h, 206
postVarsInSynapseDynamics.cc, 186	testPostVarsInSimCode_sparse.h, 207
postVarsInSynapseDynamics_sparse.cc, 187	testPostVarsInSynapseDynamics.h, 208
preVarsInPostLearn.cc, 189	testPostVarsInSynapseDynamics_sparse.h, 209

testPreVarsInPostLearn.h, 210	REPORT_TIME, 206
testPreVarsInPostLearn_sparse.h, 211	TOTAL_TIME, 206
testPreVarsInSimCode.h, 212	testPostVarsInSimCode_sparse.cu, 207
testPreVarsInSimCode_sparse.h, 213	main, 207
testPreVarsInSynapseDynamics.h, 214	TESTPREVARSINSIMCODE_CU, 207
testPreVarsInSynapseDynamics_sparse.h, 215	testPostVarsInSimCode_sparse.h, 207
TOTAL_TME	DT, 207
Izh_sparse_sim.h, 147	REPORT_TIME, 207
MBody1_project/model/classol_sim.h, 107	TOTAL_TIME, 207
MBody_delayedSyn_project/model/classol_sim.h,	testPostVarsInSynapseDynamics.cu, 208
108	main, 208
MBody_individualID_project/model/classol_sim.h,	TESTPREVARSINSYNAPSEDYNAMICS_CU, 208
110	testPostVarsInSynapseDynamics.h, 208
MBody_userdef_project/model/classol_sim.h, 111	DT, 208
OneComp_sim.h, 177	REPORT_TIME, 208
PoissonIzh_sim.h, 181	TOTAL_TIME, 208
TOTALT	testPostVarsInSynapseDynamics_sparse.cu, 209
HHVClampParameters.h, 143	main, 209
TRAUBMILES	TESTPREVARSINSYNAPSEDYNAMICS_SPA↔
modelSpec.h, 174	RSE_CU, 209
TRAUBMILES_ALTERNATIVE	testPostVarsInSynapseDynamics_sparse.h, 209
modelSpec.h, 174	DT, 209
TRAUBMILES FAST	REPORT_TIME, 209
modelSpec.h, 174	TOTAL_TIME, 209
TRAUBMILES PSTEP	testPreVarsInPostLearn.cu, 210
modelSpec.h, 174	main, 210
TRAUBMILES_SAFE	TESTPREVARSINSIMCODE_CU, 210
modelSpec.h, 174	testPreVarsInPostLearn.h, 210
TRUE	DT, 210
modelSpec.h, 173	REPORT_TIME, 210
tS	TOTAL_TIME, 210
lzh_sparse_project/generate_run.cc, 128	testPreVarsInPostLearn_sparse.cu, 211
MBody1_project/generate_run.cc, 128	main, 211
MBody_delayedSyn_project/generate_run.cc, 129	TESTPREVARSINPOSTLEARN SPARSE CU,
MBody_individualID_project/generate_run.cc, 130	211
MBody_userdef_project/generate_run.cc, 131	testPreVarsInPostLearn_sparse.h, 211
toString.h, 216	DT, 211
testHelper.h, 203	REPORT TIME, 211
testPostVarsInPostLearn.cu, 204	TOTAL_TIME, 211
main, 204	testPreVarsInSimCode.cu, 212
TESTPREVARSINSIMCODE CU, 204	main, 212
testPostVarsInPostLearn.h, 204	TESTPREVARSINSIMCODE_CU, 212
DT, 204	testPreVarsInSimCode.h, 212
REPORT TIME, 204	DT, 212
TOTAL TIME, 204	REPORT_TIME, 212
testPostVarsInPostLearn_sparse.cu, 205	TOTAL_TIME, 212
main, 205	testPreVarsInSimCode_sparse.cu, 213
TESTPREVARSINPOSTLEARN SPARSE CU,	main, 213
205	TESTPREVARSINSIMCODE_CU, 213
testPostVarsInPostLearn_sparse.h, 205 DT, 205	testPreVarsInSimCode_sparse.h, 213 DT, 213
REPORT_TIME, 205	REPORT_TIME, 213
TOTAL_TIME, 205	TOTAL_TIME, 213
testPostVarsInSimCode.cu, 206	testPreVarsInSynapseDynamics.cu, 214
main, 206	main, 214
TESTPREVARSINSIMCODE_CU, 206	TESTPREVARSINSYNAPSEDYNAMICS_CU, 214
testPostVarsInSimCode.h, 206	testPreVarsInSynapseDynamics.h, 214
DT, 206	DT, 214

REPORT_TIME, 214 TOTAL_TIME, 214	Izh_sparse_project/generate_run.cc, 128 MBody1_project/generate_run.cc, 129
testPreVarsInSynapseDynamics sparse.cu, 215	MBody_delayedSyn_project/generate_run.cc, 130
main, 215	MBody_individualID_project/generate_run.cc, 130
TESTPREVARSINSYNAPSEDYNAMICS_SPA↔	MBody_userdef_project/generate_run.cc, 131
RSE_CU, 215	OneComp_project/generate_run.cc, 132
testPreVarsInSynapseDynamics_sparse.h, 215	PoissonIzh_project/generate_run.cc, 132
DT, 215	toString.h, 216
REPORT TIME, 215	toString.h, 215
- · · ·	_TOSTRING_H_, 216
TOTAL_TIME, 215	tS, 216
theDev	
global.h, 140	toString, 216
theRates	toUpper
classol, 59	lzh_sparse_project/generate_run.cc, 128
theSize	MBody1_project/generate_run.cc, 129
utils.h, 219	MBody_delayedSyn_project/generate_run.cc, 130
theW	MBody_individualID_project/generate_run.cc, 130
postVarsInPostLearn, 82	MBody_userdef_project/generate_run.cc, 131
postVarsInPostLearn_sparse, 83	truevar_init
postVarsInSimCode, 84	helper.h, 141
postVarsInSimCode_sparse, 84	truevar_initexpHH
postVarsInSynapseDynamics, 85	helper.h, 141
postVarsInSynapseDynamics_sparse, 86	
preVarsInPostLearn, 87	UINT
preVarsInPostLearn_sparse, 87	experiment.h, 115
preVarsInSimCode, 88	UIntSz
preVarsInSimCode_sparse, 89	global.h, 140
	uniqueRunId
preVarsInSynapseDynamics, 90	Schmuker2014_classifier, 101
preVarsInSynapseDynamics_sparse, 90	update_input_data_on_device
thresholdConditionCode	Schmuker2014_classifier, 99
neuronModel, 65	updateClusterSpikeCountAN
timer	Schmuker2014_classifier, 99
experiment.h, 115	updateIndividualSpikeCountPN
Izh_sparse_sim.h, 147	Schmuker2014_classifier, 99
MBody1_project/model/classol_sim.h, 108	updateWeights PN AN
MBody_delayedSyn_project/model/classol_sim.h,	Schmuker2014_classifier, 99
109	updateWeights_PN_AN_on_device
MBody_individualID_project/model/classol_sim.h,	Schmuker2014_classifier, 99
110	utils.h, 216
MBody_userdef_project/model/classol_sim.h, 111	_UTILS_H_, 218
OneComp_sim.h, 177	CHECK_CUDA_ERRORS, 218
PoissonIzh_sim.h, 181	gennError, 218
VClampGA.h, 220	nModels, 219
timestepsPerRecording	
Schmuker2014_classifier, 101	postSynModels, 219
timing	preparePostSynModels, 218
NNmodel, 80	prepareStandardModels, 218
tmpVarNames	prepareWeightUpdateModels, 218
neuronModel, 65	theSize, 219
tmpVarTypes	weightUpdateModels, 219
	writeHeader, 219
neuronModel, 65	V
toLower	V
lzh_sparse_project/generate_run.cc, 128	inputSpec, 63
MBody1_project/generate_run.cc, 129	VClampGA.cu, 219
MBody_delayedSyn_project/generate_run.cc, 129	main, 219
MBody_individualID_project/generate_run.cc, 130	VClampGA.h, 220
MBody_userdef_project/generate_run.cc, 131	iT, 220
toString	R, 220

RAND, 220	write_input_to_file
RG, 220	classIzh, 50
t, 220	neuronpop, 66
timer, 220	write_kcdnsyns
VR_DATA_FILENAME	classol, 58
experiment.h, 115	write_para
value	helper.h, 141
Parameter, 80	write_pnkcsyns
value substitutions	classol, 58, 59
stringutils.h, 199	write_pnlhisyns
var_init_fullrange	classol, 59
helper.h, 141	writeHeader
var_reinit	utils.h, 219
helper.h, 141	uno, 210
varNames	xorwow setup
	GeNNHelperKrnls.cu, 138
neuronModel, 65	der i i i i i i i i i i i i i i i i i i i
postSynModel, 81	
weightUpdateModel, 104	
varTypes	
neuronModel, 65	
postSynModel, 81	
weightUpdateModel, 105	
vectorContains	
experiment.cu, 113	
verbose	
CodeHelper, 60	
Vexp	
helper.h, 142	
vrData	
Schmuker2014_classifier, 101	
WEIGHT_DELTA_PN_AN	
experiment.h, 115	
WEIGHT RN PN	
experiment.h, 115	
WEIGHT_WTA_AN_AN	
experiment.h, 115	
WEIGHT_WTA_PN_PN	
experiment.h, 115	
weightUpdateModel, 103	
dpNames, 104	
dps, 104	
evntThreshold, 104	
extraGlobalSynapseKernelParameterTypes, 104	
extraGlobalSynapseKernelParameters, 104	
needPostSt, 104	
needPreSt, 104	
pNames, 104	
simCode, 104	
simCodeEvnt, 104	
simLearnPost, 104	
synapseDynamics, 104	
varNames, 104	
varTypes, 105	
weightUpdateModel, 104	
weightUpdateModels	
utils.h, 219	
winningClass	
Schmuker2014 classifier 101	