# Topic 14:

# **Interpolating Curves**

- Intro to curve interpolation & approximation
- Polynomial interpolation
- Bézier curves
- Cardinal splines

## Parametric Polynomial Curves

Recall a linear curve (line) is:

$$p(t) = a_1 t + a_0$$

A cubic curve is similarly:

$$\begin{aligned} x(t) &= a_0 t^2 - a_1 t^2 + a_1 t - a_2 \\ y(t) &= b_0 t^2 - b_0 t^2 + b_1 t - b_2 \\ x(t) &= a_0 t^2 - a_1 t^2 + a_1 t - a_2 \end{aligned}$$

...or 
$$p(t) = d_3t^3 + d_2t^2 + d_1t + d_0$$
, where  $d_i = [a_i, b_i, c_{ij}]^T$ 

Cubics are commonly used in graphics because curves of lower order commonly have too little flexibility (only planar, no curvature control), while curves of higher order are unnecessarily complex and make it easy to introduce undesired wiggles.

#### Hermite Basis Matrix

An example of constraints for a cubic Hermite for eg. are end points and end tangents. i.e.  $P_1$ , $R_1$  at t=0 and  $P_4$ , $R_4$  at t=1. Plugging these constraints into p(t) = TA we get.

$$\begin{array}{l} B \\ p(0) = P_1 = \left[ \ 0 \ 0 \ 0 \ 1 \ \right] A_h \\ p(1) = P_4 = \left[ \ 1 \ 1 \ 1 \ 1 \ \right] A_h \\ p'(0) = R_1 = \left[ \ 0 \ 0 \ 1 \ 0 \ \right] A_h \\ => G=BA, A=MG => M=B^{-1} \\ p'(1) = R_4 = \left[ \ 3 \ 2 \ 1 \ 0 \ \right] A_h \end{array}$$

### Interactive Design of Curves

Goal: Expand the capabilities of shapes beyond lines and conics, simple analytic functions and to allow design constraints.

#### Design Issues:

- Continuity (smoothness)
- · Control (local vs. global)
- · Interpolation vs. approximation of constraints
- · Other geometric properties

(planarity, tangent/curvature control)

• Efficient analytic representation

## Designing Polynomial Curves from constraints

p(t) = TA , where T is powers of t. for a cubic T=[t<sup>3</sup> t<sup>2</sup> t<sup>1</sup> 1].

Written with geometric constraints p(t) = TMG, where M is the **Basis matrix** of a design curve and G the specific design constraints.

An example of constraints for a cubic Hermite for eg. are end points and end tangents. i.e.  $P_1, R_1$  at t=0 and  $P_4, R_4$  at t=1. Plugging these constraints into p(t) = TA we get.

```
\begin{array}{l} p(0) = P_1 = [\; 0\; 0\; 0\; 1\; ]\; A_h \\ p(1) = P_4 = [\; 1\; 1\; 1\; 1\; ]\; A_h \\ p'(0) = R_1 = [\; 0\; 0\; 1\; 0\; ]\; A_h \end{array} \quad => \quad G=BA,\; A=MG => M=B^{-1} p'(1) = R_4 = [\; 3\; 2\; 1\; 0\; ]\; A_h \end{array}
```

#### Hermite Basis Matrix

 $\begin{bmatrix} 0 & 0 & 0 & 1 \end{bmatrix}^{-1} \\ \begin{bmatrix} 1 & 1 & 1 & 1 \end{bmatrix} \\ \begin{bmatrix} 0 & 0 & 1 & 0 \end{bmatrix} \\ \begin{bmatrix} 3 & 2 & 1 & 0 \end{bmatrix}$   $= M_{hermite}$   $\begin{bmatrix} 2 & -2 & 1 & 1 \\ [-3 & 3 & -2 & -1] \\ [0 & 0 & 1 & 0] \\ [1 & 0 & 0 & 0] \end{bmatrix}$ 

#### Bezier Basis Matrix

A cubic Bezier can be defined with four points where:  $P_1$ ,  $R_1$  at t=0 and  $P_4$ ,  $R_4$  at t=1 for a Hermite.  $R_1 = 3(P_2-P_1)$  and  $R_4 = 3(P_4-P_3)$ .

We can thus compute the Bezier Basis Matrix by finding the matrix that transforms  $[P_1 P_2 P_3 P_4]^T$  into  $[P_1 P_4 R_1 R_4]^T$  i.e.

B H=[1000] [0001] [-3 3 0 0] [00-33]

 $M_{bezier} = M_{hermite *} B_H$ 

#### **Bezier Basis Functions**

[-1 3-31]

[3-630]

[-3 3 0 0]

[1000]

The columns of the Basis Matrix form Basis Functions such that:  $p(t) = f_1(t)P_1 + f_2(t)P_2 + f_3(t)P_3 + f_4(t)P_4$ 

From the matrix:

$$f_i(t) = \binom{n}{i} * (1-t)^{(n-i)} * t^i$$

These are also called Bernstein polynomials.

## Geometric continuity at a joint of two curves

Geometric Continuity

G<sub>0</sub>: curves are joined

G<sub>1</sub>: first derivatives are proportional at the join point

The curve tangents thus have the same direction,

but not necessarily the same magnitude.

i.e.,  $C_1'(1) = (a,b,c)$  and  $C_2'(0) = (k*a, k*b, k*c)$ .

G2: first and second derivatives are proportional at join point Parametric Continuity

C<sub>0</sub>: curves are joined

C<sub>1</sub>: first derivatives equal

C<sub>2</sub>: first and second derivatives are equal

If t is taken to be time, the acceleration is continuous.

C<sub>n</sub>: nth derivatives are equal

#### **Bezier Basis Functions**

[-1 3-31]

[3-630]

[-3 3 0 0] [1000]

The columns of the Basis Matrix form Basis Functions such that:  $p(t) = f_1(t)P_1 + f_2(t)P_2 + f_3(t)P_3 + f_4(t)P_4$ 

From the matrix:

$$f_i(t) = \binom{n}{i} * (1-t)^{(n-i)} * t^i$$

These are also called Bernstein polynomials.

#### **Basis Functions**

Basis functions can be thought of as interpolating functions. Note: actual interpolation of any point only happens if its Basis function is 1 and all others are zero at some t.

Often Basis functions for design curves sum to 1 for all t. This gives the curve some nice properties like affine invariance and the convex hull property when the function are additionally non-negative.

#### Local vs. Global control

Changing a point on the Bezier changes the curve mostly near the point, but a little bit everywhere...

Precise local control can be handled by splines where the Basis functions of points symmetrically increase from 0 to a maximum value over a window and then decrease to 0.

The curve is strictly affected by the point over this parameter range or window.