We are now Refinitiv, formerly the Financial and Risk business of Thomson Reuters. We've set a bold course for the future – both ours and yours – and are introducing our new brand to the world.

As our brand migration will be gradual, you will see traces of our past through documentation, videos, and digital platforms.

Thank you for joining us on our brand journey.



# Transport API Java Edition V3.2

# DACS LOCK API DEVELOPERS GUIDE

**JAVA EDITION** 



#### © Thomson Reuters 2015 - 2018. All rights reserved.

Thomson Reuters, by publishing this document, does not guarantee that any information contained herein is and will remain accurate or that use of the information will ensure correct and faultless operation of the relevant service or equipment. Thomson Reuters, its agents and employees, shall not be held liable to or through any user for any loss or damage whatsoever resulting from reliance on the information contained herein.

This document contains information proprietary to Thomson Reuters and may not be reproduced, disclosed, or used in whole or part without the express written permission of Thomson Reuters.

Any Software, including but not limited to, the code, screen, structure, sequence, and organization thereof, and Documentation are protected by national copyright laws and international treaty provisions. This manual is subject to U.S. and other national export regulations.

Nothing in this document is intended, nor does it, alter the legal obligations, responsibilities or relationship between yourself and Thomson Reuters as set out in the contract existing between us.

# **Contents**

Chapter 1	Introduction	1
1.1	Product Description	1
1.2	IDN Versus Elektron	1
1.3	Audience	1
1.4	Organization of Manual	2
1.5	References	
1.6	Conventions	
1.6.1	Typographic	
1.6.2	Programming	
1.7	Glossary	
Chapter 2	DACS-Compliant Source Server Applications	5
2.1	Overview	
2.2	Establish Subservice Names	
2.3	Define Entitlement Codes	
2.4	Create and Write Locks	
2.5	Publish the Map	
2.6	Provide a Mechanism to Read the Map and Supply it to the DACS Station	
Chapter 3	DACS Lock API	8
3.1	DACS Lock Operation	
3.2	Forming a DACS Lock	
3.3	DACS Lock Contents	
3.4	Compression of DACS Locks	
3.5	Compounding DACS Locks	
3.6	Transport of DACS Locks	
3.7	Compound DACS Lock in Relation to Permissioning	
Chapter 4	DACS Lock API Components	
4.1	JDACSLock Methods	. 14
4.2	Supporting Objects	. 16
4.2.1	DacsLock Interface	. 16
4.2.2	DacsError Interface	. 16
4.3	Constant Definitions	. 17
4.3.1	DacsReturnCodes Definitions	. 17
4.3.2	DacsOperations Interface	. 17
Appendix A	Example Program	18

# **Chapter 1 Introduction**

# 1.1 Product Description

The goal of permissioning is to control access to data by users. Using an entitlement system such as DACS (Data Access Control System), permission profiles can be defined identifying what each user is allowed to access. DACS is the entitlement system for the Thomson Reuters Enterprise Platform (TREP). DACS permission checks take place in the Market Data Client application. In order to perform a permission check for an item, DACS must have 'requirements' information for the item and a profile for the user (a.k.a. content based permissioning).

DACS requirements information is organized as numeric expressions. Each subservice of a service, e.g. all the data from an exchange, is assigned a (series of) numeric entitlement codes (PEs). The numeric entitlement codes are transported with items as they move from source servers to Market Data Client applications on the TREP. In order to accommodate the most general case in which information from multiple sources is combined to form new items (such as in compound servers), the requirements information for an item is a Boolean expression containing these entitlement codes. For an item obtained directly from a source, this expression is usually a single term. When a compound server combines two items to form a new (compound) item, it must also combine the requirements information to form a new (compound) requirement.

The name of the subservice associated with an entitlement code is maintained in tables within the DACS database and operational permission checking subsystem. The table that relates the entitlement codes for a service to the subservice names for that service is called the map for the service.

Requirements are transported on TREP in protocol messages called locks. The DACS Lock API provides functions to manipulate locks in a manner such that the source application need not know any of the details of the encoding scheme or message structure. For a source server to be DACS compliant, based on content, it must publish locks for the items it publishes; i.e., the source server application must produce lock events. Any item published without a lock or with a null lock is available to everybody permissioned for that service, even those without subservice permissions.

If a source server introduces (new) data to TREP that originates outside the network on which the application is running, then the application developer is also responsible for providing the map information for the service.

In addition to source servers that publish new data directly from a vendor, there are also compound servers that gather market information from other sources, manipulate that information, and then re-publish it on TREP. These servers must read locks from the Transport API Java Edition to combine them before publishing compound items. Again, the DACS Lock API provides functions to assist with this process. Compound sources must also use a special form of user ID when connecting to the TREP network.

Note: Subject-based sources do not require locks.

## 1.2 IDN Versus Elektron

Thomson Reuters's new ultra-high speed network Elektron has replaced the older IDN network. All references herein are made to Elektron. However, for historical reasons in the DACS administrative screens, this network is still referred to as IDN. For this reason, the terms Elektron and IDN are interchangeable throughout this document.

# 1.3 Audience

This guide is intended for software programmers who wish to incorporate the DACS Locks into the development of their source applications.

# 1.4 Organization of Manual

The material presented in this guide is divided into the following sections:

CHAPTER	CONTENT / TOPIC
Chapter 1, Introduction	A description of this manual and its conventions.
Chapter 2, DACS-Compliant Source Server Applications	For subservice-level permissioning, a DACS-compliant source server must satisfy a series of requirements.
Chapter 3, DACS Lock API	Explains the data flow of a DACS Lock and its operations.
Chapter 4, DACS Lock API Components	Describes DACS Lock API components and their required properties.
Appendix A, Example Program	Lists an example program that was created using the DACS Lock API.

**Table 1: Manual Overview** 

#### 1.5 References

- Transport API C Edition Developers Guide
- DACS Lock API Reference Manual

#### 1.6 Conventions

# 1.6.1 Typographic

This manual observes the following typographic conventions:

- Java classes, methods, and types are shown in orange, Courier New font.
- Parameters, filenames, tools, utilities, and directories are shown in **Bold** font.
- Document titles and variable values are shown in *italics*.
- When initially introduced, concepts are shown in Bold, Italics.
- Longer code examples (one or more lines of code) are shown in Courier New font against an orange background. Code comments are shown in green font color. For example:

# 1.6.2 Programming

Transport API Java Edition Standard conventions were followed.

# 1.7 Glossary

TERM	DESCRIPTION
API	Application Programming Interface
Application	A program that accesses data from and/or publishes data to the system.
Compound Item	A data item prepared from data items retrieved from the system.
Concrete service	A set of real-time data items published by a source server. Each concrete service is identified on DACS by a unique name (known as a network).
Data Access Control System (DACS)	A tool that allows customers to automatically control who is permitted to use which sets of data in their TREP.
EDF	Elektron Data Feeds
EDF Direct	Elektron Data Feed Direct
EED	Elektron Edge Device, the access point for consuming data from Elektron.
Elektron	Thomson Reuters's open, global, ultra-high-speed network and hosting environment, which allows users to access and share various types of content.
EMA	Elektron Message API
Entitlement Code	If a vendor service is permissioned down to the subservice level, an entitlement code must be provided with each item. Based on mapping tables provided by the vendor, DACS uses this code to determine the information provider and/or vendor product associated with an item.
ETA	Elektron Transport API
Exchange	A commercial establishment at which or through which trading of financial instruments takes place. Exchanges are information providers.
Exchange Map Logic	The logic used to construct requirements when an item is supplied by more than one exchange. If OR logic is used, the user only needs permission to access one of the exchanges that supplies the item. If AND logic is used, the user must have permission to access all of the exchanges that supply the item.
Map Program	An application associated with a particular vendor service which requests permissioning data from the vendor host and then uses that data to construct various mapping tables required by DACS.
Mapping Tables	These tables are used by DACS to derive the requirement for an item. They map entitlement codes to vendor products and, if applicable, to information providers (exchanges and specialist services).
Network Service	See concrete service.
PE	Permissionable Entity. A number used to designate the permissioning basis of a data item on Elektron (or TREP). (Same as entitlement code.)
Permissioning	The control of access to and publication of data items by users.
Product	A subset of the data items delivered by an information vendor for which there is a single charge (based on vendor criteria).

**Table 2: Glossary and Acronyms** 

TERM	DESCRIPTION
Product Map Logic	The logic used to construct requirements when an item is supplied by more than one product. If OR logic is used, the user only needs permission to access one of the products that supplies the item. If AND logic is used, the user must have permission to access all of the products that supply the item.
Profile	Information, including a list of subservices, that is used during permission checking. There is a profile associated with each user.
RFA	Robust Foundation API
Service	This term is used in two ways by DACS in a market data system environment. See concrete service and vendor service.
Service ID	A unique numeric ID assigned to each network service. On a TREP network, all valid service IDs for a particular system are listed in the global configuration file rmds.cnf.
Source	An application or server capable of supplying or transmitting information.
Source Server	An application program which provides a concrete service. More than one source server can provide the same concrete service.
Specialist Data Service	A set of data items provided by a third party (i.e. not from an exchange and not from the vendor delivering the data items to the site).
Subservice	A named set of items delivered by a vendor which are authorized as a group; e.g. all instruments traded on NYSE or all items that make up the product Securities 2000.
Subservice Type	There are three types of subservices:  Products Exchanges Specialist Service
TREP	Thomson Reuters Enterprise Platform.
User	A person with a unique, system-wide name.
Vendor Service	A vendor may offer more than one type of data delivery service to a customer. For example, Thomson Reuters provides the Elektron service. Each vendor service is identified on DACS by a unique name.  Each vendor service is associated with one or more concrete services. For example the Elektron service may be published on the network by any combination of these concrete services: IDN Selectserver and Reuters Data Feed.

Table 2: Glossary and Acronyms (Continued)

# **Chapter 2 DACS-Compliant Source Server Applications**

# 2.1 Overview

To permission at the subservice level, the item's permissioning requirements must be available at locations other than just the source. For DACS to permission a source service below the service level, the source must:

- 1. Create locks containing permissioning information, and
- 2. Map entitlement codes in the locks to subservice names.

For subservice level permissioning, a DACS-compliant source server must:

- Establish Subservice Names
- Define Entitlement Codes
- Create and Write Locks
- Publish the Map
- Provide a Mechanism to Read the Map and Supply it to the DACS Station

# 2.2 Establish Subservice Names

If a source server provides a service that is subdivided into subservices, each subservice must have a symbolic name. For Elektron, symbolic names represent Thomson Reuters products, exchanges, or specialist data services, and are subsets of the service being provided by the vendor. An item might be in zero, one, or more subservices.

At the time a source publishes an item on the TREP, the source must associate with the item the identities of any subservices to which the item belongs. For example, an Elektron source might identify that an item belongs to the subset of items from the New York Stock Exchange and is part of the Equities 2000 product.

For users, the system administrator grants or denies access to items in the various subservices using symbolic names. The system administrator performing permissioning will not deal with arbitrary numeric encodings such as via PEs (Permissionable Entity).

# 2.3 Define Entitlement Codes

The second requirement is that an entitlement code (a number) must be associated with each subservice name. A subservice can have one or more associated entitlement codes. Whenever a source publishes an item, the source designates the subservice(s) to which the item belongs as a Boolean expression in entitlement codes. Entitlement codes are needed when combining permissioning information from multiple sources to permission compound items (i.e., made from more than one source).

The PE used for permissioning on IDN (FID 1, PROD PERM) is an example of an entitlement code.

The list of subservice names and associated entitlement codes is called the *map* for the source.

#### 2.4 **Create and Write Locks**

Whenever a source server opens a data stream, it must write a lock containing the item's entitlement code expression. The source server must use an existing Thomson Reuters API to publish permissionable data on the TREP.

One of the capabilities of such an API is to create the lock. The arguments to the API function include a list of entitlement codes and the Boolean operator (AND or OR), which indicates how to logically combine them. After the lock is created, it must be posted to the TREP.

A source application can post a revised lock at any time.

#### 2.5 Publish the Map

The source must publish, as data items, the map of its entitlement codes and subservice names (or use map\_generic to load a map through the use of a file). As an example, the map for the Elektron service is published as a series of RICs referred to as the Reuters Product Definition Pages.<sup>1</sup>

Within the map data there must be a readily available data item with a date-time stamp. The value of this date-time stamp must be the date and time at which the map was last changed. The objective is to permit the application that reads the map to read a single item and determine whether the remaining data has changed (and thus needs to be reread).

The map items (records or pages) must be available to a user and application that have no subservice permissions so that the map can be retrieved at a new site that does not yet have permissions distributed.

**Note:** For Elektron services, template files containing preliminary mapping information are provided with the DACS software so that subservice permissioning can be set up before the latest map is retrieved from the source. If a template file is not provided with a third-party source application, it is important to not require subservice permissioning so that the map can be retrieved from the source.

<sup>1.</sup> Refer to the Reuters Product Definition Pages User Guide to see how Thomson Reuters communicates permissioning information for its products.

# 2.6 Provide a Mechanism to Read the Map and Supply it to the DACS Station

To load map data, you can either use the Generic map collect program (**map\_generic**) or download the latest map. The DACS database must contain the source's map data so that:

- The DACS administrator can assign permissions to subservices for a service
- The DACS operational subsystem can perform permission checks

As mentioned previously, the source should publish this map. Additionally, the source application developer should provide a map collection program designed to:

- Request the map items from the source.
- Determine if there were any changes since the last map was received.
- Convert any revised information into a file that can be loaded into the DACS database.

The source application developer may also want to provide a map monitor program that can run periodically to retrieve the latest map and see if any changes have occurred since the last map collection (by checking the date-time stamp). Based on the status reported by the monitor program, the administrator knows when the map collection program needs to be run.

DACS does not care about the format of the map published by the source as long as the map collection program for that source produces an appropriately formatted permission map file.

For further details on the map collect and proper permission map file formatting, refer to the DACS the DACS Lock API Reference Manual specific to the version of DACS that you run.



**Tip:** The DACS software package comes with a map collection program for the Elektron service.

# Chapter 3 DACS Lock API

# 3.1 DACS Lock Operation

The DACS Lock contains requirements for an item that a vendor source deems necessary. On the Market Data Client LAN, users are entitled to specific capabilities. Therefore, when a Lock, which contains requirements, is tested against the capabilities of the user, enough information is available to permission the following:

PERMISSIONING OPERATION
USER -> APPLICATION
USER -> SERVICE
USER -> SUB-SERVICE (entitlement codes)

**Table 3: DACS Permissioning Capabilities** 

DACS Locks are critical to the operation of the DACS system for content-based sources. Subject-based sources do not require locks. The DACS Lock contains the requirements for the requested item. The data flow of a DACS Lock and its operation are depicted in the remaining sections of this chapter.

# 3.2 Forming a DACS Lock

The source server is responsible for creating a DACS Lock. What information is encoded within the DACS Lock is vendor-specific. Two examples are presented to clarify the formation of DACS Locks with respect to a source server. Figure 1 demonstrates the input requirements, the DACS Lock API to be called, and the transport mechanism of the DACS Lock from the source server to the market data client application.




Figure 1. Forming a DACS Lock for EDF

Figure 1 presents the following information:

- The DACS Station (via use of its map collect utility) is responsible for retrieving Exchange, Product, and Subservice mappings. For dynamic mapping, the Elektron server must retrieve mapping tables from the datafeed line.
- It is up to the Elektron server if it retrieves all the mapping tables based on the customer site requirements and on the capabilities of the server's datafeed line.
- The DACS Lock API function that makes the DACS Lock receives the item's list of entitlement codes. For most Items, this is a single PE. However, other items (e.g., a NEWS2000 Item) can have PE lists that include up to 256 entitlement codes. For this reason, the DACS Lock API function might include an operator (AND/OR) with its PE list. Thus, in the case of a NEWS2000 item, the PE list is assigned an OR operator, while other PE lists might include the AND operator.
- The DACS Lock must be sent before the image so that the Market Data Client application (via the Transport API) can permission the item as soon as the image arrives, instead of having to hold the image and wait for the Lock.

## 3.3 DACS Lock Contents

A DACS Lock must contain information relevant to the requirements for the requested item. Because a DACS Lock needs to minimize communication costs, a source server encodes these requirements into a single numeric number. In Figure 1, you can see that the source server creates a table that maps these textual requirements to associated numeric values. By supplying an operator to the DACS Lock API function that creates DACS Locks, complex requirements can be managed by the source server. Thus an item's requirements are determined by comparing its PE to the mapping tables.

Figure 1 illustrates the following requirements in the source server mapping tables:

PE	REQUIREMENTS
456	NYSE & Money 2000 & (NY   LONDON)
985	LSE & (Energy 2000   Money 2000) & NY
1027	NWEX & (Energy 2000   Markets 2000) & LONDON

**Table 4: Item Requirement Formulations** 

A source server can add requirements to the DACS Lock for an item by including extra entitlement codes in the PE list assigned to the appropriate DACS Lock API class. For example, if a Source Server specifies that only a **Page\_Call** application can use an item, then the source server creates a new PE with that requirement and attaches it to the PE for that item using the AND operator.

PE	REQUIREMENTS
5000	Page_Call

Table 5: PE Example that can Add Extra Requirements to an Item

So if an Item has a **PE = 456**, and the Source Server requires only **Page\_Call** access, then the Source Server passes entitlement codes **456** and **5000** as parameters to the appropriate DACS Lock API function that builds the DACS Locks from the PE lists.

# 3.4 Compression of DACS Locks

To minimize physical size, DACS Locks are compressed based on the Binary Coded Decimal (BCD) algorithm. For example, the DACS Lock API must make a lock with the following PE requirements:

ELEKTRON (IDN)	BRIDGE
1027 & (456   985) & 5000	1 & 2

Table 6: PE Requirements for a Compound Item

The BCD compression algorithm converts numeric PE values and interprets operator functions according to the following table:

OPERATION	REPLACED NIBBLE VALUE
numeric 0 – 9	0 - 9
"&" and operation	A
" " or operation	В
"EOF" End of DACS Lock	С
"EOS" End of Source Server PE List	D

**Table 7: Operator and BCD Interpretation Table** 




Figure 2. DACS Lock Array after Compression

By using the compression mapping in Table 7, the DACS Lock API creates the unsigned character array in Figure 2, which illustrates some of the advantages to using this compression:

- The compression does not limit the maximum value of a PE, other than a possible machine maximum that can be manipulated easily with the software language (i.e., (2<sup>32</sup>)-1 for an unsigned long).
- BCD compression is simple and fast without resulting in excessive computation.
- The compressed DACS Lock is smaller then the actual ASCII string if it were sent.

# 3.5 Compounding DACS Locks

The previous example, in Figure 2, had two source server PE lists within the DACS Lock. This situation is possible when a compound server combines items from more than one source server type. To create a compound DACS Lock, the compound server calls the DACS Lock API function that, when given the constituent item DACS Locks, creates a DACS Locks that contains all of the constituent item requirements. To minimize the size of a DACS Lock, the DACS Lock API uses Boolean algebra rules to minimize entitlement codes within the PE list whenever possible.

Some rules are:

```
(A | B) & A = A

A & A & B = A & B

A | A | B = A | B
```

A compound server stores all constituent item DACS Locks until the item is no longer required. This functionality is required in the event a new DACS Lock is received by the compound server for an open item, in which case the compound server must update the compound item's DACS Lock. After updating a DACS Lock, the compound server must forward its new compound item DACS Lock to those servers that have the compound item open.

# 3.6 Transport of DACS Locks

DACS Locks for compound servers might grow larger then the maximum size of a single message, in which case the server splits the DACS Lock across multiple messages.

# 3.7 Compound DACS Lock in Relation to Permissioning

The previous sections explain the rules for constructing and transporting the DACS Locks. Figure 3 shows the data flow functionality of a DACS Lock in an operating environment with two source servers (Bridge and EDF), a compound server, and a Market Data client application. In this example the Market Data client application requests an item from the compound server. The item is made from constituent items from the EDF and Bridge Servers.




Figure 3. Compound Locks

# **Chapter 4 DACS Lock API Components**

# 4.1 JDACSLock Methods

The JDacsLock interface allows the application to obtain lock data created by specific parameters or to obtain a combined lock. The table below summarizes the methods provided by the JDacsLock interface.

METHOD	DESCRIPTION
createJDacsLock	This static method returns an instance of the JDacsLock that provides all the methods in this table.
createLock	This static method returns an instance of DacsLock.
createDacsError	This static method returns an instance of DacsError.
createLock	<ul> <li>This method generates a new lock from the following:</li> <li>serviceld: identifies the serviceld with which the lock is associated.</li> <li>operation: a character, that defines a valid operation. Refer to DacsOperation for a definition of operations.</li> <li>ProductEntityList is a sorted array of product entities. The productEntityListLength is set by the application to identify how many array elements apply. Note that the actual array length might be greater than the productEntityListLength. The application can reuse this array when creating several locks to avoid garbage collection.</li> <li>The lock instance is owned by an application and obtained via the createLock() method and the application should allocate the data buffer. The createLock() method will populate lock data into the buffer. If the buffer is too small, a return value and errorId will indicate this. The data (ByteBuffer) will have its position set to the start of lock bytes and is limited by the end of the lock.</li> <li>This method takes a DacsError object and populates the errorId and text an error occurs. An error instance is own by an application, and obtained via the createError() method.</li> </ul>
	A return value will indicate whether the operation was successful. For a list of DACS return codes, refer to Section 4.3.1.
calculateLockLength	This method calculates the length of a lock from the following information: serviceld, operation, and productEntityList (refer to the createLock method for descriptions of these parameters). These parameters are the same parameters from the createLock method, with the exception of DacsLock, as it does not populate the lock. The application can use this method prior to createLock() to find the length of the lock data and thus determine the ideal size of the DacsLock.data() buffer.

**Table 8: JDacsLock Interface** 

METHOD	DESCRIPTION
combineLock	This method generates a new lock from the LockList. LockList in an array of Locks. The lockListLength is set by application to identify how many array elements apply. Note that the actual array length can be greater than the lockListLength. The application may reuse this array when creating several locks to avoid garbage collection.
	The lock instance is owned by the application and obtained via the <pre>createLock()</pre> method. The application should allocate the data buffer.
	This method populates lock data into this buffer. If the buffer is too small, a return value and <pre>errorId</pre> will indicate this. The data (ByteBuffer) will have its position set to the start of the lock bytes and limited by the end of lock.
	If error conditions happen, the method populates a <code>DacsError</code> object with an <code>errorId</code> and associated text. The error instance is owned by the application, and obtained via the <code>createError()</code> method. A return value will indicate whether the operation was successfully. For a list of DACS return codes, refer to Section 4.3.1.
calculateCombineLockLength	This method calculates the length of a new lock generated from the LockList. The parameters are identical to the parameters of the combineLock method, with the exception of DacsLock, as it does not populate the lock. An application can use this method prior to combineLock() to determine the length of lock data and thus the ideal size of the DacsLock.data() buffer.
equals	A static utility method that compares two <b>ByteBuffer</b> s for equality.  The method returns <b>true</b> if the length of buffers (from position to limit) is equal and the data is identical. This method is useful when comparing two locks.

Table 8: JDacsLock Interface (Continued)

# 4.2 Supporting Objects

The JDacsLock interface utilizes the following interfaces:

- DacsLock Interface
- DacsError Interface

#### 4.2.1 DacsLock Interface

The DacsLock interface consists of the following methods:

METHOD	DESCRIPTION
data	Accessor methods that allow the application to set and get an instance of <b>ByteBuffer</b> associated with this object.
length	Returns the length of lock data.
startPosition	Returns the starting position of the lock data.
equals	Compares the lock data with the <b>DacsLock</b> parameter. If the data is equal, it returns true; false otherwise.
	In the event of an error, equals populates a DacsError object with an errorld and text as appropriate. The error instance is owned by the application and obtained via the createError() method.
	A return value will indicate whether the operation was successful. For a list of DACS return codes, refer to Section 4.3.1.
сору	Performs a deep copy of this DACS Lock into the <b>DacsLock</b> parameter.
	In the event of an error, copy takes a DacsError object and populates its errorld and text as appropriate. The error instance is owned by the application, and obtained via the createError() method.
	A return value will indicate whether the operation was successful. For a list of DACS return codes, refer to Section 4.3.1.

**Table 9: DacsLock Interface Methods** 

#### 4.2.2 DacsError Interface

The **DacsError** interface consists of the following methods:

	A DACS-specific return code, that specifies an error if it occurs.  For a list of DACS return codes, refer to Section 4.3.1.
text()	Returns text describing the error identified by the specific <b>errorld</b> .

**Table 10: DacsError Interface Methods** 

# 4.3 Constant Definitions

The JDacsLock interface uses constants defined in:

- DacsReturnCodes Definitions
- The DacsOperations Interface

#### 4.3.1 DacsReturnCodes Definitions

The DacsReturnCodes class uses the following return codes:

ERROR	DESCRIPTION
NO_ERROR	The operation was successful.
FAULT	An unexpected fault occurred.
BAD_OPERATOR	The operator parameter is out of range.
NO_LOCKS	A locks parameter was not supplied.
INVALID_LOCK	An invalid lock parameter is supplied.
INVALID_ARGUMENT	A null argument was supplied.
V4_COMBINE_NOT_ALLOWED	A lock list contained locks with different versions.
BUFFER_TOO_SMALL	The lock buffer is too small for lock data.

**Table 11: DacsReturnCodes Definitions** 

# 4.3.2 DacsOperations Interface

The DacsOperations interface uses the following operations:

OPERATION	DESCRIPTION
AND_OPERATION	The type of 'AND' operator.
OR_OPERATION	The type of 'OR' operator.

**Table 12: DacsOperations Operations** 

# **Appendix A** Example Program

The following is some example code created using the DACS Lock API:

```
package com.thomsonreuters.upa.examples.authlock;
import java.nio.ByteBuffer;
public class authLock
    JDacsLock _dacsInterface = JDacsLock.createJDacsLock();
    DacsError _error = JDacsLock.createDacsError();
    ByteBufferPool _pool = new ByteBufferPool();
    public static void main(String[] args)
        AuthLockExample dacsExample = new AuthLockExample();
        dacsExample.authLock();
        System.exit(0);
    public void authLock()
        // calculate lock length
        \//\ set the input parameters: serviceId, operation, productEntityList
        int serviceId = 5000;
        char operation = DacsOperations.OR_OPERATION;
        long[] productEntityList = new long[256];
        int productEntityListLength = 1;
        productCodeList[0] = 62;
        // calculate the length of the new lock
        int len = _dacsInterface.calculateLockLength(serviceId, operation, productEntityList,
                productEntityListLength, _error);
        if (len >= 0)
            System.err.println("calculateLockLength() Success, length = " + len);
        else
            System.err.println("calculateLockLength() failed " + _error.errorId() + _error.text());
        // create lock
        // create the lock object
        DacsLock lock1 = JDacsLock.createLock();
```

```
// use the calculated lock data length to get the ByteBuffer from pool
ByteBuffer lockData = _pool.getBuffer(len);
// populate the lock data
int ret = _dacsInterface.createLock(serviceId, operation, productEntityList,
       productEntityListLength, lock1, _error);
if (ret == DacsReturnCodes.NO_ERROR)
    System.out.println("createLock() - Success");
else
    System.err.println("createLock() failed " + _error.errorId() + _error.text());
// calculate length of combined lock
// assume lock2, lock3 have been created
DacsLock [] lockList = new DacsLock[100];
int lockListLength = 3;
lockList[0] = lock1;
lockList[1] = lock2;
lockList[2] = lock3;
// get the length of combined lock
len = _dacsInterface.calculateCombineLockLength(lockList, lockListLength, _error);
if (len >= 0)
    System.err.println("calculateCombineLockLength() Success, length = " + len);
}
else
{
    System.err.println("calculateCombineLockLength() failed " + _error.errorId() +
           _error.text());
}
// populate the combined lock
DacsLock combinedLock = JDacsLock.createLock();
combinedLock.data(_pool.getBuffer(len));
ret = _dacsInterface.combineLock(combinedLock, lockList, lockListLength, _error);
if (ret > 0)
   System.err.println("combineLock() Success");
}
else
    System.err.println("combineLock() failed " + _error.errorId() + _error.text());
// compare the locks using method on DacsLock
```

 $\hfill \odot$  2015 - 2018 Thomson Reuters. All rights reserved.

Republication or redistribution of Thomson Reuters content, including by framing or similar means, is prohibited without the prior written consent of Thomson Reuters. 'Thomson Reuters' and the Thomson Reuters logo are registered trademarks and trademarks of Thomson Reuters and its affiliated companies.

Any third party names or marks are the trademarks or registered trademarks of the relevant third party.

Document ID: ETAJ320REDAC.180 Date of issue: 27 April 2018

