

PRELIMINARY

SIMPLY RICH

$\mathbf{Z}\mathbf{K}^{\mathsf{TM}}$

The Developer's Reference

Version 2.1.1

September 2006

Potix Corporation

Revision 20

Copyright © Potix Corporation. All rights reserved.
The material in this document is for information only and is subject to change without notice. While reasonable efforts have been made to assure its accuracy, Potix Corporation assumes no liability resulting from errors or omissions in this document for from the use of the information contained herein.
Potix Corporation may have patents, patent applications, copyright or other intellectual property rights covering the subject matter of this document. The furnishing of this document does not give you any license to these patents, copyrights or other ntellectual property.
Potix Corporation reserves the right to make changes in the product design without reservation and without notification to its users.
The Potix logo and ZK are trademarks of Potix Corporation.
All other product names are trademarks, registered trademarks, or trade names of their respective owners.

Table of Contents

1.	Introduction	10
2.	The ZK User Interface Markup Language	11
	Implicit Objects	11
	applicationScope - java.util.Map	11
	arg - java.util.Map	11
	componentScope - java.util.Map	11
	desktop - com.potix.zk.ui.Desktop	12
	desktopScope - java.util.Map	12
	each - java.lang.Object	12
	event - com.potix.zk.ui.event.Event or derived	12
	forEachStatus - com.potix.zk.ui.util.ForEachStatus	12
	page - com.potix.zk.ui.Page	13
	pageScope - java.util.Map	
	requestScope - java.util.Map	
	self - com.potix.zk.ui.Component	
	session - com.potix.zk.ui.Session	
	sessionScope - java.util.Map	
	spaceOwner - com.potix.zk.ui.IdSpace	
	spaceScope - java.util.Map	
	Processing Instructions	
	The component Directive	14
	The import Directive	
	The init Directive	
	The page Directive	
	The taglib Directive	
	The variable-resolver Directive	19
	ZK Elements	20
	The XML Namespace	20
	The attribute Element	20
	The custom-attributes Element	21
	The zk Element	22
	The zscript Element	23
	ZK Attributes	24
	The forEach Attribute	25
	The if Attribute	25
	The unless Attribute	25

	The use Attribute	. 25
3.	EL Expressions	.26
	Overview	26
	Using EL Expressions	. 26
	Variables	26
	Implicit Objects	26
	Literals	. 26
	Operators	26
	Functions	. 26
	Standard Implicit Objects that ZK supports	. 27
	applicationScope - java.util.Map	. 27
	cookie - java.util.Map	27
	header - java.util.Map	27
	headerValues - java.util.Map	27
	pageContext - javax.servlet.jsp.PageContext	27
	pageScope - java.util.Map	. 27
	param - java.util.Map	. 27
	paramValues - java.util.Map	. 28
	requestScope - java.util.Map	28
	sessionScope - java.util.Map	. 28
	ZK Implicit Objects	28
4.	The XUL Components	. 29
	Overview	29
	XulElement	
	Components	
	Audio	
	Box	
	Button	
	Caption	
	Checkbox	
	Column	
	Columns	
	Combobox	
	Comboitem	
	Datebox	
	Decimalbox	
	Div	

Grid	. 30
Groupbox	. 30
Hbox	. 30
Html	30
Iframe	. 30
Image	30
Include	. 31
Intbox	. 31
Label	. 31
Listbox	. 31
Listcell	31
Listfoot	. 31
Listfooter	. 31
Listhead	31
Listheader	. 31
Listitem	. 31
Menu	31
Menubar	. 31
Menuitem	32
Menupopup	. 32
Menuseparator	32
Popup	32
Popupset	
Radio	
Radiogroup	. 32
Row	. 32
Rows	. 32
Separator	32
Slider	
Space	
Splitter	. 33
Style	. 33
Tab	. 33
Tabbox	. 33
Tabpanel	
Tabpanels	. 33
Tabs	
Textbox	. 33
Timer	. 33
Toolbar	. 33

	Toobarbutton	33
	Tree	33
	Treecell	34
	Treechildren	34
	Treecol	34
	Treecols	. 34
	Treeitem	34
	Treerow	34
	Vbox	34
	Window	34
9	Supplemental Classes	. 34
	AbstractListModel	. 34
	Constraint	34
	Constrainted	34
	Fileupload	35
	ListModel	35
	ListitemRenderer	35
	Messagebox	35
	RendererCtrl	35
	SimpleContraint	35
	SimpleContraint.	
	SimpleListModel	
5. T	·	. 35
	SimpleListModel	. 35 .36
	SimpleListModel	. 35 .36 36
	SimpleListModel	.35 . 36 36
	SimpleListModel	.35 .36 36 36
C	SimpleListModel	.35 .36 36 36 36 37
C	SimpleListModel	.35 .36 36 36 37
C	SimpleListModel The XHTML Components Overview URL and encodeURL AbstractTag Raw Components A	.35 .36 36 36 37 .37
C	SimpleListModel The XHTML Components Overview. URL and encodeURL. AbstractTag. Raw. Components. A. Abbr.	. 35 .36 .36 .37 .37 .37
C	SimpleListModel. The XHTML Components. Overview. URL and encodeURL. AbstractTag. Raw. Components. A. Abbr. Acronym.	. 35 .36 .36 .37 .37 .37 .37
C	SimpleListModel	. 35 .36 .36 .36 .37 .37 .37 .37
C	SimpleListModel. The XHTML Components. Overview. URL and encodeURL. AbstractTag. Raw. Components. A. Abbr. Acronym.	. 35 .36 .36 .36 .37 .37 .37 .37 .37
C	SimpleListModel	. 35 .36 .36 .37 .37 .37 .37 .37 .37
C	SimpleListModel	. 35 .36 .36 .37 .37 .37 .37 .37 .37 .37
C	SimpleListModel	. 35 .36 .36 .37 .37 .37 .37 .37 .37 .38
C	SimpleListModel	. 35 .36 .36 .37 .37 .37 .37 .37 .37 .37 .38 .38

Button	. 38
Caption	38
Cite	38
Code	38
Collection	38
Colgroup	. 38
Dd	38
Del	39
Dfn	39
Dir	. 39
Div	39
DI	39
Dt	. 39
Em	. 39
Embed	39
Fieldset	39
Font	. 39
Form	. 39
H1	39
H2	40
H3	40
H4	40
Head	40
Hr	. 40
Html	40
I	40
Iframe	. 40
Img	40
Input	40
Ins	. 40
Isindex	40
Kbd	. 41
Label	. 41
Legend	41
Li	. 41
Link	41
Мар	41
Menu	41
Meta	41
Nohr	41

	Object	. 41
	Ol	. 41
	Optgroup	. 41
	Option	. 42
	P	42
	Pre	42
	Q	. 42
	S	. 42
	Sam	. 42
	Script	
	Select	42
	Small	
	Span	
	Strong	
	Style	
	Sub	
	Sup	
	Table	
	Tbody	
	Td	
	Text	
	Textarea	
	Tfoot	
	Th	
	Thead	
	Title	
	Tr	
	Tt	
	UI	
	Var	. 44
9	Supplement Classes	. 44
	Fileupload	. 44
	Messagebox	. 44
Apı	pendix A. WEB-INF/web.xml	. 45
7	ZK Loader	. 45
	The Initial Parameters	
-	ZK AU Engine	
-	7K Session Cleaner	45

2	ZK Filter	46
	The Initial Parameters	46
	How to Specify in web.xml	46
9	Sample of web.xml	47
Αpı	pendix B. WEB-INF/zk.xml	49
	Overview	
	The listener Element	
	The log Element	. 52
	The desktop-config Element	53
	The session-config Element	54
	The language-config Element	
	The system-config Element	55
	The el-config Element	
	The error-page Element	58

1. Introduction

Welcome to ZK, the simplest way to make Web applications rich.

The Developer's Reference fully describes properties and methods of components. For concepts, features, refer to the Developer's Guide. For installation, refer to the Quick Start Guide.

2. The ZK User Interface Markup Language

Implicit Objects

For scripts (aka., zsccript) and EL expressions embedded in a ZUML page, there are a set of implicit objects that enable developers to access components more efficiently.

applicationScope - java.util.Map

A map of custom attributes associated with the Web application. It is the same as the getAttributes method in the com.potix.zk.ui.WebApp interface.

A Web application is a WAR, and each Web application has an independent set of custom attributes. These attributes are used mainly to communicate among different desktops and sessions.

If the client is based on HTTP, such as a Web browser, this is the same map of attributes stored in <code>javax.servlet.ServletContext</code>. In other words, you could use it communicate with other servlets, such as JSF.

arg - java.util.Map

The the argument passed to the createComponents method in com.potix.zk.ui.Executions class. Ιt miaht be null, depending how createComponents is called.

It is the same as self.desktop.execution.arg.

```
params.put("name", "John");
Executions.createComponents("/my.zul", null, params);
```

Then, in my.zul,

```
<window title="${arg.name}">
...
```

Notice that arg is available only when creating the components for the included page, say my.zul. On the other hand, all events, including onCreate, are processed later. Thus, if you want to access arg in the onCreate's listener, use the getArg method of the com.potix.zk.ui.event.CreateEvent Class.

componentScope - java.util.Map

A map of custom attributes associated with the component. It is the same as the getAttributes method in the com.potix.zk.ui.Component interface.

desktop - com.potix.zk.ui.Desktop

The current desktop. It is the same as self.desktop.

```
desktop.getPage("main");
```

desktopScope - java.util.Map

A map of custom attributes associated with the desktop. It is the same as the getAttributes method in the com.potix.zk.ui.Desktop interface.

It is mainly used to communicate among pages in the same desktop.

each - java.lang.Object

The current item of the collection being iterated, when ZK evaluates an iterative element. An iterative element is an element with the forEach attribute.

```
<listbox width="100px">
  <listitem label="${each}" forEach="${contacts}"/>
  </listbox>
```

event - com.potix.zk.ui.event.Event or derived

The current event. Available for the event listener only.

```
<textbox onChanging="react(event.value)"/>
<combobox onChanging="autoComplete()"/>
<zscript>
void react(String value) {
...
}
void autoComplete() {
  String value = event.getValue();
...
}
</zscript>
```

forEachStatus - com.potix.zk.ui.util.ForEachStatus

The status of an iteration. ZK exposes the information relative to the iteration taking place when evaluating the iterative element.

page - com.potix.zk.ui.Page

The current page. It is the same as self.page.

pageScope - java.util.Map

A map of custom attributes associated with the current page. It is the same as the getAttributes method in the com.potix.zk.ui.Page interface.

requestScope - java.util.Map

A map of custom attributes associated with the current execution. It is the same as getAttributes method in the com.potix.zk.ui.Execution interface.

self - com.potix.zk.ui.Component

The component itself. In other words, it is the closest component, depicted as follows.

```
<listbox>
  <zscript>self.getItems();</zscript><!-- self is listbox -->
  stitem value="ab" label="${self.value}"/><!-- self is listitem -->
  <zscript>self.getSelectedIndex();</zscript><!-- self is listbox -->
</listbox>
```

session - com.potix.zk.ui.Session

The session. It is similar to javax.servlet.http.HttpSession¹.

sessionScope - java.util.Map

A map of custom attributes associated with the session. It is the same as the <code>getAttributes</code> method in the <code>com.potix.zk.ui.Session</code> interface.

If the client is based on HTTP, such as a Web browser, this is the same map of attributes stored in <code>javax.servlet.http.HttpSession</code>. In other words, you could use it communicate with other servlets, such as JSF.

spaceOwner - com.potix.zk.ui.IdSpace

The space owner of this component. It is the same as self.spaceOwner.

¹ ZK session actually encapsulates the HTTP session to make ZK applications independent of HTTP.

```
spaceScope - java.util.Map
```

A map of custom attributes associated with the ID space containing this component.

Processing Instructions

The XML processing instructions describe how to process the ZUML page. They will be processed first before processing XML elements.

The component Directive

```
<?component name="myName" macro-uri="/mypath/my.zul"
  [prop1="value1"] [prop2="value2"]... ?>
<?component name="myName" [class="myPackage.myClass"]
  [extend="true"] [mold-name="myMoldName"] [mold-uri="/myMoldUri"]
  [prop1="value1"] [prop2="value2"]... ?>
```

Defines a new component. There are two formats: by-macro and by-class.

The by-macro Format

```
<?component name="myName" macro-uri="/mypath/my.zul"
[prop1="value1"] [prop2="value2"]... ?>
```

You could define a new component based on a ZUML page. It is also called the *macro component*. In other words, once an instance of the new component is created, it creates child components based on the specified ZUML page (the macro-uri attribute).

In additions, you could specify the initial properties (such as prop1 in the above example), such that they are always passed to the macro component (thru the arg variable).

The by-class Format

```
<?component name="myName" [class="myPackage.myClass"]
  [extend="true"] [mold-name="myMoldName"] [mold-uri="/myMoldUri"]
  [prop1="value1"] [prop2="value2"]...?>
```

In addition to defining a component by a ZUML page (aka., a macro component), You could define a new component by implementing a class that implements the com.potix.zk.ui.Component interface. Then, use the by-class format to declare such kind of components for a page.

To define a new component, you have to specify at least the class attribute, which is used by ZK to instantiate a new instance of the component.

In addition to defining a new component, you can override properties of existent

components by specifying extend="true". In other words, if extend="true" is specified, the previous definition of the component (with the same name) is loaded as the default value and then override only properties that are specified in this directive.

For example, assume you want to use MyWindow instead of the default window, com.potix.zul.html.Window, for all windows defined in this ZUML page. Then, you can declare it as follows.

```
<?component name="window" extend="true" class="MyWindow"?>
...
<window>
...
</window>
```

It is equivalent to the following codes.

```
<window use="MyWindow">
...
</window>
```

In addition, you could specify the properties to initialize. For example, you want to use the style class called blue for all buttons used in this page, then you could:

```
<?component name="button" extend="true" sclass="blue"?>
```

Similarly, you could use the following definition to use OK as the default label for all buttons specified in this page.

```
<?component name="button" extend="true" label="OK"?>
```

Notice that the properties won't be applied if a component is created manually (by <code>zscript</code> or by Java codes). If you still want them to be applied with the initialial properties, you could invoke the <code>applyProperties</code> method as follows.

```
<zscript>
  Button btn = new Button();
  btn.applyProperties(); //apply the initial properties
</zscript>
```

class

[Optional]

Used to specify the class to instantiate an instance of such kind of components. Unlike other directives, the class can be defined with <code>zscript</code>.

extend

[Optional]

If specified with "true", the existent definition will be loaded to initialize the new component definition. In other words, it *extends* the existent definition instead of defining

a brand-new one.

macro-uri

[Required if the by-macro format is used]

Used with the by-macro format to specify the URI of the ZUML page, which is used as the template to create components.

mold-name

[Optional][Default: default]

Used with the by-class format to specify the mold name. If mold-name is specified, mold-uri must be specified, too.

mold-uri

[Optional]

Used with the by-class format to specify the mold URI. If mold-uri is specified but mold-name is not specified, the mold name is assumed as default.

name

[Required]

The component name. If an existent component is defined with the same name, the existent component is completely invisible in this page. If the by-class format is used, the attributes of the existent components are used to initialize the new components and then override with what are defined in this processing instruction.

The import Directive

```
<?import uri="..."?>
```

It imports the component definitions and initiators defined in another ZUML page. In other words, it imports the component and init directives from the specified page.

A typical use is that you put a set of component definitions in one ZUML page, and then import it in other ZUML pages, such that they share the same set of component definitions, additional to the system default.

```
<!-- special.zul: Common Definitions -->
<?init zscript="/WEB-INF/macros/special.zs"?>
<?component name="special" macro-uri="/WEB-INF/macros/special.zuml" class="Special"?>
<?component name="another" macro-uri="/WEB-INF/macros/another.zuml"?>
```

where the Special class is assumed to be defined in /WEB-INF/macros/special.zs.

Then, other ZUML pages can share the same set of component definitions as follows.

```
<?import uri="special.zul"?>
...
<special/><!-- you can use the component defined in special.zul -->
```

Notes

- Unlike other directives, the import directives must be at the topmost level, i.e., at the the same level as the root element.
- The imported component definitions in the imported page are also imported. For example, if A imports B and B imports C, then A imports both C and B component definitions. If there is a name conflict, A overrides B, while B overrides C.
- Once the component definitions is imported, it won't be changed until the page is change, no matter the imported page is changed or not.

uri

[Required]

The URI of a ZUML page which the component definitions will be imported from.

The init Directive

```
<?init class="..." [arg0="..."] [arg1="..."] [arg2="..."] [arg3="..."]?>
<?init zscript="..." [arg0="..."] [arg1="..."] [arg2="..."] [arg3="..."]?>
```

There are two formats. The first format is to specify a class that is used to do the application-specific initialization. The second format is to specify a <code>zscript</code> file to do the application-specific initialization.

The initialization takes place before the page is evaluated and attached to a desktop. Thus, the getDesktop, getId and getTitle method will return null, when initializing. To retrieve the current desktop, you could use the com.potix.zk.ui.Execution interface.

You could specify any number of the init directive. The specified class must implement the com.potix.zk.ui.util.Initator interface.

```
<?init class="MyInit1"?>
<?init class="MyInit2"?>
```

class

[Optional]

A class name that must implement the <code>com.potix.zk.ui.util.Initator</code> interface. Unlike the <code>init</code> directive, the class name cannot be the class that is defined in zscript codes.

An instance of the specified class is constructed and its doInit method is called in the

Page Initial phase (i.e., before the page is evaluated). The doFinally method is called after the page has been evaluated. The doCatch method is called if an exception occurs during the evaluation.

Thus, you could also use it for cleanup and error handling.

zscript

[Optional]

A script file that will be evaluated in the Page Initial phase.

arg0, arg1...

[Optional]

You could specify any number of arguments. It will be passed to the doInit method if the first format is used, or as the args variable if the second format is used. Note: the first argument is arg0, the second is arg1 and follows.

The page Directive

```
<?page [id="..."] [title="..."] [style="..."] [language="xul/html"]?>
```

It describes attributes of a page.

id

[Optional][Default: generated automatically]

Specifies the identifier of the page, such that we can retrieve it back. If an alphabetical identifier is assigned, it will be available to scripts (aka., zscript) and EL expressions embedded in ZUML pages.

```
<?page id="${param.id}"?>
```

title

[Optional][Default: none]

Specifies the page title that will be shown as the title of the browser.

It can be changed dynamically by calling the setTitle method in the com.potix.zk.ui.Page interface.

```
<?page title="${param.title}"?>
```

style

[Optional][Default: width:100%]

Specifies the CSS style used to render the page. If not specified, it depends on the mold. The default mold uses width:100% as the default value.

```
<?page style="width:100%;height:100%"?>
```

language

[Optional][Default: depending on the extension][xul/html | xhtml]

Specifies the language of this page.

Currently, it supports xul/html and xhtml.

The taglib Directive

```
<?tablib uri="/myURI" prefix="my"?>
```

This directive is used to load a taglib file, which defines a set of EL functions. The format of a taglib file is the same as that of JSP taglib files.

In the following example, we loads functions defined in <code>core.dsp.tld</code> and then use the function called 1.

```
<?taglib uri="/WEB-INF/tld/web/core.dsp.tld" prefix="c"?>
<window title="${c:l('my.title')}">
...
</window>
```

uri

[Required]

A URL of the taglib file. Unlike other URL and URI, it doesn't interpret \sim or * specially. And, the page and the taglib files it references must be in the same Web application.

prefix

[Required]

A prefix used to identify functions defined in this taglib file. The prefix could be any non-empty string.

The variable-resolver Directive

```
<?variable-resolver class="..."?>
```

Specifies the variable resolver that will be used by the <code>zscript</code> interpreter to resolve unknown variables. The specified class must implement the <code>com.potix.zk.ui.util.VariableResolver</code> interface.

You can specify multiple variable resolvers with multiple variable-resolver directives. The

later declared one has higher priority.

Notice that the variable-resolver directives are evaluated before the init directives, so the zscript codes referenced by the init directives are affected by the variable resolver.

The following is an example when using ZK with the Spring framework. It resolves Java Beans declared in the Spring framework, such that you access them directly.

```
<?variable-resolver class="com.potix.zkplus.spring.DelegatingVariableResolver"?>
```

class

[Optional]

A class name that must implement the <code>com.potix.zk.ui.util.VariableResolver</code> interface. Unlike the <code>init</code> directive, the class name cannot be the class that is defined in zscript codes.

ZK Elements

ZK elements are special XML elements that are used to control ZUML pages other than creating components.

The XML Namespace

If there is name conflicts, you could specify the XML name space:

```
http://www.potix.com/2005/zk
```

```
<zk:attribute xmlns:zk="http://www.potix.com/2005/zk">
...
```

The attribute Element

```
<attribute name="myName">myValue</attribute>
```

It defines a XML attribute of the enclosing element. The content of the element is the attribute value, while the <code>name</code> attribute specifies the attribute name. It is useful if the value of an attribute is sophisticated, or the attribute is conditional.

```
<button label="Hi">
   <attribute name="onClick">alert("Hi") </attribute>
</button>
```

It is equivalent to

```
<button label="Hi" onClick="alert(&quot;Hi&quot;)"/>
```

Another example:

```
<button>
<attribute name="label" if="${param.happy}">Hello World!</attribute>
</button>
```

name

[Required]

Specifies the attribute name.

if

[Optional][Default: true]

Specifies the condition to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to false.

unless

[Optional][Default: false]

Specifies the condition *not* to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to true.

The custom-attributes Element

```
<custom-attributes
  [scope="component|space|page|desktop|session|application]
  attr1="value1" [attr2="value2"...]/>
```

It defines a set of custom attributes of the specified scope. You could specify as many as attributes you want. These attributes can be retrieve by the getAttribute method of the Component interface with the specified scope.

```
<custom-attributes cd="${param.cd}" a.b="ab"/>
```

scope

[optional][Default: component]

Specifies the scope to which the custom attributes are associated. If not specified, the component enclosing this element is the default scope to use.

if

[Optional][Default: true]

Specifies the condition to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to false.

unless

```
[Optional][Default: false]
```

Specifies the condition *not* to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to true.

The zk Element

```
\langle zk \rangle \dots \langle /zk \rangle
```

It is a special element used to aggregate other components. Unlike a real component (say, hbox or div), it is not part of the component tree being created. In other words, it doesn't represent any component. For example,

is equivalent to

The main use is to represent multiple root elements in XML format.

The other use is to iterate over versatile components.

if

[Optional][Default: true]

Specifies the condition to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to false.

unless

```
[Optional][Default: false]
```

Specifies the condition *not* to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to true.

forEach

[Optional][Default: *ignored*]

It specifies a collection of objects, such that the zk element will be evaluated repeatedly against each object in the collection. If not specified or empty, this attribute is ignored. If non-collection object is specified, it is evaluated only once as if a single-element collection is specified.

The zscript Element

```
<zscript>Java codes</zscript>
<zscript src="uri"/>
```

It defines a piece of Java codes that will be interpreted when the page is evaluated. It has two formats as shown above. The first format is used to embed Java codes directly in the page. The second format is used to reference an external file that contains Java codes.

```
<zscript>
alert("Hi");
</zscript>
<zscript src="/codes/my.bs"/>
```

Like other ZK elements, it is not a component but a special XML element.

src

[Optional][Default: none]

Specifies the URI of the file containing Java codes. If specified, the Java codes will be loaded as if they are embedded directly.

Note: the file shall contain the Java source codes that can be interpreted by BeanShell. Don't specify a class file (aka. byte codes).

Like other URL and URI, it has several characteristics as follows.

- 1. It is relative to the servlet context path (aka., the <code>getContextPath</code> method from the <code>javax.servlet.http.HttpServletRequest</code> interface). In other words, ZK will prefix it with the servlet context automatically.
- 2. It resolves "~" to other Web application (aka., different ServletContext). Notice that Web server administrator might disable Web applications from peeking other's content².
- 3. It accepts "*" for loading browser and Locale dependent style sheet.

The algorithm to resolve "*" is as follows.

- If there is one "*" is specified in an URL or URI such as /my*.css, then "*" will be replaced with a proper Locale depending on the preferences of user's browser. For example, user's preferences is de_DE, then ZK searches /my_de_DE.css, /my_de.css, and /my.css one-by-one from your Web site, until any of them is found. If none of them is found, /my.css is still used.
- If two or more "*" are specified in an URL or URI such as "/my*/lang*.css", then the first "*" will be replaced with "ie" for Internet Explorer and "moz" for other browsers³.

 If the last "*" will be replaced with a proper Locale as described above.
- All other "*" are ignored.

if

[Optional][Default: true]

Specifies the condition to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to false.

unless

[Optional][Default: false]

Specifies the condition *not* to evaluate this element. This element is ignored if the value specified to this attribute is evaluated to true.

ZK Attributes

ZK attributes are used to control the associated element, other than initializing the data member.

² Refer to the getContext meth from the javax.servlet.ServletContext interface.

³ In the future editions, we will use different codes for browsers other than IE and FF.

The forEach Attribute

It specifies a collection of objects, such that the associated element will be evaluated repeatedly against each object in the collection. If not specified or empty, this attribute is ignored, and the element is evaluated only once. If non-collection object is specified, it is evaluated only once as if a single-element collection is specified.

For each iteration, two variables, each and forEachStatus, are assigned automatically to let developers control how to evaluate the associated element.

College	Graduate
College: Best	Better: A++
College: Better	Better: A+
	Better: A

The if Attribute

It specified the condition to evaluate the associated element. In other words, the associated element and all its child elements are ignored, if the condition is evaluated to false.

The unless Attribute

It specified the condition *not* to evaluate the associated element. In other words, the associated element and all its child elements are ignored, if the condition is evaluated to true.

The use Attribute

It specifies a class to create a component instead of the default one. In the following example, MyWindow is used instead of the default class, com.potix.zul.html.Window.

```
<window use="MyWindow"/>
```

3. EL Expressions

This chapter describes the details about applying EL expressions to ZUML pages.

Overview

EL expressions use the syntax \${expr}. For example,

```
<element attr1="${bean.property}".../>
${map[entry]}
<another-element>${3+counter} is ${empty map}</another-element>
```

When an EL expression is used as an attribute value, it could return any kind of objects as long as the component accepts it. For example, the following expression will be evaluated to a Boolean object.

```
<window if="${some > 10}">
```

Using EL Expressions

EL expressions can be used

- In static text
- In any attribute's value including XML elements and XML processing instructions.

Variables

Implicit Objects

Literals

Operators

Functions

Using Functions

Defining Functions

Standard Implicit Objects that ZK supports

Like using EL expressions in JSP pages, you could use most of standard implicit objects in ZUML pages.

applicationScope - java.util.Map

A map of application-scoped attributes (String, Object).

cookie - java.util.Map

A map of cookies of the request. (String, Cookie).

header - java.util.Map

A map of headers of the request. (String, String).

headerValues - java.util.Map

A map of headers of the request. (String, String[]).

pageContext - javax.servlet.jsp.PageContext

The page context.

pageScope - java.util.Map

A map of page-scoped attributes (String, Object).

Notice: the page concept is a bit different from JSP because a ZK page exists across requests.

param - java.util.Map

A map of parameters of the request (String, String).

```
paramValues - java.util.Map
```

A map of parameters of the request. (String, String[]).

```
requestScope - java.util.Map
```

A map of request-scoped attributes (String, Object).

```
sessionScope - java.util.Map
```

A map of session-scoped attributes (String, Object).

ZK Implicit Objects

All variables defined in ZK scripts (aka., zscript) are available for the EL expressions. Thus, all implicit objects described in the previous chapter are also the implicit objects for the EL expressions. You are free to use self, event, componentScope and others. Refer to the **Implict Objects** section in the **ZK User Interface Markup Language** chapter.

4. The XUL Components

Overview

- All XUL components are packed in the com.potix.zul.html package.
- The XML name space is http://www.potix.com/2005/zul
- The extensions include xul and zul.
- The component names are case-sensitive. They are all in lower-cases.

XulElement

All XHTML components are derived from the com.potix.zul.html.impl.XulElement class.

Com	nponents	
	Audio	
	Вох	
	Button	
	Caption	
	Checkbox	
	Column	

Columns			
Combobox			
Comboitem			
Datebox			
Decimalbox			
Div			
Grid			
Groupbox			
Hbox			
Html			
Iframe			
Image			

Include		
Intbox		
Label		
Listbox		
Listcell		
Listfoot		
Listfooter		
Listhead		
Listheader		
Listitem		
Menu		
Menubar		

Menuitem		
Menupopup		
Menuseparator		
Popup		
Popupset		
Radio		
Radiogroup		
Row		
Rows		
Separator		
Slider		
Space		

Splitter			
Style			
Tab			
Tabbox			
Tabpanel			
Tabpanels			
Tabs			
Textbox			
Timer			
Toolbar			
Toobarbutton			
Tree			

	Treecell
	Treechildren
	Treecol
	Treecols
	Treeitem
	Treerow
	Vbox
	Window
Sup	plemental Classes
	AbstractListModel
	Constraint
	Constrainted

Fileupload		
ListModel		
ListitemRenderer		
Messagebox		
RendererCtrl		
SimpleContraint		
SimpleListModel		

5. The XHTML Components

Overview

- All XHTML components are packed in the com.potix.zhtml package.
- The XML name space is http://www.w3.org/1999/xhtml
- The extensions include htm, html, xhtml and zhtml.
- The component names are case-insensitive. Developers could use any combination of lower or upper cases.

URL and encodeURL

A XHTML component generates attributes directly to native HTML tags. It means, unlike XUL, it doesn't prefix the servlet context path to attributes for specifying URL. For example, the following codes don't work (unless the servlet context is "").

```
<img href="/my/good.png"/>
```

Rather, you shall use the <code>encodeURL</code> function in EL expressions as follows.

```
<?taglib uri="/WEB-INF/tld/web/core.dsp.tld" prefix="p"?>
...
<img href="${p:encodeURL('/my/good.png')}"/>
```

In Java, you shall use the encodeURL method from com.potix.zk.ui.Execution.

Notice that XUL components and all ZK features that accept an URL will invoke the encodeURL method automatically⁴.

AbstractTag

All XHTML components are derived from the com.potix.zhtml.impl.AbstractTag class.

A XHTML component is a thin wrapper that encapsulates a native HTML tag. It is different from a XUL component or other none-native component in several ways.

• By implementing the com.potix.zk.ui.ext.RawId interface, the universal identifier (getUuid) is the same as the identifier (getId).

⁴ The reason not to handle XHTML compoents is that we don't know which attribute requires URL.

• By implementing the com.potix.zk.ui.ext.DynamicAttributes interface, all XHTML components support arbitrary attributes. In other words, any attribute name is legal (as long as the targeted browser supports).

Raw

A special component, <code>com.potix.zhtml.Raw</code>, used to represent any component that is not declared in the following section (i.e., not in lang.xml). In other words, if any unrecognized component name is found, an instance of <code>Raw</code> is created, such that a proper HTML tag will be generated correspondingly. In other words, any component name is legal (as long as the targeted browser supports).

<marquee align="top">...</marquee>

It is equivalent to

new Raw().setDynamicAttribute("align", "top");

Components

Α

Abbr

Acronym

Address

Area

В

Base		
Big		
Blockquote		
Body		
Br		
Button		
Caption		
Cite		
Code		
Collection		
Colgroup		
Dd		

Del			
Dfn			
Dir			
Div			
DI			
Dt			
Em			
Embed			
Fieldset			
Font			
Form			
H1			

H2		
Н3		
Н4		
Head		
Hr		
Html		
I		
Iframe		
Img		
Input		
Ins		
Isindex		

Kbd			
Label			
Legend			
Li			
Link			
Мар			
Menu			
Meta			
Nobr			
Object			
OI			
Optgroup			

Option			
P			
Pre			
Q			
S			
Sam			
Script			
Select			
Small			
Span			
Strong			
Style			

Sub			
Sup			
Table			
Tbody			
Td			
Text			
Textarea			
Tfoot			
Th			
Thead			
Title			
Tr			

Tt			
UI			
Var			

Supplement Classes

Fileupload

Messagebox

Appendix A. WEB-INF/web.xml

To add ZK a Web application, you have to add servlets, listeners and a optional filter to web.xml.

ZK Loader

[Required] Class: com.potix.zk.ui.http.DHtmlLayoutServlet

DHtmlLayoutServlet is a servlet used to load ZUML pages when the Web server receives URL requests sent by users.

It is suggested to map this servlet to the zul and zhtml extensions as shown in the **Sample** section below. It is OK if you want to map xul and html, too.

The Initial Parameters

init-param	Descriptions
update-uri	[Required]
	It specifies the URI which the ZK AU engine is mapped to.
	For example, if the ZK AU engine is mapped to /zkau/*, by use of servlet-mapping, then specify /zkau for this parameter.
	Note: if the servlet container is used with other Web server, like Apache, you have to map this update URI to the servlet container (in additions to zul and $zhtml$ files).

ZK AU Engine

[Required] Class: com.potix.zk.au.http.DHtmlUpdateServlet

DHtmlUpdateServlet is a servlet that handles AJAX requests asynchronously and automatically.

Notice that the URL pattern mapped to this engine must be consistent with the update-uri parameter of the ZK Loader.

ZK Session Cleaner

[Required] Class: com.potix.zk.ui.http.HttpSessionListener

ZK: Developer's Reference Page 45 of 58 Potix Corporation

HttpSessionListener is a listener used to clean up memory when a HTTP session is destroyed.

ZK Filter

[Optional] Class: com.potix.zk.ui.http.DHtmlLayoutFilter

DHtmlLayoutFilter is a filter to post-process the responses generated by other servlets. Its role is similar to the ZK Loader. Unlike the ZK Loader, which loads static ZUML pages from Web applications directly, the ZK filter is designed to process dynamic pages generated by other servlets, say JSP or JSF. It enables developers to add rich user interfaces to existent servlets written in any technology.

The Initial Parameters

init-param	Descriptions
extension	[Optional][Default: html]
	It specifies how to process the response generated by other servlets.
	If html or zhtml, XHTML is assumed to be the default namespace. If xul or zul, XUL is assumed to be the default namespace.
charset	[Optional][Default: UTF-8]
	It specifies the default charset for the output of this filter.
	If an empty string is specified as follows, the container's default is used. In other words, the setCharacterEncoding method of
	javax.servlet.ServletResponse is not called.
	<pre><param-value></param-value></pre>

How to Specify in web.xml

```
<filter>
    <filter-name>zkFilter</filter-name>
         <filter-class>com.potix.zk.ui.http.DHtmlLayoutFilter</filter-class>
</filter>
```

Sample of web.xml

```
<web-app version="2.4" xmlns="http://java.sun.com/xml/ns/j2ee"</pre>
xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"
xsi:schemaLocation="http://java.sun.com/xml/ns/j2ee
http://java.sun.com/xml/ns/j2ee/web-app 2 4.xsd">
  <!-- //// -->
  <!-- ZK -->
  stener>
      <description>Used to cleanup when a session is destroyed</description>
     <display-name>ZK Session Cleaner</display-name>
      <listener-class>com.potix.zk.ui.http.HttpSessionListener/listener-class>
  </listener>
  <servlet>
      <description>ZK loader for evaluating ZUML pages</description>
     <servlet-name>zkLoader</servlet-name>
     <servlet-class>com.potix.zk.ui.http.DHtmlLayoutServlet</servlet-class>
     <!-- Must. Specifies URI of the update engine (DHtmlUpdateServlet).
     It must be the same as <url-pattern> for the update engine.
     <init-param>
         <param-name>update-uri
         <param-value>/zkau</param-value>
      </init-param>
      <load-on-startup>1</load-on-startup><!-- MUST -->
  </servlet>
  <servlet-mapping>
      <servlet-name>zkLoader/servlet-name>
      <url-pattern>*.zul</url-pattern>
  </servlet-mapping>
  <servlet-mapping>
     <servlet-name>zkLoader</servlet-name>
      <url-pattern>*.zhtml</url-pattern>
  </servlet-mapping>
  <servlet>
      <description>The asynchronous update engine for ZK</description>
     <servlet-name>auEngine</servlet-name>
     <servlet-class>com.potix.zk.au.http.DHtmlUpdateServlet</servlet-class>
  </servlet>
  <servlet-mapping>
     <servlet-name>auEngine</servlet-name>
      <url-pattern>/zkau/*</url-pattern>
  </servlet-mapping>
  <!-- //// -->
  <!-- MIME mapping -->
  <mime-mapping>
      <extension>gif</extension>
      <mime-type>image/gif</mime-type>
```

```
</mime-mapping>
  <mime-mapping>
      <extension>html</extension>
      <mime-type>text/html</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>htm</extension>
      <mime-type>text/html</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>jpeg</extension>
      <mime-type>image/jpeg</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>jpg</extension>
      <mime-type>image/jpeg</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>js</extension>
      <mime-type>application/x-javascript</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>png</extension>
      <mime-type>image/png</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>txt</extension>
      <mime-type>text/plain</mime-type>
  </mime-mapping>
  <mime-mapping>
     <extension>xml</extension>
      <mime-type>text/xml</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>zhtml</extension>
      <mime-type>text/html</mime-type>
  </mime-mapping>
  <mime-mapping>
      <extension>zul</extension>
      <mime-type>text/html</mime-type>
  </mime-mapping>
  <welcome-file-list>
     <welcome-file>index.zul</welcome-file>
     <welcome-file>index.zhtml</welcome-file>
      <welcome-file>index.html</welcome-file>
      <welcome-file>index.htm</welcome-file>
  </welcome-file-list>
</web-app>
```

Appendix B. WEB-INF/zk.xml

WEB-INF/zk.xml is the configuration descriptor of ZK. This file optional. If you need to configure ZK differently from the default, you could provide a file called zk.xml under the WEB-INF directory.

Overview

The root element must be $\langle zk \rangle$. Then, you could specify any combination of the following element under the root element.

The listener Element

You could specify any number of listener elements. Each of them could have two child elements, description and listener-class, where description is optional.

```
<zk>
    <listener>
        <listener-class>my.MyInit</listener-class>
        </listener>
</zk>
```

The type of a listener depends on what interface it implements. For example, if a listener implements the <code>com.potix.zk.ui.event.EventThreadInit</code> interface, then it is used to listen when an event processing thread is initialized. A listener could implement multiple interfaces and it will be used whenever the corresponding interface is about to call.

The com.potix.zk.ui.event.EventThreadInit Interface

It is implemented by a listener class that will be used to initialize an event processing thread, before an event is dispatched to it for processing.

If a listener implements this interface, an instance is created, and then the prepare method is called in the main servlet (aka., the servlet thread). Then, the init method is called in the event processing thread.

If a developer wants to prevent an event from being processed, he can throw an exception in the prepare method. On the other hand, exceptions thrown by the init method are ignored (and only logged).

A typical use of this feature is to implement auto-authentication. For example, JBoss⁵ required you to call SecurityAssociation.setPrincipal to grant permissions of a user to the event processing thread, as described in the **Initialization Before Processing**

⁵ http://www.jboss.org

Each Event section, the **Event Listening and Processing** chapter.

The com.potix.zk.ui.event.EventThreadCleanup interface

It is implemented by a listener class that will be used to cleanup an event processing thread, after it has processed an event.

Exceptions thrown by the init method are ignored (and only logged).

A typical use of this feature is to clean up unclosed transaction.

Once registered, an instance is constructed and the cleanup method is called after leaving the event processing thread.

The com.potix.zk.ui.event.EventThreadSuspend interface

It is implemented by a listener class that will be called before an event processing thread is going to be suspended.

If a listener implements this interface, an instance is created, and then the beforeSuspend method, when an event processing thread is going to suspended. It happens in the event processing thread.

A developer can prevent can prevent an event processing thread from being suspended by throwing an exception.

A typical use of this feature is to limit the number of suspended threads.

The com.potix.zk.ui.event.EventThreadResume interface

It is implemented by a listener class that will be called after an event processing thread is resumed or aborted.

If a listener implements this interface, an instance is create, and then the afterResume method is called, after an event processing thread has been resumed, or aborted.

If an event processing thread is resumed, the afterResume method is called in the event processing thread (so it shares the same thread-local storage with EventThreadSuspend).

If an event processing thread is aborted (due to, say, cleaning up a desktop), the afterResume method is called in other thread (maybe another event processing thread, maybe a cleanup thread).

The com.potix.zk.ui.util.ApplicationInit interface

It is implemented by a listener class that will be used to initialize a ZK application.

When a ZK application is created, it invokes the init method of this interface such that developers could plug the application-specific codes to initialize the application.

The com.potix.zk.ui.util.ApplicationCleanup interface

It is implemented by a listener class that will be used to cleanup a ZK application that is being destroyed.

When a ZK application is going to be destroyed, it invokes the cleanup method of this interface such that developers could plug the application-specific codes to cleanup the application.

The com.potix.zk.ui.util.SessionInit interface

It is implemented by a listener class that will be used to initialize a new session.

When ZK Loader created a new session, it invokes the init method of this interface such that developers could plug the application-specific codes to initialize a session.

A developer can prevent a session from being created by throwing an exception in the init method.

The com.potix.zk.ui.util.SessionCleanup interface

It is implemented by a listener class that will be used to cleanup a session that is being destroyed.

When ZK Loader is going to destroy a session, it invokes the cleanup method of this interface such that developers could plug the application-specific codes to cleanup a session.

The com.potix.zk.ui.util.DesktopInit interface

It is implemented by a listener class that will be used to initialize a new desktop.

When ZK Loader created a new desktop, it invokes the init method of this interface such that developers could plug the application-specific codes to initialize a desktop.

A developer can prevent a desktop from being created by throwing an exception in the init method.

The com.potix.zk.ui.util.DesktopCleanup interface

It is implemented by a listener class that will be used to cleanup a desktop that is being destroyed.

When ZK Loader is going to destroy a desktop, it invokes the cleanup method of this interface such that developers could plug the application-specific codes to cleanup a desktop.

The com.potix.zk.ui.util.ExecutionInit interface

It is implemented by a listener class that will be used to initialize a new execution.

When ZK Loader and Update Engine created a new execution, it invokes the init method of this interface such that developers could plug the application-specific codes to initialize an execution.

Tip: Executions might be stacked. To know whether it is the first execution since a (Servlet) request is processed, you can check whether the parent argument is null.

A developer can prevent an execution from being created by throwing an exception in the init method.

The com.potix.zk.ui.util.ExecutionCleanup interface

It is implemented by a listener class that will be used to cleanup an execution that is being destroyed.

When ZK Loader is going to destroy an execution, it invokes the cleanup method of this interface such that developers could plug the application-specific codes to cleanup an execution.

The com.potix.zk.ui.util.Monitor interface

It is implemented by a listener class that will be used to monitor the statuses of ZK. Unlike other listener, there is at most one monitor listener for each Web application.

ZK provides an implementation named <code>com.potix.zk.ui.util.Statistic</code>, which accumulates the statistic data in the memory. It is a good starting point to understand the load of your ZK application.

The log Element

By default, ZK's logger depends on how the Web server is configured. However, you could configure ZK to load and monitor i3-log.conf as described in the **Logger** section of the **Beyond ZK** chapter.

```
<log>
     <log-base>com.potix</log-base>
</log>
```

If you want to use the same logging mechanism in your application, you could configure ZK to handle all loggers as follows.

```
<log>
     <log-base></log-base>
</log>
```

where an empty string means all packages, not just com.potix in the previous example.

The desktop-config Element

The allowed child elements include theme-uri, desktop-timeout and file-check-period. At most one desktop-config element is allowed for each zk.xml.

```
<desktop-config>
  <theme-uri>/my/blue**.css</theme-uri>
  <desktop-timeout>3600</desktop-timeout>
  <file-check-period>5</file-check-period>
</desktop-config>
```

The theme-uri Element

[Default: none]

It specifies the URI of an addition theme (aka., style sheets).

Like other URI, it accepts "*" for loading browser and Locale dependent style sheet. Refer to the **Browser and Locale Dependent URI** section in the **Internationalization** chapter for details.

Notice:

- 1. All style sheets defined in lang.xml and lang-addon.xml are loaded, no matter this parameter is defined or not. It is convenient for developers to override certain styles.
- 2. Each JAR could specify a lang-addon.xml file (under the metainfo/zk directory), so you could specify style sheets there if you have more than one style sheets.
- 3. You could specify extra CSS files for individual ZUML pages by use of the style component. Refer to the **ZUML with the XUL Component Set** chapter.

The desktop-timeout Element

[Default: 3600]

It specifies the time, in seconds, between client requests before a desktop is invalidated. A negative time indicates the session should never timeout.

The file-check-period Element

[Default: 5]

It specifies the time, in seconds, to wait before checking whether a file is modified.

For better performance, ZK has employed a cache to store parsed ZUML file. The time specified here controls how often ZK checks whether a file is modified. The larger the number the better the performance.

The session-config Element

The allowed child elements include session-timeout and max-desktops-per-session. At most one session-config element is allowed for each zk.xml.

```
<session-config>
  <timeout-uri>/my-timeout.zul</timeout-uri>
  <session-timeout>1800</session-timeout>
  <max-desktops-per-session>10</max-desktops-per-session>
</session-config>
```

The timeout-uri Element

[Default: *null*]

It specifies the target URI that will be used to redirect users to, when the desktop no longer exists – it is usually caused by session timeout. If this element is omitted, an error message will be shown up at the browser to alert users for what happens.

To reload the same URI again, you can specify an *empty* content as follows.

```
<session-timeout></session-timeout>
```

The session-timeout Element

[Default: depending on the Web server]

It specifies the time, in seconds, between client requests before a session is invalidated. A negative time indicates the session should never timeout.

The max-desktops-per-session Element

[Default: 10]

It specifies the maximal allowed number of desktops per session. A desktop represents a HTML page for a browser. In other words, this number controls the number of concurrent browser windows allowed per session.

The language-config Element

The allowed child elements include addon-uri. At most one language-config element is allowed for each zk.xml.

```
<language-config>
  <addon-uri>/WEB-INF/lang-addon.xml</addon-uri>
  <addon-uri>/WEB-INF/lang-addon2.xml</addon-uri>
```

</language-config>

The addon-uri Element

[Default: none]

It specifies the URI of language add-on definitions. To specify more than one URIs, you have to define them with multiple addon-uri.

A language addon is used to add new components and override the definitions of existent components. Refer to **the Component Development Guide**.

The system-config Element

The allowed child elements include max-event-threads. At most one system-config element is allowed for each zk.xml.

The max-event-threads Element

[Default: 100]

It specifies the maximal allowed number of event handling threads. ZK will reuse the event processing threads until it exceeds the number specified here.

The max-upload-size Element

[Default: 5120]

It specifies the maximal allowed size, in kilobytes, to upload a file from the client.

The response-charset Element

[Default: UTF-8]

It specifies the charset for the rendering result of a ZUML page. In other words, it is used to load the ZUML page by the ZK Loader (i.e., DHtmlLayoutServlet).

If you want to use the container's default value, you can specify an empty string as follows.

The locale-provider-class Element

[Default: null]

It specifies which class used to determine the locale for a given session. The class must have a default constructor (without any argument), and implement the com.potix.zk.ui.sys.LocaleProvider interface.

The timeZone-provider-class Element

[Default: null]

It specifies which class used to determine the time zone for a given session. The class must have a default constructor (without any argument), and implement the com.potix.zk.ui.sys.TimeZoneProvider interface.

The cache-provider-class Element

[Default: com.potix.zk.ui.impl.SessionDesktopCacheProvider]

It specifies which class used to implement the desktop cache. The class must have a default constructor (without any argument), and implement the com.potix.zk.ui.sys.DesktopCacheProvider interface.

One instance of the cache provider is created and shared for each Web application, so you have to synchronize the access properly.

Available implementations are as follows.

Class	Description
com.potix.zk.ui.impl. SessionDesktopCacheProvider	It stores all desktops from the same session in one single cache. It is simple and fast, but not supporting clustering.
com.potix.zk.ui.impl. GlobalDesktopCacheProvider	It stores all desktops from the same Web application in one single cache. In other words, it doesn't count on session at all.
	It is useful because some Web server, e.g, BEA WebLogic ⁶ , might be configured to use independent sessions for each request.

The ui-factory-class Element

[Default: com.potix.zk.ui.http.SimpleUiFactory]

6 http://www.bea.com

It specifies which class used to create desktops and pages, and to convert URL to a page definition. The class must have a default constructor (without any argument), and implement the <code>com.potix.zk.ui.sys.UiFactory</code> interface.

One instance of the UI factory is created and shared for each Web application, so you have to synchronize the access properly.

A common use is to load page definitions and other UI information from the database, rather than from the resources of the Web application.

In additions, you might use it to implement a controller in a MVC model, such that it creates the correct desktop based on the request URL.

Available implementations are as follows.

Class	Description
com.potix.zk.ui.http. SimpleUiFactory	The default UI factory. The sessions generated by this factory is <i>not</i> serializable
com.potix.zk.ui.http. SerializableUiFactory	The sessions generated by this factory is serializable. If you want to store sessions when the Web server is shutdown and restore them after it started, you can specify this implementation.

The engine-class Element

[Default: com.potix.zk.ui.impl.UiEngineImpl]

It specifies which class used to implement the UI Engine. The class must have a default constructor (without any argument), and implement the <code>com.potix.zk.ui.sys.UiEngine</code> interface.

One instance of the UI egnine is created and shared for each Web application, so you have to synchronize the access properly.

The el-config Element

The allowed child elements include evaluator-class. At most one el-config element is allowed for each zk.xml.

```
<el-config>
    <evaluator-class>my.MyExpressionEvaluatorImpl</evaluator-class>
</el-config>
```

The evaluator-class Element

[Default: org.apache.commons.el.ExpressionEvaluatorImpl]

It specifies the class used to evaluate EL expressions. If not specified, ZK uses the EL

implementation from the Apache group, org.apache.commons.el.ExpressionEvaluatorImpl. If your Web server uses another implementation, you have to specify a proper class here.

The error-page Element

```
<error-page>
  <exception-type>ClassName</exception-type>
  <location>the error page's URI</location>
</error-page>
```

It specifies an error page used when an un-caught exception is thrown in updating a ZUML page (e.g., in an event listener). Each page is associated with an exception type, aka, a class deriving from <code>java.lang.Throwable</code>. You can specify multiple error pages, each with a different exception type. When an error occurs, ZK searches the proper error page by examing the exception type one-by-one. If none is found, it shows, by default, an alert message at the client.

The error page's root element must be a window component. It becomes a modal dialog once shown up at the client.