fabric8io/fabric8-maven-plugin

Roland Huß

Version 3.1.1, 2016-08-04

fabric8-maven-plugin

1. Introduction	2
1.1. Building Images	2
1.2. Kubernetes and OpenShift Resources	2
1.3. Configuration	2
1.4. Examples	3
1.4.1. Zero-Config	4
1.4.2. XML Configuration	6
1.4.3. Resource Fragments	8
2. Installation	10
3. Goals	11
3.1. fabric8:resource	11
3.2. fabric8:build	11
3.2.1. Kubernetes Build	11
3.2.2. OpenShift Build	12
3.2.3. Configuration	13
3.2.4. Image Configuration	15
3.2.5. Build Configuration	16
3.2.6. Assembly	20
3.2.7. Environment and Labels	23
3.2.8. Startup Arguments	24
3.2.9. Build Args	25
3.3. fabric8:push	26
3.4. fabric8:deploy	26
3.5. fabric8:watch	26
4. Generators	30
4.1. Stock Generators	31
4.1.1. spring-boot	31
4.1.2. java-exec	31
4.1.3. karaf	31
4.2. Generator API	31
5. Enrichers	32
6. Profiles	33
7. Access configuration	34
7.1. Docker Access	34
7.2. OpenShift and Kubernetes Access	34
8. Registry handling	
9. Authentication	
9.1. Pull vs. Push Authentication	38

9.2. OpenShift Authentication	39
9.3. Password encryption	39

$\ensuremath{\text{@}}$ 2016 The original authors.



This document is work-in-progress. The most matures chaters are the Introduction and the description of the fabric8:build goal.

Chapter 1. Introduction

The **fabric8-maven-plugin** (f8-m-p) brings your Java applications on to Kubernetes and OpenShift. It provides a tight integration into Maven builds and benefits from the build information already provided. This plugin focus on two tasks: *Building Docker images* and *creating Kubernetes and OpenShift resource descriptors*. It can be configured very flexibly and supports multiple configuration models for creating: A *Zero-Config* setup allows for a quick ramp-up with some opinionated defaults. For more advanced requirementes an *XML configuration* provides additional configuration options which can be added to the pom.xml. For the full power in order to tune all facets of the creation external *resource fragments* and *Dockerfiles* can be used.

This introduction will explain how f8-m-p supports these tasks and demonstrates the different configuration models with examples.

1.1. Building Images

The **fabric8:build** goal is for creating Docker images which carry the actual application and which can be deployed on Kubernetes or OpenShift. It is easy to include build artifacts and their dependencies. The plugin uses the assembly descriptor format from the maven-assembly-plugin to specify the content which will be added to a sub-directory in the image (/deployments by default). Images that are built with this plugin can then be pushed to public or private Docker registries with **fabric8:push**.

Depending on the operational mode, for building the actual image either a Docker daemon is contacted directly or an OpenShift Docker Build is performed.

A special **fabric8:watch** goal allows for reacting on code changes and automatic recreation of images or copying new artifacts into running container.

These image related features are inherited from the fabric8io/docker-maven-plugin which is transparently included in this plugin.

1.2. Kubernetes and OpenShift Resources

With **fabric8:resource** Kubernetes and OpenShift resource descriptors can be created from the build information for creating the corresponding resource object. These files are packaged within the Maven artifacts created and can be deployed to a running orchestration platform with **fabric8:deploy**.

You only specify a fragment of the real resource descriptors which will be enriched by this plugin with various extra informations taken from the build. This drastically can reduce boilerplate code for common scenarios. It is also possible to auto-create resource objects like services or replica-set without explicitly declaring it.

1.3. Configuration

In order to capture many use case scenarios, there are three levels of configuration:

- **Zero-Config** mode makes some decisions based what is present in the pom.xml like what base image to use or which ports to expose. This is great for starting up things and for keeping quickstart applications small and tidy.
- XML plugin configuration mode is similar to what docker-maven-plugin provides. This allows for type safe configuration with IDE support, but only a subset of possible resource descriptor features is provided.
- **Kubernetes & OpenShift resource fragments** are user provided YAML files that can be *enriched* by the plugin. This allows expert users to use plain configuration file with all their capabilities, but also to add project specific build information and avoid boilerplate code.

The following table gives an overview of the different models.

Table 1. Configuration Models

Model	Docker Images	Resource Descriptors
Zero- Config	Generators are used to creatin Docker image configurations. Generators can detect certain aspects of the build (e.g. whether Spring Boot is used) and then choose some default like the base image, which ports to expose and the startup command. The can be configured, but offer only a few options.	Default Enrichers will create a default Service and Deployment (DeploymentConfig for OpenShift) when no other resource objects are provided. Depending on the image they can detect which port to expose in the service. As with Generators, Enrichers support a limited set of configuration options.
XML configur ation	f8-m-p inherits the XML based configuration for building images from the docker-maven-plugin and provides the same functionality. It supports an assembly descriptor for specifying the content of the Docker image.	A subset of possible resource objects can be configured with a dedicated XML syntax. With a decent IDE you get autocompletion on most object and inline documentation for the available configuration elements. The provide configuration can be still enhanced by Enhancers which is useful for adding e.g. labels and annotation containing build or other information.
Fragmen ts and	Like the docker-maven-plugin f8-m-p supports external Dockerfiles too, which are referenced from the plugin configuration.	Resource descriptors can be provied as external YAML files which specify a skeleton. This skeleton is then filled by Enrichers which add labels and more. Maven properties within these files are resolved to thier values. With this model you can use every Kubernetes / OpenShift resource object with all their flexibility, but still get the benefit of adding build informations.

1.4. Examples

Let's have a look at some code. The following examples will demonstrate all three configurations variants:

1.4.1. Zero-Config

This minimal but full working example pom.xml shows how a simple spring boot application can be dockerized and prepared for Kubernetes and OpenShift. The full example can be found in directory samples/zero-config.

```
< project>
 <modelVersion>4.0.0</modelVersion>
 <groupId>io.fabric8
 <artifactId>fabric8-maven-sample-zero-config</artifactId>
 <version>3.1.1
 <packaging>jar</packaging>
 <parent>
   <groupId>org.springframework.boot
   <artifactId>spring-boot-starter-parent</artifactId> ①
   <version>1.3.6.RELEASE
 </parent>
 <dependencies>
   <dependency>
     <groupId>org.springframework.boot
     <artifactId>spring-boot-starter-web</artifactId> ②
   </dependency>
 </dependencies>
 <build>
   <plugins>
     <plugin>
       <groupId>org.springframework.boot
       <artifactId>spring-boot-maven-plugin</artifactId> 3
     </plugin>
     <plugin>
       <groupId>io.fabric8
       <artifactId>fabric8-maven-plugin</artifactId> 4
       <version>3.1.1
     </plugin>
   </plugins>
 </build>
</project>
```

- ① This minimalistic spring boot application uses the spring-boot parent POM for setting up dependencies and plugins
- ② The Spring Boot web starter dependency enables a simple embedded Tomcat for serving Spring MVC apps
- ③ The spring-boot-maven-plugin is responsible for repackaging the application into a fat jar, including all dependencies and the embedded Tomcat

4 The fabric8-maven-plugin enables the automatic generation of a Docker image and Kubernetes / OpenShift descriptors including this Spring application.

This setup make some opinionated decisions for you:

- As base image fabric8/java-alpine-openjdk8-jdk is chosen which enables Jolokia and jmx_exporter. It also comes with a sophisticated startup script.
- It will create a Kubernetes Deployment and a Service as resource objects
- It exports port 8080 as the application service port (and 8778 and 9779 for Jolokia and jmx_exporter access, respectively)

These choices can be influenced by configuration options as decribed in Spring Boot Generator.

To start the Docker image build, you simply run

mvn package fabric8:build

This will create the Docker image against a running Docker daemon (which must be accessible either via Unix Socker or with the URL set in DOCKER_HOST). Alternatively, when using mvn-Dfabric8.mode=openshift package fabric8:build and connected to an OpenShift cluster, then a Docker build will be performed on OpenShift which at the end creates an ImageStream.

To deploy the resources to the cluster call

mvn fabric8:resource fabric8:deploy

By default a *Service* and a *Deployment* object pointing to the created Docker image is created. When running in OpenShift mode, a *Service* and *DeploymentConfig* which refers the *ImageStream* created with fabric8; build will be installed.

Of course you can bind all those fabric8-goals to execution phases as well, so that they are called along with standard lifecycle goals like install:

1.4.2. XML Configuration



XML based configuration is implemented only partially and not recommended to use right now.

Altough the Zero-config mode with its generators can be tweaked with options up to a certain degree. In many cases more flexibility and power is required, though. For this an XML based plugin configuration can be use, much similar to the XML configuration used by docker-maven-plugin.

The plugin configuration can be roughly divided into the following sections:

- A global configuration options are responsible for tuning the behaviour of plugin goals
- <images> section which defines the Docker images to build. It has the same syntax as the similar configuration of docker-maven-plugin (except that <run> and <external> sub-elements are ignored)
- <resource> is used to defined the resource descriptors for deploying on an OpenShift or Kuberneres cluster.
- <generator> is for configuring generators which are responsible for creating images. Generators are used as an alternative to a dedicates <images> section.
- <enricher> is used to configure various aspects of enrichers for creating or enhancing resource descriptors.

A working example can be found in the samples/xml-config directory. An extract of the plugin configuration is shown in the next example

Example for an XML configuration

```
<configuration>
```

```
<images> ①
  <image>
    <name>xml-config-demo:1.0.0
    <!-- "alias" is used to correlate to the containers in the pod spec -->
    <alias>camel-app</alias>
    <build>
      <from>fabric8/java
      <assembly>
        <basedir>/deployments</basedir>
        <descriptorRef>artifact-with-dependencies</descriptorRef>
      </assembly>
      <env>
        <JAVA_LIB_DIR>/deployments///
JAVA_LIB_DIR>
        <JAVA_MAIN_CLASS>org.apache.camel.cdi.Main</JAVA_MAIN_CLASS>
      </env>
    </build>
  </image>
</images>
<resources> ②
  <labels> ③
    <group>quickstarts</group>
  </labels>
  <deployment> 4
    <name>${project.artifactId}</name>
    <replicas>1</replicas>
    <containers> ⑤
      <container>
        <alias>camel-app</alias> ⑥
        <ports>
          <port>8778</port>
        </ports>
        <mounts>
          <scratch>/var/scratch</scratch>
        </mounts>
      </container>
    </containers>
    <volumes> ⑦
      <volume>
        <name>scratch</name>
        <type>emptyDir</type>
      </volume>
    </volumes>
  </deployment>
  <services> ®
    <service>
      <name>camel-service</name>
```

- ① Standard docker-maven-plugin configuration for building one single Docker image
- ② Kubernetes / OpenShift resources to create
- 3 Labels which should be applied globally to all resource objects
- 4 Definition of a Deployment to create
- ⑤ Container to include in the deployment
- 6 An *alias* is used to correlate a container's image with the image definition in the <images> section where each image carry an alias. Can be omitted if only a single image is used
- 7 Volume definitions used in a Deployment's ReplicaSet
- 8 One or more Service definitions.

The XML resource configuration is based on plain Kubernetes resource objects. For creating OpenShift resource descriptor an automatic conversion will happen, e.g. from Kubernetes Deployment to an OpenShift DeploymentConfig.

1.4.3. Resource Fragments

The third configuration option is to use an external configuration in form of YAML resource descriptors which are located in the src/main/fabric8 directory. Each resource get is own file, which contains some skeleton of a resource description. The plugin will pick up the resource, enriches it and the combines all to a single kubernetes.yml and openshift.yml. Within these descriptor files you are can freely use any Kubernetes feature. Note, that in order to support simultaneously both OpenShift and Kubernetes, there is currently no way to specify OpenShift feature only this way (but this might change).

Let's have a look at an example from samples/external-resources. This is a plain spring-boot application, whose images are auto generated like in the Zero-Config case. The resource fragments are in src/mainfabric8.

```
spec:
 replicas: 1
 template:
    spec:
      volumes:
        - name: config
          gitRepo:
            repository: 'https://github.com/jstrachan/sample-springboot-config.git'
            revision: 667ee4db6bc842b127825351e5c9bae5a4fb2147
            directory: .
      containers:
        - volumeMounts:
            - name: config
              mountPath: /app/config
          env:
            - name: KUBERNETES_NAMESPACE
              valueFrom:
                fieldRef:
                  apiVersion: v1
                  fieldPath: metadata.namespace
      serviceAccount: ribbon
```

As you can see, there is no metadata section as expected for each Kubernetes resource object. This section will be created automatically by fabric8-maven-plugin. The object's Kind, if not given, will be extracted from the filename. In this case its a Deployment because the file is called deployment.xml. For each supported resource type such a mapping exists. In addition you could specify a name in like in myapp-deployment.xml to give the resource a fixed name. Otherwise it will be automatically extracted from project information (i.e. the artificact id).

Here also the reference to the image is missing. In this case it will be automatically connected to the image you are building with this plugin (And you already know, that the image definition comes either from a generator or by a dedicated image plugin configuration).



For building images there is also an alternative mode using external Dockerfiles, in addition to the XML based configuration. Refer to fabric8:build for details.

Now that we have seen some examples for the various ways how this plugin can be used, the following sections will describe the plugin goals and extension points in detail.

Chapter 2. Installation

This plugin is available from Maven central and can be connected to pre- and post-integration phase as seen below. The configuration and available goals are described below.

```
<plugin>
 <groupId>io.fabric8
 <artifactId>fabric8-maven-plugin</artifactId>
 <version>3.1.1
 <configuration>
     . . . .
    <images>
       <!-- A single's image configuration -->
       <image>
          . . .
         <build>
           . . . .
         </build>
       </image>
    </images>
 </configuration>
 <!-- Connect fabric8:resource and fabric8:build to lifecycle phases -->
 <executions>
   <execution>
       <id>fabric8</id>
      <goals>
        <goal>resource</goal>
        <goal>build</goal>
       </goals>
   </execution>
 </executions>
</plugin>
```

Chapter 3. Goals

This plugin supports the following goals, which are explained in the next sections:

Table 2. Plugin Goals

Goal	Description
fabric8:build	Build images
fabric8:push	Push images to a registry
fabric8:resource	Create Kubernetes or OpenShift resource descriptors
fabric8:deploy	Deploy resources decriptors to a cluster
fabric8:watch	Watch for doing rebuilds and redeployments

Depending on whether the OpenShift or Kubernetes operational mode is used, the workflow and the performed actions differs :

Table 3. Workflows

Use Case	Kubernetes	OpenShift
Build	fabric8:build fabric8:push * Creates a image against an exposed Docker daemon (with a docker.tar) * Pushes the image to a registry which is then referenced from the configuration	fabric8:build * Creates or uses a BuildConfig * Creates or uses an ImageStream which can be referenced by the deployment descriptors in a DeploymenConfig * Starts an OpenShift build with a docker.tar as input
Deploy	fabric8:deploy * Applies a Kubernetes resource descriptor to cluster	fabric8:deploy * Applies an OpenShift resource descriptor to a cluster

3.1. fabric8:resource



This is a placeholder. Will be filled soon.

3.2. fabric8:build

This goal is for building Docker images. Images can be build in two ways which depend on the mode (property: fabric8.mode). This mode can have be either kubernetes for a standard Docker build (the default) or openshift for an OpenShift build.

By default the mode is set to auto. In this case the plugin tries to detect which kind of build should be performed by contaction the API server. If this fails or if no cluster access is conigured e.g. with oc login then the mode is set to kubernetes.

3.2.1. Kubernetes Build

If the mode is set to kubernetes then a normal Docker build is performed. The connection

configuration to access the Docker daemon is described in Access Configuration.

In order to make the generated images available to the Kubernetes cluster the generated images need to be pushed to a registry with the goal **fabric8:push**. This is not necessary for single node clusters, though as their is no need to distribute images.

3.2.2. OpenShift Build

For the mode openshift OpenShift specific Builds can be performed. These are so called Binary Source builds ("binary builds" in short), where the data specified with the build configuration is send directly to OpenShift as a binary archive.

There are two kind of binary builds supporte by this plugin, which can be selected with the configuration option buildStrategy (property fabric8.build.strategy)

Table 4. Build Strategies

buildStrateg y	Description
s2i	The Source-to-Image (S2I) build strategy uses so called builder images for creating new application images from binary build data. The builder image to use is taken from the base image configuration specified with from in the image build configuration. See below for a list of builder images which can be used with this plugin.
docker	A Docker Build is similar to a normal Docker build except that it is done by the OpenShift cluster and not by a Docker daemon. In addition this build pushes the generated image to the OpenShift internal registry so that it is accessbile in the whole cluster.

Both build strategies update an Image Stream after the image creation.

The Build Config and Image streams can be managed by this plugin. If they do not exist, they will be automatically created by fabric8:build. If they do already exist, they are reused, except when the config option recreate (property fabric8.build.recreate) is set to a value as described in Configuration.

This image stream created can then be referenced directly from a Deployment Configuration objects created by **fabric8:resource**.

In order to be able to to create these OpenShift resource objects access to an OpenShift installation is required. The access parameters are described in Access Configuration.

Regardless which build mode is used, the images are configured in the same way.

The configuration consists of two parts: A global section which defines the overall behaviour of this plugin. And a <images> section which defines how the one or more images should be build.

Many of the options below are relevant for the Kubernetes Workflow or the OpenShift Workflow with Docker builds as they influence how the Docker image is build.

For an S2I binary build mostly the Assembly is relevant because it depends on the builder image

how to interpret the content of the uploaded docker.tar.

3.2.3. Configuration

The following sections describe the usual configuration, which is similar to the build configuration used in the docker-maven-plugin.

In addition a more automatic way for creating predefined build configuration can be performed with so called Generators. Generators are very flexibel and can be easily created. These are described in an extra section.

Global configuration parameters specify overall behavior common for all images to build. Some of the configuration options are shared with other goals.

Table 5. Global configuration

Element	Description	Property
apiVersion	Use this variable if you are using an older version of docker not compatible with the current default use to communicate with the server.	docker.apiVe rsion
authConfig	Authentication information when pulling from or pushing to Docker registry. There is a dedicated section Authentication for how doing security.	
autoPull	Decide how to pull missing base images or images to start: * on: Automatic download any missing images (default) * off: Automatic pulling is switched off * always: Pull images always even when they are already exist locally * once: For multi-module builds images are only checked once and pulled for the whole build.	docker.autoP ull
buildRecrea te	If the effective mode is openshift then this option decides how the OpenShift resource objects associated with the build should be treated when they already exist: *buildConfig or bc: Only the BuildConfig is recreated * imageStream or is: Only the ImageStream is recreated * all: Both, BuildConfig and ImageStream are recreated * none: Neither BuildConfig nor ImageStream is recreated The default is none.	fabric8.buil d.recreate
buildStrateg y	If the effective mode is openshift then this option sets the build strategy. This can be: * s2i for a Source-to-Image build with a binary source * docker for a Docker build with a binary source By default S2I is used	fabric8.buil dStrategy
certPath	Path to SSL certificate when SSL is used for communicating with the Docker daemon. These certificates are normally stored in ~/.docker/. With this configuration the path can be set explicitly. If not set, the fallback is first taken from the environment variable DOCKER_CERT_PATH and then as last resort ~/.docker/. The keys in this are expected with it standard names ca.pem, cert.pem and key.pem. Please refer to the Docker documentation for more information about SSL security with Docker.	docker.certP ath

Element	Description	Property
dockerHost	The URL of the Docker Daemon. If this configuration option is not given, then the optional <machine> configuration section is consulted. The scheme of the URL can be either given directly as http or https depending on whether plain HTTP communication is enabled or SSL should be used. Alternatively the scheme could be tcp in which case the protocol is determined via the IANA assigned port: 2375 for http and 2376 for https. Finally, Unix sockets are supported by using the scheme unix together with the filesystem path to the unix socket. The discovery sequence used by the docker-maven-plugin to determine the URL is: . value of dockerHost (docker.host) . the Docker host associated with the docker-machine named in <machine>, i.e. the DOCKER_HOST from docker-machine env. See below for more information about Docker machine support the value of the environment variable DOCKER_HOST unix:///var/run/docker.sock if it is a readable socket.</machine></machine>	docker.host
image	In order to temporarily restrict the operation of plugin goals this configuration option can be used. Typically this will be set via the system property docker.image when Maven is called. The value can be a single image name (either its alias or full name) or it can be a comma separated list with multiple image names. Any name which doesn't refer an image in the configuration will be ignored.	docker.image
machine	Docker machine configuration. See Docker Machine for possible values	
mode	The build mode which can be * kubernetes : A Docker image will be created by calling a Docker daemon. See Kubernetes Build for details. * openshift : An OpenShift Build will be triggered, which can be either a Docker binary build or a S2I binary build, depending on the configuration buildStrategy. See OpenShift Build for details. * auto : The plugin tries to detect the mode by contacting the configured cluster. auto is the default.	fabric8.mode
maxConnec tions	Number of parallel connections are allowed to be opened to the Docker Host. For parsing log output, a connection needs to be kept open (as well for the wait features), so don't put that number to low. Default is 100 which should be suitable for most of the cases.	docker.maxCo nnections
namespace	Namespace to use when accessing Kubernetes or OpenShift	fabric8.name space
outputDirec tory	Default output directory to be used by this plugin. The default value is target/docker and is only used for the goal fabric8:build.	docker.targe t.dir
portPropert yFile	Global property file into which the mapped properties should be written to. The format of this file and its purpose are also described in Port Mapping.	
profile	Profile to which contains enricher and generators configuration. See Profiles for details.	fabric8.profile
registry	Specify globally a registry to use for pulling and pushing images. See Registry handling for details.	docker.regis try

Element	Description	Property
resourceDir *	Directory where fabric8 resources are stored. This is also the directory where a custom profile is looked up	fabric8.reso urceDir
skip	With this parameter the execution of this plugin can be skipped completely.	docker.skip
skipBuild	If set not images will be build (which implies also <i>skip.tag</i>) with fabric8:build	docker.skip. build
skipBuildPo m	If set the build step will be skipped for modules of type pom	docker.skip. build.pom
skipTag	If set to true this plugin won't add any tags to images that have been built with fabric8:build	docker.skip. tag
skipMachin e	Skip using docker machine in any case	docker.skip. machine
sourceDirec tory	Default directory that contains the assembly descriptor(s) used by the plugin. The default value is <pre>src/main/docker</pre> . This option is only relevant for the <pre>fabric8:build</pre> goal.	docker.sourc e.dir
verbose	Boolean attribute for switching on verbose output like the build steps when doing a Docker build. Default is false	docker.verbo se

3.2.4. Image Configuration

The configuration how images should be created a defined in a dedicated <images> sections. These are specified for each image within the <images> element of the configuration with one <image> element per image to use.

The <image> element can contain the following sub elements:

Table 6. Image Configuration

Element	Description
name	Each < image > configuration has a mandatory, unique docker repository <i>name</i> . This can include registry and tag parts, but also placeholder parameters. See below for a detailed explanation.
alias	Shortcut name for an image which can be used for identifying the image within this configuration. This is used when linking images together or for specifying it with the global image configuration element.
registry	Registry to use for this image. If the name already contains a registry this takes precedence. See Registry handling for more details.
build	Element which contains all the configuration aspects when doing a fabric8:build . This element can be omitted if the image is only pulled from a registry e.g. as support for integration tests like database images.

Name placeholders

When specifying the name you can use several placeholders which are replaced during runtime by

this plugin. In addition you can use regular Maven properties which are resolved by Maven itself.

Table 7. Placeholders

Placeholder	Description
%g	The last part of the Maven group name, sanitized so that it can be used as username on GitHub. Only the part after the last dot is used. E.g. for a group id io.fabric8 this placeholder would insert fabric8
%a	A sanitized version of the artefact id so that it can be used as part of an Docker image name. I.e. it is converted to all lower case (as required by Docker)
%v	The project version. Synonym to \${project.version}
%l	If the project version ends with -SNAPSHOT then this placeholder is latest, otherwise its the full version (same as %v)
%t	If the project version ends with -SNAPSHOT this placeholder resolves to snapshot- <timestamp> where timestamp has the date format yyMMdd-HHmmss-SSSS (eg snapshot-). This feature is especially useful during development in oder to avoid conflicts when images are to be updated which are still in use. You need to take care yourself of cleaning up old images afterwards, though.</timestamp>

The <build> section is mandatory and is explained in below.

Example for <image>

- ① One or more <image>' definitions
- 2 The Docker image name used when creating the image.
- 3 An alias which can be used in other parts of the plugin to reference to this image. This alias must be unique.
- 4 A <build> section as described in Build Configuration

3.2.5. Build Configuration

There are two different modes how Images can be built:

Inline plugin configuration

With an inline plugin configuration all information required to build the image is contained in the plugin configuration. By default its the standard XML based configuration for the plugin but can be switched to a property based configuration syntax as described in the section External configuration. The XML configuration syntax is recommended because of its more structured and typed nature.

When using this mode, the Dockerfile is created on the fly with all instructions extracted from the configuration given.

External Dockerfile

Alternatively an external Dockerfile template can be used. This mode is switch on by using one of these two configuration options within the <build> configuration section.

- **dockerFileDir** specifies a directory containing a **Dockerfile** that will be used to create the image.
- **dockerFile** specifies a specific Dockerfile. The **dockerFileDir** is set to the directory containing the file.

If dockerFileDir is a relative path looked up in \${project.basedir}/src/main/docker. You can make easily an absolute path by prefixing with \${project.basedir}.

Any additional files located in the dockerFileDir directory will also be added to the build context as well as any files specified by an assembly. However, you still need to insert ADD or COPY directives yourself into the Dockerfile.

If this directory contains a .maven-dockerignore (or alternatively, a .maven-dockerexclude file), then it is used for excluding files for the build. Each line in this file is treated as an FileSet exclude pattern as used by the maven-assembly-plugin. It is similar to .dockerignore when using Docker but has a slightly different syntax (hence the different name).

If this directory contains a .maven-docker include file, then it is used for including only those files for the build. Each line in this file is also treated as an FileSet exclude pattern as used by the maven-assembly-plugin.

Except for the assembly configuration all other configuration options are ignored for now.

For the future it is planned to introduce special keywords lile DMP_ADD_ASSEMBLY which can be used in the Dockerfile template to placing the configuration resulting from the additional configuration.

The following example uses a Dockerfile in the directory src/main/docker/demo:

Example

All build relevant configuration is contained in the <build> section of an image configuration. In addition to <dockerFileDir> and <dockerFile> the following configuration options are available:

Table 8. Build configuration

Element	Description	
args	Map specifying the value of Docker build args which should be used when building the image with an external Dockerfile which uses build arguments. The key-value syntax is the same as when defining Maven properties (or labels or env). This argument is ignored when no external Dockerfile is used. Build args can also be specified as properties as described in Build Args	
assembly	specifies the assembly configuration as described in Build Assembly	
cleanup	Cleanup dangling (untagged) images after each build (including any containers created from them). Default is try which tries to remove the old image, but doesn't fail the build if this is not possible because e.g. the image is still used by a running container. Use remove if you want to fail the build and none if no cleanup is requested.	
nocache	Don't use Docker's build cache. This can be overwritten by setting a system property docker.nocache when running Maven.	
cmd	A command to execute by default (i.e. if no command is provided when a container for this image is started). See Startup Arguments for details.	
entryPoint	An entrypoint allows you to configure a container that will run as an executable. See Startup Arguments for details.	
env	The environments as described in Setting Environment Variables and Labels.	
from	The base image which should be used for this image. If not given this default to busybox:latest and is suitable for a pure data image. In case of an S2I Binary build this parameter specifies the S2I Builder Image to use, which by default is fabric8/s2i-java:latest.	
labels	Labels as described in Setting Environment Variables and Labels.	

Element	Description
maintainer	The author (MAINTAINER) field for the generated image
ports	The exposed ports which is a list of <port> elements, one for each port to expose.</port>
runCmds	Commands to be run during the build process. It contains run elements which are passed to the shell. The run commands are inserted right after the assembly and after workdir in to the Dockerfile. This tag is not to be confused with the <run> section for this image which specifies the runtime behaviour when starting containers.</run>
optimise	if set to true then it will compress all the runCmds into a single RUN directive so that only one image layer is created.
compression	The compression mode how the build archive is transmitted to the docker daemon (fabric8:build) and how docker build archives are attached to this build as sources (fabric8:source). The value can be none (default), gzip or bzip2.
skip	if set to true disables building of the image. This config option is best used together with a maven property
tags	List of additional tag elements with which an image is to be tagged after the build.
user	User to which the Dockerfile should switch to the end (corresponds to the USER Dockerfile directive).
volumes	List of volume elements to create a container volume.
workdir	Directory to change to when starting the container.

From this configuration this Plugin creates an in-memory Dockerfile, copies over the assembled files and calls the Docker daemon via its remote API.

```
<build>
 <from>java:8u40</from>
 <maintainer>john.doe@example.com</maintainer>
 <tags>
    <tag>latest</tag>
    <tag>${project.version}</tag>
 </tags>
 <ports>
    <port>8080</port>
 </ports>
 <volumes>
    <volume>/path/to/expose</volume>
 </volumes>
 <entryPoint>
   <!-- exec form for ENTRYPOINT -->
   <exec>
      <arg>java</arg>
      <arg>-jar</arg>
      <arg>/opt/demo/server.jar</arg>
    </exec>
 </entryPoint>
 <assembly>
    <mode>dir</mode>
    <basedir>/opt/demo</basedir>
    <descriptor>assembly.xml</descriptor>
 </assembly>
</build>
```

In order to see the individual build steps you can switch on verbose mode either by setting the property docker.verbose or by using <verbose>true/verbose> in the Global configuration

3.2.6. Assembly

The <assembly> element within <build> is has an XML struture and defines how build artifacts and other files can enter the Docker image.

Table 9. Assembly Configuration

Element	Description
basedir	Directory under which the files and artifacts contained in the assembly will be copied within the container. The default value for this is /maven.
inline	Inlined assembly descriptor as described in Assembly Descriptor below.
descriptor	Path to an assembly descriptor file, whose format is described Assembly Descriptor below.

Element	Description
descriptorRef	Alias to a predefined assembly descriptor. The available aliases are also described in Assembly Descriptor below.
dockerFileDir	Directory containing an external DockerfileThis option is deprecated, please use <dockerfiledir> directly in the <build> section.</build></dockerfiledir>
exportBasedir	Specification whether the basedir should be exported as a volume. This value is true by default except in the case the basedir is set to the container root (/). It is also false by default when a base image is used with from since exporting makes no sense in this case and will waste disk space unnecessarily.
ignorePermiss ions	Specification if existing file permissions should be ignored when creating the assembly archive with a mode dir. This value is false by default. <i>This property is deprecated, use a</i> permissionMode of ignore instead.
mode	Mode how the how the assembled files should be collected: * dir: Files are simply copied (default), * tar: Transfer via tar archive * tgz: Transfer via compressed tar archive * zip: Transfer via ZIP archive The archive formats have the advantage that file permission can be preserved better (since the copying is independent from the underlying files systems), but might triggers internal bugs from the Maven assembler (as it has been reported in #171)
permissions	Permission of the files to add: * ignore to use the permission as found on files regardless on any assembly configuration * keep to respect the assembly provided permissions, exec for setting the executable bit on all files (required for Windows when using an assembly mode dir) * auto to let the plugin select exec on Windows and keep on others. keep is the default value.
user	User and/or group under which the files should be added. The user must already exist in the base image. It has the general format user[:group[:run-user]]. The user and group can be given either as numeric user- and group-id or as names. The group id is optional. If a third part is given, then the build changes to user root before changing the ownerships, changes the ownerships and then change to user run-user which is then used for the final command to execute. This feature might be needed, if the base image already changed the user (e.g. to 'jboss') so that a chown from root to this user would fail. For example, the image jboss/wildfly use a "jboss" user under which all commands are executed. Adding files in Docker always happens under the UID root. These files can only be changed to "jboss" is the chown command is executed as root. For the following commands to be run again as "jboss" (like the final standalone.sh), the plugin switches back to user jboss (this is this "run-user") after changing the file ownership. For this example a specification of jboss:jboss:jboss would be required.

In the event you do not need to include any artifacts with the image, you may safely omit this element from the configuration.

Assembly Descriptor

With using the inline, descriptor or descriptorRef option it is possible to bring local files, artifacts and dependencies into the running Docker container. A descriptor points to a file describing the data to put into an image to build. It has the same format as for creating assemblies with the maven-assembly-plugin with following exceptions:

- <formats> are ignored, the assembly will allways use a directory when preparing the data container (i.e. the format is fixed to dir)
- The <id> is ignored since only a single assembly descriptor is used (no need to distinguish multiple descriptors)

Also you can inline the assembly description with a inline description directly into the pom file. Adding the proper namespace even allows for IDE autocompletion. As an example, refer to the profile inline in the `data-jolokia-demo's pom.xml.

Alternatively descriptorRef can be used with the name of a predefined assembly descriptor. The following symbolic names can be used for descriptorRef:

Table 10. Predefined Assembly Descriptors

Assembly Reference	Description
artifact-with- dependencies	Attaches project's artifact and all its dependencies. Also, when a classpath file exists in the target directory, this will be added to.
artifact	Attaches only the project's artifact but no dependencies.
project	Attaches the whole Maven project but with out the target/ directory.
rootWar	Copies the artifact as ROOT.war to the exposed directory. I.e. Tomcat will then deploy the war under the root context.

Example

will add the created artifact with the name \${project.build.finalName}.\${artifact.extension} and all jar dependencies in the the baseDir (which is /maven by default).

All declared files end up in the configured basedir (or /maven by default) in the created image.

If the assembly references the artifact to build with this pom, it is required that the package phase is included in the run. This happens either automatically when the fabric8:build target is called as part of a binding (e.g. is fabric8:build is bound to the pre-integration-test phase) or it must be ensured when called on the command line:

Example

```
mvn package fabric8:build
```

This is a general restriction of the Maven lifecycle which applies also for the maven-assembly-plugin itself.

In the following example a dependency from the pom.xml is included and mapped to the name jolokia.war. With this configuration you will end up with an image, based on busybox which has a directory /maven containing a single file jolokia.war. This volume is also exported automatically.

Example

Another container can now connect to the volume an 'mount' the /maven directory. A container from consol/tomcat-7.0 will look into /maven and copy over everything to /opt/tomcat/webapps before starting Tomcat.

If you are using the artifact or artifact-with-dependencies descriptor, it is possible to change the name of the final build artifact with the following:

Example

```
<build>
    <finalName>your-desired-final-name</finalName>
    ...
</build>
```

Please note, based upon the following documentation listed here, there is no guarantee the plugin creating your artifact will honor it in which case you will need to use a custom descriptor like above to achieve the desired naming.

Currently the jar and war plugins properly honor the usage of finalName.

3.2.7. Environment and Labels

When creating a container one or more environment variables can be set via configuration with the env parameter

```
<env>
    <JAVA_HOME>/opt/jdk8</JAVA_HOME>
    <CATALINA_OPTS>-Djava.security.egd=file:/dev/./urandom</CATALINA_OPTS>
</env>
```

If you put this configuration into profiles you can easily create various test variants with a single image (e.g. by switching the JDK or whatever).

It is also possible to set the environment variables from the outside of the plugin's configuration with the parameter envPropertyFile. If given, this property file is used to set the environment variables where the keys and values specify the environment variable. Environment variables specified in this file override any environment variables specified in the configuration.

Labels can be set inline the same way as environment variables:

Example

```
<labels>
    <com.example.label-with-value>foo</com.example.label-with-value>
    <version>${project.version}</version>
    <artifactId>${project.artifactId}</artifactId>
</labels>
```

3.2.8. Startup Arguments

Using entryPoint and cmd it is possible to specify the entry point or cmd for a container.

The difference is, that an entrypoint is the command that always be executed, with the cmd as argument. If no entryPoint is provided, it defaults to /bin/sh -c so any cmd given is executed with a shell. The arguments given to docker run are always given as arguments to the entrypoint, overriding any given cmd option. On the other hand if no extra arguments are given to docker run the default cmd is used as argument to entrypoint.

```
See this stackoverflow question for a detailed explanation.
```

A entry point or command can be specified in two alternative formats:

Table 11. Entrypoint and Command Configuration

Mode	Description
shell	Shell form in which the whole line is given to shell -c for interpretation.
exec	List of arguments (with inner <args>) arguments which will be given to the exec call directly without any shell interpretation.</args>

Either shell or params should be specified.

```
<entryPoint>
  <!-- shell form -->
    <shell>java -jar $HOME/server.jar</shell>
</entryPoint>
```

Example

This can be formulated also more dense with:

Example

```
<!-- shell form -->
<entryPoint>java -jar $HOME/server.jar</entryPoint>
```

or

Example

```
<entryPoint>
  <!-- exec form -->
    <arg>java</arg>
    <arg>-jar</arg>
    <arg>/opt/demo/server.jar</arg>
    </entryPoint>
```

INFO

Startup arguments are not used in S2I builds

3.2.9. Build Args

As described in section Configuration for external Dockerfiles Docker build arg can be used. In addition to the configuration within the plugin configuration you can also use properties to specify them:

- Set a system property when running Maven, eg.: -Ddocker.buildArg.http_proxy=http://proxy:8001. This is especially useful when using predefined Docker arguments for setting proxies transparently.
- Set a project property within the pom.xml, eg.:

```
<docker.buildArg.myBuildArg>myValue</docker.buildArg.myBuildArg>
```

Please note that the system property setting will always override the project property. Also note that for all properties which are not Docker predefined properties, the external Dockerfile must contain an ARGS instruction.

3.3. fabric8:push



Section needs review and rearrangments

This goal uploads images to the registry which have a <build> configuration section. The images to push can be restricted with with the global option image (see Global Configuration for details). The registry to push is by default docker.io but can be specified as part of the images's name name the Docker way. E.g. docker.test.org:5000/data:1.5 will push the image data with tag 1.5 to the registry docker.test.org at port 5000. Security information (i.e. user and password) can be specified in multiple ways as described in section Authentication.

Table 12. Push options

Element	Description	Property
skipPush	If set to true the plugin won't push any images that have been built.	docker.skip. push
pushRegistr y	The registry to use when pushing the image. See Registry Handling for more details.	docker.push. registry
retries	How often should a push be retried before giving up. This useful for flaky registries which tend to return 500 error codes from time to time. The default is 0 which means no retry at all.	docker.push. retries

3.4. fabric8:deploy



This is a placeholder. Will be filled soon.

3.5. fabric8:watch



Section needs review and rearrangments

When developing and testing applications you will often have to rebuild Docker images and restart containers. Typing fabric8:build and fabric8:start all the time is cumbersome. With fabric8:watch you can enable automatic rebuilding of images and restarting of containers in case of updates.

fabric8:watch is the top-level goal which perform these tasks. There are two watch modes, which can be specified in multiple ways:

• build: Automatically rebuild one or more Docker images when one of the files selected by an assembly changes. This works for all files included directly in assembly.xml but also for arbitrary dependencies.

```
$ mvn package fabric8:build fabric8:watch -Ddocker.watchMode=build
```

This mode works only when there is a <build> section in an image configuration. Otherwise no automatically build will be triggered for an image with only a <run> section. Note that you need the package phase to be executed before otherwise any artifact created by this build can not be included into the assembly. As described in the section about fabric8:start this is a Maven limitation. * run: Automatically restart container when their associated images changes. This is useful if you pull a new version of an image externally or especially in combination with the build mode to restart containers when their image has been automatically rebuilt. This mode works reliably only when used together with fabric8:start.

Example

```
$ mvn fabric8:start fabric8:watch -Ddocker.watchMode=run
```

- both: Enables both build and run. This is the default.
- none: Image is completely ignored for watching.
- copy: Copy changed files into the running container. This is the fast way to update a container, however the target container must support hot deply, too so that it makes sense. Most application servers like Tomcat supports this.

The mode can also be both or none to select both or none of these variants, respectively. The default is both.

fabric8:watch will run forever until it is interrupted with CTRL-C after which it will stop all containers. Depending on the configuration parameters keepContainer and removeVolumes the stopped containers with their volumes will be removed, too.

When an image is removed while watching it, error messages will be printed out periodically. So don't do that ;-)

Dynamically assigned ports stay stable in that they won't change after a container has been stopped and a new container is created and started. The new container will try to allocate the same ports as the previous container.

If containers are linked together network or volume wise, and you update a container which other containers dependent on, the dependant containers are not restarted for now. E.g. when you have a "service" container accessing a "db" container and the "db" container is updated, then you "service" container will fail until it is restarted, too.

A future version of this plugin will take care of restarting these containers, too (in the right order), but for now you would have to do this manually.

This maven goal can be configured with the following top-level parameters:

Table 13. Watch configuration

Element	Description	Property
watchMode	Watch mode specifies what should be watched * build : Watch changes in the assembly and rebuild the image in case * run : Watch a container's image whether it changes and restart the container in case * copy : Changed files are copied into the container. The container can be either running or might be already exited (when used as a <i>data container</i> linked into a <i>platform container</i>). Requires Docker >= 1.8. * both : build and run combined * none : Neither watching for builds nor images. This is useful if you use prefactored images which won't be changed and hence don't need any watching. none is best used on an per image level, see below how this can be specified.	docker.watch Mode
watchInterv al	Interval in milliseconds how often to check for changes, which must be larger than 100ms. The default is 5 seconds.	docker.watch Interval
watchPostG oal	A maven goal which should be called if a rebuild or a restart has been performed. This goal must have the format <plugingroupid>:<pluginartifactid>:<goal> and the plugin must be configured in the pom.xml. For example a post-goal io.fabric8:fabric8:delete-pods will trigger the deletion of PODs in Kubernetes which in turn triggers are new start of a POD within the Kubernetes cluster. The value specified here is the the default post goal which can be overridden by <postgoal> in a <watch> configuration.</watch></postgoal></goal></pluginartifactid></plugingroupid>	
watchPostE xec	A command which is executed within the container after files are copied into this container when watchMode is copy. Note that this container must be running.	
keepRunnin g	If set to true all container will be kept running after fabric8:watch has been stopped. By default this is set to false.	docker.keepR unning
keepContai ner	As for fabric8:stop, if this is set to true (and keepRunning is disabled) then all container will be removed after they have been stopped. The default is true.	docker.keepC ontainer
removeVolu mes	if set to true will remove any volumes associated to the container as well. This option will be ignored if either keepContainer or keepRunning are true.	docker.remov eVolumes

Image specific watch configuration goes into an extra image-level <watch> section (i.e. <image><watch>...</watch></image>). The following parameters are recognized:

Table 14. Watch configuration for a single image

Element	Description
mode	Each image can be configured for having individual watch mode. These take precedence of the global watch mode. The mode specified in this configuration takes precedence over the globally specified mode.
interval	Watch interval can be specified in milliseconds on image level. If given this will override the global watch interval.

Element	Description
postGoal	Post Maven plugin goal after a rebuild or restart. The value here must have the format <plugingroupid>:<pluginartifactid>:<goal> (e.g. io.fabric8:fabric8:delete-pods)</goal></pluginartifactid></plugingroupid>
postExec	Command to execute after files are copied into a running container when mode is copy.

Here is an example how the watch mode can be tuned:

Example

```
<configuration>
   <!-- Check every 10 seconds by default -->
   <watchInterval>10000</watchInterval>
   <!-- Watch for doing rebuilds and restarts -->
   <watchMode>both</watch>
   <images>
      <image>
         <!-- Service checks every 5 seconds -->
         <alias>service</alias>
         . . . .
         <watch>
            <interval>5000</interval>
         </watch>
      </image>
      <image>
         <!-- Database needs no watching -->
         <alias>db<alias>
         . . . .
         <watch>
            <mode>none</mode>
         </watch>
      </image>
      . . . .
   </images>
</configuration>
```

Given this configuration

Example

```
mvn package fabric8:build fabric8:start fabric8:watch
```

You can build the service image, start up all containers and go into a watch loop. Again, you need the package phase in order that the assembly can find the artifact build by this project. This is a Maven limitation. The db image will never be watch since it assumed to not change while watching.

Chapter 4. Generators

The usual way to define Docker images is with the plugin configuration as explained in **fabric8:build**. This can either be done completly within the pom.xml or by refering to an external Dockerfile. Since fabric8-maven-plugin includes our docker-maven-plugin the way how images are built is identical.

However, this plugin provides an additional route for defining image configurations. This is done by so called *Generators*. A generator is a Java component providing an auto-detection mechanism for certain build type like a Spring Boot build or a plain Java build. As soon as a generator detects that it is applicable it will be called with the list of images configured in the pom.xml. Typically a generator only creates dynamically an image configuration if this list is empty. But a generator is free to also add new images to an existing list or even change the current image list.

You can easily create your own generator as explained in Generator API. This section however will focus on existing generators and how you can configure them.

By default, this plugin includes already a set of generators, which are explained in detail below. These generators are enabled by default, but you can easil disable them or only select a certain set of generators. Each generator has a *name*, which is unique for a generator.

The generator configuration is embedded in a <generator > configuration section:

Example for a generator configuration

- ① Start of generators' configuration.
- ② Generators can be included and excluded. Includes have precedence, and the generators are called in the given order.
- 3 Configuration for individual generators.
- 4 The config is a map of supported config values. Each section is embedded in a tag named after the generator.

Generators can be configured with a <generator> section. The following sub-elements are supported.

Table 15. Generator configuration

Element	Description
<includes></includes>	Contains one ore more <include> elements with generator names which should be include. If given, only this list of generators are included in this order.</include>
<excludes></excludes>	Holds one or more <exclude> elemens with generator names to exclude. This mean all the detected generators are used except the ones mentioned in this section.</exclude>
<config></config>	Configuration for all generators. Each generator support a specific set of configuration values as described in the documentation. The subelements of this section are tags named as the generator to configure. E.g. for generator spring-boot, the sub-element is called <spring-boot>. This element then holds the specific generator configuration like <name> for specifying the final image name. See above for an example</name></spring-boot>

fabric8-maven-plugin comes with a set of default generators which are described in the next section Stock Generators. These are enabled by default. In addition, custom generators can be easily added by simply declaring a compile scoped dependency in the pom.xml. How this can be done and how such a generator can be implemented is described in Generator API.

4.1. Stock Generators

- 4.1.1. spring-boot
- 4.1.2. java-exec
- 4.1.3. karaf

4.2. Generator API

Chapter 5. Enrichers



This is a placeholder. Will be filled soon.

• Should be passive. E.g. if already set don't override.

Chapter 6. Profiles



This is a placeholder. Will be filled soon.

Chapter 7. Access configuration

7.1. Docker Access



This section is work-in-progress and not yet finished

For Kubernetes builds the fabric8-maven-plugin uses the Docker remote API so the URL of your Docker Daemon must be specified. The URL can be specified by the dockerHost or machine configuration, or by the DOCKER_HOST environment variable. If not given

The Docker remote API supports communication via SSL and authentication with certificates. The path to the certificates can be specified by the certPath or machine configuration, or by the DOCKER_CERT_PATH environment variable.

7.2. OpenShift and Kubernetes Access

Chapter 8. Registry handling

Docker uses registries to store images. The registry is typically specified as part of the name. I.e. if the first part (everything before the first /) contains a dot (.) or colon (:) this part is interpreted as an address (with an optionally port) of a remote registry. This registry (or the default docker.io if no registry is given) is used during push and pull operations. This plugin follows the same semantics, so if an image name is specified with a registry part, this registry is contacted. Authentication is explained in the next section.

There are some situations however where you want to have more flexibility for specifying a remote registry. This might be, because you do not want to hard code a registry into pom.xml but provide it from the outside with an environment variable or a system property.

This plugin supports various ways of specifying a registry:

- If the image name contains a registry part, this registry is used unconditionally and can not be overwritten from the outside.
- If an image name doesn't contain a registry, then by default the default Docker registry docker.io is used for push and pull operations. But this can be overwritten through various means:
 - If the <image> configuration contains a <registry> subelement this registry is used.
 - Otherwise, a global configuration element <registry> is evaluated which can be also provided as system property via -Ddocker.registry.
 - Finally an environment variable DOCKER_REGISTRY is looked up for detecting a registry.

This registry is used for pulling (i.e. for autopull the base image when doing a fabric8:build) and pushing with docker.push. However, when these two goals a are combined on the command line like in mvn -Ddocker.registry=myregistry:5000 package fabric8:build fabric8:push the same registry is used for both operation. For a more fine grained control, separate registries for *pull* and *push* can be specified.

- In the plugin's configuration with the parameters <pullRegistry> and <pushRegistry>, respectively.
- With the system properties docker.pull.registry and docker.push.registry, respectively.

```
<configuration>
 <registry>docker.jolokia.org:443</registry>
 <images>
    <image>
     <!-- Without an explicit registry ... -->
     <name>jolokia/jolokia-java</name>
     <!-- ... hence use this registry -->
     <registry>docker.ro14nd.de</registry>
    <image>
    <image>
     <name>postgresql</name>
     <!-- No registry in the name, hence use the globally
           configured docker.jolokia.org:443 as registry -->
      . . . .
    </image>
    <image>
     <!-- Explicitely specified always wins -->
     <name>docker.example.com:5000/another/server
    </image>
 </images>
</configuration>
```

There is some special behaviour when using an externally provided registry like described above:

- When *pulling*, the image pulled will be also tagged with a repository name **without** registry. The reasoning behind this is that this image then can be referenced also by the configuration when the registry is not specified anymore explicitly.
- When *pushing* a local image, temporarily a tag including the registry is added and removed after the push. This is required because Docker can only push registry-named images.

Chapter 9. Authentication

When pulling (via the autoPull mode of fabric8:start) or pushing image, it might be necessary to authenticate against a Docker registry.

There are three different ways for providing credentials:

- Using a <authConfig> section in the plugin configuration with <username> and <password> elements.
- Providing system properties docker.username and docker.password from the outside
- Using a <server> configuration in ~/.m2/settings.xml
- Login into a registry with docker login

Using the username and password directly in the pom.xml is not recommended since this is widely visible. This is most easiest and transparent way, though. Using an <authConfig> is straight forward:

The system property provided credentials are a good compromise when using CI servers like Jenkins. You simply provide the credentials from the outside:

Example

```
mvn -Ddocker.username=jolokia -Ddocker.password=s!cr!t fabric8:push
```

The most secure and also the most mavenish way is to add a server to the Maven settings file $\sim/.m2/settings.xml$:

```
<server>
    <id>docker.io</id>
    <username>jolokia</username>
    <password>s!cr!t</password>
    </server>
    ....
</servers>
```

The server id must specify the registry to push to/pull from, which by default is central index docker.io (or index.docker.io / registry.hub.docker.com as fallbacks). Here you should add your docker.io account for your repositories. If you have multiple accounts for the same registry, the second user can be specified as part of the ID. In the example above, if you have a second accorunt 'fabric8io' then use an <id>docker.io/fabric8io</id> for this second entry. I.e. add the username with a slash to the id name. The default without username is only taken if no server entry with a username appended id is chosen.

As a final fallback, this plugin consults ~/.docker/config.json for getting to the credentials. Within this file credentials are stored when connecting to a registry with the command docker login from the command line.

9.1. Pull vs. Push Authentication

The credentials lookup described above is valid for both push and pull operations. In order to narrow things down, credentials can be be provided for pull or push operations alone:

In an <authConfig> section a sub-section <pull> and/or <push> can be added. In the example below the credentials provider are only used for image push operations:

Example

When the credentials are given on the command line as system properties, then the properties docker.pull.username / docker.push.username / docker.push.password are

used for pull and push operations, respectively (when given). Either way, the standard lookup algorithm as described in the previous section is used as fallback.

9.2. OpenShift Authentication

When working with the default registry in OpenShift, the credentials to authtenticate are the OpenShift username and access token. So, a typical interaction with the OpenShift registry from the outside is:

```
oc login
...
mvn -Ddocker.registry=docker-registry.domain.com:80/default/myimage \
-Ddocker.username=$(oc whoami) \
-Ddocker.password=$(oc whoami -t)
```

(note, that the image's user name part ("default" here") must correspond to an OpenShift project with the same name to which you currently connected account has access).

This can be simplified by using the system property docker.useOpenShiftAuth in which case the plugin does the lookup. The equivalent to the example above is

```
oc login
...
mvn -Ddocker.registry=docker-registry.domain.com:80/default/myimage \
-Ddocker.useOpenShiftAuth
```

Alternatively the configuration option <useOpenShiftAuth</pre> can be added to the <authConfig</pre> section.

For dedicted *pull* and *push* configuration the system properties docker.pull.useOpenShiftAuth and docker.push.useOpenShiftAuth are available as well as the configuration option <useOpenShiftAuth> in an <pull> or <push> section within the <authConfig> configuration.

9.3. Password encryption

Regardless which mode you choose you can encrypt password as described in the Maven documentation. Assuming that you have setup a *master password* in ~/.m2/security-settings.xml you can create easily encrypted passwords:

Example

```
$ mvn --encrypt-password
Password:
{QJ6wvuEfacMHklqsmrtrn1/ClOLqLm8hB7yUL23KOKo=}
```

This password then can be used in authConfig, docker.password and/or the <server> setting configuration. However, putting an encrypted password into authConfig in the pom.xml doesn't make

much sense, since this password is encrypted with an individual master password.	