Jin-Soo Kim (jinsoo.kim@snu.ac.kr)

Systems Software Research Lab.


Seoul National University


Spring 2018

# Assembly I: Basic Operations




#### Basic Execution Environment





# IA-32 Registers




# Moving Data (I)

- Moving data: movq Src, Dest
  - Move 8-byte ("quad") word
- Operand types
  - Immediate: constant integer data
    - Like C constant, but prefixed with '\$'
    - Encoded with 1, 2, or 4 bytes
    - e.g. **\$0x400**, **\$-533**
  - Register: one of 16 integer registers
    - But %rsp reserved for special use
    - Others have special uses for particular instructions
  - Memory: 8 consecutive bytes of memory
    - Various "addressing modes"

%rax
%rbx
%rcx
%rdx
%rsi
%rdi
%rsp
%rbp
%r8
%r9
%r10
%r10 %r11
%r11
%r11 %r12
%r11 %r12 %r13

# Moving Data (2)

- movq operand combinations
  - Cannot do memory-memory transfer with a single instruction



## Simple Addressing Modes

- Normal (R) Mem[Reg[R]]
  - Register R specifies memory address
  - Pointer dereferencing in C
  - e.g. movq (%rcx), %rax
- Displacement D(R) Mem[Reg[R]+D]
  - Register R specifies start of memory region
  - Constant displacement D specifies offset
  - e.g. movq 8(%rbp), %rdx

# General Addressing Modes

```
D(Rb,Ri,S) Mem[Reg[Rb]+S*Reg[Ri]+D]
```

- D: constant "displacement": 1, 2, or 4 bytes
- Rb: Base register: any of 16 integer registers
- Ri: Index register: any, except for %rsp
- S: Scale: 1, 2, 4, or 8

#### Special cases

- (Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]
- D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]
- (Rb,Ri,S) Mem[Reg[Rb]+S\*Reg[Ri]]
- Useful to access arrays and structures

# Addressing Modes: Example

Address computation

Expression	Computation	Address
0x8(%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)	0xf000 + 0x100	0xf100
(%rdx,%rcx,4)	0xf000 + 4*0x100	0xf400
0x80(,%rdx,2)	2*0xf000 + 0x80	0x1e080

# Swap Example

Source code in C:


```
void swap(long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```

Corresponding assembly code:

```
swap:
    movq (%rdi), %rax
    movq (%rsi),%rdx
    movq %rdx, (%rdi)
    movq %rax, (%rsi)
    ret
```

# Understanding Swap (I)

```
void swap(long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```





Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

```
swap:
  movq   (%rdi), %rax # t0 = *xp
  movq   (%rsi), %rdx # t1 = *yp
  movq   %rdx, (%rdi) # *xp = t1
  movq   %rax, (%rsi) # *yp = t0
  ret
```

# Understanding Swap (2)

```
void swap(long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```







Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

```
swap:
  movq (%rdi), %rax # t0 = *xp
  movq (%rsi), %rdx # t1 = *yp
  movq %rdx, (%rdi) # *xp = t1
  movq %rax, (%rsi) # *yp = t0
  ret
```


# Understanding Swap (3)






Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

# Understanding Swap (4)






Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

```
swap:
  movq (%rdi), %rax # t0 = *xp
  movq (%rsi), %rdx # t1 = *yp
  movq %rdx, (%rdi) # *xp = t1
  movq %rax, (%rsi) # *yp = t0
  ret
```

# Understanding Swap (5)

```
void swap(long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```




Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

```
swap:
  movq (%rdi), %rax # t0 = *xp
  movq (%rsi), %rdx # t1 = *yp
  movq %rdx, (%rdi) # *xp = t1
  movq %rax, (%rsi) # *yp = t0
  ret
```

# Understanding Swap (5)

```
void swap(long *xp, long *yp)
{
    long t0 = *xp;
    long t1 = *yp;
    *xp = t1;
    *yp = t0;
}
```



Register	Variable
%rdi	хр
%rsi	ур
%rax	t0
%rdx	t1

```
swap:
  movq (%rdi), %rax # t0 = *xp
  movq (%rsi), %rdx # t1 = *yp
  movq %rdx, (%rdi) # *xp = t1
  movq %rax, (%rsi) # *yp = t0
  ret
```

# Arithmetic/Logical Operations (I)

#### Two operand instructions

```
    addq

          Src, Dest
                          Dest = Dest + Src
subq
          Src, Dest
                          Dest = Dest - Src
mulq
          Src, Dest
                          Dest = Dest * Src (unsigned)
                          Dest = Dest * Src (signed)
• imulq
          Src, Dest
salq
          Src, Dest
                          Dest = Dest << Src (= shlq)
                          Dest = Dest >> Src (arithmetic)
          Src, Dest
sarq
                          Dest = Dest >> Src (logical)
shrq
          Src, Dest
          Src, Dest
                          Dest = Dest ^ Src
xorq
                          Dest = Dest & Src
andq
          Src, Dest
          Src, Dest
                          Dest = Dest | Src
• orq
```

# Arithmetic/Logical Operations (2)

One operand instructions

```
    incq Dest Dest = Dest + I
    decq Dest Dest = Dest - I
    negq Dest Dest Dest = - Dest
    notq Dest Dest = ~ Dest
```

See books for more instructions

#### Address Computation Instruction

- leal *Src*, *Dest* 
  - *Src* is address mode expression
  - Set *Dest* to address denoted by expression

#### Uses

- Computing address without a memory reference
  - e.g. translation of p = &x[i];
- Computing arithmetic expression of the form x + k\*y
  - k = 1, 2, 4, or 8

```
long m12 (long x) {
  return x * 12;
}
leaq (%rdi, %rdi, 2), %rax
salq $2, %rax
```

#### Example: arith

```
long arith (long x, long y, long z) {
    long t1 = x+y;
    long t2 = z+t1;
    long t3 = x+4;
    long t4 = y * 48;
    long t5 = t3 + t4;
    long rval = t2 * t5;
    return rval;
}
x in %rdi
y in %rsi
z in %rdx
```

# Example: logical

```
int logical (int x, int y) {
   int t1 = x^y;
   int t2 = t1 >> 17;
   int mask = (1 << 13) - 7;
   int rval = t2 & mask;
   return rval;
}</pre>
x in %edi
y in %esi
y in %esi
```

# **CISC** Properties


- Complex Instruction Set Computer (CISC)
  - Instruction can reference different operand types
    - Immediate, register, memory
  - Arithmetic operations can read/write memory
    - Source or destination can be a memory address
  - Memory reference can involve complex computation
    - Rb + S \* Ri + D
    - Useful for arithmetic expressions, too
  - Instructions can have varying lengths
    - x86-64 instructions can range from 1 to 15 bytes

## Machine-level Programming


- Assembly code is textual form of binary object code
- Low-level representation of program
  - Explicit manipulation of registers
  - Simple and explicit instructions
  - Minimal concept of data types
  - Many C control constructs must be implemented with multiple instructions

# Summary

#### **Machine Models**



#### **Assembly**



#### **Data**

- 1) char
- 2) int, float
- 3) double
- 4) struct, array
- 5) pointer

- 1) byte
- 2) 2-byte word
- 3) 4-byte long word
- 4) 8-byte quad word
- 5) contiguous byte allocation
- 6) address of initial byte

#### **Control**

- 1) loops
- 2) conditionals
- 3) switch
- 4) Proc. call
- 5) Proc. return

- 1) branch/jump
- 2) call
- 3) ret