Lecturer: Clear all the cells and set up MATLAB

In [1]:

format compact clear all


Elementary Signals

The preparatory reading for this section is <u>Chapter 1 of Karris</u> (https://ebookcentral.proquest.com/lib/swansea-ebooks/reader.action?docID=3384197&ppg=75#ppg=17) which

- begins with a discussion of the elementary signals that may be applied to electrical circuits
- · introduces the unit step, unit ramp and dirac delta functions
- · presents the sampling and sifting properties of the delta function and
- concludes with examples of how other useful signals can be synthesised from these elementary signals.

An annotatable copy of partial notes and in-class examples for this presentation will be distributed before the first class meeting as **Worksheet 3** the handouts section for week 1 of the _Content Library of the **OneNote Class Notebook**. You can also view the notes for this presentation as a webpage (https://cpjobling.github.io/eg-247-textbook/elementary_signals/index.html)) and as a downloadable https://cpjobling.github.io/cpjobling/eg-247-textbook/elementary_signals/elementary_signals.pdf).

Consider the network shown below, where the switch is closed at time t = T.



Express the output voltage v_{out} as a function of the unit step function, and sketch the appropriate waveform.

Solution


Before the switch is closed at t < T,

$$V_{\text{out}} = 0.$$

After the switch is closed for t > T,

$$V_{\rm out} = V_{\rm s}$$
.


We imagine that the voltage jumps instantaneously from 0 to $V_{\scriptscriptstyle \mathcal{S}}$ volts at t=T seconds.



We call this type of signal a step function.

The Unit Step Function

$$u_0(t) = \begin{cases} 0 & t < 0 \\ 1 & t > 0 \end{cases}$$



In Matlab

In Matlab, we use the heaviside function (Named after Oliver Heaviside (http://en.wikipedia.org/wiki/Oliver Heaviside)).


In [2]:

```
%%file plot_heaviside.m
syms t
ezplot(heaviside(t),[-1,1])
heaviside(0)
```

Created file '/Users/eechris/dev/eg-247-textbook/content/elementary_signals/plot_heaviside.m'.

In [3]:

plot_heaviside



Note that, so that it can be plotted, Matlab defines the *heaviside function* slightly differently from the mathematically ideal unit step:

heaviside(t) =
$$\begin{cases} 0 & t < 0 \\ 1/2 & t = 0 \\ 1 & t > 0 \end{cases}$$


Simple Signal Operations

Amplitude Scaling

Sketch $Au_0(t)$ and $-Au_0(t)$

In [4]:


```
syms t;
u0(t) = heaviside(t); % rename heaviside function for ease of use
A = 2; % so signal can be plotted
ezplot(A*u0(t),[-1,1]),grid,title('Applitude scaling $$Au_0(t)$$','interpreter','latex')
```



Note that the signal is scaled in the y direction.

In [5]:

 $ezplot(-A*u0(t),[-1,1]),grid,title('Amplitude scaling and mirroring $$-Au_0(t) $$','interpreter','latex')$




Note that, because of the sign, the signal is mirrored about the x axis as well as being scaled by 2.

Time Reversal

Sketch $u_0(-t)$

In [6]:

 $ezplot(A*u0(-t),[-1,1]),grid,title('Time reversal <math>Au_0(-t)$,'interpreter','l atex')




The sign on the function argument -t causes the whole signal to be reversed in time. Note that another way of looking at this is that the signal is mirrored about the y axis.

Time Delay and Advance

Sketch $u_0(t-T)$ and $u_0(t+T)$

In [7]:


T = 1; % again to make the signal plottable. ezplot(u0(t - T),[-1,2]),grid,title('Time delay $\u_0(t - T),\u_1(t - T),\u_1(t - T),\u_1(t - U),\u_1(t - U),\u_1(t$



This is a *time delay* ... note for $u_0(t-T)$ the step change occurs T seconds **later** than it does for $u_0(t)$.

In [8]:

ezplot(u0(t + T),[-2,1]),grid,title('Time advance $\u_0(t + T)$,'interpreter', 'latex')



This is a *time advance* ... note for $u_0(t+T)$ the step change occurs T seconds **earlier** than it does for $u_0(t)$.


Examples

We will work through some examples in class. See Worksheet 3 (worksheet3).

Synthesis of Signals from the Unit Step

Unit step functions can be used to represent other time-varying functions such as rectangular pulses, square waves and triangular pulses. See <u>Worksheet 3 (worksheet3)</u> for the examples that we will look at in class.

The Ramp Function



In the circuit shown above i_s is a constant current source and the switch is closed at time t=0.

When the current through the capacitor $i_c(t)=i_s$ is a constant and the voltage across the capacitor is

$$v_c(t) = \frac{1}{C} \int_{-\infty}^{t} i_c(\tau) \ d\tau$$

where τ is a dummy variable.

Since the switch closes at t = 0, we can express the current $i_c(t)$ as

$$i_c(t) = i_s u_0(t)$$

and if $v_c(t) = 0$ for t < 0 we have

$$v_{c}(t) = \frac{1}{C} \int_{-\infty}^{t} i_{s} u_{0}(\tau) d\tau = \underbrace{\frac{i_{s}}{C} \int_{-\infty}^{0} i_{c}(\tau) d\tau}_{0} + \frac{i_{s}}{C} \int_{0}^{t} i_{c}(\tau) d\tau$$


So, the voltage across the capacitor can be represented as

$$v_C(t) = \frac{i_s}{C} t u_0(t)$$

To sketch the wave form, let's arbitrarily let C and i_s be one and then plot with MATLAB.

In [12]:

```
C = 1; is = 1;
vc(t)=(is/C)*t*u0(t);
ezplot(vc(t),[-1,4]),grid,title('A ramp function')
```



This type of signal is called a **ramp function**. Note that it is the *integral* of the step function (the resistor-capacitor circuit implements a simple integrator circuit).

The unit ramp function is defined as

$$u_1(t) = \int_{-\infty}^t u_0(\tau) d\tau$$

so

$$u_1(t) = \begin{cases} 0 & t < 0 \\ t & t \ge 0 \end{cases}$$

and

$$u_0(t) = \frac{d}{dt}u_1(t)$$

Note


Higher order functions of t can be generated by the repeated integration of the unit step function.

For future reference, you should determine $u_2(t)$, $u_3(t)$ and $u_n(t)$ for yourself and make a note of the general rule:

$$u_{n-1} = \frac{1}{n} \frac{d}{dt} u_n(t)$$

Details are given in equations 1.26—1.29 in Karris.

The Dirac Delta Function



In the circuit shown above, the switch is closed at time t=0 and $i_L(t)=0$ for t<0. Express the inductor current $i_L(t)$ in terms of the unit step function and hence derive an expression for $v_L(t)$.

Solution

$$v_L(t) = L \frac{di_L}{dt}$$

Because the switch closes instantaneously at t = 0

$$i_L(t) = i_s u_0(t)$$

Thus

$$v_L(t) = i_s L \frac{d}{dt} u_0(t).$$

To solve this problem we need to invent a function that represents the derivative of the unit step function. This function is called $\delta(t)$ or the *dirac delta* function (named after <u>Paul Dirac</u> (http://en.wikipedia.org/wiki/Paul Dirac)).

The delta function

The unit impulse or the delta function, denoted as $\delta(t)$, is the derivative of the unit step.

This function is tricky because $u_0(t)$ is discontinuous at t=0 but it must have the properties

$$\int_{-\infty}^{t} \delta(\tau)d\tau = u_0(t)$$

and

$$\delta(t) = 0 \; \forall \; t \neq 0.$$

Sketch of the delta function



MATLAB Confirmation

```
In [11]:
```

```
syms is L;
vL(t) = is * L * diff(u0(t))

vL(t) =
L*is*dirac(t)
```

Note that we can't plot dirac(t) in MATLAB with ezplot.

Important properties of the delta function

Sampling Property

The sampling property of the delta function states that

$$f(t)\delta(t-a) = f(a)\delta(t-a)$$

or, when a = 0,

$$f(t)\delta(t) = f(0)\delta(t)$$

Multiplication of any function f(t) by the delta function $\delta(t)$ results in sampling the function at the time instants for which the delta function is not zero.

The study of descrete-time (sampled) systems is based on this property.

You should work through the proof for youself.

Sifting Property

The sifting property of the delta function states that

$$\int_{-\infty}^{\infty} f(t)\delta(t-\alpha)dt = f(\alpha)$$

That is, if multiply any function f(t) by $\delta(t-\alpha)$, and integrate from $-\infty$ to $+\infty$, we will get the value of f(t) evaluated at $t=\alpha$.

You should also work through the proof for yourself.

Higher Order Delta Fuctions

the nth-order delta function is defined as the nth derivative of $u_0(t)$, that is

$$\delta^n(t) = \frac{d^n}{dt^n} [u_0(t)]$$

The function $\delta'(t)$ is called the *doublet*, $\delta''(t)$ is called the *triplet* and so on.

By a procedure similar to the derivation of the sampling property we can show that

$$f(t)\delta'(t-a) = f(a)\delta'(t-a) - f'(t)\delta(t-a)$$

Also, derivation of the sifting property can be extended to show that

$$\int_{-\infty}^{\infty} f(t)\delta^n(t-\alpha)dt = (-1)^n \frac{d^n}{dt^n} [f(t)]\bigg|_{t=\alpha}$$

Summary

In this chapter we have looked at some elementary signals and the theoretical circuits that can be used to generate them.

Takeaways

- You should note that the unit step is the *heaviside function* $u_0(t)$.
- Many useful signals can be synthesized by use of the unit step as a "gating function" in combination with other signals
- That unit ramp function $u_1(t)$ is the integral of the step function.
- The *Dirac delta* function $\delta(t)$ is the derivative of the unit step function. We sometimes refer to it as the *unit impulse function*.
- The delta function has sampling and sifting properties that will be useful in the development of *time* convolution and sampling theory.

Examples

We will do some of these in class. See worksheet3 (worksheet3).

Homework

These are for you to do later for further practice. See Homework 1 (../homework/hw1).