## **Approximation of Fractions**

floating point values in a computer system are *approximations* of fractional values. Because we are dealing with powers of two, we can only precisely represent numbers that can be written as  $x * 2^y$ . Other values, like 1/5 for example, must be approximated. We represent numbers with fractional components in binary in the form:

Where the (.) is called the *binary point*. Bits to the left of the binary point are weighted with positive powers of two while bits to right are weighted with negative pwoers of two.

Example: 101.11

```
101.11
 = (1 * 2^2) + (0 * 2^1) + (1 * 2^0) + (1 * 2 ^ -1) + (1 * 2^{-2}) 
 = (4) + (0) + (1) + (1/2) + (1/4) 
 = 5 3/4
```

Consider the following two for loops:

```
int i;
for(i=0;i<MAXLOOPS;i++);
float j;
for(j=0;<MAXLOOPS;j++);</pre>
```

Using the clock() function (#include), we can compute the clock ticks needed to process each for loop. Running with MAXLOOPS defined as 100000, will produce results similar to ~320 ticks for the integer loop and 540 ticks for the floating point loop! Even on something as trivial as incrementing the counter variable in a for-loop, using a float for the counter decreases the speed by over 60%! WHY?!?

## **IEEE 754 representation**

IEEE 754 is a standard for implementing floating point computation. It defines two basic formats, a single precision floating point (float) and a double precision floating point (double). IEEE 754 represented a number in the form of:

```
V = (-1)^s \times M \times 2^s (E - bias) where:
```

- s is the sign bit that designates if the number is positive or negative.
- *M* is called the **significand** and is a fractional binary number.
- E is the **exponent** and weighs the value by a power of 2.
- the **bias** is an offset that is introduced the help make comparisons of floating points faster. The bias is computed using the word length of the exponent by: 2<sup>(k-1)</sup> 1. (127 for single precision, 1023 for double precision).

IEEE 754 is an example of using a fixed-bit width encoding. where we have 1 bit for the sign, followed by k bits to designate the exponent and n bits to encode the fractional component. For single precision, k=8 and n =23. For double precision, k=11 and n=52.

## Example: Convert the following single precision IEEE 724 into a decimal value

0xC0D00000

- 2) Now we group:

```
1-bit sign [1]
8-bits exponent [1000 0001]
23-bits significand [101 0000 0000 0000 0000]
```

3) evaluate the exponent:

4) compute the significant:

```
(1*2^{-1}) + (1*2^{-3})
= (1/2) + (1/8)
= 5/8
= .625
```

(-4) + (127) = 123

5) put it together:

```
V = (-1)^s * (M) * 2^(E-bias)
= (-1)^(1) * (.625) * 2^(129-127)
= (-1) * (.625) * (4)
= -2.5
```

Example: Convert the following decimal value to a single precision IEEE 724:

```
.085
```

Step 4: approximate the fractional part in binary form:

exponent: 0111 1011

fraction: 010 1110 0001 0100 0111 1011

0011 1101 1010 1110 0001 0100 0111 1011

To Hex: 0x3DAE147B