Operating Systems

Operating Systems
Sina Meraji
U of T



Announcements



- A2 is announced
- Midterm will be on July 4th(class time)
 - Location TBD
- No Class next week(Study break)

Recap



- Last time we looked at memory management techniques
 - Fixed partitioning
 - Dynamic partitioning
 - Paging

Example Address Translation




- Suppose addresses are 16 bits, pages are 4K (4096 bytes)
 - How many bits of the address do we need for offset?
 - 12 bits (2^12 = 4096)
 - What is the maximum number of pages for a process?
 - 2⁴

Example Address Translation


- To translate virtual address: 0x3468
 - Extract page number (high-order 4 bits)
 -> page = vaddr >> 12 == 3
 - Get frame number from page table
 - Combine frame number with page offset
 - offset = vaddr % 4096
 - paddr = frame * 4096 + offset
 - paddr = (frame << 12) | offset

logical -> virtual address real -> physical address

 15 12	. — —
0011	0100 0110 1000
Pg #	Offset




Page Lookups Overview



- What's wrong with this approach?
 - Need 2 references for address lookup (first page table, then actual memory)
- Idea: Use hardware cache of page table entries
 - Translation Lookaside Buffer (TLB)
 - Small hardware cache of recently used translations

Page Lookups Overview



- What's wrong with this approach?
 - Need 2 references for address lookup (first page table, then actual memory)
- Idea: Use hardware cache of page table entries
 - Translation Lookaside Buffer (TLB)
 - Small, fully-associative hardware cache of recently used translations

TLBs



Translate virtual page #s into PTEs (not physical addrs)

- Can be done in a single machine cycle hardware, runs in parallel
- TLBs implemented in hardware
 - Fully associative cache (all entries looked up in parallel)
 - Cache tags are virtual page numbers
 - Cache values are PTEs (entries from page tables)
 - With PTE + offset, can directly calculate physical address

TLBs



- TLBs are small (64 1024 entries)
- Still, address translations for most instructions are handled using the TLB
 - >99% of translations, but there are misses (TLB miss)...

so during hit miss, update pages associated with the missed address space

- TLBs exploit <u>locality</u>
 - Processes only use a handful of pages at a time
 - 16-48 entries/pages (64-192K)
 - Only need those pages to be "mapped"
 - Hit rates are therefore very important

Managing TLBs



- Who places translations into the TLB (loads the TLB)?
 - Hardware (Memory Management Unit)

Software loaded TLB (OS)

Managing TLBs



- Who places translations into the TLB (loads the TLB)?
 - Hardware (Memory Management Unit)
 - Knows where page tables are in main memory
 - OS maintains tables, HW accesses them directly
 - Tables have to be in HW-defined format (inflexible)
 - Software loaded TLB (OS)
 - TLB faults to the OS, OS finds appropriate PTE, loads it in TLB
 - Must be fast (but still 20-200 cycles)
 CPU specific instruction to change TLB
 - CPU ISA has instructions for manipulating TLB
 - Tables can be in any format convenient for OS (flexible)

Managing TLBs (2)


if more than 1 processes mapped to same frame#, howerver only one frame may be used, with value bit = 1



- OS ensures that TLB and page tables are consistent
 - When it changes the protection bits of a PTE, it needs to invalidate the PTE if it is in the TLB
- Reload TLB on a process context switch


```
Invalidate all entries
Why?
new pages...
1. disk -> memory
2. set value bit = 1
3. update TLB
```

- When the TLB misses and a new PTE has to be loaded, a cached PTE must be evicted
 - Choosing PTE to evict is called the TLB replacement policy
 - Implemented in hardware, often simple



What happens if not all pages of all processes fit into physical memory?

Summary so far: Paging



Page

Disk

What happens if page is evicted from main memory?

- Set PTE to "invalid"
- Store disk location in PTE

How much space does a page table take up?



- Need one PTE per page
- 32 bit virtual address space w/ 4K pages
 - = 2²⁰ PTEs i.e. 2²⁰ pages = 1MB pages
- 4 bytes/PTE = 4MB/page table
- 25 processes = 100MB just for page tables!
 - And modern processors have 64-bit address spaces -> 16 petabytes for page table!


Solutions


- Hierarchical (multi-level) page tables
- Hashed page tables
- Inverted page tables

Managing Page Tables

- How can we reduce space overhead?
 - Observation: Only need to map the portion of the address space actually being used (tiny fraction of entire addr space)
- How do we only map what is being used?
 - Can dynamically extend page table...
 - Does not work if addr space is sparse (internal fragmentation)
- Use another level of indirection: two-level page tables (or multi-level page tables)


Motivation: two-level page tables





Multilevel Page Tables






(a) A 32-bit address with two page table fields.(b) Two-level page tables.

Two-Level Page Tables

Virtual addresses (VAs) have three parts:

- Master page number, secondary page number, and offset
- Master page table maps VAs to secondary page table
- Secondary page table maps page number to physical frame
- Offset selects address within physical frame



2-Level Paging Example

- 32-bit virtual address space
 - 4K pages, 4 bytes/PTE
 - How many bits in offset?
 - 4K = 12 bits, leaves 20 bits

Waster page numberSecondaryOffset10 bits10 bits12 bits

assumes 4KB in both master and 4KB (1K entries) in every secondary page for this question


- Want master/secondary page tables in 1 page each:
 - 4K/4 bytes = 1K entries.
 - How many bits to address 1K entries?
 - 10 bits
 - master = 10 bits

a total of 1K * 1K = 10^6 addresses = 2^20 addresses

- offset = 12 bits
- secondary = 32 10 12 = 10 bits
- This is why 4K is common page size! for 32bit


Pentium Address Translation





Pentium Address Translation





Inverted Page Tables



- Keep one table with an entry for each physical page frame
- Entries record which virtual page # is stored in that frame
 - Need to record process id as well
- Less space, but lookups are slower have to go through the entire table.
 - References use virtual addresses, table is indexed by physical addresses
 - Use hashing (again!) to reduce the search time


Efficient Translations

- Our original page table scheme already doubled the cost of doing memory lookups
 - One lookup into the page table, another to fetch the data
- Two-level page tables triple the cost!
 - Two lookups into the page tables, a third to fetch the data
 - And this assumes the page table is in memory
- TLB's hide the cost for frequently-used pages

Page allocation & eviction

- What happens when new page is allocated?
 - Initially, pages are allocated from memory
 - When memory fills up:
 - Some other page needs to be evicted from memory
 - This is why physical memory pages are called "frames"
 - Evicted pages go to disk (the swap file)
 - When it evicts a page, the OS sets the PTE as invalid and stores the location of the page in the swap file in the PTE

Recap: Paging



Disk


- Load page in memory
- Update PTE

Page Faults




- What happens when a process accesses a page that has been evicted?
 - When a process accesses the page, the invalid PTE will cause a trap (page fault)
 - 3. The trap will run the OS page fault handler
 - 4. Handler uses the invalid PTE to locate page in swap file
 - 5. Reads page into a physical frame, updates PTE to point to it
 - 6. Restarts process

Policy Decisions



- Page tables, MMU, TLB, etc. are mechanisms that make virtual memory possible
- Next, we'll look at policies for virtual memory management:
- Fetch Policy when to fetch a page
 - Placement Policy where to put the page
 - Replacement Policy what page to evict to make room?


Demand Paging



- Timing: Disk read is initiated when the process needs the page
- Request size: Process can only page fault on one page at a time, disk sees single page-sized read
- What alternative do we have?


Prepaging (aka Prefetching)





- Predict future page use at time of current fault
 - On what should we base the prediction? What if it's wrong?

Policy Decisions



- Page tables, MMU, TLB, etc. are mechanisms that make virtual memory possible
- Next, we'll look at policies for virtual memory management:
 - Fetch Policy when to fetch a page
 - Demand paging vs. Prepaging



Placement Policy - where to put the page

- Are some physical pages preferable to others?
- Replacement Policy what page to evict to make room?
 - Lots and lots of possible algorithms!

Placement Policy



- In paging systems, memory management hardware can translate any virtual-to-physical mapping equally well
- Why would we prefer some mappings over others?
 - NUMA (non-uniform memory access) multiprocessors
 - Any processor can access entire memory, but local memory is faster
 - Cache performance
 - Choose physical pages to minimize cache conflicts
- These are active research areas!

Policy Decisions



- Page tables, MMU, TLB, etc. are mechanisms that make virtual memory possible
- Next, we'll look at policies for virtual memory management:
 - Fetch Policy when to fetch a page
 - Demand paging vs. Prepaging
 - Placement Policy where to put the page
 - Are some physical pages preferable to others?
- Replacement Policy what page to evict to make room?
 - Lots and lots of possible algorithms!

Evicting the best page

goal is to reduce fault rate



- The goal of the replacement algorithm is to reduce the fault rate by selecting the best victim page to remove
- Replacement algorithms are evaluated on a <u>reference</u> string by counting the number of page faults

order in which we accesses the pages in the future

- Let's start by cheating a little bit ...
 - Assume we know the reference string what is the best replacement policy in this case?

Evicting the best page

Page address list: 2,3,2,1,5,4,5,3,5,3,2



Cold misses:

first access to a page (unavoidable)

2	

2	
3	

2	
3	

2	
3	
Ж	

2
3
5

Capacity misses:

caused by replacement due to limited size of memory

- Lesson 1:
 - The best page to evict is the one <u>never</u> used again
 - Will never fault on it

Evicting the best page

Page address list: 2,3,2,1,5,4,5,3,5,3,2




4

3


5

Cold misses:

first access to a page (unavoidable)







Capacity misses:

caused by replacement due to limited size of memory

Lesson 2:

- Never is a long time, so picking the page closest to "never" is the next best thing
- Evicting the page that won't be used for the longest period of time minimizes the number of page faults
- Proved by Belady, 1966


Belady's Algorithm

- Belady's algorithm is known as the <u>optimal</u> page replacement algorithm because it has the lowest fault rate for any page reference stream (aka OPT or MIN)
 - Idea: Replace the page that will not be used for the longest period of time
 - Problem: Have to know the future perfectly
- Why is Belady's useful then? Use it as a yardstick
 - Compare implementations of page replacement algorithms with the optimal to gauge room for improvement
 - If optimal is not much better, then algorithm is pretty good
 - If optimal is much better, then algorithm could use some work
 - Random replacement is often the lower bound



- First-in-first-out (FIFO)
- Least-recently-used (LRU)
- Least-frequently-used
- Most-frequently-used
- Many of these require book-keeping ...
- Let's start with algorithms that require only information contained in PTE

Page Table Entries (PTE)





- Modify (M)
 - says whether or not page has been written
- Reference (R) read/write
 - says whether page has been accessed
 - is cleared periodically (e.g. at clock interrupt)
- Valid (V)
 - says whether PTE can be used
- Protection bits:
 - what operations are allowed on page

used for replacement algos

Not-Recently-Used (NRU)



Divide pages into 4 classes:

- Class1: Not referenced, not modified
- Class 2: Not referenced, modified
- Class 3: Referenced, not modified
- Class 4: Referenced, modified

 Remove page at random from lowestnumbered class that's not empty

First-In First-Out (FIFO)



- FIFO is an obvious algorithm and simple to implement
 - Maintain a list of pages in order in which they were paged in
 - On replacement, evict the one brought in longest time ago
- Why might this be good?
 - Maybe the one brought in the longest ago is not being used
- Why might this be bad?
 - Then again, maybe it's not
 - We don't have any info to say one way or the other
- FIFO suffers from "Belady's Anomaly"
 - The fault rate might actually increase when the algorithm is given more memory (very bad)

Example of Belady's anomaly

Page Address List: 0,1,2,3,0,1,4,0,1,2,3,4

					\wedge						<u> </u>	\ \	
	0	1	2	3	0	1	4	0	1	2	3	4	ω
Youngest	0	1	2	3	0	1	4	4	4	2	3	3	frar 9 fa
		0	1	2	3	0	1	1	1	4	2	2	frames, 9 faults
Oldest			0	1	2	3	0	0	0	1	4	4	
	_		_	_	1	1 .				_			<u> </u>
Anomaly	0	1	2	3	0	1	4	0	1	2	3	4	
Youngest	0	1	2	3	3	3	4	0	1	2	3	4	4 fra
		0	1	2	2	2	3	4	0	1	2	3	frames, 0 faults
			0	1	1	1	2	3	4	0	1	2	ts
Oldest				0	0	0	1	2	3	4	0	1	

Second-Chance



Idea:

- FIFO (First-in-first-out) considers only age
- NRU (Not recently used) considers only usage
- Maybe we should combine the two!
- Second chance algorithm:
 - Don't evict the oldest page if it has been used.
 - Evict the oldest page that has not been used.
- Pages that are used often enough to keep reference bits set will not be replaced

Implementing Second Chance (clock)




Replace page that is "old enough"

- Arrange all of physical page frames in a big circle (clock)
- A clock hand is used to select a good LRU candidate
 - Sweep through the pages in circular order like a clock
 - If the ref bit (aka use bit) is off, it hasn't been used recently
 - Evict the page
 - If the ref bit is on
 - Turn it off and go to next page
- Arm moves quickly when pages are needed
- Low overhead when plenty of memory

Modelling Clock





setting R -> if R was 1 guarantees that its always possible to find victim

- 1st page fault:
 - Advance hand to frame 4, use frame 3
- 2nd page fault (assume none of these pages are referenced)
 - Advance hand to frame 6, use frame 5

Least Recently Used (LRU)



- LRU uses reference information to make a more informed replacement decision
 - Idea: We can't predict the future, but we can make a guess based upon past experience
 - On replacement, evict the page that has not been used for the longest time in the past (Belady's: future)
 - When does LRU do well? When does LRU do poorly?
- On average performs very well (close to Belady)

But

CSC369H1S

Implementing Exact LRU

- Option 1:
 - Time stamp every reference

hardware

- Evict page with oldest time stamp
- time stemp has to be updated on every memory reference **Problems:**
 - Need to make PTE large enough to hold meaningful time stamp (may double size of page tables, TLBs)
 - Need to examine every page on eviction to find one with oldest time stamp
- Option 2:
 - Keep pages in a stack. On reference, move the page to the top of the stack. On eviction, replace page at bottom.
 - Problems:
 - Need costly software operation to manipulate stack on **EVERY** memory reference!

CSC369H1S 11/03/2004



Modelling Exact LRU



Page Address List: 0,1,2,3,0,1,4,0,1,2,3,4

•	1	I	1	1	I	1	ı	ı	1	İ	1	1	
3 Frames	0	1	2	3	0	1	4	0	1	2	3	4	
MRU page	0	1	2	3	0	1	4	0	1	2	3	4	0 fs
		0	1	2	3	0	1	4	0	1	2	3	faults
LRU page			0	1	2	3	0	1	4	0	1	2	
	ı	ı	ı	ı	ı	ı	ı	ı	ı	ı	I	I	
4 Frames	0	1	2	3	0	1	4	0	1	2	3	4	
MRU page	0	1	2	3	0	1	4	0	1	2	3	4	8 5
		0	1	2	3	0	1	4	0	1	2	3	faults
			0	1	2	3	0	1	4	0	1	2	
LRU page				0	1	2	3	3	3	4	0	1	

Approximating LRU



- Exact LRU is too costly to implement
- LRU approximations use the PTE reference bit
- Basic Idea:
 - Initially, all R bits are zero; as processes execute, bits are set to 1 for pages that are used
 - Periodically examine the R bits we do not know order of use, but we know pages that were (or were not) used
- Additional-Reference-Bits Algorithm
 - Keep a counter for each page
 - At regular intervals, for every page do:
 - Shift R bit into high bit of counter register
 - Shift other bits to the right
 - Pages with "larger" counters were used more recently

Counting-based Replacement



- Count number of uses of a page
- Least-Frequently-Used (LFU)
 - Replace the page used least often
 - Pages that are heavily used at one time tend to stick around even when not needed anymore
 - Newly allocated pages haven't had a chance to be used much
- Most-Frequently-Used (MFU)
 - Favours new pages
- Neither is common, both are poor approximations of OPT



	Ease of implementation	Performance
 Not-recently-used (NRU) First-in-first-out (FIFO) Least-recently-used (LRU) Least-frequently-used Most-frequently-used 	+ + - -	



	Ease of implementation	Performance
 Not-recently-used (NRU) 	+	~
First-in-first-out (FIFO)	+	~
 Least-recently-used (LRU) 	■ too much space	++
Least-frequently-used	_	-
 Most-frequently-used 	_	-



Ease of implementation	Performance
+	~
+	~
-	++
-	-
-	-
+	+
	implementation +

Fixed vs. Variable Space

- In a multiprogramming system, we need a way to allocate memory to competing processes
- Problem: How to determine how much memory to give to each process?
 - Fixed space algorithms
 - Each process is given a limit of pages it can use
 - When it reaches the limit, it replaces from its own pages
 - Local replacement
 - Some processes may do well while others suffer
 - Variable space algorithms
 - Process' set of pages grows and shrinks dynamically
 - Global replacement one process can ruin it for the rest
 - Local replacement replacement and set size are separate



Working Set Model



- How do you decide how large the fixed or variable space for a process should be?
- Depends on access pattern ...

Process 1

6152162751

5 pages {1,2,5,6,7}

Process 2

4433413444

2 or 3 pages {3,4} or {1,3,4}

Working Set Model




- A working set of a process is used to model the dynamic locality of its memory usage
 - Defined by Peter Denning in 60's
- Definition
 - WS(t,∆) = {pages P such that P was referenced in the time interval (t, t-∆)}
 - t = time, $\Delta = working set window (measured in page refs)$
- A page is in the working set (WS) only if it was referenced in the last △ references
- ...2 **6 1 5 2 1 6 7 5 1** 6

$$\longleftrightarrow$$

$$WS(t1) = \{1,2,5,6,7\}$$

123**444343444**1



Working Set Size



- The working set size is the number of pages in the working set
 - The number of pages referenced in the interval (t, t-∆)
- The working set size changes with program locality
 - During periods of poor locality, you reference more pages
 - Within that period of time, the working set size is larger
- Intuitively, want the working set to be the set of pages a process needs in memory to prevent heavy faulting
 - Each process has a parameter ∆ that determines a working set with few faults
 - Denning: Don't run a process unless working set is in memory

Working Set Problems



- Problems
 - How do we determine \triangle ? machine learning?
 - How do we know when the working set changes?
- Too hard to answer
 - So, working set is not used in practice as a page replacement algorithm
- However, it is still used as an abstraction
 - The intuition is still valid
 - When people ask, "How much memory does Netscape need?", they are in effect asking for the size of Netscape's working set

Page Fault Frequency (PFF)



- Page Fault Frequency (PFF) is a variable space algorithm that uses a more ad-hoc approach
 - Monitor the fault rate for each process
 - If the fault rate is above a high threshold, give it more memory
 - So that it faults less
 - But not always (FIFO, Belady's Anomaly)
 - If the fault rate is below a low threshold, take away memory
 - Should fault more
 - But not always
- Hard to use PFF to distinguish between changes in locality and changes in size of working set

Thrashing

- Page replacement algorithms avoid thrashing
 - When more time is spent by the OS in paging data back and forth from disk than executing user programs
 - No time spent doing useful work (making progress)
 - In this situation, the system is overcommitted
 - No idea which pages should be in memory to reduce faults
 - Could just be that there isn't enough physical memory for all of the processes in the system
 - Ex: Running Windows Vista with 4 MB of memory...
 - Possible solutions
 - Swapping write out all pages of a process and suspend it
 - Buy more memory



Windows XP Paging Policy



- Local page replacement
 - Per-process FIFO
 - Pages are stolen from processes using more than their minimum working set
 - Processes start with a default of 50 pages
 - XP monitors page fault rate and adjusts workingset size accordingly
 - On page fault, cluster of pages around the missing page are brought into memory

Linux Paging



- Global replacement, like most Unix
- Modified second-chance clock algorithm
 - Pages age with each pass of the clock hand
 - Pages that are not used for a long time will eventually have a value of zero
- Continually under development...