Homework 4 Solutions

Problem 1

Let's compare reservoirs with normal and reverse faulting regimes (onshore). For both regimes, plot the limits of S_1 and S_3 versus depth from 0 to 5km assuming hydrostatic pore pressure and a state of stress limited by frictional strength of faults. Assume sliding friction coefficient is $\mu=0.6$. For both regimes, how does changing μ from 0.6 to 1.0 change the maximum possible differential stress S_1-S_3 at a fixed depth of z=5km? Explain what that friction coefficient change physically means.

Normal faulting occurs in tectonically passive or extensional environments, such that $S_V > S_{Hmax} > S_{hmin}$, where $S_1 = S_V$, $S_2 = S_{Hmax}$, $S_3 = S_{hmin}$. Hydraulic fractures in this environment are vertical.

Reverse faulting occurs in "strong" tectonically compressive environments, such that $S_{Hmax} > S_{hmin} > S_V$, where $S_1 = S_{Hmax}$, $S_2 = S_{hmin}$, $S_3 = S_V$. Hydraulic fractures in this environment are horizontal.

We assume the pore pressure gradient is 10 MPa/km and the overburden gradient is 23 MPa/km.

q (friction parameter function of the friction angle) is related to μ (friction coefficient) through the equation:

$$q = (\sqrt{\mu^2 + 1} + \mu)^2$$

From the below graphs, the higher the friction coefficient (μ), the larger $\sigma_1 - \sigma_3$ is. Physically this means a stronger fault.

In general, σ_3 (minimum effective stress) is related to σ_1 (maximum effective stress) through the equation:

$$\sigma_1 = S_o + q\sigma_3$$

Because there is a lack of cohesive strength in the Earth's crust at the large scale we have:

$$\sigma_1 = q\sigma_3$$


$$\sigma_3 = \frac{\sigma_1}{a}$$

Where $\sigma_1 = S_1 - P_p$ and $\sigma_3 = S_3 - P_p$

```
In [2]: import numpy as np
         import matplotlib.pyplot as plt
         # Pressure Gradients Assumed
         PpGradient = 10 # dPp/dz = 10 MPa/km
         SvGradient = 23 # dSv/dz = 23 MPa/km
         ## Case when friction coefficient is 0.6
         mu1 = 0.6 # define mu, friction coefficient
         q1=(((mu1**2+1)**0.5)+mu1)**2 # calculates q, friction parameter function of the friction angle
         print ("When the friction coefficent u=0.6, q is calculated to be", round(q1,2))
         # Normal Faulting
         plt.subplot(3, 2, 1)
         depth = np.linspace(0, 5, 5) # depth in km
         plt.plot(depth*PpGradient, depth, '-b', label='$P_p$',) # Pp (Data)
plt.plot(depth*SvGradient, depth, '-r', label='$S_1=S_v$') # S1 = Sv (Data)
         plt.plot((depth*SvGradient-depth*PpGradient)/q1+depth*PpGradient, depth, '--g', label='$5_3=5_{hmin}$') #53 = Shmin (Calculated)
         # Plot labels
         plt.xlabel('Pressure [MPa]')
         plt.ylabel('Depth [km]')
         plt.title("Normal Faulting ($\mu=0.6$)")
         plt.legend()
         # Axis range
plt.xlim([0, 140])
         plt.ylim([5, 0])
         # Reverse Faulting
         plt.subplot(3, 2, 2)
         depth = np.linspace(0, 5, 5) # depth in km
         plt.plot(depth*PpGradient, depth, '-b', label='$P_p$') # Pp (Data)
         plt.plot((depth*SvGradient-depth*PpGradient)*q1+depth*PpGradient, depth, '--g', label='$S_1=S_{Hmax}$') # 51 = SHmax (Calculated)
         plt.plot(depth*SvGradient, depth, '-r', label='$S_3=S_v$') # S3 = Sv (Data)
         # Plot labels
         plt.xlabel('Pressure [MPa]')
plt.ylabel('Depth [km]')
         plt.title("Reverse Faulting ($\mu=0.6$)")
         plt.legend()
         # Axis range
         plt.xlim([0, 500])
         plt.ylim([5, 0])
```

```
## Case when friction coefficient is 1
mu2 = 1 # define mu, friction coefficient
q2=(((mu2**2+1)**0.5)+mu2)**2 # calculates q, friction parameter function of the friction angle
print ("When the friction coefficent u=1, q is calculated to be",round(q2,2))
# Normal Faulting
plt.subplot(3, 2, 3)
depth = np.linspace(0, 5, 5) # depth in km
plt.plot(depth*PpGradient, depth, '-b', label='$P_p$',) # Pp (Data) plt.plot(depth*SvGradient, depth, '-r', label='$5_1=5_v$') # S1 = Sv (Data)
plt.plot((depth*SvGradient-depth*PpGradient)/q1+depth*PpGradient, depth, '--g', label='$5_3=5_{hmin}$') #S3 = Shmin (Calculated)
 # Plot labels
plt.xlabel('Pressure [MPa]')
plt.ylabel('Depth [km]')
plt.title("Normal Faulting ($\mu=1$)")
plt.legend()
# Axis range
plt.xlim([0, 140])
plt.ylim([5, 0])
# Reverse Faulting
plt.subplot(3, 2, 4)
depth = np.linspace(0, 5, 5) # depth in km
plt.plot(depth*PpGradient, depth, '-b', label='$P_p$') # Pp (Data)
plt.plot((depth*SvGradient-depth*PpGradient)*q1+depth*PpGradient, depth, '--g', label='$5_1=5_{Hmax}$') # 51 = SHmax (Calculated)
plt.plot(depth*SvGradient, depth, '-r', label='$S_3=S_v$') # S3 = Sv (Data)
 # Plot labels
plt.xlabel('Pressure [MPa]')
plt.ylabel('Depth [km]')
plt.title("Reverse Faulting ($\mu=1$)")
plt.legend()
# Axis range
plt.xlim([0, 500])
plt.ylim([5, 0])
## Comparing S1-S3
# Normal Faulting
plt.subplot(3, 2, 5)
depth = np.linspace(0, 5, 5) # depth in km
S1 = depth*SvGradient
S3_1 = (depth*SvGradient-depth*PpGradient)/q1+depth*PpGradient
S3_2 = (depth*SvGradient-depth*PpGradient)/q2+depth*PpGradient
plt.plot(S1-S3_1, depth, label='$\mu=0.6$') # S1-S3 (friction coefficient is 0.6)
plt.plot(S1-S3_2, depth, label='$\mu=1$') # S1-S3 (friction coefficient is 1)
 # Plot labels
plt.xlabel('Pressure [MPa]')
plt.ylabel('Depth [km]')
plt.title("Normal Faulting ($5_1-S_3$)")
plt.legend()
# Axis ranae
plt.xlim([0, 140])
plt.ylim([5, 0])
# Reverse Faulting
plt.subplot(3, 2, 6)
depth = np.linspace(0, 5, 5) # depth in km
S1_1 = (depth*SvGradient-depth*PpGradient)*q1+depth*PpGradient
S1_2 = (depth*SvGradient-depth*PpGradient)*q2+depth*PpGradient
S3 = depth*SvGradient
plt.plot(51_1-53, depth, label='\mbox{\mbox{$\mbox{$\mbox{$\mbox{$\mbox{$\mbox{$}\mbox{$\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\mbox{$}\m
# Plot Labels
plt.xlabel('Pressure [MPa]')
plt.ylabel('Depth [km]')
plt.title("Reverse Faulting ($S_1-S_3$)")
plt.legend()
 # Axis range
plt.xlim([0, 500])
plt.ylim([5, 0])
# Change plot size
fig = plt.gcf()
fig.set_size_inches(15, 15)
print("In the below graphs, dashed line signifies stresses that were calculated while solid line indicates stresses that were")
print("directly calculated from assumed pressure gradients")
```

When the friction coefficent u=0.6, q is calculated to be 3.12 When the friction coefficent u=1, q is calculated to be 5.83 In the below graphs, dashed line signifies stresses that were calculated while solid line indicates stresses that were directly calculated from assumed pressure gradients



In [3]: import pandas as pd
 excel_file = 'Hw4.xlsx'
 DataQ2 = pd.read_excel(excel_file, sheet_name=0)
 DataQ2.head()

Out[3]:

	Normal Faulting	Depth [km]	Pp [MPa]	Sv [MPa]	σν [MPa]	Shmin [MPa]	σhmin [MPa]	\$1-\$3 [MPa]	Reverse Faulting	SHmax [MPa]	σHmax [MPa]	\$1-\$3 [MPa].1	-	-,1	2	3	4
0	Sv > SHmax > Shmin	0	0	0	0	0.00000	0.00000	0.00000	SHmax > Shmin > Sv	0.00000	0.00000	0.00000	-	Pore Pressure Gradient	dPp/dz	10	[Mpa/km]
1	-	1	10	23	13	14.16743	4.16743	8.83257	-	50.55257	40.55257	27.55257	-	Overburden Gradient	dSv/dz	23	[Mpa/km]
2	-	2	20	46	26	28.33486	8.33486	17.66514	-	101.10514	81.10514	55.10514	-	Friction Coefficient	μ	0.6	[-]
3	-	3	30	69	39	42.50229	12.50229	26.49771	-	151.65771	121.65771	82.65771	-	Friction Parameter Function	q	3.11943	[-]
4	-	4	40	92	52	56.66972	16.66972	35.33028	-	202.21028	162.21028	110.21028	-	-	-	-	-

A given site offshore (sea floor at 500ft) is subjected to a Normal Faulting stress regime. Over-pressure is first detected at 1500 ft (TVD) and at 2000ft overpressure is $\lambda_p=0.78$. Calculate the total minimum horizontal stress S_hmin at this depth assuming frictional equilibrium of faults and friction angle 30° . Draw the corresponding Mohr circle with a solid line and draw an additional Mohr circle with a dashed line assuming hydrostatic pressure. (Assume typical water and lithostatic gradients)

We assume the pore pressure gradient is 0.44 psi/ft and the overburden gradient is 1 psi/ft.

The overburden at 2000 ft is the summation of the overlying hydrostatic head of water and the remaining pressure head to that depth:

$$S_v = 500 \times 0.44 + 1500 \times 1 = 1720 psi$$

The actual pore pressure at any depth beyond 1500 ft TVD where overpressure was first detected can be calculated since the overpressure parameter λ_p of 0.78 is given. The actual pore pressure at 2000 ft would be:

$$P_p = S_v \times \lambda_p = 1720 \times 0.78 = 1342 psi$$

So the effective vertical stress is:

$$\sigma_v = S_v - P_p = 1720 - 1342 = 378psi$$

In general, σ_3 (minimum effective stress) is related to σ_1 (maximum effective stress) through the equation:

$$\sigma_1 = S_o + q\sigma_3$$

Because there is a lack of cohesive strength in the Earth's crust at the large scale we have:

$$\sigma_1 = q\sigma_3$$

$$\sigma_3 = \frac{\sigma_1}{q}$$

q (friction parameter function of the friction angle) is related to ϕ (friction angle) through the equation

$$q=\frac{1+sin\varphi}{1-sin\varphi}=\frac{1+sin(30^\circ)}{1-sin(30^\circ)}=3$$

For a normal faulting regime, $\sigma_V > \sigma_{Hmax} > \sigma_{hmin}$, where $\sigma_1 = \sigma_V$, $\sigma_2 = \sigma_{Hmax}$, $\sigma_3 = \sigma_{hmin}$, we can calculate σ_{hmin} to be:

$$\sigma_{hmin} = \frac{\sigma_V}{q} = \frac{378}{3} = 126psi$$

The total minimum horizontal stress is:

$$S_{hmin} = \sigma_{hmin} + P_p = 126 + 1342 = 1468psi$$

This procedure can be repeated for hydrostatic pressure (overpressure parameter λ_p of 0.44) to give

$$\sigma_v = S_v - P_p = 1720 - 880 = 840psi$$

$$\sigma_{hmin} = \frac{\sigma_V}{q} = \frac{840}{3} = 280psi$$

In [4]: import pandas as pd

```
excel_file = 'HW4.xlsx'
DataQ2 = pd.read_excel(excel_file, sheet_name=1)
DataQ2.head()
```

Out[4]:


	Location	Depth [ft]	Actual Pp [psi]	Normal Pp [psi]	Sv [psi]	Actual σν [psi]	Normal σν [psi]	Actual Shmin [psi]	Normal Shmin [psi]	Actual σhmin [psi]	Normal σhmin [psi]	Pore Pressure Gradient	dPp/dz	0.44	[psi/ft]
0	Surface	0	0.0	0	0	0.0	0	0.000000	0.000000	0.000000	0.000000 -	Overburden Gradient	dSv/dz	1.00	[psi/ft]
1	Seafloor	500	220.0	220	220	0.0	0	220.000000	220.000000	0.000000	0.000000 -	Overpressure Parameter	λр	0.78	[-]
2	Rock	1500	660.0	660	1220	560.0	560	846.666667	846.666667	186.666667	186.666667 -	Friction Angle	φ	30.00	[°]
3	TVD	2000	1341.6	880	1720	378.4	840	1467.733333	1160.000000	126.133333	280.000000 -	Friction Parameter Function	q	3.00	[-]

```
In [5]: import numpy as np
    import matplotlib.pyplot as plt

Depth = DataQ2['Depth [ft]']
    Pp_normal = DataQ2['Normal Pp [psi]']
    Pp_actual = DataQ2['Normal Shmin [psi]']
    Shmin_normal = DataQ2['Normal Shmin [psi]']
    Shmin_actual = DataQ2['Actual Shmin [psi]']
    Sv = DataQ2['Sv [psi]']


# Change plot size
fig = plt.gcf()
fig.set_size_inches(8, 8)

# Plot data
plt.plot(Pp_normal,Depth,'--b', label='Normal $P_p$')
plt.plot(Shmin_actual,Depth,'--b', label='Actual $p_p$')
plt.plot(Shmin_actual,Depth,'-g', label='$5_min$')
plt.plot(Sv,Depth,'-r', label='$5_v$')
# Plot tabels
plt.xlabel('Pressure [psi]')
plt.ylabel('Depth [ft]')
plt.legend()
# Axis range
plt.xlim([0, 2000])
plt.ylim([2000, 0])
plt.ylim([2000, 0])
plt.show()
```




```
In [6]: import numpy as np
         import matplotlib.pyplot as plt
         # Function for Mohr's Circle
         def plotMohr3D1(sig3,sig2,sig1):
             circle1X=[]
             circle1Y=[]
             circle2X=[]
             circle2Y=[]
             circle3X=[]
             circle3Y=[]
             for i in np.linspace(0,np.pi):
                 circle1X.append((sig2-sig3)/2*np.cos(i) + (sig3+(sig2-sig3)/2))
                 circle2X.append((sig1-sig2)/2*np.cos(i) + (sig2+(sig1-sig2)/2))
                 circle3X.append((sig1-sig3)/2*np.cos(i) + (sig3+(sig1-sig3)/2))
                 circle1Y.append((sig2-sig3)/2*np.sin(i) )
                 circle2Y.append((sig1-sig2)/2*np.sin(i) )
             circle3Y.append((sig1-sig3)//*np.sin(i) )
plt.plot(circle2X,circle2Y,'-',label=r'$\lambda_p=0.78$')
             # Plot Labels
             plt.xlabel(r'$\sigma \; [MPa]$')
             plt.ylabel(r'$\tau \; [MPa]$')
             # Plot layout
             plt.axis('square')
             plt.tight_layout()
             # Axis range
             plt.xlim([0, 1000])
             plt.ylim([0, 400])
         def plotMohr3D2(sig3,sig2,sig1):
             circle1X=[]
             circle1Y=[]
             circle2X=[]
             circle2Y=[]
             circle3X=[]
             circle3Y=[]
             for i in np.linspace(0.np.pi):
                 circle1X.append((sig2-sig3)/2*np.cos(i) + (sig3+(sig2-sig3)/2))
                 circle2X.append((sig1-sig2)/2*np.cos(i) + (sig2+(sig1-sig2)/2))
                 circle3X.append((sig1-sig3)/2*np.cos(i) + (sig3+(sig1-sig3)/2))
                 circle1Y.append((sig2-sig3)/2*np.sin(i) )
                 circle2Y.append((sig1-sig2)/2*np.sin(i) )
                 circle3Y.append((sig1-sig3)/2*np.sin(i) )
             plt.plot(circle2X,circle2Y,'--',label=r'$\lambda_p=0.44$')
             # Plot labels
             plt.xlabel(r'$\sigma \; [psi]$')
             plt.ylabel(r'$\tau \; [psi]$')
             # Plot layout
             plt.axis('square')
             plt.tight_layout()
             # Axis range
             plt.xlim([0, 1000])
             plt.ylim([0, 400])
         # Plot 2d Mohr Circles
         plotMohr3D1(0,126,378) # overpressure parameter of 0.78
         plotMohr3D2(0,280,840) # overpressure parameter of 0.44
         # Plot shear failure envelope
         phi = (30 / 180) * np.pi # calculate friction angle
         q = (1+np.sin(phi))/(1-np.sin(phi)) # calculate friction parameter function of the friction angle
        mu = (q-1)/(2*(q)**0.5) * calculate friction coefficient plt.plot([0,1000],[0, 1000 * mu],'k-',label=r'$\tau = 0.577 \sigma_n$')
         # Change plot size
         fig = plt.gcf()
         fig.set_size_inches(8, 6)
         # Plot legend
         plt.legend()
```

Out[6]: <matplotlib.legend.Legend at 0xc200350>



Find out the orientations of (a) a hydraulic fracture and (b) a shear fracture both created in a site subjected to stresses $S_v < S_{hmin} < S_{Hmax}$ where S_{Hmax} strikes E-W and $\mu = 0.8$.



The strike line is a line representing the intersection of the feature of interest with a horizontal plane. The magnitude of the strike (ϕ) is the angle between the strike line and north. Strike can be given in quadrant convention (N45°E) or in azimuth convention (a single three digit number ranging from 0 to 360° measured from the North in clockwise direction (045°).

The dip (δ) is the angle between a horizontal plane and the feature under consideration. Dip is given by the number $(0^{\circ}-90^{\circ})$ as well as a letter (N,S,E,W) with rough direction in which the bed is dipping downwards.

We have a reverse fault since $S_v < S_{hmin} < S_{Hmax}$

a) For hydraulic fracture,

Hydraulic fracture will propagate along a plane perpendicular to the least principal stress. In this case, the hydraulic fracture would propagate in the horizontal direction perpendicular to S_{ν} .

Strike (ϕ) = 090° (E-W)

Dip (δ) = 90°

b) For shear fracture,

Orientation of shear fracture (α) is expressed in degrees from a vertical plane perpendicular to S_{Hmax} :

$$\varphi = tan^{-1}(\mu) = tan^{-1}(0.8) = 38.7^{\circ}$$

$$\alpha = 45^{\circ} + \frac{\varphi}{2} = 45 + \frac{38.7^{\circ}}{2} = 64.3^{\circ}$$

The hanging wall block will move up along the direction of S_{Hmax} relative to the foot wall.

For shear fracture 1 (SF1),

Strike (ϕ) = 000° (N-S)


Dip (δ) = 25.7°W

For shear fracture 2 (SF2),

Strike (ϕ) = 000° (N-S)

Dip $(\delta) = 25.7^{\circ}E$

Find out the orientations of (a) a hydraulic fracture and (b) a shear fracture both created in a site subjected to stresses $S_{hmin} < S_{\nu} < S_{Hmax}$ where S_{Hmax} strikes W20°N and $\mu = 0.5$.



We have a strike-slip fault since $S_{hmin} < S_{v} < S_{Hmax}$

a) For hydraulic fracture,

Hydraulic fracture will propagate along a plane perpendicular to the least principal stress. In this case, the hydraulic fracture would propagate in a direction perpendicular to $S_H max$.

Strike (ϕ) = 110° (W20°N or E20°S)

Dip (δ) = 90°

b) For shear fracture,

Orientation of shear fracture (eta) is expressed in degrees from a vertical plane perpendicular to S_{Hmax} :

$$\varphi = tan^{-1}(\mu) = tan^{-1}(0.5) = 26^{\circ}$$

$$\beta = 45^{\circ} + \frac{\varphi}{2} = 45 + \frac{26^{\circ}}{2} = 58^{\circ}$$

For shear fracture 1 (SF1),

Strike (ϕ) = 078° (W12°S)

Dip (δ) = 90°

For shear fracture 2 (SF2),

Strike (ϕ) = 142° (W52°N)

Dip (δ) = 90°

For the following faults: (i) draw the corresponding points in a stereonet (lower hemisphere projection) map, (ii) convert to strike to azimuth convention, and (iii) draw equivalent geological map symbols.

```
a) N55°E, 45°SE
b) E20°S, 60°NE
c) N20°W, 25°SW
d) S10°W, 60°NW
```

```
In [7]: import matplotlib.pyplot as plt
         import matplotlib.transforms as mtransforms
         import numpy as np
         import mplstereonet
         # Basic quadrant and strike/dip parsing (https://github.com/joferkington/mplstereonet)
         print('Parse quadrant azimuth measurements')
         for original in ['N55E', 'E20S', 'N20W', 'S10W']:
            azi = mplstereonet.parse_quadrant_measurement(original)
             print('"{}" --> {:.1f}'.format(original, azi))
         print('\nParse quadrant strike/dip measurements.')
         def parse_sd(original, seperator):
             strike, dip = mplstereonet.parse_strike_dip(*original.split(seperator))
print('"{}" --> Strike: {:.1f}, Dip: {:.1f}'.format(original, strike, dip))
        parse_sd('N55E/45SE', '/')
parse_sd('E20S/60NE', '/')
parse_sd('N20W/25SW', '/')
parse_sd('S10W/60NW', '/')
         # Strike and dip data to be plotted
         strike =np.array([55,290,160,190])
         dip = np.array([45,60,25,60])
         legend = ['a) N55°E/45°SE','b) E20°S/60°NE','c) N20°W/25°SW','d) S10°W/60°NW']
         # Convert data to polar coordinates
         theta = (strike + 90)/180 * np.pi
         r = dip
         # Polar plot
         ax = plt.subplot(111, projection='polar')
         # Change plot size
         fig = plt.gcf()
         fig.set_size_inches(10, 10)
         # Plot size
         fig = plt.figure(figsize=(15, 20))
         # Polar plot properties
         ax.set theta zero location("N")
         ax.set_theta_direction(-1)
         ax.set_xticklabels(['$0°$'(N)', '$45°$', '$90°$ (E)', '$135°$', '$180°$ (5)', '$225°$', '$270°$ (W)', '$315°$'])
         ax.set_rlabel_position(70)
         # Axis range
         ax.set_ylim(0,90)
         for i in range(len(strike)):
             ax.scatter(theta[i], r[i],label=legend[i])
             ax.text(theta[i] * (1 + 0), r[i] * (1 + 0), '%d, %d' % (strike[i], r[i]))
         ax.legend(loc="center right",bbox_to_anchor=(0.8, 0, 0.5, 1))
         plt.show()
```

```
Parse quadrant azimuth measurements
 "N55E" --> 55.0
"E20S" --> 110.0
  "N20W" --> 340.0
"S10W" --> 190.0
 Parse quadrant strike/dip measurements.
 "NS5E/45SE" --> Strike: 55.0, Dip: 45.0
"E20S/60NE" --> Strike: 290.0, Dip: 60.0
"N20W/25SW" --> Strike: 160.0, Dip: 25.0
"S10W/60NW" --> Strike: 190.0, Dip: 60.0
                         315°
                                                                                                                         45°
                                                                                          290, 60
                                                                                                                                 \80
                                                                                                                          70
                                                                                                                   60
                                                                                                            \50
                                                                                                      \40
                                                                                               \30
                                 490, 60
                                                                                        \20

    a) N55°E/45°SE
    b) E20°S/60°NE
    c) N20°W/25°SW
    d) S10°W/60°NW

                                                                                  10
   270° (W)
                                                          160, 25
                                                                                             55, 45
                         225
                                                                                                                        135°
                                                                      180° (S)
a) N55°E, 45°SE
                                                         b) E20°S, 60°NE
                                                                                                                   a) N20°W, 25°SW
                                                                                                                                                                             a) S10°W, 60°NW
   N
↑
                                                             N
↑
                                                                                                                                                                                N
```

In a given reservoir under study stresses are $S_{hmin}=40MPa$, $S_{Hmax}=60MPa$, $S_v=45MPa$, $P_p=20MPa$, and S_{hmin} acts E-W. For each of the faults below, calculate (using the Mohr Circle method if possible) the normal and shear stress on the plane of the fault and then determine if the fault is prone to slip ($\mu=0.6$).

With $P_p = 20MPa$, we have:

$$\sigma_{hmin} = \sigma_3 = 20MPa$$
, $\sigma_{Hmax} = \sigma_1 = 40MPa$, $\sigma_v = \sigma_2 = 25MPa$

In general, the shear and normal effective stresses are given by:

$$\sigma_n = C + R \times \cos(2 \times \alpha)$$

$$\tau = R \times \sin(2 \times \alpha)$$

a) Fault with strike north-south, dip 65° to the east

With $S_{v}>S_{hmin}$ we have dip-slip normal

$$\begin{array}{l} C = \frac{\sigma_2 + \sigma_3}{2} = \frac{25 + 20}{2} = 22.5 MPa \\ R = \frac{\sigma_2 - \sigma_3}{2} = \frac{25 - 20}{2} = 2.5 MPa \\ \alpha = 65^{\circ} \\ \tau = 2.5 \times sin(2 \times 65^{\circ}) = 1.91 MPa \\ \sigma_n = 22.5 + 2.5 \times cos(2 \times 65^{\circ}) = 20.9 MPa \\ \frac{\tau}{\sigma_n} = 0.09 < 0.6 \text{ implies no slip} \end{array}$$

b) Fault with strike east-west, dip 35° to the north

With $S_{Hmax} > S_V$ we have dip-slip reverse

$$\begin{array}{l} C = \frac{\sigma_1 + \sigma_2}{2} = \frac{40 + 25}{2} = 32.5 MPa \\ R = \frac{\sigma_1 - \sigma_2}{2} = \frac{40 - 25}{2} = 7.5 MPa \\ \alpha = 55^{\circ} \\ \tau = 7.5 \times sin(2 \times 55^{\circ}) = 7.0 MPa \\ \sigma_n = 32.5 + 7.5 \times cos(2 \times 55^{\circ}) = 29.9 MPa \\ \frac{\tau}{\sigma_n} = 0.23 < 0.6 \text{ implies no slip} \end{array}$$


c) Fault with strike 060°, dip 90°

With $S_{Hmax} > S_{hmin}$ we have strike-slip left-lateral

$$\begin{array}{l} C = \frac{\sigma_1 + \sigma_3}{2} = \frac{40 + 20}{2} = 30MPa \\ R = \frac{\sigma_1 - \sigma_3}{2} = \frac{40 - 20}{2} = 10MPa \\ \alpha = 30^{\circ} \\ \tau = 10 \times sin(2 \times 30^{\circ}) = 8.7MPa \\ \sigma_n = 30 + 10 \times cos(2 \times 30^{\circ}) = 35MPa \\ \frac{\sigma}{\sigma_n} = 0.24 < 0.6 \text{ implies no slip} \end{array}$$

d) Fault with strike 030°, dip 25°

Oblique can't solve so easily...



```
In [8]: import numpy as np
            import matplotlib.pyplot as plt
           # Function for Mohr's Circle
def plotMohr3D(sig3,sig2,sig1):
                 circle1X=[]
                 circle1Y=[]
                 circle2X=[]
                 circle2Y=[]
                 circle3X=[]
                 circle3Y=[]
                 for i in np.linspace(0,np.pi):
                      irine|1X.append((sig2-sig3)/2*np.cos(i) + (sig3+(sig2-sig3)/2))
circle2X.append((sig1-sig2)/2*np.cos(i) + (sig2+(sig1-sig2)/2))
circle3X.append((sig1-sig3)/2*np.cos(i) + (sig3+(sig1-sig3)/2))
                      circle1Y.append((sig2-sig3)/2*np.sin(i) )
                       circle2Y.append((sig1-sig2)/2*np.sin(i) )
                       circle3Y.append((sig1-sig3)/2*np.sin(i) )
                 plt.plot(circle1X,circle1Y,'r')
plt.plot(circle2X,circle2Y,'g')
plt.plot(circle3X,circle3Y,'b')
                 # Plot labels
                 plt.xlabel(r'$\sigma \; [MPa]$')
plt.ylabel(r'$\tau \; [MPa]$')
                 # Plot layout
                 plt.axis('square')
                 plt.tight_layout()
                 # Axis range
                 plt.xlim([0, 50])
                 plt.ylim([0, 16])
            # Plot 2d Mohr Circles
            plotMohr3D(20,25,40) # overpressure parameter of 0.78
           # Change plot size
fig = plt.gcf()
            fig.set_size_inches(10, 15)
```

