Sparkle user guide

Koen van der Blom January 14, 2021

1 Quick start

Follow these steps:

- ?? Install Sparkle
- ?? Prepare your configuration environment
- ?? Execute commands

1.1 Installing Sparkle

- 1. Copy the Sparkle files to your desired directory
- 2. Install Python 3.5 (other 3.x versions may work, but were not tested with the packages included in the requirements.txt file.
- 3. Install Swig 3.0 With Anaconda: conda install swig=3.0
- 4. Install requirements.txt: pip install -r requirements.txt With Anaconda: /home/<username>/<anaconda_dir>/envs/<env_name>/bin/pip install -r requirements.txt
- 5. Install epstopdf as described in Section ??

1.2 Configuration

Configuring an algorithm has the following minimal requirements for the algorithm (for an example of a solver directory see Section ??):

- ?? Make the solver executable work on Grace
- ?? An algorithm wrapper called sprakle_smac_wrapper.py
- ?? A PCS (parameter configuration space) file
- The runsolver binary (e.g. from Examples/Resources/Solvers/PbO-CCSAT-Generic/)

Further, training and testing instance sets are needed (for an example of a solver directory see Section ??). For the purpose of testing whether your configuration setup works with Sparkle, it is advised to primarily use instances that are solved (relatively) quickly even with the default parameters.

1.2.1 Making your algorithm run on Grace

[inline] Add helpful tips when available Shell and Python scripts should work as is. If a compiled binary does not work, you may have to compile it on Grace and manually install packages on Grace that are needed by your algorithm.

1.2.2 Creating a wrapper for your algorithm

A template for the wrapper that connects your algorithm with Sparkle is available at Examples/Resources/Solvers/template/sparkle_smac_wrapper.py. Within this template a number of TODOs are indicated where you are likely to need to make changes for your specific algorithm. You can also compare the different example solvers to get an idea for what kind of changes are needed.

1.2.3 Parameter configuration space (PCS) file

The PCS (parameter configuration space) format¹ is used to pass the possible parameter ranges of an algorithm to Sparkle in a .pcs file. For an example see e.g. Examples/Resources/Solvers/PbO-CCSAT-Generic/PbO-CCSAT-params_test.pcs.

In this file you should enter all configurable parameters of your algorithm. Note that parameters such as the random seed used by the algorithm should not be configured and therefore should also not be included in the PCS file.

1.3 Executing commands

Executing commands in Sparkle is as simple as running them in the top directory of Sparkle, for example:

Commands/initialise.py

Do note that when running on a cluster additional arguments may be needed, for instance under Slurm the above command would change to:

srun -N1 -n1 -p graceTST Commands/initialise.py

In the Examples/ directory a number of common command sequences are given. For instance, for configuration with specified training and testing sets see e.g. Examples/configure_solver_pbo-ccsat.sh for an example of a sequence of commands to execute. Note that these example scripts should not be executed directly, but one command at a time, to give each command time to complete before starting the next one.

 $^{^1\}mathrm{See}$: http://aclib.net/cssc2014/pcs-format.pdf

2 File structure

2.1 General

Before doing anything, the following subdirectories are present in the Sparkle directory:

```
Commands/
Components/
Documentation/
Examples/
Settings/
Test_Cases/
```

Based on various Sparkle commands, the following additional subdirectories may be generated:

```
Configuration_Reports/
Extractors/
Feature_Data/
?? Instances/
LOG/
Performance_Data/
Records/
Reference_Lists/
?? Solvers/
Sparkle_Portfolio_Selector/
TMP/
```

2.2 A typical instance directory

An instance directory should look something like this:

```
Instances/
  Example_Instance_Set/
  instance_a.cnf
  instance_b.cnf
    ...
  instance_z.cnf
```

This directory simply contains a collection of instances, as example here SAT instances in the CNF format are given.

2.3 A typical solver directory

A solver directory should look something like this:

```
Solver/
Example_Solver/
solver
sparkle_smac_wrapper.py
parameters.pcs
runsolver
```

Here solver is a binary executable of the solver that is to be configured. The sprakle_smac_wrapper.py is a wrapper that Sparkle should call to run the solver with specific settings, and then returns a result for the configurator. In parameters.pcs the configurable parameters are described in the PCS format. Finally, runsolver is a binary executable of the runsolver tool. This allows Sparkle to make fair time measurements for all configuration experiments.

Note: Currently the runsolver binary has to be in every solver directory, it can be found in the Examples/Resources/Solvers/PbO-CCSAT-Generic/directory.

3 Selection

3.1 Requirements

3.1.1 Solver directory

An example solver directory, in this case for the SAT solver CSCCSat.

```
Solver/
  CSCCSat/
  CSCCSat
  sparkle_run_default_wrapper.py
```

3.1.2 sparkle_run_default_wrapper.py

The sparkle_run_default_wrapper.py has two functions that need to be implemented for each algorithm:

- print_command(instance_file, seed_str: str, cutoff_time_str: str)
- print_output(terminal_output_file)

print_command(...) should print a command line call that Sparkle can use to run the algorithm on a given instance file. Ideally, for reproducibility purposes, the seed provided by Sparkle should also be passed to the algorithm. If the algorithm requires this, the cutoff time can also be passed to the algorithm. However, in this case the cutoff time should be made very large. For instance by multiplying by ten with: cutoff_time_str = str(int(cutoff_time_str) * 10). This is necessary to ensure Sparkle stops the algorithm after the cutoff time, rather than the algorithm itself. By doing this it is ensured runtime measurements are always done by Sparkle, and thus consistent between algorithms that might measure time differently.

print_output(...) should process the algorithm output. If the performance measure is RUNTIME, this function only needs to output the algorithm status. For all QUALITY performance measures both the algorithm status and the solution quality have to be given. Run time is measured by Sparkle internally, but can be overwritten by the user if desired. They should be printed in formatted as in the example below:

```
quality = 8734
status = SUCCESS
```

3.2 Run solvers

The run_solvers command runs each solver on every instance (set) currently in the Sparkle platform for which there are no performance values yet.

4 Commands

[inline] Add missing subsections with details of other commands Currently the following commands are available in Sparkle (listed alphabetically):

```
add_feature_extractor.py
   add_instances.py
?? add_solver.py
   cleanup_current_sparkle_platform.py
   cleanup_temporary_files.py
   compute_features_parallel.py
   compute_features.py
   compute_marginal_contribution.py
?? configure_solver.py
   construct_sparkle_portfolio_selector.py
?? generate_report_for_configuration.py
   generate_report_for_test.py
   generate_report.py
?? initialise.py
   load_record.py
   remove_feature_extractor.py
   remove_instances.py
   remove_record.py
   remove_solver.py
   run_ablation.py
   run_solvers_parallel.py
   run_solvers.py
   run_sparkle_portfolio_selector.py
   run_status.py
   save_record.py
```

```
system_status.py
?? validate_configured_vs_default.py
```

Arguments in [square brackets] are optional, arguments without brackets are mandatory. Input in <chevrons> indicate required text input, {curly brackets} indicate a set of inputs to choose from.

4.1 add_solver.py

Add a solver to the Sparkle platform.

Arguments:

```
[--run-solver-later]
[--nickname <nickname>]
[--parallel]
--deterministic {0, 1}
<solver_source_directory>
```

4.2 configure_solver.py

Configure a solver in the Sparkle platform.

Arguments:

```
--solver <solver>
--instance-set-train <instance-set-train>
[--instance-set-test <instance-set-test>]
--validate
--ablation
```

Note that the test instance set is only used if the **--ablation** or **--validation** flags are given.

4.3 generate_report_for_configuration.py

Generate a report describing the configuration results for a solver and specific instance sets in the Sparkle platform.

Arguments:

```
--solver <solver>
[--instance-set-train <instance-set-train>]
[--instance-set-test <instance-set-test>]
```

Note that if a test instance set is given, the training instance set must also be given. When only a solver is given, Sparkle generates a report for the most recent configuration experiment with that solver.

4.4 initialise.py

Initialise the Sparkle platform, this command does not have any arguments.

4.5 run_ablation.py

Runs parameter importance between the default and configured parameters with ablation. This command requires a finished configuration for the solver instance pair.

Arguments:

```
--solver <solver>
[--instance-set-train <instance-set-train>]
[--instance-set-test <instance-set-test>]
```

Note that if no test instance set is given, the validation is performed on the training set.

4.6 validate_configured_vs_default.py

Test the performance of the configured solver and the default solver by doing validation experiments on the training and test sets.

Arguments:

```
--solver <solver>
--instance-set-train <instance-set-train>
[--instance-set-test <instance-set-test>]
```

5 Settings

5.1 Sparkle settings

Most settings can be controlled through Settings/sparkle_settings.ini. Possible settings are summarised per category in Sect. ??. For any settings that are not provided the defaults will be used. Meaning, in the extreme case, that if the settings file is empty (and nothing is set through the command line) everything will run with default values.

For convenience after every command Settings/latest.ini is written with the used settings. This can, for instance, be used to provide the same settings to the next command in a chain. E.g. for validate_configured_vs_default after configure_solver. The used settings are also recorded in the relevant Output/ subdirectory. Note that when writing settings Sparkle always uses the name, and not an alias.

5.1.1 Example sparkle_settings.ini

This is a short example to show the format, see the settings file in Settings/sparkle_settings.ini for more.

```
[general]
performance_measure = RUNTIME
target_cutoff_time = 60
```

```
[configuration]
  number_of_runs = 25
  [slurm]
  number_of_runs_in_parallel = 25
5.1.2 Names and possible values
     [general]
     performance_measure
     aliases: smac_run_obj
     values: {RUNTIME, QUALITY_ABSOLUTE (also: QUALITY})}
     target\_cutoff\_time
     aliases: smac_each_run_cutoff_time, cutoff_time_each_performance_computation
     values: integer
     penalty_multiplier
     aliases: penalty_number
     values: integer
     solution_verifier
     aliases: N/A
     values: {NONE, SAT}
     note: Only available for SAT solving.
     [configuration]
     budget_per_run
     aliases: smac_whole_time_budget
     values: integer
     number_of_runs
     aliases: num_of_smac_runs
     values: integer
     [smac]
     target_cutoff_length
     aliases: smac_each_run_cutoff_length
     values: {max} (other values: whatever is allowed by SMAC)
     [ablation]
```

racing

aliases: ablation_racing

values: boolean

[slurm]

number_of_runs_in_parallel

aliases: smac_run_obj

values: integer

clis_per_node aliases: N/A values: integer

note: Not really a Slurm option, will likely be moved to another section.

5.2 Priorities

Settings provided through different channels have different priorities as follows:

low Default – Default values will be overwritten if a value is given through any other mechanism;

medium File - Settings form the Settings/sparkle_settings.ini overwrite default values, but are overwritten by settings given through the command line:

high-1 Command line file – Settings files provided through the command line, overwrite default values and other settings files.

high-2 Command line – Settings given through the command line overwrite all other settings, including settings files provided through the command line.

5.3 Slurm (focused on Grace)

Slurm settings can be specified in the Settings/sparkle_slurm_settings.txt file. Currently these settings are inserted as is in any srun or sbatch calls done by Sparkle. This means that any options exclusive to one or the other currently should not be used (see Section ??).

5.3.1 Tested options

Below a list of tested Slurm options for srun and sbatch is included. Most other options for these commands should also be safe to use (given they are valid), but have not been explicitly tested. Note that any options related to commands other than srun and sbatch should not be used with Sparkle, and should not be included in Settings/sparkle_slurm_settings.txt.

- --partition / -p
- --exclude
- --nodelist

5.3.2 Disallowed options

The options below are exclusive to sbatch and are thus disallowed:

```
--array
```

- --clusters
- --wrap

The options below are exclusive to srun and are thus disallowed:

```
--label
```

5.3.3 Nested srun calls

A number of Sparkle commands internally call the srun command, and for those commands the provided settings need to match the restrictions of your call to a Sparkle command. Take for instance the following command:

```
srun -N1 -n1 -p graceTST Commands/configure_solver.py
--solver Solvers/Yahsp3 --instances-train Instances
/Depots_train_few/
```

This call restricts itself to the graceTST partition (the graceTST partition only consists of node 22). So if the settings file contains the setting --exclude=ethnode22, all available nodes are excluded, and the command cannot execute any internal srun commands it may have.

Finally, Slurm ignores nested partition settings for srun, but not for sbatch. This means that if you specify the graceTST partition (as above) in your command, but the graceADA partition in the settings file, Slurm will still execute any nested srun commands on the graceTST partition only.

6 Required packages

6.1 Sparkle on Grace

Grace is the computing cluster of the ADA group² at LIACS, Leiden University. Since not all packages required by Sparkle are installed on the system, some have to be installed local to the user.

6.1.1 epstopdf

The epstopdf package (or a package containing it) is required for Sparkle's reporting component to work (e.g. generate_report, generate_report_for_configuration), it can be installed in your user directory as follows:

1. Download epstopdf

```
wget http://mirrors.ctan.org/support/epstopdf.zip
```

²http://ada.liacs.nl/