

# **Technical note:** How create a SWAP file on a Linux server

Gilles Celli & Nicolas d'Oreye

## **RATIONALE:**

The present document explains how to create a swap file on a Linux computer e.g. when there is not enough RAM to process a MSBAS inversion.

The procedure was set up by Gilles Celli for the specific case of a server (named "dellrack") that had only 512 Gb of RAM at ECGS, thought it had 2 separate SSD (Samsung PM981 NVME of 1024GB).

When Kubuntu was installed on the server, a 128GB SWAP partition was allocated on the first SSD (/dev/nvmen0). Resizing this partition could be a risky task when a OS is already installed.

A solution is to add a 512GB swapfile. A drawback is that a SWAP file on a SSD could reduce the SSD'slifespan. A swap file on a mechanical Harddisc would be better, however the RAID partition is XFS formatted, which doesn't allow Swap file creation (hole error!).

So it was decided to create a 512GB swap file on /dev/nvme1 (second SSD)

Note: on Mac computer, swap should be automatic...

#### TABLE OF CONTENT

- Check swap first
- o Add additional swap file (not a partition!) to the second SSD on dellrack
- Mount SWAP file at boot
- o Enable ZSWAP 2023.06.08
- Edit /etc/default/grub
- Update grub
- o Tune Swap space settings (Swappiness, cache pressure)
- Change values of swappinness vfs cache pressure in /etc/sysctl.conf
- Resources

## CHECK SWAP FIRST

First we check the swap already used: this displays the 127GB swap partition on the first SS /dev/nvme0

#sudo swapon --show

```
NAME
                                                SIZE USED PRIO
                                     TYPE
/dev/nvme0n1p4
                                     partition 127,7G OB -2
```

#df -h

```
Filesystem Size Used Avail Use% Mounted on
tmpfs 51G 4,4M 51G 1% /run
/dev/nvme0n1p3 808G 164G 603G 22% /
tmpfs 251G 0 251G 0% /dev/shm
tmpfs 5,0M 4,0K 5,0M 1% /run/lock
/dev/nvme0n1p1 796M 23M 774M 3% /boot/efi
dellrack-data-pool 49T 640K 49T 1% /mnt/dellrack data
tmpfs 51G 64K 51G 1% /run/user/501
/dev/nvme0n1p2 5,0G 3,2G 1,9G 63% /media/nicolas/OS
/dev/nvme1n1 938G 515G 376G 58% /media/nicolas/Data
//hp-storeeasy.ecgs.welter/hp-D3602-Data RAID5 81T 71T 9,5T 89% /mnt/3602
//hp-storeeasy.ecgs.welter/hp-D3600-Data Share1 55T 47T 8,2T 86%
/mnt/3600
//syno-data.ecgs.welter/Syno Data 1 26T 6,4T 19T 26% /mnt/syno data 1
//syno-sar.ecgs.welter/DataSAR 44T 35T 9,3T 79% /mnt/syno sar
//hp-storeeasy.ecgs.welter/hp-D3601-Data RAID6 73T 63T 11\overline{1} 87% /mnt/3601
//hp-storeeasy.ecgs.welter/hp-1650-Data Share1 55T 41T 14T 75% /mnt/1650
//hpe1660.ecgs.welter/hp1660 73T 6,8T 67T 10% /mnt/1660
//hpe1660.ecgs.welter/D3610 91T 501G 91T 1% /mnt/3610
//syno-congo.ecgs.welter/DATARDC 11T 4,0T 6,5T 39% /mnt/syno congo
```

## ADD ADDITIONAL SWAP FILE (NOT A PARTITION!) TO THE SECOND SSD ON **DELLRACK**

```
#sudo mkdir /media/nicolas/Data/SWAP512GB
#sudo fallocate -1 512GB /media/nicolas/Data/SWAP512GB/swapfile
#sudo chmod 600 /media/nicolas/Data/SWAP512GB/swapfile
#sudo mkswap /media/nicolas/Data/SWAP512GB/swapfile
```

```
Setting up swapspace version 1, size = 512 GiB (549755809792 bytes)
no label, UUID=b5f15fd2-38f0-4ba6-8c86-b2cb58a957bc
```

#sudo swapon /media/nicolas/Data/SWAP512GB/swapfile

After enabling the swapfile it will show up with command swapon --show

```
#sudo swapon --show
```

```
NAME
                                  TYPE
                                            SIZE USED PRIO
/dev/nvme0n1p4
                                  partition 127,7G OB -2
/media/nicolas/Data/SWAP512GB/swapfile file 512G 0B
```

or check with: # free -h

```
total used free shared buff/cache available
Mem: 501Gi 4,4Gi 495Gi 80Mi 1,2Gi 494Gi
Swap: 639Gi 0B 639Gi
```

## MOUNT SWAP FILE AT BOOT

Edit /etc/fstab and check if the SSD disc is first mounted (/dev/nvme1n1 on mount /media/nicolas/Data)

Note: I had some issues mounting the SWAP file because the mount point of /dev/nvme1n1 was not present in /etc/fstab. /dev/nvme1n1 was only mounted when user "nicolas" logged in from KDE Plasma.

By adding the line UUID=6e48816a-67f2-4e07-bfd8-e6836f255deb /media/nicolas/Data ext4 errors=remount-ro 0 1 to /etc/fstab the partition was correctly mounted to /media/nicolas/Data and after that we could mount the 512GB swap file.

```
# /dev/nvme1n1 (Second SSD of two SSDs) which only contains Data & OS
UUID=6e48816a-67f2-4e07-bfd8-e6836f255deb /media/nicolas/Data
errors=remount-ro 0
```

The add the swap file by editing again /etc/fstab by adding the lines:

```
# Swap file of 512GB on second SSDs (dev/nvme1n1)
/media/nicolas/Data/SWAP512GB/swapfile none swap
                                                 sw 0
```

## ENABLE ZSWAP - 2023.06.08

- **ZSWAP:** The frontswap system hooks attempts to swap out pages and uses zswap as write-back-cache for a HDD/SSD swap device: An attempt is made to compress the page and if it contains poorly compressible data it is directly written to the disk. If the data is compressed, it is stored in the pool of zswap memory. If pages are swapped out of memory when the total compressed pages in RAM exceeds a certain size, the Least Recently Used (LRU) compressed page is written to the disk as it is unlikely to be required soon.
- Benefits: Very efficient use RAM and disk based swap. Minimizes Disk I/O by both reducing the number of writes and reads required (data is compressed and held in RAM) and by reducing the bandwidth of these I/O operations as the data is in a compressed form.
- Limitations: It is an enhancement of disk based swap systems and hence depends on a swap partition on the hard disk.

• Status: Merged into the 3.11 mainline linux kernel.

## **EDIT /ETC/DEFAULT/GRUB**

Add zswap.enabled=1 to line: GRUB\_CMDLINE\_LINUX\_DEFAULT

GRUB CMDLINE LINUX DEFAULT="quiet splashi zswap.enabled=1"

#### UPDATE GRUB

Finally, update Grub using the **update-grub** command.

sudo update-grub

## TUNE SWAP SPACE SETTINGS (SWAPPINESS, CACHE PRESSURE)

Firstly, check the value of the "swappiness" parameter, which indicates how often the system is going to swap data out of the RAM to the added swap space. The parameter's value will lie between "0" and "100".

By default it's 100:

cat /proc/sys/vm/swappiness

100

Another parameter's value that we are going to tune is "vfs\_cache\_pressure". This parameter controls the cache dentry and inode information.

#cat /proc/sys/vm/vfs cache pressure

100

## CHANGE VALUES OF SWAPPINNESS VFS CACHE PRESSURE IN /ETC/SYSCTL.CONF

Edit /etc/sysctl.conf and add following lines:

```
# Gilles - added vm.max map count and swappiness and cache pressure -
2023.06.01
# See: https://www.digitalocean.com/community/tutorials/how-to-add-swap-
space-on-ubuntu-22-04
vm.max_map_count=524288
vm.swappiness=20
vm.vfs cache pressure=40
```

## Activate with command (or reboot):

```
sudo sysctl -p
```

# **RESOURCES**

https://ubunlog.com/en/mejorar-rendimiento-ubuntu-gracias-zswap/

https://askubuntu.com/questions/471912/zram-vs-zswap-vs-zcache-ultimate-guide-when-touse-which-one

https://linuxhint.com/add-swap-space-ubuntu-22-04/

https://www.digitalocean.com/community/tutorials/how-to-add-swap-space-on-ubuntu-22-04