

Ərk Scripting and Commands

A guide for using ∂rk commands, and writing scripts Version 0.831

Summary			
Connection Scripts and "Callable" Scripts	2		
Miscellany			
Script Editor			
•			
IRC Commands	,5		
/away [MESSAGE]			
/back			
/invite CHANNEL NICKNAME			
/join CHANNEL [KEY]			
/list [TERMS]			
/me TEXT			
/mode TARGET MODE [ARGUMENTS]	•		
/msg TARGET MESSAGE			
/nick NICKNAME /notice TARGET MESSAGE			
/notice TARGET MESSAGE /oper USERNAME PASSWORD			
/part CHANNEL [MESSAGE]	,		
/quit [MESSAGE]	,		
/quit [MESSAGE] /send MESSAGE	,		
/time [SERVER]	,		
/topic CHANNEL TEXT			
/version SERVER [SERVER]			
/who TEXT			
/whois NICKNAME	-		
/whowas NICKNAME [MAXIMUM ENTRIES] [SERVER]			
Ərk Commands	· · · · · · · · · · · · · · · · · ·		
/alias NAME MESSAGE			
/argcount NUMBER MESSAGE			
/clear	,		
/connect [SERVER] [PORT]	-		
/connectscript SERVER [PORT]	-		
/edit [FILENAME]			
/exit	-		
/help	-		
/macro NAME ARG_COUNT MESSAGE	10		
/macrohelp NAME MESSAGE	1:		
/macrousage NAME MESSAGE	1:		
/msgbox MESSAGE	1:		
/preferences	1:		
/print MESSAGE	1:		
/reconnect [SERVER] [PORT]	1:		
/refresh	1:		
/ressl [SERVER] [PORT]	1:		
/script FILENAME [ARGUMENT]	12		
/settings	12		
/ssl [SERVER] [PORT]	12		
/style FILENAME	12		
/switch [WINDOW_NAME]	12		
/unmacro NAME	12		
/wait TIME	13		
Macro examples	14		

Summary

Much like other popular IRC clients, users can input commands into the chat input widget to control the ∂ rk IRC client. To use these commands, type the command, followed by any arguments, into the same widget that you enter chat text, and press the enter button.

To execute multiple commands at the same time, ∂ rk also features scripts. Multiple commands (one per line) can be entered into a text file, and ∂ rk will execute the commands in that file. Scripts can either be executed directly by using the <code>/script</code> command, or can be executed automatically on connection to a specific server.

If a script contains a line without a command, and only contains text, the text will be sent as a message to the window that was used to call the script; if it's a channel window, it will be sent as a public message to the channel, and it's a private chat window, it will be sent as a chat message to the user you're chatting with. If the script is called from a server console window (or executed with the editor or by clicking the "Run Script" button) the text will not be sent as a message. Macros that "resolve" to plain text (that is, if the macro does not execute a command) will also be sent as a message if called from a channel or private chat window, and will not be sent if called from a server console window.

Connection Scripts and "Callable" Scripts

Ork uses two different kinds of scripts: connection scripts (which can be automatically executed upon connection to a server, and are set in the connection dialog) and "callable" scripts (scripts that are executed by the /script command or the "Run Script" button on non-chat windows).

Connection scripts are executed with *no* arguments, and, thus, can't use the <code>/argcount</code> command (if this command is called, it is simply ignored). Connection scripts also can't use the <code>/msgbox</code> command. Other than these two exceptions, they function just like other scripts.

"Callable" scripts are executed with whatever arguments are passed to the /script command; scripts executed with the "Run Script" button are executed with no arguments (calls to /argcount will be executed, however, any script using the command to look for anything other than zero (0) arguments will stop execution).

Miscellany

Ərk scripts have the ".erk" file extension. When using the /script command, the file extension does not have to be included; when looking for the file, Ərk will append the file

extension if necessary. Scripts saved with the **Script Editor** will *always* have the ".erk" file extension.

Ork will always execute the commands on the server associated with the window that called the script (and connection scripts will always execute on the server being connected to); to execute scripts on any server the client is connected to, use the **Script Editor**, accessible with the **/edit** command.

By default, ∂ rk will look for scripts in the 'scripts' subdirectory in the 'settings' directory. If ∂ rk is launched with the --scripts command-line flag (with a different directory name as an argument), ∂ rk will use this directory instead of the default. This will also change the default save directory for the **Script Editor**, as well as where it looks for installed scripts.

Macros created with the /macro command can be optionally saved and reloaded every time Θ rk is ran; this behavior is enabled by default. To turn this off (that is: do not save macros or reload them on start), uncheck the "Save macros" option in the "Preferences" dialog.

Script Editor

Ərk features a built-in script editor. It can open, edit, and save scripts, execute them on any server Ərk is connected to, and features syntax highlighting. To open the editor, use the **/edit** command, or click on the "Script Editor" entry in the "Settings" menu.



- **1. Menu bar.** Here you can select scripts to open, save any new scripts or edits, and the normal tools you'd expect to find in a text editor. The "Insert Command" menu contains shortcuts to insert commonly used commands.
- **2. File name.** The name of the script being edited.
- 3. **Execute.** Clicking this button executes the script in the editor on the selected Θ rk client connection.
- **4. Client selector.** This contains a list of all the servers that ∂ rk is connected to, allowing you to select which connection you want to execute the script on. The hostname of the server, followed by the nickname in use on that server, is displayed.
- 5. **Open connection script.** This will load the connection script for the currently selected client. If one does not exist, the editor will be set up to edit and save a new one.
- 6. **Editor.** Here, you can type your script, or edit any script you open. It features syntax highlighting (comments, commands, channel names, and alias variables are colored differently from the rest of the text). Currently, there is no option to customize the colors used; this will change in future versions.
- **7. Client details.** This displays the hostname/IP address used to connect to the currently selected client, as well as the nickname in use.

IRC Commands

The these commands are for controlling the IRC connection (for example, joining and leaving channels, sending chat messages, etc); these commands should be familiar to users of other IRC clients such as mIRC or HexChat. Three commands (/invite, /part and /topic) will behave differently depending on where the command is entered; it will behave one way if it is entered into a chat window (for private chat or channel chat) or if it's entered into a console window (the window which displays data sent by the connected IRC server). One command, /me, cannot be entered into a non-chat window.

Called from any window

/away [MESSAGE...]

Sets the client to **AWAY**. If MESSAGE is included, **MESSAGE** will be sent to any user that sends a private message to the client.

Called from any window

/back

Sets the client to status to "back", and disables /away functionality.

Called from a chat window

/invite [CHANNEL] NICKNAME

Invites NICKNAME to the current channel if

CHANNEL is omitted; invites NICKNAME to CHANNEL

if a channel is included.

Called from any other window

/invite CHANNEL NICKNAME

Invites NICKNAME to CHANNEL.

Called from any window

/join CHANNEL [KEY]

joins **CHANNEL**. If **KEY** is included, it will be passed to the server as part of the join request.

Called from any window

/list [TERMS]

Displays a list of all channels on the server if **TERMS** is omitted; displays a list of channels matching **TERMS** if **TERMS** is included. **TERMS** can contain wildcards such as * or ?.

Called from a chat window

Called from any other window

/me TEXT

Sends **TEXT** to the current chat as a CTCP action message. The command can *only* be called from a chat window.

Called from a chat window

/mode [TARGET] MODE [ARGUMENTS]

Sets a **MODE** on the current channel if **TARGET** is omitted; sets a channel or user **MODE** if **TARGET** (which can be a channel or nickname) is included.

Called from any other window

/mode TARGET MODE [ARGUMENTS]

Sets a **MODE** on **TARGET** (which can be a channel or nickname).

Called from any window

/msg TARGET MESSAGE...

Sends a private message to **TARGET** (which can be a channel or a nickname).

Called from any window

/nick NICKNAME

Changes NICKNAME. If someone is already using NICKNAME, an error is displayed to the client.

Called from any window

/notice TARGET MESSAGE...

Sends a **NOTICE** to **TARGET** (which can be a channel or a nickname).

Called from any window

/oper USERNAME PASSWORD

Logs into a server operator account using **USERNAME** and **PASSWORD**.

Called from a chat window

/part [CHANNEL] [MESSAGE]

Leaves the current channel if **CHANNEL** is omitted; leaves **CHANNEL** if a channel is included. **MESSAGE** is the message displayed to other users when leaving; **MESSAGE** is optional.

Called from any other window

/part CHANNEL [MESSAGE]

Leaves **CHANNEL**. **MESSAGE** is the message displayed to other users when leaving; **MESSAGE** is optional.

Called from any window

/quit [MESSAGE...]

Disconnects from the current server. If **MESSAGE** is included, this will be sent to any channels the client is in before it disconnects.

Called from any window

/send MESSAGE

Sends **MESSAGE** to the server as a raw text; the outgoing message will not be altered. This is to allow the client to send messages to the server that the client doesn't normally support.

/time [SERVER]

Displays local time for the server currently connected to, or the **SERVER** specified.

Called from a chat window

Called from any other window

/topic [CHANNEL] TEXT...

/topic CHANNEL TEXT...

Sets the topic for the current channel if **CHANNEL** is omitted; sets the topic for another channel if **CHANNEL** is included.

Sets the topic for **CHANNEL**.

Called from any window

/version SERVER [SERVER...]

Requests server software version information from one or more **SERVERS**.

Called from any window

/who TEXT

Displays a list of users who's nickname matches **TEXT**.

Called from any window

/whois NICKNAME

Displays information about a specific user using **NICKNAME**.

Called from any window

/whowas NICKNAME [MAXIMUM ENTRIES] [SERVER]

Displays information about users with a **NICKNAME** that no longer exists.

Ərk Commands

The rest of the commands control the Ərk client software itself. Most of these commands can be entered into any window; however, the /help command will display slightly different output depending on what kind of window the command is called from. Five commands, /argcount, /alias, /_alias, /msgbox, and /wait, can't be called by any window, and can only be called from scripts. If called with no arguments, the /connect, /reconnect, /ressl, and /ssl commands will open the "Connect" dialog with the appropriate options pre-selected.

If a "script only" command is called with the incorrect number of arguments or an argument in incorrect type (for example, calling /wait with a non-number argument), script execution will stop immediately and an error message with the reason for the error will be displayed.

Available only for scripts

/alias NAME MESSAGE...

Creates a new alias (called an "alias variable" in this document). Any script or command ran after this one (including the commands that follow the <code>/alias</code> command) that contains a dollar sign followed by <code>NAME</code> (<code>\$NAME</code>) will have that instance replaced with <code>MESSAGE</code>. If the interpolation symbol (\$) is included in NAME, it will be stripped, allowing for use of the alias variable normally (thus, if the command <code>/alias *EXAMPLE My message</code> is executed, using the alias variable would referenced with <code>\$EXAMPLE</code>, not <code>\$\$EXAMPLE</code>). This command is <code>only</code> available for use in scripts; however, alias variables are interpolated into <code>any</code> input, including the text typed into the text input widget. Alias variables are "global"; once created, they are usable in any script or command input. Alias variables can also be overloaded (or overwritten) by any other script.

Available only for scripts

/_alias NAME MESSAGE...

Creates a new alias (called an "alias variable" in this document). Unlike the **/alias** command, this alias variable is *not* exported for use in other scripts/commands (thus, it is not "global"); this alias will only be interpolated for the script that it is defined it.

Available only for scripts

/argcount NUMBER MESSAGE...

Checks to make sure that a script is called with the proper **NUMBER** of arguments; if not enough or too many arguments are passed to the script, **MESSAGE** is displayed and script execution stops immediately. This command cannot be called from connection scripts.

/clear

Clears the current chat display. If settings that alter the display of the chat text (such as adding/removing/changing timestamps or changing the chat's style) the clearing will be "undone", and previous chat will again be viewable. If called from the script editor, or the "Run Script" button, the server console will be cleared.

Called from any window

/connect [SERVER] [PORT]

Causes the client to connect to an IRC **SERVER**. If **PORT** is omitted, a default of 6667 is used. If **SERVER** and **PORT** is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

/connectscript SERVER [PORT]

Opens the connect script for **SERVER** and **PORT** and executes it. If **PORT** is excluded, a default port of 6667 is assumed. Alternately, the **SERVER** and **PORT** can be passed to this command in the "**SERVER**: **PORT**" format.

Called from any window

/edit [FILENAME]

Opens up the built-in script editor; if a **FILENAME** is passed as an argument, the **FILENAME** is loaded into the script editor. If a complete path to **FILENAME** is not provided, the client will look in the scripts directory (in **settings\scripts**, or set by the **--scripts** command-line flag) for the file; the "**.erk**" file extension can be omitted.

Called from any window

/exit

Disconnects from all servers and exits the client.

Called from a chat window	Called from any other window
/help	/help
Displays a list of commands useful in channel and private message sessions, as well as all macros.	Displays a list of all commands and macros.

/macro NAME ARG COUNT MESSAGE...

Creates a macro¹, allowing for new, custom command creation. **NAME** is the command that will trigger the command (in the form /NAME), ARG_COUNT is the number of arguments that the macro will accept, and **MESSAGE** is the output of the macro, which will be processed like a command. If ARG_COUNT is set to * (asterix), the macro will accept any number of arguments (including zero). If a macro is called with an incorrect number of arguments, an error is displayed, and the macro will not run.

Macros cannot have the same NAME as an existing command.

Arguments passed to the macro are interpolated into **MESSAGE** much like arguments to the **/script** command: instances of **\$1** will be replaced with the first argument, **\$2** with the second, and so on. There are other optional symbols that can be interpolated into **MESSAGE**:

SYMBOL	REPLACED WITH
\$+	All arguments
\$-	All arguments except for the first argument
\$NICK	The nickname the client is using
\$USERNAME	The username the client is using
\$REALNAME	The real name the client is using
\$HOSTNAME	The hostname of the server the client is connected to; if that is unknown, the server and port, delimited by a colon
\$SERVER	The IP address or hostname used to connect to the server the client is connected to
\$PORT	The port address on the server used to connect to the server the client is connected to
\$WHERE	If the window the macro is called from is a server console, the hostname or server and port of the server. If the window the macro is called from is a channel or private chat, the name of the channel or the user being chatted with

If a macro using **NAME** already exists, it will be overwritten with the new macro.

For example, many IRC clients have included a macro called /trout, which, when called with a nickname as an argument, sends a CTCP action message to the current chat describing the user "hitting" the targeted nickname with a trout. To create this macro, you would issue this command:

/macro trout 1 /me slaps \$1 with a trout

To call this macro (and "slap" your friend Bob with said trout), you could issue the command /trout Bob, which would send the command /me slaps Bob with a trout.

^{1 &}quot;A macro...is a rule or pattern that specifies how a certain input should be mapped to a replacement output." *Wikipedia*

/macrohelp NAME MESSAGE...

Sets the text displayed for the NAMEd macro when the /help command is used.

Called from any window

/macrousage NAME MESSAGE...

Sets the argument description for the **NAME**d macro when the **/help** command is used or when the macro is called with an incorrect number of arguments.

Available only for scripts

/msgbox MESSAGE...

Displays a message box with a custom MESSAGE.

Called from any window

/preferences

Opens the "Preferences" dialog.

Called from any window

/print MESSAGE...

Displays **MESSAGE** in the client's current window. If **/print** is called from a window, the **MESSAGE** will be displayed in that window; if **/print** is called by any other method (like via the "Run Script" button, or from the script editor), the **MESSAGE** will be displayed in the server's console window.

Called from any window

/reconnect [SERVER] [PORT]

Causes the client to connect to an IRC **SERVER**, with the option to reconnect upon disconnection turned on.. If **PORT** is omitted, a default of 6667 is used. If **SERVER** and **PORT** is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

/refresh

Requests a new list of channels from the server, and stores the new list in an internal cache.

Called from any window

/ressl [SERVER] [PORT]

Causes the client to connect to an IRC **SERVER** via SSL/TLS, with the option to reconnect upon disconnection turned on. If **PORT** is omitted, a default of 6697 is used. If **SERVER** and **PORT** is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

/script FILENAME [ARGUMENT ...]

Opens FILENAME, reads its contents into memory, and executes it as a list of commands; each additional ARGUMENT, is passed to the script. Any errors found in the script are displayed to the current window.

ARGUMENTS can be used in the script much like /alias variables: \$1 is replaced with the first argument, \$2 with the second, and so on. To interpolate all ARGUMENTS as a single string, use \$0. ARGUMENTS are interpolated into the script before /alias variables. If a line in a script doesn't contain a valid command, it will be sent to the current window as chat text, just as if the user entered it as chat text; if the current window is a non-chat window, the text will be ignored. If a complete path to FILENAME is not provided, the client will look in the scripts directory (in settings\scripts, or set by the --scripts command-line flag) for the file; the ".erk" file extension can be omitted.

Called from any window

/settings

Opens the client's settings dialog.

Called from any window

/ssl [SERVER] [PORT]

Causes the client to connect to an IRC **SERVER** via SSL/TLS. If **PORT** is omitted, a default of 6697 is used. If **SERVER** and **PORT** is omitted, the connection dialog is displayed. The client's current nickname, username, and real name is used.

Called from any window

/style FILENAME

Loads a style file (created with the "Style Editor", accessible from the "Preferences" dialog) into the current chat. If a complete path to **FILENAME** is not provided, the client will look in the styles directory (in **settings**\ **styles**, or set by the **--styles** command-line flag) for the file.

Called from any window

/switch [WINDOW_NAME]

Switches the current displayed channel. If **WINDOW_NAME** is omitted, a list of available channels/private chats is displayed.

Called from any window

/unmacro NAME

Deletes a macro.

Available only for scripts

/wait TIME

Causes a script to pause for **TIME** seconds. This command is *only* available for use in scripts.

Macro examples

Greeter macro

Command /m

/macro hi 1 /msg \$WHERE Welcome to \$WHERE, \$1!

Creates a macro to welcome someone to whatever channel you're in. Pass the nickname of whoever you want to welcome to the channel as the first argument, and it will send a public message to channel welcoming them. For example, if you were in a channel named **#erk**, and you wanted to welcome a new user named Alice to the channel, you'd execute:

Description

/hi Alice

Which would send the following public message to **#erk**: "Welcome to #erk, Alice!"

Trout macro

Command

/macro trout 1 /me slaps \$1 with a trout.

Creates a macro to send the old classic message. Pass the nickname of the user you'd like to slap, and it will send a CTCP action message to the current channel or private chat. For example, to slap a user named Bob:

Description

/trout Bob

Which would send the following CTCP action message to the chat: "[your nickname] slaps Bob with a trout.

Special attention trout macro

Command

/macro trouts * /me slaps \$1 with a trout, and \$- too

Creates a macro to send a new classic message. Pass the nickname of the main target, and a short list of other targets to the macro to send the new CTCP action message. For example, to slap Bob, Alice, and Dave:

Description

/trouts Bob Alice and Dave

Which would send the following CTCP action message to the chat: "[your nickname] slaps Bob with a trout, and Alice and Dave, too"