

Ərk IRC Client, Version 0.840

Plugin Guide

A guide for writing plugins for the Ərk IRC Client

https://github.com/nutjob-laboratories/erk

Plugin Guide1			
Summary3			
Installing Ərk Plugins3			
Uninstalling Ərk Plugins			
Writing an Ərk Plugin			
Plugin Attributes			
name			
descriptiondescription	_		
author	_		
version	_		
sourcewebsite	_		
Plugin Methods			
load			
unloadunload			
tick			
received			
sentconnect.			
input			
public			
private			
join			
partnotice	-		
ctcp			
Built-In Methods			
autocomplete			
channels1	10		
console			
directory1			
exec			
log1			
msgbox1	12		
print			
scriptsend			
sysmsq			
topic			
uptime1	14		
userinput			
users			
	_		
Plugin Packages1			
Package Name			
Package Icon	. 7		
Plugin Icons			
Plugin Icons	L 7		
Plugin Icons	L7 L8		
Plugin Icons	L7 L8 L9		
Plugin Icons	L7 L8 L9 20		
Plugin Icons	L7 L8 L9 20		

Summary

An Θ rk *plugin* is a file containing one of more Python 3 classes that inherit from **erk.Plugin**. A *package* is a directory that contains one or more files containing Θ rk plugins, along with other optional files that either contain metadata or graphics. A plugin can be used to create new commands and features, automate functionality, and so much more.

In this document, the term "plugin" is used for both plugins and packages; if a distinction between the two terms is necessary, the correct term is used.

Installing Ork Plugins

Ork plugins "live" in a directory named "plugins", in the main Ork installation directory. To install a plugin, simply place it in the "plugins" directory. To install exported plugin packages created with the Ork editor, click on the "Install plugin" entry in the "Plugins" menu and select the zip file containing the package; the zip file will be extracted into Ork's plugin directory.

Uninstalling Ork Plugins

Delete (or otherwise remove) the plugin file or package from the "plugins" directory. Alternately, click on the "Uninstall plugin" entry in the "Plugins" menu.

Writing an Ərk Plugin

The first step is creating a new Python 3 class that inherits from **erk.Plugin**. To get access to this class, import it from Θ rk:

```
1 from erk import *
```

Then, create the rest of the class. The following plugin will do *nothing*, but it's a complete example that shows what a plugin should look like:

```
1 from erk import *
3 class ExamplePlugin(Plugin):
        def __init__(self):
 5
             self.name = "An Example Plugin"
 6
             self.description = "Example plugin for documentation"
7
8
        def received(self,client,line):
9
             pass
10
11
        def sent(self,client,line):
12
             pass
13
14
        def load(self):
15
             pass
16
17
        def unload(self):
18
             pass
19
20
        def input(self,client,name,text):
21
             pass
22
23
        def connect(self,client):
24
             pass
25
26
        def public(self,client,channel,user,message):
27
             pass
28
29
        def private(self,client,user,message):
30
             pass
31
32
        def notice(self,client,target,user,message):
33
             pass
34
35
        def join(self,client,channel,user):
36
             pass
37
38
        def part(self,client,channel,user):
39
             pass
40
41
        def tick(self,client):
42
             pass
43
44
        def ctcp(self,client,user,channel,tag,message):
45
             pass
```

Plugin Attributes

Plugins have only two *required* attributes: **name** and **description**. Plugins can also possess four other optional attributes: **author**, **version**, **source**, and **website**.

name

This is the name of the plugin. It must be unique (that is, no other loaded plugin can use the same name). It can contain spaces. All plugins are required to have a **name** attribute.

description

This describes the plugin. It can also contain spaces, but it does not have to be unique. All plugins are required to have a **description** attribute.

author

The name of the person (or persons) who created/maintain the plugin.

version

A string representing the plugin's version.

source

A URL to where users can obtain the source code or information about the source code of the plugin.

website

A URL where users can obtain the plugin, information about the plugin, or information about the person (or persons) who wrote the plugin.

Plugin Methods

There are thirteen methods a plugin can have; they are not required to have any specific methods, but *they must have at least one of the methods* to be a valid plugin.

Most of the methods are passed an instance of the Twisted IRC client as a first argument. This is the instance that Θ rk uses to communicate with the IRC connection associated with the event or window that triggered the method's execution. At this time, Θ rk uses version 20.3 of Twisted during development; the documentation for this object can be found at the Twisted website. The instance has been modified so that any outgoing messages are displayed in the client (so, if you use the \mathbf{msg} () method to send a PRIVMSG command, the message sent will be displayed in the appropriate channel or private chat window).

1 a a d	
load	
Arguments	None
Description	This method is executed as soon as the plugin is loaded into memory.
unload	
Arguments	None
Description	This method is executed when the plugin is unloaded from memory; if not otherwise unloaded, this method is executed when Θ rk shuts down.
tick	
Arguments	<pre>client (instance of twisted.words.protocols.irc.IRCClient)</pre>
Description	This method is executed every second the Θ rk client is connected to a server.
received	
Arguments	<pre>client (instance of twisted.words.protocols.irc.IRCClient), line (string)</pre>
Description	This method is executed every time the $\ \Theta rk$ client receives a line of data from the server.

¹twisted.words.protocols.irc.IRCClient

²https://twistedmatrix.com/documents/current/api/twisted.words.protocols.irc.IRCClient.html

sent

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

line (string)

Description This method is executed every time the Θ rk client sends a line of data to the

server.

connect

Arguments

client (instance of twisted.words.protocols.irc.IRCClient)

Description

This method is executed when the Ərk client is completes registration with a

server.

input

Arguments

client (instance of twisted.words.protocols.irc.IRCClient),
name (string), text (string)

Description

This method is executed whenever a user enters text into the Θ rk IRC client and presses enter. **name** contains the "name" of the window the text was entered into. If entered into a non-chat server console, **name** will be set to "_Server"; other wise, **name** will contain the name of the channel the text was entered into (if entered into a channel chat window) or the nickname of a user (if entered into a private chat window). **text** contains the text that was entered into the window.

This method is intended to be used to implement new commands for the Θ rk client. To prevent any further processing of user input, have this method return **True**. Be careful with this. It's trivially easy to implement a plugin that can prevent *any* user input at all:

```
1 def input(self,client,name,text):
2    return True
```

Only return **True** if no further processing of the text is required; for example, when implementing a custom command, returning **True** prevents the user's command input being sent to the server as a PRIVMSG.

Ork will try to detect any plugins that maliciously prevent user input and refuse to load them; this is not perfect (or even close to perfect) and should not be relied on.

public

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

channel (string), user (string), message (string)

Description This method is executed when the Θ rk client receives a public (channel) chat

message. **channel** contains the name of the channel the chat originated from. **user** contains information about the user that sent the message; this is

presented in the format provided by the server: nickname!

username@hostname. **message** contains the contents of the message sent.

private

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

user (string), message (string)

Description This method is executed when the Θ rk client receives a private chat

message. **user** contains information about the user that sent the message;

this is presented in the format provided by the server: **nickname!**

username@hostname. **message** contains the contents of the message sent.

join

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

channel (string), user (string)

Description This method is executed when the Θ rk client receives a channel join

notification. **channel** contains the name of the channel the user joined. **user** contains information about the user that joined; this is presented in the format provided by the convert nickname lucername@hestname.message

provided by the server: nickname!username@hostname. message

contains the contents of the message sent.

part

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

channel (string), user (string)

Description This method is executed when the Θ rk client receives a channel part

notification. **channel** contains the name of the channel the user left. **user** contains information about the user that left the channel; this is presented in the format provided by the server: **nickname!username@hostname**.

message contains the contents of the message sent.

notice

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

target (string), user (string), message (string)

Description This method is executed when the Θ rk client receives a notice message.

target contains the name of the user or channel the notice was sent to. user contains information about the user that sent the message; this is

presented in the format provided by the server: nickname!

username@hostname. **message** contains the contents of the message sent.

ctcp

Arguments client (instance of twisted.words.protocols.irc.IRCClient),

user (string), channel (string), tag (string), message (string)

Description This method is executed when the Θ rk client receives an unrecognized CTCP

message. **user** contains information about the user that sent the message;

this is presented in the format provided by the server: **nickname!**

username@hostname. **channel** contains the channel (or nickname) the message was sent from. **tag** contains the CTCP message tag sent in the

message. **message** contains the contents of the message sent.

Built-In Methods

Plugins also contain several built-in methods to interact with the 7rk IRC client.

autocomplete

Arguments match (string), replacement (string)

Returns Nothing

Description Adds an entry to the auto-completer. **match** is the text the auto-

completer should try to match to; **replacement** is what the auto-completer will output if a match is found. For example, assume that a plugin has created a new command, "/new", that takes one argument. To add this new command to the auto-completer, set **match** to "/new", and **replacement** to "/new" (the same as **match**, but with a space appended); if the user types "/ne" and hits tab, it will be replaced with "/new ", ready for the user to type in the command's argument. Entries added to the auto-completer will only work if the "Auto-complete"

Commands" option is enabled in the "Settings" dialog.

channels

Arguments None
Returns List

Description Returns a list of channels that Θ rk is in on the current IRC server. If

called before Θ rk is connected to a server, or if Θ rk is not in any

channels, this will return an empty list.

console

Arguments text (string)

Returns Nothing

Description Writes to the console window associated with the client that triggered

the plugin method's execution. This method will always fail in a plugin's

load() and unload() methods.

directory

Arguments None Returns Str

Description Returns the directory the package the plugin is located in, or the plugins

directory (if the plugin is a non-package). *This method cannot be called from __init__!* The internal value that this method relies on is

populated when the plugin is loaded into Θ rk; calling it from the __init__ method will cause a fatal error, and Θ rk will not start

properly.

exec

Arguments data (string)

Returns True if the command was processed, and False if not

Description Processes a string as if it were input by a user into the current chat's

text input. This allows plugins to execute commands without using the Twisted IRC client. If passed a string without a input command, the string will be passed to the server as chat. This method will always fail in a plugin's **load()** and **unload()** methods. For more information,

please see the Erk Scripting and Commands guide.

info

Arguments None Returns String

Description Returns a string containing the application name and version of the Θ rk

IRC client.

log

Arguments

name (string), text (string)

Returns

Nothing

Description

Writes text to a specific Θ rk chat window. log() can only write text to a window associated with the client that triggered the plugin method's execution. That means that log() can write to channel windows that the client has joined or private message sessions that are open and ongoing. log() cannot write text to windows associated with another client. log() cannot write text to windows associated with another client. log() cannot write text to windows associated with another window you want to write to; log() should contain the text you want to write. log() want to the log() if logging is turned on.

For example, to write to the chat window for the channel "#erk", you could use **self.log("#erk", "This is the text to write")**.

You cannot **log()** text to windows associated with another client. If you are trying to use **log()** from the **input()** method, for example, the only windows you can write to must be on the same server the window that triggered the method is associated with.

This method will always fail in a plugin's **load()** and **unload()** methods.

msgbox

Arguments

text (string)

Returns

Nothing

Description

Displays a message box stating **text** to the user. Like message boxes in most operating systems/GUI display libraries, the message box is modal, and must be dismissed by clicking "OK" before any further interaction with Θ rk is possible.



print

Arguments text (string)

Returns Nothing

Description Writes to the current window displayed in Θ rk, whether it's a server

console, channel chat, or private chat; if there is no current window, the method will fail silently and not display any text. This method will always

fail in a plugin's load() and unload() methods.

script

Arguments filename (string)

Returns Nothing

Description Executes an Θ rk script on a separate thread; control will return to the

plugin immediately after calling this method. Functionally, this works exactly like the /script command (see *Erk Scripting and Commands*). You can pass a complete file path and name, or a partial one; Ərk will look for the script in the assigned script directory, and will attach the ".erk" file extension if necessary. This method will always fail in a

plugin's load() and unload() methods.

send

Arguments data (string)

Returns Nothing

Description Sends a raw, unprocessed string to the current IRC server. This allows

plugins to send commands that are otherwise unsupported by Θrk .

sysmsg

Arguments text (string)

Returns Nothing

Description Writes a system message to the current window displayed in Θ rk,

whether it's a server console, channel chat, or private chat; if there is no current window, the method will fail silently and not display any text. This method will always fail in a plugin's **load()** and **unload()**

methods.

topic

Arguments channel (string)

Returns Str or None

Description Returns the topic of a given channel, if known. If the unknown, returns

None.

uptime

Arguments None Returns Int

Description Returns the length of time (in seconds) that Θ rk has been connected to

the IRC server that triggered the plugin's execution. This method will always return 0 (zero) in a plugin's **load()** and **unload()** methods.

userinput

Arguments text (string)


Returns String if the user entered text into the dialog and clicked "Ok" or None if

the user clicked "Cancel".

Description Opens a dialog to get information from the user; the dialog will contain

the plugin's name as the title, and **text** will appear before the text entry

widget.



users

Arguments channel (string)

Returns List

Description Returns a list of users in a given channel, without any status symbols (@

for operators, + for voiced users, etc), if Θ rk is present in that channel; if Θ rk is not present in the channel, or is not connected to an IRC server,

this method will return an empty list.

write

Arguments

name (string), text (string)

Returns

Nothing

Description

Writes text to a specific Θ rk chat window. write() can only write text to a window associated with the client that triggered the plugin method's execution. That means that write() can write to channel windows that the client has joined or private message sessions that are open and ongoing. write() cannot write text to windows associated with another client. name should contain the name of the channel or user nick whose window you want to write to; text should contain the text you want to write. text can contain HTML. Any text written will not be saved to the log, if logging is turned on.

For example, to write to the chat window for the channel "#erk", you could use **self.write("#erk","This is the text to write")**.

You cannot write() text to windows associated with another client. If you are trying to use write() from the input() method, for example, the only windows you can write to must be on the same server the window that triggered the method is associated with.

This method will always fail in a plugin's **load()** and **unload()** methods.

Plugin Packages

Plugins should be in their own directory in the "plugins" directory; this directory name can be any valid string for a Python module. This directory/plugin combination is called a "package".

For example, let's assume you have an Θ rk plugin named "myplugin.py". You've decided that you want to use "dans_plugins" as your package name. Create a directory in your Θ rk plugin directory named "dans_plugins", and copy/mode "myplugin.py" into the new directory. Your plugin package now looks like:

```
dans_plugins
    myplugin.py
```

This is all you need for a plugin package. However, how the package (and the plugins it contains) are displayed in the Θ rk GUI can be further customized.

Package Name



The plugin's Python name is displayed as the package's name by default. If you'd like to customize this (for example, change the package's name to include punctuation not normally allowed by Python), create a file named "package.txt" (or just "package") in the root directory of the package. Write the new name in this file as the first and only line. Using the above example, if you wanted your "dans_plugin" package to be displayed as "Dan's Erk Plugins", you would write "Dan's Erk Plugins" in the package's "package.txt".

Package Icon



To create a custom icon for a package, create a PNG file with the desired icon image and place it in the root directory of the package; change the package icon's filename to "package.png". This icon will be displayed in Θ rk's "Plugins" menu. Optional; if omitted, the default package icon will be used.

Plugin Icons



An icon can be specified for a plugin; this is the icon that will be displayed in Θ rk's "Plugins" menu. To set an icon, place a PNG with the same name as the plugin's class file name with the extension ".py" replaced with ".png" in the same directory as the plugin's package. The icon should be 25 pixels by 25 pixels to be displayed properly. Optional; if omitted, the default plugin icon will be used.

Use Ərk to generate a "blank" plugin


The Ork client has a command-line flag that will generate a "blank" plugin package, ready to be edited. It will create a directory with a Python-safe name in the user's current directory, and place all the files needed for a plugin in it.

```
C:\> python erk.py --generate "My brand new plugin"
Creating plugin package Mybrandnewplugin...
Done!
C:\>
```


The new package will not load into Θ rk; it must be edited. It includes a plugin source code skeleton ("plugin.py"), a package name file ("package.txt"), and default icons for both the package and plugin.

Once edited, simply copy the package directory into Θ rk's plugin directory.

Pluggər, the Ərk Plugin Editor



Ork has a built-in editor and development environment for writing plugins. By default, it is hidden; to make the editor accessible, open the "Preferences" dialog (on the "Settings" menu), and open the "Extensions" section. Turn on "Plugin development mode".






The next time the "Tools" menu is opened, it will feature a number of new options. The features will remain available until "Development mode" is turned off.

To start the editor, click on "Pluggər". The editor features colored syntax highlighting for Python code, and many of the features a code-oriented text editor would feature.

Development mode

Development mode also activates a number of features to make plugin development easier. Every plugin entry in the "Plugins" menu gets new options:



- **Edit**. Click to edit the plugin's source file in the editor.
- **Execute load()**. This will force the plugin's **load()** method to execute (if the plugin has a **load()** method).
- **Execute unload()**. This will force the plugin's **unload()** method to execute (if the plugin has an **unload()** method).


The main "Tools" menu also gets four new options:

- Pluggər. This opens the code editor.
- **Export Plugin**. Any installed plugins can be exported to a zip file; this file an then be used with the "Install" option.
- **Open plugin directory**. This will open Θ rk's plugin directory in the computer's file explorer.
- **Load new plugins**. This will load any new plugins, into memory. If the plugin hasn't been loaded, the plugin's **load()** method will be executed.


Features

The editor features almost everything you need to create plugins and plugin packages for Θ rk easily. These tools include a package creator, a tool to export installed plugin packages, and a plugin code generator.

All three of these features can be found in the "Tools" menu:



• **New package**. This brings up a dialog asking the user for a package name and description:



This information is used to create an all-new plugin package in Θ rk's plugin directory. This includes plugin and package icons, "package.txt", and a new plugin source file (named "plugin.py"); this file is opened in the editor, ready for editing.

- **Insert template**. This brings up a dialog asking for plugin information, and uses that data to generate a "blank" plugin, which is inserted wherever the cursor is in the editor.
- **Export package**. This will bring up a dialog allowing the user to select any installed package; the selected package will be placed in a zip archive and saved. This archive can now be installed with the "Install plugin" menu option in Ərk's "Plugins" menu.

Examples

"Hello, world!" plugin

This plugin will implement new command: "/hello". This will display the traditional "Hello, world!" message in the window where the command was entered; the new command will be added to the auto-completer as well.

```
1 from erk import *
 3 class HelloWorld(Plugin):
        def __init__(self):
5
             self.name = "Hello World plugin"
 6
             self.description = "Example plugin for documentation"
7
8
       def load(self):
            self.autocomplete("/hello","/hello")
9
10
        def input(self,client,name,text):
11
12
             # Look for our new command
13
             if text=="/hello":
14
15
16
                  # Found it! Now lets display our message
17
                  self.print("Hello, world!")
18
                  # Now, we return "True" to make sure that
19
                  # "/hello" isn't sent to the IRC server as
20
                  # a chat messages
21
22
                  return True
```

Note taking plugin

This plugin will introduce three new commands: "/note" (for adding a note), "/notes" (for displaying all stored notes), and "/clear" (for deleting all stored notes).

```
1 from erk import *
 2
3 class Notes(Plugin):
       def __init__(self):
 5
             self.name = "Note taking plugin"
 6
             self.description = "Example plugin for documentation"
7
             self.notes = []
8
       def load(self):
9
            self.autocomplete("/clear","/clear")
10
            self.autocomplete("/note","/note ")
11
12
            self.autocomplete("/notes","/notes")
13
        def input(self,client,name,text):
14
15
             # Tokenize the input
16
17
             tokens = text.split()
18
             # Handle the "/clear" command
19
             # This will delete any stored notes
20
21
             if len(tokens)>0 and tokens[0].lower()=="/clear":
22
                  self.notes = []
23
                  return True
24
             # Handle the "/note" command
25
             # This adds a new note to the stored notes
26
             if len(tokens)>0 and tokens[0].lower()=="/note":
27
                  tokens.pop(0)
28
                  n = ' '.join(tokens)
29
30
                  self.notes.append(n)
31
                  return True
32
             # Handle the "/notes" command
33
             # This will display any stored notes
34
             if len(tokens)>0 and tokens[0].lower()=="/notes":
35
36
                  # If there are no stored notes, let the
37
                  # user know and return
38
39
                  if len(self.notes)==0:
                       self.print("No notes found")
40
41
                       return True
42
                  # Format the note list using HTML
43
                  t = ""
44
                  for n in self.notes:
45
                       t = t + ""+n+""
46
                  t = t + ""
47
48
                  # Display the stored notes to the user
49
                  self.print(t)
50
```