

# **Modification History**

Revision	Date	Originator	Comments
2	08/05/2016	Zoom custom engineering	Support login zoom user

Note that the windows SDK from Zoom is distributed under a separate SDK agreement. Please make sure that you read the terms and conditions of the SDK agreement before using the SDK.



# 1.Introduction and Pre-Requisite


In order to use the SDK, you need to make sure that the RETS API and the mobile SDK is enabled in your account. If not, please contact your account rep or contact Zoom support. Our windows SDK is written in C++ - if you are writing a C#/.NET application, you need to make sure that you can call the C++ library functions from within your application space.

Note that our SDK support meeting services and do not support messaging currently.

• Get the SDK key and secret from your zoom account. This key/sec is same as the one used for mobile SDK



Get the REST API Key/Sec from your zoom account



• Call REST API "getbyemail" and this should return the user id and user token




# API Playground

API Endpoint:	https://api.zoom.us/v1/user/getbyemail
API Key: *	KuqoKDxjQT2dtdb9Yis47A
Pl Secret: *	ylQrZ6uPduFwZ2QpPyhtGawPytNqAEdKYdGd
Pata Type:	• JSON
lser Email Address: *	abc@test.us
₋ogin Type: <b>*</b>	● Work Email
Post Data:	View Source View Source



### 2.SDK Architecture and Workflow




Zoom SDK supports two options for user authentication.

- 1. You can pass the user id of the user to the SDK initialization and all the meetings will start on that user's account. This is referred to as API user
- 2. There are times it might be cumbersome to get the user id and you might want to distribute your app to all Zoom users in this case, you can ask the user to enter the Zoom login credentials (username /password) in your app and then pass it to the SDK. This is referred to as normal user



### API User join/start and leave


### API user Join/start and leave meeting Sequence





Normal User join/start and leave meeting


## Login(Normal) user Join/start and leave meeting Sequence





Normal User list/schedule/edit/delete meeting

## Normal user schedule list edit delete meeting Sequence





### 3.SDK Functions

### 3.1. Initialization

You can find these APIs in zoom\_sdk.h. Please call zoom sdk APIs in main ui thread for thread safe operation.

Initialize zoom sdk:

```
//Initialization code
     ZOOM_SDK_NAMESPACE::InitParam param_;
     param_.strWebDomain = _T("https://zoom.us/");
     aram_.emLanguageID = ZOOM_SDK_NAMESPACE::LANGUAGE_English;//ZOOM_SDK_NAMESPACE::SDK_LANGUAGE_ID
     //branding, if you don't config, use zoom as defeault
     param_.strBrandingName = "Zoom";
     param_.strSupportUrl = "https://support.zoom.us/";
     param_.hResInstance = your resource module handle;
     param_.uiWindowIconBigID = your windows title big icon id;
     param .uiWindowIconBigID = your windows title samll icon id;
     ZOOM_SDK_NAMESPACE::SDKError err = ZOOM_SDK_NAMESPACE::InitSDK(param_);
     switch (err)
13. {
     case ZOOM_SDK_NAMESPACE::SDKERR_SUCCESS:
        {
         //success
        }
        break:
     default:
         //error handle
         }
         break;
```

Cleanup zoom sdk before you exit your application.

```
    //Cleanup code
    ZOOM_SDK_NAMESPACE::CleanUPSDK();
```

### 3.2. Authentication Service

You should do authentication first when you start to use zoom sdk and include auth service interface.h

• Create authentication service



```
1. //Create Auth Service
2. ZOOM_SDK_NAMESPACE::IAuthService* pAuthService(NULL);
3. ZOOM_SDK_NAMESPACE::IAuthServiceEvent* pAuthServiceEvent;//implement yourself
4. ZOOM_SDK_NAMESPACE::SDKError err = ZOOM_SDK_NAMESPACE::CreateAuthService(&pAuthService);
5. if (ZOOM_SDK_NAMESPACE::SDKERR_SUCCESS == err && pAuthService)
6. {
7.  pAuthService->SetEvent(pAuthServiceEvent);
8.  //do you logic
9. }
```

#### Auth SDK

```
1.    //Auth sdk
2.    ZOOM_SDK_NAMESPACE::AuthParam authParam;
3.    authParam.appKey = L"your app key";
4.    authParam.appSecret = L"your app secret";
5.    pAuthService->SDKAuth(authParam);
6.
7.    //Auth sdk callback
8.    //implement yourself
9.    virtual void IAuthServiceEvent::onAuthenticationReturn(AuthResult ret) = 0;
```

### Login end user

```
1.  //Login end user
2.  ZOOM_SDK_NAMESPACE::LoginParam param_;
3.  param_.bRememberMe = true or false;
4.  param_.userName = L"your account";
5.  param_.password = L"your password";
6.  pAuthService->Login(param_);
7.
8.  //Login callback
9.  //implement yourself
10.  virtual void IAuthServiceEvent::onLoginRet(LOGINSTATUS ret, IAccountInfo* pAccountInfo) = 0;
```

### Logout end user

```
    //logout end user
    pAuthService->LogOut();
    //Logout callback
    //implement yourself
    virtual void IAuthServiceEvent::onLogout() = 0;
```

#### Destroy auth service

```
    //Destroy auth service
    ZOOM_SDK_NAMESPACE::DestroyAuthService(pAuthService);
```



## 3.3. Pre-meeting Service

If you want to use this service, include premeeting service interface.h.

• Create Pre-Meeting Service:

```
1. //Create premeeting service
2. ZOOM_SDK_NAMESPACE::IPreMeetingService* pPreMeetingService(NULL);
3. ZOOM_SDK_NAMESPACE::IPreMeetingServiceEvent* pPreMeetingServiceEvent(NULL);//implement yourself
4. ZOOM_SDK_NAMESPACE::SDKError err = ZOOM_SDK_NAMESPACE::CreatePreMeetingService(&pPreMeetingService);
5. if (ZOOM_SDK_NAMESPACE::SDKERR_SUCCESS == err && pPreMeetingService)
6. {
7.     pPreMeetingService->SetEvent(pPreMeetingServiceEvent);
8.     //do your logic
9. }
```

Schedule Meeting

```
//Schedule meeting
2. IScheduleMeetingItem* pScheduleMeetingItem = ZOOM_SDK_NAMESPACE::IPreMeetingService::CreateScheduleMee
    tingItem();
    if (pScheduleMeetingItem)
4. {
        //optional
         pScheduleMeetingItem->SetAllowJoinBeforeHost(true);
         pScheduleMeetingItem->SetMeetingPassword(password);
         pScheduleMeetingItem->SetUsePMIAsMeetingID(true);
         pScheduleMeetingItem->TurnOffVideoForHost(true);
         pScheduleMeetingItem->TurnOffVideoForAttendee(true);
         //
         pScheduleMeetingItem->SetStartTime(starttime)
         pScheduleMeetingItem->SetDurationInMinutes(duration);
         pScheduleMeetingItem->SetMeetingTopic(topic);
         pPreMeetingService->ScheduleMeeting(pScheduleMeetingItem);
         ZOOM_SDK_NAMESPACE::IPreMeetingService::DestoryScheduleMeetingItem(pScheduleMeetingItem);
    //Schedule meeting callback
    //implement yourself
   IPreMeetingServiceEvent
    virtual void onScheduleOrEditMeeting(PremeetingAPIResult result, UINT64 meetingUniqueID) = 0;
```

Edit Meeting



```
//Edit meeting
     IScheduleMeetingItem* pEditMeetingItem = ZOOM_SDK_NAMESPACE::IPreMeetingService::CreateScheduleMeeting
     if (pEditMeetingItem)
         //optional
         pEditMeetingItem->SetAllowJoinBeforeHost(true);
         pEditMeetingItem->SetMeetingPassword(password);
         pEditMeetingItem->SetUsePMIAsMeetingID(true);
         pEditMeetingItem->TurnOffVideoForHost(true);
         pEditMeetingItem->TurnOffVideoForAttendee(true);
         pEditMeetingItem->SetStartTime(starttime)
         pEditMeetingItem->SetDurationInMinutes(duration);
         pEditMeetingItem->SetMeetingTopic(topic);
         pPreMeetingService->EditMeeting(meetingUniqueID, pEditMeetingItem);
         {\tt ZOOM\_SDK\_NAMESPACE::IPreMeetingService::DestoryScheduleMeetingItem(pEditMeetingItem);}
18. }
20. //Edit meeting callback
21. //implement yourself
IPreMeetingServiceEvent
23. virtual void onScheduleOrEditMeeting(PremeetingAPIResult result, UINT64 meetingUniqueID) = 0;
```

Delete Meeting

```
    //Delete meeting
    pPreMeetingService->DeleteMeeting(meetingUniqueID);
    //Delete meeting callback
    //implement yourself
    IPreMeetingServiceEvent
    virtual void onDeleteMeeting(PremeetingAPIResult result) = 0;
```

List Meeting

```
    //List meeting
    pPreMeetingService->ListMeeting();
    //List meeting callback
    //implement yourself
    IPreMeetingServiceEvent
    virtual void onListMeeting(PremeetingAPIResult result, IList<UINT64 >* lstMeetingList) = 0;
```

Get meeting item by ID

Refer the header file for the details.

Destroy Pre-Meeting Service

```
    //Destroy premeeting service
    ZOOM_SDK_NAMESPACE::DestroyPreMeetingService(pPreMeetingService);
```



## 3.4. Meeting Service

If you want to use this service, include meeting service interface.h.

• Create meeting service

```
//Create meeting service
//Com_SDK_NAMESPACE::IMeeting Service vent* pMeeting Service Event;//implement yourself
//Com_SDK_NAMESPACE::SDKError err = ZOOM_SDK_NAMESPACE::Create Meeting Service (& pMeeting Service);
//Create meeting service
//implement yourself
//Create meeting Service Event;//implement yourself
//Create meeting Service Event;//implement yourself
//Create meeting Service PMeeting Service Event;//implement yourself
//Com_SDK_NAMESPACE::SDKERR_SUCCESS == err & pMeeting Service PMeeting Serv
```

Destroy meeting service

```
    //Destroy meeting service
    ZOOM_SDK_NAMESPACE::DestroyMeetingService(pMeetingService);
```

## 3.4.1. Meeting controller

• Start meeting for API user

```
//Start meeting for api user
ZOOM SDK NAMESPACE::StartParam startParam;
3. startParam.userType = ZOOM_SDK_NAMESPACE::SDK_UT_APIUSER;
4. ZOOM_SDK_NAMESPACE::StartParam4APIUser& apiuserParam = startParam.param.apiuserStart;
5. apiuserParam.userID = L"your user id, get this via RestAPI";
     apiuserParam.userToken = L"your user id, get this via RestAPI";
     apiuserParam.userName = L"your display name"
     apiuserParam.meetingNumber = 123456789;///you can schedule meeting via RestAPI
     apiuserParam.isDirectShareDesktop = false;///direct share desktop or not when you start meeting
10. apiuserParam.hDirectShareAppWnd = NULL;///direct share window or not when you start meeting
     pMeetingService->Start(startParam);
    //Start meeting callback
14. //implement yourself, for more details please read comments of IMeetingServiceEvent in head file
IMeetingServiceEvent
16. virtual void onMeetingStatusChanged(MeetingStatus status, int iResult = 0) = 0;
17. virtual void onUserJoin(IList<unsigned int >* lstUserID, const wchar_t* strUserList = NULL) = 0;
     virtual void onUserAudioStatusChange(IList<IUserAudioStatus* >* lstAudioStatusChange, const wchar_t* s
     trAudioStatusList = NULL) = 0;
```



#### Start meeting for End user

```
//Start meeting for end user
ZOOM_SDK_NAMESPACE::StartParam startParam;
startParam.userType = ZOOM_SDK_NAMESPACE::SDK_UT_NORMALUSER;
ZOOM_SDK_NAMESPACE::StartParam4NormalUser& normalParam = startParam.param.normaluserStart;
normalParam.meetingNumber = 0;//your meeting number or 0 for instance meeting
normalParam.isDirectShareDesktop = false;///direct share desktop or not when you start meeting
normalParam.hDirectShareAppWnd = NULL;///direct share window or not when you start meeting
pMeetingService->Start(startParam);
//Start meeting callback
//implement yourself, for more details please read comments of IMeetingServiceEvent in head file
IMeetingServiceEvent
virtual void onMeetingStatusChanged(MeetingStatus status, int iResult = 0) = 0;
virtual void onUserJoin(IList<unsigned int >* lstUserID, const wchar_t* strUserList = NULL) = 0;
virtual void onUserAudioStatusChange(IList<IUserAudioStatus* >* lstAudioStatusChange, const wchar_t* strUserList = NULL) = 0;
```

### • Join Meeting for API user

```
//Join meeting for api user
     ZOOM_SDK_NAMESPACE::JoinParam joinParam;
     joinParam.userType = ZOOM_SDK_NAMESPACE::SDK_UT_APIUSER;
     ZOOM SDK NAMESPACE::JoinParam4APIUser& apiParam = joinParam.param.apiuserJoin;
4.
     apiParam.meetingNumber = 123456789;//meeting number you want to join
     apiParam.userName = L"your display name";
     apiParam.psw = L"Meeting's password";
     apiParam.isDirectShareDesktop = false;///direct share desktop or not when you start meeting
     apiParam.hDirectShareAppWnd = NULL;///direct share window or not when you start meeting
     apiParam.toke4enfrocelogin = L"token for enforce login meeting";//if the meeting is just for signed us
     er.
     apiParam.participantId = L"participant Id";///for meeting participant report list, need web backend en
     pMeetingService->Join(joinParam);
     //join meeting callback
     //implement yourself, for more details please read comments of IMeetingServiceEvent in head file
     IMeetingServiceEvent
     virtual void onMeetingStatusChanged(MeetingStatus status, int iResult = 0) = 0;
     virtual void onUserJoin(IList<unsigned int >* lstUserID, const wchar_t* strUserList = NULL) = 0;
19. virtual void onUserAudioStatusChange(IList<IUserAudioStatus* >* lstAudioStatusChange, const wchar_t* s
     trAudioStatusList = NULL) = 0;
```

#### Join meeting for end user



```
//Join meeting for end user

    ZOOM_SDK_NAMESPACE::JoinParam joinParam;

     joinParam.userType = ZOOM_SDK_NAMESPACE::SDK_UT_NORMALUSER;
     ZOOM_SDK_NAMESPACE::JoinParam4NormalUser& normalParam = joinParam.param.normaluserJoin;
5. normalParam.meetingNumber = 123456789;//meeting number you want to join
normalParam.userName = L"your display name";

 normalParam.psw = L"Meeting's password";

     normalParam.isDirectShareDesktop = false;///direct share desktop or not when you start meeting
     normalParam.hDirectShareAppWnd = NULL;///direct share window or not when you start meeting
     pMeetingService->Join(joinParam);
//join meeting callback
13. //implement yourself, for more details please read comments of IMeetingServiceEvent in head file
14. IMeetingServiceEvent
15. virtual void onMeetingStatusChanged(MeetingStatus status, int iResult = 0) = 0;
16. virtual void onUserJoin(IList<unsigned int >* lstUserID, const wchar_t* strUserList = NULL) = 0;
     virtual void onUserAudioStatusChange(IList<IUserAudioStatus* >* lstAudioStatusChange, const wchar_t* s
     trAudioStatusList = NULL) = 0;
```

• Other interfaces

Please refer the Zoom SDK.chm

## 3.4.2. Meeting UI controller

You can get this controller after you have been in the meeting. If not, you can't use this controller.

Usage

```
//How to user meeting ui controller
2. ZOOM_SDK_NAMESPACE::IMeetingUIController* pMeetingUIController = pMeetingService->GetUIController();
if (pMeetingUIController)
{
    //control meeting ui, such as
    pMeetingUIController->EnterFullScreen(true, false); //Enter full screen mode
    pMeetingUIController->ExitFullScreen(true, false);//Exit full screen mode
    pMeetingUIController->ShowChatDlg(param_);//show chat
    pMeetingUIController->SwitchToVideoWall();//switch to video wall mode
    //for more details, you can read the IMeetingUIController comments or Zoom SDK.chm
}
```

# **3.4.3.** Meeting Configuration controller

You can set configuration before you call start/join meeting API. And if the meeting is ended or left, the configuration will be reset automatically.



Usage

## 3.4.4. Meeting Annotation controller

You can get this controller when someone or you are sharing. If not, you can't use this controller.

Usage

```
//How to user meeting annotation
2. ZOOM_SDK_NAMESPACE::IAnnotationController* pAnnoCtrl = pMeetingService->GetAnnotationController();
if (pAnnoController)
4. {
5.    //show zoom annotation bar
    pAnnoController->StartAnnotation(leftpos, toppos);
pAnnoController->StopAnnotation();
8.    //set color of the tools
9.    pAnnoController->SetColor(color);
10.    //set tool of the annotation
11.    pAnnoController->SetTool(type);
12.    //for more details, you can read the IAnnotationController comments in head file or Zoom SDK.chm
13. }
```

### Meeting Event

All of meeting event define at IMeetingServiceEvent. You can refer the header file or Zoom SDK.chm

### 3.5. Setting Service

If you want to user this service, include setting service interface.h.

• Usage



```
//How to use setting service
//Loom_SDK_NAMESPACE::ISettingService* pSettingService(NULL);
//Loom_SDK_NAMESPACE::SDKError err = ZOOM_SDK_NAMESPACE::CreateSettingService(&pSettingService);
//Loom_SDK_NAMESPACE::SDKERR_SUCCESS == err && pSettingService)
//Loom_SDK_NAMESPACE::DestroySettingService(pSettingService);
//Destroy setting service
//Destroy setting service
//Destroy setting service
//Destroy setting service
```