Université Libre de Bruxelles

Synthèse


Fluid mechanics II MECA-H-305

Auteur : Enes Ulusoy Professeur : Gérard Degrez

../../Builder/ulb.jpg

Appel à contribution

Synthèse Open Source



que si le cours change, la synthèse doit être changée en conséquence. On peut retrouver le code source à l'adresse suivante

https://github.com/nenglebert/Syntheses

Pour contribuer à cette synthèse, il vous suffira de créer un compte sur *Github.com*. De légères modifications (petites coquilles, orthographe, ...) peuvent directement être faites sur le site! Vous avez vu une petite faute? Si oui, la corriger de cette façon ne prendra que quelques secondes, une bonne raison de le faire!

Pour de plus longues modifications, il est intéressant de disposer des fichiers : il vous faudra pour cela installer LATEX, mais aussi git. Si cela pose problème, nous sommes évidemment ouverts à des contributeurs envoyant leur changement par mail ou n'importe quel autre moyen.

Le lien donné ci-dessus contient aussi le README contient de plus amples informations, vous êtes invités à le lire si vous voulez faire avancer ce projet!

Licence Creative Commons

Le contenu de ce document est sous la licence Creative Commons : Attribution-NonCommercial-ShareAlike 4.0 International (CC BY-NC-SA 4.0). Celle-ci vous autorise à l'exploiter pleinement, compte- tenu de trois choses :



- 1. Attribution; si vous utilisez/modifiez ce document vous devez signaler le(s) nom(s) de(s) auteur(s).
- 2. Non Commercial; interdiction de tirer un profit commercial de l'œuvre sans autorisation de l'auteur
- 3. Share alike; partage de l'œuvre, avec obligation de rediffuser selon la même licence ou une licence similaire

Si vous voulez en savoir plus sur cette licence :

http://creativecommons.org/licenses/by-nc-sa/4.0/

Merci!

Contents

1	Generalities			1
	1.1	Fundamental laws		1
		1.1.1	Mass conservation equation	2
		1.1.2	Newton's second law: Momentum equation	4
		1.1.3	Angular momentum equation	6
		1.1.4	Energy equation - First principle of thermodynamics	7
		1.1.5	Summary - Complementary equation	8
		1.1.6	Boundary conditions	13
	1.2	Specia	l cases	13
		1.2.1	General case	13

Chapter 1

Generalities

1.1 Fundamental laws

Reminder

Let's first remind the 3 basic principles of Fluid mechanics I:

- Mass conservation: The mass of a closed system remains constant in time. This is much a definition of a closed system than a principle. We have to notice that related to Einstein law of relativity, $E = mc^2$, mass must vary with energy. But if we exclude nuclear reactions, our approximation is valid. Indeed, the square of light velocity has a greater impact on energy than the mass term. If the energy exchange is huge like in nuclear reaction, mass vary, but in smaller energies domain (combustion for example), the mass can be considered as constant.
- Newton's law: the time rate of change of momentum of a closed system is equal to the sum of the forces applied on the system.
- First principle of thermodynamics: the time rate of change of the total energy of a closed system is equal to the sum of the power of the forces applied on the system and the thermal power provided to the system.

Useful equations

ch1/1.png

Let's consider the integral on a moving volume of a function depending on time and position $f(\vec{x},t)$. Imagine that Figure 1.1 represents the moving volume at initial time containing mass m. An infinitesimal part of that volume contains an infinitesimal mass $dm = \rho dV$, where ρ is mass density. We deduce the expression of the total mass at any time by that of the initial time

Figure 1.1
$$M(t_0) = \int_{V(t_0)} \rho(\vec{x}, t_0) dV \qquad \Rightarrow M(t) = \int_{V(t)} \rho(\vec{x}, t) dV \quad (1.1)$$

By considering $\rho(\vec{x},t)$ as $f(\vec{x},t)$, the derivative of the integral is given by

Reynolds transport theorem

$$\frac{d}{dt} \int_{V(t)} f(\vec{x}, t) \, dV = \int_{V(t)} \frac{\partial f}{\partial t} (\vec{x}, t) \, dV + \oint_{S(t) = \partial V(t)} f(\vec{x}, t) \vec{b} \, \vec{n} \, dS \tag{1.2}$$

where \vec{b} is the surface displacement velocity.

The second equation that will be used in the development is given by

Gauss theorem
$$\oint_{S=\partial V} \vec{a}\,\vec{n}\,dS = \int_V \nabla \vec{a}\,dV \eqno(1.3)$$

1.1.1 Mass conservation equation

If V(t) is the moving volume occupied by the closed system as time varies, then by definition of a closed system $\frac{dM(t)}{dt} = 0$. The corresponding equation using Reynolds transport theorem is

$$M(t) = \int_{V(t)} \rho \, dV \qquad \Rightarrow \frac{dM(t)}{dt} = \int_{V(t)} \frac{\partial \rho}{\partial t} \, dV + \oint_{S(t) = \partial V(t)} \rho \, \vec{b} \, \vec{n} \, dS = 0 \tag{1.4}$$

ch1/2.png

We have to express that this volume is not traversed by material. There is no flux of fluid and the particles in the volume are always the same. By definition, the infinitesimal distance traveled by the surface and the fluid are

$$d\vec{x} = \vec{b} dt \qquad and \qquad d\vec{x}' = \vec{u} dt \tag{1.5}$$

Figure 1.2 where \vec{u} is the fluid velocity. Under wich condition do we know that the fluid has not traversed the boundary? We have to define the relative dispolacement $d\vec{x}' - d\vec{x}$ of the fluid in regard to the fluid. For a closed system

$$(d\vec{x}' - d\vec{x}) \cdot \vec{n} = 0 \quad \Leftrightarrow \quad dt(\vec{u} - \vec{b}) \cdot \vec{n} = 0 \quad \Leftrightarrow \quad (\vec{u} - \vec{b}) \cdot \vec{n} = 0$$

$$\Rightarrow \quad \vec{b}\vec{n} = \vec{u}\vec{n}$$
(1.6)

Mass conservation equation for closed systems (integral form)

$$\int_{V(t)} \frac{\partial \rho}{\partial t} \, dV + \oint_{S(t) = \partial V(t)} \rho \underbrace{\vec{b} \, \vec{n}}_{=\vec{u} \, \vec{n}} \, dS = 0 \tag{1.7}$$

How to write this equation in a different way? Let's consider now a fixed open system composed of fluid particles in the fixed volume $V_0(t) = V(t_0)$. Similarly to the previous point, the mass variation in this fixed volume is expressed like

$$M_0(t) = \int_{V_0(t)} \rho \, dV \qquad \Rightarrow \int_{V_0(t)} \frac{\partial \rho}{\partial t} \, dV + \oint_{S_0(t) = \partial V_0(t)} \rho \, \vec{b} \, \vec{n} \, dS. \tag{1.8}$$

The volume integral expresses the variable mass in the fixed volume and the surface integral is nul due to the nul surface velocity (since the volume is fixed). This relation enables us to write the

Mass conservation equation for fixed open systems (integral form)

$$\frac{dM_0}{dt} + \underbrace{\oint_{S_0(t) = \partial V_0(t)} \rho \, \vec{u} \, \vec{n} \, dS = 0}_{\text{mass flow out of the system}} \tag{1.9}$$

Let's finally consider an arbitrary open system containing fluid particles in a moving volume $V_*(t)$ such that $V_*(t_0) = V(t_0) = V_0$. Similarly we have using the Reynolds transport theorem

$$M_*(t) = \int_{V_*(t)} \rho \, dV \qquad \Rightarrow \frac{dM_*(t)}{dt} = \int_{V_*(t)} \frac{\partial \rho}{\partial t} \, dV + \oint_{S_*(t) = \partial V_*(t)} \rho \, \vec{b} \, \vec{n} \, dS \tag{1.10}$$

Using the definition of the volume at $t = t_0$, we can equalize the volume integral with that of (1.7) to find

Mass conservation equation for arbitrary open systems (integral form)

$$\frac{dM_*(t_0)}{dt} + \oint_{S(t_0) = \partial V(t_0)} \rho(\vec{u} - \vec{b}) \, \vec{n} \, dS = 0$$
(1.11)

Let's now take (1.7) again and apply Gauss theorem

$$\int_{V(t)} \frac{\partial \rho}{\partial t} dV + \oint_{S(t) = \partial V(t)} \rho \underbrace{\vec{u} \, \vec{n}}_{\vec{a}} dS = 0 \quad \text{with} \quad \oint_{S(t)} \rho \underbrace{\vec{u} \, \vec{n}}_{\vec{a}} dS = \int_{V(t)} \nabla \rho \vec{u} \, dV \\
\Leftrightarrow \int_{V(t)} \left[\frac{\partial \rho}{\partial t} + \nabla \rho \vec{u} \right] dV = 0 \tag{1.12}$$

For this last equation to be true for all systems, the integrated term must be equal to zero

Mass conservation equation (differential form (1) - divergent form)

$$\frac{\partial \rho}{\partial t} + \nabla \rho \vec{u} = 0 \tag{1.13}$$

ch1/3.png

In order to find the second differential form, let's consider 2 points Q and P as described in Figure 1.3. The difference of density between the 2 points is

Figure 1.3

$$\rho_Q(t+dt) - \rho_P(t) = \rho(x_1 + dx_1, x_2 + dx_2, x_3 + dx_3, t + dt) - \rho(x_1, x_2, x_3)$$

$$= d\rho = \frac{\partial \rho}{\partial x_1} dx_1 + \frac{\partial \rho}{\partial x_2} dx_2 + \frac{\partial \rho}{\partial x_3} dx_3 + \frac{\partial \rho}{\partial t} dt$$
(1.14)

In general, the fluid particles at P(t) and Q(t+dt) are different. However, if $dx_1 = u_1 dt, dx_2 = u_2 dt, dx_3 = u_3 dt$, then the fluid particles at the 2 points are the same. By making appear these velocities in (1.14),

$$d\rho = \left(\frac{\partial \rho}{\partial x_1} u_1 + \frac{\partial \rho}{\partial x_2} u_2 + \frac{\partial \rho}{\partial x_3} u_3 + \frac{\partial \rho}{\partial t}\right) dt \tag{1.15}$$

Finally, after dividing by dt the 2 members of the equation, we obtain the definition of the time rate of change of density when I follow the fluid $\dot{\rho}$. As (1.13) can be expressed in term of indicial notation like

$$\frac{\partial \rho}{\partial t} + u_i \frac{\partial \rho}{\partial x_i} + \rho \frac{\partial u_i}{\partial x_i} = 0 \tag{1.16}$$

Replacing the sum of first and second term by $\dot{\rho}$ gives the last form

Mass conservation equation (differential form
$$(2)$$
 - substancial form)

$$\dot{\rho} + \rho \nabla \vec{u} = 0 \tag{1.17}$$

1.1.2 Newton's second law: Momentum equation

ch1/4.png

Momentum in this course is noted $\vec{P}(t)$. For closed systems,

$$\frac{d\vec{P}(t)}{dt} = \sum \vec{F} = \frac{d}{dt} \int_{V(t)} \rho \vec{u} \, dV \tag{1.18}$$

where $\rho \vec{u}$ is the momentum density. We will spell out the expression of the 2 members. First, the derivative, using the Reynolds transport theorem gives

Figure 1.4

$$\frac{d\vec{P}}{dt} = \int_{V(t)} \frac{\partial \rho \vec{u}}{\partial t} \, dV + \oint_{S(t) = \partial V(t)} \rho \vec{u}(\vec{u}\vec{n}) \, dS \tag{1.19}$$

This written in indicial notation

$$\frac{dP_i}{dt} = \int_{V(t)} \frac{\partial \rho u_i}{\partial t} \, dV + \oint_{S(t) = \partial V(t)} \underbrace{\rho u_i u_j}_{tensor: \vec{u} \otimes \vec{u}} n_j \, dS$$

$$= \int_{V(t)} \frac{\partial \rho u_i}{\partial t} \, dV + \oint_{S(t) = \partial V(t)} \rho(\vec{u} \otimes \vec{u}) \vec{n} \, dS$$
(1.20)

and by applying Gauss theorem to the surface integral

$$\frac{d\vec{P}}{dt} = \int_{V(t)} \left[\frac{\partial \rho \vec{u}}{\partial t} + \nabla \rho \vec{u} \otimes \vec{u} \right] dV \qquad and \qquad \frac{dP_i}{dt} = \int_{V(t)} \left[\frac{\partial \rho u_i}{\partial t} + \frac{\partial}{\partial x_j} (\rho u_i u_j) \right] dV \quad (1.21)$$

Based on the previous forms, we can generalize this for any arbitrary function ϕ

$$\begin{split} \frac{d}{dt} \int_{V(t)} \rho \phi \, dV &= \int_{V(t)} \left[\frac{\partial \rho \phi}{\partial t} + \frac{\partial}{\partial x_j} \rho \phi u_j \right] dt \\ &= \int_{V(t)} \left[\rho \frac{\partial \phi}{\partial t} + \phi \underbrace{\left(\frac{\partial \rho}{\partial t} + \frac{\partial \rho u_j}{\partial x_j} \right)}_{=0 \ (1.13)} + \rho u_j \frac{\partial \phi}{\partial x_j} \right] dV \\ &= \int_{V(t)} \rho \left[\frac{\partial \phi}{\partial t} + u_j \frac{\partial \phi}{\partial x_j} \right] dV \end{split} \tag{1.22}$$

Similarly to thermodynamics courses, we can introduce an extensive variable Φ and an intensive ϕ to have

General relation for any arbitrary function in closed systems

$$\frac{d\Phi}{dt} = \int_{V(t)} \left[\frac{\partial \rho \phi}{\partial t} + \nabla \rho \phi \vec{u} \right] dV = \int_{V(t)} \rho \dot{\phi} \, dV \tag{1.23}$$

For the specific case where $\Phi = \vec{P}$ and $\phi = \vec{u}$, we obtain

$$\frac{d\vec{P}}{dt} = \int_{V(t)} \rho \underbrace{\left[\frac{\partial \vec{u}}{\partial t} + \vec{u} \nabla \vec{u}\right]}_{i} dV \tag{1.24}$$

We can now express the forces applied on the system. There are 2 main classes :

ullet Distance forces (volume) $ec{F}_V$:

This type of force allows a body to influence another without being in contact with.

— The most present one is gravity which is applied on each fluid particles $(d\vec{F} = dm\vec{g})$. We can imagine that there exists a force density \vec{f} such that

$$\vec{F}_V = \int_{V(t)} \vec{f} \, dV = \int_{V(t)} \rho \vec{a} \, dV$$
 (1.25)

where \vec{a} is a force per unit mass, so an acceleration (gravity: $\vec{f} = \rho \vec{g}$).

— If we have an electric material, we can talk about electromagnetic forces, which can be modelled as

$$\vec{f} = \rho_c(\vec{E} + \vec{u} \times \vec{B}) + \vec{J} \times \vec{B} \tag{1.26}$$

where ρ_c is the charge density $[C/m^3]$ and the second term is the Lorentz force. Indeed, if we have a lot of particles, we can talk of an average velocity $\vec{v}_k = \vec{u} + \vec{C}_k$, where C_k is a particular velocity due to molecular agitation. The force applied on the system is

$$\vec{F}_k = q_k [\vec{E} + \vec{v}_k \times \vec{B}] \qquad \Leftrightarrow \qquad \underbrace{\frac{\sum \vec{F}_k}{V}}_{\rho_c} = \underbrace{\frac{\sum q_k}{V}}_{V} (\vec{E} + \vec{u} \times \vec{B}) + \underbrace{\frac{\sum q_k \vec{C}_k}{V}}_{\vec{I}} \times \vec{B} \quad (1.27)$$

Mollecules are in general neutral, but containing non-neutral regions. Fluids are essentially neutral, $\vec{F}_V = 0$ in most cases. They are called quasi-neutral fluids. Electric influenced fluids will not be considered in that course but they existence has to be known.

— They are also entrainment and Coriolis forces in rotating frame of references. These forces due to the rotation of Earth are not considered due to the small rotative velocity, unlike pomps and turbines.

• Contact forces (surface) \vec{F}_S :

ch1/5.png

Figure 1.5

These forces results from the contact of an internal and external fluid in regard of a region of surface dS(t). We have

$$d\vec{F}_S = \vec{T} dS \qquad \Rightarrow \vec{F}_S = \oint_S \vec{T} dS$$
 (1.28)

 \vec{T} is a force per unit area, a continuous function of space depending on location \vec{x} and also linearly on the infinitesimal surface orientation \vec{n} . If \vec{T} is the force per unit area for a surface element normal

to the unit vector in the j direction e_j , $\vec{T}(\vec{x}) = \vec{T}_j n_j$. (1.28) becomes

$$\vec{F}_S = \oint_S \vec{T}_j n_j dS$$
 and $F_{S_i} = \oint_S \underbrace{\tau_{j,i}}_{\sigma_{ji}} n_j dS$ (1.29)

where σ_{ji} is the stress tensor.

We can now take (1.18) and replace the terms using (1.24), (1.25) and (1.29) to obtain the

Momentum equation (integral form)

$$\frac{dP_i}{dt} = \int_{V(t)} \left[\frac{\partial \rho u_i}{\partial t} + \nabla \rho u_i \vec{u} \right] dV = \int_{V(t)} \rho \dot{u} \, dV = \int_{V(t)} \rho a_i \, dV + \oint_{S(t)} \sigma_{ji} n_j \, dS \qquad (1.30)$$

We can see that σ_{ji} and $\rho u_i u_j$ have the same mathematical nature. This is not surprising because in fact these forces result from molleculare agitation in fluids. Let's discuss it. We said that $\vec{v}_k = \vec{u} + \vec{C}_k$. Let's consider a surface element and make the hypothesis that the fluid is in rest, so the average velocity $\vec{u} = 0$. It doesn't mean that the particles are immobile, but that if all particles have the same mass (pure fluid) and if a certain number of particles are going from right to left with velocity \vec{c} , there are the same number of particles going from left to right with velocity $-\vec{c}$. There is no global mass flux. So for n particles going in one direction, the mass flux

$$2nm\vec{u} = nm\vec{c} + 2nm(-\vec{c}) = 0 \tag{1.31}$$

To obtain the momentum in direction x_1 , we have to multiply the mass flow in this direction by the velocity in this direction

$$nm(\vec{c} \cdot \vec{e_1})c_1 + nm(-\vec{c_1} \cdot \vec{e_1})(-c_1) = 2nmc_1^2$$
(1.32)

The global momentum flux traversing the unit surface is so positive going out of the volume. We need so a balance force in the opposite direction to keep the mass in. This explains the presence and nature of σ_{ii} which is a momentum flux.

Let's finally establish the differential form of the momentum equation, applying Gauss theorem to the second right side of (1.30)

$$\int_{V(t)} \rho a_i \, dV + \oint_{S(t)} \sigma_{ji} n_j \, dS = \int_{V(t)} \left[\rho a_i + \frac{\partial \sigma_{ji}}{\partial x_j} \right] dV \tag{1.33}$$

and by considering the whole equation

$$\int_{V(t)} \left[\frac{\partial \rho u_i}{\partial t} + \frac{\partial \rho u_i u_j}{\partial x_i} - \rho a_i - \frac{\partial \sigma_{ji}}{\partial x_i} \right] dV = 0 = \int_{V(t)} \left[\rho \dot{u}_i - \rho a_i - \frac{\partial \sigma_{ji}}{\partial x_i} \right] dV$$
 (1.34)

and for this to be true for all systems we consider, we obtain

Momentum equation (differential form (1) - divergent form)

$$\frac{\partial \rho u_i}{\partial t} + \frac{\partial \rho u_i u_j}{\partial x_j} = \rho a_i + \frac{\partial \sigma_{ji}}{\partial x_j} \qquad and \qquad \frac{\partial \rho \vec{u}}{\partial t} + \nabla \rho \vec{u} \otimes \vec{u} = \rho \vec{a} + \nabla \bar{\sigma}$$
 (1.35)

Momentum equation (differential form (2) - substancial form)

$$\rho a_i + \frac{\partial \sigma_{ji}}{\partial x_j} = \rho \dot{u}_i \quad and \quad \rho \vec{a} + \nabla \bar{\bar{\sigma}} = \rho \dot{\vec{u}}$$
 (1.36)

1.1.3 Angular momentum equation

This is a corollary of the momentum equation that states that the time rate of change of the angular momentum of a closed system is equal to the sum of the torques applied to the system. There is no additional information except that the stress tensor should be symetric

$$\sigma_{ji} = \sigma_{ij} \tag{1.37}$$

1.1.4 Energy equation - First principle of thermodynamics

If we note \mathcal{E} the total energy of the system, the first principle tells that

$$\frac{d\mathcal{E}}{dt} = \dot{W} + \dot{Q} \tag{1.38}$$

where \dot{W} is the mechanical power provided by the forces applied on the system and \dot{Q} the thermal power provided to the system. We will proceed like the previous equation expressing first the left side then the right side. If we note E the total energy per unit mass, e the internal energy per unit mass and k the kinetic energy per unit mass (potential energy is not considered in order not to take into account power coming from potential forces)

$$\mathcal{E} = \int_{V(t)} E \, dm = \int_{V(t)} \rho E \, dV = \int_{V(t)} \rho(e+k) \, dV \qquad with \quad k = \frac{\vec{u}\vec{u}}{2}$$
 (1.39)

The time derivative of the energy using the Reynolds transport theorem, then the Gauss theorem is

$$\frac{d\mathcal{E}}{dt} = \int_{V(t)} \frac{\rho(e+k)}{dt} dV + \oint_{S(t)} \rho(e+k) \vec{u} \vec{n} dS$$

$$= \int_{V(t)} \left[\frac{\rho(e+k)}{dt} + \nabla \rho(e+k) \vec{u} \right] dV = \int_{V(t)} \rho(e+k) dV$$
(1.40)

Let's now go on with with the mechanical power expression. We expressed in (1.30) that there are volume and surface forces. These multiplied by the velocity and using Gauss gives

$$\dot{W} = \int_{V(t)} \rho a_i u_i \, dV + \oint_{S(t)} \sigma_{ji} u_i n_j \, dS = \int_{V(t)} \left[\rho a_i u_i + \frac{\partial}{\partial x_j} \sigma_{ji} u_i \right] dV \tag{1.41}$$

ch1/6.png

For the thermal power expression, we need to introduce a new concept that is the heat flux vector \vec{q} which qualifies a thermal power per unit area leaving the surface. Physically, there is only two heat transport mecanism which are radiation and conduction. Indeed, convection is a specific conduction case where the temperature gradient region becomes thinner and favorises the exchange. The thermal power is

Figure 1.6

$$\dot{Q} = -\oint_{S(t)} \vec{q}\vec{n} \, dS = -\int_{V(t)} \nabla \vec{q} \, dV \tag{1.42}$$

Replacing the terms of (1.38) by (1.40), (1.41) and (1.42) gives

Total energy equation (integral form)

$$\int_{V(t)} \frac{\rho(e+k)}{dt} \, dV + \oint_{S(t)} \rho(e+k) \vec{u} \vec{n} \, dS = \int_{V(t)} \rho \vec{a} \vec{u} \, dV + \oint_{S(t)} (\bar{\sigma} \vec{n}) \vec{u} \, dS - \oint_{S(t)} \vec{q} \vec{n} \, dS \quad (1.43)$$

The differential form is obtained using Gauss theorem for the two sides and regrouping all the terms into one integral

$$\int_{V(t)} \left[\frac{\rho(e+k)}{dt} + \nabla \rho(e+k)\vec{u} - \rho \vec{a}\vec{u} - \nabla \bar{\sigma}\vec{u} + \nabla \vec{q} \right] dV = 0$$

$$\Leftrightarrow \int_{V(t)} \left[\rho(e + k) - \rho \vec{a}\vec{u} - \nabla \bar{\sigma}\vec{u} + \nabla \vec{q} \right] dV = 0$$
(1.44)

And considering the fact that this has to be true for all systems, we obtain the two last forms

Total energy equation (differential form (1) - divergent form)

$$\frac{\rho(e+k)}{dt} + \nabla \rho(e+k)\vec{u} = \rho \vec{a}\vec{u} + \nabla \bar{\bar{\sigma}}\vec{u} - \nabla \vec{q}$$
 (1.45)

Total energy equation (differential form (2) - substantial form)

$$\rho(e + k) = \rho(\dot{e} + \dot{k}) = \rho \vec{a} \vec{u} + \nabla \bar{\sigma} \vec{u} - \nabla \vec{q}$$
(1.46)

Let's finally establish the distribution of the forces in the different energies. If we multiply (1.36) by velocity \vec{u} and if we observe that $\dot{k} = \frac{\dot{u}_i u_i + u_i \dot{u}_i}{2} = u_i \dot{u}_i$, we obtain

Kinetic - Mechanical energy equation

$$\vec{u}\left(\rho a_i + \frac{\partial \sigma_{ji}}{\partial x_j} = \rho \dot{u}_i\right) \qquad \Leftrightarrow \qquad \rho \underbrace{u_i \dot{u}_i}_{\dot{k}} = \rho u_i a_i + \frac{u_i \partial \sigma_{ji}}{\partial x_j} \tag{1.47}$$

The difference between total energy (1.46) and kinetic energy (1.47) gives the internal energy

Internal energy equation
$$\rho\dot{e}=0+\sigma_{ji}\frac{\partial u_i}{\partial x_j}-\nabla\vec{q} \eqno(1.48)$$

We see that volume forces only contributes to the kinetic energy, heat flux only to the internal energy and the suface forces to both.

1.1.5 Summary - Complementary equation

Let's make the inventory of the 3 substancial equations that we found. How many equations and unknowns do we have?

- In continuity equation (1.17), ρ and u_i are 4 unknowns in 3D.
- In momentum equation (1.36), a_i is an external applied force so is known, σ_{ji} consists in 6 unknowns (symetric matrix).
- In internal energy equation (1.48), e and \vec{q} are 4 most unknowns.

The total unknowns number is 14. The number of disponible equations is 5, 1 thanks to the energy, 1 thanks to the continuity and 3 thanks to the vectorial momentum equation. In this stage, we haven't made any assumption on the nature of the material we're considering. These equations are valid for an elastic solid as a fluid. The main difference is that solids resist to a deformation whereas fluid doesn't. But fluid resists to a rate of deformation. The way that stress tensor σ_{ji} is related to the displacement field is called the constitutive equations.

Constitutive relations

For a fluid, the stress tensor depends on the fluid rate of deformation (rate of strain). To express σ_{ji} , we have to find a quantity in the field of motion of the fluid that represents the rate of strain. If the velocity field $\vec{u}(\vec{x},t)$ was uniform, not depending on \vec{x} , the fluid will be moving as a bulk and there is no rate of deformation. The rate of strain must be somehow related to the

velocity gradient tensor $\nabla \otimes \vec{u}$. We know that all tensors can be decomposed in an antisymetric and symetric part like

$$\nabla \otimes \vec{u} = \frac{\partial u_j}{\partial x_i} = \Omega_{ji} + S_{ij} = \frac{1}{2} \left(\frac{\partial u_j}{\partial x_i} - \frac{\partial u_i}{\partial x_j} \right) + \frac{1}{2} \left(\frac{\partial u_j}{\partial x_i} + \frac{\partial u_i}{\partial x_j} \right). \tag{1.49}$$

For a constant gradient velocity field, the velocity field is linear in the coordinates

$$u_j = \frac{\partial u_j}{\partial x_i} x_i = \Omega_{ji} x_i + S_{ij} x_i \tag{1.50}$$

Let's look to the mathematical nature of the antisymetric part. If we express using Kronecker δ , we have

$$\Omega_{ji} = \frac{1}{2} \left(\frac{\partial u_j}{\partial x_i} - \frac{\partial u_i}{\partial x_j} \right) = \frac{1}{2} \delta_{kij} \delta_{kqp} \frac{\partial u_p}{\partial x_q} \qquad with \quad \delta_{kij} \delta_{kqp} = \delta_{iq} \delta_{jp} - \delta_{ip} \delta_{jq}$$
 (1.51)

Knowing that $(a \times b)_k = \delta_{kpq} a_p b_q$, we can introduce the **curle** (rotationnel) of velocity called vorticity $\vec{\omega}$

$$\delta_{kqp} \frac{\partial u_p}{\partial x_q} = (\nabla \times \vec{u})_k \qquad \Rightarrow \nabla \times \vec{u} = \vec{\omega}$$
 (1.52)

Let's look to the way this is linked to (1.50)

$$u_j^{AS} = \Omega_{ji} x_i = \frac{1}{2} \delta_{jki} \omega_k x_i = \frac{1}{2} (\vec{\omega} \times \vec{x})_j \qquad \Leftrightarrow \qquad \vec{u}^{AS} = \frac{1}{2} \vec{\omega} \times \vec{x}$$
 (1.53)

In conclusion, we see that the antisymetric part consists in a pure rotation velocity field, a rigid body motion of angular velocity $\frac{1}{2}\vec{\omega}$ without strain. $\vec{\omega}$ is twice the angular velocity of fluid particles around themselves. The quantity representative of the fluid rate of strain can only be the symetric part of the velocity gradient tensor called the rate of strain tensor. For a fluid, $\sigma_{ij} = f(S_{ij})$.

To determine the nature of this relationship, we will assume that σ_{ij} is a linear function of S_{pq} . This is called

Newton's assumption for stresses
$$\sigma_{ij} = a_{ij} + b_{ijpq}S_{pq}. \tag{1.54}$$

In this equation, b_{ijpq} is a tensor with four indices, but we know that it's symetric with respect to pq and ij because S is symetric with respect to pq and ij, leading to $6 \times 6 = 36$ coefficients. Symetric tensor a_{ij} counts 6 coefficients, for a total of 42 coefficients.

If we assume that the fluid is **isotropic**, meaning that the fluid react in the same way whatever the sollicitation direction. For example, let's take a case of S_{ij} where all coefficients are null except the S_{11} term. Diagonal terms represent a rate of elongation/stretch while the off-diagonal terms represent an angular deformation between two perpendicular direction. The assumption means that if the rate of stress is not in 1 direction but 2, the fluid reaction will be the same. In other words, if we make a rotation of coordinates, the relation in the rotated frame of reference must be the same. In that case, the relation reduces to

$$\sigma_{ij} = a\delta_{ij} + bS_{ij} + c\delta_{ij}S_{kk} \tag{1.55}$$

where only 3 coefficient must be found. It is natural to think that air and water have no preferential direction unlike certain solid as wood that has a preferential direction related to the

orientation of fibers. Blood or dissolved polymer chains are examples of non isotropic fluids. We will from now consider the fluid to be isotropic.

In (1.55) a is a constant that represents the stress present when the fluid is at rest. The surface force associated to that component is purely normal

$$\sigma_{ij}n_j = a\delta_{ij}n_j = an_i \tag{1.56}$$

This constant corresponds to the pressure exerted by the fluid at rest. Because of its application in the opposite direction to the normal, it's negative. The two other coefficients represents the 2 coefficients of viscosity

$$a = -p \qquad b = 2\mu \qquad c = \lambda \tag{1.57}$$

The stress tensor equation can so be written with a pressure stress and a viscous stress part like

$$\sigma_{ij} = -p\delta_{ij} + \tau_{ij} \quad with \quad \tau_{ij} = 2\mu S_{ij} + \lambda \delta_{ij} S_{kk}$$
 (1.58)

An alternative form to that is the following

$$\tau_{ij} = 2\mu \underbrace{\left(S_{ij} + \frac{1}{3}\delta_{ij}S_{kk}\right)}_{\equiv S_{ij}^S} + \underbrace{\left(\lambda + \frac{2\mu}{3}\right)}_{\equiv \mu_V} \delta_{ij}S_{kk} \tag{1.59}$$

This notation is necessary to make appear the part of the strain tensor which has no trace S_{ij}^{S} , called the rate of shear. Indeed

$$S_{ii}^S = S_{ii} - \frac{1}{3}\delta_{ii}S_{kk} = 0 (1.60)$$

This means that S_{ij}^S represents the trace less part of the rate of **strain** tensor called the sheer rate tensor. What is now S_{kk} ?

$$S_{kk} = \frac{1}{2} \left(\frac{\partial u_k}{\partial x_k} + \frac{\partial u_k}{\partial x_k} \right) = \frac{\partial u_k}{\partial x_k} = \nabla \vec{u}$$
 (1.61)

The divergence of the velocity is related to the rate of dilatation of the fluid, the change of volume. We decomposed the rate of strain in a part representing the deformation without change of volume (pure deformation) and another with change of volume (μ_V is the bulk viscosity). Another expression for τ_{ij} with a final net gain of 3 unknowns is

$$\tau_{ij} = 2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u} \tag{1.62}$$

At this stage, we have to determine still 6 unknowns from the 9 at the beginning.

Heat flux

We discussed about the fact that heat flux propagates using 2 physical mechanism: conduction and radiation. In the energy equation it's the divergence of the heat fluc that appears. In most application, the radiative effect does not imply heat accumulation or loss. The fluids are so transparent to radiative heat flux $\nabla \bar{q}^{rad} = 0$. We only have conduction and the Fourier law says that

$$\vec{q} \propto \nabla T = d\nabla T = -\kappa \nabla T \qquad \Leftrightarrow \qquad q_i = -\kappa \frac{\partial T}{\partial x_i}$$
 (1.63)

The negative sign comes from the fact that heat goes from hot to cold (decrease of T). We have a net gain of 1 unknown with this equation.

Thermodynamics

At this stage, we are using 4 thermodynamics intensive variables which are ρ , e, p, T. We know that for a single phase fluid, the variance is 2, meaning that we can use 2 thermodynamics equations of state (EoS) relating them. For example, for a alorically and thermally perfect gas, we will have

$$p = \rho RT \qquad and \qquad e = c_v T \tag{1.64}$$

We have a net gain of 2 unknows, so there remains 2 unknowns.

Transport coefficients

The remaining variables are the shear viscosity μ , the bulk viscosity μ_V and thermal conductivity κ . These are functions of the thermodynamic state. For example for gases we have the relations

$$\mu = f(T)$$
 and $Pr = \frac{\mu c_p}{\kappa} = cst \Leftrightarrow \kappa = \frac{\mu(T)c_p(T)}{Pr}$ (1.65)

The bulk viscosity is more difficult to determine, but it can be shown that for monoatomic gases (no internal degrees of freedom) $\mu_V = 0$. For diatomic gases it's much more delcate to measure, but it has been shown that for many flows, the flows is insensitive to the variation of value of bulk viscosity. In fact, for fluids without divergence of velocity, we don't care about μ_V because there is no variation of volume (1.62). We will so make the following assumption

Stokes assumption
$$\mu_V = 0 \quad \text{even for other gases.} \eqno(1.66)$$

We're done, we have as many equations as variables. We mentioned the first principle of thermodynamics but not the second. Let's analyse that.

Second principle of thermodynamics

We will reuse the internal energy equation (1.48), replace σ_{ij} by it's expression in (1.58) and use the fact that $\frac{\partial u_i}{\partial x_i} = \Omega_{ij} + S_{ij}$

$$\rho \dot{e} = \sigma_{ij} \frac{\partial u_i}{\partial x_j} - \frac{\partial q_i}{\partial x_i} = -p \delta_{ij} \frac{\partial u_i}{\partial x_j} + (2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}) (S_{ij} + \Omega_{ij}) - \frac{\partial q_i}{\partial x_i}$$
(1.67)

where Ω_{ij} doesn't contribute because the contraction of the symetric tensor by the antisymetric tensor is equal to 0. We have the relation

$$S_{ij}^{S} = S_{ij} - \frac{1}{3}\delta_{ij}\nabla\vec{u} \qquad \Leftrightarrow \qquad S_{ij} = S_{ij}^{S} + \frac{1}{3}\delta_{ij}\nabla\vec{u}$$
 (1.68)

Combined to the fact that $\delta_{ij} \frac{\partial u_i}{\partial x_j} = \frac{\partial u_i}{\partial x_i} = \nabla \vec{u}$, we obtain

$$\rho \dot{e} = -p\nabla \vec{u} + (2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}) \left(S_{ij}^S + \frac{1}{3} \delta_{ij} \nabla \vec{u} \right) - \nabla \vec{q}$$
(1.69)

The mass conservation equation tells us that we can write the divergence as

$$\dot{\rho} + \rho \nabla \vec{u} = 0 \qquad \Leftrightarrow \qquad \nabla \vec{u} = -\frac{\dot{\rho}}{\rho} = -\rho \left(\frac{\dot{\rho}}{\rho^2}\right) = \rho \left(\frac{\dot{1}}{\rho}\right) = \rho \dot{v}$$
 (1.70)

If we replace the divergence in the previous equation, we have

$$\rho \dot{e} = -\rho p \dot{v} + (2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}) \left(S_{ij}^S + \frac{1}{3} \delta_{ij} \nabla \vec{u} \right) - \nabla \vec{q}$$

$$(1.71)$$

The first term here looks like the reversible work -pdv in thermodynamics and is so the reversible contribution to the internal energy. Let's make this appear by bringing this to the left side. We make appear $\rho[\dot{e}+p\dot{v}]$, but we have the famous Gibbs relation $de=Tds-pdv \Leftrightarrow \dot{e}=T\dot{s}-p\dot{v}$. We have now

$$\rho \dot{s} = \frac{\left(2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}\right) \left(S_{ij}^S + \frac{1}{3} \delta_{ij} \nabla \vec{u}\right)}{T} - \frac{\nabla \vec{q}}{T}$$

$$(1.72)$$

If we remind the relation we demonstrated before for any variable $\dot{\Phi} = \int_V \rho \dot{\phi} dV$, we can make the analogy here to say that when this is integrated over a volume, it gives the time rate of change of the entropy of the closed system that's initially inside this volume. We have to identify the reversible part in this equation. We know that the reversible entropy rate of exchange for a uniform system and its integral over a closed surface is given by

$$\frac{\vec{q}dS}{T} \qquad \Rightarrow \qquad \oint_{S} \frac{\vec{q}}{T} (-\vec{n}) \, dS = -\int_{V} \nabla \frac{\vec{q}}{T} \, dV. \tag{1.73}$$

We see that we have to make appear a this in the last equation. But we know that

$$\frac{\nabla \vec{q}}{T} = \nabla \frac{\vec{q}}{T} - \vec{q} \nabla \left(\frac{1}{T}\right) = \nabla \frac{\vec{q}}{T} + \vec{q} \frac{\nabla T}{T^2}$$
(1.74)

And by introducing this into the relation (1.72), we make appear the reversible entropy rate of exchange

$$\rho \dot{s} = -\nabla \frac{\vec{q}}{T} - \frac{\vec{q}\nabla T}{T^2} + \frac{(2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}) \left(S_{ij}^S + \frac{1}{3} \delta_{ij} \nabla \vec{u}\right)}{T}$$
(1.75)

We also know that $\vec{q} = -\kappa \nabla T$, making appear $(\nabla T)^2$

$$\rho \dot{s} = -\nabla \frac{\vec{q}}{T} + \frac{\nabla T \nabla T}{T^2} + \frac{(2\mu S_{ij}^S + \mu_V \delta_{ij} \nabla \vec{u}) \left(S_{ij}^S + \frac{1}{3} \delta_{ij} \nabla \vec{u}\right)}{T}$$
(1.76)

If we imagine a fluid at rest with only a heat exchange operating on it, the third term = 0, the first term is reversible so anyway the sign and the second term must be positive. This implies $\kappa \geq 0$ due to the square of the other variables (the heat has to go from hot to cold). Let's expand the third term

$$\rho \dot{s} = -\nabla \frac{\vec{q}}{T} + \frac{\nabla T \nabla T}{T^2} + \frac{1}{T} \left[2\mu S_{ij}^S S_{ij}^S + \underline{\mu_V} \nabla \vec{u} \delta_{ij} S_{ij}^S + 2\mu S_{ij}^S \frac{\delta_{ij}}{3} \nabla \vec{u} + \mu_V \frac{\delta_{ij} \delta_{ij}}{3} (\nabla \vec{u})^2 \right]$$
(1.77)

In this last equation, the second and third terms are nul because $S_{ii}^S = 0$. Let's imagine that we have a fluid with only dilation and no shear S_{ij}^S , the last term must be positive and so μ_V has to be positive (≥ 0). In the other hand, for the first term, we have a quadratic form (sum of squares ≥ 0), so μ has to be positive. To verify the second principle, we have to verify these 3 inequalities. In fluid mechanics, we don't have to worry about the second principle, it's built in the equations as long as the transport coefficient are positive.

1.1.6 Boundary conditions

We have now to establish the boundary conditions which makes the difference between the flow cases. First of all, we have two main categories of flows:

- External flows (unbounded domain)
 - For example, a flow over a wing, assuming that atmosphere extends to infinity. In that case we have far field boundary conditions, what happens far from the body $(u \to u_{\infty}, p \to p_{\infty}, T \to T_{\infty})$.
- Internal flows (bounded domain)

For example, a flow in a pipe or a fluid in a rotating machine like a pump. In that case we don't have the far field conditions but the inlet and outlet boundary conditions but this problem is not discussed here.

Solid surfaces

In both case we have solid surfaces, we have to make a distinction. We wrote the equation for the general case of a viscous flow, but there is flows where the viscous stresses can be neglected (not = 0!) leading to what we call the **inviscid flows**. Let's analyse the two cases.

Viscous flows

Viiscosity is associated to the exchange of momentum between neighboring fluid layers due to molecular agitation. If we have a molecule coming from a low velocity region to a high velocity region, it slows down the molecule there and inversely. The same occurs when a fluid particle enter in contact with solid surfaces, it exchange momentum. The result is that velocity and temperature fields must be continuous

$$\vec{u}_{fluid} = \vec{u}_{wall}$$
 and $T_{fluid} = T_{wall}$ (1.78)

In particular, for a surface at rest, the fluid must be at rest on the solid surface as well. This is called the **no-slip condition**.

Inviscid flows

For inviscid flows, this mecanism doesn't exist, the fluid may slip. The boundary condition is that the fluid can't go throw the solid

$$\vec{u}_{fluid}\vec{n} = \vec{u}_{wall}\vec{n} \tag{1.79}$$

This is called the slip/no penetration condition. The previous condition is stronger because in fact $\vec{u} = \vec{u}_n \vec{n} + \vec{u}_t$ includes the tangential condition too.

1.2 Special cases

1.2.1 General case

The generale equations are the following