Process Management

Process vs Program

- An operating system executes a variety of programs that run as a process.
- **Process** is a program in execution.
- Process is considered as an instance of a program, replete with registers, variables, and a program counter
- A process is an activity of some kind. It has a program, input, output and a state.
- A **program** is a set of instructions, written to complete some task
- Program is **passive** entity stored on disk (**executable file**); process is **active**
 - o Program becomes process when an executable file is loaded into memory
- Execution of program started via GUI mouse clicks, command line entry of its name, etc are examples of processes
- If a program is running twice, it counts as two processes.

The difference between a process and a program is subtle, but absolutely crucial. An analogy may help you here. Consider a culinary-minded computer scientist who is **baking a birthday cake** for his young daughter. He has a birthday cake recipe and a kitchen well stocked with all the input: flour, eggs, sugar, extract of vanilla, and so on. In this analogy, the **recipe is the program**, that is, an algorithm expressed in some suitable notation, the **computer scientist is the processor** (CPU), and the **cake ingredients are the input data**. The **process is the activity consisting of our baker reading the recipe, fetching the ingredients, and baking the cake**. Now imagine that the computer scientist's son comes running in screaming his head off, saying that he has been stung by a bee. The computer scientist **records where he was in the recipe (the state of the current process is saved)**, gets out a first aid book, and begins following the directions in it. Here we see **the processor being switched from one process (baking) to a higher-priority process (administering medical care)**, each having a **different program (recipe versus first aid book)**. When the bee sting has been taken care of, the computer scientist **goes back to his cake**, continuing at the point where he left off.

NOTE: A single processor may be shared among several processes, with some scheduling algorithm being accustomed to determine when to stop work on one process and service a different one. In contrast, a program is something that may be stored on disk, not doing anything.

A program and a process are related terms but are not same. The major difference between program and process is that program is a group of instructions to carry out a specified task whereas the process is a program in execution. While a process is an active entity, a program is *considered to be a passive one*.

Multiple parts in a process

- The program code, also called **text section**
- Current activity including **program counter**, processor registers
- Stack containing temporary data
 - o Function parameters, return addresses, local variables
- **Data section** containing global variables
- **Heap** containing memory dynamically allocated during run time




Figure: A process in memory

Memory Layout of a C Program




Figure: Memory Layout od a C Program

Multiprogramming

- In Multiprogramming, to execute the processes, only one CPU is used.
- In a multiprogramming system there are one or more programs loaded in main memory which are ready to execute. Only one program at a time is able to get the CPU for executing its instructions (i.e., there is at most one process running on the system) while all the others are waiting their turn.
- Multiprogramming is based on context switching which doesn't allow CPU to sit idle thereby maximizing CPU utilization.

The Process Model

- In this model, all the runnable software on the computer, sometimes including the operating system, is organized into a number of **sequential processes**, or just processes for short. A process is just an instance of an executing program, including the current values of the program counter, registers, and variables.
- Conceptually, each process has its own virtual CPU. In reality, of course, the real CPU switches back and forth from process to process, but to understand the system, it is much

- easier to think about a collection of processes running in (pseudo) parallel than to try to keep track of how the CPU switches from program to program. This rapid switching back and forth is called multiprogramming.
- In any **multiprogramming system**, the CPU switches from process to process quickly, running each for tens or hundreds of milliseconds. While, strictly speaking, at any one instant the CPU is running only one process, in the course of 1 second it may work on several of them, giving the illusion of parallelism. Sometimes people speak of *pseudoparallelism* in this context, to contrast it with the true hardware parallelism of *multiprocessor* systems (which have two or more CPUs sharing the same physical memory).

Illustration of the multiprogramming concept

• In following figure (a) we see a computer multiprogramming four programs in memory. In figure (b) we see four processes, each with its own flow of control (i.e., its own logical program counter), and each one running independently of the other ones. Of course, there is only one physical program counter, so when each process runs, its logical program counter is loaded into the real program counter. When it is finished (for the time being), the physical program counter is saved in the process' stored logical program counter in memory. In figure(c) we see that, viewed over a long enough time interval, all the processes have made progress, but at any given instant only one process is actually running.




Figure : (a) Multiprogramming of four programs. (b) Conceptual model of four independent, sequential processes. (c) Only one program is active at once.

Process Creation

Operating systems need some way to create processes. Events which can cause process creation

- System initialization.
- Execution of a process creation system call by a running process.
- A user request to create a new process.
- Initiation of a batch job.

Process Termination

After a process has been created, it starts running and does whatever its job is. However, nothing lasts forever, not even processes.

Events which cause process termination:

- Normal exit (voluntary).
- Error exit (voluntary).
- Fatal error (involuntary).
- Killed by another process (involuntary).

Process States

As a process executes, it changes **state**. The state of a process is defined in part by the current activity of that process. A process may be in one of the following states:

- New: The process is being created
- Running: Instructions are being executed
- Waiting: The process is waiting for some event to occur (such as an I/O completion or reception of a signal).
- **Ready**: The process is waiting to be assigned to a processor
- **Terminated**: The process has finished execution




Figure: Process states

Process Control Block

- To implement the process model, the operating system maintains a table (an array of structures), called the process table, with one entry per process. This is also called as process control block (PCB) or task control block.
- Each process is represented in the operating system by a process control block (PCB.
- A PCB is shown in following figure. It contains many pieces of information associated with a specific process, including these:
 - Process state running, waiting, etc.
 - Program counter location of instruction to next execute
 - CPU registers contents of all process-centric registers
 - CPU scheduling information- priorities, scheduling queue pointers
 - Memory-management information memory allocated to the process
 - Accounting information CPU used, clock time elapsed since start, time limits
 - I/O status information I/O devices allocated to process, list of open files




Figure: A process control block (PCB).

Following figure shows some of the key fields in a typical system. The fields in the first column relate to process management. The other two relate to memory management and file management, respectively. It should be noted that precisely which fields the process table has is highly system dependent, but this figure gives a general idea of the kinds of information needed.

Process management	Memory management	File management
Registers	Pointer to text segment info	Root directory
Program counter	Pointer to data segment info	Working directory
Program status word	Pointer to stack segment info	File descriptors
Stack pointer		User ID
Process state		Group ID
Priority		
Scheduling parameters		
Process ID		
Parent process		
Process group		
Signals		
Time when process started		
CPU time used		
Children's CPU time		
Time of next alarm		

Figure: Some of the fields of a typical process table / PCB entry.

Threads

- A **thread** is a light-weight smallest part of a process that can run concurrently with the other parts (other threads) of the same process. It has a separate path of execution
- A process can have multiple threads.
- Threads are independent. If a thread gets an exception or an error at the time of its execution, it doesn't affect the execution of the other threads.
- All the threads share a common memory and have their own stack, local variables and program counter.
- Because threads have some of the properties of processes, they are sometimes called lightweight processes.
- When multiple threads are executed in parallel at the same time, this process is known as **multithreading**.
- Each thread belongs to exactly one process and no thre.ad can exist outside a process. Each thread represents a separate flow of control.

• A thread has:

- A **program counter** that keeps track of which instruction to execute next.
- **Registers**, which hold its current working variables.
- A stack, which contains the execution history, with one frame for each procedure called but not yet returned from

Thread vs Process

- Although a thread must execute in some process, the thread and its process are different concepts and can be treated separately.
- Processes are used to group resources together; threads are the entities scheduled for execution on the CPU.
- What threads add to the process model is to allow multiple executions to take place in the same process environment, to a large degree independent of one another
- Having multiple threads running in parallel in one process is analogous to having multiple processes running in parallel in one computer.
 - ▶ In the former case, the *threads share an address space and other resources*.
 - ▶ In the latter case, processes share physical memory, disks, printers, and other resources.

- Because threads have some of the properties of processes, they are sometimes called lightweight processes.
- The term **multithreading** is also used to describe the situation of allowing multiple threads in the same process
- In following figure (a) we see three traditional processes. Each process has its own address space and a single thread of control. In contrast, in (b) we see a single process with three threads of control. Although in both cases we have three threads, in (a) each of them operates in a different address space, whereas in (b) all three of them share the same address space




Figure: (a) Three processes each with one thread. (b) One process with

- Different threads in a process are not as independent as different processes.
- Like a traditional process (i.e., a process with only one thread), a thread can be in any one
 of several states: running, blocked, ready, or terminate.
 - Most modern applications are multithreaded
 - Threads run within application
 - Multiple tasks with the application can be implemented by separate threads
 - Process creation is heavy-weight while thread creation is light-weight




Figure: Single-threaded and multithreaded processes.

Benefits of threads

- Responsiveness may allow continued execution if part of process is blocked, especially important for user interfaces
- Resource Sharing threads share resources of process, easier than shared memory or message passing
- Economy cheaper than process creation, thread switching lower overhead than context switching
- Scalability process can take advantage of multicore architectures

User and Kernel Space Threads

• There are two main places to implement threads: **user space** and the **kernel**.

User level threads

- In **user level threads**, the threads package is put entirely in user space. The kernel knows nothing about them. User level threads are managed by users.
- The user-level threads are implemented and managed in user space.

- As far as the kernel is concerned, it is managing ordinary, single-threaded processes. The
 first, and most obvious, advantage is that a user-level threads package can be implemented
 on an operating system that does not support threads.
- With this approach, threads are implemented by a library (thread library).
- The threads run on top of a *run-time system*, which is a collection of procedures that manage threads.
- When threads are managed in user space, each process needs its own private **thread table** to keep track of the threads in that process (This table is analogous to the kernel's process table, except that it keeps track only of the per-thread properties, such as each thread's program counter, stack pointer, registers, state, and so forth. The thread table is managed by the run-time system.)
- User-level threads are small and much faster than kernel level threads.




Figure: A user-level threads package

Advantages:

- Thread table contains info about threads (program counter, stack pointer...) so that
 run time system can manage them
- If thread blocks, run time system stores thread info in table and finds new thread to run.
- They allow each process to have its own customized scheduling algorithm.
- o The procedure that saves the thread's state and the scheduler are just local procedures, so invoking them is much more efficient than making a kernel call.
- User-level threads are easier and faster to create than kernel-level threads. They can also be more easily managed.
- User-level threads can be run on any operating system.
- There are no kernel mode privileges required for thread switching in user-level threads.

Limitations:

- The entire process is blocked if one user-level thread performs blocking operation.
- There is a lack of coordination between threads and operating system kernel.

Kernel Level Threads

- ▶ **Kernel-level threads** are handled by the operating system directly and the thread management is done by the kernel.
- ▶ The kernel knows about and manages the threads. No run-time system is needed.
- ▶ No thread table in each process.
- ▶ The **kernel has a thread table** that keeps track of all the threads in the system. The kernel's thread table holds each thread's registers, state, and other information.
- ▶ The information is the same as with user-level threads, but now kept in the kernel instead of in user space (inside the run-time system). This information is a subset of the information that traditional kernels maintain about their single threaded processes, that is, the process state. In addition, the kernel also maintains the traditional process table to keep track of processes.
- ▶ When a thread wants to create a new thread or destroy an existing thread, it makes a kernel call, which then does the creation or destruction by updating the kernel thread table




Figure: A threads package managed by the kernel.

Advantages:

- Kernel keeps same thread table as user table
- If thread blocks, kernel just picks another one
 - Not necessarily from same process!
- When one thread blocks, other threads from process can be scheduled

Limitations:

- Kernel-level threads are slower to create as well as manage as compared to user-level threads.
- Expensive to manage the threads in the kernel and takes valuable kernel space

Hybrid approach of implementing threads

- Multiplex user-level threads onto kernel level threads
 - Various ways have been investigated to try to combine the advantages of user level threads with kernel-level threads. One way is use kernel-level threads and then multiplex user-level threads onto some or all of them




Figure: Multiplexing user-level threads onto kernel-level threads.

- When this approach is used, the programmer can determine how many kernel threads to use and how many user-level threads to multiplex on each one. This model gives the ultimate in flexibility
- With this approach, the kernel is aware of only the kernel-level threads and schedules those. Some of those threads may have multiple user-level threads multiplexed on top of them. These user-level threads are created, destroyed, and scheduled just like user-level threads in a process that runs on an operating system without multithreading capability. In this model, each kernel-level thread has some set of user-level threads that take turns using it.

Hybrid Approach

- ✓ Kernel is aware of kernel threads only
- ✓ User level threads are scheduled, created destroyed independently of kernel thread
- ✓ Programmer determines how many user level and how many kernel level threads to use

Inter Process Communication

Inter Process Communication (IPC) is the mechanism provided by the operating system that allows processes to communicate with each other. This communication could involve a process letting another process know that some event has occurred or the transferring of data from one process to another.

- ➤ A process **is independent** if it does not share data with any other processes executing in the system.
- ➤ A process is **cooperating** if it can affect or be affected by the other processes executing in the system.
- An independent process is not affected by the execution of other processes while a cooperating process can be affected by other executing processes.
- > Cooperating process can affect or be affected by other processes, including sharing data
- ➤ Cooperating processes need interprocess communication (IPC)
- There are several reasons for providing an environment that allows **process cooperation**:
 - Information sharing: Since several applications may be interested in the same piece of information (for instance, copying and pasting), we must provide an environment to allow concurrent access to such information.
 - Computation speedup: If we want a particular task to run faster, we must break it into subtasks, each of which will be executing in parallel with the others. Notice that such a speedup can be achieved only if the computer has multiple processing cores.
 - Modularity: We may want to construct the system in a modular fashion, dividing the system functions into separate processes or threads.

Three Issues to deal with

1. How to do IPC

— How one process can pass information to another?

2. How to deal with process conflicts

- Making sure two or more processes do not get in each other's way.
- For example, **two processes** in an **airline reservation system** each trying to **grab** the last seat on a plane for a different customer.

3. How to do correct sequencing when dependencies are present

— If process **A produces data** and process **B prints them**, B **has to wait** until A has produced some data before starting to print

NOTE:

SAME ISSUES FOR THREADS AS FOR PROCESSES-SAME SOLUTIONS AS WELL!!

Two Models of IPC

Cooperating processes require an inter process communication (IPC) mechanism that will allow them to exchange data— that is, send data to and receive data from each other. There are two fundamental models of inter process communication:

- Shared memory
- Message passing
- In the **shared-memory model**, a region of memory that is shared by the cooperating processes is established. Processes can then exchange information by reading and writing data to the shared region.
- In the **message-passing model**, communication takes place by means of messages exchanged between the cooperating processes




Figure: Communications models. (a) Shared memory. (b) Message passing.

Race Conditions

- The Situations, where two or more processes are reading or writing some shared data and the final result depends on who runs precisely when, are called **race conditions**.
- A race condition is a condition when there are many processes and every process shares the data (resource) with each other and accessing the data (resource) concurrently, and the output of execution depends on a particular sequence in which they share the data (resource) and access
- The inconsistent output produced by race conditions may cause bugs that are difficult to detect.
- Unfortunately, with increasing parallelism due to increasing numbers of cores, race condition are becoming more common.

Example to illustrate race condition

- To see how interprocess communication works in practice, let us now consider a simple but common example: a print spooler.
- When a process wants to print a file, it enters the file name in a special **spooler directory**.
- Another process, the **printer daemon**, periodically checks to see if there are any files to be printed, and if there are, it prints them and then removes their names from the directory.
- Imagine that our spooler directory has a very large number of slots, numbered 0, 1, 2, ..., each one capable of holding a file name.
- Also imagine that there are **two shared variables**, *out*, which points to the next file to be printed, and *in*, which points to the next free slot in the directory.
- At a certain instant, slots 0 to 3 are empty (the files have already been printed) and slots 4 to 6 are full (with the names of files queued for printing). More or less simultaneously, processes A and B decide they want to queue a file for printing. (This situation is shown in figure below)




Figure: Two processes want to access shared memory at the same time

.

- Let's assume the following situation
 - Process A reads in and stores the value, 7, in a local variable called next free slot
 - Just then a clock interrupt occurs and the CPU decides that process A has run long enough, so it switches to process B.
 - **Process** *B* **also reads** *in* and also gets a 7. It, too, stores it in *it's* local variable next free slot
 - At this instant both processes think that the next available slot is 7.
 - **Process B now continues to run**. It stores the name of its file in slot 7 and updates *in* to be an 8. Then it goes off and does other things.
 - Eventually, **process** *A* **runs again**, starting from the place it left off. It looks at $next_free_slot$, finds a 7 there, and writes its file name in slot 7, erasing the name that process *B* just put there. Then it computes next free slot + 1, which is 8, and sets in to 8.
 - The spooler directory is now internally consistent, so the printer daemon will not notice anything wrong, but process *B* will never receive any output.
 - User *B* will hang around the printer for years, wistfully hoping for output that never comes
 - This situation is **race condition**

How to avoid races

- ✓ **Mutual exclusion**—only one process at a time can use a shared variable/file
- ✓ **Critical regions-**shared memory which leads to races
- ✓ **Solution-** Ensure that two processes can't be in the critical region at the same time

Critical Regions (Critical Sections)

- Sometimes a process has to access shared memory or files, or do other critical things that can lead to races.
- That part of the program where the shared memory is accessed is called the **critical region** or **critical section**.
- If we could arrange matters such that no two processes were ever in their critical regions at the same time, we could avoid races.
- Although this requirement avoids race conditions, *it is not sufficient* for having parallel processes cooperate correctly and efficiently using shared data. We need following four conditions to hold to have a good solution: (**Properties of a good solution**)
 - No two processes may be simultaneously inside their critical regions. (Mutual exclusion)
 - 2. No assumptions may be made about speeds or the number of CPUs.
 - 3. No process running outside its critical region may block any process.
 - 4. No process should have to wait forever to enter its critical region. (*No starvation*)
- In an abstract sense, the behavior that we want is shown in following figure.
 - Here process A enters its critical region at time T_1 .
 - ▶ A little later, at time T₂ process B attempts to enter its critical region but fails because another process is already in its critical region and we allow only one at a time.
 - ▶ Consequently, B is temporarily suspended until time T₃ when A leaves its critical region, allowing B to enter immediately.
 - ▶ Eventually B leaves (at T₄) and we are back to the original situation with no processes in their critical regions.




Figure: Mutual exclusion using critical regions

Implementing Mutual Exclusion

- The key to avoid race conditions in situations involving shared memory, shared files, and shared everything else is to find some way to prohibit more than one process from reading and writing the shared data at the same time. Put in other words, what we need is **mutual exclusion**, that is, some way of making sure that if one process is using a shared variable or file, the other processes will be excluded from doing the same thing.
- ▶ There are different ways to implement mutual exclusion

Mutual Exclusion with Busy Waiting

- ▶ Techniques for achieving mutual exclusion, so that while one process is busy updating shared memory in its critical region, no other process will enter its critical region and cause trouble.
 - Disabling interrupts
 - Lock variables
 - Strict alternation
 - Peterson's solution
 - * Test and Set Lock (The TSL Instruction)

Disabling interrupts

- ▶ On a single-processor system, the simplest solution is to have each process disable all interrupts just after entering its critical region and re-enable them just before leaving it.
- ▶ **Idea:** process disables interrupts, enters critical region, enables interrupts when it leaves critical region.

▶ Problems:

- It is unwise to give user processes the power to turn off interrupts. Process might never enable interrupts, crashing system
- Won't work on multi-core chips (or multiprocessor system) as disabling interrupts only
 effects one CPU at a time.
 - Disabling interrupts affects only the CPU that executed the disable instruction.
 The other ones will continue running and can access the shared memory.

Lock variables

- It is a software solution.
- Consider having a single, shared (lock) variable, initially 0.
- When a process wants to enter its critical region, it first tests the lock.
 - o If the lock is 0, the process sets it to 1 and enters the critical region.
 - o If the lock is already 1, the process just waits until it becomes 0.

Thus.

- \Im lock = 0 => no process is in its critical section
- $rac{1}{2}$ lock = 1 => some process is in its critical section.

Problem:

* Race condition

- ▶ If process P₁ sees the value of lock variable 0 and before it can set it to 1 context switch occurs.
- ▶ Now process P₂ runs and finds value of lock variable 0, so it sets value to 1, enters critical region.
- ▶ At some point of time P₁ resumes, sets the value of lock variable to 1, enters critical region.

Now two processes are in their critical regions accessing the same shared memory, which violates the mutual exclusion condition.

Strict alternation

- This approach is the software mechanism implemented at user mode.
- It is a busy waiting solution which can be implemented only for two processes.
- In this approach, the integer variable **turn**, initially 0, keeps track of whose turn it is to enter the critical region and examine or update the shared memory
 - ✓ Initially, **turn** value is set to 0.
 - ✓ turn = 0 means it is the turn of process P_0 to enter the critical section.
 - ✓ **turn** = 1 means it is the turn of process P_1 to enter the critical section.
- IDEA: First me, then you!

```
while (TRUE) {
                                                 while (TRUE) {
                          /* loop */;
                                                                            /* loop */;
   while (turn != 0)
                                                     while (turn != 1)
   critical_region();
                                                     critical_region():
   turn = 1:
                                                     turn = 0;
   noncritical_region();
                                                     noncritical_region();
}
                                                 }
               (a)
                                                                 (b)
```

Figure: A proposed solution (Strict alternation) to the critical-region problem. (a) Process 0. (b) Process 1.

This mechanism works as explained in the following scenes-

Scenario 1	Scenario 2	Scenario 3
 Process 0 (P₀) arrives. It executes the <i>turn!</i> =0 instruction. Since <i>turn</i> value is set to 0, so it returns 0 (i.e. FALSE) to the while loop. The while loop condition breaks. Process P₀ enters the critical section and executes. Now, even if process P₀ gets preempted in the middle, process P1 cannot enter the critical section. Process 1(P₁) cannot enter unless process P₀ completes and sets the turn value to 1. 	 Process P1 arrives. It executes the <i>turn!</i> = 1 instruction. Since <i>turn</i> value is set to 0, so it returns 1 (i.e. TRUE) to the while loop. The returned value 1 does not break the while loop condition. The process P1 is trapped inside an infinite while loop. (busy waiting) The while loop keeps the process P1 busy until the <i>turn</i> value becomes 1 and its condition breaks. 	 Process P₀ comes out of the critical section and sets the <i>turn</i> value to 1. The while loop condition of process P₁ breaks. Now, the process P₁ waiting for the critical section enters the critical section and execute. Now, even if process P₁ gets preempted in the middle, process P₀ cannot enter the critical section.

Problems with strict alternation

Consider following scenario:

- Process 0 (P₀) exits the critical region and sets *turn* to 1. Process 1 (P₁) is also executing in non-critical region At this point turn is 1 and both processes are executing in their noncritical regions.
- Suddenly, P_0 finishes its noncritical region and goes back to the top of its loop. Unfortunately, it is not permitted to enter its critical region now, because *turn* is 1 and P_1 is busy with its noncritical region. It hangs in its while loop until process P_1 sets *turn* to 0.

This situation violates condition 3 set out above ("No process running outside its critical region may block any process."): process 0 is being blocked by a process not in its critical region.

- Taking turns is not a good idea when one of the processes is much slower than the other.
- Problems:
 - Employs busy waiting-while waiting for the cr, a process spins
 - If one process is outside the cr and it is its turn, then other process has to wait until outside guy finishes both outside AND inside (cr) work

NOTES:

- ❖ Continuously testing a variable until some value appears is called *busy waiting*. It should usually be avoided, since it wastes CPU time. Only when there is a reasonable expectation that the wait will be short is busy waiting used. A lock that uses busy waiting is called a *spin lock*.
- ❖ In fact, this solution (strict alternation) requires that the two processes **strictly alternate in entering their critical regions,** for example, in spooling files. Neither one would be permitted to spool two in a row. While this algorithm does avoid all races, it is not really a serious candidate as a solution because it violates condition 3.

Peterson's Solution

- ❖ It is a classical software-based solution to the critical section
- This solution is restricted to two processes that alternate execution between their critical sections and remainder sections.

```
#define FALSE 0
#define TRUE
#define N
                2
                                          /* number of processes */
int turn:
                                          /* whose turn is it? */
int interested[N]:
                                          /* all values initially 0 (FALSE) */
void enter_region(int process);
                                          /* process is 0 or 1 */
     int other;
                                          /* number of the other process */
                                          /* the opposite of process */
     other = 1 - process;
     interested[process] = TRUE;
                                          /* show that you are interested */
     turn = process:
                                          /* set flag */
     while (turn == process && interested[other] == TRUE) /* null statement */;
}
void leave_region(int process)
                                         /* process: who is leaving */
     interested[process] = FALSE;
                                         /* indicate departure from critical region */
}
```

Figure: Peterson's solution for achieving mutual exclusion.

- Before using the shared variables (i.e., before entering its critical region), each process calls **enter region** with its own process number, 0 or 1, as parameter.
 - This call will cause it to wait, if need be, until it is safe to enter.
- After it has finished with the shared variables, the process calls **leave_region** to indicate that it is done and to allow the other process to enter, if it so desires.
- Let us see how this solution works. Initially neither process is in its critical region.
 - o Now process 0 calls *enter_region*.
 - It indicates its interest by setting its array element and sets *turn* to 0.
 - Since process 1 is not interested, *enter_region* returns immediately. (no busy waiting)
 - If process 1 now makes a call to *enter_region*, it will hang there until *interested*[0] goes to *FALSE*, an event that happens only when process 0 calls *leave_region* to exit the critical region.
 - Now consider the case that both processes call *enter region* almost simultaneously.
 Both will store their process number in *turn*. Whichever store is done last is the one that counts; the first one is overwritten and lost.
 - Suppose that process 1 stores last, so turn is 1. When both processes come to the while statement, process 0 executes it zero times and enters its critical region.
 - Process 1 loops and does no enter its critical region until process 0 exits its critical region.

Disadvantages:

- ▶ Peterson's solution is limited to two processes.
- ▶ It involves Busy Waiting.

Test and Set Lock

- Hardware based solution.
- It uses a test and set instruction to provide the synchronization among the processes executing concurrently.
- Some computers, especially those designed with multiple processors in mind, have an instruction like TSL RX, LOCK (Test and Set Lock) that works as follows.
 - It reads the contents of the memory word *lock* into register RX and then stores a nonzero value at the memory address *lock*.
 - ** TSL reads lock into register and stores NON ZERO VALUE in lock (e.g. process number)
 - The operations of reading the word and storing into it are guaranteed to be indivisible no other processor can access the memory word until the instruction is finished. The CPU executing the TSL instruction locks the memory bus to prohibit other CPUs from accessing memory until it is done.
 - * Instruction is atomic: done by freezing access to memory bus line (bus is disabled)
 - TSL instruction is an instruction that returns the old value of a memory location and sets the memory location value to nonzero as a single atomic operation.
 - If one process is currently executing a test-and-set, no other process is allowed to begin another test-and-set until the first process test-and-set is finished.
 - TSL is atomic. Memory bus is locked until it is finished executing.
- To use the TSL instruction, a shared variable, *lock*, is used to coordinate access to shared memory.
 - When *lock* is 0, any process may set it to 1 using the TSL instruction and then read or write the shared memory.
 - When it is done, the process sets *lock* back to 0 using an ordinary move instruction.
 - \square *lock* = 0 means the critical section is currently vacant and no process is present inside it.
 - \square *lock* = 1 means the critical section is currently occupied and a process is present inside it.

```
enter_region:

TSL REGISTER,LOCK

CMP REGISTER,#0

JNE enter_region

RET

| copy lock to register and set lock to 1
| was lock zero?
| if it was nonzero, lock was set, so loop
| return to caller; critical region entered

| leave_region:
| MOVE LOCK,#0
| RET | store a 0 in lock
| return to caller
```

Figure:: Entering and leaving a critica:region using the TSL instruction.

- ➤ The TSL instruction can be used to prevent two processes from simultaneously entering their critical regions. The solution is given in above figure (algorithm).
- There a four-instruction subroutine (*enter_region*) in a fictitious (but typical) assembly language is shown.
 - ▶ The first instruction (*TSL REGISTER*, *LOCK*) copies the old value of lock to the register and then sets lock to 1.
 - ▶ Then the old value is compared with 0 (CMP REGISTER, #0).
 - ▶ If it is nonzero, the lock was already set, so the program just goes back to the beginning and tests it again. (*REGISTER*, #0)
 - ▶ Sooner or later it will become 0 (when the process currently in its critical region is done with its critical region), and the subroutine returns, with the lock set. (*RET*)
- ▶ Another subroutine, *Leave_region* is used for clearing the lock which is very simple. The program just stores a 0 in lock. No special synchronization instructions are needed.

Disadvantages:

- ▶ It is a busy waiting solution which keeps the CPU busy when the process is actually waiting.
- ▶ TSL doesn't provide Architectural Neutrality. It depends on the hardware platform. The TSL instruction is provided by the operating system. Some platforms might not provide that. Hence it is not Architectural natural.

Main Problem in Peterson's solution and TSL instruction

- ▶ Both Peterson's solution and the solutions using TSL are correct, but both have the defect of requiring busy waiting.
- In essence, what these solutions do is this: when a process wants to enter its critical region, it checks to see if the entry is allowed. If it is not, the process just sits in a tight loop waiting until it is.
- Not only does this approach waste CPU time, but it can also have unexpected effects (Priority Inversion Problem)

Problems:

- ▼ Busy waiting waste of CPU time
- ▼ Priority Inversion Problem

Priority Inversion Problem

- Priority inversion is the situation when high priority process is waiting for low priority process.
- Consider a computer with two processes, H, with high priority, and L, with low priority.
 - The scheduling rules are such that H is run whenever it is in ready state.
 - At a certain moment, with L in its critical region, H becomes ready to run (e.g., an I/O operation completes).
 - H now begins busy waiting, but since L is never scheduled while H is running, L never gets the chance to leave its critical region, so H loops forever.
- This situation is sometimes referred to as the **priority inversion problem.**

Solutions:

There are some interposes communication primitives that block instead of wasting CPU time when they are not allowed to enter their critical regions.

Sleep and Wakeup

- There are some interposes communication primitives that block instead of wasting CPU time when they are not allowed to enter their critical regions. One of the simplest is the sleep and wakeup.
- As its name suggests, it uses two system calls: **sleep** and **wakeup**. If a process is unable to enter a critical section, it is put to sleep (i.e. temporarily suspended). Afterwards, when the critical section is no longer occupied, the process is woken up.
 - Sleep is a system call that causes the caller to block, that is, be suspended until another process wakes it up.
 - The wakeup call has one parameter, the process to be awakened.
- The concept of sleep and wake is very simple. If the critical section is not empty then the process will go and sleep. It will be waked up by the other process which is currently executing inside the critical section so that the process can get inside the critical section.

Example to show how the sleep and wakeup primitives are used

Producer Consumer Problem

- Also known as the bounded-buffer problem
- Two processes share a common, fixed-size buffer. One of them, the producer, puts information into the buffer, and the other one, the consumer, takes it out.




Figure: Producer-Consumer Problem

(It is also possible to generalize the problem to have \mathbf{m} producers and \mathbf{n} consumers, but we will consider only the case of one producer and one consumer because this assumption simplifies the solutions.)

- Trouble arises when the producer wants to put a new item in the buffer, but it is already full. The solution is for the producer to go to sleep, to be awakened when the consumer has removed one or more items. Similarly, if the consumer wants to remove an item from the buffer and sees that the buffer is empty, it goes to sleep until the producer puts something in the buffer and wakes it up.
- To keep track of the number of items in the buffer, we will need a variable, *count*. If the maximum number of items the buffer can hold is *N*,
 - The **producer's code** will first test to see if *count* is *N*. If it is, the producer will go to sleep; if it is not, the producer will add an item and increment count.
 - The consumer's code is similar: first test count to see if it is 0. If it is, go to sleep; if it is nonzero, remove an item and decrement the counter. Each of the processes also tests to see if the other should be awakened, and if so, wakes it up. The code for both producer and consumer is shown in following figure.

```
/* number of slots in the buffer */
#define N 100
                                                      /* number of items in the buffer */
int count = 0;
void producer(void)
     int item;
     while (TRUE) {
                                                      /* repeat forever */
           item = produce_item();
                                                      /* generate next item */
           if (count == N) sleep();
                                                      /* if buffer is full, go to sleep */
                                                      /* put item in buffer */
           insert_item(item):
                                                      /* increment count of items in buffer */
           count = count + 1;
           if (count == 1) wakeup(consumer);
                                                      /* was buffer empty? */
     }
}
void consumer(void)
     int item;
     while (TRUE) {
                                                      /* repeat forever */
           if (count == 0) sleep();
                                                      /* if buffer is empty, got to sleep */
           item = remove_item();
                                                      /* take item out of buffer */
           count = count - 1;
                                                      /* decrement count of items in buffer */
           if (count == N - 1) wakeup(producer);
                                                      /* was buffer full? */
           consume_item(item):
                                                      /* print item */
     }
}
```

Figure: The producer-consumer problem with a fatal race condition

Problem:

This approach sounds simple enough, but it leads to the same kinds of race conditions we saw earlier with the spooler directory. It can occur because access to *count* is unconstrained. As a consequence, the following situation could possibly occur.

- ▶ The buffer is empty and the consumer has just read *count* to see if it is 0.
- ▶ At that instant, the scheduler decides to stop running the consumer temporarily and start running the producer.
- ▶ The producer inserts an item in the buffer, increments *count*, and notices that it is now 1.
- Reasoning that *count* was just 0, and thus the consumer must be sleeping, the producer calls *wakeup* to wake the consumer up.
- ▶ Unfortunately, the consumer is not yet logically asleep, so the wakeup signal is lost.

- ▶ When the consumer next runs, it will test the value of *count* it previously read, find it to be 0, and **go to sleep**.
- ▶ Sooner or later the producer will fill up the buffer and also go to sleep. Both will sleep forever.

NOTE: The essence of the problem here is that a wakeup sent to a process that is not (yet) sleeping is lost. If it were not lost, everything would work.

Semaphore

- A semaphore is a variable that provides an abstraction for controlling access of a shared resource by multiple processes in a parallel programming environment.
- There are 2 types of semaphores:

1. Binary semaphores

- Binary semaphores can take only 2 values (0/1).
- Binary semaphores have 2 methods associated with it (up, down / lock, unlock).
- They are used to acquire locks.

2. Counting semaphores

— Counting semaphore can have possible values more man two.

NOTE: Dijkstra (1965) suggested using an integer variable to count the number of wakeups saved for future use. In his proposal, a new variable type, which he called a **semaphore**, was introduced. A semaphore could have the value 0, indicating that no wakeups were saved, or some positive value if one or more wakeups were pending.

- Two operations on semaphores : **down** and **up**
 - Down checks semaphore. If not zero, decrements semaphore. If zero, process goes to sleep
 - Up increments semaphore. If more than one process asleep, one is chosen randomly and enters critical region (first does a down)
- Checking the value, changing it, and possibly going to sleep, are all done as a single, indivisible atomic action. It is guaranteed that once a semaphore operation has started, no other process can access the semaphore until the operation has completed or blocked. This atomicity is absolutely essential to solving synchronization problems and avoiding race conditions.

The operation of incrementing the semaphore and waking up one process is also indivisible.
 No process ever blocks doing an up, just as no process ever blocks doing a wakeup in the earlier model.

Solving Producer-Consumer Problem using Semaphores

```
#define N 100
                                                 /* number of slots in the buffer */
typedef int semaphore;
                                                 /* semaphores are a special kind of int */
semaphore mutex = 1:
                                                 /* controls access to critical region */
semaphore empty = N;
                                                 /* counts empty buffer slots */
semaphore full = 0;
                                                 /* counts full buffer slots */
void producer(void)
     int item:
     while (TRUE) {
                                                 /* TRUE is the constant 1 */
           item = produce_item();
                                                 /* generate something to put in buffer */
           down(&empty);
                                                 /* decrement empty count */
           down(&mutex);
                                                 /* enter critical region */
           insert_item(item);
                                                 /* put new item in buffer */
           up(&mutex):
                                                 /* leave critical region */
           up(&full);
                                                 /* increment count of full slots */
     }
}
void consumer(void)
     int item;
     while (TRUE) {
                                                 /* infinite loop */
           down(&full);
                                                 /* decrement full count */
                                                 /* enter critical region */
           down(&mutex);
           item = remove_item();
                                                 /* take item from buffer */
           up(&mutex);
                                                 /* leave critical region */
                                                 /* increment count of empty slots */
           up(&empty);
           consume_item(item);
                                                 /* do something with the item */
     }
}
```

Figure: The producer-consumer problem using semaphores

- Three semaphores: *full, empty* and *mutex* are used in this solution.
 - Full counts full slots (initially 0)
 - Empty counts empty slots (initially N (number of slots in the buffer))
 - Mutex makes sure that the producer and consumer do not access at the same time. (initially 1)
- If each process does a down just before entering its critical region and an up just after leaving it, mutual exclusion is guaranteed
- We want functions *insert_item* and *remove_item* such that the following hold:
 - Mutually exclusive access to buffer: At any time only one process should be executing (either insert_item or remove_item).
 - *No buffer overflow:* A process executes insert_item only when the buffer is not full (i.e., the process is blocked if the buffer is full).
 - *No buffer underflow:* A process executes remove_item only when the buffer is not empty (i.e., the process is blocked if the buffer is empty).
 - *No busy waiting.*
 - *No producer starvation:* A process does not wait forever at insert_item() provided the buffer repeatedly becomes full.
 - No consumer starvation: A process does not wait forever at remove_item()
 provided the buffer repeatedly becomes empty.
- In this example semaphores are used in two different ways:
 - 1. **For Mutual Exclusion:** The *mutex* semaphore is used for mutual exclusion. It is designed to guarantee that only one process at a time will be reading or writing the buffer and the associated variables.
 - 2. **For Synchronization:** The *full* and *empty* semaphores are needed to guarantee that certain event sequences do or do not occur. In this case, they ensure that the producer stops running when the buffer is full, and that the consumer stops running when it is empty.

Limitations

≥ Little errors cause disasters.

- In Producer consumer with semaphores, interchange of two downs in producer code causes deadlock
 - Suppose that the two downs in the producer's code were reversed in order, so *mutex* was decremented before *empty* instead of after it.
 - If the buffer were completely full, the producer would block, with *mutex* set to 0.
 - Consequently, the next time the consumer tried to access the buffer, it would do a down on *mutex*, now 0, and block too.
 - Both processes would stay blocked forever and no more work would ever be done.
 - This unfortunate situation is a deadlock situation.

Mutexes

- When the semaphore's ability to count is not needed, a simplified version of the semaphore, called a mutex, is sometimes used. Mutexes are good only for managing mutual exclusion to some shared resource or piece of code. They are easy and efficient to implement, which makes them especially useful in thread packages that are implemented entirely in user space.
- A **mutex** is a shared variable that can be in one of two states: unlocked or locked. Consequently, only 1 bit is required to represent it, but in practice an integer often is used, with 0 meaning unlocked and all other values meaning locked.
- Two procedures are used with mutexes. When a thread (or process) needs access to a critical region, it calls *mutex lock*. If the mutex is currently unlocked (meaning that the critical region is available), the call succeeds and the calling thread is free to enter the critical region.
- On the other hand, if the mutex is already locked, the calling thread is blocked until the thread in the critical region is finished and calls *mutex unlock*.
- If multiple threads are blocked on the mutex, one of them is chosen at random and allowed to acquire the lock.
- Because mutexes are so simple, they can easily be implemented in user space
- provided that a TSL or XCHG instruction is available. The code for *mutex lock* and
- *mutex unlock* for use with a user-level threads package are shown below:

mutex_lock:

TSL REGISTER, MUTEX

CMP REGISTER,#0

JZE ok

CALL thread_yield

JMP mutex_lock

ok: RET

copy mutex to register and set mutex to 1

was mutex zero?

if it was zero, mutex was unlocked, so return

mutex is busy; schedule another thread

try again

return to caller; critical region entered

mutex_unlock:

MOVE MUTEX,#0

RET

store a 0 in mutex return to caller

Monitors

— A higher-level synchronization primitive

- A **monitor** is a collection of procedures, variables, and data structures that are all grouped together in a special kind of module or package.
- Processes may call the procedures in a monitor whenever they want to, but they cannot directly access the monitor's internal data structures from procedures declared outside the monitor
- In a monitor it is the job of the compiler, not the programmer to enforce mutual exclusion.
- Monitors have an important property that makes them useful to achieve mutual exclusion: only one process at a time can be in the monitor.
- Monitor is a **language construct** which enforces mutual exclusion and blocking mechanism
- C does not have monitor

```
monitor example
    integer i;
    condition c;

procedure producer();
...
end;

procedure consumer();
...
end;
end monitor;
```

Figure: A monitor - a picture

- Only one process at a time can be in the monitor
 - When a process calls a monitor, the first thing done is to check if another process is in the monitor. If so, calling process is suspended.
- Need to enforce blocking as well
 - Use condition variables
 - Use wait, signal operations on condition variables
- When a monitor discovers that it can't continue (e.g. buffer is full), issues a signal on a condition variable (e.g. full) causing process (e.g. producer) to block
- Another process is allowed to enter the monitor (e.g. consumer). This process can issue a signal, causing blocked process (producer) to wake up
- Process issuing signal leaves monitor

A skeleton of the **producer-consumer problem with monitors** is given in following figure in an imaginary language, Pidgin Pascal

```
monitor ProducerConsumer
      condition full, empty;
      integer count;
      procedure insert(item: integer);
      begin
            if count = N then wait(full);
            insert_item(item);
            count := count + 1;
            if count = 1 then signal(empty)
      end;
      function remove: integer;
      begin
            if count = 0 then wait(empty);
            remove = remove_item;
            count := count - 1;
            if count = N - 1 then signal(full)
      end;
      count := 0;
end monitor;
procedure producer;
begin
      while true do
      begin
            item = produce_item;
            ProducerConsumer.insert(item)
      end
end;
procedure consumer;
begin
      while true do
      begin
            item = ProducerConsumer.remove;
            consume_item(item)
      end
end;
```

Figure: An outline of the producer-consumer problem with monitors. Only one monitor procedure at a time is active. The buffer has N slots

Limitations

- You need a language which supports monitors (eg: Java).
- OS's are written in C

NOTE:

- Monitors and semaphores only work for shared memory
- They don't work for multiple CPU's which have their own private memory (Eg: A distributed system consisting of multiple CPUs, each with its own private memory and connected by a local area network.)

Conclusion: The conclusion is that semaphores are too low level and monitors are not usable except in a few programming languages. Also, none of the primitives allow information exchange between machines. Something else (Message Passing) is needed.

Message Passing

- Message Passing is information exchange between machines
- This method of interprocess communication **uses two primitives**: *send* and *receive*, which, like semaphores and unlike monitors, are system calls rather than language constructs
- Two primitives in Message Passing
 - 1. Send: It is used to send the message.

send (destination, &message)

Here, *destination* is the process to which sender want to send *message* and message is what the sender wants to send.

2. Receive: It is used to receive the message.

receive (source,&message)

Here, *source* is the process that has sent message and *message* is what the sender has sent.

— Message passing is commonly used in parallel programming systems. One well-known message-passing system, for example, is MPI (Message-Passing Interface).

The Producer-Consumer Problem with Message Passing

```
#define N 100
                                               /* number of slots in the buffer */
void producer(void)
     int item;
                                               /* message buffer */
     message m;
     while (TRUE) {
          item = produce_item();
                                               /* generate something to put in buffer */
                                               /* wait for an empty to arrive */
          receive(consumer, &m);
                                               /* construct a message to send */
          build_message(&m, item);
                                               /* send item to consumer */
          send(consumer, &m);
     }
}
void consumer(void)
     int item, i;
     message m;
     for (i = 0; i < N; i++) send(producer, &m); /* send N empties */
     while (TRUE) {
          receive(producer, &m);
                                               /* get message containing item */
          item = extract_item(&m);
                                              /* extract item from message */
          send(producer, &m);
                                              /* send back empty reply */
                                               /* do something with the item */
          consume_item(item);
}
```

Classical IPC problems

Dining Philosophers Problem

- In 1965, Dijkstra posed and then solved a synchronization problem he called the **dining** philosophers problem. Since that time, everyone inventing yet another synchronization primitive has felt obligated to demonstrate how wonderful the new primitive is by showing how elegantly it solves the dining philosopher's problem.
- The problem can be stated quite simply as follows

Five philosophers are seated around a circular table. Each philosopher has a plate of spaghetti. The spaghetti is so slippery that a philosopher needs two forks to eat it. Between each pair of plates is one fork. The life of a philosopher consists of alternating periods of eating and thinking. When a philosopher gets sufficiently hungry, she tries to acquire her left and right forks, one at a time, in either order. If successful in acquiring two forks, she eats for a while, then puts down the forks, and continues to think. The key question is: Can you write a program for each philosopher that does what it is supposed to do and never gets stuck?




Figure: Lunch time in the Philosophy Department (Layout of Table in Dining Philosophers Problem).

- \square A dining table with N plates and N forks
- **☑** N Philosophers eat or think
- **☑** Eating needs two forks
- ☑ Pick one fork at a time
- **☑** How to prevent deadlock?
- An obvious solution is illustrated in following figure. The procedure *take_fork* waits until the specified fork is available and then seizes it.

```
#define N 5
                                               /* number of philosophers */
void philosopher(int i)
                                               /* i: philosopher number, from 0 to 4 */
     while (TRUE) {
                                               /* philosopher is thinking */
           think();
                                               /* take left fork */
           take_fork(i);
           take_fork((i+1) \% N);
                                               /* take right fork; % is modulo operator */
                                               /* yum-yum, spaghetti */
           eat();
           put_fork(i);
                                               /* put left fork back on the table */
                                               /* put right fork back on the table */
           put_fork((i+1) \% N);
     }
```

Figure: A nonsolution to the dining philosophers problem

- *Instruct each philosopher to behave as follows:*
 - ▶ Think until the left fork is available; when it is, pick it up
 - ▶ Think until the right fork is available; when it is, pick it up
 - ▶ Eat
 - ▶ Put the left fork down
 - ▶ Put the right fork down
 - ▶ Repeat from the start

- ➤ Unfortunately, this solution is wrong.
 - Suppose that all five philosophers take their left forks simultaneously.
 - None will be able to take their right forks, and there will be a **deadlock**.

➤ We could easily modify the program so that after taking the left fork, the program checks to see if the right fork is available. If it is not, the philosopher puts down the left one, waits for some time, and then repeats the whole process.

This proposal too, **fails**, although for a different reason:

- ▶ Suppose all the philosophers could start the algorithm simultaneously, picking up their left forks, seeing that their right forks were not available, putting down their left forks, waiting, and picking up their left forks again simultaneously, and so on, forever.
- A situation like this, in which all the programs continue to run indefinitely but fail to make any progress, is called **starvation**.


A solution presented below is deadlock-free and allows the maximum parallelism for an arbitrary number of philosophers.

- It uses an array, state, to keep track of whether a philosopher is eating, thinking, or hungry (trying to acquire forks).
- A philosopher may move into eating state only if neither neighbor is eating.
- Philosopher i's neighbors are defined by the macros LEFT and RIGHT. In other words, if i is 2, LEFT is 1 and RIGHT is 3
- The program uses an **array of semaphores**, one per philosopher, **so hungry philosophers** can block if the needed forks are busy.
- Note that each process runs the procedure philosopher as its main code, but the other procedures, take_forks, put_forks, and test, are ordinary procedures and not separate processes.
- A philosopher can only move to eating state if neither neighbor is eating.

```
#define N
                                            /* number of philosophers */
#define LEFT
                      (i+N-1)%N
                                            /* number of i's left neighbor */
                                            /* number of i's right neighbor */
#define RIGHT
                      (i+1)%N
                                            /* philosopher is thinking */
#define THINKING
#define HUNGRY
                      1
                                            /* philosopher is trying to get forks */
                                            /* philosopher is eating */
#define EATING
                      2
typedef int semaphore;
                                            /* semaphores are a special kind of int */
int state[N];
                                            /* array to keep track of everyone's state */
semaphore mutex = 1;
                                            /* mutual exclusion for critical regions */
semaphore s[N];
                                            /* one semaphore per philosopher */
void philosopher(int i)
                                            /* i: philosopher number, from 0 to N-1 */
     while (TRUE) {
                                            /* repeat forever */
                                            /* philosopher is thinking */
           think();
           take_forks(i);
                                            /* acquire two forks or block */
           eat();
                                            /* yum-yum, spaghetti */
           put_forks(i);
                                            /* put both forks back on table */
}
void take_forks(int i)
                                            /* i: philosopher number, from 0 to N-1 */
     down(&mutex);
                                            /* enter critical region */
                                            /* record fact that philosopher i is hungry */
     state[i] = HUNGRY;
                                            /* try to acquire 2 forks */
     test(i);
     up(&mutex);
                                            /* exit critical region */
                                            /* block if forks were not acquired */
     down(&s[i]);
}
                                            /* i: philosopher number, from 0 to N-1 */
void put_forks(i)
                                            /* enter critical region */
     down(&mutex);
     state[i] = THINKING;
                                            /* philosopher has finished eating */
     test(LEFT);
                                            /* see if left neighbor can now eat */
                                            /* see if right neighbor can now eat */
     test(RIGHT);
     up(&mutex);
                                            /* exit critical region */
}
void test(i) /* i: philosopher number, from 0 to N-1 */
     if (state[i] == HUNGRY && state[LEFT] != EATING && state[RIGHT] != EATING) {
           state[i] = EATING;
           up(&s[i]);
}
```

Figure : A solution to the dining philosophers problem

Sleeping Barber Problem



Figur:Barber Shop and Sleeping Barber

- ▶ This problem is based on a hypothetical barbershop with one barber.
- ▶ There is a barber shop which has one barber, one barber chair, and n chairs for waiting customers.
- ▶ The following rules apply:
 - If there is no customer, then the barber sleeps in his own chair.
 - When a customer arrives, he has to wake up the barber.
 - If there are many customers and the barber is cutting a customer's hair, then the remaining customers either wait if there are empty chairs in the waiting room or they leave if no chairs are empty.
 - When the barber finishes a haircut, he inspects the waiting room to see if there are any waiting customers and falls asleep if there are none.
- ▶ Based on a naïve analysis, the above description should ensure that the shop functions correctly, with the barber cutting the hair of anyone who arrives until there are no more customers, and then sleeping until the next customer arrives.

- ▶ In practice, there are a number of problems that can occur that are illustrative of general scheduling problems.
- ▶ Some cases: (problems)
 - A customer may arrive and observe that the barber is cutting hair, so he goes to the waiting room. While he is on his way, the barber finishes the haircut he is doing and goes to check the waiting room. Since there is no one there (the customer not having arrived yet), he goes back to his chair and sleeps. The barber is now waiting for a customer and the customer is waiting for the barber.
 - Two customers may arrive at the same time when there happens to be a single seat in the waiting room. They observe that the barber is cutting hair, go to the waiting room, and both attempt to occupy the single chair.
- ❖ The solution of this problem is to include three Semaphores.
 - The first one, customers, to count the number of customers present in the waiting room.
 - The second one, **barbers**, for the barber. 0 and 1 are used to signify if the barber is idle or not.
 - The third, **mutex**, is for mutual exclusion. It is needed for the program to run.
- ❖ We also need a variable, **waiting**, which also counts the waiting customers. The reason for having waiting is that there is no way to read the current value of a semaphore
- ❖ When the barber shows up for work in the morning, he executes the procedure **barber**, causing him to block on the semaphore **customers** because it is initially 0. The barber then goes to sleep. He stays asleep until the first customer shows up.
- ❖ When a customer arrives, he executes **customer**, starting by acquiring **mutex** to enter a critical region. If another customer enters shortly thereafter, the second one will not be able to do anything until the first one has released **mutex**. The customer then checks to see if the number of waiting customers is less than the number of chairs. If not, he releases **mutex** and leaves without a haircut.
- ❖ If there is an available chair, the customer increments the integer variable, waiting. Then he does an up on the semaphore customers, thus waking up the barber. At this point, the customer and the barber are both awake. When the customer releases mutex, the barber grabs it, does some housekeeping, and begins the haircut.
- * When the haircut is over, the customer exits the procedure and leaves the shop.

```
#define CHAIRS 5 /*number of chairs for waiting customers */
typedef int semaphore;
semaphore customers = 0;
                                 /* number of waiting customers */
semaphore barbers = 0; /* number of barbers waiting for customers */
semaphore mutex = 1;
                          /* for mutual exclusion */
void barber(void)
{
     while (TRUE)
    {
     down(&customers); /* go to sleep if number of customers is 0 */
      down(&mutex); /* acquire access to 'waiting' */
      waiting = waiting - 1; /* decrement count of waiting customers */
                           /* one barber is now ready to cut hair */
      up(&barbers);
                           /* release 'waiting' */
      up(&mutex);
      cut_hair(); /* cut hair, non-CR */
      }
}
void customer(void)
{
      down(&mutex); /* enter CR */
      if (waiting < CHAIRS)</pre>
      waiting = waiting + 1; /* increment count of waiting customers */
      up(&customers); /* wake up barber if necessary */
      up(&mutex); /* release access to 'waiting' */
      down(&barbers); /* wait if no free barbers */
      get_haircut(); /* non-CR */
      }
      else
      {
      up(mutex); /* shop is full, do not wait */
```

}

Assignment: Discuss about Readers - Writers problem in IPC with solution.

Process Scheduling

- When a computer is multiprogrammed, it frequently has multiple processes or threads competing for the CPU at the same time. This situation occurs whenever two or more of them are simultaneously in the ready state.
- If only one CPU is available, a choice has to be made which process to run next. The part of the operating system that makes the choice is called the **scheduler**, and the algorithm it uses is called the **scheduling algorithm**.

The **process scheduling** is the activity of the process scheduler that handles the removal of the running process from the CPU and the selection of another process on the basis of a particular strategy.

☑ Process scheduler selects among available processes for next execution on CPU core

Who cares about scheduling algorithms?

- Batch servers
- Time sharing machines
- Networked servers
- You care if you have a bunch of users and/or if the demands of the jobs differ

Who doesn't care about scheduling algorithms?

- PC's
 - One user who only competes with himself for the CPU

Process Behavior

Nearly all *processes alternate bursts of computing with (disk or network) I/O requests*. (Process execution consists of cycle of CPU execution and I/O wait).

Some processes, such as the one in following figure (a), *spend most of their time computing*, while other processes, such as the one shown in (b), *spend most of their time waiting for I/O*.




Figure: Bursts of CPU usage alternate with periods of waiting for I/O. (a) A CPU-bound process. (b) An I/O-bound process

- ☑ The processes which spends most of their time computing are called compute-bound or CPU bound process
- ☑ The processes which spends most of their time waiting for I/O are called **I/O bound** process
- ☑ **CPU Burst** is the time that a process spends on the CPU executing some code. CPU Burst deals with the **running state** of the process.
- ☑ **I/O Burst** is the time that a process spends in waiting for the completion of the I/O request. I/O Burst deals with the **waiting state** of the process.
- ☑ Compute-bound processes typically have long CPU bursts and thus infrequent I/O waits, whereas I/O-bound processes have short CPU bursts and thus frequent I/O waits.
- ✓ Note that the key factor is the length of the CPU burst, not the length of the I/O burst.
 - I/O-bound processes are I/O bound because they do not compute much between
 I/O requests, not because they have especially long I/O requests.
 - o It takes the same time to issue the hardware request to read a disk block no matter how much or how little time it takes to process the data after they arrive.

The basic idea: If an I/O-bound process wants to run, it should get a chance quickly so that it can issue its disk request and keep the disk busy

CPU Scheduler and Dispatcher

- Whenever the CPU becomes idle, the operating system must select one of the processes in the ready queue to be executed. The selection process is carried out by the **sort-term scheduler** (or **CPU scheduler**). The scheduler selects a process from the processes in memory that are ready to execute and allocates the CPU to that processes.
- ☑ The **dispatcher** is the module that gives control of the CPU to the processes selected by the short-term scheduler. The time it's takes for the dispatcher to stop one process and start another running is known as the **dispatch latency.**

When to Schedule?

A key issue related to scheduling is when to make scheduling decisions. It turns out that there are a variety of situations in which scheduling is needed.

- When a new process is created, a decision needs to be made whether to run the parent process or the child process.
- When a process exits. The process can no longer run (since it no longer exists), so some other process must be chosen from the set of ready processes.
- When a process blocks on I/O, on a semaphore, or for some other reason, another process has to be selected to run.
- When an I/O interrupt occur. If the interrupt came from an I/O device that has now completed its work, some process that was blocked waiting for the I/O may now be ready to run. It is up to the scheduler to decide whether to run the newly ready process, the process that was running at the time of the interrupt, or some third process.

Preemptive and Nonpreemptive Scheduling

Scheduling algorithms can be divided into two categories with respect to how they deal with clock interrupts.

Nonpreemptive Scheduling

- A **nonpreemptive** scheduling algorithm picks a process to run and then just lets it run until it blocks (either on I/O or waiting for another process) or voluntarily releases the CPU
- Even if it runs for many hours, it will not be forcibly suspended. In effect, no scheduling decisions are made during clock interrupts.

Preemptive Scheduling

- A **preemptive** scheduling algorithm picks a process and lets it run for a maximum of some fixed time.
- If it is still running at the end of the time interval, it is suspended and the scheduler picks another process to run (if one is available).
- Doing preemptive scheduling requires having a clock interrupt occur at the end of the time interval to give control of the CPU back to the scheduler.

In preemptive scheduling, the CPU is allocated to the processes for a limited time whereas, in Non-preemptive scheduling, the CPU is allocated to the process till it terminates or switches to the waiting state.

Scheduling Criteria

Different CPU-scheduling algorithms have different properties, and the choice of a particular algorithm may favor one class of processes over another. In choosing which algorithm to use in a particular situation, we must consider the properties of the various algorithms. Many criteria have been suggested for comparing CPU-scheduling algorithms. Some of them are as follows:

- **CPU utilization** keep the CPU as busy as possible
- Throughput number of processes that complete their execution per time unit
- **Turnaround time** amount of time to execute a particular process
- Waiting time amount of time a process has been waiting in the ready queue
- Response time amount of time it takes from when a request was submitted until the first response is produced

Turnaround Time = Completion Time - Arrival Time

Waiting Time = Turnaround Time – Burst Time

Response Time = First CPU Entry Time – Arrival Time

Categories of Scheduling Algorithms

In different environments different scheduling algorithms are needed. This situation arises because different application areas (and different kinds of operating systems) have different goals. In other words, what the scheduler should optimize for is not the same in all systems. Three environments worth distinguishing are

- 1. Batch systems.
- 2. Interactive systems.
- 3. Real time systems.

Scheduling Algorithm Goals

In order to design a scheduling algorithm, it is necessary to have some idea of what a good algorithm should do. Some goals depend on the environment (batch, interactive, or real time), but some are desirable in all cases. Some goals are listed below:

All systems

Fairness - giving each process a fair share of the CPU
Policy enforcement - seeing that stated policy is carried out
Balance - keeping all parts of the system busy

Batch systems

Throughput - maximize jobs per hour

Turnaround time - minimize time between submission and termination

CPU utilization - keep the CPU busy all the time

Interactive systems

Response time - respond to requests quickly Proportionality - meet users' expectations

Real-time systems

Meeting deadlines - avoid losing data Predictability - avoid quality degradation in multimedia systems

Scheduling Algorithm Optimization Criteria

- Max CPU utilization
- Max throughput
- Min turnaround time

- Min waiting time
- Min response time

Batch System Scheduling


- ❖ First-come first-served
- Shortest job first
- ❖ Shortest remaining time next

First-Come, First-Served (FCFS) Scheduling

- ❖ By far the simplest CPU-scheduling algorithm is the **first-come first-serve** (**FCFS**) scheduling algorithm.
- ❖ With this scheme, the process that requests the CPU first is allocated the CPU first.
- Processes are scheduled in the order they arrived.
- ❖ The implementation of the FCFS policy is easily managed with a FIFO queue.
- ❖ When a process enters the ready queue, its PCB is linked onto the tail of the queue. When the CPU is free, it is allocated to the process at the head of the queue. The running process is then removed from the queue.
- ❖ FCFS scheduling algorithm is nonpreemptive
- ***** Example:

Process ID	Arrival Time	Burst Time
P1	4	5
P2	6	4
P3	0	3
P4	6	2
P5	5	4

Gantt Chart for FCFS scheduling:



We know,

Turnaround Time = Completion Time – Arrival Time

Waiting Time = Turnaround Time – Burst Time

Process ID	Completion Time	Turnaround Time	Waiting Time
P1	9	9 - 4 = 5	5 - 5 = 0
P2	17	17 - 6 = 11	11 - 4 = 7
P3	3	3 - 0 = 3	3 - 3 = 0
P4	19	19 - 6 = 13	13 - 2 = 11
P5	13	13 - 5 = 8	8 - 4 = 4

- Average Turnaround Time = (5+11+3+13+8)/5 = 8 unit
- Average Turnaround Time = (0+7+0+11+4)/5 = 4.4 unit

Advantage:

- Tt is simple and fair.
- Tt can be easily implemented using queue data structure.
- Tt does not lead to starvation since every process gets chance to execute

Disadvantages:

- The average waiting time under the FCFS policy is often quite long.
- It does not consider the priority or burst time of the processes.
- © Convoy effect is possible.
 - o All small I/O bound processes wait for one big CPU bound process to acquire CPU.
 - Short process behind long process

Problem-01:

Consider the set of 5 processes whose arrival time and burst time are given below. If the CPU scheduling policy is FCFS, calculate the average waiting time and average turn-around time.

Process	Arrival time	Burst time
P1	3	4
P2	5	3
P3	0	2
P4	5	1
P5	4	3

Solution:

Gantt Chart-

0 2	2 3	3 7	' 1	10 1	13 1	4
P3		P1	P 5	P2	P4	

Here, black box represents the idle time of CPU.

Now, we know-

- Turnaround Time = Completion Time— Arrival Time
- Waiting time = Turnaround Time Burst time

Process	Completion time	Turnaround Time	Waiting Time
P1	7	7 – 3 = 4	4-4=0
P2	13	13 – 5 = 8	8 – 3 = 5
P3	2	2 - 0 = 2	2-2=0
P4	14	14 – 5 = 9	9 - 1 = 8
P5	10	10 – 4 = 6	6 - 3 = 3

Average Turnaround Time =
$$(4 + 8 + 2 + 9 + 6) / 5 = 29 / 5 = 5.8$$
 unit

Average Waiting Time =
$$(0 + 5 + 0 + 8 + 3) / 5 = 16 / 5 = 3.2$$
 unit

Problem-02:

Consider the set of 3 processes whose arrival time and burst time are given below. If the CPU scheduling policy is FCFS, calculate the average waiting time and average turn -around time.

Process	Arrival Time	Burst Time
P1	0	2
P2	3	1
P3	5	6

Solution:

Gantt Chart-



Here, black box represents the idle time of CPU.

Now, we know-

- Turnaround Time = Completion Time Arrival Time
- Waiting time = Turnaround Time Burst time

Process	Completion Time	Turnaround time	Waiting time
P1	2	2-0=2	2-2=0
P2	4	4 - 3 = 1	1 - 1 = 0
Р3	11	11-5=6	6 - 6 = 0

Now,

Average Turnaround time = (2 + 1 + 6) / 3 = 9 / 3 = 3 unit

Average waiting time = (0 + 0 + 0) / 3 = 0 / 3 = 0 unit

Shortest-Job-First (SJF) Scheduling

- Need to know run times in advance
- The process, that requires shortest time to complete execution is served first
- Associate with each process the length of its next CPU burst
 - Use these lengths to schedule the process with the shortest time
- The implementation of the SJF strategy is easily managed by using a FIFO queue.
 - All processes in a queue are sorted in ascending order by their required CPU bursts
 - When CPU becomes free, a process from first position in a queue is selected to run
- SJF may be optimal gives minimum average waiting time for a given set of processes.
 (Optimal only when the jobs are available simultaneously)
- Types: Preemptive and Nonpreemptive

•	Example:	<u>Processs</u>	<u>Arrival Time</u>	<u>Burst Time</u>
		P_1	0.0	6
		P_2	2.0	8
		P_3	4.0	7
		P_4	5.0	3

• SJF (preemptive) scheduling chart:

P_1	P_4	<i>P</i> ₃	P_2	
0	6	Q	16	24

- Turnaround Time = Completion Time Arrival Time
- Waiting time = Turnaround Time Burst time

Process	Completion Time	Burst Time	Turnaround Time	Waiting Time
P_1	6	6	6 - 0 = 6	6 - 6 = 0
P_2	24	8	24 - 2 = 22	22 - 8 = 14
P_3	16	7	16 - 4= 12	12 - 7 = 5
P_4	9	3	9 - 5 = 4	4 - 3 = 1

Average Turnaround time =
$$(6 + 22 + 12 + 4) / 4 = 44 / 4 = 11$$
 unit

Average waiting time =
$$(0 + 14 + 5 + 1) / 3 = 20 / 4 = 5$$
 unit

Advantages:

- Reduced average waiting time compared to FCFS
- Good responses for short processes

Disadvantages:

- It is difficult to estimate the time required for a process to execute
- Starvation is possible for long processes. They may wait forever.

Problem-01:

Consider the set of 5 processes whose arrival time and burst time are given below. If the CPU scheduling policy is SJF non-preemptive, calculate the average waiting time and average turn - around time.

Process	Arrival Time	Burst time
P1	3	1
P2	1	4
P3	4	2
P4	0	6
P5	2	3

Solution-

Gantt Chart-

() 6	5 7	' 9) 1	2 16
	P4	P1	P3	P5	P2

Now, we know-

- Turnaround time = Completion Time— Arrival time
- Waiting time = Turnaround time Burst time

Process Id	Completion Time	Turnaround time	Waiting time
P1	7	7 – 3 = 4	4-1=3
P2	16	16 – 1 = 15	15 – 4 = 11
P3	9	9 – 4 = 5	5-2=3
P4	6	6 - 0 = 6	6 - 6 = 0
P5	12	12 - 2 = 10	10 - 3 = 7

Now,

- Average Turnaround time = (4 + 15 + 5 + 6 + 10) / 5 = 40 / 5 = 8 unit
- Average waiting time = (3 + 11 + 3 + 0 + 7) / 5 = 24 / 5 = 4.8 unit

Exercise: Schedule the given processes using SJF preemptive and find average turnaround time and average waiting time

Process ID	Burst Time	Arrival Time
P0	8	5
P1	5	0
P2	9	4
P3	2	1

Shortest Remaining Time Next (SRTN) Scheduling

- Also called Shortest-Remaining-Time-First (SRTF) scheduling
- The process whose remaining running time is shortest, is served first.
- Preemptive version of SJF scheduling.
- When a new job arrives, its total time is compared to the current process' remaining time.
 - If the new job needs less time to finish than the current process, the current process is suspended and the new job is started (i.e. current process preempted)
- This strategy can also be implemented by using sorted FIFO queue.
 - All the processes in a queue are sorted in ascending order on their remaining run time
 - When CPU becomes free, a process from the first position of queue is selected to run.

Example:

<u>Process</u>	Arrival Time	Burst Time
P_1	0	8
P_2	1	4
P_3	2	9
P_4	3	5

Preemptive SJF (or SRTN or SRTF) Gantt Chart

	P ₁		P ₂	P_4	P_1		P_3	
()	1	5	5 1	0	17		26

Process	Completion	Burst Time	Turnaround	Waiting
	Time		Time	Time
P_1	17	8	17 - 0 = 17	17 - 8 = 9
P_2	5	4	5 - 1 = 4	4 - 4 = 0
P_3	26	9	26 - 2 = 24	24 - 9 = 15
P_4	10	5	10 - 3 = 7	7–5=2

Average waiting time = (17+4+24+7)/4 = 52/4 = 13

Average waiting time = (9+0+15+2)/4 = 26/4 = 6.5

Advantages:

- Less average waiting time than SJF
- This scheme allows new short jobs to get good service.

Disadvantages:

- Requires additional computation for calculating remaining time.
- Favors short processes. Starvation is possible for long processes. Long process may wait forever.
- Context switch overhead is there.

Problem-01:

Consider the set of 5 processes whose arrival time and burst time are given below:

Process	Arrival time	Burst time
P1	3	1
P2	1	4
P3	4	2
P4	0	6
P5	2	3

If the CPU scheduling policy is SJF preemptive, calculate the average waiting time and average turn-around time.

Solution:

Gantt Chart:

() 1	1 3	3 4	. 6	5 8	3 1	1 10	ô
	P4	P2	P1	P2	P3	P5	P4	

Now, we know-

- Turnaround Time = Completion Time Arrival Time
- Waiting time = Turnaround Time Burst time

Process	Completion Time	Turnaround time	Waiting time
P1	4	4-3=1	1 - 1 = 0
P2	6	6 - 1 = 5	5-4=1
P3	8	8 - 4 = 4	4-2=2
P4	16	16 - 0 = 16	16 - 6 = 10
P5	11	11 - 2 = 9	9 - 3 = 6

Now,

- Average Turn Around time = (1 + 5 + 4 + 16 + 9) / 5 = 35 / 5 = 7 unit
- Average waiting time = (0 + 1 + 2 + 10 + 6) / 5 = 19 / 5 = 3.8 unit

Problem-02:

• Consider the set of 6 processes whose arrival time and burst time are given below. If the CPU scheduling policy is shortest remaining time first, calculate the average waiting time and average turn -around time.

Process	Arrival time	Burst time
P1	0	7
P2	1	5
P3	2	3
P4	3	1
P5	4	2
P6	5	1

Solution:

Gantt chart:

(0 1	l :	2 3	3 4	1 6	3 7	7 9	9 1	3 1	9
	P1	P2	P3	P4	P3	P 6	P 5	P2	P1	

Process	Completion Time	Turn Around time	Waiting time
P1	19	19 – 0 = 19	19 - 7 = 12
P2	13	13 - 1 = 12	12 - 5 = 7
P3	6	6 - 2 = 4	4 - 3 = 1
P4	4	4 - 3 = 1	1 - 1 = 0
P5	9	9 - 4 = 5	5 - 2 = 3
P6	7	7-5=2	2 - 1 = 1

Average Turn Around time =
$$(19 + 12 + 4 + 1 + 5 + 2) / 6 = 43 / 6 = 7.17$$
 unit

Average waiting time =
$$(12 + 7 + 1 + 0 + 3 + 1) / 6 = 24 / 6 = 4$$
 unit

Exercises:

1. Consider the set of 3 processes whose arrival time and burst time are given below. If the CPU scheduling policy is SRTF, calculate the average waiting time and average turn-around time. (Answer: 5, 12.33)

Process	Arrival time	Burst time
P1	0	9
P2	1	4
P3	2	9

2. Consider the set of following four processes whose arrival time and burst time are given in milliseconds. Now schedule the processes using SJF and SRTF and also compare the average waiting time. (Answer: SJF = 4, SRTF = 3)

Arrival Time	Burst Time
0.0	7
2.0	4
4.0	1
5.0	4
	0.0 2.0 4.0

3. Consider the set of 4 processes whose arrival time and burst time are given below. If the CPU scheduling policy is SRTF, calculate the average waiting time and average turn-around time.


Process ID		Arrivo	l Time		Burst Time	
P1		(0		10	
P2			3		6	
P3		;	7		1	
P4		1	В		3	
0 3	3	7 8	10	13	5	20
P1	P2	P3	P2	P4	P1	

Scheduling in Interactive Systems

- Round robin
- Priority
- Multiple Queues

Round-Robin (RR) Scheduling

- ☑ One of the oldest, simplest, fairest, and most widely used algorithms
- ☑ Each process is assigned a time interval, called **time quantum or time slice**.
- ☑ The process is allowed to run only for this time interval (time quantum).
- ☑ Here, two scenarios are possible:
 - A process is either blocked or terminated before the quantum has elapsed. In this case CPU switching is done and another process (if any) is scheduled to run.
 - The process needs CPU burst longer than the time quantum. In this case process runs till the end of time quantum. Then it is preempted and another process runs. The preempted process is added to the end of ready queue.



- When a quantum time is over or process completes execution (whichever is earlier), it starts new process. Selection of new process is as per FCFS scheduling algorithm.
- ☑ This strategy can be implemented using FIFO queue.
 - If any process comes, or process releases CPU, or process is preempted. It is moved to the end of the queue.


The ready queue is treated as circular queue.

- ☑ When CPU becomes free, a process from the first position in a queue is selected to run.
- \square If there are *n* processes in the ready queue and the time quantum is *q*, then each process gets 1/n of the CPU time in chunks of at most *q* time units at once. No process waits more than (n-1)q time units.

Example: RR Scheduling with quantum = 4 (Arrival time is 0 for all processes)

<u>Process</u>	Burst Time
P_1	24
P_2	3
P_3	3

The Gantt chart is:



Process ID	Completion Time	Turnaround Time	Waiting Time
P1	30	30 - 0 = 30	30 - 24 = 6
P2	7	7 - 0 = 7	7 - 3 = 4
P3	10	10 - 0 = 10	10 - 3 = 7

- Average Turnaround time = (30 + 7 + 10) / 3 = 47 / 3 = 15.66 unit
- Average waiting time = (6+4+7)/3 = 17/3 = 5.66 unit

Advantages:

- * It is simple, fare and most widely used algorithm.
- Don't need to know run times in advance
- Tt gives the best performance in terms of average response time.
- Tt is best suited for time sharing system, client server architecture and interactive system.

Disadvantages:

- There is the overhead of context switch.
- It's performance heavily depends on time quantum. Selection of time quantum is crucial.
 - If time quantum is too short, it causes frequent context switches and lowers CPU efficiency.
 - If it is too long, it causes poor response for short interactive processes.
- Priorities cannot be set for the processes.

NOTES:

- ☑ 80% of CPU bursts should be shorter than quantum time
- ☑ A quantum around 20–50 msec is often a reasonable compromise

Problem-01:

Consider the set of 5 processes whose arrival time and burst time are given below. If the CPU scheduling policy is Round Robin with time quantum = 2 unit, calculate the average waiting time and average turn-around time.

Process Id	Arrival time	Burst time
P1	0	5
P2	1	3
P3	2	1
P4	3	2
P5	4	3

Solution-

Gantt Chart-

0 2	2 4	1 5	5 7	' 9	9 1	1 1	12 1	3 14	4
P1	P2	P 3	P1	P4	P 5	P2	P1	P 5	

Process	Completion Time	Turn Around time	Waiting time
P1	13	13 - 0 = 13	13 - 5 = 8
P2	12	12 – 1 = 11	11 - 3 = 8
P3	5	5 - 2 = 3	3 - 1 = 2
P4	9	9 - 3 = 6	6-2=4
P5	14	14 - 4 = 10	10 - 3 = 7

- Average Turnaround time = (13 + 11 + 3 + 6 + 10) / 5 = 43 / 5 = 8.6 unit
- Average waiting time = (8 + 8 + 2 + 4 + 7) / 5 = 29 / 5 = 5.8 unit


Problem-02:

Consider the set of 6 processes whose arrival time and burst time are given below. If the CPU scheduling policy is Round Robin with time quantum = 2, calculate the average waiting time and average turn-around time.

Process	Arrival time	Burst time
P1	0	4
P2	1	5
P3	2	2
P4	3	1
P5	4	6
P6	6	3

Solution-

Gantt chart-



Process	Completion Time	Turnaround time	Waiting time
P1	8	8 - 0 = 8	8 - 4 = 4
P2	18	18 - 1 = 17	17 - 5 = 12
P3	6	6 - 2 = 4	4 - 2 = 2
P4	9	9 - 3 = 6	6 - 1 = 5
P5	21	21 - 4 = 17	17 - 6 = 11
P6	19	19 - 6 = 13	13 - 3 = 10

- Average Turn Around time = (8 + 17 + 4 + 6 + 17 + 13) / 6 = 65 / 6 = 10.84 unit
- Average waiting time = (4 + 12 + 2 + 5 + 11 + 10) / 6 = 44 / 6 = 7.33 unit

Problem-03:

Consider the set of 4 processes whose arrival time and burst time are given below. If the CPU scheduling policy is Round Robin with time quantum = 4, calculate the average waiting time and average turn-around time.

Process	Arrival time	Burst time
P0	0	10
P1	1	6
P2	3	2
P3	5	4

Exercise:

Consider the set of 6 processes whose arrival time and burst time are given below. If the CPU scheduling policy is Round Robin with time quantum = 3, calculate the average waiting time and average turn-around time. (Answer: 16, 21.33)

Process	Arrival time	Burst time
P1	5	5
P2	4	6
P3	3	7
P4	1	9
P5	2	2
P6	6	3

.

Priority Scheduling

Even on a PC with a single owner, there may be multiple processes, some of them more important than others. For example, a daemon process sending electronic mail in the background should be assigned a lower priority than a process displaying a video film on the screen in real time.

IDEA: Each process is assigned a priority, and the runnable process with the highest priority is allowed to run.

- A priority is associated with each process, and the CPU is allocated to the process with the highest priority
- Priorities can be assigned to processes statically or dynamically
- Priorities are generally indicated by some fixed range of numbers, such as 0 to 10 or 0 to
 4,095. However, there is no general agreement on whether 0 is the highest or lowest
 priority. Some systems use low numbers to represent low priority; others use low
 numbers for high priority.
- Equal-priority processes are scheduled in FCFS order.
- Round-robin scheduling makes the implicit assumption that all processes are equally important
- An SJF algorithm is simply a priority algorithm where the priority (p) is the inverse of the (predicted) next CPU burst. The larger the CPU burst, the lower the priority, and vice versa.
- Two types:
 - Preemptive
 - A preemptive priority scheduling algorithm will preempt the CPU if the priority of the newly arrived process is higher than the priority of the currently running process.
 - Nonpreemptive
 - A nonpreemptive priority scheduling algorithm will simply put the new process at the head of the ready queue.

Nonpreemptive Priority Scheduling

- The process, that has highest priority, is served first.
- Once a process is selected, it runs until it blocks for I/O or some event or it terminates
- This strategy can be implemented by using sorted FIFO queue.
 - ▶ All process in a queue are sorted based on their priority with highest priority process at the front of the queue.
 - ▶ When CPU becomes free, a process from the first position in a queue is selected to run.

Example: (lower integer represents higher priority and, arrival time of all process is 0 and order of arrival is P_1 , P_2 , P_3 , P_4 , P_5)

<u>Process</u>	<u>Burst Time</u>	<u>Priority</u>
P_{1}	10	3
P_2	1	1
P_3	2	4
P_4	1	5
P_5	5	2

Priority scheduling Gantt Chart



Average waiting time = 8.2

Advantages:

▶ Priority is considered, so critical processes can get better response

Disadvantages:

▶ Starvation – low priority processes may never execute

NOTE: This problem can be solve by using the technique, aging.

- ☑ Aging— gradually increase the priority of processes that wait in the system for a long time.
- ☑ For example, if priorities range from 127 (low) to 0 (high), we could periodically (say, every second) increase the priority of a waiting process by 1. Eventually, even a process with an initial priority of 127 would have the highest priority in the system and would be executed. In fact, it would take a little over 2 minutes for a priority-127 process to age to a priority-0 process.


Preemptive Priority Scheduling

- The process, that has highest priority, is served first
- When a new process arrives, it's priority is compared with priority of currently running process.
 - ▶ If the new process has higher priority than the current process, the currently running process is suspended and new process is allowed to run.
- This strategy can be implemented by using sorted FIFO queue.
 - ▶ All process in a queue are sorted based on their priority with highest priority process at the front of the queue.
 - ▶ When CPU becomes free, a process from the first position in a queue is selected to run.

Example: (lower integer represents higher priority)

Process	Arrival Time	Burst Time	Priority
P0	0	10	5
P1	1	6	4
P2	3	2	2
P3	5	4	0

▶ Priority scheduling Gantt Chart



We know,

Turnaround Time = Exit - Arrival Time

Waiting Time = Trunaround Time – Burst Time

Process	Arrival	Burst	Completion	Turnaround	Waiting Time
	Time	Time	Time	Time	
P0	0	10	22	22 - 0 = 22	22–10 = 12
P1	1	6	13	13 - 1 = 12	12 - 6 = 6
P2	3	2	5	5 - 3 = 2	2-2=0
P3	5	4	9	9-5=4	4-4=0

- Average Turnaround time = (22+12+2+4)/4 = 40/4 = 10 unit
- Average waiting time = (12 + 6 + 0 + 0) / 4 = 18 / 4 = 4.5 unit

Advantages:

▶ Priority is considered, so critical processes can get better response

Disadvantages:

- ► Starvation low priority processes may never execute (solution : aging)
- Context switching overhead is there.

Problem 01:

Consider the following 7 processes P1, P2, P3, P4, P5, P6 and P7. Schedule the process using nonpreemptive priority scheduling algorithm and compute the average turn-around time and average waiting time. (Lower integer represents higher priority)

Process ID	Priority	Arrival Time	Burst Time
P1	2	0	3
P2	6	2	5
P3	3	1	4
P4	5	4	2
P5	7	6	9
P6	4	5	4
P7	10	7	10

Solution:

Gantt chart:

P	1	Р3	P6	P4	P2	P5	P7	
()	3	7	11	13	18	27	37

Process	Priority	Arrival	Burst	Completion	Turnaround	Waiting
Id		Time	Time	Time	Time	Time
P1	2	0	3	3	3 - 0 = 3	3-3=0
P2	6	2	5	18	18 - 2 = 16	16 – 5 = 11
P3	3	1	4	7	7 - 1 = 6	6 - 4 = 2
P4	5	4	2	13	13 - 4 = 9	9-2 = 7
P5	7	6	9	27	27-6 = 21	21 - 9 = 12
P6	4	5	4	11	11 - 5 = 6	6–4 = 2
P7	10	7	10	37	37 - 7 = 30	30 – 10 = 20

- Average Turnaround time = (3+16+6+9+21+6+30)/7 = 91/7 = 13 unit
- Average waiting time = (0 + 11 + 2 + 7 + 12 + 2 + 20) / 7 = 54 / 7 = 7.714 unit

Problem-02:

Consider the set of 5 processes whose arrival time and burst time are given below. If the CPU scheduling policy is priority preemptive, calculate the average waiting time and average turnaround time. (Higher number represents higher priority)

Process Id	Arrival time	Burst time	Priority
P1	0	4	2
P2	1	3	3
P3	2	1	4
P4	3	5	5
P5	4	2	5

Solution:

Gantt Chart-

(0 1	1 2	2 3	8 8	3 1	0 1	2 1	5
	P1	P2	P 3	P4	P 5	P2	P1	

Process Id	Completion Time	Turnaround time	Waiting time
P1	15	15 - 0 = 15	15 - 4 = 11
P2	12	12 - 1 = 11	11 - 3 = 8
P3	3	3-2=1	1 - 1 = 0
P4	8	8 - 3 = 5	5 - 5 = 0
P5	10	10 - 4 = 6	6 - 2 = 4

Now,

- Average Turn Around time = (15 + 11 + 1 + 5 + 6) / 5 = 38 / 5 = 7.6 unit
- Average waiting time = (11 + 8 + 0 + 0 + 4) / 5 = 23 / 5 = 4.6 unit

Another Example:

Priority Scheduling with Round-Robin

(Smaller value of priority represents higher priority arrival time of all process is 0)

Process	Burst Time	Priority
$P_{_{I}}$	4	3
P_{2}	5	2
$P_{\mathfrak{Z}}$	8	2
$P_{_{\mathcal{4}}}$	7	1
P_{s}	3	3

- Run the process with the highest priority. Processes with the same priority run round-robin
- Gantt Chart with time quantum = 2



Multilevel Queue Scheduling

- ⇒ With both priority and round-robin scheduling, all processes may be placed in a single queue, and the scheduler then selects the process with the highest priority to run.
- ⇒ A multilevel Queue Scheduling algorithm partitions the ready queue into several separate queues.
 - The processes are permanently assigned to one queue, generally based on some property of the process, such as memory space, process priority, or process type.
 - Each queue has its own scheduling algorithm.

Example: Separate queues might be used for foreground and background processes

 The foreground queue might be scheduled by an RR algorithm, while the background queue is scheduled by an FCFS algorithm

Overview of Real Time System Scheduling

- A real-time system is one in which time plays an essential role.
- Real-time systems are generally categorized as **hard real time**, meaning there are absolute deadlines that must be met—or else!— and **soft real time**, meaning that missing an occasional deadline is undesirable, but nevertheless tolerable.
 - Hard Real Time System: robot control in a factory
 - Soft Real Time System: CD player
- The events that a real-time system may have to respond to can be further categorized as periodic (meaning they occur at regular intervals) or aperiodic (meaning they occur unpredictably).
- Real-time scheduling algorithms can be **static or dynamic**. The former (static) make their scheduling decisions before the system starts running. The latter (dynamic) make their scheduling decisions at run time, after execution has started.
 - Static scheduling works only when there is perfect information available in advance about the work to be done and the deadlines that have to be met.
 - Dynamic scheduling algorithms do not have these restrictions.


Process Deadlocks

Introduction

A set of processes is deadlocked if each process in the set is waiting for an event that only another process in the set can cause.

Because all the processes are waiting, none of them will ever cause any event that could wake up any of the other members of the set, and all the processes continue to wait forever.

Deadlocks are a set of blocked processes each holding a resource and waiting to acquire resource held by other process.



Figute: (a) process is requesting resource and a recource is in holding process (b) a deadlock scenario

Example:

- Two processes **A** and **B** each want to record a scanned document on a CD.
- A requests permission to use Scanner and is granted.
- **B** is programmed differently and requests the CD recorder first and is also granted.
- Now, **A** asks for the CD recorder, but the request is denied until **B** releases it. Unfortunately, instead of releasing the CD recorder **B** asks for Scanner. At this point both processes are blocked and will remain so forever. This situation is called **deadlock**.

Resources

- In short, a resource is anything that must be acquired, used, and released over the course
 of time.
- The resources include devices, data records, files, and so forth.
- A resource can be a hardware device (e.g., a Blu-ray drive) or a piece of information (e.g., a record in a database).
- A computer will normally have many different resources that a process can acquire.
- A major class of deadlocks involves resources to which some process has been granted exclusive access
- The abstract sequence of events required to use a resource is given below.
 - 1. Request the resource.
 - 2. Use the resource.
 - 3. Release the resource.

Preemptable and Non-preemptable Resources

- Resources come in two types: **preemptable** and **nonpreemptable**.
- A preemptable resource is that resource which can be taken away from the process owning it with no ill effects.

Example: Memory

- Consider, for example, a system with 1 GB of user memory, one printer, and two
 1-GB processes that each want to print something.
- Process A requests and gets the printer, then starts to compute the values to print. Before it has finished the computation, it exceeds its time quantum and is swapped out to disk.
- Process B now runs and tries, unsuccessfully as it turns out, to acquire the printer. Potenially, we now have a deadlock situation, because A has the printer and B has the memory, and neither one can proceed without the resource held by the other.
- Fortunately, it is possible to preempt (take away) the memory from B by swapping it out and swapping A in. Now A can run, do its printing, and then release the printer. No deadlock occurs.
- A **nonpreemptable resource**, is that resource which cannot be taken away from its current owner process without potentially causing failure.

Example: Blue-Ray recorder, Printer

- If a process has begun to burn a Blu-ray, suddenly taking the Blu-ray recorder away from it and giving it to another process will result in a garbled Blu-ray. Blu-ray recorders are **not preemptable** at an arbitrary moment.
- Whether a resource is preemptible depends on the context
- In general, deadlocks involve nonpreemptable resources.
- Potential deadlocks that involve preemptable resources can usually be resolved by reallocating resources from one process to another.

Deadlock Characterization

- Deadlock characterization describes the distinctive features that are the cause of deadlock occurrence
- The following four conditions must hold for there to be a (resource) deadlock
 - 1. Mutual exclusion condition.
 - Each resource is either currently assigned to exactly one process or is available.

2. Hold-and-wait condition.

 Processes currently holding resources that were granted earlier can request new resources.

3. No-preemption condition.

Resources previously granted cannot be forcibly taken away from a process.
 They must be explicitly released by the process holding them.

4. Circular wait condition.

— There must be a circular list of two or more processes, each of which is waiting for a resource held by the next member of the chain.

All four of these conditions must be present for a deadlock to occur

Resource – Allocation Graph

- The four conditions for deadlock can be modeled using directed graphs.
- The graphs have two kinds of nodes: processes, shown as circles, and resources, shown as squares.
- A directed arc from a resource node (square) to a process node (circle) means that the resource has previously been requested by, granted to, and is currently held by that process. In following figure (a), resource R is currently assigned to process A.
- A directed arc from a process to a resource means that the process is currently blocked waiting for that resource. In Figure (b), process B is waiting for resource S.
- In Figure (c) we see a deadlock: process C is waiting for resource T, which is currently held by process D. Process D is not about to release resource T because it is waiting for resource U, held by C. Both processes will wait forever.
- A cycle in the graph means that there is a deadlock involving the processes and resources in the cycle (assuming that there is one resource of each kind). In this example, the cycle is C T D –U C.




Figure: Resource allocation graphs. (a) Holding a resource. (b) Requesting a resource (c) Deadlock.

Basic Facts in resource allocation graph

- If graph contains no cycles \Rightarrow no deadlock
- If graph contains a cycle ⇒
 - if only one instance per resource type, then deadlock
 - if several instances per resource type, possibility of deadlock

Methods for Handling Deadlocks

In general, following four strategies are used for dealing with deadlocks

- 1. Just ignore the problem.
 - Maybe if you ignore it, it will ignore you.
- 2. Detection and recovery.
 - Let them occur, detect them, and take action.
- 3. Dynamic avoidance by careful resource allocation.
- 4. Prevention, by structurally negating one of the four conditions

Ostrich Algorithm

When storm approaches, an ostrich puts it's head in the sand (ground) and pretends (imagines) that there is no problem at all.

- "Stick your head in sand and pretend there is no problem at all"
- Deadlock ignorance strategy
- Ignore the deadlock and pretend that deadlock never occur
- Reasonable if
 - Deadlock occur very rarely
 - Deadlock is difficult to detect
 - Cost of deadlock prevention is high

Deadlock prevention

- o If we can ensure that at least one of four conditions of deadlock is never satisfied, then deadlocks will be structurally impossible
- To prevent the system from deadlocks, one of the four discussed conditions that may create a deadlock should be invalidated.
- o Deadlock can be prevented by attacking the one of the four conditions that leads to deadlock.
 - Attacking the Mutual Exclusion Condition
 - No deadlock if each resource can be assigned to more than one process.

- We cannot assign some resources to more than one process at a time such as CD Recorder, Printer etc...
- So this solution is not feasible.

Attacking the Hold and Wait Condition

- If we can prevent processes that hold resources from waiting for more resources, we can eliminate deadlocks
 - One way to achieve this goal is to require processes to request all their resources before starting execution.
 - A process is allowed to run if all resources it needed is available. Otherwise nothing will be allocated and it will just wait.
- Problem with this strategy is that a process may not know required resources at start of run.
- Resource will not be used optimally.

Attacking the No Preemption Condition

- When a process P0 request some resource R which is held by another process P1 then resource R is forcibly taken away from the process P1 and allocated to P0
- This strategy is tricky at best and impossible at worst.
- Consider a process holds the printer, halfway through its job; taking the printer away from this process without having any ill effect is not possible.
 - This is not a possible option.

Attacking the Circular Wait Condition

- The circular wait can be eliminated in several ways
- One way is simply to have a rule saying that a process is entitled only to a single resource at any moment. If it needs a second one, it must release the first one.
 - For a process that needs to copy a huge file from a tape to a printer, this restriction is unacceptable.
- Another way to avoid the circular wait is to provide a global numbering of all the resources, as shown in below
 - 1) Printer 2) Scanner
 - 3) Plotter 4) Tape Drive
 - 5) CD Rom

- Now the rule is that: processes can request resources whenever they want to, but all requests must be made in numerical order.
- A process need not acquire them all at once.
- Resource graph can never have cycle.
- Assume A has i and B has j are where i and j are distinct resources and they will have different numbers.
 - If i > j, then A is not allowed to request j because that is lower than what it already has.
 - If i < j, then B is not allowed to request i because that is lower than what it already has

A process may request 1st a printer, then tape drive. But it may not request 1st a plotter, then the printer.

Summary of approaches to deadlock prevention

Condition	Approach	
Mutual exclusion	Spool everything	
Hold and wait	Request all resources initially	
No preemption	Take resources away	
Circular wait	Order resources numerically	


Deadlock Avoidance

Given some additional information on how each process will request resources, it is possible to construct an algorithm that will avoid deadlock states. The algorithm will dynamically examine the resource allocation operations to ensure that there won't be a circular wait on resources. One of the deadlock avoidance algorithms is **Banker's algorithm**.

- Deadlock can be avoided by allocating resources carefully.
- Carefully analyze each resource request to see if it can be safely granted
- An algorithm is needed which can always avoid deadlock by making right choice all the time (one of such algorithms is Banker's Algorithm)

Safe and unsafe state

- Resource allocation state is defined by the number of available and allocated resources and
 the maximum demand of the processes. When a process requests an available resource,
 system must decide if immediate allocation leaves the system in a safe state
- A state is said to be **safe** if there is some scheduling order in which every process can run to completion even if all of them suddenly request their maximum number of resources immediately.
- From a safe state the system can guarantee that all processes will finish; from an unsafe state, no such guarantee can be given.
- If the system is in a safe state, there can be no deadlock. If the system is in an unsafe state, there is the possibility of deadlock.



Example: The state in following figure (a) is safe

- In following figure (a) we have a state in which
 - A total of 10 instances of the resource exist.
 - A has three instances of the resource but may need as many as nine eventually.
 - B currently has two and may need four altogether, later.
 - Similarly, C also has two but may need an additional five.
 - Seven resources already allocated, three tare still free.




Figure: Demonstration that the state in (a) is safe

- ☑ The state of figure (a) is safe because there exists a sequence of allocations that allows all processes to complete.
 - The scheduler can simply run B exclusively, until it asks for and gets two more instances of the resource, leading to the state of Fig. (b).
 - When B completes, we get the state of Fig.(c).
 - Then the scheduler can run C, leading eventually to Fig. (d).
 - When C completes, we get Fig (e).
 - Now A can get the six instances of the resource it needs and also complete.
 - Thus, the state of fig. (a) is safe because the system, by careful scheduling, can avoid deadlock.

But, state in following figure (b) is unsafe.




Figure : Demonstration that the state in (b) is not safe.

- Now suppose we have the initial state shown in Fig.(a), but this time A requests and gets another resource, giving Fig.(b).
- © Can we find a sequence that is guaranteed to work?
- Let us try.
 - The scheduler could run B until it asked for all its resources, as shown in Fig.(c).
 - Eventually, B completes and we get the state of Fig (d).
 - At this point we are stuck. We only have four instances of the resource free, and each of the active processes needs five.
- There is no sequence that guarantees completion.
- Thus, the allocation decision that moved the system from above Fig. (a) to (b) went from a safe to an unsafe state.

The Banker's algorithm

- The Banker's Algorithm is modeled on the way a small-town banker might deal with a group of customers to whom he has granted lines of credit. (Years ago, banks did not lend money unless they knew they could be repaid.)
- The Banker's algorithm is a resource allocation and deadlock avoidance algorithm developed by Dijkstra.
- Resource allocation state is defined by the number of available and allocated resources and the maximum demand of the processes. When a process requests an available resource, system must decide if immediate allocation leaves the system in a safe state.

The Banker algorithm does the simple task –

- Figranting the request leads to an unsafe state the request is denied.
- If granting the request leads to safe state the request is carried out.

Basic Facts:

- \square If a system is in safe state \Rightarrow no deadlocks.
- \square If a system is in unsafe state \Rightarrow possibility of deadlock.
- \square Avoidance \Rightarrow ensure that a system will never enter an unsafe state.

The Banker's Algorithm for a Single Resource

- Resource of only type is considered (eg: tape drive)
- Resource allocation state is defined by the number of available and allocated resources and the maximum demand of the processes. When a process requests an available resource, system must decide if immediate allocation leaves the system in a safe state.

The Banker algorithm does the simple task –

- If granting the request leads to an unsafe state the request is denied.
- If granting the request leads to safe state the request is carried out.

Example: (Safe State)

- Available units = 10
- In following figure (a) we see four customers (processes), A, B, C, and D, each of whom has been granted a certain number of credit units (e.g., 1 unit is 1K dollars).
- The banker knows that not all customers will need their maximum credit immediately, so he has reserved only 10 units (resources say tape drives) rather than 22 to service them. (In this analogy, customers are processes, units are, say, tape drives, and the banker is the operating system.)

	Has	Max
Α	0	6
В	0	5
С	0	4
D	0	7

Free: 10

(a)

• The customers go about their respective businesses, making loan requests from time to time (i.e., asking for resources). At a certain moment, the situation is as shown in following figure (b).

	Has	Max
Α	1	6
В	1	5
С	2	4
D	4	7

Free: 2

(b)

• This state is safe because with two units left, the banker can delay any requests except C's, thus letting C finish and release all four of his resources. With four units in hand, the banker can let either D or B have the necessary units, and so on.

Example: (Unsafe State)

• Consider what would happen if a request from B for one more unit were granted in above Fig(b). We would have situation as in following Fig(c), which is unsafe.

Has Max			
Α	1	6	
В	2	5	
С	2	4	
D	4	7	

Free: 1

(c)

- If all the customers suddenly asked for their maximum loans, the banker could not satisfy any of them, and we would have a **deadlock**.
 - NOTE: An unsafe state does not imply the existence or even eventual existence of a deadlock. What an unsafe state does imply is that some unfortunate sequence of events might lead a deadlock.

Problem 01: State whether the given processes are in deadlock or not. Given that resource instance is 10.

Process	Allocated	Maximum
A	3	9
В	2	4
С	2	7

Solution:

Calculating needed resources, using

Needed = Maximum - Allocated

We get,

Process	Allocated	Maximum	Needed
A	3	9	6
В	2	4	2
С	2	7	5

Here currently,

Total allocation = 3+2+2=7

So, free = total available – current allocation = 10 - 7 = 3

With current free resources process B can be executed, since need of $B \le Free \, i.e \, 2 \le 3$. So, B executes. After execution of B it release the resources allocated by it. Total free resource becomes,

free = current free + Allocation by B
=
$$(1+2+2) = 5$$

Now, with current free resources process C can be executed, since need of $C \le Free i.e \le 5 \le 5$. So, C executes. After execution of C it release the resources allocated by it. Total free resource becomes,

free = current free + Allocation by C
=
$$(0+5+2) = 7$$

With current free resources process A can be executed, since need of $A \le Free i.e 6 \le 7$. So, A executes. After execution of A it releases the resources allocated by it. Total free resource becomes

free = current free + Allocation by A
=
$$(1+6+3) = 10$$

Here all the process runs successfully hence they are is safe state and occurs no deadlock. Safe sequence is: $\mathbf{B} \rightarrow \mathbf{C} \rightarrow \mathbf{A}$

The Banker's Algorithm for a Multiple Resource

The banker's algorithm can be generalized to handle multiple resources (the resources of multiple types say printers, tape drives, plotters, Blue –ray)


Algorithm

- 1. Look for a row, R, whose unmet resource needs are all smaller than or equal to A (Available resources). If no such row exists, the system will eventually deadlock since no process can run to completion (assuming processes keep all resources until they exit).
- 2. Assume the process of the chosen row requests all the resources it needs (which is guaranteed to be possible) and finishes. Mark that process as terminated and add all of its resources to the A vector
- 3. Repeat steps 1 and 2 until either all processes are marked terminated (in which case the initial state was safe) or no process is left whose resource needs can be met (in which case the system was not safe).

NOTE: If several processes are eligible to be chosen in step 1, it does not matter which one is selected: the pool of available resources either gets larger, or at worst, stays the same.

Example:

- ✓ In following figure left matrix shows how many of each resource are currently assigned to each of the five processes (A, B, C, D and E).
- ▼ The matrix on the right shows how many resources each process still needs in order to complete.



- ✓ As in the single-resource case, processes must state their total resource needs before executing, so that the system can compute the right-hand matrix at each instant.
- ▼ The three vectors (E, P and A) at the right of the figure show the existing, possessed and available resources.
 - E represents the number of existing resources
 - P represents the number of possessed resources
 - A, represents number of the available resources
 - \boxtimes E = (6 3 4 2) means the system has 6 tape drives, 3 plotters, 4 printers and 2 blue –rays (existing)
 - \square P = (5 3 2 2) means 5 tape drives, 3 plotters, 2 printers and 2 blue-rays are currently used by processes (possessed).
 - \square A = (1 0 2 0) means 1 tape drive and 2 printers are free now (available)
- ▼ The available resource vector is just the difference between what the system has and what is currently in use

- The current state in above figure is safe.
 - Suppose that process B now makes a request for the printer. This request can be granted because the resulting state is still safe (process D can finish, and then processes A or E, followed by the rest).
 - Now imagine that after giving B one of the two remaining printers, E wants the last printer. Granting that request would reduce the vector of available resources to (1 0 0 0), which leads to deadlock, so E's request must be deferred for a while.

Limitations:

- Although in theory the algorithm is wonderful, in practice it is essentially useless because processes rarely know in advance what their maximum resource needs will be.
- In addition, the number of processes is not fixed, but dynamically varying as new users log
 in and out.
- Furthermore, resources that were thought to be available can suddenly vanish (tape drives can break).

Problem 01: A system has four process P1, P2, P3 and P4 and three resources R1, R2 and R3 with existing resources E = (15, 9, 5). After allocating resources to all the processes available resources becomes A = (3, 2, 0). State whether the process is safe or not using banker's algorithm. If safe, write the safe sequence.

Process	Allocation		Maximum		Need				
	R1	R2	R3	R1	R2	R3	R1	R2	R3
P1	3	0	1	3	2	2	0	2	1
P2	5	4	1	6	8	2	1	4	1
Р3	2	2	0	3	2	4	1	0	4
P4	2	1	3	4	2	3	2	1	0

NOTE: If Need is not given, it can be calculated using Need = Maximum - Allocation

Solution: We have A = (3, 2, 0)

Step 1: With current available resources A = (3, 2, 0) P4 can be executed. Since need of P4 \leq A i.e. $(2, 1, 0) \leq (3, 2, 0)$ so P4 executes after complete execution of P4 it releases the resources which is allocated by it. Now total current available resources A becomes,

A = previous free + Allocation by P4

$$A = (3, 2, 0) + (2, 1, 3) = (5, 3, 3)$$

Step 2: With current available resources A = (5, 3, 3) P1 can be executed. Since need of P1 \leq A i.e. $(0, 2, 1) \leq (5, 3, 3)$ so P1 executes. After complete execution of P1 it releases the resources which is allocated by it. Now total current available resources A becomes,

A = previous free + Allocation by P1

$$A = (5,3,3) + (3,0,1) = (8,3,4)$$

Step 3: With current available resources A = (8, 3, 4) P3 can be executed. Since need of P3 \leq A i.e. $(1,0,4) \leq (8,3,4)$ so P3 executes After complete execution of P3 it releases the resources which is allocated by it. Now total current available resources A becomes,

A = previous free + Allocation by P3

$$A = (8,3,4) + (2,2,0) = (10,5,4)$$

Step 4: With current available resources A = (10, 5, 4) P2 can be executed. Since need of P2 \leq A i.e. $(1,4,1) \leq (10,5,4)$ so P2 executes After complete execution of P2 it releases the resources which is allocated by it. Now total current available resources A becomes,

A = previous free + Allocation by P2

$$A = (10,5,4) + (5,4,1) = (15,9,5)$$

Here all the process runs hence they are in safe state and occurs **no deadlock.** Safe sequence is:

$$P4 \rightarrow P1 \rightarrow P3 \rightarrow P2$$

Deadlock Detection

- System allows deadlock to occur and tries to detect when it happens, and then takes some action recover after the fact.
- When this technique is used, the system does not attempt to prevent deadlocks from occurring. Instead, it lets them occur, tries to detect when this happens, and then takes some action to

Deadlock Detection with One Resource of Each Type

- There is only one resource of each type.
- Such a system might have one scanner, one Blu-ray recorder, one plotter, and one tape drive, but no more than one of each class of resource.
- For a system with one instance of each resource, we can detect deadlock by constructing a resource allocation graph
 - If the graph contains one or more cycles, a deadlock exists. Any process that is part of the cycle is deadlocked.
 - F If no cycle exists, the system is not deadlocked

Example:

Consider a system with seven processes, A through G, and six resources, R through W. The state of which resources are currently owned and which ones are currently being requested is as follows:

- 1. Process A holds R and wants S.
- 2. Process B holds nothing but wants T.
- 3. Process C holds nothing but wants S.
- 4. Process D holds U and wants S and T.
- 5. Process E holds T and wants V.
- 6. Process F holds W and wants S.
- 7. Process G holds V and wants U.

The question is: "Is this system deadlocked, and if so, which processes are involved?"

Solution:

From given information, we can construct resource allocation graph as follows:




Figure: (a) A resource graph. (b) A cycle extracted from (a).

- Processes D, E and G are all deadlocked.
- Processes A, C and F are not deadlocked because S can be allocated to any one of them, which then finishes and take by other two processes in turn.

Many algorithms for detecting cycles in directed graphs are known. One of them is given below:

- 1. For each node, N, in the graph, perform the following five steps with N as the starting node.
- 2. Initialize L (a dynamic data structure) to the empty list, and designate all the arcs as unmarked.
- 3. Add the current node to the end of L and check to see if the node now appears in L two times. If it does, the graph contains a cycle (listed in L) and the algorithm terminates.
- 4. From the given node, see if there are any unmarked outgoing arcs. If so, go to step 5; if not, go to step 6.
- 5. Pick an unmarked outgoing arc at random and mark it. Then follow it to the new current node and go to step 3.
- 6. If this node is the initial node, the graph does not contain any cycles and the algorithm terminates. Otherwise, we have now reached a dead end. Remove it and go back to the previous node, that is, the one that was current just before this one, make that one the current node, and go to step 3.

In above example, the algorithm is traced as follows

- We are starting from node D.
- Empty list L = ()
- Add current node so Empty list = (D).
- From this node there is one outgoing arc to T so add T to list.
- So list become L = (D, T).
- Continue this step....so we get list as below L = (D, T, E)....... L = (D, T, E, V, G, U, D)
- In the above step in list the node D appears twice, so deadlock.

Deadlock Detection with Multiple Resources of Each Type

- ❖ When multiple copies of some of the resources exist, a different approach is needed to detect deadlocks. A matrix-based algorithm for detecting deadlock among n processes, P₁ through Pn is presented here.
- Let the number of resource classes be m, with E1 resources of class 1, E_2 resources of class 2, and generally, E_i resources of class i $(1 \le i \le m)$.
 - E is the **existing resource vector**. It gives the total number of instances of each resource in existence.
 - For example, if class 1 is tape drives, then $E_1 = 2$ means the system has two tape drives
- ❖ At any instant, some of the resources are assigned and are not available. Let A be the available resource vector, with A_i giving the number of instances of resource i that are currently available (i.e., unassigned).
 - If both of our two tape drives are assigned, A_1 will be 0.
- ❖ The two arrays, C and R are taken. Where
 - C = the current allocation matrix
 - -- R = the request matrix.
 - The ith row of C tells how many instances of each resource class P_i currently holds. Thus,
 - C_{ij} is the number of instances of resource j that are held by process i.
 - Similarly, R_{ij} is the number of instances of resource j that P_i wants.

❖ These four data structures are shown in following figure




Figure: The four data structures needed by the deadlock detection algorithm.

❖ An important invariant holds for these four data structures. In particular, every resource is either allocated or is available. This observation means that

$$\sum_{i=1}^{n} C_{ij} + A_j = E_j$$

In other words, if we add up all the instances of the resource j that have been allocated and to this add all the instances that are available, the result is the number of instances of that resource class that exist.

- ❖ The deadlock detection algorithm is based on comparing vectors.
 - Mathematically, $A \le B$ holds if and only if $Ai \le Bi$ for $1 \le i \le m$.

Main Idea:

- ☑ Each process is initially said to be unmarked.
- As the algorithm progresses, processes will be marked, indicating that they are able to complete and are thus not deadlocked.
- ☑ When the algorithm terminates, any unmarked processes are known to be deadlocked.

(This algorithm assumes a worst-case scenario: all processes keep all acquired resources until they exit.)

The deadlock detection algorithm can now be given as follows.

- 1. Look for an unmarked process, Pi, for which the ith row of R is less than or equal to A.
- 2. If such a process is found, add the ith row of C to A, mark the process, and go back to step 1.
- 4. If no such process exists, the algorithm terminates.

Example:

$$E = \begin{pmatrix} 4 & 2 & 3 & 1 \end{pmatrix} \qquad A = \begin{pmatrix} 2 & 1 & 0 & 0 \end{pmatrix}$$
Current allocation matrix
$$C = \begin{bmatrix} 0 & 0 & 1 & 0 \\ 2 & 0 & 0 & 1 \\ 0 & 1 & 2 & 0 \end{bmatrix} \qquad R = \begin{bmatrix} 2 & 0 & 0 & 1 \\ 1 & 0 & 1 & 0 \\ 2 & 1 & 0 & 0 \end{bmatrix}$$

Let us consider three processes and four resource classes, which we have arbitrarily labeled tape drives, plotters, scanners, and Blu-ray drives.

- Process 1 has one scanner. Process 2 has two tape drives and a Blu-ray drive. Process 3 has a plotter and two scanners.
- Each process needs additional resources, as shown by the R matrix.

To run the deadlock detection algorithm, we look for a process whose resource request can be satisfied.

- The first one cannot be satisfied because there is no Blu-ray drive available.
- The second cannot be satisfied either, because there is no scanner free.
- Fortunately, the third one can be satisfied, so process 3 runs and eventually returns all its resources, giving

A = previous free + Allocation by P3
$$A = (2\ 1\ 0\ 0\) + (0\ 1\ 2\ 0)$$

$$A = (2\ 2\ 2\ 0)$$

— At this point process 2 can run and return its resources, giving

$$A = previous free + Allocation by P2$$

$$A = (2\ 2\ 2\ 0) + (2\ 0\ 0\ 1)$$

$$A = (4 \ 2 \ 2 \ 1)$$

- Now the remaining process can run. There **is no deadlock** in the system.
- ♣ Suppose that process 3 needs a Blu-ray drive as well as the two tape drives and the plotter. None of the requests can be satisfied, so the entire system will eventually be **deadlocked**. Even if we give process 3 its two tape drives and one plotter, the system deadlocks when it requests the Blu-ray drive.

Another example:

Five processes P_0 through P_4 ; three resource types A (7 instances), B (2 instances), and C (6 instances)

	<u>Allocation</u>	Request	<u>Available</u>
	ABC	ABC	ABC
P_0	0 1 0	000	000
P_1	200	202	
P_2	303	000	
P_3	2 1 1	100	
P_4	002	002	

- Sequence $\langle P_0, P_2, P_3, P_1, P_4 \rangle$ can run without deadlock
- But there is deadlock if request of P₂ is (001)

Recovery From Deadlock

Suppose that our deadlock detection algorithm has succeeded and detected a deadlock. Some way is needed to recover and get the system going again. Once the deadlock has been detected, it can be recovered through various ways.

a) Recovery through Preemption

- In this method, a resource can be temporarily taken away from its current owner and given to another process.
- The ability to take a resource away from a process, have another process use it and then give it back without the process noticing it, is highly dependent on the nature of the resource.
- Recovering this way is frequently difficult or impossible.




Figure: P1 has R1 and P2 has R2. If P1 requests R2 then deadlock occurs. It is recovered by temporarily taking away R2 from P2 and giving to P1

b) Recovery through Rollback

- PCB and resources state are periodically save at "checkpoint"
- When a deadlock is detected, it is easy to see which resources are needed. To do the recovery, a process that owns a needed resource is rolled back to an earlier checkpoint when it did not have the resource.
- The resource can now be assigned to one of the deadlocked processes.
- All the work done since the checkpoint is lost (e.g., output printed since the checkpoint must be discarded, since it will be printed again).
- In effect, the process is reset to an earlier moment when it did not have the resource, which is now assigned to one of the deadlocked processes.
- If the restarted process tries to acquire the resource again, it will have to wait until it becomes available.

NOTE: Checkpointing a process means that its state is written to a file so that it can be restarted later. The checkpoint contains not only the memory image, but also the resource state, in other words, which resources are currently assigned to the process




Figure: State of process A is saved at file F1 at some point of time (first checkpoint) then A has acquired resource R. At another time, state of A is saved on File F2 (second checkpoint). After that Process B has requested the resource R which caused deadlock. Now the Process A is rolled back to the first checked point.

c) Recovery through Killing Processes

- ❖ The crudest but simplest way to break a deadlock is to kill one or more processes.
 - o One way is to kill all the processes involved in deadlock
 - o Another way is to kill process one by one
 - After killing each process check for deadlock
 - If deadlock recovered then stop killing more processes
 - Otherwise kill another process




Figure: To recover from this deadlock, first kill P3 then P2

Deadlock vs Starvation

S.N.	Deadlock	Starvation
1.	All processes keep waiting for each other to	High priority processes keep executing
	complete and none get executed	and low priority processes are blocked
2.	Resources are blocked by the processes	Resources are continuously utilized by
		high priority processes
3.	Necessary conditions Mutual Exclusion,	Priorities are assigned to the processes
	Hold and Wait, No preemption, Circular	
	Wait	
4.	Also known as Circular wait	Also known as lived lock
5.	It can be prevented by avoiding the necessary	It can be prevented by aging
	conditions for deadlock	