
Operating Systems: Internals and Design Principles, 6/E William Stallings

Chapter 5 Concurrency: Mutual **Exclusion** and Synchronization

Dave Bremer
Otago Polytechnic, N.Z.
©2008, Prentice Hall




Roadmap

- Principals of Concurrency
 - Mutual Exclusion: Hardware Support
 - Semaphores
 - Monitors
 - Message Passing
 - Readers/Writers Problem








Multiple Processes

- Central to the design of modern Operating Systems is managing multiple processes
 - Multiprogramming
 - Multiprocessing
 - Distributed Processing
- Big Issue is Concurrency
 - Managing the interaction of all of these processes






Concurrency

Concurrency arises in:

- Multiple applications
 - Sharing time
- Structured applications
 - Extension of modular design
- Operating system structure
 - OS themselves implemented as a set of processes or threads





Key Terms

Table 5.1 Some Key Terms Related to Concurrency

atomic operation	A sequence of one or more statements that appears to be indivisible; that is,
	no other process can see an intermediate state or interrupt the operation.

critical section A section of code within a process that requires access to shared resources and that must not be executed while another process is in a corresponding section of code

deadlock A situation in which two or more processes are unable to proceed because

each is waiting for one of the others to do something.

livelock A situation in which two or more processes continuously change their states

in response to changes in the other process(es) without doing any useful

work.

mutual exclusion The requirement that when one process is in a critical section that accesses

shared resources, no other process may be in a critical section that accesses

any of those shared resources.

race condition A situation in which multiple threads or processes read and write a shared

data item and the final result depends on the relative timing of their

execution.

starvation A situation in which a runnable process is overlooked indefinitely by the

scheduler; although it is able to proceed, it is never chosen.





Interleaving and Overlapping Processes

 Earlier (Ch2) we saw that processes may be interleaved on uniprocessors





Figure 2.12 Multiprogramming and Multiprocessing







Interleaving and Overlapping Processes

 And not only interleaved but overlapped on multi-processors










Difficulties of Concurrency

- Sharing of global resources
- Optimally managing the allocation of resources
- Difficult to locate programming errors as results are not deterministic and reproducible.








A Simple Example

```
void echo()
{
  chin = getchar();
  chout = chin;
  putchar(chout);
}
```







A Simple Example: On a Multiprocessor

Process P1 Process P2

•


chin = getchar();

chin = getchar();

chout = chin; chout = chin;

putchar(chout); .

putchar(chout);




Enforce Single Access

- If we enforce a rule that only one process may enter the function at a time then:
- P1 & P2 run on separate processors
- P1 enters echo first,
 - P2 tries to enter but is blocked P2 suspends
- P1 completes execution
 - P2 resumes and executes echo








Race Condition

- A race condition occurs when
 - Multiple processes or threads read and write data items
 - They do so in a way where the final result depends on the order of execution of the processes.
- The output depends on who finishes the race last.







Operating System Concerns

- What design and management issues are raised by the existence of concurrency?
- The OS must
 - Keep track of various processes
 - Allocate and de-allocate resources
 - Protect the data and resources against interference by other processes.
 - Ensure that the processes and outputs are independent of the processing speed



Process Interaction

Table 5.2 Process Interaction

Degree of Awareness	Relationship	Influence That One Process Has on the Other	Potential Control Problems
Processes unaware of each other	Competition	 Results of one process independent of the action of others Timing of process may be affected 	 Mutual exclusion Deadlock (renewable resource) Starvation
Processes indirectly aware of each other (e.g., shared object)	Cooperation by sharing	 Results of one process may depend on information obtained from others Timing of process may be affected 	 Mutual exclusion Deadlock (renewable resource) Starvation Data coherence
Processes directly aware of each other (have com- munication primitives available to them)	Cooperation by commu- nication	 Results of one process may depend on information obtained from others Timing of process may be affected 	 Deadlock (consum- able resource) Starvation




Competition among Processes for Resources

Three main control problems:

- Need for Mutual Exclusion
 - Critical sections
- Deadlock
- Starvation








Requirements for Mutual Exclusion

- Only one process at a time is allowed in the critical section for a resource
- A process that halts in its noncritical section must do so without interfering with other processes
- No deadlock or starvation








Requirements for Mutual Exclusion

- A process must not be delayed access to a critical section when there is no other process using it
- No assumptions are made about relative process speeds or number of processes
- A process remains inside its critical section for a finite time only








Roadmap

- Principals of Concurrency
- → Mutual Exclusion: Hardware Support
 - Semaphores
 - Monitors
 - Message Passing
 - Readers/Writers Problem








Disabling Interrupts

- Uniprocessors only allow interleaving
- Interrupt Disabling
 - A process runs until it invokes an operating system service or until it is interrupted
 - Disabling interrupts guarantees mutual exclusion
 - Will not work in multiprocessor architecture








Pseudo-Code

```
while (true) {
   /* disable interrupts */;
   /* critical section */;
   /* enable interrupts */;
   /* remainder */;
}
```








Special Machine Instructions

- Compare&Swap Instruction
 - also called a "compare and exchange instruction"
- Exchange Instruction








Compare&Swap Instruction

```
int compare and swap (int *word,
 int testval, int newval)
  int oldval;
  oldval = *word;
  if (oldval == testval) *word = newval;
  return oldval;
```








Mutual Exclusion (fig 5.2)

```
/* program mutualexclusion */
const int n = /* number of processes */;
int bolt;
void P(int i)
   while (true) {
     while (compare_and_swap(bolt, 0, 1) == 1)
         /* do nothing */;
      /* critical section */;
      bolt = 0;
      /* remainder */;
void main()
  bolt = 0;
   parbegin (P(1), P(2), ..., P(n));
```








Exchange instruction

```
void exchange (int register, int
  memory)
{
  int temp;
  temp = memory;
  memory = register;
  register = temp;
}
```







Exchange Instruction (fig 5.2)

```
/* program mutualexclusion */
int const n = /* number of processes**/;
int bolt;
void P(int i)
   int keyi = 1;
   while (true) {
      do exchange (keyi, bolt)
      while (keyi != 0);
      /* critical section */;
      bolt = 0;
      /* remainder */;
void main()
   bolt = 0;
   parbegin (P(1), P(2), ..., P(n));
```







Hardware Mutual Exclusion: Advantages

- Applicable to any number of processes on either a single processor or multiple processors sharing main memory
- It is simple and therefore easy to verify
- It can be used to support multiple critical sections






Hardware Mutual Exclusion: Disadvantages

- Busy-waiting consumes processor time
- Starvation is possible when a process leaves a critical section and more than one process is waiting.
 - Some process could indefinitely be denied access.
- Deadlock is possible








Roadmap

- Principals of Concurrency
- Mutual Exclusion: Hardware Support
- Semaphores
 - Monitors
 - Message Passing
 - Readers/Writers Problem







Semaphore

- Semaphore:
 - An integer value used for signalling among processes.
- Only three operations may be performed on a semaphore, all of which are atomic:
 - initialize,
 - Decrement (semWait)
 - increment. (semSignal)






Semaphore Primitives

```
struct semaphore {
     int count;
     queueType queue;
void semWait(semaphore s)
     s.count--;
     if (s.count < 0) {
          /* place this process in s.queue */;
          /* block this process */;
void semSignal(semaphore s)
     s.count++;
     if (s.count <= 0) {
          /* remove a process P from s.queue */;
          /* place process P on ready list */;
```



Figure 5.3 A Definition of Semaphore Primitives






Binary Semaphore Primitives

```
struct binary semaphore {
     enum {zero, one} value;
     queueType queue;
void semWaitB(binary semaphore s)
     if (s.value == one)
          s.value = zero;
     else {
            /* place this process in s.queue */;
            /* block this process */;
void semSignalB(semaphore s)
     if (s.queue is empty())
          s.value = one;
     else {
            /* remove a process P from s.queue */;
            /* place process P on ready list */;
```










Strong/Weak Semaphore


- A queue is used to hold processes waiting on the semaphore
 - In what order are processes removed from the queue?
- Strong Semaphores use FIFO
- Weak Semaphores don't specify the order of removal from the queue







Example of Strong Semaphore Mechanism





Example of Semaphore Mechanism








Figure 5.5 Example of Semaphore Mechanism

Mutual Exclusion Using Semaphores


```
/* program mutualexclusion */
const int n = /* number of processes */;
semaphore s = 1;
void P(int i)
    while (true) {
          semWait(s);
          /* critical section */;
          semSignal(s);
          /* remainder */;
void main()
    parbegin (P(1), P(2), . . ., P(n));
```








Processes Using Semaphore





proceed in parallel but that critical regions are serialized.



Producer/Consumer Problem

General Situation:


- One or more producers are generating data and placing these in a buffer
- A single consumer is taking items out of the buffer one at time
- Only one producer or consumer may access the buffer at any one time

• The Problem:

 Ensure that the Producer can't add data into full buffer and consumer can't remove data from empty buffer









Functions

Assume an infinite buffer b with a linear array of elements

Producer	Consumer
while (true) {	while (true) {
/* produce item v */	while (in <= out)
b[in] = v;	/*do nothing */;
in++;	w = b[out];
}	out++;
	/* consume item w */
	}



Buffer




Note: shaded area indicates portion of buffer that is occupied

Figure 5.8 Infinite Buffer for the Producer/Consumer Problem








Incorrect Solution

```
/* program producerconsumer */
int n;
binary semaphore s = 1, delay = 0;
void producer()
     while (true) {
          produce();
          semWaitB(s);
          append();
          n++;
          if (n==1) semSignalB(delay);
          semSignalB(s);
void consumer()
     semWaitB(delay);
     while (true) {
          semWaitB(s);
          take();
          n--;
          semSignalB(s);
          consume();
          if (n==0) semWaitB(delay);
void main()
     n = 0;
     parbegin (producer, consumer);
```







Possible Scenario


Table 5.4 Possible Scenario for the Program of Figure 5.9

	Producer	Consumer	S	n	Delay
1			1	0	0
2	semWaitB(s)		0	0	0
3	n++		0	1	0
4	if (n==1) (semSignalB(delay))		0	1	1
5	semSignalB(s)		1	1	1
6		semWaitB(delay)	1	1	0
7		semWaitB(s)	0	1	0
8		n	0	0	0
9		semSignalB(s)	1	0	0
10	semWaitB(s)		0	0	0
11	n++		0	1	0
12	if (n==1) (semSignalB(delay))		0	1	1
13	semSignalB(s)		1	1	1
14		if (n==0) (semWaitB(delay))	1	1	1
15		semWaitB(s)	0	1	1
16		n	0	0	1
17		semSignalB(s)	1	0	1
18		if (n==0) (semWaitB(delay))	1	0	0
19		semWaitB(s)	0	0	0
20		n	0	-1	0
21		semiSignlaB(s)	1	-1	0





NOTE: White areas represent the critical section controlled by semaphore s




Correct Solution

```
/* program producerconsumer */
int n;
binary semaphore s = 1, delay = 0;
void producer()
     while (true) {
          produce();
          semWaitB(s);
          append();
          n++;
          if (n==1) semSignalB(delay);
          semSignalB(s);
void consumer()
     int m; /* a local variable */
     semWaitB(delay);
     while (true) {
          semWaitB(s);
          take();
          n--;
          m = n;
          semSignalB(s);
          consume();
          if (m==0) semWaitB(delay);
void main()
     n = 0;
     parbegin (producer, consumer);
```










Semaphores

```
/* program producerconsumer */
semaphore n = 0, s = 1;
void producer()
     while (true) {
          produce();
          semWait(s);
          append();
          semSignal(s);
          semSignal(n);
void consumer()
     while (true) {
          semWait(n);
          semWait(s);
          take();
          semSignal(s);
          consume();
void main()
     parbegin (producer, consumer);
```





Figure 5.11 A Solution to the Infinite-Buffer Producer/Consumer Problem
Using Semaphores



Bounded Buffer


Block on:	Unblock on:		
Producer: insert in full buffer	Consumer: item inserted		
Consumer: remove from empty buffer	Producer: item removed		












Semaphores

```
/* program boundedbuffer */
const int sizeofbuffer = /* buffer size */;
semaphore s = 1, n= 0, e= sizeofbuffer;
void producer()
     while (true) {
          produce();
          semWait(e);
          semWait(s);
          append();
          semSignal(s);
          semSignal(n);
void consumer()
     while (true) {
          semWait(n);
          semWait(s);
          take();
          semSignal(s);
          semSignal(e);
          consume();
void main()
     parbegin (producer, consumer);
```








Functions in a Bounded Buffer

Producer	Consumer
while (true) {	while (true) {
/* produce item v */	while (in == out)
while ((in + 1) % n == out) /*	/* do nothing */;
do nothing */;	w = b[out];
b[in] = v;	out = (out + 1) % n;
in = (in + 1) % n	/* consume item w */
}	}




Demonstration Animations

- Producer/Consumer
 - Illustrates the operation of a producer-consumer buffer.
- Bounded-Buffer Problem Using Semaphores
 - Demonstrates the bounded-buffer consumer/producer problem using semaphores.








Roadmap

- Principals of Concurrency
- Mutual Exclusion: Hardware Support
- Semaphores
- Monitors
 - Message Passing
 - Readers/Writers Problem








Monitors

- The monitor is a programming-language construct that provides equivalent functionality to that of semaphores and that is easier to control.
- Implemented in a number of programming languages, including
 - Concurrent Pascal, Pascal-Plus,
 - Modula-2, Modula-3, and Java.





Chief characteristics

- Local data variables are accessible only by the monitor
- Process enters monitor by invoking one of its procedures
- Only one process may be executing in the monitor at a time









Synchronization

- Synchronisation achieved by condition variables within a monitor
 - only accessible by the monitor.
- Monitor Functions:
 - —Cwait(c): Suspend execution of the calling process on condition c
 - —Csignal(c) Resume execution of some process blocked after a cwait on the same condition






Structure of a Monitor





Bounded Buffer Solution Using Monitor

```
/* program producerconsumer */
monitor boundedbuffer;
char buffer [N];
                                                      /* space for N items */
int nextin, nextout;
                                                        /* buffer pointers */
int count:
                                              /* number of items in buffer */
cond notfull, notempty;
                              /* condition variables for synchronization */
void append (char x)
    if (count == N) cwait(notfull);  /* buffer is full; avoid overflow */
    buffer[nextin] = x;
    nextin = (nextin + 1) % N;
    count++;
    /* one more item in buffer */
    csignal(notempty);
                                            /* resume any waiting consumer */
void take (char x)
    if (count == 0) cwait(notempty); /* buffer is empty; avoid underflow */
    x = buffer[nextout];
    nextout = (nextout + 1) % N;
    count--;
                                               /* one fewer item in buffer */
    csignal(notfull);
                                            /* resume any waiting producer */
                                                           /* monitor body */
                                               /* buffer initially empty */
    nextin = 0; nextout = 0; count = 0;
```




Solution Using Monitor

```
void producer()
    char x;
    while (true) {
    produce(x);
    append(x);
void consumer()
    char x;
    while (true) {
      take(x);
      consume(x);
void main()
    parbegin (producer, consumer);
```








Bounded Buffer Monitor

```
void append (char x)
    while(count == N) cwait(notfull); /* buffer is full; avoid overflow */
    buffer[nextin] = x;
    nextin = (nextin + 1) % N;
    count++;
                                                /* one more item in buffer */
    cnotify(notempty);
                                            /* notify any waiting consumer */
void take (char x)
    while(count == 0) cwait(notempty); /* buffer is empty; avoid underflow */
    x = buffer[nextout];
    nextout = (nextout + 1) % N;
    count --;
                                               /* one fewer item in buffer */
    cnotify(notfull);
                                            /* notify any waiting producer */
```

Figure 5.17 Bounded Buffer Monitor Code for Mesa Monitor








Roadmap

- Principals of Concurrency
- Mutual Exclusion: Hardware Support
- Semaphores
- Monitors
- Message Passing
 - Readers/Writers Problem








Process Interaction

- When processes interact with one another, two fundamental requirements must be satisfied:
 - synchronization and
 - communication.
- Message Passing is one solution to the second requirement
 - Added bonus: It works with shared memory and with distributed systems






Message Passing

- The actual function of message passing is normally provided in the form of a pair of primitives:
- send (destination, message)
- receive (source, message)








Synchronization

- Communication requires synchronization
 - Sender must send before receiver can receive
- What happens to a process after it issues a send or receive primitive?
 - Sender and receiver may or may not be blocking (waiting for message)








Blocking send, Blocking receive

- Both sender and receiver are blocked until message is delivered
- Known as a rendezvous
- Allows for tight synchronization between processes.








Non-blocking Send

- More natural for many concurrent programming tasks.
- Nonblocking send, blocking receive
 - Sender continues on
 - Receiver is blocked until the requested message arrives
- Nonblocking send, nonblocking receive
 - Neither party is required to wait








Addressing

- Sendin process need to be able to specify which process should receive the message
 - Direct addressing
 - Indirect Addressing








Direct Addressing

- Send primitive includes a specific identifier of the destination process
- Receive primitive could know ahead of time which process a message is expected
- Receive primitive could use source parameter to return a value when the receive operation has been performed






Indirect addressing

- Messages are sent to a shared data structure consisting of queues
- Queues are called mailboxes
- One process sends a message to the mailbox and the other process picks up the message from the mailbox







Indirect Process Communication




Figure 5.18 Indirect Process Communication

General Message Format









Figure 5.19 General Message Format




Mutual Exclusion Using Messages

```
/* program mutualexclusion */
const int n = /* number of processes */;
void P(int i)
   message msg;
   while (true) {
     receive (box, msg);
     /* critical section */;
     send (box, msq);
     /* remainder */;
void main()
   create mailbox (box);
   send (box, null);
   parbegin (P(1), P(2), . . ., P(n));
```



Figure 5.20 Mutual Exclusion Using Messages




Producer/Consumer Messages

```
const int
   capacity = /* buffering capacity */;
   null = /* empty message */;
int i;
void producer()
   message pmsg;
   while (true) {
     receive (mayproduce, pmsq);
     pmsq = produce();
     send (mayconsume, pmsq);
void consumer()
   message cmsq;
   while (true) {
     receive (mayconsume, cmsq);
     consume (cmsq);
     send (mayproduce, null);
void main()
   create mailbox (mayproduce);
   create mailbox (mayconsume);
   for (int i = 1; i <= capacity; i++) send (mayproduce, null);</pre>
   parbegin (producer, consumer);
```







Roadmap

- Principals of Concurrency
- Mutual Exclusion: Hardware Support
- Semaphores
- Monitors
- Message Passing
- -> Readers/Writers Problem








- A data area is shared among many processes
 - Some processes only read the data area,
 some only write to the area
- Conditions to satisfy:
 - 1. Multiple readers may read the file at once.
 - 2. Only one writer at a time may write
 - 3. If a writer is writing to the file, no reader may read it.



interaction of readers and writers.



Readers have Priority

```
/* program readersandwriters */
int readcount;
semaphore x = 1, wsem = 1;
void reader()
   while (true) {
     semWait (x);
     readcount++;
     if (readcount == 1) semWait (wsem);
     semSignal (x);
     READUNIT();
     semWait (x);
     readcount--;
     if (readcount == 0) semSignal (wsem);
     semSignal (x);
void writer()
   while (true) {
     semWait (wsem);
     WRITEUNIT();
     semSignal (wsem);
void main()
   readcount = 0;
   parbegin (reader, writer);
```





Writers have Priority


```
/* program readersandwriters */
int readcount, writecount;
semaphore x = 1, y = 1, z = 1, wsem = 1, rsem = 1;
void reader()
   while (true) {
     semWait (z);
          semWait (rsem);
               semWait (x);
                    readcount++;
                    if (readcount == 1) semWait (wsem);
               semSignal (x);
          semSignal (rsem);
     semSignal (z);
     READUNIT();
     semWait (x);
          readcount--;
          if (readcount == 0) semSignal (wsem);
     semSignal (x);
```

Writers have Priority

```
void writer ()
   while (true) {
     semWait (y);
          writecount++;
          if (writecount == 1) semWait (rsem);
     semSignal (y);
     semWait (wsem);
     WRITEUNIT();
     semSignal (wsem);
     semWait (y);
          writecount--;
          if (writecount == 0) semSignal (rsem);
     semSignal (y);
void main()
   readcount = writecount = 0;
   parbegin (reader, writer);
```








Message Passing

```
void reader(int i)
   message rmsq;
      while (true) {
         rmsq = i;
         send (readrequest, rmsg);
         receive (mbox[i], rmsq);
         READUNIT ();
         rmsq = i;
         send (finished, rmsq);
void writer(int j)
   message rmsg;
  while(true) {
      rmsq = j;
      send (writerequest, rmsg);
      receive (mbox[j], rmsq);
      WRITEUNIT ();
      rmsq = j;
      send (finished, rmsq);
```

```
controller()
void
      while (true)
         if (count > 0) {
            if (!empty (finished)) {
               receive (finished, msq);
               count++;
            else if (!empty (writerequest)) {
               receive (writerequest, msg);
               writer id = msq.id;
               count = count - 100;
            else if (!empty (readrequest)) {
               receive (readrequest, msq);
               count--:
               send (msg.id, "OK");
         if (count == 0) {
            send (writer id, "OK");
            receive (finished, msq);
            count = 100;
         while (count < 0) {
            receive (finished, msq);
            count++;
```



Message Passing

```
void controller()
      while (true)
         if (count > 0) {
            if (!empty (finished)) {
               receive (finished, msg);
               count++;
            else if (!empty (writerequest)) {
               receive (writerequest, msg);
               writer id = msq.id;
               count = count - 100;
            else if (!empty (readrequest)) {
               receive (readrequest, msg);
               count--;
               send (msg.id, "OK");
         if (count == 0) {
            send (writer id, "OK");
            receive (finished, msg);
            count = 100;
         while (count < 0) {
            receive (finished, msq);
            count++;
```



