

Operating System

Chapter 12: I/O Management



Overview

- I/O management is a major component of OS design and operation
 - important aspect of computer operation
 - I/O devices is the way computer to interact with user and other systems
 - I/O devices vary greatly
 - various methods to control them performance varies


device drivers encapsulate device details; presents an uniform interface

new types of devices frequently emerges

I/O Hardware

- Incredible variety of I/O devices
 - storage, communication, human-interface
- Common concepts: signals from I/O devices interface with computer
 - bus: an interconnection between components (including CPU)
 - port: connection point for device
 - controller: component that control the device
 - can be integrated to device or separate circuit board
 - usually contains processor, microcode, private memory, bus controller, etc
- I/O access can use polling or interrupt

A Typical PC Bus Structure



I/O Hardware

- Some CPU architecture has dedicated I/O instructions
 - e.g., x86: in, out, ins, outs
- Devices usually provide registers for data and control I/O of device
 - device driver places (pointers to) commands and data to register
 - registers include data-in/data-out, status, control (or command) register
 - typically 1-4 bytes, or FIFO buffer
- Devices are assigned addresses for registers or on-device memory
 - direct I/O instructions
 - to access (mostly) registers
 - memory-mapped I/O
 - data and command registers mapped to processor address space
 - to access (large) on-device memory (graphics)

I/O Ports on PCs (Partial)

I/O address range (hexadecimal)	device	
000-00F	DMA controller	
020–021	interrupt controller	
040–043	timer	
200–20F	game controller	
2F8-2FF	serial port (secondary)	
320-32F	hard-disk controller	
378–37F	parallel port	
3D0-3DF	graphics controller	
3F0-3F7	diskette-drive controller	
3F8-3FF	serial port (primary)	

Polling

For each I/O operation:

- busy-wait if device is busy (status register)
- send the command to the device controller (command register)
- read status register until it indicates command has been executed
- read execution status, and possibly reset device status


```
While (STATUS == BUSY)
   ; // wait until device is not busy
Write data to DATA register
Write command to COMMAND register
   (starts the device and executes the command)
While (STATUS == BUSY)
   ; // wait until device is done with your request
```

Polling requires busy wait

reasonable if device is fast; inefficient if device slow

Interrupts


- Polling requires busy-wait, inefficient use of CPU resource
- Interrupts can avoid busy-wait
 - device driver send a command to the controller, and return
 - OS can schedule other activities
 - device will interrupt the processor when command has been executed
 - OS retrieves the result by handling the interrupt



- Interrupt-based I/O requires context switch at start and end
 - if interrupt frequency is extremely high, context switch wastes CPU time
 - solution: use polling instead
 - example: NAPI in Linux enables polling under very high network load

Interrupt-Driven I/O Cycle

- the device controller *raises* an interrupt by asserting a signal on the interrupt request line
- the CPU catches the interrupt and dispatches it to the interrupt handler
- the handler *clears* the interrupt by servicing the device.



Intel Pentium Interrupt Vector Table

vector number	description	
0	divide error	
1	debug exception	
2	null interrupt	
3	breakpoint	
4	INTO-detected overflow	
5	bound range exception	
6	invalid opcode	
7	device not available	
8	double fault	
9	coprocessor segment overrun (reserved)	
10	invalid task state segment	
11	segment not present	
12	stack fault	
13	general protection	
14	page fault	
15	(Intel reserved, do not use)	
16	floating-point error	
17	alignment check	
18	machine check	
19–31	(Intel reserved, do not use)	
32–255	maskable interrupts	


Interrupts

- Interrupt is also used for exceptions
 - protection error for access violation
 - page fault for memory access error
 - software interrupt for system calls

- Multi-CPU systems can process interrupts concurrently
 - sometimes a CPU may be dedicated to handle interrupts
 - interrupts can also have CPU affinity


Direct Memory Access

- DMA transfer data directly between I/O device and memory
 - OS only need to issue commands, data transfers bypass the CPU
 - no programmed I/O (one byte at a time), data transferred in large blocks
 - it requires DMA controller in the device or system



- OS issues commands to the DMA controller
 - a command includes: operation, memory address for data, count of bytes...
 - usually it is the pointer of the command written into the command register
 - when done, device interrupts CPU to signal completion


Six Steps of DMA Transfer



Application I/O Interface

- I/O system calls encapsulate device behaviors in generic classes
 - in Linux, devices can be accessed as files; low-level access with ioctl
- Device-driver layer hides differences among I/O controllers from kernel
 - each OS has its own I/O subsystem and device driver frameworks
 - new devices talking already-implemented protocols need no extra work

Kernel I/O Structure



Characteristics of I/O Devices

- Devices vary in many dimensions
 - character-stream or block
 - sequential or random-access
 - synchronous or asynchronous (or both) sharable or dedicated
 - speed of operation
 - read-write, read only, or write only

aspect	variation	example
data-transfer mode	character block	terminal disk
access method	sequential random	modem CD-ROM
transfer schedule	synchronous asynchronous	tape keyboard
sharing	dedicated sharable	tape keyboard
device speed	latency seek time transfer rate delay between operations	
I/O direction	read only write only read–write	CD-ROM graphics controller disk

Characteristics of I/O Devices

- Broadly, I/O devices can be grouped by the OS into
 - block I/O: read, write, seek
 - character I/O (Stream)
 - memory-mapped file access
 - network sockets

Block and Character Devices

- Block devices access data in blocks, such as disk drives...
 - commands include read, write, seek
 - raw I/O, direct I/O, or file-system access
 - memory-mapped file access possible (e.g., memory-mapped files)
 - DMA
- Character devices include keyboards, mice, serial ports...
 - very diverse types of devices

Network Devices

- Varying enough from block and character to have own interface
 - very different from pipe, mailbox...

- Popular interface for network access is the socket interface
 - it separates network protocol from detailed network operation
 - network operations are implemented as sockets
 - e.g., Unix socket


Clocks and Timers

- Clocks and timers can be considered as character devices
 - very important devices as they provide current time, elapsed time, timer
- Normal resolution about 1/60 second, some OS provides higher-resolution ones

Synchronous/Asynchronous I/O

- Synchronous I/O includes blocking and non-blocking I/O
 - blocking I/O: process suspended until I/O completed
 - ✓ easy to use and understand, but may be less efficient.
 - ✓ insufficient for some needs
 - non-blocking I/O: I/O calls return as much data as available
 - ✓ process does not block, returns whatever existing data (read or write)
 - ✓ use select to find if data is ready, then use read or write to transfer data
- Asynchronous I/O: process runs while I/O executes,
 - I/O subsystem signals process when I/O completed via signal or callback
 - difficult to use but very efficient

Two I/O Methods




Kernel I/O Subsystem

- I/O scheduling
 - to queue I/O requests via per-device queue
 - to schedule I/O for fairness and quality of service
- Buffering store data in memory while transferring between devices
 - to cope with device speed mismatch: receive from network and write to ssd, double buffering
 - to cope with device transfer size mismatch: network buffer reassembly of message
 - to maintain "copy semantics": write()

Kernel I/O Subsystem

- Caching: hold a copy of data for fast access
 - key to performance
 - sometimes combined with buffering
 - Buffer in memory is also used as caching for file operations
- Spooling: hold output if device can serve only one request at a time
 - i.e., printing
- Device reservation: provides exclusive access to a device
 - system calls for allocation and de-allocation
 - watch out for deadlock

Device-status Table



- The wait queue is attached to a device-status table. The kernel manages this table that contains an entry for each I/O device
- Each table entry indicates the device's type, address, and state (not functioning, idle, or busy)

Error Handling


- Some OSes try to recover from errors
 - e.g., device unavailable, transient write failures
 - sometimes via retrying the read or write
 - some systems have more advanced error handling
 - track error frequencies, stop using device with high error frequency
- Some OSes just return an error number or code when I/O request fails
 - system error logs hold problem reports

I/O Protection

- OS need to protect I/O devices
 - e.g., keystrokes can be stolen by a keylogger if keyboard is not protected
 - always assume user may attempt to obtain illegal I/O access
- To protect I/O devices:
 - define all I/O instructions to be privileged
 - I/O must be performed via system calls
 - memory-mapped I/O and I/O ports must be protected too

Use System Call to Perform I/O


- To prevent users from performing illegal I/O
 - all I/O instructions are privileged instructions
- Users cannot issue I/O instructions directly. they must do it through the operating system.
- To do I/O, a user program executes a system call to request that the operating system perform I/O on its behalf



Kernel Data Structures

- Kernel keeps state info for I/O components
 - e.g., open file tables, network connections, character device state
 - many data structures to track buffers, memory allocation, "dirty" blocks
 - sometimes very complicated
- Some OS uses message passing to implement I/O, e.g., Windows
 - message with I/O information passed from user mode into kernel
 - message modified as it flows through to device driver and back to process


UNIX I/O Kernel Structure



I/O Requests to Hardware

- System resource access needs to be mapped to hardware
- Consider reading a file from disk for a process:
 - determine device holding file
 - translate name to device representation
 - FAT, UNIX: major/minor
 - physically read data from disk into buffer
 - make data available to requesting process
 - return control to process


Life Cycle of An I/O Request



Performance

- I/O is a major factor in system performance
 - CPU to execute device driver, kernel I/O code
 - context switches due to interrupts
 - data buffering and copying
 - network traffic especially stressful

Network Communications: high context switch



Improve Performance

- Reduce number of context switches
- Reduce data copying
- Reduce interrupts by using large transfers, smart controllers, polling Use DMA
- Use smarter hardware devices
- Balance CPU, memory, bus, and I/O performance for highest throughput
- Move user-mode processes / daemons to kernel threads

Questions?

