IBM Resilient



Incident Response Platform

FUNCTION DEVELOPER'S GUIDE v1.1

Licensed Materials - Property of IBM

© Copyright IBM Corp. 2010, 2018. All Rights Reserved.

US Government Users Restricted Rights: Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Resilient Incident Response Platform Function Developer's Guide

Version	Publication	Notes	
1.1	October 2018	Documented Resilient Circuits V31 commands and included additional	
		coding guidelines.	
1.0	June 2018	Initial release.	

Table of Contents

1.	Obje	ctive	5
2.	Over	view	5
	2.1.	Resilient Incident Response Platform	5
	2.2.	Integration Architecture	7
	2.3.	Function Processor	8
	2.4.	Resilient Circuits	9
	2.5.	Development Overview	9
	2.6.	Developer Website	.10
3.	Prere	equisites	.11
4.	Confi	iguring Resilient Circuits	.12
	4.1.	Install Resilient Circuits	.12
	4.2.	Install Integrations	.12
	4.3.	Create the Configuration File and Log Directory	.13
	4.4.	Edit the Configuration File	.13
	4.5.	Pull Configuration Values	.15
	4.6.	Add Values to Keystore	.15
	4.7.	Run Resilient Circuits	.15
	4.7.1	. Run Multiple Instances	.15
	4.7.2	. Monitor Config File for Changes	.16
	4.7.3	. Override Configuration Values	.16
	4.8.	Run as a Service	.16
	4.8.1	. Systemd on RHEL	.16
	4.8.2	. Windows	.17
5.	Deve	loping Functions	.19
	5.1.	Create the Resilient Platform Components	.19
	5.1.1.	Naming Conventions	.20
	5.1.2	. Input Field Considerations	.21
	5.1.3	Post-Process Script Considerations	.22
	5.2.	Write the Function Processor	.23
	5.3.	Modify the Selftest Module	.24
	5.4.	Run the Function	.25
	5.5.	Test the Function	.26
	5.6.	Package Your Function	.27
	5.6.1	. Create Your Package	.27
	5.6.2	. Document Your Package	.28
	5.6.3	Deploy to a Different Resilient Platform	.29
	5.6.4	. Publish Your Function	.29
6	Codi	ng Considerations	30

6.1.	Data Flow	30
6.2.	Error Handling	30
	Logging	
6.4.	Data Results	30
6.5.	Linking to 3rd Party Integration Objects	31
6.6.	Rich Text	31
6.7.	Temporary files	
	Avoid using self	

1. Objective

This guide provides the information to integrate the Resilient Incident Response Platform with your organization's existing security and IT investments using the functions feature. Integrations makes security alerts instantly actionable, provides valuable intelligence and incident context, and enables adaptive response to complex cyber threats.

This guide is intended for programmers, testers, architects and technical managers interested in developing and testing integrations with the Resilient platform. It assumes a general understanding of the Resilient platform, message-oriented middleware (MOM) systems, and a knowledge of writing scripts in Python.

2. Overview

You should familiarize yourself with the Resilient architecture and the relevant Resilient features, as described in the following sections, before designing and writing functions.

2.1. Resilient Incident Response Platform

The Resilient Incident Response Platform is a central hub for incident responses. It is customizable so that it can be tailored to meet the needs of your company or organization. The focus of these customizations is the dynamic playbook, which is the set of rules, conditions, business logic, workflows and tasks used to respond to an incident. The Resilient platform updates the response automatically as the incident progresses and is modified.

You should be familiar with your organization's customized Resilient playbook when designing an integration. In particular, you should be familiar with the following playbook components:

- Rule. A set of conditional statements that identify relationships and run responses
 accordingly. Rules define a set of activities that are triggered when conditions are met.
 Activities include setting incident field values, inserting tasks into the task list, launching
 workflows, running internal scripts to implement business logic and placing items on message
 destinations to be acted upon by remote programs.
- Workflow. A graphically designed set of activities that allows you to create a complex set of
 operations. You can use workflows to implement sophisticated business processes that can
 be invoked by rules. Workflows can contain various components, such as scripts, functions,
 and message destinations.
- Message destination. The location where data is posted and made accessible to remote programs. The message includes details about an object and the activity taken. You can configure rules, workflows and functions to send messages to one or more message destinations.
- Custom field. Design element used in incident layouts to capture specific data. An integrated system can populate a custom field.
- Data table. Design element that organizes data in a tabular format. An integrated system can
 populate the table.

- Function. A Resilient object that sends data to a remote function processor through a
 message destination. The function processor is the remote code component that performs an
 activity and returns the results. The results are acted upon by scripts, rules, and workflow
 decision points to dynamically orchestrate the security incident response activities. Functions
 simplify development of integrations by wrapping each activity into an individual workflow
 component. A function consists of the following components:
 - Inputs. Data that is acted on by the function processor. The inputs can be provided by a Resilient user or by a pre-process script.
 - Pre-process script. A script that is used to dynamically set the value of one or more of the function's input fields. You can use the script to retrieve the current value of a property then provide that value to the function as an input. A pre-process script cannot perform write activities on objects, such as changing incident values or adding artifacts.
 - Output. Result of the function processor. A post-process script can act upon this result. If saved, objects within the same workflow instance and executed after the function can also access the data.
 - Post-process script. A script that performs an activity in response to the result provided by the function. The script can change incident values, add artifacts, add data table rows, and more.


For more information about the Resilient platform and dynamic playbooks, refer to the Resilient Incident Response Platform Playbook Designer Guide.

2.2. Integration Architecture

The Resilient platform has a full-featured REST API that sends and receives JSON formatted data. It has complete access to almost all Resilient features, including but not limited to; creating and updating incidents and tasks, managing users and groups, and creating artifacts and attachments.

To perform an integration with functions, your Resilient platform must subscribe to the Action Module. This is an extension to the Resilient platform that allows implementation of custom behaviors beyond what is possible in the Resilient internal scripting feature. It is built on Apache ActiveMQ. The STOMP message protocol is used for Python based integrations. Custom behaviors are triggered by adding a message destination to a rule defined in the Resilient platform and subscribing your integration code to that message destination.

The following diagram shows the relationship between the integration component, REST API, Action Module and Resilient platform.




The Resilient platform contains an interactive Rest API browser that allows you to access the Resilient REST API and try out any endpoint on the system. When logged into the Resilient platform, click on your account name at the top right and select **Help/Contact**. Here you can access the complete API Reference guide, including schemas for all of the JSON sent and received by the API, and the interactive Rest API.

2.3. Function Processor

Resilient functions send data to external programs called function processors. The function processor can then perform integration work, for example:

- Performing a lookup, such as for information about a user or machine in an asset database, and returning the data values found.
- Searching SIEM logs, such as for an IP address, a URL or a server name, and returning a list
 of events.
- Sending a file attachment to a sandbox for analysis, producing a report and a collection of observables.
- Opening a ticket in an ITSM system with a type, name and description, and returning the ticket-ID.
- Triggering an external action and then returning results for use in workflows, tasks and other decisions.

In the Resilient platform, a rule is configured on an incident, an artifact or other object. When the rule fires, it runs a workflow that could have multiple steps. Those steps can include functions that send input parameters to the function processor using a message destination, receive the results, and use the results to update the Resilient incident, to decide the direction of subsequent workflow steps or in a variety of other ways.



The Resilient Circuits framework is required and makes it extremely simple to develop and deploy functions using Python. The function processor component is a Python class that implements *function methods*. These functions are called by the framework when the Resilient platform invokes the function from a workflow.

2.4. Resilient Circuits

Resilient Circuits is a Python circuits framework that automatically manages authenticating and connecting to the STOMP connection and REST API in the Resilient platform. It simplifies creating integrations by allowing you to focus on writing the behavior logic. It is the preferred method for writing integrations.

You can use Resilient Circuits to manage your functions as well as other types of integrations. Each integration has its own section in the app configuration file. This file stores information about the Resilient platform, such as user credentials, as well as variables for your functions.

Resilient Circuits use the Resilient helper module, which is a Python library to facilitate easy use of the Rest API.

2.5. Development Overview

Before you write function, you must understand the purpose of the function, the inputs the function needs to perform its activity, the expected results, and the actions or decisions to be made based on the results.

The following procedure provides a high-level overview of the development process. The subsequent sections in this guide provide the details.

- 1. Install and configure Resilient Circuits and the Resilient helper module on your integration system. You do not need to repeat this step if you have previously installed Resilient Circuits.
- 2. Log into the Resilient platform and create one or more functions and associated components, such as message destination and workflow.
- 3. Export the Resilient platform settings to an export file.
- 4. Using Resilient Circuits and codegen, write the function processor, which is the code for the integration.
 - **TIP**: If you have access to functions that are similar to the one you wish to create, use that function as a template to save time.
- 5. Use the pip install command to deploy the function to the Resilient platform and test the function by triggering the workflow and checking the results. If you make any changes to any of the function's components, export the Resilient platform settings and repackage your function processor using codegen.
- 6. Write a document that provides information on deploying and using the function.
- 7. Package your function, all its components and the document then distribute it to other Resilient administrators. They can deploy the package to any Resilient platform at the same or later version as your test platform.
- 8. Optionally, share your package with other developers in the IBM Resilient developer community.

2.6. Developer Website

The Resilient developer web site contains the core Resilient helper module and Resilient Circuit packages, additional integration packages, documentation and examples. The links are provided below.

- IBM Resilient Success Hub. If you have not already, use this link to request access.
- <u>IBM Resilient Developer website</u>. Provides overview information and access to various areas of development, such as developing playbooks and publishing integrations.
- IBM Resilient Github. Provides access to library modules, community-provided extensions, example scripts, and developer documentation. It also contains the Resilient Circuits and helper module packages. This is also accessible from the developer website reference page.
- <u>Releases</u>. Lists the apps by Resilient Incident Response Platform release. You can also download from this page.

3. Prerequisites

Before starting, make sure your environment meets the following prerequisites:

- Resilient platform V30 or V31 (preferably in a test environment) with the Resilient Action Module.
- A dedicated Resilient account to use as the API user. In most integrations, the account must have the permission to view and edit incidents, and view and modify administrator and customization settings. You need to know the account username and password.
- Resilient Circuits and Resilient helper module, V30 or V31. You should be familiar with the Resilient Circuits framework, as described in Configuring Resilient Circuits.
- A text editor.
- A basic knowledge of Python.
- If using a system for integration other than the one used by the Resilient platform, the system must have access to the Resilient platform and have one of the following configurations:
 - o Red Hat Enterprise Linux 7.4 with Python 2.7 or later, or Python 3.4 or later.
 - o Windows with Python 2.7 or later, or Python 3.4 or later.

IBM Resilient recommends that you use a Resilient platform in a test environment to create the function, message destination, rules, workflows and other components needed for your integration. Once tested, you can deploy the integration into any Resilient platform that is at the same or later version as your test platform.

4. Configuring Resilient Circuits

Typically, you install the Resilient helper module and Resilient Circuits framework on the same system as your Resilient platform; however, you can install and manage your integration from a different system. Using a different system is useful if you have multiple Resilient integration packages in your environment.

4.1. Install Resilient Circuits

The installation procedures assume that all the packages are to be installed on the same system as the Resilient platform and that you have downloaded the Resilient Circuits and Resilient helper module packages from IBM Resilient Github.

Install the Resilient helper module and Resilient Circuits framework as follows:

- 1. Use ssh to connect to your Resilient appliance.
- 2. Go to the folder where the installers are located.
- 3. Update your pip version using this command:

```
sudo pip install --upgrade pip
```

4. Update your setup tools using this command:

```
sudo pip install --upgrade setuptools
```

- 5. Log out of your system and log in with a new session to ensure your environment is correct.
- 6. Install the Resilient helper module using the instructions in the readme file.
- 7. Install the Resilient Circuits package using the instructions in the readme file.

You should see a "successfully installed" message for Resilient helper module and Resilient Circuits.

4.2. Install Integrations

Once you install the Resilient Circuits and helper module, you can optionally install components, such as functions or other types of integration packages. Some are available for download from GitHub and you can write your own as well. Use the following procedure to install and configure a component.

- 1. Use ssh to connect to your Resilient appliance.
- 2. Go to the folder where the installers are located.
- 3. Install your chosen component using the following command:

```
pip install <package name>-x.x.x.tar.gz
```

4. Verify that the component installed using the resilient-circuits list command.

```
resilient-circuits list
```

5. Follow the instructions in the component's readme file to configure the component.

4.3. Create the Configuration File and Log Directory

The Resilient Circuits package requires a configuration file and logging directory.

The configuration file defines essential configuration settings for all resilient-circuits components running on the system. If you have multiple Resilient integration packages, they use the same configuration file.

Other integration components may have additional requirements.

Note to Windows Users: To run integration commands on a Windows system, use resilient-circuits.exe. For example, "resilient-circuits.exe run" rather than "resilient-circuits run".

The examples in this guide use the default name, app.config, as the name of the Resilient Circuits configuration file.

Perform the following to create the configuration file:

- 1. Create a directory on the system where Resilient Circuits can write log files.
- 2. Use one of the following commands to generate a base configuration file.
 - Option 1: Create a directory '.resilient' in your home directory with a file in it called app.config, which is the default and preferred option.

```
resilient-circuits config -c
```

 Option 2: Sometimes it is necessary to create a configuration file in a different location or give it a different name. You need to store the full path to the environment variable, APP_CONFIG_FILE.

```
resilient-circuits config -c /path/to/<filename>.config
```

If APP_CONFIG_FILE is not set, then the application looks for a file called "app.config" in the local directory where the run command is launched from. This can be useful during development of a new component.

4.4. Edit the Configuration File

The [resilient] section of the configuration file controls how the core resilient_circuits and Resilient packages access the Resilient platform.

Open the configuration file in the text-editor of your choice and update the [resilient] section with your Resilient appliance hostname/IP and credentials and the absolute path to the logs directory you created. The following table describes all the required and optional values that can be included in this section.

NOTE: If on a Windows system and you edit the file with Notepad, please ensure that you save it as type **All Files** to avoid a new extension being added to the filename, and use UTF-8 encoding.

Parameter	Required?	Description
logfile	N	Name of rotating logfile that is written to logdir. Default is app.log.
logdir	N	Path to directory to write log files. If not specified, program checks environment variable DEFAULT_LOG_DIR for path. If that is not set, then defaults to a directory called "log" located wherever Resilient Circuits is launched.
log_level	N	Level of log messages written to stdout and the logfile. Levels are: CRITICAL, ERROR, WARN, INFO (default), and DEBUG.
host	Y	IP or hostname for the Resilient platform.

Parameter	Required?	Description
org	Y, if multiple orgs	Name of the Resilient organization. This is required only if the user account is used with more than one Resilient organization.
email	Y	User account for authenticating to the Resilient platform. It is recommended that this account is dedicated to integrations.
password	Y	Password for the Resilient user account.
no_prompt_password	N	If set to False (default) and the "password" value is missing from this config file, the user is prompted for a password.
		If set to True, the user is not prompted.
stomp_port	N	Port number for STOMP. Default is 65001.
componentsdir	N	Path to directory containing additional Python modules. Resilient Circuits load the components from this directory.
noload	N	Comma-separated list of: a. Installed components that should not be loaded. b. Module names in the componentsdir that should not be loaded. Example: my_module, my_other_module, InstalledComponentX
proxy_host	N	IP or Host for Proxy to use for STOMP connection. By default, no proxy is used.
proxy_port	N	Port number for Proxy to use for STOMP connection. By default, no proxy is used.
proxy_user	N	Username for authentication to Proxy to use for STOMP connection. If a proxy_host is specified and no proxy_user specified, then assumed no authentication is required.
proxy_password	N	Password for authentication to Proxy to use for STOMP connection. Used in conjunction with proxy_user.
cafile	N	Path and file name of the PEM file to use as the list of trusted Certificate Authorities for SSL verification when the Resilient platform is using untrusted self-signed certificates. If there is a PEM file, use a second instance of cafile to set to True or False. If set to False, certificate verification is not performed and the PEM file is used. If set to True (default), allow only trusted certs.

Whenever you install a new component package for Resilient Circuits, you need to update your app.config file to include any required section(s) for the new component(s). After installing the package, run:

resilient-circuits config -u

If using Resilient Circuits V31, you can choose specific packages:

resilient-circuits config -u -l <package1> <package2>

If using an alternate file location for your app.config file, you need to specify it when you update.

resilient-circuits config -u /path/to/app.config

This adds a new section to your existing config file with default values. Depending on the requirements of the component, you may need to modify those defaults to fit your environment, such as credentials to a 3rd party system.

4.5. Pull Configuration Values

Values in the config file can be pulled from a compatible keystore system on your OS. This is useful for values like password that you would prefer not to store in plain text. To retrieve a value from a keystore, set it to ^< key>. For example:

```
[resilient]
password=^resilient_password
```

Values in your config file can also be pulled from environment variables. To retrieve a value from the environment, set it to \$<key>. For example:

```
[resilient]
password=$resilient_password
```

4.6. Add Values to Keystore

The Resilient package includes a utility to add all of the keystore-based values from your app.config file to your system's compatible keystore system. Once you have created the keys in your app.config file, run res-keyring and you are prompted to create the secure values to store.

```
res-keyring
Configuration file: /Users/kexample/.resilient/app.config
Secrets are stored with 'keyring.backends.OS_X'
[resilient] password: <not set>
Enter new value (or <ENTER> to leave unchanged):
```

4.7. Run Resilient Circuits

Once configuration is complete, you can run Resilient Circuits with the following command:

```
resilient-circuits run
```

If everything has been successful, you should see lots of output to your shell, including a components loaded message. For example:

```
<load_all_success[loader] ( )>
     2017-03-06 11:04:35,525 INFO [app] Components loaded
```

You can stop the application running with ctrl+c.

4.7.1. Run Multiple Instances

Running the application creates a hidden file called "resilient_circuits_lockfile" in a ".resilient" directory in your home directory. This is to prevent multiple copies of the application from running at once. If your particular situation requires running multiple instances of Resilient Circuits, you can override this behavior by specifying an alternate location for the lockfile via an "APP_LOCK_FILE" environment variable.

4.7.2. Monitor Config File for Changes

You can configure Resilient Circuits to monitor the app.config file for changes. When it detects a change has been saved, it updates its connection to the Resilient appliance and notifies all components of the change. To enable this option, install the "watchdog" package.

pip install watchdog

Now you can run with:

resilient-circuits run -r

Without the –r option, changes to the app.config file have no impact on a running instance of Resilient Circuits. Note that not all components currently handle the reload event and may continue using the previous configuration until Resilient Circuits is restarted.

4.7.3. Override Configuration Values

Sometimes it is necessary to override one or more values from your app.config file when running Resilient Circuits. For example, you may want to temporarily run with the log level set to DEBUG. To accomplish this, run Resilient Circuits with:

resilient-circuits run --loglevel DEBUG

You can also use optional parameters to run the application when the values being overridden are required and missing from the config file.

For a complete list of optional arguments for overrides, run:

resilient-circuits run -- --help

4.8. Run as a Service

You can configure Resilient Circuits to run as a service on a Red Hat Enterprise Linux or Windows system.

4.8.1. Systemd on RHEL

Systemd is a process control program available on a variety of modern Linux systems. It is available on the RHEL-based Resilient appliance. You need to create an OS user for the service. On RHEL Linux:

sudo adduser integration --home /home/integration

Systemd uses unit configuration files to define services. Copy the configuration file provided below to your integration machine and edit as necessary. The configuration file defines the following properties:

- OS user account to use.
- Directory from where it should run.
- Any required environment variables.
- Command to run the integrations, such as resilient-circuits run.
- Dependencies.

Here is an example of a configuration file. Copy this text to a file called resilient_circuits.service and edit the content to match your setup. If you are not running on the Resilient appliance, then the "After" and "Requires" lines in the [Unit] section should be removed.

```
[Unit]
Description=Resilient-Circuits Service
After=resilient.service
Requires=resilient.service

[Service]
Type=simple
User=integration
WorkingDirectory=/home/integration
ExecStart=/usr/local/bin/resilient-circuits run
Restart=always
TimeoutSec=10
Environment=APP_CONFIG_FILE=/home/integration/.resilient/app.config
Environment=APP_LOCK_FILE=/home/integration/.resilient/resilient_circuits.lock

[Install]
WantedBy=multi-user.target
```

Copy this to the configuration directory and tell systemd to reload and enable the new service:

```
cp resilient_circuits.service /etc/systemd/system/resilient_circuits.service
sudo chmod 664 /etc/systemd/system/ resilient_circuits.service
sudo systemctl daemon-reload
sudo systemctl enable resilient circuits.service
```

To start or stop the resilient_circuits service, run:

```
sudo systemctl start resilient_circuits.service
sudo systemctl stop resilient circuits.service
```

4.8.2. **Windows**


Resilient Circuits can be configured to run as a service. It requires the pywin32 library, which should be downloaded from <u>sourceforge</u>. Instructions for downloading and installing the correct package are at the bottom of the screen and must be followed carefully. Do not use the pypi/pip version of pywin32.

Installation of the wrong version of the pywin32 library will likely result in a Resilient service that installs successfully but is unable to start.

Now run:

resilient-circuits.exe service install

Once installed, you can update the service to start up automatically and run as a user account.



It is recommended that you log in as whichever user account the service will run as to generate the config file and confirm that the integration runs successfully with "resilient-circuits.exe run" before starting the service.

Commands to start, stop, and restart the service are provided as well.

```
resilient-circuits.exe service start
resilient-circuits.exe service stop
resilient-circuits.exe service restart
```

5. Developing Functions

Before you write a function, you must understand the purpose of the function, the inputs the function needs to perform its activity, the expected results, and the actions or decisions to be made based on the results.

If you wish, you can create multiple functions related to the same integration and include all of them in one package.

TIP: If you have access to functions that are similar to the one you wish to create, use that function as a template to save time.

5.1. Create the Resilient Platform Components

Before you write the function processor code, you need to create the function and associated components as follows. For detailed procedures on creating each component, see the *Resilient Incident Response Platform Playbook Designer Guide*.

- 1. Review the conventions in Naming Conventions before creating the function and its components.
- 2. Log in to the Resilient platform as a user with permission to view and modify the customization settings.
- 3. Go to the Message Destinations tab and create a message destination for the function. Set the Type to **Queue** and Expect Acknowledgement to **Yes**.
- 4. Go to the Functions tab and create the function then define its properties:
 - Name: Enter a unique name that describes the purpose of the function.
 - API Name: Generated by the system and based on the Name field. This is the name you
 use when you write your function processor.
 - Message destination: Select the message destination you created in the previous step.
 - **Description**: Enter a description of the function's purpose (what it does), overview of the inputs (and guides to logic needed in pre-process script), and overview of outputs (and guides to logic needed in post-process script).
 - **Inputs**: One or more fields whose values are inputs for the function.
- 5. If you require custom fields to gather or receive specific data for your integration, perform the following:
 - a. Go to the **Layouts** tab.
 - b. Determine where to place the fields by selecting the tab or **New Incident Wizard**.
 - c. Create the fields. Take note of the API Access name of each field for use in your code.
- 6. If you require a data table to receive data from the function, perform the following:
 - a. Go to the Layouts tab.
 - b. Determine where to place the data table by selecting the tab.
 - Create the data table. Take note of the API Access name of the data table for use in your code.
- 7. Go to the **Workflows** tab and create or modify one or more workflows to include the function. You may wish to create an example workflow to show how the function should be used, which you can later package with your function. This is handy for functions that rely on complex data handling in pre-process or post-process scripts.

- 8. Add the function then enter the following:
 - a. Determine whether to enter the input values manually in the Input tab or use a preprocess script to determine the input values.
 - b. Choose whether to save the output of a function for use in the pre- or post-process scripts for functions further in the workflow.
- Enter the input values or enter a post-process script. In either case, see Input Field Considerations for guidelines.
- 10. Enter a post-process script to act upon the result. See Post-Process Script Considerations **Error! Reference source not found.** for guidelines.
- 11. At the Rules tab, create the rule to execute the workflow you created. Make sure that the rule does not include a message destination. The function defines the message destination. You may wish to create an example rule to show how the function should be used, which you can later package with your function.
- 12. Go to Administrator Settings then click the **Organization** tab. Use the **Migrate Settings – Export** feature to export the Resilient platform settings to an export file. See the *Resilient Incident Response Platform System Administrator Guide* for details.

5.1.1. Naming Conventions

The name of your integration package should reflect the type of integration as well as be unique. Here are a few examples:

- LDAP Query
- McAfee ePO Integration
- Elasticsearch Query
- Cisco Get Domains

The names of the components in your package should reflect your package name, as follows:

- Use a unique prefix for your function and components, such as the product or provider name.
 Using LDAP Query as example, the components would be as follows. When you enter the name of a component, the API name replaces spaces with underscores.
 - Function name: Idap query
 - Message destination name: Idap_query
 - o Input field: Idap guery inputname
 - Data table: Idap query datatable
 - Custom field: Idap_query_fieldname

You do not need to add a prefix to commonly used fields, such as incident_id, task_id, attachment_id, and artifact_id.

- If you package rules that are meant as examples, you should use the prefix, Example, such as: "Example: Query LDAP"
- If you package workflows that are meant as examples, you should also use the prefix, Example. In your function, you use the API name of the workflow, so an example of a workflow name would be: Example_Idap_query_workflowname

5.1.2. Input Field Considerations

Consider the following when defining input fields.

- Input fields are referenced via the inputs object, for example inputs.id.
- For any ID input field, you must define the corresponding input field type as Number.
 Frequently used ID input fields include:
 - o incident id
 - o artifact id
 - o task id
 - o attachment id
- When sending an ID field to an input field, you must define the input field as Numeric.
- Text Areas, such as incident.description, must to be passed to input fields using the 'content' property. For example: inputs.fn_description = incident.description.content
- In the Resilient platform, use the Tooltip field to provide extra information about the input. Use an example if helpful.
- Use care when processing Textarea fields, which can contain rich text. Rich text is passed to
 your function as HTML tags. For example, a bold word is passed as 'word'. This can
 be confusing to integration applications that do not anticipate this tagging. In most cases, it
 makes sense to strip out these tags.
- An alternative to naming individual input fields for each parameter to pass to an integration, use a single input field containing a JSON string:

```
inputs.test_details = """{{ "incidentId": "{0}",
   "name": "{1}",
   "description": "{2}" }}""".format(str(incident.id), incident.name,
   incident.description.content)
```

Decoding this input field may require the removal of control characters:

```
test_details = kwargs.get("test_details") # text

mpa = {}.fromkeys(range(32))
dict = json.loads(test_details.translate(mpa))
log.info("incidentId: "+dict['incidentId'])
```

 Binary format, such as an attachment, is not supported. If a function needs the content of an attachment, do not send it through input fields. Instead, the integration needs to call the resilient_client of its super class to get the file content. For example:

Input fields can be a composite of multiple Resilient fields, for example:

You should test all required input parameters for a valid entry. You can also enforce this when defining the input field (Requirement: Always). Pre-process scripts are needed for field assignment.

```
incident_id = kwargs.get('incident_id')
  if not incident_id:
    raise FunctionError('incident_id is required')
```

5.1.3. Post-Process Script Considerations

Consider the following when defining post-process scripts.

- Use the results object to access the data returned from an integration. Due to limitations in the way Python scripts can be written, the syntax to access the JSON data can vary:
 - results.matched_list should be used rather than results['matched_list']
 - o results.matched_list['file'] should be used for the next level item
- Failed post-process scripts may cause a workflow to remain in the running state. For a given incident, click the **Actions** button then select **Action Status** to verify the successful completion of a function. Click the **Actions** button then select **Workflow status** to terminate any workflow with failed actions.
- Use dict.get("key") when testing whether data exists for that key. The dict["key"] may cause the script to fail if "key" does not exist.

5.2. Write the Function Processor

A function processor component, in this framework, is a Python class that implements *function methods*. These functions are called by the framework when the Resilient platform invokes the function from a workflow.

To write the Python code that performs the function's integration logic, start by using codegen to generate a Python package with a boilerplate implementation. This package includes everything needed to make your function installable. Besides your code, it can include the function definition, custom fields, data tables, workflows and rules, which you created on the Resilient platform.

```
resilient-circuits codegen --package pckg name --function func name
```

NOTE: To see additional options, such as packaging multiple functions, see Package Your Function.

The following example packages a function called lookup_mode_by_id and a workflow called lookup_model into a package called fn_model.

```
$ resilient-circuits codegen -p fn_model -f lookup_model_by_id --workflow lookup_model
Codegen is based on the organization export from 2018-04-12 14:46:34.355000.
Writing ./fn_model/MANIFEST.in
Writing ./fn_model/README.md
Writing ./fn_model/fn_model/LICENSE
Writing ./fn_model/fn_model/__init__.py
Writing ./fn_model/fn_model/components/__init__.py
Writing ./fn_model/fn_model/components/lookup_model_by_id.py
Writing ./fn_model/fn_model/util/__init__.py
Writing ./fn_model/fn_model/util/config.py
Writing ./fn_model/fn_model/util/customize.py
Writing ./fn_model/setup.py
Writing ./fn_model/tests/test_lookup_model_by_id.py
Writing ./fn_model/tox.ini
$
```

The result is a directory containing the essential files for an installable Python package that implements the function or functions specified. Within this package, the function code itself is a simple script, such as the one below, that you can edit to add your integration logic. This script is a *component* with a method, decorated with <code>@function()</code> that tells the Resilient Circuits framework how to call it.

```
# yield StatusMessage("starting...")
# yield StatusMessage("done...")

results = {
        "value": "xyz"
}

# Produce a FunctionResult with the results
    yield FunctionResult(results)
except Exception:
    yield FunctionError()
```

First, the function gets its parameters (model_id, in this case). The boilerplate implementation logs the values for ease of debugging, although you may want to change that if it's too noisy.

At any stage during the function's processing, you can enter <code>yield StatusMessage("...")</code>, which provides a status message that will display to the Resilient user in the Action Status dialog. If your function might run for several seconds or minutes, this can be a useful way to show progress.

The results are a Python dictionary, containing named values that will be available in the workflow output and post-process script. If possible, your functions should return a small 'results' dictionary with one or a few named values. In this case, you should include enough documentation to help your users understand how to find and use these results in a custom workflow.

5.3. Modify the Selftest Module

If using Resilient Circuits V31 or later, one of the boilerplate templates created when you use codegen is the selftest module. The selftest module provides the means to diagnose issues before escalating them. You can configure a run-time capability to test connectivity and configuration issues by modifying this module, which is located in a folder called selftest.py under the util directory.

One of the basic tests is a connectivity test. IBM Resilient suggests that you configure the module to perform a non-invasive test, such as a login or simple query.

You determine the results that would be useful for a self-diagnostic. The selftest result is configured to return a state of success, failure or unimplemented.

Once you complete your package, you can use the selftest command to test the function, as follows:

```
resilient-circuits selftest
```

If you have multiple packages, you can run selftest on one or more specific integrations:

```
resilient-circuits selftest -1 <integration 1> <integration n>
```

5.4. Run the Function

Before running the function, you must install this package so that Resilient Circuits can load it. The most convenient way to install during development is with pip's editable flag (or -e). Using this, you can edit your source files directly without needing to reinstall after any changes.

```
pip install --editable ./pckg name/
```


Run the integration code from the command-line, as follows. The framework reads your configuration file, connects to the Resilient platform, finds and loads all the installed components, then subscribes to the message destination for each function processor component. Leave it running; when a function is invoked, the code handles it.

```
resilient-circuits run
2018-04-12 16:10:31,814 INFO [app] Configuration file:
/home/integration/.resilient/app.config
2018-04-12 16:10:31,816 INFO [app] Resilient server:
myserver.resilientsystems.com
2018-04-12 16:10:31,817 INFO [app] Resilient user: api@example.com
2018-04-12 16:10:31,818 INFO [app] Resilient org: PartnerLab
2018-04-12 16:10:31,818 INFO [app] Logging Level: INFO
2018-04-12 16:10:38,075 INFO [component_loader] Loading 1 components
2018-04-12 16:10:38,076 INFO [component_loader]
'fn model.components.lookup model by id.FunctionComponent' loading
2018-04-12 16:10:38,089 INFO [stomp component] Connect to
myserver.resilientsystems.com:65001
2018-04-12 16:10:38,090 INFO [actions component]
'fn model.components.lookup model by id.FunctionComponent' function
'lookup model by id' registered to 'function example'
2018-04-12 16:10:38,091 INFO [app] Components loaded
2018-04-12 16:10:38,094 INFO [app] App Started
2018-04-12 16:10:38,196 INFO [actions component] STOMP attempting to connect
2018-04-12 16:10:38,198 INFO [stomp component] Connect to Stomp...
2018-04-12 16:10:38,199 INFO [client] Connecting to
myserver.resilientsystems.com:65001 ...
2018-04-12 16:10:38,825 INFO [client] Connection established
2018-04-12 16:10:39,090 INFO [client] Connected to stomp broker [session=ID:ip-
1-2-3-252.srv.resilientsystems.com-35733-1523282148180-5:243, version=1.2]
2018-04-12 16:10:39,092 INFO [stomp component] Connected to
failover: (ssl://myserver.resilientsystems.com:65001)?maxReconnectAttempts=1,sta
rtupMaxReconnectAttempts=1
2018-04-12 16:10:39,093 INFO [stomp component] Client HB: 0 Server HB: 15000
2018-04-12 16:10:39,094 INFO [stomp component] No Client heartbeats will be
sent
2018-04-12 16:10:39,095 INFO [stomp component] Requested heartbeats from
server.
2018-04-12 16:10:39,098 INFO [actions component] STOMP connected.
2018-04-12 16:10:39,205 INFO [actions component] Subscribe to message
destination 'function example'
2018-04-12 16:10:39,206 INFO [stomp component] Subscribe to message destination
actions.201.function example
```


The framework is running and waiting for the function to be called.

5.5. Test the Function

You test the function by using it from the Resilient platform. Use a rule to trigger the workflow that contains the function. The rule can be a menu-item rule, which displays an action for its object (such as incident, artifact or task) when the conditions are met, or an automatic rule that runs the workflow when an object is created or modified and meets the rule's pre-defined conditions.



For this example, the workflow runs on an artifact, so the rule is a menu-item rule that appears as an action in each incident's artifact action menu, accessible from the [...] button.




Select your action to start the workflow and call your function.

At the integration console, you see the function message arrive, including the logging message to print the function's parameters as part of the boilerplate code.

```
2018-04-12 16:24:23,235 INFO [actions_component] Event: <lookup_model_by_id[] (id=219, workflow=lookup_model, user=who@example.com) 2018-04-12 16:23:20.221000> Channel: functions.function_example 2018-04-12 16:24:23,237 INFO [lookup_model_by_id] model_id: 0e6499e91482f47df46fcaebb28bac985193aab331beeb5bc553162b422c1f21
```

The incident's Action Status menu shows that status of each rule, which can be pending (queued for delivery to the function processor), processed successfully, or with an error. In the following example, the action completed with success and included a status message.



If you need to make any changes to any of the function's elements, export the Resilient platform settings and repackage your function processor using codegen.

Consider implementing the actual integration code to the 3rd party system in a separate module from that which manages the Resilient framework. This separation of logic allows you to test the 3rd party integration separate from the code as part of Resilient Circuits.

```
components/
    <function_code>.py
    <3rd_party_integration_code>.py

tests/
    test_<function_code>.py
    test <3rd_party_integration_code>.py
```

You can also use the Resilient Circuits sefltest command as a troubleshooting aid.

5.6. Package Your Function

When satisfied with the test results, you can package your function and components for use with other Resilient platforms. You can deploy the package to a Resilient platform in your environment different than the one you were using for testing, or make it available to the Resilient community.

5.6.1. Create Your Package

The following is the basic command you use to create a Python package containing your function:

```
resilient-circuits codegen --p <package name> --function <function name>
```

When you are ready to share your package, you need to include all the related components, such as the rules, workflows, message destinations and any custom fields and data tables. To do this, use arguments such as --workflow, --rule, --m (message destination) and --datatable. Use --h to list all the arguments. You also need to have the file exported from the Resilient platform, which contains the related components. The following command includes a workflow and rule, and specifies the export file:

```
resilient-circuits codegen --p <package_name> --function <name> --workflow <name> --rule <name> --exportfile <filename>
```

If using a rule or script name that contains spaces, use quotation marks around the name and be aware that the name is case sensitive. For example:

```
resilient-circuits codegen -m fn_cisco_enforcement --rule "Cisco Get Domains" --datatable cisco enforcement
```

NOTE: The --exportfile is needed only if the most recently created export file (.res) in Downloads is not the intended file or the export file you want is in a different location.

Optionally, you can specify multiple functions to codegen into the package by specifying each function name with the --function parameter. To see a list of functions on your integration system, enter the following command. Codegen returns the file path to the function, which you can open using a text editor such as vi or nano.

```
resilient-circuits codegen
Available functions:
    ldap_search
    ldap_disable_user
```

NOTE: The codegen -o argument, shown as follows, should only be used if you need to create a single Python file with a specific name.

```
resilient-circuits codegen --function <function name> -o <function name>.py
```

If you have previously created a package and you need to recreate it, you can use the reload option (only with Resilient Circuits V31 or later). This is useful when you wish to add more components without specifying the components you added the last time you created the package. To use the reload option, you must specify the name of the package to be reloaded. The following example reloads your package with all previous components then adds a new rule.

```
resilient-circuits codegen --reload <package name> --rule "Cisco Add Domain"
```

This command also saves the existing customize.py as customize-*yyymmdd-hhmm*ss.bak in the util directory of the package.

NOTE: You cannot reload a package generated with a version of Resilient Circuits prior to V31. If you wish to use reload, you need to rename your customize.py then generate a new package using Resilient Circuits V31. You can then use reload for the new package.

5.6.2. Document Your Package

IBM Resilient suggests that you create a document that describes the function and all its components. It should discuss how to install it, its basic purpose, and a complete description of each component.

If your package contains custom fields and data tables, make sure to document that the Resilient playbook designer should include these in the incident layouts, since the fields and data tables cannot be automatically added to layouts. When possible, provide details on the intended incident layouts, such as a New Incident Wizard or a specific incident tab.

You should also document that re-importing a function's custom fields and custom data tables does not restore any layout changes made. Therefore, the layout changes may need to be recreated.

5.6.3. Deploy to a Different Resilient Platform

You can deploy the function to any Resilient platform at the same version or greater as your test platform. You do this by compressing the .py files into a tar.gz file then distributing that file. Your package should include the functions and all their components.

Resilient administrators must have a Resilient Circuits installation that points to their Resilient platform. The administrators can use the following command to import the function and its components directly into the platform.

pip install <pkg name>.tar.gz

Optionally, the administrators can unzip the package and use the following command.

pip install ./pckg name/

Once installed, the administrators use the Resilient Circuits customize utility to update the Resilient platform with any missing message destinations, function definitions, and other design elements. The command is:

resilient-circuits customize

If using Resilient Circuits V31 or later, the administrators can choose which functions to install as follows:

resilient-circuits customize -1 <function name1> <function name2>

The optional parameter, -y, applies all the customizations without asking for confirmation.

Each installed package that includes a "customize" entry-point is called and returns a collection of customizations described in Resilient JSON format. These are used to update the Resilient platform.

The customize command only rebuilds those components that were referenced from the codegen command line. For example, if you indicated --workflow, then workflows are rebuilt during the customize process.

5.6.4. Publish Your Function

In addition to deploying your functions to other Resilient platforms in your environment, you can share your functions with the Resilient community if you are an IBM Technology partner or employee. For information about becoming a technology partner, see the IBM PartnerWorld page.

IBM Resilient provides two locations for sharing functions, IBM Security X-Force App Exchange, and Resilient Community Apps on Github.

The IBM Security X-Force App Exchange allows you to make your function available to others in the Resilient community. You have the option to update the function as needed. For more information on submission requirements, see the <u>Publishing Integrations</u> page.

The Resilient Community Apps on Github also allows you to share your function source code with others. Members can copy, modify and enhance your function using the pull request mechanism. See the Resilient Community Apps page for a list of apps, with developer information at the bottom of this web page.

You can choose to submit to one or both locations.

6. Coding Considerations

The following sections provide advice and recommendations to consider when creating your function.

6.1. Data Flow

Functions are blocking until results are returned. Returning FunctionError() aborts the result of a workflow.

All functions are stateless. No persistence of data is retained between function calls.

6.2. Error Handling

The high level code should be covered with try / except / finally blocks. Any exception should describe the issue for Resilient Action Status log. The finally block should be used to perform any connection closing, temporary file cleanup, and so on.

Do not use <code>yield FunctionError()</code> within try/except. It causes the message destination message to remain stuck. Each time Resilient Circuits is restarted, the message is attempted again. The better solution is call <code>raise FunctionError()</code> and then the except block can perform the <code>yield</code>. The <code>yield FunctionError()</code> also interferes with <code>finally</code> in try/except/finally. The fix is to change <code>yield</code> to <code>raise</code>.

6.3. Logging

Log information for debugging purposes. Sensitive information should never be logged, but can be obscured. For example, user.email@example.com can become us***@example.com.

6.4. Data Results

Use the function, FunctionResult(), to return the JSON for post-process script processing. A sample result should be included in the function's description field.

As much as possible, return top-level items or lists of items (or combinations):

```
{
   'item1': 'result1',
   'item2': 'result2'
}
```

or

Links back to the integration application are supported by creating a Resilient custom field, such as a Textarea with rich text enabled. Add the custom field to an incident's Summary section for easy access. In the workflow's post-processing script, add code similar to this:

```
incident.properties.pd_incident_url = "<a href='{}'
target='blank'>Link</a>".format(results.pd['incident']['html_url'])
```

Data tables are a convenient way to return and display row results. There are a number of considerations to bear in mind with their use:

- Data tables are global to an incident (as are all custom fields). This means that the table rows
 are not unique to a specific object, such as an artifact.
- In order to deal with the shared use of tables, add two columns to a table to identify the search argument (such as artifact.value) and a timestamp when the results were returned.

6.5. Linking to 3rd Party Integration Objects

Perform the following to create a live URL link back to the integrated system, such as a ticketing system.

- 1. Create a new incident custom field as a text area with Rich Text enabled.
- 2. Add it to the summary section of an incident's layout.
- 3. In the function's post-process script, build the URL as an HTML anchor:

```
incident.properties.pd_incident_url = "<a href='{}' target='blank'>reference
Link</a>".format(results.pd['incident']['html url'])
```

6.6. Rich Text

Rich text fields may contain HTML markup. This format may be undesirable for the target integration system. A method such as the one below can strip off the HTML elements, preserving some of the new line format:

6.7. Temporary files

For integrations that read from or write to files, one method to create temporary files is to use Python's tempfile:

```
import tempfile
...
with tempfile.NamedTemporaryFile() as temp_file:
```

In situations when filehandles are used, consider using StringIO instead. This avoids any OS interaction with files:

```
import StringIO
...
with StringIO(filedata) as temp_file:
```

For more information, see https://docs.python.org/2.7/library/stringio.html.

Temporary files can behave differently depending on the operating system, such as opening a file a second time while the named temporary file is still open. This works on Unix but not on Windows NT or later. To avoid this, create the temp file with the delete=False flag so the file is not deleted when closed, close the file before trying to read/write a second time and then explicitly delete the file when done rather than depending on NamedTemporaryFile to do it. The Floss function in the Resilient App Exchange contains an example of how to do this.

6.8. Avoid using self.

Using <code>self.</code> in functions is not thread-safe. This means that <code>self.</code> is shared by all functions (even though they are running in different threads). Therefore, a statement such as: self.connection = Connection will likely be overwritten when more than one function is invoked and running at the same time.

The better solution is to use Class level variables and only use self. for class function and Resilient static functions.