KIWI Project

openSUSE-KIWI Image System Cookbook

Project, Design and Implementation by Marcus Schaefer (ms@suse.de)

*



Author: Marcus Schaefer

Date: August 17, 2010

Version: 4.56

openSUSE-KIWI Image System—Cookbook

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or (at your option) version 1.3; with the Invariant Section being this copyright notice and license. A copy of the license version 1.2 is included in the appendix entitled "GNU Free Documentation License".

SUSE®, openSUSE®, the openSUSE® logo, Novell®, the Novell® logo, the N® logo, are registered trademarks of Novell, Inc. in the United States and other countries. Linux® is a registered trademark of Linux Torvalds. All other thrid party trademarks are the property of their respective owners.

All information found in this book has been compiled with utmost attention to detail. However, this does not guarantee complete accuracy. Neither Novell, Inc., SUSE Linux Products GmbH, the authors, nor the translators shall be held liable for possible errors or the consequences thereof.

Contents

1	Introduction	7		
2	Boot Process			
3	3.1.1 <image/> Element	13 15 16 16 16 27 28 30		
4	4.1 History	35 35 35		
5	Maintenance of Operating System Images	39		
6	Create a Clean Repository Set First			
7	7.1 Adapt the Example's config.xml	45 45 45		
8	8.1 Building the suse-live-iso Example	47 47 47 48 48		

9	USB	Image—Live-Stick System	51
	9.1	Building the suse-live-stick Example	51
		Using the Image	52
		Flavours	52
		9.3.1 Split Stick	53
		9.3.2 LVM Support	53
		7.0.2 EVIII Support	50
10	VMX	Image—Virtual Disks	55
	10.1	Building the suse-vm-guest Example	55
		Using the Image	55
		Flavours	56
		10.3.1 VMware support	56
		10.3.2 LVM Support	57
11	PXE :	Image—Thin Clients	59
	11.1	Setting Up the Required Services	59
		11.1.1 Atftp Server	59
		11.1.2 DHCP Server	60
	11.2	Building the suse-pxe-client Example	60
		Using the Image	61
		Flavours	62
		11.4.1 The PXE Client Control File	62
		11.4.2 The PXE Client Configuration File	62
		11.4.3 User another than tftp as download protocol	67
		11.4.4 RAM only image	67
		11.4.5 Union Image	68
		11.4.6 Split Image	68
		11.4.7 Root Tree Over NFS	69
		11.4.8 Root Tree Over NBD	69
		11.4.9 Root Tree Over AoE	69
			0,
12	OEM	Image—Preload Systems	71
	12.1	Building the suse-oem-preload Example	71
		Using the Image	72
		Flavors	72
		12.3.1 Influencing the OEM Partitioning	73
		12.3.2 LVM Support	73
		12.3.3 Partition Based Installation	73
13		Image—Paravirtual Systems	75
	13.1	Building the suse-xen-guest Example	75
		Using the Image	76
	13.3	Flavours	76
11	ECO.	Imaga Amazon Flastic Compute Cloud	77
14		Image—Amazon Elastic Compute Cloud Building the suse-xen-guest Example for EC2	77
			78
	14.4	Using the Image	/ O

15 KIWI Testsuite 15.1 Testsuite Packages	
Index	83
A Appendix—KIWI man pages	85

1 Introduction

The openSUSE KIWI Image System provides a complete operating system image solution for Linux supported hardware platforms as well as for virtualisation systems like Xen, VMWare, etc. The KIWI architecture was designed as a two level system. The first stage, based on a valid *software package source*, creates a so called *unpacked image* according to the provided image description. The second stage creates from a required unpacked image an operating system image. The result of the second stage is called a *packed image* or short an image.




Figure 1.1: Image Serving Architecture

Because this document contains conceptual information about an image system, it is important to understand what an operating system image is all about. A normal installation process is starting from a given installation source and installs single pieces of software until the system is complete. During this process there may be manual user intervention required. However an operating system image represents an already completed *installation* encapsulated as a file and optionally includes the configuration for a specific task. Such an operating system starts working as soon as the image has been brought to a system storage device no matter if this is a volatile or non volatile storage. The process of creating an image takes place without user interaction. This means all requirements of the encapsulated system has to be fulfilled before the image is created. All of this information is stored in the *image description*.

2 Basic Workflow

Contents

2.1	Boot Process	11
2.2	Boot Parameters	11
2.3	Common and Distribution Specific Code	12

The creation of an image with KIWI is always divided into two basic steps. These are the *prepare* and the *create* step. The create step requires the prepare step to be exited successfully. Within this first prepare step, KIWI builds of a new root tree or, in KIWI speak, a new unpacked image. The building of a new root tree consists of the creation of the directory specified to hold it and the installation of the selected packages on it. The installation of software packages is driven by a packagemanager. KIWI supports the smart and zypper package managers. The prepare step executes the following major stages:

• Creating Root Directory

To prevent accidental deletion of an existing root tree, KIWI will stop with an error message if this folder already exists, unless the option --force-new-root is used in which case the existing root will be deleted.

Installing Packages

First the selected package manager (smart by default) is instructed to use the repositories specified in the image description file. Then the packages specified in the bootstrap section are installed. These packages are installed externally to the target root system (i. e. not chroot'ed) and establish the initial environment so the rest of the process may run chroot'ed. Essential packages in this section are filesystem and glibc-locale. In practice you only need to specify those two, since the rest of the packages will be pulled because of the dependency system. To save space in your image you could schedule a set of packages for deletion after the package installation phase is over by listing them in the delete section.

Executing of User Defined Script config.sh

At the end of the preperation stage the optional script named <code>config.sh</code> is called. This script should be used to configure the system which means for example the activation of services. For a detailed description what functions are already available to configure the system please refer to the KIWI::config.sh manual page

Managing New Root Tree

At this point you can make changes on your unpacked image so it fits your

purpose better. Bear in mind that changes at this point will be discarded and not repeated automatically if you rerun the *prepare* phase unless you include them in your original config.xml file and/or config.sh script. Please also note that the image description has been copied into the new root below the directory <new-root>/image. Any subsequent create step will read the image description information from the new root tree and not from the original image description location. According to this if you need to change the image description data after the prepare call has finished you need to change it inside the new root tree as well as in your original description directory to prevent loosing the change when your root tree will be removed later for some reason.

After the prepare step has finished successfully a subsequent building of an image file or, in KIWI speak, a new packed image follows. The building of an image requires a successfully prepared new root tree in the first place. Using this tree multiple image types can be created. So to speak it's possible to create a VMware image and a Xen image from the same prepared root tree. The create step executes the following major stages:

Executing User Defined Script images.sh

At the beginning of the creation stage the optional script named images.sh is called. This script has no distinctive use case like config.sh but is most often used to remove packages which were pulled in by a dependency but are not really required for the later use of the operating system. For a detailed description what functions are already available to images.sh please refer to the KIWI::images.sh manual page

Creating Requested Image Type

What image type(s) a kiwi image supports depends on what types has been setup in the main image description file config.xml. At least one type must be setup. The following picture shows what image types are currently supported by KIWI:




Figure 2.1: Image Types

Detailed information including a step by step guidance how to call kiwi and how to make use of the result image can be found in the image type specific sections later in this document.

2.1 Boot Process

Todays Linux systems are using a special boot image to control the boot process. This boot image is called initrd. The linux kernel loads this initial ramdisk which is a compressed cpio archive into RAM and calls init or if present the program named linuxrc. The KIWI image system also takes care for the creation of this boot image. Each image type has it's own special boot code and shares the common parts in a set of module functions. The image descriptions for the boot images are provided by KIWI and thus the user has in almost all cases no need to take care for the boot image.




Figure 2.2: Boot process

Furthermore KIWI automatically creates this boot image along with the requested image type. It does that by calling itself in a prepare and create call. There is no difference in terms of the description of such a boot image compared to the system image description. The system image description is the one the user creates and this image represents the later operating system whereas the boot image only lives temporarly in RAM as long as the system image will be activated. The boot image descriptions are stores in /usr/share/kiwi/image/*boot and can be build in the same way as the system image. The boot image without a corresponding system image doesn't make sense though.

2.2 Boot Parameters

When booting an image created by KIWI using one of the provided boot images there are some useful kernel parameters mainly meant for debugging purposes. Please note the following parameters are only useful if the KIWI initrd is used. In

case of any other initrd code written by yourself or simply because KIWI replaced itself with the distribution specfic mkinitrd tool the parameters might not have any effect.

• kiwidebug=1

If the boot process encounters a fatal error the system normally reacts with a reboot after 120 secconds. This so called exception can be influenced by the kiwidebug parameter. If set to 1 the system will stop and provide the user with a shell prompt instead of a reboot. Within that shell some basic standard commands are available which could help to find the cause of the problem

• kiwistderr=/dev/...

While the system boots KIWI writes messages to tty1 and tty3. The tty1 messages are highlevel information whereas the tty3 messages represents the shell debug output and any error messages from the commands called. With the kiwistderr parameter one can combine both message sets and specify where to write them to. It's very common to set /dev/console as possible alternative to the default logging behaviour

2.3 Common and Distribution Specific Code

KIWI has been developed to be usable for any Linux distribution. By design of a Linux distribution there are differences between each of them. With KIWI we provide on one hand the code which is common to all Linux distributions according to standards and on the other hand there is also code where we have to distinguish between the distribution type.

In case of such specific tasks which are almost all in the area of booting, KIWI provides a set of functions which all have to come with a distribution prefix. As this project uses SUSE Linux as base distribution all required distribution specific tasks has been implemented for SUSE and could be missing for other distributions. The existing implementation for SUSE turns out to be adapted to other distributions very easily though.

A look into the code therefore will show you functions which are prefixed by "suse" as well as scripts whose names starts with "suse-". At any time you see such a script or function you can be assured that this is something distribution specific and needs to be adapted if you plan to use KIWI with another distribution than SUSE. For example, the boot workflow is controlled by a program called linuxrc which is in KIWI a script represented by suse-linuxrc. Another example would be the function called suseStripKernel which is able to remove everything but a specified list of kernel drivers from the SUSE kernel.

The prefixed implementation allows us to integrate all the distribution specific tasks into one project but this of course requires the help and knowledge of the people who are familiar with their preferred Linux distribution.

3 KIWI Image Description

Contents

3.1	The co	onfig.xml File	15
	3.1.1	<pre><image/> Element</pre>	15
	3.1.2	<pre><description> Element</description></pre>	16
	3.1.3	<pre><pre>files> Element</pre></pre>	16
	3.1.4	<pre><pre><pre><pre>ferences> Element</pre></pre></pre></pre>	16
	3.1.5	<pre><users> Element</users></pre>	27
	3.1.6	<pre><drivers> Element</drivers></pre>	28
	3.1.7	<pre><repository> Element</repository></pre>	28
	3.1.8	<pre><packages> Element</packages></pre>	30

In order to be able to create an image with KIWI a so called image description must be created. The image description is represented by a directory which has to contain at least one file named config.xml or alternatively *.kiwi. A good start for such a description can be found in the examples provided in /usr/share/doc/packages/kiwi/examples.




Figure 3.1: Image description directory

The following additional information is optional for the process of building an image but most often mandatory for the functionality of the later operating system.

images.sh
 Optional configuration script while creating the packed image. This script is called at the beginning of the image creation process. It is designed to clean-up the image system. Affected are all the programs and files only needed while the unpacked image exists.

• config.sh

Optional configuration script while creating the unpacked image. This script is called at the end of the installation but *before* the package scripts have run. It is designed to configure the image system, such as the activation or deactivation of certain services (insserv). The call is not made until after the switch to the image has been made with *chroot*.

• root/

Subdirectory that contains special files, directories, and scripts for adapting the image environment **after** the installation of all the image packages. The entire directory is copied into the root of the image tree using cp -a.

• config-yast-firstboot.xml

Configuration file for the control of the yast2 firstboot service. Similar to the autoyast approach yast also provides a boot time service called firstboot. Unfortunately there is no GUI available to setup the firstboot but a good documentation in /usr/share/doc/packages/yast2-firstboot. Once you have created such a firstboot file in your image description directory, KIWI will process on the file and setup your image as follows:

- 1. KIWI enables the firstboot service.
- 2. While booting the image, YaST is started in firstboot mode.
- 3. The firstboot service handles the instructions listed in the file config-yast-firstboot.xml.
- 4. If the process finished successfully, the environment is cleaned and first-boot won't be called at next reboot.

• config-yast-autoyast.xml

Configuration file which has been created by autoyast. To be able to create such an autoyast profile you should first call:

1 yast2 autoyast

Once you have saved the information from the autoyast UI as config-yast-autoyast. xml file in your image description directory KIWI will process on the file and setup your image as follows:

- 1. While booting the image YaST is started in autoyast mode automatically
- 2. The autoyast description is parsed and the instructions are handled by YaST. In other words the *system configuration* is performed
- 3. If the process finished successfully the environment is cleaned and autoyast won't be called at next reboot.

• config-cdroot.tgz

Archive which is used for ISO images only. The data in the archive is uncompressed and stored in the CD/DVD root directory. This archive can be used, for example, to integrate a license file or readme information directly readable from the CD or DVD.

- config-cdroot.sh
 Along with the config-cdroot.tgz one can provide a script which allows to manipulate the extracted data.
- config/
 Optional Subdirectory that contains Bash scripts that are called after the
 installation of all the image packages, primarily in order to remove the parts
 of a package that are not needed for the operating system. The name of the
 Bash script must resemble the package name listed in the config.xml.

3.1 The config.xml File

The mandatory image definition file is divided into different sections which describes information like the image name and type as well as the packages and patterns the image should consist of.

The following information explains the basic structure of the XML document. When KIWI is called, the XML structure is validated by a RELAX NG based schema. For details on attributes and values please refer to the schema documentation file at /usr/share/doc/packages/kiwi/kiwi.rng.html.

3.1.1 <image> Element

```
1  <image schemaversion="3.5" name="iname"
2  displayname="text"
3  inherit="path" kiwirevision="number"
4  id="10_digit_number">
5  <!-- ... ->
6  </image>
```

The image definition starts with an <image> tag and requires the schema format at version 2.0. The attribute name specifies the name of the image which is also used for the filenames created by KIWI. Because we don't want spaces in filenames the name attribute must not have any spaces in its name.

The following optional attributes can be inserted in the <image> tag:

- displayname allows setup of the boot menu title for isolinux and grub. So you can have *suse-SLED-foo* as the image name but something like *my cool Image* as the boot display name.
- inherit inherits the packages information from another image description
- kiwirevision
 specifies a KIWI SVN revision number which is known to build a working image from this description. If the KIWI SVN revision is less than the specified value, the process will exit. The currently used SVN revision can be queried by calling kiwi --version.

 id sets an identification number which appears as file /etc/ImageID within the image.

Inside the image section the following mandatory and optional subelements exists. The simplest image description must define the elements <description>, cpreferences>, <repository> and <packages> (at least one of type="bootstrap").

3.1.2 <description> Element

The mandatory description section contains information about the creator of this image description. The attribute type could be either of the value system which indicates this is a system image description or at value boot for boot image descriptions.

3.1.3 <profiles> Element

```
1 cprofiles>
2 cprofile name="name" description="text"/>
3 <!-- ... -->
4
```

The optional profiles section lets you maintain one image description while allowing for variation of the sections packages and drivers that are included. A separate profile element must be specified for each variation. The profile child element, which has name and description attributes, specifies an alias name used to mark sections as belonging to a profile, and a short description explaining what this profile does.

To mark a set of packages/drivers as belonging to a profile, simply annotate them with the profiles attribute. It is also possible to mark sections as belonging to multiple profiles by separating the names in the profiles attribute with a comma. If a packages/drivers tag does not have a profiles attribute, it is assumed to be present for all profiles.

3.1.4 ces> Element

7 </preferences>

The mandatory preferences section contains information about the supported image type(s), the used packagemanager, the version of this image, and optional attributes. The image version must be a three-part version number of the format: **Major.Minor.Release**. In case of changes to the image description the following rules should apply:

- For smaller image modifications that do not add or remove any new packages, only the release number is incremented. The config.xml file remains unchanged.
- For image changes that involve the addition or removal of packages the minor number is incremented and the release number is reset.
- For image changes that change the size of the image file the major number is incremented.

By default KIWI use the smart packagemanager but it is also possible to use the SUSE packagemanager called zypper.

In general the specification of one spreferences> section is sufficient. However, it's possible to specify multiple <preferences> sections and distinquish between the sections via the profiles attribute. Data may also be shared between different profiles. Using profiles it is possible to, for example, configure specific preferences for OEM image generation. Activation of a given spreferences> during image generation is triggered by the use of the --add-profile command line argument. For each <preferences> block at least one type element must be defined. It is possible to specify multiple <type> elements in any spreferences> block. To set a given <type> description as the default image use the boolean attribute primary and set its value to true. The image type to be created is determined by the value of the image attribute. The following list describes the supported types and possible values of the image attribute:

• image="cpio"

Use the cpio image type to specify the generation os a boot image (intrd). When generating a boot image it is possible to specify a specific boot profile and boot kernel using the optional bootprofile="default" and bootkernel ="std" attributes.

A boot image should group the various supported kernels into profiles. If the user chooses not to use the profiles supplied by KIWI, it is required that one profile named std be created. This profile will be used if no other bootkernel is specified. Further it is required to create a profile named default. This profile is used when no bootprofile is specified.

It is recommended that special configurations that omit drivers, use special drivers and/or special packages be specified as profiles.

The bootprofile and bootkernel attribute are respected within the definition of a system image. Us the attribute and value type="system" of the <description> element to specify the creation of a system image. The val-

ues of the bootprofile and bootkernel attributes are used by KIWI when generating the boot image.

• image="ec2"

Setting the image attribute value to ec2 causes the generation of an Amazon Machine Image (AMI) for the AWS (Amazon Web Services) Elastic Compute Cloud (EC2). The AMI is an image comparable to a VMware or Xen guest image. It can be transferred to the AWS Simple Storage Service and used within the AWS infrastructure. Configuration of the AMI is accomplished with the optional ec2config element, specified as a child of the <type> element.

• image="iso"

Specify the key-value pair image="iso" to generate a live system suitable for deployment on optical media (CD or DVD). Use the boot="isoboot/suse-*" attribute when generating this image type to select the apropriate boot image for optical media. In addition the optional flags attribute may be set to the following values with the effects described below:

- clic: Creates a fuse based compressed read-only filesystem which allows write operations into a cow file.
- compressed: Compressed filesystem with squashfs and use a link list to mount the system read-write. An additional split section controls the read-write information.
- unified: Compressed filesystem with squashfs mounted with an aufs based overlay mount to allow read-write access.

If the flags attribute is not used the filesystem will not be compressed and no union filesystem is used. In this case it is recommended to specify a split section as a child of this type element. The specification of a split block is also recommended when flags=compressed is used.

• image="oem"

Use this type to create a virtual disk system suitable in a preload setting. In addition specify the attributes filesystem, and boot="oemboot/suse-*" to control the filesystem used for the virtual and to specify the proper boot image. Using the optional format attribute and setting the value to iso or usb will create self installing images suitable for optical media or a USB stick, respectively. Booting from the media will deploy the OEM preload image onto the selected storage device of the system. It is also possible to configure the system to use logical volumes. Use the optional lvm attribute and specify the logical volume configuration with the lvmvolumes child element. The default volume group name is kiwiVG. Further configuration of the image is performed using the appropriate *config child block.

• image="pxe"

Creating a network boot image is supported by KIWI with the image="pxe" type. When specifying the creation of a netwoork boot image use the filesystem and boot="netboot/suse-*" attributes to specify the filesystem of the image and the proper boot image. To compress the image file set the compressed boolean attribute to true. This setting will compress the image file and has

no influence on the filesystem used within the image. The compression is often use to support better transfer times when the pxe image is pushed to the boot server over a network connection. The pxe image layout is controlled by using the pxedeploy child element.

• image="split"

The split image support allows the creation of an image as split files. Using this technique one can assign different filesystems and different read-write properties to the different sections of the image. The oem, pxe, usb, and vmx types can be created as a split system image. Use the boot="oem|netboot|usb|vmx/suse-*" attribute to select the underlying type of the split image. The attributes fsreadwrite, fsreadonly are used to controll the read-write properties of the filesystem specified as the attributes value. Use the appropriate *config child block to specify the properties of the underlying image. For example when building a OEM based split image use the <oemconfig> child section.

• image="usb"

Use the usb value to create a USB stick image. Set the filesystem attribute to the desired supported filesystem for the image and use the boot="usbboot/suse-*" attribute to select the USB boot image for the system. For a USB image you may also select GRUB or Syslinux as a bootloader by setting the optional bootloader attribute to grub ot syslinux, respectively. The USB image may also be created with LVM support. The same rules as indicated for the OEM image apply.

• image="vmx"

Creation of a virtual disk system is enabled with the vmx value of the image attribute. Set the filesystem of the virtual disk with the filesystem attribute and select the appropriate boot image by setting boot="vmxboot/suse-*". The optional format attribute is used to specify one of the virtualization formats supported by qemu, such as vmdk (also the VMware format) or qcow2. For the virtual disk image the optional vga attribute may be used to configure the kernel framebuffer device. Acceptable values can be found in the Linux kernel documentation for the framebuffer device (Documentation/fb/vesafb.txt). KIWI also supports the selection of the booloader for the virtual disk according to the rules indicated for the USB system. Last but not least the virtual disk system may also be created with a LVM based layout by using the lvm attribute. The previously indicated rules apply. Use the machine child element to specify appropriate configuration of the virtual disk system.

• image="xen"

Use this type to create a Xen para-virtual guest image. The filesystem and boot="xenboot/suse-*" attributes specify the filesystem type used and select the proper boot image, respectively. Use the machine child element to specify configuration options of the Xen guest image.

All of the mentioned types can specify the boot attribute which tells KIWI to call itself to build the requested boot image (initrd). It is possible to tell KIWI to

check for an already built boot image which is a so called *prebuilt boot image*. To activate searching for an appropriate prebuilt boot image the type section also provides the attribute checkprebuilt="true|false". If specified KIWI will search for a prebuilt boot image in a directory named /usr/share/kiwi/image/*boot/*-prebuilt. Example: If the boot attribute was set to isoboot/suse-10.3 and checkprebuilt is set to true KIWI will search the prebuilt boot image in /usr/share/kiwi/image/isoboot/suse-10.3-prebuilt. The directory KIWI searches for the prebuilt boot images can also be specified at the commandline with the --prebuiltbootimage parameter.

Within the preferences section there are the following optional attributes:

- rpm-check-signatures Specifies whether RPM should check the package signature or not
- rpm-excludedocs Specifies whether RPM should skip installing package documentation
- rpm-force
 Specifies whether RPM should be called with --force
- keytable
 Specifies the name of the console keymap to use. The value corresponds to
 a map file in /usr/share/kbd/keymaps. The KEYTABLE variable in /etc/
 sysconfig/keyboard file is set according to the keyboard mapping.
- timezone
 Specifies the time zone. Available time zones are located in the /usr/share/
 zoneinfo directory. Specify the attribute value relative to /usr/share/zoneinfo.
 For example, specify Europe/Berlin for /usr/share/zoneinfo/Europe/Berlin.
 KIWI uses this value to configure the timezone in /etc/localtime for the image
- locale

 Specifies the name of the UTF-8 locale to use, which defines the contents of the RC_LANG system environment variable in /etc/sysconfig/language. Please note only UTF-8 locales are supported here which also means that the encoding must *not* be part of the locale information. The KIWI schema validates the locale string according to the following pattern:

 [a-z]{2}_[A-Z]{2}(, [a-z]{2}_[A-Z]{2})*. This means you have to speci-
- boot-theme
 Specifies the name of the gfxboot and bootsplash theme to use

fiy the locale like the following example: en_US or en_US,de_DE

- defaultdestination
 Used if the --destdir option is not specified when calling KIWI
- defaultroot
 Used if the option --root is not specified when calling KIWI
- defaultbaseroot
 Used if the option --base-root is not specified when calling KIWI. It's possible to prepare and create an image using a predefined non empty root

directory as base information. This could speedup the build process a lot if the base root path already contains most of the image data.

• kernelcmdline

Specifies additional kernel parameters. The following example disables kernel messages: kernelcmdline="quiet"

The <type> element may contain child elements to provide specific configuration information for the given type. The following lists the supported child elements:

• ec2config

The optional ec2config block is used to specify information relevant only to AWS EC2 images. The following information can be provided:

```
1  <ec2config>
2   <ec2accountnr>
3     Your AWS account number
4     </ec2accountnr>
5     <ec2certfile>
6     Path to the AWS cert-*.pem file
7     </ec2certfile>
8     <ec2privatekeyfile>
9     Path to the AWS pk-*.pem file
10     </ec2privatekeyfile>
11     </ec2config>
```

• lvmvolumes

Using the optional lvmvolumes section it possible to create a LVM (Logical Volume Management) based storage layout. By default the volume group is named kiwiVG. It is possible to change the name of the group by setting the lvmgroup attribute to the desired name. Individual volumes within the volume group are specified using the volume element.

The following example shows the creation of a volume named usr and a volume named var inside the volume group systemVG.

With the optional freespace attribute it is possible to add space to the volume. If the freespace attribute is not set the created volume will be 80 % to 90 % full. Using the optional size attribute the absolute size of the given volume is specified. The size attribute takes precedence over the freespace attribute. Should the specified size be too small the value will be ignored and a volume with approximately 80 % to 90 % fill will be created.

• oemconfig By default the oemboot process will create/modify a swap, /home and / partition. It is possible to influence the behavior by the oem-* elements explained below. KIWI uses this information to create the file /config.

oempartition as part of the automatically created oemboot boot image. The format of the file is a simple key=value format and created by the KIWIConfig.sh function named baseSetupOEMPartition().

- - <oem-boot-title>text</oem-boot-title> By default the string OEM will be used as the boot manager menu entry when KIWI creates the grub configuration during deployment. The oem-boot-title element allows you to set a custom name for the grub menu entry. This value is represented by the OEM_BOOT_TITLE variable in config.oempartition.
 - <oem-home>true | false</oem-home»
 Specify if a partition for the home directory should be created. Creation of a home partition is the default behavior. This value is represented by the OEM_WITHOUTHOME variable in config.oempartition.
 - <oem-kiwi-initrd>true | false</oem-kiwi-initrd>
 If this element is set to true (default value is false) the oemboot boot image (initrd) will not be replaced by the system (mkinitrd) created initrd. This option is useful when the system is installed on removable storage such as a USB stick or a portable external drive. For movable devices it is potentially necessary to detect the storage location during every boot. This detection process is part of the oemboot boot image. This value is represented by the OEM_KIWI_INITRD variable in config. oempartition.
 - <oem-reboot>true|false</oem-reboot> Specify if the system is to be rebooted after the oem image has been deployed to the designated storage device (default value is false). This value is represented by the OEM_REBOOT variable in config.oempartition.
 - <oem-recovery>true|false</oem-recovery>
 If this element is set to true (default value is false), KIWI will create a recovery archivefrom the prepared root tree. The archive will appear as /recovery.tar.bz2 in the image file. During first boot of the image a single recovery partition will be created and the recovery archive will be moved to the recovery partition. An additional boot menu entry is created that when selected restores the original root tree on the system. The user information on the /home partition or in the /home directory is not affected by the recovery process. This value is represented by the OEM_RECOVERY variable in config.oempartition.
 - <oem-recoveryID>partition-id</oem-recoveryID> Specify the partition type for the recovery partition. The default is to create a Linux partition (id = 83). This value is represented by the OEM_RECOVERY_ID variable in config.oempartition.

- <oem-swap>true | false</oem-swap>
 Specify if a sawp partition should be create. The creation of a swap partition is the default behavior. This value is represented by the OEM_WITHOUTSWAP variable in config.oempartition.
- <oem-swapsize>number in MB</oem-swapsize> Set the size of the swap partition. If a swpa partition is to be created and the size of the swap partition is not specified with this optional element, KIWI will calculate the size of the swpar partition and create a swap partition equal to two times the RAM installed on the system at initial boot time. This value is represented by the OEM_SWAPSIZE variable in config.oempartition
- <oem-systemsize>number in MB</oem-systemsize>
 Set the size of the root partition. This value is represented by the variable OEM_SYSTEMSIZE in config.oempartition

• pxedeploy

Information contained in the optional pxedeploy section is only considered if the image attribute of the type element is set to pxe. In order to use a PXE image it is necessary to create a network boot infrastructure. Creation of the network boot infrastructure is simplified by the KIWI provided package kiwi-pxeboot. This package configures the basic PXE boot environment as expected by KIWI pxe images. The kiwi-pxeboot package creates a directory structure in /srv/tftpboot. Files created by the KIWI create step need to be copied to the /srv/tftpboot directory structure. For additional details about the PXE image please refere to the PXE Image chapter later in this document.

In addition to the image files it is necessary that information be provided about the client setup. This information, such as the image to be used or the partitioning, is contained in a file with the name config.<MAC-Address> in the directory /srv/tftpboot/KIWI. The content of this file is created automatically by KIWI if the pexedeploy section is provided in the image description. A pxedeploy section is outlined below:

```
<pxedeploy server="IP" blocksize="4096">
     <timeout>seconds</timeout>
     <kernel>kernel-file</kernel>
     <initrd>initrd-file</initrd>
     <partitions device="/dev/sda">
       <partition type="swap" number="1" size="MB"/>
       <partition type="L" number="2" size="MB"</pre>
         mountpoint="/" target="true"/>
       <partition type="fd" number="3"/>
     </partitions>
10
     <union ro="dev" rw="dev" type="aufs|clicfs|unionfs"/>
11
     <configuration source="/KIWI/../file" dest="/../file"</pre>
12
                    arch="..."/>
     <configuration .../>
  </pxedeploy>
```

- The server attribute is used to specify the IP address of the PXE server. The blocksize attributes specifies the blocksize for the image download. Other protocols are supported by KIWI but require the kiwiserver and kiwiservertype kernel parameters to be set when the client boots.
- The value of the optional timeout element specifies the grub timeout in seconds to be used when the KIWI initrd configures and installs the grub boot loader on the client machine after the first deployment to allow standalone boot.
- Passing kernel parameters is possible with the use of the optional kernelcmdline attribute in the <type> section. The value of this attribute is a
 string specifying the settings to be passed to the kernel by the grub bootloader. The KIWI initrd includes these kernel options when installing
 grub for standalone boot
- The optional kernel and initrd elements are used to specify the file names for the kernel and initrd on the boot server respectively. When using a special boot method not supported by the distribution's standard mkinitrd, it is imperative that the KIWI initrd remains on the PXE server and also be used for local boot. If the configured image uses the split type or the pexedeploy section includes any union information the kernel and initrd elements must be used.
- The partitions section is required if the system image is to be installed on a disk or other permanent storage device. Each partition is specified with one partition child element. The mandatory type attribute specifies the partition type. The possible values are the sfdisk supported types, use the following command to obtain a list of supported values:

```
sfdisk --list-type
```

The required number attribute provides the the number of the partition to be created. The size of the partition may be specified with the optional size attribute. The optional mountpoint attribute provides the value for the mount point of the partition. The optional boolean target attribute identifies the partion as the system image target partition. KIWI always generates the swap partition as the first partition of the netboot boot image. By default the second partition is used for the system image. Use the boolean target attribute to change this behavior. Providing the value image for the size attribute triggers KIWI into calculating the required size for this partition. The calculated size is sufficient for the created image.

- If the system image is based on a read-only filesystem such as squashfs and should be mounted in read-write mode use the optional union element. The type attribute is used to specify one of the supported overlay filesystem (aufs, clicfs, or unionfs). Use the ro attribute to point to the read only device and the rw attribute to point to the read-write device.
- The optional configuration element is used to integrate a network client's configuration files that are stored on the server. The source attribute

specifies the path on the server for the file to be downloaded. The dest attribute specifies destination of the downloaded file on the network client starting at the root (/) of the filesystem. Multiple configuration elements may be specified such that multiple files can be transferred to the network client. In addition configuration files can be bound to a specific client architecture by setting the optional arch attribute. To specify multiple architectures use a comma separated string.

• size

Use the size element to specify the image size in Megabytes or Gigabytes. The unit attribute specifies whether the given value will be interpreted as Megabytes (unit="M") or Gigabytes (unit="G"). The optional boolean attribute additive specifies whether or not the given size should be added to the size of the generated image or not.

In the event of a size specification that is too small for the generated image, KIWI will expand the size automatically unless the image size exceeds the specified size by 100 MB or more. In this case KIWI will generate an error and exit.

Should the given size exceed the necessary size for the image KIWI will not alter the image size as the free space might be required for proper execution of components within the image.

If the size element is not used KIWI will create an image with containing approxiamtely 30% free space.

```
1 <size unit="M">1000</size>
```

• split

For images of type split or iso the information provided in the optional split section is is considered if the compressed attribute is is set to true. With the configuration in this block it is possible to determine which files are writable and whether these files should be persentently writable or temporarily. Note that for ISO images only temporary write access is possible.

When processing the provided configuration KIWI distinguishes between directories and files. For example, providing /etc as the value of the name attribute indicates that the /etc directory should be writable. However, this does not include any of the files or sub-directories within /etc. The content of /etc is populated as symbolic links to the read-only files. The advantage of setting only a directory to read-write access is that any newly created files will be stored on the disk instead of in tmpfs. Creating read-write access to a directory and it's files requires two specifications as showb below.

Use the except element to specify exceptions to previously configured rules.

• machine

The optional machine section serves to specify information about a VM guest machine. Using the data provided in this section, KIWI will create a guest configuration file required to run the image on the target machine.

If the target is a VMware virtual machine indicated by the format attribute set to vmdk, KIWI creates a VMware configuration file. If the target is a Xen virtual machine indicated by the domain attribute in the machine section KIWI will create a Xen guest config file.

The sample block below shows the general outline of the information that can be specified to generate the configuration file

- arch

The virtualized architecture. Supported values are ix86 or x86_64. The default value is ix86.

- memory

The mandatory memory attribute specifies how much memory in MB should be allocated for the virtual machine

- HWversion

The VMware hardware version number, the default value is 3.

- guestOS

The guestOS identifier. For the ix86 architecture the default value is suse and for the x86_64 architecture suse-64 is the default. At this point only the SUSE and SLES guestOS types are supported.

- domain

The Xen domain setup. This could be either a dom0 which is the host

machine hosting the guests and therefore doesn't require a configuration file, or it could be set to domU which indicates this is a guest and also requires a guest configuration which is created by KIWI.

The following information can be provided to setup the virtual main storage device and CD/DVD drive connection:

- controller
 - Supported values for the mandatory controller attribute are ide and scsi.
- id

The mandatory id attribute specifies the disk id. If only one disk is set the id value should be set to 0.

- device

The device attribute specifies the disk that should appear in the para virtual instance. Therefore only relevant for Xen

The following information can be provided to setup the virtual network interface:

- driver

The mandatory driver attribute specifies the driver to be used for the virtual network card. The supported values are e100, vlance, and vmxnet. If the vmxnet driver is specified the vmware tools must be installed in the image.

- interface

The mandatory interface attribute specifies the interface number. If only one interface is set the value should be set to 0.

- mode

The network mode used to communicate outside the VM. In many cases the bridged mode is used.

3.1.5 <users> Element

The optional users element lists the users belonging to the group specified with the group attribute. At least one user child element must be specified as part of the users element. Multiple users elements may be specified.

The attributes home, id, name, pwd, realname, and shell specify the created users home directory, the user name, the user's password, the user's real name, and the user's login shell, respectively. By default the value of the password attribute

is expected to be an encrypted string. An encrypted password can be created using kiwi --createpassword. It is also possible to specify the password as a non encrypted string by using the pwdformat attribute and setting it's value to "plain". KIWI will then encrypt the password prior to the user being added to the system.

All specified users and groups will be created if they do not already exist. By default the defined users will be part of the group specified with the group attribute of the users element and the default group called "users". If it is desired to have the specified users to only be part of the given group it is necessary to specify the id attribute. It is recommended to use a group id greater than 100.

3.1.6 <drivers> Element

The optional drivers element is only useful for boot images (initrd). As a boot image doesn't need to contain the complete kernel one can save a lot of space if only the required drivers are part of the image. Therefore the drivers section exists. If present only the drivers which matches the file names or glob patterns will be included into the boot image. The type attribute specifies one of the following driver types:

- drivers
 Each file is specified relative to the /lib/modules/<Version>/kernel directory.
- netdrivers
 Each file is specified relative to the /lib/modules/<Version>/kernel/drivers
 directory.
- scsidrivers
 Each file is specified relative to the /lib/modules/<Version>/kernel/drivers
- usbdrivers
 Each file is specified relative to the /lib/modules/<Version>/kernel/drivers
 directory.

According to the driver type the specified files are searched in the corresponding directory. The information about the drivernames is provided as environment variable named like the value of the type attribute and is processed by the function <code>suseStripKernel</code>. According to this along with a boot image description a script called <code>images.sh</code> must exist which calls this function in order to allow the driver information to have any effect.

3.1.7 <repository> Element

```
1 <repository type="type" status="replaceable"
2 alias="name" priority="number">
```

- 3 <source path="URL"/>
- 4 </repository>

The mandatory repository element specifies the source URL and type used by the package manager. The type attribute specifies the repository type which must be supported by the package manager. At the moment KIWI supports the package managers smart and zypper whereas smart has support for more repository types compared to zypper. Therefore the possible values for the type attribute has beend copied from smart. The following table shows the possible repo types:

Туре	smart Support	zypper Support
apt-deb	yes	no
apt-rpm	yes	no
deb-dir	yes	no
mirrors	yes	no
red-carpet	yes	yes
rpm-dir	yes	yes
rpm-md	yes	yes
slack-site	yes	no
up2date-mirrors	yes	no
urpmi	yes	no
yast2	yes	yes

Within the repository section there are the following optional attributes:

- status="replaceable"
 - This attribute makes only sense for boot image descriptions. It indicates that the repository is allowed to become replaced by the repositories defined in the system image descriptions. Because KIWI automatically builds the boot image if required it should create that image from the same repositories which are used to build the system image to make sure both fit together. Therefore it is required to allow the repository to become overwritten which is indicated by the status attribute.
- alias="name"
 Specifies an alternative name used to identify the source channel. If not set the source attribute value is used and builds the alias name by replacing each "/" with a "_". An alias name should be set if the source argument doesn't really explain what this repository contains
- priority="number"

 Specifies the repository priority assigned to all packages available in this repository. For smart the following applies: If the exact same package is available in more than one channel, the repository with the *highest* priority number is used. The value 0 means "no priority is set". For zypper the following applies: If the exact same package is available in more than one channel, the repository with the *lowest* priority number is used. The value 99 means "no priority is set".

The source child element contains the path attribute, which specifies the location (URL) of the repository. The path specification can be any of the following, and can include the %arch macro which is expanded to the architecture of the image building host.

- this://<path>
 A relative path name, which is relative to the image description directory being referenced.
- iso://<path/to/isofile>
 A path to a local .iso file which is then loopback mounted and used as a local path based repository. Alternatively one can do the loop mount himself and point a standard local path to the mounted directory
- http://<url>A http protocol based network location
- https://<url>A https protocol based network location
- ftp://<url>A ftp protocol based network location
- opensuse://<Project-Name>
 A special http based network location which is created from the given open-SUSE buildservice project name. The result is pointing to an rpm-md repository on the openSUSE buildservice. For example: path="opensuse://openSUSE: 10.3/standard"
- file:///local/path
 A local path which should be an absolute path description. The file://
 prefix is optional and could also be omitted.
- obs://\$dir1/\$dir2

 A special buildservice path whereas \$dir1 and \$dir2 represents the build-service project location. If this type is used as part of a boot attribute KIWI evaluates it to this://images/\$dir1/\$dir2 and if used as part of a repository source path attribute it evaluates to this://repos/\$dir1/\$dir2

Multiple repository sections are allowed and combined by the used package manager. By default the package manager will always use the latest packages available.

3.1.8 <packages> Element

The mandatory packages element specifies the list of packages (element <package>) and patterns (element <ppensusePattern>) to be used with the image. The value of the type attribute specifies how the packages and patterns listed are handled, supported values are as follows:

• bootstrap

Bootstrap packages, list of packages for the new operating system root tree. The packages list the required components to support a chroot environment in the new system root tree, such a glibc.

• delete

Delete packages, list of packages to be deleted from the image being created.

When using the delete type only <package> elements are considered, all other specifications such as <persecond specifications such as <persecond specifications are ignored. The given package names are stored in the \$delete environment variable of the /.profile file created by KIWI. The list of package names is returned by the baseGet-PackagesForDeletion() function. This list can then be used to delete the packages ignoring requirements or dependencies. This can be accomplished in the config.sh or images.sh script with the following code snippet:

```
rpm -e --nodeps --noscripts \
2 $(rpm -q 'baseGetPackagesForDeletion' | grep -v "is⊔not⊔ installed")
```

Note, that the delete value is indiscriminate of the image type being built.

image

Image packages, list of packages to be installed in the image.

iso

Image packages, a list of additional packages to be installed when building an ISO image.

• oem

Image packages, a list of additional packages to be installed when building an OEM image.

pxe

Image packages, a list of additional packages to be installed when building an PXE image.

usb

Image packages, a list of additional packages to be installed when building a USB image.

- vmx
 Image packages, a list of additional packages to be installed when building a vmx virtual image of any format.
- xen
 Image packages, a list of additional packages to be installed when building a Xen host or guest.

Using Patterns

Using a pattern name enhances the package list with a number of additional packages belonging to this pattern. Support for patterns is SUSE-specific, and available with openSUSE 10.1 or later. The optional patternType and patternPackageType attributes specify which pattern references or packages should be used in a given pattern. The values of these attributes are only evaluated, if the KIWI pattern solver is used. If the new (up to SUSE 11.0) satsolver pattern solver is used these values are ignored because the satsolver can't handle that at the moment. Allowed values for the pattern* attributes are:

- onlyRequired Incorporates only patterns and packages that are required by the given pattern
- plusSuggested
 Incorporates patterns and packages that are required and suggested by the given pattern
- plusRecommended Incorporates patterns and packages that are required and recommended by the given pattern.

By default, only required patterns and packages are used. The result list of packages is solved into a clean conflict free list of packages by the package manager. This for example means that including a suggested package may include required and recommended packages as well according to the dependencies. If a pattern contains unwanted packages, you can use the ignore element to specify an ignore list, with the name attribute containing the package name. Please note that you can't ignore a package if it is required by a package dependency of another package in your list. The packagemanager will automatically pull in the package even if you have ignored it.

Architecture Restrictions

To restrict a package to a specific architecture, use the arch attribute to specify a comma separated list of allowed architectures. Such a package is only installed if the build systems architecture (uname -m) matches one of the specified values of the arch attribute.

Image Type Specific Packages

If a package is only required for a specific type of image and replaces another package you can use the replaces attribute to tell KIWI to install the package by replacing another one. For example you can specify the kernel package in the type ="image" section as

```
1 <package name="kernel-default" replaces="kernel-xen"/>
and in the type="xen" section as
1 <package name="kernel-xen" replaces="kernel-default"/>
```

The result is the xen kernel if you request a xen image and the default kernel in any other case.

Packages to Become Included Into the Boot Image

The optional attributes bootinclude and bootdelete can be used to mark a package inside the system image description to become part of the corresponding boot image (initrd). This feature is most often used to specify bootsplash and/or graphics boot related packages inside the system image description but they are required to be part of the boot image as the data is used at boot time of the image. If the bootdelete attribute is specified along with the bootinclude attribute this means that the selected package will be marked as a "to become deleted" package and is removed by the contents of the images. sh script of the corresponding boot image description

Data not Available as Packages to Become Included

With the optional archive element it's possible to include any kind of data into the image. The archive elements expects the name of a tarball which must exist as part of the system image description. KIWI then picks up the tarball and installs it into the image. If the bootinclude attribute is set along with the archive element the data will also become installed into the boot image.

4 Creating Appliances with KIWI

Contents

4.1	History	35
4.2	The KIWI Model	35

4.1 History

Traditionally, many computing functions were written as software applications running on top of a general-purpose operating system. The consumer (whether home computer user or the IT department of a company) bought a computer, installed the operating system or configured a pre-installed operating system, and then installed one or more applications on top of the operating system. An e-mail server was just an e-mail application running on top of Linux, Unix, Microsoft Windows, or some other operating system, on a computer that was not designed specifically for that application.

4.2 The KIWI Model

With KIWI we started to use a different model. Instead of installing firewall software on top of a general purpose computer/operating system, the designers/engineers built images that are designed specifically for the task. These are so called appliances. When building appliances with KIWI the following proceeding has proven to work reliably. Nevertheless the following is just a recommendation and can be adapted to special needs and environments.

- 1. First you should choose an appropriate image description template from the provided KIWI examples and add/adapt repository and/or package names according to the distribution you want to build an image for
- 2. Allow the image to create an in-place git repository to allow tracking of non binary changes. This is done by adding the following into your config.sh script.

baseSetupPlainTextGITRepository

3. Prepare the preliminary version of your new appliance by calling kiwi --prepare... and refer to chapter 9 (USB image - Live-Stick System) for details.

- 4. Decide for a testing environment. In my opinion a real hardware based test machine which allows to boot from USB is a good and fast approach. According to this make sure you have a usb type in your config.xml
 - 1 <type filesystem="ext3_boot="usbboot/suse-...">usb</type>
- 5. Create the preliminary live stick image of your new appliance by calling kiwi --create... After successful creation of the image files find an USB stick which is able to store your appliance and plug it into a free USB port on your image build machine. Use the kiwi --bootstick... call to deploy the image on the stick. Refer to chapter 9 (USB image Live-Stick System) for details.
- 6. Plug in the stick on your test machine and boot it.
- 7. After your test system has successfully booted from stick login into your appliance and start to tweak the system according to your needs. This includes all actions required to make the appliance work as you wish. Before you start take care for the following:
 - Create an initial package list. This can be done by calling:

```
rpm -qa | sort > /tmp/deployPackages
```

 Check the output of the command git status and include everything which is unknown to git and surely will not be changed by you and will not become part of the image description overlay files to the /. gitignore files

After the initial package list exists and the git repository is clean you can start to configure the system. You never should install additional software just by installing an unmanaged archive or build and install from source. It's very hard to find out what binary files had been installed and it's also not architecture safe. If there is really no other way for the software to become part of the image you should address this issue directly in your image description and the config.sh script but not after the initial deployment has happened.

- 8. As soon as your system works as expected your new appliance is ready to enter the final stage. At this point you have done several changes to the system but they are all tracked and should now become part of your image description. To include the changes into your image description the following process should be used:
 - Check the differences between the currently installed packages and the initial deployment list. This can be done by calling:

```
rpm -qa | sort > /tmp/appliancePackages
diff -u /tmp/deployPackages /tmp/appliancePackages
```

Add those packages which are labeled with (+) to the <packages type ="image"> section of your config.xml file and remove those packages which has been removed (—) appropriately. If there are packages which has been removed against the will of the package manager make sure

you address the uninstallation of these packages in your config.sh script. If you have installed packages from repositories which are not part of your config.xml file you should also add these repositories in order to allow kiwi to install the packages

• Check the differences made in the configuration files. This can be easily done by calling:

```
git diff > /tmp/appliancePatch
```

The created patch should become part of your image description and you should make sure the patch is applied when preparing the image. According to this the command:

```
patch -p0 < appliancePatch</pre>
```

needs to be added as part of your config.sh script

• Check for new non binary files added. This can be done by calling:

```
1 git status
```

All files not under version control so far will be listed by the command above. Check the contents of this list make sure to add all files which are not created automatically to become part of your image description. To do this simply clone (copy) these files with respect to the filesystem structure as overlay files in your image description root/ directory.

9. All your valuable work is now stored in one image description and can be re-used in all KIWI supported image types.

Congratulation! To make sure the appliance works as expected prepare a new image tree and create an image from the new tree. If you like you can deactivate the creation of the git repository which will save you some space on the filesystem. If this appliance is a server I recommend to leave the repository because it allows you to keep track of changes during the live time of this appliance.

5 Maintenance of Operating System Images

Creating an image often results in an appliance solution for a customer and gives you the freedom of a working solution at that time. But software develops and you don't want your solution to become outdated. Because of this together with an image people always should think of *image-maintenance*. The following paragraph just reflects ideas how to maintain images created by KIWI:




Figure 5.1: Image maintenance scenarios

The picture above shows two possible scenarios which requires an image to become updated. The first reason for updating an image are changes to the software, for example a new kernel should be used. If this change doesn't require additional software or changes in the configuration the update can be done by kiwi itself using its --upgrade option. In combination with --upgrade KIWI allows to add an

additional repository which may be needed if the updated software is not part of the original repository. An important thing to know is that this additional repository is *not* stored into the original config.xml file of the image description.

Another reason for updating an image beside software updates are configuration changes or enhancements, for example an image should have replaced its browser with another better browser or a new service like apache should be enabled. In principal it's possible to do all those changes manually within the physical extend but concerning maintenance this would be a nightmare. Why, because it will leave the system in an unversioned condition. Nobody knows what has changed since the very first preparation of this image. So in short **dont't modify physical extends manually**. Changes to the image configuration should be done within the image description. The image description itself should be part of a versioning system like subversion. All changes can be tracked down then and maybe more important can be assigned to product tags and branches. As a consequence an image must be prepared from scratch and the old physical extend could be removed.

6 System to Image Migration

Contents

6.1	Create a Clean Repository Set First	41
6.2	Watch the Overlay and Unpackaged Files	42
6.3	Checklist	42
6.4	Turn my System Into an Image	43

KIWI provides an experimental module which allows you to turn your running system into an image description. This migration allows you to clone your currently running system into an image. The process has the following limitations at the moment:

- Works for SUSE systems only (with zypper on board)
- The process works semi automatically which means depending on the complexity of the system some manual postprocessing might be necessary

When calling KIWI's migrate mode it will try to find the base version of your operating system and uses the currently active repositories specified in the zypper database to match the software which exists in terms of packages and patterns. The result is a list of packages and patterns which represents your system so far. Of course there are normally some data which doesn't belong to any package. These are for example configurations or user data. KIWI collects all this information and would copy it as overlay files as part of the image description. The process will skip all remote mounted filesystems and concentrate only on local filesystems.

6.1 Create a Clean Repository Set First

When starting with the migration it is useful to let kiwi know about all the repositories from which packages has been installed to the system. In a first step call:

```
kiwi --migrate mySystem
```

This will create an HTML report where you can check which packages and patterns could be assigned to the given base repository. In almost all cases there will be information about packages which couldn't be assigned. You should go to that list and think of the repository which contains that packages (pacman, etc). If something is missing add it either to the zypper list on your system or use the KIWI options --add-repo ...-add-repotype.

Continue calling the following command until your list is clean You should continue the migration if you have a clean list of solved packages without any package skipped except you know that this package can't be provided or is not worth to become part of the migration.

```
1 kiwi --migrate mySystem --nofiles [ --skip package ... ]
```

6.2 Watch the Overlay and Unpackaged Files

Files which has been modified but belong to a package will be automatically copied into the overlay directory below /tmp/mySystem/root. You should check that no modified file is a binary because such a binary would be replaced by a new install of the package anyway. As a software deloper people tend to compile software from source and copy/install them into their system. Doing this could cause binary files previously installed by a package to be reported as modified. You should remove such files from your overlay tree.

The migration also copy the entire /etc directory into the overlay root directory because it stores all important configuration files. Beside the important files there are most probably a bunch of file which doesn't belong to any package exists only for historical reasons. kiwi creates a list of files and directories to support you best in sorting out what is required and what can be ignored. Nevertheless this is the most time consuming part of your migration review. Simply click on the *all unpackaged files* link to take a look at the complete list. Those files you want to have in your image needs to be copied over to the /tmp/mySystem/root directory

6.3 Checklist

After that you should walk through the following check list

- Change author and contact in config.xml
- Set appropriate name for your image in config.xml
- Add/modify default type (oem) set in config.xml if needed
- Make sure your X11 configuration is appropriate according to the new target.
 A failsafe version was created in /tmp/mysys/root/etc/X11/xorg.conf.install
 -> fbdev based
- Make sure yast2 is installed to be able to reconfigure the system. if yast2 is not installed these tasks needs to be done else. Otherwise yast's second stage is started on first boot of the migrated image
- If you want to access any remote filesystem it's a good idea to let autoyast add them on first boot of the system
- Check your network setup in /etc/sysconfig/network. Is this setup still
 possible in the cloned environment? Make sure you check for the MAC address of the card first.

6.4 Turn my System Into an Image...

After the process has finished you should check the size of the image description. The description itself shouldn't be that big. The size of a migrated image description mainly depends on how many overlay files exists in the root/directory. You should make sure to maintain only required overlay files. Now let's try to create a clone image from the description. By default an OEM image which is a virtual disk which is able to run on real hardware too is created. On success you will also find a ISO file which is an installable version of the OEM image. If you burn the ISO on a DVD you can use that DVD to install your cloned image on another computer.

```
kiwi -p /tmp/migrated --root /tmp/mySys
kiwi --create /tmp/mySys -d /tmp/myResult
```

If everything worked well you can test the created OEM image in any full virtual operating system environment like Qemu or VMware. Once created the image description can serve for all image types KIWI supports.

7 Installation Source

Contents

7.1	Adapt the Example's config.xml	45
7.2	Create a Local Installation Source	45

Before you start to use any of the examples provided in the following chapters your build system has to have a valid installation source for the distribution you are about to create an image for. By default all examples will connect to the network to find the installation source. It depends on your network bandwidth how fast an image creation process is and in almost all cases it is better to prepare a local installation source first.

7.1 Adapt the Example's config.xml

If you can make sure you have a local installation source it's important to change the path attribute inside of the repository element of the appropriate example to point to your local source directory. A typically default repository element looks like the following:

7.2 Create a Local Installation Source

The following describes how to create a local SUSE installation source which is stored below the path: /images/CDs If you are using the local path as described in this document you only need to flip the given path information inside of the example config.xml file.

1. find your SUSE standard installation CDs or the DVD and make them available to the build system. Most Linux systems auto-mount a previosly inserted media automatically. If this is the case you simply can change the directory to the auto mounted path below /media. If your system doesn't mount the device automatically you can do this with the following command:

```
mount -o loop /dev/<drive-device-name> /mnt
```

- 2. You don't have a DVD but a CD set? No problem all you need to do is copy the contents of *all* CDs into one directory. It's absolutly important that you first start with the *last* CD and copy the first CD at last. In case of CDs you should have a bundly of 4 CDs. Copy them in the order 4 3 2 1
- 3. Once you have access to the media copy the contents of the CDs/DVD to your hard drive. You need at least 4GB free space available. The following is intended to create a SUSE 11.0 installation source:

```
mkdir -p /image/CDs/full-11.0-i386/
cp -a /mnt/* /image/CDs/full-11.0-i386/
```

Remember if you have a CD set start with number 4 first and after that unplugg the CD and insert the next one to repeat the copy command until all CDs are copied into to /image

8 ISO Image—Live Systems

Contents

8.1	Building the suse-live-iso Example	47
8.2	Using the Image	47
8.3	Flavours	48
	8.3.1 Split mode	48

A live system image is an operating System on CD or DVD. In principal one can treat the CD/DVD as the hard disk of the system with the restriction that you can't write data on it. So as soon as the media is plugged into the computer the machine is able to boot from that media. After some time one can login to the system and work with it like on any other system. All write actions takes place in RAM space and therefore all changes will be lost as soon as the computer shuts down.

8.1 Building the suse-live-iso Example

The latest example provided with KIWI is based on openSUSE 11.2 and includes the base and KDE patterns.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.2
kiwi --prepare ./suse-live-iso --root /tmp/myiso
kiwi --create /tmp/myiso --type iso -d /tmp/myiso-result
```

8.2 Using the Image

There are two ways to use the generated ISO image:

- Burn the .iso file on a CD or DVD with your preferred burn program. Plug in the CD or DVD into a test computer and (re)boot the machine. Make sure the computer boot from the CD drive as first boot device.
- Use a virtualisation system to test the image directly. Testing an iso can be done with any full virtual system for example:

```
cd /tmp/myiso-result qemu -cdrom ./suse-11.2-live-iso.i686-2.5.1.iso -m 256
```

8.3 Flavours

KIWI supports different filesystems and boot methods along with the ISO image type. The provided example by default uses a squashfs compressed root filesystem. By design of this filesystem it is not possible to write data on it. To be able to write on the filesystem another filesystem called aufs is used. aufs is an overlay filesystem which allows to combine two different filesystems into one. In case of a live system aufs is used to combine the squashfs compressed read only root tree with a tmpfs RAM filesystem. The result is a full writable root tree whereas all written data lives in RAM and is therefore not persistent. squashfs and/or aufs does not exist on all versions of SUSE and therefore the flags attribute in config.xml exists to be able to have the following alternative solutions:

- flags="unified"
 Compressed and unified root tree as explained above
- flags="compressed"
 Does filesystem compression with squashfs but don't use an overlay filesystem for write support. A symbolic link list is used instead and thus a split element is required in config.xml. See the Split mode section below for details.
- flags="clic"
 Creates a FUSE based clicfs image and allows write operations into a cow file. In case of an ISO the write happens into a ramdisk.
- Flags Not Set

 If no flags attribute is set no compressed filesystem and no overlay filesystem
 will be used. The root tree will be directly part of the ISO filesystem and the
 paths: /bin, /boot, /lib, /lib64, /opt, /sbin, and /usr will be read-only.

8.3.1 Split mode

If no overlay filesystem is in use but the image filesystem is based on a compressed filesystem KIWI allows to setup which files and directories should be writable in a so called split section. In order to allow to login into the system at least the /var directory should be writable because the PAM authentification requires to be able to report any login attempt to /var/log/messages which therefore needs to be writable. The following split section can be used if the flag compressed is used:

9 USB Image—Live-Stick System

Contents

9.1	Building the suse-live-stick Example	51
9.2	Using the Image	52
9.3	Flavours	52
	9.3.1 Split Stick	53
	9.3.2 IVM Support	53

A live USB stick image is a system on USB stick which allows you to boot and run from this device without using any other storage device of the computer. It is urgently required that the BIOS of the system which you plug the stick in supports booting from USB stick. Almost all new BIOS systems support that. The USB stick serves as OS system disk in this case and you can read and write data onto it.

9.1 Building the suse-live-stick Example

The latest example provided with KIWI is based on openSUSE 11.2 and makes use of the default plus x11 pattern. The operating system is stored on a standard ext3 filesystem.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.2
kiwi --prepare ./suse-live-stick --root /tmp/mystick
```

There are two possible image types which allows you to drive the stick. Both are added into the config.xml of this example image description. If you already have access to the stick you want to run the image on the first approach should be preferred over the second one.

 The first image type named usb creates all required images for booting the OS but requires you to plug in the stick and let KIWI deploy the data onto this stick.

```
kiwi --create /tmp/mystick --type usb d /tmp/mystick-result
```

• The second image type named oem allows you to create a virtual disk which represents a virtual disk geometry including all partitions and boot information in one file. You simply can dd this file on the stick.

```
1 kiwi --create /tmp/mystick --type oem -d /tmp/mystick-result
```

9.2 Using the Image

To make use of the created images they need to be deployed on the USB stick. For the first image type (usb) you need KIWI itself to be able to deploy the image on the stick. The reason for this is that the usb image type has created the boot and the system image but there is no disk geometry or partition table available. KIWI creates a new partition table on the stick and imports the created images as follows:

```
kiwi --bootstick \

tmp/mystick-result/\
initrd-usbboot-suse-11.2.i686-2.1.1.splash.gz \
--bootstick-system \
tmp/mystick-result/\
suse-11.2-live-stick.i686-1.1.2
```

In case of the second image type (oem) you only need a tool which allows you to dump data onto a device. On Linux the most popular tool to do this is the dd command. The oem image is represented by the file with the <code>.raw</code> extension. As said this is a virtual disk which already includes partition information. But this partition information does not match the real USB stick geometry which means the KIWI boot image (oemboot) has to adapt the disk geometry on first boot. To deploy the image on the stick call:

```
dd if=/tmp/mystick-result/ \
suse-11.2-live-stick.i686-1.1.2.raw \
of=/dev/<stick-device> bs=32k
```

Testing of the live stick can be done with a test machine which boots from USB or with a virtualisation system. If you test with a virtualisation system for example qemu you should be aware that the USB stick looks like a normal disk to the system. The kiwi boot process searches for the USB stick to be able to mount the correct storage device but in a virtual environment the disk doesn't appear as a USB stick. So if your virtualisation solution doesn't provide a virtual BIOS which allows booting from USB stick you should test the stick on real hardware

9.3 Flavours

USB sticks weren't designed to serve as storage devices for operating systems. By design of these nice little gadgets their storage capacity is limited to only a few gigabytes. According to this KIWI supports compressed filesystems with USB sticks too:

• filesystem="squashfs"

This will compress the image using the squashfs filesystem. The boot process will automatically use aufs as overlay filesystem to mount the complete tree read-write. For the write part an additional ext2 partition will be created on

the stick. The support for this compression layer requires squashfs and aufs to be present in the distribution KIWI has used to build the image

• filesystem="clicfs"

Creates a fuse based clicfs image and allows write operations into a cow file.

9.3.1 Split Stick

If there is no overlay filesystem available it is also possible to define a split section in config.xml and use the split support to split the image into a compressed readonly and a read-write portion. To create a split stick the types needs to be adapted as follows:

• type setup for split usb type:

```
1 <type image="split" fsreadwrite="ext3" fsreadonly="squashfs"
2 boot="usbboot/suse-11.2"/>
```

• type setup for split oem type:

```
1 <type image="split" fsreadwrite="ext3" fsreadonly="squashfs"
2 boot="oemboot/suse-11.2"/>
```

For both types a split section inside the type section is required which defines the read-write data. A good starting point is to set /var, /home, and /etc as writable data.

If no split section is added the default split section from /usr/share/kiwi/modules/KIWISplit.txt is used

9.3.2 LVM Support

kiwi also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. KIWI creates the kiwiVG volume group and adds logical volumes as they are needed and configured according to the image type and filesystem. After boot of the system the user has full control over the volume group and is free to change/resize/increas the group and the volumes inside. Support for LVM has been added for all image types which are disk based. This includes vmx,oem and usb. In order to use LVM for the usb type just add the --lvm option as part of the kiwi kiwi --bootstick deployment or add the attribute lvm="true" as part of the type section in your config.xml file.

The optional lymvolumes section can be used to set one or more top level directories into a separate volume. See the *KIWI image description* chapter for a detailed explanation.

10 VMX Image—Virtual Disks

Contents

10.1 Building the suse-vm-guest Example	55
10.2 Using the Image	55
10.3 Flavours	56
10.3.1 VMware support	56
10.3.2 IVM Support	57

A VMX image is a virtual disk image for use in full virtualisation systems like Qemu or VMware. The image is a file containing the system represented by the configured packages in config.xml as well as partition data and bootloader information. The size of this virtual disk can be specified by using the <size> element in the config.xml file or by adding the --bootvm-disksize command line argument.

10.1 Building the suse-vm-guest Example

The vm-guest example provided with KIWI is based on recent openSUSE releases, one example configuration per release. The example uses base pattern and the virtual disk is formated using the distribution default filesystem.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.2
kiwi --prepare ./suse-vm-guest --root /tmp/myvm
kiwi --create /tmp/myvm --type vmx -d /tmp/myvm-result
```

10.2 Using the Image

The generated virtual disk image serves as the hard disk of the selected virtualization system (QEMU, VMware, etc.). The virtual hard disk format differs across virtualization environments. Some virtualization environments support multiple virtual disk formats. Using the QEMU virtualization environment the created image may be tested with the following command:

```
cd /tmp/myvm-result
qemu suse-11.2-vm-guest.i686-1.1.2.raw -m 256
```

10.3 Flavours

KIWI always generates a file in the .raw format. The .raw file is a disk image with a structure equivalent to the structure of a physical hard disk. Individual virtualization systems have specific formats to facilitate improved I/O performance to the virtual disk, represented by the image file, or additional specified virtual hard disk files. KIWI will generate a specific format when the format attribute of the type element is specified.

```
1 <type image="vmx"... format="name"/>
```

The following table lists the supported virtual disk formats

Name	Description
vmdk	Disk format for VMware
ovf	Open Virtual Format requires VMwares ovftool
qcow2	QEMU virtual disk format

10.3.1 VMware support

A VMware image is accompanied by a guest configuration file. This file includes information about the hardware to be represented to the guest image by the VMware virtualization environment as well as specification of resources such as memory.

Within the config.xml file it is possible to specify the VMware configuration settings. In addition it is possible to include selected packages in the created image that are specific to the VM image generation. The following config.xml snippet provides general guidance on the elements in config.xml.

Given the specification above KIWI will create a VMware guest configuration specifying the availability of 512 MB of RAM and an IDE disk controller interface for the VM guest. For aditional information about the configuration settings please refer to the *machine* section.

The guest configuration can be loaded through VMware user interface and may be modified through the GUI. The configuration file has the .vmx extension as shown in the example below.

```
/tmp/myvm-result/suse-11.2-vm-guest.i686-1.1.2.vmx
```

Using the format="vmdk" attribute of the <type> start tag will create the VMware formated disk image (.vmdk file) and the required VMware guest configuration (.vmx) file.

In addition it is possible to create an image for the Xen virtualization framework. By adding the bootprofile and bootkernel attributes to the <type> start tag with values of xen and xenboot, respectively. Please refer to the 13 (Xen image) chapter for additional details.

10.3.2 LVM Support

KIWI also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. KIWI creates the kiwiVG volume group and adds logical volumes as they are needed and configured according to the image type and filesystem. After boot of the system the user has full control over the volume group and is free to change/resize/increas the group and the volumes inside. Support for LVM has been added for all image types which are disk based. This includes vmx, oem and usb. In order to use LVM for the vmx type just add the --lvm option as part of the KIWI create step or add the attribute lvm="true" as part of the type section in your config.xml file.

```
kiwi --create /tmp/myvm --type vmx -d /tmp/myvm-result --lvm
```

With the optional lvmvolumes section you can set one or more top level directories into a separate volume. See the *KIWI image description* chapter for a detailed explanation.

11 PXE Image—Thin Clients

Contents

11.1 Setting Up the Required Services	59
11.1.1 Atftp Server	59
11.1.2 DHCP Server	60
11.2 Building the suse-pxe-client Example	60
11.3 Using the Image	61
11.4 Flavours	62
11.4.1 The PXE Client Control File	62
11.4.2 The PXE Client Configuration File	62
11.4.3 User another than tftp as download protocol	67
11.4.4 RAM only image	67
11.4.5 Union Image	68
11.4.6 Split Image	68
11.4.7 Root Tree Over NFS	69
11.4.8 Root Tree Over NBD	69
11.4.9 Root Tree Over AoE	69

A PXE image consists of a boot image and a system image like all other image types too. But with a PXE image the image files are available seperately and needs to be copied at specific locations of a network boot server. PXE is a boot protocol implemented in most BIOS implementations which makes it so interesting. The protocol sends DHCP requests to assign an IP address and after that it uses tftp to download kernel and boot instructions.

11.1 Setting Up the Required Services

Before you start to build pxe images with kiwi you should have setup the boot server. The boot server requires the services atftp and DHCP to run

11.1.1 Atftp Server

In order to setup the atftp server the following steps are required

1. install the packages atftp and kiwi-pxeboot

- 2. edit the file /etc/sysconfig/atftpd and set/modify the following variables:
 - ATFTPD OPTIONS="--daemon --no-multicast"
 - ATFTPD DIRECTORY="/srv/tftpboot"
- 3. run atftpd by calling the command: rcatftpd start

11.1.2 DHCP Server

In contrast to the atftp server setup the following DHCP server setup can only serve as an example. Please note that according to your network structure the IP addresses, ranges and domain settings needs to be adapted in order to allow the DHCP server to work within your network. If you already have a DHCP server running in your network you should make sure that the filename and next-server information is provided by your server. The following steps describe how to setup a new DHCP server instance:

- 1. Install the package dhcp-server
- 2. Create the file /etc/dhcpd.conf and include the following statements:

```
option domain-name "example.org";
option domain-name-servers 192.168.100.2;
option broadcast-address 192.168.100.255;
option routers 192.168.100.2;
option subnet-mask 255.255.255.0;
default-lease-time 600;
max-lease-time 7200;
ddns-update-style none; ddns-updates off;
log-facility local7;
subnet 192.168.100.0 netmask 255.255.255.0 {
   filename "pxelinux.0";
   next-server 192.168.100.2;
   range dynamic-bootp 192.168.100.5 192.168.100.20;
}
```

- 3. Edit the file /etc/sysconfig/dhcpd and setup the network interface the server should listen on:
 - DHCPD INTERFACE="eth0"
- 4. Run the dhcp server by calling: rcdhcpd start

11.2 Building the suse-pxe-client Example

The example provided with KIWI is based on openSUSE 11.2 and creates an image for a Wyse VX0 terminal with a 128MB flash card and 512MB of RAM. The image makes use of the squashfs compressed filesystem and its root tree is deployed as unified (aufs) based system.

11.3 Using the Image

In order to make use of the image all related image parts needs to be copied onto the boot server. According to the example the following steps needs to be performed:

1. Change working directory

```
cd /tmp/mypxe-result
```

2. Copy of the boot and kernel image

```
cp initrd-netboot-suse-11.2.i686-2.1.1.splash.gz \
   /srv/tftpboot/boot/initrd
cp initrd-netboot-suse-11.2.i686-2.1.1.kernel \
   /srv/tftpboot/boot/linux
```

3. Copy of the system image and md5 sum

```
cp suse-11.2-pxe-client.i686-1.2.8 \
/srv/tftpboot/image
cp suse-11.2-pxe-client.i686-1.2.8.md5 \
/srv/tftpboot/image
```

4. Copy of the image boot configuration

Normally the boot configuration applies to one client which means it is required to obtain the MAC address of this client. If the boot configuration should be used globaly the KIWI generated file can be copied as config.default

```
cp suse-11.2-pxe-client.i686-1.2.8.config \
/srv/tftpboot/KIWI/config.<MAC>
```

5. Check the PXE configuration file

The PXE configuration controls which kernel and initrd are loaded and which kernel parameters are set. When installing the kiwi-pxeboot package a default configuration is added. To make sure the configuration is valid according to this example the file /srv/tftpboot/pxelinux.cfg/default should provide the following information:

```
DEFAULT KIWI-Boot

LABEL KIWI-Boot

kernel boot/linux

append initrd=boot/initrd vga=0x314

IPAPPEND 1

LABEL Local-Boot

localboot 0

6. connect the client to the network and boot
```

11.4 Flavours

All the different PXE boot based deployment methods are controlled by the config. <MAC> (or config.default) file. When a new client boots up and there is no client configuration file the new client is registered by uploading a control file to the tftp server. The following sections informs about the control and the configuration file.

11.4.1 The PXE Client Control File

This section describes the netboot client control file:

```
hwtype.$<$MAC Address$>$
```

The control file is primarily used to set up new netboot clients. In this case, there is no configuration file corresponding to the client MAC address available. Using the MAC address information, the control file is created, which is uploaded to the TFTP servers upload directory /var/lib/tftpboot/upload.

11.4.2 The PXE Client Configuration File

This section describes the netboot client configuration file:

```
config.$<$MAC Address$>$
```

The configuration file contains data about image, configuration, synchronization, or partition parameters. The configuration file is loaded from the TFTP server directory /var/lib/tftpboot/KIWI via TFTP for previously installed netboot clients. New netboot clients are immediately registered and a new configuration file with the corresponding MAC address is created. The standard case for the deployment of a pxe image is one image file based on a read-write filesystem which is stored onto a local storage device of the client. Below, find an example to cover this case.

```
DISK=/dev/sda
PART=5;S;x,x;L;/
IMAGE=/dev/sda2;suse-11.2-pxe-client.i686;1.2.8;192.168.100.2;4096
The following format is used:
IMAGE=device;name;version;srvip;bsize;compressed,...,
CONF=src;dest;srvip;bsize,...,src;dest;srvip;bsize
PART=size;id;Mount,...,size;id;Mount
DISK=device
```

IMAGE

Specifies which image (name) should be loaded with which version (version) and to which storage device (device) it should be linked, e.g., /dev/ram1 or /dev/hda2. The netboot client partition (device) hda2 defines the root file system / and hda1 is used for the swap partition. The numbering of the hard disk device should not be confused with the RAM disk device, where /dev/ram0 is used for the initial RAM disk and can not be used as storage device for the second stage system image. SUSE recommends to use the device /dev/ram1 for the RAM disk. If the hard drive is used, a corresponding partitioning must be performed.

- srvip

Specifies the server IP address for the TFTP download. Must always be indicated, except in PART.

- bsize

Specifies the block size for the TFTP download. Must always be indicated, except in PART. If the block size is too small according to the maximum number of data packages (32768), **linuxrc** will automatically calculate a new blocksize for the download.

compressed

Specifies if the image file on the TFTP server is compressed and handles it accordingly. To specify a compressed image download only the keyword "'compressed" needs to be added. If compressed is not specified the standard download workflow is used. Note: The download will fail if you specify "compressed" and the image isn't compressed. It will also fail if you don't specify "compressed" but the image is compressed. The name of the compressed image has to contain the suffix .gz and needs to be compressed with the gzip tool. Using a compressed image will automatically deactivate the multicast download option of atftp.

CONF

Specifies a comma-separated list of source:target configuration files. The source (src) corresponds to the path on the TFTP server and is loaded via TFTP. The download is made to the file on the netboot client indicated by the target (dest).

PART

Specifies the partitioning data. The comma-separated list must contain the size (size), the type number (id), and the mount point (Mount). The size is measured in MB by default. Additionally all size specifications supported by the sfdisk program are allowed as well. The type number specifies the ID of the partition. Valid ID's are listed via the sfdisk --list-types command. The mount specifies the directory the partition is mounted to.

- The first element of the list must define the swap partition.
- The second element of the list must define the **root** partition.
- The swap partition must not contain a mount point. A lowercase letter
 x must be set instead.
- If a partition should take all the space left on a disk one can set a lower x letter as size specification.

• DISK

Specifies the hard disk. Used only with PART and defines the device via which the hard disk can be addressed, e.g., /dev/hda.

• RELOAD IMAGE

If set to a non-empty string, this forces the configured image to be loaded from the server even if the image on the disk is up-to-date. The primary purpose of this setting is to aid debugging. The option is sensible only for disk based systems.

RELOAD CONFIG

If set to a non-empty string, this forces all config files to be loaded from the server. The primary purpose of this setting is to aid debugging. The option is sensible only for disk based systems.

COMBINED IMAGE

If set to an non-empty string, indicates that the both image specified needs to be combined into one bootable image, whereas the first image defines the read-write part and the second image defines the read-only part.

• KIWI INITRD

Specifies the KIWI initrd to be used for local boot of the system. The variables value must be set to the name of the initrd file which is used via PXE network boot. If the standard tftp setup suggested with the kiwi-pxeboot package is used all initrd files resides in the boot/ directory below the tftp server path /var/lib/tftpboot. Because the tftpserver do a chroot into the tftp server path you need to specify the initrd file as the following example shows: KIWI INITRD=/boot/<name-of-initrd-file>

UNIONFS_CONFIG

For netboot and usbboot images there is the possibility to use unionfs or aufs as container filesystem in combination with a compressed system image. The recommended compressed filesystem type for the system image is **squashfs**. In case of a USB stick system the usbboot image will automatically setup the unionfs/aufs filesystem. In case of a PXE network image the

netboot image requires a config.<MAC> setup like the following example shows: UNIONFS_CONFIG=/dev/sda2,/dev/sda3,aufs. In this example the first device /dev/sda2 represents the read/write filesystem and the second device /dev/sda3 represents the compressed system image filesystem. The container filesystem aufs is then used to cover the read/write layer with the read-only device to one read/write filesystem. If a file on the read-only device is going to be written the changes inodes are part of the read/write filesystem. Please note the device specifications in UNIONFS_CONFIG must correspond with the IMAGE and PART information. The following example should explain the interconnections:

```
IMAGE=/dev/sda3;image/myImage;1.1.1;192.168.1.1;4096
PART=200;S;x,300;L;/,x;L;x
UNIONFS_CONFIG=/dev/sda2,/dev/sda3,aufs
DISK=/dev/sda
```

As the second element of the PART list must define the **root** partition it's absolutely important that the first device in UNIONFS_CONFIG references this device as read/write device. The second device of UNIONFS_CONFIG has to reference the given IMAGE device name.

• KIWI KERNEL OPTIONS

Specifies additional command line options to be passed to the kernel when booting from disk. For instance, to enable a splash screen, you might use 'vga=0x317 splash=silent'.

KIWI BOOT TIMEOUT

Specifies the number of seconds to wait at the grub boot screen when doing a local boot. The default is 10.

NBDROOT

Mount the system image root filesystem remotely via NBD (Network Block Device). This means there is a server which exports the root directory of the system image via a specified port. The kernel provides the block layer, together with a remote port that uses the nbd-server program. For more information on how to set up the server, see the nbd-server man pages. The kernel on the remote client can set up a special network block device named /dev/nb0 using the nbd-client command. After this device exists, the mount program is used to mount the root filesystem. To allow the KIWI boot image to use that, the following information must be provided:

The NBD-Device, NBD-Swap-Port-Number, NBD-Swap-Device, NBD-Write-Port-Number and NBD-Write-Device variables are optional. If the nbd root device is not set, the default values (/dev/nb0, port 2000) applies and if the nbd swap device is not set the default values (/dev/nb1, port 9210) applies. The swap space over the network using a network block device is

only established if the client has less than 48 MB of RAM. The optional NBD-Write-Port-Number and NBD-Write-Device specifies a write COW location for the root filesystem. aufs is used as overlay filesystem in this case.

AOEROOT

Mount the system image root filesystem remotely via AoE (ATA over Ethernet). This means there is a server which exports a block device representing the the root directory of the system image via the AoE subsystem. The block device could be a partition of a real or a virtual disk. In order to use the AoE subsystem I recommend to install the *aoetools* and *vblade* packages from here first: http://download.opensuse.org/repositories/system:/aoetools Once installed the following example shows how to export the local /dev/sdb1 partition via AoE:

```
vbladed 0 1 eth0 /dev/sdb1
```

Some explanation about this command, each AoE device is identified by a couple Major/Minor, with major between 0-65535 and minor between 0-255. AoE is based just over Ethernet on the OSI models so we need to indicate which ethernet card we'll use. In this example we export /dev/sdb1 with a major value of 0 and minor of 1 on the eth0 interface. We are ready to use our partition on the network! To be able to use the device kiwi needs the information which AoE device contains the root filesystem. In our example this is the device /dev/etherd/e0.1. According to this the AOEROOT variable must be set as follows:

```
AOEROOT=/dev/etherd/e0.1
```

kiwi is now able to mount and use the specified AoE device as the remote root filesystem. In case of a compressed read-only image with aufs or clicfs the AOEROOT variable can also contain a device for the write actions:

```
AOEROOT=/dev/etherd/e0.1,/dev/ram1
```

Writing to RAM is the default but you also can set another device like another aoe location or a local device for writing the data

NFSROOT

Mount the system image root filesystem remotely via NFS (Network File System). This means there is a server which exports the root filesystem of the network client in such a way that the client can mount it read/write. In order to do that, the boot image must know the server IP address and the path name where the root directory exists on this server. The information must be provided as in the following example:

```
NFSROOT=NFS.Server.IP.address;/path/to/root/tree
```

Optionally you can set a UNIONFS_CONFIG variable which defines an aufs based overlay NFS directory or device like:

```
UNIONFS_CONFIG=/tmp/kiwi-11.1-cow,nfs,aufs # write to NFS directory
UNIONFS_CONFIG=/dev/ram1,nfs,aufs # write to RAM
```

This way you can keep the original root tree clean from any modifications

• KIWI INITRD

Specifies the KIWI initrd to be used for a local boot of the system. The value must be set to the name of the initrd file which is used via PXE network boot. If the standard TFTP setup suggested with the kiwi-pxeboot package is used, all initrd files reside in the /srv/tftpboot/boot/ directory. Because the TFTP server does a chroot into the TFTP server path, you must specify the initrd file as follows:

KIWI_INITRD=/boot/name-of-initrd-file

KIWI KERNEL

Specifies the kernel to be used for a local boot of the system The same path rules as described for KIWI INITRD applies for the kernel setup:

KIWI_KERNEL=/boot/name-of-kernel-file

ERROR INTERRUPT

Specifies a message which is displayed during first deployment. Along with the message a shell is provided. This functionality should be used to send the user a message if it's clear the boot process will fail because the boot environment or something else influences the pxe boot process in a bad way.

11.4.3 User another than tftp as download protocol

By default all downloads controlled by the KIWI linuxrc code are performed by an atftp call and therefore uses the tftp protocol. With PXE the download protocol is fixed and thus you can't change the way how the kernel and the boot image (initrd) is downloaded. As soon as Linux takes over control the following download protocols http, https and ftp are supported too. KIWI makes use of the curl program to support the additional protocols.

In order to select one of the additional download protocols the following kernel parameters needs to be setup:

• kiwiserver

Name or IP address of the server who implements the protocol

kiwiservertype

Name of the download protocol which could be one of http, https or ftp

To setup this parameters edit the file /srv/tftpboot/pxelinux.cfg/default on your PXE boot server and change the append line accordingly. Please note all downloads except for kernel and initrd are now controlled by the given server and protocol. You need to make sure that this server provides the same directory and file structure as initially provided by the kiwi-pxeboot package.

11.4.4 RAM only image

If there is no local storage and no remote root mount setup the image can be stored into the main memory of the client. Please be aware that there should be still enough RAM space available for the operating system after the image has been deployed into RAM. Below, find an example:

- Use a read-write filesystem in config.xml, for example filesystem="ext3"
- Create config. < MAC>

```
IMAGE=/dev/ram1; suse-11.2-pxe-client.i686;\
1.2.8;192.168.100.2;4096
```

11.4.5 Union Image

As used in the suse-pxe-client example it is possible to make use of the aufs or unionfs overlay filesystems to combine two filesystems into one. In case of thin clients there is often the need for a compressed filesystem due to space limitations. Unfortunately all common compressed filesystems provides only read-only access. Combining a read-only filesystem with a read-write filesystem is a solution for this problem. In order to use a compressed root filesystem make sure your config.xml's filesystem attribute contains either squashfs or clicfs. Below, find an example:

11.4.6 Split Image

As an alternative to the UNIONFS_CONFIG method it is also possible to create a split image and combine the two portions with the COMBINED_IMAGE method. This allows to use different filesystems without the need for an overlay filesystem to combine them together. Below find an example:

- add a split type in config.xml, for example <type fsreadonly="squashfs" image="split" fsreadwrite="ext3" boot="netboot/suse-11.2"/>
- add a split section inside the type to describe the temporary and persistent parts. For example:

```
<file name="/var/*"/>
          <file name="/boot"/>
 11
          <file name="/boot/*"/>
 12
          <file name="/etc"/>
          <file name="/etc/*"/>
          <file name="/home"/>
          <file name="/home/*"/>
       </persistent>
    </split>
• sample config.<MAC>:
  IMAGE=/dev/sda2;suse-11.2-pxe-client.i686;\
        1.2.8;192.168.100.2;4096,\
        /dev/sda3;suse-11.2-pxe-client-read-write.i686;
        1.2.8;192.168.100.2;4096
 PART=200;S;x,500;L;/,x;L;
 DISK=/dev/sda
  COMBINED_IMAGE=yes
 KIWI_INITRD=/boot/initrd
```

11.4.7 Root Tree Over NFS

Instead of installing the image onto a local storage device of the client it is also possible to let the client mount the root tree via an NFS remote mount. Below find an example:

- Export the kiwi prepared tree via NFS
- sample config.<MAC>:

```
NFSROOT=192.168.100.7;/tmp/kiwi.nfsroot
```

11.4.8 Root Tree Over NBD

As an alternative for root over NFS it is also possible to let the client mount the root tree via a special network block device. Below find an example:

- Use nbd-server to export the KIWI prepared tree
- sample config.<MAC>

```
NBDROOT=192.168.100.7;2000;/dev/nbd0
```

11.4.9 Root Tree Over AoE

As an alternative for root over NBD it is also possible to let the client mount the root device via a special ATA over Ethernet network block device. Below find an example:

- Use the vbladed command to bind a block device to an ethernet interface. The block device can be a disk partition or a loop device (losetup) but not a directory like with NBD
- sample config.<MAC>:

AOEROOT=/dev/etherd/e0.1

This would require the command vbladed 0 1 eth0 blockdevice to be called first

12 OEM Image—Preload Systems

Contents

12.1 Building the suse-oem-preload Example	71
12.2 Using the Image	72
12.3 Flavors	72
12.3.1 Influencing the OEM Partitioning	73
12.3.2 LVM Support	73
12.3.3 Partition Based Installation	73

An oem image is a virtual disk image representing all partitions and bootloader information in the same fashion it exists on a physical disk. The image format matches the format of the VMX image type. All flavors discussed previously for the VMX image type apply to the OEM image type.

The basic idea behind an oem image is to provide the virtual disk data for OEM vendors to support easy deployment of the system to physical storage media. The deployment can be performed from any OS including Windows as long as a tool to dump data onto a disk device exists and is used. The oem image type may also be used to deploy an image on a USB stick. A USB stick is simply a removable physical storage device.

12.1 Building the suse-oem-preload Example

The OEM example provided with kiwi is based on recent openSUSE releases, one example configuration per release, and includes the default and x11 patterns. The image type is a split type utilizing the distributions default filesystem format for the read-write partition and the squashfs filesystem for the read-only partition. Using the additional installiso attribute creates an installable ISO image. When booting from the ISO image the OEM disk image will be deployed to the storage media on the booting machine (after confirmation by the user).

The commands provided below use the openSUSE 11.2 based example built for the x86 architecture.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.2
kiwi --prepare ./suse-oem-preload --root /tmp/myoem
kiwi --create /tmp/myoem --type split -d /tmp/myoem-result
```

12.2 Using the Image

The virtual disk image created by KIWI with the commands shown above can be tested using virtualization software such as QEMU, VMware, or VirtualBox. The virtual disk is represented by the file with the .raw extension, whereas the file with the .iso extension represents the installation disk for this oem image. The ISO image is bootable (filename.iso) and can be burned to optical media. It is recommended to test the image on a bare test system. The following command shows how to use qemu to test the oem disk image (filename.raw).

```
cd /tmp/myoem-result
qemu suse-11.2-oem-preload.i686-1.1.2.raw -m 512
```

or using the dd command you can dump the image onto a test hard disk or USB stick and upon reboot select the appropriate device as the boot device in the BIOS:

```
cd /tmp/myoem-result
dd if=suse-11.2-oem-preload.i686-1.1.2.raw \
of=/dev/<device> bs=32k
```

Please note, when testing an oem image using the virtual disk image, i.e. the .raw file, the geometry of the disk image is not changed and therefore retains the disk geometry of the host system. This implies that the re-partitioning performed for a physical disk install during the oem boot workflow will be skipped.

You can test the installation procedure in a virtual environment using the .iso file. In this case the re-partitioning code in the boot image will be executed. The following commnads show this procedure using QEMU.

```
cd /tmp/myoem-result
qemu-img create /tmp/mydisk 20G
qemu -hda /tmp/mydisk -cdrom \
suse-11.2-oem-preload.i686-1.1.2.iso \
-boot d
```

12.3 Flavors

As indicated above the use of the installiso and installstick attributes for the oem image supports the creation of an installation image. The installation image can be created in two formats, one suitable for CD/DVD media and a second suitable for a USB stick. The self installing image deploys the oem image onto the selected storage device. The installation process is a simple image dump using the dd command. During this process the target system remains in terminal mode. The following configuration snippets show the use of the installiso and installstick attributes to create the ISO or USB installation image format respectively.

- <type image="name" ... installiso="true"/>
 Creates a .iso file which can be burned in CD or DVD. This represents an installation CD
- <type image="name" ... installstick="true"/>
 Creates a .raw.install file which can be dumped (dd) on a USB stick. This represents an installation Stick

12.3.1 Influencing the OEM Partitioning

By default the oemboot process will create/modify a swap, /home and / partition. It is possible to influence the behavior with the oem-* elements. See the *KIWI image description* chapter for details.

12.3.2 LVM Support

KIWI also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. KIWI creates the kiwiVG volume group, unless the lvmgroup attribute has been set, and adds logical volumes to the group based on the configuration given by the lvmvolumes block for this type. The filesystem for the volume group is determined by the filesystem attribute of the type element. After booting the system the user has full control over the volume group and is free to change (resize/increase) the group and the volumes inside. Support for LVM has been added for all disk based image types. This includes the vmx, oem and usb image types. In order to use LVM for the oem type just add the --lvm command line option when executing the create step or add the attribute lvm="true" to of the type element in your config.xml file.

```
1 kiwi --create /tmp/myoem --type oem -d /tmp/myoem-result --lvm
```

With the optional **lvmvolumes** section you can specify to have one or more top level directories in a separate volume. See the *KIWI image description* chapter for a detailed explanation.

12.3.3 Partition Based Installation

The default installation method of an OEM is dumping the entire virtual disk on the selected target disk and repartition the disk to the real geometry. This works but will also wipe everything which was on the disk before. KIWI also supports the installation into already existing partitions. This means the user can setup a disk with free partitions for the KIWI OEM installation process. This way already existing data will not be touched. In order to activate the partition based install mode the following oem option has to be set in config.xml:

1 <oem-partition-install>true</oem-partition-install>

Compared to the disk based install the following differences should be mentioned:

- The bootloader will be setup to boot the installed system. There is no multiboot setup. The user has to take care for the setup of a multiboot bootloader himself.
- The oem options for system, swap and home doesn't have any effect if the installation happens in predefined partitions
- There is no support for remote (PXE) OEM installation because kiwi has to loop mount the disk image in order to access the partitions which can't be done remotely
- The raw disk image is stored uncompressed on the install media. This is because KIWI needs to loop mount the disk image which it can't do if the file is only available as compressed version. This means the install media in this mode will be approximately double the size of a standard install media

13 Xen Image—Paravirtual Systems

Contents

13.1 Building the suse-xen-guest Example	75
13.2 Using the Image	76
13.3 Flavours	76

Xen is a free software virtual machine monitor. It allows several guest operating systems to be executed on the same computer hardware at the same time.

A Xen system is structured with the Xen hypervisor as the lowest and most privileged layer. Above this layer are one or more guest operating systems, which the hypervisor schedules across the physical CPUs. The first guest operating system, called in Xen terminology "domain 0" (dom0), is booted automatically when the hypervisor boots and given special management privileges and direct access to the physical hardware. The system administrator logs into dom0 in order to start any further guest operating systems, called "domain U" (domU) in Xen terminology.

A Xen image is a virtual disk like a vmx but with the xen kernel installed. In order to run it a Xen dom0 server needs to run. Xen images in KIWI makes use of the PVGrub method supported by current Xen versions. Xen extracts the kernel and initrd from the virtual disk as well as the grub configuration and displays the menu which allows emulation of the Grub console

13.1 Building the suse-xen-guest Example

The latest example provided with kiwi is based on openSUSE 11.3 and includes the base pattern.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.2
kiwi --prepare ./suse-xen-guest \
--root /tmp/myxen

kiwi --create /tmp/myxen \
--type vmx -d /tmp/myxen-result
```

13.2 Using the Image

In order to run a domain U the Xen tool xm needs to be called in conjunction with the KIWI genereated domain U configuration file

```
begin{verbatim}

xm create -c \
    /tmp/myxen-result/\
suse-11.2-xen-guest.i686-1.1.2.xenconfig
begin{verbatim}
```

13.3 Flavours

With KIWI you can provide the information required to create a guest configuration as part of the config.xml file. Additionally you can group special packages which you may only need in this para virtual environment with a profile.

If this information is present KIWI will create a Xen domain U configuration with 512 MB of RAM and expects the disk at /dev/xvda. Additional information to setup the Xen guest machine properties are explained in the machine section. The KIWI Xen domain U configuration is stored in the file:

```
/tmp/myxen-result/\
suse-11.2-xen-guest.i686-1.1.2.xenconfig
```

14 EC2 Image—Amazon Elastic Compute Cloud

Contents

14.1 Building the suse-xen-guest Example for EC2	77
14.2 Using the Image	78

The Amazon Elastic Compute Cloud (Amazon EC2) web service provides you with the ability to execute arbitrary applications in our computing environment. To use Amazon EC2 you simply:

- 1. Create an Amazon Machine Image (AMI) containing all your software, including your operating system and associated configuration settings, applications, libraries, etc. Such an AMI can be created by the KIWI ec2 image format. In order to do that KIWI makes use of the tools provided by Amazon. Your build system should have these tools installed. Due to license issues we are not allowed to distribute the tools which means you need to download, install and setup them from here:
 - http://aws.amazon.com/documentation/ec2/
- 2. Upload this AMI to the Amazon S3 (Amazon Simple Storage Service) service. This gives us reliable, secure access to your AMI.
- 3. Register your AMI with Amazon EC2. This allows us to verify that your AMI has been uploaded correctly and to allocate a unique identifier for it.
- 4. Use this AMI ID and the Amazon EC2 web service APIs to run, monitor, and terminate as many instances of this AMI as required. Currently, Amazon provides command line tools and Java libraries but you may also directly access the SOAP-based API.

Please note while instances are running, you are billed for the computing and network resources that they consume. You should start creating an ec2 with KIWI after you can make sure your system is prepared for ec2 which means if you call the command ec2-describe-images -a you will get a valid output.

14.1 Building the suse-xen-guest Example for EC2

One example provided with KIWI is based on openSUSE 11.3 and includes the base pattern plus the vim editor.

Before you run KIWI you need to include some of your ec2 account information into the image description config.xml file. The box below shows the values you need to adapt:

After that call KIWI as follows:

14.2 Using the Image

The generated image needs to be transferred over to Amazon which is done by the ec2-upload-bundle tool. You can do this by calling:

```
1 ec2-upload-bundle -b myImages \
2 -a <AWS Key ID> -s <AWS secret Key ID> \
3 -m /tmp/myec2/\
4 suse-11.1-xen-guest.i686-1.1.2.ami.manifest.xml
```

After this is done the image needs to be registered in order to receive a so called AMI id which starts with ami- followed by a random key sequence. To register call:

```
ec2-register myImages/\
suse-11.1-xen-guest.i686-1.1.2.ami.manifest.xml
```

The result is the AMI id which you need to run an instance from your image. The command ec2-describe-images allows you to review your registered images. Since you will be running an instance of a public AMI, you will need to use a public/private keypair to ensure that only you will have access. One half of this keypair will be embedded into your instance, allowing you to login securely without a password using the other half of the keypair. Every keypair you generate requires a name. Be sure to choose a name that is easy to remember, perhaps one that describes the image's content. For our example we'll use the name gsg-keypair.

```
ec2-add-keypair gsg-keypair
```

The private key returned needs to be saved in a local file so that you can use it later. Using your favorite text editor, create a file named id_rsa-gsg-keypair and paste everything between (and including) the ----BEGIN RSA PRIVATE KEY---- and ----END RSA PRIVATE KEY---- lines into it. To review your keypairs call:

```
ec2-describe-keypairs
```

We are almost done now but to be able to run an instance it's required to select an appropriate AKI ID from the *Amazon Kernel Image IDs* table below. For this host, *aki-407d9529* is being chosen, because we are bundling an AMI representing a virtual disk with PVGrub. If the table below is outdated just check the current ID list at Amazon directly

AKI	Name
aki-407d9529	ec2-public-images/pv-grub-hd0-
	V1.01-i386.gz.manifest.xml
aki-427d952b	ec2-public-images/pv-grub-hd0-
	V1.01-x86_64.gz.manifest.xml

Fire up your new ec2 instance with the following command:

```
ec2-run-instances ami-... \
--kernel aki-407d9529 \
-k gsg-keypair
```

To check the state of your instance(s) call the following command:

```
ec2-describe-instances
```

If you see your instance at the status: **running** you can login into it. If you can't make sure you have allowed port 22 to be available

```
ec2-authorize default -p 22
```

2 \end{verbatim}

Congratulations! You made it and can now use Amazons storage and computing power.

15 KIWI Testsuite

Contents

15.1 Testsuite Packages	81
15.2 Creating a Test	81

The KIWI test suite is useful to perform basic quality checks on the image root directory. The test cases are stored in subdirectories below /usr/share/kiwi/tests. To run the testsuite call KIWI as follows:

```
kiwi \option{testsuite} <image-root> \bs \\
hspace*{1cm}[ \option{test} name \option{test} name ... ]
```

If not test names are set the default tests rpm and ldd run. The name of a test corresponds with the name of the directory the test is implemented in.

15.1 Testsuite Packages

If a test requires special software to be installed but this software is not an essential part of the image itself it can be specified as testsuite packages in the system image config.xml as follows:

```
1 <packages type="testsuite">\\
2 \hspace*{1cm}<package name="..."/>\\
3 </packages>
```

The testsuite packages are installed when calling KIWI with the testsuite option and are removed after the tests has finished.

15.2 Creating a Test

The test itself is defined by a xml description test-case.xml and its template definition file /usr/share/kiwi/modules/KIWISchemaTest.rnc The following example shows the basic structure of the rpm test:

```
crequirements
creq type="directory">/var/lib/rpm</req>
creq type="file">/var/lib/rpm/_db.000</req>
creq type="file">/var/lib/rpm/Packages</req>
creq type="file">/var/lib/rpm/Packages</req>
c/requirements>

ctest type="binary" place="extern">
cfile>rpm.sh</file>
cparams>CHROOT</params>
c/test>
content
co
```

There are basically two sections called equirements and test. In requirements you define what files/directories or packages has to be present in your image to run the test. For example if you need to check the rpm database, the database has to be present within the image. All requirements are checked, and if any of them fail the test won't be executed and an error message is printed. There are three types of requirements:

- file
 Existence of a file
- **directory**Existence of a directory
- rpm-package
 Existence of a package

The test section defines the test script. It could be a binary, shell script or any other kind of executable. Scripts are expected to be in the same directory as where the xml definition for the test resides. There are two types of scripts, extern and intern.

- external scripts are executed outside of the image and are preferred. Their first parameter should be CHROOT. This parameter is changed to the real path of the image chroot directory.
- internal scripts are executed inside image using the chroot command. Files are copied into the image and deleted after execution.

A test script always has to return 0 in case of a test to pass, or 1 if any error occur. All messages printed to standard and error output are stored and printed out of the test has failed.

Index

Amazon Machine Image, 77 Amazon S3, see Aazon Simple Storage Service77 Amazon Simple Storage Service, 77 AMI, see Aazon Machine Image77	config.oempartition, 22 config.xml, 13, 15, 36, 42, 45, 51, 55, 56 hwtype. <mac address="">, 62 recovery.tar.bz2, 22 xorg.conf.install, 42</mac>
boot process, 11 chroot, 82	cp, 14 curl, 67
Cloud, see E277	11
commands	dd, 51, 52, 72
chroot, 82	EC2 cas VMI images EC277
config.sh, 9, 10, 31, 35–37, 83	EC2, see KWI images, EC277 ec2-describe-images, 77, 78
cp, 14	examples
curl, 67	DHCP server, 60
dd, 51, 52, 72	suse-vm-guest, 55
ec2-describe-images, 77, 78	susc-viii-guest, 33
git status, 36	filesystem
gzip, 63	compression, 48
images.sh, 10, 28, 31, 33	FUSE, 48
index.sh, 83	
kiwi, 15, 28, 35, 36, 54	git status, 36
KIWIConfig.sh, 22	gzip, 63
linuxrc, 11, 12	images.sh, 10, 28, 31, 33
rcdhcpd start, 60	index.sh, 83
sfdisk, 64	index.sii, 00
smart, 17, 29	kiwi, 15, 28, 35, 36, 54
suse-linuxrc, 12	KIWI images
uname, 32	appliance, 35–37
vbladed, 70	description, 13–33
xm, 76	EC2, 77–79
yast2, 42	ISO, 47–49
zypper, 17, 29	maintenance, 39–40
config.sh, 9, 10, 31, 35–37, 83	migration, 41–43
configuration files	OEM, 71–74
.gitignore, 36	PXE, 59–70
config-cdroot.tgz, 14	testing, 81–82
config-yast-firstboot.xml, 14	USB, 51–54
config. <mac address="">, 62</mac>	vmx, 55–57

workflow, 7–12 Xen, 75–76 KIWI Setup of installation sources instsourcesetup, 45–46	config.sh, 9, 14, 35, 37 images.sh, 10, 13, 33 sfdisk, 64 smart, 17, 29
KIWIConfig.sh, 22	suse-linuxrc, 12
linuxrc, 11, 12 LVM, 53	uname, 32
man pages, 83 network setup, 42 NFS (Network File System), 66, 69	vbladed, 70 vmdk, 56 VMware, 55 support, 56 vmdk, 56
options —add-profile, 17 —add-repo, 41	Xen, 75–76 xm, 76
—add-repotype, 41	yast2, 42
—base-root, 20 —bootstick, 36, 54 —bootvm-disksize, 55 —create, 36 —createpassword, 28 —daemon, 60 —destdir, 20 —force, 20 —force-new-root, 9 —list-types, 64 —lvm, 54, 57 —no-multicast, 60 —prebuiltbootimage, 20 —prepare, 35 —root, 20 —upgrade, 39 —version, 15 overlay, 42 ovf, 56	zypper, 17, 29
package managers	
smart, 9 zypper, 9	
qcow2, 56 Qemu, 43, 55	
rcdhcpd start, 60	
scripts config-cdroot.sh, 15	

A Appendix—KIWI man pages

The following pages will show you the man page of KIWI and the functions which can be used within config.sh and index.sh

- man kiwi
- man kiwi::config.sh
- man kiwi::index.sh

Name

kiwi — Creating Operating System Images

Synopsis

```
kiwi { -l | --list }
kiwi { -o | --clone } image-path { -d } destination
kiwi { -b | --build } image-path { -d } destination
```

Basics

KIWI is a complete imaging solution that is based on an image description. Such a description is represented by a directory which includes at least one config.xml file and may as well include other files like scripts or configuration data. The kiwi-templates package provides example descriptions based on a JeOS system. JeOS means Just enough Operating System. KIWI provides image templates based on that axiom which means a JeOS is a small, text only based image including a predefined remote source setup to allow installation of missing software components at a later point in time.

Detailed description of the kiwi image system exists in the system design document in file:///usr/share/doc/packages/kiwi/kiwi.pdf. KIWI always operates in two steps. The kiwi --build option just combines both steps into one to make it easier to start with kiwi. The first step is the preparation step and if that step was successful, a creation step follows which is able to create different image output types. If you have started with an example and want to add you own changes it might be a good idea to clone of from this example. This can be done by simply copying the entire image description or you can let kiwi do that for you by using the kiwi --clone command.

In the preparation step, you prepare a directory including the contents of your new filesystem based on one or more software package source(s) The creation step is based on the result of the preparation step and uses the contents of the new image root tree to create the output image. If the image type ISO was requested, the output image would be a file with the suffix .iso representing a live system on CD or DVD. Other than that kiwi is able to create images for virtual and para-virtual (Xen) environments as well as for USB stick, PXE network clients and OEM customized Linux systems.

Image Preparation and Creation

```
kiwi { -p | --prepare } image-path
[-r | --root image-root | --chache directory]
kiwi { -c | --create } image-root
{ -d | --destdir destination } [--type image-type]
```

Image Upgrade

If the image root tree is stored and not removed, it can be used for upgrading the image according to the changes made in the repositories used for this image. If a distributor provides an update channel for package updates and an image config.xml includes this update channel as repository, it is useful to store the image root tree and upgrade the tree according to changes on the update channel. Given that the root tree exists it's also possible to add or remove software and recreate the image of the desired type

kiwi { -u | --upgrade } image-root [--add-packagename] [--add-patternname]

System to Image Migration

The migration module allows you to migrate your currently running system into an image description. The module will check for files not managed by a package manager and also inspects your system for package pattern and file consistency according to the currently active repositories. The system requires the zypper backend in order to work properly. The migration process creates a cache file so that subsequent calls of the migration runs much faster. Please have in mind that if your system has changed (files created/deleted, etc) the cache file might not be worth to become reused. In this case you should remove the cache first and start from scratch. The option --nofiles will prevent the system from searching for unpackaged and packaged but modified files The option --notemplate will prevent the creation of the image description files which are needed if you want to use kiwi to create a clone image from the result of the migration. With the options --exclude and --skip you can tell the system to ignore specific directories and/or packages. This makes sense if you know before that some data is not worth to become migrated or can be restored easily later inside the cloned image like software repositories. The migration process will always place it's result into the /tmp/\$OptionValueOf-m directory. The reason for this is because /tmp is always excluded from the migration operation and therefore we can safely place new files there without influencing the migration itself. You should have at least 50 MB free space for the cache file and the image description all the rest are just hard links. As one result a HTML based report file is created which contains important information about the system. You are free to ignore that information but with the risk that the migrated image does not represent the same system which is running at the moment. The less issues left in the report the better is the result. In most cases a manual fine tuning is required. This includes the repository selection and the unmanaged files along with the configuration details of your currently running operating system. You should understand the module as a helper to migrate running servers into images. The implementation is still under construction so expect better migration results in future releases:)

kiwi { -m | --migrate } name [--exclude directory...] [--skip package...] [--nofiles] [--notemplate]

Image Postprocessing Modes

The KIWI post-processing modes are used for special image deployment tasks, like installing the image on a USB stick. So to say they are the third step after preparation and creation. kiwi calls the postprocessing modules automatically according to the specified output image type and attributes but it's also possible to call them manually.

kiwi --bootstick initrd [--bootstick-system systemImage] [--bootstick-device device]

kiwi --bootvm initrd --bootvm-system systemImage [--bootvm-disksize size]

```
kiwi --booted initrd
kiwi --installed initrd --installed-system vmx-system-image
kiwi --installstick initrd --installstick-system vmx-system-image
```

Image format conversion

The KIWI format conversion is useful to perform the creation of another image output format like vmdk for VMware or ovf the open virtual machine format. Along with the conversion kiwi also creates the virtual machine configuration according to the format if there is a machine section specified in the xml description

```
kiwi --convert systemImage [--format vmdk/ovf/gcow2]
```

Testsuite

The KIWI test suite is useful to perform basic quality checks on the image root directory. The test cases are stored in subdirectories below /usr/share/kiwi/tests.

```
kiwi --testsuite image-root [--test name...]
```

Helper Tools

The helper tools provide optional functions like creating a crypted password string for the users section of the config.xml file or signing the image description with an md5sum hash as well as adding splash data to the boot image used by the bootloader and the testsuite mode which allows testing the integrity of the new root tree.

```
kiwi --createpassword
kiwi --createhash image-path
kiwi {-i|--info } ImagePath {--select
  repo-patterns|patterns|types|sources|size|profiles|packages }
kiwi --setup-splash initrd
```

The following list describes the helper tools more detailed

```
[--createpassword]
```

Create a crypted password hash and prints it on the console. The user can use the string as value for the pwd attribute in the XML users section

```
[--createhash image-path]
```

Sign your image description with a md5sum. The result is written to a file named .checksum.md and is checked if kiwi creates an image from this description

```
[-i|--info image-path--select selection]
```

List general information about the image description. So far you can get information about the

available patterns in the configured repositories with repo-patterns, a list of used patterns for this image with patterns, a list of supported image types with types, a list of source URL's with sources, an estimation about the install size and the size of the packages marked as to be deleted with size, a list of profiles with profiles, and a list of solved packages to become installed with packages.

```
[--setup-splash initrd]
```

Create splash screen from the data inside the initrd and re-create the initrd with the splash screen attached to the initrd cpio archive. This enables the kernel to load the splash screen at boot time. If splashy is used only a link to the original initrd will be created

Global Options

```
[--base-root base-path]
```

Refers to an already prepared root tree. Kiwi will use this tree to skip the first stage of the prepare step and run the second stage directly.

```
[--base-root-mode copy/union/recycle]
```

Specifies the overlay mode for the base root tree. This can be either a copy of the tree, a union mount or the tree itself. The last mode (recycle) will modify the base root tree which might make it obsolete as base root for other kiwi calls

```
[--add-profile profile-name]
```

Use the specified profile. A profile is a part of the XML image description and therefore can enhance each section with additional information. For example adding packages.

```
[--set-repo URL]
```

Set/Overwrite repo URL for the first listed repo. The change is temporary and will not be written to the XML file.

```
[--set-repotype type]
```

Set/Overwrite repo type for the first listed repo. The supported repo types depends on the packagemanager. Commonly supported are rpm-md, rpm-dir and yast2. The change is temporary and will not be written to the XML file.

```
[--set-repoalias name]
```

Set/Overwrite alias name for the first listed repo. Alias names are optional free form text. If not set the source attribute value is used and builds the alias name by replacing each '/' with a '_'. An alias name should be set if the source argument doesn't really explain what this repository contains. The change is temporary and will not be written to the XML file.

```
[--set-repoprio number]
```

Set/Overwrite priority for the first listed repo. Works with the smart packagemanager only. The Channel priority assigned to all packages available in this channel (0 if not set). If the exact same package is available in more than one channel, the highest priority is used.

```
[--add-repo URL, --add-repotype type--add-repoalias name--add-repoprio number]
```

Add the given repository and type for this run of an image prepare or upgrade process. Multiple --add-repo/--add-repotype options are possible. The change will not be written to the config.xml file

```
[--ignore-repos]
```

Ignore all repositories specified so far, in XML or elsewhere. This option should be used in conjunction with subsequent calls to --add-repo to specify repositories at the commandline that override previous specifications.

```
[--logfile Filename|terminal]
```

Write to the log file Filename instead of the terminal.

```
[--gzip-cmd cmd]
```

Specify an alternate command to run when compressing boot and system images. Command must accept **gzip** options.

[--log-port PortNumber]

Set the log server port. By default port 9000 is used. If multiple KIWI processes runs on one system it's recommended to set the logging port per process.

[--package-manager smart/zypper]

Set the package manager to use for this image. If set it will temporarly overwrite the value set in the xml description.

[-A|--target-arch *i586*|*x86*_64|armv5tel|ppc]

Set a special target-architecture. This overrides the used architecture for the image-packages in zypp.conf. When used with smart this option doesn't have any effect.

[--debug]

Prints a stack trace in case of internal errors

[--verbose 1/2/3]

Controls the verbosity level for the instsource module

Image Preparation Options

[-rl--root RootPath]

Set up the physical extend, chroot system below the given root-path path. If no --root option is given, KIWI will search for the attribute defaultroot in config.xml. If no root directory is known, a **mktmp** directory will be created and used as root directory.

[--force-new-root]

Force creation of new root directory. If the directory already exists, it is deleted.

Image Upgrade/Preparation Options

[--cache directory]

When specifying a cache directory kiwi will create a cache each for patterns and packages and re-use them if possible for subsequent root tree preparations of this and/or other images

[--add-package package]

Add the given package name to the list of image packages multiple --add-package options are possible. The change will not be written to the xml description.

[--add-pattern name]

Add the given pattern name to the list of image packages multiple --add-pattern options are possible. The change will not be written to the xml description. Patterns can be handled by SuSE based repositories only.

[--del-package package]

Removes the given package by adding it the list of packages to become removed. The change will not be written to the xml description.

Image Creation Options

[-d|--destdir DestinationPath]

Specify destination directory to store the image file(s) If not specified, KIWI will try to find the attribute defaultdestination which can be specified in the preferences section of the config.xml file. If it exists its value is used as destination directory. If no destination information

can be found, an error occurs.

[-t|--type *Imagetype*]

Specify the output image type to use for this image. Each type is described in a type section of the preferences section. At least one type has to be specified in the config.xml description. By default, the types specifying the *primary* attribute will be used. If there is no primary attribute set, the first type section of the preferences section is the primary type. The types are only evaluated when kiwi runs the --create step. With the option --type one can distinguish between the types stored in config.xml

[-sl--strip]

Strip shared objects and executables only make sense in combination with --create

[--prebuiltbootimage *Directory*]

Search in *Directory* for pre-built boot images.

[--isocheck]

in case of an iso image the checkmedia program generates a md5sum into the iso header. If the --isocheck option is specified a new boot menu entry will be generated which allows to check this media

[--lvm]

Use the logical volume manager to control the disk. The partition table will include one lvm partition and one standard ext2 boot partition. Use of this option makes sense for the create step only and also only for the image types: vmx, oem and usb

[--fs-blocksize number]

When calling kiwi in creation mode this option will set the block size in bytes. For ISO images with the old style ramdisk setup a blocksize of 4096 bytes is required

[--fs-journalsize number]

When calling kiwi in creation mode this option will set the journal size in mega bytes for ext[23] based filesystems and in blocks if the reiser filesystem is used

[--fs-inodesize number]

When calling kiwi in creation mode this option will set the inode size in bytes. This option has no effect if the reiser filesystem is used

[--fs-inoderatio number]

Set the bytes/inode ratio. This option has no effect if the reiser filesystem is used

[--fs-max-mount-count number]

When calling kiwi in creation mode this option will set the number of mounts after which the filesystem will be checked. Set to 0 to disable checks. This option applies only to ext[234] filesystems.

[--fs-check-interval number]

When calling kiwi in creation mode this option will set the maximal time between two filesystem checks. Set to 0 to disable time-dependent checks. This option applies only to ext[234] filesystems.

[--partitioner fdisk/parted]

Select the tool to create partition tables. Supported are fdisk (sfdisk) and parted. By default fdisk is used

[--check-kernel]

Activates check for matching kernels between boot and system image. The kernel check also tries to fix the boot image if no matching kernel was found.

For More Information

More information about KIWI, its files can be found at:

http://en.opensuse.org/Portal:KIWI

KIWI wiki

config.xml

The configuration XML file that contains every aspect for the image creation.

file:///usr/share/doc/packages/kiwi/kiwi.pdf

The system design document which describes some details about the building process.

file:///usr/share/doc/packages/kiwi/schema/kiwi.xsd.html

The KIWI RelaxNG XML Schema documentation.

file:///usr/share/doc/packages/kiwi/schema/test.xsd.html

The KIWI RelaxNG XML Schema documentation.

Name

KIWI::config.sh — Configuration File for KIWI image description

Description

The kiwi image description allows to have an optional config.sh script in place. This script should be designed to take over control of adding the image operating system configuration. Configuration in that sense means stuff like activating services, creating configuration files, prepare an environment for a firstboot workflow, etc. What you shouldn't do in config.sh is breaking your systems integrity by for example removing packages or pieces of software. Something like that can be done in images.sh. config.sh is called *after* the user and groups have been set up. If there are SUSE Linux related YaST xml information these are validated before config.sh is called too. If you exit config.sh with an exit code != 0 kiwi will exit with an error too.

Example 1. Template

Common functions

The .kconfig file allows to make use of a common set of functions. Those which are SUSE Linux specific starts with the name *suse*. Those which are common to all linux systems starts with the name *base*. The following list describes which functions are available for config.sh

```
[baseGetProfilesUsed]
```

Return the name(s) of profiles used to build this image

[baseSetRunlevel {value}]

Set the default run level

[baseSetupBoot]

Set up the linuxrc as init

[baseSetupBusyBox {-f}]

activates busybox if installed for all links from the busybox/busybox.links file - you can choose custom apps to be forced into busybox with the "-f" option as first parameter example:

baseSetupBusyBox -f /bin/zcat /bin/vi

[baseSetupInPlaceGITRepository]

Create an in place git repository of the root directory. This process may take some time and you may expect problems with binary data handling

[baseSetupInPlaceSVNRepository {path_list}]

Create an in place subversion repository for the specified directories. A standard call could look like this baseSetupInPlaceSVNRepository /etc /srv /var/log

[baseSetupPlainTextGITRepository]

Create an in place git repository of the root directory containing all plain/text files.

[baseSetupUserPermissions]

Search all home directories of all users listed in /etc/passwd and change the ownership of all files to belong to the correct user and group

[baseStripAndKeep {list of info-files to keep}]

helper function for strip* functions read stdin lines of files to check for removing params: files which should be keep

[baseStripDocs {list of docu names to keep}]

remove all documentation, except one given as parameter

[baseStripInfos {list of info-files to keep}]

remove all info files, except one given as parameter

[baseStripLocales {list of locales}]

remove all locales, except one given as parameter

[baseStripMans {list of manpages to keep}]

remove all manual pages, except one given as parameter example: baseStripMans more less

[baseStripRPM]

remove rpms defined in config.xml under image=delete section

[baseStripTools {list of toolpath} {list of tools}]

helper function for suseStripInitrd function params: toolpath, tools

[baseStripUnusedLibs]

remove libraries which are not directly linked against applications in the bin directories

[baseUpdateSysConfig {filename} {variable} {value}]

update sysconfig variable contents

[Debug {message}]

Helper function to print a message if the variable DEBUG is set to 1

[Echo {echo commandline}]

Helper function to print a message to the controling terminal

[Rm {list of files}]

Helper function to delete files and anounce it to log

[Rpm {rpm commandline}]

Helper function to the rpm function and anounce it to log

[suseActivateDefaultServices]

Call all postin scriptlets which among other things activates all required default services using suseInsertService

[suseActivateServices]

Check all services in /etc/init.d/ and activate them by calling suseInsertService

[suseCloneRunlevel {runlevel}]

Clone the given runlevel to work in the same way as the default runlevel 3.

[suseConfig]

Setup keytable language and timezone if specified in config.xml and call SuSEconfig afterwards [suseInsertService {servicename}]

Recursively insert a service. If there is a service required for this service it will be inserted first. The suse insserv program is used here

[suseRemoveService {servicename}]

Remove a service and its dependant services using the suse insserv program

[suseService {servicename} {onloff}]

Activate/Deactivate a service by using the chkconfig program The function requires the service name and the value on or off as parameters

[suseServiceDefaultOn]

Activates the following services to be on by default using the chkconfig program: boot.rootfsck boot.cleanup boot.localfs boot.localnet boot.clock policykitd dbus consolekt haldaemon network atd syslog cron kbd

[suse Setup Product Information]

This function will use zypper to search for the installed product and install all product specific packages. This function only makes sense if zypper is used as packagemanager

[suseStripPackager {-a}]

Remove smart o zypper packages and db files Also remove rpm package and db if "-a" given

Profile environment variables

The .profile environment file contains a specific set of variables which are listed below. Some of the functions above makes use of the variables.

[\$kiwi_compressed]

The value of the compressed attribute set in the type element in config.xml

[\$kiwi_delete]

A list of all packages which are part of the packages section with type='delete' in config.xml [\$kiwi_drivers]

A comma seperated list of the driver entries as listed in the drivers section of the config.xml. Similar variables exists for the usbdrivers and scsidrivers sections

[\$kiwi_iname]

The name of the image as listed in config.xml

[\$kiwi_iversion]

The image version string major.minor.release

[\$kiwi_keytable]

The contents of the keytable setup as done in config.xml

[\$kiwi_language]

The contents of the locale setup as done in config.xml

[\$kiwi_profiles]

A list of profiles used to build this image

[\$kiwi_size]

The predefined size value for this image. This is not the computed size but only the optional size value of the preferences section in config.xml

[\$kiwi_timezone]

The contents of the timezone setup as done in config.xml

[\$kiwi_type]

The basic image type. Can be a simply filesystem image type of ext2 ext3 reiserfs squashfs cpio or one of the following complex image types: iso split usb vmx oem xen pxe

kiwi::images.sh

Name

KIWI::images.sh — Configuration File for KIWI image description

Description

The kiwi image description allows to have an optional images.sh script in place. This script is called at the beginning of the kiwi create step. It is allowed to remove software there to shrink down the size of the image. Most often images.sh is used for boot images because they needs to be small. As images.sh is called in the create step you should be aware to design the script in a way that it can be called multiple times without shooting itself into its knee. As kiwi allows to create different image types from one previosly prepared tree one needs to take into account that images.sh can be called more than one time. If you exit images.sh with an exit code != 0 kiwi will exit with an error too.

Example 1. Template

Common functions

The .kconfig file allows to make use of a common set of functions. Those which are SUSE Linux specific starts with the name *suse*. Those which are common to all linux systems starts with the name *base*. The following list describes which functions are available for images.sh

kiwi::images.sh

Return the list of packages setup in the packages type='delete' section of the config.xml used to build this image

[baseSetupOEMPartition]

Writes the file /config.oempartition depending on the following config.xml parameters: oem-reboot, oem-swapsize, oem-systemsize, oem-home,oem-swap,oem-boot-title,oem-recovery, oem-kiwi-initrd. kiwi takes the information from config.xml and creates the config.oempartition file as part of the automatically created boot image (initrd). The information must be available as part of the boot image because it controls the OEM repartition workflow on first boot of an OEM image. Detailed information about the meaning of each option can be found in the OEM chapter in the kiwi cookbook

[suseGFXBoot {theme} {loadertyp}]

This function requires the gfxboot and at least one bootsplash-theme-* package to be installed in order to work correctly. The function creates from this package data a graphics boot screen for the isolinux and grub boot loaders. Additionally it creates the bootsplash files for the resolutions 800x600 1024x768 and 1280x1024

[suseStripKernel]

This function removes all kernel drivers which are not listed in the *drivers sections of the config.xml file

[suseStripInitrd]

This function removes a whole bunch of tools binaries and libraries which are not required in order to boot a suse system with kiwi.

[Rm {list of files}]

Helper function to delete files and anounce it to log

[Rpm {rpm commandline}]

Helper function to the rpm function and anounce it to log

[Echo {echo commandline}]

Helper function to print a message to the controling terminal

[Debug {message}]

Helper function to print a message if the variable DEBUG is set to 1

Profile environment variables

The .profile environment file contains a specific set of variables which are listed below. Some of the functions above makes use of the variables.

[\$kiwi_iname]

The name of the image as listed in config.xml

[\$kiwi_iversion]

The image version string major.minor.release

[\$kiwi_keytablee]

The contents of the keytable setup as done in config.xml

[\$kiwi_language]

The contents of the locale setup as done in config.xml

[\$kiwi_timezone]

The contents of the timezone setup as done in config.xml

[\$kiwi_delete]

A list of all packages which are part of the packages section with type='delete' in config.xml

[\$kiwi_profiles]

A list of profiles used to build this image

[\$kiwi_drivers]

A comma seperated list of the driver entries as listed in the drivers section of the config.xml. Similar

kiwi::images.sh

variables exists for the usbdrivers and scsidrivers sections

[\$kiwi_size]

The predefined size value for this image. This is not the computed size but only the optional size value of the preferences section in config.xml

[\$kiwi_compressed]

The value of the compressed attribute set in the type element in config.xml [\$kiwi_type]

The basic image type. Can be a simply filesystem image type of ext2 ext3 reiserfs squashfs cpio or one of the following complex image types: iso split usb vmx oem xen pxe