


COMPACT OBJECT MERGERS: POPULATION ASTROPHYSICS AND STATISTICS

COMPAS is a platform for the exploration of populations of compact binaries formed through isolated binary evolution (Stevenson et al., 2017; Vigna-Gómez et al., 2018; Barrett et al., 2018; Neijssel et al., 2019; Broekgaarden et al., 2019; Stevenson et al., 2019; Chattopadhyay et al., 2020). The COMPAS population synthesis code is flexible, fast and modular, allowing rapid simulation of binary star evolution. The complete COMPAS suite includes the population synthesis code together with a collection of tools for sophisticated statistical treatment of the synthesised populations.



Visit http://compas.science for more information.

Contents

Revision History	4
User Guide	5
COMPAS Input	5
Grids	5
COMPAS Output	9
Developer Guide	15
SINGLE STAR EVOLUTION	16
Class Hierarchy	16
Evolution Model	18
BINARY STAR EVOLUTION	21
Class Hierarchy	21
Evolution Model	22
Object Identifiers	22
Services	24
PROGRAM OPTIONS	25
RANDOM NUMBERS	26
Logging & Debugging	28
Error Handling	39
FLOATING-POINT COMPARISONS	43
CONSTANTS FILE – constants.h	43
PROGRAMMING STYLE AND CONVENTIONS	46
Object-Oriented Programming	46
Programming Style	47
Naming Conventions	49
COMPILATION & REQUIREMENTS	50
Appendix A – Program Options	
Appendix B – Log File Record Specification: Stellar Properties	62
Stellar Properties	62
Supernova events/states	79
Appendix C – Log File Record Specification: Binary Properties	81
Binary Properties	81
Appendix D – Log File Record Specification: Program Options	93
Program Option Properties	93
Appendix E – Default Log File Record Specifications	94
SSE Parameters	94
BSE System Parameters	95
BSE Detailed Output	96
BSE Double Compact Objects	98

BSE Common Envelopes	99
BSE Supernovae	10
BSE Pulsar Evolution	102
Appendix F – Example Log File Record Specifications File	102

Revision History

Date	Version	Description	Author
2012-2019		Original COMPAS manual	Team COMPAS
1 September 2019	0.1	Initial draft	Jeff Riley
20 September 2019	0.2	Updated compilation requirements	Jeff Riley
1 October 2019	0.3	Added (minimal) CHE documentation	Jeff Riley
21 October 2019	0.4	Added Grids documentation	
		Added Programming Style and Conventions	
		Added Appendices A-E	
		Reformatted for User Guide, Developer Guide etc.	Jeff Riley
18 December 2019	0.5	Updated Grids documentation for kick values	Jeff Riley
20 December 2019	0.6	Updated Appendices A, B, D, E	Jeff Riley
23 January 2020	0.7	Updated Grids documentation for kick values	Jeff Riley
31 March 2020	1.0	Updated for Beta release	Jeff Riley
22 April 2020	1.1	Updated to reflect pre2ndSN -> preSN variable	Simon Stevenson
		changes	
27 April 2020	1.2	Updated to reflect SSE Grid file changes	Jeff Riley

User Guide

Installation instructions for COMPAS and its dependencies are shown in the COMPAS Getting Started guide provided in the COMPAS suite. Please refer to that guide for dependency requirements etc.

COMPAS Input

COMPAS provides wide-ranging functionality and affords users much flexibility in determining how the synthesis and evolution of stars (single or binary) is conducted. Users configure COMPAS functionality and provide initial conditions via the use of program options, described in Appendix A – Program Options. Initial conditions can also be provided via Grid files, described below.

A convenient method of managing the many program options provided by COMPAS (Appendix A – Program Options) is the example Python script provided in the COMPAS suite. The example script provided is pythonSubmitDefault.py – users should copy and modify their copy of the script to match their experimental requirements. Refer to the Getting Started guide for more details.

Grids

Grid functionality allows users to specify a grid of initial values for both Single Star Evolution (SSE) and Binary Star Evolution (BSE).

For SSE, users can supply a text file that contains initial mass values and, optionally, metallicity and supernova kick related values, and COMPAS will evolve individual stars with those initial values (one star per record).

For BSE, users can supply a text file that contains initial mass and metallicity values for the binary constituent stars, as well as the initial separation or orbital period, and eccentricity, of the binary (one binary star per record of initial values).

Grid File Format

Grid files are comma-separated text files, with column headers denoting the meaning of the data in the column (with an exception for SSE Grid files – see below for details).

Grid files may contain comments. Comments are denoted by the hash/pound character ('#'). The hash character and any text following it on the line in which the hash character appears is ignored. The hash character can appear anywhere on a line - if it is the first character then the entire line is a comment and ignored, or it can follow valid characters on a line, in which case the characters before the hash are processed, but the hash character and any text following it is ignored. Blank lines are ignored.

Notwithstanding the exception for SSE Grid files mentioned above, the first non-comment, non-blank line in a Grid file must be the header record. The header record is a comma-separated list of strings that denote the meaning of the data in each of the columns in the file.

Data records follow the header record. Data records, with an exception for SSE data files described below, are comma-separated lists of non-negative floating-point numbers. Any data field that contains a negative number, or characters that do not convert to floating-point numbers, is considered an error and will cause processing of the Grid file to be abandoned – an error message will be displayed.

Data records are expected to contain the same number of columns as the header record. If a data record contains more columns than the header record, data beyond the number of columns in the header record is ignored. If a data record contains fewer columns than the header record, missing data values (by position) are set equal to 0.0 - a warning message will be displayed.

BSE Grid File

Header Record

The BSE Grid file header record must be a comma-separated list of strings taken from the following list (case is not significant):

Header String	Column meaning
Mass_1	mass value to be assigned to the primary star, in M_{\odot}
Mass_2	mass value to be assigned to the secondary star, in M_{\odot}
Metallicity_1	metallicity value to be assigned to the primary star
Metallicity_2	metallicity value to be assigned to the secondary star
Separation	separation of the stars – the semi-major axis value to be assigned to the binary, in AU
Eccentricity	eccentricity value to be assigned to the binary
Period	orbital period value to be assigned to the binary, in days
Kick_Velocity_Random_1	value to be used as the kick velocity magnitude random number, used to draw the kick velocity, for the primary star should it undergo a supernova event. This must be a floating-point number in the range [0.0, 1.0). If this column is present in the grid file, the kick velocity for the primary star, should it
	undergo a supernova event, will be drawn from the appropriate distribution at the time of the SN event. This column is used in preference to the <i>Kick_Velocity_1</i> column if both are present in the grid file.
Kick_Velocity_1	value to be used as the (drawn) kick velocity for the primary star should it undergo a supernova event, in <i>kms</i> ^-1. If both this column and <i>Kick_Velocity_Random_1</i> are present in the grid file, <i>Kick_Velocity_Random_1</i> will be used in preference to <i>Kick_Velocity_1</i> .
Kick_Theta_1	value to be as the angle between the orbital plane and the 'z' axis of the supernova vector for the primary star should it undergo a supernova event, in <i>radians</i>
Kick_Phi_1	value to be used as the angle between 'x' and 'y', both in the orbital plane of the supernova vector, for the primary star should it undergo a supernova event, in <i>radians</i>
Kick_Mean_Anomaly_1	value to be used as the mean anomaly at the instant of the supernova for the primary star should it undergo a supernova event – should be uniform in [0, 2pi)
Kick_Velocity_Random_2	value to be used as the kick velocity magnitude random number, used to draw the kick velocity, for the secondary star should it undergo a supernova event. This must be a floating-point number in the range [0.0, 1.0).
	If this column is present in the grid file, the kick velocity for the secondary star, should it undergo a supernova event, will be drawn from the appropriate distribution at the time of the SN event. This column is used in preference to the <i>Kick_Velocity_2</i> column if both are present in the grid file.
Kick_Velocity_2	value to be used as the (drawn) kick velocity for the secondary star should it undergo a supernova event, in <i>kms</i> ^-1. If both this column and <i>Kick_Velocity_Random_2</i> are present in the grid file, <i>Kick_Velocity_Random_2</i> will be used in preference to <i>Kick_Velocity_2</i> .
Kick_Theta_2	value to be as the angle between the orbital plane and the 'z' axis of the supernova vector for the secondary star should it undergo a supernova event, in <i>radians</i>
Kick_Phi_2	value to be used as the angle between 'x' and 'y', both in the orbital plane of the supernova vector, for the secondary star should it undergo a supernova event, in <i>radians</i>
Kick_Mean_Anomaly_2	value to be used as the mean anomaly at the instant of the supernova for the secondary star should it undergo a supernova event – should be uniform in [0, 2pi)

All header strings in **bold** in the table above are required in the header record, with the exception of Separation and Period: one of Separation and Period *must* be present, but both *may* be present.

The header strings in *italics* in the table above (the kick-related header strings) are not mandatory. However, if one of the kick-related header strings is present, then *all must* be present.

The order of the columns in the BSE Grid file is not significant.

Data Record

See the general description of data records above.

As for the header record, only one of Separation and Period is required to be present, but both may be present. The period may be used to calculate the separation of the binary. If the separation is present it is used as the value for the semi-major axis of the binary, regardless of whether the period is present (Separation has precedence over Period). If the period is present, but separation is not, the separation is calculated form the masses of the stars and the period given.

Also as for the header record, the kick-related values are not mandatory, but if one of the kick-related values is given, then all must be given.

SSE Grid File

Header Record

The SSE Grid file header record must be a comma-separated list of strings taken from the following list (case is not significant):

Header String	Column meaning
Mass	mass value () to be assigned to the star (M_{\odot})
Metallicity	metallicity value to be assigned to the star
Kick_Velocity_Random	value to be used as the kick velocity magnitude random number, used to draw the kick velocity, for the star should it undergo a supernova event. This must be a floating-point number in the range [0.0, 1.0).
	If this column is present in the grid file, the kick velocity for the star, should it undergo a supernova event, will be drawn from the appropriate distribution at the time of the SN event. This column is used in preference to the Kick_Velocity column if both are present in the grid file.
Kick_Velocity	value to be used as the (drawn) kick velocity for the star should it undergo a supernova event, in kms^-1. If both this column and Kick_Velocity_Random are present in the grid file, Kick_Velocity_Random will be used in preference to Kick_Velocity.

The SSE Grid file is only required to list Mass values for each star, with Metallicity and Kick values being optional. If the Metallicity column is omitted, the metallicity value assigned to the star is the user-specified value for metallicity via the program options (OPTIONS—Metallicity()).

If the Metallicity column is omitted from the SSE Grid file, the header is optional: if there is only one column of data in the SSE Grid file it is assumed to be the Mass column, and no header is required (though may be present). If the Metallicity column header is present, the Mass column header is required.

The order of the columns in the SSE Grid file is not significant.

Data Record

COMPAS Output

Summary and status information during the evolution of stars is written to stdout; how much is written depends upon the value of the *quiet* program option.

Detailed information is written to log files (described below). All COMPAS output files are created inside a container directory, specified by the *output-container* program option. If BSE Detailed Output log files are created (see the *detailedOutput* program option) they will be created inside a containing directory named 'Detailed_Output' within the COMPAS output container directory. Also created in the COMPAS container directory is a filed named 'Run_Details' in which COMPAS records some details of the run (COMPAS version, start time, program option values etc.).

COMPAS defines several standard log files that may be produced depending upon the simulation type (Single Star Evolution (SSE), or Binary Star Evolution (BSE), and the value of various program options. The standard log files are:

- SSE Parameters log file
- BSE System Parameters log file
- BSE Detailed Output log file
- BSE Double Compact Objects log file
- BSE Common Envelopes log file
- BSE Supernovae log file
- BSE Pulsar Evolution log file

Standard Log File Record Specifiers

Each standard log file has an associated log file record specifier that defines what data are to be written to the log files. Each record specifier is a list of known properties that are to be written as the log record for the log file associated with the record specifier. Default record specifiers for each of the standard log files are shown in Appendix E – Default Log File Record Specifications. The standard log file record specifiers can be defined by the user at run-time (see Standard Log File Record Specification below).

When specifying known properties, the property name must be prefixed with the property type. The current list of valid property types available for use is:

- STAR PROPERTY
- STAR 1 PROPERTY
- STAR 2 PROPERTY
- SUPERNOVA PROPERTY
- COMPANION PROPERTY
- BINARY PROPERTY
- PROGRAM OPTION

The stellar property types (all types except BINARY_PROPERTY AND PROGRAM_OPTION) must be paired with properties from the stellar property list, the binary property type BINARY_PROPERTY with properties from the binary property list, and the program option type PROGRAM_OPTION with properties from the program option property list.

Standard Log File Record Specification

The standard log file record specifiers can be changed at run-time by supplying a definitions file via the *logfile-definitions* program option.

The syntax of the definitions file is fairly simple. The definitions file is expected to contain zero or more log file record specifications, as explained below.

For the following specification:

Logfile Definitions File specification:

```
<def file> ::= { <rec spec> }
<rec spec> ::= <rec name> <op> "{" { [ <props list> ] } "}" <spec delim>
          ::= "SSE PARMS REC"
<rec name>
                                                  # SSE only
             "BSE_SYSPARMS_REC"
                                                  # BSE only
             "BSE DCO REC"
                                                  # BSE only
             "BSE SNE REC"
                                                  # BSE only
             "BSE CEE REC"
                                                  # BSE only
             "BSE PULSARS REC"
                                                  # BSE only
             "BSE DETAILED REC"
                                                  # BSE only
          ::= "=" | "+=" | "-="
<0p>
props list> ::=  spec> [  delim>  list> ]
<spec delim> ::= " " | EOL
cprop_delim> ::= "," | <spec_delim>
# SSE only
             "STAR 1 PROPERTY"
                                                  # BSE only
             "STAR 2 PROPERTY"
                                                  # BSE only
             "SUPERNOVA PROPERTY" |
                                                  # BSE only
             "COMPANION PROPERTY" |
                                                  # BSE only
             "BINARY PROPERTY"
                                                  # BSE only
             "PROGRAM OPTION"
                                                  # SSE or BSE
(see definitions in constants.h)
```

The file may contain comments. Comments are denoted by the hash/pound character ('#'). The hash character and any text following it on the line in which the hash character appears is ignored by the parser. The hash character can appear anywhere on a line - if it is the first character then the entire line is a comment and ignored by the parser, or it can follow valid symbols on a line, in which case the symbols before the hash character are parsed and interpreted by the parser.

A log file specification record is initially set to its default value (see Appendix E – Default Log File Record Specifications). The definitions file informs the code as to the modifications to the default values the user wants. This means that the definitions log file is not mandatory, and if the definitions file is not present, or contains no valid record specifiers, the log file record definitions will remain at their default values.

The assignment operator given in a record specification (<op> in the file specification above) can be one of "=", "+=", and "-=". The meanings of these are:

"=" means that the record specifier should be assigned the list of properties specified in the braced-list following the "=" operator. The value of the record specifier prior to the assignment is discarded, and the new value set as described.

"+=" means that the list of properties specified in the braced-list following the "+=" operator should be appended to the existing value of the record specifier. Note that the new properties are appended to the existing list, so will appear at the end of the list (properties are printed in the order they appear in the list).

"-=" means that the list of properties specified in the braced-list following the "-=" operator should be subtracted from the existing value of the record specifier.

Example Log File Definitions File entries:

A full example Log File Record Specifications File is shown in Appendix F – Example Log File Record Specifications File.

The record specifications in the definitions file are processed individually in the sequence they appear in the file, and are cumulative: for record specifications pertaining to the same record name, the output of earlier specifications is input to later specifications.

For each record specification:

- Properties requested to be added to an existing record specification that already exist in that record specification are ignored. Properties will not appear in a record specification twice.
- Properties requested to be subtracted from an existing record specification that do not exist in that record specification are ignored.

Note that neither of those circumstances will cause a parse error for the definitions file – in both cases the user's intent is satisfied.

Standard Log File Format

Each standard log file consists three header records followed by data records. Header records and data records are delimiter separated fields, with the delimiter being that specified by the logfile-delimiter program option (COMMA, TAB or SPACE), and the fields as specified by the log file record specifier.

The header records for all files are:

Header record 1: Column Data Type Names

Header record 2: Column Units (where applicable)

Header record 3: Column Headings

Column Data Type Names are taken from the set {BOOL, INT, FLOAT, STRING}, where

BOOL the data value will be a boolean value. Boolean data values will be recorded in the log file in either numerical format (1 or 0, where 1 = TRUE and 0 = FALSE), or string format ('TRUE' or 'FALSE'), depending upon the value of the print-bool-as-string program option.

INT the data value will be an integer number

FLOAT the data value will be a floating-point number

STRING the data value will be a text string

Column Units is a string indicating the units of the corresponding data values (e.g. 'Msol*AU^2*yr^-1', 'Msol', 'AU', etc.). The Column Units value may be blank where units are not applicable, or may be one of:

'Count' the data value is the total of a counted entity

'State' the data value describes a state (e.g. 'Unbound' state is 'TRUE' or 'FALSE')
'Event' the data value describes an event status (e.g. 'Simultaneous RLOF' is 'TRUE')

Column Headings are string labels that describe the corresponding data values. The heading strings for stellar properties of constituent stars of a binary will have appropriate identifiers appended. That is, heading strings for:

STAR_1_PROPERTY::properties will have "_1" appended STAR_2_PROPERTY::properties will have "_2" appended SUPERNOVA_PROPERTY::properties will have "_SN" appended COMPANION PROPERTY::properties will have " CP" appended

Developer Guide

Team COMPAS welcomes the active involvement of colleagues and others interested in the field in the ongoing development and improvement of the COMPAS software. We hope this Developer Guide helps anyone interested in contributing to the COMPAS software. We expect this guide to be a living document and improve along with the improvements made to the software.

SINGLE STAR EVOLUTION

Class Hierarchy

The main class for single star evolution is the **Star** class.

The Star class is a wrapper that abstracts away the details of the star and the evolution. Internally the Star class maintains a pointer to an object representing the star being evolved, with that object being an instance of one of the following classes:

MS_lte_07

MS_gt_07

CH

HG

FGB

CHeB

EAGB

TPAGB

HeMS

HeHG

HeGB

HeWD

COWD

ONeWD

NS

BH

MR

which track the phases from Hurley et al. 2000, with the exception of the CH class for Chemically Homogeneous stars, which is not described in Hurley et al. 2000.

Three other SSE classes are defined:

BaseStar MainSequence GiantBranch

These extra classes are included to allow inheritance of common functionality.

The BaseStar class is the main class for the underlying star object held by the Star class. The BaseStar class defines all member variables, and many member functions that provide common functionality. Similarly, the MainSequence and GiantBranch classes provide repositories for common functionality for main sequence and giant branch stars respectively.

The inheritance chain follows the phases described in Hurley et al. 2000 (again, with the exception of the CH, not described by Hurley et al. 2000), and is as follows:

```
Star BaseStar \rightarrow MainSequence \rightarrow ( MS_lte_07 ) ( MS_gt_07 ) \rightarrow CH ( GiantBranch ) \rightarrow HG \rightarrow FGB \rightarrow CheB \rightarrow EAGB \rightarrow TPAGB \rightarrow HeMS \rightarrow HeHG \rightarrow HeGB \rightarrow HeWD \rightarrow COWD \rightarrow OneWD \rightarrow NS \rightarrow BH \rightarrow MR
```

CH (Chemically Homogeneous) stars inherit from MS_gt_07 because (in this implementation) they are just (large) main sequence stars that have a static radius.

HG (Hertzsprung Gap) stars inherit from the GiantBranch because they share the Giant Branch Parameters described in Hurley et al. 2000, section 5.2.

Each class in the inheritance chain has its own set of member functions that calculate various attributes of the star according to the phase the class represents (using the equations and parameters from Hurley et al. 2000 where applicable).

Evolution Model

The stellar evolution model is driven by the Evolve() function in the Star class which evolves the star through its entire lifetime by doing the following:

DO:

- 1. calculate time step
 calculate the giant branch parameters (as necessary)
 calculate the timescales
 choose time step
- 2. save the state of the underlying star object
- 3. DO:
- a) evolve a single time step
- b) if too much change revert to the saved state reduce the size of the time step

UNTIL timestep not reduced

- 4. resolve any mass loss
 - a) update initial mass (mass0)
 - b) update age after mass loss
 - c) apply mass transfer rejuvenation factor
- 5. evolve to the next stellar type if necessary

WHILE the underlying star object is not one of: { HeWD, COWD, ONeWD, NS, BH, MR }

Evolving the star through a single time step (step 3a above) is driven by the UpdateAttributesAndAgeOneTimestep() function in the BaseStar class which does the following:

- 1. check if the star should be a massless remnant
- 2. check if the star is a supernova

if evolution on the phase should be performed

- 3. evolve the star on the phase update stellar attributes
- 4. check if the star should evolve off the current phase to a different stellar type else
- 5. ready the star for the next time step

Evolving the star on its current phase, and off the current phase and preparing to evolve to a different stellar type, is handled by two functions in the BaseStar class: EvolveOnPhase() and ResolveEndOfPhase().

The EvolveOnPhase() function does the following:

- 1. Calculate Tau
- 2. Calculate CO Core Mass
- 3. Calculate Core Mass
- 4. Calculate He Core Mass
- 5. Calculate Luminosity
- 6. Calculate Radius
- 7. Calculate Envelope Mass
- 8. Calculate Perturbation Mu
- 9. Perturb Luminosity and Radius
- 10. Calculate Temperature
- 11. Resolve possible envelope loss

Each of the calculations in the EvolveOnPhase() function is performed in the context of the star evolving on its current phase. Each of the classes implements their own version of the calculations (via member functions) – some may inherit functions from the inheritance chain, while others might just return the value unchanged if the calculation is not relevant to their stellar type.

The ResolveEndOfPhase() function does the following:

- 1. Resolve possible envelope loss
- 2. Calculate Tau
- 3. Calculate CO Core Mass
- 4. Calculate Core Mass
- 5. Calculate He Core Mass
- 6. Calculate Luminosity
- 7. Calculate Radius
- 8. Calculate Envelope Mass
- 9. Calculate Perturbation Mu
- 10. Perturb Luminosity and Radius
- 11. Calculate Temperature
- 12. Evolve star to next phase

Each of the calculations in the ResolveEndOfPhase() function is performed in the context of the star evolving off its current phase to the next phase.

The remainder of the code (in general terms) supports these main driver functions.

BINARY STAR EVOLUTION

Class Hierarchy

The main class for single star evolution is the **BinaryStar** class. The BinaryStar class is a wrapper that abstracts away the details of the binary star and the evolution. Internally the BinaryStar class maintains a pointer to an object representing the binary star being evolved, with that object being an instance of the BaseBinaryStar class.

The BaseBinaryStar class is the main class for the underlying binary star object held by the BinaryStar class. The BaseBinaryStar class defines all member variables that pertain specifically to a binary star, and many member functions that provide binary-star specific functionality. Internally the BaseBinaryStar class maintains pointers to the two BinaryConstituentStar class objects that constitute the binary star.

The BinaryConstituentStar class inherits from the Star class, so objects instantiated from the BinaryConstituentStar class inherit the characteristics of the Star class, particularly the stellar evolution model. The BinaryConstituentStar class defines member variables and functions that pertain specifically to a constituent star of a binary system but that do not (generally) pertain to single stars that are not part of a binary system (there are some functions that are defined in the BaseStar class and its derived classes that deal with binary star attributes and behaviour – in some cases the stellar attributes that are required to make these calculations reside in the BaseStar class so it is easier and cleaner to define the functions there).

The inheritance chain is as follows:

```
BinaryStar → BaseBinaryStar

(Star → ) BinaryConstituentStar (star1)
(Star → ) BinaryConstituentStar (star2)
```

Evolution Model

The binary evolution model is driven by the Evolve() function in the BaseBinaryStar class which evolves the star through its entire lifetime by doing the following:

```
if (touching OR secondary too small)
       STOP = true
else
       calculate initial time step
       STOP = false
DO WHILE !STOP AND !max iterations:
       evolve a single time step
               evolve each constituent star a single time step (see SSE evolution)
       if (unbound OR touching OR Massless Remnant)
               STOP = true
       else
               evaluate the binary
                       calculate lambdas if necessary
                       calculate zetas if necessary
                       calculate mass transfer
                       calculate winds mass loss
                       if common envelope
                               resolve common envelope
                       else if supernova
                              resolve supernova
                       else
                               resolve mass changes
                       evaluate supernovae
                       resolve tides
                       calculate total energy and angular momentum
                       update magnetic field and spin: both constituent stars
               if (unbound OR touching OR merger)
                       STOP = true
               else
                       if NS+BH
                               resolve coalescence
                               if AIS exploratory phase
                                      calculate DCO Hit
                               STOP = true
                       else
                               if (WD+WD OR max time)
                                      STOP = true
                               else
                                      if NOT max iterations
                                              calculate new time step
```

OBJECT IDENTIFIERS

All objects (instantiations of a class) are assigned unique object identifiers of type OBJECT_ID (unsigned long int - see constants.h for the typedef). In the original COMPAS code, all binary star

objects were assigned unique object ids – this is just an extension of that so that all objects created in the COMPAS code are assigned unique ids. The purpose of the unique object id is to aid in object tracking and debugging.

As well as unique object ids, all objects are assigned an object type (of type OBJECT_TYPE – see constants.h for the enum class declaring OBJECT_TYPE), and a stellar type where applicable (of type STELLAR_TYPE – see constants.h for the enum class declaring STELLAR_TYPE).

Objects should expose the following functions:

```
OBJECT_ID ObjectId() const { return m_ObjectId; }
OBJECT_TYPE ObjectType() const { return m_ObjectType; }
STELLAR_TYPE StellarType() const { return m_StellarType; }
```

If any of the functions are not applicable to the object, then they must return "*::NONE (all objects should implement ObjectId() correctly).

Any object that uses the Errors service (i.e. the SHOW_* macros) <u>must</u> expose these functions: the functions are called by the SHOW_* macros (the Errors service is described later in this document).

SERVICES

A number of services have been provided to help simplify the code. These are:

- Program Options
- Random Numbers
- Logging and Debugging
- Error Handling

The code for each service is encapsulated in a singleton object (an instantiation of the relevant class). The singleton design pattern allows the definition of a class that can only be instantiated once, and that instance effectively exists as a global object available to all the code without having to be passed around as a parameter. Singletons are a little anti-OO, but provided they are used judiciously are not necessarily a bad thing, and can be very useful in certain circumstances.

PROGRAM OPTIONS

A Program Options service is provided encapsulated in a singleton object (an instantiation of the Options class).

The Options class member variables are private, and public getter functions have been created for the program options currently used in the code.

The Options service can be accessed by referring to the Options::Instance() object. For example, to retrieve the value of the "quiet" program option, call the Quiet() getter function:

```
bool quiet = Options::Instance()→Quiet();
```

Since that could become unwieldy, there is a convenience macro to access the Options service. The macro just defines "OPTIONS" as "Options::Instance()", so retrieving the value of the "quiet" program option can be written as:

```
bool quiet = OPTIONS→Quiet();
```

The Options service must be initialised before use. Initialise the Options service by calling the Initialise() function:

COMMANDLINE STATUS programStatus = OPTIONS->Initialise(argc, argv);

(see constants.h for details of the COMMANDLINE STATUS type)

RANDOM NUMBERS

A Random Number service is provided, with the gsl Random Number Generator encapsulated in a singleton object (an instantiation of the Rand class).

The Rand class member variables are private, and public functions have been created for random number functionality required by the code.

The Rand service can be accessed by referring to the Rand::Instance() object. For example, to generate a uniform random floating point number in the range [0, 1), call the Random() function:

```
double u = Rand::Instance() \rightarrow Random();
```

Since that could become unwieldy, there is a convenience macro to access the Rand service. The macro just defines "RAND" as "Rand::Instance()", so calling the Random() function can be written as:

```
double u = RAND \rightarrow Random();
```

The Rand service must be initialised before use. Initialise the Rand service by calling the Initialise() function:

RAND->Initialise();

Dynamically allocated memory associated with the gsl random number generator should be returned to the system by calling the Free() function:

RAND→**Free()**;

before exiting the program.

The Rand service provides the following public member functions:

void Initialise()

Initialises the gsl random number generator. If the environment variable GSL_RNG_SEED exists, the gsl random number generator is seeded with the value of the environment variable, otherwise it is seeded with the current time.

void Free()

Frees any dynamically allocated memory.

unsigned long int Seed(const unsigned long p_Seed)

Sets the seed for the gsl random number generator to p Seed. The return value is the seed.

unsigned long int DefaultSeed()

Returns the gsl default seed (gsl_rng_default_seed)

double Random(void)

Returns a random floating point number uniformly distributed in the range [0.0, 1.0)

double Random(const double p Lower, const double p Upper)

Returns a random floating point number uniformly distributed in the range [p_Lower, p_Upper), where p_Lower <= p_Upper.

(p_Lower and p_Upper will be swapped if p_Lower > p Upper as passed)

double RandomGaussian(const double p_Sigma)

Returns a Gaussian random variate, with mean 0.0 and standard deviation p Sigma

int RandomInt(const int p_Lower, const int p_Upper)

Returns a random integer number uniformly distributed in the range [p_Lower, p_Upper), where p_Lower <= p_Upper.

(p Lower and p Upper will be swapped if p Lower > p Upper as passed)

int RandomInt(const int p Upper)

Returns a random integer number uniformly distributed in the range $[0, p_Upper)$, where $0 \le p$ Upper. Returns 0 if p Upper ≤ 0 .

LOGGING & DEBUGGING

A logging and debugging service is provided encapsulated in a singleton object (an instantiation of the Log class).

The logging functionality was first implemented when the Single Star Evolution code was refactored, and the base-level of logging was sufficient for the needs of the SSE code. Refactoring the Binary Star Evolution code highlighted the need for expanded logging functionality. To provide for the logging needs of the BSE code, new functionality was added almost as a wrapper around the original, base-level logging functionality. Some of the original base-level logging functionality has almost been rendered redundant by the new functionality implemented for BSE code, but it remains (almost) in its entirety because it may still be useful in some circumstances.

When the base-level logging functionality was created, debugging functionality was also provided, as well as a set of macros to make debugging and the issuing of warning messages easier. A set of logging macros was also provided to make logging easier. The debug macros are still useful, and their use is encouraged (rather than inserting print statements using std::cout or std::cerr).

When the BSE code was refactored, some rudimentary error handling functionality was also provided in the form of the Errors service - an attempt at making error handling easier. Some of the functionality provided by the Errors service supersedes the DBG_WARN* macros provided as part of the Log class, but the DBG_WARN* macros are still useful in some circumstances (and in fact are still used in various places in the code). The LOG* macros are somewhat less useful, but remain in case the original base-level logging functionality (that which underlies the expanded logging functionality) is used in the future (as mentioned above, it could still be useful in some circumstances). The Errors service is described later in this document.

The expanded logging functionality introduces Standard Log Files - described later in this document.

Base-Level Logging

The Log class member variables are private, and public functions have been created for logging and debugging functionality required by the code.

The Log service can be accessed by referring to the Log::Instance() object. For example, to stop the logging service, call the Stop() function:

$$Log::Instance() \rightarrow Stop();$$

Since that could become unwieldy, there is a convenience macro to access the Log service. The macro just defines "LOGGING" as "Log::Instance()", so calling the Stop() function can be written as:

LOGGING→Stop();

The Log service must be initialised before logging and debugging functionality can be used. Initialise logging by calling the Start() function:

```
LOGGING→Start(
       outputPath.
                             - location of logfiles
       containerName,
                              - directory to be created at p LogBasePath to hold all log files
       logfilePrefix,
                              - prefix for logfile names (can be blank)
                              - logging level (integer) (see below)
       logLevel,
       logClasses,
                              - array of enabled logging classes (strings) (see below)
                              - debug level (integer) (see below)
       debugLevel,
                              - array of enabled debug classes (strings) (see below)
       debugClasses,
       debugToLogfile,
                              - flag (boolean) indicating whether debug statements should also be
                               written to log file
       errorsToLogfile,
                              - flag (boolean) indicating whether error messages should also be
                               written to log file
       delimiter
                              - string (usually single character) to be used as the default field
                               delimiter in log file records
)
```

Start() returns nothing (void function).

The Log service should be stopped before exiting the program – this ensures all open log files are flushed to disk and closed properly. Stop logging by calling the Stop() function:

```
LOGGING→Stop(
objectStats - { number of objects (stars or binaries) requested, count created }
)
Stop() flushes any closes any open log files.
Stop() returns nothing (void function).
```

The Log service provides the following public member functions:

```
void Start(
 outputPath,
                       - location of logfiles- the directory in which log files will be created
 containerName,
                        - directory to be created at p LogBasePath to hold all log files
 logfilePrefix,
                        - prefix for logfile names (can be blank)
                        - logging level (integer) (see below)
 logLevel,
                       - array of enabled logging classes (strings) (see below)
 logClasses,
 debugLevel,
                        - debug level (integer) (see below)
 debugClasses,
                        - array of enabled debug classes (strings) (see below)
 debugToLogfile,
                        - flag (boolean) indicating whether debug statements should also be
                         written to log file
 errorsToLogfile,
                        - flag (boolean) indicating whether error messages should also be
                         written to log file
 delimiter
                        - string (usually single character) to be used as the default field
                         delimiter in log file records
)
```

Initialises the logging and debugging service. Logging parameters are set per the program options specified (using default values if no options are specified by the user). The log file container directory is created. If a directory with the name as given by the *containerName*

parameter already exists, a version number will be appended to the directory name. The Run_Details file is created within the logfile container directory. Log files to which debug statements and error messages will be created and opened if required.

Stops the logging and debugging service. All open log files are flushed to disk and closed (including and Standard Log Files open - see description of Standard Log Files later in this document). The Run Details file is populated and closed.

bool Enabled()

Returns a boolean indicating whether the Log service is enabled – true indicates the Log service is enable and available; false indicates the Log service is not enable and so not available.

int Open(

logFileName,	- the name of the log file to be created and opened. This should be the filename only – the path, prefix and extensions are added by the logging service. If the file already exists, the logging service will append a version number to the name if necessary (see <i>append</i> parameter below).
append,	- flag (boolean) indicating whether the file should be opened in append mode (i.e. existing data is preserved) and new records written to the file appended, or whether a new file should be opened (with version number if necessary).
timeStamps,	- flag (boolean) indicating whether timestamps should be written with each log file record.
labels	- flag (boolean) indicating whether a label should be written with each log record. This is useful when different types of logging data is being written to the same log file file.
delimiter	- (optional) string (usually single character) to be used as the field delimiter in this log file. If <i>delimiter</i> is not provided the default delimiter is used (as parameter to Start()).

Opens a log file. If the append parameter is true and a file name *logFilename* exists, the existing file will be opened and the existing contents retained, otherwise a new file will be created and opened (not a Standard Log File - see description of Standard Log Files later in this document).

The log file container directory is created at the path specified by the *outputPath* parameter passed to the Start() function. New log files are created in the logfile container directory. BSE

Detailed log files are created in the Detailed_Output directory, which is created in the log file container directory if required.

The filename is prefixed by the *logfilePrefix* parameter passed to the Start() function.

The file extension is based on the *delimiter* parameter passed to the Start() function: if the delimiter is SPACE, the file extension is ".txt"; if the delimiter is TAB the file extension is ".tsv"; if the delimiter is COMMA the file extension is ".csv".

If a file with the name as given by the *logFilename* parameter already exists, and the *append* parameter is false, a version number will be appended to the filename before the extension (this functionality is largely redundant since the implementation of the log file container directory).

The log file identifier (integer) is returned to the caller - a value of -1 indicates the log file was not opened successfully. Multiple log files can be open simultaneously – referenced by the identifier returned.

```
bool Close(logFileId,- the identifier of the log file to be closed (as returned by Open())
```

Closes the log file specified by the *logFileId* parameter. If the log file specified by the *logFileId* parameter is open, it is flushed to disk and closed. The function returns a boolean indicating whether the file was closed successfully.

Writes an unformatted record to the specified log file. If the Log service is enabled and the specified log file is active, and the log class and log level passed are enabled (see discussion of log classes and levels), the string is written to the file.

The function returns a boolean indicating whether the record was written successfully. If an error occurred the log file will be disabled.

bool Put(logFileId,	- the identifier of the log file to be written
logClass,	- string specifying the log class to be associated with the record to be written. Can be blank.
logLevel,	- integer specifying the log level to be associated with the record to be written.
logString,	- the string to be written to the log file.

Writes a minimally formatted record to the specified log file. If the Log service is enabled and the specified log file is active, and the log class and log level passed are enabled (see discussion of log classes and levels), the string is written to the file.

If labels are enabled for the log file, a label will be prepended to the record. The label text will be the *logClass* parameter.

If timestamps are enabled for the log file, a formatted timestamp is prepended to the record. The timestamp format is *yyyymmdd hh:mm:ss*.

The function returns a boolean indicating whether the record was written successfully. If an error occurred the log file will be disabled.

bool Debug(debugClass,	- string specifying the debug class to be associated with the record to be written. Can be blank.
debugLevel,	- integer specifying the debug level to be associated with the record to be written.
debugString,	- the string to be written to stdout (and optionally to file)

Writes *debugString* to stdout and, if logging is active and so configured (via program option debug-to-file), writes *debugString* to the debug log file.

The function returns a boolean indicating whether the record was written successfully. If an error occurred writing to the debug log file, the log file will be disabled.

Writes *debugString* to stdout and, if logging is active and so configured (via program option debug-to-file), writes *debugString* to the debug log file, then waits for user input.

The function returns a boolean indicating whether the record was written successfully. If an error occurred writing to the debug log file, the log file will be disabled.

```
bool Error(errorString,- the string to be written to stdout (and optionally to file)
```

Writes *errorString* to stdout and, if logging is active and so configured (via program option errors-to-file), writes *errorString* to the error log file, then waits for user input.

The function returns a boolean indicating whether the record was written successfully. If an error occurred writing to the error log file, the log file will be disabled.

```
void Squawk(
squawkString, - the string to be written to stderr)
```

Writes *squawkString* to stderr.

```
void Say(
sayClass,

string specifying the log class to be associated with the record to be written. Can be blank.

sayLevel,

integer specifying the log level to be associated with the record to be written.

sayString,

the string to be written to stdout
```

Writes sayString to stdout.

The filename to which debug records are written when Start() parameter "debugToLogfile" is true is declared in constants.h — see the LOGFILE enum class and associate descriptor map LOGFILE DESCRIPTOR. Currently the name is 'Debug Log'.

Extended Logging

The Logging service was extended to support standard log files for Binary Star Evolution (SSE also uses the extended logging). The standard log files defined are:

- SSE Parameters log file
- BSE System Parameters log file
- BSE Detailed Output log file
- BSE Double Compact Objects log file
- BSE Common Envelopes log file
- BSE Supernovae log file
- BSE Pulsar Evolution log file

The Logging service maintains information about each of the standard log files, and will handle creating, opening, writing and closing the files. For each execution of the COMPAS program that evolves binary stars, one (and only one) of each of the log file listed above will be created, except for the Detailed Output log in which case there will be one log file created for each binary star evolved.

The Log service provides the following public member functions specifically for managing standard log files:

```
void LogSingleStarParameters(Star, Id)
void LogBinarySystemParameters(Binary)
void LogDetailedOutput(Binary, Id)
void LogDoubleCompactObject(Binary)
void LogCommonEnvelope(Binary)
void LogSupernovaDetails(Binary)
void LogPulsarEvolutionParameters(Binary)
```

Each of the BSE functions is passed a pointer to the binary star for which details are to be logged, and in the case of the Detailed Output log file, an integer identifier (typically the loop index of the binary star) that is appended to the log file name.

The SSE function is passed a pointer to the single star for which details are to be logged, and an integer identifier (typically the loop index of the star) that is appended to the log file name.

Each of the functions listed above will, if necessary, create and open the appropriate log file. Internally the Log service opens (creates first if necessary) once at first use, and keeps the files open for the life of the program.

The Log service provides a further two functions to manage standard log files:

bool CloseStandardFile(LogFile)

Flushes and closes the specified standard log file. The function returns a boolean indicating whether the log file was closed successfully.

bool CloseAllStandardFiles()

Flushes and closes all currently open standard log files. The function returns a boolean I indicating whether all standard log files were closed successfully.

Standard log file names are supplied via program options, with default values declared in constants.h.

Logging & Debugging Macros

Logging Macros

The following macros are provide for logging:

```
LOG(id, ...)
```

Writes log record to log file specified by "id". Use:

LOG(id, string) writes "string" to log file specified by "id"

LOG(id, level, string) writes "string" to log file specified by "id" if "level" is <= "id" in

Start()

LOG(id, class, level, string) writes "string" to log file specified by "id"

if "class" is in "logClasses" in Start() and

if "level" is <= "logLevel" in Start()

default "class" is ""; default "level" is 0

Examples:

```
LOG(SSEfileId, "This is a log record");
LOG(OutputFile2Id, "The value of x is " << x << " km");
LOG(MyLogfileId, 2, "Log string");
LOG(SSEfileId, "CHeB", 4, "This is a CHeB only log record");
```

LOG ID(id, ...)

Writes log record prepended with calling function name to log file. Use:

LOG ID(id) writes name of calling function to log file specified by "id"

LOG ID(id, string) writes "string" prepended with name of calling function to log

file specified by "id"

LOG_ID(id, level, string) writes "string" prepended with name of calling function to log

file specified by "id" if "level" is <= "logLevel" in Start()

LOG ID(id, class, level, string) writes "string" prepended with name of calling function to log

file specified by "id"

if "class" is in "logClasses" in Start() and if "level" is <= "logLevel" in Start()

default "class" is ""; default "level" is 0

Examples:

LOG ID(Outf1Id)

LOG_ID(Outf2Id, "This is a log record");

LOG_ID(MyLogfileId, "The value of x is " << x << " km");

LOG ID(OutputFile2Id, 2, "Log string");

LOG ID(CHeBfileId, "CHeB", 4, "This is a CHeB only log record");

LOG IF(id, cond, ...)

Writes log record to log file if the condition given by "cond" is met. Use:

LOG IF(id, cond, string) writes "string" to log file specified by "id"

if "cond" is true

LOG IF(id, cond, level, string) writes "string" to log file specified by "id"

if "cond" is true and

if "level" is <= "logLevel" in Start()

LOG_IF(id, cond, class, level, string) writes "string" to log file specified by "id"

if "cond" is true and

if "class" is in "logClasses" in Start() and if "level" is <= "logLevel" in Start()

"cond" is any logical statement and is required; default "class" is ""; default "level" is 0

Examples:

```
LOG_IF(MyLogfileId, a > 1.0, "This is a log record");
LOG(SSEfileId, (b == c && a > x), "The value of x is " << x << " km");
LOG(CHeBfileId, flag, 2, "Log string");
LOG(SSEfileId, (x >= y), "CHeB", 4, "This is a CHeB only log record");
```

LOG ID IF(id, ...)

Writes log record prepended with calling function name to log file if the condition given by "cond" is met. Use: see LOG ID(id, ...) and LOG IF(id, cond, ...) above.

The logging macros described above are provided in a verbose variant. The verbose macros function the same way as their non-verbose counterparts, with the added functionality that the log records written to the log file will be reflected on stdout as well. The verbose logging macros are:

```
LOGV(id, ...)
LOGV_ID(id, ...)
LOGV_IF(id, cond, ...)
LOGV_ID_IF(id, cond, ...)
```

A further four macros are provided that allow writing directly to stdout rather than the log file. These are:

```
SAY(...)
SAY_ID(...)
SAY_IF(cond, ...)
SAY_ID_IF(cond, ...)
```

The SAY macros function the same way as their LOG counterparts, but write directly to stdout instead of the log file. The SAY macros honour the logging classes and level.

Debugging Macros

A similar set of macros is also provided for debugging purposes.

The debugging macros write directly to stdout rather than the log file, but their output can also be written to the log file if desired (see the debugToLogfile parameter of Start(), and the debug-to-file program option described above).

A major difference between the logging macros and the debugging macros is that the debugging macros can be defined away. The debugging macro definitions are enclosed in an #ifdef enclosure, and are only present in the source code if #DEBUG is defined. This means that if #DEBUG is not defined (#undef), all debugging statements using the debugging macros will be removed from the source code by the preprocessor before the source is compiled. Un-defining #DEBUG not only prevents bloat of unused code in the executable, it improves performance. Many of the functions in the code are called hundreds of thousands, if not millions, of times as the stellar evolution proceeds. Even if the debugging classes and debugging level are set so that no debug statement is displayed, just checking the debugging level every time a function is called increases the run-time of the program. The suggested us is to enable the debugging macros (#define DEBUG) while developing new code, and disable them (#undef DEBUG) to produce a production version of the executable.

The debugging macros provided are:

```
DBG(...)analgous to the LOG(...) macroDBG_ID(...)analgous to the LOG_ID(...) macroDBG_IF(cond, ...)analgous to the LOG_IF(...) macroDBG ID IF(cond, ...)analgous to the LOG ID IF(...) macro
```

Two further debugging macros are provided:

```
DBG_WAIT(...)
DBG_WAIT_IF(cond, ...)
```

The DBG_WAIT macros function in the same way as their non-wait counterparts (DBG(...) and DBG_IF(cond, ...) with the added functionality that they will pause execution of the program and wait for user input before proceeding.

A set of macros for printing warning message is also provided. These are the DBG_WARN macros:

```
DBG_WARN(...) analgous to the LOG(...) macro
DBG_WARN_ID(...) analgous to the LOG_ID(...) macro
DBG_WARN_IF(...) analgous to the LOG_IF(...) macro
DBG_WARN_ID_IF(...) analgous to the LOG_ID_IF(...) macro
```

The DBG_WARN macros write to stdout via the SAY macro, so honour the logging classes and level, and are not written to the debug or errors files.

Note that the "id" parameter of the "LOG" macros (to specify the logfileId) is not required for the DBG macros (the filename to which debug records are written is declared in constants.h – see the LOGFILE enum class and associate descriptor map LOGFILE_DESCRIPTOR).

ERROR HANDLING

An error handling service is provided encapsulated in a singleton object (an instantiation of the Errors class).

The Errors service provides global error handling functionality. Following is a brief description of the Errors service (full documentation coming soon...):

Errors are defined in the error catalog in constants.h (see ERROR_CATALOG). It could be useful to move the catalog to a file so it can be changed without changing the code, or even have multiple catalogs provided for internationalisation – a task for later.

Errors defined in the error catalog have a scope and message text. The scope is used to determine when/if an error should be printed.

The current values for scope are:

NEVER the error will not be printed

ALWAYS the error will always be printed

FIRST the error will be printed only on the first time it is

encountered anywhere in the program

FIRST IN OBJECT TYPE the error will be printed only on the first time it is

encountered anywhere in objects of the same type

(e.g. Binary Star objects)

FIRST IN STELLAR TYPE the error will be printed only on the first time it is

encountered anywhere in objects of the same stellar

type (e.g. HeWD Star obejcts)

FIRST IN OBJECT ID the error will be printed only on the first time it is

encountered anywhere in an object instance

FIRST IN FUNCTION the error will be printed only on the first time it is

encountered anywhere in the same function of an object instance (i.e. will print more than once if encountered in the same function name in different

objects)

The Errors service provides methods to print both warnings and errors - essentially the same thing, but warning messages are prefixed with "WARNING:", whereas error messages are prefixed with "ERROR:".

Errors and warnings are printed by using the macros defined in ErrorsMacros.h. They are:

Error macros:

SHOW ERROR(error number)

Prints "ERROR: " followed by the error message associated with "error_number" (from the error catalog)

SHOW ERROR(error number, error string)

Prints "ERROR: " followed by the error message associated with "error_number" (from the error catalog), and appends "error string"

SHOW ERROR IF(cond, error number)

If "cond" is TRUE, prints "ERROR: " followed by the error message associated with "error_number" (from the error catalog)

SHOW_ERROR_IF(cond, error_number, error_string)

If "cond" is TRUE, prints "ERROR: " followed by the error message associated with "error_number" (from the error catalog), and appends "error_string"

Warning macros:

SHOW WARN(error number)

Prints "WARNING: " followed by the error message associated with "error_number" (from the error catalog)

SHOW WARN(error number, error string)

Prints "WARNING: " followed by the error message associated with "error_number" (from the error catalog), and appends "error_string"

SHOW WARN IF(cond, error number)

If "cond" is TRUE, prints "WARNING: " followed by the error message associated with "error_number" (from the error catalog)

SHOW_WARN_IF(cond, error_number, error_string)

If "cond" is TRUE, prints "WARNING: " followed by the error message associated with "error_number" (from the error catalog), and appends "error_string"

Error and warning message always contain:

The object id of the calling object

The object type of the calling object

The stellar type of the calling object (will be "NONE" if the calling object is not a star-type object)

The function name of the calling function

Any object that uses the Errors service (i.e. the SHOW_* macros) must expose the following functions:

```
OBJECT_ID ObjectId() const { return m_ObjectId; }
OBJECT_TYPE ObjectType() const { return m_ObjectType; }
STELLAR_TYPE StellarType() const { return m_StellarType; }
```

These functions are called by the SHOW_* macros. If any of the functions are not applicable to the object, then they must return "*::NONE (all objects should implement ObjectId() correctly).

The filename to which error records are written when Start() parameter "errorsToLogfile" is true is declared in constants.h – see the LOGFILE enum class and associate descriptor map LOGFILE_DESCRIPTOR. Currently the name is 'Error_Log'.

FLOATING-POINT COMPARISONS

Floating-point comparisons are inherently problematic. Testing floating-point numbers for equality, or even inequality, is fraught with problems due to the internal representation of floating-point numbers: floating-point numbers are stored with a fixed number of binary digits, which limits their precision and accuracy. The problems with floating-point comparisons are even more evident if one or both of the numbers being compared are the results of (perhaps several) floating-point operations (rather than comparing constants).

To avoid the problems associated with floating-point comparisons it is (almost always) better to do any such comparisons with a tolerance rather than an absolute comparison. To this end, a floating-point comparison function has been provided, and (almost all of) the floating-point comparisons in the code have been changed to use that function. The function uses both an absolute tolerance and a relative tolerance, which are both declared in constants.h. Whether the function uses a tolerance or not can be changed by #define-ing or #undef-ing the "COMPARE_WITH_TOLERANCE" flag in constants.h (so the change is a compile-time change, not run-time).

The compare function is defined in utils.h and is implemented as follows:

If COMPARE_WITH_TOLERANCE is defined, p_X and p_Y are compared with tolerance values, whereas if COMPARE_WITH_TOLERANCE is not defined the comparison is an absolute comparison.

The function returns an integer indicating the result of the comparison:

- -1 indicates that p X is considered to be less than p Y
- 0 indicates p X and p Y are considered to be equal
- +1 indicates that p X is considered to be greater than p Y

The comparison is done using both an absolute tolerance and a relative tolerance. The tolerances can be defined to be the same number, or different numbers. If the relative tolerance is defined as 0.0, the comparison is done using the absolute tolerance only, and if the absolute tolerance is defined as 0.0 the comparison is done with the relative tolerance only.

Absolute tolerances are generally more effective when the numbers being compared are small – so using an absolute tolerance of (say) 0.0000005 is generally effective when comparing single-digit numbers (or so), but is less effective when comparing numbers in the thousands or millions. For comparisons of larger numbers a relative tolerance is generally more effective (the actual tolerance is wider because the relative tolerance is multiplied by the larger absolute value of the numbers being compared).

There is a little overhead in the comparisons even when the tolerance comparison is disabled, but it shouldn't be prohibitive.

CONSTANTS FILE - constants.h

As well as plain constant values, many distribution and prescription identifiers are declared in constants.h. These are mostly declared as enum classes, with each enum class having a corresponding

map of labels. The benefit is that the values of a particular (e.g.) prescription are limited to the values declared in the enum class, rather than any integer value, so the compiler will complain if an incorrect value is inadvertently used to reference that prescription.

For example, the Common Envelope Lambda Prescriptions are declared in constants.h thus:

```
enum class CE LAMBDA PRESCRIPTION: int {
     FIXED, LOVERIDGE, NANJING, KRUCKOW, DEWI
};
const std::unordered map<CE LAMBDA PRESCRIPTION, std::string>
CE LAMBDA PRESCRIPTION LABEL = {
    { CE LAMBDA PRESCRIPTION::FIXED,
                                          "LAMBDA FIXED" },
                                          "LAMBDA LOVERIDGE" },
    { CE LAMBDA PRESCRIPTION::LOVERIDGE,
    { CE LAMBDA PRESCRIPTION::NANJING,
                                          "LAMBDA NANJING" },
                                          "LAMBDA KRUCKOW" },
    { CE LAMBDA PRESCRIPTION:: KRUCKOW,
    { CE LAMBDA PRESCRIPTION::DEWI,
                                          "LAMBDA DEWI" }
};
```

Note that the values allowed for variables of type CE_LAMBDA_PRESCRIPTION are limited to FIXED, LOVERIDGE, NANJING, KRUCKOW and DEWI — anything else will cause a compiler error.

The unordered map CE_LAMBDA_PRESCRIPTION_LABEL is indexed by CE_LAMBDA_PRESCRIPTION and declares a string label for each CE_LAMBDA_PRESCRIPTION. The strings declared in CE_LAMBDA_PRESCRIPTION_LABEL are used by the Options service to match user input to the required CE_LAMBDA_PRESCRIPTION. These strings can also be used if an English description of the value of a variable is required: instead of just printing an integer value that maps to a CE_LAMBDA_PRESCRIPTION, the string label associated with the prescription can be printed.

Stellar types are also declared in constants.h via an enum class and associate label map. This allows stellar types to be referenced using symbolic names rather than an ordinal number. The stellar types enum class is STELLAR TYPE, and is declared as:

```
enum class STELLAR TYPE: int {
    MS LTE 07,
    MS GT 07,
    HERTZSPRUNG GAP,
    FIRST GIANT BRANCH,
    CORE HELIUM BURNING,
    EARLY ASYMPTOTIC GIANT BRANCH,
    THERMALLY PULSING ASYMPTOTIC GIANT BRANCH,
    NAKED HELIUM STAR MS,
    NAKED HELIUM STAR HERTZSPRUNG GAP,
    NAKED HELIUM STAR GIANT BRANCH,
    HELIUM WHITE DWARF,
    CARBON OXYGEN WHITE DWARF,
    OXYGEN NEON WHITE DWARF,
    NEUTRON STAR,
    BLACK HOLE,
    MASSLESS REMNANT,
    CHEMICALLY HOMOGENEOUS,
    STAR,
    BINARY STAR,
    NONE
};
```

Ordinal numbers can still be used to reference the stellar types, and because of the order of definition in the enum class the ordinal numbers match those given in Hurley et al. 2000.

The label map STELLAR_TYPE_LABEL can be used to print text descriptions of the stellar types, and is declared as:

```
const std::unordered_map<STELLAR_TYPE, std::string> STELLAR_TYPE_LABEL = {
 { STELLAR_TYPE::MS_LTE_07,
                                                                               "Main_Sequence_<=_0.7" },
                                                                               "Main_Sequence > 0.7" },
"Hertzsprung_Gap" },
   STELLAR TYPE::MS GT 07,
 { STELLAR TYPE::HERTZSPRUNG GAP,
 { STELLAR TYPE::FIRST GIANT BRANCH,
                                                                               "First_Giant_Branch" },
 { STELLAR TYPE::CORE HELIUM BURNING,
                                                                               "Core Helium Burning" },
  { STELLAR TYPE:: EARLY ASYMPTOTIC GIANT BRANCH,
                                                                               "Early_Asymptotic_Giant_Branch" },
 { STELLAR TYPE::THERMALLY PULSING ASYMPTOTIC GIANT BRANCH, "Thermally Pulsing Asymptotic Giant Branch" }, 
{ STELLAR TYPE::NAKED_HELIUM_STAR_MS, "Naked_Helium_Star_MS" },
 { STELLAR TYPE::NAKED HELIUM STAR HERTZSPRUNG GAP, { STELLAR TYPE::NAKED_HELIUM_STAR_GIANT_BRANCH,
                                                                              "Naked_Helium_Star_Hertzsprung_Gap" },
"Naked_Helium_Star_Giant_Branch" },
 { STELLAR TYPE::HELIUM WHITE DWARF, { STELLAR TYPE::CARBON OXYGEN WHITE DWARF,
                                                                               "Helium White Dwarf"
                                                                               "Carbon-Oxygen White Dwarf" },
 { STELLAR_TYPE::OXYGEN_NEON_WHITE_DWARF, 
{ STELLAR_TYPE::NEUTRON_STAR,
                                                                               "Oxygen-Neon_White_Dwarf" },
                                                                               "Neutron_Star" },
 { STELLAR_TYPE::BLACK_HOLE, 
{ STELLAR_TYPE::MASSLESS_REMNANT,
                                                                               "Black Hole" },
                                                                               "Massless Remnant" },
 { STELLAR TYPE::CHEMICALLY_HOMOGENEOUS, { STELLAR_TYPE::STAR,
                                                                               "Chemically_Homogeneous" },
                                                                               "Star" },
                                                                               "Binary_Star" },
 { STELLAR_TYPE::BINARY_STAR,
                                                                               "Not_a_Star!" }
 { STELLAR TYPE::NONE,
};
```

PROGRAMMING STYLE AND CONVENTIONS

Everyone has their own preferences and style, and the nature of a project such as COMPAS will reflect that. However, there is a need to suggest some guidelines for programming style, naming conventions etc. Following is a description of some of the elements of programming style and naming conventions used to develop COMPAS v2. These may evolve over time.

Object-Oriented Programming

COMPAS is written in C++, an object-oriented programming (OOP) language, and OOP concepts and conventions should apply throughout the code. There are many texts and web pages devoted to understanding C++ and OOP – following is a brief description of the key OOP concepts:

Abstraction

For any entity, product, or service, the goal of abstraction is to handle the complexity of the implementation by hiding details that don't need to be known in order to use, or consume, the entity, product, or service. In the OOP paradigm, hiding details in this way enables the consumer to implement more complex logic on top of the provided abstraction without needing to understand the hidden implementation details and complexity. (There is no suggestion that consumers shouldn't understand the implementation details, but they shouldn't need to in order to consume the entity, product, or service).

Abstraction in C++ is achieved via the use of *objects* – an object is an instance of a *class*, and typically corresponds to a real-world object or entity (in COMPAS, usually a star or binary star). An object maintains the state of an object (via class member variables), and provides all necessary means of changing the state of the object (by exposing public class member functions (methods)). A class may expose public functions to allow consumers to determine the value of class member variables ("getters"), and to se the value of class member variables ("setters").

Encapsulation

Encapsulation binds together the data and functions that manipulate the data in an attempt to keep both safe from outside interference and accidental misuse. An encapsulation paradigm that does not allow calling code to access internal object data and permits access through functions only is a strong form of abstraction. C++ allows developers to enforce access restrictions explicitly by defining class member variables and functions as *private*, *protected*, or *public*. These keywords are used throughout COMPAS to enforce encapsulation.

There are very few circumstances in which a consumer should change the value of a class member variable directly (via the use of a setter function) – almost always consumers should present new situational information to an object (via a public member function), and allow the object to respond to the new information. For example, in COMPAS, there should be almost no reason for a consumer of a star object to directly change (say) the radius of the star – the consumer should inform the star object of new circumstances or events, and allow the star object to respond to those events (perhaps changing the value of the radius of the star). Changing a single class member variable directly introduces the possibility that related class member variables (e.g. other attributes of stars) will not be changed accordingly. Moreover, developers changing the code in the future should, in almost all cases, expect that the state of an object is maintained consistently by the object, and that there should be no unexpected side-effects caused by calling non class-member functions. In short, changing the state of an object outside the object is potentially unsafe and should be avoided where possible.

Inheritance

Inheritance allows classes to be arranged in a hierarchy that represents *is-a-type-of* relationships. All *non-private* class member variables and functions of the parent (base) class are available to the child (derived) class (and, therefore, child classes of the child class). This allows easy re-use of the same

procedures and data definitions, in addition to describing real-world relationships in an intuitive way. C++ allows multiple inheritance – a class may inherit from multiple parent classes.

Derived classes can define additional class member variables (using the *private*, *protected*, and *public* access restrictions), which will be available to any descendent classes (subject to inheritance rules), but will only be available to ancestor classes via the normal access methods (getters and setters).

Polymorphism

Polymorphism means *having many forms*. In OOP, polymorphism occurs when there is a hierarchy of classes and they are related by inheritance.

Following the discussion above regarding inheritance, in the OOP paradigm, and C++ specifically, derived classes can override methods defined by ancestor classes, allowing a derived class to implement functions specific to its circumstances. This means that a call to a class member function will cause a different function to be executed depending on the type of object that invokes the function. Descendent classes of a class that has overridden a base class member function inherit the overridden function (but can override it themselves).

COMPAS makes heavy use of inheritance and polymorphism, especially for the implementation of the different stellar types.

Programming Style

The goal of coding to a suggested style is readability and maintainability – if many developers implement code in COMPAS with their own coding style, readability and maintainability will be more difficult than if a consistent style is used throughout the code. Strict adherence isn't really necessary, but it will make it easier on all COMPAS developers if the coding style is consistent throughout.

Comments

An old, but good, rule-of-thumb is that any file that contains computer code should be about one-third code, one-third comments, and one-third white space. Adhering to this rule-of-thumb just makes the code a bit easier on the eye, and provides some description (at least of the intention) of the implementation.

Braces

The placement of braces in C++ code (actually, any code that uses braces to enclose scope) is a contentious issue, with many developers having long-held, often dogmatic preferences. COMPAS (so far) uses the K&R style ("the one true brace style") - the style used in the original Unix kernel and Kernighan and Ritchie's book *The C Programming Language*.

The K&R style puts the opening brace on the same line as the control statement:

```
while (x == y) {
    something();
    somethingelse();
}
```

Note also the space between the keyword *while* and the opening parenthesis, and the closing parenthesis and the opening brace.

Indentation

There is ongoing debate in the programming community as to whether indentation should be achieved using spaces or tabs (strange, but true...). The use of spaces is more common. COMPAS (so far) has a mix of both – whatever is convenient (pragmatism is your friend...).

COMPAS uses an indentation size of 4 spaces.

Function Parameters

In most cases, function parameters should be input only – meaning that the values of function parameters should not be changed by the function. Anything that needs to be changed and returned to the caller should be returned as a functional return. There are a few exceptions to this in COMPAS – all were done for performance reasons, and are documented in the code.

To avoid unexpected side-effects, developers should expect (in most cases) that any variables they pass to a function will remain unchanged – all changes should be returned as a functional return.

Performance & Optimisation

In general COMPAS developers should code for performance – within reason. Bear in mind that many functions will be called many, many thousands of times (in some cases, millions) in one execution of the program.

- Avoid calculating values inside loops that could be calculated once outside the loop.
- Try to use constants where possible.
- Use multiplication in preference to functions such as *pow()* and *sqrt()* (note that *pow()* is very expensive computationally; *sqrt()* is expensive, but much less expensive than *pow()*).
- Don't optimise to the point that readability and maintainability is compromised. Bear in mind that most compilers are good at optimising, and are very forgiving of less-than-optimally-written code (though they are not miracle workers...).

Naming Conventions

COMPAS (so far) uses the following naming conventions:

- all variable names should be in camelCase don't use underscore_to_separate_words
- function names should be in camelCase, beginning with an uppercase letter. Function names should be descriptive.
- class member variable names are prefixed with "m_", and the character immediately following the prefix should be uppercase (in most cases sometimes, for well-known names or words that are always written in lowercase, lowercase might be used)
- local variable names are just camelCase, beginning with a lowercase letter (again, with the caveat that sometimes, for well-known names or words that are always written in uppercase, uppercase might be used)
- function parameter names are prefixed with "p_", and the character immediately following the prefix should be uppercase (again, with the caveat that sometimes, for well-known names or words that are always written in lowercase, lowercase might be used)

COMPILATION & REQUIREMENTS

Please refer to the COMPAS Getting Started guide.

Appendix A - Program Options

-h [--help]

Prints COMPAS help.

-v [--version]

Print COMPAS version string.

--allow-rlof-at-birth

Allow binaries that have one or both stars in RLOF at birth to evolve as overcontact systems. Default = FALSE

-- allow-touching-at-birth

Allow binaries that are touching at birth to be included in the sampling.

Default = FALSE

--angularMomentumConservationDuringCircularisation

Conserve angular momentum when binary is circularised when entering a Mass Transfer episode.

Default = FALSE

--circulariseBinaryDuringMassTransfer

Circularise binary when it enters a Mass Transfer episode.

Default = FALSE

--common-envelope-allow-main-sequence-survive

Allow main sequence donors to survive common envelope evolution.

Default = FALSE

--debug-to-file

Write debug statements to file.

Default = FALSE

--detailedOutput

Print detailed output to file.

Default = FALSE

--errors-to-file

Write error messages to file.

Default = FALSE

--evolve-pulsars

Evolve pulsar properties of Neutron Stars.

Default = FALSE

--evolve-unbound-systems

Continue evolving stars even if the binary is disrupted.

Default = FALSE

--lambda-calculation-every-timeStep

Calculate all values of lambda at each timestep.

Default = FALSE

--massTransfer

Enable mass transfer.

Default = TRUE

--pair-instability-supernovae

Enable pair instability supernovae (PISN).

Default = FALSE

--populationDataPrinting

Print details of population.

Default = FALSE

--print-bool-as-string

Print boolean properties as 'TRUE' or 'FALSE'.

Default = FALSE

--pulsational-pair-instability

Enable mass loss due to pulsational-pair-instability (PPI).

Default = FALSE

--quiet

Suppress printing to stdout.

Default = FALSE

--revised-energy-formalism-Nandez-Ivanova

Enable revised energy formalism of Nandez & Ivanova.

Default = FALSE

--single-star

Evolve single star(s).

Default = FALSE

--use-mass-loss

Enable mass loss.

Default = FALSE

--zeta-calculation-every-timestep

Calculate all values of MT zetas at each timestep.

Default = FALSE

--random-seed

Random seed.

Default = 0

--debug-level

Determines which print statements are displayed for debugging.

Default = 0

--log-level

Determines which print statements are included in the logfile.

Default = 0

--maximum-number-timestep-iterations

Maximum number of timesteps to evolve binary.

Default = 99999

-n [--number-of-binaries]

Specify the number of binaries to simulate.

Default = 10

--single-star-mass-steps

Specify the number of mass steps for single star evolution.

Default = 100

--common-envelope-alpha

Common Envelope efficiency alpha.

Default = 1.0

--common-envelope-alpha-thermal

Thermal energy contribution to the total envelope binding energy.

Defined such that lambda = alpha th * lambda b + (1.0 - alpha th) * lambda g.

Default = 1.0

--common-envelope-lambda

Common Envelope lambda.

Default = 0.1

--common-envelope-lambda-multiplier

Multiply lambda by some constant.

Default = 1.0

--common-envelope-mass-accretion-constant

Value of mass accreted by NS/BH during common envelope evolution if assuming all NS/BH accrete same amount of mass.

Used when --common-envelope-mass-accretion-prescription = CONSTANT, ignored otherwise.

Default = 0.0

--common-envelope-mass-accretion-max

Maximum amount of mass accreted by NS/BHs during common envelope evolution (Msol). Default = 0.1

--common-envelope-mass-accretion-min

Minimum amount of mass accreted by NS/BHs during common envelope evolution (Msol).

Default = 0.04

--common-envelope-recombination-energy-density

Recombination energy density (ergs/g).

Default = 1.5E+13

--common-envelope-slope-Kruckow

Common Envelope slope for Kruckow lambda.

Default = -0.8

--eccentricity-max

Maximum eccentricity to generate.

Default = 1.0

--eccentricity-min

Minimum eccentricity to generate.

Default = 0.0

--eddington-accretion-factor

Multiplication factor for Eddington accretion for NS & BH, i.e. >1 is super-eddington and 0 is no accretion.

Default = 1.0

--fix-dimensionless-kick-velocity

Fix dimensionless kick velocity uk to this value.

Default = n/a (not used if option not present)

--initial-mass-max

Maximum mass (in Msol) to generate using given IMF.

Default = 100.0

--initial-mass-min

Minimum mass (in Msol) to generate using given IMF.

Default = 8.0

--initial-mass-power

Single power law power to generate primary mass using given IMF.

Default = -2.3

--kick-direction-power

Power for power law kick direction distribution.

Default = 0.0 = isotropic, +ve = polar, -ve = in plane

--kick-scaling-factor

Arbitrary factor used to scale kicks.

Default = 1.0

--kick-velocity-max

Maximum drawn kick velocity in km s^-1.

Must be > 0 if using --kick-velocity-distribution=FLAT

Default = -1.0

--kick-velocity-sigma-CCSN-BH

Sigma for chosen kick velocity distribution for black holes.

Default = 250.0 km s^{-1}

--kick-velocity-sigma-CCSN-NS

Sigma for chosen kick velocity distribution for neutron stars.

Default = 250.0 km s^{-1}

--kick-velocity-sigma-ECSN

Sigma for chosen kick velocity distribution for ECSN.

Default = 30.0 km s^{-1}

--kick-velocity-sigma-USSN

Sigma for chosen kick velocity distribution for USSN.

Default = 30.0 km s^{-1}

--luminous-blue-variable-multiplier

Multiplicative constant for LBV mass loss.

Default = 1.5, use 10 for Mennekens & Vanbeveren 2014

--mass-ratio-max

Maximum mass ratio m2/m1 to generate.

Default = 1.0

--mass-ratio-min

Minimum mass ratio m2/m1 to generate.

Default = 0.0

--mass-transfer-fa

Mass Transfer fraction accreted, when the FIXED mass transfer prescription is used.

Default = 1.0 (fully conservative)

--mass-transfer-jloss

Specific angular momentum with which the non-accreted system leaves the system.

Used when --mass-transfer-angular-momentum-loss-prescription = ARBITRARY, ignored otherwise.

Default = 1.0

--mass-transfer-thermal-limit-C

Mass Transfer Thermal rate factor for the accretor.

Default = 10.0

--maximum-evolution-time

Maximum time to evolve binaries (Myr).

Default = 13700.0

--maximum-mass-donor-Nandez-Ivanova

Maximum donor mass allowed for the revised common envelope formalism of Nandez & Ivanova (Msol).

Default = 2.0

--maximum-neutron-star-mass

Maximum mass of a neutron star (Msol).

Default = 3.0

--MCBUR1

minimum core mass at base of the AGB to avoid fully degenerate CO core formation (Msol); e.g., 1.6 in Hurley prescription, 1.83 in Fryer and Belczynski models to

Default = 1.6

-z [--metallicity]

Metallicity (Zsol)

Default = 0.02

--minimum-secondary-mass

Minimum mass of secondary to generate (Msol).

Default = 0.0

--neutrino-mass-loss-bh-formation-value

Amount of mass lost in neutrinos during BH formation (either as fraction or in solar masses, depending on neutrino-mass-loss-bh-formation setting).

Default = 0.1

--orbital-period-max

Maximum period to generate (days)

Default = 1000.0

--orbital-period-min

Minimum period to generate (days).

Default = 1.1

--PISN-lower-limit

Minimum core mass for PISN (Msol).

Default = 60.0

--PISN-upper-limit

Maximum core mass for PISN (Msol).

Default = 135.0

--PPI-lower-limit

Minimum core mass for PPI (Msol).

Default = 35.0

--PPI-upper-limit

Maximum core mass for PPI (Msol).

Default = 60.0

--pulsar-birth-magnetic-field-distribution-max

Maximum (log10) pulsar birth magnetic field.

Default = 13.0

--pulsar-birth-magnetic-field-distribution-min

Minimum (log10) pulsar birth magnetic field.

Default = 11.0

--pulsar-birth-spin-period-distribution-max

Maximum pulsar birth spin period (ms).

Default = 100.0

--pulsar-birth-spin-period-distribution-min

Minimum pulsar birth spin period (ms).

Default = 0.0

--pulsar-magnetic-field-decay-massscale

Mass scale on which magnetic field decays during accretion (Msol).

Default = 0.025

--pulsar-magnetic-field-decay-timescale

Timescale on which magnetic field decays (Myr).

Default = 1000.0

--pulsar-minimum-magnetic-field

log10 of the minimum pulsar magnetic field (Gauss).

Default = 8.0

--semi-major-axis-max

Maximum semi-major axis to generate (AU).

Default = 1000.0

--semi-major-axis-min

Minimum semi-major axis to generate (AU).

Default = 0.1

--single-star-mass-max

Maximum mass for single star evolution (Msol).

Default = 100.0

--single-star-mass-min

Minimum mass for single star evolution (Msol).

Default = 5.0

--wolf-rayet-multiplier

Multiplicative constant for WR winds.

Default = 1.0

--zeta-adiabatic-arbitrary

Value of logarithmic derivative of radius with respect to mass, zeta adiabatic.

Default = 1.0E+04

--zeta-radiative-giant-star

Value of logarithmic derivative of radius with respect to mass, zeta for radiative-envelope giant-like stars, including Hertzsprung gap stars.

Default = 6.5

--zeta-main-sequence

Value of logarithmic derivative of radius with respect to mass, zeta on the main sequence.

Default = 2.0

--black-hole-kicks

Black hole kicks relative to NS kicks (options: FULL, REDUCED, ZERO, FALLBACK).

Default = FALLBACK

--case-bb-stability-prescription

Prescription for the stability of case BB/BC mass transfer (options: ALWAYS_STABLE, ALWAYS_STABLE_ONTO_NSBH, TREAT_AS_OTHER_MT, NEVER_STABLE).

Default = ALWAYS_STABLE

--chemically-homogeneous-evolution

Chemically Homogeneous Evolution mode (options: NONE, OPTIMISTIC, PESSIMISTIC). Default = NONE

--common-envelope-lambda-prescription

CE lambda prescription.

(options:

LAMBDA_FIXED, LAMBDA_LOVERIDGE, LAMBDA_NANJING, LAMBDA_KRUCKOW, LAMBDA_DEWI) Default = LAMBDA_NANJING

--common-envelope-mass-accretion-prescription

Assumption about whether NS/BHs can accrete mass during common envelope evolution.

(options: ZERO, CONSTANT, UNIFORM, MACLEOD)

Default = ZERO

--envelope-state-prescription

Prescription for determining whether the envelope of the star is convective or radiative.

(options: LEGACY, HURLEY, FIXED TEMPERATURE)

Default = LEGACY

--stellar-zeta-prescription

Prescription for stellar zeta.

(options: STARTRACK, SOBERMAN, HURLEY, ARBITRARY)

Default = SOBERMAN

-e [--eccentricity-distribution]

Initial eccentricity distribution, e.

(options:

ZERO, FIXED, FLAT, THERMALISED, GELLER+2013, THERMAL, DUQUENNOYMAYOR 1991, SANA2012, IMPORTANCE).

Default = ZERO

--fryer-supernova-engine

Supernova engine type if using Fryer et al. 2012 fallback prescription.

(options: DELAYED, RAPID).

Default = DELAYED

--grid

Grid filename.

Default = "

-i [--initial-mass-function]

Initial mass function, (options: SALPETER, POWERLAW, UNIFORM, KROUPA)
Default = KROUPA

--kick-direction

Natal kick direction distribution.

(options: ISOTROPIC, INPLANE, PERPENDICULAR, POWERLAW, WEDGE, POLES)

Default = ISOTROPIC

--kick-velocity-distribution

Natal kick velocity distribution.

(options:

ZERO, FIXED, FLAT, MAXWELLIAN, MUELLER2016, MUELLER2016MAXWELLIAN, BRAYEL-DRIDGE, MULLERMANDEL)

Default = MAXWELLIAN

--logfile-BSE-common-envelopes

Filename for BSE Common Envelopes logfile.

Default = 'BSE Common Envelopes'

--logfile-BSE-detailed-output

Filename for BSE Detailed Output logfile.

Default = 'BSE_Detailed_Output'

--logfile-BSE-double-compact-objects

Filename for BSE Double Compact Objects logfile.

Default = 'BSE Double Compact Objects'

--logfile-BSE-pulsar-evolution

Filename for BSE Pulsar Evolution logfile.

Default = 'BSE Pulsar Evolution'

--logfile-BSE-supernovae

Filename for BSE Supernovae logfile.

Default = 'BSE Supernovae'

--logfile-BSE-system-parameters

Filename for BSE System Parameters logfile.

Default = 'BSE System Parameters'

--logfile-definitions

Filename for logfile record definitions.

Default = "

--logfile-delimiter

Field delimiter for logfile records.

Default = TAB

--logfile-name-prefix

Prefix for logfile names.

Default = "

--logfile-SSE-parameters

Filename for SSE Parameters logfile.

Default = 'SSE Parameters'

--mass-loss-prescription

Mass loss prescription, (options: NONE, HURLEY, VINK).

Default = VINK

-q [--mass-ratio-distribution]

Initial mass ratio distribution for q=m2/m1.

(options: FLAT, DUQUENNOYMAYOR1991, SANA2012).

Default = FLAT

--mass-transfer-accretion-efficiency-prescription

Mass Transfer Accretion Efficiency prescription, (options: THERMAL, FIXED).

Default = THERMAL

--mass-transfer-angular-momentum-loss-prescription

Mass Transfer Angular Momentum Loss prescription.

(options: JEANS, ISOTROPIC, CIRCUMBINARY, ARBITRARY)

Default = ISOTROPIC

--mass-transfer-rejuvenation-prescription

Mass Transfer Rejuvenation prescription, (options: NONE, STARTRACK).

Default = NONE

--mass-transfer-thermal-limit-accretor

Mass Transfer Thermal Accretion limit multiplier, (options: CFACTOR, ROCHELOBE).

Default = CFACTOR

--neutrino-mass-loss-bh-formation

Assumption about neutrino mass loss during BH formation.

(options: FIXED FRACTION, FIXED MASS).

Default = FIXED FRACTION

--neutron-star-equation-of-state

Neutron star equation of state, (options: SSE, ARP3).

Default = SSE

-c [--output-container]

Container (directory) name for output files.

Default = 'COMPAS Output'

-o [--outputPath]

Path to which output is saved (i.e. directory in which the output container is created).

Default = CWD ('.')

--pulsar-birth-magnetic-field-distribution

Pulsar Birth Magnetic Field distribution.

(options: ZERO, FIXED, FLATINLOG, UNIFORM, LOGNORMAL).

Default = ZERO

--pulsar-birth-spin-period-distribution

Pulsar Birth Spin Period distribution, (options: ZERO, FIXED, UNIFORM, NORMAL).

Default = ZERO

--pulsational-pair-instability-prescription

Pulsational Pair Instability prescription, (options: COMPAS, STARTRACK, MARCHANT).

Default = COMPAS

--remnant-mass-prescription

Choose remnant mass prescription.

(options: HURLEY2000, BELCZYNSKI2002, FRYER2012, MULLER2016, MULLERMANDEL) Default = FRYER2012

--rotational-velocity-distribution

Initial rotational velocity distribution, (options: ZERO, HURLEY, VLTFLAMES). Default = ZERO

-a [--semi-major-axis-distribution]

Initial semi-major axis distribution, a. (options: FLATINLOG, CUSTOM, DUQUENNOYMAYOR1991, SANA2012) Default = FLATINLOG

--debug-classes

Debug classes enabled.
Default = '' (None)

--log-classes

Logging classes enabled. Default = '' (None)

Appendix B – Log File Record Specification: Stellar Properties

As described in **Standard Log File Record Specifiers**, when specifying known properties in a log file record specification record, the property name must be prefixed with the property type.

The current list of valid stellar property types available for use is:

• STAR PROPERTY for SSE

STAR_1_PROPERTY for the primary star of a binary for BSE
 STAR_2_PROPERTY for the secondary star of a binary for BSE

• SUPERNOVA PROPERTY for the exploding star in a supernova for BSE

• COMPANION_PROPERTY for the companion of the exploding star in a supernova for BSE

For example, to specify the property TEMPERATURE for an individual star being evolved for SSE, use:

```
STAR PROPERTY::TEMPERATURE
```

To specify the property TEMPERATURE for the primary star in a binary star being evolved for BSE, use:

```
STAR 1 PROPERTY::TEMPERATURE
```

To specify the property TEMPERATURE for the supernova star in a binary star being evolved for BSE, use:

```
SUPERNOVA_PROPERTY::TEMPERATURE
```

Following is the list of stellar properties available for inclusion in log file record specifiers.

Stellar Properties

AGE

Header string: Age Data type: DOUBLE

COMPAS variable: BaseStar::m Age

Effective age (changes with mass loss/gain) (Myr)

ANGULAR MOMENTUM

Header string: Ang Momentum

Data type: DOUBLE

COMPAS variable: BaseStar::m AngularMomentum

Angular momentum (Msol AU^2 yr-1)

BINDING ENERGY AT COMMON ENVELOPE

Header string: Binding_Energy@CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m_CEDetails.bindingEnergy

Absolute value of the envelope binding energy (ergs) at the onset of unstable RLOF, used for

calculating post-CE separation.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

BINDING ENERGY FIXED

Header string: BE_Fixed Data type: DOUBLE

COMPAS variable: BaseStar::m BindingEnergies.fixed

Absolute value of the envelope binding energy (ergs) calculated using a fixed lambda parameter.

Calculated using lambda = m Lambdas.fixed

BINDING ENERGY KRUCKOW

Header string: BE_Kruckow

Data type: DOUBLE

COMPAS variable: BaseStar::m BindingEnergies.kruckow

Absolute value of the envelope binding energy (ergs) calculated using the fit by Vigna-Gomez et al.

(2018) to Kruckow et al. (2016).

Calculated using alpha = OPTIONS->CommonEnvelopeSlopeKruckow()

BINDING ENERGY LOVERIDGE

Header string: BE_Loveridge

Data type: DOUBLE

COMPAS variable: BaseStar::m BindingEnergies.loveridge

Absolute value of the envelope binding energy (ergs) calculated as per Loveridge et al. (2001).

Calculated using lambda = m Lambdas.loveridge

BINDING ENERGY LOVERIDGE WINDS

Header string: BE_Loveridge_Winds

Data type: DOUBLE

COMPAS variable: BaseStar::m BindingEnergies.loveridgeWinds

Absolute value of the envelope binding energy (ergs) calculated as per Webbink 1984 & Loveridge

et al. 2011 including winds.

Calculated using lambda = m Lambdas.loveridgeWinds

BINDING ENERGY NANJING

Header string: BE Nanjing

Data type: DOUBLE

COMPAS variable: BaseStar::m BindingEnergies.nanjing

Absolute value of the envelope binding energy (ergs) calculated as per Xu & Li, 2010.

Calculated using lambda = m Lambdas.nanjing

BINDING ENERGY POST COMMON ENVELOPE

Header string: Binding Energy>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.bindingEnergy

Absolute value of the binding energy (ergs) immediately after CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

BINDING ENERGY PRE COMMON ENVELOPE

Header string: Binding Energy<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.bindingEnergy

Absolute value of the envelope binding energy (ergs) at the onset of unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

CHEMICALLY HOMOGENEOUS MAIN SEQUENCE

Header string: CH on MS

Data type: BOOL

COMPAS variable: BaseStar::m CHE

Flag to indicate whether the star evolved as a CH star for its entire MS lifetime.

TRUE indicates star evolved as CH star for entire MS lifetime

FALSE indicates star spun down and switched from CH to a normal MS

CO CORE MASS

Header string: Mass_CO_Core

Data type: DOUBLE

COMPAS variable: BaseStar::m COCoreMass

Carbon-Oxygen core mass (Msol).

CO CORE MASS AT COMMON ENVELOPE

Header string: Mass CO Core@CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.COCoreMass

Carbon-Oxygen core mass (Msol) at the onset of unstable RLOF leading to the CE. Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

CO CORE MASS AT COMPACT OBJECT FORMATION

Header string: : Mass CO Core@CO

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.COCoreMassAtCOFormation

Carbon-Oxygen core mass (Msol) immediately prior to a supernova.

CORE MASS

Header string: Mass_Core Data type: DOUBLE

COMPAS variable: BaseStar::m CoreMass

Core mass (Msol)

CORE MASS AT COMMON ENVELOPE

Header string: Mass Core@CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m_CEDetails.CoreMass Core mass (Msol) at the onset of unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

CORE MASS AT COMPACT OBJECT FORMATION

Header string: Mass Core@CO

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.CoreMassAtCOFormation

Core mass (Msol) immediately prior to a supernova.

DRAWN KICK VELOCITY

Header string: Drawn Kick Velocity

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.drawnKickVelocity

Magnitude of natal kick velocity (kms^-1) without accounting for fallback (km s^-1).

Supplied by user in grid file or drawn from distribution (default).

This value is used to calculate the actual kick velocity

DT

Header string: dT Data type: DOUBLE

COMPAS variable: BaseStar::m Dt

Current timestep (Myr).

DYNAMICAL TIMESCALE

Header string: Tau Dynamical

Data type: DOUBLE

COMPAS variable: BaseStar::m DynamicalTimescale

Dynamical time (Myr) .

DYNAMICAL TIMESCALE POST COMMON ENVELOPE

Header string: Tau Dynamical>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.dynamicalTimescale

Dynamical time (Myr) immediately following common envelope event.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

DYNAMICAL TIMESCALE PRE COMMON ENVELOPE

Header string: Tau Dynamical<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.dynamicalTimescale

Dynamical timescale (Myr) immediately prior to common envelope event.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

ECCENTRIC ANOMALY

Header string: Eccentric Anomaly

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.eccentricAnomaly

Eccentric anomaly calculated using Kepler's equation.

ENV_MASS

Header string: Mass_Env Data type: DOUBLE

COMPAS variable: BaseStar::m EnvMass

Envelope mass (Msol) calculated using Hurley et al. 2000.

ERROR

Header string: Error Data type: INT

COMPAS variable: <derived from BaseStar::m_Error>

Error number (if error condition exists, else 0).

EXPERIENCED CCSN

Header string: Experienced_CCSN

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the star exploded as a core-collapse supernova at any time prior to the current timestep.

EXPERIENCED ECSN

Header string: Experienced ECSN

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past >

Flag to indicate whether the star exploded as an electron-capture supernova at any time prior to the current timestep.

EXPERIENCED PISN

Header string: Experienced PISN

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the star exploded as a pair-instability supernova at any time prior to the

current timestep.

EXPERIENCED PPISN

Header string: Experienced_PPISN

Data type: BOOL

COMPAS variable: <derived from BaseStar::m_SupernovaDetails.events.past>

Flag to indicate whether the star exploded as a pulsational pair-instability supernova at any time

prior to the current timestep.

EXPERIENCED RLOF

Header string: Experienced RLOF

Data type: BOOL

COMPAS variable: <derived from BinaryConstituentStar::m_RLOFDetails.experiencedRLOF> Flag to indicate whether the star has overflowed its Roche Lobe at any time prior to the current timestep.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

EXPERIENCED SN TYPE

Header string: Experienced SN Type

Data type: INT

COMPAS variable: <derived from BaseStar::m_SupernovaDetails.events.past> The type of supernova event experienced by the star prior to the current timestep.

Printed as one of $\{NONE = 0, CCSN = 1, ECSN = 2, PISN = 4, PPISN = 8, USSN = 16\}$

(see section Supernova events/states below for explanation)

EXPERIENCED USSN

Header string: Experienced USSN

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the star exploded as an ultra-stripped supernova at any time prior to the

current timestep.

FALLBACK FRACTION

Header string: Fallback Fraction

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.fallbackFraction

Fallback fraction during a supernova.

HE CORE MASS

Header string: Mass He Core

Data type: DOUBLE

COMPAS variable: BaseStar::m HeCoreMass

Helium core mass (Msol).

HE CORE MASS AT COMMON ENVELOPE

Header string: Mass He Core@CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m_CEDetails.HeCoreMass Helium core mass (Msol) at the onset of unstable RLOF leading to the CE..

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

HE CORE MASS AT COMPACT OBJECT FORMATION

Header string: Mass He Core@CO

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.HeCoreMassAtCOFormation

Helium core mass (Msol) at immediately prior to a of supernova.

HYDROGEN POOR

Header string: Hydrogen Poor

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.hydrogenContent>

Flag to indicate if star is hydrogen poor.

HYDROGEN RICH

Header string: Hydrogen Rich

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.hydrogenContent>

Flag to indicate if star is hydrogen rich.

ID

Header string: ID

Data type: UNSIGNED LONG INT

COMPAS variable: BaseStar::m ObjectId

Unique object identifier for c++ object – used in debugging to identify objects.

INITIAL STELLAR TYPE

Header string: Stellar Type@ZAMS

Data type: INT

COMPAS variable: BaseStar::m InitialStellarType

Stellar type at zero age main-sequence (per Hurley at al. 2000).

Note that this property has the same header string as INITIAL_STELLAR_TYPE_NAME below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

INITIAL STELLAR TYPE NAME

Header string: Stellar_Type@ZAMS

Data type: STRING

COMPAS variable: <derived from BaseStar::m_InitialStellarType>
Stellar type at zero age main-sequence name (per Hurley at al. 2000).

e.g. "First_Giant_Branch", "Core_Helium_Burning", "Early_Asymptotic_Giant_Branch", etc. Note that this property has the same header string as INITIAL_STELLAR_TYPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

IS CCSN

Header string: CCSN Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.current>

Flag to indicate whether the star is currently a core-collapse supernova.

IS ECSN

Header string: ECSN Data type: BOOL

COMPAS variable: derived from BaseStar::m_SupernovaDetails.events.current> Flag to indicate whether the star is currently an electron-capture supernova.

IS PISN

Header string: PISN Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.current>

Flag to indicate whether the star is currently a pair-instability supernova.

IS PPISN

Header string: PPISN Data type: BOOL

COMPAS variable: <derived from BaseStar::m_SupernovaDetails.events.current> Flag to indicate whether the star is currently a pulsational pair-instability supernova.

IS RLOF

Header string: RLOF Data type: BOOL

COMPAS variable: <derived from BinaryConstituentStar::m_RLOFDetails.isRLOF> Flag to indicate whether the star is currently undergoing Roche Lobe overflow. Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

IS USSN

Header string: USSN Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.current>

Flag to indicate whether the star is currently an ultra-stripped supernova.

KICK VELOCITY

Header string: Applied Kick Velocity

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.kickVelocity

Magnitude of natal kick velocity (kms^-1) received during a supernova.

Calculate using the drawn kick velocity (see BaseStar::CalculateSNKickVelocity() for details)

LAMBDA AT COMMON ENVELOPE

Header string: Lambda@CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.lambda

Common-envelope lambda parameter calculated at the unstable RLOF leading to the CE. Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

LAMBDA DEWI

Header string: Dewi Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.dewi

Common envelope lambda parameter calculated as per Dewi & Tauris (2000) using the fit from

Appendix A of Claeys et al. (2014).

LAMBDA FIXED

Header string: Lambda Fixed

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.fixed

Universal common envelope lambda parameter specified by the user (program option --common-

envelope-lambda).

LAMBDA KRUCKOW

Header string: Kruckow Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.kruckow

Common envelope lambda parameter calculated as per Kruckow et al. (2016) with the alpha

exponent set by OPTIONS->CommonEnvelopeSlopeKruckow().

From Kruckow et al. 2016 (arXiv:1610.04417), fig 1.

Spectrum fit to the region bounded by the upper and lower limits as shown in Kruckow+ 2016

LAMBDA KRUCKOW BOTTOM

Header string: Kruckow Bottom

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.kruckowBottom

Common envelope lambda parameter calculated as per Kruckow et al. (2016) with the alpha

exponent set to -1.0.

From Kruckow et al. 2016 (arXiv:1610.04417), fig 1.

Spectrum fit to the region bounded by the upper and lower limits as shown in Kruckow+ 2016

LAMBDA KRUCKOW MIDDLE

Header string: Kruckow Middle

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.kruckowMiddle

Common envelope lambda parameter calculated as per Kruckow et al. (2016) with the alpha

exponent set to -4/5.

From Kruckow et al. 2016 (arXiv:1610.04417), fig 1.

Spectrum fit to the region bounded by the upper and lower limits as shown in Kruckow+ 2016

LAMBDA KRUCKOW TOP

Header string: Kruckow Top

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.kruckowTop

Common envelope lambda parameter as per Kruckow et al. (2016) with the alpha exponent set to -

2/3.

From Kruckow et al. 2016 (arXiv:1610.04417), fig 1.

Spectrum fit to the region bounded by the upper and lower limits as shown in Kruckow+ 2016

LAMBDA LOVERIDGE

Header string: Loveridge Data type: DOUBLE

COMPAS variable: BaseStar::m_Lambdas.loveridge

Common envelope lambda parameter calculated per Webbink 1984 & Loveridge et al. 2011.

LAMBDA LOVERIDGE WINDS

Header string: Loveridge Winds

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.loveridgeWinds

Common envelope lambda parameter calculated per Webbink 1984 & Loveridge et al. 2011

including winds.

Note: currently this evaluates the same as BINDING ENERGY LOVERIDGE

LAMBDA NANJING

Header string: Lambda Nanjing

Data type: DOUBLE

COMPAS variable: BaseStar::m Lambdas.nanjing

Common envelope lambda parameter calculated as per Xu & Li (2010).

From X.-J. Xu and X.-D. Li arXiv:1004.4957 (v1, 28Apr2010) as implemented in STARTRACK

LBV PHASE FLAG

Header string: LBV Phase Flag

Data type: BOOL

COMPAS variable: BaseStar::m LBVphaseFlag

Flag to indicate if the star ever entered the luminous blue variable phase.

LUMINOSITY

Header string: Luminosity Data type: DOUBLE

COMPAS variable: BaseStar::m Luminosity

Luminosity (Lsol).

LUMINOSITY POST COMMON ENVELOPE

Header string: Luminosity>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.luminosity

Luminosity (Lsol) immediately following common envelope event.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

LUMINOSITY PRE COMMON ENVELOPE

Header string: Luminosity<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.luminosity

Luminosity (Lsol) at the onset of unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

MASS

Header string: Mass Data type: DOUBLE

COMPAS variable: BaseStar::m Mass

Mass (Msol).

MASS 0

Header string: Mass_0 Data type: DOUBLE

COMPAS variable: BaseStar::m Mass0

Effective initial mass (Msol).

MASS LOSS DIFF

Header string: dmWinds Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m MassLossDiff

The amount of mass lost due to winds (Msol)

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

MASS TRANSFER CASE INITIAL

Header string: MT Case

Data type: INT

COMPAS variable: BinaryConstituentStar::m MassTransferCase

Indicator of mass transfer type when first RLOF occurs, if any (one of {NONE, A, B, C, D})

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

MASS TRANSFER DIFF

Header string: dmMT Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m MassTransferDiff

Amount of mass (Msol) accreted or donated during a mass transfer episode.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

MDOT

Header string: Mdot Data type: DOUBLE

COMPAS variable: BaseStar::m Metallicity

Mass loss rate (Msol yr^-1).

MEAN ANOMALY

Header string: SN_Kick_Mean_Anomaly

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.meanAnomaly

Mean anomaly of supernova kick, supplied by user in grid file, default = random number between 0

and 2pi.

See https://en.wikipedia.org/wiki/Mean anomaly for explanation

METALLICITY

Header string: Metallicity@ZAMS

Data type: DOUBLE

COMPAS variable: BaseStar::m Metallicity

Metallicity.

MZAMS

Header string: Mass@ZAMS

Data type: DOUBLE

COMPAS variable: BaseStar::m MZAMS

ZAMS Mass (Msol).

NUCLEAR TIMESCALE

Header string: Tau_Nuclear

Data type: DOUBLE

COMPAS variable: BaseStar::m_NuclearTimescale

Nuclear timescale (Myr).

NUCLEAR TIMESCALE POST COMMON ENVELOPE

Header string: Tau Nuclear>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.nuclearTimescale

Nuclear timescale (Myr) immediately following common envelope event.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

NUCLEAR TIMESCALE PRE COMMON ENVELOPE

Header string: Tau Nuclear<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.nuclearTimescale

Nuclear timescale (Myr) at the onset of unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

OMEGA

Header string: Omega Data type: DOUBLE

COMPAS variable: BaseStar::m Omega

Angular frequency (yr^-1).

OMEGA BREAK

Header string: Omega Break

Data type: DOUBLE

COMPAS variable: BaseStar::m OmegaBreak

Break-up angular frequency (yr^-1).

OMEGA ZAMS

Header string: Omega@ZAMS

Data type: DOUBLE

COMPAS variable: BaseStar::m OmegaZAMS

Angular frequency at ZAMS (yr^-1).

ORBITAL ENERGY POST SUPERNOVA

Header string: Orbital Energy>SN

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m PostSNeOrbitalEnergy

Absolute value of orbital energy immediately following supernova event (Msol AU^2 yr^-2).

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

ORBITAL ENERGY PRE SUPERNOVA

Header string: Orbital Energy<SN

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m_PreSNeOrbitalEnergy Orbital energy immediately prior to supernova event (Msol AU^2 yr^-2).

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

PULSAR MAGNETIC FIELD

Header string: Pulsar Mag Field

Data type: DOUBLE

COMPAS variable: BaseStar::m PulsarDetails.magneticField

Pulsar magnetic field strength (G).

PULSAR SPIN DOWN RATE

Header string: Pulsar_Spin_Down

Data type: DOUBLE

COMPAS variable: BaseStar::m PulsarDetails.spinDownRate

Pulsar spin-down rate.

PULSAR SPIN FREQUENCY

Header string: Pulsar Spin Freq

Data type: DOUBLE

COMPAS variable: BaseStar::m PulsarDetails.spinFrequency

Pulsar spin angular frequency (rads s^-1).

PULSAR SPIN PERIOD

Header string: Pulsar Spin Period

Data type: DOUBLE

COMPAS variable: BaseStar::m PulsarDetails.spinPeriod

Pulsar spin period (ms).

RADIAL EXPANSION TIMESCALE

Header string: Tau_Radial Data type: DOUBLE

COMPAS variable: BaseStar::m RadialExpansionTimescale

e-folding time (Myr) of stellar radius.

RADIAL EXPANSION TIMESCALE POST COMMON ENVELOPE

Header string: Tau Radial>CE

Data type: DOUBLE

COMPAS variable: : BinaryConstituentStar::m CEDetails.postCEE.radialExpansionTimescale

e-folding time (Myr) of stellar radius immediately following common envelope event. Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

RADIAL EXPANSION TIMESCALE PRE COMMON ENVELOPE

Header string: Tau Radial<CE

Data type: DOUBLE

COMPAS variable: : BinaryConstituentStar::m CEDetails.preCEE.radialExpansionTimescale

e-folding time (Myr) of stellar radius at the onset of unstable RLOF leading to the CE. Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

RADIUS

Header string: Radius Data type: DOUBLE

COMPAS variable: BaseStar::m Radius

Radius (Rsol).

RANDOM SEED

Header string: SEED

Data type: UNSIGNED LONG

COMPAS variable: BaseStar::m_RandomSeed Seed for random number generator for this star.

RECYCLED NEUTRON STAR

Header string: Recycled NS

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the object was a recycled neutron star at any time prior to the current

timestep (was a neutron star accreting mass).

RLOF ONTO NS

Header string: RLOF->NS

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the star transferred mass to a neutron star at any time prior to the current

timestep.

RUNAWAY

Header string: Runaway

Data type: BOOL

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.past>

Flag to indicate whether the star was unbound by a supernova event at any time prior to the current

timestep.

(Unbound after supernova event and not a WD, NS, BH or MR)

RZAMS

Header string: R@ZAMS Data type: DOUBLE

COMPAS variable: BaseStar::m RZAMS

ZAMS Radius (Rsol)

SN TYPE

Header string: SN Type

Data type: INT

COMPAS variable: <derived from BaseStar::m SupernovaDetails.events.current>

The type of supernova event currently being experienced by the star.

Printed as one of $\{NONE = 0, CCSN = 1, ECSN = 2, PISN = 4, PPISN = 8, USSN = 16\}$

(see section Supernova events/states below for explanation)

STELLAR TYPE

Header string: Stellar Type

Data type: INT

COMPAS variable: BaseStar::m StellarType

Stellar type (per Hurley at al. 2000)

Note that this property has the sam.e header string as STELLAR TYPE NAME below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE NAME

Header string: Stellar Type

Data type: STRING

COMPAS variable: <derived from BasteStar::m StellarType>

Stellar type name (per Hurley at al. 2000).

e.g. "First Giant Branch", "Core Helium Burning", "Early Asymptotic Giant Branch", etc. Note that this property has the same header string as STELLAR TYPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE PREV

Header string: Stellar Type Prev

Data type: INT

COMPAS variable: BaseStar::m StellarTypePrev

Stellar type (per Hurley at al. 2000) at previous timestep.

Note that this property has the same header string as STELLAR TYPE PREV NAME below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE PREV NAME

Header string: Stellar Type Prev

Data type: STRING

COMPAS variable: <derived from BaseStar::m StellarTypePrev> Stellar type name (per Hurley at al. 2000) at previous timestep.

e.g. "First Giant Branch", "Core Helium Burning", "Early Asymptotic Giant Branch", etc. Note that this property has the same header string as STELLAR TYPE PREV above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SUPERNOVA KICK VELOCITY MAGNITUDE RANDOM NUMBER

Header string: SN Kick Magnitude Random Number

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.kickVelocityRandom

Random number for drawing the supernova kick velocity magnitude (if required).

Either supplied by user in grid file, default = drawn from uniform random distribution 0..1

SUPERNOVA PHI

Header string: SN Kick Phi

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.phi

Angle between 'x' and 'y', both in the orbital plane of supernovae vector (rad).

Either supplied by user in grid file, default = drawn from uniform random distribution 0..2pi

SUPERNOVA THETA

Header string: SN_Kick_Theta

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.theta

Angle between the orbital plane and the 'z' axis of supernovae vector (rad).

Either supplied by user in grid file, default = drawn from specified distribution (option –

kick direction)

TEMPERATURE

Header string: Teff Data type: DOUBLE

COMPAS variable: BaseStar::m Temperature

Effective temperature (Tsol).

TEMPERATURE_POST_COMMON_ENVELOPE

Header string: Teff>CE Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m_CEDetails.postCEE.temperature Effective temperature (Tsol) immediately following common envelope event.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

TEMPERATURE PRE COMMON ENVELOPE

Header string: Teff<CE Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.temperature

Effective temperature (Tsol) at the unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

THERMAL TIMESCALE

Header string: Tau_Thermal

Data type: DOUBLE

COMPAS variable: BaseStar::m ThermalTimescale

Thermal timescale (Myr).

THERMAL TIMESCALE POST COMMON ENVELOPE

Header string: Tau Thermal>CE

Data type: DOUBLE

COMPAS variable: : BinaryConstituentStar::m CEDetails.postCEE.thermalTimescale

Thermal timescale immediately following common envelope event (Myr).

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

THERMAL TIMESCALE PRE COMMON ENVELOPE

Header string: Tau Thermal<CE

Data type: DOUBLE

 $COMPAS\ variable:: Binary Constituent Star:: m_CED etails.pre CEE. thermal Time scale$

Thermal timescale (Myr) at the onset of the unstable RLOF leading to the CE.

Applies only to constituent stars of a binary system (i.e. does not apply to SSE star)

TIME

Header string: Time Data type: DOUBLE

COMPAS variable: BaseStar::m Time

Time since ZAMS (Myr).

TIMESCALE MS

Header string: tMS
Data type: DOUBLE

COMPAS variable: BaseStar::m Timescales[tMS]

Main Sequence timescale (Myr).

TOTAL MASS AT COMPACT OBJECT_FORMATION

Header string: Mass Total@CO

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.totalMassAtCOFormation

Total mass of the star at the beginning of a supernova event (Msol).

TRUE ANOMALY

Header string: True Anomaly(psi)

Data type: DOUBLE

COMPAS variable: BaseStar::m SupernovaDetails.trueAnomaly

True anomaly (rad) calculated using Kepler's equation.

See https://en.wikipedia.org/wiki/True anomaly for explanation

ZETA HURLEY

Header string: Zeta_Hurley

Data type: DOUBLE

COMPAS variable: BaseStar::m Zetas.hurley

Adiabatic exponent calculated per Hurley et al. (2002) using core mass.

ZETA HURLEY HE

Header string: Zeta Hurley He

Data type: DOUBLE

COMPAS variable: BaseStar::m Zetas.hurleyHe

Adiabatic exponent calculated per (Hurley et al. 2002) using He core mass.

ZETA SOBERMAN

Header string: Zeta Soberman

Data type: DOUBLE

COMPAS variable: BaseStar::m Zetas.soberman

Adiabatic exponent calculated per Soberman, Phinney, van den Heuvel (1997) using core mass.

ZETA SOBERMAN HE

Header string: Zeta_Soberman_He

Data type: DOUBLE

COMPAS variable: BaseStar::m_Zetas.sobermanHe

Adiabatic exponent calculated per Soberman, Phinney, van den Heuvel (1997) using He-core mass.

Supernova events/states

Supernova events/states, both current ("is") and past ("experienced"), are stored within COMPAS as bit maps. That means different values can be ORed or ANDed into the bit map, so that various events or states can be set concurrently.

The values shown below for the SN_EVENT type are powers of 2 so that they can be used in a bit map and manipulated with bit-wise logical operators. Any of the individual supernova event/state types that make up the SN_EVENT type can be set independently of any other event/state.

```
enum class SN EVENT: int {
 NONE
                  = 1,
 CCSN
 ECSN
                  = 2,
 PISN
                  =4.
                  = 8.
 PPISN
 USSN
                  = 16,
 RUNAWAY
                  = 32,
 RECYCLED NS = 64,
 RLOF ONTO NS = 128
};
const COMPASUnorderedMap<SN_EVENT, std::string> SN_EVENT_LABEL = {
                                     "No Supernova" },
  { SN EVENT::NONE,
                                     "Core Collapse Supernova" },
   SN EVENT::CCSN,
                                     "Electron Capture Supernova" },
   SN EVENT::ECSN,
                                     "Pair Instability Supernova" },
   SN EVENT::PISN,
   SN EVENT::PPISN,
                                     "Pulsational Pair Instability Supernova" },
                                     "Ultra Stripped Supernova" },
   SN EVENT::USSN,
   SN EVENT::RUNAWAY,
                                     "Runaway Companion" },
   SN EVENT::RECYCLED NS, "Recycled Neutron Star" },
   SN EVENT::RLOF ONTO NS,
                                     "Donated Mass to Neutron Star through RLOF" }
};
```

A convenience function (shown below) is provided in utils.cpp to interpret the bit map. Given an SN EVENT bitmap (current or past), it returns (in priority order):

```
SN_EVENT::CCSN iff CCSN bit is set and USSN bit is not set SN_EVENT::ECSN iff ECSN bit is set SN_EVENT::PISN iff PISN bit is set SN_EVENT::PISN iff PPISN bit is set SN_EVENT::USSN iff USSN bit is set otherwise
```

```
\mbox{*} Returns a single SN type based on the SN_EVENT parameter passed
 * Returns (in priority order):
        SN_EVENT::CCSN iff CCSN bit is set and USSN bit is not set SN_EVENT::ECSN iff ECSN bit is set SN_EVENT::PISN iff PISN bit is set
        SN EVENT:: PPISN iff PPISN bit is set
        SN_EVENT::USSN iff USSN bit is set
        SN_EVENT::NONE otherwise
 * @param [IN] p_SNEvent
                                                   SN EVENT mask to check for SN event type
 * @return
                                                                        SN EVENT
 */
SN EVENT SNEventType(const SN EVENT p SNEvent) {
     if ((p_SNEvent & (SN_EVENT::CCSN | SN_EVENT::USSN)) == SN_EVENT::CCSN )
        return SN_EVENT::CCSN;
     if ((p_SNEvent & SN_EVENT::ECSN ) == SN_EVENT::ECSN ) return SN_EVENT::ECSN;
if ((p_SNEvent & SN_EVENT::PISN ) == SN_EVENT::PISN ) return SN_EVENT::PISN;
if ((p_SNEvent & SN_EVENT::PPISN) == SN_EVENT::PPISN ) return SN_EVENT::PPISN;
if ((p_SNEvent & SN_EVENT::USSN ) == SN_EVENT::USSN ) return SN_EVENT::USSN;
     return SN EVENT::NONE;
```

Appendix C – Log File Record Specification: Binary Properties

As described in **Standard Log File Record Specifiers**, when specifying known properties in a log file record specification record, the property name must be prefixed with the property type.

Currently there is a single binary property type available for use: BINARY_PROPERTY.

For example, to specify the property SEMI_MAJOR_AXIS_PRE_COMMON_ENVELOPE for a binary star being evolved in BSE, use:

BINARY_PROPERTY::SEMI_MAJOR_AXIS_PRE_COMMON_ENVELOPE

Following is the list of binary properties available for inclusion in log file record specifiers.

Binary Properties

CIRCULARIZATION TIMESCALE

Header string: Tau_Circ Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CircularizationTimescale

Tidal circularisation timescale (Myr).

COMMON ENVELOPE ALPHA

Header string: CE_Alpha Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_CEDetails.alpha

Common envelope alpha (efficiency) parameter

User-supplied via command line option --common-envelope-alpha.

COMMON ENVELOPE AT LEAST ONCE

Header string: CEE Data type: BOOL

COMPAS variable: <derived from BaseBinaryStar::m CEDetails.CEEcount>

Flag to indicate if there has been at least one common envelope event.

COMMON ENVELOPE EVENT COUNT

Header string: CE_Event_Count Data type: UNSIGNED INT

COMPAS variable: BaseBinaryStar::m CEDetails.CEEcount

The number of common envelope events.

DIMENSIONLESS KICK VELOCITY

Header string: Kick Velocity(uK)

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m uK

Dimensionless kick velocity supplied by user (see option --fix-dimensionless-kick-velocity).

DOUBLE CORE COMMON ENVELOPE

Header string: Double Core CE

Data type: BOOL

COMPAS variable: BaseBinaryStar::m CEDetails.doubleCoreCE

Flag to indicate double-core common envelope.

DT

Header string: dT Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m Dt

Current timestep (Myr).

ECCENTRICITY

Header string: Eccentricity Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m Eccentricity

Orbital eccentricity.

ECCENTRICITY AT DCO FORMATION

Header string: Eccentricity@DCO

Data type: DOUBLE

Orbital eccentricity at DCO formation.

ECCENTRICITY INITIAL

Header string: Eccentricity@ZAMS

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m EccentricityInitial

Orbital eccentricity at ZAMS.

Supplied by user via grid file or sampled from distribution (see –eccentricity-distribution option)

(default)

ECCENTRICITY POST COMMON ENVELOPE

Header string: Eccentricity>CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.postCEE.eccentricity

Eccentricity immediately following common envelope event.

ECCENTRICITY PRE SUPERNOVA

Header string: Eccentricity<SN

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m EccentricityPreSN

Current timestep (Myr)

Eccentricity of the binary immediately prior to supernova event

ECCENTRICITY PRE COMMON ENVELOPE

Header string: Eccentricity Data type: DOUBLE<CE

COMPAS variable: BaseBinaryStar::m CEDetails.preCEE.eccentricity

Eccentricity at the onset of RLOF leading to the CE.

ECCENTRICITY PRIME

Header string: Eccentricity Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m EccentricityPrime

Post-SN eccentricity.

ERROR

Header string: Error Data type: INT

COMPAS variable: <derived from BaseBinaryStar::m Error>

Error number (if error condition exists, else 0).

ID

Header string: ID

Data type: UNSIGNED LONG INT

COMPAS variable: BaseBinaryStar::m ObjectId

Unique object identifier for c++ object – used in debugging to identify objects.

IMMEDIATE RLOF POST COMMON ENVELOPE

Header string: Immediate RLOF>CE

Data type: BOOL

COMPAS variable: BaseBinaryStar::m RLOFDetails.immediateRLOFPostCEE

Flag to indicate if either star overflows its Roche lobe immediately following common envelope

event.

LUMINOUS BLUE VARIABLE FACTOR

Header string: LBV Multiplier

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_LBVfactor Luminous blue variable wind mass loss multiplier

User-supplied via option --luminous-blue-variable-multiplier.

MASS 1 FINAL

Header string: Core_Mass_1

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m Mass1Final

Mass of the primary star (Msol) after losing its envelope (assumes complete loss of envelope).

MASS 1 POST COMMON ENVELOPE

Header string: Mass 1>CE

Data type: DOUBE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.mass

Mass of the primary star (Msol) immediately following common envelope event.

MASS 1 PRE COMMON ENVELOPE

Header string: Mass 1<CE

Data type: DOUBE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.mass

Mass of the primary star (Msol) immediately prior to common envelope event.

MASS 2 FINAL

Header string: Core Mass 2

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m Mass2Final

Mass of the secondary star (Msol) after losing its envelope (assumes complete loss of envelope).

MASS 2 POST COMMON ENVELOPE

Header string: Mass 2>CE

Data type: DOUBE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.mass

Mass of the secondary star (Msol) immediately following common envelope event.

MASS 2 PRE COMMON ENVELOPE

Header string: Mass 2<CE

Data type: DOUBE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.mass

Mass of the secondary star (Msol) immediately prior to common envelope event.

MASS ENV 1

Header string: Mass_Env_1

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m MassEnv1

Envelope mass of the primary star (Msol).

MASS ENV 2

Header string: Mass_Env_2

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m MassEnv2

Envelope mass of the secondary star (Msol).

MASSES EQUILIBRATED

Header string: Equilibrated

Data type: BOOL

COMPAS variable: BaseBinaryStar::m MassesEquilibrated

Flag to indicate whether chemically homogeneous stars had masses equilibrated and orbit circular-

ised due to Roche lobe overflow during evolution.

MASSES EQUILIBRATED AT BIRTH

Header string: Equilibrated At Birth

Data type: BOOL

COMPAS variable: BaseBinaryStar::m MassesEquilibratedAtBirth

Flag to indicate whether stars had masses equilibrated and orbit circularised at birth due to Roche

lobe overflow.

MASS TRANSFER TRACKER HISTORY

Header string: MT History

Data type: INT

COMPAS variable: <derived from BaseBinaryStar::m MassTransferTrackerHistory>

Indicator of mass transfer history for the binary.

Will be printed as one of:

NO MASS TRANSFER = 0

STABLE FROM 1 TO 2 = 1

 $STABLE_FROM_2_TO_1 = 2$

CE FROM 1 TO 2 = 3

 $CE_FROM_2_TO_1 = 4$

CE_DOUBLE_CORE = 5

CE BOTH MS = 6

CE MS WITH CO = 7

MERGES IN HUBBLE TIME

Header string: Merges_Hubble_Time

Data type: BOOL

COMPAS variable: BaseBinaryStar::m MergesInHubbleTime

Flag to indicate if the binary compact remnants merge within a Hubble time.

OPTIMISTIC COMMON ENVELOPE

Header string: Optimistic CE

Data type: BOOL

COMPAS variable: BaseBinaryStar::m CEDetails.optimisticCE

Flag that returns TRUE if we have a Hertzsprung-gap star, and we allow it to survive the CE.

ORBITAL VELOCITY

Header string: Orbital Velocity

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_OrbitalVelocity

Orbital velocity (km s^-1).

ORBITAL VELOCITY PRE SUPERNOVA

Header string: Orbital Velocity<SN

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_OrbitalVelocityPreSN Orbital velocity (km s^-1) immediately prior to supernova event.

RADIUS_1_POST_COMMON_ENVELOPE

Header string: Radius 1>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.radius

Radius of the primary star (Rsol) immediately following common envelope event.

RADIUS 1 PRE COMMON ENVELOPE

Header string: Radius 1<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.radius

Radius of the primary star (Rsol) at the onset of RLOF leading to the common-envelope episode.

RADIUS 2 POST COMMON ENVELOPE

Header string: Radius 2>CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.radius

Radius of the secondary star (Rsol) immediately following common envelope event.

RADIUS 2 PRE COMMON ENVELOPE

Header string: Radius 2<CE

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m CEDetails.preCEE.radius

Radius of the secondary star (Rsol)at the onset of RLOF leading to the common-envelope episode.

RANDOM SEED

Header string: SEED

Data type: UNSIGNED LONG

COMPAS variable: BaseBinaryStar::m_RandomSeed Seed for random number generator for this binary star.

(supplied by user via option—random-seed, default generated from system time)

ROCHE LOBE RADIUS 1

Header string: RocheLobe 1/a

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m RocheLobeRadius

Roche radius of the primary star (Rsol).

ROCHE LOBE RADIUS 2

Header string: RocheLobe_2/a

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m RocheLobeRadius

Roche radius of the secondary star (Rsol).

ROCHE LOBE RADIUS 1 POST COMMON ENVELOPE

Header string: RocheLobe 1>CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.postCEE.rocheLobe1to2

Roche radius of the primary star (Rsol) immediately following common envelope event.

ROCHE LOBE RADIUS 2 POST COMMON ENVELOPE

Header string: RocheLobe 2>CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.postCEE.rocheLobe2to1

Roche radius of the secondary star (Rsol) immediately following common envelope event.

ROCHE LOBE RADIUS 1 PRE COMMON ENVELOPE

Header string: RocheLobe 1<CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.preCEE.rocheLobe1to2

Roche radius of the primary star (Rsol) at the onset of RLOF leading to the common-envelope epi-

sode.

ROCHE LOBE RADIUS 2 PRE COMMON ENVELOPE

Header string: RocheLobe 2<CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.preCEE.rocheLobe2to1

Roche radius of the secondary star (Rsol) at the onset of RLOF leading to the common-envelope

episode.

ROCHE LOBE TRACKER 1

Header string: Radius_1/RL

Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m RocheLobeTracker

Ratio of the primary star's stellar radius to Roche radius (R/RL), evaluated at periapsis

ROCHE LOBE TRACKER 2

Header string: Radius_2/RL Data type: DOUBLE

COMPAS variable: BinaryConstituentStar::m RocheLobeTracker

Ratio of the secondary star's stellar radius to Roche radius (R/RL), evaluated at periapsis.

SECONDARY TOO SMALL FOR DCO

Header string: Secondary << DCO

Data type: BOOL

COMPAS variable: BaseBinaryStar::m SecondaryTooSmallForDCO

Flag to indicate that the secondary star was born too small for the binary to evolve into a DCO.

SEMI MAJOR AXIS AT DCO FORMATION

Header string: Separation@DCO

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m SemiMajorAxisAtDCOFormation

Semi-major axis(AU) at DCO formation.

SEMI MAJOR AXIS INITIAL

Header string: Separation@ZAMS

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m SemiMajorAxisInitial

Semi-major axis (AU) at ZAMS.

SEMI MAJOR AXIS POST COMMON ENVELOPE

Header string: Separation>CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_CEDetails.postCEE.semiMajorAxis Semi-major axis (AU) immediately following common envelope event.

SEMI MAJOR AXIS PRE SUPERNOVA

Header string: Separation<SN

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_SemiMajorAxisPreSN Semi-major axis (AU) immediately prior to supernova event.

Note that this property has the same header string as

SEMI_MAJOR_AXIS_PRE_SUPERNOVA_RSOL below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SEMI MAJOR AXIS PRE SUPERNOVA RSOL

Header string: Separation<SN

Data type: DOUBLE

COMPAS variable: <derived from BaseBinaryStar::m SemiMajorAxisPreSN>

Semi-major axis (Rsol) immediately prior to supernova event.

Note that this property has the same header string as SEMI_MAJOR_AXIS_PRE_SUPERNOVA above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SEMI MAJOR AXIS PRE COMMON ENVELOPE

Header string: Separation<CE

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m CEDetails.preCEE.semiMajorAxis

Semi-major axis(AU) at the onset of RLOF leading to the common-envelope episode.

SEMI MAJOR AXIS PRIME

Header string: Separation Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m SemiMajorAxisPrime

Semi-major axis of the binary (AU).

Note that this property has the same header string as SEMI_MAJOR_AXIS_PRIME_RSOL below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SEMI MAJOR AXIS PRIME RSOL

Header string: Separation Data type: DOUBLE

COMPAS variable: <derived from BaseBinaryStar::m SemiMajorAxisPrime>

Semi-major axis of the binary (RSOL).

Note that this property has the same header string as SEMI_MAJOR_AXIS_PRIME above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SIMULTANEOUS RLOF

Header string: Simultaneous RLOF

Data type: BOOL

COMPAS variable: BaseBinaryStar::m RLOFDetails.simultaneousRLOF

Flag to indicate that both stars are undergoing RLOF.

STABLE_RLOF_POST_COMMON_ENVELOPE

Header string: Stable RLOF>CE

Data type: BOOL

COMPAS variable: BaseBinaryStar::m RLOFDetails.stableRLOFPostCEE

Flag to indicate stable mass transfer after common envelope event.

STELLAR MERGER

Header string: Merger Data type: BOOL

COMPAS variable: BaseBinaryStar::m StellarMerger

Flag to indicate the stars merged (stars were touching) during evolution.

STELLAR MERGER AT BIRTH

Header string: Merger At Birth

Data type: BOOL

COMPAS variable: BaseBinaryStar::m_StellarMergerAtBirth Flag to indicate the stars merged (stars were touching) at birth.

STELLAR TYPE 1 POST COMMON ENVELOPE

Header string: Stellar Type 1>CE

Data type: INT

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type (per Hurley at al. 2000) of the primary star immediately following common envelope event

Note that this property has the same header string as

STELLAR_TYPE_NAME_1_POST_COMMON_ENVELOPE below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE 1 PRE COMMON ENVELOPE

Header string: Stellar Type 1<CE

Data type: INT

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type (per Hurley at al. 2000) of the primary star at the onset of RLOF leading to the common-envelope episode.

Note that this property has the same header string as

STELLAR_TYPE_NAME_1_PRE_COMMON_ENVELOPE below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE 2 POST COMMON ENVELOPE

Header string: Stellar Type 2>CE

Data type: INT

COMPAS variable: BinaryConstituentStar::m_CEDetails.postCEE.stellarType Stellar type of the secondary star immediately following common envelope event.

Note that this property has the same header string as

STELLAR_TYPE_NAME_2_POST_COMMON_ENVELOPE below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE 2 PRE COMMON ENVELOPE

Header string: Stellar Type 2<CE

Data type: INT

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type (per Hurley at al. 2000) of the secondary star at the onset of RLOF leading to the common-envelope episode.

Note that this property has the same header string as

STELLAR_TYPE_NAME_2_PRE_COMMON_ENVELOPE below. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE NAME 1 POST COMMON ENVELOPE

Header string: Stellar Type 1>CE

Data type: STRING

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type name (per Hurley at al. 2000) of the primary star immediately following common envelope event.

 $e.g. \ "First_Giant_Branch", "Core_Helium_Burning", "Early_Asymptotic_Giant_Branch", etc.$

Note that this property has the same header string as

STELLAR_TYPE_1_POST_COMMON_ENVELOPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE NAME 1 PRE COMMON ENVELOPE

Header string: Stellar_Type_1<CE

Data type: STRING

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type name (per Hurley at al. 2000) of the primary star at the onset of RLOF leading to the common-envelope episode.

e.g. "First_Giant_Branch", "Core_Helium_Burning", "Early_Asymptotic_Giant_Branch", etc.

Note that this property has the same header string as

STELLAR_TYPE_1_PRE_COMMON_ENVELOPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE NAME 2 POST COMMON ENVELOPE

Header string: Stellar Type 2>CE

Data type: STRING

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type name (per Hurley at al. 2000) of the secondary star immediately following common envelope event.

e.g. "First_Giant_Branch", "Core_Helium_Burning", "Early_Asymptotic_Giant_Branch", etc.

Note that this property has the same header string as

STELLAR_TYPE_2_POST_COMMON_ENVELOPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

STELLAR TYPE NAME 2 PRE COMMON ENVELOPE

Header string: Stellar Type 2<CE

Data type: STRING

COMPAS variable: BinaryConstituentStar::m CEDetails.postCEE.stellarType

Stellar type name (per Hurley at al. 2000) of the secondary star at the onset of RLOF leading to the common-envelope episode.

e.g. "First_Giant_Branch", "Core_Helium_Burning", "Early_Asymptotic_Giant_Branch", etc.

Note that this property has the same header string as

STELLAR_TYPE_2_PRE_COMMON_ENVELOPE above. It is expected that one or the other is printed in any file, but not both. If both are printed then the file will contain two columns with the same header string.

SUPERNOVA STATE

Header string: Supernova State

Data type: INT

COMPAS variable: <derived from BaseBinaryStar::m SupernovaState>

Indicates which star(s) went supernova.

Will be printed as one of:

0 = no supernova

1 =Star 1 is the supernova

2 = Star 2 is the supernova

3 = Both stars are supernovae

SYNCHRONIZATION TIMESCALE

Header string: Tau_Sync Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m SynchronizationTimescale

Tidal synchronisation timescale (Myr).

SYSTEMIC_VELOCITY

Header string: Systemic Velocity

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_SystemicVelocity Post-supernova systemic (center-of-mass) velocity (km s^-1).

TIME

Header string: Time Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m Time

Time (Myrs) since ZAMS.

TIME TO COALESCENCE

Header string: Coalescence Time

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m TimeToCoalescence

Time between formation of double compact object and gravitational-wave driven merger (Myr).

TOTAL ANGULAR MOMENTUM PRIME

Header string: Ang Momentum Total

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m TotalAngularMomentumPrime

Total angular momentum calculated using regular conservation of energy (Msol AU² yr¹-1).

TOTAL ENERGY PRIME

Header string: Energy Total

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m TotalAngularMomentumPrime

Total energy calculated using regular conservation of energy (Msol AU² yr⁻¹).

UNBOUND

Header string: Unbound Data type: BOOL

COMPAS variable: BaseBinaryStar::m Unbound

Flag to indicate the binary is unbound (or has become unbound after a supernova event).

WOLF RAYET FACTOR

Header string: WR_Multiplier

Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m_WolfRayetFactor Multiplicative constant for Wolf-Rayet mass loss rate User-supplied via option --wolf-rayet-multiplier.

ZETA LOBE

Header string: Zeta_Lobe Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m ZetaLobe

The logarithmic derivative of Roche lobe radius with respect to donor mass for q = Md / Ma at the

onset of the RLOF.

ZETA STAR

Header string: Zeta_Star Data type: DOUBLE

COMPAS variable: BaseBinaryStar::m ZetaStar

Mass-radius exponent of the star at the onset of the RLOF. Calculated differently based on the

value of -zeta-prescription.

Appendix D – Log File Record Specification: Program Options

As described in **Standard Log File Record Specifiers**, when specifying known properties in a log file record specification record, the property name must be prefixed with the property type.

Currently there is a single program option property type available for use: PROGRAM_OPTION.

For example, to specify the program option property RANDOM SEED, use:

PROGRAM OPTION::RANDOM SEED

Following is the list of program option properties available for inclusion in log file record specifiers.

Program Option Properties

KICK VELOCITY DISTRIBUTION SIGMA CCSN BH

Header string: Sigma Kick CCSN BH

Data type: DOUBLE

COMPAS variable: Options::kickVelocityDistributionSigmaCCSN BH

Value of program option --kick-velocity-sigma-CCSN-BH

KICK VELOCITY DISTRIBUTION SIGMA CCSN NS

Header string: Sigma Kick CCSN NS

Data type: DOUBLE

COMPAS variable: Options::kickVelocityDistributionSigmaCCSN BH

Value of program option --kick-velocity-sigma-CCSN-NS

KICK VELOCITY DISTRIBUTION SIGMA FOR ECSN

Header string: Sigma Kick ECSN

Data type: DOUBLE

COMPAS variable: Options::kickVelocityDistributionSigmaForECSN

Value of program option --kick-velocity-sigma-ECSN

KICK VELOCITY DISTRIBUTION SIGMA FOR USSN

Header string: Sigma Kick USSN

Data type: DOUBLE

COMPAS variable: Options::kickVelocityDistributionSigmaForUSSN

Value of program option --kick-velocity-sigma-USSN

RANDOM SEED

Header string: SEED_(ProgramOption)
Data type: UNSIGNED LONG INT
COMPAS variable: Options::randomSeed
Value of program option –random-seed

Appendix E – Default Log File Record Specifications

Following are the default log file record specifications for each of the standard log files. These specifications can be overridden by the use of a log file specifications file via the logfile-definitions program option.

SSE Parameters

```
const ANY_PROPERTY_VECTOR SSE_PARAMETERS_REC = {
 STAR PROPERTY::AGE,
 STAR_PROPERTY::DT,
 STAR PROPERTY::TIME,
 STAR PROPERTY::STELLAR TYPE,
 STAR PROPERTY::METALLICITY,
 STAR PROPERTY::MASS 0,
 STAR_PROPERTY::MASS,
 STAR PROPERTY::RADIUS,
 STAR_PROPERTY::RZAMS,
 STAR_PROPERTY::LUMINOSITY,
 STAR PROPERTY::TEMPERATURE,
 STAR PROPERTY::CORE MASS,
 STAR PROPERTY::CO CORE MASS,
 STAR PROPERTY::HE CORE MASS,
 STAR_PROPERTY::MDOT,
 STAR_PROPERTY::TIMESCALE_MS
```

BSE System Parameters

```
const ANY PROPERTY VECTOR BSE SYSTEM PARAMETERS REC = {
 BINARY_PROPERTY::ID,
BINARY_PROPERTY::RANDOM_SEED,
 STAR 1 PROPERTY::MZAMS,
 STAR 2 PROPERTY::MZAMS.
 BINARY PROPERTY::SEMI MAJOR AXIS INITIAL,
 BINARY_PROPERTY::ECCENTRICITY_INITIAL,
 STAR 1 PROPERTY::SUPERNOVA KICK VELOCITY MAGNITUDE RANDOM NUMBER,
 STAR 1 PROPERTY::SUPERNOVA THETA,
 STAR 1 PROPERTY::SUPERNOVA PHI,
 STAR 1 PROPERTY::MEAN_ANOMALY,
 STAR 2 PROPERTY::SUPERNOVA KICK VELOCITY MAGNITUDE RANDOM NUMBER,
 STAR 2 PROPERTY::SUPERNOVA THETA,
 STAR 2 PROPERTY::SUPERNOVA PHI,
 STAR_2_PROPERTY::MEAN_ANOMALY,
 STAR 1 PROPERTY::OMEGA ZAMS,
 STAR_2_PROPERTY::OMEGA_ZAMS,
 PROGRAM_OPTION::KICK_VELOCITY_DISTRIBUTION SIGMA CCSN NS,
 PROGRAM OPTION::KICK VELOCITY DISTRIBUTION SIGMA CCSN BH,
 PROGRAM OPTION::KICK VELOCITY DISTRIBUTION SIGMA FOR ECSN,
 PROGRAM OPTION::KICK VELOCITY DISTRIBUTION_SIGMA_FOR_USSN,
 BINARY PROPERTY::LUMINOUS BLUE VARIABLE FACTOR,
 BINARY PROPERTY::WOLF RAYET FACTOR,
 BINARY PROPERTY::COMMON ENVELOPE ALPHA,
 STAR 1 PROPERTY::METALLICITY,
 STAR 2 PROPERTY::METALLICITY,
 BINARY_PROPERTY::UNBOUND,
 BINARY PROPERTY::STELLAR MERGER,
 BINARY_PROPERTY::STELLAR_MERGER_AT_BIRTH,
 STAR_1_PROPERTY::INITIAL_STELLAR_TYPE,
 STAR_1_PROPERTY::STELLAR_TYPE,
 STAR_2_PROPERTY::INITIAL_STELLAR_TYPE,
 STAR 2 PROPERTY::STELLAR TYPE,
 BINARY_PROPERTY::ERROR
};
```

BSE Detailed Output

```
const ANY PROPERTY VECTOR BSE DETAILED OUTPUT REC = {
 BINARY_PROPERTY::ID,
BINARY_PROPERTY::RANDOM_SEED,
BINARY_PROPERTY::DT,
BINARY_PROPERTY::TIME,
BINARY_PROPERTY::SEMI_MAJOR_AXIS_PRIME_RSOL,
BINARY_PROPERTY::ECCENTRICITY_PRIME,
STAR_1_PROPERTY::M7AMS
  STAR 1 PROPERTY::MZAMS,
  STAR 2 PROPERTY::MZAMS.
 STAR 1 PROPERTY::MASS_0,
  STAR 2 PROPERTY::MASS_0,
  STAR 1 PROPERTY::MASS,
  STAR 2 PROPERTY::MASS
  STAR 1 PROPERTY::ENV MASS,
 STAR_2_PROPERTY::ENV_MASS,
 STAR 1 PROPERTY::CORE_MASS,
  STAR_2_PROPERTY::CORE_MASS,
  STAR 1 PROPERTY::HE CORE MASS,
  STAR 2 PROPERTY::HE CORE MASS,
  STAR 1 PROPERTY::CO CORE MASS,
 STAR 2 PROPERTY::CO_CORE_MASS,
  STAR 1 PROPERTY::RADIUS,
  STAR 2 PROPERTY::RADIUS,
  BINARY PROPERTY::ROCHE LOBE RADIUS 1,
  BINARY PROPERTY::ROCHE LOBE RADIUS 2,
  BINARY PROPERTY::ROCHE LOBE TRACKER 1,
  BINARY PROPERTY::ROCHE LOBE TRACKER 2,
  STAR 1 PROPERTY::OMEGA,
  STAR_2_PROPERTY::OMEGA,
  STAR_1_PROPERTY::OMEGA_BREAK,
  STAR_2_PROPERTY::OMEGA_BREAK,
  STAR_1_PROPERTY::INITIAL_STELLAR_TYPE,
  STAR 2 PROPERTY::INITIAL STELLAR TYPE,
  STAR_1_PROPERTY::STELLAR_TYPE,
  STAR_2_PROPERTY::STELLAR_TYPE,
  STAR_1_PROPERTY::AGE,
  STAR_2_PROPERTY::AGE,
  STAR_1_PROPERTY::LUMINOSITY,
  STAR_2_PROPERTY::LUMINOSITY,
  STAR 1 PROPERTY::TEMPERATURE,
  STAR 2 PROPERTY::TEMPERATURE,
  STAR_1_PROPERTY::ANGULAR_MOMENTUM,
  STAR_2_PROPERTY::ANGULAR_MOMENTUM,
  STAR_1_PROPERTY::DYNAMICAL_TIMESCALE, STAR_2_PROPERTY::DYNAMICAL_TIMESCALE,
  STAR_1_PROPERTY::THERMAL_TIMESCALE,
  STAR_2_PROPERTY::THERMAL_TIMESCALE, STAR_1_PROPERTY::NUCLEAR_TIMESCALE,
  STAR 2 PROPERTY::NUCLEAR TIMESCALE,
  STAR_1_PROPERTY::ZETA_SOBERMAN,
  STAR 2 PROPERTY::ZETA SOBERMAN,
  STAR_1_PROPERTY::ZETA_SOBERMAN_HE,
  STAR_2_PROPERTY::ZETA_SOBERMAN_HE,
  STAR_1_PROPERTY::ZETA_HURLEY,
  STAR_2_PROPERTY::ZETA_HURLEY,
  STAR 1 PROPERTY::ZETA_HURLEY_HE,
  STAR 2 PROPERTY::ZETA HURLEY HE,
  STAR_1_PROPERTY::MASS LOSS DIFF,
  STAR 2 PROPERTY::MASS LOSS DIFF,
  STAR 1 PROPERTY::MASS TRANSFER DIFF,
  STAR 2 PROPERTY::MASS TRANSFER DIFF,
  BINARY PROPERTY::TOTAL ANGULAR MOMENTUM PRIME,
```

```
BINARY_PROPERTY::TOTAL_ENERGY_PRIME,
  STAR_1_PROPERTY::LAMBDA_NANJING,
  STAR 2 PROPERTY::LAMBDA NANJING,
  STAR 1 PROPERTY::LAMBDA LOVERIDGE,
  STAR 2 PROPERTY::LAMBDA LOVERIDGE,
 STAR_1_PROPERTY::LAMBDA_KRUCKOW_TOP,
STAR_2_PROPERTY::LAMBDA_KRUCKOW_TOP,
STAR_1_PROPERTY::LAMBDA_KRUCKOW_MIDDLE,
STAR_2_PROPERTY::LAMBDA_KRUCKOW_MIDDLE,
STAR_1_PROPERTY::LAMBDA_KRUCKOW_BOTTOM,
STAR_2_PROPERTY::LAMBDA_KRUCKOW_BOTTOM,
STAR_1_PROPERTY::LAMBDA_KRUCKOW_BOTTOM,
  STAR_1_PROPERTY::METALLICITY,
  STAR 2_PROPERTY::METALLICITY,
  BINARY PROPERTY::MASS TRANSFER TRACKER HISTORY,
  STAR_1_PROPERTY::PULSAR_MAGNETIC_FIELD,
  STAR_2_PROPERTY::PULSAR_MAGNETIC_FIELD,
  STAR_1_PROPERTY::PULSAR_SPIN_FREQUENCY,
  STAR_2_PROPERTY::PULSAR_SPIN_FREQUENCY,
  STAR 1 PROPERTY::PULSAR SPIN DOWN RATE,
  STAR_2_PROPERTY::PULSAR_SPIN_DOWN_RATE,
  STAR 1 PROPERTY::RADIAL EXPANSION TIMESCALE,
  STAR 2 PROPERTY::RADIAL EXPANSION TIMESCALE
};
```

BSE Double Compact Objects

```
const any property_vector bse_double_compact_objects_rec = {
    BINARY_property::Id,
    BINARY_property::Random_seed,
    BINARY_property::Semi_major_axis_at_doo_formation,
    BINARY_property::Becentricity_at_doo_formation,
    BINARY_property::Mass,
    Star_1_property::Mass,
    Star_1_property::Mass,
    Star_2_property::Mass,
    Star_2_property::Time_to_coalescence,
    BINARY_property::Time_to_coalescence,
    BINARY_property::Mass_transfer_case_initial,
    Star_2_property::Mass_transfer_case_initial,
    Star_2_property::Mass_transfer_case_initial,
    Star_1_property::Merges_in_hubble_time,
    Star_1_property::Recycled_neutron_star,
    Star_2_property::Recycled_neutron_star,
};
```

BSE Common Envelopes

STAR 2 PROPERTY:: IS RLOF,

```
const ANY PROPERTY VECTOR BSE COMMON ENVELOPES REC = {
 BINARY_PROPERTY::ID,
BINARY_PROPERTY::RANDOM_SEED,
BINARY_PROPERTY::TIME,
 STAR 1 PROPERTY::LAMBDA AT COMMON ENVELOPE,
 STAR 2 PROPERTY::LAMBDA AT COMMON ENVELOPE,
 STAR_1_PROPERTY::BINDING_ENERGY_PRE_COMMON_ENVELOPE, STAR_2_PROPERTY::BINDING_ENERGY_PRE_COMMON_ENVELOPE,
 BINARY_PROPERTY::ECCENTRICITY_PRE_COMMON_ENVELOPE, BINARY_PROPERTY::ECCENTRICITY_POST_COMMON_ENVELOPE,
 BINARY PROPERTY::SEMI MAJOR AXIS PRE COMMON ENVELOPE
 BINARY PROPERTY::SEMI MAJOR AXIS POST COMMON ENVELOPE,
 BINARY PROPERTY::ROCHE LOBE RADIUS 1 PRE COMMON ENVELOPE.
 BINARY PROPERTY::ROCHE LOBE RADIUS 1 POST COMMON ENVELOPE,
 BINARY_PROPERTY::ROCHE_LOBE_RADIUS_2_PRE_COMMON_ENVELOPE,
 BINARY PROPERTY::ROCHE LOBE RADIUS 2 POST COMMON ENVELOPE,
 BINARY_PROPERTY::MASS 1 PRE COMMON ENVELOPE,
 BINARY PROPERTY::MASS ENV 1,
 BINARY PROPERTY::MASS 1 FINAL,
 BINARY PROPERTY::RADIUS 1 PRE COMMON ENVELOPE,
 BINARY PROPERTY::RADIUS 1 POST COMMON ENVELOPE,
 BINARY PROPERTY::STELLAR TYPE 1 PRE COMMON ENVELOPE,
 STAR 1 PROPERTY::STELLAR TYPE,
 STAR 1 PROPERTY::LAMBDA FIXED,
 STAR 1 PROPERTY::LAMBDA NANJING,
 STAR 1 PROPERTY::LAMBDA LOVERIDGE,
 STAR 1 PROPERTY::LAMBDA LOVERIDGE WINDS,
 STAR 1 PROPERTY::LAMBDA KRUCKOW,
 STAR_1_PROPERTY::BINDING_ENERGY_FIXED,
 STAR_1_PROPERTY::BINDING_ENERGY_NANJING,
 STAR_1_PROPERTY::BINDING_ENERGY_LOVERIDGE,
 STAR_1_PROPERTY::BINDING_ENERGY_LOVERIDGE_WINDS,
 STAR_1_PROPERTY::BINDING_ENERGY_KRUCKOW,
 BINARY_PROPERTY::MASS_2_PRE_COMMON_ENVELOPE,
 BINARY_PROPERTY::MASS_ENV_2,
 BINARY_PROPERTY::MASS_2_FINAL,
 BINARY_PROPERTY::RADIUS_2_PRE_COMMON_ENVELOPE, BINARY_PROPERTY::RADIUS_2_POST_COMMON_ENVELOPE,
 BINARY_PROPERTY::STELLAR_TYPE_2_PRE_COMMON_ENVELOPE,
 STAR_2_PROPERTY::STELLAR_TYPE,
 STAR 2 PROPERTY::LAMBDA FIXED,
 STAR_2_PROPERTY::LAMBDA_NANJING,
 STAR 2 PROPERTY::LAMBDA LOVERIDGE,
 STAR_2_PROPERTY::LAMBDA_LOVERIDGE_WINDS,
 STAR 2 PROPERTY::LAMBDA KRUCKOW,
 STAR 2 PROPERTY::BINDING ENERGY FIXED,
 STAR_2_PROPERTY::BINDING_ENERGY_NANJING,
 STAR_2_PROPERTY::BINDING_ENERGY_LOVERIDGE,
 STAR 2 PROPERTY::BINDING ENERGY LOVERIDGE WINDS,
 STAR_2_PROPERTY::BINDING_ENERGY_KRUCKOW,
 BINARY PROPERTY::MASS TRANSFER TRACKER HISTORY,
 BINARY_PROPERTY::STELLAR_MERGER,
 BINARY_PROPERTY::OPTIMISTIC_COMMON_ENVELOPE,
 BINARY PROPERTY::COMMON ENVELOPE EVENT COUNT,
 BINARY_PROPERTY::DOUBLE_CORE_COMMON_ENVELOPE,
 STAR 1 PROPERTY:: IS RLOF,
 STAR 1 PROPERTY::LUMINOSITY PRE COMMON ENVELOPE,
 STAR 1 PROPERTY::TEMPERATURE PRE COMMON ENVELOPE,
 STAR 1 PROPERTY::DYNAMICAL TIMESCALE PRE COMMON ENVELOPE,
 STAR 1 PROPERTY::THERMAL TIMESCALE PRE COMMON ENVELOPE,
 STAR 1 PROPERTY::NUCLEAR TIMESCALE PRE COMMON ENVELOPE,
```

```
STAR 2 PROPERTY::LUMINOSITY PRE COMMON_ENVELOPE,
STAR 2 PROPERTY::TEMPERATURE PRE COMMON_ENVELOPE,
STAR 2 PROPERTY::DYNAMICAL TIMESCALE PRE COMMON_ENVELOPE,
STAR 2 PROPERTY::THERMAL_TIMESCALE PRE COMMON_ENVELOPE,
STAR 2 PROPERTY::NUCLEAR_TIMESCALE PRE_COMMON_ENVELOPE,
BINARY_PROPERTY::ZETA_STAR_COMPARE,
BINARY_PROPERTY::ZETA_RLOF_ANALYTIC,
BINARY_PROPERTY::SYNCHRONIZATION_TIMESCALE,
BINARY_PROPERTY::CIRCULARIZATION_TIMESCALE,
STAR 1 PROPERTY::RADIAL_EXPANSION_TIMESCALE_PRE_COMMON_ENVELOPE,
STAR 2 PROPERTY::RADIAL_EXPANSION_TIMESCALE_PRE_COMMON_ENVELOPE,
BINARY_PROPERTY::IMMEDIATE_RLOF_POST_COMMON_ENVELOPE,
BINARY_PROPERTY::SIMULTANEOUS_RLOF

};
```

BSE Supernovae

```
const ANY PROPERTY VECTOR BSE SUPERNOVAE REC = {
 BINARY_PROPERTY::ID,
BINARY_PROPERTY::RANDOM_SEED,
 SUPERNOVA_PROPERTY::DRAWN KICK VELOCITY,
 SUPERNOVA PROPERTY::KICK VELOCITY,
 SUPERNOVA PROPERTY::FALLBACK FRACTION,
 BINARY_PROPERTY::ORBITAL_VELOCITY_PRE_SUPERNOVA,
 BINARY PROPERTY::DIMENSIONLESS KICK VELOCITY,
 SUPERNOVA PROPERTY::TRUE ANOMALY,
 SUPERNOVA PROPERTY::SUPERNOVA THETA,
 SUPERNOVA PROPERTY::SUPERNOVA_PHI,
 SUPERNOVA PROPERTY::SN TYPE,
 BINARY PROPERTY::UNBOUND,
 SUPERNOVA PROPERTY::TOTAL MASS AT COMPACT OBJECT FORMATION,
 COMPANION_PROPERTY::MASS,
 SUPERNOVA PROPERTY::CO CORE MASS AT COMPACT OBJECT FORMATION,
 SUPERNOVA PROPERTY::MASS,
 SUPERNOVA PROPERTY::EXPERIENCED RLOF,
 SUPERNOVA PROPERTY::STELLAR TYPE,
 BINARY PROPERTY::SUPERNOVA STATE,
 SUPERNOVA PROPERTY::STELLAR TYPE PREV,
 COMPANION PROPERTY::STELLAR TYPE PREV,
 SUPERNOVA PROPERTY::CORE MASS AT COMPACT OBJECT FORMATION,
 SUPERNOVA PROPERTY::HE CORE MASS AT COMPACT OBJECT FORMATION,
 BINARY PROPERTY::TIME,
 BINARY PROPERTY::ECCENTRICITY PRE SUPERNOVA,
 BINARY PROPERTY::ECCENTRICITY,
 BINARY PROPERTY::SEMI MAJOR AXIS PRE SUPERNOVA RSOL,
 BINARY PROPERTY::SEMI_MAJOR_AXIS_PRIME_RSOL,
 BINARY_PROPERTY::SYSTEMIC_VELOCITY,
 SUPERNOVA PROPERTY::HYDROGEN RICH,
 SUPERNOVA PROPERTY::HYDROGEN POOR,
 COMPANION PROPERTY::RUNAWAY
};
```

BSE Pulsar Evolution

```
const any _property_vector bse_pulsar_evolution_rec = {
    BINARY _property::id,
    BINARY _property::random_seed,
    Star_1 _property::mass,
    Star_2 _property::stellar_type,
    Star_2 _property::stellar_type,
    BINARY _property::stellar_type,
    BINARY _property::semi_major_axis_prime_rsol,
    BINARY _property::mass_transfer_tracker_history,
    Star_1 _property::pulsar_magnetic_field,
    Star_2 _property::pulsar_magnetic_field,
    Star_1 _property::pulsar_spin_frequency,
    Star_1 _property::pulsar_spin_frequency,
    Star_2 _property::pulsar_spin_frequency,
    Star_2 _property::pulsar_spin_down_rate,
    Star_2 _property::pulsar_spin_down_rate,
    BINARY _property::Time,
    BINARY _property::Dt
};
```

Appendix F – Example Log File Record Specifications File

Following is an example log file record specifications file. COMPAS can be configured to use this file via the logfile-definitions program option.

This file (COMPAS_Output_Definitions.txt) is also delivered as part of the COMPAS github repository.

```
# sample standard log file specifications file
# the '#' character and anything following it on a single line is considered a comment
# (so, lines starting with '#' are comment lines)
# case is not significant
# specifications can span several lines
# specifications for the same log file are cumulative
# if a log file is not specified in this file, the default specification is used
# SSE Parameters
# start with the default SSE Parameters specification and add ENV MASS
sse parms rec += { STAR PROPERTY::ENV MASS }
# take the updated SSE Parameters specification and add ANGULAR MOMENTUM
sse parms rec += { STAR PROPERTY::ANGULAR MOMENTUM }
# take the updated SSE Parameters specification and subtract MASS 0 and MDOT
sse parms rec -= { STAR PROPERTY::MASS 0, STAR PROPERTY::MDOT }
# BSE System Parameters
bse_sysparms_rec = {
                                                    # set the BSE System Parameters specification to:
    BINARY_PROPERTY::ID,
                                                    # ID of the binary
    BINARY_PROPERTY::RANDOM_SEED,
STAR_1_PROPERTY::MZAMS,
                                                   # RANDOM_SEED for the binary
# MZAMS for Star1
    STAR 2 PROPERTY::MZAMS
                                                   # MZAMS for Star2
# ADD to the BSE System Parameters specification:
# SEMI MAJOR AXIS INITIAL for the binary
# ECCENTRICITY INITIAL for the binary
# SUPERNOVA THETA for Starl and SUPERNOVA PHI for Starl
bse_sysparms_rec += {
    BINARY PROPERTY::SEMI MAJOR AXIS INITIAL,
    BINARY PROPERTY:: ECCENTRICITY INITIAL,
    STAR 1 PROPERTY::SUPERNOVA THETA, STAR 1 PROPERTY::SUPERNOVA PHI
bse sysparms rec += {
                                                         # ADD to the BSE System Parameters specification:
    SUPERNOVA_PROPERTY::IS_ECSN,
                                                         # IS ECSN for the supernova star
                                                        # IS_SN for the supernova star
    SUPERNOVA_PROPERTY::IS_SN,
    SUPERNOVA PROPERTY::IS USSN,
                                                         # IS USSN for the supernova star
    SUPERNOVA_PROPERTY::EXPERIENCED_PISN, # EXPERIENCED_PISN for the supernova star
SUPERNOVA_PROPERTY::EXPERIENCED_PISN, # EXPERIENCED_PISN for the supernova star
BINARY_PROPERTY::SURVIVED_SUPERNOVA_EVENT, # SURVIVED_SUPERNOVA_EVENT for the binary
SUPERNOVA_PROPERTY::MZAMS, # MZAMS for the supernova star
    COMPANION PROPERTY::MZAMS
                                                         # MZAMS for the companion star
# SUBTRACT from the BSE System Parameters specification:
# RANDOM_SEED for the binary
# ID for the binary
bse_sysparms_rec -= {
                                                # SUBTRACT from the BSE System Parameters specification:
    BINARY PROPERTY::RANDOM_SEED,
                                                 # RANDOM SEED for the binary
    BINARY PROPERTY::ID
                                                 # ID for the binary
# BSE Double Compas Objects
```

```
# set the BSE Double Compact Objects specifivation to MZAMS for Star1, and MZAMS for Star2
BSE_DCO_Rec = {STAR_1_PROPERTY::MZAMS,STAR_2_PROPERTY::MZAMS}
# set the BSE Double Compact Objects specification to empty - nothing will be printed
# (file will not be created)
BSE_DCO_Rec = {}
# BSE Supernovae
                             # set spec empty - nothing will be printed (file will not be created)
BSE_SNE_Rec = {}
# BSE Common Envelopes
BSE CEE Rec = { }
                            # set spec empty - nothing will be printed (file will not be created)
# BSE Pulsars
# line ignored (comment). BSE Pulsars specification will be default
# BSE_Pulsars_Rec= { STAR_1_PROPERTY::MASS, STAR_2_PROPERTY::MASS }
# BSE Detailed Output
BSE Detailed Rec={} # set spec empty - nothing will be printed (file will not be created)
```