KIWI Project

openSUSE - KIWI Image System Cookbook

Project, Design and Implementation by Marcus Schaefer (ms@suse.de)

*



Author: Marcus Schaefer

Date: November 17, 2009

Version: 3.74

Contents

1	Introduction	7
2	Basic workflow2.1 Boot process	9 11 11 12
3	KIWI image description 3.1 config.xml	13 15 16 16 17 21 22 24 27 28 32
4	Creating Appliances with KIWI 4.1 History	33 33
5	Maintenance of Operating System Images	37
7	System to image migration 6.1 Create a clean repository set first 6.2 Create a migration report first 6.3 Migrate my system 6.4 Turn my system into an image Installation Source 7.1 Adapt the example's config.xml 7.2 Create a local installation source	39 40 40 41 43 43
8	ISO image - Live Systems 8.1 Building the suse-live-iso example	45

		Using the image
	8.3	Flavours
		8.3.1 Split mode
9	USB	image - Live-Stick System 49
	9.1	Building the suse-live-stick example
	9.2	Using the image
	9.3	Flavours
		9.3.1 Split stick
		9.3.2 LVM support
10	VMX	image - Virtual Disks 55
		Building the suse-vm-guest example
		Using the image
		Flavours
	10.5	10.3.1 VMware support
		11
		10.3.2 LVM support
11	PXE	image - Thin Clients 59
	11.1	Setting up the required services
		11.1.1 atftp server
		11.1.2 DHCP server
	11.2	Building the suse-pxe-client example
		Using the image
		Flavours
		11.4.1 The pxe client Control File
		11.4.2 The pxe client Configuration File
		11.4.3 User another than tftp as download protocol
		11.4.4 RAM only image
		0
		11.4.7 root tree over NFS
		11.4.8 root tree over NBD
		11.4.9 root tree over AoE
12	OEM	image - Preload Systems 71
	12.1	Building the suse-oem-preload example
		Using the image
		Flavours
		12.3.1 Influencing the oem partitioning
		12.3.2 LVM support
12	YEN	image - Paravirtual Systems 75
13		Building the suse-xen-guest example
		Using the image
	13.3	Flavours

14 EC2 image - Amazon Elastic Compute C 14.1 Building the suse-ec2-guest example 14.2 Using the image			
15 KIWI testsuite 15.1 testsuite packages			
Index			83
16 Appendix - Kiwi man pages			85

1 Introduction

The openSUSE KIWI Image System provides a complete operating system image solution for Linux supported hardware platforms as well as for virtualisation systems like Xen, VMWare, etc. The KIWI architecture was designed as a two level system. The first stage, based on a valid **software package source**, creates a so called **unpacked image** according to the provided image description. The second stage creates from a required unpacked image an operating system image. The result of the second stage is called a **packed image** or short an image.



Figure 1.1: Image Serving Architecture

Because this document contains conceptual information about an image system, it is important to understand what an operating system image is all about. A normal installation process is starting from a given installation source and installs single pieces of software until the system is complete. During this process there may be manual user intervention required. However an operating system image represents an already completed *installation* encapsulated as a file and optionally includes the configuration for a specific task. Such an operating system starts working as soon as the image has been brought to a system storage device no matter if this is a volatile or non volatile storage. The process of creating an image takes place without user interaction. This means all requirements of the encapsulated system has to be fulfilled before the image is created. All of this information is stored in the **image description**.

2 Basic workflow

Contents

2.1	Boot process	11
2.2	Boot parameters	11
2.3	Common and Distribution specific code	12

The creation of an image with KIWI is always divided into two basic steps. These are the **prepare** and the **create** step. the create step requires the prepare step to be exited successfully. Within this first prepare step kiwi builds of a new root tree or, in kiwi-speak, a new unpacked image. The building of a new root tree consists of the creation of the directory specified to hold it and the installation of the selected packages on it. The installation of software packages is driven by a packagemanager. KIWI supports the smart and zypper package managers. The prepare step executes the following major stages:

• Root directory creation

To prevent accidental deletion of an existing root tree, kiwi will stop with an error message if this folder already exists, unless the option –force-new-root is used in which case the existing root will be deleted.

Package installation

First the selected package manager (smart by default) is instructed to use the repositories specified in the image description file. Then the packages specified in the 'bootstrap' section are installed. These packages are installed externally to the target root system (i.e. not chroot'ed) and establish the initial environment so the rest of the process may run chroot'ed. Essential packages in this section are filesystem and glibc-locale. In practice you only need to specify those two, since the rest of the packages will be pulled because of the dependency system. To save space in your image you could schedule a set of packages for deletion after the package installation phase is over by listing them in the 'delete' section.

• User defined script config.sh

At the end of the preparation stage the optional script named config.sh is called. This script should be used to configure the system which means for example the activation of services. For a detailed description what functions are already available to configure the system please refer to the KIWI::config.sh manual page

• Managing the new root tree

At this point you can make changes on your unpacked image so it fits your

purpose better. Bear in mind that changes at this point will be discarded and not repeated automatically if you rerun the 'prepare' phase unless you include them in your original config.xml file and/or config.sh script. Please also note that the image description has been copied into the new root below the directory <new-root>/image. Any subsequent create step will read the image description information from the new root tree and not from the original image description location. According to this if you need to change the image description data after the prepare call has finished you need to change it inside the new root tree as well as in your original description directory to prevent loosing the change when your root tree will be removed later for some reason.

After the prepare step has finished successfully a subsequent building of an image file or, in kiwi-speak, a new packed image follows. The building of an image requires a successfully prepared new root tree in the first place. Using this tree multiple image types can be created. So to speak it's possible to create a VMware image and a XEN image from the same prepared root tree. The create step executes the following major stages:

User defined script images.sh

At the beginning of the creation stage the optional script named images.sh is called. This script has no distinctive use case like config.sh but is most often used to remove packages which were pulled in by a dependency but are not really required for the later use of the operating system. For a detailed description what functions are already available to images.sh please refer to the KIWI::images.sh manual page

• Create the requested image type

What image type(s) a kiwi image supports depends on what types has been setup in the main image description file config.xml. At least one type must be setup. The following picture shows what image types are currently supported by kiwi:



Figure 2.1: Image Types

Detailed information including a step by step guidance how to call kiwi and how to make use of the result image can be found in the image type specific sections later in this document.

2.1 Boot process

Todays linux systems are using a special boot image to control the boot process. This boot image is called **initrd**. The linux kernel loads this initial ramdisk which is a compressed cpio archive into RAM and calls init or if present the program named linuxrc. The KIWI image system also takes care for the creation of this boot image. Each image type has it's own special boot code and shares the common parts in a set of module functions. The image descriptions for the boot images are provided by KIWI and thus the user has in almost all cases no need to take care for the boot image.



Figure 2.2: Boot process

Furthermore KIWI automatically creates this boot image along with the requested image type. It does that by calling itself in a prepare and create call. There is no difference in terms of the description of such a boot image compared to the system image description. The system image description is the one the user creates and this image represents the later operating system whereas the boot image only lives temporarly in RAM as long as the system image will be activated. The boot image descriptions are stores in /usr/share/kiwi/image/*boot and can be build in the same way as the system image. The boot image without a corresponding system image doesn't make sense though.

2.2 Boot parameters

When booting an image created by kiwi using one of the provided boot images there are some useful kernel parameters mainly meant for debugging purposes. Please note the following parameters are only useful if the kiwi initrd is used. In case of any other initrd code written by yourself or simply because kiwi replaced itself with the distribution specfic mkinitrd tool the parameters might not have any effect.

• kiwidebug=1

If the boot process encounters a fatal error the system normally reacts with a reboot after 120 secconds. This so called exception can be influenced by the kiwidebug parameter. If set to 1 the system will stop and provide the user with a shell prompt instead of a reboot. Within that shell some basic standard commands are available which could help to find the cause of the problem

• kiwistderr=/dev/...

While the system boots kiwi writes messages to tty1 and tty3. The tty1 messages are highlevel information whereas the tty3 messages represents the shell debug output and any error messages from the commands called. With the kiwistderr parameter one can combine both message sets and specify where to write them to. It's very common to set /dev/console as possible alternative to the default logging behaviour

2.3 Common and Distribution specific code

KIWI has been developed to be usable for any Linux distribution. By design of a Linux distribution there are differences between each of them. With KIWI we provide on one hand the code which is common to all Linux distributions according to standards and on the other hand there is also code where we have to distinguish between the distribution type.

In case of such specific tasks which are almost all in the area of booting, KIWI provides a set of functions which all have to come with a distribution prefix. As this project uses SUSE Linux as base distribution all required distribution specific tasks has been implemented for SUSE and could be missing for other distributions. The existing implementation for SUSE turns out to be adapted to other distributions very easily though.

A look into the code therefore will show you functions which are prefixed by "suse" as well as scripts whose names starts with "suse-". At any time you see such a script or function you can be assured that this is something distribution specific and needs to be adapted if you plan to use KIWI with another distribution than SUSE. For example the boot workflow is controlled by a program called linuxrc which is in KIWI a script represented by suse-linuxrc. Another example would be the function called suseStripKernel which is able to remove everything but a specified list of kernel drivers from the SUSE kernel.

The prefixed implementation allows us to integrate all the distribution specific tasks into one project but this of course requires the help and knowledge of the people who are familiar with their preferred linux distribution.

3 KIWI image description

Contents

3.1	config	.xml	15
	3.1.1	image element	15
	3.1.2	description element	16
	3.1.3	profiles element	16
	3.1.4	preferences element	17
	3.1.5	users element	21
	3.1.6	drivers element	21
	3.1.7	repository element	22
	3.1.8	packages element	24
	3.1.9	vmwareconfig element	27
	3.1.10	xenconfig element	28
	3.1.11	split element	32

In order to be able to create an image with kiwi a so called image description must be created. The image description is represented by a directory which has to contain at least one file named **config.xml** or alternatively *.kiwi. A good start for such a description can be found in the examples provided in /usr/share/doc/packages/kiwi/examples.




Figure 3.1: Image description directory

The following additional information is optional for the process of building an image but most often mandatory for the functionality of the later operating system.

• images.sh

Optional configuration script while creating the packed image. This script is called at the beginning of the image creation process. It is designed to clean-up the image system. Affected are all the programs and files only needed while the unpacked image exists.

config.sh

Optional configuration script while creating the unpacked image. This script is called at the end of the installation but **before** the package scripts have run. It is designed to configure the image system, such as the activation or deactivation of certain services (insserv). The call is not made until after the switch to the image has been made with **chroot**.

• root/

Subdirectory that contains special files, directories, and scripts for adapting the image environment **after** the installation of all the image packages. The entire directory is copied into the root of the image tree using cp -a.

• config-yast-firstboot.xml

Configuration file for the control of the yast2 firstboot service. Similar to the autoyast approach yast also provides a boot time service called firstboot. Unfortunately there is no GUI available to setup the firstboot but a good documentation in /usr/share/doc/packages/yast2-firstboot. Once you have created such a firstboot file in your image description directory KIWI will process on the file and setup your image as follows:

- 1. KIWI enables the firstboot service
- 2. While booting the image YaST is started in firstboot mode
- 3. The firstboot service handles the instructions listed in the config-yast-firstboot.xml
- 4. If the process finished successfully the environment is cleaned and first-boot won't be called at next reboot.

config-yast-autoyast.xml

Configuration file which has been created by autoyast. To be able to create such an autoyast profile you should first call:



Once you have saved the information from the autoyast UI as config-yast-autoyast.xml file in your image description directory KIWI will process on the file and setup your image as follows:

- 1. While booting the image YaST is started in autoyast mode automatically
- 2. The autoyast description is parsed and the instructions are handled by YaST. In other words the **system configuration** is performed
- 3. If the process finished successfully the environment is cleaned and autoyast won't be called at next reboot.

config-cdroot.tgz

Archive which is used for ISO images only. The data in the archive is uncompressed and stored in the CD/DVD root directory. This archive can be used, for example, to integrate a license file or readme information directly readable from the CD or DVD.

· config-cdroot.sh

Along with the config-cdroot.tgz one can provide a script which allows to manipulate the extracted data.

config/

Optional Subdirectory that contains Bash scripts that are called after the installation of all the image packages, primarily in order to remove the parts of a package that are not needed for the operating system. The name of the Bash script must resemble the package name listed in the config.xml

3.1 config.xml

The mandatory image definition file is divided into different sections which describes information like the image name and type as well as the packages and patterns the image should consist of. The following information explains the basic structure of the XML document. When KIWI is called the XML structure is validated by a RelaxNG based schema. For details on attributes and values please refer to the schema documentation file at /usr/share/doc/packages/ kiwi/kiwi.rng.html.

3.1.1 image element

The image definition starts with an image tag and requires the schema format at version 2.0. The attribute name specifies the name of the image which is also used for the file names created by KIWI. Because we don't want spaces in file names the name attribute must not have any spaces in its name.

• The optional attribute displayname allows setup of the boot menu title for isolinux and grub. So you can have *suse-SLED-foo* as the image name but something like *my cool Image* as the boot display name.

- The optional attribute inherit allows to inherit the packages information from another image description.
- The optional attribute kiwirevision allows to specify a kiwi SVN revision number which is known to build a working image from this description. If the kiwi SVN revision is less than the specified value the process will exit. The currently used SVN revision can be queried by calling kiwi —version
- The optional attribute id allows to set an identification number which appears as file /etc/ImageID within the image.

Inside the **image** section the following mandatory and optional subelements exists. The simplest image description must define the elements **description**, **preferences**, **repository** and **packages** (at least one of type="bootstrap").

3.1.2 description element

The mandatory description section contains information about the creator of this image description. The attribute **type** could be either of the value "system" which indicates this is a system image description or at value "boot" for boot image descriptions.

3.1.3 profiles element

The optional profiles section lets you maintain one image description while allowing for variation of the sections packages and drivers that are included. A separate profile element must be specified for each variation. The profile child element, which has name and description attributes, specifies an alias name used to mark sections as belonging to a profile, and a short description explaining what this profile does.

To mark a set of packages/drivers as belonging to a profile, simply annotate them with the **profiles** attribute. It is also possible to mark sections as belonging to multiple profiles by separating the names in the **profiles** attribute with a comma. If a packages/drivers tag does not have a profiles attribute, it is assumed to be present for all profiles.

3.1.4 preferences element

The mandatory preferences section contains information about the supported image type(s), the used packagemanager, the version of this image and optional attributes. The image version must be a three-part version number of the format: **Major.Minor.Release**. In case of changes to the image description the following rules should apply:

- For smaller image modifications that do not add or remove any new packages, only the release number is incremented. The config.xml file remains unchanged.
- For image changes that involve the addition or removal of packages the minor number is incremented and the release number is reset.
- For image changes that change the size of the image file the major number is incremented.

By default kiwi use the **smart** packagemanager but it is also possible to use the SUSE packagemanager called **zypper**.

Normally one preferences section is enough but it's possible to share data between different namespaces, so called profiles. According to this it's possible to have for example two preferences sections whereas one contains specific oem options and the other doesn't. This allows to add specific type based information while building the image.

At least one type must be set to be able to build an image from this description. Multiple type lines are allowed whereas you can specify with the boolean attribute named **primary** which should be the primary image if no type is requested on creation. The following list describes the possible types and their attributes:

usb

Use this type to create a USB stick system along with the attributes **filesystem** and **boot="usbboot/suse-*"** In addition to that type you can specify which bootloader to use. The optional attribute **bootloader** is used to setup

either grub or syslinux as bootloader types. Setting the bootloader also works for vmx images but not for oem images. In case of an oem image only the distribution supported bootloader (grub) is allowed. The optional **lvm** attribute allows you to activate LVM support and place the root filesystem into logical volumes of the kiwiVG volume group

vmx

Use this type to create a virtual disk system along with the attributes **filesystem**, **boot="vmxboot/suse-*"** and optionally **format**. The format attribute spcifies one of the qemu supported virtualization formats, for example vmdk or qcow2. The optional attribute **vga** can be specified to configure the kernel framebuffer mode. Detailed information about the possible values can be found in /usr/src/linux/Documentation/fb/vesafb.txt. The vga attribute also works for the image types usb and oem. The optional **lvm** attribute allows you to activate LVM support and place the root filesystem into logical volumes of the kiwiVG volume group

oem

Use this type to create a preload virtual disk system along with the attributes **filesystem**, **boot="oemboot/suse-*"** and optionally **format**. If the format attribute is set to "iso" or "usb" KIWI will additionally create an installation media suitable for a CD/DVD or an USB stick. This installation media takes over the task of deploying the preload system onto the storage devices which it detects at boot time. If the optional **lvm** attribute is set the root filesystem of the oem system is placed into logical volumes of the kiwiVG volume group.

pxe

Use this type to create a network boot image along with the attributes **filesystem** and **boot="netboot/suse-*"** Additionally the attribute **compressed** specifies whether the image file should be compressed or not. This is not the filesystem compression just the image file compression most often used to transfer the compressed version over to the boot server.

• iso

Use this type to create a live system on CD or DVD along with the attributes **boot="isoboot/suse-*"** and optionally **flags**. If no flags are specified the filesystem will not be compressed and no union filesystem is used. Allowed flags are:

- unified: Compress filesystem with squashfs and mount the system readwrite with an aufs based overlay mount
- compressed: Compress filesystem with squashfs and use a link list to mount the system read-write. An additional split section controls the read-write information
- dmsquash: Creates an ext3 image file and puts that into a squashfs filesystem. On boot the root tree is mounted via a device mapper snapshot device to allow full write access over the complete tree.
- clic: Creates a fuse based compressed read-only filesystem which allows write operations into a cow file

If no flags or the flags "compressed" are set an additional **split** section is recommended.

xen

Use this type to create a Xen enabled para-virtual gues image along with the attributes **filesystem** and **boot="xenboot/suse-*"**

• split

Use this type if you want to use one of the types **usb,vmx,oem or pxe** but as a split image. The split image support allows to create the image as split files wheras one part represents the read-write data and the other part represents the read-only data. Different filesystems can be assigned to each portion. According to this use this type together with the attributes **fsreadwrite**, **fsreadonly** and

boot="usb|vmx|oem|netboot/suse-*"

• cpio

Use this type if your image is a boot image (intrd). Along with this type the optional attributes bootprofile="default" and/or bootkernel="std" exists. A boot image should group the different kernels it supports in profiles. It's mandatory to have one profile named std which is used if no other bootkernel is specified. Profiles which leaves only a subset of drivers or packages should also be grouped in profiles. It's mandatory to have one profile named default which is used if no other bootprofile is specified. Within the system image one can select the group by also specifying a bootprofile and/or bootkernel attribute. These information is passed automatically to kiwi when it builds the boot image.

All of the mentioned types can specify the **boot** attribute which tells kiwi to call itself to build the requested boot image (initrd). It is possible to tell kiwi to check for an already built boot image which is a so called **prebuilt boot image**. To activate searching for an appropriate prebuilt boot image the type section also provides the attribute **checkprebuilt="true|false"**. If specified kiwi will search for a prebuilt boot image in a directory named */usr/share/kiwi/image/*boot/*-prebuilt*. Example: If the boot attribute was set to isoboot/suse-10.3 and checkprebuilt is set to true kiwi will search the prebuilt boot image in /usr/share/kiwi/image/isoboot/suse-10.3-prebuilt. The directory kiwi searches for the prebuilt boot images can also be specified at the commandline with the —**prebuiltbootimage** parameter.

Within the preferences section there are the following optional attributes:

• size

Specifies the size of the image with a numerical value in Megabytes or Gigabytes. Use the "unit" attribute to assign the unit **M** for Megabytes or **G** for Gigabytes. KIWI extends the image size automatically if the specified value is too small. If the actual size is more than 100MB larger than the specified size, KIWI aborts with an error message. KIWI does not automatically reduce the image size if the specified value is too large, because the extra space might be needed to, for example, run custom scripts. If no size is specified, KIWI uses the required size plus approximately 30% free space. The

optional "additive" attribute can be set to tell kiwi to use the required size for the image plus the given size as additional free space. The "additive" attribute is a bool attribute and can be set to either true or false.

• rpm-check-signatures

Specifies whether RPM should check the package signature or not

• rpm-excludedocs

Specifies whether RPM should skip installing package documentation

• rpm-force

Specifies whether RPM should be called with -force

keytable

Specifies the name of the console keymap to use. The value corresponds to a map file in /usr/share/kbd/keymaps. The KEYTABLE variable in /etc/sysconfig/keyboard file is set according to the keyboard mapping.

timezone

Specifies the time zone. Available time zones are located in the /usr/share/-zoneinfo directory. Specify the attribute value relative to /usr/share/zone-info. For example, specify Europe/Berlin for /usr/share/zoneinfo/Europe/Berlin. KIWI uses this value to configure the timezone in /etc/localtime for the image

locale

Specifies the name of the locale to use, which defines the contents of the RC_LANG system environment variable in /etc/sysconfig/language

boot-theme

Specifies the name of the gfxboot and bootsplash theme to use

• defaultdestination

Used if the –destdir option is not specified when calling KIWI

defaultroot

Used if the option –root is not specified when calling KIWI

defaultbaseroot

Used if the option –base-root is not specified when calling KIWI. It's possible to prepare and create an image using a predefined non empty root directory as base information. This could speedup the build process a lot if the base root path already contains most of the image data.

3.1.5 users element

```
<users group="users" id="number">
        <user pwd="..." home="dir"
            name="user" id="number"/>
            ...
</users> ...
```

The optional users element specifies the users to be added to the image. The group attribute specifies the group the users belong to. If this group does not exist, it is created. A user element must be specified for each group. The user child element specifies the users belonging to that group, and the name, pwd and home attributes specifies the username, crypted password, and path to the home directory. The password can be created by the kiwi ——createpassword tool.

3.1.6 drivers element

```
<drivers type="type" profiles="name">
    <file name="filename"/>
    ...
</drivers>
```

The optional drivers element is only useful for boot images (initrd). As a boot image doesn't need to contain the complete kernel one can save a lot of space if only the required drivers are part of the image. Therefore the drivers section exists. If present only the drivers which matches the file names or glob patterns will be included into the boot image. The type attribute specifies one of the following driver types:

drivers

Each file is specified relative to the /lib/modules/<Version>/kernel directory.

netdrivers

Each file is specified relative to the /lib/modules/<Version>/kernel/drivers directory.

• scsidrivers

Each file is specified relative to the /lib/modules/<Version>/kernel/drivers

usbdrivers

Each file is specified relative to the /lib/modules/<Version>/kernel/drivers directory.

According to the driver type the specified files are searched in the corresponding directory. The information about the drivernames is provided as environment variable named like the value of the type attribute and is processed by the function **suseStripKernel**. According to this along with a boot image description a script called **images.sh** must exist which calls this function in order to allow the driver information to have any effect.

3.1.7 repository element

```
<repository type="type"
    status="replaceable"
    alias="name"
    priority="number">
        <source path="URL"/>
</repository>
...
```

The mandatory repository section specifies the source URL and type used by the package manager. The type attribute specifies the repository type which must be supported by the package manager. At the moment KIWI supports the package managers smart and zypper whereas smart has support for more repository types compared to zypper. Therefore the possible values for the type attribute has beend copied from smart. The following table shows the possible repo types:

type	smart	zypper
apt-deb	yes	no
apt-rpm	yes	no
deb-dir	yes	no
mirrors	yes	no
red-carpet	yes	yes
rpm-dir	yes	yes
rpm-md	yes	yes
slack-site	yes	no
up2date-mirrors	yes	no
urpmi	yes	no
yast2	yes	yes

Within the repository section there are the following optional attributes:

• status="replaceable"

This attribute makes only sense for boot image descriptions. It indicates that the repository is allowed to become replaced by the repositories defined in the system image descriptions. Because kiwi automatically builds the boot image if required it should create that image from the same repositories which are used to build the system image to make sure both fit together. Therefore it is required to allow the repository to become overwritten which is indicated by the status attribute.

• alias="name"

Specifies an alternative name used to identify the source channel. If not set the source attribute value is used and builds the alias name by replacing each "/" with a "_". An alias name should be set if the source argument doesn't really explain what this repository contains

• priority="number"

Specifies the repository priority assigned to all packages available in this repository. For **smart** the following applies: If the exact same package is available in more than one channel, the repository with the **highest** priority number is used. The value 0 means **no priority is set**. For **zypper** the following applies: If the exact same package is available in more than one channel, the repository with the **lowest** priority number is used. The value 99 means **no priority is set**.

The source child element contains the path attribute, which specifies the location (URL) of the repository. The path specification can be any of the following, and can include the %arch macro which is expanded to the architecture of the image building host.

• this://<path>

A relative path name, which is relative to the image description directory being referenced.

• iso://<path/to/isofile

A path to a local .iso file which is then loopback mounted and used as a local path based repository. Alternatively one can do the loop mount himself and point a standard local path to the mounted directory

http://<url>

A http protocol based network location

https://<url>

A https protocol based network location

• ftp://<url>

A ftp protocol based network location

• opensuse://<Project-Name>

A special http based network location which is created from the given open-SUSE buildservice project name. The result is pointing to an rpm-md repository on the openSUSE buildservice. For example: path="opensuse://openSUSE:10.3/standard"

• file:///local/path

A local path which should be an absolute path description. The file:// prefix is optional and could also be omitted.

obs://\$dir1/\$dir2

A special buildservice path whereas \$dir1 and \$dir2 represents the build-service project location. If this type is used as part of a boot attribute kiwi evaluates it to this://images/\$dir1/\$dir2 and if used as part of a repository source path attribute it evaluates to this://repos/\$dir1/\$dir2

Multiple repository sections are allowed and combined by the used package manager. By default the package manager will always use the latest packages available.

3.1.8 packages element

```
<packages type="type" profiles="name"</pre>
          patternType="type"
         patternPackageType="type"
    <package name="name" arch="arch"/>
    <package name="name" replaces="name"/>
    <package name="name"</pre>
          bootinclude="true" bootdelete="true"/>
    <archive name="name"
          bootinclude="true"/>
    <package .../>
    <opensusePattern name="name"/>
    <opensusePattern .../>
    <opensuseProduct name="name"/>
    <opensuseProduct .../>
    <ignore name="name"/>
    <ignore .../>
</packages>
```

The mandatory packages element specifies the list of packages and pattern names to be used with the image. There are five different types of package sets or patterns, specified with the type attribute:

image

Image packages, list of packages used to finish the image installation. All packages which make up the image are listed here

bootstrap

Bootstrap packages, list of packages used to start creating a new operating system root tree. Basic components which are required to chroot into that system, such as glibc, are listed here.

delete

Delete packages, list of packages stored for later deletion. The package names are available in the \$delete environment variable of the /.profile file created by KIWI. The baseGetPackagesForDeletion() function returns the contents of this environment variable, and can be used to delete the packages while ignoring requirements or dependencies. According to this a config.sh or images.sh script needs to be provided such as the following code snippet shows:

```
rpm -e --nodeps --noscripts \
    $(rpm -q 'baseGetPackagesForDeletion' | grep -v "is not installed")
```

xen

Xen required packages, list of packages used when the image needs support for Xen-based virtualization.

vmware

VMware required packages, list of packages used when the image needs support for VMware- or generic based full virtualization.

Using patterns

Using a pattern name enhances the package list with a number of additional packages belonging to this pattern. Support for patterns is SUSE-specific, and available with openSUSE 10.1 or later. The optional patternType and patternPackageType attributes specify which pattern references or packages should be used in a given pattern. The values of these attributes are only evaluated if the KIWI pattern solver is used. If the new (up to SUSE 11.0) satsolver pattern solver is used these values are ignored because the satsolver can't handle that at the moment. Allowed values for the pattern* attributes are:

onlyRequired

Incorporates only patterns and packages that are required by the given pattern

plusSuggested

Incorporates patterns and packages that are required and suggested by the given pattern

plusRecommended

Incorporates patterns and packages that are required and recommended by the given pattern.

By default, only required patterns and packages are used. The result list of packages is solved into a clean conflict free list of packages by the package manager. This for example means that including a suggested package may include required and recommended packages as well according to the dependencies. If a pattern contains unwanted packages, you can use the ignore element to specify an ignore list, with the name attribute containing the package name. Please note that you can't ignore a package if it is required by a package dependency of another pack-

age in your list. The packagemanager will automatically pull in the package even if you have ignored it.

Architecture restrictions

To restrict a package to a specific architecture, use the **arch** attribute to specify a comma separated list of allowed architectures. Such a package is only installed if the build systems architecture (uname -m) matches one of the specified values of the arch attribute.

Image type specific packages

If a package is only required for a specific type of image and replaces another package you can use the **replaces** attribute to tell kiwi to install the package by replacing another one. For example you can specify the kernel package in the type=image section as

```
<package name="kernel-default" replaces="kernel-xen"/>
```

and in the type=xen section as

```
<package name="kernel-xen" replaces="kernel-default"/>
```

The result is the xen kernel if you request a xen image and the default kernel in any other case.

Packages to become included into the boot image

The optional attributes **bootinclude** and **bootdelete** can be used to mark a package inside the system image description to become part of the corresponding boot image (initrd). This feature is most often used to specify bootsplash and/or graphics boot related packages inside the system image description but they are required to be part of the boot image as the data is used at boot time of the image. If the bootdelete attribute is specified along with the bootinclude attribute this means that the selected package will be marked as a *to become deleted* package and is removed by the contents of the images.sh script of the corresponding boot image description

Data not available as packages to become included

With the optional **archive** element it's possible to include any kind of data into the image. The archive elements expects the name of a tarball which must exist as part of the system image description. kiwi then picks up the tarball and installs it into the image. If the **bootinclude** attribute is set along with the archive element the data will also become installed into the boot image.

3.1.9 vmwareconfig element

The optional vmwareconfig section is used if the image description includes a packages section of type **vmware**. In this case kiwi is able to create the guest configuration file required to run the image within VMware. The guest configuration file can also be created by the VMware toolkit itself but with the pre-created guest configuration created by kiwi it is possible to provide an all in one bundle ready to run in VMware. The following general information can be provided to create the VMware (.vmx) configuration file:

arch

The virtualized architecture. Can be one of ix86 or x86_64 Bydefault ix86 is used.

memory

The mandatory memory attribute specified how much memory in MB should be allocated for the virtual machine

HWversion

The VMware hardware version number. By default version 3 is used

guestOS

The guestOS identifier. By default suse is used on ix86 and suse-64 for x86_64. At the moment only the suse and sles guestOS types are supported

usb

The bool value **usb** specifies whether the guest machine should provide a virtual USB controller or not.

The following information can be provided to setup the VMware virtual main storage device and CD/DVD drive connection.

controller

The mandatory controller attribute can be either ide or scsi disk

id

The mandatory id attribute specifies the disk id. If only one disk is set the id value should be set to 0

The following information can be provided to setup the VMware virtual network interface

driver

The mandatory driver to use for the virtual network card. Possible values are vlance, e1000 or vmxnet. vmxnet requires the vmware tools to be part of the image

interface

The mandatory network interface number. If only one interface is set the value should be set to 0

mode

The network mode used to communicate outside the VM. In many cases the bridged mode is used.

3.1.10 xenconfig element

The optional xenconfig section is used if the image description includes a packages section of type **xen**. In this case kiwi is able to create the guest configuration file required to run the image within Xen. According to this it's possible to provide an all in one bundle ready to run in Xen. The following general information can be provided to create the Xen (.xenconfig) configuration file:

memory

The mandatory memory attribute specified how much memory in MB should be allocated for the para virtual machine

The following information can be provided to setup the Xen para virtual main storage device as part of a **xendisk** section

• device

The mandatory device which should appear in the para virtual instance

The default Xen configuration uses bridging within domain 0 to allow all domains to appear on the network as individual hosts. In order to create the bridge which can be used by the Xen virtual network interface(s) the script "/etc/xen/scripts/network-bridge start" can be called to create a bridge as shown in the following picture:



Figure 3.2: Illustration on network-bridge and vif-bridge

Additional information on how to setup networking with Xen can be found here: http://wiki.xensource.com/xenwiki/XenNetworking The following information can be provided to setup the Xen network bridge as part of one ore more xenbridge section(s).

name

The name of the network interface which is the bridge between the physical device (peth) and the virtual device(s) (vif).

• mac

The optional mac address value for the virtual interface inside the DOM(x).

```
<deploy server="IP" blocksize="4096">
    <timeout>seconds</timeout>
    <commandline>kernel-options</commandline>
    <kernel>kernel-file</kernel>
    <initrd>initrd-file</initrd>
    <partitions device="/dev/sda">
        <partition type="swap" number="1" size="MB"/>
        <partition type="L" number="2" size="MB"</pre>
                  mountpoint="/" target="true"/>
        <partition type="fd" number="3"/>
    </partitions>
    <union ro="dev" rw="dev" type="aufs | unionfs"/>
    <configuration source="/KIWI/../file" dest="/../file"</pre>
                   arch="..."/>
    <configuration .../>
</deploy>
```

The optional deploy section is only useful if you build the **pxe** image type. For this type an additional network boot infrastructure needs to be set up. To ease the process of setting up such a boot server kiwi provides a package called kiwi-pxeboot. This package sets up the basic pxe boot environment like kiwi expects it. The package will setup a directory structure in /srv/tftpboot. The result files of the kiwi image build process needs to be copied to that location. A detailed explanation of what file needs to be copied and where is provided in the PXE Image chapter later in this document. Among the image files itself it is required to provide an information how KIWI should handle the machine it should be install with the created image. Information like which image should be used or how to partition the machine needs to be provided in a file called config. <MAC-Address> below the directory /srv/tftpboot/KIWI. The reason for the deploy section is to allow KIWI to create that file according to the information provided in the image description.

- The server and blocksize attributes specify the TFTP server which controls the download of image files. KIWI also supports other protocols than tftp but in order to do that the variables **kiwiserver** and **kiwiservertype** must be set as kernel parameter when the client boots.
- The optional timeout section specifies the grub timeout in seconds which is used when the KIWI initrd configures and installs the grub boot loader on the machine after the first deployment to allow standalone boot.
- The optional commandline section specifies the kernel options which should be passed to the kernel by the grub bootloader. the KIWI initrd includes this kernel options when installing the grub for standalone boot
- The optional kernel and initrd sections specifies the KIWI kernel and initrd files on the boot server. In case of a special boot method which is not supported by the distribution standard mkinitrd the KIWI initrd needs to stay on the system and needs to be used for local boot as well. So if your system image makes use of the split type or your deploy section includes any union information the kernel and initrd sections must be provided.
- The partitions section is required if you want to install the system image on a disk or any other permanent storage device. Each partition is specified by one partition subtag which defines the type (see sfdisk -list-type), partition number, size, optional mountpoint, and optional information on if this partition is the system image target partition. With the KIWI netboot boot image, the first partition is always the swap partition, while the second partition is used, by default, for the system image. With the optional target flag, you can specify a partition other than the second partition to install the system image on. If size is set to "image", KIWI calculates the required size for this partition in order to have enough space for the later image.
- The optional union section is used if the system image is based on a read-only filesystem such as squashfs and should be mounted read-write by using an overlay filesystem like aufs or by a device. mapper setup with the dmsquash type. In this case, KIWI creates an additional write partition, then combines

both partitions with the given overlay filesystem or device map. Currently, there are two such filesystems: unionfs and aufs (aufs is the preferred file system). The partition that holds the read-only system image must be set as the ro attribute value, and the partition that serves as the write partition must be set the rw attribute value.

• The optional configuration section can be used to integrate a network client's configuration files which are stored remotely on the server. The source attribute specifies the path on the server used by a TFTP client program to download the file, and the dest attribute specifies the target relative to the root (/) of the network client. Each file is specified by one configuration section and can be bound to a specific set of architectures separated by comma.

3.1.11 split element

```
<split>
    <temporary>
        <!- read/write access to: ->
        <file name="/var"/>
        <file name="/var/*"/>
        <!- but not on this file: ->
        <except name="/etc/shadow"/>
    </temporary>
    <persistent>
        <!- persistent read/write access to: ->
        <file name="/etc"/>
        <file name="/etc/*"/>
        <!- but not on this file: ->
        <except name="/etc/passwd"/>
    </persistent>
</split>
```

The optional split section is used if your image type is split or iso combined with the attribute compressed. The split section controls which files of your splitted image should be writable and whether they are persistantly writable or only temporarly. In case of an iso image all data specified can only be temporarly writable by design of the live system image type.

The split section distinguishes between directory and files. The information of "/etc" would make /etc a writable directory however none of the files *within* /etc are affected. They remain symbolic links to the real files in the read-only area. The main advantage to putting just a directory in the read-write area is that any new files created there are stored on the disk instead of tmpfs. If all the files in /etc should also be part of the read-write area and according to this put a complete directory including all its files into the read-write area two lines are required as shown above.

4 Creating Appliances with KIWI

Contents

4.1	History	33
4.2	The KIWI model	33

4.1 History

Traditionally, many computing functions were written as software applications running on top of a general-purpose operating system. The consumer (whether home computer user or the IT department of a company) bought a computer, installed the operating system or configured a pre-installed operating system, and then installed one or more applications on top of the operating system. An e-mail server was just an e-mail application running on top of Linux, Unix, Microsoft Windows, or some other operating system, on a computer that was not designed specifically for that application.

4.2 The KIWI model

With KIWI we started to use a different model. Instead of installing firewall software on top of a general purpose computer/operating system, the designers/engineers built images that are designed specifically for the task. These are so called appliances. When building appliances with KIWI the following proceeding has proven to work reliably. Nevertheless the following is just a recommendation and can be adapted to special needs and environments.

- 1. First you should choose an appropriate image description template from the provided kiwi examples and add/adapt repository and/or package names according to the distribution you want to build an image for
- 2. Allow the image to create an in-place git repository to allow tracking of non binary changes. This is done by adding the following into your config.sh script

base Setup Plain Text GIT Repository

- 3. Prepare the preliminary version of your new appliance by calling **kiwi – prepare** Refer to chapter 9 (USB image Live-Stick System) for details.
- 4. Decide for a testing environment. In my opinion a real hardware based test machine which allows to boot from USB is a good and fast approach. According to this make sure you have a usb type in your config.xml

```
<type filesystem="ext3"
boot="usbboot/suse-...">usb</type>
```

- 5. Create the preliminary live stick image of your new appliance by calling **kiwi**-create After successful creation of the image files find an USB stick which is able to store your appliance and plug it into a free USB port on your image build machine. Use the **kiwi** -bootstick ... call to deploy the image on the stick. Refer to chapter 9 (USB image Live-Stick System) for details.
- 6. Plug in the stick on your test machine and boot it
- 7. After your test system has successfully booted from stick login into your appliance and start to tweak the system according to your needs. This includes all actions required to make the appliance work as you wish. Before you start take care for the following:
 - Create an initial package list. This can be done by calling:

• Check the output of the command **git status** and include everything which is unknown to git and surely will not be changed by you and will not become part of the image description overlay files to the /.gitignore files

After the initial package list exists and the git repository is clean you can start to configure the system. You never should install additional software just by installing an unmanaged archive or build and install from source. It's very hard to find out what binary files had been installed and it's also not architecture safe. If there is really no other way for the software to become part of the image you should address this issue directly in your image description and the config.sh script but not after the initial deployment has happened.

8. As soon as your system works as expected your new appliance is ready to enter the final stage. At this point you have done several changes to the system but they are all tracked and should now become part of your image description. To include the changes into your image description the following process should be used:

• Check the differences between the currently installed packages and the initial deployment list. This can be done by calling:

rpm -qa | sort > /tmp/appliancePackages
diff -u /tmp/deployPackages /tmp/appliancePackages

Add those packages which are labeled with (+) to the <packages type="image"> section of your config.xml file and remove those packages which has been removed (-) appropriately. If there are packages which has been removed against the will of the package manager make sure you address the uninstallation of these packages in your config.sh script. If you have installed packages from repositories which are not part of your config.xml file you should also add these repositories in order to allow kiwi to install the packages

• Check the differences made in the configuration files. This can be easily done by calling:

git diff > /tmp/appliancePatch

The created patch should become part of your image description and you should make sure the patch is applied when preparing the image. According to this the command:

patch -p0 < appliancePatch

needs to be added as part of your config.sh script

• Check for new non binary files added. This can be done by calling:

git status

All files not under version control so far will be listed by the command above. Check the contents of this list make sure to add all files which are not created automatically to become part of your image description. To do this simply clone (copy) these files with respect to the filesystem structure as overlay files in your image description *root/* directory

9. All your valuable work is now stored in one image description and can be re-used in all KIWI supported image types. Congratulation! To make sure the appliance works as expected prepare a new image tree and create an image from the new tree. If you like you can deactivate the creation of the git repository which will save you some space on the filesystem. If this

appliance is a server I recommend to leave the repository because it allows you to keep track of changes during the live time of this appliance.

5 Maintenance of Operating System Images

Creating an image often results in an appliance solution for a customer and gives you the freedom of a working solution at that time. But software develops and you don't want your solution to become outdated. Because of this together with an image people always should think of **image-maintenance**. The following paragraph just reflects ideas how to maintain images created by kiwi:



Figure 5.1: Image maintenance scenarios

The picture above shows two possible scenarios which requires an image to become updated. The first reason for updating an image are changes to the software, for example a new kernel should be used. If this change doesn't require additional software or changes in the configuration the update can be done by kiwi itself using its **upgrade** option. In combination with **upgrade** kiwi allows to add an additional repository which may be needed if the updated software is not part of the

original repository. An important thing to know is that this additional repository is **not** stored into the original config.xml file of the image description.

Another reason for updating an image beside software updates are configuration changes or enhancements, for example an image should have replaced its browser with another better browser or a new service like apache should be enabled. In principal it's possible to do all those changes manually within the physical extend but concerning maintenance this would be a nightmare. Why, because it will leave the system in an unversioned condition. Nobody knows what has changed since the very first preparation of this image. So in short **dont't modify physical extends manually**. Changes to the image configuration should be done within the image description. The image description itself should be part of a versioning system like subversion. All changes can be tracked down then and maybe more important can be assigned to product tags and branches. As a consequence an image must be prepared from scratch and the old physical extend could be removed.

6 System to image migration

Contents

(5.1	Create a clean repository set first	39
(5.2	Create a migration report first	40
(5.3	Migrate my system	40
(5.4	Turn my system into an image	41

KIWI provides an experimental module which allows you to turn your running system into an image description. This migration allows you to clone your currently running system into an image. The process has the following limitations at the moment:

- Works for SUSE systems only
- You can't rely on the result to be a 100% ready to use copy of your system. This means some manual postprocessing might be necessary

When calling KIWI's migrate mode it will try to find the base version of your operating system and assigns a predefined repository to recreate the data which exists in terms of packages. The code inspect your system and creates a list of packages and patterns which represents your system so far. Of course there are normally some data which doesn't belong to any package. These are your configurations your user data and all other stuff. KIWI collects all this information and would copy it as overlay files as part of the image description. The process will skip all remote mounted filesystems and concentrate only on local filesystems.

6.1 Create a clean repository set first

When starting with the migration it is useful to let kiwi know about all the repositories from which packages has been installed to the system. In a first step call:

```
kiwi --migrate mySys --destdir /tmp/migrated \
--report-packlist
```

This will only check which packages and patterns could be assigned to the given base repository. In almost all cases there will be information about packages which couldn't be assigned. You should go to that list and think of the repository which contains that packages (pacman, etc...). A good starting point is the output of

zypper sl --details. If you know about the repositories just add then in subsequent calls like:

```
kiwi --migrate mySys --destdir /tmp/migrated \
    --add-repo \
    http://packman.mirrors.skynet.be/pub/packman/suse/11.0 \
    --add-repotype rpm-dir
    --report-packlist
```

You should continue the migration if you have a clean list of solved packages without any package skipped except you know that this package can't be provided or is not worth to become part of the migration.

6.2 Create a migration report first

When running the next step of the migration I recommend to create a report first:

```
kiwi --migrate mySys --destdir /tmp/migrated \
--add-repo ... --add-repotype ...
--report
```

After that call you should walk through the following check list

- check the contents of the config.sh script. The migration added at least the services your system runs and adds them to the configuration script. Check this service list
- check the report file contents. All data which doesn't belong to a package are listed there. You should make sure whether you need them all or if you could exclude some of them. As a recommendation, you should have as little as possible overlay files.
- check the created config.xml image description file. You should at least make sure if the repository is correct and if you need more repositories for packages which are not part of the base repository for example

6.3 Migrate my system...

After the check list you will have a good impression of your system. What data is there what's not part of packages what doesn't need to be part of the image description and so on. You can exclude the directories which you don't need according to the report file with the --exclude parameter. Now you can call migrate

again and let it copy the overlay files too:

6.4 Turn my system into an image...

After the process has finished you should check the size of the image description. The description itself shouldn't be that big. The size of a migrated image description mainly depends on how many overlay files exists in the root/ directory. You should really make sure whether you need them all or not. Now let's try to create a clone image from the description. The most appropriate image type to do this is the virtual disk image (vmx)

```
kiwi -p /tmp/migrated --root /tmp/mySys
kiwi --create /tmp/mySys -d /tmp/myResult \
--type vmx
```

If everything worked well you can test the created virtual disk image in any full virtual operating system environment like QEMU or VMware. Once created the image description can serve for all image types kiwi supports.

7 Installation Source

Contents

7.1 Adapt the example's config.xml	 43
7.2 Create a local installation source	 43

Before you start to use any of the examples provided in the following chapters your build system has to have a valid installation source for the distribution you are about to create an image for. By default all examples will connect to the network to find the installation source. It depends on your network bandwidth how fast an image creation process is and in almost all cases it is better to prepare a local installation source first.

7.1 Adapt the example's config.xml

If you can make sure you have a local installation source it's important to change the path attribute inside of the <repository> element of the appropriate example to point to your local source directory. A typically default repository element looks like the following:

7.2 Create a local installation source

The following describes how to create a local SUSE installation source which is stored below the path: /images/CDs If you are using the local path as described in this document you only need to flip the given path information inside of the example config.xml file.

1. find your SUSE standard installation CDs or the DVD and make them available to the build system. Most linux systems auto-mount a previosly inserted media automatically. If this is the case you simply can change the directory to the auto mounted path below /media. If your system doesn't mount the device automatically you can do this with the following command:

mount -o loop /dev/<drive-device-name> /mnt

- 2. You don't have a DVD but a CD set? No problem all you need to do is copy the contents of **all** CDs into one directory. It's absolutly important that you first start with the **last** CD and copy the first CD at last. In case of CDs you should have a bundly of 4 CDs. Copy them in the order 4 3 2 1
- 3. Once you have access to the media copy the contents of the CDs / DVD to your hard drive. You need at least 4GB free space available. The following is intended to create a SUSE 11.0 installation source:

```
mkdir -p /image/CDs/full-11.0-i386/
cp -a /mnt/* /image/CDs/full-11.0-i386/
```

Remember if you have a CD set start with number 4 first and after that unplugg the CD and insert the next one to repeat the copy command until all CDs are copied into to /image

8 ISO image - Live Systems

Contents

8.1	Building the suse-live-iso example	45
8.2	Using the image	45
8.3	Flavours	46
	8.3.1 Split mode	47

A live system image is an operating System on CD or DVD. In principal one can treat the CD/DVD as the hard disk of the system with the restriction that you can't write data on it. So as soon as the media is plugged into the computer the machine is able to boot from that media. After some time one can login to the system and work with it like on any other system. All write actions takes place in RAM space and therefore all changes will be lost as soon as the computer shuts down.

8.1 Building the suse-live-iso example

The latest example provided with kiwi is based on openSUSE 11.0 and includes the base + kde patterns.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-live-iso \
    --root /tmp/myiso --add-profile KDE
```

```
kiwi --create /tmp/myiso \
--type iso -d /tmp/myiso-result
```

8.2 Using the image

There are two ways to use the generated ISO image:

- Burn the .iso file on a CD or DVD with your preferred burn program. Plug in the CD or DVD into a test computer and (re)boot the machine. Make sure the computer boot from the CD drive as first boot device.
- Use a virtualisation system to test the image directly. Testing an iso can be done with any full virtual system for example:

```
cd /tmp/myiso-result
qemu -cdrom \
./suse-11.0-live-iso.i686-2.5.1.iso -m 256
```

8.3 Flavours

KIWI supports different filesystems and boot methods along with the ISO image type. The provided example by default uses a squashfs compressed root filesystem. By design of this filesystem it is not possible to write data on it. To be able to write on the filesystem another filesystem called aufs is used. aufs is an overlay filesystem which allows to combine two different filesystems into one. In case of a live system aufs is used to combine the squashfs compressed read only root tree with a tmpfs RAM filesystem. The result is a full writable root tree whereas all written data lives in RAM and is therefore not persistent. squashfs and/or aufs does not exist on all versions of SUSE and therefore the flags attribute in config.xml exists to be able to have the following alternative solutions:

• flags="unified" Compressed and unified root tree as explained above

• flags="compressed"

Does filesystem compression with squashfs but don't use an overlay filesystem for write support. A symbolic link list is used instead and thus a split element is required in config.xml. See the Split mode section below for details.

flags="dmsquash"

Creates an ext3 image file and puts that into a squashfs filesystem. On boot the root tree is mounted via a device mapper snapshot device to allow full write access over the complete tree. No other overlay filesystem is required.

• flags="clic"

Creates a fuse based clicfs image and allows write operations into a cow file. In case of an ISO the write happens into a ramdisk.

flags not set

If no flags attribute is set no compressed filesystem and no overlay filesystem will be used. The root tree will be directly part of the ISO filesystem and the paths: /bin, /boot, /lib, /lib64, /opt, /sbin and /usr will be read-only.

8.3.1 Split mode

If no overlay filesystem is in use but the image filesystem is based on a compressed filesystem KIWI allows to setup which files and directories should be writable in a so called split section. In order to allow to login into the system at least the /var directory should be writable because the PAM authentification requires to be able to report any login attempt to /var/log/messages which therefore needs to be writable. The following split section can be used if the flag compressed is used:

9 USB image - Live-Stick System

Contents

9.1	Building the suse-live-stick example 49	
9.2	Using the image	
9.3	Flavours	
	9.3.1 Split stick	
	9.3.2 LVM support	

A live USB stick image is a system on USB stick which allows you to boot and run from this device without using any other storage device of the computer. It is urgently required that the BIOS of the system which you plug the stick in supports booting from USB stick. Almost all new BIOS systems support that. The USB stick serves as OS system disk in this case and you can read and write data onto it.

9.1 Building the suse-live-stick example

The latest example provided with kiwi is based on openSUSE 11.0 and makes use of the default plus x11 pattern. The operating system is stored on a standard ext3 filesystem.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-live-stick \
    --root /tmp/mystick
```

There are two possible image types which allows you to drive the stick. Both are added into the config.xml of this example image description. If you already have access to the stick you want to run the image on the first approach should be preferred over the second one.

 The first image type named "usb" creates all required images for booting the OS but requires you to plug in the stick and let kiwi deploy the data onto this stick.

```
kiwi --create /tmp/mystick --type usb \
-d /tmp/mystick-result
```

• The second image type named "oem" allows you to create a virtual disk which represents a virtual disk geometry including all partitions and boot information in one file. You simply can "dd" this file on the stick.

```
kiwi --create /tmp/mystick --type oem \
-d /tmp/mystick-result
```

9.2 Using the image

To make use of the created images they need to be deployed on the USB stick. For the first image type (usb) you need kiwi itself to be able to deploy the image on the stick. The reason for this is that the usb image type has created the boot and the system image but there is no disk geometry or partition table available. kiwi creates a new partition table on the stick and imports the created images as follows:

```
kiwi --bootstick \
   /tmp/mystick-result/\
   initrd-usbboot-suse-11.0.i686-2.1.1.splash.gz \
   --bootstick-system \
   /tmp/mystick-result/\
   suse-11.0-live-stick.i686-1.1.2
```

In case of the second image type (oem) you only need a tool which allows you to dump data onto a device. On Linux the most popular tool to do this is the **dd** command. The oem image is represented by the file with the .raw extension. As said this is a virtual disk which already includes partition information. But this partition information does not match the real USB stick geometry which means the kiwi boot image (oemboot) has to adapt the disk geometry on first boot. To deploy the image on the stick call:

```
dd if=/tmp/mystick-result/\
   suse-11.0-live-stick.i686-1.1.2.raw \
   of=/dev/<stick-device> bs=32k
```

Testing of the live stick can be done with a test machine which boots from USB or with a virtualisation system. If you test with a virtualisation system for example qemu you should be aware that the USB stick looks like a normal disk to the system. The kiwi boot process searches for the USB stick to be able to mount the correct storage device but in a virtual environment the disk doesn't appear as a USB stick. So if your virtualisation solution doesn't provide a virtual BIOS which allows booting from USB stick you should test the stick on real hardware

9.3 Flavours

USB sticks weren't designed to serve as storage devices for operating systems. By design of these nice little gadgets their storage capacity is limited to only a few G-bytes. According to this KIWI supports compressed filesystems with USB sticks too:

• filesystem="squashfs"

This will compress the image using the squashfs filesystem. The boot process will automatically use aufs as overlay filesystem to mount the complete tree read-write. For the write part an additional ext2 partition will be created on the stick. The support for this compression layer requires squashfs and aufs to be present in the distribution KIWI has used to build the image

• filesystem="dmsquash"

Creates an ext3 image file and puts that into a squashfs filesystem. On boot the root tree is mounted via a device mapper snapshot device to allow full write access over the complete tree.

• filesystem="clicfs"

Creates a fuse based clicfs image and allows write operations into a cow file.

9.3.1 Split stick

If there is no overlay filesystem available it is also possible to define a split section in config.xml and use the split support to split the image into a compressed read-only and a read-write portion. To create a split stick the types needs to be adapted as follows:

type setup for split usb type:

```
<type fsreadwrite="ext3" fsreadonly="squashfs"
boot="usbboot/suse-11.0">split</type>
```

• type setup for split oem type:

```
<type fsreadwrite="ext3" fsreadonly="squashfs"
boot="oemboot/suse-11.0">split</type>
```

For both types a split section is required which defines the read-write data. A good starting point is to set /var, /home and /etc as writable data.

If no split section is added the default split section from /usr/share/kiwi/modules/KIWISplit.txt is used

9.3.2 LVM support

kiwi also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. kiwi creates the kiwiVG volume group and adds logical volumes as they are needed and configured according to the image type and filesystem. After boot of the system the user has full control over the volume group and is free to change/resize/increas the group and the volumes inside. Support for LVM has been added for all image types which are disk based. This includes vmx,oem and usb. In order to use LVM for the usb type just add the --lvm option as part of the kiwi kiwi --bootstick deployment or add the attribute lvm="true" as part of

the **type** section in your config.xml file.

The optional **lvmvolumes** section can be used to set one or more top level directories into a separate volume. For example you want to put /usr and /var into different volumes add the following lvmvolumes section:

The optional freespace attribute let you add additional free space for that volume. If you don't set any freespace the volume will be about 80% to 90% full.

10 VMX image - Virtual Disks

Contents

10.1 Building the suse-vm-guest example	55
10.2 Using the image	55
10.3 Flavours	56
10.3.1 VMware support	56
10.3.2 LVM support	57

A VMX image is a virtual disk image for use in full virtualisation systems like QEMU or VMware. The image represents a file which includes partition data and bootloader information. The size of this virtual disk can be influenced by either the <size> element in your config.xml file or by the parameter —bootvm-disksize

10.1 Building the suse-vm-guest example

The latest example provided with kiwi is based on openSUSE 11.0 and makes use of the base pattern. The operating system is stored on a standard ext3 filesystem.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-vm-guest \
    --root /tmp/myvm
```

```
kiwi --create /tmp/myvm \
--type vmx -d /tmp/myvm-result
```

10.2 Using the image

The generated virtual disk image serves as the harddisk of the selected virtualisation system. The setup of the virtual hard disk differes from the variety of the

virtualisation systems. A very simply to use system is the QEMU virtualisation software. To run your image in qemu call:

```
cd /tmp/myvm-result
qemu suse-11.0-vm-guest.i686-1.1.2.raw -m 256
```

10.3 Flavours

Because there are many virtualisation systems available there are also many virtual disk formats. The .raw format KIWI always creates has the same structure as you can find on a real hard disk. For virtualisation software it makes sense to have specific formats to increase the I/O performance when reading or writing data onto the disk from within the virtual system. If you want to tell KIWI to create an additional disk format just extend the type information of the config.xml file by a format attribute.

rm1 C 11 ·	. 11 1	1.		. 1 • . 1	1 1 1 C
The tellerating	table cr	1011C 2 11C	t of cumo	rtad viirtiia	dick tormate
The following	Lable Si	iuvvs a iisi	L OI SUDDO	itcu viituai	uisk iuimats

Name	Description
vvfat	Disk format DOS FAT32
vpc	Virtual PC read only disk
bochs	Disk format for Bochs emulator
dmg	Disk format for Mac OS X
cloop	Compressed loop
vmdk	Disk format for VMware
ovf	Open Virtual Format requires VMwares ovftool
qcow2	QEMU virtual disk format
qcow	QEMU virtual disk format
cow	QEMU virtual disk format

10.3.1 VMware support

VMware is a very popular and fast virtualisation platform which is the reason why KIWI has special support for it. VMware requires a so called guest configuration which includes information about what hardware should make up the guest and how much ressources should be provided to the guest. With KIWI you can provide the information required to create a guest configuration as part of the config.xml file. Additionally you can group special packages which you may only need in this virtual environment.

```
<packages type="vmware">
    <!-- packages you need in VMware only -->
    </packages>
    <vmwareconfig memory="512">
         <vmwaredisk controller="ide" id="0"/>
         </vmwareconfig>
```

If this information is present KIWI will create a VMware guest configuration with 512 MB of RAM and an IDE disk controller interface. Additional information to setup the VMware guest machine properties are explained in the **vmwareconfig** section. The written guest configuration file can be easily loaded and changed by the native graphics user provided with VMware. The KIWI VMware guest configuration is stored in the file:

```
tmp/myvm-result/suse-11.0-vm-guest.i686-1.1.2.vmx
```

Together with the **format="vmdk"** attribute KIWI creates a VMware based image (.vmdk file) and the required VMware guest configuration (.vmx)

You can also create an image for the Xen virtualization framework. To do this, you simply need to specify the 'xen' **bootprofile** and the 'nex' **bootkernel** in your config.xml type section. Don't be curious about the name 'nex' as bootkernel. The reason for this is just because the name of the boot profile is xen and the name of the kernel is also xen. Therefore I simply decided to use the reverse name for it. Like VMware, Xen has a configuration file as well. Refer to chapter 13 (Xen image) for details.

10.3.2 LVM support

kiwi also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. kiwi creates the kiwiVG volume group and adds logical volumes as they are needed and configured according to the image type and filesystem. After boot of the system the user has full control over the volume group and is free to change/resize/increas the group and the volumes inside. Support for LVM has been added for all image types which are disk based. This includes vmx,oem and usb. In order to use LVM for the vmx type just add the --lvm option as part of the kiwi create step or add the attribute lvm="true" as part of the type section in your config.xml file.

```
kiwi --create /tmp/myvm --type vmx \
-d /tmp/myvm-result --lvm
```

With the optional **lvmvolumes** section you can set one or more top level directories into a separate volume. For example you want to put /usr and /var into different volumes add the following lvmvolumes section:

The optional freespace attribute let you add additional free space for that volume. If you don't set any freespace the volume will be about 80% to 90% full.

11 PXE image - Thin Clients

Contents

11.1 Setting up the required services	59	
11.1.1 atftp server	59	
11.1.2 DHCP server	60	
11.2 Building the suse-pxe-client example	60	
11.3 Using the image	61	
11.4 Flavours	62	
11.4.1 The pxe client Control File	62	
11.4.2 The pxe client Configuration File	62	
11.4.3 User another than tftp as download protocol	67	
11.4.4 RAM only image	67	
11.4.5 union image	68	
11.4.6 split image	68	
11.4.7 root tree over NFS	69	
11.4.8 root tree over NBD	69	
11.4.9 root tree over AoE	69	

A pxe image consists of a boot image and a system image like all other image types too. But with a pxe image the image files are available seperately and needs to be copied at specific locations of a network boot server. PXE is a boot protocol implemented in most BIOS implementations which makes it so interesting. The protocol sends DHCP requests to assign an IP address and after that it uses tftp to download kernel and boot instructions.

11.1 Setting up the required services

Before you start to build pxe images with kiwi you should have setup the boot server. The boot server requires the services **atftp** and **DHCP** to run

11.1.1 atftp server

In order to setup the atftp server the following steps are required

1. install the packages atftp and kiwi-pxeboot

- 2. edit the file /etc/sysconfig/atftpd and set/modify the following variables:
 - ATFTPD OPTIONS="--daemon --no-multicast"
 - ATFTPD_DIRECTORY="/srv/tftpboot"
- 3. run atftpd by calling the command: rcatftpd start

11.1.2 DHCP server

In contrast to the atftp server setup the following DHCP server setup can only serve as an example. Please note that according to your network structure the IP addresses, ranges and domain settings needs to be adapted in order to allow the DHCP server to work within your network. If you already have a DHCP server running in your network you should make sure that the filename and next-server information is provided by your server. The following steps describe how to setup a new DHCP server instance:

- 1. install the package dhcp-server
- 2. create the file /etc/dhcpd.conf and include the following statements:

```
option domain-name "example.org";
option domain-name-servers 192.168.100.2;
option broadcast-address 192.168.100.255;
option routers 192.168.100.2;
option subnet-mask 255.255.255.0;
default-lease-time 600;
max-lease-time 7200;
ddns-update-style none; ddns-updates off;
log-facility local7;
subnet 192.168.100.0 netmask 255.255.255.0 {
   filename "pxelinux.0";
   next-server 192.168.100.2;
   range dynamic-bootp 192.168.100.5 192.168.100.20;
}
```

- 3. edit the file /etc/sysconfig/dhcpd and setup the network interface the server should listen on:
 - DHCPD INTERFACE="eth0"
- 4. run the dhcp server by calling: rcdhcpd start

11.2 Building the suse-pxe-client example

The example provided with kiwi is based on openSUSE 11.0 and creates an image for a Wyse VX0 terminal with a 128MB flash card and 512MB of RAM. The image makes use of the squashfs compressed filesystem and its root tree is deployed as unified (aufs) based system.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-pxe-client \
    --root /tmp/mypxe
```

```
kiwi --create /tmp/mypxe --type pxe \
-d /tmp/mypxe-result
```

11.3 Using the image

In order to make use of the image all related image parts needs to be copied onto the boot server. According to the example the following steps needs to be performed:

Change working directory

```
cd /tmp/mypxe-result
```

2. Copy of the boot and kernel image

```
cp initrd-netboot-suse-11.0.i686-2.1.1.splash.gz \
    /srv/tftpboot/boot/initrd
cp initrd-netboot-suse-11.0.i686-2.1.1.kernel \
    /srv/tftpboot/boot/linux
```

3. Copy of the system image and md5 sum

```
cp suse-11.0-pxe-client.i686-1.2.8 \
   /srv/tftpboot/image
cp suse-11.0-pxe-client.i686-1.2.8.md5 \
   /srv/tftpboot/image
```

4. Copy of the image boot configuration

Normally the boot configuration applies to one client which means it is required to obtain the MAC address of this client. If the boot configuration should be used globaly the KIWI generated file can be copied as config.default

```
cp suse-11.0-pxe-client.i686-1.2.8.config \
   /srv/tftpboot/KIWI/config.<MAC>
```

5. Check the PXE configuration file

The PXE configuration controls which kernel and initrd are loaded and which kernel parameters are set. When installing the kiwi-pxeboot package a default configuration is added. To make sure the configuration is valid according to this example the file /srv/tftpboot/pxelinux.cfg/default should provide the following information:

```
DEFAULT KIWI-Boot

LABEL KIWI-Boot

kernel boot/linux

append initrd=boot/initrd vga=0x314

IPAPPEND 1

LABEL Local-Boot
localboot 0
```

6. connect the client to the network and boot

11.4 Flavours

All the different PXE boot based deployment methods are controlled by the config. <MAC> (or config.default) file. When a new client boots up and there is no client configuration file the new client is registered by uploading a control file to the tftp server. The following sections informs about the control and the configuration file.

11.4.1 The pxe client Control File

This section describes the netboot client control file:

```
hwtype.<MAC Address>
```

The control file is primarily used to set up new netboot clients. In this case, there is no configuration file corresponding to the client MAC address available. Using the MAC address information, the control file is created, which is uploaded to the TFTP servers upload directory /var/lib/tftpboot/upload.

11.4.2 The pxe client Configuration File

This section describes the netboot client configuration file:

```
config.<MAC Address>
```

The configuration file contains data about image, configuration, synchronization, or partition parameters. The configuration file is loaded from the TFTP server directory <code>/var/lib/tftpboot/KIWI</code> via TFTP for previously installed netboot clients. New netboot clients are immediately registered and a new configuration file with the corresponding MAC address is created. The standard case for the deployment

of a pxe image is one image file based on a read-write filesystem which is stored onto a local storage device of the client. Below, find an example to cover this case.

```
DISK=/dev/sda
PART=5;S;x,x;L;/
IMAGE=/dev/sda2;suse-11.0-pxe-client.i686;1.2.8;192.168.100.2;4096
```

The following format is used:

```
IMAGE=device;name;version;srvip;bsize;compressed,...,
```

CONF=src;dest;srvip;bsize,..., src;dest;srvip;bsize

PART=size;id;Mount,...,size;id;Mount

DISK=device

IMAGE

Specifies which image (name) should be loaded with which version (version) and to which storage device (device) it should be linked, e.g., /dev/ram1 or /dev/hda2. The netboot client partition (device) hda2 defines the root file system "/" and hda1 is used for the swap partition. The numbering of the hard disk device should not be confused with the RAM disk device, where /dev/ram0 is used for the initial RAM disk and can not be used as storage device for the second stage system image. SUSE recommends to use the device /dev/ram1 for the RAM disk. If the hard drive is used, a corresponding partitioning must be performed.

- srvip

Specifies the server IP address for the TFTP download. Must always be indicated, except in PART.

bsize

Specifies the block size for the TFTP download. Must always be indicated, except in PART. If the block size is too small according to the maximum number of data packages (32768), **linuxrc** will automatically calculate a new blocksize for the download.

compressed

Specifies if the image file on the TFTP server is compressed and handles it accordingly. To specify a compressed image download only the keyword "'compressed" needs to be added. If compressed is not specified the standard download workflow is used. Note: The download will fail if you specify "compressed" and the image isn't compressed. It will also fail if you don't specify "compressed" but the image is compressed. The name of the compressed image has to contain the suffix .gz and needs to be compressed with the gzip tool. Using a compressed image will automatically deactivate the multicast download option of atftp.

CONF

Specifies a comma-separated list of source:target configuration files. The

source (src) corresponds to the path on the TFTP server and is loaded via TFTP. The download is made to the file on the netboot client indicated by the target (dest).

PART

Specifies the partitioning data. The comma-separated list must contain the size (size), the type number (id), and the mount point (Mount). The size is measured in MB by default. Additionally all size specifications supported by the sfdisk program are allowed as well. The type number specifies the ID of the partition. Valid ID's are listed via the *sfdisk* –*list-types* command. The mount specifies the directory the partition is mounted to.

- The first element of the list must define the swap partition.
- The second element of the list must define the **root** partition.
- The swap partition must not contain a mount point. A lowercase letter x must be set instead.
- If a partition should take all the space left on a disk one can set a lower x letter as size specification.

DISK

Specifies the hard disk. Used only with PART and defines the device via which the hard disk can be addressed, e.g., /dev/hda.

• RELOAD IMAGE

If set to a non-empty string, forces the configured image to be loaded from the server even if the image on the disk is up-to-date. Used mainly for debugging purposes, this option only makes sense on diskful systems.

RELOAD CONFIG

If set to an non-empty string, forces all config files to be loaded from the server. Used mainly for debugging purposes, this option only makes sense on diskful systems.

• COMBINED IMAGE

If set to an non-empty string, indicates that the both image specified needs to be combined into one bootable image, whereas the first image defines the read-write part and the second image defines the read-only part.

• KIWI INITRD

Specifies the kiwi initrd to be used for local boot of the system. The variables value must be set to the name of the initrd file which is used via PXE network boot. If the standard tftp setup suggested with the kiwi-pxeboot package is used all initrd files resides in the **boot**/ directory below the tftp server path /var/lib/tftpboot. Because the tftpserver do a chroot into the tftp server path you need to specify the initrd file as the following example shows: KIWI_INITRD=/boot/<name-of-initrd-file>

• UNIONFS_CONFIG

For netboot and usbboot images there is the possibility to use unionfs or aufs as container filesystem in combination with a compressed system image. The recommended compressed filesystem type for the system image is **squashfs**. In case of a usb-stick system the usbboot image will automatically setup the unionfs/aufs filesystem. In case of a PXE network image the netboot image requires a config.<MAC> setup like the following example shows: UNIONFS_CONFIG=/dev/sda2,/dev/sda3,aufs. In this example the first device /dev/sda2 represents the read/write filesystem and the second device /dev/sda3 represents the compressed system image filesystem. The container filesystem aufs is then used to cover the read/write layer with the read-only device to one read/write filesystem. If a file on the read-only device is going to be written the changes inodes are part of the read/write filesystem. Please note the device specifications in UNIONFS_CONFIG must correspond with the IMAGE and PART information. The following example should explain the interconnections:

```
IMAGE=/dev/sda3;image/myImage;1.1.1;192.168.1.1;4096
PART=200;S;x,300;L;/,x;L;x
UNIONFS_CONFIG=/dev/sda2,/dev/sda3,aufs
DISK=/dev/sda
```

As the second element of the PART list must define the **root** partition it's absolutely important that the first device in UNIONFS_CONFIG references this device as read/write device. The second device of UNIONFS_CONFIG has to reference the given IMAGE device name.

• KIWI KERNEL OPTIONS

Specifies additional command line options to be passed to the kernel when booting from disk. For instance, to enable a splash screen, you might use 'vga=0x317 splash=silent'.

KIWI_BOOT_TIMEOUT

Specifies the number of seconds to wait at the grub boot screen when doing a local boot. The default is 10.

NBDROOT

Mount the system image root filesystem remotely via NBD (Network Block Device). This means there is a server which exports the root directory of the system image via a specified port. The kernel provides the block layer, together with a remote port that uses the nbd-server program. For more information on how to set up the server, see the nbd-server man pages. The kernel on the remote client can set up a special network block device named /dev/nb0 using the nbd-client command. After this device exists, the mount program is used to mount the root filesystem. To allow the KIWI boot image to use that, the following information must be provided:

The NBD-Device, NBD-Swap-Port-Number, and NBD-Swap-Device variables are optional. If they are not set, the default values are used (/dev/nb0 for the NBD-Device, port number 9210 for the NBD-Swap-Port-Number, and /de-v/nb1 for the NBD-Swap-Device). The swap space over the network using a

network block device is only established if the client has less than 48 MB of RAM.

AOEROOT

Mount the system image root filesystem remotely via AoE (ATA over Ethernet). This means there is a server which exports a block device representing the the root directory of the system image via the AoE subsystem. The block device could be a partition of a real or a virtual disk. In order to use the AoE subsystem I recommend to install the *aoetools* and *vblade* packages from here first:

http://download.opensuse.org/repositories/system:/aoetools Once installed the following example shows how to export the local /dev/sdb1 partition via AoE:

vbladed 0 1 eth0 /dev/sdb1

Some explanation about this command, each AoE device is identified by a couple Major/Minor, with major between 0-65535 and minor between 0-255. AoE is based just over Ethernet on the OSI models so we need to indicate which ethernet card we'll use. In this example we export /dev/sdb1 with a major value of 0 and minor of 1 on the eth0 interface. We are ready to use our partition on the network! To be able to use the device kiwi needs the information which AoE device contains the root filesystem. In our example this is the device /dev/etherd/e0.1. According to this the AOEROOT variable must be set as follows:

AOEROOT=/dev/etherd/e0.1

kiwi is now able to mount and use the specified AoE device as the remote root filesystem.

NFSROOT

Mount the system image root filesystem remotely via NFS (Network File System). This means there is a server which exports the root filesystem of the network client in such a way that the client can mount it read/write. In order to do that, the boot image must know the server IP address and the path name where the root directory exists on this server. The information must be provided as in the following example:

NFSROOT=NFS.Server.IP.address;/path/to/root/tree

• KIWI INITRD

Specifies the KIWI initrd to be used for a local boot of the system. The value must be set to the name of the initrd file which is used via PXE network boot. If the standard TFTP setup suggested with the kiwi-pxeboot package is used, all initrd files reside in the /srv/tftpboot/boot/ directory. Because the TFTP server does a chroot into the TFTP server path, you must specify the initrd file as follows:

KIWI_INITRD=/boot/name-of-initrd-file

• KIWI KERNEL

Specifies the kernel to be used for a local boot of the system The same path

rules as described for KIWI_INITRD applies for the kernel setup:

KIWI_KERNEL=/boot/name-of-kernel-file

ERROR INTERRUPT

Specifies a message which is displayed during first deployment. Along with the message a shell is provided. This functionality should be used to send the user a message if it's clear the boot process will fail because the boot environment or something else influences the pxe boot process in a bad way.

11.4.3 User another than tftp as download protocol

By default all downloads controlled by the kiwi linuxrc code are performed by an atftp call and therefore uses the tftp protocol. With PXE the download protocol is fixed and thus you can't change the way how the kernel and the boot image (initrd) is downloaded. As soon as linux takes over control the following download protocols http, https and ftp are supported too. KIWI makes use of the **curl** program to support the additional protocols.

In order to select one of the additional download protocols the following kernel parameters needs to be setup:

kiwiserver

Name or IP address of the server who implements the protocol

kiwiservertype

Name of the download protocol which could be one of http, https or ftp

To setup this parameters edit the file /srv/tftpboot/pxelinux.cfg/default on your PXE boot server and change the append line accordingly. Please note all downloads except for kernel and initrd are now controlled by the given server and protocol. You need to make sure that this server provides the same directory and file structure as initially provided by the kiwi-pxeboot package.

11.4.4 RAM only image

If there is no local storage and no remote root mount setup the image can be stored into the main memory of the client. Please be aware that there should be still enough RAM space available for the operating system after the image has been deployed into RAM. Below, find an example:

- use a read-write filesystem in config.xml, for example filesystem="ext3"
- sample config. <MAC>

```
IMAGE=/dev/ram1; suse-11.0-pxe-client.i686;\
1.2.8;192.168.100.2;4096
```

11.4.5 union image

As used in the suse-pxe-client example it is possible to make use of the aufs or unionfs overlay filesystems to combine two filesystems into one. In case of thin clients there is often the need for a compressed filesystem due to space limitations. Unfortunately all common compressed filesystems provides only read-only access. Combining a read-only filesystem with a read-write filesystem is a solution for this problem. In order to use a compressed root filesystem make sure your config.xml's filesystem attribute contains either squashfs or dmsquash. Below, find an example:

11.4.6 split image

As an alternative to the UNIONFS_CONFIG method it is also possible to create a split image and combine the two portions with the COMBINED_IMAGE method. This allows to use different filesystems without the need for an overlay filesystem to combine them together. Below find an example:

- add a split type in config.xml, for example
 type fsreadonly="squashfs" fsreadwrite="ext3" boot="netboot/suse-11.0">split</type>
- add a split section to describe the writable portion, for example:

sample config.<MAC>

11.4.7 root tree over NFS

Instead of installing the image onto a local storage device of the client it is also possible to let the client mount the root tree via an NFS remote mount. Below find an example:

- Export the kiwi prepared tree via NFS
- sample config.<MAC>

```
NFSROOT=192.168.100.7;/tmp/kiwi.nfsroot
```

11.4.8 root tree over NBD

As an alternative for root over NFS it is also possible to let the client mount the root tree via a special network block device. Below find an example:

- Use nbd-server to export the kiwi prepared tree
- sample config.<MAC>

```
NBDROOT=192.168.100.7;2000;/dev/nbd0
```

11.4.9 root tree over AoE

As an alternative for root over NBD it is also possible to let the client mount the root device via a special ATA over Ethernet network block device. Below find an example:

• Use the vbladed command to bind a block device to an ethernet interface. The block device can be a disk partition or a loop device (losetup) but not a directory like with NBD

• sample config.<MAC>

AOEROOT=/dev/etherd/e0.1

This would require the command " $vbladed\ 0\ 1\ eth0\ blockdevice$ " to be called first

12 OEM image - Preload Systems

Contents

12.1 Building the suse-oem-preload example	. 71
12.2 Using the image	. 72
12.3 Flavours	. 72
12.3.1 Influencing the oem partitioning	72
12.3.2 LVM support	74

An oem image is a virtual disk image representing all partitions and bootloader information like it exists on a real disk. The image format is the same compared to the VMX image type. All flavours explained in the VMX chapter also applies to the OEM type.

The original idea of an oem image is to provide this virtual disk data to OEM vendors which now are able to deploy the system independently onto their storage media. The deployment can happen from any OS including Windows if a tool to dump data on a disk device exists. The oem image type is also used to deploy images on USB sticks because in principal it is the same workflow.

12.1 Building the suse-oem-preload example

The latest example provided with kiwi is based on openSUSE 11.0 and includes the patterns default plus x11. The image type is a split type whereas the read-write filesystem is ext3 and the read-only filesystem is squashfs. The additional format attribute also creates an installable ISO image for deploying the image from CD.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-oem-preload \
    --root /tmp/myoem
```

```
kiwi --create /tmp/myoem --type split \
-d /tmp/myoem-result
```

12.2 Using the image

Testing the oem virtual disk can be done with a virtualisation software like QEMU or VMware. The virtual disk is represented by the .raw extension whereas the .iso extension represents the installation disk for this oem image. The installation disk should be tested on a bare test system For the .raw test just call:

```
cd /tmp/myoem-result
qemu suse-11.0-oem-preload.i686-1.1.2.raw \
-m 512
```

or dump the image on a test hard disk and select it as boot device in the BIOS:

```
cd /tmp/myoem-result
dd if=suse-11.0-oem-preload.i686-1.1.2.raw \
   of=/dev/<device> bs=32k
```

Please note if you test an oem image the virtual disk geometry of the image is the same as the disk geometry inside the host system. According to this the oem boot workflow will skip the re-partitioning which is performed if there would be a real disk

12.3 Flavours

An interesting part of an oem image is that it can be turned into an installation image too. This means it is possible to create an installation CD / DVD or USB stick which deploysthe oem based image onto the selected storage device. The installation process is a simply dd of the image onto the selected device so don't expect any user interaction or GUI here to pop up. KIWI supports two types of installation media:

- <type ... format="iso">...</type>
 Creates a .iso file which can be burned in CD or DVD. This represents an installation CD
- <type ... format="usb">...</type>
 Creates a .raw.install file which can be dumped (dd) on a USB stick. This represents an installation Stick

12.3.1 Influencing the oem partitioning

By default the oemboot process will create/modify a swap, /home and / partition. It is possible to influence the behavior by the following oem-* elements which

can be optionally specified within the **preferences** section of your system image XML description. KIWI uses this to create the file /**config.oempartition** as part of the automatically created oemboot boot image. The format of the file is a simple key=value format and created by the KIWIConfig.sh function named baseSetupO-EMPartition. Following oem-* elements can be specified:

• <oem-reboot>true | false</oem-reboot>

This allows to reboot the oem system after initial deployment. This value is represented by the variable OEM REBOOT in config.oempartition

• <oem-swapsize>number in MB</oem-swapsize>

Set the size of the swap partition. This value is represented by variable OEM_SWAPSIZE in config.oempartition

<oem-systemsize>number in MB</oem-systemsize>

Set the size of the / partition. This value is represented by the variable OEM SYSTEMSIZE in config.oempartition

<oem-home>true|false</oem-home>

Specify if a home partition should be create. This value is represented by the variable OEM WITHOUTHOME in config.oempartition.

<oem-swap>true|false</oem-swap>

Specify if a spaw partition should be create. This value is represented by the variable OEM WITHOUTSWAP in config.oempartition.

<oem-boot-title>text</oem-boot-title>

By default the string **OEM** will be appended to the boot manager menu when KIWI creates the grub configuration during first deployment. The oem-boot-title value allows to set a custom name which is used instead of OEM. This value is represented by the variable OEM_BOOT_TITLE in config.oempartition.

<oem-recovery>true|false</oem-recovery>

If this element is set to true KIWI will create a recovery archive from the prepared root tree. The archive will appear as /recovery.tar.bz2 within the initial image file. During first boot of the image a single recovery partition will be created and the recovery archive will be moved into that partition. An additional boot menu entry will be created which allows to restore the original root tree information. The user information on the /home partition or in the /home directory are not affected by that recovery process

<oem-kiwi-initrd>true|false</oem-kiwi-initrd>

If this element is set to true the initial oemboot boot image (initrd) will **not** be replaced by the system (mkinitrd) created initrd. This option makes sense if the target storage device for the image is not a fixed disk but for example an USB stick. In that case it might be required to re-detect the storage location on first boot which is done as part of the oemboot boot image

12.3.2 LVM support

kiwi also provides support for LVM (Logical Volume Management). In this mode the disk partition table will include one lvm partition and one standard ext2 boot partition. kiwi creates the kiwiVG volume group and adds logical volumes as they are needed and configured according to the image type and filesystem. After boot of the system the user has full control over the volume group and is free to change/resize/increas the group and the volumes inside. Support for LVM has been added for all image types which are disk based. This includes vmx,oem and usb. In order to use LVM for the oem type just add the --lvm option as part of the kiwi create step or add the attribute lvm="true" as part of the type section in your config.xml file.

```
kiwi --create /tmp/myoem --type oem \
-d /tmp/myoem-result --lvm
```

With the optional **lvmvolumes** section you can set one or more top level directories into a separate volume. For example you want to put /usr and /var into different volumes add the following lvmvolumes section:

The optional freespace attribute let you add additional free space for that volume. If you don't set any freespace the volume will be about 80% to 90% full.

13 XEN image - Paravirtual Systems

Contents

13.1 Building the suse-xen-guest example	75
13.2 Using the image	76
13.3 Flavours	76

Xen is a free software virtual machine monitor. It allows several guest operating systems to be executed on the same computer hardware at the same time.

A Xen system is structured with the Xen hypervisor as the lowest and most privileged layer.[1] Above this layer are one or more guest operating systems, which the hypervisor schedules across the physical CPUs. The first guest operating system, called in Xen terminology "domain 0" (dom0), is booted automatically when the hypervisor boots and given special management privileges and direct access to the physical hardware. The system administrator logs into dom0 in order to start any further guest operating systems, called "domain U" (domU) in Xen terminology.

A xen image is a filesystem based image file which requires the Xen dom0 running or the project called Xenner which emulates the capabilities of the domain 0. The image created with kiwi can only be used together with the xen tools.

13.1 Building the suse-xen-guest example

The latest example provided with kiwi is based on openSUSE 11.0 and includes the base pattern.

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.0
kiwi --prepare ./suse-xen-guest \
    --root /tmp/myxen
```

```
kiwi --create /tmp/myxen \
--type xen -d /tmp/myxen-result
```

13.2 Using the image

In order to run a domain U the Xen tool **xm** needs to be called in conjunction with the KIWI genereated domain U configuration file

```
xm create -c \
   /tmp/myxen-result/\
   suse-11.0-xen-guest.i686-1.1.2.xenconfig
```

13.3 Flavours

With KIWI you can provide the information required to create a guest configuration as part of the config.xml file. Additionally you can group special packages which you may only need in this para virtual environment.

If this information is present KIWI will create a Xen domain U (or domain 0) configuration with 512 MB of RAM and expects the disk at /dev/sda. Additional information to setup the Xen guest machine properties are explained in the **xenconfig** section. The KIWI Xen domain U configuration is stored in the file:

```
/tmp/myxen-result/\
suse-11.0-xen-guest.i686-1.1.2.xenconfig
```

14 EC2 image - Amazon Elastic Compute Cloud

Contents

14.1 Building the suse-ec2-guest example	77
14.2 Using the image	78

The Amazon Elastic Compute Cloud (Amazon EC2) web service provides you with the ability to execute arbitrary applications in our computing environment. To use Amazon EC2 you simply:

- 1. Create an Amazon Machine Image (AMI) containing all your software, including your operating system and associated configuration settings, applications, libraries, etc. Such an AMI can be created by the kiwi ec2 image type. In order to do that kiwi makes use of the tools provided by Amazon. Your build system should have these tools installed. Due to license issues we are not allowed to distribute the tools which means you need to download, install and setup them from here:
 - http://docs.amazonwebservices.com/AmazonEC2/gsg/2006-06-26
- 2. Upload this AMI to the Amazon S3 (Amazon Simple Storage Service) service. This gives us reliable, secure access to your AMI.
- 3. Register your AMI with Amazon EC2. This allows us to verify that your AMI has been uploaded correctly and to allocate a unique identifier for it.
- 4. Use this AMI ID and the Amazon EC2 web service APIs to run, monitor, and terminate as many instances of this AMI as required. Currently, Amazon provides command line tools and Java libraries but you may also directly access the SOAP-based API.

Please note while instances are running, you are billed for the computing and network resources that they consume. You should start creating an ec2 with kiwi after you can make sure your system is prepared for ec2 which means if you call the command ec2-describe-images -a you will get a valid output.

14.1 Building the suse-ec2-guest example

One example provided with kiwi is based on openSUSE 11.0 and includes the base pattern plus the vim editor.

Before you run kiwi you need to include some of your ec2 account information into the image description config.xml file. The box below shows the values you need to adapt:

```
<type primary="true"
  ec2accountnr="12345678911"
  ec2privatekeyfile="Path to EC2 private key file"
  ec2certfile="Path to EC2 public certificate file"
>ec2</type>
```

After that call kiwi as follows:

```
cd /usr/share/doc/packages/kiwi/examples
cd suse-11.1
kiwi --prepare ./suse-ec2-guest \
    --root /tmp/myec2
```

```
kiwi --create /tmp/myec2 \
--type ec2 -d /tmp/myec2-result
```

14.2 Using the image

The generated image needs to be transferred over to Amazon which is done by the ec2-upload-bundle tool. You can do this by calling:

```
ec2-upload-bundle -b myImages \
-a <AWS Key ID> -s <AWS secret Key ID> \
-m /tmp/myec2/\
suse-11.1-ec2-guest.i686-1.1.2.ami.manifest.xml
```

After this is done the image needs to be registered in order to receive a so called AMI id which starts with **ami-** followed by a random key sequence. To register call:

```
ec2-register myImages/\
suse-11.1-ec2-guest.i686-1.1.2.ami.manifest.xml
```

The result is the AMI id which you need to run an instance from your image. The command ec2-describe-images allows you to review your registered images. Since you will be running an instance of a public AMI, you will need to use a public/private keypair to ensure that only you will have access. One half of this keypair will be embedded into your instance, allowing you to login securely without a password using the other half of the keypair. Every keypair you generate requires a name. Be sure to choose a name that is easy to remember, perhaps one that describes the image's content. For our example we'll use the name gsg-keypair.

```
ec2-add-keypair gsg-keypair
```

The private key returned needs to be saved in a local file so that you can use it later. Using your favorite text editor, create a file named **id_rsa-gsg-keypair** and paste everything between (and including) the ——*BEGIN RSA PRIVATE KEY*—— and ——*END RSA PRIVATE KEY*—— lines into it. To review your keypairs call:

```
ec2-describe-keypairs
```

We are almost done now but to be able to run an instances you also need to specify which kernel and boot image (initrd) should be used to run the instance. Kernels are registered as aki.... images and initrd's are registered as ari.... images at Amazon. You will need to select a aki/ari image that matches your ami. The following table shows which Distributions are supported at the moment:

Distro	ARI id	AKI id	Arch
SLES11	ari-c31effaa	aki-c11effa8	ix86
SLES11	ari-cd1effa4	aki-cb1effa2	x86_64
openSUSE 11.1	n/a	n/a	ix86
openSUSE 11.1	n/a	n/a	x86_64

For this example we need the id's provided for openSUSE 11.1. Unfortunately there are no public ID's available at the moment. As soon as they are the following command are required to fire up your new ec2 instance:

```
ec2-run-instances ami-... \
--kernel aki-... --ramdisk ari-... \
-k gsg-keypair
```

To check the state of your instance(s) call the following command:

If you see your instance at the status: **running** you can login into it. If you can't make sure you have allowed port 22 to be available

Congratulations! You made it and can now use Amazons storage and computing power.

15 KIWI testsuite

Contents

```
      15.1 testsuite packages
      81

      15.2 Creating a test
      81
```

The KIWI test suite is useful to perform basic quality checks on the image root directory. The test cases are stored in subdirectories below /usr/share/kiwi/tests. To run the testsuite call kiwi as follows:

```
kiwi — testsuite < image-root > \
[ — test name — test name ... ]
```

If not test names are set the default tests rpm and ldd run. The name of a test corresponds with the name of the directory the test is implemented in.

15.1 testsuite packages

If a test requires special software to be installed but this software is not an essential part of the image itself it can be specified as testsuite packages in the system image config.xml as follows:

The testsuite packages are installed when calling kiwi with the testsuite option and are removed after the tests has finished.

15.2 Creating a test

The test itself is defined by a xml description "test-case.xml" and its template definition file /usr/share/kiwi/modules/KIWISchemaTest.rnc The following example shows the basic structure of the rpm test:

There are basically two sections called "equirements" and "test". In requirements you define what files/directories or packages has to be present in your image to run the test. For example if you need to check the rpm database, the database has to be present within the image. All requirements are checked, and if any of them fail the test won't be executed and an error message is printed. There are three types of requirements:

- file Existence of a file
- **directory**Existence of a directory
- rpm-package
 Existence of a package

The test section defines the test script. It could be a binary, shell script or any other kind of executable. Scripts are expected to be in the same directory as where the xml definition for the test resides. There are two types of scripts, extern and intern.

- external scripts are executed outside of the image and are preferred. Their first parameter should be CHROOT. This parameter is changed to the real path of the image chroot directory.
- internal scripts are executed inside image using the "chroot" command. Files are copied into the image and deleted after execution.

A test script always has to return 0 in case of a test to pass, or 1 if any error occur. All messages printed to standard and error output are stored and printed out of the test has failed.

Index

```
Appendix, 82
configuration files
   config.<MAC Address>, 62
   hwtype.<MAC Address>, 62
KIWI images
   appliance, 32
   description, 12
   ec2, 76
   iso, 44
   maintenance, 36
   migration, 38
   oem, 70
   pxe, 58
   testing, 80
   usb, 47
   vmx, 53
   workflow, 7
   xen, 74
KIWI Setup of installation sources
   instsourcesetup, 41
```

16 Appendix - Kiwi man pages

The following pages will show you the man page of kiwi and the functions which can be used within config.sh and index.sh

- man kiwi
- man kiwi::config.sh
- man kiwi::index.sh

Name

kiwi — Creating Operating System Images

Synopsis

```
kiwi { -l | --list }
kiwi { -o | --clone } image-path { -d } destination
kiwi { -b | --build } image-path { -d } destination
```

Basics

KIWI is a complete imaging solution that is based on an image description. Such a description is represented by a directory which includes at least one config.xml file and may as well include other files like scripts or configuration data. The kiwi-templates package provides example descriptions based on a JeOS system. JeOS means Just enough Operating System. KIWI provides image templates based on that axiom which means a JeOS is a small, text only based image including a predefined remote source setup to allow installation of missing software components at a later point in time.

Detailed description of the kiwi image system exists in the system design document in file:///usr/share/doc/packages/kiwi/kiwi.pdf. KIWI always operates in two steps. The kiwi --build option just combines both steps into one to make it easier to start with kiwi. The first step is the preparation step and if that step was successful, a creation step follows which is able to create different image output types. If you have started with an example and want to add you own changes it might be a good idea to clone of from this example. This can be done by simply copying the entire image description or you can let kiwi do that for you by using the kiwi --clone command.

In the preparation step, you prepare a directory including the contents of your new filesystem based on one or more software package source(s) The creation step is based on the result of the preparation step and uses the contents of the new image root tree to create the output image. If the image type ISO was requested, the output image would be a file with the suffix .iso representing a live system on CD or DVD. Other than that kiwi is able to create images for virtual and para-virtual (Xen) environments as well as for USB stick, PXE network clients and OEM customized Linux systems.

Image Preparation and Creation

```
kiwi { -p | --prepare } image-path
[-r | --root image-root]
kiwi { -c | --create } image-root
{ -d | --destdir destination} [--type image-type]
```

Image Upgrade

If the image root tree is stored and not removed, it can be used for upgrading the image according to the changes made in the repositories used for this image. If a distributor provides an update channel for package updates and an image config.xml includes this update channel as repository, it is useful to store the image root tree and upgrade the tree according to changes on the update channel. Given that the root tree exists it's also possible to add or remove software and recreate the image of the desired type

```
kiwi { -u | --upgrade } image-root [--add-packagename]
```

System to Image Migration

The migration module allows you to migrate your currently running system into an image description. The module will check for files not managed by a package manager and it will suggest a repository from which this operating system could be rebuild. The result is quite useful but in most cases a manual fine tuning is required. This includes the repository selection and the unmanaged files along with the configuration details of your currently running operating system.

```
kiwi { -m | --migrate } name --destdir destination-path [--exclude directory...] [--report]
```

Image Postprocessing Modes

The KIWI post-processing modes are used for special image deployment tasks, like installing the image on a USB stick. So to say they are the third step after preparation and creation. kiwi calls the postprocessing modules automatically according to the specified output image type and attributes but it's also possible to call them manually.

```
kiwi --bootstick initrd[--bootstick-system systemImage][--bootstick-device device]
```

kiwi --bootvm initrd --bootvm-system systemImage [--bootvm-disksize size] [--bootvm-format format]

```
kiwi --booted initrd
```

kiwi --installcd initrd --installcd-system vmx-system-image

kiwi --installstick initrd --installstick-system vmx-system-image

Testsuite

The KIWI test suite is useful to perform basic quality checks on the image root directory. The test cases are stored in subdirectories below /usr/share/kiwi/tests.

```
kiwi --testsuite image-root [--test name...]
```

Helper Tools

The helper tools provide optional functions like creating a crypted password string for the users section of the config.xml file or signing the image description with an md5sum hash as well as adding splash data to the boot image used by the bootloader and the testsuite mode which allows testing the integrity of the new root tree.

```
kiwi --createpassword
kiwi --createhash image-path
kiwi {-i|--info } ImagePath {--select
  repo-patterns/patterns/types/sources/size/profiles/packages }
kiwi --setup-splash initrd
```

The following list describes the helper tools more detailed

```
[--createpassword]
```

Create a crypted password hash and prints it on the console. The user can use the string as value for the pwd attribute in the XML users section

```
[--createhash image-path]
```

Sign your image description with a md5sum. The result is written to a file named .checksum.md and is checked if kiwi creates an image from this description

```
[-i|--info image-path--select selection]
```

List general information about the image description. So far you can get information about the available patterns in the configured repositories with repo-patterns, a list of used patterns for this image with patterns, a list of supported image types with types, a list of source URL's with sources, an estimation about the install size and the size of the packages marked as to be deleted with size, a list of profiles with profiles, and a list of solved packages to become installed with packages.

```
[--setup-splash initrd]
```

Create splash screen from the data inside the initrd and re-create the initrd with the splash screen attached to the initrd cpio archive. This enables the kernel to load the splash screen at boot time. If splashy is used only a link to the original initrd will be created

Global Options

```
[--base-root base-path]
```

Refers to an already prepared root tree. Kiwi will use this tree to skip the first stage of the prepare step and run the second stage directly.

```
[--base-root-mode copy/union/recycle]
```

Specifies the overlay mode for the base root tree. This can be either a copy of the tree, a union mount or the tree itself. The last mode (recycle) will modify the base root tree which might make it obsolete as base root for other kiwi calls

```
[--add-profile profile-name]
```

Use the specified profile. A profile is a part of the XML image description and therefore can enhance each section with additional information. For example adding packages.

```
[--set-repo URL]
```

Set/Overwrite repo URL for the first listed repo. The change is temporary and will not be written to the XML file.

```
[--set-repotype type]
```

Set/Overwrite repo type for the first listed repo. The supported repo types depends on the packagemanager. Commonly supported are rpm-md, rpm-dir and yast2. The change is temporary and will not be written to the XML file.

```
[--set-repoalias name]
```

Set/Overwrite alias name for the first listed repo. Alias names are optional free form text. If not set the source attribute value is used and builds the alias name by replacing each '/' with a '_'. An alias name should be set if the source argument doesn't really explain what this repository contains. The change is temporary and will not be written to the XML file.

```
[--set-repoprio number]
```

Set/Overwrite priority for the first listed repo. Works with the smart packagemanager only. The Channel priority assigned to all packages available in this channel (0 if not set). If the exact same package is available in more than one channel, the highest priority is used.

```
[--add-repo URL, --add-repotype type--add-repoalias name--add-repoprio number]
```

Add the given repository and type for this run of an image prepare or upgrade process. Multiple --add-repo/--add-repotype options are possible. The change will not be written to the config.xml file

```
[--ignore-repos]
```

Ignore all repositories specified so far, in XML or elsewhere. This option should be used in conjunction with subsequent calls to --add-repo to specify repositories at the commandline that override previous specifications.

```
[--logfile Filename|terminal]
```

Write to the log file Filename instead of the terminal.

```
[--gzip-cmd cmd]
```

Specify an alternate command to run when compressing boot and system images. Command must accept **gzip** options.

```
[--log-port PortNumber]
```

Set the log server port. By default port 9000 is used. If multiple KIWI processes runs on one system it's recommended to set the logging port per process.

```
[--package-manager smart/zypper]
```

Set the package manager to use for this image. If set it will temporarly overwrite the value set in the xml description.

```
[-A|--target-arch i586|x86_64|armv5tel|ppc]
```

Set a special target-architecture. This overrides the used architecture for the image-packages in zypp.conf. When used with smart this option doesn't have any effect.

```
[--debug]
```

Prints a stack trace in case of internal errors

```
[--verbose 1/2/3]
```

Controls the verbosity level for the instsource module

Image Preparation Options

```
[-rl--root RootPath]
```

Set up the physical extend, chroot system below the given root-path path. If no --root option is given, KIWI will search for the attribute defaultroot in config.xml. If no root directory is known, a **mktmp** directory will be created and used as root directory.

```
[--force-new-root]
```

Force creation of new root directory. If the directory already exists, it is deleted.

Image Upgrade/Preparation Options

[--add-package package]

Add the given package name to the list of image packages multiple --add-package options are possible. The change will not be written to the xml description.

[--del-package package]

Removes the given package by adding it the list of packages to become removed. The change will not be written to the xml description.

Image Creation Options

[-d|--destdir DestinationPath]

Specify destination directory to store the image file(s) If not specified, KIWI will try to find the attribute <code>defaultdestination</code> which can be specified in the <code>preferences</code> section of the <code>config.xml</code> file. If it exists its value is used as destination directory. If no destination information can be found, an error occurs.

[-t|--type Imagetype]

Specify the output image type to use for this image. Each type is described in a type section of the preferences section. At least one type has to be specified in the config.xml description. By default, the types specifying the *primary* attribute will be used. If there is no primary attribute set, the first type section of the preferences section is the primary type. The types are only evaluated when kiwi runs the --create step. With the option --type one can distinguish between the types stored in config.xml

[-sl--strip]

Strip shared objects and executables only make sense in combination with --create

[--prebuiltbootimage Directory]

Search in *Directory* for pre-built boot images.

[--isocheck]

in case of an iso image the checkmedia program generates a md5sum into the iso header. If the --isocheck option is specified a new boot menu entry will be generated which allows to check this media

[--lvm]

Use the logical volume manager to control the disk. The partition table will include one lvm partition and one standard ext2 boot partition. Use of this option makes sense for the create step only and also only for the image types: vmx, oem and usb

[--fs-blocksize number]

When calling kiwi in creation mode this option will set the block size in bytes. For ISO images with the old style ramdisk setup a blocksize of 4096 bytes is required

[--fs-journalsize number]

When calling kiwi in creation mode this option will set the journal size in mega bytes for ext[23] based filesystems and in blocks if the reiser filesystem is used

[--fs-inodesize number]

When calling kiwi in creation mode this option will set the inode size in bytes. This option has no effect if the reiser filesystem is used

[--fs-inoderatio number]

Set the bytes/inode ratio. This option has no effect if the reiser filesystem is used

[--partitioner fdisk/parted]

Select the tool to create partition tables. Supported are fdisk (sfdisk) and parted. By default fdisk is used

[--check-kernel]

Activates check for matching kernels between boot and system image. The kernel check also tries to fix the boot image if no matching kernel was found.

For More Information

More information about KIWI, its files can be found at:

http://en.opensuse.org/Build_Service/KIWI/Cookbook

KIWI wiki

config.xml

The configuration XML file that contains every aspect for the image creation.

file:///usr/share/doc/packages/kiwi/kiwi.pdf

The system design document which describes some details about the building process.

file:///usr/share/doc/packages/kiwi/schema/kiwi.xsd.html

The KIWI RelaxNG XML Schema documentation.

file:///usr/share/doc/packages/kiwi/schema/test.xsd.html

The KIWI RelaxNG XML Schema documentation.

kiwi::config.sh

Name

KIWI::config.sh — Configuration File for KIWI image description

Description

The kiwi image description allows to have an optional config.sh script in place. This script should be designed to take over control of adding the image operating system configuration. Configuration in that sense means stuff like activating services, creating configuration files, prepare an environment for a firstboot workflow, etc. What you shouldn't do in config.sh is breaking your systems integrity by for example removing packages or pieces of software. Something like that can be done in images.sh. config.sh is called *after* the user and groups have been set up. If there are SUSE Linux related YaST xml information these are validated before config.sh is called too. If you exit config.sh with an exit code != 0 kiwi will exit with an error too.

Example 1. Template

Common functions

The .kconfig file allows to make use of a common set of functions. Those which are SUSE Linux specific starts with the name *suse*. Those which are common to all linux systems starts with the name *base*. The following list describes which functions are available for config.sh

```
[baseCleanMount]
```

Umount the system filesystems /proc /dev/pts /sys

[baseSetupUserPermissions]

Search all home directories of all users listed in /etc/passwd and change the ownership of all files to belong to the correct user and group

[baseSetupBoot]

kiwi::config.sh

Set up the linuxrc as init

[baseSetupBusyBox {-f}]

activates busybox if installed for all links from the busybox/busybox.links file - you can choose custom apps to be forced into busybox with the "-f" option as first parameter example: baseSetupBusyBox -f /bin/zcat /bin/vi

[baseStripRPM]

remove rpms defined in config.xml under image=delete section

[baseStripUnusedLibs]

remove libraries which are not directly linked against applications in the bin directories

[baseUpdateSysConfig {filename} {variable} {value}]

update sysconfig variable contents

[baseGetPackagesForDeletion]

Return the name(s) of packages which will be deleted

[baseGetProfilesUsed]

Return the name(s) of profiles used to build this image

[baseSetupInPlaceSVNRepository {path_list}]

Create an in place subversion repository for the specified directories. A standard call could look like this baseSetupInPlaceSVNRepository /etc /srv /var/log

[baseSetupPlainTextGITRepository]

Create an in place git repository of the root directory containing all plain/text files.

[baseSetupInPlaceGITRepository]

Create an in place git repository of the root directory. This process may take some time and you may expect problems with binary data handling

[baseStripMans {list of manpages to keep}]

remove all manual pages, except one given as parameter example: baseStripMans more less

[baseStripDocs {list of docu names to keep}]

remove all documentation, except one given as parameter

[baseStripLocales {list of locales}]

remove all locales, except one given as parameter

[baseStripInfos {list of info-files to keep}]

remove all info files, except one given as parameter

[baseStripAndKeep {list of info-files to keep}]

helper function for strip* functions read stdin lines of files to check for removing params: files which should be keep

[baseStripTools {list of toolpath} {list of tools}]

helper function for suseStripInitrd function params: toolpath, tools

[suseInsertService {servicename}]

Recursively insert a service. If there is a service required for this service it will be inserted first. The suse insserv program is used here

[suseRemoveService {servicename}]

Remove a service and its dependant services using the suse insserv program

[suseStripPackager {-a}]

Remove smart o zypper packages and db files Also remove rpm package and db if "-a" given [suseActivateServices]

Check all services in /etc/init.d/ and activate them by calling suseInsertService

[suseActivateDefaultServices]

Call all postin scriptlets which among other things activates all required default services using suseInsertService

[suseService {servicename} {onloff}]

Activate/Deactivate a service by using the chkconfig program The function requires the service name and the value on or off as parameters

[suseServiceDefaultOn]

kiwi::config.sh

Activates the following services to be on by default using the chkconfig program: boot.rootfsck boot.cleanup boot.localfs boot.localnet boot.clock policykitd dbus consolekt haldaemon network atd syslog cron kbd

[suseConfig]

Setup keytable language and timezone if specified in config.xml and call SuSEconfig afterwards [suseCloneRunlevel {runlevel}]

Clone the given runlevel to work in the same way as the default runlevel 3.

[suseSetupProductInformation]

This function will use zypper to search for the installed product and install all product specific packages. This function only makes sense if zypper is used as packagemanager

[Rm {list of files}]

Helper function to delete files and anounce it to log

[Rpm {rpm commandline}]

Helper function to the rpm function and anounce it to log

[Echo {echo commandline}]

Helper function to print a message to the controling terminal

[Debug {message}]

Helper function to print a message if the variable DEBUG is set to 1

Profile environment variables

The .profile environment file contains a specific set of variables which are listed below. Some of the functions above makes use of the variables.

[\$kiwi_iname]

The name of the image as listed in config.xml

[\$kiwi_iversion]

The image version string major.minor.release

[\$kiwi_keytable]

The contents of the keytable setup as done in config.xml

[\$kiwi_language]

The contents of the locale setup as done in config.xml

[\$kiwi timezone]

The contents of the timezone setup as done in config.xml

[\$kiwi_delete]

A list of all packages which are part of the packages section with type='delete' in config.xml [\$kiwi_profiles]

A list of profiles used to build this image

[\$kiwi_drivers]

A comma seperated list of the driver entries as listed in the drivers section of the config.xml. Similar variables exists for the usbdrivers and scsidrivers sections

[\$kiwi_size]

The predefined size value for this image. This is not the computed size but only the optional size value of the preferences section in config.xml

[\$kiwi_compressed]

The value of the compressed attribute set in the type element in config.xml

[\$kiwi_type]

The basic image type. Can be a simply filesystem image type of ext2 ext3 reiserfs squashfs cpio or one of the following complex image types: iso split usb vmx oem xen pxe

kiwi::images.sh

Name

KIWI::images.sh — Configuration File for KIWI image description

Description

The kiwi image description allows to have an optional images.sh script in place. This script is called at the beginning of the kiwi create step. It is allowed to remove software there to shrink down the size of the image. Most often images.sh is used for boot images because they needs to be small. As images.sh is called in the create step you should be aware to design the script in a way that it can be called multiple times without shooting itself into its knee. As kiwi allows to create different image types from one previosly prepared tree one needs to take into account that images.sh can be called more than one time. If you exit images.sh with an exit code != 0 kiwi will exit with an error too.

Example 1. Template

Common functions

The .kconfig file allows to make use of a common set of functions. Those which are SUSE Linux specific starts with the name *suse*. Those which are common to all linux systems starts with the name *base*. The following list describes which functions are available for images.sh

kiwi::images.sh

Return the list of packages setup in the packages type='delete' section of the config.xml used to build this image

[baseSetupOEMPartition]

Writes the file /config.oempartition depending on the following config.xml parameters: oem-reboot, oem-swapsize, oem-systemsize, oem-home,oem-swap,oem-boot-title,oem-recovery, oem-kiwi-initrd. kiwi takes the information from config.xml and creates the config.oempartition file as part of the automatically created boot image (initrd). The information must be available as part of the boot image because it controls the OEM repartition workflow on first boot of an OEM image. Detailed information about the meaning of each option can be found in the OEM chapter in the kiwi cookbook

[suseGFXBoot {theme} {loadertyp}]

This function requires the gfxboot and at least one bootsplash-theme-* package to be installed in order to work correctly. The function creates from this package data a graphics boot screen for the isolinux and grub boot loaders. Additionally it creates the bootsplash files for the resolutions 800x600 1024x768 and 1280x1024

[suseStripKernel]

This function removes all kernel drivers which are not listed in the *drivers sections of the config.xml file

[suseStripInitrd]

This function removes a whole bunch of tools binaries and libraries which are not required in order to boot a suse system with kiwi.

[Rm {list of files}]

Helper function to delete files and anounce it to log

[Rpm {rpm commandline}]

Helper function to the rpm function and anounce it to log

[Echo {echo commandline}]

Helper function to print a message to the controling terminal

[Debug {message}]

Helper function to print a message if the variable DEBUG is set to 1

Profile environment variables

The .profile environment file contains a specific set of variables which are listed below. Some of the functions above makes use of the variables.

[\$kiwi_iname]

The name of the image as listed in config.xml

[\$kiwi_iversion]

The image version string major.minor.release

[\$kiwi_keytablee]

The contents of the keytable setup as done in config.xml

[\$kiwi_language]

The contents of the locale setup as done in config.xml

[\$kiwi_timezone]

The contents of the timezone setup as done in config.xml

[\$kiwi_delete]

A list of all packages which are part of the packages section with type='delete' in config.xml

[\$kiwi_profiles]

A list of profiles used to build this image

[\$kiwi_drivers]

A comma seperated list of the driver entries as listed in the drivers section of the config.xml. Similar

kiwi::images.sh

variables exists for the usbdrivers and scsidrivers sections

[\$kiwi_size]

The predefined size value for this image. This is not the computed size but only the optional size value of the preferences section in config.xml

[\$kiwi_compressed]

The value of the compressed attribute set in the type element in config.xml [\$kiwi_type]

The basic image type. Can be a simply filesystem image type of ext2 ext3 reiserfs squashfs cpio or one of the following complex image types: iso split usb vmx oem xen pxe