pFUnit

Generated by Doxygen 1.7.6

Fri Dec 27 2013 14:21:46

Contents

1	pFU	nit 2 - Documentation - Version 0.0 (2013-1227-1 MLR)	1				
	1.1	Overview	1				
	1.2	Contents	1				
	1.3	See Also	2				
	1.4	Copyright	2				
2	Obta	ining pFUnit	3				
3	Inst	llation	5				
	3.1	Installing pFUnit	5				
	3.2	Prerequisites	5				
	3.3	Obtaining pFUnit					
	3.4	Manifest - What's in the directory? 6					
	3.5	Configuration					
	3.6	Building pFUnit					
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8				
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8				
		3.6.3 OPENMP	8				
		3.6.4 Cleaning	9				
		3.6.5 Documentation	9				
	3.7	Installation					
		3.7.1 Installation - Serial	9				
		2.7.0 Installation MDI	Λ				

		3.7.3	Installation - OPENMP	10
		3.7.4	Installation - DEFAULT DIRECTORY	10
4	Usag	e		11
	4.1	Usage		11
		4.1.1	Usage - Configuration	11
		4.1.2	Usage - Hello World	11
		4.1.3	Usage - Preprocessor	12
5	Deve	lopmen	t	13
6	Feed	back &	Support	15
	6.1	Feedba	ıck	15
	6.2	Suppor	t	15
7	FAQ	and Tip	s s	17
	7.1	FAQ .		17
		7.1.1	Zero Tests Run	17
		7.1.2	Some Tests Are Not Running	17
	7.2	Tips .		18
		7.2.1	Environment Modules	18
		7.2.2	Compile Time Errors	18
		7.2.3	Intermediate files used by pFUnit	18
8	Platfo	orm Spe	ecific Notes	19
	8.1	Mac OS	SX	19
	8.2	Window	vs/CYGWIN	19
9	Ackn	owledg	ments	21
10	Knov	vn Insta	Illations & Versions	23
11	TOD	0		25
12	The I	Preproc	essor - pFUnitParser	27

CONTENTS iii

	12.1	Using T	The Preprocessor	 27
		12.1.1	Configuration - testSuites.inc	 28
		12.1.2	Invocation	 28
		12.1.3	Preprocessor Input File (.pf)	 28
		12.1.4	Directives	 29
			12.1.4.1 @Test	 29
			12.1.4.2 @MPITest	 29
			12.1.4.3 @Assert	 30
			12.1.4.4 @Parameters	 31
			12.1.4.5 @TestCase	 31
13			eprocessor Directives	33
	13.1		ert Preprocessor Directives	
			@assertEqual	
			@assertTrue	
			@assertFalse	
			@assertLessThan	
		13.1.5	@assertLessThanOrEqual	 34
		13.1.6	@assertGreaterThan	 34
		13.1.7	@assertGreaterThanOrEqual	 34
		13.1.8	@assertIsMemberOf	 34
		13.1.9	@assertContains	 34
		13.1.10	@assertAny	 34
		13.1.11	@assertAll	 34
		13.1.12	2@assertNotAll	 34
		13.1.13	3@assertNone	 34
		13.1.14	4 @assertIsPermutationOf	 34
		13.1.15	@assertExceptionRaised	 34
		13.1.16	6@assertSameShape	 34
		13.1.17	7@assertIsNaN	 34
		13.1.18	3@assertIsFinite	 34

iv CONTENTS

14	Revision Notes	35
15	Data Type Index	37
	15.1 Class Hierarchy	37
16	Data Type Index	41
	16.1 Data Types List	41
17	Data Type Documentation	45
	17.1 pFUnitParser::Action Class Reference	45
	17.2 add_mod Module Reference	46
	17.3 addComplex_mod Module Reference	47
	17.4 CodeUtilities::ArrayDescription Class Reference	47
	17.5 Assert_mod Module Reference	48
	17.5.1 Detailed Description	48
	17.6 AssertBasic_mod Module Reference	48
	17.6.1 Detailed Description	49
	17.7 AssertInteger_mod Module Reference	49
	17.7.1 Detailed Description	50
	17.8 GenerateRealArrayNewSignature::AssertRealArrayArgument Class - Reference	50
	17.9 pFUnitParser::AtAfter Class Reference	51
	17.10pFUnitParser::AtAssert Class Reference	52
	17.11pFUnitParser::AtBefore Class Reference	52
	17.12pFUnitParser::AtBegin Class Reference	53
	17.13pFUnitParser::AtMpiAssert Class Reference	54
	17.14pFUnitParser::AtMpiTest Class Reference	54
	17.15pFUnitParser::AtParameters Class Reference	55
	17.16pFUnitParser::AtSuite Class Reference	56
	17.17pFUnitParser::AtTest Class Reference	56
	17.18pFUnitParser::AtTestCase Class Reference	57
	17.19BaseTestRunner_mod Module Reference	58
	17.19.1 Detailed Description	58

CONTENTS v

17.20BeforeAfter_mod Module Reference	. 59
17.21BrokenSetUpCase_mod Module Reference	. 59
17.22BrokenTestCase_mod Module Reference	. 59
17.23GenerateRealArrayNewSignature::constraintASSERTEQUAL Class Reference	. 60
17.23.1 Constructor & Destructor Documentation	. 60
17.23.1.1init	. 61
17.23.2 Member Data Documentation	. 61
17.23.2.1 name1	. 61
17.23.2.2 tolerance	. 61
17.24mods::pre::pre2::dataString Class Reference	. 61
17.25DebugListener_mod Module Reference	. 62
17.25.1 Detailed Description	. 62
17.26CodeUtilities::declaration Class Reference	. 63
17.27DynamicTestCase_mod Module Reference	. 63
17.27.1 Detailed Description	. 64
17.28Exception_mod Module Reference	. 64
17.29Fixture_mod Module Reference	. 65
17.30 Fixture Test Case_mod Module Reference	. 65
17.31 CodeUtilities::fortranSubroutineSignature Class Reference	. 66
17.32Halo_mod Module Reference	. 66
17.33mods::pre::pre_If::IfDirective Class Reference	. 66
17.34CodeUtilities::implementation Class Reference	. 67
17.35CodeUtilities::interfaceBlock Class Reference	. 67
17.36mods::pre::pre_If::interval Class Reference	. 68
17.37GenerateRealArrayNewSignature::lsWithinTolerance Class Reference	. 68
17.38Test_RestrictSphericalCoordinates_mod::LatLonCase Type Reference	. 69
17.39LinearInterpolator_mod Module Reference	. 69
17.40MakeInfinity_mod Module Reference	. 69
17.40.1 Detailed Description	. 70
17.41 MakeNaN_mod Module Reference	. 70

vi CONTENTS

17.41.1 Detailed Description	70
17.42MockCall_mod Module Reference	71
17.42.1 Detailed Description	71
17.43MockListener_mod Module Reference	72
17.44testParser::MockParser Class Reference	72
17.45MockRepository_mod Module Reference	72
17.45.1 Detailed Description	73
17.46MockSUT_mod Module Reference	73
17.47testParser::MockWriter Class Reference	74
17.48CodeUtilities::module Class Reference	74
17.49MpiContext_mod Module Reference	75
17.49.1 Detailed Description	75
17.50MpiStubs_mod Module Reference	75
17.50.1 Detailed Description	76
17.51MpiTestCase_mod Module Reference	76
17.51.1 Detailed Description	77
17.52MpiTestMethod_mod Module Reference	77
17.52.1 Detailed Description	77
17.53ParallelContext_mod Module Reference	78
17.53.1 Detailed Description	78
17.54ParallelException_mod Module Reference	79
17.54.1 Detailed Description	79
17.55ParameterizedTestCase_mod Module Reference	80
17.55.1 Detailed Description	80
17.56Params_mod Module Reference	80
17.56.1 Detailed Description	81
17.57pFUnitParser::Parser Class Reference	81
17.58Test_Parameters_mod::peCase Type Reference	82
17.59pFUnit Module Reference	82
17.59.1 Detailed Description	83
17.60pFUnit mod Module Reference	83

CONTENTS vii

17.60.1 Detailed Description
17.61PrivateException_mod Module Reference
17.61.1 Detailed Description
17.62mods::pre::pre2::procDirective Class Reference
17.62.1 Member Function/Subroutine Documentation
17.62.1.1 addTokenRE
17.63RemoteProxyTestCase_mod Module Reference
17.63.1 Detailed Description
17.64mods::pre::pre_Repeat::RepeatDirective Class Reference
17.65ResultPrinter_mod Module Reference
17.65.1 Detailed Description
17.66RobustRunner_mod Module Reference
17.66.1 Detailed Description
17.67robustTestSuite_mod Module Reference
17.68CodeUtilities::routineUnit Class Reference
17.69SerialContext_mod Module Reference
17.69.1 Detailed Description
17.70SimpleTestCase_mod Module Reference
17.71SourceLocation_mod Module Reference
17.71.1 Detailed Description
17.72SphericalCoordinates_mod Module Reference
17.73TestListener_mod::startTest Interface Reference
17.74StringConversionUtilities_mod Module Reference
17.74.1 Detailed Description
17.75SubsetRunner_mod Module Reference
17.75.1 Detailed Description
17.76SurrogateTestCase_mod Module Reference
17.76.1 Detailed Description
17.77SUT_mod Module Reference
17.78Test_Assert_mod Module Reference
17.79Test_AssertBasic_mod Module Reference

viii CONTENTS

17.80Test_AssertComplex_mod Module Reference
17.81Test_AssertInteger_mod Module Reference
17.82Test_AssertReal_mod Module Reference
17.83Test_BasicOpenMP_mod Module Reference
17.84Test_Exception_mod Module Reference
17.85Test_FixtureTestCase_mod Module Reference
17.86Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 99
17.87Test_LinearInterpolator_mod Module Reference
17.88Test_MockCall_mod Module Reference
17.89Test_MockRepository_mod Module Reference
17.90Test_mod Module Reference
17.90.1 Detailed Description
17.91Test_MpiContext_mod Module Reference
17.92Test_MpiException_mod Module Reference
17.93Test_MpiTestCase_mod Module Reference
17.94Test_Parameters_mod::Test_Parameters Interface Reference 103
17.95Test_Parameters_mod Module Reference
17.96Test_RestrictSphericalCoordinates_mod::Test_RestrictSpherical- Coordinates Interface Reference
17.97Test_RestrictSphericalCoordinates_mod Module Reference 105
17.98Test_RobustRunner_mod Module Reference
17.99Test_SimpleTestCase_mod Module Reference
17.10 T est_StringConversionUtilities_mod Module Reference
17.10 Test_TestMethod_mod Module Reference
17.10 Z est_TestResult_mod Module Reference
17.103est_TestSuite_mod Module Reference
17.104est_UnixProcess_mod Module Reference
17.105estCase_mod Module Reference
17.105. Detailed Description
17.10 6 estFailure_mod Module Reference
17.106. Detailed Description

CONTENTS ix

17.10 mods::pre::pre_lf::TestlfDirective Class Reference
17.108nods::pre::interleavedp::TestInterleaved Class Reference 109
17.10 9 estListener_mod Module Reference
17.109. Detailed Description
17.11 © estMethod_mod Module Reference
17.110. Detailed Description
17.11 mods::pre::parseArgs::TestParseArgs Class Reference
17.112estParser::TestParseLine Class Reference
17.112. Member Function/Subroutine Documentation
17.112.1.1testAtMpiTest
17.112.1.2iestAtTest
17.112.1.3testMatchAtAfter
17.112.1.4testMatchAtAssertEqual
17.112.1.5testMatchAtAssertOther
17.112.1.&estMatchAtBefore
17.112.1.7testMatchAtMpiAssert
17.112.1.&estMatchAtSuite
17.112.1.9testMatchAtTestCase
17.118hods::pre::pre_Repeat::TestRepeatDirective Class Reference
17.114estResult_mod Module Reference
17.114. Detailed Description
17.115 estRunner_mod Module Reference
17.115. Detailed Description
17.11 6 estSuite_mod Module Reference
17.116. Detailed Description
17.117 hrowFundamentalTypes_mod Module Reference
17.117. Detailed Description
17.118 Inix Pipe Interfaces _mod Module Reference
17.118. Detailed Description
17.119JnixProcess_mod Module Reference
17.119. Detailed Description

x CONTENTS

17.12 Generate Real Array New Signature:: VECTOR_NORM Class Reference . 119

Generated on Fri Dec 27 2013 14:21:13 for pFUnit by Doxygen

pFUnit 2 - Documentation - Version 0.0 (2013-1227-1 MLR)

Quick link to the code!

1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

1.2 Contents

- Installation
 - Obtaining pFUnit
- Usage

- Development
- Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

1.4 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

Installation

3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- · Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
 - Building pFUnit for testing serial codes (Non-MPI)
 - Building pFUnit for testing parallel codes (MPI)
 - OPENMP
 - Cleaning
 - Documentation
- Installation

3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.1., IBM's XLF)
- The Message Passing Interface (MPI)
- · GNU Make
- Python

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

3.5 Configuration 7

GNUmakefile - The top level makefile for building and installing pFUnit.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

\$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen

3.6 Building pFUnit

8 Installation

3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

3.6.3 OPENMP

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

3.7 Installation 9

```
$make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src_clean' to remove intermediate products in subdirectories.

3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following.

```
$ make documentation
```

Or to make a reference manual.

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

3.7 Installation

3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

10 Installation

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildlt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ pushd Examples
$ ./buildIt
```

3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

To test, set PFUNIT and go into Examples/MPI Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo/Semi-Automatic
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

Usage

- Usage Configuration
- Usage Hello World
- Usage Preprocessor

4.1 Usage

4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/Semi--Automatic/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
subroutine testHelloWorld()
```

12 Usage

```
use pfunit_mod
implicit none
@assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

4.1.3 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

Development

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

14 Development

Feedback & Support

- Feedback
- Support

6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

FAQ and Tips

- FAQ
 - Zero Tests Run
 - Some Tests Are Not Running
- Tips
 - Environment Modules
 - Compile Time Errors
 - Intermediate files used by pFUnit

7.1 FAQ

7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD_TEST_SUITE (the_suite_to_add), one to a line.
- There is no <code>-DUSE_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

18 FAQ and Tips

Solutions:

 There is no -DUSE_MPI passed to the compiler during the build. Please add as in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

7.2 Tips

7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

Platform Specific Notes

8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

Acknowledgments

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

Known Installations & Versions

TBD

TODO

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

26 TODO

The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
 - Configuration testSuites.inc
 - Invocation
 - Preprocessor Input File (.pf)
 - Directives
 - * @Test
 - * @MPITest
 - * @Assert (or Preprocessor Directives)
 - * @Parameters
 - * @TestCase

12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's semi-automatic/tests subdirectory.

12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' semi-automatic/tests subdirectories in the Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
 - @Assert

12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive. For example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

12.1.4.2 @MPITest

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI_Halo:

```
@mpiTest( npes=[1,2,3])
subroutine testHaloInterior(this)
    use Halo_mod
    use pfunit_mod
    implicit none
    class (MpiTestMethod) :: this

    integer, parameter :: N = 2
    real :: a(N,0:N+1)
    integer :: p

    p = this%getProcessRank()
    a(:,1:N) = p
    a(:,0) = -1
    a(:,N+1) = -1

call haloFill(a, this%getMpiCommunicator())
@assertEqual(real(p), a(1,1))
```

```
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found,'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- · @assertTrue
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- · @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- · @assertSameShape
- · @assertIsNaN
- · @assertIsFinite

12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

@Assert Preprocessor Directives

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

13.1 @Assert Preprocessor Dire	ctives
--------------------------------	--------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

Revision Notes

- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
 MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

36 Revision Notes

Data Type Index

15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

pFUnitParser::Action
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtParameters
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
add mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
AssertBasic mod
AssertInteger_mod
GenerateRealArrayNewSignature::AssertRealArrayArgument 50
BaseTestRunner_mod
BeforeAfter_mod
BrokenSetUpCase_mod
BrokenTestCase_mod
mods::pre::pre2::dataString 61
DebugListener_mod
CodeUtilities::declaration

Dynamic lestCase_mod
Exception_mod
Fixture_mod
FixtureTestCase_mod
CodeUtilities::fortranSubroutineSignature
Halo_mod
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre_:lf::interval
Test_RestrictSphericalCoordinates_mod::LatLonCase 69
LinearInterpolator_mod
MakeInfinity_mod
MakeNaN_mod
$MockCall_mod \ldots \ldots$
MockListener_mod
testParser::MockParser
MockRepository_mod
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
MpiStubs_mod
MpiTestCase_mod
MpiTestMethod_mod
ParallelContext_mod
ParallelException_mod
ParameterizedTestCase_mod
Params_mod
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
pFUnit_mod
PrivateException_mod
mods::pre2::procDirective
mods::pre::pre_lf::lfDirective
mods::pre::pre_Repeat::RepeatDirective
RemoteProxyTestCase_mod
ResultPrinter_mod
RobustRunner_mod
robustTestSuite mod
CodeUtilities::routineUnit
GenerateRealArrayNewSignature::constraintASSERTEQUAL 60
GenerateRealArrayNewSignature::IsWithinTolerance
GenerateRealArrayNewSignature::VECTOR_NORM
SerialContext_mod

SimpleTestCase_mod	91
SourceLocation_mod	92
SphericalCoordinates_mod	92
TestListener_mod::startTest	93
StringConversionUtilities_mod	
SubsetRunner_mod	. 94
SurrogateTestCase_mod	95
SUT_mod	. 95
Test_Assert_mod	96
Test AssertBasic mod	96
Test_AssertComplex_mod	96
Test_AssertInteger_mod	
Test AssertReal mod	
Test_BasicOpenMP_mod	
Test_Exception_mod	
Test FixtureTestCase mod	
Test_LinearInterpolator_mod::Test_LinearInterpolator	
Test_LinearInterpolator_mod	
Test MockCall mod	
Test_MockRepository_mod	
Test_mod	
Test MpiContext mod	
Test MpiException mod	
Test_MpiTestCase_mod	
Test_Parameters_mod::Test_Parameters	
Test Parameters mod	
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates	
Test RestrictSphericalCoordinates mod	
Test RobustRunner mod	
Test_SimpleTestCase_mod	
Test_StringConversionUtilities_mod	
Test_TestMethod_mod	
Test_TestResult_mod	
Test_TestSuite_mod	107
Test UnixProcess mod	
TestCase mod	
TestFailure mod	
mods::pre::pre_lf::TestlfDirective	
mods::pre::interleavedp::TestInterleaved	
TestListener mod	
TestMethod mod	
mods::pre::parseArgs::TestParseArgs	
testParser::TestParseLine	
mods::pre::pre Repeat::TestRepeatDirective	
TestResult mod	
16911 169011_HIUU	. 114
TestRunner_mod	

estSuite_mod	16
hrowFundamentalTypes_mod	17
InixPipeInterfaces_mod	18
InixProcess mod	18

Data Type Index

16.1 Data Types List

Here are the data types with brief descriptions:

pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
<briefdescription></briefdescription>
AssertBasic_mod
<briefdescription></briefdescription>
AssertInteger_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::AssertRealArrayArgument 50
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtParameters
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
BaseTestRunner_mod
<briefdescription></briefdescription>
BeforeAfter_mod
BrokenSetLinCase mod 59

BrokenTestCase_mod	59
GenerateRealArrayNewSignature::constraintASSERTEQUAL	60
mods::pre::pre2::dataString	61
DebugListener mod	
<briefdescription></briefdescription>	62
CodeUtilities::declaration	63
DynamicTestCase mod	
<pre></pre>	63
Exception_mod	64
Fixture_mod	65
FixtureTestCase_mod	65
	66
CodeUtilities::fortranSubroutineSignature	
Halo_mod	66
mods::pre::pre_lf::lfDirective	66
CodeUtilities::implementation	67
CodeUtilities::interfaceBlock	67
mods::pre::pre_lf::interval	68
GenerateRealArrayNewSignature::IsWithinTolerance	68
Test_RestrictSphericalCoordinates_mod::LatLonCase	69
LinearInterpolator_mod	69
MakeInfinity_mod	
<briefdescription></briefdescription>	69
MakeNaN_mod	
<briefdescription></briefdescription>	
	70
•	70
MockCall_mod	70 71
MockCall_mod <briefdescription></briefdescription>	
MockCall_mod <briefdescription></briefdescription>	71
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser </briefdescription>	71 72
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod</briefdescription>	71 72 72
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> </briefdescription></briefdescription>	71 72 72 72
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod</briefdescription></briefdescription>	71 72 72 72 73
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod testParser::MockWriter</briefdescription></briefdescription>	71 72 72 72 73 74
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod testParser::MockWriter CodeUtilities::module</briefdescription></briefdescription>	71 72 72 72 73 74
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod testParser::MockWriter CodeUtilities::module MpiContext_mod</briefdescription></briefdescription>	71 72 72 72 73 74 74
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod testParser::MockWriter CodeUtilities::module MpiContext_mod <briefdescription></briefdescription></briefdescription></briefdescription>	71 72 72 72 73 74
MockCall_mod <briefdescription> MockListener_mod testParser::MockParser MockRepository_mod <briefdescription> MockSUT_mod testParser::MockWriter CodeUtilities::module MpiContext_mod <briefdescription> MpiStubs_mod</briefdescription></briefdescription></briefdescription>	71 72 72 72 73 74 74 75
MockCall_mod	71 72 72 72 73 74 74 75 75
MockCall_mod	71 72 72 72 73 74 74 75
MockCall_mod	71 72 72 72 73 74 74 75 75
MockCall_mod	71 72 72 72 73 74 74 75 75
MockCall_mod	71 72 72 72 73 74 74 75 75 76
MockCall_mod	71 72 72 72 73 74 74 75 75 76


ParameterizedTestCase_mod
<briefdescription></briefdescription>
Params_mod
<briefdescription></briefdescription>
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
<pre></pre>
pFUnit mod
PrivateException_mod
<pre><briefdescription></briefdescription></pre>
mods::pre::pre2::procDirective
RemoteProxyTestCase_mod
<pre></pre>
mods::pre::pre_Repeat::RepeatDirective
ResultPrinter mod
<pre></pre>
RobustRunner mod
<pre></pre>
robustTestSuite_mod
CodeUtilities::routineUnit
SerialContext mod
<pre></pre>
SimpleTestCase_mod
SourceLocation mod
<pre></pre>
SphericalCoordinates_mod
TestListener_mod::startTest
StringConversionUtilities_mod
<pre></pre>
SubsetRunner mod
<pre></pre>
SurrogateTestCase_mod
<pre></pre>
SUT_mod
Test_Assert_mod
Test_AssertBasic_mod
Test_AssertComplex_mod
Test AssertInteger mod
Test AssertReal mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test FixtureTestCase mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
iest_Linearinterpolator_inou

Test_MockCall_mod	100
Test_MockRepository_mod	101
Test_mod	
<briefdescription></briefdescription>	101
Test_MpiContext_mod	102
Test_MpiException_mod	102
Test_MpiTestCase_mod	102
Test_Parameters_mod::Test_Parameters	103
Test_Parameters_mod	103
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates .	104
Test_RestrictSphericalCoordinates_mod	105
Test_RobustRunner_mod	
Test_SimpleTestCase_mod	
Test_StringConversionUtilities_mod	
Test_TestMethod_mod	
Test TestResult mod	
Test TestSuite mod	
Test UnixProcess mod	
TestCase_mod	
 <briefdescription></briefdescription>	107
TestFailure mod	
<pre><briefdescription></briefdescription></pre>	108
mods::pre::pre_lf::TestlfDirective	
mods::pre::interleavedp::TestInterleaved	
TestListener mod	
<pre><briefdescription></briefdescription></pre>	110
TestMethod mod	
<pre><briefdescription></briefdescription></pre>	111
mods::pre::parseArgs::TestParseArgs	
testParser::TestParseLine	
mods::pre::pre_Repeat::TestRepeatDirective	
TestResult mod	
<pre><briefdescription> Note: A possible extension point for user-</briefdescription></pre>	
specialized TestResults	114
TestRunner mod	
<pre></pre>	115
TestSuite mod	
<pre></pre>	116
ThrowFundamentalTypes mod	
<pre><briefdescription></briefdescription></pre>	117
UnixPipeInterfaces_mod	
<pre></pre>	118
UnixProcess mod	110
<pre> </pre> <pre> <a< td=""><td>112</td></a<></pre>	112
GenerateRealArrayNewSignature::VECTOR_NORM	
denotation carriagness or indicate the contract of the contrac	113

Data Type Documentation

17.1 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



• def apply

The documentation for this class was generated from the following file:

pFUnitParser.py

17.2 add_mod Module Reference

Public Member Functions

- real function add (x, y)
- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- Robust/Semi-Automatic/src/add.F90
- Simple/Semi-Automatic/src/add.F90
- Simple_Windows/Semi-Automatic/src/add.F90

17.3 addComplex_mod Module Reference

Public Member Functions

- complex function, dimension(size(z0)) add (z0, z1)
- complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following files:

- Semi-Automatic/src/addComplex.F90
- · Windows/Semi-Automatic/src/addComplex.F90

17.4 CodeUtilities::ArrayDescription Class Reference

Public Member Functions

- def __init___
- def NAME
- def DECLARE
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

Public Attributes

- fType
- kind
- rank

The documentation for this class was generated from the following file:

CodeUtilities.py

17.5 Assert_mod Module Reference

<BriefDescription>

17.5.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

17.6 AssertBasic mod Module Reference

<BriefDescription>

Data Types

- interface assertEqual
- interface assertExceptionRaised
- · interface assertFalse
- · interface assertIsFinite
- interface assertIsNaN
- interface assertTrue
- interface fail
- type UnusableArgument

- subroutine assertExceptionRaisedMessage (message)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- · logical function, public nonConformable (shapeA, shapeB)
- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN_double (x, message, location)
- subroutine assertIsFinite_single (x, message, location)
- subroutine assertIsFinite_double (x, message, location)

17.6.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertBasic.F90

17.7 AssertInteger_mod Module Reference

<BriefDescription>

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

Public Member Functions

- subroutine assertEqualInteger1D1D_ (expected, found, message, location)
- subroutine assertEqualInteger0D1D_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D_ (expected, found, message, location)
- subroutine assertLessThan_ (a, b, message, location)

17.7.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

17.8 GenerateRealArrayNewSignature::AssertRealArrayArgument Class Reference

Public Member Functions

def __init__

- def updateDescriptions
- def getExpectedDescription
- def getFoundDescription
- def getTolerance

Public Attributes


- expectedFType
- expectedPrecision
- expectedRank
- foundFType
- foundPrecision
- foundRank
- tolerance
- expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

17.9 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



Public Member Functions

- def __init__
- · def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.10 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.11 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

• pFUnitParser.py

17.12 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



Public Member Functions

- def __init__
- · def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.13 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.14 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



- def __init__
- def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.15 pFUnitParser::AtParameters Class Reference

Inheritance diagram for pFUnitParser::AtParameters:



Public Member Functions

- def __init__
- def match
- · def action

Public Attributes


· parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.16 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.17 pFUnitParser::AtTest Class Reference

Inheritance diagram for pFUnitParser::AtTest:



- def __init__
- def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.18 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



Public Member Functions

- def __init__
- def match
- · def action

Public Attributes

parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.19 BaseTestRunner_mod Module Reference

<BriefDescription>

Data Types

- type BaseTestRunner
- interface run

17.19.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

17.20 BeforeAfter_mod Module Reference

Public Member Functions

- subroutine first (this)
- subroutine last (this)
- · subroutine succeeds (this)
- subroutine fails (this)

Public Attributes

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

· beforeAfter.pf

17.21 BrokenSetUpCase_mod Module Reference

Data Types

• type BrokenSetUpCase

Public Member Functions

• type(BrokenSetUpCase) function, pointer, public newBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

17.22 BrokenTestCase_mod Module Reference

Data Types

• type BrokenTestCase


• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

17.23 GenerateRealArrayNewSignature::constraintASSERTEQUA-L Class Reference

Inheritance diagram for GenerateRealArrayNewSignature::constraintASSERTEQUAL:



Public Member Functions

def __init__

This next line actually generates the text of the code.

Public Attributes

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

17.23.1 Constructor & Destructor Documentation

```
17.23.1.1 def GenerateRealArrayNewSignature::constraintASSERTE-QUAL::__init__ ( self, expectedDescr, foundDescr, tolerance )
```

This next line actually generates the text of the code.

17.23.2 Member Data Documentation

17.23.2.1 GenerateRealArrayNewSignature::constraintASSERTEQUAL::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

17.23.2.2 GenerateRealArrayNewSignature::constraintASSERTEQUAL::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

17.24 mods::pre::pre2::dataString Class Reference

Public Member Functions

- def __init__
- def insert
- def getLength
- def getPosition
- · def setPosition
- def getItem
- def getDataAtPosition
- def getData
- def getSlice
- def getSliceForward
- def removeSlice
- · def getCurrentData
- · def insertAtCurrent

- · def append
- def advanceAndGetNextData
- def validPosition
- def findToEnd
- def match
- · def matchToEnd
- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

Public Attributes

- data
- position

The documentation for this class was generated from the following file:

pre2.py

17.25 DebugListener_mod Module Reference

<BriefDescription>

Data Types

• type DebugListener

Public Member Functions

• subroutine startTest (this, testName)

17.25.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DebugListener.F90

17.26 CodeUtilities::declaration Class Reference

Public Member Functions

- def __init__
- · def generate

Public Attributes

- simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.27 DynamicTestCase_mod Module Reference

 $<\!\!\text{BriefDescription}\!\!>$

Data Types

- interface delete
- type **DynamicTestCase**
- · interface testmethod

Public Member Functions

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

17.27.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

17.28 Exception_mod Module Reference

Data Types

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- · interface throw

Public Member Functions

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public catchAny (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()

- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

17.29 Fixture mod Module Reference

Public Member Functions

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()
- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following files:

- Semi-Automatic/tests/fixtureTests.pf
- · Windows/Semi-Automatic/tests/fixtureTests.pf

17.30 FixtureTestCase_mod Module Reference

Data Types

- interface delete
- type FixtureTestCase

Public Member Functions

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- · subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

FixtureTestCase.F90

17.31 CodeUtilities::fortranSubroutineSignature Class Reference

Public Member Functions

- def init
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

Public Attributes

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.32 Halo_mod Module Reference

Public Member Functions

• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

17.33 mods::pre::pre_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre_If::IfDirective:



Public Member Functions

• def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_lf.py

17.34 CodeUtilities::implementation Class Reference

Public Member Functions

- def __init__
- def generate

Public Attributes

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.35 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.36 mods::pre::pre_lf::interval Class Reference

Public Member Functions

- def init
- · def getInterval
- def setInterval
- · def getStart
- def getEnd

Public Attributes


- start
- end
- interval

The documentation for this class was generated from the following file:

pre_lf.py

17.37 GenerateRealArrayNewSignature::IsWithinTolerance Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::IsWithinTolerance:



Public Member Functions

• def __init__

Public Attributes

- rank
- · precision

- name
- fType
- · declaration
- · declarations

The documentation for this class was generated from the following file:

· GenerateRealArrayNewSignature.py

17.38 Test_RestrictSphericalCoordinates_mod::LatLonCase Type - Reference

Public Attributes

- real lat
- real lon
- · real restrictedLat
- · real restrictedLon

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.39 LinearInterpolator_mod Module Reference

Data Types

- · interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

• LinearInterpolator.F90

17.40 MakeInfinity_mod Module Reference

<BriefDescription>

Public Member Functions

- real(r32) function, public makeInf_32 ()
- real(r64) function, public makeInf_64 ()

17.40.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MakeInfinity.F90

17.41 MakeNaN mod Module Reference

```
<BriefDescription>
```

Public Member Functions

- real(r32) function, public makeNaN_32 ()
- real(r64) function, public makeNaN_64 ()

17.41.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MakeNaN.F90

17.42 MockCall_mod Module Reference

<BriefDescription>

Data Types

· type MockCall

Public Member Functions

• type(MockCall) function, public **newMockCall** (name)

17.42.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockCall.F90

17.43 MockListener_mod Module Reference

Data Types

• type MockListener

Public Member Functions

• subroutine startTest (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

17.44 testParser::MockParser Class Reference

Public Member Functions

- def __init___
- · def nextLine

Public Attributes

- line
- outputFile
- · outLines
- · tests
- · mpitests
- · currentSelfObjectName

The documentation for this class was generated from the following file:

testParser.py

17.45 MockRepository_mod Module Reference

<BriefDescription>

Data Types

• type MockRepository

Public Member Functions

- type(MockRepository) function, pointer, public **newMockRepository** ()
- subroutine expectCall (this, obj, method)

17.45.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MockRepository.F90

17.46 MockSUT mod Module Reference

Data Types

· type MockSUT

Public Member Functions

- type(MockSUT) function, allocatable, public newMockSUT (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.47 testParser::MockWriter Class Reference

Public Member Functions

- def init
- def write

Public Attributes

parser

The documentation for this class was generated from the following file:

testParser.py

17.48 CodeUtilities::module Class Reference

Public Member Functions

- def __init__
- def generate
- def addDeclaration
- def addImplementation
- · def addRoutineUnit
- def addInterfaceBlock
- def getName
- def setFileName
- def getFileName

Public Attributes

- name
- · declarations
- · implementations
- · generation
- fileName

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.49 MpiContext_mod Module Reference

<BriefDescription>

Data Types

- type MpiContext
- interface newMpiContext

Public Member Functions

- subroutine barrier (this)
- integer function getMpiCommunicator (this)

17.49.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiContext.F90

17.50 MpiStubs_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public MPI_Comm_rank (comm, rank, ier)
- subroutine, public MPI_Comm_size (comm, size, ier)
- subroutine, public MPI_Comm_dup (comm, newComm, ier)
- subroutine, public MPI Comm group (comm, group, ier)
- subroutine, public MPI_Group_range_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI_Comm_create (comm, group, newComm, ier)

Public Attributes

- integer, parameter, public MPI_COMM_WORLD = -1
- integer, parameter, public MPI_COMM_NULL = -1
- integer, parameter, public MPI_COMM_SUCCESS = 0

17.50.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MpiStubs.F90

17.51 MpiTestCase_mod Module Reference

<BriefDescription>

Data Types

- · type MpiTestCase
- · interface runMethod

Public Member Functions

- recursive subroutine runBare (this)
- subroutine setUp (this)

17.51.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestCase.F90

17.52 MpiTestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

17.52.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestMethod.F90

17.53 ParallelContext_mod Module Reference

<BriefDescription>

Data Types

- interface allReduceLogical
- interface gatherInteger
- interface gatherLogical
- · interface gatherString
- interface getNumProcesses
- type ParallelContext
- interface processRank
- · interface sum

17.53.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParallelContext.F90

17.54 ParallelException_mod Module Reference

<BriefDescription>

Data Types

- interface any Exceptions
- interface getNumExceptions

Public Member Functions

• subroutine, public gather (context)

17.54.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• ParallelException.F90

17.55 ParameterizedTestCase_mod Module Reference

<BriefDescription>

Data Types

- type AbstractTestParameter
- interface getParameterString
- type ParameterizedTestCase

Public Attributes

• integer, parameter, public MAX_LEN_LABEL = 32

17.55.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParameterizedTestCase.F90

17.56 Params_mod Module Reference

<BriefDescription>

Public Attributes

```
• integer, parameter R32 = selected_real_kind(p=6)
```

- integer, parameter **R64** = selected_real_kind(p=14)
- integer, parameter **C32** = selected_real_kind(p=6)
- integer, parameter C64 = selected_real_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

17.56.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Params.F90

17.57 pFUnitParser::Parser Class Reference

Public Member Functions

- def __init__
- def run
- def nextLine
- def makeSuite
- def final

Public Attributes

- inputFile
- outputFile
- moduleName
- suiteName
- testCase
- setUp
- tearDown
- · defaultName
- fileName
- lineNumber
- parameters
- parameterType
- · tests
- · mpitests
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

17.58 Test_Parameters_mod::peCase Type Reference

Public Attributes

- integer p1
- integer p2

The documentation for this type was generated from the following file:

• parameterizedTests.pf

17.59 pFUnit Module Reference

<BriefDescription>

17.59.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

17.60 pFUnit_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public initialize (useMpi)
- subroutine, public finalize ()

17.60.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

17.61 PrivateException_mod Module Reference

<BriefDescription>

Data Types

- type Exception
- type ExceptionList
- interface newException

Public Member Functions

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

Public Attributes

- integer, parameter, public **MAXLEN_MESSAGE** = 80*15
- integer, parameter, public **MAXLEN_FILE_NAME** = 80
- character(len=*), parameter, public NULL_MESSAGE = "

17.61.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• Exception.F90

17.62 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



Public Member Functions

- def __init__
- def getLength
- · def match
- def evaluate
- def getNewPosition
- def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- def finditerTokenToPosition
- def makeTokenErrorMessage

Public Attributes

- name
- newPosition
- · tokens
- TokenREs

17.62.1 Member Function/Subroutine Documentation

```
17.62.1.1 def mods::pre2::procDirective::addTokenRE( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = ''')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

• pre2.py

17.63 RemoteProxyTestCase_mod Module Reference

<BriefDescription>

Data Types

• interface RemoteProxyTestCase

17.63.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

17.64 mods::pre::pre_Repeat::RepeatDirective Class Reference

Inheritance diagram for mods::pre::pre_Repeat::RepeatDirective:



Public Member Functions

• def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_Repeat.py

17.65 ResultPrinter_mod Module Reference

<BriefDescription>

Data Types

• type ResultPrinter

Public Member Functions

- type(ResultPrinter) function, public **newResultPrinter** (unit)
- subroutine addError (this, testName, exceptions)
- subroutine **startTest** (this, testName)
- subroutine **printHeader** (this, runTime)

17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

17.66 RobustRunner_mod Module Reference

<BriefDescription>

Data Types

- · interface RobustRunner
- type TestCaseMonitor

Public Member Functions

- type(RobustRunner) function newRobustRunner_unit (remoteRunCommand, unit)
- · subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

17.66.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· RobustRunner.F90

17.67 robustTestSuite mod Module Reference

Public Member Functions

- type(TestSuite) function, public **suite** ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

17.68 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



Public Member Functions

- def __init__
- def setName
- · def getName
- def setDeclaration
- · def addDeclaration
- def setImplementation
- def getDeclaration
- · def getDeclarations
- def getImplementation
- · def clearDeclarations

Public Attributes

- name
- declaration
- · declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.69 SerialContext_mod Module Reference

<BriefDescription>

Data Types

• type SerialContext

Public Member Functions

• type(SerialContext) function, public newSerialContext ()

Public Attributes

 type(SerialContext), parameter, public THE_SERIAL_CONTEXT = Serial-Context(1)

17.69.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

17.70 SimpleTestCase_mod Module Reference

Data Types

- · interface method
- type SimpleTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete_ (this)

The documentation for this module was generated from the following file:

• SimpleTestCase.F90

17.71 SourceLocation mod Module Reference

<BriefDescription>

Data Types

• type SourceLocation

Public Attributes

- character(len=MAXLEN_FILE_NAME), parameter, public UNKNOWN_FILE_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN_LINE_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN_SOURCE_LOCATION = SourceLocation()

17.71.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

17.72 SphericalCoordinates_mod Module Reference

Data Types

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

17.73 TestListener_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

17.74 StringConversionUtilities_mod Module Reference

<BriefDescription>

Data Types

· interface toString

Public Member Functions

- character(len=len_trim(a)+1+len_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)

Public Attributes

• integer, parameter, public **MAXLEN_STRING** = 80

17.74.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

17.75 SubsetRunner_mod Module Reference

<BriefDescription>

Data Types

· interface SubsetRunner

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

17.75.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SubsetRunner.F90

17.76 SurrogateTestCase_mod Module Reference

<BriefDescription>

Data Types

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

17.76.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

17.77 SUT_mod Module Reference

Data Types

• type SUT

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.78 Test Assert mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test Assert.F90

17.79 Test AssertBasic mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()

The documentation for this module was generated from the following file:

• Test AssertBasic.F90

17.80 Test_AssertComplex_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testEquals_C_complexScalar ()
- subroutine testEquals_C_0D1D ()
- subroutine testEquals_C_1D_nonConformable1 ()
- subroutine testEquals_C_2D_SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent1
- subroutine testEquals_C_MultiD_SingleElementDifferent2
- subroutine testEquals_C_MultiD_SingleElementDifferent3
- subroutine testEquals_C_MultiD_SingleElementDifferent4
- subroutine testEquals_C_MultiD_SingleElementDifferent5
- subroutine testEquals C MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff1 ()

- subroutine testEquals C MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff3 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff4 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff5 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff6 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff8 ()
- subroutine testEquals_ScalarWithTolerance ()
- subroutine testEquals C MultiDWithTolerance ()
- subroutine testEquals_C_MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals_C_MultiDWithTolerance64_1 ()
- subroutine testEquals_C_MultiDWithTolerance64_2 ()
- subroutine testEquals C MultiDSourceLocation ()
- subroutine testEquals_4DPComplex_DifferenceReport ()
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

Test AssertComplex.F90

17.81 Test_AssertInteger_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqual_equal ()

The documentation for this module was generated from the following file:

· Test AssertInteger.F90

17.82 Test AssertReal mod Module Reference

- type(TestSuite) function, public suite ()
- subroutine testEquals_0D1D ()
- subroutine testEquals_1D_nonConformable1 ()
- subroutine testEquals_2D_SingleElementDifferent ()

- subroutine testEquals MultiD SingleElementDifferent ()
- subroutine testEquals_MultiD_SingleElementDifferent1
- subroutine testEquals_MultiD_SingleElementDifferent2
- subroutine testEquals MultiD SingleElementDifferent3
- subroutine testEquals_MultiD_SingleElementDifferent4
- subroutine testEquals MultiD SingleElementDifferent5
- subroutine testEquals MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff5 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals_ScalarWithToleranceNoMsg ()
- subroutine testEquals_VectorWithToleranceNoMsg ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals MultiDWithTolerance1 ()
- subroutine testEquals MultiDWithTolerance64 ()
- subroutine testEquals_MultiDWithTolerance64_1 ()
- subroutine testEquals_MultiDWithTolerance64_2 ()
- subroutine testEquals MultiDSourceLocation ()
- subroutine testEquals ScalarAndLocation ()
- subroutine testEquals ScalarInfinity equal ()
- subroutine testEquals ScalarInfinity unequal A ()
- subroutine testEquals ScalarInfinity unequal B ()
- subroutine testEquals_ScalarInfinity_unequal_C ()
- · subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

Test_AssertReal.F90

17.83 Test_BasicOpenMP_mod Module Reference

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()

• subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

Test BasicOpenMP.F90

17.84 Test_Exception_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

The documentation for this module was generated from the following file:

• Test_Exception.F90

17.85 Test_FixtureTestCase_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test FixtureTestCase.F90

17.86 Test_LinearInterpolator_mod::Test_LinearInterpolator Type - Reference

Public Member Functions

type(Test_LinearInterpolator) function newTest_LinearInterpolator (name, userMethod)

- · procedure setUp
- procedure tearDown
- · procedure runMethod

Public Attributes

- type(LinearInterpolator) interpolator
- procedure(runMethod), pointer **userMethod** = > null()

The documentation for this type was generated from the following file:

· Test_LinearInterpolator.pf

17.87 Test_LinearInterpolator_mod Module Reference

Data Types

• type Test_LinearInterpolator

Public Member Functions

- type(Test_LinearInterpolator) function newTest_LinearInterpolator (name, userMethod)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine runMethod (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

· Test_LinearInterpolator.pf

17.88 Test_MockCall_mod Module Reference

Public Member Functions

• type(TestSuite) function, public suite ()

- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

• Test_MockCall.F90

17.89 Test_MockRepository_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.90 Test mod Module Reference

<BriefDescription>

Data Types

- interface countTestCases
- interface run
- type Test

17.90.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Test.F90

17.91 Test_MpiContext_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

· Test MpiContext.F90

17.92 Test_MpiException_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine test_anyExceptions_none (this)
- subroutine test_getNumExceptions (this)
- subroutine test_gather (this)

The documentation for this module was generated from the following file:

· Test MpiException.F90

17.93 Test_MpiTestCase_mod Module Reference

Data Types

- interface method
- type Test_MpiTestCase

Public Member Functions

- type(TestSuite) function, public **suite** ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- · recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

· Test MpiTestCase.F90

17.94 Test Parameters mod::Test Parameters Interface Reference

Public Member Functions

- procedure, nopass getParameters
- procedure **getParameterString** => getParameterString_
- procedure runMethod
- type(Test_Parameters) function **newTest** (name, method, npe, p1, p2)

Public Attributes

- integer p1
- integer p2
- procedure(runMethod), pointer **userMethod** = > null()

The documentation for this interface was generated from the following file:

· parameterizedTests.pf

17.95 Test Parameters mod Module Reference

Data Types

- type peCase
- interface Test_Parameters

Public Member Functions

- type(Test_Parameters) function **newTest** (name, method, npe, p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()
- character(:) function, allocatable getParameterString_ (this)
- subroutine runMethod (this)
- subroutine, public testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

17.96 Test_RestrictSphericalCoordinates_mod::Test_Restrict-SphericalCoordinates Interface Reference

Public Member Functions

- · procedure, nopass getParameters
- procedure getParameterString
- procedure runMethod
- type(Test_RestrictSphericalCoordinates) function newTest (name, method, lat, lon, restrictedLat, restrictedLon)

Public Attributes

- · real lat
- · real lon
- real restrictedLat
- · real restrictedLon
- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted
- procedure(runMethod), pointer userMethod = > null()

The documentation for this interface was generated from the following file:

• Test_RestrictedSphericalCoordinates.pf

17.97 Test_RestrictSphericalCoordinates_mod Module Reference

Data Types

- type LatLonCase
- interface Test RestrictSphericalCoordinates

Public Member Functions

- type(Test_RestrictSphericalCoordinates) function newTest (name, method, lat, lon, restrictedLat, restrictedLon)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- character(:) function, allocatable getParameterString (this)
- subroutine runMethod (this)

The documentation for this module was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.98 Test_RobustRunner_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

• Test RobustRunner.F90

17.99 Test_SimpleTestCase_mod Module Reference

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()

• subroutine testRunSuite ()

The documentation for this module was generated from the following file:

• Test_SimpleTestCase.F90

17.100 Test_StringConversionUtilities_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test_StringConversionUtilities.F90

17.101 Test_TestMethod_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

• Test_TestMethod.F90

17.102 Test_TestResult_mod Module Reference

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

• Test TestResult.F90

17.103 Test_TestSuite_mod Module Reference

Data Types

• type Verbose

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()
- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

The documentation for this module was generated from the following file:

• Test_TestSuite.F90

17.104 Test_UnixProcess_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testIsActive ()

The documentation for this module was generated from the following file:

• Test_UnixProcess.F90

17.105 TestCase_mod Module Reference

<BriefDescription>

Data Types

- type ConcreteSurrogate
- interface runMethod
- type TestCase
- type TestCaseReference

Public Member Functions

- recursive subroutine runBare (this)
- recursive subroutine runBare_surrogate (this)

17.105.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestCase.F90

17.106 TestFailure_mod Module Reference

<BriefDescription>

Data Types

• type TestFailure

17.106.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

17.107 mods::pre::pre_lf::TestIfDirective Class Reference

Public Member Functions

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse
- def testIFTestTrue1
- def testIFTestTrue2
- def testIFClearTokens
- · def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

pre_lf.py

17.108 mods::pre::interleavedp::TestInterleaved Class Reference

Public Member Functions

· def test_InOrder

- def test_NumberMismatch
- · def test OrderMismatch1
- def test_OrderMismatch2
- def test_OrderMismatch3
- def test ElseMid1
- def test_ElseMid2
- · def test ElseMid3
- def test_ElseMid4
- def test ElseMid5
- def test_ElseMid6
- def test_ElseMid7
- def test_ElseMid8
- def test_ElseMid9
- def test_ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

17.109 TestListener_mod Module Reference

<BriefDescription>

Data Types

- interface addFailure
- interface endTest
- type ListenerPointer
- interface startTest
- · type TestListener

17.109.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestListener.F90

17.110 TestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface empty
- interface newTestMethod
- type TestMethod

17.110.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestMethod.F90

17.111 mods::pre::parseArgs::TestParseArgs Class Reference

Public Member Functions

- · def test_ParseArgs_OneArgWithBrackets1
- def test_ParseArgs_OneArgWithBrackets2
- def test_ParseArgs_OneArgWithBrackets3
- def test_ParseArgs_OneArgWithBrackets4
- def test_ParseArgs_OneArgWithBrackets5
- · def test ParseArgs OneArgWithBrackets6
- def test_ParseArgs_OneArgWithBrackets7
- · def test ParseArgs oneArg
- def test_ParseArgs_twoArgs1
- def test_ParseArgs_twoArgs2
- def test_ParseArgs_oneArgArray1
- def test_ParseArgs_TwoArgArray
- def test_ParseArgs_ThreeArgs

The documentation for this class was generated from the following file:

· parseArgs.py

17.112 testParser::TestParseLine Class Reference

- def testCppSetLineAndFile
- · def testGetSubroutineName
- def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtMpiTest
- · def testMatchAtTestCase
- def testMatchAtAssertEqual
- · def testMatchAtAssertOther
- def testMatchAtMpiAssert
- · def testMatchAtBefore
- · def testMatchAtAfter
- · def testMatchAtSuite

17.112.1 Member Function/Subroutine Documentation

17.112.1.1 def testParser::TestParseLine::testAtMpiTest (self)

Check that a line starting with ' \emptyset mpitest' is detected as an annotation and that optional parameters are collected.

17.112.1.2 def testParser::TestParseLine::testAtTest(self)

Check that a line starting with '@test' is detected as an annotation.

17.112.1.3 def testParser::TestParseLine::testMatchAtAfter(self)

Check that a line starting with '@after*' ...

17.112.1.4 def testParser::TestParseLine::testMatchAtAssertEqual (self)

Check that a line starting with '@assertEqual' is detected as an annotation.

17.112.1.5 def testParser::TestParseLine::testMatchAtAssertOther (self)

Check that a line starting with '@assert*' is detected as an annotation.

17.112.1.6 def testParser::TestParseLine::testMatchAtBefore (self)

Check that a line starting with '@before*' \dots

17.112.1.7 def testParser::TestParseLine::testMatchAtMpiAssert (self)

Check that a line starting with '@mpiAssert*' is detected as an annotation.

17.112.1.8 def testParser::TestParseLine::testMatchAtSuite (self)

Check that a line starting with '@suite changes the suite name \dots

17.112.1.9 def testParser::TestParseLine::testMatchAtTestCase(self)

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

· testParser.py

17.113 mods::pre::pre_Repeat::TestRepeatDirective Class Reference

Public Member Functions

- def test copyBlock1
- def test_copyBlock2
- def test_copyBlock2Vars
- def test_copyBlock2VarsMulti
- def test_copyBlock2VarsMultiWithStrings
- · def test copyNaiveRecursion
- def test copyNaiveRecursion1
- def test_copyFunction1

The documentation for this class was generated from the following file:

pre_Repeat.py

17.114 TestResult_mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Data Types

• type TestResult

- $\bullet \ \ \mathsf{type}(\mathsf{TestResult}) \ \mathsf{function}, \ \ \mathsf{pointer}, \ \mathsf{public} \ \boldsymbol{\mathsf{newTestResult}} \ ()$
- · subroutine addError (this, aTest, exceptions)
- · integer function failureCount (this)
- subroutine addListener (this, listener)

17.114.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestResult.F90

17.115 TestRunner_mod Module Reference

<BriefDescription>

Data Types

- interface newTestRunner
- type TestRunner

Public Member Functions

- type(TestRunner) function newTestRunner_unit (unit)
- subroutine **run** (this, aTest, context)
- subroutine startTest (this, testName)

17.115.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestRunner.F90

17.116 TestSuite_mod Module Reference

<BriefDescription>

Data Types

- interface newTestSuite
- type TestReference
- type TestSuite

Public Member Functions

• recursive subroutine addTest (this, aTest)

17.116.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

TestSuite.F90

17.117 ThrowFundamentalTypes_mod Module Reference

<BriefDescription>

Data Types

- interface throwDifferentValues
- interface throwDifferentValuesWithLocation

Public Member Functions

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN_SHAPE) function, public locationFormat (iLocation)

17.117.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

17.118 UnixPipeInterfaces_mod Module Reference

<BriefDescription>

Data Types

- · interface fgets
- · interface free
- · interface getdelim
- · interface getline
- · interface pclose
- · interface popen

Public Attributes

• integer(C_INT), parameter, public **CLOSE_FAILED** = -1

17.118.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixPipeInterfaces.F90

17.119 UnixProcess_mod Module Reference

<BriefDescription>

Data Types

· interface UnixProcess

Public Member Functions

- · character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

17.119.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

UnixProcess.F90

GenerateRealArrayNewSignature::VECTOR_NORM Class -17.120 Reference

Inheritance diagram for GenerateRealArrayNewSignature::VECTOR_NORM:



Public Member Functions

• def __init__

Public Attributes

- rank
- fType
- precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py