### pFUnit

Generated by Doxygen 1.7.6

Tue Feb 4 2014 15:20:07

# **Contents**

1	pFU	nit 2 - Documentation - Version 0.0 (2014-0204-1519 MLR)	1
	1.1	Overview	1
	1.2	Contents	1
	1.3	See Also	2
	1.4	LICENSE	2
	1.5	Copyright	2
2	Obta	aining pFUnit	3
3	Insta	allation	5
	3.1	Installing pFUnit	5
	3.2	Prerequisites	5
	3.3	Obtaining pFUnit	6
	3.4	Manifest - What's in the directory?	6
	3.5	Configuration	7
	3.6	Building pFUnit	8
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8
		3.6.3 OPENMP	9
		3.6.4 Cleaning	9
		3.6.5 Documentation	9
		3.6.6 CMAKE	0
	27	Installation	Λ

ii	CONTENTS
-	OOMIEMO

		3.7.1	Installation - Serial	10
		3.7.2	Installation - MPI	10
		3.7.3	Installation - OPENMP	11
		3.7.4	Installation - DEFAULT DIRECTORY	11
4	Usag	je		13
	4.1	Usage		13
		4.1.1	Usage - Configuration	13
		4.1.2	Usage - Hello World	13
		4.1.3	Usage - Preprocessor	14
5	Deve	elopmen	ut .	15
6	Feed	lback &	Support	17
	6.1	Feedba	nck	17
	6.2	Suppor	t	17
7	FAQ	and Tip	os estados esta	19
	7.1	FAQ .		19
		7.1.1	Zero Tests Run	19
		7.1.2	Some Tests Are Not Running	19
	7.2	Tips .		20
		7.2.1	Environment Modules	20
		7.2.2	Compile Time Errors	20
		7.2.3	Intermediate files used by pFUnit	20
8	Platf	orm Spe	ecific Notes	21
	8.1	Mac OS	SX	21
	8.2	Window	vs/CYGWIN	21
9	Ackr	nowledg	ments	23
10	Knov	wn Insta	allations & Versions	25
11	TOD	0		27

CONTENTS iii

12	The I	Preproc	cessor - pFUnitParser	29
	12.1	Using 1	The Preprocessor	29
		12.1.1	Configuration - testSuites.inc	30
		12.1.2	Invocation	30
		12.1.3	Command Line Options	30
		12.1.4	Preprocessor Input File (.pf)	30
		12.1.5	Directives	31
			12.1.5.1 @Test	31
			12.1.5.2 @MPITest	31
			12.1.5.3 @Assert	32
			12.1.5.4 @Parameters	33
			12.1.5.5 @TestCase	33
13			eprocessor Directives	35
	13.1		ert Preprocessor Directives	
			@assertEqual	
		13.1.2	@assertTrue	36
		13.1.3	@assertFalse	36
		13.1.4	@assertLessThan	36
		13.1.5	@assertLessThanOrEqual	36
		13.1.6	@assertGreaterThan	36
		13.1.7	@assertGreaterThanOrEqual	36
		13.1.8	@assertIsMemberOf	36
		13.1.9	@assertContains	36
		13.1.10	O@assertAny	36
		13.1.11	I @assertAll	36
		13.1.12	2@assertNotAll	36
		13.1.13	3@assertNone	36
		13.1.14	4 @assertIsPermutationOf	36
		13.1.15	5@assertExceptionRaised	36
		13.1.16	6@assertSameShape	36

		13.1.17 @assertIsNaN	36
		13.1.18 @assertIsFinite	36
14	Revi	sion Notes	37
15	Data	Type Index	39
	15.1	Class Hierarchy	39
16	Data	Type Index	43
	16.1	Data Types List	43
17	Data	Type Documentation	49
	17.1	AbstractTestParameter_mod Module Reference	49
	17.2	pFUnitParser::Action Class Reference	49
	17.3	add_mod Module Reference	50
	17.4	addComplex_mod Module Reference	51
	17.5	CodeUtilities::ArrayDescription Class Reference	51
	17.6	Assert_mod Module Reference	51
		17.6.1 Detailed Description	52
	17.7	AssertBasic_mod Module Reference	52
		17.7.1 Detailed Description	53
	17.8	AssertInteger_mod Module Reference	53
		17.8.1 Detailed Description	54
	17.9	GenerateRealArrayNewSignature::AssertRealArrayArgument Class - Reference	54
	17.10	DpFUnitParser::AtAfter Class Reference	55
	17.1	pFUnitParser::AtAssert Class Reference	56
	17.12	2pFUnitParser::AtBefore Class Reference	56
	17.13	BpFUnitParser::AtBegin Class Reference	57
	17.14	4pFUnitParser::AtMpiAssert Class Reference	57
	17.15	ppFUnitParser::AtMpiTest Class Reference	58
	17.16	SpFUnitParser::AtSuite Class Reference	59
	17.17	7pFUnitParser::AtTest Class Reference	59

CONTENTS v

17.18pFUnitParser::AtTestCase Class Reference 60
17.19pFUnitParser::AtTestParameter Class Reference 61
17.20TestCaseB_mod::B_Parameter Type Reference 61
17.21 BaseTestRunner_mod Module Reference 62
17.21.1 Detailed Description
17.22BeforeAfter_mod Module Reference 63
17.23BrokenSetUpCase_mod Module Reference 63
17.24BrokenTestCase_mod Module Reference 63
17.25TestCaseC_mod::C_Parameter Type Reference 64
17.26Cases_mod Module Reference
17.27GenerateRealArrayNewSignature::constraintASSERTEQUAL Class Reference
17.27.1 Constructor & Destructor Documentation
17.27.1.1init
17.27.2 Member Data Documentation
17.27.2.1 name1
17.27.2.2 tolerance
17.28mods::pre::pre2::dataString Class Reference
17.29DebugListener_mod Module Reference 67
17.29.1 Detailed Description
17.30CodeUtilities::declaration Class Reference
17.31 DynamicTestCase_mod Module Reference
17.31.1 Detailed Description
17.32Exception_mod Module Reference 69
17.33Fixture_mod Module Reference
17.34FixtureTestCase_mod Module Reference
17.35CodeUtilities::fortranSubroutineSignature Class Reference 70
17.36Halo_mod Module Reference
17.37mods::pre::pre_If::IfDirective Class Reference
17.38CodeUtilities::implementation Class Reference
17.39CodeUtilities::interfaceBlock Class Reference

vi CONTENTS

17.40 mods::pre_:pre_If::interval Class Reference	72
17.41GenerateRealArrayNewSignature::IsWithinTolerance Class Reference .	73
17.42Test_RestrictSphericalCoordinates_mod::LatLonCase Type Reference .	74
17.43LinearInterpolator_mod Module Reference	74
17.44MakeInfinity_mod Module Reference	74
17.44.1 Detailed Description	75
17.45MakeNaN_mod Module Reference	75
17.45.1 Detailed Description	75
17.46 MockCall_mod Module Reference	76
17.46.1 Detailed Description	76
17.47MockListener_mod Module Reference	77
17.48testParser::MockParser Class Reference	77
17.49MockRepository_mod Module Reference	78
17.49.1 Detailed Description	78
17.50 MockSUT_mod Module Reference	78
17.51testParser::MockWriter Class Reference	79
17.52CodeUtilities::module Class Reference	79
17.53MpiContext_mod Module Reference	80
17.53.1 Detailed Description	80
17.54MpiStubs_mod Module Reference	81
17.54.1 Detailed Description	81
17.55MpiTestCase_mod Module Reference	82
17.55.1 Detailed Description	82
17.56MpiTestCaseB_mod::MpiTestCaseB Type Reference	83
17.57MpiTestCaseB_mod Module Reference	83
17.58MpiTestMethod_mod Module Reference	84
17.58.1 Detailed Description	84
17.59MpiTestParameter_mod Module Reference	84
17.60pFUnitParser::MyError Class Reference	85
17.61Cases_mod::MyParamType Type Reference	85
17.62Cases_mod::MyTestCase Type Reference	86

CONTENTS vii

17.63TestCaseC_mod::newC_Parameter Interface Reference
17.64ParallelContext_mod Module Reference
17.64.1 Detailed Description
17.65ParallelException_mod Module Reference
17.65.1 Detailed Description
17.66ParameterizedTestCase_mod Module Reference
17.66.1 Detailed Description
17.67Params_mod Module Reference
17.67.1 Detailed Description
17.68pFUnitParser::Parser Class Reference
17.69Test_Parameters_mod::peCase Type Reference
17.70pFUnit Module Reference
17.70.1 Detailed Description
17.71pFUnit_mod Module Reference
17.71.1 Detailed Description
17.72PrivateException_mod Module Reference
17.72.1 Detailed Description
17.73mods::pre::pre2::procDirective Class Reference
17.73.1 Member Function/Subroutine Documentation 94
17.73.1.1 addTokenRE
17.74RemoteProxyTestCase_mod Module Reference
17.74.1 Detailed Description
17.75mods::pre::pre_Repeat::RepeatDirective Class Reference 95
17.76ResultPrinter_mod Module Reference
17.76.1 Detailed Description
17.77RobustRunner_mod Module Reference
17.77.1 Detailed Description
17.78robustTestSuite_mod Module Reference
17.79CodeUtilities::routineUnit Class Reference
17.80SerialContext_mod Module Reference
17.80.1 Detailed Description

viii CONTENTS

17.81 Simple Test Case_mod Module Reference
17.82SourceLocation_mod Module Reference
17.82.1 Detailed Description
17.83SphericalCoordinates_mod Module Reference
17.84TestListener_mod::startTest Interface Reference
17.85StringConversionUtilities_mod Module Reference
17.85.1 Detailed Description
17.86SubsetRunner_mod Module Reference
17.86.1 Detailed Description
17.87SurrogateTestCase_mod Module Reference
17.87.1 Detailed Description
17.88SUT_mod Module Reference
17.89Test_Assert_mod Module Reference
17.90Test_AssertBasic_mod Module Reference
17.91Test_AssertComplex_mod Module Reference
17.92Test_AssertInteger_mod Module Reference
17.93Test_AssertReal_mod Module Reference
17.94Test_BasicOpenMP_mod Module Reference
17.95Test_Exception_mod Module Reference
17.96Test_FixtureTestCase_mod Module Reference
17.97Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 108
17.98Test_LinearInterpolator_mod Module Reference
17.99Test_MockCall_mod Module Reference
17.10 Test_MockRepository_mod Module Reference
17.10 Test_mod Module Reference
17.101. Detailed Description
17.10 Test_MpiContext_mod Module Reference
17.103est_MpiException_mod Module Reference
17.104est_MpiTestCase_mod Module Reference
17.105est_Parameters_mod::Test_Parameters Type Reference
17.10 Test Parameters mod Module Reference

CONTENTS ix

17.107/est_RestrictSphericalCoordinates_mod::Test_RestrictSpherical-
Coordinates Type Reference
17.108est_RestrictSphericalCoordinates_mod Module Reference
17.10 <b>9</b> est_RobustRunner_mod Module Reference
17.11 <b>©</b> est_SimpleTestCase_mod Module Reference
17.11 Test_StringConversionUtilities_mod Module Reference
17.11 <b>Z</b> est_TestMethod_mod Module Reference
17.11 <b>3</b> est_TestResult_mod Module Reference
17.114est_TestSuite_mod Module Reference
17.115est_UnixProcess_mod Module Reference
17.11 <b>6</b> estA_mod Module Reference
17.117estCase_mod Module Reference
17.117. Detailed Description
17.118estCaseA_mod::TestCaseA Type Reference
17.11 <b>9</b> estCaseA_mod Module Reference
17.12 <b>©</b> estCaseB_mod::TestCaseB Type Reference
17.12TestCaseB_mod Module Reference
17.12 <b>7</b> estCaseC_mod::TestCaseC Type Reference
17.12 <b>3</b> estCaseC_mod Module Reference
17.124estFailure_mod Module Reference
17.124. Detailed Description
17.125nods::pre::pre_lf::TestlfDirective Class Reference
17.12@nods::pre::interleavedp::TestInterleaved Class Reference
17.12 <b>T</b> estListener_mod Module Reference
17.127. Detailed Description
17.12 <b>8</b> estMethod_mod Module Reference
17.128. Detailed Description
17.12@nods::pre::parseArgs::TestParseArgs Class Reference
17.13@estParser::TestParseLine Class Reference
17.130. Member Function/Subroutine Documentation
17.130.1.1testAtMpiTest

x CONTENTS

17.130.1.2testAt lest
17.130.1.3testAtTestFail
17.130.1.4testAtTestNoParens
17.130.1.5testAtTestSkipComment
17.130.1.@testMatchAtAfter
17.130.1.7testMatchAtAssertEqual
17.130.1.&testMatchAtAssertOther
17.130.1.9testMatchAtBefore
17.130.1.1t@stMatchAtMpiAssert
17.130.1.1testMatchAtSuite
17.130.1.1t2estMatchAtTestCase
17.13 mods::pre::pre_Repeat::TestRepeatDirective Class Reference 126
17.13 <b>2</b> estResult_mod Module Reference
17.132. Detailed Description
17.13 <b>3</b> estRunner_mod Module Reference
17.133. Detailed Description
17.134estSuite_mod Module Reference
17.134. Detailed Description
17.135hrowFundamentalTypes_mod Module Reference
17.135. Detailed Description
17.136InixPipeInterfaces_mod Module Reference
17.136. Detailed Description
17.13 vnix Process_mod Module Reference
17.137. Detailed Description
17.13&enerateRealArrayNewSignature::VECTOR_NORM Class Reference . 132
17.139VrapbeforeAfter Module Reference
17.14 <b>0</b> VrapMpiTestCaseB_mod Module Reference
17.14Wrapsimple Module Reference
17.142VrapTestA_mod Module Reference
17.14 <b>%</b> VrapTestCaseA_mod Module Reference
17.14\PrapTestCaseB_mod Module Reference

CONTENTS	xi		
17.145WrapTestCaseC_mod Module Reference	134		

# pFUnit 2 - Documentation - Version 0.0 (2014-0204-1519 MLR)

Quick link to the code!

### 1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

### 1.2 Contents

- Installation
  - Obtaining pFUnit
- Usage

- Development
- · Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

### 1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

### 1.4 LICENSE

Rights of use for GSC-15,137-1 F-UNIT, also known as pFUnit, are defined by the N-ASA Open Source Agreement (version 1.3). The LICENSE document may be found in the head directory of the pFUnit distribution.

### 1.5 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

# **Obtaining pFUnit**

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

### Installation

### 3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
  - Building pFUnit for testing serial codes (Non-MPI)
  - Building pFUnit for testing parallel codes (MPI)
  - OPENMP
  - Cleaning
  - Documentation
- Installation

### 3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.3, 4.9.0, IBM's XLF)
- The Message Passing Interface (MPI)
- OpenMP
- · GNU Make
- Python

Note: Recent changes have exposed a latent bug in GCC 4.8.2. The fix is available in the GCC 4.9 development branch and will also appear in GCC 4.8.3 when that is released. Users that require older versions of GCC should use pFUnit 2.1.x.

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

### 3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

### 3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

3.5 Configuration 7

CMakeLists.txt - Initial support for cmake-based builds.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

GNUmakefile - The top level makefile for building and installing pFUnit.

LICENSE - The NASA Open Source Agreement for GSC-15,137-1 F-UNIT, also known as pFUnit.

README-INSTALL - Basic documentation on pFUnit installation and use.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

### 3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90\_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90\_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

8 Installation

```
$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen
```

### 3.6 Building pFUnit

### 3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (for example in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

### 3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

#### **3.6.3 OPENMP**

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

```
$ make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

### 3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src\_clean' to remove intermediate products in subdirectories.

#### 3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following from the top level of your pFUnit distribution.

Or to make a reference manual.

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

10 Installation

#### 3.6.6 **CMAKE**

Initial support for CMAKE has been implemented. At this writing, a basic functionality is available.

3. The process for building pFUnit using cmake is as follows. In the top directory of the distribution make a new directory to support the build, then change to that directory and run cmake (pointing back to the source) to generate the required makefiles.

```
$ mkdir build
$ cd build
$ # e.g. cmake -DMPI=YES -DOPENMP=NO -DINSTALL_PATH=<A path> <path to source>
$ cmake -DMPI=NO ..
$ make tests
```

One may also set the environment variable PFUNIT instead of setting INSTALL\_PATH on the cmake command line as given above.

4. If the build is successful, then at this point make install should work.

### 3.7 Installation

### 3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL\_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL\_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ cd Examples
$ ./buildIt
```

#### 3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

3.7 Installation 11

To test, set PFUNIT and go into Examples/MPI\_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

### 3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

### 3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL\_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

12 Installation

# **Usage**

- Usage Configuration
- · Usage Hello World
- Usage Preprocessor

### 4.1 Usage

### 4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90\_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

### 4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
subroutine testHelloWorld()
    use pfunit_mod
```

14 Usage

```
implicit none
@assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

### 4.1.3 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

# **Development**

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL\_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

16 Development

# Feedback & Support

- Feedback
- Support

### 6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

### 6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

# **FAQ** and Tips

- FAQ
  - Zero Tests Run
  - Some Tests Are Not Running
- Tips
  - Environment Modules
  - Compile Time Errors
  - Intermediate files used by pFUnit

### 7.1 FAQ

### 7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD\_TEST\_SUITE (the\_suite\_to\_add), one to a line.
- There is no <code>-DUSE\_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

### 7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

20 FAQ and Tips

### Solutions:

There is no -DUSE\_MPI passed to the compiler during the build. Please add as
in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

### 7.2 Tips

#### 7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

### 7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

### 7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

# **Platform Specific Notes**

### 8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

### 8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

# **Acknowledgments**

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

# **Known Installations & Versions**

master - The cutting edge of pFUnit development.

pfunit\_2.1.0 - A feature freeze prior to a major upgrade of the preprocessor.

# **TODO**

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

28 TODO

# The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
  - Configuration testSuites.inc
  - Invocation
  - Command Line Options
  - Preprocessor Input File (.pf)
  - Directives
    - \* @Test
    - \* @MPITest
    - \* @Assert (or Preprocessor Directives)
    - \* @Parameters
    - \* @TestCase

# 12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's "tests" subdirectory.

### 12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

### 12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
    $(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

### 12.1.3 Command Line Options

The executable test program provides several command line options, when "include/driver.F90" is used, as it is automatically when using the PFUNIT preprocessor.

-v or -verbose	Verbose execution.
-d or -debug	Provide debugging information.
-h	Print help message.

### 12.1.4 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' "tests" subdirectories in the - Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
  - @Assert

#### 12.1.5 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

#### 12.1.5.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive. For example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

#### 12.1.5.2 @MPITest

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI Halo:

```
@mpiTest( npes=[1,2,3])
subroutine testHaloInterior(this)
```

```
use Halo_mod
  use pfunit_mod
   implicit none
  class (MpiTestMethod) :: this
   integer, parameter :: N = 2
  real :: a(N,0:N+1)
   integer :: p
   p = this%getProcessRank()
   a(:,1:N) = p
   a(:,0) = -1
   a(:,N+1) = -1
   call haloFill(a, this%getMpiCommunicator())
  @assertEqual(real(p), a(1,1))
   @assertEqual(real(p), a(2,1))
   @assertEqual(real(p), a(1,2))
   @assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

#### 12.1.5.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found, 'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains

- · @assertAny
- · @assertAll
- · @assertNotAll
- · @assertNone
- @assertIsPermutationOf
- · @assertExceptionRaised
- @assertSameShape
- · @assertIsNaN
- @assertIsFinite

#### 12.1.5.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the getParameters method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

### 12.1.5.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

# **@Assert Preprocessor Directives**

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

13.1 @Assert Preprocessor Dire	ctives
--------------------------------	--------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

# **Revision Notes**

- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
   MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

38 Revision Notes

# **Data Type Index**

# 15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter_mod	49
pFUnitParser::Action	49
pFUnitParser::AtAfter	55
pFUnitParser::AtAssert	56
pFUnitParser::AtBefore	56
pFUnitParser::AtBegin	57
pFUnitParser::AtMpiAssert	57
pFUnitParser::AtSuite	59
pFUnitParser::AtTest	59
pFUnitParser::AtMpiTest	58
pFUnitParser::AtTestCase	60
pFUnitParser::AtTestParameter	61
add_mod	50
addComplex_mod	
CodeUtilities::ArrayDescription	
Assert_mod	
AssertBasic_mod	
AssertInteger_mod	53
GenerateRealArrayNewSignature::AssertRealArrayArgument	54
TestCaseB_mod::B_Parameter	61
BaseTestRunner_mod	62
BeforeAfter_mod	63
BrokenSetUpCase_mod	63
BrokenTestCase_mod	63
TestCaseC mod::C Parameter	64

Cases_mod	4
mods::pre::pre2::dataString	6
DebugListener_mod	7
CodeUtilities::declaration	8
DynamicTestCase_mod	8
Exception_mod	9
Fixture_mod	0
FixtureTestCase_mod	0
CodeUtilities::fortranSubroutineSignature	0
Halo_mod	1
CodeUtilities::implementation	2
CodeUtilities::interfaceBlock	2
mods::pre_ifr:interval	2
Test_RestrictSphericalCoordinates_mod::LatLonCase	4
LinearInterpolator_mod	4
MakeInfinity_mod	4
MakeNaN_mod	5
MockCall mod	6
MockListener mod	7
MockRepository mod	8
MockSUT mod	8
testParser::MockWriter	9
CodeUtilities::module	9
MpiContext_mod	0
	1
MpiTestCase_mod	2
MpiTestCaseB_mod::MpiTestCaseB	3
MpiTestCaseB_mod	3
MpiTestMethod_mod	4
MpiTestParameter_mod	4
pFUnitParser::MyError	5
Cases_mod::MyParamType	
Cases_mod::MyTestCase	
TestCaseC_mod::newC_Parameter	
ParallelContext mod	
ParallelException_mod	
ParameterizedTestCase_mod	8
Params_mod	7
pFUnitParser::Parser	_
testParser::MockParser	
Test_Parameters_mod::peCase	
pFUnit	
pFUnit_mod	
PrivateException_mod	
mods::pre2::procDirective	4

mods::pre::pre_Repeat::RepeatDirective         95           RemoteProxyTestCase_mod         95           ResultPrinter_mod         96           RobustRunner_mod         97           robustTestSuite_mod         98           CodeUtilities::routineUnit         98           GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SurrogateTestCase_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertInteger_mod         106           Test_AssertReal_mod         106           Test_AssertReal_mod         106           Test_Exception_mod         107
ResultPrinter_mod         96           RobustRunner_mod         97           robustTestSuite_mod         98           CodeUtilities::routineUnit         98           GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertComplex_mod         105           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         106           Test_Exception_mod         107
RobustRunner_mod         97           robustTestSuite_mod         98           CodeUtilities::routineUnit         98           GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SubsetRunner_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertBasic_mod         105           Test_AssertReal_mod         106           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
robustTestSuite_mod         98           CodeUtilities::routineUnit         98           GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertInteger_mod         106           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
CodeUtilities::routineUnit         98           GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SubsetRunner_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         105           Test_AssertBasic_mod         105           Test_AssertComplex_mod         105           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
GenerateRealArrayNewSignature::constraintASSERTEQUAL         65           GenerateRealArrayNewSignature::lsWithinTolerance         73           GenerateRealArrayNewSignature::VECTOR_NORM         132           SerialContext_mod         99           SimpleTestCase_mod         100           SourceLocation_mod         100           SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SubsetRunner_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         105           Test_AssertBasic_mod         105           Test_AssertComplex_mod         105           Test_AssertReal_mod         106           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
GenerateRealArrayNewSignature::IsWithinTolerance       73         GenerateRealArrayNewSignature::VECTOR_NORM       132         SerialContext_mod       99         SimpleTestCase_mod       100         SourceLocation_mod       100         SphericalCoordinates_mod       101         TestListener_mod::startTest       101         StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
GenerateRealArrayNewSignature::VECTOR_NORM       132         SerialContext_mod       99         SimpleTestCase_mod       100         SourceLocation_mod       100         SphericalCoordinates_mod       101         TestListener_mod::startTest       101         StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SerialContext_mod       99         SimpleTestCase_mod       100         SourceLocation_mod       100         SphericalCoordinates_mod       101         TestListener_mod::startTest       101         StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SimpleTestCase_mod       100         SourceLocation_mod       100         SphericalCoordinates_mod       101         TestListener_mod::startTest       101         StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SourceLocation_mod       100         SphericalCoordinates_mod       101         TestListener_mod::startTest       101         StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SphericalCoordinates_mod         101           TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SubsetRunner_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertComplex_mod         105           Test_AssertInteger_mod         106           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
TestListener_mod::startTest         101           StringConversionUtilities_mod         101           SubsetRunner_mod         102           SurrogateTestCase_mod         103           SUT_mod         104           Test_Assert_mod         104           Test_AssertBasic_mod         105           Test_AssertComplex_mod         105           Test_AssertInteger_mod         106           Test_AssertReal_mod         106           Test_BasicOpenMP_mod         107           Test_Exception_mod         107
StringConversionUtilities_mod       101         SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SubsetRunner_mod       102         SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SurrogateTestCase_mod       103         SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
SUT_mod       104         Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
Test_Assert_mod       104         Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
Test_AssertBasic_mod       105         Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
Test_AssertComplex_mod       105         Test_AssertInteger_mod       106         Test_AssertReal_mod       106         Test_BasicOpenMP_mod       107         Test_Exception_mod       107
Test_AssertInteger_mod
Test_AssertReal_mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test_FixtureTestCase_mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
Test_MockCall_mod
Test_MockRepository_mod
Test_mod
Test MpiContext mod
Test_MpiException_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates . 112
Test RestrictSphericalCoordinates mod
Test_RobustRunner_mod
Test_SimpleTestCase_mod
Test_StringConversionUtilities_mod
Test TestMethod mod
Test TestResult mod
Test_TestSuite_mod

Test_UnixProcess_mod
$TestA\_mod\ldots\ldots\ldots\ldots\ldots\ldots116$
$TestCase\_mod \ldots \ldots$
TestCaseA_mod::TestCaseA
TestCaseA_mod
$TestCaseB\_mod:: TestCaseB \dots \dots$
$TestCaseB\_mod \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $
$TestCaseC\_mod:: TestCaseC \ \dots \ $
$TestCaseC\_mod \ldots \ldots \ldots 120$
$TestFailure\_mod \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $
$mods::pre::pre\_lf::TestIfDirective \\ \dots $
$mods::pre::interleavedp::TestInterleaved \dots \dots$
TestListener_mod
$TestMethod\_mod  .  .  .  .  .  .  .  .  .  $
$mods::pre::parseArgs::TestParseArgs \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $
$test Parser :: Test Parse Line \\ \ldots \\ \ldots \\ \ldots \\ 124$
$mods::pre::pre\_Repeat::TestRepeatDirective \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $
TestResult_mod
$TestRunner\_mod  \dots  \dots  \dots  128$
$TestSuite\_mod \dots \dots$
ThrowFundamentalTypes_mod
UnixPipeInterfaces_mod
UnixProcess_mod
WrapbeforeAfter
$Wrap Mpi Test Case B\_mod \ \dots \ $
Wrapsimple
$WrapTestA\_mod \ldots \ldots 133$
$Wrap Test Case A\_mod \ \dots \ $
$Wrap Test Case B\_mod \ \dots \ $
WrapTestCaseC mod 134

# **Data Type Index**

# 16.1 Data Types List

Here are the data types with brief descriptions:

AbstractTestParameter_mod
pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
<briefdescription></briefdescription>
AssertBasic_mod
<briefdescription></briefdescription>
AssertInteger_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::AssertRealArrayArgument 54
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
pFUnitParser::AtTestParameter 6
TestCaseB_mod::B_Parameter 6
BaseTestRunner_mod
<briefdescription></briefdescription>

44

BeforeAfter_mod	63
BrokenSetUpCase_mod	63
	63
TestCaseC_mod::C_Parameter	64
Cases_mod	64
GenerateRealArrayNewSignature::constraintASSERTEQUAL	65
mods::pre::pre2::dataString	66
DebugListener_mod	
<briefdescription></briefdescription>	67
CodeUtilities::declaration	68
DynamicTestCase_mod	
· · · · · · · · · · · · · · · · · · ·	68
Exception_mod	69
Fixture_mod	70
FixtureTestCase_mod	70
CodeUtilities::fortranSubroutineSignature	70
Halo_mod	71
mods::pre::pre_lf::lfDirective	71
CodeUtilities::implementation	72
CodeUtilities::interfaceBlock	72
mods::pre::pre_lf::interval	72
GenerateRealArrayNewSignature::IsWithinTolerance	73
Test_RestrictSphericalCoordinates_mod::LatLonCase	74
LinearInterpolator_mod	74
MakeInfinity_mod	
<briefdescription></briefdescription>	74
MakeNaN_mod	
<briefdescription></briefdescription>	75
MockCall_mod	
<briefdescription></briefdescription>	76
	77
testParser::MockParser	77
MockRepository_mod	
	78
	78
	79
	79
MpiContext_mod	
•	80
MpiStubs_mod	
•	81
MpiTestCase_mod	
1	82
	83
MpiTestCaseB_mod	83

MpiTestMethod_mod	
<pre></pre>	4
MpiTestParameter_mod	4
pFUnitParser::MyError	5
Cases_mod::MyParamType	5
Cases_mod::MyTestCase	6
TestCaseC_mod::newC_Parameter	6
ParallelContext_mod	
<briefdescription></briefdescription>	6
ParallelException_mod	
<pre><briefdescription></briefdescription></pre>	7
ParameterizedTestCase mod	
<briefdescription></briefdescription>	8
Params_mod	
<briefdescription></briefdescription>	9
pFUnitParser::Parser	0
Test_Parameters_mod::peCase	1
pFUnit	
<pre></pre>	1
pFUnit mod	
<pre>- &lt; BriefDescription&gt;</pre>	2
PrivateException mod	
<pre></pre>	3
mods::pre::pre2::procDirective	4
RemoteProxyTestCase_mod	
<briefdescription></briefdescription>	5
mods::pre::pre_Repeat::RepeatDirective	5
ResultPrinter mod	
<pre></pre>	6
RobustRunner_mod	
<pre></pre>	7
robustTestSuite_mod	8
CodeUtilities::routineUnit	8
SerialContext mod	
<pre></pre>	9
SimpleTestCase mod	0
SourceLocation mod	
<briefdescription></briefdescription>	0
SphericalCoordinates_mod	
TestListener mod::startTest	
StringConversionUtilities mod	
<pre></pre>	1
SubsetRunner mod	
<pre></pre>	2
SurrogateTestCase_mod	
<briefdescription></briefdescription>	3
· · · · · · · · · · · · · · · · · · ·	-

Test_Assert_mod
Test_AssertBasic_mod
Test_AssertComplex_mod
Test_AssertInteger_mod
Test_AssertReal_mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test_FixtureTestCase_mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
Test_MockCall_mod
Test_MockRepository_mod
Test_mod
<briefdescription></briefdescription>
Test_MpiContext_mod
Test_MpiException_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates . 112
Test_RestrictSphericalCoordinates_mod
Test_RobustRunner_mod
Test_SimpleTestCase_mod
Test_StringConversionUtilities_mod
Test TestMethod mod
rest_restiviethod_mod
Test_TestResult_mod
Test_TestResult_mod
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       4         SpriefDescription>       116         TestCaseA_mod::TestCaseA       117
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       4         SriefDescription>       116         TestCaseA_mod::TestCaseA       117         TestCaseA_mod       117
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       4         SriefDescription>       116         TestCaseA_mod::TestCaseA       117         TestCaseA_mod       117         TestCaseB_mod::TestCaseB       118
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       116         < BriefDescription>       116         TestCaseA_mod::TestCaseA       117         TestCaseB_mod       117         TestCaseB_mod       118         TestCaseB_mod       118
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       116         TestCaseA_mod::TestCaseA       117         TestCaseA_mod       117         TestCaseB_mod::TestCaseB       118         TestCaseC_mod::TestCaseC       119
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       116         TestCaseA_mod::TestCaseA       117         TestCaseA_mod       117         TestCaseB_mod::TestCaseB       118         TestCaseC_mod       118         TestCaseC_mod::TestCaseC       119         TestCaseC_mod       120
Test_TestResult_mod         115           Test_TestSuite_mod         115           Test_UnixProcess_mod         115           TestA_mod         116           TestCase_mod         116           TestCaseA_mod::TestCaseA         117           TestCaseA_mod         117           TestCaseB_mod::TestCaseB         118           TestCaseB_mod         118           TestCaseC_mod::TestCaseC         119           TestCaseC_mod         120           TestFailure_mod         120
Test_TestResult_mod       115         Test_TestSuite_mod       115         Test_UnixProcess_mod       115         TestA_mod       116         TestCase_mod       16         CestCaseA_mod::TestCaseA       117         TestCaseA_mod       117         TestCaseB_mod::TestCaseB       118         TestCaseB_mod       118         TestCaseC_mod::TestCaseC       119         TestCaseC_mod       120         TestFailure_mod       2         SpriefDescription>       120
Test_TestResult_mod         115           Test_TestSuite_mod         115           Test_UnixProcess_mod         115           TestA_mod         116           TestCase_mod         116           CestCaseA_mod::TestCaseA         117           TestCaseA_mod         117           TestCaseB_mod::TestCaseB         118           TestCaseB_mod         118           TestCaseC_mod::TestCaseC         119           TestCaseC_mod         120           TestFailure_mod <briefdescription>         120           mods::pre::pre_lf::TestlfDirective         121</briefdescription>
Test_TestResult_mod         115           Test_TestSuite_mod         115           Test_UnixProcess_mod         115           TestA_mod         116           TestCase_mod         116           CestCaseA_mod::TestCaseA         117           TestCaseA_mod         117           TestCaseB_mod::TestCaseB         118           TestCaseB_mod         118           TestCaseC_mod::TestCaseC         119           TestCaseC_mod         120           TestFailure_mod            < BriefDescription>         120           mods::pre::pre_lf::TestlfDirective         121           mods::pre::interleavedp::TestInterleaved         122
Test_TestResult_mod         115           Test_TestSuite_mod         115           Test_UnixProcess_mod         115           TestA_mod         116           TestCase_mod         116           TestCaseA_mod::TestCaseA         117           TestCaseA_mod         117           TestCaseB_mod::TestCaseB         118           TestCaseB_mod         118           TestCaseC_mod::TestCaseC         119           TestCaseC_mod         120           TestFailure_mod         28riefDescription>           Mods::pre::pre_lf::TestlfDirective         121           mods::pre::interleavedp::TestInterleaved         122           TestListener_mod

mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult mod
- StriefDescription Note: A possible extension point for user-
specialized TestResults
TestRunner_mod
<briefdescription></briefdescription>
TestSuite_mod
<briefdescription></briefdescription>
ThrowFundamentalTypes_mod
<briefdescription></briefdescription>
UnixPipeInterfaces_mod
<briefdescription></briefdescription>
UnixProcess_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::VECTOR_NORM
WrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WrapTestCaseC_mod

# **Data Type Documentation**

# 17.1 AbstractTestParameter\_mod Module Reference

**Data Types** 


- type AbstractTestParameter
- interface toString

The documentation for this module was generated from the following file:

AbstractTestParameter.F90

# 17.2 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



### **Public Member Functions**

· def apply

The documentation for this class was generated from the following file:

pFUnitParser.py

## 17.3 add\_mod Module Reference

### **Public Member Functions**

- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- · Robust/src/add.F90
- · Simple/src/add.F90

## 17.4 addComplex\_mod Module Reference

### **Public Member Functions**

complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following file:

· addComplex.F90

# 17.5 CodeUtilities::ArrayDescription Class Reference

### **Public Member Functions**

- def \_\_init\_\_
- def NAME
- def DECLARE
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

### **Public Attributes**

- fType
- kind
- rank

The documentation for this class was generated from the following file:

· CodeUtilities.py

## 17.6 Assert\_mod Module Reference

<BriefDescription>

## 17.6.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

### 17.7 AssertBasic mod Module Reference

<BriefDescription>

## **Data Types**

- · interface assertEqual
- interface assertExceptionRaised
- interface assertFalse
- · interface assertIsFinite
- interface assertIsNaN
- interface assertTrue
- interface fail
- type UnusableArgument

### **Public Member Functions**

- subroutine assertExceptionRaisedMessage (message)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- logical function, public nonConformable (shapeA, shapeB)

- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN double (x, message, location)
- subroutine assertIsFinite\_single (x, message, location)
- subroutine assertIsFinite\_double (x, message, location)

### 17.7.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertBasic.F90

## 17.8 AssertInteger\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

#### **Public Member Functions**

- subroutine assertEqualInteger1D1D\_ (expected, found, message, location)
- subroutine assertEqualInteger0D1D\_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D\_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D\_ (expected, found, message, location)
- subroutine assertLessThan\_ (a, b, message, location)

## 17.8.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

# 17.9 GenerateRealArrayNewSignature::AssertRealArrayArgument Class Reference

### **Public Member Functions**

- def \_\_init\_\_\_
- def updateDescriptions
- def getExpectedDescription
- def getFoundDescription
- def getTolerance

### **Public Attributes**


- expectedFType
- expectedPrecision
- expectedRank
- foundFType
- foundPrecision
- foundRank
- tolerance
- · expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

# 17.10 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.11 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



**Public Member Functions** 

- def \_\_init\_\_
- def match
- · def appendSourceLocation
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.12 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



### **Public Member Functions**

- def \_\_init\_\_
- def match
- · def action

### **Public Attributes**


### parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.13 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.14 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- def appendSourceLocation
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.15 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



### **Public Member Functions**

def \_\_init\_\_

#### **Public Attributes**


- parser
- keyword

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.16 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



#### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.17 pFUnitParser::AtTest Class Reference

 $Inheritance\ diagram\ for\ pFUnitParser:: AtTest:$ 



#### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

#### **Public Attributes**


- parser
- keyword

The documentation for this class was generated from the following file:

· pFUnitParser.py

# 17.18 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



- def \_\_init\_\_
- def match
- · def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.19 pFUnitParser::AtTestParameter Class Reference

Inheritance diagram for pFUnitParser::AtTestParameter:



#### **Public Member Functions**

- def init
- def match
- def action

#### **Public Attributes**

· parser

The documentation for this class was generated from the following file:

• pFUnitParser.py

# 17.20 TestCaseB\_mod::B\_Parameter Type Reference

- · procedure toString
- procedure toString

#### **Public Attributes**

- real phi
- · real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

# 17.21 BaseTestRunner\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

- type BaseTestRunner
- interface run2

#### **Public Member Functions**

• subroutine setDebug (this)

# 17.21.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

#### 17.22 BeforeAfter\_mod Module Reference

#### **Public Member Functions**

- subroutine first (this)
- subroutine last (this)
- · subroutine succeeds (this)
- subroutine fails (this)

#### **Public Attributes**

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

• Examples/MPI\_Halo/tests/beforeAfter.pf

# 17.23 BrokenSetUpCase\_mod Module Reference

# **Data Types**

• type BrokenSetUpCase

#### **Public Member Functions**

 $\bullet \ \ \mathsf{type}(\mathsf{BrokenSetUpCase}) \ \mathsf{function}, \ \ \mathsf{pointer}, \ \mathsf{public} \ \boldsymbol{\mathsf{newBrokenSetUpCase}} \ ()$ 

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

# 17.24 BrokenTestCase\_mod Module Reference

# **Data Types**

• type BrokenTestCase

#### **Public Member Functions**

• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

# 17.25 TestCaseC\_mod::C\_Parameter Type Reference

#### **Public Member Functions**

- · procedure toString
- procedure toString

#### **Public Attributes**

- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

# 17.26 Cases\_mod Module Reference

# **Data Types**

- type MyParamType
- type MyTestCase


- type(MyParamType) function newMyParam (i)
- type(MyTestCase) function newMyTestCase (param)
- subroutine test\_odd (this)
- subroutine test\_even (this)
- character(:) function, allocatable **toString** (this)

The documentation for this module was generated from the following file:

· Test\_Cases.pf

# 17.27 GenerateRealArrayNewSignature::constraintASSERTEQUA-L Class Reference

Inheritance diagram for GenerateRealArrayNewSignature::constraintASSERTEQUAL:



#### **Public Member Functions**

def init

This next line actually generates the text of the code.

#### **Public Attributes**

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

#### 17.27.1 Constructor & Destructor Documentation

```
17.27.1.1 def GenerateRealArrayNewSignature::constraintASSERTE-QUAL::__init__ ( self, expectedDescr, foundDescr, tolerance )
```

This next line actually generates the text of the code.

#### 17.27.2 Member Data Documentation

#### 17.27.2.1 GenerateRealArrayNewSignature::constraintASSERTEQUAL::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

#### 17.27.2.2 GenerateRealArrayNewSignature::constraintASSERTEQUAL::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

# 17.28 mods::pre::pre2::dataString Class Reference

- def \_\_init\_\_\_
- def insert
- def getLength
- · def getPosition
- · def setPosition
- · def getItem
- · def getDataAtPosition
- def getData
- · def getSlice
- · def getSliceForward
- · def removeSlice
- def getCurrentData
- def insertAtCurrent
- · def append
- def advanceAndGetNextData
- def validPosition
- def findToEnd
- · def match
- · def matchToEnd

- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

# **Public Attributes**

- data
- · position

The documentation for this class was generated from the following file:

• pre2.py

# 17.29 DebugListener\_mod Module Reference

<BriefDescription>

# **Data Types**

• interface DebugListener

#### **Public Member Functions**

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

# 17.29.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· DebugListener.F90

# 17.30 CodeUtilities::declaration Class Reference

**Public Member Functions** 

- def \_\_init\_\_\_
- · def generate

#### **Public Attributes**

- simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.31 DynamicTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface delete
- type DynamicTestCase
- · interface testmethod

#### **Public Member Functions**

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

# 17.31.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

# 17.32 Exception\_mod Module Reference

# **Data Types**

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- interface throw

# **Public Member Functions**

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public catchAny (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()
- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

#### 17.33 Fixture\_mod Module Reference

#### **Public Member Functions**

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following file:

· fixtureTests.pf

# 17.34 FixtureTestCase mod Module Reference

# **Data Types**

- · interface delete
- type FixtureTestCase

#### **Public Member Functions**

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

• FixtureTestCase.F90

# 17.35 CodeUtilities::fortranSubroutineSignature Class Reference

- def \_\_init\_\_\_
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

#### **Public Attributes**

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.36 Halo\_mod Module Reference

#### **Public Member Functions**


• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

# 17.37 mods::pre::pre\_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre\_lf::lfDirective:



#### **Public Member Functions**

· def evaluate

#### **Public Attributes**

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.38 CodeUtilities::implementation Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- · def generate

**Public Attributes** 

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.39 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.40 mods::pre::pre\_lf::interval Class Reference

- def \_\_init\_\_
- · def getInterval
- · def setInterval
- def getStart
- def getEnd

**Public Attributes** 


- start
- end
- · interval

The documentation for this class was generated from the following file:

• pre\_lf.py

# 17.41 GenerateRealArrayNewSignature::IsWithinTolerance Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::IsWithinTolerance:



**Public Member Functions** 

• def \_\_init\_\_

**Public Attributes** 

- rank
- · precision
- name
- fType
- declaration
- declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

# 17.42 Test\_RestrictSphericalCoordinates\_mod::LatLonCase Type - Reference

#### **Public Member Functions**

· procedure toString

#### **Public Attributes**

- real lat
- · real lon
- real restrictedLat
- · real restrictedLon

The documentation for this type was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

# 17.43 LinearInterpolator\_mod Module Reference

# **Data Types**

- interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

· LinearInterpolator.F90

# 17.44 MakeInfinity\_mod Module Reference

<BriefDescription>

- real(r32) function, public makeInf\_32 ()
- real(r64) function, public makeInf\_64 ()

# 17.44.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MakeInfinity.F90

# 17.45 MakeNaN\_mod Module Reference

<BriefDescription>

# **Public Member Functions**

- real(r32) function, public makeNaN\_32 ()
- real(r64) function, public makeNaN\_64 ()

# 17.45.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MakeNaN.F90

# 17.46 MockCall\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

· type MockCall

# **Public Member Functions**

• type(MockCall) function, public **newMockCall** (name)

#### 17.46.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MockCall.F90

# 17.47 MockListener\_mod Module Reference

# **Data Types**

• type MockListener

#### **Public Member Functions**


• subroutine **startTest** (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

# 17.48 testParser::MockParser Class Reference

Inheritance diagram for testParser::MockParser:



#### **Public Member Functions**

- def \_\_init\_\_
- def nextLine
- def reset

# **Public Attributes**

- saveLines
- lines
- outputFile
- outLines
- userTestCase
- userTestMethods
- · currentSelfObjectName

The documentation for this class was generated from the following file:

· testParser.py

# 17.49 MockRepository\_mod Module Reference

<BriefDescription>

# **Data Types**

• type MockRepository

#### **Public Member Functions**

- type(MockRepository) function, pointer, public newMockRepository ()
- · subroutine expectCall (this, obj, method)

# 17.49.1 Detailed Description

```
<\!\!\text{BriefDescription}\!\!>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MockRepository.F90

# 17.50 MockSUT mod Module Reference

# **Data Types**

• type MockSUT

#### **Public Member Functions**

- type(MockSUT) function, allocatable, public **newMockSUT** (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

# 17.51 testParser::MockWriter Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- def write

#### **Public Attributes**

parser

The documentation for this class was generated from the following file:

testParser.py

# 17.52 CodeUtilities::module Class Reference

- def \_\_init\_\_
- def generate
- def addDeclaration
- def addImplementation
- · def addRoutineUnit
- def addInterfaceBlock
- · def getName
- · def setFileName
- def getFileName

#### **Public Attributes**

- name
- · declarations
- · implementations
- generation
- fileName

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.53 MpiContext\_mod Module Reference

<BriefDescription>

# **Data Types**

- type MpiContext
- interface newMpiContext

#### **Public Member Functions**

- subroutine barrier (this)
- integer function getMpiCommunicator (this)

# 17.53.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MpiContext.F90

# 17.54 MpiStubs\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- subroutine, public MPI\_Comm\_rank (comm, rank, ier)
- subroutine, public MPI\_Comm\_size (comm, size, ier)
- subroutine, public MPI\_Comm\_dup (comm, newComm, ier)
- subroutine, public MPI\_Comm\_group (comm, group, ier)
- subroutine, public MPI\_Group\_range\_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI\_Comm\_create (comm, group, newComm, ier)

#### **Public Attributes**

- integer, parameter, public MPI\_COMM\_WORLD = -1
- integer, parameter, public MPI\_COMM\_NULL = -1
- integer, parameter, public MPI\_COMM\_SUCCESS = 0

#### 17.54.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MpiStubs.F90

# 17.55 MpiTestCase\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

type MpiTestCase

# **Public Member Functions**

- recursive subroutine runBare (this)
- integer function getMpiCommunicator (this)
- integer function getProcessRank (this)

# 17.55.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> <Or starting here...>
```

The documentation for this module was generated from the following file:

MpiTestCase.F90

# 17.56 MpiTestCaseB\_mod::MpiTestCaseB Type Reference

#### **Public Member Functions**

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

· integer componentl

The documentation for this type was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

# 17.57 MpiTestCaseB\_mod Module Reference

# **Data Types**

type MpiTestCaseB

### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- MpiTestCaseB.F90
- MpiTestCaseB.pf

# 17.58 MpiTestMethod\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

# 17.58.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

MpiTestMethod.F90

# 17.59 MpiTestParameter\_mod Module Reference

# **Data Types**

• type MpiTestParameter

# **Public Member Functions**

 type(MpiTestParameter) function, public newMpiTestParameter (num ProcessesRequested) The documentation for this module was generated from the following file:

• MpiTestParameter.F90

# 17.60 pFUnitParser::MyError Class Reference

Inherits Exception.

**Public Member Functions** 

- def \_\_init\_\_
- def \_\_str\_\_

#### **Public Attributes**

value

The documentation for this class was generated from the following file:

• pFUnitParser.py

# 17.61 Cases\_mod::MyParamType Type Reference

**Public Member Functions** 

procedure toString

#### **Public Attributes**

• integer i

The documentation for this type was generated from the following file:

• Test\_Cases.pf

# 17.62 Cases\_mod::MyTestCase Type Reference

#### **Public Attributes**

• integer i

The documentation for this type was generated from the following file:

· Test\_Cases.pf

# 17.63 TestCaseC\_mod::newC\_Parameter Interface Reference

#### **Public Member Functions**

- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)

The documentation for this interface was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

# 17.64 ParallelContext\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface allReduceLogical
- · interface gatherInteger
- · interface gatherLogical
- interface gatherString
- · interface getNumProcesses
- type ParallelContext
- · interface processRank
- · interface sum

# 17.64.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelContext.F90

# 17.65 ParallelException\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface any Exceptions
- interface getNumExceptions

#### **Public Member Functions**

• subroutine, public gather (context)

# 17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParallelException.F90

# 17.66 ParameterizedTestCase\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

• type ParameterizedTestCase

#### **Public Attributes**

• integer, parameter, public MAX\_LEN\_LABEL = 32

# 17.66.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParameterizedTestCase.F90

#### 17.67 Params\_mod Module Reference

<BriefDescription>

#### **Public Attributes**

- integer, parameter **R32** = selected\_real\_kind(p=6)
- integer, parameter R64 = selected\_real\_kind(p=14)
- integer, parameter **C32** = selected\_real\_kind(p=6)
- integer, parameter **C64** = selected\_real\_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

## 17.67.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Params.F90

# 17.68 pFUnitParser::Parser Class Reference

Inheritance diagram for pFUnitParser::Parser:



#### **Public Member Functions**

- def \_\_init\_\_
- def commentLine
- def run
- def isComment
- · def nextLine
- def printHeader
- def printTail
- def printWrapUserTestCase
- def printRunMethod
- def printParameterHeader
- def printMakeSuite
- def addSimpleTestMethod
- def addMpiTestMethod
- def addUserTestMethod
- def printMakeCustomTest
- def makeWrapperModule
- def final

#### **Public Attributes**

- fileName
- inputFile
- outputFile
- · defaultSuiteName
- suiteName
- · currentLineNumber
- userModuleName
- userTestCase
- userTestMethods

- wrapModuleName
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.69 Test\_Parameters\_mod::peCase Type Reference

**Public Member Functions** 

· procedure toString

#### **Public Attributes**

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

# 17.70 pFUnit Module Reference

<BriefDescription>

## **Public Member Functions**

• integer function run ()

# 17.70.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

# 17.71 pFUnit\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- subroutine, public initialize (useMpi)
- subroutine, public finalize (successful)

# 17.71.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

# 17.72 PrivateException\_mod Module Reference

<BriefDescription>

# **Data Types**

- type Exception
- type ExceptionList
- interface newException

#### **Public Member Functions**

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

# **Public Attributes**

- integer, parameter, public **MAXLEN\_MESSAGE** = 80\*15
- integer, parameter, public MAXLEN\_FILE\_NAME = 80
- character(len=\*), parameter, public **NULL\_MESSAGE** = "

# 17.72.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Exception.F90

# 17.73 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



#### **Public Member Functions**

- def init
- · def getLength
- · def match
- · def evaluate
- def getNewPosition
- · def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- · def finditerTokenToPosition
- def makeTokenErrorMessage

#### **Public Attributes**

- name
- newPosition
- · tokens
- TokenREs

#### 17.73.1 Member Function/Subroutine Documentation

```
17.73.1.1 def mods::pre::pre2::procDirective::addTokenRE( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = ''')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

pre2.py

# 17.74 RemoteProxyTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

• interface RemoteProxyTestCase

## 17.74.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

# 17.75 mods::pre::pre\_Repeat::RepeatDirective Class Reference

 $Inheritance\ diagram\ for\ mods::pre::pre\_Repeat::Repeat Directive:$ 



#### **Public Member Functions**

· def evaluate

#### **Public Attributes**

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_Repeat.py

#### 17.76 ResultPrinter mod Module Reference

<BriefDescription>

# **Data Types**

· type ResultPrinter

#### **Public Member Functions**

- type(ResultPrinter) function, public newResultPrinter (unit)
- subroutine addError (this, testName, exceptions)
- subroutine startTest (this, testName)
- subroutine printHeader (this, runTime)

#### 17.76.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

#### 17.77 RobustRunner\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface RobustRunner
- type TestCaseMonitor

#### **Public Member Functions**

- type(RobustRunner) function newRobustRunner\_unit (remoteRunCommand, unit)
- subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

# 17.77.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RobustRunner.F90

# 17.78 robustTestSuite\_mod Module Reference

#### **Public Member Functions**


- type(TestSuite) function, public suite ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

# 17.79 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



#### **Public Member Functions**

- def \_\_init\_\_\_
- def setName
- · def getName
- def setDeclaration
- def addDeclaration
- def setImplementation
- · def getDeclaration
- · def getDeclarations
- def getImplementation
- def clearDeclarations

#### **Public Attributes**

- name
- declaration
- · declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.80 SerialContext\_mod Module Reference

<BriefDescription>

# **Data Types**

· type SerialContext

#### **Public Member Functions**

• type(SerialContext) function, public newSerialContext ()

# **Public Attributes**

 type(SerialContext), parameter, public THE\_SERIAL\_CONTEXT = Serial-Context()

## 17.80.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

# 17.81 SimpleTestCase\_mod Module Reference

# **Data Types**

- · interface method
- type SimpleTestCase

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- · subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete\_ (this)

The documentation for this module was generated from the following file:

· SimpleTestCase.F90

# 17.82 SourceLocation mod Module Reference

<BriefDescription>

# **Data Types**

• type SourceLocation

#### **Public Attributes**

- character(len=MAXLEN\_FILE\_NAME), parameter, public UNKNOWN\_FILE\_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN\_LINE\_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN\_SOURCE\_LOCATION = SourceLocation()

# 17.82.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

# 17.83 SphericalCoordinates\_mod Module Reference

# **Data Types**

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

# 17.84 TestListener\_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

# 17.85 StringConversionUtilities\_mod Module Reference

<BriefDescription>

# **Data Types**

· interface toString

#### **Public Member Functions**

- character(len=len\_trim(a)+1+len\_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)

#### **Public Attributes**

• integer, parameter, public MAXLEN\_STRING = 80

#### 17.85.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

# 17.86 SubsetRunner\_mod Module Reference

<BriefDescription>

# **Data Types**

· interface SubsetRunner

#### **Public Member Functions**

- subroutine addFailure (this, testName, exceptions)
- subroutine **startTest** (this, testName)

#### 17.86.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SubsetRunner.F90

# 17.87 SurrogateTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

#### 17.87.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

# 17.88 SUT\_mod Module Reference

**Data Types** 

• type SUT

The documentation for this module was generated from the following file:

Test\_MockRepository.F90

# 17.89 Test\_Assert\_mod Module Reference

**Public Member Functions** 

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test\_Assert.F90

#### 17.90 Test AssertBasic mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()

The documentation for this module was generated from the following file:

Test AssertBasic.F90

# 17.91 Test\_AssertComplex\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testEquals C complexScalar ()
- subroutine testEquals C 0D1D ()
- subroutine testEquals\_C\_1D\_nonConformable1 ()
- subroutine testEquals C 2D SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent1
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent2
- subroutine testEquals C MultiD SingleElementDifferent3
- subroutine testEquals C MultiD SingleElementDifferent4
- subroutine testEquals C MultiD SingleElementDifferent5
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff1 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff5 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff6 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals C MultiDWithTolerance ()
- subroutine testEquals\_C\_MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals\_C\_MultiDWithTolerance64\_1 ()

- subroutine testEquals C MultiDWithTolerance64 2 ()
- subroutine testEquals\_C\_MultiDSourceLocation ()
- subroutine testEquals\_4DPComplex\_DifferenceReport ()
- · subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

Test\_AssertComplex.F90

# 17.92 Test\_AssertInteger\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertEqual equal ()

The documentation for this module was generated from the following file:

Test AssertInteger.F90

## 17.93 Test\_AssertReal\_mod Module Reference

## **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testEquals\_0D1D ()
- subroutine testEquals\_1D\_nonConformable1 ()
- subroutine testEquals 2D SingleElementDifferent ()
- subroutine testEquals\_MultiD\_SingleElementDifferent ()
- subroutine testEquals\_MultiD\_SingleElementDifferent1
- subroutine testEquals\_MultiD\_SingleElementDifferent2
- subroutine testEquals\_MultiD\_SingleElementDifferent3
- subroutine testEquals\_MultiD\_SingleElementDifferent4
- subroutine testEquals\_MultiD\_SingleElementDifferent5
   subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff()
- subroutine testEquals MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff5 ()

- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff7 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff8 ()
- subroutine testEquals\_ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals\_VectorWithToleranceNoMsg ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals MultiDWithTolerance1 ()
- subroutine testEquals MultiDWithTolerance64 ()
- subroutine testEquals\_MultiDWithTolerance64\_1 ()
- subroutine testEquals MultiDWithTolerance64 2 ()
- subroutine testEquals\_MultiDSourceLocation ()
- subroutine testEquals\_ScalarAndLocation ()
- subroutine testEquals\_ScalarInfinity\_equal ()
- subroutine testEquals ScalarInfinity unequal A ()
- subroutine testEquals\_ScalarInfinity\_unequal\_B ()
- subroutine testEquals\_ScalarInfinity\_unequal\_C ()
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

• Test AssertReal.F90

# 17.94 Test\_BasicOpenMP\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()
- subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

Test BasicOpenMP.F90

# 17.95 Test\_Exception\_mod Module Reference

#### **Public Member Functions**

• type(TestSuite) function, public suite ()

- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

The documentation for this module was generated from the following file:

• Test Exception.F90

# 17.96 Test\_FixtureTestCase\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

Test\_FixtureTestCase.F90

# 17.97 Test\_LinearInterpolator\_mod::Test\_LinearInterpolator Type - Reference

**Public Member Functions** 

- · procedure setUp
- · procedure tearDown

#### **Public Attributes**

• type(LinearInterpolator) interpolator

The documentation for this type was generated from the following file:

• Test\_LinearInterpolator.pf

# 17.98 Test\_LinearInterpolator\_mod Module Reference

#### **Data Types**

• type Test\_LinearInterpolator

#### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

Test\_LinearInterpolator.pf

#### 17.99 Test MockCall mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

• Test MockCall.F90

# 17.100 Test\_MockRepository\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

# 17.101 Test\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface countTestCases
- interface run
- type Test

# 17.101.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

# 17.102 Test\_MpiContext\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

Test\_MpiContext.F90

# 17.103 Test\_MpiException\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine test\_anyExceptions\_none (this)
- subroutine test getNumExceptions (this)
- subroutine test\_gather (this)

The documentation for this module was generated from the following file:

• Test\_MpiException.F90

# 17.104 Test\_MpiTestCase\_mod Module Reference

# **Data Types**

- · interface method
- type Test\_MpiTestCase

## **Public Member Functions**

- type(TestSuite) function, public **suite** ()
- type(Test\_MpiTestCase) function, public newTest\_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

Test\_MpiTestCase.F90

# 17.105 Test\_Parameters\_mod::Test\_Parameters Type Reference

#### **Public Attributes**

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

#### 17.106 Test Parameters mod Module Reference

# **Data Types**

- type peCase
- type Test\_Parameters

#### **Public Member Functions**

- type(Test\_Parameters) function newTest (testParameter)
- type(peCase) function newPeCase (p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()
- character(:) function, allocatable toString (this)
- subroutine testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

# 17.107 Test\_RestrictSphericalCoordinates\_mod::Test\_Restrict-SphericalCoordinates Type Reference

#### **Public Attributes**

- real lat
- real lon
- real restrictedLat
- · real restrictedLon

- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted

The documentation for this type was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

# 17.108 Test\_RestrictSphericalCoordinates\_mod Module Reference

# **Data Types**

- type LatLonCase
- type Test RestrictSphericalCoordinates

#### **Public Member Functions**

- type(Test\_RestrictSphericalCoordinates) function newTest (testParameter)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test\_RestrictedSphericalCoordinates.pf

# 17.109 Test RobustRunner mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

Test\_RobustRunner.F90

# 17.110 Test\_SimpleTestCase\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()
- subroutine testRunMethodShouldFail ()

The documentation for this module was generated from the following file:

• Test\_SimpleTestCase.F90

# 17.111 Test\_StringConversionUtilities\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test\_StringConversionUtilities.F90

## 17.112 Test TestMethod mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

Test\_TestMethod.F90

#### 17.113 Test\_TestResult\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

· Test TestResult.F90

#### 17.114 Test TestSuite mod Module Reference

# **Data Types**

• type Verbose

#### **Public Member Functions**

- type(TestSuite) function, public **suite** ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()
- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

The documentation for this module was generated from the following file:

• Test TestSuite.F90

# 17.115 Test\_UnixProcess\_mod Module Reference

#### **Public Member Functions**

• type(TestSuite) function, public suite ()

• subroutine testIsActive ()

The documentation for this module was generated from the following file:

• Test\_UnixProcess.F90

# 17.116 TestA\_mod Module Reference

#### **Public Member Functions**

- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)
- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)

The documentation for this module was generated from the following files:

- TestA.F90
- TestA.pf

# 17.117 TestCase\_mod Module Reference

<BriefDescription>

#### **Data Types**

- type ConcreteSurrogate
- type TestCase
- type TestCaseReference

# **Public Member Functions**

- recursive subroutine runBare (this)
- recursive subroutine runBare\_surrogate (this)

# 17.117.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestCase.F90

# 17.118 TestCaseA\_mod::TestCaseA Type Reference

**Public Member Functions** 

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

• integer componentI

The documentation for this type was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

# 17.119 TestCaseA\_mod Module Reference

# **Data Types**

• type TestCaseA

#### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

# 17.120 TestCaseB\_mod::TestCaseB Type Reference

#### **Public Member Functions**

- procedure setUp
- · procedure tearDown
- procedure setUp
- · procedure tearDown

# **Public Attributes**

- integer, dimension(:), allocatable table
- · real phi
- · real theta

The documentation for this type was generated from the following files:

- · ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

# 17.121 TestCaseB\_mod Module Reference

# **Data Types**

- type B\_Parameter
- type TestCaseB

#### **Public Member Functions**

- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine **testB** (this)
- · character(:) function, allocatable toString (this)
- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- · ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

# 17.122 TestCaseC\_mod::TestCaseC Type Reference

## **Public Member Functions**

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

- integer, dimension(:), allocatable table
- · real phi
- real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- MpiParameterizedTestCaseC.pf

#### 17.123 TestCaseC\_mod Module Reference

#### **Data Types**

- type C\_Parameter
- interface newC Parameter
- type TestCaseC

#### **Public Member Functions**

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C\_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)
- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C\_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

# 17.124 TestFailure mod Module Reference

<BriefDescription>

# **Data Types**

type TestFailure

# 17.124.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

# 17.125 mods::pre::pre\_lf::TestlfDirective Class Reference

**Public Member Functions** 

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse
- def testIFTestTrue1
- def testIFTestTrue2
- def testIFClearTokens
- · def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.126 mods::pre::interleavedp::TestInterleaved Class Reference

# **Public Member Functions**

- def test\_InOrder
- · def test NumberMismatch
- def test\_OrderMismatch1
- def test\_OrderMismatch2
- def test\_OrderMismatch3
- def test ElseMid1
- · def test\_ElseMid2
- def test\_ElseMid3
- def test\_ElseMid4
- def test\_ElseMid5
- def test ElseMid6
- def test\_ElseMid7
- def test\_ElseMid8
- def test\_ElseMid9
- def test ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

# 17.127 TestListener mod Module Reference

<BriefDescription>

# **Data Types**

- · interface addFailure
- interface endTest
- type ListenerPointer
- interface startTest
- type TestListener

# 17.127.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestListener.F90

# 17.128 TestMethod\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface empty
- interface newTestMethod
- type TestMethod

# 17.128.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

# 17.129 mods::pre::parseArgs::TestParseArgs Class Reference

#### **Public Member Functions**

- · def test\_ParseArgs\_OneArgWithBrackets1
- · def test ParseArgs OneArgWithBrackets2
- def test\_ParseArgs\_OneArgWithBrackets3
- def test\_ParseArgs\_OneArgWithBrackets4
- def test ParseArgs OneArgWithBrackets5
- def test\_ParseArgs\_OneArgWithBrackets6
- def test\_ParseArgs\_OneArgWithBrackets7
- def test\_ParseArgs\_oneArg
- def test\_ParseArgs\_twoArgs1
- def test\_ParseArgs\_twoArgs2
- · def test ParseArgs oneArgArray1
- def test\_ParseArgs\_TwoArgArray
- def test\_ParseArgs\_ThreeArgs

The documentation for this class was generated from the following file:

· parseArgs.py

#### 17.130 testParser::TestParseLine Class Reference

#### **Public Member Functions**

- def testCppSetLineAndFile
- · def testGetSubroutineName
- · def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtTestNoParens
- def testAtTestFail

- def testAtTestSkipComment
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- · def testMatchAtAssertOther
- def testMatchAtMpiAssert
- · def testMatchAtBefore
- · def testMatchAtAfter
- def testMatchAtSuite

#### 17.130.1 Member Function/Subroutine Documentation

#### 17.130.1.1 def testParser::TestParseLine::testAtMpiTest( self )

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

#### 17.130.1.2 def testParser::TestParseLine::testAtTest( self )

Check that a line starting with ' $\mbox{@test'}$  is detected as an annotation.

#### 17.130.1.3 def testParser::TestParseLine::testAtTestFail ( self )

Check that useful error is sent if next line is not properly formatted.

#### 17.130.1.4 def testParser::TestParseLine::testAtTestNoParens ( self )

Check that test procedure with no parens is accepted.

## 17.130.1.5 def testParser::TestParseLine::testAtTestSkipComment ( self )

Ignore comment lines between @test and subroutine foo().

#### 17.130.1.6 def testParser::TestParseLine::testMatchAtAfter( self)

Check that a line starting with '@after\*' ...

#### 17.130.1.7 def testParser::TestParseLine::testMatchAtAssertEqual ( self )

Check that a line starting with '@assertEqual' is detected as an annotation.

#### 17.130.1.8 def testParser::TestParseLine::testMatchAtAssertOther( self)

Check that a line starting with '@assert\*' is detected as an annotation.

#### 17.130.1.9 def testParser::TestParseLine::testMatchAtBefore ( self )

Check that a line starting with '@before\*' ...

#### 17.130.1.10 def testParser::TestParseLine::testMatchAtMpiAssert ( self )

Check that a line starting with '@mpiAssert\*' is detected as an annotation.

#### 17.130.1.11 def testParser::TestParseLine::testMatchAtSuite ( self )

Check that a line starting with '@suite changes the suite name ...

#### 17.130.1.12 def testParser::TestParseLine::testMatchAtTestCase ( self )

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

· testParser.py

# 17.131 mods::pre::pre\_Repeat::TestRepeatDirective Class Reference

#### **Public Member Functions**

- def test\_copyBlock1
- def test\_copyBlock2

- · def test\_copyBlock2Vars
- · def test\_copyBlock2VarsMulti
- def test\_copyBlock2VarsMultiWithStrings
- def test\_copyNaiveRecursion
- def test\_copyNaiveRecursion1
- def test\_copyFunction1

The documentation for this class was generated from the following file:

• pre\_Repeat.py

## 17.132 TestResult\_mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

# **Data Types**

• type TestResult

#### **Public Member Functions**

- type(TestResult) function, public **newTestResult** ()
- subroutine addError (this, aTest, exceptions)
- integer function failureCount (this)
- subroutine addListener (this, listener)

#### 17.132.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestResult.F90

# 17.133 TestRunner\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

- interface newTestRunner
- type TestRunner

# **Public Member Functions**

- type(TestRunner) function **newTestRunner\_unit** (unit)
- type(TestResult) function run (this, aTest, context)
- subroutine startTest (this, testName)

# 17.133.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestRunner.F90

#### 17.134 TestSuite mod Module Reference

<BriefDescription>

# **Data Types**

- interface newTestSuite
- type TestReference
- type TestSuite

#### **Public Member Functions**

• recursive subroutine addTest (this, aTest)

# 17.134.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestSuite.F90

# 17.135 ThrowFundamentalTypes\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface throwDifferentValues
- interface throwDifferentValuesWithLocation

#### **Public Member Functions**

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN\_SHAPE) function, public locationFormat (iLocation)

## 17.135.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

# 17.136 UnixPipeInterfaces\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface fgets
- · interface free
- · interface getdelim
- · interface getline
- · interface pclose
- · interface popen

#### **Public Attributes**

• integer(C\_INT), parameter, public **CLOSE\_FAILED** = -1

# 17.136.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· UnixPipeInterfaces.F90

#### 17.137 UnixProcess mod Module Reference

<BriefDescription>

## **Data Types**

• interface UnixProcess

## **Public Member Functions**

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

# 17.137.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· UnixProcess.F90

# 17.138 GenerateRealArrayNewSignature::VECTOR\_NORM Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::VECTOR\_NORM:



**Public Member Functions** 

• def \_\_init\_\_

**Public Attributes** 

- rank
- fType
- precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

# 17.139 WrapbeforeAfter Module Reference

The documentation for this module was generated from the following file:

· beforeAfter.F90

# 17.140 WrapMpiTestCaseB\_mod Module Reference

# **Data Types**

- interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, npesRequested)

The documentation for this module was generated from the following file:

· MpiTestCaseB.F90

# 17.141 Wrapsimple Module Reference

The documentation for this module was generated from the following file:

• simple.F90

# 17.142 WrapTestA\_mod Module Reference

The documentation for this module was generated from the following file:

· TestA.F90

# 17.143 WrapTestCaseA\_mod Module Reference

#### **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- · subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod)

The documentation for this module was generated from the following file:

TestCaseA.F90

# 17.144 WrapTestCaseB\_mod Module Reference

# **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter)

The documentation for this module was generated from the following file:

• ParameterizedTestCaseB.F90

# 17.145 WrapTestCaseC\_mod Module Reference

#### **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

# **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter, npesRequested)

The documentation for this module was generated from the following file:

• MpiParameterizedTestCaseC.F90