pFUnit

Generated by Doxygen 1.7.6

Thu Feb 13 2014 22:24:01

Contents

1	pFU	nit 2 - Documentation - Version 0.0 (2014-0206-0848 MLR)	1
	1.1	Overview	1
	1.2	Contents	1
	1.3	See Also	2
	1.4	LICENSE	2
	1.5	Copyright	2
2	Obta	nining pFUnit	3
3	Insta	allation	5
	3.1	Installing pFUnit	5
	3.2	Prerequisites	5
	3.3	Obtaining pFUnit	6
	3.4	Manifest - What's in the directory?	6
	3.5	Configuration	7
	3.6	Building pFUnit	8
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8
		3.6.3 OPENMP	9
		3.6.4 Cleaning	9
		3.6.5 Documentation	9
		3.6.6 CMAKE	10
	27	Installation	10

	3.7.1	Installation - Serial	10
	3.7.2	Installation - MPI	10
	3.7.3	Installation - OPENMP	11
	3.7.4	Installation - DEFAULT DIRECTORY	11
Usag	je		13
4.1	Usage		13
	4.1.1	Usage - Configuration	13
	4.1.2	Usage - Hello World	13
4.2	Usage	- Preprocessor	14
4.3	_		
	4.3.1		
	4.3.2	Command Line Options	
		·	
Deve	elopmer	nt en	17
Feed	lback &	Support	19
6.1	Feedba	ack	19
6.2	Suppor	t	19
FAQ	and Tip	os	21
7.1	FAQ .		21
	7.1.1	Zero Tests Run	21
	7.1.2	Some Tests Are Not Running	21
7.2	Tips .		22
	7.2.1	Environment Modules	22
	7.2.2	Compile Time Errors	22
	7.2.3	Intermediate files used by pFUnit	22
Plati	orm Sp	ecific Notes	23
8.1	Mac O	sx	23
8.2	Windov	ws/CYGWIN	23
Ackı	nowledg	iments	25
	4.1 4.2 4.3 Deve 6.1 6.2 FAQ 7.1 7.2 Platt 8.1 8.2	3.7.2 3.7.3 3.7.4 Usage 4.1 Usage 4.1.1 4.1.2 4.2 Usage 4.3 Compil 4.3.1 4.3.2 Developmer Feedback & 6.1 Feedback & 6.2 Support FAQ and Tip 7.1 FAQ 7.1.1 7.1.2 7.2 Tips 7.2.1 7.2.2 7.2.3 Platform Sp 8.1 Mac Of 8.2 Window	3.7.2 Installation - MPI 3.7.3 Installation - OPENMP 3.7.4 Installation - DEFAULT DIRECTORY Usage 4.1 Usage 4.1.1 Usage - 4.1.2 Usage - Hello World 4.2 Usage - Preprocessor 4.3 Compiling and Executing The Test 4.3.1 - Compiling and Executing the Tests (MPI PARALLEL) 4.3.2 Command Line Options Development Feedback & Support 6.1 Feedback 6.2 Support FAQ and Tips 7.1 FAQ 7.1.1 Zero Tests Run 7.1.2 Some Tests Are Not Running 7.2 Tips 7.2.1 Environment Modules 7.2.2 Compile Time Errors 7.2.3 Intermediate files used by pFUnit Platform Specific Notes 8.1 Mac OSX

CONTENTS iii

10	10 Known Installations & Versions	27
11	11 TODO	29
12	12 The Preprocessor - pFUnitParser	31
	12.1 Using The Preprocessor	 31
	12.1.1 Configuration - testSuites.inc	 32
	12.1.2 Invocation	 32
	12.1.3 Preprocessor Input File (.pf)	 32
	12.1.4 Directives	 33
	12.1.4.1 @Test	 33
	12.1.4.2 @MPITest	 33
	12.1.4.3 @Assert	 34
	12.1.4.4 @Parameters	 35
	12.1.4.5 @TestCase	 35
40	40 CA	
13	13 @Assert Preprocessor Directives	37
	13.1 @Assert Preprocessor Directives	38
	13.1.1 @assertEqual	38
	13.1.2 @assertTrue	38
	13.1.3 @assertFalse	38
	13.1.4 @assertLessThan	38
	13.1.5 @assertLessThanOrEqual	
	13.1.6 @assertGreaterThan	
	13.1.7 @assertGreaterThanOrEqual	 38
	13.1.8 @assertIsMemberOf	 38
	13.1.9 @assertContains	 38
	13.1.10 @assertAny	 38
	13.1.11 @assertAll	 38
	13.1.12@assertNotAll	 38
	13.1.13 @assertNone	 38
	13.1.14 @assertIsPermutationOf	 38

V	CONTENTS
	~~

	13.1.15 @assertExceptionRaised	38
	13.1.16 @assertSameShape	38
	13.1.17 @assertIsNaN	38
	13.1.18 @assertIsFinite	38
11	Revision Notes	39
14	nevision notes	33
15	Data Type Index	41
	15.1 Class Hierarchy	41
10	Data Time Index	45
10	Data Type Index	45
	16.1 Data Types List	45
17	Data Type Documentation	51
	17.1 AbstractTestParameter_mod Module Reference	51
	17.2 pFUnitParser::Action Class Reference	51
	17.3 add_mod Module Reference	52
	17.4 addComplex_mod Module Reference	53
	17.5 CodeUtilities::ArrayDescription Class Reference	53
	17.6 Assert_mod Module Reference	53
	17.6.1 Detailed Description	54
	17.7 AssertBasic_mod Module Reference	54
	17.7.1 Detailed Description	55
	17.8 AssertInteger_mod Module Reference	55
	17.8.1 Detailed Description	56
	17.9 GenerateRealArrayNewSignature::AssertRealArrayArgument Class -	
	Reference	
	17.10pFUnitParser::AtAfter Class Reference	
	17.11pFUnitParser::AtAssert Class Reference	
	17.12pFUnitParser::AtBefore Class Reference	
	17.13pFUnitParser::AtBegin Class Reference	
	17.14pFUnitParser::AtMpiAssert Class Reference	
	17.15pFUnitParser::AtMpiTest Class Reference	60

CONTENTS v

17.16pFUnitParser::AtSuite Class Reference 61	1
17.17pFUnitParser::AtTest Class Reference 61	1
17.18pFUnitParser::AtTestCase Class Reference	2
17.19pFUnitParser::AtTestParameter Class Reference 63	3
17.20TestCaseB_mod::B_Parameter Type Reference 63	3
17.21BaseTestRunner_mod Module Reference	1
17.21.1 Detailed Description	1
17.22BeforeAfter_mod Module Reference	5
17.23BrokenSetUpCase_mod Module Reference 65	5
17.24BrokenTestCase_mod Module Reference 65	5
17.25TestCaseC_mod::C_Parameter Type Reference	3
17.26Cases_mod Module Reference	3
17.27GenerateRealArrayNewSignature::constraintASSERTEQUAL Class Reference	7
17.27.1 Constructor & Destructor Documentation 67	7
17.27.1.1init	7
17.27.2 Member Data Documentation	3
17.27.2.1 name1	3
17.27.2.2 tolerance	3
17.28mods::pre::pre2::dataString Class Reference	3
17.29DebugListener_mod Module Reference 69	9
17.29.1 Detailed Description	9
17.30CodeUtilities::declaration Class Reference)
17.31DynamicTestCase_mod Module Reference)
17.31.1 Detailed Description	1
17.32Exception_mod Module Reference	1
17.33Fixture_mod Module Reference	2
17.34FixtureTestCase_mod Module Reference	2
17.35CodeUtilities::fortranSubroutineSignature Class Reference	2
17.36Halo_mod Module Reference	3
17.37mods::pre_ipre_If::IfDirective Class Reference	3

vi CONTENTS

17.38CodeUtilities::implementation Class Reference
17.39CodeUtilities::interfaceBlock Class Reference
17.40mods::pre::pre_lf::interval Class Reference
17.41 GenerateRealArrayNewSignature::lsWithinTolerance Class Reference . 75
17.42Test_RestrictSphericalCoordinates_mod::LatLonCase Type Reference . 76
17.43LinearInterpolator_mod Module Reference
17.44MakeInfinity_mod Module Reference
17.44.1 Detailed Description
17.45MakeNaN_mod Module Reference
17.45.1 Detailed Description
17.46MockCall_mod Module Reference
17.46.1 Detailed Description
17.47MockListener_mod Module Reference
17.48testParser::MockParser Class Reference
17.49MockRepository_mod Module Reference
17.49.1 Detailed Description
17.50MockSUT_mod Module Reference
17.51testParser::MockWriter Class Reference
17.52CodeUtilities::module Class Reference
17.53MpiContext_mod Module Reference
17.53.1 Detailed Description
17.54MpiStubs_mod Module Reference
17.54.1 Detailed Description
17.55MpiTestCase_mod Module Reference
17.55.1 Detailed Description
17.56MpiTestCaseB_mod::MpiTestCaseB Type Reference
17.57MpiTestCaseB_mod Module Reference
17.58MpiTestMethod_mod Module Reference
17.58.1 Detailed Description
17.59MpiTestParameter_mod Module Reference
17.60pFUnitParser::MyError Class Reference

CONTENTS vii

17.61Cases_mod::MyParamType Type Reference
17.62Cases_mod::MyTestCase Type Reference
17.63TestCaseC_mod::newC_Parameter Interface Reference
17.64ParallelContext_mod Module Reference
17.64.1 Detailed Description
17.65ParallelException_mod Module Reference 89
17.65.1 Detailed Description
17.66ParameterizedTestCase_mod Module Reference
17.66.1 Detailed Description
17.67Params_mod Module Reference
17.67.1 Detailed Description
17.68pFUnitParser::Parser Class Reference
17.69Test_Parameters_mod::peCase Type Reference
17.70pFUnit Module Reference
17.70.1 Detailed Description
17.71pFUnit_mod Module Reference
17.71.1 Detailed Description
17.72PrivateException_mod Module Reference
17.72.1 Detailed Description
17.73mods::pre::pre2::procDirective Class Reference
17.73.1 Member Function/Subroutine Documentation 96
17.73.1.1 addTokenRE
17.74RemoteProxyTestCase_mod Module Reference
17.74.1 Detailed Description
17.75mods::pre::pre_Repeat::RepeatDirective Class Reference
17.76ResultPrinter_mod Module Reference
17.76.1 Detailed Description
17.77RobustRunner_mod Module Reference
17.77.1 Detailed Description
17.78robustTestSuite_mod Module Reference
17.79CodeUtilities::routineUnit Class Reference

viii CONTENTS

17.80 SerialContext_mod Module Reference
17.80.1 Detailed Description
17.81 SimpleTestCase_mod Module Reference
17.82SourceLocation_mod Module Reference
17.82.1 Detailed Description
17.83SphericalCoordinates_mod Module Reference
17.84TestListener_mod::startTest Interface Reference
17.85StringConversionUtilities_mod Module Reference
17.85.1 Detailed Description
17.86SubsetRunner_mod Module Reference
17.86.1 Detailed Description
17.87SurrogateTestCase_mod Module Reference
17.87.1 Detailed Description
17.88SUT_mod Module Reference
17.89Test_Assert_mod Module Reference
17.90Test_AssertBasic_mod Module Reference
17.91Test_AssertComplex_mod Module Reference
17.92Test_AssertInteger_mod Module Reference
17.93Test_AssertReal_mod Module Reference
17.94Test_BasicOpenMP_mod Module Reference
17.95Test_Exception_mod Module Reference
17.96Test_FixtureTestCase_mod Module Reference
17.97Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 110
17.98Test_LinearInterpolator_mod Module Reference
17.99Test_MockCall_mod Module Reference
17.100 Sest_MockRepository_mod Module Reference
17.10 Test_mod Module Reference
17.101. Detailed Description
17.10 Test_MpiContext_mod Module Reference
17.103est_MpiException_mod Module Reference
17.104est_MpiParameterizedTestCase_mod Module Reference

CONTENTS ix

17.105est_MpiTestCase_mod Module Reference
17.10 6 est_Parameters_mod::Test_Parameters Type Reference
17.107est_Parameters_mod Module Reference
17.10 8 est_RestrictSphericalCoordinates_mod::Test_RestrictSpherical-Coordinates Type Reference
17.10¶est_RestrictSphericalCoordinates_mod Module Reference
17.11 0 est_RobustRunner_mod Module Reference
17.11 T est_SimpleTestCase_mod Module Reference
17.11 Z est_StringConversionUtilities_mod Module Reference
17.11 3 est_TestMethod_mod Module Reference
17.114est_TestResult_mod Module Reference
17.115est_TestSuite_mod Module Reference
17.11 6 est_UnixProcess_mod Module Reference
17.117estA_mod Module Reference
17.118estCase_mod Module Reference
17.118. Detailed Description
17.11 9 estCaseA_mod::TestCaseA Type Reference
17.12 0 estCaseA_mod Module Reference
17.12TestCaseB_mod::TestCaseB Type Reference
17.12 T estCaseB_mod Module Reference
17.12 3 estCaseC_mod::TestCaseC Type Reference
17.124estCaseC_mod Module Reference
17.125estFailure_mod Module Reference
17.125. Detailed Description
17.12@nods::pre::pre_lf::TestIfDirective Class Reference
17.12 mods::pre::interleavedp::TestInterleaved Class Reference
17.128estListener_mod Module Reference
17.128. Detailed Description
17.12¶estMethod_mod Module Reference
17.129. Detailed Description
17.13@nods::pre::parseArgs::TestParseArgs Class Reference

X CONTENTS

17.13 lestParser::TestParseLine Class Reference
17.131. Member Function/Subroutine Documentation
17.131.1.1testAtMpiTest
17.131.1.2testAtTest
17.131.1.3testAtTestFail
17.131.1.4testAtTestNoParens
17.131.1.5testAtTestSkipComment
17.131.1.6testMatchAtAfter
17.131.1.7testMatchAtAssertEqual
17.131.1.8testMatchAtAssertOther
17.131.1.9testMatchAtBefore
17.131.1.1testMatchAtMpiAssert
17.131.1.1testMatchAtSuite
17.131.1.1testMatchAtTestCase
17.132hods::pre::pre_Repeat::TestRepeatDirective Class Reference 129
17.13 3 estResult_mod Module Reference
17.133. Detailed Description
17.134estRunner_mod Module Reference
17.134. Detailed Description
17.135estSuite_mod Module Reference
17.135. Detailed Description
17.136 hrowFundamental Types_mod Module Reference
17.136. Detailed Description
17.13 DnixPipeInterfaces_mod Module Reference
17.137. Detailed Description
17.138JnixProcess_mod Module Reference
17.138. Detailed Description
17.13&enerateRealArrayNewSignature::VECTOR_NORM Class Reference . 134
17.14@VrapbeforeAfter Module Reference
17.14WrapMpiTestCaseB_mod Module Reference
17.14 Nrapsimple Module Reference

CONTENTS	XI

17.14\surapTestA_mod Module Reference							. 136
17.144WrapTestCaseA_mod Module Referen	nce .						. 136
17.145WrapTestCaseB_mod Module Referen	nce .						. 136
17.146VrapTestCaseC_mod Module Referen	nce .						. 137

pFUnit 2 - Documentation - Version 0.0 (2014-0206-0848 MLR)

Quick link to the code!

1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

1.2 Contents

- Installation
 - Obtaining pFUnit
- Usage

- Development
- · Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

1.4 LICENSE

Rights of use for GSC-15,137-1 F-UNIT, also known as pFUnit, are defined by the N-ASA Open Source Agreement (version 1.3). The LICENSE document may be found in the head directory of the pFUnit distribution.

1.5 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

Installation

3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
 - Building pFUnit for testing serial codes (Non-MPI)
 - Building pFUnit for testing parallel codes (MPI)
 - OPENMP
 - Cleaning
 - Documentation
- Installation

3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.3, 4.9.0, IBM's XLF)
- The Message Passing Interface (MPI)
- OpenMP
- · GNU Make
- Python

Note: Recent changes have exposed a latent bug in GCC 4.8.2. The fix is available in the GCC 4.9 development branch and will also appear in GCC 4.8.3 when that is released. Users that require older versions of GCC should use pFUnit 2.1.x.

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

3.5 Configuration 7

CMakeLists.txt - Initial support for cmake-based builds.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

GNUmakefile - The top level makefile for building and installing pFUnit.

LICENSE - The NASA Open Source Agreement for GSC-15,137-1 F-UNIT, also known as pFUnit.

README-INSTALL - Basic documentation on pFUnit installation and use.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

8 Installation

```
$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen
```

3.6 Building pFUnit

3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (for example in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

3.6.3 OPENMP

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

```
$ make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src_clean' to remove intermediate products in subdirectories.

3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following from the top level of your pFUnit distribution.

Or to make a reference manual.

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

10 Installation

3.6.6 **CMAKE**

Initial support for CMAKE has been implemented. At this writing, a basic functionality is available.

3. The process for building pFUnit using cmake is as follows. In the top directory of the distribution make a new directory to support the build, then change to that directory and run cmake (pointing back to the source) to generate the required makefiles.

```
$ mkdir build
$ cd build
$ # e.g. cmake -DMPI=YES -DOPENMP=NO -DINSTALL_PATH=<A path> <path to source>
$ cmake -DMPI=NO ..
$ make tests
```

One may also set the environment variable PFUNIT instead of setting INSTALL_PATH on the cmake command line as given above.

4. If the build is successful, then at this point make install should work.

3.7 Installation

3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ cd Examples
$ ./buildIt
```

3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

3.7 Installation 11

To test, set PFUNIT and go into Examples/MPI_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

12 Installation

Usage

- Usage Configuration
- Usage Hello World
- Usage Preprocessor
- · Compiling and Executing The Test

4.1 Usage

4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
```

14 Usage

```
subroutine testHelloWorld()
  use pfunit_mod
  implicit none
  @assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

4.2 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

4.3 Compiling and Executing The Test

An example of a GNU make rule for for the final step of compiling a test follows.

To execute the tests, one invokes "./tests.x" with the appropriate command line options (see below).

4.3.1 - Compiling and Executing the Tests (MPI PARALLEL)

One invokes MPI-based parallel tests according to the MPI framework being used. For example:

```
$ mpirun -np 4 tests.x
```

4.3.2 Command Line Options

The executable test program provides several command line options, when "include/driver.F90" is used, as it is automatically when using the PFUNIT preprocessor.

-v or -verbose	Verbose execution.
-d or -debug	Provide debugging information.
-h	Print help message.
-o <outputfile></outputfile>	Direct pFUnit messages to a file.
-robust	Use the robust runner. Runs tests as
	processes so failures do not halt testing.
-skip <number of="" skip="" tests="" to=""></number>	Use the subset runner, which runs a
	subset of the tests in a suite.

An example from Examples/Robust:

\$./tests.x -robust

16 Usage

Development

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

18 Development

Feedback & Support

- Feedback
- Support

6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

FAQ and Tips

- FAQ
 - Zero Tests Run
 - Some Tests Are Not Running
- Tips
 - Environment Modules
 - Compile Time Errors
 - Intermediate files used by pFUnit

7.1 FAQ

7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD_TEST_SUITE (the_suite_to_add), one to a line.
- There is no <code>-DUSE_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

22 FAQ and Tips

Solutions:

There is no -DUSE_MPI passed to the compiler during the build. Please add as
in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

7.2 Tips

7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

Platform Specific Notes

8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

Acknowledgments

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

Known Installations & Versions

master - The cutting edge of pFUnit development.

pfunit_2.1.0 - A feature freeze prior to a major upgrade of the preprocessor.

TODO

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

30 TODO

The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
 - Configuration testSuites.inc
 - Invocation
 - Command Line Options
 - Preprocessor Input File (.pf)
 - Directives
 - * @Test
 - * @MPITest
 - * @Assert (or Preprocessor Directives)
 - * @Parameters
 - * @TestCase

12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's "tests" subdirectory.

12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' "tests" subdirectories in the - Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
 - @Assert

12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive.

also supports MPI-parallel tests (see @MPITest).

An example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

12.1.4.2 @MPITest

is deprecated as now handles this case.

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI Halo:

```
@Test( npes=[1,2,3])
subroutine testHaloInterior(this)
  use Halo_mod
  use pfunit_mod
  implicit none
  class (MpiTestMethod) :: this
  integer, parameter :: N = 2
  real :: a(N,0:N+1)
  integer :: p

p = this%getProcessRank()
  a(:,1:N) = p
```

```
a(:,0) = -1
a(:,N+1) = -1

call haloFill(a, this%getMpiCommunicator())

@assertEqual(real(p), a(1,1))
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))

end subroutine testHaloInterior
```

12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found,'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- @assertTrue
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf

- · @assertExceptionRaised
- · @assertSameShape
- · @assertIsNaN
- · @assertIsFinite

12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

@Assert Preprocessor Directives

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

13.1 @Assert Preprocessor Dire	ctives
--------------------------------	--------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

Revision Notes

- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
 MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

40 Revision Notes

Data Type Index

15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter_mod	51
pFUnitParser::Action	51
pFUnitParser::AtAfter	57
pFUnitParser::AtAssert	58
pFUnitParser::AtBefore	58
pFUnitParser::AtBegin	59
pFUnitParser::AtMpiAssert	59
pFUnitParser::AtSuite	61
pFUnitParser::AtTest	61
pFUnitParser::AtMpiTest	60
pFUnitParser::AtTestCase	62
pFUnitParser::AtTestParameter	63
add_mod	52
addComplex_mod	53
CodeUtilities::ArrayDescription	53
Assert_mod	53
AssertBasic_mod	54
AssertInteger_mod	55
GenerateRealArrayNewSignature::AssertRealArrayArgument	56
TestCaseB_mod::B_Parameter	63
BaseTestRunner_mod	64
BeforeAfter_mod	65
BrokenSetUpCase_mod	65
BrokenTestCase_mod	65
TestCaseC_mod::C_Parameter	66

Cases_mod	ò
mods::pre::pre2::dataString	3
DebugListener_mod	Э
CodeUtilities::declaration	C
DynamicTestCase_mod	C
Exception_mod	1
Fixture_mod	2
FixtureTestCase_mod	2
CodeUtilities::fortranSubroutineSignature	2
Halo_mod	3
CodeUtilities::implementation	4
CodeUtilities::interfaceBlock	4
mods::pre_:lf::interval	4
Test_RestrictSphericalCoordinates_mod::LatLonCase	3
LinearInterpolator_mod	3
MakeInfinity_mod	3
MakeNaN_mod	7
MockCall_mod	3
MockListener_mod	9
MockRepository_mod)
MockSUT_mod)
testParser::MockWriter	1
CodeUtilities::module	1
MpiContext_mod	2
MpiStubs_mod	3
MpiTestCase_mod	4
MpiTestCaseB_mod::MpiTestCaseB	5
MpiTestCaseB_mod	5
MpiTestMethod_mod	3
MpiTestParameter_mod	3
pFUnitParser::MyError	7
Cases_mod::MyParamType	7
Cases_mod::MyTestCase	3
TestCaseC_mod::newC_Parameter	3
ParallelContext_mod	3
ParallelException_mod	9
ParameterizedTestCase_mod)
Params_mod	1
pFUnitParser::Parser	2
testParser::MockParser	9
Test_Parameters_mod::peCase	3
pFUnit	
pFUnit_mod	
PrivateException_mod	
mods::pre::pre2::procDirective	
1 1 2 P 22 22 2 2 2 2 2 2 2 2 2 2 2 2 2	

mods::pre::pre_lf::lfDirective	
RemoteProxyTestCase_mod	. 97
ResultPrinter mod	
RobustRunner mod	
robustTestSuite_mod	
CodeUtilities::routineUnit	
GenerateRealArrayNewSignature::constraintASSERTEQUAL	
GenerateRealArrayNewSignature::IsWithinTolerance	
•	
GenerateRealArrayNewSignature::VECTOR_NORM	
SerialContext_mod	
SimpleTestCase_mod	
SourceLocation_mod	
SphericalCoordinates_mod	
TestListener_mod::startTest	
StringConversionUtilities_mod	
SubsetRunner_mod	
SurrogateTestCase_mod	
SUT_mod	
Test_Assert_mod	
Test_AssertBasic_mod	
Test_AssertComplex_mod	
Test_AssertInteger_mod	
Test_AssertReal_mod	
Test_BasicOpenMP_mod	
Test_Exception_mod	
Test_FixtureTestCase_mod	. 110
Test_LinearInterpolator_mod::Test_LinearInterpolator	
Test_LinearInterpolator_mod	
Test_MockCall_mod	
Test_MockRepository_mod	
Test_mod	
Test_MpiContext_mod	
Test_MpiException_mod	. 113
Test_MpiParameterizedTestCase_mod	
Test_MpiTestCase_mod	
Test_Parameters_mod::Test_Parameters	. 114
Test_Parameters_mod	. 114
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates	. 115
Test_RestrictSphericalCoordinates_mod	. 115
Test_RobustRunner_mod	. 116
Test_SimpleTestCase_mod	. 116
Test_StringConversionUtilities_mod	. 116
Test_TestMethod_mod	. 117
Test_TestResult_mod	. 117

Test_TestSuite_mod
Test_UnixProcess_mod
TestA_mod
TestCase_mod
TestCaseA_mod::TestCaseA
TestCaseA_mod
TestCaseB_mod::TestCaseB
TestCaseB_mod
TestCaseC_mod::TestCaseC
TestCaseC_mod
TestFailure_mod
mods::pre::pre_lf::TestlfDirective
mods::pre::interleavedp::TestInterleaved
TestListener_mod
TestMethod_mod
mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult_mod
TestRunner_mod
TestSuite_mod
ThrowFundamentalTypes_mod
UnixPipeInterfaces_mod
UnixProcess_mod
WrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA_mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WranTestCaseC mod 137

Data Type Index

16.1 Data Types List

Here are the data types with brief descriptions:

AbstractTestParameter_mod
pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
<briefdescription></briefdescription>
AssertBasic_mod
<briefdescription></briefdescription>
AssertInteger_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::AssertRealArrayArgument
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtSuite
pFUnitParser::AtTest 61
pFUnitParser::AtTestCase
pFUnitParser::AtTestParameter
TestCaseB_mod::B_Parameter
BaseTestRunner_mod
<briefdescription></briefdescription>

BeforeAfter_mod	
BrokenSetUpCase_mod	65
BrokenTestCase_mod	65
TestCaseC_mod::C_Parameter	66
Cases_mod	66
GenerateRealArrayNewSignature::constraintASSERTEQUAL	
mods::pre::pre2::dataString	68
DebugListener_mod	
<briefdescription></briefdescription>	69
CodeUtilities::declaration	70
DynamicTestCase_mod	
<briefdescription></briefdescription>	70
Exception_mod	71
Fixture_mod	
FixtureTestCase_mod	
CodeUtilities::fortranSubroutineSignature	
Halo_mod	
mods::pre_ipre_lf::lfDirective	
CodeUtilities::implementation	
CodeUtilities::interfaceBlock	
mods::pre_ipre_lf::interval	
GenerateRealArrayNewSignature::IsWithinTolerance	
Test RestrictSphericalCoordinates mod::LatLonCase	
LinearInterpolator_mod	
MakeInfinity mod	
<pre></pre>	76
MakeNaN mod	. •
<pre></pre>	77
MockCall_mod	
<pre></pre>	78
MockListener mod	
testParser::MockParser	
MockRepository mod	
<pre></pre>	80
MockSUT_mod	
testParser::MockWriter	
CodeUtilities::module	
MpiContext_mod	٠.
<pre></pre>	82
·	-
MniStubs mod	
MpiStubs_mod <briefdescription></briefdescription>	83
<pre></pre>	83
<pre></pre>	
<pre></pre>	84
<pre></pre>	84 85

MpiTestMethod_mod	
•	36
	36
	37
	37
	38
	88
ParallelContext mod	
<pre><briefdescription></briefdescription></pre>	88
ParallelException_mod	
<u></u>	39
ParameterizedTestCase mod	
<briefdescription></briefdescription>	90
Params_mod	
<pre><briefdescription></briefdescription></pre>	91
	92
	93
pFUnit	
<pre></pre>	93
pFUnit mod	
<pre></pre>	94
PrivateException_mod	
<pre><briefdescription></briefdescription></pre>	95
mods::pre::pre2::procDirective	96
RemoteProxyTestCase_mod	
<briefdescription></briefdescription>	97
mods::pre::pre_Repeat::RepeatDirective	97
ResultPrinter_mod	
<briefdescription></briefdescription>	8
RobustRunner_mod	
<briefdescription></briefdescription>	9
robustTestSuite_mod	00
CodeUtilities::routineUnit	00
SerialContext_mod	
<briefdescription></briefdescription>)1
SimpleTestCase_mod)2
SourceLocation_mod	
<briefdescription></briefdescription>)2
SphericalCoordinates_mod)3
TestListener_mod::startTest)3
StringConversionUtilities_mod	
<briefdescription></briefdescription>)3
SubsetRunner_mod	
<pre></pre>)4
SurrogateTestCase_mod	
<briefdescription></briefdescription>)5
•	

SUI_mod
Test_Assert_mod
Test_AssertBasic_mod
Test_AssertComplex_mod
Test_AssertInteger_mod
Test_AssertReal_mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test_FixtureTestCase_mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
Test_MockCall_mod
Test_MockRepository_mod
Test_mod
<briefdescription></briefdescription>
Test_MpiContext_mod
Test_MpiException_mod
Test_MpiParameterizedTestCase_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
Test RestrictSphericalCoordinates mod::Test RestrictSphericalCoordinates . 115
T - D
Test RestrictSphericalCoordinates mod
Test_RestrictSphericalCoordinates_mod
Test_RestrictSphericalCoordinates_mod
Test_RobustRunner_mod
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 48 CestGescription> 118
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 8riefDescription> 118 TestCaseA_mod::TestCaseA 118
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod::TestCaseA 119 TestCaseA_mod 120
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod::TestCaseA 119 TestCaseA_mod 120 TestCaseB_mod::TestCaseB 120
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod::TestCaseA 119 TestCaseA_mod 120 TestCaseB_mod::TestCaseB 120 TestCaseB_mod 120
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod 119 TestCaseA_mod 120 TestCaseB_mod 120 TestCaseB_mod 121 TestCaseC_mod::TestCaseC 122 TestCaseC_mod::TestCaseC 122
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod 119 TestCaseA_mod 120 TestCaseB_mod 120 TestCaseB_mod 121 TestCaseC_mod::TestCaseC 122 TestCaseC_mod 122
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod::TestCaseA 119 TestCaseA_mod 120 TestCaseB_mod 120 TestCaseB_mod 121 TestCaseC_mod::TestCaseC 122 TestCaseC_mod 122 TestFailure_mod 122
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod 118 TestCaseA_mod::TestCaseA 119 TestCaseA_mod 120 TestCaseB_mod::TestCaseB 120 TestCaseC_mod::TestCaseC 122 TestCaseC_mod 122 TestCaseC_mod 122 TestFailure_mod 123 CestFailure_mod 123 CestFailure_mod 123 CestFailure_mod 123 CestFailure_mod 123
Test_RobustRunner_mod 116 Test_SimpleTestCase_mod 116 Test_StringConversionUtilities_mod 116 Test_TestMethod_mod 117 Test_TestResult_mod 117 Test_TestSuite_mod 117 Test_UnixProcess_mod 118 TestA_mod 118 TestCase_mod 118 TestCaseA_mod 120 TestCaseA_mod 120 TestCaseB_mod 120 TestCaseB_mod 121 TestCaseC_mod 122 TestCaseC_mod 122 TestFailure_mod 28

TestMethod_mod
<briefdescription></briefdescription>
mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult mod
specialized TestResults
TestRunner mod
<pre></pre>
TestSuite mod
- <briefdescription></briefdescription>
ThrowFundamentalTypes mod
<briefdescription></briefdescription>
UnixPipeInterfaces mod
<pre><briefdescription></briefdescription></pre>
UnixProcess_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::VECTOR_NORM
WrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA_mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WrapTestCaseC_mod

Data Type Documentation

17.1 AbstractTestParameter_mod Module Reference

Data Types


- type AbstractTestParameter
- interface toString

The documentation for this module was generated from the following file:

AbstractTestParameter.F90

17.2 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



Public Member Functions

· def apply

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.3 add_mod Module Reference

Public Member Functions

- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- · Robust/src/add.F90
- · Simple/src/add.F90

17.4 addComplex_mod Module Reference

Public Member Functions

complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following file:

· addComplex.F90

17.5 CodeUtilities::ArrayDescription Class Reference

Public Member Functions

- def __init__
- def NAME
- def DECLARE
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

Public Attributes

- fType
- kind
- rank

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.6 Assert_mod Module Reference

<BriefDescription>

17.6.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

17.7 AssertBasic mod Module Reference

<BriefDescription>

Data Types

- · interface assertEqual
- interface assertExceptionRaised
- · interface assertFalse
- · interface assertIsFinite
- interface assertIsNaN
- interface assertTrue
- interface fail
- · type UnusableArgument

Public Member Functions

- subroutine assertExceptionRaisedMessage (message)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- logical function, public nonConformable (shapeA, shapeB)

- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN double (x, message, location)
- subroutine assertIsFinite_single (x, message, location)
- subroutine assertIsFinite_double (x, message, location)

17.7.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertBasic.F90

17.8 AssertInteger_mod Module Reference

<BriefDescription>

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

Public Member Functions

- subroutine assertEqualInteger1D1D_ (expected, found, message, location)
- subroutine assertEqualInteger0D1D_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D_ (expected, found, message, location)
- subroutine assertLessThan_ (a, b, message, location)

17.8.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

17.9 GenerateRealArrayNewSignature::AssertRealArrayArgument Class Reference

Public Member Functions

- def __init__
- def updateDescriptions
- def getExpectedDescription
- def getFoundDescription
- def getTolerance

Public Attributes


- expectedFType
- expectedPrecision
- expectedRank
- foundFType
- foundPrecision
- foundRank
- tolerance
- · expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

17.10 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.11 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



Public Member Functions

- def __init__
- def match
- · def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.12 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



Public Member Functions

- def __init__
- def match
- · def action


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.13 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.14 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.15 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



Public Member Functions

def __init__


- parser
- keyword

The documentation for this class was generated from the following file:

pFUnitParser.py

17.16 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.17 pFUnitParser::AtTest Class Reference

Inheritance diagram for pFUnitParser::AtTest:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


- parser
- keyword

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.18 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



- def __init__
- def match
- · def action


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.19 pFUnitParser::AtTestParameter Class Reference

Inheritance diagram for pFUnitParser::AtTestParameter:



Public Member Functions

- def init
- def match
- def action

Public Attributes

· parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.20 TestCaseB_mod::B_Parameter Type Reference

- · procedure toString
- procedure toString

- real phi
- · real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.21 BaseTestRunner_mod Module Reference

```
<BriefDescription>
```

Data Types

- type BaseTestRunner
- interface run2

Public Member Functions

• subroutine setDebug (this)

17.21.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

17.22 BeforeAfter_mod Module Reference

Public Member Functions

- subroutine first (this)
- subroutine last (this)
- subroutine succeeds (this)
- · subroutine fails (this)

Public Attributes

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

• Examples/MPI_Halo/tests/beforeAfter.pf

17.23 BrokenSetUpCase_mod Module Reference

Data Types

• type BrokenSetUpCase

Public Member Functions

 $\bullet \ \ \mathsf{type}(\mathsf{BrokenSetUpCase}) \ \mathsf{function}, \ \ \mathsf{pointer}, \ \mathsf{public} \ \boldsymbol{\mathsf{newBrokenSetUpCase}} \ ()$

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

17.24 BrokenTestCase_mod Module Reference

Data Types

• type BrokenTestCase

Public Member Functions

• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

17.25 TestCaseC_mod::C_Parameter Type Reference

Public Member Functions

- procedure toString
- · procedure toString

Public Attributes

- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.26 Cases_mod Module Reference

Data Types

- type MyParamType
- type MyTestCase


- type(MyParamType) function newMyParam (i)
- type(MyTestCase) function newMyTestCase (param)
- subroutine test_odd (this)
- subroutine test_even (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test_Cases.pf

17.27 GenerateRealArrayNewSignature::constraintASSERTEQUA-L Class Reference

Inheritance diagram for GenerateRealArrayNewSignature::constraintASSERTEQUAL:



Public Member Functions

def init

This next line actually generates the text of the code.

Public Attributes

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

17.27.1 Constructor & Destructor Documentation

17.27.1.1 def GenerateRealArrayNewSignature::constraintASSERTE-QUAL::__init__ (self, expectedDescr, foundDescr, tolerance)

This next line actually generates the text of the code.

17.27.2 Member Data Documentation

17.27.2.1 GenerateRealArrayNewSignature::constraintASSERTEQUAL::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

17.27.2.2 GenerateRealArrayNewSignature::constraintASSERTEQUAL::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

17.28 mods::pre::pre2::dataString Class Reference

- def __init__
- def insert
- def getLength
- · def getPosition
- · def setPosition
- · def getItem
- def getDataAtPosition
- · def getData
- · def getSlice
- · def getSliceForward
- · def removeSlice
- def getCurrentData
- def insertAtCurrent
- · def append
- · def advanceAndGetNextData
- · def validPosition
- def findToEnd
- · def match
- def matchToEnd

- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

- data
- · position

The documentation for this class was generated from the following file:

• pre2.py

17.29 DebugListener_mod Module Reference

<BriefDescription>

Data Types

• interface DebugListener

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

17.29.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· DebugListener.F90

17.30 CodeUtilities::declaration Class Reference

Public Member Functions

- def __init___
- · def generate

Public Attributes

- · simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.31 DynamicTestCase_mod Module Reference

<BriefDescription>

Data Types

- · interface delete
- type DynamicTestCase
- · interface testmethod

Public Member Functions

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

17.31.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

17.32 Exception_mod Module Reference

Data Types

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- interface throw

Public Member Functions

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public catchAny (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()
- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

· Exception.F90

17.33 Fixture_mod Module Reference

Public Member Functions

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following file:

· fixtureTests.pf

17.34 FixtureTestCase mod Module Reference

Data Types

- · interface delete
- type FixtureTestCase

Public Member Functions

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

• FixtureTestCase.F90

17.35 CodeUtilities::fortranSubroutineSignature Class Reference

- def __init__
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.36 Halo_mod Module Reference

Public Member Functions

• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

17.37 mods::pre::pre_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre_lf::lfDirective:



Public Member Functions

· def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_lf.py

17.38 CodeUtilities::implementation Class Reference

Public Member Functions

- def __init__
- · def generate

Public Attributes

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.39 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.40 mods::pre::pre_lf::interval Class Reference

- def __init__
- · def getInterval
- · def setInterval
- · def getStart
- def getEnd


- start
- end
- · interval

The documentation for this class was generated from the following file:

• pre_lf.py

17.41 GenerateRealArrayNewSignature::IsWithinTolerance Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::lsWithinTolerance:



Public Member Functions

• def __init__

Public Attributes

- rank
- · precision
- name
- fType
- declaration
- declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

17.42 Test_RestrictSphericalCoordinates_mod::LatLonCase Type - Reference

Public Member Functions

· procedure toString

Public Attributes

- real lat
- · real lon
- real restrictedLat
- · real restrictedLon

The documentation for this type was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

17.43 LinearInterpolator_mod Module Reference

Data Types

- interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

· LinearInterpolator.F90

17.44 MakeInfinity_mod Module Reference

<BriefDescription>

- real(r32) function, public makeInf_32 ()
- real(r64) function, public makeInf_64 ()

17.44.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MakeInfinity.F90

17.45 MakeNaN_mod Module Reference

<BriefDescription>

Public Member Functions

- real(r32) function, public makeNaN_32 ()
- real(r64) function, public makeNaN_64 ()

17.45.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MakeNaN.F90

17.46 MockCall_mod Module Reference

```
<BriefDescription>
```

Data Types

· type MockCall

Public Member Functions

• type(MockCall) function, public **newMockCall** (name)

17.46.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MockCall.F90

17.47 MockListener_mod Module Reference

Data Types

• type MockListener

Public Member Functions


• subroutine **startTest** (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

17.48 testParser::MockParser Class Reference

Inheritance diagram for testParser::MockParser:



Public Member Functions

- def __init__
- def nextLine
- def reset

Public Attributes

- saveLines
- lines
- outputFile
- outLines
- userTestCase
- userTestMethods
- · currentSelfObjectName

The documentation for this class was generated from the following file:

· testParser.py

17.49 MockRepository_mod Module Reference

<BriefDescription>

Data Types

• type MockRepository

Public Member Functions

- type(MockRepository) function, pointer, public newMockRepository ()
- subroutine expectCall (this, obj, method)

17.49.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MockRepository.F90

17.50 MockSUT mod Module Reference

Data Types

• type MockSUT

Public Member Functions

- type(MockSUT) function, allocatable, public **newMockSUT** (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.51 testParser::MockWriter Class Reference

Public Member Functions

- def __init__
- def write

Public Attributes

parser

The documentation for this class was generated from the following file:

testParser.py

17.52 CodeUtilities::module Class Reference

- def __init__
- def generate
- def addDeclaration
- def addImplementation
- · def addRoutineUnit
- def addInterfaceBlock
- · def getName
- def setFileName
- def getFileName

- name
- · declarations
- · implementations
- generation
- fileName

The documentation for this class was generated from the following file:

CodeUtilities.py

17.53 MpiContext_mod Module Reference

<BriefDescription>

Data Types

- type MpiContext
- interface newMpiContext

Public Member Functions

- subroutine barrier (this)
- integer function **getMpiCommunicator** (this)

17.53.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MpiContext.F90

17.54 MpiStubs_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public MPI_Comm_rank (comm, rank, ier)
- subroutine, public MPI_Comm_size (comm, size, ier)
- subroutine, public MPI_Comm_dup (comm, newComm, ier)
- subroutine, public MPI_Comm_group (comm, group, ier)
- subroutine, public MPI_Group_range_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI_Comm_create (comm, group, newComm, ier)

Public Attributes

- integer, parameter, public MPI_COMM_WORLD = -1
- integer, parameter, public MPI_COMM_NULL = -1
- integer, parameter, public MPI_COMM_SUCCESS = 0

17.54.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MpiStubs.F90

17.55 MpiTestCase_mod Module Reference

```
<BriefDescription>
```

Data Types

type MpiTestCase

Public Member Functions

- recursive subroutine runBare (this)
- integer function getMpiCommunicator (this)
- integer function getProcessRank (this)

17.55.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> <Or starting here...>
```

The documentation for this module was generated from the following file:

· MpiTestCase.F90

17.56 MpiTestCaseB_mod::MpiTestCaseB Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

· integer componentl

The documentation for this type was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

17.57 MpiTestCaseB_mod Module Reference

Data Types

type MpiTestCaseB

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine **setUp** (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- MpiTestCaseB.F90
- MpiTestCaseB.pf

17.58 MpiTestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

17.58.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

MpiTestMethod.F90

17.59 MpiTestParameter_mod Module Reference

Data Types

• type MpiTestParameter

Public Member Functions

 type(MpiTestParameter) function, public newMpiTestParameter (num ProcessesRequested) The documentation for this module was generated from the following file:

• MpiTestParameter.F90

17.60 pFUnitParser::MyError Class Reference

Inherits Exception.

Public Member Functions

- def __init__
- def __str__

Public Attributes

value

The documentation for this class was generated from the following file:

• pFUnitParser.py

17.61 Cases_mod::MyParamType Type Reference

Public Member Functions

procedure toString

Public Attributes

• integer i

The documentation for this type was generated from the following file:

• Test_Cases.pf

17.62 Cases_mod::MyTestCase Type Reference

Public Attributes

• integer i

The documentation for this type was generated from the following file:

· Test_Cases.pf

17.63 TestCaseC_mod::newC_Parameter Interface Reference

Public Member Functions

- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)

The documentation for this interface was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.64 ParallelContext_mod Module Reference

<BriefDescription>

Data Types

- · interface allReduceLogical
- interface gatherInteger
- · interface gatherLogical
- interface gatherString
- · interface getNumProcesses
- type ParallelContext
- · interface processRank
- · interface sum

17.64.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelContext.F90

17.65 ParallelException_mod Module Reference

<BriefDescription>

Data Types

- interface any Exceptions
- interface getNumExceptions

Public Member Functions

• subroutine, public gather (context)

17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParallelException.F90

17.66 ParameterizedTestCase_mod Module Reference

```
<BriefDescription>
```

Data Types

• type ParameterizedTestCase

Public Attributes

• integer, parameter, public MAX_LEN_LABEL = 32

17.66.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParameterizedTestCase.F90

17.67 Params_mod Module Reference

<BriefDescription>

Public Attributes

- integer, parameter **R32** = selected_real_kind(p=6)
- integer, parameter R64 = selected_real_kind(p=14)
- integer, parameter **C32** = selected_real_kind(p=6)
- integer, parameter C64 = selected_real_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

17.67.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Params.F90

17.68 pFUnitParser::Parser Class Reference

Inheritance diagram for pFUnitParser::Parser:



Public Member Functions

- def __init__
- def commentLine
- def run
- def isComment
- · def nextLine
- def printHeader
- def printTail
- def printWrapUserTestCase
- def printRunMethod
- def printParameterHeader
- def printMakeSuite
- def addSimpleTestMethod
- def addMpiTestMethod
- def addUserTestMethod
- def printMakeCustomTest
- def makeWrapperModule
- def final

Public Attributes

- fileName
- inputFile
- outputFile
- · defaultSuiteName
- suiteName
- currentLineNumber
- userModuleName
- userTestCase
- userTestMethods

- wrapModuleName
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

17.69 Test_Parameters_mod::peCase Type Reference

Public Member Functions

· procedure toString

Public Attributes

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

17.70 pFUnit Module Reference

<BriefDescription>

Public Member Functions

• integer function run ()

17.70.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

17.71 pFUnit_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public initialize (useMpi)
- subroutine, public finalize (successful)

17.71.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

17.72 PrivateException_mod Module Reference

<BriefDescription>

Data Types

- type Exception
- type ExceptionList
- interface newException

Public Member Functions

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

Public Attributes

- integer, parameter, public **MAXLEN_MESSAGE** = 80*15
- integer, parameter, public MAXLEN_FILE_NAME = 80
- character(len=*), parameter, public **NULL_MESSAGE** = "

17.72.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Exception.F90

17.73 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



Public Member Functions

- def init
- · def getLength
- · def match
- · def evaluate
- def getNewPosition
- · def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- · def finditerTokenToPosition
- def makeTokenErrorMessage

Public Attributes

- name
- newPosition
- · tokens
- TokenREs

17.73.1 Member Function/Subroutine Documentation

```
17.73.1.1 def mods::pre::pre2::procDirective::addTokenRE ( self, args, key, defaultToken, prefix = r'' (?i) [ \t ] *''', postfix = '' )
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

pre2.py

17.74 RemoteProxyTestCase_mod Module Reference

<BriefDescription>

Data Types

• interface RemoteProxyTestCase

17.74.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

17.75 mods::pre::pre_Repeat::RepeatDirective Class Reference

Inheritance diagram for mods::pre::pre Repeat::RepeatDirective:



Public Member Functions

• def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_Repeat.py

17.76 ResultPrinter mod Module Reference

<BriefDescription>

Data Types

· type ResultPrinter

Public Member Functions

- type(ResultPrinter) function, public newResultPrinter (unit)
- subroutine addError (this, testName, exceptions)
- subroutine startTest (this, testName)
- subroutine **printHeader** (this, runTime)

17.76.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

17.77 RobustRunner_mod Module Reference

<BriefDescription>

Data Types

- · interface RobustRunner
- type TestCaseMonitor

Public Member Functions

- type(RobustRunner) function newRobustRunner_unit (remoteRunCommand, unit)
- subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

17.77.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RobustRunner.F90

17.78 robustTestSuite_mod Module Reference

Public Member Functions


- type(TestSuite) function, public suite ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

17.79 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



Public Member Functions

- def __init___
- def setName
- · def getName
- def setDeclaration
- def addDeclaration
- def setImplementation
- · def getDeclaration
- def getDeclarations
- def getImplementation
- def clearDeclarations

Public Attributes

- name
- declaration
- declarations
- · implementation

· CodeUtilities.py

17.80 SerialContext_mod Module Reference

<BriefDescription>

Data Types

· type SerialContext

Public Member Functions

• type(SerialContext) function, public newSerialContext ()

Public Attributes

 type(SerialContext), parameter, public THE_SERIAL_CONTEXT = Serial-Context()

17.80.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

17.81 SimpleTestCase_mod Module Reference

Data Types

- · interface method
- type SimpleTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- · subroutine, public method2 (this)
- · subroutine, public methodWith2Exceptions (this)
- subroutine delete_ (this)

The documentation for this module was generated from the following file:

· SimpleTestCase.F90

17.82 SourceLocation mod Module Reference

<BriefDescription>

Data Types

• type SourceLocation

Public Attributes

- character(len=MAXLEN_FILE_NAME), parameter, public UNKNOWN_FILE_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN_LINE_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN_SOURCE_LOCATION = SourceLocation()

17.82.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

17.83 SphericalCoordinates_mod Module Reference

Data Types

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

17.84 TestListener_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

17.85 StringConversionUtilities_mod Module Reference

<BriefDescription>

Data Types

· interface toString

Public Member Functions

- character(len=len_trim(a)+1+len_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)

Public Attributes

• integer, parameter, public MAXLEN_STRING = 80

17.85.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

17.86 SubsetRunner_mod Module Reference

<BriefDescription>

Data Types

· interface SubsetRunner

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine **startTest** (this, testName)

17.86.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SubsetRunner.F90

17.87 SurrogateTestCase_mod Module Reference

<BriefDescription>

Data Types

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

17.87.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

17.88 SUT_mod Module Reference

Data Types

• type SUT

The documentation for this module was generated from the following file:

Test_MockRepository.F90

17.89 Test_Assert_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test_Assert.F90

17.90 Test AssertBasic mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()

The documentation for this module was generated from the following file:

Test_AssertBasic.F90

17.91 Test_AssertComplex_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testEquals C complexScalar ()
- subroutine testEquals C 0D1D ()
- subroutine testEquals_C_1D_nonConformable1 ()
- subroutine testEquals C 2D SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals_C_MultiD_SingleElementDifferent1
- subroutine testEquals_C_MultiD_SingleElementDifferent2
- $\bullet \ \ \text{subroutine} \ \ \textbf{testEquals_C_MultiD_SingleElementDifferent3}$
- subroutine testEquals_C_MultiD_SingleElementDifferent4
- subroutine testEquals_C_MultiD_SingleElementDifferent5
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff1 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff5 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff6 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals C MultiDWithTolerance ()
- subroutine testEquals_C_MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals_C_MultiDWithTolerance64_1 ()

- subroutine testEquals C MultiDWithTolerance64 2 ()
- subroutine testEquals_C_MultiDSourceLocation ()
- subroutine testEquals_4DPComplex_DifferenceReport ()
- · subroutine assertCatch (string, location)

Test_AssertComplex.F90

17.92 Test_AssertInteger_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqual equal ()

The documentation for this module was generated from the following file:

Test AssertInteger.F90

17.93 Test_AssertReal_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testEquals_0D1D ()
- subroutine testEquals_1D_nonConformable1 ()
- subroutine testEquals 2D SingleElementDifferent ()
- subroutine testEquals_MultiD_SingleElementDifferent ()
- subroutine testEquals_MultiD_SingleElementDifferent1
- subroutine testEquals_MultiD_SingleElementDifferent2
- subroutine testEquals_MultiD_SingleElementDifferent3
- subroutine testEquals_MultiD_SingleElementDifferent4
- subroutine testEquals MultiD SingleElementDifferent5
- $\bullet \ \ \text{subroutine } \textbf{testEquals_MultiDMultiPrec_SingleEltDiff} \ ()$
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff1 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff2 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff5 ()

- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff7 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff8 ()
- subroutine testEquals_ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals_VectorWithToleranceNoMsg ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals MultiDWithTolerance1 ()
- subroutine testEquals MultiDWithTolerance64 ()
- subroutine testEquals_MultiDWithTolerance64_1 ()
- subroutine testEquals MultiDWithTolerance64 2 ()
- subroutine testEquals_MultiDSourceLocation ()
- subroutine testEquals_ScalarAndLocation ()
- subroutine testEquals_ScalarInfinity_equal ()
- subroutine testEquals ScalarInfinity unequal A ()
- subroutine testEquals ScalarInfinity unequal B ()
- subroutine testEquals ScalarInfinity unequal C ()
- subroutine assertCatch (string, location)

• Test AssertReal.F90

17.94 Test_BasicOpenMP_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()
- subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

Test BasicOpenMP.F90

17.95 Test_Exception_mod Module Reference

Public Member Functions

• type(TestSuite) function, public suite ()

- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

• Test Exception.F90

17.96 Test_FixtureTestCase_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test_FixtureTestCase.F90

17.97 Test_LinearInterpolator_mod::Test_LinearInterpolator Type - Reference

Public Member Functions

- procedure setUp
- · procedure tearDown

Public Attributes

• type(LinearInterpolator) interpolator

The documentation for this type was generated from the following file:

• Test_LinearInterpolator.pf

17.98 Test_LinearInterpolator_mod Module Reference

Data Types

• type Test_LinearInterpolator

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

Test_LinearInterpolator.pf

17.99 Test MockCall mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

• Test MockCall.F90

17.100 Test_MockRepository_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.101 Test_mod Module Reference

<BriefDescription>

Data Types

- interface countTestCases
- interface run
- type Test

17.101.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

17.102 Test_MpiContext_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

Test_MpiContext.F90

17.103 Test_MpiException_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine test_anyExceptions_none (this)
- subroutine test_getNumExceptions (this)
- subroutine test_gather (this)

The documentation for this module was generated from the following file:

Test MpiException.F90

17.104 Test_MpiParameterizedTestCase_mod Module Reference

Data Types

- type ExtendedTestParameter
- · interface method
- type Test MpiTestCase

Public Member Functions

- type(TestSuite) function, public **suite** ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, testParameter)
- subroutine testToString (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

• Test MpiParameterizedTestCase.F90

17.105 Test_MpiTestCase_mod Module Reference

Data Types

- · interface method
- type Test_MpiTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- · recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

• Test_MpiTestCase.F90

17.106 Test_Parameters_mod::Test_Parameters Type Reference

Public Attributes

- integer p1
- · integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

17.107 Test_Parameters_mod Module Reference

Data Types

- type peCase
- type Test Parameters

Public Member Functions

- type(Test_Parameters) function **newTest** (testParameter)
- type(peCase) function newPeCase (p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()

Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates Type Reference 115

- character(:) function, allocatable toString (this)
- subroutine testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

17.108 Test_RestrictSphericalCoordinates_mod::Test_Restrict-SphericalCoordinates Type Reference

Public Attributes

- · real lat
- real lon
- · real restrictedLat
- real restrictedLon
- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.109 Test_RestrictSphericalCoordinates_mod Module Reference

Data Types

- type LatLonCase
- type Test_RestrictSphericalCoordinates

Public Member Functions

- type(Test RestrictSphericalCoordinates) function **newTest** (testParameter)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

17.110 Test RobustRunner mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

• Test RobustRunner.F90

17.111 Test_SimpleTestCase_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()
- subroutine testRunMethodShouldFail ()

The documentation for this module was generated from the following file:

· Test SimpleTestCase.F90

17.112 Test_StringConversionUtilities_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test_StringConversionUtilities.F90

17.113 Test TestMethod mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

• Test_TestMethod.F90

17.114 Test_TestResult_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

• Test_TestResult.F90

17.115 Test_TestSuite_mod Module Reference

Data Types

• type Verbose

Public Member Functions

- type(TestSuite) function, public **suite** ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()

- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

· Test TestSuite.F90

17.116 Test UnixProcess mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testIsActive ()

The documentation for this module was generated from the following file:

Test UnixProcess.F90

17.117 TestA mod Module Reference

Public Member Functions

- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)
- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)

The documentation for this module was generated from the following files:

- TestA.F90
- TestA.pf

17.118 TestCase_mod Module Reference

<BriefDescription>

Data Types

- type ConcreteSurrogate
- type TestCase
- type TestCaseReference

Public Member Functions

- recursive subroutine runBare (this)
- recursive subroutine runBare_surrogate (this)

17.118.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestCase.F90

17.119 TestCaseA_mod::TestCaseA Type Reference

Public Member Functions

- · procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

• integer componentI

The documentation for this type was generated from the following files:

- TestCaseA.F90
- TestCaseA.pf

17.120 TestCaseA mod Module Reference

Data Types

• type TestCaseA

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

17.121 TestCaseB_mod::TestCaseB Type Reference

Public Member Functions

- · procedure setUp
- · procedure tearDown
- · procedure setUp
- · procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- real phi
- · real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.122 TestCaseB mod Module Reference

Data Types

- type B_Parameter
- type TestCaseB

Public Member Functions

- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)
- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.123 TestCaseC_mod::TestCaseC Type Reference

Public Member Functions

- procedure setUp
- · procedure tearDown
- · procedure setUp
- · procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.124 TestCaseC_mod Module Reference

Data Types

- type C_Parameter
- interface newC Parameter
- type TestCaseC

Public Member Functions

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine **testB** (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.125 TestFailure_mod Module Reference

```
<BriefDescription>
```

Data Types

• type TestFailure

17.125.1 Detailed Description

```
<\!\!\text{BriefDescription}\!\!>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

17.126 mods::pre::pre_lf::TestIfDirective Class Reference

Public Member Functions

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse
- def testIFTestTrue1
- def testIFTestTrue2
- · def testIFClearTokens
- · def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

• pre_lf.py

17.127 mods::pre::interleavedp::TestInterleaved Class Reference

Public Member Functions

- · def test InOrder
- def test_NumberMismatch
- · def test_OrderMismatch1
- def test_OrderMismatch2
- · def test OrderMismatch3
- def test_ElseMid1
- def test ElseMid2
- def test_ElseMid3
- · def test_ElseMid4
- def test_ElseMid5
- def test_ElseMid6
- def test_ElseMid7
- · def test_ElseMid8
- def test_ElseMid9
- · def test_ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

17.128 TestListener_mod Module Reference

<BriefDescription>

Data Types

- · interface addFailure
- interface endTest
- type ListenerPointer
- interface startTest
- · type TestListener

17.128.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestListener.F90

17.129 TestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface empty
- interface newTestMethod
- type TestMethod

17.129.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

17.130 mods::pre::parseArgs::TestParseArgs Class Reference

Public Member Functions

- · def test ParseArgs OneArgWithBrackets1
- def test_ParseArgs_OneArgWithBrackets2
- def test ParseArgs OneArgWithBrackets3
- def test_ParseArgs_OneArgWithBrackets4
- def test_ParseArgs_OneArgWithBrackets5
- def test_ParseArgs_OneArgWithBrackets6
- def test_ParseArgs_OneArgWithBrackets7
- def test_ParseArgs_oneArg
- · def test ParseArgs twoArgs1
- def test_ParseArgs_twoArgs2
- · def test_ParseArgs_oneArgArray1
- def test_ParseArgs_TwoArgArray
- def test_ParseArgs_ThreeArgs

The documentation for this class was generated from the following file:

· parseArgs.py

17.131 testParser::TestParseLine Class Reference

Public Member Functions

- def testCppSetLineAndFile
- · def testGetSubroutineName
- · def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtTestNoParens
- def testAtTestFail
- def testAtTestSkipComment
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- def testMatchAtAssertOther
- def testMatchAtMpiAssert
- def testMatchAtBefore
- · def testMatchAtAfter
- · def testMatchAtSuite

17.131.1 Member Function/Subroutine Documentation

17.131.1.1 def testParser::TestParseLine::testAtMpiTest (self)

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

17.131.1.2 def testParser::TestParseLine::testAtTest(self)

Check that a line starting with '@test' is detected as an annotation.

17.131.1.3 def testParser::TestParseLine::testAtTestFail (self)

Check that useful error is sent if next line is not properly formatted.

17.131.1.4 def testParser::TestParseLine::testAtTestNoParens (self)

Check that test procedure with no parens is accepted.

17.131.1.5 def testParser::TestParseLine::testAtTestSkipComment (self)

Ignore comment lines between @test and subroutine foo().

17.131.1.6 def testParser::TestParseLine::testMatchAtAfter(self)

Check that a line starting with '@after*' \dots

17.131.1.7 def testParser::TestParseLine::testMatchAtAssertEqual (self)

Check that a line starting with '@assertEqual' is detected as an annotation.

17.131.1.8 def testParser::TestParseLine::testMatchAtAssertOther(self)

Check that a line starting with '@assert*' is detected as an annotation.

17.131.1.9 def testParser::TestParseLine::testMatchAtBefore (self)

Check that a line starting with '@before*' ...

17.131.1.10 def testParser::TestParseLine::testMatchAtMpiAssert (self)

Check that a line starting with '@mpiAssert*' is detected as an annotation.

17.131.1.11 def testParser::TestParseLine::testMatchAtSuite (self)

Check that a line starting with 'esuite changes the suite name \dots

17.131.1.12 def testParser::TestParseLine::testMatchAtTestCase (self)

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

testParser.py

17.132 mods::pre::pre_Repeat::TestRepeatDirective Class Reference

Public Member Functions

- def test copyBlock1
- · def test_copyBlock2
- · def test_copyBlock2Vars
- · def test_copyBlock2VarsMulti
- def test_copyBlock2VarsMultiWithStrings
- def test_copyNaiveRecursion
- · def test_copyNaiveRecursion1
- def test_copyFunction1

The documentation for this class was generated from the following file:

• pre_Repeat.py

17.133 TestResult mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Data Types

• type TestResult

Public Member Functions

- type(TestResult) function, public newTestResult ()
- subroutine addError (this, aTest, exceptions)
- integer function failureCount (this)
- subroutine addListener (this, listener)

17.133.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestResult.F90

17.134 TestRunner_mod Module Reference

<BriefDescription>

Data Types

- interface newTestRunner
- type TestRunner

Public Member Functions

- type(TestRunner) function newTestRunner_unit (unit)
- type(TestResult) function run (this, aTest, context)
- subroutine startTest (this, testName)

17.134.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestRunner.F90

17.135 TestSuite_mod Module Reference

<BriefDescription>

Data Types

- interface newTestSuite
- type TestReference
- type TestSuite

Public Member Functions

• recursive subroutine addTest (this, aTest)

17.135.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestSuite.F90

17.136 ThrowFundamentalTypes_mod Module Reference

<BriefDescription>

Data Types

- · interface throwDifferentValues
- interface throwDifferentValuesWithLocation

Public Member Functions

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN_SHAPE) function, public locationFormat (iLocation)

17.136.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

17.137 UnixPipeInterfaces_mod Module Reference

<BriefDescription>

Data Types

- interface fgets
- · interface free
- interface getdelim
- interface getline
- interface pclose
- interface popen

Public Attributes

• integer(C_INT), parameter, public CLOSE_FAILED = -1

17.137.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixPipeInterfaces.F90

17.138 UnixProcess_mod Module Reference

<BriefDescription>

Data Types

· interface UnixProcess

Public Member Functions

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable **getDelim** (this, delimeter)
- integer function getPid (this)

17.138.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

UnixProcess.F90

17.139 GenerateRealArrayNewSignature::VECTOR_NORM Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::VECTOR_NORM:



Public Member Functions

def __init__

Public Attributes

- rank
- fType
- · precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

· GenerateRealArrayNewSignature.py

17.140 WrapbeforeAfter Module Reference

The documentation for this module was generated from the following file:

• beforeAfter.F90

17.141 WrapMpiTestCaseB_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, npesRequested)

The documentation for this module was generated from the following file:

• MpiTestCaseB.F90

17.142 Wrapsimple Module Reference

The documentation for this module was generated from the following file:

• simple.F90

17.143 WrapTestA_mod Module Reference

The documentation for this module was generated from the following file:

TestA.F90

17.144 WrapTestCaseA_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod)

The documentation for this module was generated from the following file:

TestCaseA.F90

17.145 WrapTestCaseB_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter)

The documentation for this module was generated from the following file:

· ParameterizedTestCaseB.F90

17.146 WrapTestCaseC_mod Module Reference

Data Types

- · interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter, npesRequested)

The documentation for this module was generated from the following file:

• MpiParameterizedTestCaseC.F90