# pFUnit

Generated by Doxygen 1.7.6

Thu Feb 6 2014 08:48:49

# **Contents**

1	pFU	FUnit 2 - Documentation - Version 0.0 (2014-0206-0848 MLR) 1			
	1.1	Overview	1		
	1.2	Contents	1		
	1.3	See Also	2		
	1.4	LICENSE	2		
	1.5	Copyright	2		
2	Obta	nining pFUnit	3		
3	Insta	allation	5		
	3.1	Installing pFUnit	5		
	3.2	Prerequisites	5		
	3.3	Obtaining pFUnit	6		
	3.4	Manifest - What's in the directory? 6			
	3.5	Configuration	7		
	3.6	Building pFUnit	8		
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8		
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8		
		3.6.3 OPENMP	9		
		3.6.4 Cleaning	9		
		3.6.5 Documentation	9		
		3.6.6 CMAKE	10		
	2.7	Installation	10		

	00175176
1	CONTENTS
1	OOMILIAIS

		3.7.1	Installation - Serial	10	
		3.7.2	Installation - MPI	10	
		3.7.3	Installation - OPENMP	11	
		3.7.4	Installation - DEFAULT DIRECTORY	11	
_					
4	Usag	-		13	
	4.1				
		4.1.1	Usage - Configuration		
		4.1.2	Usage - Hello World		
	4.2	Usage	- Preprocessor	14	
	4.3	Compi	ling and Executing The Test	14	
		4.3.1	- Compiling and Executing the Tests (MPI PARALLEL)	14	
		4.3.2	Command Line Options	15	
5	Deve	elopmer	nt .	17	
	Devi	оторино		.,	
6	Feed	dback &	Support	19	
	6.1	Feedba	ack	19	
	6.2	Suppo	rt	19	
7	FAQ	and Tip	os	21	
	7.1			21	
		7.1.1	Zero Tests Run		
		7.1.2	Some Tests Are Not Running		
	7.2				
	1.2	7.2.1	Environment Modules		
		7.2.1	Compile Time Errors		
			•		
		7.2.3	Intermediate files used by pFUnit	22	
8	Plati	form Sp	ecific Notes	23	
	8.1	Mac O	SX	23	
	8.2	Window	ws/CYGWIN	23	
9	Δcki	nowledo	aments	25	
9	ACK	knowledgments 25			

CONTENTS iii

10	Known Insta	llations & Versions	27
11	TODO		29
12	The Preproc	essor - pFUnitParser	31
	12.1 Using T	he Preprocessor	31
	12.1.1	Configuration - testSuites.inc	32
	12.1.2	Invocation	32
	12.1.3	Preprocessor Input File (.pf)	32
	12.1.4	Directives	33
		12.1.4.1 @Test	33
		12.1.4.2 @MPITest	33
		12.1.4.3 @Assert	34
		12.1.4.4 @Parameters	35
		12.1.4.5 @TestCase	35
13	@Assert Pre	processor Directives	37
	13.1 @Asset	rt Preprocessor Directives	38
	13.1.1	@assertEqual	38
	13.1.2	@assertTrue	38
	13.1.3	@assertFalse	38
	13.1.4	@assertLessThan	38
	13.1.5	@assertLessThanOrEqual	38
	13.1.6	@assertGreaterThan	38
	13.1.7	@assertGreaterThanOrEqual	38
	13.1.8	@assertIsMemberOf	38
	13.1.9	@assertContains	38
	13.1.10	@assertAny	38
	13.1.11	@assertAll	38
	13.1.12	@assertNotAll	38
	13.1.13	@assertNone	38
	13.1.14	@assertIsPermutationOf	38

V	CONTENTS
	~~

	13	3.1.15 @assertExceptionRaised	38
	13	3.1.16 @assertSameShape	38
	13	3.1.17 @assertIsNaN	38
	13	3.1.18 @assertIsFinite	38
1.1	Dovinie	on Notes	20
14	Revisio	on Notes	39
15	Data Ty	ype Index	41
	15.1 C	lass Hierarchy	41
16	Data Ty	ype Index	45
	16.1 D	ata Types List	45
17	Data Ty	ype Documentation	51
	17.1 A	bstractTestParameter_mod Module Reference	51
	17.2 pl	FUnitParser::Action Class Reference	51
	17.3 a	dd_mod Module Reference	52
	17.4 a	ddComplex_mod Module Reference	53
	17.5 C	odeUtilities::ArrayDescription Class Reference	53
	17.6 A	ssert_mod Module Reference	53
	1	7.6.1 Detailed Description	54
	17.7 A	ssertBasic_mod Module Reference	54
	13	7.7.1 Detailed Description	55
	17.8 A	ssertInteger_mod Module Reference	55
	1	7.8.1 Detailed Description	56
		ienerateRealArrayNewSignature::AssertRealArrayArgument Class - deference	56
	17.10pl	FUnitParser::AtAfter Class Reference	57
	17.11pl	FUnitParser::AtAssert Class Reference	58
	17.12pl	FUnitParser::AtBefore Class Reference	58
	17.13pl	FUnitParser::AtBegin Class Reference	59
		FUnitParser::AtMpiAssert Class Reference	
	17.15pl	FUnitParser::AtMpiTest Class Reference	60

CONTENTS v

17.16pFUnitParser::AtSuite Class Reference 61
17.17pFUnitParser::AtTest Class Reference 61
17.18pFUnitParser::AtTestCase Class Reference 62
17.19pFUnitParser::AtTestParameter Class Reference 63
17.20TestCaseB_mod::B_Parameter Type Reference 63
17.21BaseTestRunner_mod Module Reference 64
17.21.1 Detailed Description
17.22BeforeAfter_mod Module Reference
17.23BrokenSetUpCase_mod Module Reference 65
17.24BrokenTestCase_mod Module Reference
17.25TestCaseC_mod::C_Parameter Type Reference
17.26Cases_mod Module Reference
17.27GenerateRealArrayNewSignature::constraintASSERTEQUAL Class Reference
17.27.1 Constructor & Destructor Documentation 67
17.27.1.1init
17.27.2 Member Data Documentation
17.27.2.1 name1
17.27.2.2 tolerance
17.28mods::pre::pre2::dataString Class Reference
17.29DebugListener_mod Module Reference 69
17.29.1 Detailed Description
17.30CodeUtilities::declaration Class Reference
17.31 DynamicTestCase_mod Module Reference
17.31.1 Detailed Description
17.32Exception_mod Module Reference
17.33Fixture_mod Module Reference
17.34FixtureTestCase_mod Module Reference
17.35CodeUtilities::fortranSubroutineSignature Class Reference
17.36Halo_mod Module Reference
17.37mods::pre_lf::lfDirective Class Reference

vi CONTENTS

17.38CodeUtilities::implementation Class Reference
17.39CodeUtilities::interfaceBlock Class Reference
17.40 mods::pre::pre_If::interval Class Reference
17.41GenerateRealArrayNewSignature::IsWithinTolerance Class Reference . 75
17.42Test_RestrictSphericalCoordinates_mod::LatLonCase Type Reference . 76
17.43LinearInterpolator_mod Module Reference
17.44MakeInfinity_mod Module Reference
17.44.1 Detailed Description
17.45MakeNaN_mod Module Reference
17.45.1 Detailed Description
17.46 MockCall_mod Module Reference
17.46.1 Detailed Description
17.47MockListener_mod Module Reference
17.48testParser::MockParser Class Reference
17.49MockRepository_mod Module Reference
17.49.1 Detailed Description
17.50 MockSUT_mod Module Reference
17.51testParser::MockWriter Class Reference
17.52CodeUtilities::module Class Reference
17.53MpiContext_mod Module Reference
17.53.1 Detailed Description
17.54MpiStubs_mod Module Reference
17.54.1 Detailed Description
17.55MpiTestCase_mod Module Reference
17.55.1 Detailed Description
17.56MpiTestCaseB_mod::MpiTestCaseB Type Reference
17.57MpiTestCaseB_mod Module Reference
17.58MpiTestMethod_mod Module Reference
17.58.1 Detailed Description
17.59MpiTestParameter_mod Module Reference
17.60pFUnitParser::MyError Class Reference

CONTENTS vii

17.61Cases_mod::MyParamType Type Reference
17.62Cases_mod::MyTestCase Type Reference
17.63TestCaseC_mod::newC_Parameter Interface Reference
17.64ParallelContext_mod Module Reference
17.64.1 Detailed Description
17.65ParallelException_mod Module Reference
17.65.1 Detailed Description
17.66ParameterizedTestCase_mod Module Reference
17.66.1 Detailed Description
17.67Params_mod Module Reference
17.67.1 Detailed Description
17.68pFUnitParser::Parser Class Reference
17.69Test_Parameters_mod::peCase Type Reference
17.70pFUnit Module Reference
17.70.1 Detailed Description
17.71pFUnit_mod Module Reference
17.71.1 Detailed Description
17.72PrivateException_mod Module Reference
17.72.1 Detailed Description
17.73mods::pre::pre2::procDirective Class Reference
17.73.1 Member Function/Subroutine Documentation 96
17.73.1.1 addTokenRE
17.74RemoteProxyTestCase_mod Module Reference
17.74.1 Detailed Description
17.75mods::pre::pre_Repeat::RepeatDirective Class Reference
17.76ResultPrinter_mod Module Reference
17.76.1 Detailed Description
17.77RobustRunner_mod Module Reference
17.77.1 Detailed Description
17.78robustTestSuite_mod Module Reference
17.79CodeUtilities::routineUnit Class Reference

viii CONTENTS

17.80 SerialContext_mod Module Reference
17.80.1 Detailed Description
17.81 SimpleTestCase_mod Module Reference
17.82SourceLocation_mod Module Reference
17.82.1 Detailed Description
17.83 Spherical Coordinates_mod Module Reference
17.84TestListener_mod::startTest Interface Reference
17.85StringConversionUtilities_mod Module Reference
17.85.1 Detailed Description
17.86SubsetRunner_mod Module Reference
17.86.1 Detailed Description
17.87SurrogateTestCase_mod Module Reference
17.87.1 Detailed Description
17.88SUT_mod Module Reference
17.89Test_Assert_mod Module Reference
17.90Test_AssertBasic_mod Module Reference
17.91Test_AssertComplex_mod Module Reference
17.92Test_AssertInteger_mod Module Reference
17.93Test_AssertReal_mod Module Reference
17.94Test_BasicOpenMP_mod Module Reference
17.95Test_Exception_mod Module Reference
17.96Test_FixtureTestCase_mod Module Reference
17.97Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 110
17.98Test_LinearInterpolator_mod Module Reference
17.99Test_MockCall_mod Module Reference
17.10@Test_MockRepository_mod Module Reference
17.10 Test_mod Module Reference
17.101. Detailed Description
17.10 <b>T</b> est_MpiContext_mod Module Reference
17.103est_MpiException_mod Module Reference
17.104est_MpiTestCase_mod Module Reference

CONTENTS ix

17.105est_Parameters_mod::Test_Parameters Type Reference
17.10 <b>6</b> est_Parameters_mod Module Reference
17.10 <b>T</b> est_RestrictSphericalCoordinates_mod::Test_RestrictSpherical- Coordinates Type Reference
17.10 <b>8</b> est_RestrictSphericalCoordinates_mod Module Reference
17.10 <b>9</b> est_RobustRunner_mod Module Reference
17.11 <b>0</b> est_SimpleTestCase_mod Module Reference
17.11 <b>T</b> est_StringConversionUtilities_mod Module Reference
17.11 <b>2</b> rest_TestMethod_mod Module Reference
17.113est_TestResult_mod Module Reference
17.114est_TestSuite_mod Module Reference
17.115est_UnixProcess_mod Module Reference
17.116 est A_mod Module Reference
17.117estCase_mod Module Reference
17.117. Detailed Description
17.11 <b>8</b> estCaseA_mod::TestCaseA Type Reference
17.11¶estCaseA_mod Module Reference
17.12 <b>0</b> estCaseB_mod::TestCaseB Type Reference
17.12TestCaseB_mod Module Reference
17.12 <b>T</b> estCaseC_mod::TestCaseC Type Reference
17.12 <b>3</b> estCaseC_mod Module Reference
17.124estFailure_mod Module Reference
17.124. Detailed Description
17.125nods::pre_:pre_lf::TestlfDirective Class Reference
17.12@nods::pre::interleavedp::TestInterleaved Class Reference
17.12 <b>7</b> estListener_mod Module Reference
17.127. Detailed Description
17.128estMethod_mod Module Reference
17.128. Detailed Description
17.12@nods::pre::parseArgs::TestParseArgs Class Reference
17.13@estParser::TestParseLine Class Reference

x CONTENTS

17.130. Member Function/Subroutine Documentation	. 127
17.130.1.1testAtMpiTest	. 127
17.130.1.2lestAtTest	. 127
17.130.1.3testAtTestFail	. 127
17.130.1.4testAtTestNoParens	. 127
17.130.1.5estAtTestSkipComment	. 127
17.130.1.@estMatchAtAfter	. 127
17.130.1.7testMatchAtAssertEqual	. 128
17.130.1.8testMatchAtAssertOther	. 128
17.130.1.9testMatchAtBefore	. 128
17.130.1.1testMatchAtMpiAssert	. 128
17.130.1.1testMatchAtSuite	. 128
17.130.1.112estMatchAtTestCase	. 128
17.13 mods::pre::pre_Repeat::TestRepeatDirective Class Reference	. 128
17.13 <b>Z</b> estResult_mod Module Reference	. 129
17.132. Detailed Description	. 129
17.13 <b>3</b> estRunner_mod Module Reference	. 130
17.133. Detailed Description	. 130
17.134estSuite_mod Module Reference	. 131
17.134. Detailed Description	. 131
17.135 hrowFundamentalTypes_mod Module Reference	. 131
17.135. Detailed Description	. 132
17.136 Inix Pipe Interfaces _ mod Module Reference	. 132
17.136. Detailed Description	. 133
17.13®nixProcess_mod Module Reference	. 133
17.137. Detailed Description	. 133
17.13&enerateRealArrayNewSignature::VECTOR_NORM Class Reference	. 134
17.139VrapbeforeAfter Module Reference	. 135
17.14@VrapMpiTestCaseB_mod Module Reference	. 135
17.14Wrapsimple Module Reference	. 135
17.142VrapTestA_mod Module Reference	. 135

CONTENTS	xi
17.143VrapTestCaseA mod Module Reference	136
17.14WrapTestCaseB_mod Module Reference	136

# pFUnit 2 - Documentation - Version 0.0 (2014-0206-0848 MLR)

Quick link to the code!

### 1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

### 1.2 Contents

- Installation
  - Obtaining pFUnit
- Usage

- Development
- · Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

### 1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

### 1.4 LICENSE

Rights of use for GSC-15,137-1 F-UNIT, also known as pFUnit, are defined by the N-ASA Open Source Agreement (version 1.3). The LICENSE document may be found in the head directory of the pFUnit distribution.

## 1.5 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

# **Obtaining pFUnit**

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

# Installation

## 3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- · Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
  - Building pFUnit for testing serial codes (Non-MPI)
  - Building pFUnit for testing parallel codes (MPI)
  - OPENMP
  - Cleaning
  - Documentation
- Installation

# 3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.3, 4.9.0, IBM's XLF)
- The Message Passing Interface (MPI)
- OpenMP
- · GNU Make
- Python

Note: Recent changes have exposed a latent bug in GCC 4.8.2. The fix is available in the GCC 4.9 development branch and will also appear in GCC 4.8.3 when that is released. Users that require older versions of GCC should use pFUnit 2.1.x.

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

### 3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

### 3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

3.5 Configuration 7

CMakeLists.txt - Initial support for cmake-based builds.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

GNUmakefile - The top level makefile for building and installing pFUnit.

LICENSE - The NASA Open Source Agreement for GSC-15,137-1 F-UNIT, also known as pFUnit.

README-INSTALL - Basic documentation on pFUnit installation and use.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

### 3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90\_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90\_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

8 Installation

```
$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen
```

## 3.6 Building pFUnit

### 3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (for example in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

### 3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

#### **3.6.3 OPENMP**

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

```
$ make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

### 3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src\_clean' to remove intermediate products in subdirectories.

#### 3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following from the top level of your pFUnit distribution.

Or to make a reference manual.

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

10 Installation

#### 3.6.6 **CMAKE**

Initial support for CMAKE has been implemented. At this writing, a basic functionality is available.

3. The process for building pFUnit using cmake is as follows. In the top directory of the distribution make a new directory to support the build, then change to that directory and run cmake (pointing back to the source) to generate the required makefiles.

```
$ mkdir build
$ cd build
$ # e.g. cmake -DMPI=YES -DOPENMP=NO -DINSTALL_PATH=<A path> <path to source>
$ cmake -DMPI=NO ..
$ make tests
```

One may also set the environment variable PFUNIT instead of setting INSTALL\_PATH on the cmake command line as given above.

4. If the build is successful, then at this point make install should work.

#### 3.7 Installation

#### 3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL\_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL\_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ cd Examples
$ ./buildIt
```

#### 3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

3.7 Installation 11

To test, set PFUNIT and go into Examples/MPI\_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

#### 3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

#### 3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL\_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

12 Installation

# **Usage**

- Usage Configuration
- Usage Hello World
- Usage Preprocessor
- · Compiling and Executing The Test

## 4.1 Usage

### 4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90\_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

### 4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
```

14 Usage

```
subroutine testHelloWorld()
  use pfunit_mod
  implicit none
  @assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

### 4.2 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

# 4.3 Compiling and Executing The Test

An example of a GNU make rule for for the final step of compiling a test follows.

To execute the tests, one invokes "./tests.x" with the appropriate command line options (see below).

### 4.3.1 - Compiling and Executing the Tests (MPI PARALLEL)

One invokes MPI-based parallel tests according to the MPI framework being used. For example:

```
$ mpirun -np 4 tests.x
```

## 4.3.2 Command Line Options

The executable test program provides several command line options, when "include/driver.F90" is used, as it is automatically when using the PFUNIT preprocessor.

-v or -verbose	Verbose execution.
-d or -debug	Provide debugging information.
-h	Print help message.
-o <outputfile></outputfile>	Direct pFUnit messages to a file.
-robust	Use the robust runner. Runs tests as
	processes so failures do not halt testing.
-skip <number of="" skip="" tests="" to=""></number>	Use the subset runner, which runs a
	subset of the tests in a suite.

An example from Examples/Robust:

\$ ./tests.x -robust

16 Usage

# **Development**

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL\_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

18 Development

# Feedback & Support

- Feedback
- Support

### 6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

## 6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

# **FAQ** and Tips

- FAQ
  - Zero Tests Run
  - Some Tests Are Not Running
- Tips
  - Environment Modules
  - Compile Time Errors
  - Intermediate files used by pFUnit

### 7.1 FAQ

### 7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD\_TEST\_SUITE (the\_suite\_to\_add), one to a line.
- There is no <code>-DUSE\_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

### 7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

22 FAQ and Tips

#### Solutions:

There is no -DUSE\_MPI passed to the compiler during the build. Please add as
in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

### 7.2 Tips

#### 7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

#### 7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

### 7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

# **Platform Specific Notes**

### 8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

## 8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

# **Acknowledgments**

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

## **Known Installations & Versions**

master - The cutting edge of pFUnit development.

pfunit\_2.1.0 - A feature freeze prior to a major upgrade of the preprocessor.

# **TODO**

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

30 TODO

# The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
  - Configuration testSuites.inc
  - Invocation
  - Command Line Options
  - Preprocessor Input File (.pf)
  - Directives
    - \* @Test
    - \* @MPITest
    - \* @Assert (or Preprocessor Directives)
    - \* @Parameters
    - \* @TestCase

## 12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's "tests" subdirectory.

### 12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

#### 12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

#### 12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' "tests" subdirectories in the -Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
  - @Assert

#### 12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

#### 12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive. For example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

#### 12.1.4.2 @MPITest

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI\_Halo:

```
@mpiTest( npes=[1,2,3])
subroutine testHaloInterior(this)
   use Halo_mod
   use pfunit_mod
   implicit none
   class (MpiTestMethod) :: this

   integer, parameter :: N = 2
   real :: a(N,0:N+1)
   integer :: p

   p = this%getProcessRank()
   a(:,1:N) = p
   a(:,0) = -1
   a(:,N+1) = -1

   call haloFill(a, this%getMpiCommunicator())
@assertEqual(real(p), a(1,1))
```

```
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

#### 12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found, 'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- · @assertTrue
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains
- @assertAny
- @assertAll
- @assertNotAll
- · @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- · @assertSameShape
- · @assertIsNaN
- · @assertIsFinite

#### 12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

#### 12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

# **@Assert Preprocessor Directives**

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

I3.1 @Assert	Preprocessor	<b>Directives</b>
--------------	--------------	-------------------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

## **Revision Notes**

- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
   MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

40 Revision Notes

# **Data Type Index**

## 15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter_mod	51
pFUnitParser::Action	51
pFUnitParser::AtAfter	57
pFUnitParser::AtAssert	58
pFUnitParser::AtBefore	58
pFUnitParser::AtBegin	59
pFUnitParser::AtMpiAssert	59
pFUnitParser::AtSuite	61
pFUnitParser::AtTest	61
pFUnitParser::AtMpiTest	60
pFUnitParser::AtTestCase	62
pFUnitParser::AtTestParameter	63
add_mod	52
addComplex_mod	53
CodeUtilities::ArrayDescription	53
Assert_mod	53
AssertBasic_mod	54
AssertInteger_mod	55
GenerateRealArrayNewSignature::AssertRealArrayArgument	56
TestCaseB_mod::B_Parameter	63
BaseTestRunner_mod	64
BeforeAfter_mod	65
BrokenSetUpCase_mod	65
BrokenTestCase_mod	65
TestCaseC_mod::C_Parameter	66

Cases_mod
mods::pre2::dataString
DebugListener_mod
CodeUtilities::declaration
DynamicTestCase_mod
Exception_mod
Fixture_mod
FixtureTestCase_mod
CodeUtilities::fortranSubroutineSignature
Halo_mod
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre_:pre_If::interval
Test_RestrictSphericalCoordinates_mod::LatLonCase
LinearInterpolator_mod
MakeInfinity_mod
MakeNaN_mod
MockCall_mod
MockListener_mod
MockRepository_mod
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
MpiStubs_mod
MpiTestCase_mod
MpiTestCaseB_mod::MpiTestCaseB
MpiTestCaseB_mod
MpiTestMethod_mod
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC_mod::newC_Parameter
ParallelContext mod
ParallelException_mod
ParameterizedTestCase_mod
Params mod
pFUnitParser::Parser
testParser::MockParser
Test_Parameters_mod::peCase
pFUnit
pFUnit_mod
PrivateException_mod
mods::pre::pre2::procDirective

mods::pre::pre_lf::lfDirective	
RemoteProxyTestCase_mod	. 97
ResultPrinter mod	
RobustRunner mod	
robustTestSuite_mod	
CodeUtilities::routineUnit	
GenerateRealArrayNewSignature::constraintASSERTEQUAL	
GenerateRealArrayNewSignature::IsWithinTolerance	
GenerateRealArrayNewSignature::VECTOR_NORM	
SerialContext_mod	
SimpleTestCase_mod	
SourceLocation_mod	
SphericalCoordinates_mod	
TestListener_mod::startTest	
StringConversionUtilities_mod	
SubsetRunner_mod	
SurrogateTestCase_mod	
SUT_mod	
Test_Assert_mod	. 106
Test_AssertBasic_mod	
Test_AssertComplex_mod	
Test_AssertInteger_mod	
Test_AssertReal_mod	. 108
Test_BasicOpenMP_mod	
Test_Exception_mod	
Test_FixtureTestCase_mod	. 110
Test_LinearInterpolator_mod::Test_LinearInterpolator	. 110
Test_LinearInterpolator_mod	. 111
Test_MockCall_mod	. 111
Test_MockRepository_mod	. 111
Test_mod	. 112
Test_MpiContext_mod	. 112
Test_MpiException_mod	
Test_MpiTestCase_mod	. 113
Test_Parameters_mod::Test_Parameters	. 114
Test_Parameters_mod	. 114
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates	. 114
Test_RestrictSphericalCoordinates_mod	. 115
Test_RobustRunner_mod	. 115
Test_SimpleTestCase_mod	. 116
Test_StringConversionUtilities_mod	. 116
Test_TestMethod_mod	. 116
Test_TestResult_mod	. 117
Test_TestSuite_mod	. 117

Test_UnixProcess_mod
TestA_mod
TestCase_mod
TestCaseA_mod::TestCaseA
TestCaseA_mod
TestCaseB_mod::TestCaseB
TestCaseB_mod
TestCaseC_mod::TestCaseC
TestCaseC_mod
TestFailure_mod
mods::pre::pre_lf::TestIfDirective
mods::pre::interleavedp::TestInterleaved
TestListener_mod
TestMethod_mod
mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult_mod
TestRunner_mod
TestSuite_mod
ThrowFundamentalTypes_mod
UnixPipeInterfaces_mod
UnixProcess_mod
WrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA_mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WrapTestCaseC mod 136

# **Data Type Index**

## 16.1 Data Types List

Here are the data types with brief descriptions:

AbstractTestParameter_mod
pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
<briefdescription></briefdescription>
AssertBasic_mod
<briefdescription></briefdescription>
AssertInteger_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::AssertRealArrayArgument
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtSuite
pFUnitParser::AtTest 61
pFUnitParser::AtTestCase
pFUnitParser::AtTestParameter
TestCaseB_mod::B_Parameter
BaseTestRunner_mod
<briefdescription></briefdescription>

BeforeAfter_mod						65
BrokenSetUpCase_mod						65
BrokenTestCase_mod						65
TestCaseC_mod::C_Parameter						66
Cases_mod						66
GenerateRealArrayNewSignature::constraintASSERTEQUAL						67
mods::pre::pre2::dataString						68
DebugListener_mod						
<briefdescription></briefdescription>						69
CodeUtilities::declaration						70
DynamicTestCase_mod						
<briefdescription></briefdescription>						70
Exception_mod						71
Fixture_mod						72
FixtureTestCase_mod						72
CodeUtilities::fortranSubroutineSignature						72
Halo mod						73
mods::pre_lf::lfDirective						73
CodeUtilities::implementation						74
CodeUtilities::interfaceBlock						74
mods::pre::pre_lf::interval						74
GenerateRealArrayNewSignature::IsWithinTolerance						75
Test_RestrictSphericalCoordinates_mod::LatLonCase						76
LinearInterpolator_mod						76
MakeInfinity_mod				-	· -	
<briefdescription></briefdescription>						76
MakeNaN mod				-	· -	
<pre></pre>						77
MockCall mod				-	· -	
<pre><briefdescription></briefdescription></pre>						78
MockListener mod						79
testParser::MockParser						79
MockRepository mod					-	. •
<briefdescription></briefdescription>						80
MockSUT mod						80
testParser::MockWriter						81
CodeUtilities::module						
MpiContext_mod	•	•	•		•	•
<briefdescription></briefdescription>						82
MpiStubs mod					-	-
<pre><briefdescription></briefdescription></pre>						83
MpiTestCase mod	•		•	•	-	
<pre><briefdescription></briefdescription></pre>						84
MpiTestCaseB_mod::MpiTestCaseB						85
MpiTestCaseB_mod						85
p.::5555800	•				•	

MpiTestMethod_mod
<pre></pre>
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC_mod::newC_Parameter 88
ParallelContext mod
<pre><briefdescription></briefdescription></pre>
ParallelException_mod
<pre></pre>
ParameterizedTestCase mod
<pre></pre>
Params mod
<pre></pre>
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
<pre><briefdescription></briefdescription></pre>
pFUnit mod
<pre></pre>
PrivateException_mod
<pre></pre>
mods::pre::pre2::procDirective
RemoteProxyTestCase_mod
<briefdescription></briefdescription>
mods::pre::pre_Repeat::RepeatDirective
ResultPrinter_mod
<briefdescription></briefdescription>
RobustRunner_mod
<briefdescription></briefdescription>
robustTestSuite_mod
CodeUtilities::routineUnit
SerialContext_mod
<briefdescription></briefdescription>
SimpleTestCase_mod
SourceLocation_mod
<briefdescription></briefdescription>
SphericalCoordinates_mod
TestListener_mod::startTest
StringConversionUtilities_mod
<briefdescription></briefdescription>
SubsetRunner_mod
<briefdescription></briefdescription>
SurrogateTestCase_mod
<briefdescription></briefdescription>

SUI_mod
Test_Assert_mod
Test_AssertBasic_mod
Test_AssertComplex_mod
Test_AssertInteger_mod
Test_AssertReal_mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test_FixtureTestCase_mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
Test_MockCall_mod111
Test_MockRepository_mod
Test_mod
<briefdescription></briefdescription>
Test_MpiContext_mod112
Test_MpiException_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
$Test\_RestrictSphericalCoordinates\_mod:: Test\_RestrictSphericalCoordinates \ . \ 114$
Test_RestrictSphericalCoordinates_mod
Test_RobustRunner_mod
Test_SimpleTestCase_mod
Test_StringConversionUtilities_mod
Test_TestMethod_mod
Test_TestResult_mod
Test TestSuite mod
Tool_ToolOutto_mod
Test_UnixProcess_mod
Test_UnixProcess_mod
Test_UnixProcess_mod
Test_UnixProcess_mod
Test_UnixProcess_mod
Test_UnixProcess_mod       117         TestA_mod       118         TestCase_mod       \$\text{SriefDescription}\$ \tag{118}         TestCaseA_mod::TestCaseA       119
Test_UnixProcess_mod       117         TestA_mod       118         TestCase_mod       8riefDescription>       118         TestCaseA_mod::TestCaseA       119         TestCaseA_mod       119
Test_UnixProcess_mod       117         TestA_mod       118         TestCase_mod       118 <briefdescription>       118         TestCaseA_mod::TestCaseA       119         TestCaseA_mod       119         TestCaseB_mod::TestCaseB       120</briefdescription>
Test_UnixProcess_mod       117         TestA_mod       118         TestCase_mod         118         TestCaseA_mod::TestCaseA       119         TestCaseA_mod       119         TestCaseB_mod::TestCaseB       120         TestCaseB_mod       120         TestCaseC_mod::TestCaseC       121
Test_UnixProcess_mod       117         TestA_mod       118         TestCase_mod         118         TestCaseA_mod::TestCaseA       119         TestCaseA_mod       119         TestCaseB_mod::TestCaseB       120         TestCaseC_mod::TestCaseC       121
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122           TestFailure_mod         122
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122           TestFailure_mod           22           EriefDescription>         122
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122           TestFailure_mod           122           CBriefDescription>         122           mods::pre::pre_lf::TestlfDirective         123
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122           TestFailure_mod         2           SriefDescription>         122           mods::pre::pre_lf::TestlfDirective         123           mods::pre::interleavedp::TestInterleaved         124
Test_UnixProcess_mod         117           TestA_mod         118           TestCase_mod           118           TestCaseA_mod::TestCaseA         119           TestCaseA_mod         119           TestCaseB_mod::TestCaseB         120           TestCaseB_mod         120           TestCaseC_mod::TestCaseC         121           TestCaseC_mod         122           TestFailure_mod           122           mods::pre::pre_lf::TestlfDirective         123           mods::pre::interleavedp::TestInterleaved         124           TestListener_mod         124

mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult_mod
<briefdescription> Note: A possible extension point for user-</briefdescription>
specialized TestResults
TestRunner_mod
<briefdescription></briefdescription>
TestSuite_mod
<briefdescription></briefdescription>
ThrowFundamentalTypes_mod
<briefdescription></briefdescription>
UnixPipeInterfaces_mod
<briefdescription></briefdescription>
UnixProcess_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::VECTOR_NORM
WrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA_mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WrapTestCaseC mod

# **Data Type Documentation**

## 17.1 AbstractTestParameter\_mod Module Reference

**Data Types** 


- type AbstractTestParameter
- interface toString

The documentation for this module was generated from the following file:

AbstractTestParameter.F90

## 17.2 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



### **Public Member Functions**

· def apply

The documentation for this class was generated from the following file:

pFUnitParser.py

## 17.3 add\_mod Module Reference

### **Public Member Functions**

- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- · Robust/src/add.F90
- · Simple/src/add.F90

## 17.4 addComplex\_mod Module Reference

### **Public Member Functions**

complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following file:

· addComplex.F90

## 17.5 CodeUtilities::ArrayDescription Class Reference

### **Public Member Functions**

- def \_\_init\_\_
- def NAME
- def DECLARE
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

### **Public Attributes**

- fType
- kind
- rank

The documentation for this class was generated from the following file:

· CodeUtilities.py

## 17.6 Assert\_mod Module Reference

<BriefDescription>

### 17.6.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

### 17.7 AssertBasic mod Module Reference

<BriefDescription>

### **Data Types**

- · interface assertEqual
- interface assertExceptionRaised
- interface assertFalse
- · interface assertIsFinite
- interface assertIsNaN
- interface assertTrue
- interface fail
- · type UnusableArgument

### **Public Member Functions**

- subroutine assertExceptionRaisedMessage (message)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- logical function, public nonConformable (shapeA, shapeB)

- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN double (x, message, location)
- subroutine assertIsFinite\_single (x, message, location)
- subroutine assertIsFinite\_double (x, message, location)

### 17.7.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertBasic.F90

## 17.8 AssertInteger\_mod Module Reference

<BriefDescription>

### **Data Types**

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

#### **Public Member Functions**

- subroutine assertEqualInteger1D1D\_ (expected, found, message, location)
- subroutine assertEqualInteger0D1D\_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D\_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D\_ (expected, found, message, location)
- subroutine assertLessThan\_ (a, b, message, location)

### 17.8.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

# 17.9 GenerateRealArrayNewSignature::AssertRealArrayArgument Class Reference

### **Public Member Functions**

- def \_\_init\_\_\_
- def updateDescriptions
- def getExpectedDescription
- def getFoundDescription
- def getTolerance

### **Public Attributes**


- expectedFType
- expectedPrecision
- expectedRank
- foundFType
- foundPrecision
- foundRank
- tolerance
- · expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

## 17.10 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

## 17.11 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



### **Public Member Functions**

- def \_\_init\_\_
- def match
- · def appendSourceLocation
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

## 17.12 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



### **Public Member Functions**

- def \_\_init\_\_
- def match
- · def action


#### parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.13 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.14 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- def appendSourceLocation
- def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.15 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



#### **Public Member Functions**

def \_\_init\_\_


- parser
- keyword

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.16 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



#### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.17 pFUnitParser::AtTest Class Reference

Inheritance diagram for pFUnitParser::AtTest:



#### **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

#### **Public Attributes**


- parser
- keyword

The documentation for this class was generated from the following file:

· pFUnitParser.py

# 17.18 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



- def \_\_init\_\_
- def match
- · def action


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.19 pFUnitParser::AtTestParameter Class Reference

Inheritance diagram for pFUnitParser::AtTestParameter:



**Public Member Functions** 

- def init
- def match
- def action

#### **Public Attributes**

· parser

The documentation for this class was generated from the following file:

• pFUnitParser.py

# 17.20 TestCaseB\_mod::B\_Parameter Type Reference

- · procedure toString
- procedure toString

- real phi
- · real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

## 17.21 BaseTestRunner\_mod Module Reference

```
<BriefDescription>
```

## **Data Types**

- type BaseTestRunner
- interface run2

#### **Public Member Functions**

• subroutine setDebug (this)

## 17.21.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

#### 17.22 BeforeAfter\_mod Module Reference

#### **Public Member Functions**

- subroutine first (this)
- subroutine last (this)
- · subroutine succeeds (this)
- subroutine fails (this)

#### **Public Attributes**

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

• Examples/MPI\_Halo/tests/beforeAfter.pf

# 17.23 BrokenSetUpCase\_mod Module Reference

## **Data Types**

• type BrokenSetUpCase

#### **Public Member Functions**

 $\bullet \ \ \mathsf{type}(\mathsf{BrokenSetUpCase}) \ \mathsf{function}, \ \ \mathsf{pointer}, \ \mathsf{public} \ \boldsymbol{\mathsf{newBrokenSetUpCase}} \ ()$ 

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

## 17.24 BrokenTestCase\_mod Module Reference

## **Data Types**

• type BrokenTestCase

#### **Public Member Functions**

• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

# 17.25 TestCaseC\_mod::C\_Parameter Type Reference

#### **Public Member Functions**

- · procedure toString
- · procedure toString

#### **Public Attributes**

- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

## 17.26 Cases\_mod Module Reference

## **Data Types**

- type MyParamType
- type MyTestCase


- type(MyParamType) function newMyParam (i)
- type(MyTestCase) function **newMyTestCase** (param)
- subroutine test\_odd (this)
- subroutine test\_even (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test\_Cases.pf

# 17.27 GenerateRealArrayNewSignature::constraintASSERTEQUA-L Class Reference

Inheritance diagram for GenerateRealArrayNewSignature::constraintASSERTEQUAL:



#### **Public Member Functions**

def init

This next line actually generates the text of the code.

#### **Public Attributes**

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

#### 17.27.1 Constructor & Destructor Documentation

```
17.27.1.1 def GenerateRealArrayNewSignature::constraintASSERTE-QUAL::__init__ ( self, expectedDescr, foundDescr, tolerance )
```

This next line actually generates the text of the code.

#### 17.27.2 Member Data Documentation

#### 17.27.2.1 GenerateRealArrayNewSignature::constraintASSERTEQUAL::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

#### 17.27.2.2 GenerateRealArrayNewSignature::constraintASSERTEQUAL::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

· GenerateRealArrayNewSignature.py

# 17.28 mods::pre::pre2::dataString Class Reference

- def \_\_init\_\_\_
- def insert
- def getLength
- · def getPosition
- · def setPosition
- · def getItem
- def getDataAtPosition
- def getData
- · def getSlice
- · def getSliceForward
- · def removeSlice
- def getCurrentData
- def insertAtCurrent
- · def append
- def advanceAndGetNextData
- def validPosition
- def findToEnd
- · def match
- · def matchToEnd

- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

- data
- · position

The documentation for this class was generated from the following file:

• pre2.py

# 17.29 DebugListener\_mod Module Reference

<BriefDescription>

## **Data Types**

• interface DebugListener

#### **Public Member Functions**

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

## 17.29.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· DebugListener.F90

## 17.30 CodeUtilities::declaration Class Reference

**Public Member Functions** 

- def \_\_init\_\_\_
- · def generate

#### **Public Attributes**

- · simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.31 DynamicTestCase\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface delete
- type DynamicTestCase
- · interface testmethod

#### **Public Member Functions**

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

## 17.31.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

## 17.32 Exception\_mod Module Reference

# **Data Types**

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- interface throw

## **Public Member Functions**

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public catchAny (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()
- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

#### 17.33 Fixture\_mod Module Reference

#### **Public Member Functions**

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following file:

· fixtureTests.pf

## 17.34 FixtureTestCase mod Module Reference

## **Data Types**

- · interface delete
- type FixtureTestCase

#### **Public Member Functions**

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

• FixtureTestCase.F90

# 17.35 CodeUtilities::fortranSubroutineSignature Class Reference

- def \_\_init\_\_
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

## 17.36 Halo\_mod Module Reference

#### **Public Member Functions**

• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

# 17.37 mods::pre::pre\_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre\_lf::lfDirective:



#### **Public Member Functions**

· def evaluate

#### **Public Attributes**

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.38 CodeUtilities::implementation Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- · def generate

**Public Attributes** 

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

## 17.39 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.40 mods::pre::pre\_lf::interval Class Reference

- def \_\_init\_\_
- · def getInterval
- · def setInterval
- def getStart
- def getEnd


- start
- end
- interval

The documentation for this class was generated from the following file:

• pre\_lf.py

# 17.41 GenerateRealArrayNewSignature::IsWithinTolerance Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::lsWithinTolerance:



**Public Member Functions** 

• def \_\_init\_\_

**Public Attributes** 

- rank
- · precision
- name
- fType
- declaration
- declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

# 17.42 Test\_RestrictSphericalCoordinates\_mod::LatLonCase Type - Reference

#### **Public Member Functions**

· procedure toString

#### **Public Attributes**

- real lat
- · real lon
- real restrictedLat
- · real restrictedLon

The documentation for this type was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

# 17.43 LinearInterpolator\_mod Module Reference

## **Data Types**

- interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

· LinearInterpolator.F90

# 17.44 MakeInfinity\_mod Module Reference

<BriefDescription>

- real(r32) function, public makeInf\_32 ()
- real(r64) function, public makeInf\_64 ()

## 17.44.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MakeInfinity.F90

## 17.45 MakeNaN\_mod Module Reference

<BriefDescription>

## **Public Member Functions**

- real(r32) function, public makeNaN\_32 ()
- real(r64) function, public makeNaN\_64 ()

## 17.45.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MakeNaN.F90

## 17.46 MockCall\_mod Module Reference

```
<BriefDescription>
```

## **Data Types**

· type MockCall

## **Public Member Functions**

• type(MockCall) function, public **newMockCall** (name)

#### 17.46.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockCall.F90

## 17.47 MockListener\_mod Module Reference

## **Data Types**

• type MockListener

#### **Public Member Functions**


• subroutine **startTest** (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

## 17.48 testParser::MockParser Class Reference

Inheritance diagram for testParser::MockParser:



#### **Public Member Functions**

- def \_\_init\_\_
- def nextLine
- def reset

## **Public Attributes**

- saveLines
- lines
- outputFile
- outLines
- userTestCase
- userTestMethods
- · currentSelfObjectName

The documentation for this class was generated from the following file:

· testParser.py

# 17.49 MockRepository\_mod Module Reference

<BriefDescription>

## **Data Types**

• type MockRepository

#### **Public Member Functions**

- type(MockRepository) function, pointer, public newMockRepository ()
- · subroutine expectCall (this, obj, method)

## 17.49.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MockRepository.F90

## 17.50 MockSUT mod Module Reference

## **Data Types**

• type MockSUT

#### **Public Member Functions**

- type(MockSUT) function, allocatable, public **newMockSUT** (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

## 17.51 testParser::MockWriter Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- def write

#### **Public Attributes**

parser

The documentation for this class was generated from the following file:

testParser.py

## 17.52 CodeUtilities::module Class Reference

- def \_\_init\_\_
- def generate
- def addDeclaration
- def addImplementation
- · def addRoutineUnit
- def addInterfaceBlock
- · def getName
- · def setFileName
- def getFileName

- name
- · declarations
- · implementations
- generation
- fileName

The documentation for this class was generated from the following file:

CodeUtilities.py

# 17.53 MpiContext\_mod Module Reference

<BriefDescription>

## **Data Types**

- type MpiContext
- interface newMpiContext

#### **Public Member Functions**

- subroutine barrier (this)
- integer function **getMpiCommunicator** (this)

# 17.53.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MpiContext.F90

# 17.54 MpiStubs\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- subroutine, public MPI\_Comm\_rank (comm, rank, ier)
- subroutine, public MPI\_Comm\_size (comm, size, ier)
- subroutine, public MPI\_Comm\_dup (comm, newComm, ier)
- subroutine, public MPI\_Comm\_group (comm, group, ier)
- subroutine, public MPI\_Group\_range\_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI\_Comm\_create (comm, group, newComm, ier)

#### **Public Attributes**

- integer, parameter, public MPI\_COMM\_WORLD = -1
- integer, parameter, public MPI\_COMM\_NULL = -1
- integer, parameter, public MPI\_COMM\_SUCCESS = 0

#### 17.54.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MpiStubs.F90

# 17.55 MpiTestCase\_mod Module Reference

```
<BriefDescription>
```

## **Data Types**

type MpiTestCase

## **Public Member Functions**

- recursive subroutine runBare (this)
- integer function getMpiCommunicator (this)
- integer function getProcessRank (this)

## 17.55.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MpiTestCase.F90

# 17.56 MpiTestCaseB\_mod::MpiTestCaseB Type Reference

#### **Public Member Functions**

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

· integer componentl

The documentation for this type was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

# 17.57 MpiTestCaseB\_mod Module Reference

## **Data Types**

type MpiTestCaseB

#### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

# 17.58 MpiTestMethod\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

## 17.58.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

MpiTestMethod.F90

# 17.59 MpiTestParameter\_mod Module Reference

## **Data Types**

• type MpiTestParameter

## **Public Member Functions**

 type(MpiTestParameter) function, public newMpiTestParameter (num ProcessesRequested) The documentation for this module was generated from the following file:

• MpiTestParameter.F90

# 17.60 pFUnitParser::MyError Class Reference

Inherits Exception.

**Public Member Functions** 

- def \_\_init\_\_
- def \_\_str\_\_

#### **Public Attributes**

value

The documentation for this class was generated from the following file:

• pFUnitParser.py

# 17.61 Cases\_mod::MyParamType Type Reference

**Public Member Functions** 

procedure toString

#### **Public Attributes**

• integer i

The documentation for this type was generated from the following file:

• Test\_Cases.pf

# 17.62 Cases\_mod::MyTestCase Type Reference

#### **Public Attributes**

• integer i

The documentation for this type was generated from the following file:

· Test\_Cases.pf

## 17.63 TestCaseC\_mod::newC\_Parameter Interface Reference

#### **Public Member Functions**

- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)

The documentation for this interface was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

## 17.64 ParallelContext\_mod Module Reference

<BriefDescription>

## **Data Types**

- interface allReduceLogical
- interface gatherInteger
- · interface gatherLogical
- interface gatherString
- · interface getNumProcesses
- type ParallelContext
- · interface processRank
- · interface sum

## 17.64.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelContext.F90

# 17.65 ParallelException\_mod Module Reference

<BriefDescription>

## **Data Types**

- interface any Exceptions
- interface getNumExceptions

#### **Public Member Functions**

• subroutine, public gather (context)

## 17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParallelException.F90

## 17.66 ParameterizedTestCase\_mod Module Reference

```
<BriefDescription>
```

## **Data Types**

• type ParameterizedTestCase

#### **Public Attributes**

• integer, parameter, public MAX\_LEN\_LABEL = 32

## 17.66.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParameterizedTestCase.F90

#### 17.67 Params mod Module Reference

<BriefDescription>

#### **Public Attributes**

- integer, parameter **R32** = selected\_real\_kind(p=6)
- integer, parameter R64 = selected\_real\_kind(p=14)
- integer, parameter **C32** = selected\_real\_kind(p=6)
- integer, parameter C64 = selected\_real\_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

#### 17.67.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Params.F90

# 17.68 pFUnitParser::Parser Class Reference

Inheritance diagram for pFUnitParser::Parser:



#### **Public Member Functions**

- def \_\_init\_\_
- def commentLine
- def run
- def isComment
- · def nextLine
- def printHeader
- def printTail
- def printWrapUserTestCase
- def printRunMethod
- def printParameterHeader
- def printMakeSuite
- def addSimpleTestMethod
- def addMpiTestMethod
- def addUserTestMethod
- def printMakeCustomTest
- def makeWrapperModule
- def final

#### **Public Attributes**

- fileName
- inputFile
- outputFile
- · defaultSuiteName
- suiteName
- currentLineNumber
- userModuleName
- userTestCase
- userTestMethods

- wrapModuleName
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.69 Test\_Parameters\_mod::peCase Type Reference

**Public Member Functions** 

· procedure toString

#### **Public Attributes**

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

# 17.70 pFUnit Module Reference

<BriefDescription>

#### **Public Member Functions**

• integer function run ()

## 17.70.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

# 17.71 pFUnit\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- subroutine, public initialize (useMpi)
- subroutine, public finalize (successful)

## 17.71.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

# 17.72 PrivateException\_mod Module Reference

<BriefDescription>

# **Data Types**

- type Exception
- type ExceptionList
- interface newException

#### **Public Member Functions**

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

# **Public Attributes**

- integer, parameter, public MAXLEN\_MESSAGE = 80\*15
- integer, parameter, public MAXLEN\_FILE\_NAME = 80
- character(len=\*), parameter, public **NULL\_MESSAGE** = "

# 17.72.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Exception.F90

# 17.73 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



#### **Public Member Functions**

- def init
- · def getLength
- · def match
- · def evaluate
- def getNewPosition
- · def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- · def finditerTokenToPosition
- def makeTokenErrorMessage

#### **Public Attributes**

- name
- newPosition
- · tokens
- TokenREs

#### 17.73.1 Member Function/Subroutine Documentation

```
17.73.1.1 def mods::pre::pre2::procDirective::addTokenRE( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = '')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

pre2.py

# 17.74 RemoteProxyTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

• interface RemoteProxyTestCase

## 17.74.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

# 17.75 mods::pre::pre\_Repeat::RepeatDirective Class Reference

 $Inheritance\ diagram\ for\ mods::pre::pre\_Repeat::Repeat Directive:$ 



#### **Public Member Functions**

• def evaluate

#### **Public Attributes**

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_Repeat.py

#### 17.76 ResultPrinter mod Module Reference

<BriefDescription>

# **Data Types**

· type ResultPrinter

#### **Public Member Functions**

- type(ResultPrinter) function, public newResultPrinter (unit)
- subroutine addError (this, testName, exceptions)
- subroutine startTest (this, testName)
- subroutine printHeader (this, runTime)

#### 17.76.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

#### 17.77 RobustRunner\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface RobustRunner
- type TestCaseMonitor

#### **Public Member Functions**

- type(RobustRunner) function newRobustRunner\_unit (remoteRunCommand, unit)
- subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

# 17.77.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RobustRunner.F90

# 17.78 robustTestSuite\_mod Module Reference

#### **Public Member Functions**


- type(TestSuite) function, public suite ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

# 17.79 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



#### **Public Member Functions**

- def \_\_init\_\_\_
- def setName
- · def getName
- def setDeclaration
- · def addDeclaration
- def setImplementation
- · def getDeclaration
- def getDeclarations
- def getImplementation
- def clearDeclarations

#### **Public Attributes**

- name
- declaration
- declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.80 SerialContext\_mod Module Reference

<BriefDescription>

# **Data Types**

· type SerialContext

#### **Public Member Functions**

• type(SerialContext) function, public newSerialContext ()

# **Public Attributes**

 type(SerialContext), parameter, public THE\_SERIAL\_CONTEXT = Serial-Context()

## 17.80.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

# 17.81 SimpleTestCase\_mod Module Reference

# **Data Types**

- · interface method
- type SimpleTestCase

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- · subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete\_ (this)

The documentation for this module was generated from the following file:

• SimpleTestCase.F90

# 17.82 SourceLocation mod Module Reference

<BriefDescription>

# **Data Types**

• type SourceLocation

#### **Public Attributes**

- character(len=MAXLEN\_FILE\_NAME), parameter, public UNKNOWN\_FILE\_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN\_LINE\_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN\_SOURCE\_LOCATION = SourceLocation()

# 17.82.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

# 17.83 SphericalCoordinates\_mod Module Reference

# **Data Types**

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

# 17.84 TestListener\_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

# 17.85 StringConversionUtilities\_mod Module Reference

<BriefDescription>

# **Data Types**

· interface toString

#### **Public Member Functions**

- character(len=len\_trim(a)+1+len\_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)

#### **Public Attributes**

• integer, parameter, public MAXLEN\_STRING = 80

#### 17.85.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

# 17.86 SubsetRunner\_mod Module Reference

<BriefDescription>

# **Data Types**

· interface SubsetRunner

#### **Public Member Functions**

- subroutine addFailure (this, testName, exceptions)
- subroutine **startTest** (this, testName)

#### 17.86.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SubsetRunner.F90

# 17.87 SurrogateTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

#### 17.87.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

# 17.88 SUT\_mod Module Reference

**Data Types** 

• type SUT

The documentation for this module was generated from the following file:

Test\_MockRepository.F90

# 17.89 Test\_Assert\_mod Module Reference

**Public Member Functions** 

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test\_Assert.F90

#### 17.90 Test AssertBasic mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()

The documentation for this module was generated from the following file:

Test AssertBasic.F90

# 17.91 Test\_AssertComplex\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testEquals C complexScalar ()
- subroutine testEquals C 0D1D ()
- subroutine testEquals\_C\_1D\_nonConformable1 ()
- subroutine testEquals C 2D SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent1
- subroutine testEquals C MultiD SingleElementDifferent2
- subroutine testEquals C MultiD SingleElementDifferent3
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent4
- subroutine testEquals C MultiD SingleElementDifferent5
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff1 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff5 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff6 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals C MultiDWithTolerance ()
- subroutine testEquals\_C\_MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals\_C\_MultiDWithTolerance64\_1 ()

- subroutine testEquals C MultiDWithTolerance64 2 ()
- subroutine testEquals\_C\_MultiDSourceLocation ()
- subroutine testEquals\_4DPComplex\_DifferenceReport ()
- · subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

Test\_AssertComplex.F90

# 17.92 Test\_AssertInteger\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertEqual equal ()

The documentation for this module was generated from the following file:

Test\_AssertInteger.F90

# 17.93 Test\_AssertReal\_mod Module Reference

## **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testEquals\_0D1D ()
- subroutine testEquals\_1D\_nonConformable1 ()
- subroutine testEquals 2D SingleElementDifferent ()
- subroutine testEquals\_MultiD\_SingleElementDifferent ()
- subroutine testEquals\_MultiD\_SingleElementDifferent1
- subroutine testEquals\_MultiD\_SingleElementDifferent2
- subroutine testEquals\_MultiD\_SingleElementDifferent3
- subroutine testEquals\_MultiD\_SingleElementDifferent4
- subroutine testEquals\_MultiD\_SingleElementDifferent5
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff ()
   subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff1 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff5 ()

- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff7 ()
- subroutine testEquals\_MultiDMultiPrec\_SingleEltDiff8 ()
- subroutine testEquals\_ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals\_VectorWithToleranceNoMsg ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals\_MultiDWithTolerance1 ()
- subroutine testEquals MultiDWithTolerance64 ()
- subroutine testEquals\_MultiDWithTolerance64\_1 ()
- subroutine testEquals\_MultiDWithTolerance64\_2 ()
- subroutine testEquals\_MultiDSourceLocation ()
- subroutine testEquals\_ScalarAndLocation ()
- subroutine testEquals\_ScalarInfinity\_equal ()
- subroutine testEquals ScalarInfinity unequal A ()
- subroutine testEquals ScalarInfinity unequal B ()
- subroutine testEquals ScalarInfinity unequal C ()
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

• Test AssertReal.F90

# 17.94 Test\_BasicOpenMP\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()
- subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

Test BasicOpenMP.F90

# 17.95 Test\_Exception\_mod Module Reference

#### **Public Member Functions**

• type(TestSuite) function, public suite ()

- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

The documentation for this module was generated from the following file:

• Test Exception.F90

# 17.96 Test\_FixtureTestCase\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test\_FixtureTestCase.F90

# 17.97 Test\_LinearInterpolator\_mod::Test\_LinearInterpolator Type - Reference

**Public Member Functions** 

- procedure setUp
- · procedure tearDown

#### **Public Attributes**

• type(LinearInterpolator) interpolator

The documentation for this type was generated from the following file:

• Test\_LinearInterpolator.pf

# 17.98 Test\_LinearInterpolator\_mod Module Reference

#### **Data Types**

• type Test\_LinearInterpolator

#### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

Test\_LinearInterpolator.pf

#### 17.99 Test MockCall mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

• Test MockCall.F90

# 17.100 Test\_MockRepository\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

# 17.101 Test\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface countTestCases
- interface run
- type Test

# 17.101.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

# 17.102 Test\_MpiContext\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

Test\_MpiContext.F90

# 17.103 Test\_MpiException\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine test\_anyExceptions\_none (this)
- subroutine test getNumExceptions (this)
- subroutine test\_gather (this)

The documentation for this module was generated from the following file:

• Test\_MpiException.F90

# 17.104 Test\_MpiTestCase\_mod Module Reference

# **Data Types**

- · interface method
- type Test\_MpiTestCase

#### **Public Member Functions**

- type(TestSuite) function, public **suite** ()
- type(Test\_MpiTestCase) function, public newTest\_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

Test\_MpiTestCase.F90

# 17.105 Test\_Parameters\_mod::Test\_Parameters Type Reference

#### **Public Attributes**

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

#### 17.106 Test Parameters mod Module Reference

# **Data Types**

- type peCase
- type Test\_Parameters

#### **Public Member Functions**

- type(Test\_Parameters) function newTest (testParameter)
- type(peCase) function newPeCase (p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()
- character(:) function, allocatable toString (this)
- subroutine testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

# 17.107 Test\_RestrictSphericalCoordinates\_mod::Test\_Restrict-SphericalCoordinates Type Reference

#### **Public Attributes**

- real lat
- real lon
- real restrictedLat
- · real restrictedLon

- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted

The documentation for this type was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

# 17.108 Test\_RestrictSphericalCoordinates\_mod Module Reference

# **Data Types**

- type LatLonCase
- type Test\_RestrictSphericalCoordinates

#### **Public Member Functions**

- type(Test\_RestrictSphericalCoordinates) function newTest (testParameter)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test\_RestrictedSphericalCoordinates.pf

# 17.109 Test RobustRunner mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

Test\_RobustRunner.F90

# 17.110 Test\_SimpleTestCase\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()
- subroutine testRunMethodShouldFail ()

The documentation for this module was generated from the following file:

• Test\_SimpleTestCase.F90

# 17.111 Test\_StringConversionUtilities\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test\_StringConversionUtilities.F90

## 17.112 Test TestMethod mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

Test\_TestMethod.F90

#### 17.113 Test\_TestResult\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

· Test TestResult.F90

#### 17.114 Test TestSuite mod Module Reference

# **Data Types**

• type Verbose

#### **Public Member Functions**

- type(TestSuite) function, public **suite** ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()
- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

The documentation for this module was generated from the following file:

• Test TestSuite.F90

# 17.115 Test\_UnixProcess\_mod Module Reference

#### **Public Member Functions**

• type(TestSuite) function, public suite ()

• subroutine testIsActive ()

The documentation for this module was generated from the following file:

• Test\_UnixProcess.F90

# 17.116 TestA\_mod Module Reference

#### **Public Member Functions**

- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)
- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)

The documentation for this module was generated from the following files:

- TestA.F90
- TestA.pf

# 17.117 TestCase\_mod Module Reference

<BriefDescription>

#### **Data Types**

- type ConcreteSurrogate
- type TestCase
- type TestCaseReference

# **Public Member Functions**

- recursive subroutine runBare (this)
- recursive subroutine runBare\_surrogate (this)

# 17.117.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestCase.F90

# 17.118 TestCaseA\_mod::TestCaseA Type Reference

**Public Member Functions** 

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

• integer componentI

The documentation for this type was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

# 17.119 TestCaseA\_mod Module Reference

# **Data Types**

• type TestCaseA

#### **Public Member Functions**

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

# 17.120 TestCaseB\_mod::TestCaseB Type Reference

#### **Public Member Functions**

- procedure setUp
- · procedure tearDown
- procedure setUp
- · procedure tearDown

#### **Public Attributes**

- integer, dimension(:), allocatable table
- · real phi
- · real theta

The documentation for this type was generated from the following files:

- · ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

# 17.121 TestCaseB\_mod Module Reference

# **Data Types**

- type B\_Parameter
- type TestCaseB

#### **Public Member Functions**

- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine **testB** (this)
- · character(:) function, allocatable toString (this)
- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- · ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

# 17.122 TestCaseC\_mod::TestCaseC Type Reference

## **Public Member Functions**

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

#### **Public Attributes**

- integer, dimension(:), allocatable table
- · real phi
- real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- MpiParameterizedTestCaseC.pf

#### 17.123 TestCaseC\_mod Module Reference

#### **Data Types**

- type C\_Parameter
- interface newC Parameter
- type TestCaseC

#### **Public Member Functions**

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)
- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C\_Parameter) function newC\_Parameter\_phiTheta (npes, phi, theta)
- elemental function newC\_Parameter\_case (i)
- type(C\_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

# 17.124 TestFailure mod Module Reference

<BriefDescription>

# **Data Types**

type TestFailure

# 17.124.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

# 17.125 mods::pre::pre\_lf::TestlfDirective Class Reference

**Public Member Functions** 

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse
- def testIFTestTrue1
- def testIFTestTrue2
- def testIFClearTokens
- · def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

• pre\_lf.py

# 17.126 mods::pre::interleavedp::TestInterleaved Class Reference

# **Public Member Functions**

- def test\_InOrder
- · def test NumberMismatch
- def test\_OrderMismatch1
- def test\_OrderMismatch2
- def test\_OrderMismatch3
- def test ElseMid1
- · def test\_ElseMid2
- def test\_ElseMid3
- def test\_ElseMid4
- def test\_ElseMid5
- · def test ElseMid6
- def test\_ElseMid7
- def test\_ElseMid8
- def test\_ElseMid9
- def test ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

#### 17.127 TestListener mod Module Reference

<BriefDescription>

# **Data Types**

- · interface addFailure
- interface endTest
- type ListenerPointer
- interface startTest
- type TestListener

# 17.127.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestListener.F90

# 17.128 TestMethod\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface empty
- interface newTestMethod
- type TestMethod

# 17.128.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

# 17.129 mods::pre::parseArgs::TestParseArgs Class Reference

#### **Public Member Functions**

- · def test\_ParseArgs\_OneArgWithBrackets1
- · def test ParseArgs OneArgWithBrackets2
- def test\_ParseArgs\_OneArgWithBrackets3
- def test\_ParseArgs\_OneArgWithBrackets4
- def test\_ParseArgs\_OneArgWithBrackets5
- def test\_ParseArgs\_OneArgWithBrackets6
- def test\_ParseArgs\_OneArgWithBrackets7
- def test\_ParseArgs\_oneArg
- def test\_ParseArgs\_twoArgs1
- def test\_ParseArgs\_twoArgs2
- · def test ParseArgs oneArgArray1
- def test\_ParseArgs\_TwoArgArray
- def test\_ParseArgs\_ThreeArgs

The documentation for this class was generated from the following file:

· parseArgs.py

#### 17.130 testParser::TestParseLine Class Reference

#### **Public Member Functions**

- def testCppSetLineAndFile
- · def testGetSubroutineName
- · def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtTestNoParens
- def testAtTestFail

- def testAtTestSkipComment
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- · def testMatchAtAssertOther
- def testMatchAtMpiAssert
- · def testMatchAtBefore
- · def testMatchAtAfter
- def testMatchAtSuite

#### 17.130.1 Member Function/Subroutine Documentation

#### 17.130.1.1 def testParser::TestParseLine::testAtMpiTest( self )

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

#### 17.130.1.2 def testParser::TestParseLine::testAtTest( self )

Check that a line starting with ' $\mbox{@test'}$  is detected as an annotation.

#### 17.130.1.3 def testParser::TestParseLine::testAtTestFail ( self )

Check that useful error is sent if next line is not properly formatted.

## 17.130.1.4 def testParser::TestParseLine::testAtTestNoParens ( self )

Check that test procedure with no parens is accepted.

## 17.130.1.5 def testParser::TestParseLine::testAtTestSkipComment ( self )

Ignore comment lines between @test and subroutine foo().

#### 17.130.1.6 def testParser::TestParseLine::testMatchAtAfter( self)

Check that a line starting with '@after\*'  $\dots$ 

#### 17.130.1.7 def testParser::TestParseLine::testMatchAtAssertEqual ( self )

Check that a line starting with '@assertEqual' is detected as an annotation.

#### 17.130.1.8 def testParser::TestParseLine::testMatchAtAssertOther( self)

Check that a line starting with '@assert\*' is detected as an annotation.

#### 17.130.1.9 def testParser::TestParseLine::testMatchAtBefore ( self )

Check that a line starting with '@before\*' ...

#### 17.130.1.10 def testParser::TestParseLine::testMatchAtMpiAssert ( self )

Check that a line starting with '@mpiAssert\*' is detected as an annotation.

#### 17.130.1.11 def testParser::TestParseLine::testMatchAtSuite ( self )

Check that a line starting with '@suite changes the suite name ...

#### 17.130.1.12 def testParser::TestParseLine::testMatchAtTestCase ( self )

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

· testParser.py

# 17.131 mods::pre::pre\_Repeat::TestRepeatDirective Class Reference

#### **Public Member Functions**

- def test\_copyBlock1
- def test\_copyBlock2

- · def test\_copyBlock2Vars
- · def test\_copyBlock2VarsMulti
- def test\_copyBlock2VarsMultiWithStrings
- def test\_copyNaiveRecursion
- def test\_copyNaiveRecursion1
- def test\_copyFunction1

The documentation for this class was generated from the following file:

pre\_Repeat.py

#### 17.132 TestResult mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

# **Data Types**

• type TestResult

#### **Public Member Functions**

- type(TestResult) function, public **newTestResult** ()
- subroutine addError (this, aTest, exceptions)
- integer function failureCount (this)
- subroutine addListener (this, listener)

#### 17.132.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestResult.F90

# 17.133 TestRunner\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

- · interface newTestRunner
- type TestRunner

# **Public Member Functions**

- type(TestRunner) function **newTestRunner\_unit** (unit)
- type(TestResult) function run (this, aTest, context)
- subroutine startTest (this, testName)

# 17.133.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestRunner.F90

#### 17.134 TestSuite\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface newTestSuite
- type TestReference
- type TestSuite

#### **Public Member Functions**

• recursive subroutine addTest (this, aTest)

# 17.134.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestSuite.F90

# 17.135 ThrowFundamentalTypes\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface throwDifferentValues
- interface throwDifferentValuesWithLocation

#### **Public Member Functions**

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN\_SHAPE) function, public locationFormat (iLocation)

## 17.135.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

# 17.136 UnixPipeInterfaces\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface fgets
- interface free
- · interface getdelim
- · interface getline
- · interface pclose
- · interface popen

#### **Public Attributes**

• integer(C\_INT), parameter, public **CLOSE\_FAILED** = -1

# 17.136.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· UnixPipeInterfaces.F90

#### 17.137 UnixProcess mod Module Reference

<BriefDescription>

## **Data Types**

• interface UnixProcess

## **Public Member Functions**

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

# 17.137.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· UnixProcess.F90

# 17.138 GenerateRealArrayNewSignature::VECTOR\_NORM Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::VECTOR\_NORM:



**Public Member Functions** 

• def \_\_init\_\_

**Public Attributes** 

- rank
- fType
- · precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

# 17.139 WrapbeforeAfter Module Reference

The documentation for this module was generated from the following file:

· beforeAfter.F90

# 17.140 WrapMpiTestCaseB\_mod Module Reference

# **Data Types**

- interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, npesRequested)

The documentation for this module was generated from the following file:

· MpiTestCaseB.F90

# 17.141 Wrapsimple Module Reference

The documentation for this module was generated from the following file:

• simple.F90

# 17.142 WrapTestA\_mod Module Reference

The documentation for this module was generated from the following file:

· TestA.F90

# 17.143 WrapTestCaseA\_mod Module Reference

#### **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- · subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod)

The documentation for this module was generated from the following file:

TestCaseA.F90

# 17.144 WrapTestCaseB\_mod Module Reference

# **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

#### **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter)

The documentation for this module was generated from the following file:

• ParameterizedTestCaseB.F90

# 17.145 WrapTestCaseC\_mod Module Reference

#### **Data Types**

- · interface userTestMethod
- type WrapUserTestCase

# **Public Member Functions**

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter, npesRequested)

The documentation for this module was generated from the following file:

• MpiParameterizedTestCaseC.F90