pFUnit

Generated by Doxygen 1.7.6

Fri Sep 5 2014 10:48:44

Contents

1	pFU	nit 3 - Documentation - Version 2014-0905-1355-18-UTC MLR	1
	1.1	Overview	1
	1.2	Contents	1
	1.3	See Also	2
	1.4	LICENSE	2
	1.5	Copyright	2
2	Obta	aining pFUnit	3
3	Insta	allation	5
	3.1	Installing pFUnit	5
	3.2	Prerequisites	5
	3.3	Obtaining pFUnit	6
	3.4	Manifest - What's in the directory?	6
	3.5	Configuration	7
	3.6	Building pFUnit	8
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8
		3.6.3 OPENMP	9
		3.6.4 Cleaning	9
		3.6.5 Documentation	9
		3.6.6 CMAKE	0
	2.7	Installation	. ^

	00175176
1	CONTENTS
1	OOMILIAIS

		3.7.1	Installation - Serial	 10
		3.7.2	Installation - MPI	 11
		3.7.3	Installation - OPENMP	 11
		3.7.4	Installation - DEFAULT DIRECTORY	 11
4	Usa	ge		13
	4.1	Usage		 13
		4.1.1	Usage - Configuration	 13
		4.1.2	Usage - Hello World	 13
	4.2	Usage	- Preprocessor	 14
	4.3	Compi	ling and Executing The Test	 14
		4.3.1	- Compiling and Executing the Tests (MPI PARALLEL)	 14
		4.3.2	Command Line Options	 15
5	Dev	elopmei	nt	17
6	Feed	dback &	Support	19
	6.1	Feedba	ack	 19
	6.2	Suppo	rt	 19
7	FAG	and Tip	ps	21
	7.1	FAQ .		 21
		7.1.1	Zero Tests Run	 21
		7.1.2	Some Tests Are Not Running	 22
		7.1.3	Intel Fortran Version 13: -DINTEL_13	 22
	7.2	Tips .		 22
		7.2.1	Environment Modules	 22
		7.2.2	Compile Time Errors	 22
		7.2.3	Intermediate files used by pFUnit	 23
		7.2.4	Ignoring whitespace in assertions on strings	 23
8	Plat	form Sp	pecific Notes	25
	8.1	Mac O	sx	 25

iii

	8.2		vs/CYGWII											
	8.3	Intel Fo	rtran Versi	on 13:	DINT	ΓEL_1	3.	 						25
9	Ackr	nowledg	ments											27
40	1 /			V!										00
10	Knov	wn insta	allations &	versi	ons									29
11	TOD	0												31
12	The	Prenroc	essor - pF	IlnitP	areer									33
12		_	The Prepro											
	12.1		•											
			Configura											
			Invocation											
			Preproces											
		12.1.4	Directives											
			12.1.4.1											
			12.1.4.2		ITest									
			12.1.4.3	@Ass										
			12.1.4.4	@Par	amete	rs .		 						37
			12.1.4.5	@Tes	tCase			 					٠	37
13	@As	sert Pre	eprocesso	r Dire	ctives	i								39
	13.1	@Asse	rt Preproce	essor I	Directiv	ves .		 						40
		13.1.1	@assertE	qual .				 						40
		13.1.2	@assertT	rue .				 	 					40
		13.1.3	@assertF	alse .				 	 					40
		13.1.4	@assertL	.essTh	an .			 	 					40
		13.1.5	@assertL	.essTh	anOrE	qual		 	 					40
		13.1.6	@assert@	Greater	Than			 	 					40
		13.1.7	@assert@	Greater	Than(OrEqu	al .	 	 					40
		13.1.8	@assertIs											
			@assertC											
			@assertA											
			-	•										

iv CONTENTS

	13.1.11 @assertAll	. 40
	13.1.12 @assertNotAll	. 40
	13.1.13 @assertNone	. 40
	13.1.14 @assertIsPermutationOf	. 40
	13.1.15 @assertExceptionRaised	. 40
	13.1.16 @assertSameShape	. 40
	13.1.17 @assertIsNaN	. 40
	13.1.18 @assertIsFinite	. 40
14	Revision Notes	41
15	Data Type Index	43
	15.1 Class Hierarchy	. 43
16	Data Type Index	49
	16.1 Data Types List	. 49
17	Data Type Documentation	55
	17.1 AbstractTestParameter_mod Module Reference	. 55
	17.2 AbstractTestResult_mod Module Reference	. 55
	17.3 pFUnitParser::Action Class Reference	. 56
	17.4 add_mod Module Reference	. 57
	17.5 addComplex_mod Module Reference	. 57
	17.6 CodeUtilities::ArrayDescription Class Reference	. 57
	17.7 Assert_mod Module Reference	. 58
	17.7.1 Detailed Description	. 58
	17.8 AssertArraysInternalassertEqual_mod Module Reference	. 58
	17.9 AssertArraysInternalassertGreaterThan_mod Module Reference	. 61
	17.10AssertArraysInternalassertGreaterThanOrEqual_mod Module Reference	e 64
	17.11AssertArraysInternalassertLessThan_mod Module Reference	. 68
	17.12AssertArraysInternalassertLessThanOrEqual_mod Module Reference	. 70
	17.13AssertArraysInternalassertNotEqual_mod Module Reference	. 74
	17.14AssertArraysInternalassertRelativelyEqual_mod Module Reference	. 77

CONTENTS v

17.15AssertArraysSupport_mod Module Reference	80
17.16AssertBasic_mod Module Reference	80
17.16.1 Detailed Description	81
17.17AssertComplex0_mod Module Reference	82
17.18AssertComplex1_mod Module Reference	82
17.19AssertComplex2_mod Module Reference	82
17.20AssertComplex3_mod Module Reference	83
17.21 AssertComplex4_mod Module Reference	83
17.22AssertComplex5_mod Module Reference	83
17.23AssertInteger10_mod Module Reference	84
17.24AssertInteger11_mod Module Reference	84
17.25AssertInteger12_mod Module Reference	84
17.26AssertInteger13_mod Module Reference	84
17.27AssertInteger14_mod Module Reference	85
17.28AssertInteger15_mod Module Reference	85
17.29AssertInteger_mod Module Reference	85
17.29.1 Detailed Description	86
17.30AssertReal0_mod Module Reference	86
17.31 AssertReal1_mod Module Reference	87
17.32AssertReal2_mod Module Reference	87
17.33AssertReal3_mod Module Reference	88
17.34AssertReal4_mod Module Reference	88
17.35AssertReal5_mod Module Reference	89
17.36GenerateAssertsOnArrays::AssertRealArrayArgument Class Reference .	89
17.37pFUnitParser::AtAfter Class Reference	90
17.38pFUnitParser::AtAssert Class Reference	90
17.39pFUnitParser::AtBefore Class Reference	91
17.40pFUnitParser::AtBegin Class Reference	92
17.41pFUnitParser::AtMpiAssert Class Reference	92
17.42pFUnitParser::AtMpiTest Class Reference	93
17.43pFUnitParser::AtSuite Class Reference	94

vi CONTENTS

17.44pFUnitParser::AtTest Class Reference
17.45pFUnitParser::AtTestCase Class Reference
17.46pFUnitParser::AtTestParameter Class Reference
17.47TestCaseB_mod::B_Parameter Type Reference
17.48BaseTestRunner_mod Module Reference
17.48.1 Detailed Description
17.49BeforeAfter_mod Module Reference
17.50BrokenSetUpCase_mod Module Reference
17.51 BrokenTestCase_mod Module Reference
17.52TestCaseC_mod::C_Parameter Type Reference
17.53Cases_mod Module Reference
17.54GenerateAssertsOnArrays::constraintASSERT Class Reference 100
17.54.1 Constructor & Destructor Documentation
17.54.1.1init
17.54.2 Member Data Documentation
17.54.2.1 name1
17.54.2.2 tolerance
17.55mods::pre::pre2::dataString Class Reference
17.56 DebugListener_mod Module Reference
17.56.1 Detailed Description
17.57CodeUtilities::declaration Class Reference
17.58 DynamicTestCase_mod Module Reference
17.58.1 Detailed Description
17.59Exception_mod Module Reference
17.60 Fixture_mod Module Reference
17.61 FixtureTestCase_mod Module Reference
17.62CodeUtilities::fortranSubroutineSignature Class Reference
17.63AbstractTestResult_mod::getErrors Interface Reference
17.64Test_mod::getName Interface Reference
17.65AbstractTestResult_mod::getSuccesses Interface Reference
17.66Halo_mod Module Reference

CONTENTS vii

viii CONTENTS

17.90pFUnitParser::MyError Class Reference
17.91 Cases_mod::MyParamType Type Reference
17.92Cases_mod::MyTestCase Type Reference
17.93TestCaseC_mod::newC_Parameter Interface Reference
17.94ParallelContext_mod Module Reference
17.94.1 Detailed Description
17.95 Parallel Exception_mod Module Reference
17.95.1 Detailed Description
17.96 Parameterized Test Case_mod Module Reference
17.96.1 Detailed Description
17.97Params_mod Module Reference
17.97.1 Detailed Description
17.98pFUnitParser::Parser Class Reference
17.99Test_Parameters_mod::peCase Type Reference
17.10pFUnit Module Reference
17.100. Detailed Description
17.10 pFUnit_mod Module Reference
17.101. Detailed Description
17.102 rivate Exception mod Module Reference
17.102. Detailed Description
17.10anods::pre::pre2::procDirective Class Reference
17.103. Member Function/Subroutine Documentation
17.103.1.1addTokenRE
17.10RemoteProxyTestCase_mod Module Reference
17.104. Detailed Description
17.10 fnods::pre::pre_Repeat::RepeatDirective Class Reference
17.10 ResultPrinter_mod Module Reference
17.106. Detailed Description
17.10RobustRunner_mod Module Reference
17.107. Detailed Description
17.108obustTestSuite_mod Module Reference

CONTENTS ix

17.10 © ode Utilities::routine Unit Class Reference	33
17.11&erialContext_mod Module Reference	34
17.110. Detailed Description	35
17.11 SimpleTestCase_mod Module Reference	35
17.11SourceLocation_mod Module Reference	36
17.112. Detailed Description	36
17.11\$phericalCoordinates_mod Module Reference	36
17.114estListener_mod::startTest Interface Reference	37
17.11 S tringConversionUtilities_mod Module Reference	37
17.115. Detailed Description	38
17.11 6 ubsetRunner_mod Module Reference	38
17.116. Detailed Description	38
17.11SurrogateTestCase_mod Module Reference	39
17.117. Detailed Description	39
17.11 & UT_mod Module Reference	40
17.11¶est_Assert_mod Module Reference	40
17.12 0 est_AssertBasic_mod Module Reference	40
17.12Test_AssertComplex_mod Module Reference	40
17.12 T est_AssertInteger_mod Module Reference	41
17.12 3 est_AssertReal_mod Module Reference	42
17.124est_BasicOpenMP_mod Module Reference	43
17.125est_Exception_mod Module Reference	43
17.126fest_FixtureTestCase_mod Module Reference	44
17.127est_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 1	44
17.128est_LinearInterpolator_mod Module Reference	44
17.12¶est_MockCall_mod Module Reference	45
17.130est_MockRepository_mod Module Reference	45
17.13Test_mod Module Reference	45
17.131. Detailed Description	46
17.13 2 est_MpiContext_mod Module Reference	46
17.13 3 est_MpiException_mod Module Reference	47

x CONTENTS

17.134est_MpiParameterizedTestCase_mod Module Reference
17.135est_MpiTestCase_mod Module Reference
17.136 Fest_Parameters_mod::Test_Parameters Type Reference
17.137est_Parameters_mod Module Reference
17.13 \f est_RestrictSphericalCoordinates_mod::Test_RestrictSpherical- Coordinates Type Reference
17.139est_RestrictSphericalCoordinates_mod Module Reference 149
17.14 0 est_RobustRunner_mod Module Reference
17.14Test_SimpleTestCase_mod Module Reference
17.14 Z est_StringConversionUtilities_mod Module Reference
17.143est_TestMethod_mod Module Reference
17.144est_TestResult_mod Module Reference
17.145est_TestSuite_mod Module Reference
17.14 G est_UnixProcess_mod Module Reference
17.147est_XmlPrinter_mod Module Reference
17.147. Detailed Description
17.148estA_mod Module Reference
17.149estCase_mod Module Reference
17.149. Detailed Description
17.15@estCaseA_mod::TestCaseA Type Reference
17.15TestCaseA_mod Module Reference
17.15 Z estCaseB_mod::TestCaseB Type Reference
17.153estCaseB_mod Module Reference
17.154estCaseC_mod::TestCaseC Type Reference
17.155estCaseC_mod Module Reference
17.15 6 estFailure_mod Module Reference
17.156. Detailed Description
17.15 mods::pre::pre_lf::TestlfDirective Class Reference
17.15@hods::pre::interleavedp::TestInterleaved Class Reference
17.15¶estListener_mod Module Reference
17.159. Detailed Description

CONTENTS xi

17.16 T estMethod_mod Module Reference
17.160. Detailed Description
17.16 mods::pre::parseArgs::TestParseArgs Class Reference
17.162estParser::TestParseLine Class Reference
17.162. Member Function/Subroutine Documentation
17.162.1.1testAtMpiTest
17.162.1.2testAtTest
17.162.1.3testAtTestFail
17.162.1.4testAtTestNoParens
17.162.1.5testAtTestSkipComment
17.162.1. destMatchAtAfter
17.162.1.7testMatchAtAssertEqual
17.162.1.&testMatchAtAssertOther
17.162.1.9testMatchAtBefore
17.162.1.1testMatchAtMpiAssert
17.162.1.1testMatchAtSuite
17.162.1.1testMatchAtTestCase
17.162nods::pre::pre_Repeat::TestRepeatDirective Class Reference 164
17.164estResult_mod Module Reference
17.164. Detailed Description
17.165estRunner_mod Module Reference
17.165. Detailed Description
17.16 G estSuite_mod Module Reference
17.166. Detailed Description
17.167hrowFundamentalTypes_mod Module Reference
17.167. Detailed Description
17.168JnixPipeInterfaces_mod Module Reference
17.168. Detailed Description
17.169/nixProcess_mod Module Reference
17.169. Detailed Description
17.17GenerateAssertsOnArrays::VECTOR_NORM Class Reference 169

xii CONTENTS

17.17 AbstractTestResult_mod::wasSuccessful Interface Reference	70
17.172VrapbeforeAfter Module Reference	70
17.17\$WrapMpiTestCaseB_mod Module Reference	70
17.174Wrapsimple Module Reference	71
17.175VrapTestA_mod Module Reference	71
17.176VrapTestCaseA_mod Module Reference	71
17.17 WrapTestCaseB_mod Module Reference	71
17.178VrapTestCaseC_mod Module Reference	72
17.17%mlPrinter_mod Module Reference	72
17.179. Detailed Description	73

pFUnit 3 - Documentation - Version 2014-0905-1355-18-UTC MLR

Quick links to the code or the project's SourceForge site.

1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

1.2 Contents

- Installation
 - Obtaining pFUnit
- Usage

- Development
- · Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

1.4 LICENSE

Rights of use for GSC-15,137-1 F-UNIT, also known as pFUnit, are defined by the N-ASA Open Source Agreement (version 1.3). The LICENSE document may be found in the head directory of the pFUnit distribution.

1.5 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

Installation

3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
 - Building pFUnit for testing serial codes (Non-MPI)
 - Building pFUnit for testing parallel codes (MPI)
 - OPENMP
 - Cleaning
 - Documentation
- Installation

3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.3, 4.9.0, IBM's XLF)
- The Message Passing Interface (MPI)
- OpenMP
- · GNU Make
- Python

Note: Recent changes have exposed a latent bug in GCC 4.8.2. The fix is available in the GCC 4.9 development branch and will also appear in GCC 4.8.3 when that is released. Users that require older versions of GCC should use pFUnit 2.1.x.

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

3.5 Configuration 7

CMakeLists.txt - Initial support for cmake-based builds.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

GNUmakefile - The top level makefile for building and installing pFUnit.

LICENSE - The NASA Open Source Agreement for GSC-15,137-1 F-UNIT, also known as pFUnit.

README-INSTALL - Basic documentation on pFUnit installation and use.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

VERSION - Contains a string describing the current version of the framework.

3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'PFUNIT_MAX_RANK' - controls the maximum size of the arrays asserts are defined over. If PFUNIT_MAX_RANK is not set, the default is 5 and pFUnit's assertions will be able to handle arrays up to rank 5.

8 Installation

```
$ export PFUNIT_MAX_RANK=5
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

\$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen

3.6 Building pFUnit

3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (for example in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

3.6.3 OPENMP

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

```
$ make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src_clean' to remove intermediate products in subdirectories.

3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following from the top level of your pFUnit distribution.

```
$ make documentation
```

Or to make a reference manual.

10 Installation

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

3.6.6 CMAKE

Initial support for CMAKE has been implemented. At this writing, a basic functionality is available.

3. The process for building pFUnit using cmake is as follows. In the top directory of the distribution make a new directory to support the build, then change to that directory and run cmake (pointing back to the source) to generate the required makefiles.

```
$ mkdir build
$ cd build
$ # e.g. cmake -DMPI=YES -DOPENMP=NO -DINSTALL_PATH=<A path> <path to source>
$ cmake -DMPI=NO ..
$ make tests
```

One may also set the environment variable PFUNIT instead of setting INSTALL_PATH on the cmake command line as given above.

4. If the build is successful, then at this point make install should work.

3.7 Installation

3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ cd Examples
$ ./buildIt
```

3.7 Installation 11

3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

To test, set PFUNIT and go into Examples/MPI_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

12 Installation

Usage

- Usage Configuration
- Usage Hello World
- Usage Preprocessor
- · Compiling and Executing The Test

4.1 Usage

4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
```

14 Usage

```
subroutine testHelloWorld()
  use pfunit_mod
  implicit none
  @assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

4.2 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

4.3 Compiling and Executing The Test

An example of a GNU make rule for for the final step of compiling a test follows.

To execute the tests, one invokes "./tests.x" with the appropriate command line options (see below).

4.3.1 - Compiling and Executing the Tests (MPI PARALLEL)

One invokes MPI-based parallel tests according to the MPI framework being used. For example:

```
$ mpirun -np 4 tests.x
```

4.3.2 Command Line Options

The executable test program provides several command line options, when "include/driver.F90" is used, as it is automatically when using the PFUNIT preprocessor.

-v or -verbose	Verbose execution.
-d or -debug	Provide debugging information.
-h	Print help message.
-o <outputfile></outputfile>	Direct pFUnit messages to a file.
-robust	Use the robust runner. Runs tests as
	processes so failures do not halt testing.
-skip <number of="" skip="" tests="" to=""></number>	Use the subset runner, which runs a
	subset of the tests in a suite.

An example from Examples/Robust:

\$./tests.x -robust

16 Usage

Development

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

18 Development

Feedback & Support

- Feedback
- Support

6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

FAQ and Tips

- FAQ
 - Zero Tests Run
 - Some Tests Are Not Running
 - Intel Fortran Version 13: -DINTEL_13
- Tips
 - Environment Modules
 - Compile Time Errors
 - Intermediate files used by pFUnit
 - Ignoring whitespace in assertions on strings.

7.1 FAQ

7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD_TEST_SUITE (the_suite_to_add), one to a line.
- There is no <code>-DUSE_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

22 FAQ and Tips

7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

Solutions:

 There is no -DUSE_MPI passed to the compiler during the build. Please add as in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

7.1.3 Intel Fortran Version 13: -DINTEL_13

To make pFUnit work with Intel Fortran Version 13, please ensure that <code>-DINTEL_13</code> is passed to the compiler when building or using pFUnit. In the build process for pFUnit, this is added to the make variables CPPFLAGS and FPPFLAGS.

7.2 Tips

7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

7.2 Tips 23

```
$ make all COMPILER=Intel
```

7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

7.2.4 Ignoring whitespace in assertions on strings.

Several options exist for how to compare strings with assertEqual.

WhitespaceOptions:

- pleaseTrim ignores leading and trailing whitespace.
- **pleaseKeep** keeps all whitespace as significant, even discriminating between tabs and spaces.
- pleaseIgnore ignores all whitespace (spaces & tabs).

Example usages can be seen in tests/Test_AssertBasic.F90 or Examples/-Simple/tests/helloWorld.pf.

24 FAQ and Tips

Platform Specific Notes

8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

8.3 Intel Fortran Version 13: -DINTEL_13

To make pFUnit work with Intel Fortran Version 13, please ensure that <code>-DINTEL_13</code> is passed to the compiler when building or using pFUnit. In the build process for pFUnit, this is added to the make variables CPPFLAGS and FPPFLAGS.

Acknowledgments

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

Known Installations & Versions

master - The cutting edge of pFUnit development.

pfunit_2.1.0 - A feature freeze prior to a major upgrade of the preprocessor.

TODO

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

32 TODO

The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
 - Configuration testSuites.inc
 - Invocation
 - Command Line Options
 - Preprocessor Input File (.pf)
 - Directives
 - * @Test
 - * @MPITest
 - * @Assert (or Preprocessor Directives)
 - * @Parameters
 - * @TestCase

12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's "tests" subdirectory.

12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' "tests" subdirectories in the - Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
 - @Assert

12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive.

also supports MPI-parallel tests (see @MPITest).

An example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

12.1.4.2 @MPITest

is deprecated as now handles this case.

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI Halo:

```
@Test( npes=[1,2,3])
subroutine testHaloInterior(this)
   use Halo_mod
   use pfunit_mod
   implicit none
   class (MpiTestMethod) :: this

   integer, parameter :: N = 2
   real :: a(N,0:N+1)
   integer :: p

   p = this%getProcessRank()
   a(:,1:N) = p
```

```
a(:,0) = -1
a(:,N+1) = -1

call haloFill(a, this%getMpiCommunicator())

@assertEqual(real(p), a(1,1))
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found,'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- @assertTrue
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf

- · @assertExceptionRaised
- · @assertSameShape
- · @assertIsNaN
- · @assertIsFinite

12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

@Assert Preprocessor Directives

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

13.1 @ Assert P	reprocessor	Directives
-----------------	-------------	-------------------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

Revision Notes

- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
 MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

42 Revision Notes

Data Type Index

15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter_mod	55
AbstractTestResult_mod	55
pFUnitParser::Action	56
pFUnitParser::AtAfter	90
pFUnitParser::AtAssert	90
pFUnitParser::AtBefore	91
pFUnitParser::AtBegin	92
pFUnitParser::AtMpiAssert	92
pFUnitParser::AtSuite	94
	94
pFUnitParser::AtMpiTest	93
pFUnitParser::AtTestCase	95
	96
add_mod	57
addComplex_mod	57
	57
	58
	58
• -	61
	64
	68
	70
AssertArraysInternalassertNotEqual_mod	74
• -	77
	80

AssertBasic_mod
AssertComplex0_mod
AssertComplex1_mod
AssertComplex2_mod
AssertComplex3_mod
AssertComplex4_mod
AssertComplex5_mod
AssertInteger10_mod
AssertInteger11_mod
AssertInteger12_mod
AssertInteger13_mod
AssertInteger14_mod
AssertInteger15_mod
AssertInteger_mod
AssertReal0_mod
AssertReal1_mod
AssertReal2_mod
AssertReal3_mod
AssertReal4_mod
AssertReal5_mod
GenerateAssertsOnArrays::AssertRealArrayArgument
TestCaseB_mod::B_Parameter
BaseTestRunner_mod
BeforeAfter_mod
BrokenSetUpCase_mod
BrokenTestCase_mod
TestCaseC_mod::C_Parameter
Cases_mod
mods::pre2::dataString
DebugListener_mod
CodeUtilities::declaration
DynamicTestCase_mod
Exception_mod
Fixture mod
FixtureTestCase_mod
CodeUtilities::fortranSubroutineSignature
AbstractTestResult_mod::getErrors
Test_mod::getName
AbstractTestResult mod::getSuccesses
Halo_mod
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre::pre If::interval
Test_RestrictSphericalCoordinates_mod::LatLonCase
LinearInterpolator_mod
MakeInfinity_mod

MakeNaN_mod
MockCall_mod
MockListener mod
MockRepository_mod
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
MpiStubs_mod
MpiTestCase_mod
MpiTestCaseB_mod::MpiTestCaseB
MpiTestCaseB_mod
MpiTestMethod_mod
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC_mod::newC_Parameter
ParallelContext_mod
ParallelException mod
ParameterizedTestCase_mod
Params_mod
pFUnitParser::Parser
testParser::MockParser
Test_Parameters_mod::peCase
pFUnit
pFUnit_mod
PrivateException_mod
mods::pre2::procDirective
mods::pre::pre_lf::lfDirective
mods::pre::pre_Repeat::RepeatDirective
RemoteProxyTestCase mod
ResultPrinter mod
RobustRunner mod
robustTestSuite mod
CodeUtilities::routineUnit
GenerateAssertsOnArrays::constraintASSERT
GenerateAssertsOnArrays::IsWithinTolerance
GenerateAssertsOnArrays::VECTOR_NORM
SerialContext mod
SimpleTestCase_mod
SourceLocation_mod
SphericalCoordinates_mod
•
TestListener_mod::startTest
StringConversionUtilities_mod

	138
SurrogateTestCase_mod	
SUT_mod	
Test_Assert_mod	
Test_AssertBasic_mod	
Test_AssertComplex_mod	
Test_AssertInteger_mod	
Test_AssertReal_mod	142
Test_BasicOpenMP_mod	143
Test_Exception_mod	143
Test_FixtureTestCase_mod	144
Test_LinearInterpolator_mod::Test_LinearInterpolator	144
Test_LinearInterpolator_mod	144
Test_MockCall_mod	145
Test_MockRepository_mod	145
Test mod	145
Test_MpiContext_mod	146
Test_MpiException_mod	147
Test_MpiParameterizedTestCase_mod	147
Test_MpiTestCase_mod	
Test Parameters mod::Test Parameters	
Test_Parameters_mod	148
$Test_RestrictSphericalCoordinates_mod:: Test_RestrictSphericalCoordinates \ .$	149
Test_RestrictSphericalCoordinates_mod	149
Test_RestrictSphericalCoordinates_mod	150
Test_RobustRunner_mod	150 150
Test_RobustRunner_mod	150 150 150
Test_RobustRunner_mod	150 150 150 151
Test_RobustRunner_mod	150 150 150 151 151
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod	150 150 150 151 151 151
Test_RobustRunner_mod	150 150 150 151 151 151 151
Test_RobustRunner_mod . Test_SimpleTestCase_mod . Test_StringConversionUtilities_mod . Test_TestMethod_mod . Test_TestResult_mod . Test_TestSuite_mod . Test_UnixProcess_mod . Test_XmlPrinter_mod .	150 150 150 151 151 151 152 152
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod	150 150 150 151 151 151 152 152 153
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod	150 150 150 151 151 151 152 152 153 153
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA	150 150 150 151 151 151 152 152 153 153 154
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod	150 150 151 151 151 152 152 153 153 154 155
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_VnixProcess_mod Test_Amod TestA_mod TestCase_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod TestCaseB_mod::TestCaseB	150 150 151 151 151 152 152 153 153 154 155
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_VnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod TestCaseB_mod::TestCaseB TestCaseB_mod	150 150 151 151 151 152 152 153 153 154 155 155
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseB_mod::TestCaseB TestCaseB_mod TestCaseB_mod TestCaseC_mod::TestCaseC	150 150 151 151 151 152 152 153 153 154 155 156 156
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseB_mod::TestCaseB TestCaseB_mod TestCaseB_mod TestCaseC_mod TestCaseC_mod	150 150 151 151 151 152 152 153 153 154 155 156 156 157
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_XmlPrinter_mod Test_XmlPrinter_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod::TestCaseB TestCaseB_mod TestCaseB_mod TestCaseC_mod::TestCaseC TestCaseC_mod TestCaseC_mod TestCaseC_mod TestCaseC_mod	150 150 151 151 151 152 153 153 154 155 156 156 157 158
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_VnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod::TestCaseB TestCaseB_mod::TestCaseB TestCaseC_mod::TestCaseC TestCaseC_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective	150 150 151 151 151 152 152 153 153 154 155 155 156 157 158 158
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_VnixProcess_mod Test_Amod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod TestCaseB_mod::TestCaseB TestCaseB_mod TestCaseC_mod::TestCaseC TestCaseC_mod::TestCaseC TestCaseC_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective mods::pre::interleavedp::TestInterleaved	150 150 151 151 151 152 152 153 153 154 155 156 156 157 158 158 159
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod::TestCaseB TestCaseB_mod::TestCaseB TestCaseB_mod TestCaseC_mod::TestCaseC TestCaseC_mod TestFailure_mod mods::pre::pre_lf::TestlfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod	150 150 151 151 151 152 152 153 153 154 155 156 156 157 158 158 159 159
Test_RobustRunner_mod Test_SimpleTestCase_mod Test_StringConversionUtilities_mod Test_TestMethod_mod Test_TestResult_mod Test_TestSuite_mod Test_UnixProcess_mod Test_UnixProcess_mod Test_XmlPrinter_mod TestA_mod TestCase_mod TestCaseA_mod::TestCaseA TestCaseA_mod::TestCaseB TestCaseB_mod::TestCaseB TestCaseB_mod TestCaseC_mod::TestCaseC TestCaseC_mod TestFailure_mod mods::pre::pre_lf::TestlfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod	150 150 151 151 151 152 152 153 153 154 155 156 156 157 158 159 159 160

$test Parser :: Test Parse Line \\ \ldots \\ 162$
mods::pre::pre_Repeat::TestRepeatDirective
TestResult_mod
TestRunner_mod
$TestSuite_mod \ldots \ldots$
ThrowFundamentalTypes_mod
UnixPipeInterfaces_mod
UnixProcess_mod
AbstractTestResult_mod::wasSuccessful
$Wrap before After \ . \ . \ . \ . \ . \ . \ . \ . \ . \ $
$Wrap Mpi Test Case B_mod \ \dots \ $
$Wrap simple \ \dots $
$Wrap Test A_mod \ldots \ldots$
$Wrap Test Case A_mod \ \dots \ $
$Wrap Test Case B_mod \ \dots \ $
$Wrap Test Case C_mod \ \dots \ $
XmlPrinter_mod

Data Type Index

16.1 Data Types List

Here are the data types with brief descriptions:

AbstractTestParameter_mod
AbstractTestResult_mod
pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert mod
<briefdescription></briefdescription>
AssertArraysInternalassertEqual_mod
AssertArraysInternalassertGreaterThan mod 61
AssertArraysInternalassertGreaterThanOrEqual_mod
AssertArraysInternalassertLessThan mod
AssertArraysInternalassertLessThanOrEqual_mod
AssertArraysInternalassertNotEqual_mod
AssertArraysInternalassertRelativelyEqual_mod
AssertArraysSupport mod
AssertBasic_mod
Provides fundamental assertions over the most basic types, a foun-
dation for providing test services to end users
AssertComplex0_mod
AssertComplex1_mod
AssertComplex2_mod
AssertComplex3_mod
AssertComplex4_mod
AssertComplex5 mod 83

AssertInteger10_mod
AssertInteger11_mod
AssertInteger12_mod
AssertInteger13_mod
AssertInteger14_mod
AssertInteger15_mod
AssertInteger_mod
<briefdescription></briefdescription>
AssertReal0_mod
AssertReal1_mod
AssertReal2_mod
AssertReal3_mod
AssertReal4_mod
AssertReal5_mod
GenerateAssertsOnArrays::AssertRealArrayArgument
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
pFUnitParser::AtTestParameter
TestCaseB mod::B Parameter
BaseTestRunner mod
<pre><briefdescription></briefdescription></pre>
BeforeAfter mod
BrokenSetUpCase_mod
BrokenTestCase_mod
TestCaseC_mod::C_Parameter
Cases_mod
GenerateAssertsOnArrays::constraintASSERT
mods::pre::pre2::dataString
DebugListener mod
<pre></pre>
CodeUtilities::declaration
DynamicTestCase_mod
<pre></pre>
Exception mod
Fixture_mod
FixtureTestCase mod
CodeUtilities::fortranSubroutineSignature
AbstractTestResult_mod::getErrors
Test mod::getName
rest_modgetrvame

AbstractTestResult_mod::getSuccesses
Halo_mod
mods::pre::pre_lf::lfDirective
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre::pre_lf::interval
GenerateAssertsOnArrays::IsWithinTolerance
Test_RestrictSphericalCoordinates_mod::LatLonCase
LinearInterpolator_mod
MakeInfinity mod
<briefdescription></briefdescription>
MakeNaN mod
<pre></pre>
MockCall mod
<pre></pre>
MockListener mod
testParser::MockParser
MockRepository_mod
<pre></pre>
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext mod
<pre></pre>
•
MpiStubs_mod
<briefdescription></briefdescription>
MpiTestCase_mod
<briefdescription></briefdescription>
MpiTestCaseB_mod::MpiTestCaseB
MpiTestCaseB_mod
MpiTestMethod_mod
<briefdescription></briefdescription>
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC_mod::newC_Parameter
ParallelContext_mod
<briefdescription></briefdescription>
ParallelException_mod
<briefdescription></briefdescription>
ParameterizedTestCase_mod
<briefdescription></briefdescription>
Params_mod
<briefdescription></briefdescription>
pFUnitParser::Parser

Test_MpiException_mod	. 147
Test MpiParameterizedTestCase mod	
Test MpiTestCase mod	
Test Parameters mod::Test Parameters	
Test Parameters mod	
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates	
Test_RestrictSphericalCoordinates_mod	
Test RobustRunner mod	
Test_SimpleTestCase_mod	
Test_StringConversionUtilities_mod	
Test TestMethod mod	
Test_TestResult_mod	
Test TestSuite mod	
Test_UnixProcess_mod	
Test XmlPrinter mod	
Output test messages in junit.xsd-compatible XML	. 152
TestA mod	
TestCase mod	
<briefdescription></briefdescription>	. 153
TestCaseA mod::TestCaseA	
TestCaseA mod	
TestCaseB mod::TestCaseB	
TestCaseB mod	
TestCaseC mod::TestCaseC	
TestCaseC mod	
TestFailure_mod	
- <briefdescription></briefdescription>	. 158
mods::pre::pre_lf::TestlfDirective	
mods::pre::interleavedp::TestInterleaved	
TestListener mod	
<briefdescription></briefdescription>	. 159
TestMethod_mod	
<briefdescription></briefdescription>	. 160
mods::pre::parseArgs::TestParseArgs	. 161
testParser::TestParseLine	. 162
mods::pre::pre_Repeat::TestRepeatDirective	. 164
TestResult_mod	
<briefdescription> Note: A possible extension point for user-</briefdescription>	
specialized TestResults	. 164
TestRunner_mod	
<briefdescription></briefdescription>	. 165
TestSuite_mod	
<briefdescription></briefdescription>	. 166
ThrowFundamentalTypes_mod	
<briefdescription></briefdescription>	. 167

JnixPipeInterfaces_mod
<briefdescription></briefdescription>
JnixProcess_mod
<briefdescription></briefdescription>
GenerateAssertsOnArrays::VECTOR_NORM
AbstractTestResult_mod::wasSuccessful
NrapbeforeAfter
WrapMpiTestCaseB_mod
Wrapsimple
WrapTestA_mod
WrapTestCaseA_mod
WrapTestCaseB_mod
WrapTestCaseC_mod
XmlPrinter mod
<pre></pre>

Data Type Documentation

17.1 AbstractTestParameter_mod Module Reference

Data Types

- type AbstractTestParameter
- interface toString

The documentation for this module was generated from the following file:

• AbstractTestParameter.F90

17.2 AbstractTestResult_mod Module Reference

Data Types


- type AbstractTestResult
- interface errorCount
- interface failureCount
- interface getErrors
- · interface getFailures
- interface getName
- interface getRunTime
- interface getSuccesses
- interface runCount
- interface setName
- interface wasSuccessful

The documentation for this module was generated from the following file:

· AbstractTestResult.F90

17.3 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



Public Member Functions

· def apply

The documentation for this class was generated from the following file:

pFUnitParser.py

17.4 add_mod Module Reference

Public Member Functions

- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- · Robust/src/add.F90
- · Simple/src/add.F90

17.5 addComplex_mod Module Reference

Public Member Functions

• complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following file:

· addComplex.F90

17.6 CodeUtilities::ArrayDescription Class Reference

Public Member Functions

- def __init__
- def NAME
- def **DECLARE**
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

Public Attributes

- fType
- kind
- rank

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.7 Assert_mod Module Reference

```
<BriefDescription>
```

17.7.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

17.8 AssertArraysInternalassertEqual_mod Module Reference

Data Types

- interface differenceReport
- interface isWithinTolerance
- · interface valuesReport
- interface vectorNorm

- subroutine, public assertEqual_e0_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f1_real64_tol64_ (ex pected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f0_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real32_f0_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real32_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_real32_f1_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real32_f1_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_real64_f0_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real64_f0_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real64_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real64_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public **assertEqual_e1_integerdefault_f0_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_integerdefault_f1_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_integerdefault_f1_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_real32_f0_complex32_tol32_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real32_f0_complex32_tol32_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f1_complex32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real32_f1_complex32_tol32_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f0_complex64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real32_f0_complex64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_real32_f1_complex64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real32_f1_complex64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_real64_f0_complex64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_real64_f0_complex64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_real64_f1_complex64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_real64_f1_complex64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_complex32_f0_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_complex32_f0_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertEqual_e1_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e1_complex32_f1_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e0_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertEqual_e0_complex64_f1_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertEqual_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

AssertArraysInternalassertEqual.F90

17.9 AssertArraysInternalassertGreaterThan_mod Module Reference

Data Types

- interface differenceReport
- · interface isWithinTolerance
- · interface valuesReport
- interface vectorNorm

- subroutine, public assertGreaterThan_e0_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThan_e0_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e1_real32_f0_real32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e0_real32_f1_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e1_real32_f1_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e0_real64_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e1_real64_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThan_e0_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e1_real64_f0_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThan_e1_real64_f1_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_complex32_f0_complex32_tol32_- (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex32_f0_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_complex32_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex32_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThan_e0_complex32_f0_complex64_tol64_- (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex32_f0_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_complex32_f1_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex32_f1_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_complex64_f0_complex64_tol64_- (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex64_f0_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e0_complex64_f1_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThan_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

AssertArraysInternalassertGreaterThan.F90

17.10 AssertArraysInternalassertGreaterThanOrEqual_mod Module Reference

Data Types

- interface differenceReport
- interface isWithinTolerance
- interface valuesReport
- interface vectorNorm

- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThanOrEqual_e0_real32_f1_real32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real64_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThanOrEqual_e1_real64_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertGreaterThanOrEqual_e1_integerdefault_f0_- complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertGreaterThanOrEqual_e1_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex32_f0_complex32_ _tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex32_f1_complex32_ _tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex32_f1_complex32_ _tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex32_f0_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex32_f0_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex32_f1_complex64_ _tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex32_f1_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex64_f0_complex64_ _tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex64_f0_complex64_ _tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e0_complex64_f1_complex64_ _tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertGreaterThanOrEqual_e1_complex64_f1_complex64_ _tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

AssertArraysInternalassertGreaterThanOrEqual.F90

17.11 AssertArraysInternalassertLessThan_mod Module Reference

Data Types

- interface differenceReport
- · interface isWithinTolerance
- interface valuesReport
- interface vectorNorm

- subroutine, public assertLessThan_e0_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e1_integerdefault_f1_real32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e0_integerdefault_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e1_integerdefault_f1_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e0_real32_f0_real32_tol32_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real32_f0_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e0_real32_f0_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertLessThan_e1_real32_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real32_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real64_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real64_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real64_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real64_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f0_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f0_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f0_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f0_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_integerdefault_f1_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_integerdefault_f1_complex64_tol64_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThan_e1_real32_f1_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertLessThan_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real64_f0_complex64_tol64_ (ex pected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e0_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThan_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

AssertArraysInternalassertLessThan.F90

17.12 AssertArraysInternalassertLessThanOrEqual_mod Module - Reference

Data Types

- · interface differenceReport
- interface isWithinTolerance
- · interface valuesReport
- interface vectorNorm

- subroutine, public assertLessThanOrEqual_e0_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThanOrEqual_e1_real32_f0_real32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public **assertLessThanOrEqual_e1_real32_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real64_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real64_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertLessThanOrEqual_e0_real64_f1_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f0_complex32-_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f0_complex32-_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f1_complex32-_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f1_complex32-_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f0_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f0_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_integerdefault_f1_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_integerdefault_f1_complex64-_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertLessThanOrEqual_e1_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertLessThanOrEqual_e1_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e0_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertLessThanOrEqual_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

AssertArraysInternalassertLessThanOrEqual.F90

17.13 AssertArraysInternalassertNotEqual_mod Module Reference

Data Types

- interface differenceReport
- interface isWithinTolerance
- · interface valuesReport
- interface vectorNorm

- subroutine, public **assertNotEqual_e0_integerdefault_f0_real32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e0_integerdefault_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e1_integerdefault_f0_real64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertNotEqual_e0_real32_f0_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f0_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f1_real32_tol32_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real32_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real32_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real64_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real64_f0_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e0_real64_f1_real64_tol64_** (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real64_f1_real64_tol64_ (expected, e-Shape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f0_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f0_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f1_complex32_tol32_-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e0_real32_f0_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e1_real32_f0_complex32_tol32_** (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertNotEqual_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e0_real64_f0_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public **assertNotEqual_e1_real64_f0_complex64_tol64_** (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e0_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertNotEqual_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

· AssertArraysInternalassertNotEqual.F90

17.14 AssertArraysInternalassertRelativelyEqual_mod Module - Reference

Data Types

- interface differenceReport
- interface isWithinTolerance
- · interface valuesReport
- · interface vectorNorm

- subroutine, public assertRelativelyEqual_e0_integerdefault_f0_real32_tol32-_(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f0_real32_tol32-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f1_real32_tol32-_(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f1_real32_tol32-_(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f0_real64_tol64-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f0_real64_tol64-(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f1_real64_tol64-_(expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f1_real64_tol64-_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f0_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f1_real32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertRelativelyEqual_e1_real32_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real64_f0_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real64_f0_real64_tol64_ (ex pected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real64_f1_real64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_integerdefault_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertRelativelyEqual_e1_real32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_real64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_complex32_f0_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_complex32_f1_complex32_tol32_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_complex32_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_complex32_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

- subroutine, public assertRelativelyEqual_e1_complex64_f0_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e0_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)
- subroutine, public assertRelativelyEqual_e1_complex64_f1_complex64_tol64_ (expected, eShape, found, fShape, tolerance, message, location, comparison)

· AssertArraysInternalassertRelativelyEqual.F90

17.15 AssertArraysSupport_mod Module Reference

Data Types

- · interface differenceReport
- interface isWithinTolerance
- · interface valuesReport
- interface vectorNorm

The documentation for this module was generated from the following file:

AssertArraysSupport.F90

17.16 AssertBasic mod Module Reference

Provides fundamental assertions over the most basic types, a foundation for providing test services to end users.

Data Types

- · interface assertEqual
- interface assertExceptionRaised
- · interface assertFail
- interface assertFalse
- interface assertIsFinite
- · interface assertIsNaN

- interface assertTrue
- · interface fail
- type UnusableArgument

Public Member Functions

- subroutine assertExceptionRaisedMessage (message, location)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public **conformable** (shapeA, shapeB)
- logical function, public **nonConformable** (shapeA, shapeB)
- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine **assertIsNaN double** (x, message, location)
- subroutine **assertIsFinite_single** (x, message, location)
- subroutine assertIsFinite_double (x, message, location)

17.16.1 Detailed Description

Provides fundamental assertions over the most basic types, a foundation for providing test services to end users.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

For assertions on strings whitespace may or may not be significant to a test. - We now have several options for dealing with whitespace via the optional argument forWhitespace. These options are pleaseIgnore, pleaseTrim, and pleaseKeep. Usage is as follows.

call assertEqual(expectedString, foundString, & & for-Whitespace=pleaseIgnore)

WhitespaceOptions:

• pleaseTrim ignores leading and trailing whitespace.

- pleaseKeep keeps all whitespace as significant, even discriminating between tabs and spaces.
- pleaselgnore ignores all whitespace (spaces & tabs).

Example usages can be seen in tests/Test_AssertBasic.F90 or Examples/-Simple/tests/helloWorld.pf.

The documentation for this module was generated from the following file:

· AssertBasic.F90

17.17 AssertComplex0_mod Module Reference

Data Types

- · interface assertEqual
- · interface assertNotEqual
- · interface assertRelativelyEqual

The documentation for this module was generated from the following file:

· AssertComplex0.F90

17.18 AssertComplex1_mod Module Reference

Data Types

- interface assertEqual
- · interface assertNotEqual
- interface assertRelativelyEqual

The documentation for this module was generated from the following file:

AssertComplex1.F90

17.19 AssertComplex2_mod Module Reference

Data Types

· interface assertEqual

- interface assertNotEqual
- interface assertRelativelyEqual

• AssertComplex2.F90

17.20 AssertComplex3_mod Module Reference

Data Types

- interface assertEqual
- · interface assertNotEqual
- interface assertRelativelyEqual

The documentation for this module was generated from the following file:

• AssertComplex3.F90

17.21 AssertComplex4_mod Module Reference

Data Types

- interface assertEqual
- interface assertNotEqual
- interface assertRelativelyEqual

The documentation for this module was generated from the following file:

AssertComplex4.F90

17.22 AssertComplex5_mod Module Reference

Data Types

- interface assertEqual
- interface assertNotEqual
- interface assertRelativelyEqual

The documentation for this module was generated from the following file:

AssertComplex5.F90

17.23 AssertInteger10_mod Module Reference

Data Types

· interface assertEqual

The documentation for this module was generated from the following file:

· AssertInteger10.F90

17.24 AssertInteger11_mod Module Reference

Data Types

· interface assertEqual

The documentation for this module was generated from the following file:

· AssertInteger11.F90

17.25 AssertInteger12_mod Module Reference

Data Types

· interface assertEqual

The documentation for this module was generated from the following file:

· AssertInteger12.F90

17.26 AssertInteger13_mod Module Reference

Data Types

interface assertEqual

The documentation for this module was generated from the following file:

• AssertInteger13.F90

17.27 AssertInteger14_mod Module Reference

Data Types

• interface assertEqual

The documentation for this module was generated from the following file:

AssertInteger14.F90

17.28 AssertInteger15_mod Module Reference

Data Types

• interface assertEqual

The documentation for this module was generated from the following file:

• AssertInteger15.F90

17.29 AssertInteger_mod Module Reference

<BriefDescription>

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

- subroutine assertEqualInteger1D1D_ (expected, found, message, location)
- subroutine assertEqualInteger0D1D_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D_ (expected, found, message, location)
- subroutine assertLessThan_ (a, b, message, location)

17.29.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

17.30 AssertReal0_mod Module Reference

Data Types

- · interface assertEqual
- · interface assertGreaterThan
- interface assertGreaterThanOrEqual
- interface assertLessThan
- interface assertLessThanOrEqual
- interface assertNotEqual
- interface assertRelativelyEqual

Public Attributes

- integer, parameter, public L_INFINITY_NORM = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public **L2_NORM** = 2

The documentation for this module was generated from the following file:

· AssertReal0.F90

17.31 AssertReal1_mod Module Reference

Data Types

- · interface assertEqual
- · interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- · interface assertNotEqual
- interface assertRelativelyEqual

Public Attributes

- integer, parameter, public L INFINITY NORM = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public **L2_NORM** = 2

The documentation for this module was generated from the following file:

· AssertReal1.F90

17.32 AssertReal2 mod Module Reference

Data Types

- interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- interface assertLessThan
- interface assertLessThanOrEqual
- interface assertNotEqual
- interface assertRelativelyEqual

Public Attributes

- integer, parameter, public **L_INFINITY_NORM** = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public **L2_NORM** = 2

The documentation for this module was generated from the following file:

· AssertReal2.F90

17.33 AssertReal3_mod Module Reference

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- · interface assertNotEqual
- · interface assertRelativelyEqual

Public Attributes

- integer, parameter, public L INFINITY NORM = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public L2_NORM = 2

The documentation for this module was generated from the following file:

· AssertReal3.F90

17.34 AssertReal4 mod Module Reference

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- interface assertLessThan
- interface assertLessThanOrEqual
- interface assertNotEqual
- interface assertRelativelyEqual

Public Attributes

- integer, parameter, public L_INFINITY_NORM = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public L2_NORM = 2

The documentation for this module was generated from the following file:

· AssertReal4.F90

17.35 AssertReal5_mod Module Reference

Data Types

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- interface assertLessThan
- interface assertLessThanOrEqual
- · interface assertNotEqual
- interface assertRelativelyEqual

Public Attributes

- integer, parameter, public **L_INFINITY_NORM** = 0
- integer, parameter, public L1_NORM = 1
- integer, parameter, public **L2_NORM** = 2

The documentation for this module was generated from the following file:

AssertReal5.F90

17.36 GenerateAssertsOnArrays::AssertRealArrayArgument Class Reference

Public Member Functions

- def __init__
- def updateDescriptions
- def getAssertionName
- def getExpectedDescription
- · def getFoundDescription
- · def getTolerance

Public Attributes


- assertionName
- expectedFType
- · expectedPrecision
- expectedRank

- foundFType
- foundPrecision
- foundRank
- · tolerance
- · expectedDescription
- · foundDescription

GenerateAssertsOnArrays.py

17.37 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



Public Member Functions

- def __init__
- def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.38 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.39 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



- def __init__
- · def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.40 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.41 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.42 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



Public Member Functions

def __init__

Public Attributes


- parser
- keyword

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.43 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.44 pFUnitParser::AtTest Class Reference

Inheritance diagram for pFUnitParser::AtTest:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


- parser
- keyword

The documentation for this class was generated from the following file:

pFUnitParser.py

17.45 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



- def __init__
- def match
- · def action


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.46 pFUnitParser::AtTestParameter Class Reference

Inheritance diagram for pFUnitParser::AtTestParameter:



Public Member Functions

- def init
- def match
- def action

Public Attributes

parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.47 TestCaseB_mod::B_Parameter Type Reference

- · procedure toString
- procedure toString

- real phi
- real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- ParameterizedTestCaseB.pf

17.48 BaseTestRunner_mod Module Reference

<BriefDescription>

Data Types

- type BaseTestRunner
- interface run2

17.48.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

17.49 BeforeAfter_mod Module Reference

Public Member Functions

- · subroutine first (this)
- subroutine last (this)
- subroutine succeeds (this)
- · subroutine fails (this)

Public Attributes

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

• Examples/MPI_Halo/tests/beforeAfter.pf

17.50 BrokenSetUpCase_mod Module Reference

Data Types

• type BrokenSetUpCase

Public Member Functions

 $\bullet \ \ \mathsf{type}(\mathsf{BrokenSetUpCase}) \ \mathsf{function}, \ \ \mathsf{pointer}, \ \mathsf{public} \ \boldsymbol{\mathsf{newBrokenSetUpCase}} \ ()$

The documentation for this module was generated from the following file:

BrokenSetUpCase.F90

17.51 BrokenTestCase_mod Module Reference

Data Types

• type BrokenTestCase

Public Member Functions

• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

17.52 TestCaseC_mod::C_Parameter Type Reference

Public Member Functions

- procedure toString
- · procedure toString

Public Attributes

- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.53 Cases_mod Module Reference

Data Types

- type MyParamType
- type MyTestCase


- type(MyParamType) function newMyParam (i)
- type(MyTestCase) function newMyTestCase (param)
- subroutine test_odd (this)
- subroutine test_even (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test Cases.pf

17.54 GenerateAssertsOnArrays::constraintASSERT Class Reference

Inheritance diagram for GenerateAssertsOnArrays::constraintASSERT:



Public Member Functions

def __init___
 Dependency injection.

Public Attributes

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

17.54.1 Constructor & Destructor Documentation

17.54.1.1 def GenerateAssertsOnArrays::constraintASSERT::__init__ (self, assertionName, expectedDescr, foundDescr, tolerance)

Dependency injection.

Will generate "assert"+assertionName assertionName="Equal" This next line actually generates the text of the code.

17.54.2 Member Data Documentation

17.54.2.1 GenerateAssertsOnArrays::constraintASSERT::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

17.54.2.2 GenerateAssertsOnArrays::constraintASSERT::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

· GenerateAssertsOnArrays.py

17.55 mods::pre::pre2::dataString Class Reference

- def __init__
- def insert
- def getLength
- · def getPosition
- · def setPosition
- def getItem
- def getDataAtPosition
- def getData
- · def getSlice
- def getSliceForward
- def removeSlice
- def getCurrentData
- def insertAtCurrent
- def append
- def advanceAndGetNextData
- def validPosition
- def findToEnd
- def match
- def matchToEnd

- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

- · data
- · position

The documentation for this class was generated from the following file:

• pre2.py

17.56 DebugListener_mod Module Reference

<BriefDescription>

Data Types

• interface DebugListener

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

17.56.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• DebugListener.F90

17.57 CodeUtilities::declaration Class Reference

Public Member Functions

- def __init___
- · def generate

Public Attributes

- simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.58 DynamicTestCase_mod Module Reference

<BriefDescription>

Data Types

- interface delete
- type DynamicTestCase
- · interface testmethod

Public Member Functions

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

17.58.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

17.59 Exception_mod Module Reference

Data Types

- · interface any Exceptions
- · interface catch
- · interface getNumExceptions
- · interface throw

Public Member Functions

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public **catchNext** (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()
- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

17.60 Fixture_mod Module Reference

Public Member Functions

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following file:

· fixtureTests.pf

17.61 FixtureTestCase mod Module Reference

Data Types

- · interface delete
- type FixtureTestCase

Public Member Functions

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

• FixtureTestCase.F90

17.62 CodeUtilities::fortranSubroutineSignature Class Reference

- def __init__
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.63 AbstractTestResult_mod::getErrors Interface Reference

The documentation for this interface was generated from the following file:

· AbstractTestResult.F90

17.64 Test_mod::getName Interface Reference

The documentation for this interface was generated from the following file:

· Test.F90

17.65 AbstractTestResult_mod::getSuccesses Interface Reference

The documentation for this interface was generated from the following file:

AbstractTestResult.F90

17.66 Halo_mod Module Reference

Public Member Functions


• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

17.67 mods::pre::pre_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre_lf::lfDirective:



Public Member Functions

· def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

• pre_lf.py

17.68 CodeUtilities::implementation Class Reference

Public Member Functions

- def __init__
- def generate

Public Attributes

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.69 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.70 mods::pre::pre_lf::interval Class Reference

Public Member Functions

- def __init___
- · def getInterval
- def setInterval
- · def getStart
- def getEnd

Public Attributes


- start
- end
- interval

The documentation for this class was generated from the following file:

pre_lf.py

17.71 GenerateAssertsOnArrays::IsWithinTolerance Class Reference

Inheritance diagram for GenerateAssertsOnArrays::IsWithinTolerance:



Public Member Functions

def __init__

- · rank
- · precision
- name
- fType
- · declaration
- declarations

The documentation for this class was generated from the following file:

· GenerateAssertsOnArrays.py

17.72 Test_RestrictSphericalCoordinates_mod::LatLonCase Type - Reference

Public Member Functions

· procedure toString

Public Attributes

- real lat
- real lon
- real restrictedLat
- real restrictedLon

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.73 LinearInterpolator_mod Module Reference

Data Types

- interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

• LinearInterpolator.F90

17.74 MakeInfinity_mod Module Reference

<BriefDescription>

Public Member Functions

- real(r32) function, public makeInf_32 ()
- real(r64) function, public makeInf_64 ()

17.74.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MakeInfinity.F90

17.75 MakeNaN_mod Module Reference

<BriefDescription>

- real(r32) function, public makeNaN_32 ()
- real(r64) function, public makeNaN_64 ()

17.75.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MakeNaN.F90

17.76 MockCall_mod Module Reference

<BriefDescription>

Data Types

• type MockCall

Public Member Functions

• type(MockCall) function, public **newMockCall** (name)

17.76.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockCall.F90

17.77 MockListener_mod Module Reference

Data Types

· type MockListener

Public Member Functions


• subroutine startTest (this, testName)

The documentation for this module was generated from the following file:

MockListener.F90

17.78 testParser::MockParser Class Reference

Inheritance diagram for testParser::MockParser:



- def __init__
- · def nextLine
- · def reset

- saveLines
- lines
- outputFile
- outLines
- userTestCase
- userTestMethods
- · currentSelfObjectName

The documentation for this class was generated from the following file:

testParser.py

17.79 MockRepository_mod Module Reference

<BriefDescription>

Data Types

• type MockRepository

Public Member Functions

- type(MockRepository) function, pointer, public newMockRepository ()
- subroutine expectCall (this, obj, method)

17.79.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockRepository.F90

17.80 MockSUT mod Module Reference

Data Types

type MockSUT

Public Member Functions

- type(MockSUT) function, allocatable, public **newMockSUT** (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.81 testParser::MockWriter Class Reference

Public Member Functions

- def __init__
- def write

Public Attributes

parser

The documentation for this class was generated from the following file:

testParser.py

17.82 CodeUtilities::module Class Reference

Public Member Functions

- def __init___
- · def generate
- def addDeclaration
- def addImplementation
- def addRoutineUnit
- def addInterfaceBlock
- def getName
- def setFileName
- def getFileName

Public Attributes

- name
- declarations
- · implementations
- · generation
- fileName

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.83 MpiContext_mod Module Reference

<BriefDescription>

Data Types

- type MpiContext
- interface newMpiContext

- subroutine barrier (this)
- integer function **getMpiCommunicator** (this)

17.83.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

MpiContext.F90

17.84 MpiStubs_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public MPI_Comm_rank (comm, rank, ier)
- subroutine, public MPI_Comm_size (comm, size, ier)
- subroutine, public MPI_Comm_dup (comm, newComm, ier)
- subroutine, public **MPI_Comm_group** (comm, group, ier)
- subroutine, public MPI_Group_range_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI_Comm_create (comm, group, newComm, ier)

Public Attributes

- integer, parameter, public MPI_COMM_WORLD = -1
- integer, parameter, public MPI_COMM_NULL = -1
- integer, parameter, public MPI_COMM_SUCCESS = 0

17.84.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiStubs.F90

17.85 MpiTestCase_mod Module Reference

<BriefDescription>

Data Types

type MpiTestCase

Public Member Functions

- recursive subroutine runBare (this)
- integer function **getMpiCommunicator** (this)
- integer function getProcessRank (this)

17.85.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MpiTestCase.F90

17.86 MpiTestCaseB_mod::MpiTestCaseB Type Reference

Public Member Functions

- · procedure setUp
- procedure tearDown
- procedure setUp
- · procedure tearDown

Public Attributes

• integer componentI

The documentation for this type was generated from the following files:

- · MpiTestCaseB.F90
- MpiTestCaseB.pf

17.87 MpiTestCaseB_mod Module Reference

Data Types

type MpiTestCaseB

- subroutine setUp (this)
- subroutine tearDown (this)

- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

17.88 MpiTestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

17.88.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestMethod.F90

17.89 MpiTestParameter_mod Module Reference

Data Types

• type MpiTestParameter

Public Member Functions

 type(MpiTestParameter) function, public newMpiTestParameter (num-ProcessesRequested)

The documentation for this module was generated from the following file:

• MpiTestParameter.F90

17.90 pFUnitParser::MyError Class Reference

Inherits Exception.

Public Member Functions

- def __init__def __str__
- **Public Attributes**

value

The documentation for this class was generated from the following file:

pFUnitParser.py

17.91 Cases_mod::MyParamType Type Reference

Public Member Functions

procedure toString

• integer i

The documentation for this type was generated from the following file:

· Test_Cases.pf

17.92 Cases_mod::MyTestCase Type Reference

Public Attributes

• integer i

The documentation for this type was generated from the following file:

· Test_Cases.pf

17.93 TestCaseC_mod::newC_Parameter Interface Reference

Public Member Functions

- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)

The documentation for this interface was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.94 ParallelContext_mod Module Reference

<BriefDescription>

Data Types

- interface allReduceLogical
- · interface gatherInteger
- interface gatherLogical
- interface gatherString
- interface getNumProcesses
- type ParallelContext
- interface processRank
- · interface sum

17.94.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ParallelContext.F90

17.95 ParallelException_mod Module Reference

<BriefDescription>

Data Types

- interface any Exceptions
- interface getNumExceptions

Public Member Functions

• subroutine, public gather (context)

17.95.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelException.F90

17.96 ParameterizedTestCase_mod Module Reference

<BriefDescription>

Data Types

• type ParameterizedTestCase

Public Attributes

• integer, parameter, public MAX_LEN_LABEL = 32

17.96.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• ParameterizedTestCase.F90

17.97 Params_mod Module Reference

<BriefDescription>

Public Attributes

- integer, parameter **R32** = selected_real_kind(p=6)
- integer, parameter **R64** = selected_real_kind(p=14)
- integer, parameter C32 = selected_real_kind(p=6)
- integer, parameter C64 = selected_real_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

17.97.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Params.F90

17.98 pFUnitParser::Parser Class Reference

Inheritance diagram for pFUnitParser::Parser:



- def __init__
- def commentLine
- def run
- def isComment
- def nextLine
- def printHeader
- def printTail
- def printWrapUserTestCase
- def printRunMethod
- def printParameterHeader
- def printMakeSuite
- def addSimpleTestMethod
- def addMpiTestMethod
- def addUserTestMethod
- def printMakeCustomTest
- def makeWrapperModule
- def final

- fileName
- inputFile
- outputFile
- · defaultSuiteName
- suiteName
- currentLineNumber
- userModuleName
- userTestCase
- userTestMethods
- wrapModuleName
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

17.99 Test_Parameters_mod::peCase Type Reference

Public Member Functions

· procedure toString

Public Attributes

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

17.100 pFUnit Module Reference

<BriefDescription>

Public Member Functions

• integer function run ()

17.100.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

17.101 pFUnit_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public initialize (useMpi)
- subroutine, public finalize (successful)

17.101.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

17.102 PrivateException_mod Module Reference

<BriefDescription>

Data Types

- type Exception
- type ExceptionList
- interface newException

Public Member Functions

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

Public Attributes

- integer, parameter, public **MAXLEN_MESSAGE** = 80*15
- integer, parameter, public **MAXLEN_FILE_NAME** = 80
- character(len=*), parameter, public NULL_MESSAGE = "

17.102.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• Exception.F90

17.103 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



Public Member Functions

- def __init__
- def getLength
- · def match
- def evaluate
- def getNewPosition
- def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- def finditerTokenToPosition
- def makeTokenErrorMessage

Public Attributes

- name
- newPosition
- · tokens
- TokenREs

17.103.1 Member Function/Subroutine Documentation

```
17.103.1.1 def mods::pre::pre2::procDirective::addTokenRE ( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = ''')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

• pre2.py

17.104 RemoteProxyTestCase_mod Module Reference

<BriefDescription>

Data Types

• interface RemoteProxyTestCase

17.104.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

17.105 mods::pre::pre_Repeat::RepeatDirective Class Reference

Inheritance diagram for mods::pre::pre_Repeat::RepeatDirective:



Public Member Functions

• def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_Repeat.py

17.106 ResultPrinter_mod Module Reference

<BriefDescription>

Data Types

• type ResultPrinter

- type(ResultPrinter) function, public newResultPrinter (unit)
- subroutine addError (this, testName, exceptions)
- subroutine **startTest** (this, testName)
- subroutine **print** (this, result)
- subroutine printHeader (this, runTime)
- subroutine printFooter (this, result)

17.106.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

17.107 RobustRunner_mod Module Reference

<BriefDescription>

Data Types

- interface RobustRunner
- type TestCaseMonitor

- subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addFailure (this, testName, exceptions)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

17.107.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RobustRunner.F90

17.108 robustTestSuite_mod Module Reference

Public Member Functions


- type(TestSuite) function, public **suite** ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

17.109 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



Public Member Functions

- def __init__
- · def setName
- · def getName
- def setDeclaration
- def addDeclaration
- def setImplementation
- def getDeclaration
- · def getDeclarations
- def getImplementation
- · def clearDeclarations

Public Attributes

- name
- declaration
- · declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.110 SerialContext_mod Module Reference

<BriefDescription>

Data Types

• type SerialContext

Public Member Functions

• type(SerialContext) function, public newSerialContext ()

Public Attributes

 type(SerialContext), parameter, public THE_SERIAL_CONTEXT = Serial-Context()

17.110.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

17.111 SimpleTestCase_mod Module Reference

Data Types

- · interface method
- type SimpleTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete_ (this)

The documentation for this module was generated from the following file:

• SimpleTestCase.F90

17.112 SourceLocation_mod Module Reference

<BriefDescription>

Data Types

• type SourceLocation

Public Attributes

- character(len=MAXLEN_FILE_NAME), parameter, public UNKNOWN_FILE_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN_LINE_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN_SOURCE_LOCATION = SourceLocation()

17.112.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

17.113 SphericalCoordinates_mod Module Reference

Data Types

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

17.114 TestListener mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

17.115 StringConversionUtilities_mod Module Reference

A collection of utilities used throughout the framework.

Data Types

- interface toString
- type WhitespaceOptions

Public Member Functions

- character(len=len_trim(a)+1+len_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)
- logical function, public whitespacep (c)
- character(len=:) function, allocatable, public trimAll (s)
- character(len=:) function, allocatable, public trimTrailingWhitespace (s)

Public Attributes

- integer, parameter, public **MAXLEN_STRING** = 80
- type(WhitespaceOptions), parameter, public pleaseIgnore = Whitespace-Options(pleaseIgnore_)
- type(WhitespaceOptions), parameter, public pleaseTrim = Whitespace-Options(pleaseTrim)
- type(WhitespaceOptions), parameter, public pleaseKeep = Whitespace-Options(pleaseKeep_)

17.115.1 Detailed Description

A collection of utilities used throughout the framework.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

17.116 SubsetRunner_mod Module Reference

<BriefDescription>

Data Types

• interface SubsetRunner

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

17.116.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• SubsetRunner.F90

17.117 SurrogateTestCase_mod Module Reference

<BriefDescription>

Data Types

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

17.117.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

17.118 SUT mod Module Reference

Data Types

· type SUT

The documentation for this module was generated from the following file:

· Test_MockRepository.F90

17.119 Test_Assert_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test Assert.F90

17.120 Test_AssertBasic_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()
- subroutine testAssertExceptionRaised ()
- subroutine testAssertFail ()

The documentation for this module was generated from the following file:

• Test_AssertBasic.F90

17.121 Test_AssertComplex_mod Module Reference

Public Member Functions

• type(TestSuite) function, public suite ()

- subroutine testEquals C complexScalar ()
- subroutine testEquals_C_0D1D ()
- subroutine testEquals_C_1D_nonConformable1 ()
- subroutine testEquals_C_2D_SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent1
- subroutine testEquals_C_MultiD_SingleElementDifferent2
- subroutine testEquals_C_MultiD_SingleElementDifferent3
- subroutine testEquals_C_MultiD_SingleElementDifferent4
- subroutine testEquals_C_MultiD_SingleElementDifferent5
- subroutine testEquals C MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff2 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff4 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff5 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff7 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals_C_MultiDWithTolerance ()
- subroutine testEquals C MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals C MultiDWithTolerance64_1 ()
- subroutine testEquals C MultiDWithTolerance64 2 ()
- subroutine testEquals C MultiDSourceLocation ()
- subroutine testEquals_4DPComplex_DifferenceReport ()
- subroutine testEquals ComplexMultiD SingleElementNE1
- subroutine testEquals ComplexMultiD SingleElementRE1
- subroutine testEquals ComplexMultiD SingleEltVarious1
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

• Test AssertComplex.F90

17.122 Test_AssertInteger_mod Module Reference

Public Member Functions

• type(TestSuite) function, public suite ()

subroutine testAssertEqual_equal ()

The documentation for this module was generated from the following file:

· Test AssertInteger.F90

17.123 Test_AssertReal_mod Module Reference

- type(TestSuite) function, public suite ()
- subroutine testEquals 0D1D ()
- subroutine testEquals 1D nonConformable1 ()
- subroutine testEquals 2D SingleElementDifferent ()
- subroutine testEquals MultiD SingleElementDifferent ()
- subroutine testEquals MultiD SingleElementDifferent1
- subroutine testEquals MultiD SingleElementDifferent2
- subroutine testEquals_MultiD_SingleElementDifferent3
- subroutine testEquals_MultiD_SingleElementDifferent4
- subroutine testEquals_MultiD_SingleElementDifferent5
- subroutine testEquals MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff5 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals_ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals VectorWithToleranceNoMsq ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals_MultiDWithTolerance1 ()
- subroutine testEquals_MultiDWithTolerance64 ()
- subroutine testEquals MultiDWithTolerance64 1 ()
- subroutine testEquals MultiDWithTolerance64 2 ()
- subroutine testEquals MultiDSourceLocation ()
- subroutine testEquals_ScalarAndLocation ()
- subroutine testEquals ScalarInfinity equal ()
- subroutine testEquals_ScalarInfinity_unequal_A ()

- subroutine testEquals_ScalarInfinity_unequal_B ()
- subroutine testEquals_ScalarInfinity_unequal_C ()
- subroutine testEquals_MultiD_SingleElementGT1
- subroutine testEquals_MultiD_SingleElementGT2
- subroutine testEquals_MultiD_SingleEltVarious1
- subroutine testEquals_MultiD_SingleEltVarious2
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

• Test AssertReal.F90

17.124 Test_BasicOpenMP_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()
- subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

• Test_BasicOpenMP.F90

17.125 Test_Exception_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

The documentation for this module was generated from the following file:

Test_Exception.F90

17.126 Test FixtureTestCase mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test FixtureTestCase.F90

17.127 Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference

Public Member Functions

- procedure setUp
- · procedure tearDown

Public Attributes

• type(LinearInterpolator) interpolator

The documentation for this type was generated from the following file:

· Test_LinearInterpolator.pf

17.128 Test_LinearInterpolator_mod Module Reference

Data Types

• type Test_LinearInterpolator

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

· Test LinearInterpolator.pf

17.129 Test_MockCall_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

• Test MockCall.F90

17.130 Test_MockRepository_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test MockRepository.F90

17.131 Test_mod Module Reference

<BriefDescription>

Data Types

- interface countTestCases
- interface getName
- · interface run
- type Test

Public Attributes

• integer, parameter, public MAX_LENGTH_NAME = 64

17.131.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

17.132 Test_MpiContext_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

Test_MpiContext.F90

17.133 Test_MpiException_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine test_anyExceptions_none (this)
- subroutine test_getNumExceptions (this)
- subroutine test_gather (this)

The documentation for this module was generated from the following file:

Test MpiException.F90

17.134 Test_MpiParameterizedTestCase_mod Module Reference

Data Types

- type ExtendedTestParameter
- · interface method
- type Test MpiTestCase

Public Member Functions

- type(TestSuite) function, public **suite** ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, testParameter)
- subroutine testToString (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

• Test MpiParameterizedTestCase.F90

17.135 Test_MpiTestCase_mod Module Reference

Data Types

- · interface method
- type Test_MpiTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- · recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

• Test_MpiTestCase.F90

17.136 Test_Parameters_mod::Test_Parameters Type Reference

Public Attributes

- integer p1
- · integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

17.137 Test_Parameters_mod Module Reference

Data Types

- type peCase
- type Test Parameters

- type(Test_Parameters) function **newTest** (testParameter)
- type(peCase) function newPeCase (p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()

Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates Type Reference 149

- character(:) function, allocatable toString (this)
- subroutine testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

17.138 Test_RestrictSphericalCoordinates_mod::Test_Restrict-SphericalCoordinates Type Reference

Public Attributes

- · real lat
- real lon
- · real restrictedLat
- real restrictedLon
- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.139 Test_RestrictSphericalCoordinates_mod Module Reference

Data Types

- type LatLonCase
- type Test_RestrictSphericalCoordinates

Public Member Functions

- type(Test RestrictSphericalCoordinates) function **newTest** (testParameter)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

• Test_RestrictedSphericalCoordinates.pf

17.140 Test_RobustRunner_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

• Test RobustRunner.F90

17.141 Test_SimpleTestCase_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()
- subroutine testRunMethodShouldFail ()

The documentation for this module was generated from the following file:

· Test SimpleTestCase.F90

17.142 Test_StringConversionUtilities_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test_StringConversionUtilities.F90

17.143 Test TestMethod mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

• Test_TestMethod.F90

17.144 Test_TestResult_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

• Test_TestResult.F90

17.145 Test_TestSuite_mod Module Reference

Data Types

• type Verbose

- type(TestSuite) function, public suite ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()

- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

The documentation for this module was generated from the following file:

· Test_TestSuite.F90

17.146 Test_UnixProcess_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testIsActive ()

The documentation for this module was generated from the following file:

Test_UnixProcess.F90

17.147 Test_XmlPrinter_mod Module Reference

Output test messages in junit.xsd-compatible XML.

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testValidXml ()
- subroutine compareXMLFileToExpectation (xmlFile)

17.147.1 Detailed Description

Output test messages in junit.xsd-compatible XML.

Author

Halvor Lund

Date

2014 July

Note

Set up a test failure and feed it to an XML-based printer so that we can test its output. Use command line call (via "system") to try to find "xmllint," and if available, use it to validate the output against junit.xsd. Either way, check the output against a hard-coded expected result (a regression test).

The documentation for this module was generated from the following file:

• Test XmlPrinter.F90

17.148 TestA mod Module Reference

Public Member Functions

- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)
- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)

The documentation for this module was generated from the following files:

- TestA.F90
- TestA.pf

17.149 TestCase_mod Module Reference

<BriefDescription>

Data Types

- type ConcreteSurrogate
- type TestCase
- type TestCaseReference

Public Member Functions

- recursive subroutine runBare (this)
- recursive subroutine runBare surrogate (this)

17.149.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestCase.F90

17.150 TestCaseA_mod::TestCaseA Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

· integer componentl

The documentation for this type was generated from the following files:

- TestCaseA.F90
- TestCaseA.pf

17.151 TestCaseA mod Module Reference

Data Types

• type TestCaseA

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine **testA** (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

17.152 TestCaseB_mod::TestCaseB Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- · real phi
- · real theta

The documentation for this type was generated from the following files:

- ParameterizedTestCaseB.F90
- ParameterizedTestCaseB.pf

17.153 TestCaseB_mod Module Reference

Data Types

- type B_Parameter
- type TestCaseB

Public Member Functions

- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- character(:) function, allocatable toString (this)
- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.154 TestCaseC_mod::TestCaseC Type Reference

- procedure setUp
- · procedure tearDown
- · procedure setUp
- · procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- · real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.155 TestCaseC_mod Module Reference

Data Types

- type C_Parameter
- interface newC_Parameter
- type TestCaseC

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)
- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable **toString** (this)

The documentation for this module was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.156 TestFailure_mod Module Reference

```
<BriefDescription>
```

Data Types

· type TestFailure

17.156.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

17.157 mods::pre::pre_lf::TestIfDirective Class Reference

- def testTokenNotFound1
- def testNoTest
- · def testIFTestFalse

- def testIFTestTrue1
- def testIFTestTrue2
- def testIFClearTokens
- def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

pre_lf.py

17.158 mods::pre::interleavedp::TestInterleaved Class Reference

Public Member Functions

- · def test InOrder
- · def test NumberMismatch
- def test_OrderMismatch1
- def test OrderMismatch2
- def test_OrderMismatch3
- def test ElseMid1
- def test_ElseMid2
- · def test ElseMid3
- def test_ElseMid4
- · def test_ElseMid5
- def test_ElseMid6
- def test_ElseMid7
- def test_ElseMid8def test_ElseMid9
- def test ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

17.159 TestListener_mod Module Reference

<BriefDescription>

Data Types

- · interface addFailure
- interface endRun
- interface endTest
- type ListenerPointer
- interface startTest
- type TestListener

Public Member Functions

- subroutine addError (this, testName, exceptions)
- subroutine **setDebug** (this)

17.159.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestListener.F90

17.160 TestMethod_mod Module Reference

<BriefDescription>

Data Types

- interface empty
- interface newTestMethod
- type TestMethod

17.160.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

17.161 mods::pre::parseArgs::TestParseArgs Class Reference

Public Member Functions

- · def test ParseArgs OneArgWithBrackets1
- def test_ParseArgs_OneArgWithBrackets2
- · def test ParseArgs OneArgWithBrackets3
- · def test ParseArgs OneArgWithBrackets4
- def test_ParseArgs_OneArgWithBrackets5
- def test_ParseArgs_OneArgWithBrackets6
- · def test_ParseArgs_OneArgWithBrackets7
- def test_ParseArgs_oneArg
- def test ParseArgs twoArgs1
- def test_ParseArgs_twoArgs2
- def test_ParseArgs_oneArgArray1
- def test_ParseArgs_TwoArgArray
- def test_ParseArgs_ThreeArgs

The documentation for this class was generated from the following file:

parseArgs.py

17.162 testParser::TestParseLine Class Reference

Public Member Functions

- def testCppSetLineAndFile
- def testGetSubroutineName
- · def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtTestNoParens
- def testAtTestFail
- def testAtTestSkipComment
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- def testMatchAtAssertOther
- def testMatchAtMpiAssert
- · def testMatchAtBefore
- · def testMatchAtAfter
- · def testMatchAtSuite

17.162.1 Member Function/Subroutine Documentation

17.162.1.1 def testParser::TestParseLine::testAtMpiTest(self)

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

17.162.1.2 def testParser::TestParseLine::testAtTest(self)

Check that a line starting with '@test' is detected as an annotation.

17.162.1.3 def testParser::TestParseLine::testAtTestFail(self)

Check that useful error is sent if next line is not properly formatted.

17.162.1.4 def testParser::TestParseLine::testAtTestNoParens (self)

Check that test procedure with no parens is accepted.

17.162.1.5 def testParser::TestParseLine::testAtTestSkipComment (self)

Ignore comment lines between @test and subroutine foo().

17.162.1.6 def testParser::TestParseLine::testMatchAtAfter(self)

Check that a line starting with '@after*' \dots

17.162.1.7 def testParser::TestParseLine::testMatchAtAssertEqual (self)

Check that a line starting with '@assertEqual' is detected as an annotation.

17.162.1.8 def testParser::TestParseLine::testMatchAtAssertOther(self)

Check that a line starting with '@assert*' is detected as an annotation.

17.162.1.9 def testParser::TestParseLine::testMatchAtBefore (self)

Check that a line starting with '@before*' ...

17.162.1.10 def testParser::TestParseLine::testMatchAtMpiAssert (self)

Check that a line starting with '@mpiAssert*' is detected as an annotation.

17.162.1.11 def testParser::TestParseLine::testMatchAtSuite (self)

Check that a line starting with 'esuite changes the suite name \dots

17.162.1.12 def testParser::TestParseLine::testMatchAtTestCase (self)

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

testParser.py

17.163 mods::pre::pre_Repeat::TestRepeatDirective Class Reference

Public Member Functions

- · def test copyBlock1
- def test_copyBlock2
- def test_copyBlock2Vars
- · def test copyBlock2VarsMulti
- def test_copyBlock2VarsMultiWithStrings
- · def test_copyNaiveRecursion
- · def test_copyNaiveRecursion1
- def test_copyFunction1

The documentation for this class was generated from the following file:

pre_Repeat.py

17.164 TestResult mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Data Types

· type TestResult

Public Member Functions

- type(TestResult) function, public newTestResult (name)
- subroutine addError (this, aTest, exceptions)
- subroutine addSuccess (this, aTest)
- integer function failureCount (this)
- · subroutine addListener (this, listener)

17.164.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestResult.F90

17.165 TestRunner_mod Module Reference

<BriefDescription>

Data Types

- interface newTestRunner
- type TestRunner

Public Member Functions

- type(TestResult) function **run** (this, aTest, context)
- subroutine startTest (this, testName)
- subroutine addFailure (this, testName, exceptions)

17.165.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestRunner.F90

17.166 TestSuite_mod Module Reference

```
<BriefDescription>
```

Data Types

- interface newTestSuite
- type TestReference
- type TestSuite

Public Member Functions

• recursive subroutine addTest (this, aTest)

17.166.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestSuite.F90

17.167 ThrowFundamentalTypes_mod Module Reference

<BriefDescription>

Data Types

- · interface throwDifferentValues
- interface throwDifferentValuesWithLocation

Public Member Functions

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN_SHAPE) function, public locationFormat (iLocation)

17.167.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

17.168 UnixPipeInterfaces_mod Module Reference

<BriefDescription>

Data Types

- interface fgets
- · interface free
- interface getdelim
- interface getline
- interface pclose
- interface popen

Public Attributes

• integer(C_INT), parameter, public CLOSE_FAILED = -1

17.168.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixPipeInterfaces.F90

17.169 UnixProcess_mod Module Reference

<BriefDescription>

Data Types

· interface UnixProcess

Public Member Functions

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

17.169.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

UnixProcess.F90

17.170 GenerateAssertsOnArrays::VECTOR_NORM Class Reference

Inheritance diagram for GenerateAssertsOnArrays::VECTOR_NORM:



Public Member Functions

def __init___

Public Attributes

- rank
- fType
- · precision
- name
- · declaration
- · declarations

The documentation for this class was generated from the following file:

· GenerateAssertsOnArrays.py

17.171 AbstractTestResult_mod::wasSuccessful Interface Reference

The documentation for this interface was generated from the following file:

AbstractTestResult.F90

17.172 WrapbeforeAfter Module Reference

The documentation for this module was generated from the following file:

· beforeAfter.F90

17.173 WrapMpiTestCaseB_mod Module Reference

Data Types

- · interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, npesRequested)

The documentation for this module was generated from the following file:

• MpiTestCaseB.F90

17.174 Wrapsimple Module Reference

The documentation for this module was generated from the following file:

• simple.F90

17.175 WrapTestA_mod Module Reference

The documentation for this module was generated from the following file:

TestA.F90

17.176 WrapTestCaseA_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod)

The documentation for this module was generated from the following file:

TestCaseA.F90

17.177 WrapTestCaseB_mod Module Reference

Data Types

- · interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter)

The documentation for this module was generated from the following file:

• ParameterizedTestCaseB.F90

17.178 WrapTestCaseC_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter, npesRequested)

The documentation for this module was generated from the following file:

• MpiParameterizedTestCaseC.F90

17.179 XmlPrinter_mod Module Reference

<BriefDescription>

Data Types

· type XmlPrinter

- type(XmlPrinter) function, public newXmlPrinter (unit)
- subroutine addError (this, testName, exceptions)

- subroutine startTest (this, testName)
- subroutine print (this, result)
- subroutine **printHeader** (this, result)
- subroutine **printFailure** (this, label, aFailedTest)
- subroutine **printExceptions** (this, label, testName, exceptions)
- subroutine **printFailure1** (this, label, aFailedTest)
- subroutine printFailures (this, label, failures)
- subroutine **printTestName** (this, testName)
- subroutine printSuccess (this, aSuccessTest)
- subroutine printSuccesses (this, successes)
- subroutine **printFooter** (this, result)
- character(:) function, allocatable **cleanXml** (string_in)

17.179.1 Detailed Description

<BriefDescription>

Author

Halvor Lund, SINTEF Energy Research

Date

30 Jan 2014

Note

<A note here. > Need to improve the handling of nested quotes.

The documentation for this module was generated from the following file:

• XmlPrinter.F90