pFUnit

Generated by Doxygen 1.7.6

Thu Dec 11 2014 19:55:29

Contents

1	pFU	nit 3 - Documentation - Version 2014-1212-0025-15-UTC MLR	1
	1.1	Overview	1
	1.2	Contents	1
	1.3	See Also	2
	1.4	LICENSE	2
	1.5	Copyright	2
2	Obta	ining pFUnit	3
3	Insta	Illation	5
	3.1	Installing pFUnit	5
	3.2	Prerequisites	5
	3.3	Obtaining pFUnit	6
	3.4	Manifest - What's in the directory?	6
	3.5	Configuration	7
	3.6	Building pFUnit	8
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8
		3.6.3 OPENMP	9
		3.6.4 Cleaning	9
		3.6.5 Documentation	9
		3.6.6 CMAKE	0
	2.7	Installation	Λ

		3.7.1	Installation - Serial	. 10
		3.7.2	Installation - MPI	. 11
		3.7.3	Installation - OPENMP	. 11
		3.7.4	Installation - DEFAULT DIRECTORY	. 11
4	Usa	ge		13
	4.1	Usage		. 13
		4.1.1	Usage - Configuration	. 13
		4.1.2	Usage - Hello World	. 13
	4.2	Usage	- Preprocessor	. 14
	4.3	Compil	ling and Executing The Test	. 14
		4.3.1	- Compiling and Executing the Tests (MPI PARALLEL)	. 14
		4.3.2	Command Line Options	. 15
5	Deve	elopmer	nt	17
6	Feed	lback &	Support	19
	6.1	Feedba	ack	. 19
	6.2	Suppor	rt	. 19
7	FAQ	and Tip	os	21
	7.1	FAQ .		. 21
		7.1.1	Zero Tests Run	. 21
		7.1.2	Some Tests Are Not Running	. 22
		7.1.3	Intel Fortran Version 13: -DINTEL_13	. 22
		7.1.4	Segmentation Faults and Odd Link Errors	. 22
	7.2	Tips .		. 23
		7.2.1	Environment Modules	. 23
		7.2.2	Compile Time Errors	. 23
		7.2.3	Intermediate files used by pFUnit	. 23
		7.2.4	Ignoring whitespace differences in assertions on strings	. 23
8	Plati	form Sp	ecific Notes	25

CONTENTS	ii

	8.1	Mac O	SX				 						25
	8.2	Windov	vs/CYGWIN	١			 						25
	8.3	Intel Fo	ortran Versio	on 13: -D	INTEL_	13 .	 						25
9	ACKI	nowledg	ments										27
10	Kno	wn Insta	allations &	Versions	3								29
11	TOD	0											31
12	The	Preproc	essor - pF	UnitPars	er								33
	12.1	Using 1	- Γhe Preproc	cessor			 						33
		_	Configurat										
			Invocation										
		12.1.3	Preproces	sor Input	File (.p	f) .	 						34
			Directives										
			12.1.4.1	@Test .			 						35
			12.1.4.2	@MPITes	st		 						35
			12.1.4.3	@Assert			 						36
			12.1.4.4	@Param	eters .		 						37
			12.1.4.5	@TestCa	ise		 						37
13	@As	sert Pre	eprocessor	r Directiv	es								39
	13.1	@Asse	ert Preproce	ssor Dire	ectives .		 						40
		13.1.1	@assertE	qual			 						40
		13.1.2	@assertTr	'ue			 						40
		13.1.3	@assertE	qualUser	Defined	١	 						40
		13.1.4	@assertFa	alse			 						40
		13.1.5	@assertLe	essThan			 						40
		13.1.6	@assertLe	essThanC	OrEqual		 						40
		13.1.7	@assertG	reaterTha	an		 						40
		13.1.8	@assertG	reaterTha	anOrEq	ual	 						40
		13.1.9	@assertIs	Member	Of		 						40

iv CONTENTS

		13.1.10 @assertContains	41
		13.1.11 @assertAny	41
		13.1.12 @assertAll	41
		13.1.13 @assertNotAll	41
		13.1.14 @assertNone	41
		13.1.15 @assertIsPermutationOf	41
		13.1.16 @assertExceptionRaised	41
		13.1.17 @assertSameShape	41
		13.1.18 @assertIsNaN	41
		13.1.19 @assertIsFinite	41
		13.1.20 @assertAssociated	41
		13.1.21 @assertUnAssociated	41
		13.1.22 @assertAssociatedWith	41
		13.1.23 @assertUnAssociatedWith	42
		13.1.24 @assertEquivalent	42
	<u> </u>	Post Market	
4 4			
14	Revis	sion Notes	43
		Type Index	43 45
	Data		
15	Data 15.1	Type Index	45
15	Data 15.1 Data	Type Index Class Hierarchy	45
15 16	Data 15.1 Data 16.1	Type Index Class Hierarchy	45 45
15 16	Data 15.1 Data 16.1 Data	Type Index Class Hierarchy	45 45 49 55
15 16	Data 15.1 Data 16.1 Data 17.1	Type Index Class Hierarchy Type Index Data Types List Type Documentation	45 45 49 49 55
15 16	Data 15.1 Data 16.1 Data 17.1 17.2	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference	45 45 49 49 55
15 16	Data 15.1 Data 16.1 Data 17.1 17.2 17.3	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference AbstractTestResult_mod Module Reference	45 45 49 55 55
15 16	Data 15.1 Data 16.1 Data 17.1 17.2 17.3 17.4	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference AbstractTestResult_mod Module Reference pFUnitParser::Action Class Reference	45 45 49 49 55 55 56
15 16	Data 15.1 Data 16.1 Data 17.1 17.2 17.3 17.4 17.5	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference AbstractTestResult_mod Module Reference pFUnitParser::Action Class Reference add_mod Module Reference	45 49 49 55 55 56 57
15 16	Data 15.1 Data 16.1 Data 17.1 17.2 17.3 17.4 17.5 17.6	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference AbstractTestResult_mod Module Reference pFUnitParser::Action Class Reference add_mod Module Reference addComplex_mod Module Reference	45 45 49 49 55 55 56 57
15 16	Data 15.1 Data 16.1 Data 17.1 17.2 17.3 17.4 17.5 17.6	Type Index Class Hierarchy Type Index Data Types List Type Documentation AbstractTestParameter_mod Module Reference AbstractTestResult_mod Module Reference pFUnitParser::Action Class Reference add_mod Module Reference addComplex_mod Module Reference CodeUtilities::ArrayDescription Class Reference	45 45 49 49 55 55 56 57 57

CONTENTS v

17.8 AssertBasic_mod Module Reference	58
17.8.1 Detailed Description	59
17.9 GenerateAssertsOnArrays::AssertRealArrayArgument Class Reference .	60
17.10pFUnitParser::AtAfter Class Reference	61
17.11pFUnitParser::AtAssert Class Reference	61
17.12pFUnitParser::AtAssertAssociated Class Reference	62
17.13pFUnitParser::AtAssertAssociatedWith Class Reference	63
17.14pFUnitParser::AtAssertEqualUserDefined Class Reference	63
17.14.1 Detailed Description	64
17.15pFUnitParser::AtAssertEquivalent Class Reference	64
17.15.1 Detailed Description	65
17.16pFUnitParser::AtAssertUnAssociated Class Reference	65
17.17pFUnitParser::AtAssertUnAssociatedWith Class Reference	66
17.18pFUnitParser::AtBefore Class Reference	66
17.19pFUnitParser::AtBegin Class Reference	67
17.20pFUnitParser::AtMpiAssert Class Reference	67
17.21pFUnitParser::AtMpiTest Class Reference	68
17.22pFUnitParser::AtSuite Class Reference	69
17.23pFUnitParser::AtTest Class Reference	69
17.24pFUnitParser::AtTestCase Class Reference	70
17.25pFUnitParser::AtTestParameter Class Reference	71
17.26TestCaseB_mod::B_Parameter Type Reference	71
17.27BaseTestRunner_mod Module Reference	72
17.27.1 Detailed Description	72
17.28BeforeAfter_mod Module Reference	73
17.29BrokenSetUpCase_mod Module Reference	73
17.30BrokenTestCase_mod Module Reference	73
17.31 TestCaseC_mod::C_Parameter Type Reference	74
17.32Cases_mod Module Reference	74
17.33GenerateAssertsOnArrays::constraintASSERT Class Reference	75
17.33.1 Constructor & Destructor Documentation	75

vi CONTENTS

17.33.1.1init	75
17.33.2 Member Data Documentation	76
17.33.2.1 name1	76
17.33.2.2 tolerance	76
17.34mods::pre::pre2::dataString Class Reference	76
17.35 DebugListener_mod Module Reference	77
17.35.1 Detailed Description	77
17.36CodeUtilities::declaration Class Reference	78
17.37 DynamicTestCase_mod Module Reference	78
17.37.1 Detailed Description	79
17.38Exception_mod Module Reference	79
17.39 Expectation_mod Module Reference	80
17.40 Fixture_mod Module Reference	80
17.41 FixtureTestCase_mod Module Reference	81
17.42CodeUtilities::fortranSubroutineSignature Class Reference	81
17.43AbstractTestResult_mod::getErrors Interface Reference	82
17.44Test_mod::getName Interface Reference	82
17.45AbstractTestResult_mod::getSuccesses Interface Reference	82
17.46Halo_mod Module Reference	82
17.47 mods::pre_ifr::lfDirective Class Reference	82
17.48CodeUtilities::implementation Class Reference	83
17.49CodeUtilities::interfaceBlock Class Reference	83
17.50 mods::pre_ifr::interval Class Reference	84
17.51 Generate Asserts On Arrays::Is Within Tolerance Class Reference	84
$17.52 \\ Test_Restrict Spherical Coordinates_mod:: LatLon Case Type \ Reference .$	85
17.53LinearInterpolator_mod Module Reference	85
17.54MakeInfinity_mod Module Reference	86
17.54.1 Detailed Description	86
17.55MakeNaN_mod Module Reference	86
17.55.1 Detailed Description	87
17.56 Mock mod Module Reference	87

CONTENTS vii

17.56.1 Detailed Description	7
17.57MockCall_mod Module Reference	8
17.57.1 Detailed Description	8
17.58MockListener_mod Module Reference	9
17.59testParser::MockParser Class Reference	9
17.60MockRepository_mod Module Reference	0
17.60.1 Detailed Description	0
17.61 MockSUT_mod Module Reference	1
17.62testParser::MockWriter Class Reference	1
17.63CodeUtilities::module Class Reference	2
17.64MpiContext_mod Module Reference	2
17.64.1 Detailed Description	3
17.65MpiStubs_mod Module Reference	3
17.65.1 Detailed Description	4
17.66MpiTestCase_mod Module Reference	4
17.66.1 Detailed Description	4
17.67MpiTestCaseB_mod::MpiTestCaseB Type Reference	5
17.68MpiTestCaseB_mod Module Reference	5
17.69MpiTestMethod_mod Module Reference	6
17.69.1 Detailed Description	6
17.70MpiTestParameter_mod Module Reference	7
17.71pFUnitParser::MyError Class Reference	7
17.72Cases_mod::MyParamType Type Reference	7
17.73Cases_mod::MyTestCase Type Reference	8
17.74TestCaseC_mod::newC_Parameter Interface Reference 9	8
17.75ParallelContext_mod Module Reference	8
17.75.1 Detailed Description	9
17.76ParallelException_mod Module Reference	9
17.76.1 Detailed Description	0
17.77ParameterizedTestCase_mod Module Reference	0
17.77.1 Detailed Description	0

viii CONTENTS

17.78 Params_mod Module Reference	. 101
17.78.1 Detailed Description	. 101
17.79pFUnitParser::Parser Class Reference	102
17.80Test_Parameters_mod::peCase Type Reference	. 103
17.81pFUnit Module Reference	103
17.81.1 Detailed Description	104
17.82pFUnit_mod Module Reference	. 104
17.82.1 Detailed Description	. 104
17.83PrivateException_mod Module Reference	105
17.83.1 Detailed Description	. 105
17.84mods::pre2::procDirective Class Reference	. 106
17.84.1 Member Function/Subroutine Documentation	. 107
17.84.1.1 addTokenRE	. 107
17.85RemoteProxyTestCase_mod Module Reference	. 107
17.85.1 Detailed Description	. 107
17.86mods::pre::pre_Repeat::RepeatDirective Class Reference	. 108
17.87ResultPrinter_mod Module Reference	. 108
17.87.1 Detailed Description	. 109
17.88RobustRunner_mod Module Reference	. 109
17.88.1 Detailed Description	. 110
17.89robustTestSuite_mod Module Reference	. 110
17.90CodeUtilities::routineUnit Class Reference	. 110
17.91SerialContext_mod Module Reference	. 111
17.91.1 Detailed Description	112
17.92SimpleTestCase_mod Module Reference	112
17.93 SourceLocation_mod Module Reference	. 113
17.93.1 Detailed Description	. 113
17.94SphericalCoordinates_mod Module Reference	. 113
17.95TestListener_mod::startTest Interface Reference	. 114
17.96StringConversionUtilities_mod Module Reference	. 114
17.96.1 Detailed Description	. 115

CONTENTS ix

17.97SubsetRunner_mod Module Reference
17.97.1 Detailed Description
17.98SurrogateTestCase_mod Module Reference
17.98.1 Detailed Description
17.99SUT_mod Module Reference
17.10 © est_Assert_mod Module Reference
17.10Test_AssertBasic_mod Module Reference
17.10 Z est_AssertComplex_mod Module Reference
17.103est_AssertInteger_mod Module Reference
17.104est_AssertReal_mod Module Reference
17.105est_BasicOpenMP_mod Module Reference
17.10 6 est_Exception_mod Module Reference
17.107est_FixtureTestCase_mod Module Reference
17.108fest_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 121
17.109 est_LinearInterpolator_mod Module Reference
17.11 © est_MockCall_mod Module Reference
17.11 Test_MockRepository_mod Module Reference
17.11 7 est_mod Module Reference
17.112. Detailed Description
17.113est_MpiContext_mod Module Reference
17.114est_MpiException_mod Module Reference
17.115est_MpiParameterizedTestCase_mod Module Reference
17.11 6 est_MpiTestCase_mod Module Reference
17.11 T est_Parameters_mod::Test_Parameters Type Reference
17.118 Est_Parameters_mod Module Reference
17.11 9 est_RestrictSphericalCoordinates_mod::Test_RestrictSpherical-Coordinates Type Reference
17.120 Test_RestrictSphericalCoordinates_mod Module Reference
17.12Test_RobustRunner_mod Module Reference
17.12 Z est_SimpleTestCase_mod Module Reference
17.123est_StringConversionUtilities_mod Module Reference

X CONTENTS

17.124est_TestMethod_mod Module Reference
17.125est_TestResult_mod Module Reference
17.12 6 est_TestSuite_mod Module Reference
17.12Test_UnixProcess_mod Module Reference
17.128est_XmlPrinter_mod Module Reference
17.128. Detailed Description
17.12¶estA_mod Module Reference
17.130estCase_mod Module Reference
17.130. Detailed Description
17.13TestCaseA_mod::TestCaseA Type Reference
17.13ZestCaseA_mod Module Reference
17.133estCaseB_mod::TestCaseB Type Reference
17.134estCaseB_mod Module Reference
17.135estCaseC_mod::TestCaseC Type Reference
17.13 6 estCaseC_mod Module Reference
17.137estFailure_mod Module Reference
17.137. Detailed Description
17.13&nods::pre::pre_lf::TestIfDirective Class Reference
17.13@nods::pre::interleavedp::TestInterleaved Class Reference
17.14 0 estListener_mod Module Reference
17.140. Detailed Description
17.14TestMethod_mod Module Reference
17.141. Detailed Description
17.142nods::pre::parseArgs::TestParseArgs Class Reference
17.148estParser::TestParseLine Class Reference
17.143. Member Function/Subroutine Documentation
17.143.1.1testAtMpiTest
17.143.1.2iestAtTest
17.143.1.3testAtTestFail
17.143.1.4testAtTestNoParens
17.143.1.5testAtTestSkipComment

CONTENTS xi

17.143.1.@estMatchAtAfter
17.143.1.7lestMatchAtAssertAssociated
17.143.1.8testMatchAtAssertAssociatedWith
17.143.1.9testMatchAtAssertEqual
17.143.1.11@stMatchAtAssertEqualUserDefined 140
17.143.1.1testMatchAtAssertEqualUserDefinedWithMessage 141
17.143.1.1t2estMatchAtAssertEquivalent
17.143.1.16estMatchAtAssertOther
17.143.1.1testMatchAtAssertUnAssociated
17.143.1.1t6stMatchAtAssertUnAssociatedWith 141
17.143.1.1t@stMatchAtBefore
17.143.1.1testMatchAtMpiAssert
17.143.1.1testMatchAtSuite
17.143.1.119stMatchAtTestCase
17.143.1.2@stParseArgsFirstRest
17.143.1.2testParseArgsFirstSecondRest
17.14parseBrackets::TestRejoinBracketed Class Reference
17.145nods::pre::pre_Repeat::TestRepeatDirective Class Reference 142
17.146 estResult_mod Module Reference
17.146. Detailed Description
17.147estRunner_mod Module Reference
17.147. Detailed Description
17.148estSuite_mod Module Reference
17.148. Detailed Description
17.149 hrowFundamental Types mod Module Reference
17.149. Detailed Description
17.15@nixPipeInterfaces_mod Module Reference
17.150. Detailed Description
17.15UnixProcess_mod Module Reference
17.151. Detailed Description
17.15&enerateAssertsOnArrays::VECTOR_NORM Class Reference 148

xii CONTENTS

17.15 AbstractTestResult_mod::wasSuccessful Interface Reference	 	149
17.154VrapbeforeAfter Module Reference	 	149
17.15 5 VrapMpiTestCaseB_mod Module Reference	 	149
17.15@Vrapsimple Module Reference	 	149
17.15\mathbf{W}rapTestA_mod Module Reference	 	. 150
17.158VrapTestCaseA_mod Module Reference	 	. 150
17.159VrapTestCaseB_mod Module Reference	 	150
17.16WrapTestCaseC_mod Module Reference	 	. 151
17.16XmlPrinter_mod Module Reference	 	. 151
17.161. Detailed Description	 	. 152

pFUnit 3 - Documentation - Version 2014-1212-0025-15-UTC MLR

Quick links to the code or the project's SourceForge site.

1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. Initial support for OPENMP has been implemented. pF-Unit makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Advanced Software Technology Group, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

1.2 Contents

- Installation
 - Obtaining pFUnit
- Usage

- Development
- · Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

1.4 LICENSE

Rights of use for GSC-15,137-1 F-UNIT, also known as pFUnit, are defined by the N-ASA Open Source Agreement (version 1.3). The LICENSE document may be found in the head directory of the pFUnit distribution.

1.5 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

Installation

3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
 - Building pFUnit for testing serial codes (Non-MPI)
 - Building pFUnit for testing parallel codes (MPI)
 - OPENMP
 - Cleaning
 - Documentation
- Installation

3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.3, 4.9.0, IBM's XLF)
- The Message Passing Interface (MPI)
- OpenMP
- · GNU Make
- Python

Note: Recent changes have exposed a latent bug in GCC 4.8.2. The fix is available in the GCC 4.9 development branch and will also appear in GCC 4.8.3 when that is released. Users that require older versions of GCC should use pFUnit 2.1.x.

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

3.5 Configuration 7

CMakeLists.txt - Initial support for cmake-based builds.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

GNUmakefile - The top level makefile for building and installing pFUnit.

LICENSE - The NASA Open Source Agreement for GSC-15,137-1 F-UNIT, also known as pFUnit.

README-INSTALL - Basic documentation on pFUnit installation and use.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

VERSION - Contains a string describing the current version of the framework.

3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'PFUNIT_MAX_RANK' - controls the maximum size of the arrays asserts are defined over. If PFUNIT_MAX_RANK is not set, the default is 5 and pFUnit's assertions will be able to handle arrays up to rank 5.

8 Installation

```
$ export PFUNIT_MAX_RANK=5
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

\$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen

3.6 Building pFUnit

3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (for example in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

3.6.3 OPENMP

Initial (limited) support for OPENMP has been implemented. At this writing, a basic functionality is available.

The process for building pFUnit for testing OPENMP-based codes is similar to that for other paradigms.

3. To compile for OPENMP support execute make as follows.

```
$ make tests OPENMP=YES
```

4. At this point the OPENMP-enabled pFUnit is ready to be installed.

3.6.4 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src_clean' to remove intermediate products in subdirectories.

3.6.5 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following from the top level of your pFUnit distribution.

```
$ make documentation
```

Or to make a reference manual.

10 Installation

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

3.6.6 CMAKE

Initial support for CMAKE has been implemented. At this writing, a basic functionality is available.

3. The process for building pFUnit using cmake is as follows. In the top directory of the distribution make a new directory to support the build, then change to that directory and run cmake (pointing back to the source) to generate the required makefiles.

```
$ mkdir build
$ cd build
$ # e.g. cmake -DMPI=YES -DOPENMP=NO -DINSTALL_PATH=<A path> <path to source>
$ cmake -DMPI=NO ..
$ make tests
```

One may also set the environment variable PFUNIT instead of setting INSTALL_PATH on the cmake command line as given above.

4. If the build is successful, then at this point make install should work.

3.7 Installation

3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL_DIR to the location in which to place pFUnit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ cd Examples
$ ./buildIt
```

3.7 Installation 11

3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

To test, set PFUNIT and go into Examples/MPI_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

3.7.3 Installation - OPENMP

At this time the OPENMP version of pFUnit can be installed in the same way as for the serial or MPI-parallel codes. OPENMP support, tests, and examples are limited as of this writing.

3.7.4 Installation - DEFAULT DIRECTORY

If INSTALL_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

12 Installation

Usage

- Usage Configuration
- Usage Hello World
- Usage Preprocessor
- · Compiling and Executing The Test

4.1 Usage

4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
```

14 Usage

```
subroutine testHelloWorld()
  use pfunit_mod
  implicit none
  @assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

4.2 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

4.3 Compiling and Executing The Test

An example of a GNU make rule for for the final step of compiling a test follows.

To execute the tests, one invokes "./tests.x" with the appropriate command line options (see below).

4.3.1 - Compiling and Executing the Tests (MPI PARALLEL)

One invokes MPI-based parallel tests according to the MPI framework being used. For example:

```
$ mpirun -np 4 tests.x
```

4.3.2 Command Line Options

The executable test program provides several command line options, when "include/driver.F90" is used, as it is automatically when using the PFUNIT preprocessor.

-v or -verbose	Verbose execution.
-d or -debug	Provide debugging information.
-h	Print help message.
-o <outputfile></outputfile>	Direct pFUnit messages to a file.
-robust	Use the robust runner. Runs tests as
	processes so failures do not halt testing.
-skip <number of="" skip="" tests="" to=""></number>	Use the subset runner, which runs a
	subset of the tests in a suite.

An example from Examples/Robust:

\$./tests.x -robust

16 Usage

Development

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

18 Development

Feedback & Support

- Feedback
- Support

6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

FAQ and Tips

- FAQ
 - Zero Tests Run
 - Some Tests Are Not Running
 - Intel Fortran Version 13: -DINTEL_13
 - Segmentation Faults and Odd Link Errors
- Tips
 - Environment Modules
 - Compile Time Errors
 - Intermediate files used by pFUnit
 - Ignoring whitespace differences in assertions on strings.

7.1 FAQ

7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. *Solutions:*

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD_TEST_SUITE (the_suite_to_add), one to a line.
- There is no <code>-DUSE_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

22 FAQ and Tips

7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

Solutions:

 There is no -DUSE_MPI passed to the compiler during the build. Please add as in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

7.1.3 Intel Fortran Version 13: -DINTEL 13

Using version 13 is deprecated. We have encountered problems using version 13, which we believe may be due to subtle compiler bugs. We strongly recommend upgrading to the latest version possible.

To make pFUnit work with Intel Fortran Version 13, please ensure that <code>-DINTEL_13</code> is passed to the compiler when building or using pFUnit. In the build process for pFUnit, this is added to the make variables CPPFLAGS and FPPFLAGS.

7.1.4 Segmentation Faults and Odd Link Errors

Q. pFUnit fails to build or now leads to segmentation faults. Did something change?

A. One cause for failure to build or odd runtime segmentation faults is when we change compiler configurations and some object or library files are left over from a previous environment. This might be hard to spot, for example, during compiler upgrades. - Switching from one compiler to another, e.g. from Intel to GNU, is more likely to generate link-time errors if old code is still around. A few items to check follow.

- Execute make distclean or remove objects (or their directories if using CMAKE) associated with previous builds.
- Ensure pFUnit and user applications are compiled using compatible (or the same) compilers.
- Ensure the environment variable PFUNIT is set to the appropriate install directory.

7.2 Tips 23

Finally, it is quite possible that a bug has been uncovered. Please contact the development team or open a bug ticket.

7.2 Tips

7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

7.2.4 Ignoring whitespace differences in assertions on strings.

Several options exist for how to compare strings with assertEqual.

WhitespaceOptions:

- IGNORE_DIFFERENCES ignores whitespace differences (number and value).
- IGNORE_ALL strictly ignores all whitespace (spaces & tabs).
- TRIM_ALL strictly ignores leading and trailing whitespace.
- **KEEP_ALL** keeps all whitespace as significant, even discriminating between tabs and spaces.

Example usages can be seen in tests/Test_AssertBasic.F90 or Examples/-Simple/tests/helloWorld.pf.

Platform Specific Notes

8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

8.3 Intel Fortran Version 13: -DINTEL_13

To make pFUnit work with Intel Fortran Version 13, please ensure that <code>-DINTEL_13</code> is passed to the compiler when building or using pFUnit. In the build process for pFUnit, this is added to the make variables CPPFLAGS and FPPFLAGS.

Acknowledgments

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met Office)., J. Krishna (ANL).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

Known Installations & Versions

master - The current release.

development - The cutting edge of pFUnit development.

pfunit_2.1.0 - A feature freeze prior to a major upgrade of the preprocessor.

TODO

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

32 TODO

The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
 - Configuration testSuites.inc
 - Invocation
 - Command Line Options
 - Preprocessor Input File (.pf)
 - Directives
 - * @Test
 - * @MPITest
 - * @Assert (or Preprocessor Directives)
 - * @Parameters
 - * @TestCase

12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's "tests" subdirectory.

12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' "tests" subdirectories in the - Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
 - @Assert

12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive.

also supports MPI-parallel tests (see @MPITest).

An example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

12.1.4.2 @MPITest

is deprecated as now handles this case.

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI Halo:

```
@Test( npes=[1,2,3])
subroutine testHaloInterior(this)
   use Halo_mod
   use pfunit_mod
   implicit none
   class (MpiTestMethod) :: this

   integer, parameter :: N = 2
   real :: a(N,0:N+1)
   integer :: p

   p = this%getProcessRank()
   a(:,1:N) = p
```

```
a(:,0) = -1
a(:,N+1) = -1

call haloFill(a, this%getMpiCommunicator())

@assertEqual(real(p), a(1,1))
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found,'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- @assertTrue
- · @assertEqualUserDefined
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- @assertIsMemberOf
- · @assertContains
- @assertAny
- @assertAll
- @assertNotAll
- · @assertNone

- · @assertIsPermutationOf
- · @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- · @assertIsFinite
- · @assertAssociated
- · @assertUnAssociated
- · @assertAssociatedWith
- · @assertUnAssociatedWith
- · @assertEquivalent

12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
  integer :: p1, p2
  procedure(runMethod), pointer :: userMethod => null()
contains
  procedure, nopass :: getParameters
```

```
procedure :: getParameterString => getParameterString_
procedure :: runMethod
end type Test_Parameters
```

@Assert Preprocessor Directives

- · @assertEqual
- @assertTrue
- @assertEqualUserDefined
- @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- · @assertContains
- @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- · @assertIsPermutationOf
- · @assertExceptionRaised
- @assertSameShape
- · @assertIsNaN

- · @assertIsFinite
- · @assertAssociated
- @assertUnAssociated
- · @assertAssociatedWith
- · @assertUnAssociatedWith
- · @assertEquivalent

13.1 @Assert Preprocessor Directives

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertEqualUserDefined

A convenience function that allows a user to write

```
@assertEqualUserDefined(a,b)
```

instead of

```
call assertTrue(a==b,...)
```

while a more instructive error message about the arguments and source code position is added by the preprocessor. The user may add an error message as follows.

@assertEqualUserDefined(a,b,message='a and b should be equal here.')

- 13.1.4 @assertFalse
- 13.1.5 @assertLessThan
- 13.1.6 @assertLessThanOrEqual
- 13.1.7 @assertGreaterThan
- 13.1.8 @assertGreaterThanOrEqual
- 13.1.9 @assertIsMemberOf

- 13.1.10 @assertContains
- 13.1.11 @assertAny
- 13.1.12 @assertAll
- 13.1.13 @assertNotAll
- 13.1.14 @assertNone
- 13.1.15 @assertIsPermutationOf
- 13.1.16 @assertExceptionRaised
- 13.1.17 @assertSameShape
- 13.1.18 @assertIsNaN
- 13.1.19 @assertIsFinite
- 13.1.20 @assertAssociated

maps to a call to the logical intrinsic function associated.

```
@assertAssociated(a)
```

becomes

call assertTrue(associated(a))

13.1.21 @assertUnAssociated

This directive is the same as assertAssociated, except that it maps to assertFalse.

13.1.22 @assertAssociatedWith

This directive maps to a call to the logical intrinsic function associated.

```
@assertAssociatedWith(pointer,target)
```

becomes

call assertTrue(associated(pointer,target))

neglecting message and source location information.

13.1.23 @assertUnAssociatedWith

This directive is the same as assertAssociatedWith, except that it maps to assertFalse.

13.1.24 @assertEquivalent

This directive compares two logical values and throws an exception annotated with some useful information. We get a special directive for this one because comparing logicals uses the .eqv. infix operator in standard Fortran. The arguments a and b below may be 1d arrays.

```
@assertEquivalent(a,b)
```

becomes

```
call assertTrue(a.eqv.b)
```

neglecting the specification of message and source location information.

Revision Notes

- 2014-1211 Minor updates for 3.0.2. MLR
- 2014-1110, 2014-1031 Minor edits. MLR
- · 2014-0915 Minor updates for 3.0.1. MLR
- 2014-0404 Updated for release of 3.0. TLC
- 2014-0131, 2014-0205. Updated. MLR
- 2013-1227. First note of OPENMP additions by T. Clune. MLR.
- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
 MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

44 Revision Notes

Data Type Index

15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AbstractTestParameter_mod
AbstractTestResult_mod
pFUnitParser::Action
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtAssertAssociated
pFUnitParser::AtAssertAssociatedWith
pFUnitParser::AtAssertEqualUserDefined
pFUnitParser::AtAssertEquivalent
pFUnitParser::AtAssertUnAssociated
pFUnitParser::AtAssertUnAssociatedWith
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtMpiTest
pFUnitParser::AtTestCase
pFUnitParser::AtTestParameter
add mod
addComplex mod
CodeUtilities::ArrayDescription
Assert_mod
AssertBasic mod
GenerateAssertsOnArrays::AssertRealArrayArgument 60

TestCaseB_mod::B_Parameter
BaseTestRunner_mod
BeforeAfter_mod
BrokenSetUpCase_mod
BrokenTestCase_mod
TestCaseC_mod::C_Parameter
Cases_mod
mods::pre2::dataString
DebugListener_mod
CodeUtilities::declaration
DynamicTestCase_mod
Exception_mod
Expectation_mod
Fixture_mod
FixtureTestCase_mod
CodeUtilities::fortranSubroutineSignature
AbstractTestResult_mod::getErrors
Test_mod::getName
AbstractTestResult_mod::getSuccesses
Halo_mod
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre_:lf::interval
Test_RestrictSphericalCoordinates_mod::LatLonCase
LinearInterpolator_mod
MakeInfinity_mod
MakeNaN_mod
Mock_mod
MockCall mod
MockListener_mod
MockRepository_mod
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
MpiStubs_mod
MpiTestCase_mod
MpiTestCaseB_mod::MpiTestCaseB
MpiTestCaseB_mod
MpiTestMethod_mod
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC mod::newC Parameter
ParallelContext_mod

48

Test_MpiTestCase_mod	124
Test Parameters mod::Test Parameters	
Test_Parameters_mod	
Test RestrictSphericalCoordinates mod::Test RestrictSphericalCoordinates	
Test_RestrictSphericalCoordinates_mod	
Test_RobustRunner_mod	
Test_SimpleTestCase_mod	
Test StringConversionUtilities mod	
Test_TestMethod_mod	
Test TestResult mod	
Test TestSuite mod	
Test UnixProcess mod	
Test XmlPrinter mod	
TestCase mod	
TestCaseA mod::TestCaseA	. 131
TestCaseA mod	. 132
TestCaseB mod::TestCaseB	. 132
TestCaseB mod	. 133
TestCaseC mod::TestCaseC	. 133
TestCaseC_mod	. 134
TestFailure_mod	. 135
mods::pre::pre_lf::TestIfDirective	. 135
mods::pre::interleavedp::TestInterleaved	. 136
TestListener_mod	. 136
TestMethod_mod	. 137
mods::pre::parseArgs::TestParseArgs	. 138
testParser::TestParseLine	. 139
parseBrackets::TestRejoinBracketed	. 142
mods::pre::pre_Repeat::TestRepeatDirective	. 142
TestResult_mod	. 143
TestRunner_mod	. 144
TestSuite_mod	. 145
ThrowFundamentalTypes_mod	
UnixPipeInterfaces_mod	. 146
UnixProcess_mod	
AbstractTestResult_mod::wasSuccessful	
WrapbeforeAfter	. 149
WrapMpiTestCaseB_mod	. 149
Wrapsimple	
WrapTestA_mod	. 150
WrapTestCaseA_mod	
WrapTestCaseB_mod	
WrapTestCaseC_mod	
XmlPrinter_mod	. 151

Data Type Index

16.1 Data Types List

Here are the data types with brief descriptions:

AbstractTestParameter_mod	55
AbstractTestResult_mod	55
pFUnitParser::Action	56
add_mod	57
addComplex_mod	57
CodeUtilities::ArrayDescription	57
Assert_mod	
<briefdescription></briefdescription>	58
AssertBasic_mod	
Provides fundamental assertions over the most basic types, a foun-	
dation for providing test services to end users	58
GenerateAssertsOnArrays::AssertRealArrayArgument	60
pFUnitParser::AtAfter	61
pFUnitParser::AtAssert	61
pFUnitParser::AtAssertAssociated	62
pFUnitParser::AtAssertAssociatedWith	63
pFUnitParser::AtAssertEqualUserDefined	63
pFUnitParser::AtAssertEquivalent	64
pFUnitParser::AtAssertUnAssociated	65
pFUnitParser::AtAssertUnAssociatedWith	66
pFUnitParser::AtBefore	66
pFUnitParser::AtBegin	67
pFUnitParser::AtMpiAssert	67
pFUnitParser::AtMpiTest	68
pFUnitParser::AtSuite	69

pFUnitParser::AtTest	69
pFUnitParser::AtTestCase	70
pFUnitParser::AtTestParameter	71
	71
BaseTestRunner_mod	
<briefdescription></briefdescription>	72
	73
	73
• —	73
	74
	74
	75
	76
DebugListener_mod	
_	77
·	78
DynamicTestCase_mod	. •
•	78
·	79
• –	80
. –	80
	81
	81
	82
	82
•	82
	82
	82
• • –	83
•	83
	84
	84
	85
	85
MakeInfinity mod	00
17	86
MakeNaN_mod	00
	86
Mock mod	00
-	07
the second secon	87
MockCall_mod <pre></pre>	00
· · · · · · · · · · · · · · · · · · ·	88
	89
	89
MockRepository_mod	00
<briefdescription></briefdescription>	90

MockSUT mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
<briefdescription></briefdescription>
MpiStubs_mod
<briefdescription></briefdescription>
MpiTestCase_mod
<briefdescription></briefdescription>
MpiTestCaseB_mod::MpiTestCaseB
MpiTestCaseB_mod
MpiTestMethod_mod
<briefdescription></briefdescription>
MpiTestParameter_mod
pFUnitParser::MyError
Cases_mod::MyParamType
Cases_mod::MyTestCase
TestCaseC_mod::newC_Parameter
ParallelContext_mod
<briefdescription></briefdescription>
ParallelException_mod
<briefdescription></briefdescription>
ParameterizedTestCase_mod
<briefdescription></briefdescription>
Params_mod
<briefdescription></briefdescription>
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
<briefdescription></briefdescription>
pFUnit_mod
<briefdescription></briefdescription>
PrivateException_mod
<briefdescription></briefdescription>
mods::pre::pre2::procDirective
RemoteProxyTestCase_mod
<briefdescription></briefdescription>
mods::pre::pre_Repeat::RepeatDirective
ResultPrinter_mod
<briefdescription></briefdescription>
RobustRunner_mod
<briefdescription></briefdescription>
robustTestSuite_mod
CodeUtilities::routineUnit
SerialContext_mod
<briefdescription></briefdescription>

SimpleTestCase_mod
SourceLocation_mod
<briefdescription></briefdescription>
SphericalCoordinates_mod
TestListener_mod::startTest
StringConversionUtilities_mod
A collection of utilities used throughout the framework
SubsetRunner_mod
<briefdescription></briefdescription>
SurrogateTestCase_mod
<briefdescription></briefdescription>
SUT_mod
Test_Assert_mod
Test_AssertBasic_mod
Test_AssertComplex_mod
Test_AssertInteger_mod
Test_AssertReal_mod
Test_BasicOpenMP_mod
Test_Exception_mod
Test FixtureTestCase mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test_LinearInterpolator_mod
Test_MockCall_mod
Test_MockRepository_mod
Test_mod
<briefdescription></briefdescription>
Test_MpiContext_mod
Test_MpiException_mod
Test_MpiParameterizedTestCase_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates . 120
Test_RestrictSphericalCoordinates_mod
Test RobustRunner mod
Test SimpleTestCase mod
Test StringConversionUtilities mod
Test_TestMethod_mod
Test TestResult mod
Test TestSuite mod
Test UnixProcess mod
Test XmlPrinter mod
Output test messages in junit.xsd-compatible XML
TestA_mod
TestCase_mod
- <briefdescription></briefdescription>

TestCaseA_mod::TestCaseA
TestCaseA_mod
TestCaseB_mod::TestCaseB
TestCaseB_mod
TestCaseC_mod::TestCaseC
TestCaseC_mod
TestFailure_mod
<briefdescription></briefdescription>
mods::pre::pre_lf::TestlfDirective
mods::pre::interleavedp::TestInterleaved
TestListener_mod
<briefdescription></briefdescription>
TestMethod_mod
<briefdescription></briefdescription>
mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
parseBrackets::TestRejoinBracketed
mods::pre::pre_Repeat::TestRepeatDirective
TestResult_mod
<briefdescription> Note: A possible extension point for user-</briefdescription>
specialized TestResults
TestRunner mod
<pre></pre>
<pre></pre>
<pre> <briefdescription></briefdescription></pre>
<briefdescription></briefdescription>
<pre> <briefdescription></briefdescription></pre>
<briefdescription></briefdescription>
<briefdescription></briefdescription>
<briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 145 <briefdescription> 145 ThrowFundamentalTypes_mod 145 <briefdescription> 145 UnixPipeInterfaces_mod 146 <briefdescription> 146 UnixProcess_mod 147</briefdescription></briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod <briefdescription> 145 ThrowFundamentalTypes_mod <briefdescription> 145 UnixPipeInterfaces_mod <briefdescription> 146 UnixProcess_mod <briefdescription> 147 GenerateAssertsOnArrays::VECTOR_NORM 148</briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 3 <briefdescription> 145 ThrowFundamentalTypes_mod 3 <briefdescription> 145 UnixPipeInterfaces_mod 3 <briefdescription> 146 UnixProcess_mod 3 <briefdescription> 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149</briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 145 ThrowFundamentalTypes_mod 145 <briefdescription> 145 UnixPipeInterfaces_mod 146 <briefdescription> 146 UnixProcess_mod 147 <briefdescription> 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapbeforeAfter 149</briefdescription></briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 345 ChriefDescription> 145 ThrowFundamentalTypes_mod 345 UnixPipeInterfaces_mod 345 UnixProcess_mod 346 UnixProcess_mod 347 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapMpiTestCaseB_mod 149</briefdescription>
<briefdescription>144TestSuite_mod145<briefdescription>145ThrowFundamentalTypes_mod145<briefdescription>145UnixPipeInterfaces_mod146<briefdescription>146UnixProcess_mod147<briefdescription>147GenerateAssertsOnArrays::VECTOR_NORM148AbstractTestResult_mod::wasSuccessful149WrapbeforeAfter149WrapMpiTestCaseB_mod149Wrapsimple149</briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 345 ChriefDescription> 145 UnixPipeInterfaces_mod 345 UnixPipeInterfaces_mod 346 UnixProcess_mod 346 UnixProcess_mod 347 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapMpiTestCaseB_mod 149 WrapSimple 149 WrapTestA_mod 150</briefdescription>
<briefdescription> 144 TestSuite_mod 145 ThrowFundamentalTypes_mod 145 UnixPipeInterfaces_mod 145 UnixProcess_mod 146 UnixProcess_mod 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapbeforeAfter 149 Wrapsimple 149 WrapTestA_mod 150 WrapTestCaseA_mod 150</briefdescription>
<briefdescription> 144 TestSuite_mod 145 ThrowFundamentalTypes_mod 145 <briefdescription> 145 UnixPipeInterfaces_mod 146 <briefdescription> 146 UnixProcess_mod 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapMpiTestCaseB_mod 149 WrapSimple 149 WrapTestA_mod 150 WrapTestCaseB_mod 150 WrapTestCaseB_mod 150 WrapTestCaseB_mod 150</briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 145 ThrowFundamentalTypes_mod 145 <briefdescription> 145 UnixPipeInterfaces_mod 146 <briefdescription> 146 UnixProcess_mod 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapDeforeAfter 149 WrapMpiTestCaseB_mod 149 WrapTestA_mod 150 WrapTestCaseB_mod 150 WrapTestCaseC_mod 150 WrapTestCaseC_mod 151</briefdescription></briefdescription></briefdescription>
<briefdescription> 144 TestSuite_mod 145 ThrowFundamentalTypes_mod 145 <briefdescription> 145 UnixPipeInterfaces_mod 146 <briefdescription> 146 UnixProcess_mod 147 GenerateAssertsOnArrays::VECTOR_NORM 148 AbstractTestResult_mod::wasSuccessful 149 WrapMpiTestCaseB_mod 149 WrapSimple 149 WrapTestA_mod 150 WrapTestCaseB_mod 150 WrapTestCaseB_mod 150 WrapTestCaseB_mod 150</briefdescription></briefdescription></briefdescription>

Data Type Documentation

17.1 AbstractTestParameter_mod Module Reference

Data Types

- type AbstractTestParameter
- interface toString

The documentation for this module was generated from the following file:

• AbstractTestParameter.F90

17.2 AbstractTestResult_mod Module Reference

Data Types


- type AbstractTestResult
- interface errorCount
- interface failureCount
- interface getErrors
- · interface getFailures
- interface getName
- interface getRunTime
- interface getSuccesses
- interface runCount
- interface setName
- interface wasSuccessful

The documentation for this module was generated from the following file:

AbstractTestResult.F90

17.3 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



Public Member Functions

· def apply

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.4 add_mod Module Reference

Public Member Functions

- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- · Robust/src/add.F90
- · Simple/src/add.F90

17.5 addComplex_mod Module Reference

Public Member Functions

• complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following file:

· addComplex.F90

17.6 CodeUtilities::ArrayDescription Class Reference

Public Member Functions

- def __init__
- def NAME
- def **DECLARE**
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

Public Attributes

- fType
- kind
- rank

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.7 Assert_mod Module Reference

<BriefDescription>

17.7.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

17.8 AssertBasic_mod Module Reference

Provides fundamental assertions over the most basic types, a foundation for providing test services to end users.

Data Types

- · interface assertEqual
- interface assertExceptionRaised
- · interface assertFail
- · interface assertFalse
- interface assertIsFinite
- · interface assertIsNaN
- interface assertTrue
- · interface fail
- type UnusableArgument

Public Member Functions

- subroutine assertExceptionRaisedMessage (message, location)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- logical function, public nonConformable (shapeA, shapeB)
- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN_double (x, message, location)
- subroutine assertIsFinite_single (x, message, location)
- subroutine **assertIsFinite_double** (x, message, location)

17.8.1 Detailed Description

Provides fundamental assertions over the most basic types, a foundation for providing test services to end users.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

For assertions on strings whitespace may or may not be significant to a test. We now have several options for dealing with whitespace via the optional argument <code>Whitespace</code>. These options are <code>IGNORE_ALL</code>, <code>TRIM_ALL</code>, and <code>KEEP_ALL</code>. - Usage is as follows.

call assertEqual(expectedString, foundString, & & Whitespace=IGNORE_ALL)

WhitespaceOptions:

- TRIM_ALL ignores leading and trailing whitespace.
- KEEP_ALL keeps all whitespace as significant, even discriminating between tabs and spaces.
- IGNORE_ALL ignores all whitespace (spaces & tabs).

Example usages can be seen in tests/Test_AssertBasic.F90 or Examples/-Simple/tests/helloWorld.pf.

The documentation for this module was generated from the following file:

· AssertBasic.F90

17.9 GenerateAssertsOnArrays::AssertRealArrayArgument Class - Reference

Public Member Functions

- def init
- · def updateDescriptions
- def getAssertionName
- def getExpectedDescription
- · def getFoundDescription
- def getTolerance

Public Attributes

- assertionName
- expectedFType
- · expectedPrecision
- expectedRank


- foundFType
- foundPrecision
- foundRank
- tolerance
- · expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

GenerateAssertsOnArrays.py

17.10 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.11 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.12 pFUnitParser::AtAssertAssociated Class Reference

Inheritance diagram for pFUnitParser::AtAssertAssociated:



- def __init__
- def match
- def appendSourceLocation
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.13 pFUnitParser::AtAssertAssociatedWith Class Reference

Inheritance diagram for pFUnitParser::AtAssertAssociatedWith:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.14 pFUnitParser::AtAssertEqualUserDefined Class Reference

Inheritance diagram for pFUnitParser::AtAssertEqualUserDefined:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes

parser

17.14.1 Detailed Description


Convenience directive replacing (a,b) with a call to assertTrue(a==b) and an error message, if none is provided when invoked.

The documentation for this class was generated from the following file:

pFUnitParser.py

17.15 pFUnitParser::AtAssertEquivalent Class Reference

Inheritance diagram for pFUnitParser::AtAssertEquivalent:



Public Member Functions

def __init__

- · def match
- def appendSourceLocation
- def action

Public Attributes

parser

17.15.1 Detailed Description


Convenience directive replacing (a,b) with a call to assertTrue(a.eqv.b) and an error message, if none is provided when invoked.

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.16 pFUnitParser::AtAssertUnAssociated Class Reference

Inheritance diagram for pFUnitParser::AtAssertUnAssociated:



Public Member Functions

- def __init__
- def match
- · def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.17 pFUnitParser::AtAssertUnAssociatedWith Class Reference

Inheritance diagram for pFUnitParser::AtAssertUnAssociatedWith:



Public Member Functions

- def __init__
- def match
- · def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.18 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



- def __init___
- def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.19 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.20 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



Public Member Functions

- def __init__
- def match
- def appendSourceLocation
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.21 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



Public Member Functions

def __init__

Public Attributes


- parser
- keyword

The documentation for this class was generated from the following file:

pFUnitParser.py

17.22 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.23 pFUnitParser::AtTest Class Reference

 $Inheritance\ diagram\ for\ pFUnitParser:: At Test:$



Public Member Functions

- def __init__
- def match
- def action

Public Attributes


- parser
- keyword

The documentation for this class was generated from the following file:

· pFUnitParser.py

17.24 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



- def __init__
- def match
- · def action

Public Attributes


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

17.25 pFUnitParser::AtTestParameter Class Reference

Inheritance diagram for pFUnitParser::AtTestParameter:



Public Member Functions

- def init
- def match
- def action

Public Attributes

· parser

The documentation for this class was generated from the following file:

• pFUnitParser.py

17.26 TestCaseB_mod::B_Parameter Type Reference

- · procedure toString
- procedure toString

Public Attributes

- real **phi**
- · real theta

The documentation for this type was generated from the following files:

- · ParameterizedTestCaseB.F90
- ParameterizedTestCaseB.pf

17.27 BaseTestRunner_mod Module Reference

<BriefDescription>

Data Types

- type BaseTestRunner
- interface run2

17.27.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

17.28 BeforeAfter_mod Module Reference

Public Member Functions

- subroutine first (this)
- subroutine last (this)
- · subroutine firstAndLastCalled (this)
- subroutine succeeds (this)
- subroutine fails (this)

Public Attributes

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

· Examples/MPI Halo/tests/beforeAfter.pf

17.29 BrokenSetUpCase_mod Module Reference

Data Types

• type BrokenSetUpCase

Public Member Functions

• type(BrokenSetUpCase) function, pointer, public newBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

17.30 BrokenTestCase_mod Module Reference

Data Types

• type BrokenTestCase

Public Member Functions

• subroutine tearDown (this)

The documentation for this module was generated from the following file:

• BrokenTestCase.F90

17.31 TestCaseC_mod::C_Parameter Type Reference

Public Member Functions

- · procedure toString
- procedure toString

Public Attributes

- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.32 Cases_mod Module Reference

Data Types

- type MyParamType
- type MyTestCase


- type(MyParamType) function newMyParam (i)
- type(MyTestCase) function newMyTestCase (param)
- subroutine test_odd (this)
- subroutine test_even (this)
- character(:) function, allocatable **toString** (this)

The documentation for this module was generated from the following file:

· Test Cases.pf

17.33 GenerateAssertsOnArrays::constraintASSERT Class Reference

Inheritance diagram for GenerateAssertsOnArrays::constraintASSERT:



Public Member Functions

def __init__
 Dependency injection.

Public Attributes

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

· tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

17.33.1 Constructor & Destructor Documentation

17.33.1.1 def GenerateAssertsOnArrays::constraintASSERT::__init__ (self, assertionName, expectedDescr, foundDescr, tolerance)

Dependency injection.

Will generate "assert"+assertionName assertionName="Equal" This next line actually generates the text of the code.

17.33.2 Member Data Documentation

17.33.2.1 GenerateAssertsOnArrays::constraintASSERT::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

17.33.2.2 GenerateAssertsOnArrays::constraintASSERT::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

· GenerateAssertsOnArrays.py

17.34 mods::pre::pre2::dataString Class Reference

- def __init__
- def insert
- def getLength
- · def getPosition
- · def setPosition
- def getItem
- def getDataAtPosition
- · def getData
- · def getSlice
- def getSliceForward
- · def removeSlice
- def getCurrentData
- def insertAtCurrent
- def append
- · def advanceAndGetNextData
- · def validPosition
- def findToEnd
- · def match
- def matchToEnd

- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

Public Attributes

- data
- · position

The documentation for this class was generated from the following file:

• pre2.py

17.35 DebugListener_mod Module Reference

<BriefDescription>

Data Types

• interface DebugListener

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine **startTest** (this, testName)

17.35.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· DebugListener.F90

17.36 CodeUtilities::declaration Class Reference

Public Member Functions

- def __init___
- · def generate

Public Attributes

- · simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.37 DynamicTestCase_mod Module Reference

<BriefDescription>

Data Types

- · interface delete
- type DynamicTestCase
- · interface testmethod

Public Member Functions

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

17.37.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

17.38 Exception_mod Module Reference

Data Types

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- interface throw

Public Member Functions

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public **catchNext** (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()
- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

17.39 Expectation_mod Module Reference

Data Types

- type Expectation
- · type Predicate
- · type Subject
- interface subVoid

Public Member Functions

- type(Predicate) function, public newPredicate (name)
- type(Subject) function, public **newSubject** (name, sub)
- type(Subject) function, public newSubjectNameOnly (name)
- type(Expectation) function, public newExpectation (subj, pred)

Public Attributes

- type(Predicate), parameter, public wasCalled = Predicate('wasCalled')
- type(Predicate), parameter, public wasNotCalled = Predicate('wasNotCalled')
- type(Predicate), parameter, public wasCalledOnce = Predicate('wasCalledOnce')

The documentation for this module was generated from the following file:

· Expectation.F90

17.40 Fixture_mod Module Reference

Public Member Functions

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following file:

fixtureTests.pf

17.41 FixtureTestCase_mod Module Reference

Data Types

- · interface delete
- type FixtureTestCase

Public Member Functions

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

FixtureTestCase.F90

17.42 CodeUtilities::fortranSubroutineSignature Class Reference

Public Member Functions

- def init
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

Public Attributes

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.43 AbstractTestResult_mod::getErrors Interface Reference

The documentation for this interface was generated from the following file:

· AbstractTestResult.F90

17.44 Test_mod::getName Interface Reference

The documentation for this interface was generated from the following file:

• Test.F90

17.45 AbstractTestResult_mod::getSuccesses Interface Reference

The documentation for this interface was generated from the following file:

AbstractTestResult.F90

17.46 Halo_mod Module Reference

Public Member Functions


• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

Halo.F90

17.47 mods::pre::pre_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre_lf::lfDirective:



Public Member Functions

• def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_lf.py

17.48 CodeUtilities::implementation Class Reference

Public Member Functions

- def __init__
- def generate

Public Attributes

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.49 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.50 mods::pre::pre_lf::interval Class Reference

Public Member Functions

- def __init__
- def getInterval
- def setInterval
- def getStart
- def getEnd

Public Attributes


- start
- end
- interval

The documentation for this class was generated from the following file:

• pre_lf.py

17.51 GenerateAssertsOnArrays::IsWithinTolerance Class Reference

 $Inheritance\ diagram\ for\ Generate Asserts On Arrays:: Is Within Tolerance:$



Public Member Functions

def __init__

Public Attributes

- rank
- · precision
- name

- fType
- declaration
- declarations

The documentation for this class was generated from the following file:

· GenerateAssertsOnArrays.py

17.52 Test_RestrictSphericalCoordinates_mod::LatLonCase Type - Reference

Public Member Functions

· procedure toString

Public Attributes

- real lat
- real lon
- real restrictedLat
- real restrictedLon

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.53 LinearInterpolator_mod Module Reference

Data Types

- interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

• LinearInterpolator.F90

17.54 MakeInfinity_mod Module Reference

<BriefDescription>

Public Member Functions

- real(r32) function, public makeInf_32 ()
- real(r64) function, public makeInf_64 ()

17.54.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MakeInfinity.F90

17.55 MakeNaN_mod Module Reference

<BriefDescription>

- real(r32) function, public makeNaN_32 ()
- real(r64) function, public makeNaN_64 ()

17.55.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MakeNaN.F90

17.56 Mock_mod Module Reference

<BriefDescription>

Data Types

• type Mock

17.56.1 Detailed Description

 $<\!\!\text{BriefDescription}\!\!>$

Author

Tom Clune, NASA/GSFC

Date

12 May 2014

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· Mock.F90

17.57 MockCall_mod Module Reference

```
<BriefDescription>
```

Data Types

· type MockCall

Public Member Functions

• type(MockCall) function, public **newMockCall** (name)

17.57.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

MockCall.F90

17.58 MockListener_mod Module Reference

Data Types

• type MockListener

Public Member Functions


• subroutine startTest (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

17.59 testParser::MockParser Class Reference

Inheritance diagram for testParser::MockParser:



Public Member Functions

- def __init__
- def nextLine
- def reset

Public Attributes

- saveLines
- lines
- outputFile
- outLines
- userTestCase
- userTestMethods
- · currentSelfObjectName

The documentation for this class was generated from the following file:

· testParser.py

17.60 MockRepository_mod Module Reference

<BriefDescription>

Data Types

- interface addExpectationThat_
- type MockRepository
- interface registerMockCallBy_
- · interface subVoid

Public Member Functions

- type(MockRepository) function, pointer, public newMockRepository ()
- subroutine expectCall (this, obj, method)

Public Attributes

- integer, parameter, public MAX_LEN_METHOD_NAME = 32
- integer, parameter, public MAX_LEN_CALL_REGISTRATION = 32
- class(MockRepository), pointer, public **MockRepositoryPointer** = > null()

17.60.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockRepository.F90

17.61 MockSUT_mod Module Reference

Data Types

· type MockSUT

Public Member Functions

- type(MockSUT) function, allocatable, public newMockSUT (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test_MockRepository.F90

17.62 testParser::MockWriter Class Reference

Public Member Functions

- def __init__
- def write

Public Attributes

parser

The documentation for this class was generated from the following file:

testParser.py

17.63 CodeUtilities::module Class Reference

Public Member Functions

- def __init___
- · def generate
- def addDeclaration
- def addImplementation
- def addRoutineUnit
- def addInterfaceBlock
- def getName
- def setFileName
- · def getFileName

Public Attributes

- name
- · declarations
- · implementations
- generation
- fileName

The documentation for this class was generated from the following file:

CodeUtilities.py

17.64 MpiContext_mod Module Reference

<BriefDescription>

Data Types

- type MpiContext
- interface newMpiContext

- subroutine barrier (this)
- integer function getMpiCommunicator (this)

17.64.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiContext.F90

17.65 MpiStubs_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public MPI_Comm_rank (comm, rank, ier)
- subroutine, public MPI_Comm_size (comm, size, ier)
- subroutine, public MPI_Comm_dup (comm, newComm, ier)
- subroutine, public **MPI_Comm_group** (comm, group, ier)
- subroutine, public $MPI_Group_range_incl$ (group, n, ranges, newGroups, ier)
- subroutine, public MPI_Comm_create (comm, group, newComm, ier)

Public Attributes

- integer, parameter, public MPI_COMM_WORLD = -1
- integer, parameter, public MPI_COMM_NULL = -1
- integer, parameter, public MPI_COMM_SUCCESS = 0

17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MpiStubs.F90

17.66 MpiTestCase_mod Module Reference

<BriefDescription>

Data Types

• type MpiTestCase

Public Member Functions

- recursive subroutine runBare (this)
- integer function getMpiCommunicator (this)
- integer function getProcessRank (this)

17.66.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MpiTestCase.F90

17.67 MpiTestCaseB_mod::MpiTestCaseB Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

· integer componentl

The documentation for this type was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

17.68 MpiTestCaseB_mod Module Reference

Data Types

type MpiTestCaseB

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)

- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- MpiTestCaseB.F90
- · MpiTestCaseB.pf

17.69 MpiTestMethod_mod Module Reference

<BriefDescription>

Data Types

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

17.69.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestMethod.F90

17.70 MpiTestParameter_mod Module Reference

Data Types

• type MpiTestParameter

Public Member Functions

 type(MpiTestParameter) function, public newMpiTestParameter (num-ProcessesRequested)

The documentation for this module was generated from the following file:

• MpiTestParameter.F90

17.71 pFUnitParser::MyError Class Reference

Inherits Exception.

Public Member Functions

- def __init__def __str__
- **Public Attributes**

value

The documentation for this class was generated from the following file:

pFUnitParser.py

17.72 Cases_mod::MyParamType Type Reference

Public Member Functions

· procedure toString

Public Attributes

• integer i

The documentation for this type was generated from the following file:

· Test_Cases.pf

17.73 Cases_mod::MyTestCase Type Reference

Public Attributes

• integer i

The documentation for this type was generated from the following file:

· Test_Cases.pf

17.74 TestCaseC_mod::newC_Parameter Interface Reference

Public Member Functions

- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)

The documentation for this interface was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.75 ParallelContext_mod Module Reference

<BriefDescription>

Data Types

- interface allReduceLogical
- interface gatherInteger
- interface gatherLogical
- interface gatherString
- interface getNumProcesses
- type ParallelContext
- interface processRank
- interface sum

17.75.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelContext.F90

17.76 ParallelException_mod Module Reference

<BriefDescription>

Data Types

- interface any Exceptions
- interface getNumExceptions

Public Member Functions

• subroutine, public gather (context)

17.76.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParallelException.F90

17.77 ParameterizedTestCase_mod Module Reference

<BriefDescription>

Data Types

• type ParameterizedTestCase

Public Attributes

• integer, parameter, public MAX_LEN_LABEL = 32

17.77.1 Detailed Description

<BriefDescription>

```
Author
```

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParameterizedTestCase.F90

17.78 Params_mod Module Reference

<BriefDescription>

Public Attributes

- integer, parameter **R32** = selected_real_kind(p=6)
- integer, parameter R64 = selected_real_kind(p=14)
- integer, parameter **C32** = selected_real_kind(p=6)
- integer, parameter **C64** = selected_real_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

17.78.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Params.F90

17.79 pFUnitParser::Parser Class Reference

Inheritance diagram for pFUnitParser::Parser:



Public Member Functions

- def __init__
- def commentLine
- def run
- def isComment
- def nextLine
- def printHeader
- def printTail
- def printWrapUserTestCase
- def printRunMethod
- def printParameterHeader
- · def printMakeSuite
- def addSimpleTestMethod
- def addMpiTestMethod
- def addUserTestMethod
- def printMakeCustomTest
- def makeWrapperModule
- · def final

Public Attributes

- fileName
- inputFile
- outputFile
- · defaultSuiteName
- suiteName
- currentLineNumber
- userModuleName
- userTestCase
- userTestMethods
- wrapModuleName
- · actions

The documentation for this class was generated from the following file:

pFUnitParser.py

17.80 Test_Parameters_mod::peCase Type Reference

Public Member Functions

· procedure toString

Public Attributes

- integer p1
- integer p2

The documentation for this type was generated from the following file:

· parameterizedTests.pf

17.81 pFUnit Module Reference

<BriefDescription>

Public Member Functions

• integer function run ()

17.81.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

17.82 pFUnit_mod Module Reference

<BriefDescription>

Public Member Functions

- subroutine, public initialize (useMpi)
- subroutine, public finalize (successful)

17.82.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

17.83 PrivateException_mod Module Reference

<BriefDescription>

Data Types

- type Exception
- type ExceptionList
- interface newException

Public Member Functions

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

Public Attributes

- integer, parameter, public **MAXLEN_MESSAGE** = 80*15
- integer, parameter, public **MAXLEN_FILE_NAME** = 80
- character(len=*), parameter, public NULL_MESSAGE = "

17.83.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Exception.F90

17.84 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



Public Member Functions

- def __init__
- def getLength
- def match
- def evaluate
- def getNewPosition
- def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- def finditerTokenToPosition
- def makeTokenErrorMessage

Public Attributes

- name
- newPosition
- · tokens
- TokenREs

17.84.1 Member Function/Subroutine Documentation

```
17.84.1.1 def mods::pre::pre2::procDirective::addTokenRE( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = ''')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

· pre2.py

17.85 RemoteProxyTestCase_mod Module Reference

<BriefDescription>

Data Types

• interface RemoteProxyTestCase

17.85.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

17.86 mods::pre::pre_Repeat::RepeatDirective Class Reference

Inheritance diagram for mods::pre::pre_Repeat::RepeatDirective:



Public Member Functions

· def evaluate

Public Attributes

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre_Repeat.py

17.87 ResultPrinter_mod Module Reference

<BriefDescription>

Data Types

· type ResultPrinter

Public Member Functions

- type(ResultPrinter) function, public **newResultPrinter** (unit)
- subroutine addError (this, testName, exceptions)
- subroutine startTest (this, testName)
- subroutine **print** (this, result)
- · subroutine printHeader (this, runTime)
- subroutine printFooter (this, result)

17.87.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

17.88 RobustRunner_mod Module Reference

<BriefDescription>

Data Types

- interface RobustRunner
- type TestCaseMonitor

Public Member Functions

- subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine **startTest** (this, testName)
- subroutine addFailure (this, testName, exceptions)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

17.88.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· RobustRunner.F90

17.89 robustTestSuite_mod Module Reference

Public Member Functions


- type(TestSuite) function, public suite ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

17.90 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



Public Member Functions

- def __init__
- def setName
- · def getName
- def setDeclaration
- def addDeclaration
- def setImplementation
- · def getDeclaration
- · def getDeclarations
- · def getImplementation
- def clearDeclarations

Public Attributes

- name
- declaration
- · declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

17.91 SerialContext_mod Module Reference

<BriefDescription>

Data Types

· type SerialContext

Public Member Functions

 $\bullet \ \ \mathsf{type}(\mathsf{SerialContext}) \ \mathsf{function}, \ \ \mathsf{public} \ \boldsymbol{\mathsf{newSerialContext}} \ ()$

Public Attributes

 type(SerialContext), parameter, public THE_SERIAL_CONTEXT = Serial-Context()

17.91.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

17.92 SimpleTestCase_mod Module Reference

Data Types

- · interface method
- type SimpleTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete_ (this)

The documentation for this module was generated from the following file:

• SimpleTestCase.F90

17.93 SourceLocation_mod Module Reference

<BriefDescription>

Data Types

· type SourceLocation

Public Attributes

- character(len=MAXLEN_FILE_NAME), parameter, public UNKNOWN_FILE_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN_LINE_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN_SOURCE_LOCATION = SourceLocation()

17.93.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

17.94 SphericalCoordinates_mod Module Reference

Data Types

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

· SphericalCoordinates.F90

17.95 TestListener_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

17.96 StringConversionUtilities_mod Module Reference

A collection of utilities used throughout the framework.

Data Types

- · interface toString
- type WhitespaceOptions

Public Member Functions

- character(len=len_trim(a)+1+len_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)
- logical function, public whitespacep (c)
- character(len=:) function, allocatable, public trimAll (s)
- character(len=:) function, allocatable, public trimTrailingWhitespace (s)

Public Attributes

- integer, parameter, public MAXLEN_STRING = 80
- type(WhitespaceOptions), parameter, public IGNORE_ALL = Whitespace-Options(IGNORE_ALL_)
- type(WhitespaceOptions), parameter, public TRIM_ALL = WhitespaceOptions(-TRIM_ALL_)
- type(WhitespaceOptions), parameter, public KEEP_ALL = WhitespaceOptions(-KEEP_ALL_)
- type(WhitespaceOptions), parameter, public IGNORE_DIFFERENCES = -WhitespaceOptions(IGNORE_DIFFERENCES_)

17.96.1 Detailed Description

A collection of utilities used throughout the framework.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

17.97 SubsetRunner_mod Module Reference

<BriefDescription>

Data Types

• interface SubsetRunner

Public Member Functions

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

17.97.1 Detailed Description

 $<\!\!\text{BriefDescription}\!\!>$

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• SubsetRunner.F90

17.98 SurrogateTestCase_mod Module Reference

<BriefDescription>

Data Types

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

17.98.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

17.99 SUT_mod Module Reference

Data Types

· type SUT

The documentation for this module was generated from the following file:

• Test MockRepository.F90

17.100 Test_Assert_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test Assert.F90

17.101 Test_AssertBasic_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()
- subroutine testAssertExceptionRaised ()
- subroutine testAssertFail ()

The documentation for this module was generated from the following file:

· Test AssertBasic.F90

17.102 Test_AssertComplex_mod Module Reference

Public Member Functions

• type(TestSuite) function, public **suite** ()

- subroutine testEquals_C_complexScalar ()
- subroutine testEquals_C_0D1D ()
- subroutine testEquals_C_1D_nonConformable1 ()
- subroutine testEquals C 2D SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent1
- subroutine testEquals_C_MultiD_SingleElementDifferent2
- subroutine testEquals_C_MultiD_SingleElementDifferent3
- subroutine testEquals_C_MultiD_SingleElementDifferent4
- subroutine testEquals C MultiD SingleElementDifferent5
- subroutine testEquals C MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff2 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff3 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff5 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff6 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff7 ()
- subroutine testEquals_C_MultiDMultiPrec_SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals_C_MultiDWithTolerance ()
- subroutine testEquals_C_MultiDWithTolerance1 ()
- subroutine testEquals_C_MultiDWithTolerance64 ()
- subroutine testEquals C MultiDWithTolerance64 1 ()
- subroutine testEquals C MultiDWithTolerance64 2 ()
- subroutine testEquals C MultiDSourceLocation ()
- subroutine testEquals_4DPComplex_DifferenceReport ()
- subroutine testEquals ComplexMultiD SingleElementNE1
- subroutine testEquals_ComplexMultiD_SingleElementRE1
- subroutine testEquals_ComplexMultiD_SingleEltVarious1
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

Test AssertComplex.F90

17.103 Test_AssertInteger_mod Module Reference

Public Member Functions

• type(TestSuite) function, public suite ()

• subroutine testAssertEqual equal ()

The documentation for this module was generated from the following file:

Test AssertInteger.F90

Test AssertReal mod Module Reference 17.104

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testEquals 0D1D ()
- subroutine testEquals 1D nonConformable1 ()
- subroutine testEquals 2D SingleElementDifferent ()
- subroutine testEquals MultiD SingleElementDifferent ()
- subroutine testEquals MultiD SingleElementDifferent1
- subroutine testEquals MultiD SingleElementDifferent2
- subroutine testEquals_MultiD_SingleElementDifferent3
- subroutine testEquals MultiD SingleElementDifferent4
- subroutine testEquals MultiD SingleElementDifferent5
- subroutine testEquals MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 ()
- subroutine testEquals_MultiDMultiPrec_SingleEltDiff5 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff6 () subroutine testEquals MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals VectorWithToleranceNoMsq ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals_MultiDWithTolerance1 ()
- subroutine testEquals MultiDWithTolerance64 ()
- subroutine testEquals MultiDWithTolerance64 1 ()
- subroutine testEquals MultiDWithTolerance64_2 ()
- subroutine testEquals MultiDSourceLocation ()
- subroutine testEquals_ScalarAndLocation ()
- subroutine testEquals ScalarInfinity equal ()
- subroutine testEquals_ScalarInfinity_unequal_A ()

- subroutine testEquals_ScalarInfinity_unequal_B ()
- subroutine testEquals ScalarInfinity unequal C ()
- subroutine testEquals_MultiD_SingleElementGT1
- subroutine testEquals_MultiD_SingleElementGT2
- subroutine testEquals_MultiD_SingleEltVarious1
- subroutine testEquals_MultiD_SingleEltVarious2
- subroutine assertCatch (string, location)

The documentation for this module was generated from the following file:

· Test AssertReal.F90

17.105 Test_BasicOpenMP_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithOpenMP ()
- subroutine testSerializeExceptions ()

The documentation for this module was generated from the following file:

• Test_BasicOpenMP.F90

17.106 Test_Exception_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumExceptions ()
- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

The documentation for this module was generated from the following file:

Test_Exception.F90

17.107 Test FixtureTestCase mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test FixtureTestCase.F90

17.108 Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown

Public Attributes

• type(LinearInterpolator) interpolator

The documentation for this type was generated from the following file:

· Test LinearInterpolator.pf

17.109 Test_LinearInterpolator_mod Module Reference

Data Types

• type Test_LinearInterpolator

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

· Test LinearInterpolator.pf

17.110 Test_MockCall_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

Test MockCall.F90

17.111 Test_MockRepository_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testNoAction ()

The documentation for this module was generated from the following file:

· Test MockRepository.F90

17.112 Test_mod Module Reference

<BriefDescription>

Data Types

- interface countTestCases
- interface getName
- interface run
- type Test

Public Attributes

• integer, parameter, public MAX_LENGTH_NAME = 64

17.112.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

17.113 Test_MpiContext_mod Module Reference

Public Member Functions

- type(TestSuite) function, public **suite** ()
- subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

• Test_MpiContext.F90

17.114 Test_MpiException_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine test_anyExceptions_none (this)
- subroutine test_getNumExceptions (this)
- subroutine test_gather (this)

The documentation for this module was generated from the following file:

• Test MpiException.F90

17.115 Test_MpiParameterizedTestCase_mod Module Reference

Data Types

- type ExtendedTestParameter
- · interface method
- type Test MpiTestCase

Public Member Functions

- type(TestSuite) function, public suite ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, testParameter)
- subroutine testToString (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

· Test MpiParameterizedTestCase.F90

17.116 Test_MpiTestCase_mod Module Reference

Data Types

- · interface method
- type Test MpiTestCase

Public Member Functions

- type(TestSuite) function, public **suite** ()
- type(Test_MpiTestCase) function, public newTest_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- · recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

• Test_MpiTestCase.F90

17.117 Test_Parameters_mod::Test_Parameters Type Reference

Public Attributes

- integer p1
- integer p2

The documentation for this type was generated from the following file:

parameterizedTests.pf

17.118 Test_Parameters_mod Module Reference

Data Types

- type peCase
- type Test Parameters

Public Member Functions

- type(Test_Parameters) function **newTest** (testParameter)
- type(peCase) function newPeCase (p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()

- character(:) function, allocatable toString (this)
- subroutine testParamBroken (this)

The documentation for this module was generated from the following file:

· parameterizedTests.pf

17.119 Test_RestrictSphericalCoordinates_mod::Test_Restrict-SphericalCoordinates Type Reference

Public Attributes

- · real lat
- real lon
- · real restrictedLat
- · real restrictedLon
- type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted

The documentation for this type was generated from the following file:

· Test_RestrictedSphericalCoordinates.pf

17.120 Test_RestrictSphericalCoordinates_mod Module Reference

Data Types

- type LatLonCase
- type Test_RestrictSphericalCoordinates

Public Member Functions

- type(Test RestrictSphericalCoordinates) function **newTest** (testParameter)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- character(:) function, allocatable toString (this)

The documentation for this module was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

17.121 Test RobustRunner mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

• Test RobustRunner.F90

17.122 Test_SimpleTestCase_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()
- subroutine testRunMethodShouldFail ()

The documentation for this module was generated from the following file:

• Test SimpleTestCase.F90

17.123 Test_StringConversionUtilities_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test_StringConversionUtilities.F90

17.124 Test TestMethod mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

• Test_TestMethod.F90

17.125 Test_TestResult_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

• Test_TestResult.F90

17.126 Test_TestSuite_mod Module Reference

Data Types

• type Verbose

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()

- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

The documentation for this module was generated from the following file:

• Test_TestSuite.F90

17.127 Test_UnixProcess_mod Module Reference

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testIsActive ()

The documentation for this module was generated from the following file:

• Test_UnixProcess.F90

17.128 Test_XmlPrinter_mod Module Reference

Output test messages in junit.xsd-compatible XML.

Public Member Functions

- type(TestSuite) function, public suite ()
- subroutine testValidXml ()
- subroutine compareXMLFileToExpectation (xmlFile)

17.128.1 Detailed Description

Output test messages in junit.xsd-compatible XML.

Author

Halvor Lund

Date

2014 July

Note

Set up a test failure and feed it to an XML-based printer so that we can test its output. Use command line call (via "system") to try to find "xmllint," and if available, use it to validate the output against junit.xsd. Either way, check the output against a hard-coded expected result (a regression test).

The documentation for this module was generated from the following file:

• Test XmlPrinter.F90

17.129 TestA mod Module Reference

Public Member Functions

- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)
- subroutine testMethodA ()
- subroutine testMethodB ()
- subroutine testMethodC (this)

The documentation for this module was generated from the following files:

- TestA.F90
- · TestA.pf

17.130 TestCase mod Module Reference

<BriefDescription>

Data Types

- type ConcreteSurrogate
- type TestCase
- type TestCaseReference

Public Member Functions

- recursive subroutine runBare (this)
- recursive subroutine runBare_surrogate (this)

17.130.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

TestCase.F90

17.131 TestCaseA_mod::TestCaseA Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

· integer componentl

The documentation for this type was generated from the following files:

- TestCaseA.F90
- · TestCaseA.pf

17.132 TestCaseA mod Module Reference

Data Types

type TestCaseA

Public Member Functions

- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)

The documentation for this module was generated from the following files:

- · TestCaseA.F90
- · TestCaseA.pf

17.133 TestCaseB_mod::TestCaseB Type Reference

Public Member Functions

- procedure setUp
- procedure tearDown
- procedure setUp
- · procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- real phi
- · real theta

The documentation for this type was generated from the following files:

- · ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.134 TestCaseB_mod Module Reference

Data Types

- type B_Parameter
- type TestCaseB

Public Member Functions

- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)
- type(TestCaseB) function newTestCaseB (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- · character(:) function, allocatable toString (this)

The documentation for this module was generated from the following files:

- ParameterizedTestCaseB.F90
- · ParameterizedTestCaseB.pf

17.135 TestCaseC_mod::TestCaseC Type Reference

- procedure setUp
- procedure tearDown
- procedure setUp
- procedure tearDown

Public Attributes

- integer, dimension(:), allocatable table
- real phi
- · real theta

The documentation for this type was generated from the following files:

- MpiParameterizedTestCaseC.F90
- MpiParameterizedTestCaseC.pf

17.136 TestCaseC_mod Module Reference

Data Types

- type C_Parameter
- interface newC_Parameter
- type TestCaseC

- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C_Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable toString (this)
- type(TestCaseC) function newTestCaseC (testParameter)
- subroutine setUp (this)
- subroutine tearDown (this)
- subroutine testA (this)
- subroutine testB (this)
- subroutine testC (this)
- type(C_Parameter) function newC_Parameter_phiTheta (npes, phi, theta)
- elemental function newC_Parameter_case (i)
- type(C Parameter) function, allocatable paramGenerator ()
- character(:) function, allocatable **toString** (this)

The documentation for this module was generated from the following files:

- MpiParameterizedTestCaseC.F90
- · MpiParameterizedTestCaseC.pf

17.137 TestFailure_mod Module Reference

<BriefDescription>

Data Types

· type TestFailure

17.137.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestFailure.F90

17.138 mods::pre::pre_lf::TestIfDirective Class Reference

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse

- def testIFTestTrue1
- def testIFTestTrue2
- def testIFClearTokens
- def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

pre_lf.py

17.139 mods::pre::interleavedp::TestInterleaved Class Reference

Public Member Functions

- · def test InOrder
- · def test_NumberMismatch
- def test_OrderMismatch1
- · def test OrderMismatch2
- def test_OrderMismatch3
- def test ElseMid1
- def test_ElseMid2
- · def test ElseMid3
- def test_ElseMid4
- def test_ElseMid5
- def test_ElseMid6
- def test_ElseMid7
- def test_ElseMid8def test_ElseMid9
- def test ElseMid10

The documentation for this class was generated from the following file:

· interleavedp.py

17.140 TestListener_mod Module Reference

<BriefDescription>

Data Types

- · interface addFailure
- interface endRun
- interface endTest
- type ListenerPointer
- interface startTest
- type TestListener

Public Member Functions

- subroutine addError (this, testName, exceptions)
- subroutine setDebug (this)

17.140.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestListener.F90

17.141 TestMethod_mod Module Reference

<BriefDescription>

Data Types

- interface empty
- interface newTestMethod
- type TestMethod

17.141.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

17.142 mods::pre::parseArgs::TestParseArgs Class Reference

Public Member Functions

- · def test ParseArgs OneArgWithBrackets1
- def test_ParseArgs_OneArgWithBrackets2
- def test ParseArgs OneArgWithBrackets3
- · def test ParseArgs OneArgWithBrackets4
- def test_ParseArgs_OneArgWithBrackets5
- def test_ParseArgs_OneArgWithBrackets6
- def test_ParseArgs_OneArgWithBrackets7
- def test_ParseArgs_oneArg
- · def test ParseArgs twoArgs1
- def test_ParseArgs_twoArgs2
- · def test_ParseArgs_oneArgArray1
- def test_ParseArgs_TwoArgArray
- def test_ParseArgs_ThreeArgs

The documentation for this class was generated from the following file:

· parseArgs.py

17.143 testParser::TestParseLine Class Reference

Public Member Functions

- def testCppSetLineAndFile
- def testGetSubroutineName
- · def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtTestNoParens
- def testAtTestFail
- def testAtTestSkipComment
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- def testParseArgsFirstRest
- def testParseArgsFirstSecondRest
- def testMatchAtAssertAssociated
- def testMatchAtAssertAssociatedWith
- def testMatchAtAssertUnAssociated
- · def testMatchAtAssertUnAssociatedWith
- def testMatchAtAssertEqualUserDefined
- · def testMatchAtAssertEqualUserDefinedWithMessage
- def testMatchAtAssertEquivalent
- def testMatchAtAssertOther
- def testMatchAtMpiAssert
- · def testMatchAtBefore
- def testMatchAtAfter
- · def testMatchAtSuite

17.143.1 Member Function/Subroutine Documentation

17.143.1.1 def testParser::TestParseLine::testAtMpiTest (self)

Check that a line starting with ' \emptyset mpitest' is detected as an annotation and that optional parameters are collected.

17.143.1.2 def testParser::TestParseLine::testAtTest(self)

Check that a line starting with '@test' is detected as an annotation.

17.143.1.3 def testParser::TestParseLine::testAtTestFail(self)

Check that useful error is sent if next line is not properly formatted.

17.143.1.4 def testParser::TestParseLine::testAtTestNoParens (self)

Check that test procedure with no parens is accepted.

17.143.1.5 def testParser::TestParseLine::testAtTestSkipComment (self)

Ignore comment lines between @test and subroutine foo().

17.143.1.6 def testParser::TestParseLine::testMatchAtAfter(self)

Check that a line starting with '@after*' ...

17.143.1.7 def testParser::TestParseLine::testMatchAtAssertAssociated (self)

Check that a line starting with '@assertAssociated' is detected as an annotation.

17.143.1.8 def testParser::TestParseLine::testMatchAtAssertAssociatedWith (self)

Check that a line starting with '@assertAssociatedWith' is detected as an annotation. atAssertAssociatedWith(a,b) implies a points to b.

17.143.1.9 def testParser::TestParseLine::testMatchAtAssertEqual (self)

Check that a line starting with '@assertEqual' is detected as an annotation.

17.143.1.10 def testParser::TestParseLine::testMatchAtAssertEqualUserDefined (self)

Check that a line starting with '@assertEqualUserDefined' is detected as an annotation. at AssertEqualUserDefined(a,b) implies a points to b.

17.143.1.11 def testParser::TestParseLine::testMatchAtAssertEqualUserDefined-WithMessage (self)

Check that a line starting with '@assertEqualUserDefined' is detected as an annotation. atAssertEqualUserDefined(a,b) implies a points to b.

17.143.1.12 def testParser::TestParseLine::testMatchAtAssertEquivalent (self)

Check that a line starting with '@assertEquivalent' is detected as an annotation. atAssertEquivalent(a,b) implies a points to b.

17.143.1.13 def testParser::TestParseLine::testMatchAtAssertOther(self)

Check that a line starting with '@assert*' is detected as an annotation.

17.143.1.14 def testParser::TestParseLine::testMatchAtAssertUnAssociated (self)

Check that a line starting with '@assertUnAssociated' is detected as an annotation.

17.143.1.15 def testParser::TestParseLine::testMatchAtAssertUnAssociatedWith (self)

Check that a line starting with '@assertUnAssociatedWith' is detected as an annotation. at AssertUnAssociatedWith(a,b) implies a points to b.

17.143.1.16 def testParser::TestParseLine::testMatchAtBefore (self)

Check that a line starting with '@before*' \dots

17.143.1.17 def testParser::TestParseLine::testMatchAtMpiAssert (self)

Check that a line starting with '@mpiAssert*' is detected as an annotation.

17.143.1.18 def testParser::TestParseLine::testMatchAtSuite (self)

Check that a line starting with '@suite changes the suite name ...

17.143.1.19 def testParser::TestParseLine::testMatchAtTestCase (self)

Check that a line starting with '@testcase' is detected as an annotation.

17.143.1.20 def testParser::TestParseLine::testParseArgsFirstRest (self)

Test that the first-rest argument parsing is adequate.

17.143.1.21 def testParser::TestParseLine::testParseArgsFirstSecondRest (self)

Test that the first-second-rest argument parsing is adequate.

The documentation for this class was generated from the following file:

testParser.py

17.144 parseBrackets::TestRejoinBracketed Class Reference

Public Member Functions

- · def testRejoinBracketed
- · def testParseBrackets

The documentation for this class was generated from the following file:

parseBrackets.py

17.145 mods::pre::pre_Repeat::TestRepeatDirective Class Reference

Public Member Functions

def test_copyBlock1

- def test_copyBlock2
- · def test_copyBlock2Vars
- def test_copyBlock2VarsMulti
- def test_copyBlock2VarsMultiWithStrings
- def test_copyNaiveRecursion
- def test_copyNaiveRecursion1
- def test_copyFunction1

The documentation for this class was generated from the following file:

pre_Repeat.py

17.146 TestResult_mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Data Types

• type TestResult

Public Member Functions

- type(TestResult) function, public newTestResult (name)
- subroutine addError (this, aTest, exceptions)
- subroutine addSuccess (this, aTest)
- integer function failureCount (this)
- subroutine addListener (this, listener)

17.146.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestResult.F90

17.147 TestRunner_mod Module Reference

```
<BriefDescription>
```

Data Types

- interface newTestRunner
- type TestRunner

Public Member Functions

- type(TestResult) function run (this, aTest, context)
- subroutine startTest (this, testName)
- subroutine addFailure (this, testName, exceptions)

17.147.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestRunner.F90

17.148 TestSuite_mod Module Reference

<BriefDescription>

Data Types

- interface newTestSuite
- type TestReference
- type TestSuite

Public Member Functions

• recursive subroutine addTest (this, aTest)

17.148.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestSuite.F90

17.149 ThrowFundamentalTypes_mod Module Reference

<BriefDescription>

Data Types

- interface throwDifferentValues
- interface throwDifferentValuesWithLocation

Public Member Functions

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN_SHAPE) function, public locationFormat (iLocation)

17.149.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

17.150 UnixPipeInterfaces_mod Module Reference

<BriefDescription>

Data Types

- · interface fgets
- · interface free
- · interface getdelim
- · interface getline
- · interface pclose
- · interface popen

Public Attributes

• integer(C_INT), parameter, public **CLOSE_FAILED** = -1

17.150.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixPipeInterfaces.F90

17.151 UnixProcess mod Module Reference

<BriefDescription>

Data Types

• interface UnixProcess

Public Member Functions

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

17.151.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixProcess.F90

17.152 GenerateAssertsOnArrays::VECTOR_NORM Class Reference

Inheritance diagram for GenerateAssertsOnArrays::VECTOR_NORM:



Public Member Functions

• def __init__

Public Attributes

- rank
- fType
- · precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

• GenerateAssertsOnArrays.py

17.153 AbstractTestResult_mod::wasSuccessful Interface Reference

The documentation for this interface was generated from the following file:

AbstractTestResult.F90

17.154 WrapbeforeAfter Module Reference

The documentation for this module was generated from the following file:

• beforeAfter.F90

17.155 WrapMpiTestCaseB_mod Module Reference

Data Types

- · interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, npesRequested)

The documentation for this module was generated from the following file:

· MpiTestCaseB.F90

17.156 Wrapsimple Module Reference

The documentation for this module was generated from the following file:

• simple.F90

17.157 WrapTestA_mod Module Reference

The documentation for this module was generated from the following file:

TestA.F90

17.158 WrapTestCaseA_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod)

The documentation for this module was generated from the following file:

TestCaseA.F90

17.159 WrapTestCaseB_mod Module Reference

Data Types

- interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter)

The documentation for this module was generated from the following file:

· ParameterizedTestCaseB.F90

17.160 WrapTestCaseC_mod Module Reference

Data Types

- · interface userTestMethod
- type WrapUserTestCase

Public Member Functions

- subroutine runMethod (this)
- type(WrapUserTestCase) function, public makeCustomTest (methodName, testMethod, testParameter, npesRequested)

The documentation for this module was generated from the following file:

MpiParameterizedTestCaseC.F90

17.161 XmlPrinter_mod Module Reference

<BriefDescription>

Data Types

type XmlPrinter

- type(XmlPrinter) function, public **newXmlPrinter** (unit)
- subroutine addError (this, testName, exceptions)
- subroutine startTest (this, testName)
- subroutine print (this, result)
- subroutine printHeader (this, result)
- subroutine **printFailure** (this, label, aFailedTest)
- subroutine **printExceptions** (this, label, testName, exceptions)
- subroutine printFailure1 (this, label, aFailedTest)
- subroutine printFailures (this, label, failures)
- subroutine **printTestName** (this, testName)
- subroutine **printSuccess** (this, aSuccessTest)
- subroutine printSuccesses (this, successes)
- subroutine printFooter (this, result)
- character(:) function, allocatable cleanXml (string_in)

17.161.1 Detailed Description

<BriefDescription>

Author

Halvor Lund, SINTEF Energy Research

Date

30 Jan 2014

Note

<A note here.> Need to improve the handling of nested quotes.

The documentation for this module was generated from the following file:

· XmlPrinter.F90