### pFUnit

Generated by Doxygen 1.7.6

Tue Dec 24 2013 22:09:18

# **Contents**

pFUnit 2 - Documentation - Version 0.0 (2013-1224-1 MLR)				
	1.1	Overview	1	
	1.2	Contents	1	
	1.3	See Also	2	
	1.4	Copyright	2	
2	Obta	ining pFUnit	3	
3	Inst	llation	5	
	3.1	Installing pFUnit	5	
	3.2	Prerequisites	5	
	3.3	Obtaining pFUnit	6	
	3.4	Manifest - What's in the directory?	6	
	3.5	Configuration	7	
	3.6	Building pFUnit	7	
		3.6.1 Building pFUnit for testing serial codes (Non-MPI)	8	
		3.6.2 Building pFUnit for testing parallel codes (MPI)	8	
		3.6.3 Cleaning	8	
		3.6.4 Documentation	9	
	3.7	Installation	9	
		3.7.1 Installation - Serial	9	
		3.7.2 Installation - MPI	0	
		2.7.2 Installation DEEALILT DIDECTORY	. ^	

	00175176
1	CONTENTS
1	OOMILIAIS

4	Usaç	ge	11
	4.1	Usage	11
		4.1.1 Usage - Configuration	11
		4.1.2 Usage - Hello World	11
		4.1.3 Usage - Preprocessor	12
5	Deve	elopment	13
6	Feed	lback & Support	15
	6.1	Feedback	15
	6.2	Support	15
7	FAQ	and Tips	17
	7.1	FAQ	17
		7.1.1 Zero Tests Run	17
		7.1.2 Some Tests Are Not Running	17
	7.2	Tips	18
		7.2.1 Environment Modules	18
		7.2.2 Compile Time Errors	18
		7.2.3 Intermediate files used by pFUnit	18
8	Platf	orm Specific Notes	19
	8.1	Mac OSX	19
	8.2	Windows/CYGWIN	19
9	Ackr	nowledgments	21
10	Knov	wn Installations & Versions	23
11	TOD	0	25
12		The state of the s	27
	12.1	2 - Property	27
		<b>3</b>	28
		12.1.2 Invocation	28

CONTENTS iii

		12.1.3	Preproces	sor Input Fil	e (.pf)		 	 	 		. 28
		12.1.4	Directives				 	 	 		. 29
			12.1.4.1	@Test			 	 	 		. 29
			12.1.4.2	@MPITest			 	 	 		. 29
			12.1.4.3	@Assert .			 	 	 		. 30
			12.1.4.4	@Paramete	rs		 	 	 		. 31
			12.1.4.5	@TestCase			 	 	 		. 31
13	@ <b>A</b> s	sert Pre	enrocesso	r Directives							33
				essor Directiv			 		 		
		13.1.1	•	qual							
		13.1.2		· ·ue							
		13.1.3	@assertF	alse			 	 	 		. 34
		13.1.4	@assertL	essThan .			 	 	 		. 34
		13.1.5	@assertL	essThanOrE	qual .		 	 	 		. 34
		13.1.6	@assertG	reaterThan			 	 	 		. 34
		13.1.7	@assertG	reaterThanC	OrEqua	١.	 	 	 		. 34
		13.1.8	@assertIs	MemberOf			 	 	 		. 34
		13.1.9	@assertC	ontains			 	 	 		. 34
		13.1.10	@assertA	ny			 	 	 		. 34
		13.1.11	@assertA	II			 	 	 		. 34
		13.1.12	@assertN	otAll			 	 	 		. 34
		13.1.13	@assertN	one			 	 	 		. 34
		13.1.14	@assertIs	Permutation	Of		 	 	 		. 34
		13.1.15	@assertE	xceptionRai	sed		 	 	 		. 34
		13.1.16	@assertS	ameShape			 	 	 		. 34
		13.1.17	@assertIs	NaN			 	 	 		. 34
		13.1.18	@assertIs	Finite			 	 	 		. 34
14	Revi	sion No	tes								35
		2.2.1 140									55
15	Data	Type In	dex								37

iv CONTENTS

	15.1	Class Hierarchy	37
16	Data	Type Index	41
	16.1	Data Types List	41
17	Data	Type Documentation	45
	17.1	pFUnitParser::Action Class Reference	45
	17.2	add_mod Module Reference	46
	17.3	addComplex_mod Module Reference	47
	17.4	CodeUtilities::ArrayDescription Class Reference	47
	17.5	Assert_mod Module Reference	48
		17.5.1 Detailed Description	48
	17.6	AssertBasic_mod Module Reference	48
		17.6.1 Detailed Description	49
	17.7	AssertInteger_mod Module Reference	49
		17.7.1 Detailed Description	50
	17.8	GenerateRealArrayNewSignature::AssertRealArrayArgument Class - Reference	50
	17.9	pFUnitParser::AtAfter Class Reference	51
	17.10	DpFUnitParser::AtAssert Class Reference	52
	17.1	pFUnitParser::AtBefore Class Reference	52
	17.12	2pFUnitParser::AtBegin Class Reference	53
	17.13	BpFUnitParser::AtMpiAssert Class Reference	54
	17.14	4pFUnitParser::AtMpiTest Class Reference	54
	17.15	ppFUnitParser::AtParameters Class Reference	55
	17.16	6pFUnitParser::AtSuite Class Reference	56
	17.17	7pFUnitParser::AtTest Class Reference	56
	17.18	BpFUnitParser::AtTestCase Class Reference	57
	17.19	BBaseTestRunner_mod Module Reference	58
		17.19.1 Detailed Description	58
	17.20	DBeforeAfter_mod Module Reference	59
	17.2	BrokenSetUpCase_mod Module Reference	59

CONTENTS v

17.22BrokenTestCase_mod Module Reference	. 59
17.23GenerateRealArrayNewSignature::constraintASSERTEQUAL Class Reference	. 60
17.23.1 Constructor & Destructor Documentation	. 60
17.23.1.1init	. 61
17.23.2 Member Data Documentation	. 61
17.23.2.1 name1	. 61
17.23.2.2 tolerance	. 61
17.24mods::pre::pre2::dataString Class Reference	. 61
17.25DebugListener_mod Module Reference	. 62
17.25.1 Detailed Description	. 62
17.26CodeUtilities::declaration Class Reference	. 63
17.27DynamicTestCase_mod Module Reference	. 63
17.27.1 Detailed Description	. 64
17.28Exception_mod Module Reference	. 64
17.29Fixture_mod Module Reference	. 65
17.30FixtureTestCase_mod Module Reference	. 65
17.31CodeUtilities::fortranSubroutineSignature Class Reference	. 66
17.32Halo_mod Module Reference	. 66
17.33mods::pre::pre_lf::lfDirective Class Reference	. 66
17.34CodeUtilities::implementation Class Reference	. 67
17.35CodeUtilities::interfaceBlock Class Reference	. 67
17.36mods::pre::pre_lf::interval Class Reference	. 68
17.37GenerateRealArrayNewSignature::IsWithinTolerance Class Reference	. 68
17.38Test_RestrictSphericalCoordinates_mod::LatLonCase Type Reference	. 69
17.39LinearInterpolator_mod Module Reference	. 69
17.40MakeInfinity_mod Module Reference	. 69
17.40.1 Detailed Description	. 70
17.41 MakeNaN_mod Module Reference	. 70
17.41.1 Detailed Description	. 70
17.42MockCall_mod Module Reference	. 71

vi CONTENTS

17.42.1 Detailed Description	71
17.43MockListener_mod Module Reference	72
17.44testParser::MockParser Class Reference	72
17.45MockRepository_mod Module Reference	72
17.45.1 Detailed Description	73
17.46MockSUT_mod Module Reference	73
17.47testParser::MockWriter Class Reference	74
17.48CodeUtilities::module Class Reference	74
17.49MpiContext_mod Module Reference	75
17.49.1 Detailed Description	75
17.50MpiStubs_mod Module Reference	75
17.50.1 Detailed Description	76
17.51MpiTestCase_mod Module Reference	76
17.51.1 Detailed Description	77
17.52MpiTestMethod_mod Module Reference	77
17.52.1 Detailed Description	77
17.53ParallelContext_mod Module Reference	78
17.53.1 Detailed Description	78
17.54ParallelException_mod Module Reference	79
17.54.1 Detailed Description	79
17.55ParameterizedTestCase_mod Module Reference	80
17.55.1 Detailed Description	80
17.56Params_mod Module Reference	80
17.56.1 Detailed Description	81
17.57pFUnitParser::Parser Class Reference	81
17.58Test_Parameters_mod::peCase Type Reference	82
17.59pFUnit Module Reference	82
17.59.1 Detailed Description	83
17.60pFUnit_mod Module Reference	83
17.60.1 Detailed Description	83
17.61 Private Exception_mod Module Reference	84

CONTENTS vii

17.61.1 Detailed Description	
17.62mods::pre2::procDirective Class Reference	85
17.62.1 Member Function/Subroutine Documentation	86
17.62.1.1 addTokenRE	86
17.63RemoteProxyTestCase_mod Module Reference	86
17.63.1 Detailed Description	86
17.64mods::pre::pre_Repeat::RepeatDirective Class Reference	87
17.65ResultPrinter_mod Module Reference	87
17.65.1 Detailed Description	88
17.66RobustRunner_mod Module Reference	88
17.66.1 Detailed Description	89
17.67robustTestSuite_mod Module Reference	89
17.68CodeUtilities::routineUnit Class Reference	89
17.69SerialContext_mod Module Reference	90
17.69.1 Detailed Description	91
17.70SimpleTestCase_mod Module Reference	91
17.71 SourceLocation_mod Module Reference	92
17.71.1 Detailed Description	92
17.72SphericalCoordinates_mod Module Reference	92
17.73TestListener_mod::startTest Interface Reference	93
17.74StringConversionUtilities_mod Module Reference	93
17.74.1 Detailed Description	93
17.75SubsetRunner_mod Module Reference	94
17.75.1 Detailed Description	94
17.76SurrogateTestCase_mod Module Reference	95
17.76.1 Detailed Description	95
17.77SUT_mod Module Reference	95
17.78Test_Assert_mod Module Reference	96
17.79Test_AssertBasic_mod Module Reference	96
17.80Test_AssertComplex_mod Module Reference	96
17.81Test_AssertInteger_mod Module Reference	97

viii CONTENTS

17.82Test_AssertReal_mod Module Reference
17.83Test_Exception_mod Module Reference
17.84Test_FixtureTestCase_mod Module Reference
17.85Test_LinearInterpolator_mod::Test_LinearInterpolator Type Reference . 99
17.86Test_LinearInterpolator_mod Module Reference
17.87Test_MockCall_mod Module Reference
17.88Test_MockRepository_mod Module Reference
17.89Test_mod Module Reference
17.89.1 Detailed Description
17.90Test_MpiContext_mod Module Reference
17.91Test_MpiException_mod Module Reference
17.92Test_MpiTestCase_mod Module Reference
17.93Test_Parameters_mod::Test_Parameters Interface Reference 103
17.94Test_Parameters_mod Module Reference
17.95Test_RestrictSphericalCoordinates_mod::Test_RestrictSpherical- Coordinates Interface Reference
17.96Test_RestrictSphericalCoordinates_mod Module Reference 104
17.97Test_RobustRunner_mod Module Reference
17.98Test_SimpleTestCase_mod Module Reference
17.99Test_StringConversionUtilities_mod Module Reference
17.10 <b>0</b> est_TestMethod_mod Module Reference
17.10 <b>T</b> est_TestResult_mod Module Reference
17.10 <b>2</b> est_TestSuite_mod Module Reference
17.103est_UnixProcess_mod Module Reference
17.104estCase_mod Module Reference
17.104. Detailed Description
17.10 <b>5</b> estFailure_mod Module Reference
17.105. Detailed Description
17.10@nods::pre::pre_lf::TestlfDirective Class Reference
17.10 mods::pre::interleavedp::TestInterleaved Class Reference 109
17.108estListener_mod Module Reference

CONTENTS ix

17.108. Detailed Description
17.109estMethod_mod Module Reference
17.109. Detailed Description
17.11@nods::pre::parseArgs::TestParseArgs Class Reference
17.11 lestParser::TestParseLine Class Reference
17.111. Member Function/Subroutine Documentation
17.111.1.1testAtMpiTest
17.111.1.2testAtTest
17.111.1.3testMatchAtAfter
17.111.1.4testMatchAtAssertEqual
17.111.1.5testMatchAtAssertOther
17.111.1. @testMatchAtBefore
17.111.1.7testMatchAtMpiAssert
17.111.1.&testMatchAtSuite
17.111.1.9testMatchAtTestCase
17.112hods::pre::pre_Repeat::TestRepeatDirective Class Reference
17.113estResult_mod Module Reference
17.113. Detailed Description
17.11 <b>T</b> estRunner_mod Module Reference
17.114. Detailed Description
17.115estSuite_mod Module Reference
17.115. Detailed Description
17.1167hrowFundamentalTypes_mod Module Reference
17.116. Detailed Description
17.11 ☑nixPipeInterfaces_mod Module Reference
17.117. Detailed Description
17.118JnixProcess_mod Module Reference
17.118. Detailed Description
17.11 Senerate Real Array New Signature:: VECTOR_NORM Class Reference . 119

# pFUnit 2 - Documentation - Version 0.0 (2013-1224-1 MLR)

Quick link to the code!

#### 1.1 Overview

pFUnit is a unit testing framework enabling JUnit-like testing of serial and MPI-parallel software written in Fortran. It makes use of modern Fortran programming techniques, including object oriented programming, offering a convenient, lightweight mechanism for Fortran developers to create and run software tests that specify the desired behavior for a given piece of code. The framework was originally created by developers from NASA and NGC TASC. The project is hosted at sourceforge/projects/pfunit.

If you are using pFUnit, please leave a note/topic at Applications of pFUnit, or send a note to Tom Clune, Ph.D., Chief, Software Systems Support Office Code 610.3, NASA Goddard Space Flight Center.

Please refer revisions and comments about the documentation to Mike Rilee, Ph.-D., Rilee Systems Technologies.

#### 1.2 Contents

- Installation
  - Obtaining pFUnit
- Usage

- Development
- Feedback & Support
- FAQ and Tips
- Platform Specific Notes
- Acknowledgments
- Known Installations & Versions
- TODO
- The Preprocessor pFUnitParser
- Revision Notes

#### 1.3 See Also

- sourceforge/projects/pfunit
- NASA Modeling Guru
- JUnit.org

### 1.4 Copyright

Copyright 2005,2013 United States Government as represented by the Administrator of the National Aeronautics and Space Administration. All Rights Reserved.

# **Obtaining pFUnit**

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

### Installation

### 3.1 Installing pFUnit

Comentatry for the page.

- Prerequisites
- · Obtaining pFUnit
- · Manifest What's in the directory?
- Configuration
- Building pFUnit
  - Building pFUnit for testing serial codes (Non-MPI)
  - Building pFUnit for testing parallel codes (MPI)
  - Cleaning
  - Documentation
- Installation

### 3.2 Prerequisites

The development work for pFUnit has mostly been carried out on a mixture of systems, including high-end computers, Apple Mac OSX, and linux-based systems. A preliminary Windows/CYGWIN port has been contributed by a user. Full use of the system depends on the following being available.

6 Installation

- Fortran 2003+ (Tested with Intel 13.1+, NAG 5.3, GCC 4.8.1., IBM's XLF)
- The Message Passing Interface (MPI)
- · GNU Make
- Python

Doxygen is used to generate documentation.

The system routinely undergoes regression testing with GNU, Intel, and NAG fortran compilers and OpenMPI.

### 3.3 Obtaining pFUnit

The best way to obtain pFUnit is to clone pFUnit from the git repository from SourceForge as follows.

```
# Read Only Access
git clone git://git.code.sf.net/p/pfunit/code pFUnit
```

This will create the directory pFUnit in the current working directory.

You may also visit the project page at SourceForge and download the source tarfile "pFUnit.tar.gz" there.

http://sourceforge.net/projects/pfunit/orhttp://sourceforge.net/projects/pfunit/files/latest/download

Extracting this tarfile via a command like

'\$ tar zxf ./pFUnit.tar.gz'

will place the pFUnit files into the current working directory.

For other ways to acquire the code visit

https://sourceforge.net/p/pfunit/code/ci/master/tree/ or contact the pFUnit team.

### 3.4 Manifest - What's in the directory?

In the top level of the pFUnit distribution you will see the following files.

COPYRIGHT - Contains information pertaining to the use and distribution of pFUnit.

Examples - Contains examples of how to use pFUnit once it is installed.

3.5 Configuration 7

GNUmakefile - The top level makefile for building and installing pFUnit.

bin - Executables used to construct and perform unit tests.

include - Files to be included into makefiles or source, including use code.

source - Source code and scripts of the pFUnit library and framework.

tests - Source code for unit testing pFUnit itself.

tools - Tools used to help develop, build, and install pFUnit.

### 3.5 Configuration

Little needs to be done to configure pFUnit for the build, however there are several environment variables on which the package depends.

'F90\_VENDOR' - is set to include the correct makefile in /include, i.e. GNU, Intel, NAG, or PGI. Case insensitive file systems may cause some confusion from time-to-time.

'F90' - is set to the Fortran compiler being used: e.g. ifort for Intel, gfortran for GNU.

'COMPILER' - is set according to 'F90\_VENDOR' and is automatically set in the top level makefile.

For MPI-based unit testing, your setup may require the following as well.

'MPIF90'

```
$ export MPIF90=mpif90
```

As a convenience for working with multiple MPI configurations, you may also set the following.

'MPIRUN'

```
$ export MPIRUN=/some.path/mpirun
```

'DOXYGEN' - To generate documentation, set DOXYGEN to the desired executable. N-OTE: Doxygen Version 1.8.5 does not respect CamelCase names from Fortran source code by currently converting all to lowercase. It does this to get HTML links correct for references in the source code that also do not respect the CamelCase convention. The Fortran standard specifies case insensitivity. Doxygen 1.7.x seems to better respect CamelCase.

\$ export DOXYGEN=/opt/local/share/doxygen/doxygen-1.7.6/bin/doxygen

### 3.6 Building pFUnit

8 Installation

#### 3.6.1 Building pFUnit for testing serial codes (Non-MPI)

1. Change to the directory into which pFUnit has been placed. 2. Set the environment variables (in bash):

```
$ export F90=gfortran-mp-4.8
$ export F90_VENDOR=GNU
```

3. To build pFUnit for unit testing of serial codes, execute make. The unit tests for pFUnit itself will run automatically.

```
$ make tests
```

3.1 Occasionally on the first run through, one will get a spurious (runtime) error, for example in the unix process component.

```
Re-execute "make tests" to check again.
```

4. At this point the pFUnit object library is in the source directory, along with a large number of Fortran module files.

#### 3.6.2 Building pFUnit for testing parallel codes (MPI)

To build pFUnit for unit testing MPI-based codes, be sure that the environment is properly set up for the MPI implementation you are using. Depending on your local environment, you may need execute the build within a batch or other job queing system, e.g. an interactive batch job under PBS. The steps for building pFUnit start out the same as for the serial case above, but add MPI=YES to the environment to switch on MPI support. The MPI-based unit tests for pFUnit itself will run automatically. Again, occasionally a spurious (runtime) error may appear on the first execution.

3. Execute make as follows.

```
$ make tests MPI=YES
```

4. At this point an MPI-enabled pFUnit object library is in the source directory, along with a large number of Fortran module files.

Also, one may get some harmless "no symbols" warnings when the pFUnit library is constructed.

#### 3.6.3 Cleaning

To clean the pFUnit build directory for the space or to rebuild there are two options.

1. Make clean to remove object files and other intermediate products.

```
$ make clean
```

3.7 Installation 9

2. Make distclean to remove libraries and other more final products.

```
$ make distclean
```

3. Some directories support a 'make src\_clean' to remove intermediate products in subdirectories.

#### 3.6.4 Documentation

A start at documentation for pFUnit is in the documentation directory. Doxygen is our primary documentation tool. To make the documentation, which will be generated in the documentation directory, please invoke the following.

```
$ make documentation
```

Or to make a reference manual.

```
$ make documentation/pFUnit2-ReferenceManual.pdf
```

To select a specific version of Doxygen, please set the DOXYGEN environment variable as in Configuration. You may wish to do this if your code uses CamelCase names as current versions of Doxygen (1.8.5) do not respect this convention for Fortran.

#### 3.7 Installation

#### 3.7.1 Installation - Serial

To install pFUnit for regular use, set INSTALL\_DIR to the location in which to place pF-Unit. This can be done on the make command line. For example, after compiling pFUnit for serial use (MPI absent or MPI=NO), please try.

```
$ # In the top of the pFUnit build directory.
$ make install INSTALL_DIR=/opt/pfunit/pfunit-serial
```

Note: you may need special priveleges to install in some locations, e.g. via sudo.

To test the installation set PFUNIT to INSTALL\_DIR, then change the working directory to Examples in pFUnit distribution and execute "buildIt," which will run a number of examples. These include some expected failures.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-serial
$ pushd Examples
$ ./buildIt
```

10 Installation

#### 3.7.2 Installation - MPI

For installing an MPI-enabled pFUnit library, change to the top of the distribution and execute make with MPI=YES. You may need to "make distclean" first. After compilation and pFUnit passes its self-tests, then installation proceeds as for the serial case above.

```
$ make install INSTALL_DIR=/opt/pfunit/pfunit-parallel
```

To test, set PFUNIT and go into Examples/MPI\_Halo directory.

```
$ # In the top pFUnit build directory...
$ export PFUNIT=/opt/pfunit/pfunit-parallel
$ # The variable MPIF90 must be set to the appropriate build script.
$ export MPIF90=mpif90
$ cd Examples/MPI_Halo/Semi-Automatic
$ make
```

This will compile and run a set of parallel examples that includes intentional failures.

#### 3.7.3 Installation - DEFAULT DIRECTORY

If INSTALL\_DIR is not set, "make install" will attempt to install pFUnit into the top build directory. This will create directories such as lib and mod in the top level of the build directory and will overwrite the include/base.mk with include/base-install.mk. If this is not desired, then "make develop" will put back the original base.mk, which is the file to be used for development and building pFUnit. In general, we recommend installing to a directory that is not also the build directory.

# **Usage**

- Usage Configuration
- Usage Hello World
- Usage Preprocessor

### 4.1 Usage

#### 4.1.1 Usage - Configuration

For regular use, after installation, the same compiler/MPI development configuration that was used to build pFUnit should be used. Once the environment variables and paths associated with the environment are set, to configure pFUnit, please set the following.

'PFUNIT' - set to the directory into which pFUnit was installed.

'F90\_VENDOR' - set to Intel, GNU, NAG, or PGI accordingly.

#### 4.1.2 Usage - Hello World

For an example of a simple usage of pFUnit, see Examples/Simple/Semi--Automatic/tests.

The simplest way to write a test is to write a preprocessor input file (extension ".pf"), which is a Fortran free format file with preprocessor directives added. An example from "helloWorld.pf" follows.

```
! from helloWorld.pf
@test
subroutine testHelloWorld()
```

12 Usage

```
use pfunit_mod
implicit none
@assertEqual("Hello World!","Hello World!")
end subroutine testHelloWorld
```

One then instructs the preprocessor to construct a suite to execute these tests via the "testSuites.inc" file as follows.

```
! from testSuites.inc
ADD_TEST_SUITE(helloWorld_suite)
```

At this point, one can invoke the preprocessor to generate a Fortran file that when compiled and linked with pFUnit will execute the tests. For more information please see The Preprocessor - pFUnitParser or try out the examples in Example/Simple.

### 4.1.3 Usage - Preprocessor

Please see The Preprocessor - pFUnitParser.

# **Development**

Generally pFUnit development is performed in the build directory structure. Care should be taken to make clean or distclean in between configuration changes. As stated in - Installation, it is best to set INSTALL\_DIR and "make install" pFUnit to another directory that can be placed in a user's paths.

14 Development

# Feedback & Support

- Feedback
- Support

#### 6.1 Feedback

Feedback is welcome, please use the facilities at sourceforge/projects/pfunit to share your views.

Open a ticket for bugs, features, and patch recommendations.

If you use pFUnit, please let us know by leaving a note in our Applications of pFUnit forum, or email Tom Clune, Ph.D., NASA Goddard Space Flight Center. - Letting us know about your application helps us seek support for pFUnit's continued development and improvement.

### 6.2 Support

Please open a ticket for bugs, features, and patch recommendations. For longer term needs or considerations, please visit our discussion forums or contact — Tom Clune, Ph.D., NASA Goddard Space Flight Center.

You may also find some help at FAQ and Tips.

pFUnit supports the software development of several weather and climate simulations efforts. We constantly seek to improve and correct pFUnit for our users' benefit, granting priority to the needs of our major users. Please share with us information about your application on our Applications of pFUnit forum.

# **FAQ** and Tips

- FAQ
  - Zero Tests Run
  - Some Tests Are Not Running
- Tips
  - Environment Modules
  - Compile Time Errors
  - Intermediate files used by pFUnit

#### 7.1 FAQ

#### 7.1.1 Zero Tests Run

Symptom: The system under test compiles and runs fine, but reports zero tests run. Solutions:

- There is no testSuites.inc file. Please add a testSuites.inc that lists the suites to add via ADD\_TEST\_SUITE (the\_suite\_to\_add), one to a line.
- There is no <code>-DUSE\_MPI</code> passed to the compiler during the build. Please add to the compiler invokation. Please see Some Tests Are Not Running.

#### 7.1.2 Some Tests Are Not Running

Symptom: The system under test compiles and runs fine, but reports that some tests don't run.

18 FAQ and Tips

#### Solutions:

There is no -DUSE\_MPI passed to the compiler during the build. Please add as
in the following example.

```
% $PFUNIT/bin/pFUnitParser.py test_pio.pf test_pio.F90
% mpif90 -DUSE_MPI $PFUNIT/include/driver.F90 \
%     -I$PFUNIT/mod -L$PFUNIT/lib -lpfunit test_pio.F90
% mpirun -np 8 ./a.out
.
Time:     0.004 seconds
OK
```

### **7.2** Tips

#### 7.2.1 Environment Modules

Though not strictly required, the Environment Modules package can be a convenient way to package, maintain, and switch between environments. This can be particularly important for pFUnit, which must be built using the same tool suite being used for development, e.g. compilers, linkers, etc. [To do: A sample pFUnit modulefile is provided in the OTHER directory.]

#### 7.2.2 Compile Time Errors

Compile time errors like '"include [...]include/.mk" not found' likely signify that you are not executing make in the top level directory during a build. Alternatively, during regular usage after installation, PFUNIT has not been set.

During building, if you wish to compile in a subdirectory within the pFUnit heriarchy, please try setting the COMPILER environment variable on the make command line. For example:

```
$ make all COMPILER=Intel
```

#### 7.2.3 Intermediate files used by pFUnit

If you wish to see the intermediate files, use the target .PRECIOUS in the makefile to keep them from being deleted. For example:

```
# In GNUmakefile
.PRECIOUS: %_cpp.F90
```

# **Platform Specific Notes**

#### 8.1 Mac OSX

The MacPorts package management system is a convenient way to install and maintain many packages, including gcc which includes gfortran.

### 8.2 Windows/CYGWIN

User contributed code for Windows/CYGWIN has been added, but is currently not tested and supported by the pFUnit team. At this writing, 2013-1031, serial Examples and MPI are not known to be supported. Please contact us if you wish to either contribute or otherwise discuss this port.

# **Acknowledgments**

Thanks to the follwing for their review and comments: B. Van Aartsen, T. Clune.

Windows/CYGWIN contributions from E. Lezar.

Other acknowledgments: S.P. Santos (NCAR), M. Hambley (UK Met).

The design of pFUnit is strongly influenced by JUnit.

Initial pFUnit 2 documentation by Michael Rilee (Rilee Systems Technologies).

# **Known Installations & Versions**

TBD

# **TODO**

- Make other directory.
- Make Environment Modules example in other directory.
- Other build systems, e.g. CMake.

26 TODO

# The Preprocessor - pFUnitParser

Overview of Preprocessor (pFUnitParser.py)

- Using The Preprocessor
  - Configuration testSuites.inc
  - Invocation
  - Preprocessor Input File (.pf)
  - Directives
    - \* @Test
    - \* @MPITest
    - \* @Assert (or Preprocessor Directives)
    - \* @Parameters
    - \* @TestCase

# 12.1 Using The Preprocessor

How to write tests using the ".pf" files. We expect this to be the main way people write pFUnit-based tests. Please see the Examples directory for a wide range of examples. The .pf files themselves are generally to be found in an example's semi-automatic/tests subdirectory.

#### 12.1.1 Configuration - testSuites.inc

The include file "testSuites.inc" tells the preprocessor to generate code for TestSuites listed therein. The suite names are based on the TestCases provided in the preprocessor input file or the name of the preprocessor input file (.pf) itself. For example, if no module is defined in a .pf file, i.e. the preprocessor will define the module, one can set up a "testSuites.inc" as follows.

```
! To load "exampleTestsNoModule.pf".
ADD_TEST_SUITE(exampleTestsNoModule_suite)
```

For a .pf file that contains a module associated with a test suite the syntax is as follows.

```
! To load "exampleTests.pf" implementing the module exampleTests_mod. ADD_TEST_SUITE(exampleTests_mod_suite)
```

#### 12.1.2 Invocation

To run the preprocessor on on a preprocessor input file "exampleTests.pf", invoke:

```
$ ${PFUNIT}/bin/pFUnitParser.py exampleTests.pf exampleTests.F90
```

A convenient GNUmakefile rule is as follows.

```
%.F90: %.pf
$(PFUNIT)/bin/pFUnitParser.py $< $@</pre>
```

#### 12.1.3 Preprocessor Input File (.pf)

The preprocessor input file is a Fortran free format file that contains subroutines, including those implementing the suite of tests, or a module with the tests, TestCases, and support for parameters. The preprocessor reads and parses this file producing a fortran file implementing the tests, automating some boilerplate code. Embedded "@" directives inform the preprocessor about information needed to generate the test suite. If the .pf file does not implement a module providing a test suite, the preprocessor will use the name of .pf file referred to by "testSuites.inc". Currently only one test suite per .pf file is allowed, a limitation of the current implementation of the parser.

Many example .pf files may be found in the examples' semi-automatic/tests subdirectories in the Examples directory.

Below we present the most commonly used directives first, but in a .pf file using all of these capabilities, the most common order is as follows.

- @Parameters
- @TestCase
- @Test or @MPITest
  - @Assert

#### 12.1.4 Directives

Preprocessor "@" directives, which in keeping with Fortran style are not case sensitive, instruct the preprocessor how to interpret parts of the code relevant to the generation of the test suite. The most important directives follow.

#### 12.1.4.1 @Test

This directive is used to indicate a test routine to the preprocessor, which then includes it in the test suite. There may be multiple tests in the .pf file, each annotated by the directive. For example, from Examples/Fixture:

```
@Test
    subroutine testBracketInterior(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual([3,4], this%interpolator%getBracket(at=4.))
    end subroutine testBracketInterior

@Test
    subroutine testInterpolateAtNode(this)
        class (Test_LinearInterpolator), intent(inout) :: this
        @assertEqual(2., this%interpolator%interpolate(at=3.))
    end subroutine testInterpolateAtNode
```

#### 12.1.4.2 @MPITest

This directive indicates an MPI parallel test to the preprocessor, which then includes it in an MPI enabled test suite. The directive takes a single argument, the requested number of MPI processes to run. The syntax, exemplified by one of the tests from Examples/MPI\_Halo:

```
@mpiTest( npes=[1,2,3])
subroutine testHaloInterior(this)
    use Halo_mod
    use pfunit_mod
    implicit none
    class (MpiTestMethod) :: this

    integer, parameter :: N = 2
    real :: a(N,0:N+1)
    integer :: p

    p = this%getProcessRank()
    a(:,1:N) = p
    a(:,0) = -1
    a(:,N+1) = -1

call haloFill(a, this%getMpiCommunicator())
@assertEqual(real(p), a(1,1))
```

```
@assertEqual(real(p), a(2,1))
@assertEqual(real(p), a(1,2))
@assertEqual(real(p), a(2,2))
end subroutine testHaloInterior
```

#### 12.1.4.3 @Assert

The directives are expanded into calls to similarly named pFUnit library routines. The syntax for the directives follows the pattern for below.

```
@assertEqual(expected, found, 'An identifying or explanatory message.')
```

The preprocessor will automatically add information about source location (file & line number) to the call emitted to the test suite code. It also adds the check for exceptions.

For more information about directives, please refer to the following.

- · @assertEqual
- · @assertTrue
- · @assertFalse
- · @assertLessThan
- · @assertLessThanOrEqual
- @assertGreaterThan
- · @assertGreaterThanOrEqual
- · @assertIsMemberOf
- · @assertContains
- @assertAny
- @assertAll
- @assertNotAll
- · @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- · @assertSameShape
- · @assertIsNaN
- · @assertIsFinite

#### 12.1.4.4 @Parameters

The directive indicates the declaration of the parameterized type used to generate the iteration over the multiple parameter values. It also identifies the names of the parameters to be iterated over. The preprocessor extracts type information from the declaration of the parameter type collection that immediately follows the directive. This directive will set up the iteration. To define the parameter values per iteration the <code>getParameters</code> method of the abstract ParameterizedTest must be implemented. For example:

```
@Parameters = [p1,p2]
type, extends(AbstractTestParameter) :: exampleCase
  integer :: i
  real :: x
end type exampleCase
```

#### 12.1.4.5 @TestCase

This directive identifies to the preprocessor the TestCase declaration. The type declared at this point extends TestCase (or its extension), which includes setting methods such as the following: setUp, tearDown, runMethod, userMethod. For the extension MPITestCase, as with ParameterizedTestCase, you have the option (requirement if parameters are used) to set getParameters and getParameterString. For example:

```
@TestCase
type, extends(MPITestCase) :: Test_Parameters
   integer :: p1, p2
   procedure(runMethod), pointer :: userMethod => null()
contains
   procedure, nopass :: getParameters
   procedure :: getParameterString => getParameterString_
   procedure :: runMethod
end type Test_Parameters
```

# **@Assert Preprocessor Directives**

- @assertEqual
- @assertTrue
- · @assertFalse
- @assertLessThan
- @assertLessThanOrEqual
- @assertGreaterThan
- @assertGreaterThanOrEqual
- @assertIsMemberOf
- @assertContains
- · @assertAny
- @assertAll
- @assertNotAll
- @assertNone
- @assertIsPermutationOf
- @assertExceptionRaised
- @assertSameShape
- @assertIsNaN
- @assertIsFinite

I3.1 @Assert	Preprocessor	<b>Directives</b>
--------------	--------------	-------------------

- 13.1.1 @assertEqual
- 13.1.2 @assertTrue
- 13.1.3 @assertFalse
- 13.1.4 @assertLessThan
- 13.1.5 @assertLessThanOrEqual
- 13.1.6 @assertGreaterThan
- 13.1.7 @assertGreaterThanOrEqual
- 13.1.8 @assertIsMemberOf
- 13.1.9 @assertContains
- 13.1.10 @assertAny
- 13.1.11 @assertAll
- 13.1.12 @assertNotAll
- 13.1.13 @assertNone
- 13.1.14 @assertIsPermutationOf
- 13.1.15 @assertExceptionRaised
- 13.1.16 @assertSameShape
- 13.1.17 @assertIsNaN
- 13.1.18 @assertIsFinite

# **Revision Notes**

- 2013-1212. Initial draft of Doxygen version. MLR
- 2013-1107. Minor edits. MLR
- 2013-1031. Added user contributed code for Windows/CYGWIN & IBM's XLF.
   MLR
- 2013-0830-1359. Minor corrections and added MPIF90 to 6.2. MLR
- 2013-0806-1345. Corrected git reference. Was using old URL. MLR
- 2013-0805. Initial draft. MLR

36 Revision Notes

# **Data Type Index**

# 15.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

pFUnitParser::Action
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtParameters
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
add mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
AssertBasic mod
AssertInteger_mod
GenerateRealArrayNewSignature::AssertRealArrayArgument 50
BaseTestRunner_mod
BeforeAfter_mod
BrokenSetUpCase_mod
BrokenTestCase_mod
mods::pre::pre2::dataString 61
DebugListener_mod
CodeUtilities::declaration

Dynamic lestCase_mod
Exception_mod
Fixture_mod
FixtureTestCase_mod
CodeUtilities::fortranSubroutineSignature
Halo_mod
CodeUtilities::implementation
CodeUtilities::interfaceBlock
mods::pre_:lf::interval
Test_RestrictSphericalCoordinates_mod::LatLonCase 69
LinearInterpolator_mod
MakeInfinity_mod
MakeNaN_mod
$MockCall\_mod \ldots \ldots$
MockListener_mod
testParser::MockParser
MockRepository_mod
MockSUT_mod
testParser::MockWriter
CodeUtilities::module
MpiContext_mod
MpiStubs_mod
MpiTestCase_mod
MpiTestMethod_mod
ParallelContext_mod
ParallelException_mod
ParameterizedTestCase_mod
Params_mod
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
pFUnit_mod
PrivateException_mod
mods::pre2::procDirective
mods::pre::pre_lf::lfDirective
mods::pre::pre_Repeat::RepeatDirective
RemoteProxyTestCase_mod
ResultPrinter_mod
RobustRunner_mod
robustTestSuite mod
CodeUtilities::routineUnit
GenerateRealArrayNewSignature::constraintASSERTEQUAL 60
GenerateRealArrayNewSignature::IsWithinTolerance
GenerateRealArrayNewSignature::VECTOR_NORM
SerialContext_mod

SimpleTestCase_mod	91
SourceLocation_mod	92
SphericalCoordinates_mod	92
TestListener_mod::startTest	
StringConversionUtilities_mod	
SubsetRunner_mod	
SurrogateTestCase_mod	
SUT_mod	
Test Assert mod	
Test AssertBasic mod	
Test AssertComplex mod	
Test_AssertInteger_mod	
Test AssertReal mod	
Test_Exception_mod	
Test FixtureTestCase mod	
Test_LinearInterpolator_mod::Test_LinearInterpolator	
Test_LinearInterpolator_mod	
Test MockCall mod	
Test_MockRepository_mod	
Test mod	
Test MpiContext mod	
Test_MpiException_mod	
Test_MpiTestCase_mod	
Test_Parameters_mod::Test_Parameters	
Test Parameters mod	
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates	
Test RestrictSphericalCoordinates mod	
Test RobustRunner mod	
Test_SimpleTestCase_mod	
Test_StringConversionUtilities_mod	
Test_TestMethod_mod	
Test_TestResult_mod	
Test TestSuite mod	
	106
Test_UnixProcess_mod	106 107
Test_UnixProcess_mod	106 107 107
Test_UnixProcess_mod	. 106 . 107 . 107 . 108
Test_UnixProcess_mod	. 106 . 107 . 107 . 108 . 109
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_If::TestIfDirective mods::pre::interleavedp::TestInterleaved	. 106 . 107 . 107 . 108 . 109 . 109
Test_UnixProcess_mod	. 106 . 107 . 107 . 108 . 109 . 109
Test_UnixProcess_mod	106 107 107 108 109 109 110
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod TestMethod_mod mods::pre::parseArgs::TestParseArgs	106 107 107 108 109 109 110 111
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod TestMethod_mod mods::pre::parseArgs::TestParseArgs testParser::TestParseLine	106 107 107 108 109 109 110 111 111
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod TestMethod_mod mods::pre::parseArgs::TestParseArgs testParser::TestParseLine mods::pre::pre_Repeat::TestRepeatDirective	106 107 107 108 109 109 110 111 111 112
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_If::TestIfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod TestMethod_mod mods::pre::parseArgs::TestParseArgs testParser::TestParseLine mods::pre::pre_Repeat::TestRepeatDirective TestResult_mod	106 107 107 108 109 110 111 111 112 114 114
Test_UnixProcess_mod TestCase_mod TestFailure_mod mods::pre::pre_lf::TestIfDirective mods::pre::interleavedp::TestInterleaved TestListener_mod TestMethod_mod mods::pre::parseArgs::TestParseArgs testParser::TestParseLine mods::pre::pre_Repeat::TestRepeatDirective	106 107 107 108 109 109 110 111 111 112 114 114 115

L. L	ata	a IV	pe	Ind	aex
--	-----	------	----	-----	-----

40

ThrowFundamentallypes_mod	117
UnixPipeInterfaces_mod	117
UnixProcess mod	118

# **Data Type Index**

# 16.1 Data Types List

Here are the data types with brief descriptions:

pFUnitParser::Action
add_mod
addComplex_mod
CodeUtilities::ArrayDescription
Assert_mod
<briefdescription></briefdescription>
AssertBasic_mod
<briefdescription></briefdescription>
AssertInteger_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::AssertRealArrayArgument 50
pFUnitParser::AtAfter
pFUnitParser::AtAssert
pFUnitParser::AtBefore
pFUnitParser::AtBegin
pFUnitParser::AtMpiAssert
pFUnitParser::AtMpiTest
pFUnitParser::AtParameters
pFUnitParser::AtSuite
pFUnitParser::AtTest
pFUnitParser::AtTestCase
BaseTestRunner_mod
<briefdescription></briefdescription>
BeforeAfter_mod
BrokenSetLinCase mod 59

Conservato De al Arman Allery Circulations are a tradical A CCEDITE OLIAI	59
GenerateRealArrayNewSignature::constraintASSERTEQUAL	60
mods::pre::pre2::dataString	61
DebugListener_mod	
<briefdescription></briefdescription>	62
CodeUtilities::declaration	63
DynamicTestCase_mod	
<briefdescription></briefdescription>	63
Exception_mod	64
Fixture_mod	65
FixtureTestCase_mod	65
CodeUtilities::fortranSubroutineSignature	66
Halo_mod	66
mods::pre::pre_lf::lfDirective	66
CodeUtilities::implementation	67
CodeUtilities::interfaceBlock	67
mods::pre::pre_lf::interval	68
GenerateRealArrayNewSignature::IsWithinTolerance	68
Test RestrictSphericalCoordinates mod::LatLonCase	69
LinearInterpolator mod	69
MakeInfinity mod	
<briefdescription></briefdescription>	69
MakeNaN mod	
_ <briefdescription></briefdescription>	70
MockCall mod	
<briefdescription></briefdescription>	71
<pre></pre>	71 72
MockListener_mod	
MockListener_mod	72
MockListener_mod	72
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription></briefdescription>	72 72
MockListener_mod	72 72 72
MockListener_mod testParser::MockParser MockRepository_mod	72 72 72 73
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module</briefdescription>	72 72 72 73 74
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod</briefdescription>	72 72 72 73 74
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod</briefdescription></briefdescription>	72 72 72 73 74 74
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription>  MpiTestCase_mod</briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription>  MpiTestCase_mod  <briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription>  MpiTestCase_mod  <briefdescription>  MpiTestMethod_mod</briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75 75
MockListener_mod  testParser::MockParser  MockRepository_mod	72 72 72 73 74 74 75 75
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription>  MpiTestCase_mod  <briefdescription>  MpiTestMethod_mod  <briefdescription>  MpiTestMethod_mod  <briefdescription>  ParallelContext_mod</briefdescription></briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75 75 76
MockListener_mod  testParser::MockParser  MockRepository_mod <briefdescription>  MockSUT_mod  testParser::MockWriter  CodeUtilities::module  MpiContext_mod  <briefdescription>  MpiStubs_mod  <briefdescription>  MpiTestCase_mod  <briefdescription>  MpiTestMethod_mod  <briefdescription>  ParallelContext_mod  <briefdescription></briefdescription></briefdescription></briefdescription></briefdescription></briefdescription></briefdescription>	72 72 72 73 74 74 75 75 76 77


ParameterizedTestCase_mod
<briefdescription></briefdescription>
Params_mod
<briefdescription></briefdescription>
pFUnitParser::Parser
Test_Parameters_mod::peCase
pFUnit
<briefdescription></briefdescription>
pFUnit_mod
<briefdescription></briefdescription>
PrivateException_mod
<briefdescription></briefdescription>
mods::pre::pre2::procDirective
RemoteProxyTestCase_mod
<briefdescription></briefdescription>
mods::pre::pre_Repeat::RepeatDirective
ResultPrinter_mod
<briefdescription></briefdescription>
RobustRunner_mod
<pre></pre>
robustTestSuite mod
CodeUtilities::routineUnit
SerialContext_mod
<pre></pre>
SimpleTestCase_mod
SourceLocation mod
<pre></pre>
SphericalCoordinates mod
TestListener_mod::startTest93
StringConversionUtilities mod
<pre></pre>
SubsetRunner mod
<pre><briefdescription></briefdescription></pre>
SurrogateTestCase_mod
<pre></pre>
SUT mod
Test_Assert_mod
Test_AssertBasic_mod
Test AssertComplex mod
Test AssertInteger mod
Test AssertReal mod
Test_Exception_mod
Test_FixtureTestCase_mod
Test_LinearInterpolator_mod::Test_LinearInterpolator
Test LinearInterpolator mod
Test MockCall mod
Toot_Moditodil_Hou

Test_MockRepository_mod
Test_mod
Test_MpiContext_mod
Test_MpiException_mod
Test_MpiTestCase_mod
Test_Parameters_mod::Test_Parameters
Test_Parameters_mod
Test_RestrictSphericalCoordinates_mod::Test_RestrictSphericalCoordinates . 104
Test_RestrictSphericalCoordinates_mod
Test_RobustRunner_mod
Test_SimpleTestCase_mod
Test_StringConversionUtilities_mod
Test_TestMethod_mod
Test_TestResult_mod
Test_TestSuite_mod
Test_UnixProcess_mod
TestCase_mod
<briefdescription></briefdescription>
TestFailure_mod
<briefdescription></briefdescription>
mods::pre_:pre_If::TestIfDirective
mods::pre::interleavedp::TestInterleaved
TestListener mod
<pre></pre>
TestMethod_mod
<pre><briefdescription></briefdescription></pre>
mods::pre::parseArgs::TestParseArgs
testParser::TestParseLine
mods::pre::pre_Repeat::TestRepeatDirective
TestResult mod
<pre></pre>
specialized TestResults
TestRunner mod
<briefdescription></briefdescription>
TestSuite_mod
<briefdescription></briefdescription>
ThrowFundamentalTypes_mod
<briefdescription></briefdescription>
UnixPipeInterfaces_mod
<briefdescription></briefdescription>
UnixProcess_mod
<briefdescription></briefdescription>
GenerateRealArrayNewSignature::VECTOR_NORM

# **Data Type Documentation**

17.1 pFUnitParser::Action Class Reference

Inheritance diagram for pFUnitParser::Action:



• def apply

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.2 add\_mod Module Reference

### **Public Member Functions**

- real function add (x, y)
- real function add (x, y)
- real function add (x, y)

The documentation for this module was generated from the following files:

- Robust/Semi-Automatic/src/add.F90
- Simple/Semi-Automatic/src/add.F90
- Simple\_Windows/Semi-Automatic/src/add.F90

# 17.3 addComplex\_mod Module Reference

#### **Public Member Functions**

- complex function, dimension(size(z0)) add (z0, z1)
- complex function, dimension(size(z0)) add (z0, z1)

The documentation for this module was generated from the following files:

- Semi-Automatic/src/addComplex.F90
- · Windows/Semi-Automatic/src/addComplex.F90

# 17.4 CodeUtilities::ArrayDescription Class Reference

### **Public Member Functions**

- def \_\_init\_\_\_
- def NAME
- def DECLARE
- def DECLARESCALAR
- def KIND
- def RANK
- def FTYPE
- def EXPANDSHAPE
- def FailureMessageFork

#### **Public Attributes**

- fType
- kind
- rank

The documentation for this class was generated from the following file:

CodeUtilities.py

## 17.5 Assert\_mod Module Reference

<BriefDescription>

## 17.5.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· Assert.F90

## 17.6 AssertBasic mod Module Reference

<BriefDescription>

## **Data Types**

- interface assertEqual
- interface assertExceptionRaised
- · interface assertFalse
- · interface assertIsFinite
- interface assertIsNaN
- interface assertTrue
- interface fail
- type UnusableArgument

- subroutine assertExceptionRaisedMessage (message)
- subroutine, public assertSameShape (shapeA, shapeB, message, location)
- logical function, public conformable (shapeA, shapeB)
- · logical function, public nonConformable (shapeA, shapeB)
- subroutine, public assertAny (conditions, message, location)
- subroutine, public assertAll (conditions, message, location)
- subroutine, public assertNone (conditions, message, location)
- subroutine, public assertNotAll (conditions, message, location)
- subroutine assertIsNaN\_double (x, message, location)
- subroutine assertIsFinite\_single (x, message, location)
- subroutine assertIsFinite\_double (x, message, location)

### 17.6.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertBasic.F90

# 17.7 AssertInteger\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface assertEqual
- interface assertGreaterThan
- interface assertGreaterThanOrEqual
- · interface assertLessThan
- interface assertLessThanOrEqual
- interface locationOfFirstNonzero

#### **Public Member Functions**

- subroutine assertEqualInteger1D1D (expected, found, message, location)
- subroutine assertEqualInteger0D1D\_ (expected, found, message, location)
- subroutine assertEqualInteger2D2D\_ (expected, found, message, location)
- subroutine assertEqualInteger0D2D\_ (expected, found, message, location)
- subroutine assertLessThan\_ (a, b, message, location)

### 17.7.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· AssertInteger.F90

# 17.8 GenerateRealArrayNewSignature::AssertRealArrayArgument Class Reference

### **Public Member Functions**

def \_\_init\_\_

- def updateDescriptions
- def getExpectedDescription
- def getFoundDescription
- def getTolerance

#### **Public Attributes**


- expectedFType
- expectedPrecision
- expectedRank
- foundFType
- foundPrecision
- foundRank
- tolerance
- expectedDescription
- foundDescription

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py

# 17.9 pFUnitParser::AtAfter Class Reference

Inheritance diagram for pFUnitParser::AtAfter:



#### **Public Member Functions**

- def \_\_init\_\_
- · def match
- · def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.10 pFUnitParser::AtAssert Class Reference

Inheritance diagram for pFUnitParser::AtAssert:



**Public Member Functions** 

- def \_\_init\_\_
- def match
- def appendSourceLocation
- def action

**Public Attributes** 


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

# 17.11 pFUnitParser::AtBefore Class Reference

Inheritance diagram for pFUnitParser::AtBefore:



- def \_\_init\_\_
- def match
- def action

## **Public Attributes**


parser

The documentation for this class was generated from the following file:

• pFUnitParser.py

# 17.12 pFUnitParser::AtBegin Class Reference

Inheritance diagram for pFUnitParser::AtBegin:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- · def action

#### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.13 pFUnitParser::AtMpiAssert Class Reference

Inheritance diagram for pFUnitParser::AtMpiAssert:



**Public Member Functions** 

- def \_\_init\_\_
- def match
- def appendSourceLocation
- def action

**Public Attributes** 


parser

The documentation for this class was generated from the following file:

· pFUnitParser.py

# 17.14 pFUnitParser::AtMpiTest Class Reference

Inheritance diagram for pFUnitParser::AtMpiTest:



- def \_\_init\_\_
- def match
- · def action

## **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.15 pFUnitParser::AtParameters Class Reference

Inheritance diagram for pFUnitParser::AtParameters:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- · def action

### **Public Attributes**


#### · parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.16 pFUnitParser::AtSuite Class Reference

Inheritance diagram for pFUnitParser::AtSuite:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- def action

### **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.17 pFUnitParser::AtTest Class Reference

Inheritance diagram for pFUnitParser::AtTest:



- def \_\_init\_\_
- def match
- · def action

## **Public Attributes**


parser

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.18 pFUnitParser::AtTestCase Class Reference

Inheritance diagram for pFUnitParser::AtTestCase:



## **Public Member Functions**

- def \_\_init\_\_
- def match
- · def action

### **Public Attributes**

parser

The documentation for this class was generated from the following file:

pFUnitParser.py

## 17.19 BaseTestRunner\_mod Module Reference

<BriefDescription>

# **Data Types**

- type BaseTestRunner
- interface run

# 17.19.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• BaseTestRunner.F90

### 17.20 BeforeAfter\_mod Module Reference

#### **Public Member Functions**

- subroutine first (this)
- subroutine last (this)
- · subroutine succeeds (this)
- subroutine fails (this)

### **Public Attributes**

- integer countStart = 0
- integer countComplete = 0

The documentation for this module was generated from the following file:

· beforeAfter.pf

# 17.21 BrokenSetUpCase\_mod Module Reference

# **Data Types**

• type BrokenSetUpCase

### **Public Member Functions**

• type(BrokenSetUpCase) function, pointer, public newBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• BrokenSetUpCase.F90

## 17.22 BrokenTestCase\_mod Module Reference

## **Data Types**

• type BrokenTestCase


• subroutine tearDown (this)

The documentation for this module was generated from the following file:

BrokenTestCase.F90

# 17.23 GenerateRealArrayNewSignature::constraintASSERTEQUA-L Class Reference

Inheritance diagram for GenerateRealArrayNewSignature::constraintASSERTEQUAL:



### **Public Member Functions**

def \_\_init\_\_

This next line actually generates the text of the code.

#### **Public Attributes**

- expectedDescr
- foundDescr
- name
- name1

Add in the extra module procedures...

tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

### 17.23.1 Constructor & Destructor Documentation

```
17.23.1.1 def GenerateRealArrayNewSignature::constraintASSERTE-QUAL::__init__ ( self, expectedDescr, foundDescr, tolerance )
```

This next line actually generates the text of the code.

#### 17.23.2 Member Data Documentation

#### 17.23.2.1 GenerateRealArrayNewSignature::constraintASSERTEQUAL::name1

Add in the extra module procedures...

If needed... Kluge. Need to make makeSubroutineNames and load the extra interface entries there.

#### 17.23.2.2 GenerateRealArrayNewSignature::constraintASSERTEQUAL::tolerance

If you need another kind of code generator, perhaps conditioned on eDesc., fDesc., or tol, then that logic would go here...

E.g. to implement assertEqual(Logical(...))

The documentation for this class was generated from the following file:

GenerateRealArrayNewSignature.py

# 17.24 mods::pre::pre2::dataString Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- def insert
- def getLength
- def getPosition
- · def setPosition
- def getItem
- def getDataAtPosition
- def getData
- def getSlice
- def getSliceForward
- def removeSlice
- · def getCurrentData
- · def insertAtCurrent

- · def append
- def advanceAndGetNextData
- def validPosition
- def findToEnd
- def match
- · def matchToEnd
- def searchToEnd
- def searchToPosition
- def finditerToEnd
- def finditerToPosition

## **Public Attributes**

- data
- position

The documentation for this class was generated from the following file:

pre2.py

# 17.25 DebugListener\_mod Module Reference

<BriefDescription>

## **Data Types**

• type DebugListener

#### **Public Member Functions**

• subroutine startTest (this, testName)

## 17.25.1 Detailed Description

<BriefDescription>

#### **Author**

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DebugListener.F90

## 17.26 CodeUtilities::declaration Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- · def generate

**Public Attributes** 

- simpleDeclaration
- fullDeclaration
- name

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.27 DynamicTestCase\_mod Module Reference

<BriefDescription>

## **Data Types**

- interface delete
- type DynamicTestCase
- · interface testmethod

#### **Public Member Functions**

 type(DynamicTestCase) function, pointer, public newDynamicTestCase (test-Method, name)

#### 17.27.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• DynamicTestCase.F90

# 17.28 Exception\_mod Module Reference

#### **Data Types**

- interface any Exceptions
- · interface catch
- interface getNumExceptions
- · interface throw

#### **Public Member Functions**

- subroutine, public initializeGlobalExceptionList ()
- type(Exception) function, public catchAny (preserve)
- type(Exception) function, dimension(:), allocatable, public getExceptions ()
- logical function, public noExceptions ()
- logical function, public anyErrors ()

- subroutine, public gatherExceptions (context)
- subroutine, public clearAll ()

The documentation for this module was generated from the following file:

• Exception.F90

#### 17.29 Fixture mod Module Reference

#### **Public Member Functions**

- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()
- subroutine mySetup ()
- subroutine myTearDown ()
- subroutine testRead ()
- subroutine testEOF ()

The documentation for this module was generated from the following files:

- Semi-Automatic/tests/fixtureTests.pf
- · Windows/Semi-Automatic/tests/fixtureTests.pf

#### 17.30 FixtureTestCase\_mod Module Reference

## **Data Types**

- interface delete
- type FixtureTestCase

#### **Public Member Functions**

- type(FixtureTestCase) function, public newFixtureTestCase ()
- subroutine, public simpleTestMethod (this)
- · subroutine, public methodA (this)
- subroutine, public methodB (this)

The documentation for this module was generated from the following file:

• FixtureTestCase.F90

# 17.31 CodeUtilities::fortranSubroutineSignature Class Reference

#### **Public Member Functions**

- def init
- def setReturnFType
- def addArg
- def generateInterfaceEntry
- def generateImplementationSignature
- def generateImplementationClose

#### **Public Attributes**

- name
- ArgumentToFType
- ReturnFType
- SubroutineType

The documentation for this class was generated from the following file:

· CodeUtilities.py

#### 17.32 Halo\_mod Module Reference

#### **Public Member Functions**


• subroutine haloFill (array, communicator)

The documentation for this module was generated from the following file:

· Halo.F90

# 17.33 mods::pre::pre\_lf::lfDirective Class Reference

Inheritance diagram for mods::pre::pre\_If::IfDirective:



**Public Member Functions** 

• def evaluate

**Public Attributes** 

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.34 CodeUtilities::implementation Class Reference

**Public Member Functions** 

- def \_\_init\_\_
- def generate

**Public Attributes** 

- name
- source

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.35 CodeUtilities::interfaceBlock Class Reference

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.36 mods::pre::pre\_lf::interval Class Reference

**Public Member Functions** 

- def init
- · def getInterval
- def setInterval
- · def getStart
- def getEnd

# **Public Attributes**


- start
- end
- interval

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.37 GenerateRealArrayNewSignature::IsWithinTolerance Class - Reference

Inheritance diagram for GenerateRealArrayNewSignature::IsWithinTolerance:



**Public Member Functions** 

• def \_\_init\_\_

**Public Attributes** 

- rank
- · precision

- name
- fType
- · declaration
- · declarations

The documentation for this class was generated from the following file:

· GenerateRealArrayNewSignature.py

# 17.38 Test\_RestrictSphericalCoordinates\_mod::LatLonCase Type - Reference

**Public Attributes** 

- real lat
- real lon
- · real restrictedLat
- · real restrictedLon

The documentation for this type was generated from the following file:

· Test\_RestrictedSphericalCoordinates.pf

# 17.39 LinearInterpolator\_mod Module Reference

## **Data Types**

- · interface LinearInterpolator
- type Node

The documentation for this module was generated from the following file:

• LinearInterpolator.F90

# 17.40 MakeInfinity\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- real(r32) function, public makeInf\_32 ()
- real(r64) function, public makeInf\_64 ()

## 17.40.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC SIVO

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MakeInfinity.F90

## 17.41 MakeNaN mod Module Reference

```
<BriefDescription>
```

#### **Public Member Functions**

- real(r32) function, public makeNaN\_32 ()
- real(r64) function, public makeNaN\_64 ()

#### 17.41.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• MakeNaN.F90

# 17.42 MockCall\_mod Module Reference

<BriefDescription>

# **Data Types**

· type MockCall

#### **Public Member Functions**

• type(MockCall) function, public **newMockCall** (name)

## 17.42.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· MockCall.F90

## 17.43 MockListener\_mod Module Reference

# **Data Types**

• type MockListener

#### **Public Member Functions**

• subroutine startTest (this, testName)

The documentation for this module was generated from the following file:

· MockListener.F90

## 17.44 testParser::MockParser Class Reference

**Public Member Functions** 

- def \_\_init\_\_\_
- · def nextLine

#### **Public Attributes**

- line
- outputFile
- · outLines
- · tests
- · mpitests
- · currentSelfObjectName

The documentation for this class was generated from the following file:

testParser.py

# 17.45 MockRepository\_mod Module Reference

<BriefDescription>

## **Data Types**

• type MockRepository

#### **Public Member Functions**

- type(MockRepository) function, pointer, public **newMockRepository** ()
- subroutine expectCall (this, obj, method)

## 17.45.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MockRepository.F90

## 17.46 MockSUT mod Module Reference

## **Data Types**

· type MockSUT

#### **Public Member Functions**

- type(MockSUT) function, allocatable, public **newMockSUT** (repository)
- subroutine method1 (this)

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

## 17.47 testParser::MockWriter Class Reference

#### **Public Member Functions**

- def \_\_init\_\_
- def write

## **Public Attributes**

parser

The documentation for this class was generated from the following file:

testParser.py

# 17.48 CodeUtilities::module Class Reference

#### **Public Member Functions**

- def \_\_init\_\_
- def generate
- def addDeclaration
- def addImplementation
- · def addRoutineUnit
- def addInterfaceBlock
- def getName
- def setFileName
- def getFileName

#### **Public Attributes**

- name
- declarations
- · implementations
- · generation
- fileName

The documentation for this class was generated from the following file:

· CodeUtilities.py

# 17.49 MpiContext\_mod Module Reference

<BriefDescription>

# **Data Types**

- · type MpiContext
- interface newMpiContext

## **Public Member Functions**

- subroutine barrier (this)
- integer function getMpiCommunicator (this)

## 17.49.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiContext.F90

# 17.50 MpiStubs\_mod Module Reference

<BriefDescription>

#### **Public Member Functions**

- subroutine, public MPI\_Comm\_rank (comm, rank, ier)
- subroutine, public MPI\_Comm\_size (comm, size, ier)
- subroutine, public MPI\_Comm\_dup (comm, newComm, ier)
- subroutine, public MPI Comm group (comm, group, ier)
- subroutine, public MPI\_Group\_range\_incl (group, n, ranges, newGroups, ier)
- subroutine, public MPI\_Comm\_create (comm, group, newComm, ier)

#### **Public Attributes**

- integer, parameter, public MPI COMM WORLD = -1
- integer, parameter, public MPI\_COMM\_NULL = -1
- integer, parameter, public MPI\_COMM\_SUCCESS = 0

## 17.50.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· MpiStubs.F90

# 17.51 MpiTestCase\_mod Module Reference

<BriefDescription>

#### **Data Types**

- · type MpiTestCase
- · interface runMethod

#### **Public Member Functions**

- recursive subroutine runBare (this)
- subroutine setUp (this)

## 17.51.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestCase.F90

# 17.52 MpiTestMethod\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface mpiMethod
- type MpiTestMethod
- interface newMpiTestMethod

## 17.52.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• MpiTestMethod.F90

## 17.53 ParallelContext\_mod Module Reference

<BriefDescription>

## **Data Types**

- interface allReduceLogical
- interface gatherInteger
- interface gatherLogical
- · interface gatherString
- interface getNumProcesses
- type ParallelContext
- interface processRank
- · interface sum

## 17.53.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· ParallelContext.F90

# 17.54 ParallelException\_mod Module Reference

<BriefDescription>

## **Data Types**

- interface any Exceptions
- interface getNumExceptions

#### **Public Member Functions**

• subroutine, public gather (context)

## 17.54.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• ParallelException.F90

# 17.55 ParameterizedTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- type AbstractTestParameter
- interface getParameterString
- type ParameterizedTestCase

#### **Public Attributes**

• integer, parameter, public MAX\_LEN\_LABEL = 32

## 17.55.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ParameterizedTestCase.F90

## 17.56 Params\_mod Module Reference

<BriefDescription>

#### **Public Attributes**

```
• integer, parameter R32 = selected_real_kind(p=6)
```

- integer, parameter **R64** = selected\_real\_kind(p=14)
- integer, parameter **C32** = selected\_real\_kind(p=6)
- integer, parameter C64 = selected\_real\_kind(p=14)
- integer, parameter **NEQP** = 0
- integer, parameter **EQP** = 1
- integer, parameter GTP = 2
- integer, parameter **GEP** = 3
- integer, parameter LTP = 4
- integer, parameter **LEP** = 5
- integer, parameter **RELEQP** = 6

## 17.56.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Params.F90

# 17.57 pFUnitParser::Parser Class Reference

#### **Public Member Functions**

- def \_\_init\_\_
- def run
- def nextLine
- def makeSuite
- def final

#### **Public Attributes**

- inputFile
- outputFile
- moduleName
- suiteName
- testCase
- setUp
- tearDown
- · defaultName
- fileName
- lineNumber
- parameters
- parameterType
- · tests
- · mpitests
- actions

The documentation for this class was generated from the following file:

pFUnitParser.py

# 17.58 Test\_Parameters\_mod::peCase Type Reference

#### **Public Attributes**

- integer p1
- integer p2

The documentation for this type was generated from the following file:

• parameterizedTests.pf

# 17.59 pFUnit Module Reference

<BriefDescription>

## 17.59.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• pFUnitPackage.F90

# 17.60 pFUnit\_mod Module Reference

<BriefDescription>

## **Public Member Functions**

- subroutine, public initialize (useMpi)
- subroutine, public finalize ()

## 17.60.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

#### Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• pFUnit.F90

# 17.61 PrivateException\_mod Module Reference

<BriefDescription>

## **Data Types**

- type Exception
- type ExceptionList
- interface newException

#### **Public Member Functions**

- type(ExceptionList) function, public newExceptionList ()
- logical function noExceptions (this)

#### **Public Attributes**

- integer, parameter, public **MAXLEN\_MESSAGE** = 80\*15
- integer, parameter, public **MAXLEN\_FILE\_NAME** = 80
- character(len=\*), parameter, public NULL\_MESSAGE = "

## 17.61.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• Exception.F90

# 17.62 mods::pre::pre2::procDirective Class Reference

Inheritance diagram for mods::pre::pre2::procDirective:



#### **Public Member Functions**

- def \_\_init\_\_
- def getLength
- · def match
- def evaluate
- def getNewPosition
- def addTokenRE
- def searchTokenToEnd
- def searchTokenToPosition
- def finditerTokenToPosition
- def makeTokenErrorMessage

#### **Public Attributes**

- name
- newPosition
- · tokens
- TokenREs

#### 17.62.1 Member Function/Subroutine Documentation

```
17.62.1.1 def mods::pre2::procDirective::addTokenRE( self, args, key, defaultToken, prefix = r''' (?i) [ \t]*''', postfix = ''')
```

Add a token/create an RE with a prefix that by default ignores preceding whitespace. Stores the RE in a dictionary for this directive.

The documentation for this class was generated from the following file:

• pre2.py

# 17.63 RemoteProxyTestCase\_mod Module Reference

<BriefDescription>

## **Data Types**

• interface RemoteProxyTestCase

## 17.63.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• RemoteProxyTestCase.F90

# 17.64 mods::pre::pre\_Repeat::RepeatDirective Class Reference

Inheritance diagram for mods::pre::pre\_Repeat::RepeatDirective:



#### **Public Member Functions**

• def evaluate

#### **Public Attributes**

- startPosition
- newPosition

The documentation for this class was generated from the following file:

pre\_Repeat.py

## 17.65 ResultPrinter\_mod Module Reference

<BriefDescription>

## **Data Types**

• type ResultPrinter

#### **Public Member Functions**

- type(ResultPrinter) function, public **newResultPrinter** (unit)
- subroutine addError (this, testName, exceptions)
- subroutine **startTest** (this, testName)
- subroutine **printHeader** (this, runTime)

## 17.65.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· ResultPrinter.F90

## 17.66 RobustRunner\_mod Module Reference

<BriefDescription>

## **Data Types**

- · interface RobustRunner
- type TestCaseMonitor

#### **Public Member Functions**

- type(RobustRunner) function newRobustRunner\_unit (remoteRunCommand, unit)
- · subroutine runWithResult (this, aTest, context, result)
- subroutine launchRemoteRunner (this, numSkip)
- subroutine startTest (this, testName)
- subroutine addError (this, testName, exceptions)
- type(TestResult) function createTestResult (this)

## 17.66.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· RobustRunner.F90

## 17.67 robustTestSuite mod Module Reference

**Public Member Functions** 

- type(TestSuite) function, public **suite** ()
- subroutine testRunSucceeds ()
- subroutine testRunStops ()

The documentation for this module was generated from the following file:

• robustTestSuite.F90

## 17.68 CodeUtilities::routineUnit Class Reference

Inheritance diagram for CodeUtilities::routineUnit:



#### **Public Member Functions**

- def \_\_init\_\_
- · def setName
- · def getName
- def setDeclaration
- def addDeclaration
- def setImplementation
- def getDeclaration
- · def getDeclarations
- def getImplementation
- · def clearDeclarations

#### **Public Attributes**

- name
- declaration
- · declarations
- · implementation

The documentation for this class was generated from the following file:

· CodeUtilities.py

## 17.69 SerialContext\_mod Module Reference

<BriefDescription>

## **Data Types**

• type SerialContext

#### **Public Member Functions**

• type(SerialContext) function, public newSerialContext ()

#### **Public Attributes**

 type(SerialContext), parameter, public THE\_SERIAL\_CONTEXT = Serial-Context(1)

## 17.69.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SerialContext.F90

# 17.70 SimpleTestCase\_mod Module Reference

## **Data Types**

- · interface method
- type SimpleTestCase

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(SimpleTestCase) function, public newSimpleTestCase (name, user-Method)
- subroutine, public method1 (this)
- subroutine, public method2 (this)
- subroutine, public methodWith2Exceptions (this)
- subroutine delete\_ (this)

The documentation for this module was generated from the following file:

• SimpleTestCase.F90

## 17.71 SourceLocation mod Module Reference

<BriefDescription>

## **Data Types**

• type SourceLocation

#### **Public Attributes**

- character(len=MAXLEN\_FILE\_NAME), parameter, public UNKNOWN\_FILE\_N-AME = '<unknown file>'
- integer, parameter, public **UNKNOWN\_LINE\_NUMBER** = -1
- type(SourceLocation), parameter, public UNKNOWN\_SOURCE\_LOCATION = SourceLocation()

## 17.71.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SourceLocation.F90

# 17.72 SphericalCoordinates\_mod Module Reference

#### **Data Types**

• interface SphericalCoordinates

The documentation for this module was generated from the following file:

• SphericalCoordinates.F90

#### 17.73 TestListener\_mod::startTest Interface Reference

The documentation for this interface was generated from the following file:

· TestListener.F90

# 17.74 StringConversionUtilities\_mod Module Reference

<BriefDescription>

## **Data Types**

· interface toString

## **Public Member Functions**

- character(len=len\_trim(a)+1+len\_trim(b)) function, public appendWithSpace (a, b)
- character(len=:) function, allocatable, public nullTerminate (string)
- character(len=:) function, allocatable, public unlessScalar (vShape, string)

#### **Public Attributes**

• integer, parameter, public **MAXLEN\_STRING** = 80

#### 17.74.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• StringConversionUtilities.F90

## 17.75 SubsetRunner\_mod Module Reference

<BriefDescription>

## **Data Types**

· interface SubsetRunner

**Public Member Functions** 

- subroutine addFailure (this, testName, exceptions)
- subroutine startTest (this, testName)

## 17.75.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· SubsetRunner.F90

# 17.76 SurrogateTestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface getName
- interface runBare
- interface setName
- type SurrogateTestCase

## 17.76.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• SurrogateTestCase.F90

## 17.77 SUT\_mod Module Reference

# **Data Types**

• type SUT

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

#### 17.78 Test Assert mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertEqualStringDiffer1st ()

The documentation for this module was generated from the following file:

· Test Assert.F90

#### 17.79 Test AssertBasic mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertTrueF ()
- subroutine testAssertIsFinite ()

The documentation for this module was generated from the following file:

• Test AssertBasic.F90

## 17.80 Test\_AssertComplex\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testEquals\_C\_complexScalar ()
- subroutine testEquals\_C\_0D1D ()
- subroutine testEquals\_C\_1D\_nonConformable1 ()
- subroutine testEquals\_C\_2D\_SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent ()
- subroutine testEquals C MultiD SingleElementDifferent1
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent2
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent3
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent4
- subroutine testEquals\_C\_MultiD\_SingleElementDifferent5
- subroutine testEquals C MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff1 ()

- subroutine testEquals C MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff3 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff4 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff5 ()
- subroutine testEquals\_C\_MultiDMultiPrec\_SingleEltDiff6 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals C MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals C MultiDWithTolerance ()
- subroutine testEquals C MultiDWithTolerance1 ()
- subroutine testEquals C MultiDWithTolerance64 ()
- subroutine testEquals\_C\_MultiDWithTolerance64\_1 ()
- subroutine testEquals\_C\_MultiDWithTolerance64\_2 ()
- subroutine testEquals C MultiDSourceLocation ()
- subroutine testEquals\_4DPComplex\_DifferenceReport ()
- · subroutine assertCatch (string, location)

Test AssertComplex.F90

# 17.81 Test\_AssertInteger\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testAssertEqual\_equal ()

The documentation for this module was generated from the following file:

· Test AssertInteger.F90

# 17.82 Test AssertReal mod Module Reference

- type(TestSuite) function, public suite ()
- subroutine testEquals\_0D1D ()
- subroutine testEquals\_1D\_nonConformable1 ()
- subroutine testEquals\_2D\_SingleElementDifferent ()

- subroutine testEquals MultiD SingleElementDifferent ()
- subroutine testEquals\_MultiD\_SingleElementDifferent1
- subroutine testEquals\_MultiD\_SingleElementDifferent2
- subroutine testEquals MultiD SingleElementDifferent3
- subroutine testEquals\_MultiD\_SingleElementDifferent4
- subroutine testEquals MultiD SingleElementDifferent5
- subroutine testEquals MultiDMultiPrec SingleEltDiff ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff1 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff2 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff3 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff4 () subroutine testEquals MultiDMultiPrec SingleEltDiff5 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff6 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff7 ()
- subroutine testEquals MultiDMultiPrec SingleEltDiff8 ()
- subroutine testEquals ScalarWithTolerance ()
- subroutine testEquals ScalarWithToleranceNoMsg ()
- subroutine testEquals\_VectorWithToleranceNoMsg ()
- subroutine testEquals MultiDWithTolerance ()
- subroutine testEquals MultiDWithTolerance1 ()
- subroutine testEquals\_MultiDWithTolerance64 ()
- subroutine testEquals MultiDWithTolerance64 1 ()
- subroutine testEquals MultiDWithTolerance64 2 ()
- subroutine testEquals MultiDSourceLocation ()
- subroutine testEquals ScalarAndLocation ()
- subroutine testEquals ScalarInfinity equal ()
- subroutine testEquals ScalarInfinity unequal A ()
- subroutine testEquals ScalarInfinity unequal B ()
- subroutine testEquals\_ScalarInfinity\_unequal\_C ()
- · subroutine assertCatch (string, location)

Test AssertReal.F90

#### Test\_Exception\_mod Module Reference 17.83

- type(TestSuite) function, public suite ()
- subroutine testGetNumExceptions ()

- subroutine testCatchSucceed ()
- subroutine testGetLineNumber ()
- subroutine testGetFileName ()

• Test Exception.F90

#### 17.84 Test FixtureTestCase mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunWithFixture ()
- subroutine testBrokenTestCase ()
- subroutine testBrokenSetUpCase ()

The documentation for this module was generated from the following file:

• Test FixtureTestCase.F90

# 17.85 Test\_LinearInterpolator\_mod::Test\_LinearInterpolator Type - Reference

#### **Public Member Functions**

- type(Test\_LinearInterpolator) function newTest\_LinearInterpolator (name, userMethod)
- procedure setUp
- procedure tearDown
- procedure runMethod

#### **Public Attributes**

- type(LinearInterpolator) interpolator
- procedure(runMethod), pointer **userMethod** = > null()

The documentation for this type was generated from the following file:

• Test\_LinearInterpolator.pf

# 17.86 Test\_LinearInterpolator\_mod Module Reference

# **Data Types**

· type Test\_LinearInterpolator

#### **Public Member Functions**

- type(Test\_LinearInterpolator) function newTest\_LinearInterpolator (name, userMethod)
- subroutine setUp (this)
- subroutine tearDown (this)
- · subroutine runMethod (this)
- subroutine testBracketAtNode (this)
- subroutine testBracketInterior (this)
- subroutine testInterpolateAtNode (this)
- subroutine testInterpolateConstant (this)

The documentation for this module was generated from the following file:

· Test\_LinearInterpolator.pf

#### 17.87 Test\_MockCall\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testExpectOneIntegerArgument
- subroutine testFailExpectOneIntegerArgument

The documentation for this module was generated from the following file:

Test\_MockCall.F90

# 17.88 Test\_MockRepository\_mod Module Reference

#### **Public Member Functions**

• type(TestSuite) function, public suite ()

• subroutine testNoAction ()

The documentation for this module was generated from the following file:

• Test\_MockRepository.F90

# 17.89 Test\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface countTestCases
- interface run
- type Test

### 17.89.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• Test.F90

# 17.90 Test\_MpiContext\_mod Module Reference

# **Public Member Functions**

• type(TestSuite) function, public suite ()

• subroutine testNumProcesses1 (context)

The documentation for this module was generated from the following file:

• Test\_MpiContext.F90

# 17.91 Test\_MpiException\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine test\_anyExceptions\_none (this)
- subroutine test getNumExceptions (this)
- subroutine test\_gather (this)

The documentation for this module was generated from the following file:

• Test\_MpiException.F90

# 17.92 Test\_MpiTestCase\_mod Module Reference

#### **Data Types**

- · interface method
- type Test\_MpiTestCase

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(Test\_MpiTestCase) function, public newTest\_MpiTestCase (name, user-Method, numProcesses)
- subroutine testRunOn2Processors (this)
- subroutine brokenProcess1 (this)
- subroutine brokenOnProcess2 (this)
- subroutine testFailOn1 (this)
- subroutine testFailOn2 (this)
- subroutine testTooFewProcs (this)
- recursive subroutine runMethod (this)

The documentation for this module was generated from the following file:

Test\_MpiTestCase.F90

#### 17.93 Test Parameters mod::Test Parameters Interface Reference

#### **Public Member Functions**

- procedure, nopass getParameters
- procedure getParameterString => getParameterString\_
- procedure runMethod
- type(Test\_Parameters) function **newTest** (name, method, npe, p1, p2)

#### **Public Attributes**

- integer p1
- integer p2
- procedure(runMethod), pointer **userMethod** = > null()

The documentation for this interface was generated from the following file:

· parameterizedTests.pf

#### 17.94 Test Parameters mod Module Reference

# **Data Types**

- type peCase
- interface Test\_Parameters

#### **Public Member Functions**

- type(Test\_Parameters) function **newTest** (name, method, npe, p1, p2)
- type(peCase) function, dimension(:), allocatable getParameters ()
- character(:) function, allocatable getParameterString\_ (this)
- subroutine runMethod (this)
- subroutine, public testParamBroken (this)

The documentation for this module was generated from the following file:

• parameterizedTests.pf

# 17.95 Test\_RestrictSphericalCoordinates\_mod::Test\_Restrict-SphericalCoordinates Interface Reference

#### **Public Member Functions**

- · procedure, nopass getParameters
- procedure getParameterString
- procedure runMethod
- type(Test\_RestrictSphericalCoordinates) function newTest (name, method, lat, lon, restrictedLat, restrictedLon)

#### **Public Attributes**

- · real lat
- · real lon
- real restrictedLat
- real restrictedLon
- · type(SphericalCoordinates) unrestricted
- type(SphericalCoordinates) restricted
- procedure(runMethod), pointer userMethod = > null()

The documentation for this interface was generated from the following file:

· Test RestrictedSphericalCoordinates.pf

# 17.96 Test\_RestrictSphericalCoordinates\_mod Module Reference

# **Data Types**

- type LatLonCase
- interface Test\_RestrictSphericalCoordinates

- type(Test\_RestrictSphericalCoordinates) function newTest (name, method, lat, lon, restrictedLat, restrictedLon)
- type(LatLonCase) function, dimension(:), allocatable getParameters ()
- subroutine testRestrict (this)
- character(:) function, allocatable getParameterString (this)
- subroutine runMethod (this)

· Test RestrictedSphericalCoordinates.pf

#### 17.97 Test RobustRunner mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testRunVariety ()

The documentation for this module was generated from the following file:

• Test\_RobustRunner.F90

# 17.98 Test\_SimpleTestCase\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- type(TestSuite) function internalSuite ()
- subroutine testWorks ()
- subroutine testFails ()
- subroutine testRunSuite ()

The documentation for this module was generated from the following file:

• Test SimpleTestCase.F90

# 17.99 Test\_StringConversionUtilities\_mod Module Reference

# **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testToStringInteger1D ()

The documentation for this module was generated from the following file:

• Test\_StringConversionUtilities.F90

#### 17.100 Test\_TestMethod\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testMethodWasRun ()
- subroutine testWasRun ()

The documentation for this module was generated from the following file:

• Test\_TestMethod.F90

# 17.101 Test\_TestResult\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testGetNumRun ()
- subroutine testGetNumFailed ()
- subroutine testAddListenerEnd ()
- subroutine testAddListenerStart ()
- subroutine testAddListenerFailure ()

The documentation for this module was generated from the following file:

• Test\_TestResult.F90

### 17.102 Test\_TestSuite\_mod Module Reference

# **Data Types**

• type Verbose

- type(TestSuite) function, public suite ()
- subroutine testCountTestCases ()
- subroutine testCountTestCasesNestedA ()
- subroutine testCountTestCasesNestedB ()

- subroutine testCountTestCasesNestedC ()
- subroutine testGetTestCases ()
- subroutine myTestMethod ()

• Test\_TestSuite.F90

# 17.103 Test\_UnixProcess\_mod Module Reference

#### **Public Member Functions**

- type(TestSuite) function, public suite ()
- subroutine testIsActive ()

The documentation for this module was generated from the following file:

• Test\_UnixProcess.F90

# 17.104 TestCase\_mod Module Reference

<BriefDescription>

# **Data Types**

- type ConcreteSurrogate
- · interface runMethod
- type TestCase
- type TestCaseReference

- recursive subroutine runBare (this)
- recursive subroutine runBare\_surrogate (this)

# 17.104.1 Detailed Description

```
<BriefDescription>
```

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestCase.F90

# 17.105 TestFailure\_mod Module Reference

<BriefDescription>

**Data Types** 

• type TestFailure

# 17.105.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestFailure.F90

# 17.106 mods::pre::pre\_lf::TestlfDirective Class Reference

#### **Public Member Functions**

- def testTokenNotFound1
- def testNoTest
- def testIFTestFalse
- def testIFTestTrue1
- def testIFTestTrue2
- · def testIFClearTokens
- def testIFClearTokensUntilEnd1

The documentation for this class was generated from the following file:

pre\_lf.py

# 17.107 mods::pre::interleavedp::TestInterleaved Class Reference

- · def test InOrder
- def test\_NumberMismatch
- def test\_OrderMismatch1
- def test\_OrderMismatch2
- def test\_OrderMismatch3
- def test ElseMid1
- def test ElseMid2
- · def test\_ElseMid3
- · def test ElseMid4
- def test\_ElseMid5
- def test\_ElseMid6
- def test ElseMid7
- def test\_ElseMid8

- def test\_ElseMid9
- · def test\_ElseMid10

· interleavedp.py

# 17.108 TestListener\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface addFailure
- interface endTest
- type ListenerPointer
- interface startTest
- type TestListener

#### 17.108.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestListener.F90

#### 17.109 TestMethod\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface empty
- interface newTestMethod
- type TestMethod

#### 17.109.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

· TestMethod.F90

# 17.110 mods::pre::parseArgs::TestParseArgs Class Reference

- def test\_ParseArgs\_OneArgWithBrackets1
- · def test\_ParseArgs\_OneArgWithBrackets2
- def test\_ParseArgs\_OneArgWithBrackets3
- def test\_ParseArgs\_OneArgWithBrackets4
- def test\_ParseArgs\_OneArgWithBrackets5
- def test\_ParseArgs\_OneArgWithBrackets6
- def test\_ParseArgs\_OneArgWithBrackets7

- · def test\_ParseArgs\_oneArg
- def test\_ParseArgs\_twoArgs1
- · def test ParseArgs twoArgs2
- def test\_ParseArgs\_oneArgArray1
- def test\_ParseArgs\_TwoArgArray
- def test\_ParseArgs\_ThreeArgs

parseArgs.py

#### 17.111 testParser::TestParseLine Class Reference

#### **Public Member Functions**

- def testCppSetLineAndFile
- · def testGetSubroutineName
- def testGetSelfObjectName
- def testGetTypeName
- def testAtTest
- def testAtMpiTest
- def testMatchAtTestCase
- def testMatchAtAssertEqual
- · def testMatchAtAssertOther
- def testMatchAtMpiAssert
- def testMatchAtBefore
- def testMatchAtAfter
- · def testMatchAtSuite

#### 17.111.1 Member Function/Subroutine Documentation

#### 17.111.1.1 def testParser::TestParseLine::testAtMpiTest( self)

Check that a line starting with '@mpitest' is detected as an annotation and that optional parameters are collected.

#### 17.111.1.2 def testParser::TestParseLine::testAtTest( self )

Check that a line starting with '@test' is detected as an annotation.

#### 17.111.1.3 def testParser::TestParseLine::testMatchAtAfter( self)

Check that a line starting with '@after\*' ...

#### 17.111.1.4 def testParser::TestParseLine::testMatchAtAssertEqual ( self )

Check that a line starting with '@assertEqual' is detected as an annotation.

#### 17.111.1.5 def testParser::TestParseLine::testMatchAtAssertOther ( self )

Check that a line starting with '@assert\*' is detected as an annotation.

#### 17.111.1.6 def testParser::TestParseLine::testMatchAtBefore ( self )

Check that a line starting with '@before\*' ...

# 17.111.1.7 def testParser::TestParseLine::testMatchAtMpiAssert ( self )

Check that a line starting with '@mpiAssert\*' is detected as an annotation.

#### 17.111.1.8 def testParser::TestParseLine::testMatchAtSuite ( self )

Check that a line starting with '@suite changes the suite name ...

#### 17.111.1.9 def testParser::TestParseLine::testMatchAtTestCase( self)

Check that a line starting with '@testcase' is detected as an annotation.

The documentation for this class was generated from the following file:

testParser.py

# 17.112 mods::pre::pre\_Repeat::TestRepeatDirective Class Reference

#### **Public Member Functions**

- def test copyBlock1
- def test\_copyBlock2
- · def test\_copyBlock2Vars
- def test\_copyBlock2VarsMulti
- def test\_copyBlock2VarsMultiWithStrings
- def test\_copyNaiveRecursion
- def test\_copyNaiveRecursion1
- def test\_copyFunction1

The documentation for this class was generated from the following file:

pre\_Repeat.py

#### 17.113 TestResult\_mod Module Reference

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

### **Data Types**

· type TestResult

#### **Public Member Functions**

- type(TestResult) function, pointer, public newTestResult ()
- · subroutine addError (this, aTest, exceptions)
- integer function failureCount (this)
- subroutine addListener (this, listener)

#### 17.113.1 Detailed Description

<BriefDescription> Note: A possible extension point for user-specialized TestResults.

#### **Author**

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• TestResult.F90

# 17.114 TestRunner mod Module Reference

<BriefDescription>

# **Data Types**

- interface newTestRunner
- type TestRunner

#### **Public Member Functions**

- type(TestRunner) function newTestRunner\_unit (unit)
- subroutine run (this, aTest, context)
- subroutine **startTest** (this, testName)

# 17.114.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

· TestRunner.F90

# 17.115 TestSuite\_mod Module Reference

```
<BriefDescription>
```

# **Data Types**

- interface newTestSuite
- type TestReference
- type TestSuite

#### **Public Member Functions**

• recursive subroutine addTest (this, aTest)

#### 17.115.1 Detailed Description

```
<BriefDescription>
```

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

```
<A note here.> < Or starting here...>
```

The documentation for this module was generated from the following file:

• TestSuite.F90

# 17.116 ThrowFundamentalTypes\_mod Module Reference

<BriefDescription>

# **Data Types**

- · interface throwDifferentValues
- interface throwDifferentValuesWithLocation

#### **Public Member Functions**

- subroutine, public throwNonConformable (shapeExpected, shapeFound, location)
- character(len=MAXLEN\_SHAPE) function, public locationFormat (iLocation)

#### 17.116.1 Detailed Description

<BriefDescription>

Author

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• ThrowFundamentalTypes.F90

# 17.117 UnixPipeInterfaces\_mod Module Reference

<BriefDescription>

# **Data Types**

- interface fgets
- · interface free
- interface getdelim
- interface getline
- interface pclose
- interface popen

#### **Public Attributes**

• integer(C\_INT), parameter, public CLOSE\_FAILED = -1

# 17.117.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note

<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

• UnixPipeInterfaces.F90

# 17.118 UnixProcess\_mod Module Reference

<BriefDescription>

# **Data Types**

· interface UnixProcess

#### **Public Member Functions**

- character(len=:) function, allocatable makeCommand (baseCommand, runIn-Background)
- logical function isActive (this)
- character(len=:) function, allocatable getDelim (this, delimeter)
- integer function getPid (this)

# 17.118.1 Detailed Description

<BriefDescription>

**Author** 

Tom Clune, NASA/GSFC

Date

07 Nov 2013

Note


<A note here.> < Or starting here...>

The documentation for this module was generated from the following file:

UnixProcess.F90

#### GenerateRealArrayNewSignature::VECTOR\_NORM Class -17.119 Reference

Inheritance diagram for GenerateRealArrayNewSignature::VECTOR\_NORM:



**Public Member Functions** 

def \_\_init\_\_

# **Public Attributes**

- rank
- fType
- precision
- name
- declaration
- · declarations

The documentation for this class was generated from the following file:

• GenerateRealArrayNewSignature.py