EECS 489 Computer Networks

Fall 2019


Mosharaf Chowdhury

Material with thanks to Aditya Akella, Sugih Jamin, Philip Levis, Sylvia Ratnasamy, Peter Steenkiste, and many other colleagues.


Agenda

- TCP flow control
- TCP congestion control


TCP state transitions



TCP client lifecycle



TCP server lifecycle




5

TCP FLOW CONTROL


Recap: Sliding window

- Both sender and receiver maintain a window
- Left edge of window:
 - Sender: beginning of unacknowledged data
 - Receiver: beginning of expected data
 - »First "gap" in received data
 - »When sender gets ack, knows that receiver's window has moved
- Right edge: Left edge + constant
 - The constant is only limited by buffer size in the transport layer

Sliding window at sender




Sliding window at receiver



Solution: Advertised window (Flow Control)


- Receiver uses an "Advertised Window" (RWND) to prevent sender from overflowing its window
 - Receiver indicates value of RWND in ACKs
 - Sender ensures that the total number of bytes in flight <= RWND</p>

TCP header




Data

Sliding window at receiver



Sliding window at sender



Sliding window with flow control

- Sender: window advances when new data ACK'd
- Receiver: window advances as receiving process consumes data
- Receiver advertises to the sender where the receiver window currently ends ("righthand edge")
 - Sender agrees not to exceed this amount
- UDP does not have flow control
 - Data can be lost due to buffer overflow

Advertised window limits rate

- Sender can send no faster than RWND/RTT bytes/sec
- Receiver only advertises more space when it has consumed old arriving data
- What happens when RWND=0?
 - Sender keeps probing with one data bytes
- In original TCP design, that was the sole protocol mechanism controlling sender's rate
 - What's missing?

TCP CONGESTION CONTROL

What is congestion?

- If two packets arrive at a router at the same time
 - Router will transmit one and buffer/drop the other
- Internet traffic is bursty
 - Many packets can arrive close in time
 - Causes packet delays and drops
- Root cause: statistical multiplexing

Congestion collapse in 1980s

- Sending rate only limited by flow control
 - ▶ Dropped packets → senders (repeatedly!) retransmit
- Led to "congestion collapse" in Oct. 1986
 - Throughput on the NSF network dropped from 32Kbits/s to 40bits/sec
- "Fixed" by Van Jacobson's development of TCP's congestion control (CC) algorithms

Jacobson's fix to TCP

- Extend TCP's existing window-based protocol but adapt the window size in response to congestion
- A pragmatic and effective solution
 - Required no upgrades to routers or applications!
 - Patch of a few lines of code to TCP implementations
- Extensively researched and improved upon
 - Especially now with datacenters and cloud services

Key design considerations

- How do we know the network is congested?
 - Implicit and/or explicit signals from the network
- Who takes care of congestion?
 - End hosts (may receive some help from the network)
- How do we handle congestion?
 - Continuous adaptation

Three issues to consider

- Discovering the available (bottleneck) bandwidth
- Adjusting to variations in bandwidth
- Sharing bandwidth between flows

Abstract view



 Ignore internal structure of router and model it as a single queue for a particular input-output pair

Discovering available bandwidth



- Pick sending rate to match bottleneck bandwidth
 - Without any a priori knowledge
 - Could be gigabit link, could be a modem

Adjusting to variations in bandwidth




- Adjust rate to match instantaneous bandwidth
 - Assuming you have rough idea of bandwidth

24


Multiple flows and sharing bandwidth

• Two Issues:

- Adjust total sending rate to match bandwidth
- Allocation of bandwidth between flows



Reality



Congestion control is a resource allocation problem involving many flows, many links, and complicated global dynamics

- (0) Send without care
 - Many packet drops

- (0) Send without care
- (1) Reservations
 - Pre-arrange bandwidth allocations
 - Requires negotiation before sending packets
 - Low utilization

- (0) Send without care
- (1) Reservations
- (2) Pricing
 - Don't drop packets for the high-bidders
 - Requires payment model

- (0) Send without care
- (1) Reservations
- (2) Pricing
- (3) Dynamic Adjustment
 - Hosts infer level of congestion; adjust
 - Network reports congestion level to hosts; hosts adjust
 - Combinations of the above
 - Simple to implement but suboptimal, messy dynamics

- (0) Send without care
- (1) Reservations
- (2) Pricing
- (3) Dynamic Adjustment

- Generality of dynamic adjustment has proven to be very powerful
 - Doesn't presume business model, traffic characteristics, application requirements
 - But does assume good citizenship!

5-MINUTE BREAK!

TCP's approach in a nutshell

- Each TCP connection has a window
 - Controls number of packets in flight
- Sending rate ~Window/RTT
- Vary window size to control sending rate

Windows to keep in mind

- Congestion Window: CWND
 - Bytes that can be sent without overflowing routers
 - Computed by sender using congestion control algo.
- Flow control window: RWND
 - Bytes that can be sent without overflowing receiver
 - Determined by the receiver and reported to the sender
- Sender-side window = min {CWND, RWND}
 - Assume for this lecture that RWND >> CWND

Note

- This lecture talks about CWND in units of MSS
 - MSS (Maximum Segment Size): the amount of payload data in a TCP packet
 - This is only for the simplicity of presentation
- Real implementations maintain CWND in bytes

Two basic questions

- How does the sender detect congestion?
- How does the sender adjust its sending rate?
 - To address three issues
 - »Finding available bottleneck bandwidth
 - »Adjusting to bandwidth variations
 - »Sharing bandwidth

Detecting congestion

- Packet delays
 - Tricky: noisy signal (delay often varies considerably)
- Routers tell end hosts when they're congested
- Packet loss
 - > Fail-safe signal that TCP already has to detect
 - Complication: non-congestive loss (e.g., checksum errors)

Not all losses are the same

- Duplicate ACKs: isolated loss
 - Still getting ACKs
- Timeout: much more serious
 - Not enough dupacks
 - Must have suffered several losses
- Will adjust rate differently for each case

Rate adjustment

- Basic structure
 - Upon receipt of ACK (of new data): increase rate
 - Upon detection of loss: decrease rate
- How we increase/decrease the rate depends on the phase of congestion control we're in:
 - Discovering available bottleneck bandwidth vs.
 - Adjusting to bandwidth variations

Bandwidth discovery with "Slow Start"

- Goal: estimate available bandwidth
 - Start slow (for safety)
 - Ramp up quickly (for efficiency)
- Consider
 - > RTT = 100ms, MSS=1000bytes
 - Window size to fill 1Mbps of BW = 12.5 packets
 - Window size to fill 1Gbps = 12,500 packets
 - Either is possible!

Slow Start phase

- Sender starts at a slow rate, but increases exponentially until first loss
- Start with a small congestion window
 - Initially, CWND = 1
 - So, initial sending rate is MSS/RTT
- Double the CWND for each RTT with no loss


Slow Start in action

- For each RTT: double CWND
 - > i.e., for each ACK, CWND += 1

Linear increase per <u>ACK(CWND+1)</u> exponential increase per <u>RTT</u> (2*CWND)

Slow Start in action

- For each RTT: double CWND
 - > i.e., for each ACK, CWND += 1



When does Slow Start stop?

- Slow Start gives an estimate of available bandwidth
 - At some point, there will be loss
- Introduce a "slow start threshold" (ssthresh)
 - Initialized to a large value
- If CWND > ssthresh, stop Slow Start


Adjusting to varying bandwidth

- CWND > ssthresh
 - Stop rapid growth and focus on maintenance
- Now, want to track variations in this available bandwidth, oscillating around its current value
 - Repeated probing (rate increase) and backoff (decrease)
- TCP uses: "Additive Increase Multiplicative Decrease" (AIMD)

AIMD

- Additive increase
 - For each ACK, CWND = CWND+ 1/CWND
 - CWND is increased by one only if all segments in a CWND have been acknowledged
- Multiplicative decrease
 - > On packet loss, divide ssthresh in half and slow start
 - »ssthresh = CWND/2
 - **»**CWND = 1
 - »Initiate Slow Start
 - Note that we're ignoring the "dupAck" fix for now

Leads to the TCP "Sawtooth"



Why AIMD?

- Recall the three issues
 - Finding available bottleneck bandwidth
 - Adjusting to bandwidth variations
 - Sharing bandwidth


- Two goals for bandwidth sharing
 - Efficiency: High utilization of link bandwidth
 - Fairness: Each flow gets equal share

Why AIMD?


- Every RTT, we can do
 - Multiplicative increase or decrease: CWND→ a*CWND
 - ➤ Additive increase or decrease: CWND→ CWND + b
- Four alternatives:
 - > AIAD: gentle increase, gentle decrease
 - > AIMD: gentle increase, drastic decrease
 - MIAD: drastic increase, gentle decrease
 - MIMD: drastic increase and decrease

Simple model of congestion control

- Two users
 - rates x1 and x2
- Congestion when x1+x2 > 1
- Unused capacity
 when x1+x2 < 1
- Fair when x1 = x2



Example




AIAD

Increase: x + a_I

Decrease: x - a_D


Does not converge to fairness



User 1: x₁

AIAD Sharing Dynamics






MIMD

Increase: x*b_I

Decrease: x*b_D

 Does not converge to fairness

User 2: x₂




User 1: x₁

AIMD

• Increase: x+a₁

Decrease: x*b_D


Converges to fairness



User 1: x₁

AIMD Sharing Dynamics






MIAD

Increase: x*b_I

Decrease: x - a_D

- Does not converge to fairness
- Does not converge to efficiency
- "Analysis of the Increase and Decrease Algorithms for Congestion Avoidance in Computer Networks"
 - -- Chiu and Jain



User 1: x₁

Summary

- Flow control ensures that the sender does not overflow the receiver
- Congestion control ensures that the sender does not overflow the network
 - Discover bandwidth
 - Adjust to conditions
 - Share bandwidth with others