BANDWIDTH UTILIZATION -- MULTIPLEXING AND SPREADING

- 2.4 MULTIPLEXING
- When bandwidth of a medium is greater than bandwidth needs of the devices, the link can be shared.
- Multiplexing allows simultaneous transmission of multiple signals across a single data-link (Fig 4.21).
- The traffic increases, as data/telecommunications use increases.
- We can accommodate this increase by
 - \rightarrow adding individual links, each time a new channel is needed or \rightarrow installing higher-bandwidth links to carry multiple signals.
- Today's technology includes high-bandwidth media such as optical-fiber and satellite microwaves.
- Each has a bandwidth far in excess of that needed for the average transmission-signal.
- If the bandwidth of a link is greater than the bandwidth needs of the devices connected to it, the bandwidth is wasted.
- An efficient system maximizes the utilization of all resources; bandwidth is one of the most precious resources we have in data communications.




Figure 6.1 Dividing a link into channels

- In a multiplexed-system, "n" lines share the bandwidth of one link.
- MUX combines transmission-streams from different input-lines into a single stream (many-to-one).
- At the receiving-end, that stream is fed into a demultiplexer (DEMUX).
- DEMUX
 - \rightarrow separates the stream back into its component-transmissions (one-to-many) and \rightarrow directs the transmission-streams to different output-lines.
- Link vs. Channel:
 - 1) The link refers to the physical path.
 - 2) The channel refers to the portion of a link that carries a transmission between a given pair oflines. One link can have many channels.
- Three multiplexing techniques (Figure 6.2):
 - 1) Frequency-division multiplexing (FDM) 2) Wavelength-division multiplexing (WDM) and 3) Time-division multiplexing (TDM).
- The first two techniques are used for analog-signals.

The third one technique is used for digital-signals.




Figure 6.2 Categories of multiplexing

2.4.1 Frequency Division Multiplexing (FDM)

- FDM is an analog multiplexing technique that combines analog signals (Figure 6.3).
- FDM can be used when the bandwidth of a link is greater than the combined bandwidths of the signals to be transmitted. (Bandwidth measured in hertz).




Figure 6.3 Frequency-division multiplexing

2.4.1.1 Multiplexing Process

- Here is how it works (Figure 6.4):
 - 1) Each sending-device generates modulated-signals with different carrier-frequencies (f1, f2, & f3).
 - 2) Then, these modulated-signals are combined into a single multiplexed-signal. 3) Finally, the multiplexed-signal is transported by the link.




Figure 6.4 FDM process

- Carrier-frequencies are separated by sufficient bandwidth to accommodate the modulated-signal.
- Channels can be separated by strips of unused bandwidth called guard bands.
- Guard bands prevent signals from overlapping.
- In addition, carrier-frequencies must not interfere with the original data frequencies.
- Although FDM is considered as analog multiplexing technique, the sources can produce digital-signal.
- The digital-signal can be sampled, changed to analog-signal, and then multiplexed by using FDM.

2.4.1.2 Demultiplexing Process

- Here is how it works (Figure 6.5):
 - 1) The demultiplexer uses filters to divide the multiplexed-signal into individual-signals.
 - 2) Then, the individual signals are passed to a demodulator. 3) Finally, the demodulator
 - \rightarrow separates the individual signals from the carrier signals and \rightarrow passes the individual signals to the output-lines.





Figure 6.5 FDM demultiplexing example

Assume that a voice channel occupies a bandwidth of 4 kHz. We need to combine three voice channels into a link with a bandwidth of 12 kHz, from 20 to 32 kHz. Show the configuration, using the frequency domain. Assume there are no guard bands.

Solution

We shift (modulate) each of the three voice channels to a different bandwidth, as shown in Figure 6.6. We use the 20- to 24-kHz bandwidth for the first channel, the 24- to 28-kHz bandwidth for the second channel, and the 28- to 32-kHz bandwidth for the third one. Then we combine them as shown in Figure 6.6.




Example 2.13

Five channels, each with a 100-kHz bandwidth, are to be multiplexed together. What is the minimum bandwidth of the link if there is a need for a guard band of 10 kHz between the channels to prevent interference?

Solution


For five channels, we need at least four guard bands. This means that the required bandwidth is at least $5 \times 100 + 4 \times 10 = 540$ kHz, as shown in Figure 6.7.



Four data channels (digital), each transmitting at 1 Mbps, use a satellite channel of 1 MHz. Design an appropriate configuration, using FDM.

Solution

The satellite channel is analog. We divide it into four channels, each channel having a 250-kHz bandwidth. Each digital channel of 1 Mbps is modulated so that each 4 bits is modulated to 1 Hz. One solution is 16-QAM modulation. Figure 6.8 shows one possible configuration.



2.4.1.3 Applications of FDM

- 1) To maximize the efficiency of their infrastructure, Telephone-companies have traditionally multiplexed signals from lower-bandwidth lines onto higher-bandwidth lines.
- 2) A very common application of FDM is AM and FM radio broadcasting.
- 3) The first generation of cellular telephones (still in operation) also uses FDM.

2.4.1.4 Analog Carrier System

- To maximize the efficiency, telephone-companies have multiplexed-signals from lower-bandwidth lines onto higher-bandwidth lines.
- Many switched or leased lines are combined into bigger channels.
- For analog lines, FDM is used.
- One of these hierarchical systems used by AT&T is made up of (Figure 6.9):
 - 1) Groups
 - 2) Super groups
 - 3) Master groups, and
 - 4) Jumbo groups




Figure 6.9 Analog hierarchy

- **1) Group**: In the analog hierarchy, 12 voice channels are multiplexed onto a higher-bandwidth line to create a group.
 - A group has 48 kHz of bandwidth and supports 12 voice channels.

- **Super Group:** At the next level, up to five groups can be multiplexed to create a composite signal called a supergroup.
 - A supergroup has a bandwidth of 240 kHz and supports up to 60 voice channels.
 - Supergroups can be made up of either five groups or 60 independent voice channels. 3) **Master Groups:** At the next level, 10 supergroups are multiplexed to create a master group.
 - A master group must have 2.40 MHz of bandwidth, but the need for guard bands between the supergroups increases the necessary bandwidth to 2.52 MHz.
 - Master groups support up to 600 voice channels.
- 4) Jumbo Group: Finally, six master groups can be combined into a jumbo group.
 - A jumbo group must have 15.12 MHz (6 x 2.52 MHz) of bandwidth, but the need for guard bands b/w the master groups increases the necessary bandwidth to 16.984 MHz

The Advanced Mobile Phone System (AMPS) uses two bands. The first band of 824 to 849 MHz is used for sending, and 869 to 894 MHz is used for receiving. Each user has a bandwidth of 30 kHz in each direction. The 3-kHz voice is modulated using FM, creating 30 kHz of modulated signal. How many people can use their cellular phones simultaneously?

Solution

Each band is 25 MHz. If we divide 25 MHz by 30 kHz, we get 833.33. In reality, the band is divided into 832 channels. Of these, 42 channels are used for control, which means only 790 channels are available for cellular phone users.

2.4.2 Wavelength Division Multiplexing (WDM)

- WDM is an analog multiplexing technique that combines analog signals (Figure 6.10).
- WDM is designed to use the high-data-rate capability of fiber optical-cable.
- The data-rate of optical-cable is higher than the data-rate of metallic-cable.
- Using an optical-cable for one single line wastes the available bandwidth.
- Multiplexing allows combining several lines into one line.
- WDM is same as FDM with 2 exceptions:
 - 1) Multiplexing & demultiplexing involve optical-signals transmitted through optical-cable. 2) The frequencies are very high.




Figure 6.10 Wavelength-division multiplexing

- Here is how it works (Figure 6.11):
 - ☑ A multiplexer combines several narrow-bands of light into a wider-band of light.
 ☐ A demultiplexer divides a wider-band of light into several narrow-bands of light.
 ☐ A prism is used for combining and splitting of light sources
 - $\ \ \$ A prism bends a beam of light based on $\ \rightarrow$ angle of incidence and $\ \rightarrow$ frequency.




Figure 6.11 Prisms in wavelength-division multiplexing and demultiplexing

- Applications of WDM:
 - 1) SONET network: Multiple optical-fiber lines can be multiplexed and demultiplexed.
 - 2) Dense WDM (DWDM) can multiplex a very large number of channels by spacing channels very close to one another. DWDM achieves even greater efficiency

2.4.3 Time Division Multiplexing (TDM)

- TDM is a digital multiplexing technique that combines digital signals (Figure 6.12).
- TDM combines several low-rate channels into one high-rate one.
- FDM vs. TDM
 - 1) In FDM, a portion of the bandwidth is shared. 2) In TDM, a portion of the time is shared.
- Each connection occupies a portion of time in the link.
- Several connections share the high bandwidth of a line.





Figure 6.12 TDM

- As shown in Figure 6.12, the link is divided by time.
- Portions of signals 1, 2, 3, and 4 occupy the link sequentially.
- Digital-data from different sources are combined into one timeshared link.
- Although TDM is considered as digital multiplexing technique, the sources can produce analog-signal.
- The analog data can be sampled, changed to digital-data, and then multiplexed by using TDM.
- Two types of TDM: 1) Synchronous and 2) Statistical.

2.4.3.1 Synchronous TDM

2.4.3.1.1 Time Slots & Frames

- Each input-connection has an allotment in the output-connection even if it is not sending data.
- The data-flow of input-connection is divided into units (Figure 6.13).
- A unit can be 1 bit, 1 character, or 1 block of data.
- Each input-unit occupies one input-time-slot.
- Each input-unit
 - → becomes one output-unit and
 - → occupies one output-time-slot.
- However, duration of output-time-slot is ,,n" times shorter than duration of input-time-slot. If an input-time-slot is T s, the output-time-slot is T/n s where n = No. of connections.
- In the output-connection, a unit has a shorter duration & therefore travels faster.



- In Figure 6.14, n = 3.
- A set of data-units from each input-connection is grouped into a frame.
- For example:

If there are 3 connections, a frame is divided into 3 time-slots.

One slot is allocated for each data-unit.

One data-unit is used for each input-line.

In Figure 6.13, the data rate for each input connection is 1 kbps. If 1 bit at a time is multiplexed (a unit is 1 bit), what is the duration of

- each input slot,
- 2. each output slot, and
- 3. each frame?




Figure 6.13 Synchronous time-division multiplexing

Solution

We can answer the questions as follows:

- The data rate of each input connection is 1 kbps. This means that the bit duration is 1/1000 s
 or 1 ms. The duration of the input time slot is 1 ms (same as bit duration).
- The duration of each output time slot is one-third of the input time slot. This means that the duration of the output time slot is 1/3 ms.
- Each frame carries three output time slots. So the duration of a frame is 3 × 1/3 ms, or 1 ms.
 The duration of a frame is the same as the duration of an input unit.

Example 2.17

Figure 6.14 shows synchronous TDM with a data stream for each input and one data stream for the output. The unit of data is 1 bit. Find (1) the input bit duration, (2) the output bit duration, (3) the output bit rate, and (4) the output frame rate.




Figure 6.14

Solution

We can answer the questions as follows:

- 1. The input bit duration is the inverse of the bit rate: $1/1 \text{ Mbps} = 1 \mu s$.
- 2. The output bit duration is one-fourth of the input bit duration, or 1/4 µs.
- 3. The output bit rate is the inverse of the output bit duration, or 1/4 μs, or 4 Mbps. This can also be deduced from the fact that the output rate is 4 times as fast as any input rate; so the output rate = 4 × 1 Mbps = 4 Mbps.
- 4. The frame rate is always the same as any input rate. So the frame rate is 1,000,000 frames per second. Because we are sending 4 bits in each frame, we can verify the result of the previous question by multiplying the frame rate by the number of bits per frame.

Four 1-kbps connections are multiplexed together. A unit is 1 bit. Find (1) the duration of 1 bit before multiplexing, (2) the transmission rate of the link, (3) the duration of a time slot, and (4) the duration of a frame.

Solution


We can answer the questions as follows:


- 1. The duration of 1 bit before multiplexing is 1/1 kbps, or 0.001 s (1 ms).
- The rate of the link is 4 times the rate of a connection, or 4 kbps.
- 3. The duration of each time slot is one-fourth of the duration of each bit before multiplexing, or 1/4 ms or 250 µs. Note that we can also calculate this from the data rate of the link, 4 kbps. The bit duration is the inverse of the data rate, or 1/4 kbps or 250 µs.
- 4. The duration of a frame is always the same as the duration of a unit before multiplexing, or 1 ms. We can also calculate this in another way. Each frame in this case has four time slots. So the duration of a frame is 4 times 250 µs, or 1 ms.



2.4.3.1.2 Interleaving

- TDM can be seen as 2 fast-rotating switches (Figure 6.15): 1) First switch on the multiplexing-side and
 - 2) Second switch on the demultiplexing-side.
- The switches are synchronized and rotate at the same speed, but in opposite directions.
 - 1) On the multiplexing-side (Figure 6.16)
 - \Box As the switch opens in front of a connection, that connection has the opportunity to send a unit onto the path. This process is called *interleaving*.
 - 2) On the demultiplexing-side
 - ☐ As the switch opens in front of a connection, that connection has the opportunity to receive a unit from the path.





Four channels are multiplexed using TDM. If each channel sends 100 bytes/s and we multiplex 1 byte per channel, show the frame traveling on the link, the size of the frame, the duration of a frame, the frame rate, and the bit rate for the link.

Solution

The multiplexer is shown in Figure 6.16. Each frame carries 1 byte from each channel; the size of each frame, therefore, is 4 bytes, or 32 bits. Because each channel is sending 100 bytes/s and a frame carries 1 byte from each channel, the frame rate must be 100 frames per second. The duration of a frame is therefore 1/100 s. The link is carrying 100 frames per second, and since each frame contains 32 bits, the bit rate is 100×32 , or 3200 bps. This is actually 4 times the bit rate of each channel, which is $100 \times 8 = 800$ bps.




Figure 6.16

Example 2.20

A multiplexer combines four 100-kbps channels using a time slot of 2 bits. Show the output with four arbitrary inputs. What is the frame rate? What is the frame duration? What is the bit rate? What is the bit duration?

Solution

Figure 6.17 shows the output for four arbitrary inputs. The link carries 50,000 frames per second since each frame contains 2 bits per channel. The frame duration is therefore 1/50,000 s or $20 \,\mu s$. The frame rate is 50,000 frames per second, and each frame carries 8 bits; the bit rate is $50,000 \times 8 = 400,000$ bits or $400 \, kbps$. The bit duration is $1/400,000 \, s$, or $2.5 \, \mu s$. Note that the frame duration is 8 times the bit duration because each frame is carrying 8 bits.




Figure 6.17

2.4.3.1.3 Empty Slots

• Problem: Synchronous TDM is not efficient.

For example: If a source does not have data to send, the corresponding slot in the output-frame is empty.




Figure 6.18 Empty slots

• As shown in Figure 6.18,

Second input-line has no data to send Third input-line has discontinuous data.

• The first output-frame has 3 slots filled.

The second frame has 2 slots filled.

The third frame has 3 slots filled.

No frame is full.

• Solution: Statistical TDM can improve the efficiency by removing the empty slots from the frame.

2.4.3.1.4 Data Rate Management

- Problem in TDM: How to handle differences in the input data-rates?
- If data-rates are not the same, three strategies can be used.
- Three different strategies: 1) Multilevel multiplexing 2) Multiple-slot allocation and 3) Pulse stuffing

1) Multilevel Multiplexing

This technique is used when the data-rate of an input-line is a multiple of others.




Figure 6.19 Multilevel multiplexing

- For example:
- As shown in Figure 6.19, we have 2 inputs of 20 kbps and 3 inputs of 40 kbps.
 □ The first 2 input-lines can be multiplexed to provide a data-rate of 40 kbps.

2) Multiple Slot Allocation

Sometimes it is more efficient to allot more than 1 slot in a frame to a single input-line.




Figure 6.20 Multiple-slot multiplexing

For example:

Data-rate of multiple input-lines can be data-rate of one input-line.

- ☑ As shown in Figure 6.20, the input-line with a 50-kbps data-rate can be given 2 slots in the output-line.
- ☑ In first input line, serial-to-parallel converter is used. The converter creates two 25 kbps input lines out of one 50 kbps input line.

3) Pulse Stuffing

- Sometimes the bit-rates of sources are not multiple integers of each other. .". above 2 techniques cannot be used.
- ☑ Solution:

- \rightarrow Make the highest input data-rate the dominant data-rate. \rightarrow Then, add dummy bits to the input-lines with lower rates. \rightarrow This will increase data rates of input-line.
- → This technique is called pulse stuffing, bit padding, or bit stuffing.




Figure 6.21 Pulse stuffing

- As shown in Figure 6.21, the input-line with a lower data-rate = 46kbps is pulse-stuffed to increase the data-rate to 50 kbps.
- Now, multiplexing can take place.

2.4.3.1.5 Frame Synchronizing

• Problem: Synchronization between the multiplexer and demultiplexer is a major issue.

If the multiplexer and the demultiplexer are not synchronized, a bit belonging to one channel may be received by the wrong channel.

Solution: Usually, one or more synchronization-bits are added to the beginning of each frame. These bits are called *framing-bits*.

The framing-bits follow a pattern (frame-to-frame) that allows multiplexer and demultiplexer to synchronize.

As shown in Figure 6.22, the synchronization-information

 \rightarrow consists of 1 bit per frame and \rightarrow alternates between 0 & 1.




Figure 6.22 Framing bits

We have four sources, each creating 250 characters per second. If the interleaved unit is a character and 1 synchronizing bit is added to each frame, find (1) the data rate of each source, (2) the duration of each character in each source, (3) the frame rate, (4) the duration of each frame, (5) the number of bits in each frame, and (6) the data rate of the link.

Solution

We can answer the questions as follows:

- 1. The data rate of each source is $250 \times 8 = 2000$ bps = 2 kbps.
- Each source sends 250 characters per second; therefore, the duration of a character is 1/250 s, or 4 ms.
- Each frame has one character from each source, which means the link needs to send 250 frames per second to keep the transmission rate of each source.
- 4. The duration of each frame is 1/250 s, or 4 ms. Note that the duration of each frame is the same as the duration of each character coming from each source.
- Each frame carries 4 characters and 1 extra synchronizing bit. This means that each frame is 4 x 8 + 1 = 33 bits.
 - 6. The link sends 250 frames per second, and each frame contains 33 bits. This means that the data rate of the link is 250 × 33, or 8250 bps. Note that the bit rate of the link is greater than the combined bit rates of the four channels. If we add the bit rates of four channels, we get 8000 bps. Because 250 frames are traveling per second and each contains 1 extra bit for synchronizing, we need to add 250 to the sum to get 8250 bps.

Example 2.22

Two channels, one with a bit rate of 100 kbps and another with a bit rate of 200 kbps, are to be multiplexed. How this can be achieved? What is the frame rate? What is the frame duration? What is the bit rate of the link?

Solution

We can allocate one slot to the first channel and two slots to the second channel. Each frame carries 3 bits. The frame rate is 100,000 frames per second because it carries 1 bit from the first channel. The frame duration is 1/100,000 s, or 10 ms. The bit rate is 100,000 frames/s × 3 bits per frame, or 300 kbps. Note that because each frame carries 1 bit from the first channel, the bit rate for the first channel is preserved. The bit rate for the second channel is also preserved because each frame carries 2 bits from the second channel.

2.4.3.2 Statistical TDM

• Problem: Synchronous TDM is not efficient.

For ex: If a source does not have data to send, the corresponding slot in the output-frame is empty. Solution: Use statistical TDM.

Slots are dynamically allocated to improve bandwidth-efficiency.

Only when an input-line has data to send, the input-line is given a slot in the output-frame.

- The number of slots in each frame is less than the number of input-lines.
- The multiplexer checks each input-line in round robin fashion.

If the line has data to send;

Then, multiplexer allocates a slot for an input-line;

Otherwise, multiplexer skips the line and checks the next line.




Figure 6.26 TDM slot comparison

- In synchronous TDM (Figure 6.26a), some slots are empty because the corresponding line does not have data to send.
- In statistical TDM (Figure 6.26b), no slot is left empty.

1) Addressing

Synchronous TDM	Statistical TDM		
An output-slot needs to carry only data of the	An output-slot needs to carry both data &		
destination (Figure 6.26a).	address of the destination (Figure 6.26b).		
There is no need for addressing.	There is no fixed relationship between the inputs		
Synchronization and pre-assigned relationships	and outputs because there are no pre- assigned or		
between the inputs and outputs serve as an address.	reserved slots.		
	We need to include the address of the receiver		
	inside each slot to show where it is to be delivered.		

2) Slot Size

- ☑ Usually, a block of data is many bytes while the address is just a few bytes.
 ☐ A slot carries both data and address.
- Therefore, address-size must be very small when compared to data-size. This results in efficient transmission.
- For example:

It will be inefficient to send 1 bit per slot as data, when the address is 3 bits.

This means an overhead of 300%.

3) No Synchronization Bit

☐ In statistical TDM, the frames need not be synchronized, so synchronization-bits are not needed.

4) Bandwidth

 \square Normally, the capacity of the link is less than the sum of the capacities of each channel. \square The designers define the capacity of the link based on the statistics of the load for each channel.

2.5 SPREAD SPECTRUM

- Spread-spectrum is used in wireless applications (Figure 6.27).
- In wireless applications, all stations use air (or a vacuum) as the medium for communication.
- Goal: Stations must be able to share the air medium without interception by an attacker.

Solution: Spread-spectrum techniques add redundancy i.e. they spread the original spectrum needed for each station.

- If the required bandwidth for each station is B, spread-spectrum expands it to B_{ss} such that $B_{ss}>>B$.
- The expanded-bandwidth allows the source to place its message in a protective envelope for a more secure transmission.

(An analogy is the sending of a delicate, expensive gift. We can insert the gift in a special box to prevent it from being damaged during transportation).




Figure 6.27 Spread spectrum

- Spread-spectrum achieves its goal through 2 principles:
 - 1) The bandwidth allocated to each station needs to be, by far, larger than what is needed. This allows redundancy.
 - 2) The spreading process must occur after the signal is created by the source.
- After the signal is created by the source, the spreading process → uses a spreading-code and → spreads the bandwidth.
- The spreading-code is a series of numbers that look random, but are actually a pattern.
- Two types of spread-spectrum:
 - 1) Frequency hopping spread-spectrum (FHSS) and 2) Direct sequence spread-spectrum (DSSS).

2.5.1 Frequency Hopping Spread Spectrum (FHSS)

- This technique uses "M" different carrier-frequencies that are modulated by the source-signal.
- At one moment, the signal modulates one carrier-frequency.

At the next moment, the signal modulates another carrier-frequency.

- Although the modulation is done using one carrier-frequency at a time, 'M" frequencies are used in the long run.
- The bandwidth occupied by a source is given by




Figure 6.28 Frequency hopping spread spectrum (FHSS)

- As shown in Figure 6.28.
 - - \rightarrow uses the pattern to find the frequency to be used for this hopping period and \rightarrow passes the frequency to the frequency-synthesizer.





Figure 6.29 Frequency selection in FHSS

- As shown in Figure 6.29, assume we have 8 hopping frequencies.
 - \blacksquare Here, M = 8 and k = 3.
 - The pseudorandom code generator will create 8 different 3-bit patterns.
 - These are mapped to 8 different frequencies in the frequency table (see Figure 6.29). \Box The pattern for this station is 101, 111, 001, 000, 010, 111 & 100.
 - 1) At hopping-period 1, the pattern is 101.

The frequency selected is 700 kHz; the source-signal modulates this carrier-frequency. 2) At hopping-period 2, the pattern is 111.

The frequency selected is 900 kHz; the source-signal modulates this carrier-frequency.






Figure 6.31 Bandwidth sharing

• If there are many k-bit patterns & the hopping period is short, a sender & receiver can have privacy.

If an attacker tries to intercept the transmitted signal, he can only access a small piece of data because he does not know the spreading sequence to quickly adapt himself to the next hop.

• The scheme has also an anti-jamming effect.

A malicious sender may be able to send noise to jam the signal for one hopping period (randomly), but not for the whole period.

2.5.1.1 Bandwidth Sharing

- If the number of hopping frequencies is M, we can multiplex M channels into one by using the same B_{ss} bandwidth.
- This is possible because
 - 1) A station uses just one frequency in each hopping period. 2) Other M-1 stations uses other M-1 frequencies.
- In other words, M different stations can use the same B_{ss} if a multiple FSK (MFSK) is used.

2.5.2 Direct Sequence Spread Spectrum (DSSS)

- This technique expands the bandwidth of the original signal.
- Each data-bit is replaced with ,,n" bits using a spreading-code.
- Each bit is assigned a code of "n" bits called chips.
- The chip-rate is ,,n" times that of the data-bit (Figure 6.32).





Figure 6.32 DSSS

- For example (Figure 6.33):
 - \square Consider the Barker sequence used in a wireless LAN. Here n =11.
 - Assume that the original signal and the chips in the chip-generator use polar NRZ encoding. \Box The spreading-code is 11 chips having the pattern 10110111000.
 - If the original signal-rate is N, the rate of the spread signal is 1/N.
 - This means that the required bandwidth for the spread signal is 11 times larger than the bandwidth of the original signal.



- The spread signal can provide privacy if the attacker does not know the code.
- It can also provide immunity against interference if each station uses a different code.

2.5.2.1 Bandwidth Sharing

- Can we share a bandwidth in DSSS?
- The answer is no and yes.
 - 1) If we use a spreading-code that spreads signals that cannot be combined and separated, we cannot share a bandwidth.
 - \square For example:

Some wireless LANs use DSSS and the spread bandwidth cannot be shared.

- 2) If we use a special spreading-code that spreads signals that can be combined and separated, we can share a bandwidth.
- ☐ For example:

Cellular telephony uses DSSS and the spread bandwidth is shared b/w several users.

SWITCHING

2.6 SWITCHING

- A network is a set of connected-devices.
- Problem: Whenever we have multiple-devices, we have the problem of how to connect them to make one-to-one communication possible.
- Solution: Use Switching.
- A switched-network consists of a series of interlinked-nodes, called switches.
- Switches are devices capable of creating temporary connections between two or more devices.
- In a switched-network,
 - 1) Some nodes are connected to the end-systems (For example: PC or TP). 2) Some nodes are used only for routing.




Figure 8.1 Switched network

- As shown in Figure 8.1,
 - 1) The end-systems are labeled A, B, C, D, and so on.
 - 2) The switches are labeled I, II, III, IV, and V. Each switch is connected to multiple links.

2.6.1 Three Methods of Switching

- Three methods of Switching are (Figure 8.2):
 - 1) Circuit Switching 2)

Packet Switching and

- 3) Message Switching.
- The first two are commonly used today.
- The third has been phased out in general communications but still has networking applications.
- Packet switching can further be divided into two subcategories—virtual circuit approach and datagram approach




Figure 8.2 Taxonomy of switched networks

2.6.2 Switching and TCP/IP Layers

• Switching can happen at several layers of the TCP/IP protocol suite.

1) Switching at Physical Layer

- At the physical layer, we can have only circuit switching.
- There are no packets exchanged at the physical layer.
- The switches at the physical layer allow signals to travel in one path or another.

2) Switching at Data-Link Layer

- At the data-link layer, we can have packet switching.
- However, the term packet in this case means frames or cells.
- 2 Packet switching at the data-link layer is normally done using a virtual-circuit approach.

3) Switching at Network Layer

- At the network layer, we can have packet switching.
- In this case, either a virtual-circuit approach or a datagram approach can be used.
- © Currently the Internet uses a datagram approach, but the tendency is to move to a virtual circuit approach.

4) Switching at Application Layer

- At the application layer, we can have only message switching.
- The communication at the application layer occurs by exchanging messages.
- Conceptually, we can say that communication using e-mail is a kind of message-switched communication, but we do not see any network that actually can be called a message-switched network.

2.7 CIRCUIT SWITCHED NETWORK

• This is similar to telephone system.

- Fixed path (connection) is established between a source and a destination prior to the transfer of packets.
- A circuit-switched-network consists of a set of switches connected by physical-links (Figure 8.3).
- A connection between 2 stations is a dedicated-path made of one or more links.
- However, each connection uses only one dedicated-channel on each link.
- Normally, each link is divided into ,,n" channels by using FDM or TDM.
- The resources need to be reserved during the setup phase.

The resources remain dedicated for the entire duration of data transfer until the teardown phase.




Figure 8.3 A trivial circuit-switched network

- The virtual-circuit setup procedure
 - → first determines a path through the network &
 - → sets parameters in the switches by exchanging connect-request & connect-confirm messages
- If a switch does not have enough resources to set up a virtual circuit, the switch responds with a connect-reject message and the setup procedure fails (Figure 7.15).
- A connection-release procedure may also be required to terminate the connection.

2.7.1 Three Phases

• The communication requires 3 phases: 1) Connection-setup

2) Data-transfer 3)Connection teardown.

1) Setup Phase

- Before the 2 parties can communicate, a dedicated-circuit needs to be established.
- Normally, the end-systems are connected through dedicated-lines to the switches.

So, connection-setup means creating dedicated-channels between the switches.

- For ex: Assume system-A needs to connect to system-M. For this, following events occur:
 - i) System-A sends a setup-request to switch-I.
 - ii) Switch-I finds a channel between itself and switch-IV that can be dedicated for this purpose.
 - iii) Switch-I then sends the request to switch-IV, which finds a dedicated-channel between itself and switch-III.
 - iv) Switch-III informs system-M of system-A's intention at this time.
 - v) Finally, an acknowledgment from system-M needs to be sent in the opposite direction to system-A.
- Only after system A receives this acknowledgment is the connection established.

2) Data Transfer Phase

- After the establishment of the dedicated-circuit (channels), the two parties can transfer data. 3)

 Teardown Phase
- When one of the parties needs to disconnect, a signal is sent to each switch to release the resources.

2.7.2 Efficiency

• Circuit-switched-networks are inefficient when compared to other two types of networks because 1) Resources are allocated during the entire duration of the connection. 2) These resources are unavailable to other connections.

2.7.3 Delay

- Circuit-switched-networks have minimum delay when compared to other two types of networks During data-transfer,
 - 1) The data are not delayed at each switch.
 - 2) The resources are allocated for the duration of the connection.




Figure 8.6 Delay in a circuit-switched network

- ☑ As in the above figure, there is no waiting time at each switch. □
 The total delay is the time needed to
 - 1) Create the connection 2) Transfer-data and
 - 3) Disconnect the circuit.
- The delay caused by the setup is the sum of 4 parts:
 - 1) The propagation time of the source-computer request.
 - 2) The request signal transfer time.
 - 3) The propagation time of the acknowledgment from the destination computer. 4) The signal transfer time of the acknowledgment.
- The delay due to data-transfer is the sum of 2 parts:
 - 1) The propagation time.
 - 2) Data-transfer time which can be very long.

2.8 PACKET SWITCHED NETWORK

- The message is divided into packets of fixed or variable size.
- The packet-size is determined by \rightarrow network and
 - \rightarrow governing protocol.
- There is no resource reservation; resources are allocated on-demand.

2.8.1 Datagram Networks

- This is analogous to postal system.
- Each packet is routed independently through the network.
- Each packet has a header that contains source and destination addresses.
- Each switch examines the header to determine the next hop in the path to the destination.
- If the transmission line is busy then the packet is placed in the queue until the line becomes free.
- Packets are referred to as datagrams.
- Datagram switching is normally done at the network layer.
- In Internet, switching is done by using the datagram switching.
- Advantage:
 - 1) High utilization of transmission-line can be achieved by sharing among multiple packets.
- Disadvantages:
 - 1) Packets may arrive out-of-order, and re-sequencing may be required at the destination
 - 2) Loss of packets may occur when a switch has insufficient buffer




Figure 8.7 A datagram network with four switches (routers)

- ☐ The Figure 8.7 shows how the 4 packets are transferred from station-A to station-X. ☐ The switches are referred to as routers.
- All four packets (or datagrams) belong to the same message, but may travel different paths to reach their destination.
- This is so because the links may be involved in carrying packets from other sources and do not have the necessary bandwidth available to carry all the packets from A to X.
- This approach can cause the datagrams of a transmission to arrive at their destination out-of- order with different delays between the packets.
- Packets may also be lost or dropped because of a lack-of-resources.

It is the responsibility of an upper-layer protocol to

- \rightarrow reorder the datagrams or \rightarrow
- ask for lost datagrams.
- The datagram-networks are referred to as connectionless networks. This is because 1) The switch does not keep information about the connection state.
 - 2) There are no setup or teardown phases.
 - 3) Each packet is treated the same by a switch regardless of its source or destination.

2.8.1.1 Routing Table

- Each switch has a routing-table which is based on the destination-address.
- The routing-tables are dynamic & updated periodically.

• The destination-addresses and the corresponding forwarding output-ports are recorded in the tables.




Figure 8.8 Routing table in a datagram network

2.8.1.1.1 Destination Address

- Every packet carries a header that contains the destination-address of the packet.
- When the switch receives the packet,
 - → This destination-address is examined.
 - → The routing-table is consulted to find the corresponding port through which the packet should be forwarded
- The destination address in the header of a packet in remains the same during the entire journey of the packet.

2.8.1.1.2 Efficiency

- Datagram-networks are more efficient when compared to circuit-switched-network. This is because 1) Resources are allocated only when there are packets to be transferred.
 - 2) If a source sends a packet and there is a delay of a few minutes before another packet can be sent, the resources can be re-allocated during these minutes for other packets from other sources.

2.8.1.1.3 Delay

- Datagram-networks may have greater delay when compared to circuit-switched-network. This is because
 - 1) Each packet may experience a wait at a switch before it is forwarded.
 - 2) Since not all packets in a message necessarily travel through the same switches, the delay is notuniform for the packets of a message.




Figure 8.9 Delay in a datagram network

- \square The Figure 8.9 gives an example of delay for one single packet. \square The packet travels through two switches.
- There are three transmission times (3T), three propagation delays (slopes 3t of the lines), and two waiting times (W1+ W2).

Total delay = $3T + 3\tau + w_1 + w_2$

2.8.2 Virtual Circuit Network (VCN)

This is similar to telephone system.

- A virtual-circuit network is a combination of circuit-switched-network and datagram-network.
- Five characteristics of VCN:
 - 1) As in a circuit-switched-network, there are setup & teardown phases in addition to the data transfer phase.
 - 2) As in a circuit-switched-network, resources can be allocated during the setup phase.

As in a datagram-network, resources can also be allocated on-demand.

3) As in a datagram-network, data is divided into packets.

Each packet carries an address in the header.

However, the address in the header has local jurisdiction, not end-to-end jurisdiction. 4) As in a circuit-switched-network, all packets follow the same path established during the connection.

5) A virtual-circuit network is implemented in the data link layer.

A circuit-switched-network is implemented in the physical layer.

A datagram-network is implemented in the network layer.




Figure 8.10 Virtual-circuit network

- ☐ The Figure 8.10 is an example of a virtual-circuit network.
- The network has switches that allow traffic from sources to destinations.
- A source or destination can be a computer, packet switch, bridge, or any other device that connects other networks.

2.8.2.1 Addressing

• Two types of addressing: 1) Global and 2) Local (virtual-circuit identifier).

1) Global Addressing

- A source or a destination needs to have a global address.
- Global address is an address that can be unique in the scope of the network or internationally if the network is part of an international network.

2) Virtual Circuit Identifier

- ☑ The identifier used for data-transfer is called the virtual-circuit identifier (VCI). □ A VCI, unlike a global address, is a small number that has only switch scope. □ VCI is used by a frame between two switches.
- When a frame arrives at a switch, it has a VCI.

When the frame leaves, it has a different VCI.




Figure 8.11 Virtual-circuit identifier

2 Figure 8.11 show how the VCI in a data-frame changes from one switch to another.

2.8.2.2 Three Phases

- A source and destination need to go through 3 phases: setup, data-transfer, and teardown.
 - 1) In setup phase, the source and destination use their global addresses to help switchesmake table entries for the connection.
 - 2) In the teardown phase, the source and destination inform the switches to delete the corresponding entry.
 - 3) Data-transfer occurs between these 2 phases.

2.8.2.2.1 Data Transfer Phase

- To transfer a frame from a source to its destination, all switches need to have a table-entry for this virtual-circuit.
- The table has four columns.
- The switch holds 4 pieces of information for each virtual-circuit that is already set up.




Figure 8.12 Switch and tables in a virtual-circuit network

- As shown in Figure 8.12, a frame arrives at port 1 with a VCI of 14.
- When the frame arrives, the switch looks in its table to find port 1 and a VCI of 14.
- When it is found, the switch knows to change the VCI to 22 & send out the frame from port 3.




Figure 8.13 Source-to-destination data transfer in a virtual-circuit network

- As shown in Figure 8.13, each switch changes the VCI and routes the frame.
- The data-transfer phase is active until the source sends all its frames to the destination.
- The procedure at the switch is the same for each frame of a message.
- The process creates a virtual circuit, not a real circuit, between the source and destination.

2.8.2.2.2 Setup Phase

- A switch creates an entry for a virtual-circuit.
- For example, suppose source A needs to create a virtual-circuit to B. Two steps are required: 1) Setup-request and 2) Acknowledgment.

1) Setup Request

A setup-request frame is sent from the source to the destination (Figure 8.14).




Figure 8.14 Setup request in a virtual-circuit network

- Following events occurs:
 - **a)** Source-A sends a setup-frame to switch-1.
 - **b)** Switch-1 receives the setup-frame.

¤ Switch-1 knows that a frame going from A to B goes out through port 3. ¤ The switch-1 has a routing table. ¤ The switch

- → creates an entry in its table for this virtual-circuit
- \rightarrow is only able to fill 3 of the 4 columns.
- ¤ The switch

- \rightarrow assigns the incoming port (1) and
- \rightarrow chooses an available incoming-VCI (14) and the outgoing-port (3). \rightarrow does not yet know the outgoing VCI, which will be found during the acknowledgment step.
- ^I The switch then forwards the frame through port-3 to switch-2.
- **c)** Switch-2 receives the setup-request frame.
 - ¤ The same events happen here as at switch-1.
 - ¤ Three columns of the table are completed: In this case, incoming port (1), incoming-VCI (66), and outgoing port (2).
- **d)** Switch-3 receives the setup-request frame.
 - x Again, three columns are completed: incoming port (2), incoming-VCI (22), and outgoing-port (3).
- e) Destination-B
 - → receives the setup-frame
 - → assigns a VCI to the incoming frames that come from A, in this case 77.

 This VCI lets the destination know that the frames come from A, and no other sources.

2) Acknowledgment

☐ A special frame, called the acknowledgment-frame, completes the entries in the switchingtables (Figure 8.15).




Figure 8.15 Setup acknowledgment in a virtual-circuit network

- **a)** The destination sends an acknowledgment to switch-3.
 - ¤ The acknowledgment carries the global source and destination-addresses so the switch knows which entry in the table is to be completed.
 - ^{II} The frame also carries VCI 77, chosen by the destination as the incoming-VCI for frames from A.
 - x Switch 3 uses this VCI to complete the outgoing VCI column for this entry.
- **b)** Switch 3 sends an acknowledgment to switch-2 that contains its incoming-VCI in the table, chosen in the previous step.
 - ¤ Switch-2 uses this as the outgoing VCI in the table.
- **c)** Switch-2 sends an acknowledgment to switch-1 that contains its incoming-VCI in the table, chosen in the previous step.
 - ¤ Switch-1 uses this as the outgoing VCI in the table.

- **d)** Finally switch-1 sends an acknowledgment to source-A that contains its incoming-VCI in the table, chosen in the previous step.
- **e)** The source uses this as the outgoing VCI for the data-frames to be sent to destination-B.

2.8.2.3 Teardown Phase

- Source-A, after sending all frames to B, sends a special frame called a teardown request.
- Destination-B responds with a teardown confirmation frame.
- All switches delete the corresponding entry from their tables.

2.8.2.4 Efficiency

- Resource reservation can be made in 2 cases:
 - 1) During the setup: Here, the delay for each packet is the same.
 - 2) On demand: Here, each packet may encounter different delays.
- Advantage of on demand resource allocation:

The source can check the availability of the resources, without actually reserving it.

2.8.2.5 Delay in Virtual Circuit Networks

- There is a one-time delay for setup and a one-time delay for teardown (Figure 8.16).
- If resources are allocated during the setup phase, there is no wait time for individual packets.
- The packet is traveling through two switches (routers).
- There are three transmission times (3T), three propagation times (3τ), data transfer delay, a setup delay and a teardown delay.
- The total delay time is

Total delay $+3T + 3\tau + \text{setup delay} + \text{teardown delay}$

Circuit Switching	Datagram Packet Switching	Virtual circuit Packet switching	
Dedicate transmission path	No dedicate path	No dedicate path	
Continuous transmission of data	Transmission of packets	Transmission of packets	
Fast enough for interactive	Fast enough for interactive		
Message are not stored	Packets may be stored until delivered	Packets stored until delivered	
The path is established for entire conversation	Route established for each packet	Route established for entire conversation	
Call setup delay; negligible transmission delay	Packet transmission delay	Call setup delay; Packet transmission delay	
Busy signal if called party busy	Sender may be notified if packet not delivered	Sender notified of connection denial	
Overload may block call setup; no delay for established calls	Overload increases packet delay	Overload may block call setup; increases packet delay	
Electromechanical or computerized switching nodes	Small switching nodes	Small switching nodes	
User responsible for message loss protection	Network may be responsible for individual packets	Network may be responsible for packet sequences	
Usually no speed or code conversion	Speed and code conversion	Speed and code conversion	
Fixed bandwidth	Dynamic use of bandwidth	Dynamic use of bandwidth	
No overhead bits after call setup			