IBM Resilient



Incident Response Platform Integrations

McAfee Publish to DXL Function V1.0.0

Release Date: April 2018

Resilient Functions simplify development of integrations by wrapping each activity into an individual workflow component. These components can be easily installed, then used and combined in Resilient workflows. The Resilient platform sends data to the function component that performs an activity then returns the results to the workflow. The results can be acted upon by scripts, rules, and workflow decision points to dynamically orchestrate the security incident response activities.

This guide describes the McAfee Publish to DXL Function.

Overview

The McAfee Publish to DXL function contains the ability to publish a message to an event or a service.

This document describes the McAfee Publish to DXL function, how to configure it in custom workflows, and additional customization options.

Installation

Before installing, verify that your environment meets the following prerequisites:

- Resilient platform is version 30 or later.
- You have a Resilient account to use for the integrations. This can be any account that has
 the permission to view and modify administrator and customization settings, and read and
 update incidents. You need to know the account username and password.
- You have access to the command line of the Resilient appliance, which hosts the Resilient platform; or to a separate integration server where you will deploy and run the functions code. If using a separate integration server, you must install Python version 2.7.10 or later, or version 3.6 or later, and "pip". (The Resilient appliance is preconfigured with a suitable version of Python).

Install the Python components

The functions package contains Python components that will be called by the Resilient platform to execute the functions during your workflows. These components run in the 'resilient-circuits' integration framework.

The package also includes Resilient customizations that will be imported into the platform later.

Ensure that the environment is up to date,

```
sudo pip install --upgrade pip
sudo pip install --upgrade setuptools
sudo pip install --upgrade resilient-circuits
```

To install the package:

```
sudo pip install --upgrade fn mcafee opendxl-<1.0.0>.tar.gz
```

Configure the Python components

The 'resilient-circuits' components run as an unprivileged user, typically named `integration`. If you do not already have an `integration` user configured on your appliance, create it now.

Perform the following to configure and run the integration:

1. Using 'sudo', become the integration user.

```
sudo su - integration
```

2. Create or update the resilient-circuits configuration file.

```
or
resilient-circuits config -c
resilient-circuits config -u
```

- 3. Edit the resilient-circuits configuration file.
 - a. In the [resilient] section, ensure that you provide all the information needed to connect to the Resilient platform.
 - b. In the [fn mcafee opendxl] section, edit the settings as required.

```
dxlclient config=<absolute path to dxl config file>
```

More information on the config file and provisioning the system can be found here:

https://opendxl.github.io/opendxl-client-python/pydoc/provisioningoverview.html

Deploy customizations to the Resilient platform

The package contains the function definition that you can use in workflows, and an example workflow and rule that show how to use the function.

Install these customizations to the Resilient platform with the following command:

```
resilient-circuits customize
```

Answer the prompts to import the function, message destination, workflow and rule. The following data will be imported.

```
Function inputs: mcafee_dxl_payload, mcafee_publish_method,
mcafee_wait_for_response, mcafee_topic_name
Message Destination: McAfee DXL Message Destination
Function: McAfee TIE search hash
Workflow: (Example) McAfee Publish to DXL (Set TIE Reputation), (Example)
McAfee Publish to DXL (Tag System)
Rule: (Example) McAfee Publish to DXL (Set TIE Reputation Known
Malicious), (Example) McAfee Publish to DXL (Tag System Shut Down)
```

Run the integration framework

To test the integration package before running it in a production environment, you must run the integration manually with the following command:

```
resilient-circuits run
```

The resilient-circuits command starts, loads its components, and continues to run until interrupted. If it stops immediately with an error message, check your configuration values and retry. The following shows a successful connection to the Resilient platform and loading of components.

```
2018-04-12 12:33:49,971 INFO [app] Resilient server: 9.108.163.117
2018-04-12 12:33:49,972 INFO [app] Resilient org: TestOrg
2018-04-12 12:33:49,972 INFO [app] Logging Level: INFO
2018-04-12 12:33:49,973 WARNING [co3] Unverified HTTPS requests
(cafile=false).
2018-04-12 12:33:50,317 INFO [app] Components auto-load directory: (none)
2018-04-12 12:33:50,479 INFO [component_loader] Loading 1 components
2018-04-12 12:33:50,480 INFO [component_loader]
'fn mcafee opendxl.components.mcafee publish to dxl.FunctionComponent'
loading
2018-04-12 12:33:50,483 INFO [client] Waiting for broker list...
2018-04-12 12:33:50,521 INFO [client] Trying to connect...
2018-04-12 12:33:50,522 INFO [client] Trying to connect to broker {Unique
id: {brokerID}, Host name: tieserver.resilientsystems, IP address: <IP
Address>, Port: 8883}...
2018-04-12 12:33:50,558 INFO [client] Connected to broker {borkerID}
2018-04-12 12:33:50,606 WARNING [actions component] Unverified STOMP TLS
certificate (cafile=false)
2018-04-12 12:33:50,607 INFO [stomp component] Connect to
9.108.163.117:65001
2018-04-12 12:33:50,608 INFO [actions component]
'fn mcafee opendxl.components.mcafee publish to dxl.FunctionComponent'
function 'mcafee publish to dxl' registered to
'mcafee_dxl_message_destination'
2018-04-12 12:33:50,609 INFO [app] Components loaded
2018-04-12 12:33:50,610 INFO [app] App Started
2018-04-12 12:33:50,716 INFO [actions component] STOMP attempting to
connect
2018-04-12 12:33:50,717 INFO [stomp component] Connect to Stomp...
2018-04-12 12:33:50,717 INFO [client] Connecting to 9.108.163.117:65001
```

```
2018-04-12 12:33:50,757 INFO [client] Connection established
2018-04-12 12:33:50,858 INFO [client] Connected to stomp broker
[session=ID:resilient.localdomain-45666-1523378546811-5:11, version=1.2]
2018-04-12 12:33:50,858 INFO [stomp_component] Connected to
failover: (ssl://9.108.163.117:65001) ?maxReconnectAttempts=1, startupMaxReco
nnectAttempts=1
2018-04-12 12:33:50,858 INFO [stomp component] Client HB: 0 Server HB:
2018-04-12 12:33:50,858 INFO [stomp component] No Client heartbeats will
be sent
2018-04-12 12:33:50,859 INFO [stomp component] Requested heartbeats from
server.
2018-04-12 12:33:50,860 INFO [actions component] STOMP connected.
2018-04-12 12:33:50,961 INFO [actions component] Subscribe to message
destination 'mcafee dxl message destination'
2018-04-12 12:33:50,962 INFO [stomp component] Subscribe to message
destination actions.<orgID>.mcafee dxl message destination
```

For normal operation, resilient-circuits must run <u>continuously</u>. The recommend way to do this is to configure it to automatically run at startup. On a Red Hat appliance, this is done using a systemd unit file such as the one below. You may need to change the paths to your working directory and app.config.

The unit file should be named 'resilient circuits.service':

```
sudo vi /etc/systemd/system/resilient circuits.service
```

The contents:

```
[Unit]
Description=Resilient-Circuits Service
After=resilient.service
Requires=resilient.service
[Service]
Type=simple
User=integration
WorkingDirectory=/home/integration
ExecStart=/usr/local/bin/resilient-circuits run
Restart=always
TimeoutSec=10
Environment=APP_CONFIG_FILE=/home/integration/.resilient/app.config
Environment=APP_LOCK_FILE=/home/integration/.resilient/resilient_circuits.lock
[Install]
WantedBy=multi-user.target
```

Ensure that the service unit file is correctly permissioned:

```
sudo chmod 664 /etc/systemd/system/resilient circuits.service
```

Use the systematl command to manually start, stop, restart and return status on the service:

```
sudo systemctl resilient circuits [start|stop|restart|status]
```


Log files for systemd and the resilient-circuits service can be viewed through the journalctl command:

```
sudo journalctl -u resilient circuits --since "2 hours ago"
```

Function Description

Once the function package deploys the function, you can view it in the Resilient platform Functions tab. You can see the function details by clicking its name, as shown in the following screenshot.

Customization Settings



It also includes example workflows and rules that show how the function can be used. You can copy and modify these workflows and rules for your own needs.


Fn_mcafee_opendxl: McAfee Publish to DXL

This function takes four inputs:

```
mcafee_topic_name: Name of the topic to publish the payload to
mcafee_dxl_payload: The payload to be published.
mcafee_publish_method: Use a Service or Event
mcafee_wait_for_response: Wait for a response, only relevant if using a
Service
```

Based on the inputs, the function publishes the payload to the topic to an event or a service and then waits for a response or continues right away. The packaged examples include setting a file reputation for a provider in TIE and tagging a system in ePO. The examples when triggered will then create an incident note showing the inputs as shown below. Note to run the "(Example) McAfee Publish to DXL (Tag System)" workflow your own topic will have to be run which can be done using the following https://github.com/opendxl/opendxl-epo-service-python.

Notes



Troubleshooting

There are several ways to verify the successful operation of a function.

· Resilient Action Status

When viewing an incident, use the Actions menu to view Action Status. By default, pending and errors are displayed. Modify the filter for actions to also show Completed actions. Clicking on an action displays additional information on the progress made or what error occurred.

Resilient Scripting Log

A separate log file is available to review scripting errors. This is useful when issues occur in the pre-processing or post-processing scripts. The default location for this log file is: /var/log/resilient-scripting/resilient-scripting.log.

Resilient Logs

By default, Resilient logs are retained at /usr/share/co3/logs. The client.log may contain additional information regarding the execution of functions.

· Resilient-Circuits

The log is controlled in the <code>.resilient/app.config</code> file under the section <code>[resilient]</code> and the property <code>logdir</code>. The default file name is <code>app.log</code>. Each function will create progress information. Failures will show up as errors and may contain python trace statements.

Support

For additional support, contact $\underline{support@resilient systems.com}.$

Including relevant information from the log files will help us resolve your issue.