

# **MAGIC** Documentation

Release 5.6

The MAGIC dev team

# **CONTENTS**

1	Introduction	1
	1.1 Foreword	1
	1.2 Giving credit	2
2	Get MagIC and run it	3
	2.1 Download the code	3
	2.2 Setting up the environment variables	3
	2.3 Setting up compiler options and compiling	4
	2.4 Preparing a production run	6
3	Formulation of the (magneto)-hydrodynamics problem	7
	3.1 The reference state	8
	3.2 Boussinesq approximation	10
	3.3 Anelastic approximation	11
	3.4 Dimensionless control parameters	13
	3.5 Boundary conditions and treatment of inner core	15
4	Numerical technique	17
	4.1 Poloidal/toroidal decomposition	17
	4.2 Spherical harmonic representation	18
	4.3 Radial representation	21
	4.4 Spectral equations	22
	4.5 Time-stepping schemes	27
	4.6 Coriolis force and nonlinear terms	29
	4.7 Boundary conditions and inner core	34
5	Contributing to the code	39
	5.1 Checking the consistency of the code	39
	5.2 Advices when contributing to the code	40
	5.3 Building the documentation and contributing to it	41
6	Input parameters	43
	6.1 Grid namelist	45
	6.2 Control namelist	46
	6.3 Physical parameters namelist	50
	6.4 External Magnetic Field Namelist	58
	6.5 Start field namelist	59
	6.6 Output control namelist	62
	6.7 Mantle and Inner Core Namelists	75
7	Interactive communication with the code using signal. TAG	<b>7</b> 9

8	Outp	ut files	81
	8.1	Log file: log.TAG	83
	8.2	Default time-series outputs	83
	8.3	Additional optional time-series outputs	87
	8.4	Time-averaged radial profiles	95
	8.5	Transport properties of the reference state	
	8.6	Nonlinear mapping of the Chebyshev grid	102
	8.7	Spectra	102
	8.8	Graphic files G_#.TAG and G_ave.TAG	107
	8.9	Movie files *_mov.TAG	114
	8.10	Restart files checkpoint_*.TAG	117
	8.11	Poloidal and toroidal potentials at given depths	119
	8.12	TO outputs	124
	8.13	Radial spectra rB[r p]Spec.TAG	
	8.14	Potential files [V B T]_lmr_#.TAG	127
9	Data	visualisation and post-processing	133
	9.1	Requirements	133
	9.2	Configuration: magic.cfg file	
	9.3	Python functions and classes	135
	_		
10		ription of the Fortran modules	177
	10.1	Main program magic.f90	
	10.2	Base modules	
	10.3	MPI related modules	
	10.4	Code initialization	
	10.5	Pre-calculations	
	10.6	Time stepping	
	10.7	Linear calculation part of the time stepping (LMLoop)	
	10.8	Non-linear part of the time stepping (radial loop)	
		Chebyshev polynomials and cosine transforms	
		Legendre transforms	
		Fourier transforms	
		Linear algebra	
		Radial derivatives and integration	
		Blocking and LM mapping	
	10.15	IO: time series, radial profiles and spectra	318
	10.16	IO: graphic files, movie files, coeff files and potential files	346
	10.17	IO: RMS force balance, torsional oscillations, misc	369
	10.18	Reading and storing check points (restart files)	412
	10.19	Useful additional libraries	420
Fo	rtran l	Module Index	427
		Aodule Index	429
Ť		AVUILL HIGGS	
in	dex		431

### INTRODUCTION

### 1.1 Foreword

**MagIC** is a numerical code that can simulate fluid dynamics in a spherical shell. MagIC solves for the Navier-Stokes equation including Coriolis force, optionally coupled with an induction equation for Magneto-Hydro Dynamics (MHD), a temperature (or entropy) equation and an equation for chemical composition under both the anelastic and the Boussinesq approximations.

**MagIC** uses Chebyshev polynomials in the radial direction and spherical harmonic decomposition in the azimuthal and latitudinal directions. The time-stepping scheme relies on a semi-implicit Crank-Nicolson for the linear terms of the MHD equations and a Adams-Bashforth scheme for the non-linear terms and the Coriolis force.

**MagIC** is written in Fortran and designed to be used on supercomputing clusters. It thus relies on a hybrid parallelisation scheme using both OpenMP and MPI. Postprocessing functions written in python (requiring matplotlib and scipy) are also provided to allow a useful data analysis.




Fig. 1: Mean walltime of the MagIC code on the supercomputer stampede versus number of CPUs for a dynamo model computed at three different numerical resolutions  $(N_{\phi}, N_{\theta}, N_r)$ . The solid black lines show the ideal scalings.

MagIC is a free software. It can be used, modified and redistributed under the terms of the GNU GPL v3 licence.

# 1.2 Giving credit

In case you intend to publish scientific results obtained with the MagIC code or present them in a conference, we (the developers of MagIC) kindly ask to be acknowledged with a reference to the website https://magic-sph.github.io/ or https://github.com/magic-sph/magic.

We also suggest to give appropriate reference to one or several of the following papers:

- Boussinesq equations: Wicht (2002, PEPI, 132, 281-302)
- Anelastic equations: Gastine & Wicht (2012, Icarus, 219, 28-442)
- Boussinesq benchmark: Christensen et al. (2001, PEPI, 128, 25-34)
- Benchmark for double diffusive convection: Breuer et al. (2010, GJI, 183, 150-162)
- Anelastic benchmark: Jones et al. (2011, Icarus, 216, 120-135)
- In case you use the SHTns library for the spherical harmonics transforms (MagIC 5.3 or later), please also cite: Schaeffer (2013, GGG, 14, 751-758)

#### See also:

A (tentative) comprehensive list of the publications that have been produced to date (october 2015) using **MagIC** is accessible here. To date, more than **70 publications** have been-accepted in more than 10 different peer-reviewed journals: PEPI (19), Icarus (10), E&PSL (6), GJI (6), A&A (4), GRL (4), JFM (3), GAFD (3), Nature (2), etc.




Fig. 2: Number of peer-reviewed publications produced using MagIC

**CHAPTER** 

**TWO** 

### **GET MAGIC AND RUN IT**

### 2.1 Download the code

You can download a snapshot of the code from the Git repository using

```
$ git clone https://github.com/magic-sph/magic.git
```

In case you already have an account on github.com and uploaded a public SSH key on it, you could then rather use SSH:

```
$ git clone ssh://git@github.com/magic-sph/magic.git
```

# 2.2 Setting up the environment variables

Although not mandatory, it is strongly recommended to correctly source the environment variables of the MagIC code. It will ensure a smoother usage of the post-processing *python classes* and allow to run the *auto-test suite*. To do that, just go to the root directory of the MagIC code (magic) and source sourceme file that corresponds to your \$SHELL environment variable.

In case you use bash, ksh or zsh, just use:

```
$ source sourceme.sh
```

In case you use csh or tcsh, rather use

```
$ source sourceme.csh
```

You can make sure that the environment variables have been correctly sourced by typing:

```
$ echo $MAGIC_HOME
$ echo $PYTHONPATH
```

If you don't want to source sourceme.[c]sh on each session, you can add the following into your . bash\_profile (or .profile or .zprofile or .cshrc):

```
$ source whereverYouCheckedOut/magic/sourceme.sh
```

To get started, you then need to compile the code.

# 2.3 Setting up compiler options and compiling

The **recommended way of compiling MagIC** is to use the build system CMake, if available on your platform. Otherwise, a backup solution is provided via the manual edition of a Makefile.

### 2.3.1 Generic compiling options

For both build systems (CMake or make), several build options can be toggled using the following available options:

- ARCH Set it to '64' for 64 bit architecture or to '32' for 32 bit architecture
- PRECISION Set it to 'dble' for double-precision calculations or to 'sngl' for single-precision calculations
- OUT\_PREC Set it to 'dble' for double-precision in binary outputs or to 'sngl' for single precision
- USE\_MPI Set to yes to use MPI, set it to no if you want a serial version of the code .
- USE\_OMP Set it to yes to use the hybrid version of the code, or to no for a pure MPI (or serial) version.
- USE\_PRECOND Set to yes to perform some pre-conditioning of the matrices.
- USE\_FFTLIB This option lets you select the library you want to use for Fast Fourier Transforms. This can be set to 'JW' or 'MKL'. 'JW' refers to the inbuilt library by **J** ohannes **W** icht, while 'MKL' refers to the Intel Math Kernel Library. Use 'JW' if you don't have Intel MKL installed.
- USE\_LAPACKLIB This option allows you to select the library you want to use for LU factorisation. This can be set to 'JW', 'MKL' or 'LAPACK'. 'JW' refers to the built-in library, while 'MKL' refers to the Intel Math Kernel Library and 'LAPACK' to the Lapack library
- USE\_SHTNS Set to yes to use SHTns library for spherical harmonics transforms. The helper script install-shtns.sh is available in the bin directory to help installing SHTns.
- CMAKE\_BUILD\_TYPE Set to Debug to enable the full debug flags.

**Warning:** MagIC cannot run with openMP alone, therefore a configuration of the form USE\_MPI=no, USE\_OMP=yes will be overwritten to force USE\_OMP=no

### 2.3.2 Using CMake (recommended)

CMake is a powerful tool that can automatically detects and finds the best appropriate configuration for your platform. To use it, you just need to create a directory where you want to build the sources. For instance:

```
$ mkdir $MAGIC_HOME/build
$ cd $MAGIC_HOME/build
```

In a second step, you might want to specify your C and Fortran compilers (in case you skip this step, CMake will look for compilers for you but it might pick up another compiler as the one you might have wanted). For instance, in case you want to use the Intel compilers, you can export the following environment variables

```
$ export FC=mpiifort
$ export CC=mpiicc
```

#### for bash/ksh/zsh users and

```
$ setenv FC=mpiifort
$ setenv CC=mpiicc
```

for csh/tcsh users. At this stage you should be ready to build the code. If you simply use:

```
$ cmake ..
```

CMake will try to use the best options available on your machine (for instance it will try to locate and link the Intel Math Kernel Library). Otherwise you can pass the aforementioned available options to CMake using the generic form -DOPTION=value. For instance, in case you want to make use of the built-in libraries of MagIC and want to disable OpenMP, simply use

```
$ cmake .. -DUSE_OMP=no -DUSE_FFTLIB=JW -DUSE_LAPACKLIB=JW
```

Once you're happy with your configuration, just compile the code:

```
$ make -j
```

The executable magic.exe should have been produced in the local directory.

If you want to recompile the code from scratch do

```
$ make clean
```

to remove all the files generated by the compiler.

Once the executable is built, you are now ready to run your first production run!

### 2.3.3 Using make (backup solution)

In case CMake is not available on your platform, it is still possible to compile the code directly. Go to the directory where the source files of MagIC are contained

```
$ cd $MAGIC_HOME/src
```

### Select compiler

Edit the file named Makefile using your favourite editor and set a suitable compiler for your platform using the variable: COMPILER = value. The possible options are intel, gnu or portland compilers.

List of default compilers

Compiler Option	Normal	With MPI	
intel	ifort, icc	mpiifort, mpiicc	
gnu	gfortran, gcc	mpif90, mpicc	
portland	pgf95, pgcc	mpif90, mpicc	

**Warning:** In case you want to use intel but mpiifort and mpiicc are not available, you may also need to adapt the variables COMP\_MPFC and COMP\_MPCC.

#### **Select compiling options**

You can also modify the different compiling options by editing the values of the various parameters defined in the first lines of the Makefile. For instance, in case you want to make use of the built-in libraries and want to disable OpenMP, just define

```
USE_OMP=no
USE_FFTLIB=JW
USE_LAPACKLIB=JW
```

#### MPI INCPATH

This variable sets the path for your MPI header file mpif.h. This is in general useless if you already use the MPI wrappers such as mpiifort or mpif90 to compile the code. It might be however required to define this path for some compiler configurations: MPI\_INCPATH is usually /usr/include or /usr/include/mpi and should be found by the Makefile automatically thanks to the command mpif90 —-showme:incdirs. In case this doesn't work, you may need to specify this variable manually in the Makefile. On supercomputing clusters, this variable is in general not used.

#### Other compilers

If your available compilers are different from the options provided in the Makefile, then just create a new profile for your desired compiler by changing the options COMP\_FC and COMP\_CC for serial fortran and C compilers and COMP\_MPFC and COMP\_MPCC for the possible MPI wrappers.

Once you've set up your compiling options compile the code using

```
$ make -j
```

The compiler should then produce an executable named magic.exe.

If you want to recompile the code from scratch do

```
$ make clean
```

to remove all the files generated by the compiler.

Once the executable is built, you are now ready to run your first production run!

# 2.4 Preparing a production run

After building the executable, use one of the namelists provided in the  $MAGIC\_HOME/samples$  directory (called input.nml), adapt it to your physical problem (see *here* for an exhaustive description of the possible options) and run **MagIC** as follows:

• Running a serial version of the code (USE\_MPI=no and USE\_OMP=no):

```
$ ./magic.exe input.nml
```

• Running the code without OpenMP (USE\_MPI=yes and USE\_OMP=no) with <n\_mpi> MPI ranks:

```
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

• Running the hybrid code (USE\_MPI=yes and USE\_OMP=yes) with <n\_mpi> MPI ranks and <n\_omp> OpenMP threads:

```
$ export OMP_NUM_THREAD = <n_omp>
$ export KMP_AFFINITY=verbose,granularity=core,compact,1
$ mpiexec -n <n_mpi> ./magic.exe input.nml
```

Note that the  $n\_r\_max-1$  must be a multiple of  $n\_mpi>$ , where  $n\_r\_max$  is the number of radial grid points (see *here*).

# FORMULATION OF THE (MAGNETO)-HYDRODYNAMICS PROBLEM

The general equations describing thermal convection and dynamo action of a rotating compressible fluid are the starting point from which the Boussinesq or the anelastic approximations are developed. In MagIC, we consider a spherical shell rotating about the vertical z axis with a constant angular velocity  $\Omega$ . Equations are solve in the corotating system.

The conservation of momentum is formulated by the Navier-Stokes equation

$$\rho\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \,\boldsymbol{u}\right) = -\boldsymbol{\nabla} p + \frac{1}{\mu_0} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \rho \boldsymbol{g} - 2\rho \boldsymbol{\Omega} \times \boldsymbol{u} + \boldsymbol{\nabla} \cdot \boldsymbol{S},\tag{3.1}$$

where u is the velocity field, B the magnetic field, and p a modified pressure that includes centrifugal forces. S corresponds to the rate-of-strain tensor given by:

$$S_{ij} = 2\nu\rho \left[ e_{ij} - \frac{1}{3}\delta_{ij} \nabla \cdot \boldsymbol{u} \right],$$
  
$$e_{ij} = \frac{1}{2} \left( \frac{\partial u_i}{\partial x_j} + \frac{\partial u_j}{\partial x_i} \right).$$

Convection is driven by buoyancy forces acting on variations in density  $\rho$ . These variations have a dynamical part formulated by the continuity equation describing the conservation of mass:

$$\frac{\partial \rho}{\partial t} = -\nabla \cdot \rho u. \tag{3.2}$$

In addition an equation of state is required to formulate the thermodynamic density changes. For example the relation

$$\frac{1}{\rho}\partial\rho = -\alpha\partial T + \beta\partial p - \delta\partial\xi\tag{3.3}$$

describes density variations caused by variations in temperature T, pressure p, and composition  $\xi$ . The latter contribution needs to be considered for describing the effects of light elements released from a growing solid iron core in a so-called double diffusive approach.

To close the system we also have to formulate the dynamic changes of entropy, pressure, and composition. The evolution equation for pressure can be derived from the Navier-Stokes equation, as will be further discussed below. For entropy variations we use the so-called energy or heat equation

$$\rho T \left( \frac{\partial s}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} s \right) = \boldsymbol{\nabla} \cdot (k \boldsymbol{\nabla} T) + \boldsymbol{\Phi}_{\nu} + \lambda \left( \boldsymbol{\nabla} \times \boldsymbol{B} \right)^{2} + \epsilon, \tag{3.4}$$

where  $\Phi_{\nu}$  corresponds to the viscous heating expressed by

$$\Phi_{\nu} = 2\rho \left[ e_{ij}e_{ji} - \frac{1}{3} \left( \boldsymbol{\nabla} \cdot \boldsymbol{u} \right)^{2} \right]$$

Note that we use here the summation convention over the indices i and j. The second last term on the right hand side is the Ohmic heating due to electric currents. The last term is a volumetric sink or source term that can describe various

effects, for example radiogenic heating, the mixing-in of the light elements or, when radially dependent, potential variations in the adiabatic gradient (see below). For chemical composition, we finally use

$$\rho\left(\frac{\partial \xi}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi\right) = \boldsymbol{\nabla} \cdot (k_{\xi} \boldsymbol{\nabla} \xi) + \epsilon_{\xi}, \tag{3.5}$$

The induction equation is obtained from the Maxwell equations (ignoring displacement current) and Ohm's law (neglecting Hall effect):

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B} - \lambda \, \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.6}$$

When the magnetic diffusivity  $\lambda$  is homogeneous this simplifies to the commonly used form

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) + \lambda \, \boldsymbol{\Delta} \boldsymbol{B}. \tag{3.7}$$

The physical properties determining above equations are rotation rate  $\Omega$ , the kinematic viscosity  $\nu$ , the magnetic permeability  $\mu_0$ , gravity g, thermal conductivity k, Fick's conductivity  $k_\xi$ , magnetic diffusivity  $\lambda$ . The latter connects to the electrical conductivity  $\sigma$  via  $\lambda = 1/(\mu_0 \sigma)$ . The thermodynamics properties appearing in (3.3) are the thermal expansivity at constant pressure (and composition)

$$\alpha = -\frac{1}{\rho} \left( \frac{\partial \rho}{\partial T} \right)_{p,\xi},\tag{3.8}$$

the compressibility at constant temperature

$$\beta = \frac{1}{\rho} \left( \frac{\partial \rho}{\partial p} \right)_{T,\xi}$$

and an equivalent parameter  $\delta$  for the dependence of density on composition:

$$\delta = -\frac{1}{\rho} \left( \frac{\partial \rho}{\partial \xi} \right)_{p,T},\tag{3.9}$$

### 3.1 The reference state

The convective flow and the related processes including magnetic field generation constitute only small disturbances around a background or reference state. In the following we denote the background state with a tilde and the disturbance we are interested in with a prime. Formally we will solve equations in first order of a smallness parameters  $\epsilon$  which quantified the ratio of convective disturbances to background state:

$$\epsilon \sim \frac{T'}{\tilde{T}} \sim \frac{p'}{\tilde{p}} \sim \frac{\rho'}{\tilde{\rho}} \sim \dots \ll 1.$$
 (3.10)

The background state is hydrostatic, i.e. obeys the simple force balance

$$\nabla \tilde{p} = \tilde{\rho} \tilde{\boldsymbol{g}}. \tag{3.11}$$

Convective motions are supposed to be strong enough to provide homogeneous entropy (and composition). The reference state is thus adiabatic and its gradients can be expressed in terms of the pressure gradient (3.11):

$$\frac{\nabla \tilde{T}}{\tilde{T}} = \frac{1}{\tilde{T}} \left( \frac{\partial T}{\partial p} \right)_{s} \nabla p = \frac{\alpha}{c_{p}} \tilde{\mathbf{g}}, \tag{3.12}$$




Fig. 1: Sketch of the spherical shell model and its system of coordinate.

$$\frac{\nabla \tilde{\rho}}{\tilde{\rho}} = \frac{1}{\tilde{\rho}} \left( \frac{\partial \rho}{\partial p} \right)_s \nabla p = \beta \tilde{\rho} \tilde{\boldsymbol{g}}. \tag{3.13}$$

The reference state obviously dependence only on radius. Dimensionless numbers quantifying the temperature and density gradients are called dissipation number Di and compressibility parameter Co respectively:

$$Di = \frac{\alpha d}{c_p}\tilde{g},$$

and

$$Co = d\beta \tilde{\rho} \tilde{g}$$

Here d is a typical length scale, for example the shell thickness of the problem. The dissipation number is something like an inverse temperature scale hight while the compressibility parameters is an inverse density scale hight. The ratio of both numbers also helps to quantify the relative impact of temperature and pressure on density variations:

$$\frac{\alpha \nabla T}{\beta \nabla \rho} \approx \alpha \tilde{T} \frac{Di}{Co}.$$
(3.14)

As an example we demonstrate how to derive the first order continuity equation here. Using  $\rho = \tilde{\rho} + \rho'$  in (3.2) leads to

$$\frac{\partial \tilde{\rho}}{\partial t} + \frac{\partial \rho'}{\partial t} = -\nabla \cdot (\tilde{\rho} \boldsymbol{u}) - \nabla \cdot (\rho' \boldsymbol{u}).$$

The zero order term vanishes since the background density is considered static (or actually changing very slowly on very long time scales). The second term in the right hand side is obviously of second order. The ratio of the remaining two terms can be estimated to also be of first order in  $\epsilon$ , meaning that the time derivative of  $\rho$  is actually also of second order:

$$\frac{[\partial 
ho/\partial t]}{[oldsymbol{
abla} \cdot 
ho oldsymbol{u}]} pprox rac{
ho'}{ ilde{
ho}} pprox \epsilon \ .$$

Square brackets denote order of magnitude estimates here. We have used the fact that the reference state is static and assume time scale of changes are comparable (or slower)  $\rho'$  than the time scales represented by u and that length

3.1. The reference state

scales associated to the gradient operator are not too small. We can then neglect local variations in  $\rho'$  which means that sound waves are filtered out. This first order continuity equation thus simply reads:

$$\nabla \cdot (\tilde{\rho} \boldsymbol{u}) = 0. \tag{3.15}$$

This defines the so-called anelastic approximation where sound waves are filtered out by neglecting the local time derivative of density. This approximation is justified when typical velocities are sufficiently smaller than the speed of sound.

# 3.2 Boussinesq approximation

For Earth the dissipation number and the compressibility parameter are around 0.2 when temperature and density jump over the whole liquid core are considered. This motivates the so called Boussinesq approximation where Di and Co are assumed to vanish. The continuity equation (3.2) then simplifies further:

$$\frac{1}{\tilde{\rho}} \nabla \cdot \tilde{\rho} \boldsymbol{u} = \frac{\boldsymbol{u}}{\tilde{\rho}} \cdot \nabla \tilde{\rho} + \nabla \cdot \boldsymbol{u} \approx \nabla \cdot \boldsymbol{u} = 0.$$

When using typical number for Earth, (3.14) becomes 0.05 so that pressure effects on density may be neglected. The first order Navier-Stokes equation (after to zero order hydrostatic reference solution has been subtracted) then reads:

$$\tilde{\rho}\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \,\boldsymbol{u}\right) = -\boldsymbol{\nabla} p' - 2\rho \boldsymbol{\Omega} \times \boldsymbol{u} + \alpha \tilde{g}_o T' \frac{\boldsymbol{r}}{r_o} + \delta \tilde{g}_o \xi' \frac{\boldsymbol{r}}{r_o} + \frac{1}{\mu_0} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \tilde{\rho} \nu \Delta \boldsymbol{u}. \tag{3.16}$$

Here u and B are understood as first order disturbances and p' is the first order non-hydrostatic pressure and T' the super-adiabatic temperature and  $\xi$  the super-adiabatic chemical composition. Above we have adopted a simplification of the buoyancy term. In the Boussinesq limit with vanishing Co and a small density difference between a solid inner and a liquid outer core a linear gravity dependence provides a reasonable approximation:

$$\tilde{\boldsymbol{g}} = \tilde{g}_o \frac{\boldsymbol{r}}{r_o},$$

where we have chosen the gravity  $\tilde{g}_o$  at the outer boundary radius  $r_o$  as reference.

The first order energy equation becomes

$$\tilde{\rho}\left(\frac{\partial T'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} T'\right) = \kappa \Delta T' + \epsilon, \tag{3.17}$$

where we have assumed a homogeneous k and neglected viscous and Ohmic heating which can be shown to scale with Di as we discuss below. Furthermore, we have used the simple relation

$$\partial s \approx \frac{\tilde{\rho}c_p}{\tilde{T}}\partial T,$$

defined the thermal diffusivity

$$\kappa = \frac{k}{\tilde{\rho}c_p},$$

and adjusted the definition of  $\epsilon$ . Finally the first order equation for chemical composition becomes

$$\tilde{\rho}\left(\frac{\partial \xi'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi'\right) = \kappa_{\xi} \Delta \xi' + \epsilon_{\xi},\tag{3.18}$$

where we have assumed a homogeneous  $k_{\xi}$  and adjusted the definition of  $\epsilon_{\xi}$ .

MagIC solves a dimensionless form of the differential equations. Time is scaled in units of the viscous diffusion time  $d^2/\nu$ , length in units of the shell thickness d, temperature in units of the temperature drop  $\Delta T = T_o - T_i$  over the

shell, composition in units of the composition drop  $\Delta \xi = \xi_o - \xi_i$  over the shell and magnetic field in units  $(\mu \lambda \tilde{\rho} \Omega)^{1/2}$ . Technically the transition to the dimensionless form is achieved by the substitution

$$r \to r d$$
,  $t \to (d^2/\nu) t$ ,  $T \to \Delta T T$ ,  $\xi \to \Delta \xi \xi$ ,  $B \to (\mu \lambda \tilde{\rho} \Omega)^{1/2} B$ 

where r stands for any length. The next step then is to collect the physical properties as a few possible characteristic dimensionless numbers. Note that many different scalings and combinations of dimensionless numbers are possible. For the Navier-Stokes equation in the Boussinesq limit MagIC uses the form:

$$\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \, \boldsymbol{u}\right) = -\boldsymbol{\nabla} p' - \frac{2}{E} \boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} + \frac{Ra}{Pr} T' \frac{\boldsymbol{r}}{r_o} + \frac{Ra_{\boldsymbol{\xi}}}{Sc} \boldsymbol{\xi}' \frac{\boldsymbol{r}}{r_o} + \frac{1}{EPm} (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} + \Delta \boldsymbol{u}, \quad (3.19)$$

where  $e_z$  is the unit vector in the direction of the rotation axis and the meaning of the pressure disturbance p' has been adjusted to the new dimensionless equation form.

# 3.3 Anelastic approximation

The anelastic approximation adopts the simplified continuity (3.15). The background state can be specified in different ways, for example by providing profiles based on internal models and/or ab initio simulations. We will assume a polytropic ideal gas in the following.

### 3.3.1 Analytical solution in the limit of an ideal gas

In the limit of an ideal gas which follows  $\tilde{p} = \tilde{\rho}\tilde{T}$  and has  $\alpha = 1/\tilde{T}$ , one directly gets:

$$\begin{split} \frac{d\tilde{T}}{dr} &= -Di\,\tilde{g}(r),\\ \tilde{\rho} &= \tilde{T}^{1/(\gamma-1)}, \end{split}$$

where  $\gamma = c_p/c_v$ . Note that we have moved to a dimensionless formulations here, where all quantities have been normalized with their outer boundary values and Di refers to the respective outer boundary value. If we in addition make the assumption of a centrally-condensed mass in the center of the spherical shell of radius  $r \in [r_i, r_o]$ , i.e.  $g \propto 1/r^2$ , this leads to

$$\begin{split} \tilde{T}(r) &= Di \frac{r_o^2}{r} + (1 - Di \, r_o), \\ \tilde{\rho}(r) &= \tilde{T}^m, \\ Di &= \frac{r_i}{r_o} \left( \exp \frac{N_\rho}{m} - 1 \right), \end{split}$$

where  $N_{\rho} = \ln(\tilde{\rho}_i/\tilde{\rho}_o)$  is the number of density scale heights of the reference state and  $m = 1/(\gamma - 1)$  is the polytropic index.

#### Warning

- The relationship between  $N_{\rho}$  and the dissipation number Di directly depends on the gravity profile. The formula above is only valid when  $g \propto 1/r^2$ .
- In this formulation, when you change the polytropic index m, you also change the nature of the fluid you're modelling since you accordingly modify  $\gamma = c_p/c_v$ .

### 3.3.2 Anelastic MHD equations

In the most general formulation, all physical properties defining the background state may vary with depth. Specific reference values must then be chosen to provide a unique dimensionless formulations and we typically chose outer boundary values here. The exception is the magnetic diffusivity where we adopt the inner boundary value instead. The motivation is twofold: (i) it allows an easier control of the possible continuous conductivity value in the inner core; (ii) it is a more natural choice when modelling gas giants planets which exhibit a strong electrical conductivity decay in the outer layer.

The time scale is then the viscous diffusion time  $d^2/\nu_o$  where  $\nu_o$  is the kinematic viscosity at the outer boundary. Magnetic field is expressed in units of  $(\rho_o \mu_0 \lambda_i \Omega)^{1/2}$ , where  $\rho_o$  is the density at the outer boundary and  $\lambda_i$  is the magnetic diffusivity at the **inner** boundary.

This leads to the following sets of dimensionless equations:

$$\left(\frac{\partial \boldsymbol{u}}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \boldsymbol{u}\right) = -\boldsymbol{\nabla} \left(\frac{p'}{\tilde{\rho}}\right) - \frac{2}{E} \boldsymbol{e}_{\boldsymbol{z}} \times \boldsymbol{u} + \frac{Ra}{Pr} \tilde{g} \, s' \, \boldsymbol{e}_{\boldsymbol{r}} + \frac{Ra_{\xi}}{Sc} \tilde{g} \, \xi' \, \boldsymbol{e}_{\boldsymbol{r}} + \frac{1}{Pm \, E \, \tilde{\rho}} \left(\boldsymbol{\nabla} \times \boldsymbol{B}\right) \times \boldsymbol{B} + \frac{1}{\tilde{\rho}} \boldsymbol{\nabla} \cdot \boldsymbol{S}, \tag{3.20}$$

$$\nabla \cdot \tilde{\rho} \boldsymbol{u} = 0, \tag{3.21}$$

$$\nabla \cdot \boldsymbol{B} = 0, \tag{3.22}$$

$$\tilde{\rho}\left(\frac{\partial \xi'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla} \xi'\right) = \frac{1}{Sc} \boldsymbol{\nabla} \cdot (\kappa_{\xi}(r) \tilde{\rho} \boldsymbol{\nabla} \xi')$$
(3.23)

$$\frac{\partial \boldsymbol{B}}{\partial t} = \boldsymbol{\nabla} \times (\boldsymbol{u} \times \boldsymbol{B}) - \frac{1}{Pm} \boldsymbol{\nabla} \times (\lambda(r) \boldsymbol{\nabla} \times \boldsymbol{B}). \tag{3.24}$$

Here  $\tilde{g}$  and  $\tilde{\rho}$  are the normalized radial gravity and density profiles that reach one at the outer boundary.

### 3.3.3 Entropy equation and turbulent diffusion

The entropy equation usually requires an additional assumption in most of the existing anelastic approximations. Indeed, if one simply expands Eq. (3.4) with the classical temperature diffusion an operator of the form:

$$\epsilon \, \boldsymbol{\nabla} \cdot (K \boldsymbol{\nabla} T') + \boldsymbol{\nabla} \cdot \left( K \boldsymbol{\nabla} \tilde{T} \right),$$

will remain the right-hand side of the equation. At first glance, there seems to be a  $1/\epsilon$  factor between the first term and the second one, which would suggest to keep only the second term in this expansion. However, for astrophysical objects which exhibit strong convective driving (and hence large Rayleigh numbers), the diffusion of the adiabatic background is actually very small and may be comparable or even smaller in magnitude than the  $\epsilon$  terms representing the usual convective perturbations. For the Earth core for instance, if one assumes that the typical temperature fluctuations are of the order of 1 mK and the temperature contrast between the inner and outer core is of the order of 1000 K, then  $\epsilon \sim 10^{-6}$ . The ratio of the two terms can thus be estimated as

$$\epsilon \frac{T'/\delta^2}{T/d^2},\tag{3.25}$$

where d is the thickness of the inner core and  $\delta$  is the typical thermal boundary layer thickness. This ratio is exactly one when  $\delta = 1$  m, a plausible value for the Earth inner core.

In numerical simulations however, the over-estimated diffusivities restrict the computational capabilities to much lower Rayleigh numbers. As a consequence, the actual boundary layers in a global DNS will be much thicker and the ratio (3.25) will be much smaller than unity. The second terms will thus effectively acts as a radial-dependent heat source or sink that will drive or hinder convection. This is one of the physical motivation to rather introduce a **turbulent diffusivity** that will be approximated by

$$\kappa \tilde{\rho} \tilde{T} \nabla s$$
,

where  $\kappa$  is the turbulent diffusivity. Entropy diffusion is assumed to dominate over temperature diffusion in turbulent flows.

The choice of the entropy scale to non-dimensionalize Eq. (3.4) also depends on the nature of the boundary conditions: it can be simply the entropy contrast over the layer  $\Delta s$  when the entropy is held constant at both boundaries, or d(ds/dr) when flux-based boundary conditions are employed. We will restrict to the first option in the following, but keep in mind that depending on your setup, the entropy reference scale (and thus the Rayleigh number definition) might change.

$$\tilde{\rho}\tilde{T}\left(\frac{\partial s'}{\partial t} + \boldsymbol{u} \cdot \boldsymbol{\nabla}s'\right) = \frac{1}{Pr}\boldsymbol{\nabla}\cdot\left(\kappa(r)\tilde{\rho}\tilde{T}\boldsymbol{\nabla}s'\right) + \frac{Pr\,Di}{Ra}\boldsymbol{\Phi}_{\nu} + \frac{Pr\,Di}{Pm^2\,E\,Ra}\lambda(r)\left(\boldsymbol{\nabla}\times\boldsymbol{B}\right)^2,\tag{3.26}$$

A comparison with (3.20) reveals meaning of the different non-dimensional numbers that scale viscous and Ohmic heating. The fraction Pr/Ra simply expresses the ratio of entropy and flow in the Navier-Stokes equation, while the additional factor 1/EPm reflects the scale difference of magnetic field and flow. Then remaining dissipation number Di then expresses the relative importance of viscous and Ohmic heating compared to buoyancy and Lorentz force in the Navier-Stokes equation. For small Di both heating terms can be neglected compared to entropy changes due to advection, an limit that is used in the Boussinesq approximation.

# 3.4 Dimensionless control parameters

The equations (3.20)-(3.26) are governed by four dimensionless numbers: the Ekman number

$$E = \frac{\nu}{\Omega d^2},\tag{3.27}$$

the thermal Rayleigh number

$$Ra = \frac{\alpha_o g_o T_o d^3 \Delta s}{c_p \kappa_o \nu_o},\tag{3.28}$$

the compositional Rayleigh number

$$Ra_{\xi} = \frac{\delta_o g_o d^3 \Delta \xi}{\kappa_{\xi} \nu_o},\tag{3.29}$$

the Prandtl number

$$Pr = \frac{\nu_o}{\kappa_o},\tag{3.30}$$

the Schmidt number

$$Sc = \frac{\nu_o}{\kappa_{\xi}},\tag{3.31}$$

and the magnetic Prandtl number

$$Pm = \frac{\nu_o}{\lambda_i}. (3.32)$$

In addition to these four numbers, the reference state is controlled by the geometry of the spherical shell given by its radius ratio

$$\eta = \frac{r_i}{r_o},\tag{3.33}$$

and the background density and temperature profiles, either controlled by Di or by  $N_{\rho}$  and m.

In the Boussinesq approximation all physical properties are assumed to be homogeneous and we can drop the subindices o and i except for gravity. Moreover, the Rayleigh number can be expressed in terms of the temperature jump across the shell:

$$Ra = \frac{\alpha g_o d^3 \Delta T}{\kappa \nu}. (3.34)$$

#### See also:

In MagIC, those control parameters can be adjusted in the &phys\_param section of the input namelist.

Variants of the non-dimensional equations and control parameters result from different choices for the fundamental scales. For the length scale often  $r_o$  is chosen instead of d. Other natural scales for time are the magnetic or the thermal diffusion time, or the rotation period. There are also different options for scaling the magnetic field strength. The prefactor of two, which is retained in the Coriolis term in (3.20), is often incorporated into the definition of the Ekman number.

#### See also:

Those references timescales and length scales can be adjusted by several input parameters in the &control section of the input namelist.

### 3.4.1 Usual diagnostic quantities

Characteristic properties of the solution are usually expressed in terms of non-dimensional diagnostic parameters. In the context of the geodynamo for instance, the two most important ones are the magnetic Reynolds number Rm and the Elsasser number  $\Lambda$ . Usually the rms-values of the velocity  $u_{rms}$  and of the magnetic field  $B_{rms}$  inside the spherical shell are taken as characteristic values. The magnetic Reynolds number

$$Rm = \frac{u_{rms}d}{\lambda_i}$$

can be considered as a measure for the flow velocity and describes the ratio of advection of the magnetic field to magnetic diffusion. Other characteristic non-dimensional numbers related to the flow velocity are the (hydrodynamic) Reynolds number

$$Re = \frac{u_{rms}d}{\nu_o},$$

which measures the ratio of inertial forces to viscous forces, and the Rossby number

$$Ro = \frac{u_{rms}}{\Omega d},$$

a measure for the ratio of inertial to Coriolis forces.

$$\Lambda = \frac{B_{rms}^2}{\mu_0 \lambda_i \rho_o \Omega}$$

measures the ratio of Lorentz to Coriolis forces and is equivalent to the square of the non-dimensional magnetic field strength in the scaling chosen here.

#### See also:

The time-evolution of these diagnostic quantities are stored in the par.TAG file produced during the run of MagIC.

# 3.5 Boundary conditions and treatment of inner core

### 3.5.1 Mechanical conditions

In its simplest form, when modelling the geodynamo, the fluid shell is treated as a container with rigid, impenetrable, and co-rotating walls. This implies that within the rotating frame of reference all velocity components vanish at  $r_o$  and  $r_i$ . In case of modelling the free surface of a gas giant planets or a star, it is preferable to rather replace the condition of zero horizontal velocity by one of vanishing viscous shear stresses (the so-called free-slip condition).

Furthermore, even in case of modelling the liquid iron core of a terrestrial planet, there is no a priori reason why the inner core should necessarily co-rotate with the mantle. Some models for instance allow for differential rotation of the inner core and mantle with respect to the reference frame. The change of rotation rate is determined from the net torque. Viscous, electromagnetic, and torques due to gravitational coupling between density heterogeneities in the mantle and in the inner core contribute.

#### See also:

The mechanical boundary conditions can be adjusted with the parameters *ktopv* and *kbotv* in the *&phys\_param* section of the input namelist.

### 3.5.2 Magnetic boundary conditions and inner core conductivity

When assuming that the fluid shell is surrounded by electrically insulating regions (inner core and external part), the magnetic field inside the fluid shell matches continuously to a potential field in both the exterior and the interior regions. Alternative magnetic boundary conditions (like cancellation of the horizontal component of the field ) are also possible.

Depending on the physical problem you want to model, treating the inner core as an insulator is not realistic either, and it might instead be more appropriate to assume that it has the same electrical conductivity as the fluid shell. In this case, an equation equivalent to (3.24) must be solved for the inner core, where the velocity field simply describes the solid body rotation of the inner core with respect to the reference frame. At the inner core boundary a continuity condition for the magnetic field and the horizontal component of the electrical field apply.

#### See also:

The magnetic boundary conditions can be adjusted with the parameters *ktopb* and *kbotb* in the *&phys\_param* section of the input namelist.

### 3.5.3 Thermal boundary conditions and distribution of buoyancy sources

In many dynamo models, convection is simply driven by an imposed fixed super-adiabatic entropy contrast between the inner and outer boundaries. This approximation is however not necessarily the best choice, since for instance, in the present Earth, convection is thought to be driven by a combination of thermal and compositional buoyancy. Sources of heat are the release of latent heat of inner core solidification and the secular cooling of the outer and inner core, which can effectively be treated like a heat source. The heat loss from the core is controlled by the convecting mantle, which effectively imposes a condition of fixed heat flux at the core-mantle boundary on the dynamo. The heat flux is in that case spatially and temporally variable.

#### See also:

The thermal boundary conditions can be adjusted with the parameters *ktops* and *kbots* in the *&phys\_param* section of the input namelist.

## 3.5.4 Chemical composition boundary conditions

They are treated in a very similar manner as the thermal boundary conditions

### See also:

The boundary conditions for composition can be adjusted with the parameters *ktopxi* and *kbotxi* in the *&phys\_param* section of the input namelist.

### NUMERICAL TECHNIQUE

MagIC is a pseudo-spectral MHD code. This numerical technique was originally developed by P. Gilman and G. Glatzmaier for the spherical geometry. In this approach the unknowns are expanded into complete sets of functions in radial and angular directions: Chebyshev polynomials or Finite differences in the radial direction and spherical harmonic functions in the azimuthal and latitudinal directions. This allows to express all partial derivatives analytically. Employing orthogonality relations of spherical harmonic functions and using collocation in radius then lead to algebraic equations that are integrated in time with a mixed implicit/explicit time stepping scheme. The nonlinear terms and the Coriolis force are evaluated in the physical (or grid) space rather than in spectral space. Although this approach requires costly numerical transformations between the two representations (from spatial to spectral using Legendre and Fourier transforms), the resulting decoupling of all spherical harmonic modes leads to a net gain in computational speed. Before explaining these methods in more detail, we introduce the poloidal/toroidal decomposition.

# 4.1 Poloidal/toroidal decomposition

Any vector v that fulfills  $\nabla \cdot v = 0$ , i.e. a so-called *solenoidal field*, can be decomposed in a poloidal and a toroidal part W and Z, respectively

$$v = \nabla \times (\nabla \times W e_r) + \nabla \times Z e_r.$$

Three unknown vector components are thus replaced by two scalar fields, the poloidal potential W and the toroidal potential Z. This decomposition is unique, aside from an arbitrary radial function f(r) that can be added to W or Z without affecting v.

In the anelastic approximation, such a decomposition can be used for the mass flux  $\tilde{\rho}u$  and the magnetic field B. This yields

$$\widetilde{\rho} \boldsymbol{u} = \boldsymbol{\nabla} \times (\boldsymbol{\nabla} \times W \, \boldsymbol{e_r}) + \boldsymbol{\nabla} \times Z \, \boldsymbol{e_r}, 
\boldsymbol{B} = \boldsymbol{\nabla} \times (\boldsymbol{\nabla} \times g \, \boldsymbol{e_r}) + \boldsymbol{\nabla} \times h \, \boldsymbol{e_r}.$$
(4.1)

The two scalar potentials of a divergence free vector field can be extracted from its radial component and the radial component of its curl using the fact that the toroidal field has not radial component:

$$e_{r} \cdot \tilde{\rho} \boldsymbol{u} = -\Delta_{H} W,$$

$$e_{r} \cdot (\nabla \times \boldsymbol{u}) = -\Delta_{H} Z,$$
(4.2)

where the operator  $\Delta_H$  denotes the horizontal part of the Laplacian:

$$\Delta_H = \frac{1}{r^2 \sin \theta} \frac{\partial}{\partial \theta} \left( \sin \theta \frac{\partial}{\partial \theta} \right) + \frac{1}{r^2 \sin^2 \theta} \frac{\partial^2}{\partial^2 \phi}.$$
 (4.3)

The equation (4.1) can be expanded in spherical coordinates. The three components of  $\tilde{\rho}u$  are given by

$$\tilde{\rho} \boldsymbol{u} = -(\Delta_H W) \, \boldsymbol{e}_r + \left( \frac{1}{r} \frac{\partial W}{\partial \theta} + \frac{1}{r \sin \theta} \frac{\partial Z}{\partial \phi} \right) \, \boldsymbol{e}_{\theta} + \left( \frac{1}{r \sin \theta} \frac{\partial W}{\partial \phi} - \frac{1}{r} \frac{\partial Z}{\partial \theta} \right) \, \boldsymbol{e}_{\phi}, \tag{4.4}$$

while the curl of  $\tilde{\rho}u$  is expressed by

$$\nabla \times \tilde{\rho} \boldsymbol{u} = -\left(\Delta_{H} Z\right) \boldsymbol{e}_{\boldsymbol{r}} + \left[ -\frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \left( \frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r} \frac{\partial^{2} Z}{\partial r \partial \theta} \right] \boldsymbol{e}_{\boldsymbol{\theta}} + \left[ \frac{1}{r} \frac{\partial}{\partial \theta} \left( \frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r \sin \theta} \frac{\partial^{2} Z}{\partial r \partial \phi} \right] \boldsymbol{e}_{\boldsymbol{\phi}},$$

$$(4.5)$$

Using the horizontal part of the divergence operator

$$\nabla_{H} = \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} \sin \theta \ \boldsymbol{e}_{\theta} + \frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} \ \boldsymbol{e}_{\phi}$$

above expressions can be simplified to

$$\tilde{\rho}\boldsymbol{u} = -\Delta_H \,\,\boldsymbol{e_r} \,\, W + \boldsymbol{\nabla}_H \frac{\partial}{\partial r} \,\, W + \boldsymbol{\nabla}_H \times \boldsymbol{e_r} \,\, Z$$

and

$$\nabla \times \tilde{\rho} \boldsymbol{u} = -\Delta_H \, \boldsymbol{e}_r \, Z + \boldsymbol{\nabla}_H \frac{\partial}{\partial r} \, Z - \boldsymbol{\nabla}_H \times \Delta_H \boldsymbol{e}_r \, W .$$

Below we will use the fact that the horizontal components of the poloidal field depend on the radial derivative of the poloidal potential.

# 4.2 Spherical harmonic representation

Spherical harmonic functions  $Y_{\ell}^{m}$  are a natural choice for the horizontal expansion in colatitude  $\theta$  and longitude  $\phi$ :

$$Y_{\ell}^{m}(\theta,\phi) = P_{\ell}^{m}(\cos\theta) e^{im\phi},$$

where  $\ell$  and m denote spherical harmonic degree and order, respectively,  $P_{\ell}^{m}$  is an associated Legendre function. Different normalization are in use. Here we adopt a complete normalization so that the orthogonality relation reads

$$\int_0^{2\pi} d\phi \int_0^{\pi} \sin\theta \, d\theta \, Y_\ell^m(\theta,\phi) \, Y_{\ell'}^{m'}(\theta,\phi) = \delta_{\ell\ell'} \delta^{mm'}. \tag{4.6}$$

This means that

$$Y_{\ell}^{m}(\theta,\phi) = \left(\frac{(2\ell+1)}{4\pi} \frac{(\ell-|m|)!}{(\ell+|m|)!}\right)^{1/2} P_{\ell}^{m}(\cos\theta) e^{im\phi},$$

As an example, the spherical harmonic representation of the magnetic poloidal potential  $g(r, \theta, \phi)$ , truncated at degree and order  $\ell_{max}$ , then reads

$$g(r, \theta, \phi) = \sum_{\ell=0}^{\ell_{max}} \sum_{m=-\ell}^{\ell} g_{\ell m}(r) Y_{\ell}^{m}(\theta, \phi), \tag{4.7}$$

with

$$g_{\ell m}(r) = \frac{1}{\pi} \int_0^{\pi} d\theta \sin\theta \ g_m(r,\theta) \ P_{\ell}^m(\cos\theta), \tag{4.8}$$

$$g_m(r,\theta) = \frac{1}{2\pi} \int_0^{2\pi} d\phi \ g(r,\theta,\phi) \ e^{-im\phi}.$$
 (4.9)

The potential  $g(r, \theta, \phi)$  is a real function so that  $g_{\ell m}^{\star}(r) = g_{\ell, -m}(r)$ , where the asterisk denotes the complex conjugate. Thus, only coefficients with  $m \geq 0$  have to be considered. The same kind of expansion is made for the toroidal magnetic potential, the mass flux potentials, pressure, entropy (or temperature) and chemical composition.

The equations (4.8) and (4.9) define a two-step transform from the longitude/latitude representation to the spherical harmonic representation  $(r, \theta, \phi) \longrightarrow (r, \ell, m)$ . The equation (4.7) formulates the inverse procedure  $(r, \ell, m) \longrightarrow (r, \theta, \phi)$ . Fast-Fourier transforms are employed in the longitudinal direction, requiring (at least)  $N_{\phi} = 2\ell_{max} + 1$  evenly spaced grid points  $\phi_i$ . MagIC relies on the Gauss-Legendre quadrature for evaluating the integral (4.8)

$$g_{\ell m}(r) = \frac{1}{N_{\theta}} \sum_{j=1}^{N_{\theta}} w_j g_m(r, \theta_j) P_{\ell}^m(\cos \theta_j),$$

where  $\theta_j$  are the  $N_{\theta}$  Gaussian quadrature points defining the latitudinal grid, and  $w_j$  are the respective weights. Prestored values of the associated Legendre functions at grid points  $\theta_j$  in combination with a FFT in  $\phi$  provide the inverse transform (4.7). Generally,  $N_{\phi} = 2N_{\theta}$  is chosen, which provides isotropic resolution in the equatorial region. Choosing  $\ell_{max} = [\min(2N_{\theta}, N_{\phi}) - 1]/3$  prevents aliasing errors.

#### See also:

In MagIC, the Legendre functions are defined in the subroutine plm\_theta. The Legendre transforms from spectral to grid space are computed in the module legendre\_spec\_to\_grid, while the backward transform (from grid space to spectral space) are computed in the module legendre\_grid\_to\_spec. The fast Fourier transforms are computed in the module fft.

### 4.2.1 Special recurrence relations

The action of a horizontal Laplacian (4.3) on spherical harmonics can be analytically expressed by

$$\Delta_H Y_\ell^m = -\frac{\ell(\ell+1)}{r^2} Y_\ell^m \,. \tag{4.10}$$

They are several useful recurrence relations for the Legendre polynomials that will be further employed to compute Coriolis forces and the  $\theta$  and  $\phi$  derivatives of advection and Lorentz forces. Four of these operators are used in **MagIC**. The first one is defined by

$$\vartheta_1 = \frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \sin^2 \theta = \sin \theta \frac{\partial}{\partial \theta} + 2\cos \theta.$$

The action of this operator on a Legendre polynomials is given by

$$\vartheta_1 = (\ell+2) c_{\ell+1}^m P_{\ell+1}^m (\cos \theta) - (\ell-1) c_{\ell}^m P_{\ell-1}^m (\cos \theta),$$

where  $c_{\ell}^{m}$  is defined by

$$c_{\ell}^{m} = \sqrt{\frac{(\ell+m)(\ell-m)}{(2\ell-1)(2\ell+1)}}.$$
(4.11)

How is that implemented in the code? Let's assume we want the spherical harmonic contribution of degree  $\ell$  and order m for the expression

$$\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} (\sin \theta f(\theta)).$$

In order to employ the operator  $\vartheta_1$  for the derivative, we thus define a new function

$$F(\theta) = f(\theta) / \sin \theta$$
,

so that

$$\frac{1}{\sin \theta} \frac{\partial}{\partial \theta} [\sin \theta f(\theta)] = \vartheta_1 F(\theta).$$

Expanding  $F(\theta)$  in Legendre polynomials and using the respective orthogonality relation we can then map out the required contribution in the following way:

$$\int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m \vartheta_1 \sum_{\ell'} F_{\ell'}^m P_{\ell'}^m = (\ell+1) \, c_{\ell}^m \, F_{\ell-1}^m - \ell \, c_{\ell+1}^m \, F_{\ell+1}^m \,. \tag{4.12}$$

Here, we have assumed that the Legendre functions are completely normalized such that

$$\int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m P_{\ell'}^m = \delta_{\ell\ell'} \,.$$

#### See also:

This operator is defined in the module horizontal\_data by the variables dTheta1S for the first part of the right-hand side of (4.12) and dTheta1A for the second part.

The second operator used to formulate colatitude derivatives is

$$\vartheta_2 = \sin \theta \frac{\partial}{\partial \theta} \,.$$

The action of this operator on the Legendre polynomials reads

$$\vartheta_2 P_{\ell}^m(\cos \theta) = \ell c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) - (\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

so that

$$\int_0^{\pi} d\theta \sin \theta \, P_{\ell}^m \vartheta_2 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = (\ell - 1) \, c_{\ell}^m \, f_{\ell-1}^m - (\ell + 2) \, c_{\ell+1}^m \, f_{\ell+1}^m \,. \tag{4.13}$$

#### See also:

This operator is defined in the module horizontal\_data by the variables dTheta2S for the first part of the right-hand side of (4.13) and dTheta2A for the second part.

The third combined operator is defined by:

$$\vartheta_3 = \sin \theta \frac{\partial}{\partial \theta} + \cos \theta \, L_H \,,$$

where 
$$-L_H/r^2 = \Delta_H$$
.

Acting with  $\vartheta_3$  on a Legendre function gives:

$$\vartheta_3 P_{\ell}^m(\cos \theta) = \ell(\ell+1) c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) + (\ell-1)(\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

which results into:

$$\int_0^{\pi} d\theta \, \sin\theta \, P_{\ell}^m \vartheta_3 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = (\ell - 1)(\ell + 1) \, c_{\ell}^m \, f_{\ell-1}^m + \ell(\ell + 2) \, c_{\ell+1}^m \, f_{\ell+1}^m \,.$$
(4.14)

See also:

This operator is defined in the module horizontal\_data by the variables dTheta3S for the first part of the right-hand side of (4.14) and dTheta3A for the second part.

The fourth (and last) combined operator is defined by:

$$\vartheta_4 = \frac{1}{\sin \theta} \frac{\partial}{\partial \theta} \sin^2 \theta \, L_H = \vartheta 1 \, L_H$$

Acting with  $\vartheta_3$  on a Legendre function gives:

$$\vartheta_4 P_{\ell}^m(\cos \theta) = \ell(\ell+1)(\ell+2) c_{\ell+1}^m P_{\ell+1}^m(\cos \theta) - \ell(\ell-1)(\ell+1) c_{\ell}^m P_{\ell-1}^m(\cos \theta),$$

which results into:

$$\left| \int_0^\pi d\theta \, \sin\theta \, P_\ell^m \vartheta_4 \sum_{\ell'} f_{\ell'}^m P_{\ell'}^m = \ell(\ell-1)(\ell+1) \, c_\ell^m \, f_{\ell-1}^m - \ell(\ell+1)(\ell+2) \, c_{\ell+1}^m \, f_{\ell+1}^m \, . \right|$$
(4.15)

#### See also:

This operator is defined in the module horizontal\_data by the variables dTheta4S for the first part of the right-hand side of (4.15) and dTheta4A for the second part.

# 4.3 Radial representation

In MagIC, the radial dependencies are expanded into complete sets of functions: the Chebyshev polynomials C(x). The polynomial of degree n is defined by

$$C_n(x) = \cos [n \arccos(x)] - 1 < x < 1.$$

When truncating at degree N, the radial expansion of the poloidal magnetic potential reads

$$g_{\ell m}(r) = \sum_{n=0}^{N} g_{\ell m n} \, \mathcal{C}_n(r),$$
 (4.16)

with

$$g_{\ell mn} = \frac{2 - \delta_{n0}}{\pi} \int_{-1}^{1} \frac{dx \, g_{\ell m}(r(x)) \, \mathcal{C}_n(x)}{\sqrt{1 - x^2}}.$$
 (4.17)

The Chebyshev definition space  $(-1 \le x \le 1)$  is then linearly mapped onto a radius range  $(r_i \le r \le r_o)$  by

$$x(r) = 2\frac{r - r_i}{r_o - r_i} - 1. (4.18)$$

In addition, nonlinear mapping can be defined to modify the radial dependence of the grid-point density.

When choosing the  $N_r$  extrema of  $C_{N_r-1}$  as radial grid points,

$$x_k = \cos\left(\pi \frac{(k-1)}{N_r - 1}\right) , \quad k = 1, 2, \dots, N_r,$$
 (4.19)

the values of the Chebyshev polynomials at these points are simply given by the cosine functions:

$$C_{nk} = C_n(x_k) = \cos\left(\pi \frac{n(k-1)}{N_r - 1}\right).$$

This particular choice has two advantages. For one, the grid points become denser toward the inner and outer radius and better resolve potential thermal and viscous boundary layers. In addition, FFTs can be employed to switch between grid representation (4.16) and Chebyshev representations (4.17), rendering this procedure a fast-Chebyshev transform. Choosing  $N_T > N$  provides radial dealiasing.

#### See also:

The Chebyshev (Gauss-Lobatto) grid is defined in the module <code>chebyshev\_polynoms\_mod</code>. The cosine transforms are computed in the modules <code>cosine\_transform\_even</code> and <code>fft\_fac\_mod</code>.

# 4.4 Spectral equations

We have now introduced the necessary tools for deriving the spectral equations. Taking the **radial components** of the Navier-Stokes equation and the induction equation provides the equations for the poloidal potentials  $W(r, \theta, \phi)$  and  $g(r, \theta, \phi)$ . The **radial component of the curl** of these equations provides the equations for the toroidal counterparts  $Z(r, \theta, \phi)$  and  $h(r, \theta, \phi)$ . The pressure remains an additional unknown. Hence one more equation involving  $W_{\ell mn}$  and  $p_{\ell mn}$  is required. It is obtained by taking the **horizontal divergence** of the Navier-Stokes equation.

Expanding all potentials in spherical harmonics and Chebyshev polynomials, multiplying with  $Y_{\ell}^{m*}$ , and integrating over spherical surfaces (while making use of the orthogonality relation (4.6) results in equations for the coefficients  $W_{\ell mn}$ ,  $Z_{\ell mn}$ ,  $g_{\ell mn}$ ,  $h_{\ell mn}$ ,  $P_{\ell mn}$  and  $s_{\ell mn}$ , respectively.

### **4.4.1** Equation for the poloidal potential W

The temporal evolution of W is obtained by taking  $e_r$  of each term entering the Navier-Stokes equation. For the time-derivative, one gets using (4.2):

$$\tilde{\rho} \boldsymbol{e_r} \cdot \left( \frac{\partial \boldsymbol{u}}{\partial t} \right) = \frac{\partial}{\partial t} (\boldsymbol{e_r} \cdot \tilde{\rho} \boldsymbol{u}) = -\Delta_H \frac{\partial W}{\partial t}.$$

For the viscosity term, one gets

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} &= -\,\nu\,\Delta_H \left[ \frac{\partial^2 W}{\partial r^2} + \left\{ 2 \frac{d\ln\nu}{dr} - \frac{1}{3} \frac{d\ln\tilde{\rho}}{dr} \right\} \frac{\partial W}{\partial r} \right. \\ &- \left. \left\{ -\Delta_H + \frac{4}{3} \left( \frac{d^2\ln\tilde{\rho}}{dr^2} + \frac{d\ln\nu}{dr} \frac{d\ln\tilde{\rho}}{dr} + \frac{1}{r} \left[ 3 \frac{d\ln\nu}{dr} + \frac{d\ln\tilde{\rho}}{dr} \right] \right) \right\} W \right], \end{split}$$

**Note:** In case of a constant kinematic viscosity, the  $d \ln \nu / dr$  terms vanish. If in addition,the background density is constant, the  $d \ln \tilde{\rho} / dr$  terms also vanish. In that Boussinesq limit, this viscosity term would then be simplified as

$$\boldsymbol{e_r} \cdot \Delta \boldsymbol{u} = -\Delta_H \left[ \frac{\partial^2 W}{\partial r^2} + \Delta_H W \right].$$

Using Eq. (4.10) then allows to finally write the time-evolution equation for the poloidal potential  $W_{\ell mn}$ :

$$E \frac{\ell(\ell+1)}{r^{2}} \left[ \left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \frac{4}{3} \nu \left( \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{1}{r} \left[ 3 \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right] \right) \right\} C_{n}$$

$$-\nu \left\{ 2 \frac{d \ln \nu}{dr} - \frac{1}{3} \frac{d \ln \tilde{\rho}}{dr} \right\} C'_{n}$$

$$-\nu C''_{n} \qquad \left[ W_{\ell m n} \right]$$

$$+ \left[ C'_{n} - \frac{d \ln \tilde{\rho}}{dr} C_{n} \right] \qquad P_{\ell m n}$$

$$- \left[ \frac{Ra E}{Pr} \tilde{\rho} g(r) \right] C_{n} \qquad s_{\ell m n}$$

$$- \left[ \frac{Ra \xi E}{Sc} \tilde{\rho} g(r) \right] C_{n} \qquad \xi_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{W} = \int d\Omega Y_{\ell}^{m*} \mathcal{N}^{W} = \int d\Omega Y_{\ell}^{m*} \mathbf{e}_{r} \cdot \mathbf{F}. \qquad (4.20)$$

Here,  $d\Omega$  is the spherical surface element. We use the summation convention for the Chebyshev index n. The radial derivatives of Chebyshev polynomials are denoted by primes.

#### See also:

The exact computation of the linear terms of (4.20) are coded in the subroutines get\_wpMat

### **4.4.2** Equation for the toroidal potential Z

The temporal evolution of Z is obtained by taking the radial component of the curl of the Navier-Stokes equation (i.e.  $e_r \cdot \nabla \times$ ). For the time derivative, one gets using (4.2):

$$e_{r} \cdot \nabla \times \left( \frac{\partial \tilde{\rho} u}{\partial t} \right) = \frac{\partial}{\partial t} (e_{r} \cdot \nabla \times \tilde{\rho} u) = -\frac{\partial}{\partial t} (\Delta_{H} Z) = -\Delta_{H} \frac{\partial Z}{\partial t}.$$

The pressure gradient, one has

$$\nabla \times \left[ \tilde{\rho} \nabla \left( \frac{p'}{\tilde{\rho}} \right) \right] = \nabla \tilde{\rho} \times \nabla \left( \frac{p'}{\tilde{\rho}} \right) + \underbrace{\tilde{\rho} \nabla \times \left[ \nabla \left( \frac{p'}{\tilde{\rho}} \right) \right]}_{-0}.$$

This expression has no component along  $e_r$ , as a consequence, there is no pressure gradient contribution here. The gravity term also vanishes as  $\nabla \times (\tilde{\rho}g(r)e_r)$  has no radial component.

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times \left[ \boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} \right] &= -\nu \, \Delta_H \left[ \frac{\partial^2 Z}{\partial r^2} + \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \, \frac{\partial Z}{\partial r} \right. \\ &\left. - \left( \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^2 \ln \tilde{\rho}}{dr^2} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} - \Delta_H \right) Z \right]. \end{split}$$

Note: Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$\boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times (\Delta \boldsymbol{u}) = -\Delta_H \left[ \frac{\partial^2 Z}{\partial r^2} + \Delta_H Z \right].$$

Using Eq. (4.10) then allows to finally write the time-evolution equation for the poloidal potential  $Z_{\ell mn}$ :

$$E \frac{\ell(\ell+1)}{r^{2}} \left[ \left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \nu \left( \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \frac{d \ln \nu}{dr} + \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{2}{r} \frac{d \ln \tilde{\rho}}{dr} \right) \right\} C_{n}$$

$$-\nu \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C'_{n}$$

$$-\nu C''_{n} \qquad \right] \quad Z_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{Z} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{Z} = \int d\Omega Y_{\ell}^{m \star} e_{r} \cdot (\nabla \times \mathbf{F}) .$$

$$(4.21)$$

#### See also:

The exact computation of the linear terms of (4.21) are coded in the subroutines get zMat

### **4.4.3** Equation for pressure *P*

The evolution of equation for pressure is obtained by taking the horizontal divergence (i.e.  $\nabla_H \cdot$ ) of the Navier-Stokes equation. This operator is defined such that

$$\nabla_H \cdot \boldsymbol{a} = r \sin \frac{\partial (\sin \theta \, a_\theta)}{\partial \theta} + r \sin \frac{\partial a_\phi}{\partial \phi}.$$

This relates to the total divergence via:

$$oldsymbol{
abla} \cdot oldsymbol{a} = rac{1}{r^2} rac{\partial (r^2 a_r)}{\partial r} + oldsymbol{
abla}_H \cdot oldsymbol{a}.$$

The time-derivative term is thus expressed by

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left( \tilde{\rho} \frac{\partial \boldsymbol{u}}{\partial t} \right) &= \frac{\partial}{\partial t} \left[ \boldsymbol{\nabla}_{H} \cdot \left( \tilde{\rho} \boldsymbol{u} \right) \right], \\ &= \frac{\partial}{\partial t} \left[ \boldsymbol{\nabla} \cdot \left( \tilde{\rho} \boldsymbol{u} \right) - \frac{1}{r^{2}} \frac{\partial (r^{2} \tilde{\rho} u_{r})}{\partial r} \right], \\ &= -\frac{\partial}{\partial t} \left[ \frac{\partial (\tilde{\rho} u_{r})}{\partial r} + \frac{2 \tilde{\rho} u_{r}}{r} \right], \\ &= \frac{\partial}{\partial t} \left[ \frac{\partial (\Delta_{H} W)}{\partial r} + \frac{2}{r} \Delta_{H} W \right], \\ &= \Delta_{H} \frac{\partial}{\partial t} \left( \frac{\partial W}{\partial r} \right). \end{split}$$

We note that the gravity term vanishes since  $\nabla_H \cdot (\tilde{\rho}g(r)e_r) = 0$ . Concerning the pressure gradient, one has

$$-\boldsymbol{\nabla}_{H}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]=-\left\{\boldsymbol{\nabla}\cdot\left[\tilde{\rho}\boldsymbol{\nabla}\left(\frac{p'}{\tilde{\rho}}\right)\right]-\frac{1}{r^{2}}\frac{\partial}{\partial r}\left[r^{2}\tilde{\rho}\frac{\partial}{\partial r}\left(\frac{p'}{\tilde{\rho}}\right)\right]\right\}=-\Delta_{H}\,p'.$$

The viscosity term then reads

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left( \boldsymbol{\nabla} \cdot \boldsymbol{\mathsf{S}} \right) = & \nu \, \Delta_{H} \left[ \frac{\partial^{3} W}{\partial r^{3}} + \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) \frac{\partial^{2} W}{\partial r^{2}} \right. \\ & - \left[ \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left( \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) - \Delta_{H} \right] \frac{\partial W}{\partial r} \\ & - \left( \frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \Delta_{H} W \right]. \end{split}$$

Note: Once again, this viscous term can be greatly simplified in the Boussinesq limit:

$$\boldsymbol{\nabla}_{H}\cdot(\Delta\boldsymbol{u}) = -\Delta_{H}\left[\frac{\partial^{3}W}{\partial r^{3}} + \Delta_{H}\,\frac{\partial W}{\partial r} - \frac{2}{r}\Delta_{H}\,W\right]\;.$$

Using Eq. (4.10) then allows to finally write the equation for the pressure  $P_{\ell mn}$ :

$$E\frac{\ell(\ell+1)}{r^{2}} \left[ -\nu \left( \frac{2}{3} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} + \frac{d \ln \nu}{dr} \right) \frac{\ell(\ell+1)}{r^{2}} C_{n} \right]$$

$$\left\{ \frac{\partial}{\partial t} + \nu \frac{\ell(\ell+1)}{r^{2}} + \nu \left[ \frac{d^{2} \ln \tilde{\rho}}{dr^{2}} + \frac{d \ln \nu}{dr} \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \left( \frac{d \ln \nu}{dr} + \frac{d \ln \tilde{\rho}}{dr} \right) \right] \right\} C'_{n}$$

$$-\nu \left( \frac{d \ln \nu}{dr} - \frac{d \ln \tilde{\rho}}{dr} \right) C''_{n}$$

$$-\nu C'''_{n} \qquad \left[ W_{\ell m n} \right]$$

$$+ \left[ \frac{\ell(\ell+1)}{r^{2}} \right] C_{n} \qquad P_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{P} = -\int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{P} = -\int d\Omega Y_{\ell}^{m \star} \nabla_{H} \cdot \mathbf{F} .$$

$$(4.22)$$

#### See also:

The exact computation of the linear terms of (4.22) are coded in the subroutines get\_wpMat

**Note:** We note that the terms on the left hand side of (4.20), (4.21) and (4.22) resulting from the viscous term, the pressure gradient, the buoyancy term, and the explicit time derivative completely decouple in spherical harmonic degree and order.

The terms that do not decouple, namely Coriolis force, Lorentz force and advection of momentum, are collected on the right-hand side of (4.20), (4.21) and (4.22) into the forcing term  $\mathbf{F}$ :

$$F = -2 \tilde{\rho} e_z \times u - E \tilde{\rho} u \cdot \nabla u + \frac{1}{Pm} (\nabla \times B) \times B.$$
 (4.23)

Resolving F into potential functions is not required. Its numerical evaluation is discussed below.

### **4.4.4 Equation for entropy** s

The equation for the entropy (or temperature in the Boussinesq limit) is given by

$$\frac{1}{Pr} \left[ \left( Pr \frac{\partial}{\partial t} + \kappa \frac{\ell(\ell+1)}{r^2} \right) C_n \right]$$

$$-\kappa \left( \frac{d \ln \kappa}{dr} + \frac{d \ln \tilde{\rho}}{dr} + + \frac{d \ln \tilde{T}}{dr} + \frac{2}{r} \right) C'_n$$

$$-\kappa C''_n \qquad \left] \quad s_{\ell m n} \right]$$

$$= \mathcal{N}_{\ell m}^S = \int d\Omega Y_{\ell}^{m*} \mathcal{N}^S = \int d\Omega Y_{\ell}^{m*} \left[ -\mathbf{u} \cdot \nabla s + \frac{Pr Di}{Ra} \frac{1}{\tilde{\rho} \tilde{T}} \left( \Phi_{\nu} + \frac{\lambda}{Pm^2 E} j^2 \right) \right].$$
(4.24)

In this expression,  $j = \nabla \times B$  is the current. Once again, the numerical evaluation of the right-hand-side (i.e. the non-linear terms) is discussed *below*.

#### See also:

The exact computation of the linear terms of (4.24) are coded in the subroutines get\_sMat

### 4.4.5 Equation for chemical composition $\xi$

The equation for the chemical composition is given by

$$\frac{1}{Sc} \left[ \left( Sc \frac{\partial}{\partial t} + \kappa_{\xi} \frac{\ell(\ell+1)}{r^{2}} \right) C_{n} \right]$$

$$-\kappa_{\xi} \left( \frac{d \ln \kappa_{\xi}}{dr} + \frac{d \ln \tilde{\rho}}{dr} + \frac{2}{r} \right) C'_{n}$$

$$-\kappa_{\xi} C''_{n} \qquad \left[ -\kappa_{\xi} C''_{n} \qquad \right] \qquad \xi_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{\xi} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{\xi} = \int d\Omega Y_{\ell}^{m \star} \left[ -\mathbf{u} \cdot \nabla \xi \right].$$
(4.25)

Once again, the numerical evaluation of the right-hand-side (i.e. the non-linear term) is discussed below.

#### See also:

The exact computation of the linear terms of (4.25) are coded in the subroutines get\_xiMat

### 4.4.6 Equation for the poloidal magnetic potential q

The equation for the poloidal magnetic potential is the radial component of the dynamo equation since

$$\boldsymbol{e_r} \cdot \left(\frac{\partial \boldsymbol{B}}{\partial t}\right) = \frac{\partial}{\partial t} (\boldsymbol{e_r} \cdot \boldsymbol{B}) = -\Delta_H \frac{\partial g}{\partial t}.$$

The spectral form then reads

$$\frac{\ell(\ell+1)}{r^2} \left[ \left( \frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^2} \right) C_n - \frac{1}{Pm} \lambda C_n'' \right] g_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^g = \int d\Omega Y_\ell^{m \star} \mathcal{N}^g = \int d\Omega Y_\ell^{m \star} \mathbf{e}_{\mathbf{r}} \cdot \mathbf{D}.$$
(4.26)

#### See also:

The exact computation of the linear terms of (4.26) are coded in the subroutines get\_bMat

### 4.4.7 Equation for the toroidal magnetic potential h

The equation for the toroidal magnetic field coefficient reads

$$\frac{\ell(\ell+1)}{r^{2}} \left[ \left( \frac{\partial}{\partial t} + \frac{1}{Pm} \lambda \frac{\ell(\ell+1)}{r^{2}} \right) C_{n} - \frac{1}{Pm} \frac{d\lambda}{dr} C'_{n} - \frac{1}{Pm} \lambda C''_{n} \right] h_{\ell m n}$$

$$= \mathcal{N}_{\ell m}^{h} = \int d\Omega Y_{\ell}^{m \star} \mathcal{N}^{h} = \int d\Omega Y_{\ell}^{m \star} e_{r} \cdot (\nabla \times \mathbf{D}) . \tag{4.27}$$

#### See also:

The exact computation of the linear terms of (4.27) are coded in the subroutines get\_bMat

**Note:** We note that the terms on the left hand side of (4.26) and (4.27) resulting from the magnetic diffusion term and the explicit time derivative completely decouple in spherical harmonic degree and order.

The dynamo term does not decouple:

$$D = \nabla \times (\boldsymbol{u} \times \boldsymbol{B}) . \tag{4.28}$$

We have now derived a full set of equations (4.20), (4.21), (4.22), (4.24), (4.26) and (4.27), each describing the evolution of a single spherical harmonic mode of the six unknown fields (assuming that the terms on the right hand side are given). Each equation couples N+1 Chebyshev coefficients for a given spherical harmonic mode  $(\ell, m)$ . Typically, a collocation method is employed to solve for the Chebyshev coefficients. This means that the equations are required to be exactly satisfied at N-1 grid points defined by the equations (4.18) and (4.19). Excluded are the points  $r=r_i$  and  $r=r_o$ , where the *boundary conditions* provide additional constraints on the set of Chebyshev coefficients.

# 4.5 Time-stepping schemes

Implicit time stepping schemes theoretically offer increased stability and allow for larger time steps. However, fully implicit approaches have the disadvantage that the nonlinear-terms couple all spherical harmonic modes. The potential gain in computational speed is therefore lost at higher resolution, where one very large matrix has to be dealt with rather than a set of much smaller ones. Similar considerations hold for the Coriolis force, one of the dominating forces in the system and therefore a prime candidate for implicit treatment. However, the Coriolis term couples modes  $(\ell, m, n)$  with  $(\ell+1, m, n)$  and  $(\ell-1, m, n)$  and also couples poloidal and toroidal flow potentials. An implicit treatment of the Coriolis term therefore also results in a much larger (albeit sparse) inversion matrix.

We consequently adopt in MagIC a mixed implicit/explicit algorithm. The general differential equation in time can be written in the form

$$\frac{\partial}{\partial t}x + \mathcal{I}(x,t) = \mathcal{E}(x,t) .$$

where  $\mathcal{I}$  denotes the terms treated in an implicit time step and  $\mathcal{E}$  the terms treated explicitly, i.e.~the nonlinear and Coriolis contributions. The discretized implicit time step is given by

$$\left(\frac{x(t+\delta t)-x(t)}{\delta t}\right)_{I} = -\alpha \, \mathcal{I}(x,t+\delta t) - (1-\alpha) \, \mathcal{I}(x,t) \ .$$

where  $\alpha$  is the weight of the new time step. For  $\alpha = 0.5$  we recover a classic Crank-Nicolson algorithm.

A second order Adams-Bashforth scheme is used for the explicit time step:

$$\left(\frac{x(t+\delta t)-x(t)}{\delta t}\right)_E = \frac{3}{2} \mathcal{E}(x,t) - \frac{1}{2} \mathcal{E}(x,t-\delta t) .$$

The combination of both steps yields

$$\frac{x(t+\delta t)}{\delta t} + \alpha \, \mathcal{I}(x,t+\delta t) = \frac{x(t)}{\delta t} - (1-\alpha) \, \mathcal{I}(x,t) + \frac{3}{2} \, \mathcal{E}(x,t) - \frac{1}{2} \, \mathcal{E}(x,t-\delta t) .$$

In the code such an equation is formulated for each unknown spectral coefficient (expect pressure) of spherical harmonic degree  $\ell$  and order m and for each radial grid point  $r_k$ . Because non-linear terms and the Coriolis force are treated explicitly, the equations decouple for all spherical modes. The different radial grid points, however, couple via the Chebychev modes and form a linear algebraic system of equations that can be solved with standard methods for the different spectral contributions.

For example the respective system of equations for the modes of the poloidal magnetic potential g results from considering the radial component of the dynamo equation:

$$(\mathcal{A}_{kn} + \alpha \,\mathcal{I}_{kn}) \,g_{\ell mn}(t + \delta t) = (\mathcal{A}_{kn} - (1 - \alpha)\,\mathcal{I}_{kn}) \,g_{\ell mn}(t) + \frac{3}{2}\,\mathcal{E}_{k\ell m}(t) - \frac{1}{2}\,\mathcal{E}_{k\ell m}(t - \delta t) \tag{4.29}$$

with

$$\mathcal{A}_{kn} = \frac{\ell(\ell+1)}{r_k^2} \, \frac{1}{\delta t} \mathcal{C}_{nk} \; ,$$

$$\mathcal{I}_{kn} = \frac{\ell(\ell+1)}{r_k^2} \frac{1}{Pm} \left( \frac{\ell(\ell+1)}{r_k^2} \, \mathcal{C}_{nk} - \mathcal{C}_{nk}'' \right) \,,$$

and  $C_{nk} = C_n(r_k)$ .  $A_{kn}$  is a matrix that converts the poloidal field modes  $g_{\ell mn}$  to the radial magnetic field  $B_r(r_k, \ell m)$  for a given spherical harmonic contribution with an additional division by the time step  $\delta t$ :

Here k and n number the radial grid points and the Chebychev coefficients, respectively. Note that the Einstein sum convention is used for Chebychev modes n.

 $\mathcal{I}_{kn}$  is the matrix describing the implicit contribution which is purely diffusive here. Neither  $\mathcal{A}_{kn}$  nor  $\mathcal{I}_{kn}$  depend on time but the former needs to be updated when the time step  $\delta t$  is changed. The only explicit contribution is the nonlinear dynamo term

$$\mathcal{E}_{k\ell m}(t) = \mathcal{N}_{k\ell m}^g = \int d\Omega Y_{\ell}^{m\star} \boldsymbol{e_r} \cdot \boldsymbol{D}(t, r_k, \theta, \phi) .$$

 $\mathcal{E}_{k\ell m}$  is a one dimensional vector for all spherical harmonic combinations  $\ell m$ .

How are these operations organized in the code? Within MagIC the poloidal magnetic field potential is called b. The implicit step for the current time t and the explicit step for the previous time  $t - \delta t$  is combined into one two-dimensional array

$$ext{dbdtLast}(k,lm) = -rac{1}{2}\; \mathcal{E}_{k\ell m}(t-\delta t) - (1-lpha)\; \mathcal{I}_{kn}\; g_{\ell mn}(t)\;.$$

where k numbers the first dimension and the second dimension lm numbers the spherical harmonic modes. The explicit time step part is called dbdt in MagIC:

$$dbdt(k, \ell m) = \mathcal{E}_{k\ell m}$$

The combination of left hand side of (4.29) provides the time stepping matrix for g:

$$bmat(k, n, \ell) = A_{kn} + \alpha \mathcal{I}_{kn} .$$

There is a different time stepping matrix for each spherical harmonic degree  $\ell$ . The linear system of equations solved for the mode  $b(k, \ell m)$  at time  $t = t + \delta t$  is then

$$\begin{aligned} \operatorname{bmat}(k,n,\ell) \star \operatorname{b}_{i+1}(n,\ell m) = & \operatorname{wl} \star \operatorname{dbdt}(k,\ell m) + \operatorname{w2} \star \operatorname{dbdtLast}(k,\ell m) + \\ & \operatorname{Odt} \star \operatorname{dLh}(\ell) \star \operatorname{Or2}(k) \star \operatorname{b}_{i}(n,\ell m) \\ = & \operatorname{rhs}(k,\ell m) \end{aligned}$$

with

$${\rm w2} = -1/2 \frac{\delta t}{\delta t_{old}} \ , \ {\rm w1} = 1 - {\rm w2} \ , \ {\rm Odt} = 1/\delta t \ , \ {\rm dLh}(\ell) = \ell(\ell+1) \ , \ {\rm Or2}(k) = 1/r_k^2.$$

The respective equations for the poloidal flow potential are somewhat more complex and involve coupling to the pressure.....

**Note:** The poloidal flow potential (4.20) and the pressure (4.22) are nevertheless coupled for a given spherical harmonic mode. Likewise the poloidal flow and entropy (or temperature) equations should also couple, but here MagIC takes the shortcut of updating entropy first and using the already updated value for an explicit treatment of buoyancy.

Courant's condition offers a guideline concerning the value of  $\delta t$ , demanding that  $\delta t$  should be smaller than the advection time between two grid points. Strong Lorentz forces require an additional stability criterion that is obtained by replacing the flow speed by Alfvén's velocity in a modified Courant criterion. The explicit treatment of the Coriolis force requires that the time step is limited to a fraction of the rotation period, which may be the relevant criterion at low Ekman number when flow and magnetic field remain weak. Non-homogeneous grids and other numerical effects generally require an additional safety factor in the choice of  $\delta t$ .

### 4.6 Coriolis force and nonlinear terms

### 4.6.1 Nonlinear terms entering the equation for W

The nonlinear term  $\mathcal{N}^W$  that enters the equation for the poloidal potential (4.20) contains the radial component of the advection, the Lorentz force and Coriolis force. In spherical coordinate, the two first contributions read:

$$\tilde{\rho}\left(\boldsymbol{u}\cdot\boldsymbol{\nabla}\boldsymbol{u}\right) = \begin{cases}
A_{r} \\
A_{\theta} \\
A_{\phi}
\end{cases} = \begin{cases}
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{r}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{r}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{r}}{\partial \phi} - \frac{u_{\theta}^{2} + u_{\phi}^{2}}{r}\right) + \frac{1}{Pm}\left(j_{\theta}B_{\phi} - j_{\phi}B_{\theta}\right), \\
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{\theta}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{\theta}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{\theta}}{\partial \phi} + \frac{u_{r}u_{\theta}}{r} - \frac{\cos\theta}{r\sin\theta}u_{\phi}^{2}\right) + \frac{1}{Pm}\left(j_{\phi}B_{r} - j_{r}B_{\phi}\right), \\
-\tilde{\rho}E\left(u_{r}\frac{\partial u_{\phi}}{\partial r} + \frac{u_{\theta}}{r}\frac{\partial u_{\phi}}{\partial \theta} + \frac{u_{\phi}}{r\sin\theta}\frac{\partial u_{\phi}}{\partial \phi} + \frac{u_{r}u_{\phi}}{r} + \frac{\cos\theta}{r\sin\theta}u_{\theta}u_{\phi}\right) + \frac{1}{Pm}\left(j_{r}B_{\theta} - j_{\theta}B_{r}\right), \end{cases}$$
(4.30)

The Coriolis force can be expressed as a function of the potentials W and Z using (4.4)

$$2\tilde{\rho}\boldsymbol{e_r}\cdot(\boldsymbol{u}\times\boldsymbol{e_z})=2\sin\theta\,\tilde{\rho}u_{\phi}=\frac{2}{r}\left(\frac{\partial^2W}{\partial r\partial\phi}-\sin\theta\frac{\partial Z}{\partial\theta}\right)\,.$$

The nonlinear terms that enter the equation for the poloidal potential (4.20) thus reads:

$$\mathcal{N}^{W} = \frac{2}{r} \left( \frac{\partial^{2} W}{\partial r \partial \phi} - \sin \theta \frac{\partial Z}{\partial \theta} \right) + \mathcal{A}_{r}.$$

The  $\theta$ -derivative entering the radial component of the Coriolis force is thus the operator  $\vartheta_2$  defined in (4.12). Using the recurrence relation, one thus finally gets in spherical harmonic space:

$$\mathcal{N}_{\ell m}^{W} = \frac{2}{r} \left[ im \frac{\partial W_{\ell}^{m}}{\partial r} - (\ell - 1) c_{\ell}^{m} Z_{\ell-1}^{m} + (\ell + 2) c_{\ell+1}^{m} Z_{\ell+1}^{m} \right] + \mathcal{A}_{r\ell}^{m}.$$
(4.31)

To get this expression, we need to first compute  $\mathcal{A}_r$  in the physical space. This term is computed in the subroutine get\_nl in the module grid\_space\_arrays\_mod.  $\mathcal{A}_r$  is then transformed to the spectral space by using a Legendre and a Fourier transform to produce  $\mathcal{A}_r^m$ .

#### See also:

The final calculations of (4.31) are done in the subroutine  $get\_td$ .

### 4.6.2 Nonlinear terms entering the equation for Z

The nonlinear term  $\mathcal{N}^Z$  that enters the equation for the toroidal potential (4.21) contains the radial component of the curl of the advection and Coriolis force. The Coriolis force can be rewritten as a function of W and Z:

$$\begin{split} \boldsymbol{e_r} \cdot \boldsymbol{\nabla} \times \left[ (2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e_z} \right] &= 2\boldsymbol{e_r} \cdot \left[ (\boldsymbol{e_z} \cdot \boldsymbol{\nabla})(\tilde{\rho}\boldsymbol{u}) \right], \\ &= 2 \left[ \cos\theta \frac{\partial(\tilde{\rho}u_r)}{\partial r} - \frac{\sin\theta}{r} \frac{\partial(\tilde{\rho}u_r)}{\partial \theta} + \frac{\tilde{\rho}u_\theta \sin\theta}{r} \right], \\ &= 2 \left[ -\cos\theta \frac{\partial}{\partial r} (\Delta_H W) + \frac{\sin\theta}{r} \frac{\partial}{\partial \theta} (\Delta_H W) + \frac{\sin\theta}{r^2} \frac{\partial^2 W}{\partial r \partial \theta} + \frac{1}{r^2} \frac{\partial Z}{\partial \phi} \right]. \end{split}$$

Using the  $\vartheta$  operators defined in (4.12)-(4.15) then allows to rewrite the Coriolis force in the following way:

$$e_r \cdot \nabla \times [(2\tilde{\rho}u) \times e_z] = \frac{2}{r^2} \left( \vartheta_3 \frac{\partial W}{\partial r} - \frac{1}{r} \vartheta_4 W + \frac{\partial Z}{\partial \phi} \right).$$
 (4.32)

The contributions of nonlinear advection and Lorentz forces that enter the equation for the toroidal potential are written this way:

$$\frac{1}{r\sin\theta} \left[ \frac{\partial(\sin\theta \mathcal{A}_{\phi})}{\partial\theta} - \frac{\partial \mathcal{A}_{\theta}}{\partial\phi} \right].$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is to follow the following steps:

- 1. Compute the quantities  $\mathcal{A}_{\phi}/r\sin\theta$  and  $\mathcal{A}_{\theta}/r\sin\theta$  in the physical space. In the code, this step is computed in the subroutine get\_nl in the module grid\_space\_arrays\_mod.
- 2. Transform  $\mathcal{A}_{\phi}/r\sin\theta$  and  $\mathcal{A}_{\theta}/r\sin\theta$  to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules  $legendre\_grid\_to\_spec$  and fft. After this step  $\mathcal{A}t_{\ell}^{m}$  and  $\mathcal{A}p_{\ell}^{m}$  are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$\vartheta_1 \mathcal{A} p_\ell^m - \frac{\partial \mathcal{A} t_\ell^m}{\partial \phi} \,. \tag{4.33}$$

Using (4.32) and (4.33), one thus finally gets

$$\mathcal{N}_{\ell m}^{Z} = \frac{2}{r^{2}} \left[ (\ell - 1)(\ell + 1) c_{\ell}^{m} \frac{\partial W_{\ell-1}^{m}}{\partial r} + \ell(\ell + 2) c_{\ell+1}^{m} \frac{\partial W_{\ell+1}^{m}}{\partial r} - \frac{\ell(\ell - 1)(\ell + 1)}{r} c_{\ell}^{m} W_{\ell-1}^{m} + \frac{\ell(\ell + 1)(\ell + 2)}{r} c_{\ell+1}^{m} W_{\ell+1}^{m} + im Z_{\ell}^{m} \right] + (\ell + 1) c_{\ell}^{m} \mathcal{A} p_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{A} p_{\ell+1}^{m} - im \mathcal{A} t_{\ell}^{m}.$$
(4.34)

#### See also:

The final calculations of (4.34) are done in the subroutine  $get\_td$ .

### **4.6.3** Nonlinear terms entering the equation for *P*

The nonlinear term  $\mathcal{N}^P$  that enters the equation for the pressure (4.22) contains the horizontal divergence of the advection and Coriolis force. The Coriolis force can be rewritten as a function of W and Z:

$$\begin{split} \boldsymbol{\nabla}_{H} \cdot \left[ (2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e}_{\boldsymbol{z}} \right] &= 2\boldsymbol{e}_{\boldsymbol{z}} \cdot \left[ \boldsymbol{\nabla} \times (\tilde{\rho}\boldsymbol{u}) \right] - \left( \frac{\partial}{\partial r} + \frac{2}{r} \right) \left[ \boldsymbol{e}_{\boldsymbol{r}} \cdot (2\tilde{\rho}\boldsymbol{u} \times \boldsymbol{e}_{\boldsymbol{z}}) \right], \\ &= -2\cos\theta \, \Delta_{H} Z - 2\sin\theta \left[ -\frac{1}{r\sin\theta} \frac{\partial}{\partial \phi} \left( \frac{\partial^{2}}{\partial r^{2}} + \Delta_{H} \right) W + \frac{1}{r} \frac{\partial^{2}Z}{\partial r\partial\theta} \right] \\ &- \left( \frac{\partial}{\partial r} + \frac{2}{r} \right) \left[ 2\sin\theta \tilde{\rho} u_{\phi} \right], \\ &= 2 \left[ \frac{1}{r} \left( \Delta_{H} + \frac{\partial^{2}}{\partial r^{2}} \right) \frac{\partial W}{\partial \phi} - \cos\theta \Delta_{H} Z - \frac{\sin\theta}{r} \frac{\partial^{2}Z}{\partial r\partial\theta} \right] \\ &- \left( \frac{\partial}{\partial r} + \frac{2}{r} \right) \left[ \frac{2}{r} \left( \frac{\partial^{2}W}{\partial r\partial\phi} - \sin\theta \frac{\partial Z}{\partial\theta} \right) \right], \\ &= 2 \left( \frac{\Delta_{H}}{r} \frac{\partial W}{\partial \phi} - \frac{1}{r^{2}} \frac{\partial^{2}W}{\partial \phi\partial r} - \cos\theta \Delta_{H} Z + \frac{\sin\theta}{r^{2}} \frac{\partial Z}{\partial\theta} \right). \end{split}$$

Using the  $\vartheta$  operators defined in (4.14)-(4.15) then allows to rewrite the Coriolis force in the following way:

$$\nabla_{H} \cdot \left[ (2\tilde{\rho}\boldsymbol{u}) \times \boldsymbol{e}_{\boldsymbol{z}} \right] = \frac{2}{r^{2}} \left( -\frac{L_{H}}{r} \frac{\partial W}{\partial \phi} - \frac{\partial^{2} W}{\partial \phi \partial r} + \vartheta_{3} Z \right). \tag{4.35}$$

The contributions of nonlinear advection and Lorentz forces that enter the equation for pressure are written this way:

$$\frac{1}{r\sin\theta} \left[ \frac{\partial(\sin\theta\mathcal{A}_{\theta})}{\partial\theta} + \frac{\partial\mathcal{A}_{\phi}}{\partial\phi} \right] .$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the same three steps as for the advection term entering the equation for Z.

$$\vartheta_1 \mathcal{A} t_\ell^m + \frac{\partial \mathcal{A} p_\ell^m}{\partial \phi} \,. \tag{4.36}$$

Using (4.35) and (4.36), one thus finally gets

$$\mathcal{N}_{\ell m}^{P} = \frac{2}{r^{2}} \left[ -im \frac{\ell(\ell+1)}{r} W_{\ell}^{m} - im \frac{\partial W_{\ell}^{m}}{\partial r} + (\ell-1)(\ell+1) c_{\ell}^{m} Z_{\ell-1}^{m} + \ell(\ell+2) c_{\ell+1}^{m} Z_{\ell+1}^{m} \right] + (\ell+1) c_{\ell}^{m} \mathcal{A}t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{A}t_{\ell+1}^{m} + im \mathcal{A}p_{\ell}^{m}.$$
(4.37)

#### See also:

The final calculations of (4.37) are done in the subroutine  $get\_td$ .

### 4.6.4 Nonlinear terms entering the equation for s

The nonlinear terms that enter the equation for entropy/temperature (4.24) are twofold: (i) the advection term, (ii) the viscous and Ohmic heating terms (that vanish in the Boussinesq limit of the Navier Stokes equations).

Viscous and Ohmic heating are directly calculated in the physical space by the subroutine  $get_nl$  in the module  $grid_space_arrays_mod$ . Let's introduce  $\mathcal{H}$ , the sum of the viscous and Ohmic heating terms.

$$\mathcal{H} = \frac{Pr\,Di}{Ra} \frac{1}{\tilde{\rho}\tilde{T}} \left( \Phi_{\nu} + \frac{\lambda}{Pm^2\,E} \, j^2 \right) \,.$$

Expanding this term leads to:

$$\mathcal{H} = \frac{Pr\,Di}{Ra} \frac{1}{\tilde{\rho}\tilde{T}} \left[ \tilde{\rho}\nu \left\{ 2 \left( \frac{\partial u_r}{\partial r} \right)^2 + 2 \left( \frac{1}{r} \frac{\partial u_\theta}{\partial \theta} + \frac{u_r}{r} \right)^2 + 2 \left( \frac{1}{r\sin\theta} \frac{\partial u_\phi}{\partial \phi} + \frac{u_r}{r} + \frac{\cos\theta}{r\sin\theta} u_\theta \right)^2 \right. \\ + \left. \left( r \frac{\partial}{\partial r} \left( \frac{u_\theta}{r} \right) + \frac{1}{r} \frac{\partial u_r}{\partial \theta} \right)^2 + \left( r \frac{\partial}{\partial r} \left( \frac{u_\phi}{r} \right) + \frac{1}{r\sin\theta} \frac{\partial u_r}{\partial \phi} \right)^2 \right. \\ + \left. \left( \frac{\sin\theta}{r} \frac{\partial}{\partial \theta} \left( \frac{u_\phi}{\sin\theta} \right) + \frac{1}{r\sin\theta} \frac{\partial u_\theta}{\partial \phi} \right)^2 - \frac{2}{3} \left( \frac{d\ln\tilde{\rho}}{dr} u_r \right)^2 \right\} \\ + \frac{\lambda}{Pm^2 E} \left\{ j_r^2 + j_\theta^2 + j_\phi^2 \right\} \right].$$

$$(4.38)$$

This term is then transformed to the spectral space with a Legendre and a Fourier transform to produce  $\mathcal{H}_{\ell}^{m}$ .

The treatment of the advection term  $-u \cdot \nabla s$  is a bit different. It is in a first step rearranged as follows

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}s = -\frac{1}{\tilde{\rho}}\left[\boldsymbol{\nabla}\cdot(\tilde{\rho}s\boldsymbol{u}) - s\underbrace{\boldsymbol{\nabla}\cdot(\tilde{\rho}\boldsymbol{u})}_{-0}\right].$$

The quantities that are calculated in the physical space are thus simply the product of entropy/temperature s by the velocity components. This defines three variables defined in the grid space that are computed in the subroutine get\_nl:

$$\mathcal{US}_r = \tilde{\rho} s u_r, \quad \mathcal{US}_{\theta} = \tilde{\rho} s u_{\theta}, \quad \mathcal{US}_{\phi} = \tilde{\rho} s u_{\phi},$$

To get the actual advection term, one must then apply the divergence operator to get:

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}s = -\frac{1}{\tilde{\rho}}\left[\frac{1}{r^2}\frac{\partial}{\partial r}\left(r^2\,\mathcal{U}\mathcal{S}_r\right) + \frac{1}{r\sin\theta}\frac{\partial}{\partial\theta}\left(\sin\theta\,\mathcal{U}\mathcal{S}_\theta\right) + \frac{1}{r\sin\theta}\frac{\partial\,\mathcal{U}\mathcal{S}_\phi}{\partial\phi}\right]\,.$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is then to follow the following steps:

- 1. Compute the quantities  $r^2 \mathcal{US}_r$ ,  $\mathcal{US}_{\phi}/r\sin\theta$  and  $\mathcal{US}_{\theta}/r\sin\theta$  in the physical space. In the code, this step is computed in the subroutine get\_nl in the module grid\_space\_arrays\_mod.
- 2. Transform  $r^2 \mathcal{US}_r$ ,  $\mathcal{US}_\phi/r\sin\theta$  and  $\mathcal{US}_\theta/r\sin\theta$  to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules  $legendre\_grid\_to\_spec$  and fft. After this step  $\mathcal{US}r_\ell^m$ ,  $\mathcal{US}t_\ell^m$  and  $\mathcal{US}p_\ell^m$  are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$-\frac{1}{\tilde{\rho}} \left[ \frac{1}{r^2} \frac{\partial \mathcal{U} \mathcal{S} r_{\ell}^m}{\partial r} + \vartheta_1 \mathcal{U} \mathcal{S} t_{\ell}^m + \frac{\partial \mathcal{U} \mathcal{S} p_{\ell}^m}{\partial \phi} \right]. \tag{4.39}$$

Using (4.38) and (4.39), one thus finally gets

$$\left| \mathcal{N}_{\ell m}^{S} = -\frac{1}{\tilde{\rho}} \left[ \frac{1}{r^{2}} \frac{\partial \mathcal{U} \mathcal{S} r_{\ell}^{m}}{\partial r} + (\ell + 1) c_{\ell}^{m} \mathcal{U} \mathcal{S} t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{U} \mathcal{S} t_{\ell+1}^{m} + im \mathcal{U} \mathcal{S} p_{\ell}^{m} \right] + \mathcal{H}_{\ell}^{m}. \right|$$
(4.40)

#### See also:

The  $\theta$  and  $\phi$  derivatives that enter (4.40) are done in the subroutine  $get\_td$ . The radial derivative is computed afterwards at the very beginning of updateS.

# 4.6.5 Nonlinear terms entering the equation for $\xi$

The nonlinear term that enters the equation for chemical composition (4.25) is the advection term. This term is treated the same way as the advection term that enters the entropy equation. It is in a first step rearranged as follows

$$-\boldsymbol{u}\cdot\boldsymbol{
abla}\xi=-rac{1}{ ilde{
ho}}\left[\boldsymbol{
abla}\cdot( ilde{
ho}\xi\boldsymbol{u})-\xi\underbrace{\boldsymbol{
abla}\cdot( ilde{
ho}\boldsymbol{u})}_{=0}
ight]\,.$$

The quantities that are calculated in the physical space are thus simply the product of composition  $\xi$  by the velocity components. This defines three variables defined in the grid space that are computed in the subroutine  $qet_n1$ :

$$\mathcal{U}\mathcal{X}_r = \tilde{\rho}\xi u_r, \quad \mathcal{U}\mathcal{S}_\theta = \tilde{\rho}\xi u_\theta, \quad \mathcal{U}\mathcal{X}_\phi = \tilde{\rho}\xi u_\phi,$$

To get the actual advection term, one must then apply the divergence operator to get:

$$-\boldsymbol{u}\cdot\boldsymbol{\nabla}\xi = -\frac{1}{\tilde{\rho}}\left[\frac{1}{r^2}\frac{\partial}{\partial r}\left(r^2\,\mathcal{U}\mathcal{X}_r\right) + \frac{1}{r\sin\theta}\frac{\partial}{\partial\theta}\left(\sin\theta\,\mathcal{U}\mathcal{X}_\theta\right) + \frac{1}{r\sin\theta}\frac{\partial\,\mathcal{U}\mathcal{X}_\phi}{\partial\phi}\right]\,.$$

To make use of the recurrence relations (4.12)-(4.15), the actual strategy is then to follow the following steps:

- 1. Compute the quantities  $r^2 \mathcal{U} \mathcal{X}_r$ ,  $\mathcal{U} \mathcal{X}_\phi / r \sin \theta$  and  $\mathcal{U} \mathcal{X}_\theta / r \sin \theta$  in the physical space. In the code, this step is computed in the subroutine get\_nl in the module grid\_space\_arrays\_mod.
- 2. Transform  $r^2 \mathcal{U} \mathcal{X}_r$ ,  $\mathcal{U} \mathcal{X}_{\phi}/r \sin \theta$  and  $\mathcal{U} \mathcal{X}_{\theta}/r \sin \theta$  to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules  $legendre\_grid\_to\_spec$  and fft. After this step  $\mathcal{U} \mathcal{X} r_{\ell}^m$ ,  $\mathcal{U} \mathcal{X} t_{\ell}^m$  and  $\mathcal{U} \mathcal{X} p_{\ell}^m$  are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$-\frac{1}{\tilde{\rho}} \left[ \frac{1}{r^2} \frac{\partial \mathcal{UX} r_{\ell}^m}{\partial r} + \vartheta_1 \mathcal{UX} t_{\ell}^m + \frac{\partial \mathcal{UX} p_{\ell}^m}{\partial \phi} \right].$$

One thus finally gets

$$\mathcal{N}_{\ell m}^{\xi} = -\frac{1}{\tilde{\rho}} \left[ \frac{1}{r^2} \frac{\partial \mathcal{U} \mathcal{X} r_{\ell}^m}{\partial r} + (\ell+1) c_{\ell}^m \mathcal{U} \mathcal{X} t_{\ell-1}^m - \ell c_{\ell+1}^m \mathcal{U} \mathcal{X} t_{\ell+1}^m + im \mathcal{U} \mathcal{X} p_{\ell}^m \right].$$
(4.41)

#### See also:

The  $\theta$  and  $\phi$  derivatives that enter (4.41) are done in the subroutine  $get\_td$ . The radial derivative is computed afterwards at the very beginning of updateXi.

# 4.6.6 Nonlinear terms entering the equation for g

The nonlinear term that enters the equation for the poloidal potential of the magnetic field (4.26) is the radial component of the induction term (4.28). In the following we introduce the electromotive force  $\mathcal{F} = u \times B$  with its three components

$$\mathcal{F}_r = u_{\theta}B_{\phi} - u_{\phi}B_{\theta}, \quad \mathcal{F}_{\theta} = u_{\phi}B_r - u_rB_{\phi}, \quad \mathcal{F}_{\phi} = u_rB_{\theta} - u_{\theta}B_r.$$

The radial component of the induction term then reads:

$$\mathcal{N}^g = e_{m{r}} \cdot [m{
abla} imes (m{u} imes m{B})] = rac{1}{r \sin heta} \left[ rac{\partial \left( \sin heta \mathcal{F}_{\phi} 
ight)}{\partial heta} - rac{\partial \mathcal{F}_{ heta}}{\partial \phi} 
ight] \ .$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the usual following steps:

- 1. Compute the quantities  $r^2 \mathcal{F}_r$ ,  $\mathcal{F}_{\phi}/r \sin \theta$  and  $\mathcal{F}_{\theta}/r \sin \theta$  in the physical space. In the code, this step is computed in the subroutine get\_nl in the module grid\_space\_arrays\_mod.
- 2. Transform  $r^2 \mathcal{F}_r$ ,  $\mathcal{F}_{\phi}/r \sin \theta$  and  $\mathcal{F}_{\theta}/r \sin \theta$  to the spectral space (thanks to a Legendre and a Fourier transform). In MagIC, this step is computed in the modules  $legendre\_grid\_to\_spec$  and fft. After this step  $\mathcal{F}_{r\ell}^m$ ,  $\mathcal{F}_{\theta\ell}^m$  and  $\mathcal{F}_{\phi\ell}^m$  are defined.
- 3. Calculate the colatitude and theta derivatives using the recurrence relations:

$$\vartheta_1 \mathcal{F}_{\phi\ell}^{\ m} - \frac{\partial \mathcal{F}_{\theta\ell}^{\ m}}{\partial \phi}.$$

We thus finally get

$$\mathcal{N}_{\ell m}^{g} = (\ell + 1) c_{\ell}^{m} \mathcal{F}_{\phi_{\ell-1}}^{m} - \ell c_{\ell+1}^{m} \mathcal{F}_{\phi_{\ell+1}}^{m} - im \mathcal{F}_{\theta_{\ell}}^{m}.$$
(4.42)

#### See also:

The final calculations of (4.42) are done in the subroutine get td.

# 4.6.7 Nonlinear terms entering the equation for h

The nonlinear term that enters the equation for the toroidal potential of the magnetic field (4.27) is the radial component of the curl of the induction term (4.28):

$$\mathcal{N}^{h} = e_{r} \cdot [\nabla \times \nabla \times (\boldsymbol{u} \times \boldsymbol{B})] = e_{r} \cdot [\nabla (\nabla \cdot \boldsymbol{\mathcal{F}}) - \Delta \boldsymbol{\mathcal{F}}],$$

$$= \frac{\partial}{\partial r} \left[ \frac{1}{r^{2}} \frac{\partial (r^{2} \mathcal{F}_{r})}{\partial r} + \frac{1}{r \sin \theta} \frac{\partial (\sin \theta \,\mathcal{F}_{\theta})}{\partial \theta} + \frac{1}{r \sin \theta} \frac{\partial \mathcal{F}_{\phi}}{\partial \phi} \right]$$

$$- \Delta \mathcal{F}_{r} + \frac{2}{r^{2}} \left[ \mathcal{F}_{r} + \frac{1}{\sin \theta} \frac{\partial (\sin \theta \,\mathcal{F}_{\theta})}{\partial \theta} + \frac{1}{\sin \theta} \frac{\partial \mathcal{F}_{\phi}}{\partial \phi} \right],$$

$$= \frac{1}{r^{2}} \frac{\partial}{\partial r} \left[ \frac{r}{\sin \theta} \left( \frac{\partial (\sin \theta \,\mathcal{F}_{\theta})}{\partial \theta} + \frac{\partial \mathcal{F}_{\phi}}{\partial \phi} \right) \right] - \Delta_{H} \,\mathcal{F}_{r}.$$

To make use of the recurrence relations (4.12)-(4.15), we then follow the same steps than for the nonlinear terms that enter the equation for poloidal potential of the magnetic field g:

$$\frac{1}{r^2} \frac{\partial}{\partial r} \left[ r^2 \left( \vartheta_1 \mathcal{F} t_\ell^m + \frac{\partial \mathcal{F} p_\ell^m}{\partial \phi} \right) \right] + L_H \mathcal{F} r_\ell^m \,.$$

We thus finally get

$$\mathcal{N}_{\ell m}^{h} = \ell(\ell+1) \mathcal{F} r_{\ell}^{m} + \frac{1}{r^{2}} \frac{\partial}{\partial r} \left[ r^{2} \left\{ (\ell+1) c_{\ell}^{m} \mathcal{F} t_{\ell-1}^{m} - \ell c_{\ell+1}^{m} \mathcal{F} t_{\ell+1}^{m} + im \mathcal{F} p_{\ell}^{m} \right\} \right].$$
(4.43)

#### See also:

The  $\theta$  and  $\phi$  derivatives that enter (4.43) are computed in the subroutine  $get\_td$ . The remaining radial derivative is computed afterwards at the very beginning of updateB.

# 4.7 Boundary conditions and inner core

### 4.7.1 Mechanical boundary conditions

Since the system of equations is formulated on a radial grid, boundary conditions can simply be satisfied by replacing the collocation equation at grid points  $r_i$  and  $r_o$  with appropriate expressions. The condition of zero radial flow on

the boundaries implies that the poloidal potential has to vanish, i.e.  $W(r_o) = 0$  and  $W(r_i) = 0$ . In Chebychev representation this implies

$$C_n(r)W_{\ell mn} = 0 \quad \text{at} \quad r = r_i, r_o \quad . \tag{4.44}$$

Note that the summation convention with respect to radial modes n is used again. The no-slip condition further requires that the horizontal flow components also have to vanish, provided the two boundaries are at rest. This condition is fulfilled for

$$\frac{\partial W}{\partial r} = 0$$
 and  $Z = 0$ ,

at the respective boundary. In spectral space these conditions read

$$C'_{n}(r)W_{\ell mn} = 0 \text{ at } r = r_{i}, r_{o},$$
 (4.45)

and

$$C_n(r)Z_{\ell mn} = 0 \quad \text{at} \quad r = r_i, r_o, \tag{4.46}$$

for all spherical harmonic modes  $(\ell, m)$ . The conditions (4.44)-(4.46) replace the poloidal flow potential equations (4.20) and the pressure equation (4.22), respectively, at the collocation points  $r_i$  and  $r_o$ .

If the inner-core and/or the mantle are allowed to react to torques, a condition based on the conservation of angular momentum replaces condition (4.46) for the mode ( $\ell = 1, m = 0$ ):

$$I rac{\partial oldsymbol{\omega}}{\partial t} = oldsymbol{\Gamma} \ .$$

The tensor I denotes the moment of inertia of inner core or mantle, respectively,  $\omega$  is the mantle or inner-core rotation rate relative to that of the reference frame, and  $\Gamma$  is the respective torque.

**Free-slip boundary conditions** require that the viscous stress vanishes, which in turn implies that the non-diagonal components  $Sr_{r\phi}$  and  $S_{r\theta}$  of the rate-of-strain tensor vanish. Translated to the spectral representation this requires

$$\left[\mathcal{C}_n''(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\,\mathcal{C}_n'(r)\right]W_{\ell mn} = 0 \ \ \text{and} \ \ \left[\mathcal{C}_n'(r) - \left(\frac{2}{r} + \frac{d\ln\tilde{\rho}}{dr}\right)\,\mathcal{C}_n(r)\right]Z_{\ell mn} = 0 \ .$$

We show the derivation for the somewhat simpler Boussinesq approximation which yields the condition

$$\frac{\partial}{\partial x} \frac{\mathbf{u}_H}{x} = 0$$

where the index H denotes the horizonal flow components. In terms of poloidal and toroidal components this implies

$$\frac{\partial}{\partial r} \frac{1}{r} \left( \boldsymbol{\nabla}_{H} \frac{\partial W}{\partial r} \right) = \boldsymbol{\nabla}_{H} \frac{1}{r} \left( \frac{\partial^{2}}{\partial r^{2}} - \frac{2}{r} \frac{\partial}{\partial r} \right) W = 0$$

and

$$\frac{\partial}{\partial r} \frac{1}{r} \nabla \times \mathbf{e}_r Z = \nabla \times \mathbf{e}_r \frac{1}{r} \left( \frac{\partial}{\partial r} - \frac{2}{r} \right) Z = 0$$

which can be fulfilled with

$$\left(\frac{\partial^2}{\partial r^2} - \frac{2}{r}\frac{\partial}{\partial r}\right)W = 0$$

and

$$\left(\frac{\partial}{\partial r} - \frac{2}{r}\right)Z = 0 \ .$$

In spectral representation this then reads

$$\left(\mathcal{C}_n'' - \frac{2}{r}\mathcal{C}_n'\right)W_{\ell mn} = 0 \ \ \text{and} \ \ \left(\mathcal{C}_n' - \frac{2}{r}\mathcal{C}_n\right)Z_{\ell mn} = 0 \ .$$

## 4.7.2 Thermal boundary conditions

For Entropy or temperature in the Boussinesq approximation either fixed value of fixed flux conditions are used. The former implies

$$s = \text{const.}$$
 or  $T = \text{const.}$ 

at  $r_i$  and/or  $r_o$ , while the latter means

$$\frac{\partial}{\partial r}s = \text{const.}$$
 or  $\frac{\partial}{\partial r}T = \text{const.}$ 

In spectral representation for example the respective entropy condition read

$$C_n s_{\ell mn} = \text{const.}$$
 or  $C'_n s_{\ell mn} = \text{const.}$ 

Appropriate constant values need to be chosen and are instrumental in driving the dynamo when flux conditions are imposed.

# 4.7.3 Boundary conditions for chemical composition

For the chemical composition, either the value or the flux is imposed at the boundaries. The former implies:

$$\xi = \text{const.}$$

at  $r_i$  and/or  $r_o$ , while the latter means

$$\frac{\partial}{\partial r}\xi = \text{const.}$$

In spectral representation, this then reads

$$C_n \xi_{\ell mn} = \text{const.}$$
 or  $C'_n \xi_{\ell mn} = \text{const.}$ 

# 4.7.4 Magnetic boundary conditions and inner core

Three different magnetic boundary conditions are implemented in MagIC. The most simple one is the conceptual condition at the boundary to an infinite conductor. Surface current in this conductor will prevent the internally produced magnetic field from penetrating so that the field has to vanish at the boundary. The condition are thus the same as for a rigid flow (with boundaries at rest). We only provide the spectral representation here:

$$C_n(r)W_{\ell mn} = 0 \text{ at } r = r_i, r_o$$
 (4.47)

Note that the summation convention with respect to radial modes n is used again. The no-slip condition further requires that the horizontal flow components also have to vanish, provided the two boundaries are at rest. This condition is fulfilled for

$$C_n(r)g_{\ell mn} = 0$$
,  $C'_n(r)g_{\ell mn} = 0$  and  $C_n(r)h_{\ell mn} = 0$ . (4.48)

More complex are the conditions to an electrical insulator. Here we actually use matching condition to a potential field condition that are formulated like boundary conditions. Since the electrical currents have to vanish in the insulator we have  $\nabla \times \mathbf{B}$ , which means that the magnetic field is a potential field  $\mathbf{B}^I = -\nabla V$  with  $\Delta V = 0$ . This Laplace equation implies a coupling between radial and horizontal derivatives which is best solved in spectral space. Two potential contributions have to be considered depending whether the field is produced above the interface radius  $r_{BC}$ 

or below. We distinguish these contributions with upper indices I for internal or below and E for external or above. The total potential then has the form:

$$V_{\ell m}(r) = r_{BC} V_{\ell m}^{I} \left(\frac{r_{BC}}{r}\right)^{\ell+1} + r_{BC} V_{\ell m}^{E} \left(\frac{r}{r_{BC}}\right)^{\ell}.$$

with the two spectral potential representations  $V_{\ell m}^I$  and  $V_{\ell m}^E$ . This provides well defined radial derivative for both field contributions. For boundary  $r_o$  we have to use the first contribution and match the respective field as well as its radial derivative to the dynamo solution. The toroidal field cannot penetrate the insulator and thus simply vanishes which yields h=0 or

$$C_n h_{\ell mn} = 0$$

in spectral space. The poloidal field then has to match the potential field which implies

$$\nabla_H \frac{\partial}{\partial r} g = -\nabla_H V^I$$

for the horizontal components and

$$\frac{\nabla_H^2}{r^2}g = \frac{\partial}{\partial r}V^I$$

for the radial. In spectral space these condition can be reduce to

$$\mathcal{C'}_n(r)g_{\ell mn} = V_{lm}^I$$
 and  $\frac{\ell(\ell+1)}{r^2}\mathcal{C}_ng_{\ell mn} = -\frac{\ell+1}{r}V_{lm}^I.$ 

Combining both allows to eliminate the potential and finally leads to the spectral condition used in MagIC:

$$\left(\mathcal{C'}_n(r_o) + \frac{\ell}{r_o}\mathcal{C}_n(r_o)\right)g_{\ell mn} = 0$$

Analogous consideration lead to the respective condition at the interface to an insulating inner core:

$$\left(\mathcal{C'}_n(r_i) - \frac{\ell+1}{r_i}\mathcal{C}_n(r_i)\right)g_{\ell mn} = 0.$$

If the inner core is modelled as an electrical conductor, a simplified dynamo equation has to be solved in which the fluid flow is replaced by the solid-body rotation of the inner core. The latter is described by a single toroidal flow mode  $(\ell=1,m=0)$ . The resulting nonlinear terms can be expressed by a simple spherical harmonic expansion, where the superscript I denotes values in the inner core and  $\omega_I$  its differential rotation rate:

$$\int d\Omega Y_{\ell}^{m\star} \mathbf{e}_{r} \cdot \left[ \nabla \times \left( \mathbf{u}^{I} \times \mathbf{B}^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} g_{\ell m}^{I}(r) , \qquad (4.49)$$

$$\int d\Omega Y_{\ell}^{m\star} \mathbf{e}_{r} \cdot \left[ \nabla \times \nabla \times \left( \mathbf{u}^{I} \times \mathbf{B}^{I} \right) \right] = -i \omega_{I} m \frac{\ell(\ell+1)}{r^{2}} h_{\ell m}^{I}(r) . \tag{4.50}$$

The expensive back and forth transformations between spherical harmonic and grid representations are therefore not required for advancing the inner-core magnetic field in time.

In the inner core the magnetic potentials are again conveniently expanded into Chebyshev polynomials. The Chebyshev variable x spans the whole diameter of the inner core, so that grid points are dense near the inner-core boundary but sparse in the center. The mapping is given by:

$$x(r) = \frac{r}{r_i} \quad , \quad -r_i \le r \le r_i \quad . \tag{4.51}$$

Each point in the inner core is thus represented twice, by grid points  $(r, \theta, \phi)$  and  $(-r, \pi - \theta, \phi + \pi)$ . Since both representations must be identical, this imposes a symmetry constraint that can be fulfilled when the radial expansion comprises only polynomials of even order:

$$g_{\ell m}^{I}(r) = \left(\frac{r}{r_i}\right)^{\ell+1} \sum_{i=0}^{M-1} g_{\ell m \, 2i}^{I} \, \mathcal{C}_{2i}(r) . \tag{4.52}$$

An equivalent expression holds for the toroidal potential in the inner core. FFTs can again by employed efficiently for the radial transformation, using the M extrema of  $\mathcal{C}_{2M-1}(r)$  with x>0 as grid points.

The sets of spectral magnetic field equations for the inner and the outer core are coupled via continuity equations for the magnetic field and the horizontal electric field. Continuity of the magnetic field is assured by (i) continuity of the toroidal potential, (ii) continuity of the poloidal potential, and (iii) continuity of the radial derivative of the latter. Continuity of the horizontal electric field demands (iv) that the radial derivative of the toroidal potential is continuous, provided that the horizontal flow and the electrical conductivity are continuous at the interface. These four conditions replace the spectral equations (4.26), (4.27) on the outer-core side and equations (4.49), (4.50) on the inner-core side. Employing free-slip conditions or allowing for electrical conductivity differences between inner and outer core leads to more complicated and even non-linear matching conditions.

**CHAPTER** 

**FIVE** 

### **CONTRIBUTING TO THE CODE**

MagIC is an open-source code, we thus value any possible contribution! There are several ways to directly contribute to the code:

#### Contribute

- **Do you want to contribute to the code?** Just clone the code and start modyfing it. Make sure that your modifications *don't alter the code*, try to *document your changes* as much as you can and follow the recommended *Fortran coding style*.
- Do you want to improve the documentation? Feel free to document some missing features. The documentation is stored in the directory \$MAGIC\_HOME/doc/sphinx and relies on the documenting tool Sphinx. Some recommendations regarding documentation can be found *below*.
- Did you find a bug? Issues and feature requests should be raised in the github tracker.

# 5.1 Checking the consistency of the code

It is frequently required to check the consistency of the code, especially **after the implementation of new features**. For this reason, we developed the python test suite magic\_wizard.py, located in the directory \$MAGIC\_HOME/samples/, which tests the compilation of the code and it's results against a set of standard solutions in sample directories to check if the code produces the correct output.

You can run it as follows:

```
./magic_wizard.py <options>
```

## It supports the following options:

```
--help
                    Show usage overview
--level LEV
                          Run only tests from level LEV
--use-debug-flags
                          Compile MagIC with the debug flags
--use-mpi
                          Use MPI
--use-openmp
                          Use the hybrid version of MagIC
--use-mkl
                          Use the MKL for FFTs and Lapack calls
--use-shtns
                         Use SHTns for Legendre transforms
--use-precond USE_PRECOND Use matrix preconditioning
--nranks NRANKS
                          Specify the number of MPI ranks
--nthreads NTHREADS
                          Specify the number of threads (hybrid version)
--mpicmd MPICMD
                          Specify the mpi executable (mpiexec, mpirun, srun)
```

**Note:** Make sure that your environment variables FC and CC are correctly defined otherwise the script will use the default system compilers.

The --level LEV option defines the priority level of check and validation of the code. It has the following levels of checking:

Level	Cases to check (subdirectories)	
0	<ul> <li>Boussinesq dynamo benchmark (Christensen et al., 2001) - start from zero (dynamo_benchmark)</li> <li>Variable transport properties (viscosity, thermal diffusivity and electrical diffusivity) in an anelastic convective model (varProps)</li> <li>Test of a case that uses finite differences - restart from a case that used Chebyshev polynomials (finite_differences)</li> <li>Boussinesq dynamo benchmark (Christensen et al., 2001) - start from a saturated state (boussBenchSat)</li> <li>Double-diffusive convection benchmark (Breuer et al., 2010) - start from a saturated state (doubleDiffusion)</li> <li>Axisymmetric spherical Couette flow - this auto-test checks the axisymmetric version of MagIC (couetteAxi)</li> </ul>	
1	<ul> <li>Test reading and writing of restart files (testRestart)</li> <li>Test different grid truncations (testTruncations)</li> <li>Test mapping on to a new grid (testMapping)</li> <li>Test different outputs produced (testOutputs)</li> <li>Test different radial outputs - *R.TAG (testRadialOutputs)</li> </ul>	
2	Hydrodynamic anelastic benchmark (Jones et al., 2011) (hydro_bench_anel)	
3	$ \begin{array}{lll} \bullet & \mbox{Heat flux perturbation (fluxPerturbation)} \\ \bullet & \mbox{Isothermal model with } N_{\rho} = 3 \mbox{ (isothermal\_nrho3)} \\ \bullet & \mbox{Boussinesq} & \mbox{Dynamo benchmark for conducting and rotating inner core} \\ & \mbox{(dynamo\_benchmark\_condICrotIC)} \\ \bullet & \mbox{Anelastic dynamo with variable conductivity (varCond)} \\ \end{array} $	
4	<ul> <li>Test the writing of CMB and coeff files (testCoeffOutputs)</li> <li>Test the writing of RMS force balance (testRMSOutputs)</li> <li>Test the writing of Graphic and Movie files (testGraphMovieOutputs)</li> <li>Test the writing of TO and Geos outputs (testTOGeosOutputs)</li> </ul>	

# 5.2 Advices when contributing to the code

- Before committing your modifications always make sure that the auto-tests pass correctly.
- Try to follow the same coding style rules as in the rest of the code:
  - 1. Never use TABS but always SPACES instead
  - 2. Use 3 spaces for indentation

**Note:** These two rules can be easily set in your \$HOME/.vimrc file if you use vim:

```
au FileType fortran set shiftwidth=3
au FileType fortran set tabstop=3
au FileType fortran set expandtab
```

- 3. Never use capital letters for variable declaration or Fortran keywords
- 4. Never use dimension (len) for declaring array but rather real (cp) :: data(len)
- 5. Always use the default precisions when introducing new variables (cp)

These rules try to follow the general recommendations on modern fortran programming that can be found on www.fortran90.org or in the book Modern Fortran - style and usage by N. S. Clerman and W. Spector.

# 5.3 Building the documentation and contributing to it

The documentation is generated using Sphinx. To build it you'll thus need to install this python module on your machine. This is in general directly available on most of the Linux distributions under the name python-sphinx. Once installed, just go to the documentation directory

```
$ cd $MAGIC_HOME/doc/sphinx
```

and build the html documentation

```
$ make html
```

The complete documentation will then be built in a local directory named \$MAGIC\_HOME/doc/sphinx/.build/html.

If LaTeX is installed on your work station, it is also possible to build the corresponding manual of the documentation in the pdf format:

```
$ make latexpdf
```

The resulting pdf is then generated in a local directory named  $MAGIC\_HOME/doc/sphinx/.build/latex$ .

It is pretty straightforward to contribute to the documentation by simply adding some contents to the different rst files. Informations about reStructuredText syntax can be found on www.sphinx-doc.org, while helpful CheatSheet are accessible here or there.

**CHAPTER** 

SIX

### INPUT PARAMETERS

True runtime input parameters are read from STDIN as namelists, a Fortran feature. A namelist is identified by its unique name &name. The name-statement is followed by the parameters that are part of the namelist in the format parameter=value,. The namelist is closed by a backslash. The subroutine defaultNamelists (in the module Namelist.f90) defines a default value for each parameter. Only the parameters whose value should differ from its default have to be stated in the namelist.

An example for the short namelist defining inner core parameters is

```
&inner_core
sigma_ratio = 1.0,
nRotIc = 1
```

Comas can be used to seperate namelist entries since they are not interpreted by the code.

Magic uses the following eight namelists:

## Namelists

- 1. & grid for resolution
- 2. &control for control parameters and numerical parameters.
- 3. &phys\_param for the physical parameters.
- 4. &B\_external for setting up an external field contribution
- 5. & start\_field to define the starting fields.
- 6. &output\_control for defining the output.
- 7. &mantle for setting mantle parameters.
- 8. &inner\_core for setting inner core parameters.

The number of possible input parameters has grown to more than 100/150. Don't be confused by all the possible options though, since all parameters are internally set to a useful default value!

Practically, in a production run, the number of parameters you may want to adjust is thus much smaller. As an example, the following namelist shows you how to initiate and quickly run one of the anelastic benchmarks by (Jones et al., 2011):

```
&grid
n_r_max =97, ! 97 radial grid points
n_cheb_max =95,
n_phi_tot =288, ! 288 points in the azimuthal direction
```

(continues on next page)

(continued from previous page)

```
n_r_{ic_max} = 17
n_cheb_ic_max=15,
minc =1,
                             ! No azimuthal symmetry
&control
mode
            =1,
                              ! This is a non-magnetic case
        =1,
="test",
tag
n_time_steps=50000,
                             ! Number of time steps
courfac =2.5D0,
alffac =1.0D0,
dtmax =1.0D-4,
                             ! Maximum allowed time-step
n\_cour\_step = 5,
alpha =0.6D0,
runHours =23,
                             ! Run time (hours)
runMinutes =30,
                             ! Run time (minutes)
&phys_param
ra =1.48638035D5, ! Rayleigh number
ek =1.0D-3, ! Ekman number
pr =1.0D0, ! Prandtl number
strat =5.D0, ! Density contrast
polind =2.0D0, ! Polytropic index
radratio =0.35D0, ! Aspect ratio of
                              ! Density contrast
                             ! Polytropic index
                             ! Aspect ratio of the spherical shell
g0 = 0.D0,
g1 = 0.D0,
                             ! Gravity profile
g2
            =1.D0,
            =1,
ktops
                             ! Entropy boundary condition
kbots
             =1,
             =1,
                             ! Mechanical boundary condition
ktopv
             =1,
kbotv
&start_field
l_start_file=.false.,
start_file ="checkpoint_end.CJ3",
init_s1 =1919, ! Initial entropy perturbation pattern
             =0.01,
                             ! Amplitude of the initial perturbation
amp_s1
&output_control
n_log_step =50, ! Store time series every 50 time steps
n_graphs =1, ! 1 G_#.TAG file produced at the end of the run
n_specs =5, !
n_rsts =1, !
runid ="C.Jones bench",
                             ! 5 spectra produced during the run
                             ! 1 checkpoint_end.TAG file produced at the end of the run
&mantle
nRotMa =0
&inner_core
sigma_ratio = 0.d0,
                           ! Non-conducting inner core
nRotIC = 0,
```

This example might then be easily adapted to your desired configuration.

# 6.1 Grid namelist

This namelist defines the resolution of the computations. Keep in mind that **MagIC** is a 3D pseudo-spectral spherical shell code using Chebyshev polynomial expansions in the radial and spherical harmonic expansions in the angular directions.

#### 6.1.1 Outer Core

•  $n_r_max$  (default  $n_r_max=33$ ) is an integer which gives the number of grid points in the radial direction in the outer core ( $[r_i, r_o]$ ). If Chebyshev polynomials are used for the radial integration scheme, there are some constraints on the value of  $n_r_max$ : first of all it must be of the form 4\*n+1, where n is an integer; and second the prime decomposition of  $n_r_max$  should only contain multiple of 3, 4 and 5 (this second condition comes from the Chebyshev transforms). This constraint does not exist when finite differences are used.

**Note:** If Chebyshev polynomials are used, the possible values for  $n_r_{max}$  below 220 are hence: 17, 21, 25, 33, 37, 41, 49, 61, 65, 73, 81, 97, 101, 109, 121, 129, 145, 161, 181, 193, 201, 217,...

• n\_cheb\_max (default n\_cheb\_max=31) is an integer which is the number of terms in the Chebyshev polynomial expansion to be used in the radial direction - the highest degree of Chebyshev polynomial used being n\_cheb\_max-1. Note that n\_cheb\_max <= n\_r\_max. This quantity will not be used if finite differences are used.

Note: Adopting n cheb max=n r max-2 is usually a good choice

- n\_phi\_tot (default n\_phi\_tot=192) is an integer which gives the number of longitudinal/azimuthal grid points. It has the following constraints:
  - n\_phi\_tot must be a multiple of minc (see below)
  - n\_phi\_tot/minc must be a multiple of 4
  - n\_phi\_tot must be a multiple of 16

**Note:** The possible values for  $n\_phi\_max$  are thus: 16, 32, 48, 64, 96, 128, 192, 256, 288? 320, 384, 400, 512, 576, 640, 768, 864, 1024, 1280, 1536, 1792, 2048, ...

- l\_axi (default l\_axi=.false.) is a logical. When set to true, one considers only the axisymmetric mode (i.e. MagIC becomes a 2-D axisymmetric code).
- n\_theta\_axi (default n\_theta\_axi=0) is an integer which gives the number of latitudinal grid points when MagIC computes only the axisymmetric mode.
- **fd\_order** (default *fd\_order=2*) is an integer. This is the order of the finite difference scheme for the bulk points (possible values are 2, 4, 6).
- **fd\_order\_bound** (default *fd\_order\_bound=2*) is an integer. This is the order of the finite difference scheme for the boundary points (possible values are 1,2,3,4,5,6,...).
- **fd\_stretch** (default *fd\_stretch=0.3*) is a real. It controls the ratio between the number of points in the boundary layers and in the bulk.
- fd\_ratio (default fd\_ratio=0.1) is a real. It controls the ratio between the smallest grid spacing and the largest grid spacing.

6.1. Grid namelist 45

**Note:** When *fd\_ratio* is set to 1, the radial grid is regularly-spaced.

#### 6.1.2 Inner Core

- $n_r_{ic}$  max (default  $n_r_{ic}$  max=17) is an integer which gives the number of grid points in the radial direction in the inner core ( $[0, r_i]$ ). It too, must be of the form  $4 \times n + 1$ , where n is an integer.
- n\_cheb\_ic\_max (default n\_cheb\_ic\_max=15) is the number of terms in the Chebyshev polynomial expansion in the radial direction in the inner core. Only Chebyshev polynomials of even degrees are used in the expansion giving the highest degree used to be 2\*n\_cheb\_ic\_max-2. Note that here too, n\_cheb\_ic\_max <= n\_r\_max.

# 6.1.3 Symmetry and aliasing

- minc (default minc=1) is an integer which gives the longitudinal symmetry. e.g. minc=n would give an n-fold rotational symmetry in the azimuthal direction. One can use this to reduce computational costs when the symmetry of the solution is known. The orders of the spherical harmonic expansion (m) are multiples of minc.
- nalias (default nalias=20) is an integer which determines antialiasing used in the spherical harmonic representation. Note that 20 <= nalias <= 30.

The number of grid points in latitude  $n\_theta\_max = n\_phi\_tot/2$ . The maximum degree  $(1\_max)$  and maximum order  $(m\_max)$  of the spherical harmonic expansion are determined by nalias:

```
l_max = (nalias * n_theta_max)/30
```

#### 6.2 Control namelist

This namelist defines the numerical parameters of the problem plus the variables that control and organize the run.

• mode (default mode=0) is an integer which controls the type of calculation performed.

mode=0	Self-consistent dynamo
mode=1	Convection
mode=2	Kinematic dynamo
mode=3	Magnetic decay modes
mode=4	Magneto convection
mode=5	Linear onset of convection
mode=6	Self-consistent dynamo, but with no Lorentz force
mode=7	Super-rotating inner core or mantle, no convection and no magnetic field
mode=8	Super-rotating inner core or mantle, no convection
mode=9	Super-rotating inner core or mantle, no convection and no Lorentz force
mode=10	Super-rotating inner core or mantle, no convection, no magnetic field, no Lorentz force and no
	advection

- tag (default tag="default") is a character string, used as an extension for all output files.
- n\_time\_steps (default n\_time\_steps=100) is an integer, the number of time steps to be performed.
- **tEND** (default *tEND=0.0*) is a real, which can be used to force the code to stop when :math:t=tEND. This is only used when t/=tEND.

• alpha (default alpha=0.5) is a real. This is the weight used for current time step in implicit time step.

#### 6.2.1 Default scales

• n tScale (default n tScale=0) is an integer, which determines the time scaling

n_tScale=0	Use viscous time scale.	$d^2/\nu$
n_tScale=1	Use magnetic time scale.	$d^2/\eta$
n_tScale=2	Use thermal time scale.	$d^2/\kappa$
n_tScale=3	Use rotational time scale.	$\Omega^{-1}$

• n\_lScale (default n\_1Scale=0) is an integer which determines the reference length scale.

n_lScale=0	Use outer core.
n_lScale=1	Use total core.

• enscale (default enscale=1.0) is a real. This is the scaling for energies.

### 6.2.2 Update control

- l\_update\_v (default l\_update\_v=.true.) is a logical that specifies whether the velocity field should be time-stepped or not.
- l\_update\_b (default l\_update\_b=.true.) is a logical that specifies whether the magnetic field should be time-stepped or not.
- l\_update\_s (default l\_update\_s=.true.) is a logical that specifies whether the entropy/temperature should be time-stepped or not.

## 6.2.3 Time step control

A modified courant criteria including a modified Alfven-velocity is used to account for the magnetic field. The relative and absolute importance of flow and Alfven-velocity can be controlled by **courfac** and **alffac** respectively. The parameter **l\_cour\_alf\_damp** allows to choose wheter the actual Alven speed is used to estimate the Courant condition or if damping (see Christensen et al., GJI, 1999) is included.

- **dtstart** (default dtstart=0.0) is a real, which is used as the initial time step if the starting solution is initialized (see below) and dtstart > 0.
- dtMax (default dtMax=1e-4) is a real. This is the maximum allowed time step  $\delta t$ . If  $\delta t >$  dtmax, the time step is decreased to at least dtmax (See routine  $dt\_courant$ ). Run is stopped if  $\delta t <$  dtmin and dtmin =  $10^{-6}$  dtmax.
- courfac (default courfac=2.5) is a real used to scale velocity in courant criteria.
- alffac (default alffac=1.0) is a real, used to scale Alfven-velocity in courant criteria.
- l\_cour\_alf\_damp (default l\_cour\_alf\_damp=.true.) is a logical. This is used to decide whether the damping of the Alven waves is taken into account when estimating the Courant condition (see Christensen et al., GJI, 1999). At low Ekman numbers, this criterion might actually lead to spurious oscillations/instabilities of the code.
- n\_cour\_step (default n\_cour\_step=10) is an integer. This is the number of time steps before consecutive checking of courant criteria. Note: the courant criteria is checked always after the time step has been changed if n\_cour\_step>0.

6.2. Control namelist 47

#### 6.2.4 Run time

The total desired runtime (in human units and not in CPU units) can be specified with the three variables **runHours**, **runMinutes** and **runSeconds**.

- runHours (default runHours=0) is an integer that controls the number of run hours.
- runMinutes (default runMinutes=0) is an integer that controls the .
- runSeconds (default runSeconds=0) is an integer that controls the number of run hours.

Here is an example for a run of 23h30:

```
runHours = 23,
runMinutes = 30,
```

# 6.2.5 Hyperdiffusivity

Hyperdiffusion can be applied by multiplying the diffusion operators by a factor of the form

$$d(\ell) = 1 + D \left[ \frac{\ell + 1 - \ell_{hd}}{\ell_{max} + 1 - \ell_{hd}} \right]^{\beta}$$

for the spherical harmonic degrees  $\ell \geq \ell_{hd}$ .

- **difnu** (default difnu=0.0) is a real. This is the amplitude D of the viscous hyperdiffusion.
- difkappa (default difkappa=0.0) is a real. This is the amplitude D of the thermal hyperdiffusion.
- **difeta** (default difeta=0.0) is a real. This is the amplitude D of the magnetic hyperdiffusion.
- **Idif** (default 1 dif = 1) is an integer. This is the degree  $\ell_{hd}$  where hyperdiffusion starts to act.
- **Idifexp** (default 1 difex p = -1) is an integer. This is the exponent  $\beta$  of hyperdiffusion.

## 6.2.6 Angular momentum correction

In case of the use of stress-free boundary conditions at both boundaries, it is safer to ensure that the angular momentum is correctly conserved. This can be enforced through the following input variables:

- l\_correct\_AMe (default l\_correct\_AMe=.false.) is a logical. This is used to correct the equatorial angular momentum.
- l\_correct\_AMz (default l\_correct\_AMz=.false.) is a logical. This is used to correct the axial angular momentum.

# 6.2.7 Radial scheme and mapping of the Gauss-Lobatto grid

In MagIC, one can either use finite differences or Chebyshev polynomials for the radial integration scheme. This choice is controlled by the following input parameter:

• radial\_scheme (default radial\_scheme='CHEB') is a character string.

radial_scheme='CHEB'	Use Chebyshev polynomials
radial_scheme='FD'	Use finite differences

When Chebyshev polynomials are used, it is also possible to use a non-linear mapping function to concentrate/diperse grid points around a point inside the domain.

- l\_newmap (default l\_newmap=.false.) is a logical. A radial mapping can be applied to the Chebyshev grid when l\_newmap is set to .true.. The radial profile of the mapping function is then stored during the initialisation of the code in the file *rNM.TAG*.
- map\_function (default map\_function='arcsin') is a character string. This allows to select which mapping function is used:

map_function='TAN'	Use a tangent mapping (see Bayliss and Turkel 1992)
map_function='ARCSIN'	Use finite differences (see Kosloff and Tal-Ezer 1993)

If the tangent mapping is used, the function that re-distributes the collocation points is expressed by

$$r = \frac{1}{2} \left( \alpha_2 + \frac{\tan \left[ \lambda (r_{cheb} - x_0) \right]}{\alpha_1} \right) + \frac{r_i + r_o}{2} ,$$

where the Gauss-Lobatto collocation points are

$$r_{cheb} = \cos\left(\frac{\pi(k-1)}{N_r}\right), \quad k = 1, 2, ..., n_r, \quad n_r = n_r max$$

and  $r \in [r_i, r_o], r_{cheb} \in [-1.0, 1.0]$ . The parameters to calculate r are

$$\lambda = \frac{\tan^{-1}(\alpha_1(1 - \alpha_2))}{1 - x_0}$$

$$x_0 = \frac{K - 1}{K + 1}$$

$$K = \frac{\tan^{-1}(\alpha_1(1 + \alpha_2))}{\tan^{-1}(\alpha_1(1 - \alpha_2))}.$$

The coefficient  $\alpha_1$  determines the degree of concentration/dispersion of the grid points around  $r_{cheb} = \alpha_2$ . If  $\alpha_1$  is too high, the r function becomes nearly discontinuous. To avoid numerical problems,  $\alpha_1$  should remain close to unity.

If the arcsin mapping is used, the function that re-distributes the collocation points is given by

$$r = \frac{1}{2} \left[ \frac{\arcsin\left(\alpha_1 r_{cheb}\right)}{\arcsin\alpha_1} \right] + \frac{r_i + r_o}{2} ,$$

In the Kosloff and Tal-Ezer mapping,  $\alpha_1$  transforms the Gauss-Lobatto grid into a more regularly-spaced grid. When  $\alpha_1 \to 0$  one recovers the Gauss-Lobatto grid, while  $\alpha_1 \to 1$  yields a regular grid.

Warning: The Kosloff-Tal-Ezer mapping becomes singular when  $\alpha_1=1$ . Acceptable values are  $0<\alpha_1<1$ . Note that the error increases as  $\epsilon=\left(\frac{1-\sqrt{1-\alpha_1^2}}{\alpha_1}\right)^{N_r}$ .

- **alph1** (default alph1=0.8) is a real. This is a control parameter of the mapping function.
- alph2 (default alph2=0.0) is a real. This is a control parameter of the mapping function.

#### 6.2.8 Miscellaneous

• l\_non\_rot (default l\_non\_rot=.false.) is a logical. Use it when you want to do non-rotating numerical simulations.

6.2. Control namelist 49

• anelastic\_flavour (default anelastic\_flavour="None") is a character string. This allows to change the thermal diffusion operator used within the anelastic approximation. Possible values are:

anelastic_flavour='LBR'	Entropy diffusion
anelastic_flavour='ENT'	Entropy diffusion
anelastic_flavour='ALA'	Anelastic liquid approximation
anelastic_flavour='TDIFF'	Temperature diffusion
anelastic_flavour='TEMP'	Temperature diffusion

• **thermo\_variable** (default thermo\_variable="S") is a character string. This allows to change the default thermodynamic variable (and hence change the entropy/temperature equation used). This switch only matters when one wants to run an anelastic model. Possible values are:

thermo_variable='S'	Use entropy as a primitive variable
thermo_variable='T'	Use temperature as a primitive variable

• polo\_flow\_eq (default polo\_flow\_eq="WP") is a character string. This allows to change how the equation for the poloidal flow potential is constructed. One can either use the radial component of the Navier-Stokes equation and hence keep a coupled system that involve the poloidal potential W and the pressure p, or take the radial component of the double-curl of the Navier-Stokes equation to suppress pressure.

polo_flow_eq='WP'	Use the pressure formulation
polo_flow_eq='DC'	Use the double-curl formulation

# 6.3 Physical parameters namelist

This namelist contains all the appropriate relevant control physical parameters.

## 6.3.1 Dimensionless control parameters

• ra (default ra=0.0) is a real. This the thermal Rayleigh number expressed by

$$Ra = \frac{\alpha g_o \Delta T d^3}{\kappa \nu}$$

• raxi (default raxi=0.0) is a real. This the compositional Rayleigh number expressed by

$$Ra_{\xi} = \frac{\alpha g_o \Delta \xi d^3}{\kappa_{\xi} \nu}$$

• ek (default ek=1e-3) is a real. This is the Ekman number expressed by

$$E = \frac{\nu}{\Omega d^2}$$

• **pr** (default pr=1.0) is a real. This is the Prandtl number expressed by

$$Pr = \frac{\nu}{\kappa}$$

• sc (default sc=10.0) is a real. This is the Schmidt number expressed by

$$Sc = \frac{\nu}{\kappa_{\xi}}$$

• prmag (default prmag=5.0) is a real. This is the magnetic Prandtl number expressed by

$$Pm = \frac{\nu}{\lambda}$$

• **po** (default po=0. 0) is a real. This is the Poincaré number expressed by

$$Po = \frac{\Omega_p}{\Omega}$$

- **prec\_angle** (default *prec\_angle=23.5*) is a real. This is the angle between the precession and the rotation axes expressed in degrees.
- po\_diff (default po\_diff=0.0) is a real. This is the Poincaré number in case of differential precession of
  core and mantle assuming both have the same rotation rate Ω and only the mantle is precessing.
- diff\_prec\_angle (default diff\_prec\_angle=23.5) is a real. This is the angle between the precession and the rotation axes expressed in degrees, for differential precession.
- radratio (default radratio=0.35) is a real. This is the ratio of the inner core radius  $r_i$  to the outer core radius  $r_o$ :

$$\eta = \frac{r_i}{r_o}$$

• strat (default strat=0.0) is a real. This is the number of density scale heights of the reference state:

$$N_{\rho} = \ln \frac{\tilde{\rho}(r_i)}{\tilde{\rho}(r_o)}$$

• **DissNb** (default *DissNb=0.0*) is a real. This is the dissipation number:

$$Di = \frac{\alpha_o g_o d}{c_p}$$

**Warning:** This can only be provided as a **replacement** input of **strat**. I.E., when one wants to define a reference state, one has to specify **either** strat **or** DissNb in the input namelist.

• **polind** (default polind=1.5) is a real. This is the polytropic index, which relates the background temperature to the background density:

$$\tilde{\rho} = \tilde{T}^m$$

**Warning:** Be careful: in its current version the code only handles **adiabatic** backgrounds, therefore changing polind physically means that the nature of the fluid (in particular its Grüneisen parameter) will change. For an ideal gas, it actually always follows  $m+1=\frac{\gamma-1}{\gamma}$ 

• l\_isothermal (default l\_isothermal=.false.) is a logical. When set to .true., makes the temperature background isothermal (i.e.  $\tilde{T}=cst.$ ). In that case, the dissipation number Di vanishes and there is no viscous and Ohmic heating left. The only difference with the Boussinesq set of equations are thus restricted to the density background  $\tilde{\rho}$  and its radial derivatives that enters the viscous stress. This approximation is also called the zero Grüneisen parameter and was extensively explored by Denise Tortorella during her PhD.

#### 6.3.2 Heat sources and sinks

• epsc0 (default epsc0=0.0) is a real. This is the volumetric heat source  $\epsilon_0$  that enters the thermal equilibrium relation:

$$-\nabla \cdot \left(\tilde{\rho}\tilde{T}\nabla s\right) + \epsilon_0 f(r) = 0 \tag{6.1}$$

The radial function f(r) can be modified with the variable nVarEps that enters the same input namelist.

• **epscxi0** (default epscxi0=0.0) is a real. This is the volumetric source  $\epsilon_{\xi}$  that enters the compositional equilibrium relation:

$$-\nabla \cdot (\tilde{\rho}\nabla \xi) + \epsilon_{\xi} = 0 \tag{6.2}$$

• **nVarEps** (default nVarEps=0) is an integer. This is used to modify the radial-dependence of the volumetric heat source, i.e. f(r) that enters equation (6.1).

nVarEps=0	Constant, i.e. $f(r) = \text{cst.}$ .
nVarEps=1	Proportional to density, i.e. $f(r) = \tilde{\rho}(r)$ .
nVarEps=2	Proportional to density times temperature, i.e. $f(r) = \tilde{\rho}(r)\tilde{T}$ .

#### 6.3.3 Realistic interior models

• interior\_model (default interior\_model="None") is a character string. This defines a polynomial fit of the density profile of the interior structure of several astrophysical objects. Possible options are "earth", "jupiter", "saturn" and "sun" (the naming is not case sensitive).

**Warning:** When interior\_model is defined the variables strat, polind, g0, g1 and g2 are not interpreted.

The subroutine radial gives the exact details of the implementation.

r\_cut\_model (default r\_cut\_model=0.98) is a real. This defines the cut-off radius of the reference model,
 i.e. the fluid domain is restricted to radii with r ≤ r<sub>cut</sub>.

The following input parameters will thus define a polynomial fit to the expected interior structure of Jupiter until 99% of Jupiter's radius (assumed here at the 1 bar level)

```
interior_model="JUP",
r_cut_model =0.99e0,
```

## 6.3.4 Gravity

The radial dependence of the gravity profile can be adjusted following

$$g(r) = g_0 + g_1 \frac{r}{r_o} + g_2 \left(\frac{r_o}{r}\right)^2 \tag{6.3}$$

The three following parameters are used to set this profile

- g0 (default q0=0) is the pre-factor of the constant part of the gravity profile, i.e.  $q_0$  in equation (6.3).
- g1 (default g1=1) is the pre-factor of the linear part of the gravity profile, i.e.  $g_1$  in equation (6.3).
- **g2** (default g2=0) is the pre-factor of the  $1/r^2$  part of the gravity profile, i.e.  $g_2$  in equation (6.3).

### 6.3.5 Transport properties

• **difExp** (default difExp=-0.5) is a real. This is the exponent that is used when nVarVisc=2, nVarDiff=2 or nVarCond=4.

#### **Electrical conductivity**

There are several electrical conductivity profiles implemented in the code that can be chosen with the nVarCond input variable. The following one corresponds to a constant electrical conductivity in the deep interior  $(r < r_m)$  and an exponential decay in the outer layer.

$$\sigma(r) = 1 + (\sigma_m - 1) \left(\frac{r - r_i}{r_m - r_i}\right)^a \quad \text{for} \quad r < r_m,$$

$$\sigma(r) = \sigma_m \exp\left[a\left(\frac{r - r_m}{r_m - r_i}\right) \frac{\sigma_m - 1}{\sigma_m}\right] \quad \text{for} \quad r \ge r_m.$$
(6.4)

• **nVarCond** (default *nVarCond=0*) is an integer. This is used to modify the radial-dependence of the electrical conductivity.

nVarCond=0	Constant electrical conductivity, i.e. $\sigma = \text{cst.}$
nVarCond=1	$\sigma \propto \tanh[a(r-r_m)]$
nVarCond=2	See equation (6.4).
nVarCond=3	Magnetic diffusivity proportional to $1/\tilde{\rho}$ , i.e.
	$\lambda = rac{ ilde{ ho}_i}{ ilde{ ho}}$
nVarCond=4	Radial profile of the form:
	$\lambda = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$

- con\_RadRatio (default  $con_RadRatio=0.75$ ) is a real. This defines the transition radius  $r_m$  that enters equation (6.4).
- con\_DecRate (default con\_DecRate=9) is an integer. This defines the decay rate a that enters equation (6.4).
- con\_LambdaMatch (default  $con_LambdaMatch=0.6$ ) is a real. This is the value of the conductivity at the transition point  $\sigma_m$  that enters equation (6.4).
- con\_LambdaOut (default con\_LambdaOut=0.1) is a real. This is the value of the conduvity at the outer boundary. This parameter is only used when nVarCond=1.
- con\_FuncWidth (default con\_FuncWidth=0.25) is a real. This parameter is only used when nVarCond=1.
- r\_LCR (default  $r_LCR=2.0$ ) is a real.  $r_LCR$  possibly defines a low-conductivity region for  $r \geq r_{LCR}$ , in which the electrical conductivity vanishes, i.e.  $\lambda = 0$ .

### Thermal diffusivity

• **nVarDiff** (default *nVarDiff=0*) is an integer. This is used to change the radial-dependence of the thermal diffusivity:

nVarDiff=0	Constant thermal diffusivity $\kappa$
nVarDiff=1	Constant thermal conductivity, i.e.
	$\kappa = rac{ ilde{ ho}_i}{ ilde{ ho}(r)}$
nVarDiff=2	Radial profile of the form:
	$\kappa = \left(rac{ ilde{ ho}(r)}{ ilde{ ho}_i} ight)^lpha$
nVarDiff=3	polynomial-fit to an interior model of Jupiter
nVarDiff=4	polynomial-fit to an interior model of the Earth liquid
	core

### **Viscosity**

• nVarVisc (default nVarVisc=0) is an integer. This is used to change the radial-dependence of the viscosity:

nVarVisc=0	Constant kinematic viscosity $\nu$
nVarVisc=1	Constant dynamic viscosity, i.e.
	$ u = rac{ ilde{ ho}_o}{ ilde{ ho}(r)}$
nVarVisc=2	Radial profile of the form:
	$\nu = \left(\frac{\tilde{\rho}(r)}{\tilde{\rho}_i}\right)^{\alpha}$

where  $\alpha$  is an exponent set by the namelist input variable difExp.

# 6.3.6 Anelastic liquid equations

Warning: This part is still work in progress. The input parameters here are likely to be changed in the future.

• **epsS** (default epsS=0.0) is a real. It controls the deviation to the adiabat. It can be related to the small parameter  $\epsilon$ :

$$\epsilon \simeq \frac{\Delta T}{T} \simeq \frac{\Delta s}{c_p}$$

- **cmbHflux** (default *cmbHflux=0.0*) is a real. This is the CMB heat flux that enters the calculation of the reference state of the liquid core of the Earth, when the anelastic liquid approximation is employed.
- **slopeStrat** (default slopeStrat=20.0) is a real. This parameter controls the transition between the convective layer and the stably-stratified layer below the CMB.

### 6.3.7 Boundary conditions

#### Thermal boundary conditions

ktops (default ktops=1) is an integer to specify the outer boundary entropy (or temperature) boundary condition:

ktops=1	Fixed entropy at outer boundary: $s(r_o) = s_{top}$
ktops=2	Fixed entropy flux at outer boundary: $\partial s(r_o)/\partial r = q_t$
ktops=3	Fixed temperature at outer boundary: $T(r_o) = T_{top}$
ktops=4	Fixed temperature flux at outer boundary: $\partial T(r_o)/\partial r = q_t$

- **kbots** (default *ktops=1*) is an integer to specify the inner boundary entropy (or temperature) boundary condition
- s\_top (default  $s_top=0 0 0.0 0.0$ ) is a real array of lateraly varying outer heat boundary conditions. Each four consecutive numbers are interpreted as follows:
  - 1. Spherical harmonic degree  $\ell$
  - 2. Spherical harmonic order m
  - 3. Real amplitude (cos contribution)
  - 4. Imaginary amplitude (sin contribution)

For example, if the boundary condition should be a combination of an  $(\ell = 1, m = 0)$  sherical harmonic with the amplitude 1 and an  $(\ell = 2, m = 1)$  spherical harmonic with the amplitude (0.5, 0.5) the respective namelist entry could read:

```
s_top = 1, 0, 1.0, 0.0, 2, 1, 0.5, 0.5, ! The comas could be left away.
```

- s\_bot (default  $s_bot=0 \ 0 \ 0.0 \ 0.0$ ) is a real array. This is the same as s\_top but for the bottom boundary.
- impS (default impS=0) is an integer. This is a flag to indicate if there is a localized entropy disturbance, imposed at the CMB. The number of these input boundary conditions is stored in n\_impS (the maximum allowed is 20), and it's given by the number of sCMB defined in the same namelist. The default value of impS is zero (no entropy disturbance). If it is set in the namelist for an integer greater than zero, then sCMB has to be also defined in the namelist, as shown below.
- sCMB (default sCMB=0.0 0.0 0.0 0.0) is a real array of CMB heat boundary conditions (similar to the case of s\_bot and s\_top). Each four consecutive numbers are interpreted as follows:
  - 1. Highest amplitude value of the entropy boundary condition, stored in array peakS(20). When impS<0, peakS is a relative amplitude in comparison to the  $(\ell=0,m=0)$  contribution (for example, the case s top= 0 0 -1 0).
  - 2.  $\theta$  coordinate (input has to be given in degrees), stored in array thetaS (20).
  - 3.  $\phi$  coordinate (input has to be given in degrees), stored in array phis (20).
  - 4. Angular width (input has to be given in degrees), stored in array widthS (20).

#### Boundary conditions for chemical composition

ktopxi (default ktopxi=1) is an integer to specify the outer boundary chemical composition boundary condition:

ktopxi=1	Fixed composition at outer boundary: $\xi(r_o) = \xi_{top}$
ktopxi=2	Fixed composition flux at outer boundary: $\partial \xi(r_o)/\partial r = q_t$

- kbotxi (default ktopxi=1) is an integer to specify the inner boundary chemical composition boundary condition.
- **xi\_top** (default  $xi\_top = 0 \ 0 \ 0.0 \ 0.0$ ) is a real array of lateraly varying outer chemical composition boundary conditions. Each four consecutive numbers are interpreted as follows:
  - 1. Spherical harmonic degree  $\ell$
  - 2. Spherical harmonic order m
  - 3. Real amplitude (cos contribution)
  - 4. Imaginary amplitude (sin contribution)

For example, if the boundary condition should be a combination of an  $(\ell = 1, m = 0)$  sherical harmonic with the amplitude 1 and an  $(\ell = 2, m = 1)$  spherical harmonic with the amplitude (0.5, 0.5) the respective namelist entry could read:

```
xi_top = 1, 0, 1.0, 0.0, 2, 1, 0.5, 0.5, ! The comas could be left away.
```

- xi\_bot (default xi\_bot=0 0 0.0 0.0) is a real array. This is the same as xi\_top but for the bottom boundary.
- impXi (default <code>impXi=0</code>) is an integer. This is a flag to indicate if there is a localized chemical composition disturbance, imposed at the CMB. The number of these input boundary conditions is stored in <code>n\_impXi</code> (the maximum allowed is 20), and it's given by the number of <code>xiCMB</code> defined in the same namelist. The default value of <code>impXi</code> is zero (no chemical composiiton disturbance). If it is set in the namelist for an integer greater than zero, then <code>xiCMB</code> has to be also defined in the namelist, as shown below.
- xiCMB (default xiCMB=0.0 0.0 0.0 0.0) is a real array of CMB chemical composition boundary conditions (similar to the case of xi\_bot and xi\_top). Each four consecutive numbers are interpreted as follows:
  - 1. Highest amplitude value of the chemical composition boundary condition, stored in the array peakXi(20). When impXi<0, peakXi is a relative amplitude in comparison to the  $(\ell=0, m=0)$  contribution (for example, the case xi\_top= 0 0 -1 0).
  - 2.  $\theta$  coordinate (input has to be given in degrees), stored in array thetaXi (20).
  - 3.  $\phi$  coordinate (input has to be given in degrees), stored in array phiXi (20).
  - 4. Angular width (input has to be given in degrees), stored in array widthXi (20).

#### Mechanical boundary conditions

• **ktopv** (default ktopv=2) is an integer, which corresponds to the mechanical boundary condition for  $r=r_o$ .

ktopv=1	Stress-free outer boundary for $r=r_o$ :
	$W_{\ell m}(r=r_o) = 0,  \frac{\partial}{\partial r} \left( \frac{1}{r^2 \tilde{\rho}} \frac{\partial W_{\ell m}}{\partial r} \right) = 0$
	$\frac{\partial}{\partial r} \left( \frac{1}{r^2 \tilde{\rho}} Z_{\ell m} \right) = 0$
ktopv=2	Rigid outer boundary for $r = r_o$ :
	$W_{\ell m} = 0,  \frac{\partial W_{\ell m}}{\partial r} = 0,$
	$Z_{\ell m} = 0$

• **kbotv** (default kbotv=2) is an integer, which corresponds to the mechanical boundary condition for  $r=r_i$ .

# **Magnetic boundary conditions**

• **ktopb** (default ktopb=1) is an integer, which corresponds to the magnetic boundary condition for  $r=r_o$ .

ktopb=1	Insulating outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} + \frac{\ell}{r} g_{\ell m} = 0,  \frac{\partial h_{\ell m}}{\partial r} = 0$
ktopb=3	Finitely conducting mantle
ktopb=4	Pseudo-vacuum outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} = 0,  h_{\ell m} = 0$

• **kbotb** (default kbotb=1) is an integer, which corresponds to the magnetic boundary condition for  $r=r_i$ .

kbotb=1	Insulating inner boundary:
	$\frac{\partial g_{\ell m}}{\partial r} - \frac{\ell+1}{r} g_{\ell m} = 0,  \frac{\partial h_{\ell m}}{\partial r} = 0$
kbotb=2	Perfectly-conducting inner core:
	$g_{\ell m} = \frac{\partial g_{\ell m}}{\partial r} = 0,  \frac{\partial h_{\ell m}}{\partial r} = 0$
kbotb=3	Finitely conducting inner core
kbotb=4	Pseudo-vacuum outer boundary:
	$\frac{\partial g_{\ell m}}{\partial r} = 0,  h_{\ell m} = 0$

#### Boundary condition for spherically-symmetric pressure

• **ktopp** (default ktopp=1) is an integer, which corresponds to the boundary condition for the spherically-symmetric pressure at  $r=r_o$ .

ktopp=1	The integral of the spherically-symmetric density perturbation vanishes.	
ktopp=2	The spherically-symmetric pressure fluctuation vanishes at the outer boundary.	

# 6.4 External Magnetic Field Namelist

The namelist &B\_external provides options for imposing an external magnetic field.

# 6.4.1 Externally imposed magnetic field

•  $n_{imp}$  (default  $n_{imp} = 0$ ) is an integer controlling the type of external field applied.

n_imp=0	No external magnetic field
n_imp=1	Follows idea of Uli Christensen of external field compensating internal field such that
	radial component of magnetic field vanishes at $r/r_{cmb} = rrMP$ where rrMP is the
	'magnetopause radius' input by the user (see below)
n_imp=2	Uniform axisymmetric magnetic field of geometry given by 1_imp (see below)
n_imp=3	Uniform axisymmetric magnetic field which changes direction according to the direc-
	tion of the axial dipole of the internal magnetic field
n_imp=4	Same as n_imp=3 but the amplitude of the external field is scaled to the amplitude
	of the axial dipole of the internal field
n_imp=7	External field depends on internal axial dipole through Special Heyner feedback func-
	tions

- rrMP (default rrMP = 0.0) is a real which gives the value of 'magnetopause radius'. In other words, it gives the radius (as a fraction of r\_cmb) at which the radial component of the magnetic field vanishes due to cancelling out of external and internal magnetic field components. Used only when n\_imp = 1.
- amp imp (default amp imp = 0.0) is a real which gives the amplitude of the external magnetic field.
- **expo\_imp** (default <code>expo\_imp = 0.0</code>) is a real which gives the exponent of dependence of external magnetic field on the axial dipole of the internal magnetic field. Used for <code>n\_imp=7</code>.
- bmax\_imp (default  $bmax_imp = 0.0$ ) is a real which gives the location of the maximum of the ratio of the poloidal potentials  $g_{ext}/g_{int}$ .
- l\_imp (default l\_imp = 1) is an integer which gives the geometry (degree of spherical harmonic) of the external magnetic field. The external field is always axisymmetric, hence m = 0 always. This option is used when n\_imp = 2, 3 or 4.

# 6.4.2 Current carrying loop

To simulate experiments, an external current carrying loop, concentric to the sphere and in the equatorial plane, has been implemented in the code. It's radius is fixed at a distance  $a=r_{cmb}/0.8$  to match conditions of the Maryland 3 metre experiment.

• **l\_curr** (default *l\_curr* = .false.) is a logical that controls switching on or off of the current carrying loop.

• amp\_curr (default amp\_curr = 0.0) is a real that gives the amplitude of magnetic field produced by the current carring loop.

**Warning:** Note that an external magnetic field is incompatible with a region of low conductivity inside the spherical shell (i.e, if  $r_LCR < r_cmb$ ). Thus, while imposing an external magnetic field, make sure  $r_LCR > r_cmb$  (which is the default case). For details on  $r_LCR$ , have a look at the section on *electrical conductivity* in the namelist for *physical parameters*.

# 6.5 Start field namelist

This namelist controls whether a start field from a previous solution should be used, or a specific field should be initialized.

# 6.5.1 Reading an input file of start fields

- l\_start\_file (default l\_start\_file=.false.) is a logical that controls whether the code should to read a file named start\_file or not.
- start\_file (default start\_file="no\_start\_file") is a character string. This is the name of the restart file.
- **inform** (default *inform=-1*) is an integer that can be used to specify the format of start\_file. This ensures possible backward compatibility with previous versions of the code. You shouldn't change this value except to read very old *checkpoint\_end.TAG* files generated by older versions of MagIC.

inform=0	Oldest format used by U. Christensen
inform=1	Newer format used by U. Christensen
inform=2	Inner core introduced by J. Wicht
inform=-1	Default format

- scale\_s (default scale\_s=1.0) is a real. It can be possibly used to multiply the input entropy field from start\_file by a constant factor scale\_s.
- scale\_xi (default scale\_xi=1.0) is a real. It can be possibly used to multiply the input chemical composition field from start\_file by a constant factor scale\_xi.
- scale\_v (default scale\_v=1.0) is a real. It can be possibly used to multiply the input velocity field from start\_file by a constant factor scale\_v.
- scale\_b (default scale\_b=1.0) is a real. It can be possibly used to multiply the input magnetic field from start file by a constant factor scale b.
- tipdipole (default tipdipole=0.0) is a real that can be used to add non-axisymmetric disturbances to a start solution if non-axisymmetric parts have been lost due to mapping to a different symmetry. A  $(\ell=1, m=1)$  entropy term is added with:

$$s_{10}(r) = \text{tipdipole } \sin[\pi(r - r_i)]$$

If a magnetic field without an m=1 term is mapped into a field that permits this term, the code adds the respective poloidal field using the  $(\ell=1, m=0)$  poloidal magnetic field and scaling it with tipdipole.

• l\_reset\_t (default l\_reset\_t=.false.) is a logical that can be set to .true. in case one wants to reset the time of start file to zero.

## 6.5.2 Defining the starting conditions

#### Initialisation of entropy

The heat equation with possible heat sources and sinks given by  $epsc\theta$  is solved for the spherically-symmetric term  $(\ell=0,m=0)$  to get its radial dependence. In addition to this initial state, two other laterally varying terms can be initialized. Their radial dependence are assumed to follow:

$$s(r) = 1 - 2x^2 + 3x^4 - x^6,$$

where

$$x = 2r - r_o - r_i.$$

The initial perturbation is thus set to zero at both boundaries  $r_i$  and  $r_o$ , and reaches its maximum amplitude of amp\_s1 or amp\_s2 at the mid-shell radius  $r_i + 1/2$ .

- init\_s1 (default init\_s1=0) is an integer that controls the initial entropy. The following values are possible:
  - init\_s1=0: nothing is initialized
  - init\_s1<100: a random-noise of amplitude amp\_s1 is initialised. The subroutine initS in init\_fields.f90 gives the detail of this implementation.</li>
  - init\_s1>100: initialisation of mode with the spherical harmonic order m given by the last two (or three) digits of init\_s1 and the spherical harmonic degree \( \ell \) given by the first two (or three) digits. Here are two examples:

```
init_s1 = 0707,
amp_s1 = 0.05,
```

will introduce a perturbation on the mode  $(\ell = 7, m = 7)$  with an amplitude of 0.05.

```
init_s1 = 121121,
amp_s1 = 0.01,
```

will introduce a perturbation on the mode ( $\ell = 121, m = 121$ ) with an amplitude of 0.01.

- amp\_s1 (default amp\_s1=0.0) is a real used to contol the amplitude of the perturbation defined by init\_s1.
- init\_s2 (default init\_s2=0) is an integer that controls a second spherical harmonic degee. It follows the same specifications as init\_s1.
- amp\_s2 (default amp\_s2=0.0) is a real used to contol the amplitude of the perturbation defined by init\_s2.

#### Initialisation of chemical composition

The chemical composition equation with possible volumetric sources and sinks given by  $epscxi\theta$  is solved for the spherically-symmetric term ( $\ell=0, m=0$ ) to get its radial dependence. In addition to this initial state, two other laterally varying terms can be initialized. Their radial dependence are assumed to follow:

$$\xi(r) = 1 - 2x^2 + 3x^4 - x^6,$$

where

$$x = 2r - r_o - r_i.$$

The initial perturbation is thus set to zero at both boundaries  $r_i$  and  $r_o$ , and reaches its maximum amplitude of amp\_xi1 or amp\_xi2 at the mid-shell radius  $r_i + 1/2$ .

- init\_xi1 (default init\_xi1=0) is an integer that controls the initial chemical composition. It follows the same specifications as init\_s1.
- amp\_xi1 (default amp\_xi1=0.0) is a real used to contol the amplitude of the perturbation defined by init\_xi1.
- init\_xi2 (default init\_xi2=0) is an integer that controls a second spherical harmonic degee. It follows the same specifications as init\_s1.
- amp\_xi2 (default amp\_xi2=0.0) is a real used to contol the amplitude of the perturbation defined by init\_xi2.

#### Initialisation of magnetic field

- init\_b1 (default init\_b1=0) is an integer that controls the initial magnetic field. The following values are possible:
  - init\_b1<0: random noise initialization of all  $(\ell, m)$  modes, except for  $(\ell = 0, m = 0)$ . The subroutine initB in the file init\_fields.f90 contains the details of the implementation.
  - init\_b1=0: nothing is initialized
  - init\_b1=1: diffusive toroidal field initialized. Mode determined by imageon.
  - init\_b1=2:  $(\ell=1, m=0)$  toroidal field with a maximum field strength of amp\_b1. The radial dependence is defined, such that the field vanishes at both the inner and outer boundaries. In case of an insulating inner core:  $h(r) \approx r \sin[\phi(r-r_o)]$ . In case of a conducting inner core:  $h(r) \approx r \sin[\pi(r/r_o)]$ .
  - init\_b1=3:  $(\ell=1,m=0)$  poloidal field whose field strength is amp\_b1 at  $r=r_i$ . The radial dependence is chosen such that the current density j is independent of r:, i.e.  $\partial j/\partial r=0$ .  $(\ell=2,m=0)$  toroidal field with maximum strength amp\_b1.
  - init\_b1=4:  $(\ell = 1, m = 0)$  poloidal field as if the core were an insulator (potential field). Field strength at  $r = r_i$  is again given by amp\_b1.
  - init\_b1=5:  $(\ell = 1, m = 0)$  poloidal field with field strength amp\_b1 at  $r = r_i$ . The radial dependence is again defined by  $\partial j/\partial r = 0$ .
  - init\_b1=6:  $(\ell = 1, m = 0)$  poloidal field independend of r.
  - init\_b1=7:  $(\ell=1,m=0)$  poloidal field which fulfills symmetry condition in inner core:  $g(r) \approx \left(\frac{r}{r_i}\right)^2 \left[1-\frac{3}{5}\left(\frac{r}{r_o}\right)^2\right]$ . The field strength is given by amp\_b1 at  $r=r_o$ .
  - init\_b1=8: same poloidal field as for init\_b1=7. The toroidal field fulfills symmetry conditions in inner core and has a field strength of amp\_b1 at  $r=r_i$ :  $h(r) \approx \left(\frac{r}{r_i}\right)^3 \left\lceil 1-\left(\frac{r}{r_o}\right)^2 \right\rceil$ .
  - init\_b1=9:  $(\ell=2, m=0)$  poloidal field, which is a potential field at the outer boundary.
  - init\_b1=10: equatorial dipole only.
  - init\_b1=11: axial and equatorial dipoles.
  - init\_b1=21: toroidal field created by inner core rotation, equatorially symmetric  $(\ell=1,m=0)$ :  $h(r)={\rm ampb1} \left(\frac{r_i}{r}\right)^6$ . The field strength is given by amp\_b1 at  $r=r_i$ .
  - init\_b1=22: toroidal field created by inner core rotation, equatorially antisymmetric ( $\ell=2, m=0$ ). Same radial function as for init\_b1=21.
- amp\_b1 (default amp\_b1=0.0) is a real used to contol the amplitude of the function defined by init\_b1.

- **imagcon** (default *imagcon=0*) is an integer, which determines the imposed magnetic field for magnetoconvection. The magnetic field is imposed at boundaries.
  - imagcon=0: no magneto-convection
  - imageon<0: axial poloidal dipole imposed at ICB with a maximum magnetic field strength amp\_b1.
  - imagcon=10:  $(\ell=2, m=0)$  toroidal field imposed at ICB and CMB with a maximum amplitude amp\_b1 at both boundaries.
  - imagcon=11: same as imagcon=10 but the maximum amplitude is now amp\_b1 at the ICB and -amp\_b1 at the CMB.
  - imageon=12:  $(\ell=1, m=0)$  toroidal field with a maximum amplitude of amp\_b1 at the ICB and the CMB.
- **tmagcon** (tmagcon=0.0) is a real.

### Initialisation of velocity field

- init\_v1 (default init\_v1=0) is an integer that controls the initial velocity. The following values are possible:
  - init\_v1=0: nothing is initialized
  - init\_v1=1: a differential rotation profile of the form

$$\Omega = \Omega_{ma} + 0.5\Omega_{ic} \quad \text{for} \quad s \le r_i$$
 
$$\Omega = \Omega_{ma} \quad \text{for} \quad s > r_i$$

where  $s = r \sin \theta$  is the cylindrical radius. This profile only makes sense when one studies spherical Couette flows.

- init\_v1=2: a differential rotation profile of the form  $\Omega = \frac{\text{ampv1}}{\sqrt{1+s^4}}$  is introduced.
- init\_v1>2: a random-noise of amplitude amp\_v1 is initialised. The subroutine initV in init\_fields.f90 gives the detail of this implementation.
- amp v1 (default amp v1=0.0) is a real used to contol the amplitude of the function defined by init v1.

# 6.6 Output control namelist

This namelist contains all the parameters that can be adjusted to control the outputs and diagnostics calculated by the code.

There are four different ways to control at which time step a specific output should be written. Outputs are generally distributed over the total calculation intervall unless an output time interval is defined by a start time t\_start and a stop time t\_stop. If no t\_start is provided, the start time of the calculation is used. If no t\_stop is provided or t\_stop>t\_start the total calculation interval is assumed

1. **Prescribed number of outputs**. The outputs are distributed evenly over the total calculation interval so that the number of timesteps between two outputs is always the same, with the possible exception of the first interval. Last output is written for the last time step, and to compensate the interval before the first output may be longer. However, if t\_stop is provided, the outputs are distributed evenly over the interval [t\_stop, t\_start] with equal times intervals between them.

**Note:** These input variables are usually named with a pattern that follows  $n_{\text{outputName}}$ , for instance,  $n_{\text{graphs}}$ ,  $n_{\text{rsts}}$ ,  $n_{\text{specs}}$ ,  $n_{\text{logs}}$ , etc.

In case you want to make use of a specific time interval, the input variables follow a pattern of the form t\_outputName\_start, t\_outputName\_stop. For instance, t\_graph\_start, t\_graph\_stop, t\_log\_start, t\_log\_stop, t\_spec\_start, t\_spec\_stop, etc.

2. **User-defined interval between two outputs, given in number of time steps**. Again the last output is performed at the end of the run and a compensation may take place at the beginning.

**Note:** These input variables are usually named with a pattern that follows n\_outputName\_step, for instance, n\_graph\_step, n\_rst\_step, n\_spec\_step, n\_log\_step, n\_movie\_step, etc.

3. Defined time interval between two outputs.

**Note:** These input variables are usually named with a pattern that follows dt\_outputName, for instance,  $dt_graph$ ,  $dt_rst$ ,  $dt_spec$ ,  $dt_log$ ,  $dt_movie$ , etc.

4. **User-defined times for output**. By default 5000 different times can be defined for each output type. This can be increased by increasing n\_time\_hits in the file output\_data.f90. While the first three possibilities can only be used alternatively, the fourth one can be employed in addition to one of the two others.

**Note:** These input variables are usually named with a pattern that follows  $t_outputName$ , for instance,  $t_graph$ ,  $t_rst$ ,  $t_spec$ ,  $t_log$ ,  $t_movie$ , etc.

An important parameter in this context is <code>l\_true\_time</code>. If this is set to <code>.true.</code>, the time steps of the program are modified to meet a desired output time. This forces a recalculation of the inversion matricies and therefore requires some additional computing time. When <code>l\_true\_time=.false.</code>, the values at the timestep closest to the desired output time are chosen. Since the timesteps are generally small, this option suffices for most applications.

• l\_true\_time (default l\_true\_time=.false.) is a logical. It causes the code to change time steps to exactly meet the requested output times.

The different possible outputs control parameters are then extensively described in the following pages:

#### Possible outputs

- 1. Control standard/common outputs
- 2. CMB and radial coefficients
- 3. Storage of potentials in spectral space
- 4. Torsional oscillations diagnostics
- 5. Additional possible diagnostics

#### 6.6.1 Standard time-series outputs

The **log** outputs controls the output of all the default time series of the file: kinetic and magnetic energies (*e\_kin.TAG*, *e\_mag\_oc.TAG* and *e\_mag\_ic.TAG* files), dipole information (*dipole.TAG* file), rotation (*rot.TAG*) parameters (*par.TAG*) and various additional diagnostics (*heat.TAG*):

•  $n_{\log step}$  (default  $n_{\log step} = 50$ ) is an integer. This is the number of timesteps between two log outputs.

**Warning:** Be careful: when using too small  $n\_log\_step$ , the disk access will dramatically increases, thus decreasing the code performance.

- $\mathbf{n}$ \_logs (default n\_10qs=0) is an integer. This is the number of log-information sets to be written.
- t\_log (default t\_log=-1.0 -1.0 ...) is real array, which contains the times when log outputs are requested.
- **dt\_log** (default  $dt_1 \log 0$ . 0) is a real, which defines the time interval between log outputs.
- $t_{log\_start}$  (default  $t_{log\_start} = 0.0$ ) is a real, which defines the time to start writing log outputs.
- $t_{log\_stop}$  (default  $t_{log\_stop=0.0}$ ) is a real, which defines the time to stop writing log outputs.

#### 6.6.2 Restart files

The **rst** outputs controls the output of restart files (*checkpoint\_t\_#.TAG*) (i.e. check points in time from which the code could be restarted):

- n\_rst\_step (default n\_rst\_step=0) is an integer. This is the number of timesteps between two restart files.
- n\_rsts (default  $n_rsts=1$ ) is an integer. This is the number of restart files to be written.
- t\_rst (default t\_rst=-1.0 -1.0 ...) is real array, which contains the times when restart files are requested.
- **dt\_rst** (default \( dt\_rst = 0 \). (0) is a real, which defines the time interval between restart files.
- t\_rst\_start (default t\_rst\_start=0.0) is a real, which defines the time to start writing restart files.
- t\_rst\_stop (default t\_rst\_stop=0.0) is a real, which defines the time to stop writing restart files.
- n\_stores (default n\_stores=0) is an integer. This is another way of requesting a certain number of restart files. However, instead of creating each time a new restart file, if n\_stores > n\_rsts the restart file is overwritten, which can possibly help saving some disk space.

**Warning:** The rst files can become quite big and writting them too frequently will slow down the code. Except for very special use, the default set up should be sufficient.

# 6.6.3 Graphic files

The **graph** outputs controls the output of graphic files  $(G_\#.TAG)$  which contain a snapshot the entropy, the velocity field and the magnetic fields:

- n\_graph\_step (default n\_graph\_step=0) is an integer. This is the number of timesteps between two graphic files
- n graphs (default n graphs=1) is an integer. This is the number of graphic files to be written.
- t\_graph (default t\_graph=-1.0 -1.0 ...) is real array, which contains the times when graphic files are requested.
- **dt\_graph** (default dt\_graph=0.0) is a real, which defines the time interval between graphic files.
- t\_graph\_start (default t\_graph\_start=0.0) is a real, which defines the time to start writing graphic files.

• t\_graph\_stop (default t\_graph\_stop=0.0) is a real, which defines the time to stop writing graphic files.

## 6.6.4 Spectra

The **spec** outputs controls the output of spectra: kinetic energy spectra (*kin\_spec\_#.TAG*), magnetic energy spectra (*mag\_spec\_#.TAG*) and thermal spectra (*T\_spec\_#.TAG*):

- n\_spec\_step (default n\_spec\_step=0) is an integer. This is the number of timesteps between two spectra.
- n\_specs (default n\_specs=0) is an integer. This is the number of spectra to be written.
- t\_spec (default t\_spec=-1.0 -1.0 ...) is real array, which contains the times when spectra are requested.
- **dt\_spec** (default \( dt\_spec=0.0 \)) is a real, which defines the time interval between spectra.
- t\_spec\_start (default t\_spec\_start=0.0) is a real, which defines the time to start writing spectra.
- t\_spec\_stop (default t\_spec\_stop=0.0) is a real, which defines the time to stop writing spectra.

#### 6.6.5 Movie files

The **movie** outputs controls the output of movie files (\*\_mov.TAG).

### **Specific inputs**

• l\_movie (default l\_movie=.false.) is a logical. It needs to be turned on to get movie computed.

Several movie-files can be produced during a run (it is now limited to 30 by the variable "n\_movies\_max" in the module movie). The movies are defined by a keyword determining the fields to be plotted and an expression that determines the nature of movie (r-slice,  $\theta$ -slice,  $\phi$ -slice, etc.). The code searches this information in a character string provided for each movie. These strings are elements of the array movie:

• movie (default movie=' ', ' ', ...) is a character string array. It contains the description of the movies one wants to compute.

For example, to invoke a movie(file) that shows (stores) the radial magnetic component of the magnetic field at the CMB, you have to provide the line

```
movie(1)="Br CMB",
```

in the &output namelist. Here, Br is the keyword for the radial component of the magnetic field and CMB is the expression that defines the movie surface. If, in addition, a movie of the temperature field at the meridional slice phi=0 and a movie of the z-vorticity in the equatorial plane are desired, the following line have to be added:

```
movie(2)="Temp phi=0",
movie(3)="Vortz eq",
```

Note that the code does **not interpret spaces and ignores additional characters** that do not form a keyword or a surface definition. Thus, for example Br or Bradial are all interpreted as the same keyword. Furthermore, the interpretation is **not case-sensitive**. The following table gives the possible keywords for movie calculations and their corresponding physical meaning:

Keyword	Fields stored in movie file
Br[radial]	Radial component of the magnetic field $B_r$ .
Bt[heta]	Latitudinal component of the magnetic field $B_{\theta}$ .

Continued on next page

Table 1 – continued from previous page

	rable 1 – continued from previous page
Keyword	Fields stored in movie file
Bp[hi]	Azimuthal component of the magnetic field $B_{\phi}$ .
Bh[orizontal]	The two horizontal components of the magnetic field.
Bs	Cylindrically radial component of the magnetic field $B_s$ .
Ba[ll]	All magnetic field components.
Fieldline[s] or FL	Axisymmetric poloidal field lines in a meridional cut.
AX[ISYMMETRIC]	Axisymmetric phi component of the magnetic field for $\phi = cst$ .
B or AB	
Vr[adial]	Radial component of the velocity field $u_r$ .
Vt[heta]	Latitudinal component of the velocity field $u_{\theta}$ .
Vp[hi]	Azimuthal component of the velocity field $u_{\phi}$ .
Vh[orizontal]	Horizontal velocity field, two components depending on the surface.
Va[ll]	All velocity field components.
Streamline[s] or SL	Field lines of axisymmetric poloidal field for $\phi = cst$ .
AX[ISYMMETRIC]	Axisymmetric component of the velocity field for $\phi = cst$ .
V or AV	γ · · · · · · · · · · · · · · · · · · ·
Vz	Vertical component of the velocity at the equator + vertical component
	of the vorticity at the equator (closest point to equator).
Voz	Vertical component of the vorticity $\omega_z$ .
Vor	Radial component of the vorticity $\omega_r$ .
Vop	Azimuthal component of vorticity $\omega_{\phi}$
Tem[perature] or En-	Temperature/Entropy
tropy	Temperature, Entropy
Entropy (or	Axisymmetric temperature/entropy field for $\phi = cst$ .
Tem[perature])	Axisymmetric temperature/emropy near for $\psi = cst$ .
AX[ISYMMETRIC]	
or AT	
Heat t[ransport]	Radial advection of temperature $u_r \frac{\partial s}{\partial r}$
HEATF	Conducting heat flux $\partial s/\partial r$
AX[iSYMMETRIC]	Conducting heat max 03/01
FL Pro	Axisymmetric field line stretching.
FL Adv	Axisymmetric field line advection.
FL Dif	Axisymmetric field line diffusion.
AB Pro	Toroidal axisymmetric field production.
AB Dif	
	Toroidal axisymmetric field diffusion.
Br Pro	Production of radial magnetic field $B_r$ .
Br Adv	Advection of radial magnetic field $B_r$ .
Br Dif	Diffusion of radial magnetic field $B_r$ .
Jr L. D.	Radial component of the current $j_r$ .
Jr Pro	Production of radial current + $\Omega$ -effect.
Jr Adv	Advection of the radial component of the current $j_r$ .
Jr Dif	Diffusion of the radial component of the current $j_r$ .
Bz Pol	Poloidal part of vertical component of the magnetic field $B_z$ .
Bz Pol Pro	Production of the poloidal part of the vertical component of the magnetic field $B_z$ .
Bz Pol Adv	Advection of the poloidal part of the vertical component of the magnetic
D. D.1 D'C	field $B_z$ .
Bz Pol Dif	Diffusion of the poloidal part of the vertical component of the magnetic
Jz Tor	field $B_z$ .
L Iz Toe	Toroidal part of the vertical component of the current $(j_z)$ .

Continued on next page

Table 1 – continued from previous page

Keyword	Fields stored in movie file
Jz Tor Pro	Production of the toroidal part of the vertical component of the current
	$j_z.$
Jz Tor Adv	Advection of the toroidal part of the vertical component of the current
	$j_z.$
Jz Tor Dif	Diffusion of the toroidal part of the vertical component of the current
	$j_z.$
Bp Tor	Toroidal part of the azimuthal component of the magnetic field $B_{\phi}$ .
Bp Tor Pro	Production of the toroidal part of the azimuthal component of the mag-
	netic field $B_{\phi}$ .
Bp Tor Adv	Advection of the toroidal part of the azimuthal component of the mag-
	netic field $B_{\phi}$ .
Bp Tor Dif	Diffusion of the toroidal part of the azimuthal component of the mag-
	netic field $B_{\phi}$ .
HEL[ICITY]	Kinetic helicity $\mathcal{H} = \boldsymbol{u} \cdot (\boldsymbol{\nabla} \times \boldsymbol{u})$
AX[ISYMMETRIC	Axisymmetric component of the kinetic helicity.
HELICITY] or	
AHEL	
Bt Tor	Toroidal component of the latitudinal component of the magnetic field
	$B_{\theta}$ .
Pot Tor	Toroidal potential.
Pol Fieldlines	Poloidal fieldlines.
Br Shear	Azimuthal shear of the radial component of the magnetic field $B_r$
Lorentz[force] or LF	Lorentz force (only $\phi$ -component).
Br Inv	Inverse field apperance at CMB.

The following table gives the possible surface expression for movie calculations and their corresponding physical meaning:

Surface expression	Definition
CMB	Core-mantle boundary
Surface	Earth surface
EQ[uatot]	Equatorial plane
r=radius	Radial cut at r=radius with radius given in units of the outer core radius.
theta=colat	Latitudinal cut at theta=colat given in degrees
phi=phiSlice	Azimuthal cut ath phi=phiSlice given in degrees.
AX[isymmetric]	Axisymmetric quantity in an azimuthal plane
3D	3D array

Here is an additional example of the possible combinations to build your desired movie files.

```
l_movie = .true.,
movie(1) = "Br CMB",
movie(2) = "Vr EQ",
movie(3) = "Vortr r=0.8",
movie(4) = "Bp theta=45",
movie(5) = "Vp phi=10",
movie(6) = "entropy AX",
movie(7) = "vr 3D",
```

#### Standard inputs

- n\_movie\_step (default n\_movie\_step=0) is an integer. This is the number of timesteps between two movie outputs.
- n\_movies (default n\_movies=1) is an integer. This is the number of movie outputs to be written.
- t\_movie (default t\_movie=-1.0 -1.0 ...) is real array, which contains the times when movie outputs are requested.
- **dt\_movie** (default dt\_movie=0.0) is a real, which defines the time interval between movie outputs.
- t\_movie\_start (default t\_movie\_start=0.0) is a real, which defines the time to start writing movie outputs.
- t\_movie\_stop (default t\_movie\_stop=0.0) is a real, which defines the time to stop writing movie outputs.

## 6.6.6 Field Averages

The code can perform on-the-fly time-averaging of entropy, velocity field and magnetic field. Respective graphic output and spectra are written into the corresponding files (with *G\_ave.TAG*, *kin\_spec\_ave.TAG*, *mag\_spec\_ave.TAG*). The time-averaged energies are written into the *log.TAG* file.

• l\_average (default l\_average=.false.) is a logical, which enables the time-averaging of fields when set to .true..

**Warning:** Time-averaging has a large memory imprint as it requires the storage of 3-D arrays. Be careful, when using large truncations.

# 6.6.7 Poloidal magnetic field potential at CMB

The **cmb** outputs controls the output of poloidal field potential coefficients at the CMB  $b_{\ell m}(r=r_o)$ :  $B\_coeff\_cmb.TAG$  up to a maximum spherical harmonic degree 1 max cmb.

Note: This calculation is only enabled when <code>l\_cmb\_field=.true.or</code> when <code>l\_dt\_cmb\_field=.true.</code>

#### **Specific inputs**

- l\_cmb\_field (default l\_cmb\_field=.false.) is a logical. It needs to be turned on to get cmb files computed.
- l\_dt\_cmb\_field (default l\_dt\_cmb\_field=.false.) is a logical. When set to .true., it allows the calculation of the secular variation of the magnetic field at the CMB.
- l\_max\_cmb (default l\_max\_cmb=14) is an integer. This is the maximum spherical harmonic degree  $\ell$  stored in B\_coeff\_cmb.TAG, i.e. only  $\ell \leq \ell_{maxcmb}$  are stored. For example, the following input parameter means that the B\_coeff\_cmb.TAG file is stored up to a spherical harmonic degree of  $\ell$ :

```
l_cmb_field = .true.,
l_max_cmb = 20,
```

#### Standard inputs

- n\_cmb\_step (default  $n_cmb_step=0$ ) is an integer. This is the number of timesteps between two cmb outputs.
- $\mathbf{n}$ \_cmbs (default n\_cmbs=0) is an integer. This is the number of cmb outputs to be written.
- t\_cmb (default t\_cmb=-1.0 -1.0 ...) is real array, which contains the times when cmb outputs are requested.
- **dt\_cmb** (default dt\_cmb=0.0) is a real, which defines the time interval between cmb outputs.
- t\_cmb\_start (default t\_cmb\_start=0.0) is a real, which defines the time to start writing cmb outputs.
- t\_cmb\_stop (default t\_cmb\_stop=0.0) is a real, which defines the time to stop writing cmb outputs.

## 6.6.8 Poloidal and toroidal potentials at several depths

The coeff\_r# outputs controls the output of the poloidal and toroidal potential coefficients at several depths up to a maximum spherical harmonic degree  $l_{max_r}$ . The files  $B_{coeff_r}$ . The files  $B_{coeff_r}$ . The file  $B_{coeff_r}$ .

Note: This calculation is only enabled when l\_r\_field=.true. or when l\_r\_fieldT=.true..

### **Specific inputs**

- l\_r\_field (default l\_r\_field=.false.) is a logical. It needs to be turned on to get r\_field files computed.
- l\_r\_fieldT (default l\_r\_fieldT=.false.) is a logical. When set to .true., the thermal field is also stored in a file named T\_coeff\_r\*.TAG.
- l\_max\_r (default  $l_max_r=l_max$ ) is an integer. This is the maximum spherical harmonic degree  $\ell$  stored in the r\_field file, i.e. only  $\ell \leq \ell_{maxcmb}$  are stored.

There are two ways to specify the radial grid points where you want to store the [B|V|T]\_coeff\_r#.TAG files. You can specify a stepping n\_r\_step: in that case 5 coeff\_r#.TAG files will be stored at 5 different radial levels every n r step grid point:

```
l_r_field = .true.,
n_r_step = 6,
l_max_r = 30,
```

This will produces 5 files that contain the poloidal and toroidal potentials up to spherical harmonic degree  $\ell = 30$ :

- [B|V|T]\_coeff\_r1.TAG corresponds to the radial grid point with the index nR=6.
- [B|V|T]\_coeff\_r2.TAG to nR=12.
- [B|V|T]\_coeff\_r3.TAG to nR=18.
- [B|V|T]\_coeff\_r4.TAG to nR=24.
- [B|V|T]\_coeff\_r5.TAG to nR=30.
- $n_r$ \_step (default  $n_r$ \_step=2) is an integer. This specifies the stepping between two consecutive [B|V|T]\_coeff\_r#.TAG files.

Alternatively, the input array n\_r\_array can be used to specify the radial grid points you exactly want to store:

```
l_r_field = .true.,
n_r_array = 8, 24, 47,
l_max_r = 10,
```

This will produces 3 files that contain the poloidal and toroidal potentials up to spherical harmonic degree  $\ell = 10$ :

- [B|V|T]\_coeff\_r1.TAG corresponds to the radial grid point with the index nR=8.
- [B|V|T]\_coeff\_r2.TAG to nR=24.
- [B|V|T]\_coeff\_r3.TAG to nR=47.
- n\_r\_array (default n\_r\_array=0 0 0 ...) a an integer array. You can specify the radial grid points (starting from n\_r\_cmb=1) where you want to store the coefficients.

#### Standard inputs

- n\_r\_field\_step (default n\_r\_field\_step=0) is an integer. This is the number of timesteps between two r\_field outputs.
- n\_r\_fields (default n\_r\_fields=0) is an integer. This is the number of r\_field outputs to be written.
- t\_r\_field (default t\_r\_field=-1.0 -1.0 ...) is real array, which contains the times when r\_field outputs are requested.
- **dt\_r\_field** (default \( dt\_r\_field=0.0 \)) is a real, which defines the time interval between r\_field outputs.
- t\_r\_field\_start (default t\_r\_field\_start=0.0) is a real, which defines the time to start writing r\_field outputs.
- t\_r\_field\_stop (default t\_r\_field\_stop=0.0) is a real, which defines the time to stop writing r\_field outputs.

## 6.6.9 Poloidal and toroidal potentials in spectral and radial space

The [VIBIT]\_Imr outputs controls the output of potential files ( $V_{lmr}_{*}.TAG$ ,  $B_{lmr}_{*}.TAG$  and  $T_{lmr}_{*}.TAG$ ). These are files contain the poloidal and toroidal flow and magnetic field potentials (and entropy/temperature) written in spectral and radial spaces (for instance w ( $lm_{max}$ ,  $n_{r_{max}}$ )). These files can be pretty useful since they can be possibly used to reconstruct any quantity in the spectral space or in the physical space you may be interested in.

#### **Specific inputs**

They are two ways to store those files. The first option is to use <code>l\_storePot=.true</code>. and the corresponding time control parameters (<code>n\_pot\_step</code>, <code>t\_pot</code>, <code>n\_pots</code>, etc.). In that case the three files <code>V\_lmr\_#.TAG</code>, <code>B\_lmr\_#.TAG</code> and <code>Tpot\_#.TAG</code> will be stored. The following example will create new <code>V\_lmr\_#.TAG</code>, <code>Bpot\_#.TAG</code> and <code>T\_lmr\_#.TAG</code> files every 1000 time steps:

```
l_storePot = .true.,
n_pot_step = 1000,
```

• l\_storePot (default l\_storePot=.false.) is a logical. It needs to be turned on to store all the potentials in three different files: V\_lmr\_#.TAG, B\_lmr\_#.TAG and T\_lmr\_#.TAG.

The second option is control separately the writing of the three files using the three logicals <code>l\_storeVpot</code>, <code>l\_storeBpot</code> and <code>l\_storeTpot</code> and their corresponding time control parameters. The following example

wrill create a new  $V_{lmr}$ #.TAG file every 1000 time steps and a new  $B_{lmr}$ #.TAG file every 3000 time steps (no  $T_{lmr}$ #.TAG files are stored in that case):

```
l_storeVpot = .true.,
n_Vpot_step = 1000,
l_storeBpot = .true.,
n_Bpot_step = 3000,
l_storeTpot = .false.,
```

- l\_storeVpot (default l\_storeVpot=.false.) is a logical. It needs to be turned on to store the flow poloidal and toroidal potentials. It then writes the V\_lmr\_#.TAG file.
- **l\_storeBpot** (default *l\_storeBpot=.false.*) is a logical. It needs to be turned on to store the magnetic field poloidal and toroidal potentials. It then writes the *B\_lmr\_#.TAG* file.
- **l\_storeTpot** (default *l\_storeTpot=.false.*) is a logical. It needs to be turned on to store the entropy. It then writes the *T\_lmr #.TAG* file.

#### Standard inputs

- n\_pot\_step (default  $n_pot_step=0$ ) is an integer. This is the number of timesteps between two  $[V|B|P]_lmr$  outputs.
- **n\_pots** (default  $n_pots=1$ ) is an integer. This is the number of  $[V|B|P]_{n}$  outputs to be written.
- **t\_pot** (default  $t_{pot}=-1.0 -1.0 ...$ ) is real array, which contains the times when [V|B|P]\_lmr outputs are requested.
- **dt\_pot** (default  $dt_pot=0.0$ ) is a real, which defines the time interval between two [V|B|P]\_lmr outputs.
- t\_pot\_start (default t\_pot\_start=0.0) is a real, which defines the time to start writing [V|B|P]\_lmr outputs.
- **t\_pot\_stop** (default *t\_pot\_stop=0.0*) is a real, which defines the time to stop writing [V|B|P]\_lmr outputs.
- **n\_Vpot\_step** (default *n\_Vpot\_step=0*) is an integer. This is the number of timesteps between two V\_lmr outputs.
- n Vpots (default n Vpots=1) is an integer. This is the number of Vlmr outputs to be written.
- t\_Vpot (default t\_Vpot=-1.0 -1.0 ...) is real array, which contains the times when V\_lmr outputs are requested.
- **dt\_Vpot** (default \( dt\_\_Vpot=0.0 \)) is a real, which defines the time interval between \( V\_\text{lmr} \) outputs.
- t\_Vpot\_start (default t\_Vpot\_start=0.0) is a real, which defines the time to start writing V\_lmr outputs.
- t\_Vpot\_stop (default t\_Vpot\_stop=0.0) is a real, which defines the time to stop writing V\_lmr outputs.
- n\_Bpot\_step (default n\_Bpot\_step=0) is an integer. This is the number of timesteps between two B\_lmr outputs.
- n\_Bpots (default n\_Bpots=1) is an integer. This is the number of B\_lmr outputs to be written.
- t\_Bpot (default t\_Bpot=-1.0 -1.0 ...) is real array, which contains the times when B\_lmr outputs are requested.
- **dt\_Bpot** (default dt\_Bpot=0.0) is a real, which defines the time interval between B\_1mr outputs.
- t\_Bpot\_start (default t\_Bpot\_start=0.0) is a real, which defines the time to start writing B\_lmr outputs.
- t\_Bpot\_stop (default t\_Bpot\_stop=0.0) is a real, which defines the time to stop writing B\_lmr outputs.

- n\_Tpot\_step (default n\_Tpot\_step=0) is an integer. This is the number of timesteps between two T\_lmr outputs.
- n\_Tpots (default n\_Tpots=1) is an integer. This is the number of T\_lmr outputs to be written.
- t\_Tpot (default t\_Tpot=-1.0 -1.0 ...) is real array, which contains the times when T\_lmr outputs are requested.
- **dt\_Tpot** (default \( dt\_Tpot = 0 \). (0) is a real, which defines the time interval between T\_lmr outputs.
- t\_Tpot\_start (default t\_Tpot\_start=0.0) is a real, which defines the time to start writing T\_lmr outputs.
- t\_Tpot\_stop (default t\_Tpot\_stop=0.0) is a real, which defines the time to stop writing T\_lmr outputs.

# 6.6.10 Torsional oscillations (TO)

## **Specific inputs**

- **l\_TO** (default *l\_TO=.false.*) is a logical. It needs to be turned on to compute the torsional oscillations diagnostics (TO) computed.
- **1\_TOmovie** (default 1\_TOmovie=.false) is a logical. It needs to be turned on to store the *TO\_movie.TAG* files.
- sDens (default sDens=1.0) is a float. It gives the relative point density of the cylindrical grid (in the radial direction).
- **zDens** (default *zDens=1*.0) is a float. It gives the relative point density of the cylindrical grid (in the vertical direction).

#### Standard inputs

- n\_TO\_step (default  $n_TO_step=0$ ) is an integer. This is the number of timesteps between two TO outputs.
- **n\_TOs** (default *n\_TOs=1*) is an integer. This is the number of TO outputs to be written.
- t\_TO (default t\_TO=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- **dt\_TO** (default  $dt_TO=0$ . 0) is a real, which defines the time interval between TO outputs.
- $t_TO_start$  (default  $t_TO_start = 0.0$ ) is a real, which defines the time to start writing TO outputs.
- t TO stop (default t TO stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n TOZ step (default n TOZ step=0) is an integer. This is the number of timesteps between two TO outputs.
- n TOZs (default n TOZs=1) is an integer. This is the number of TO outputs to be written.
- t\_TOZ (default t\_TOZ=-1.0 -1.0 ...) is real array, which contains the times when TO outputs are requested.
- **dt\_TOZ** (default \( dt\_TOZ=0.0 \)) is a real, which defines the time interval between TO outputs.
- t\_TOZ\_start (default t\_TOZ\_start=0.0) is a real, which defines the time to start writing TO outputs.
- t\_TOZ\_stop (default t\_TOZ\_stop=0.0) is a real, which defines the time to stop writing TO outputs.
- n\_TOmovie\_step (default n\_TOmovie\_step=0) is an integer. This is the number of timesteps between two TO\_mov outputs.
- n\_TOmovie\_frames (default n\_TOmovies=1) is an integer. This is the number of TO\_mov outputs to be written.

- t\_TOmovie (default t\_TOmovie=-1.0 -1.0 ...) is real array, which contains the times when TO\_mov outputs are requested.
- **dt\_TOmovie** (default dt\_TOmovie=0.0) is a real, which defines the time interval between TO\_mov outputs.
- t\_TOmovie\_start (default t\_TOmovie\_start=0.0) is a real, which defines the time to start writing TO\_mov outputs.
- t\_TOmovie\_stop (default t\_TOmovie\_stop=0.0) is a real, which defines the time to stop writing TO\_mov outputs.

#### 6.6.11 RMS force balance

The code can compute the RMS contributions of the different forces that contribute to the Navier-Stokes equation and the the different terms that enter the induction equation.

- **l\_RMS** (default *l\_RMS=.false.*) is a logical, which enables the calculation of RMS force balance, when set to .true.. The outputs are stored in *dtVrms.TAG* and *dtBrms.TAG*.
- rCut (default rCut=0.0) is a float. This is the thickness of the layer which is left out at both boundaries for the RMS calculation. rCut=0.075 actually means that 7.5% below the CMB and above the ICB are disregarded in the force balance calculation.
- **rDea** (default *rDea=0.0*) is a float. This controls the dealiasing in RMS calculations. rDea=0.1 means that the highest 10% of the Chebyshev modes are set to zero.

## 6.6.12 Additional possible diagnostics

#### Geostrophy

- l\_par (default l\_par=.false.) is a logical. When set to .true., this logical enables additional calculations (for instance the degree of geostrophy). The details of these calculations can be found in the subroutine getEgeos in the Egeos.f90 file. These quantities are then stored in the columns 10-16 of the geos.TAG file.
- l\_corrMov (default l\_corrMov=.false.) is a logical. When set to .true., this logical enables the calculation of a movie file that stores North/South correlation in the CVorz\_mov.TAG file.

#### **Helicity**

• l\_hel (default l\_hel=.false.) is a logical. When set to .true., this logical enables the calculation of helicity (RMS, northern and southern hemisphere, etc.). The outputs are stored in the columns 6-9 of the helicity.TAG file.

## **Power budget**

• **l\_power** (default *l\_power.false.*) is a logical. When set to .true., this logical enables the calculation of input and output power (buoyancy, viscous and ohmic dissipations, torques). The time series are stored in *power.TAG* and *dtE.TAG* and the time-averaged radial profiles in *powerR.TAG*.

#### **Angular momentum**

• **l\_AM** (default *l\_AM=.false.*) is a logical. When set to .true., this logical enables the calculation of angular momentum. The time series are stored in *AM.TAG*.

#### Earth-likeness of the CMB field

- l\_earth\_likeness (default l\_earth\_likeness=.false.) is a logical. When set to .true., this logical enables the calculation of the Earth-likeness of the CMB magnetic field following (Christensen et al., 2010). The time series of the four criteria are stored in earth\_like.TAG.
- l\_max\_comp (default l\_max\_comp=8) is an integer. This is the maximum spherical harmonic degree used to calculate the Earth-likeness of the CMB field.

#### **Drift rates**

• l\_drift (default l\_drift=.false.) is a logical. When set to .true., this logical enables the storage of some selected coefficients to allow the calculation of the drift rate. The time series are stored in drift[V|B][DQ].TAG.

#### **Inertial modes**

• l\_iner (default l\_iner=.false.) is a logical. When set to .true., this logical enables the storage of some selected  $w(\ell, m)$  at mid-shell (stored in *inerP.TAG*) and  $z(\ell, m)$  at mid-shell (stored in *inerT.TAG*). Those files can be further used to identify inertial modes.

#### Radial spectra

- l\_rMagSpec (default l\_rMagSpec=. false) is a logical. When set to .true., the magnetic spectra for the first 6 spherical harmonic degree  $\ell$  for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrSpec.TAG and rBpSpec.TAG.
- I\_DTrMagSpec (default 1\_DTrMagSpec=.false) is a logical. When set to .true., the magnetic spectra of the magnetic field production terms for the first 6 spherical harmonic degree  $\ell$  for all radii are stored at times of log ouputs. This produces the unformatted fortran files rBrProSpec.TAG, rBrAdvSpec.TAG, rBrDifSpec.TAG, rBpProSpec.TAG, rBpAdvSpec.TAG, rBpDifSpec.TAG and rBpDynSpec.TAG. All those files have exactly the same format as the rBrSpec.TAG.

## **Heat transport**

• **l\_fluxProfs** (default *l\_fluxProfs=.false.*) is a logical. When set to .true., this logical enables the calculation of time-averaged radial heat flux profiles (conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux). The time-averaged radial profiles are stored in the *fluxesR.TAG* file.

## **Boundary layer analysis**

• l\_viscBcCalc (default l\_viscBcCalc=.false.) is a logical. When set to .true., this logical enables the calculation of time-averaged radial profiles that can be further use to determine the viscous and thermal boundary layer thicknesses: temperature, temperature variance, horizontal velocity, etc. The time-averaged radial profiles are stored in the bLayersR.TAG file.

#### Parallel/perpendicular decomposition

• l\_perpPar (default l\_perpPar=.false.) is a logical. When set to .true., this logical enables the decomposition of kinetic energy into components parallel and perpendicular to the rotation axis. The time series are stored in perpPar.TAG and the time-averaged radial profiles in perpParR.TAG.

#### **Potential vorticity**

• **l\_PV** (default *l\_PV=.false.*) is a logical. When set to .true., this logical enables some potential vorticity diagnostics. At the end of the run, the results are stored in the the files PVZ.TAG and Vcy.TAG.

#### **Pressure**

• **l\_PressGraph** (default *l\_PressGraph=.true.*) is a logical. When set to .true., this logical enables the storage of pressure in the *graphic files*.

## Time evolution of the m-spectra

- l\_energy\_modes (default l\_energy\_modes=.false.) is a logical. When set to .true., this logical enables the storage of the time-evolution of the kinetic and magnetic energy spectra for a given range of spherical harmonic orders: *time spectra*.
- m\_max\_modes (default m\_max\_modes=13) is an integer. This controls the maximum spherical harmonic order when l\_energy\_modes=.true..

## 6.6.13 Generic options

- **l\_save\_out** (default *l\_save\_out=.false.*) is a logical. When set to .true., the diagnostic files will be safely opened and closed before and after any outputs. When set to .false., the diagnostic files will be opened before the first iteration timestep and close at the end of the run. This may cost some computing time, but guarantees that only minimal information is lost in case of a crash.
- IVerbose (default *lVerbose=.false.*) is a logical. When set to .true., the code displays a lot of debugging informations.

```
Warning: Never set lVerbose to .true. for a production run!
```

• runid (default, runid="MAGIC default run") is a character string. This can be used to briefly describe your run. This information is then for instance stored in the header of the graphic files.

## 6.7 Mantle and Inner Core Namelists

#### 6.7.1 Mantle Namelist

This namelist defines mantle properties

- conductance\_ma (default conductance\_ma=0.0) is a real that defines the conductance (dimensionless) of the mantle.
- **nRotMa** (default nRotMa=0) is an integer that defines the rotation of the mantle:

nRotMa=-1	Mantle rotates with prescribed rate (see omega_ma1 and omega_ma2 below)
nRotMa=0	Fixed, non-rotating mantle
nRotMa=1	Mantle rotates according to torques

- rho\_ratio\_ma (default rho\_ratio\_ma=1) is a real which gives the density of the mantle in terms of that of the outer core.
- omega\_ma1 (default omega\_ma1=0.0) is a real which defines a mantle rotation rate (used when nRotMa=-1).
- omegaOsz\_ma1 (default omegaOsz\_ma1=0.0) is a real which prescribes the oscillation frequency of the mantle rotation rate. In this case, omega\_ma1 is the amplitude of the oscillation.
- **tShift\_ma1** (default *tShift\_ma1=0.0*) is a real which defines the time shift of the mantle rotation rate omega\_ma1.
- omega\_ma2 (default omega\_ma2=0.0) is a real which defines a second mantle rotation rate.
- omegaOsz\_ma2 (default omegaOsz\_ma2=0.0) is a real which defines the oscillation frequency of the second mantle rotation rate omega\_ma2.
- tShift\_ma2 (default tShift\_ma2=0.0) is a real which defines the time shift for omega\_ma2.

The resultant prescribed mantle rotation rate is computed as:

```
omega_ma = omega_ma1*cos(omegaOsz_ma1*(time+tShift_ma1)) + &
    omega_ma2*cos(omegaOsz_ma2*(time+tShift_ma2))
```

The following defines the parameters when one wants to excite inertial modes in the system artificially using a method similar to Rieutord et. al 2012.

- amp\_RiMaSym (default amp\_RiMaSym=0.0) is a real which defines the amplitude of forcing on the outer boundary for an equatorially symmetric mode
- omega\_RiMaSym (default omega\_RiMaSym=0.0) is a real which defines the frequency of forcing on the outer boundary for an equatorially symmetric mode
- m\_RiMaSym (default m\_RiMaSym=0.0) is an integer which defines the wavenumber of the equatorially symmetric mode one wants to excite

The following variables define the same for an equatorially anti-symmetric mode:

- amp\_RiMaAsym (default amp\_RiMaAsym=0.0)
- omega\_RiMaAsym (default omega\_RiMaAsym=0.0)
- m\_RiMaAsym (default m\_RiMaAsym=0.0)

#### 6.7.2 Inner Core Namelist

This namelist defines properties of the inner core

- **sigma\_ratio** (default *sigma\_ratio=0.0*) is a real that defines the conductivity of the inner core with respect to the value of the outer core. sigma\_ratio=0 thus corresponds to a non-conducting inner core.
- **nRotIc** (default *nRotIc=0*) is an integer that defines the rotation of the inner core. Behaves the same way as *nRotMa* (above).
- **rho\_ratio\_ic** (default *rho\_ratio\_ic=1.0*) is a real which defines the density of the inner core in terms of that of the outer core.
- **BIC** (default BIC=0.0) is a real which gives the imposed dipole field strength at the Inner Core Boundary. Having BIC > 0 implies that the inner core acts as a dipole magnet as implemented in the DTS experiment at Grenoble, France.

• Variables prescribing rotation rate of inner core The following variables are used to prescribe rotation rate of the inner core. They behave in the same way as the corresponding variables for the mantle. They are used only when nRotIC=0.

```
omega_ic1 (default omega_ic1=0.0)
omegaOsz_ic1 (default omegaOsz_ic1=0.0)
tShift_ic1 (default tShift_ic1=0.0)
omega_ic2 (default omega_ic2=0.0)
omegaOsz_ic2 (default omegaOsz_ic2=0.0)
tShift_ic2 (default tShift_ic2=0.0)
```

As with the mantle, the resultant prescribed rotation rate for the inner core is computed as:

```
omega_ic = omega_ic1*cos(omegaOsz_ic1*(time+tShift_ic1)) + &
    omega_ic2*cos(omegaOsz_ic2*(time+tShift_ic2))
```

The following, as for the mantle namelist, is for artificially exciting inertial modes in the spherical shell, but for the inner boundary.

- amp\_RiIcSym (default amp\_RiIcSym=0.0) is a real which defines the amplitude of forcing on the inner boundary for an equatorially symmetric mode
- omega\_RiIcSym (default omega\_RiIcSym=0.0) is a real which defines the frequency of forcing on the inner boundary for an equatorially symmetric mode
- m\_RiIcSym (default m\_RiIcSym=0.0) is an integer which defines the wavenumber of the equatorially symmetric mode one wants to excite

The following variables define the same for an equatorially anti-symmetric mode:

- amp\_RiIcAsym (default amp\_RiIcAsym=0.0)
- omega\_RiIcAsym (default omega\_RiIcAsym=0.0)
- m\_RiIcAsym (default m\_RiIcAsym=0.0)

# INTERACTIVE COMMUNICATION WITH THE CODE USING SIGNAL. TAG

It is possible to interactively communicate with the MagIC code **during a run**, using a file which is systematically created when the simulation starts, called **signal.TAG**. By default, this file contains only the word NOT and does nothing to the simulation. Replacing NOT by one of the following allowed keywords will have some influence on the outputs or possibly force the code to terminate its execution:

- **END**: Changing the word NOT to END will cause the code to finish after the current time step and write all the outputs as if it was programmed to finish at that time from the start. This will thus normally produce the *checkpoint\_end.TAG* file that will possibly allow you to continue this run later at your convenience.
- **GRA**: Changing the word NOT to GRA will cause the code to produce a graphic ouptut file *G\_#.TAG*. The keyword will be automatically restored to NOT once the graphic file has been produced.
- **RST**: Changing the word NOT to RST will cause the code to produce a restart file *check-point\_t#.TAG*. The keyword will then be restored to NOT once the restart file has been written.
- **SPE**: Changing the word NOT to SPE will cause the code to produce spectra *kin\_spec\_#.TAG* (and possibly *mag\_spec\_#.TAG* and *T\_spec\_#.TAG* <*secTSpecFile>* depending if the run is magnetic or not, or if it solves a temperature/entropy equation). Once the spectra files have been written, the keyword will be automatically replaced by NOT.
- **POT**: Changing the word NOT to POT will cause the code to produce the potential files *V\_lmr\_#.TAG* (and possibly *B\_lmr\_#.TAG* and *T\_lmr\_#.TAG* < *secTpotFile>* depending if the run is magnetic or not, or if it solves a temperature/entropy equation). Once the potential files have been written, the keyword will be automatically replaced by NOT.

**Note:** Those keywords are **case-insensitive**.

Instead of editing the file with your favorite editor to specify the requested keyword, we recommand using instead the shell command echo to avoid some possible crash during the code execution when writing into the signal.TAG file. For instance, if you want a *graphic output file*, just use the following command (adapted to your current *TAG*):

\$ echo GRA > signal.TAG

## **OUTPUT FILES**

While some information of a run is written into STDOUT to monitor its progress, most outputs are printed into dedicated files identified by the chosen *TAG* extension. These files can be parsed and analysed using the *python classes*. The following pages describe the content and the structure of the different type of output files:

- 1. Most of the information found in STDOUT is also written to the **log-file** called *log.TAG*. In addition, this file contains all input parameters, truncation, information on other output files, and some results like the time averaged energies (when *l\_average=.true*.).
- 2. There are several ascii files that contain the **time-evolution of integrated quantities** (energies, heat fluxes, rotation rate, Reynolds numbers, etc.) that are systematically produced:
  - Kinetic energies: *e\_kin.TAG*,
  - Magnetic energies:  $e_mag_oc.TAG$  and  $e_mag_ic.TAG$ ,
  - Rotation rates: rot. TAG,
  - Informations about the dipolar component of the magnetic field: dipole.TAG,
  - Diagnostic parameters (Reynolds, Elsasser, etc.): par.TAG,
- 3. There are **additional conditional time series** that contain the time-evolution of other physical quantities that depend on the chosen *input parameters*:
  - Angular momentum balance: AM.TAG,
  - Heat transport: heat.TAG,
  - Helicity: *helicity.TAG*,
  - Power budget: power.TAG and dtE.TAG,
  - Square velocities: u\_square.TAG,
  - Drift rates: drift[V\B][D\Q].TAG and iner[P\T].TAG,
  - Torques: SR[IC|MA].TAG,
  - Geostrophy: geos. TAG,
  - RMS calculations of the force balances: dtVrms.TAG and dtBrms.TAG,
  - Kinetic energies perpendicular and parallel to the rotation axis: *perpPar.TAG*.
- 4. Time-averaged radial profiles:
  - Kinetic energies: eKinR.TAG,
  - Magnetic energies: eMagR.TAG,
  - Diagnostic quantities: parR.TAG,

- Power budget: powerR.TAG,
- Average temperature, entropy and pressure: heatR.TAG,
- Heat fluxes: fluxesR.TAG,
- Temperature and horizontal velocities: bLayersR.TAG,
- Kinetic energies perpendicular and parallel to the rotation axis: *perpParR.TAG*.
- 5. **Radial profiles of the transport properties** of the reference state (those files will only be produced when the appropriate input option is chosen):
  - Temperature, density and gravity: anel.TAG,
  - Electrical conductivity: varCond.TAG,
  - Thermal conductivity: varDiff.TAG,
  - Kinematic viscosity: varVisc.TAG,
  - Mapping of the Chebyshev grid: rNM.TAG.
- 6. Kinetic energy, magnetic energy and temperature/entropy **spectra**:
  - Kinetic energy: kin\_spec\_#.TAG,
  - Magnetic energy: kin\_spec\_#.TAG,
  - Velocity square: u2\_spec\_#.TAG,
  - Temperature/entropy: *T\_spec\_#.TAG*,
  - Time-averaged kinetic energy: kin\_spec\_ave.TAG,
  - Time-averaged magnetic energy: mag\_spec\_ave.TAG,
  - Time-averaged temperature/entropy: *T\_spec\_ave.TAG*,
  - 2-D ([r,ell] and [r,m]) spectra: 2D\_[mag|kin|u2]\_spec\_#.TAG.
- 7. Output snapshot that contains the 3-D components of the velocity field, the magnetic field and the temperature/entropy. Those files are named **graphic files** *G\_#.TAG* (or *G\_ave.TAG* for its time-averaged counterpart).
- 8. Time evolution of some chosen fields. Those files are named **movie files**: \*\_mov.TAG.
- 9. Checkpoints outputs that will allow the code to restart. Those files are named **restart files**: *checkpoint\_end.TAG*.
- 10. **Time-evolution of the poloidal and toroidal coefficients** at diffent depths:
  - Time evolution of the poloidal magnetic field at the CMB: B coeff cmb.TAG,
  - Time evolution of the potentials at several depths: [V|T|B] coeff r#.TAG
- 11. Additional specific outputs:
  - Torsional oscillations (see *here*),
  - Potential files: V\_lmr\_#.TAG, B\_lmr\_#.TAG and T\_lmr\_#.TAG,
  - Potential vorticity files: PVZ.TAG and Vcy.TAG,
  - Magnetic spectra for various radii: rB[r|p]Spec.TAG.

# 8.1 Log file: log. TAG

This is a text file contains information about the run, including many of the things which are printed to STDOUT. It has the following information in order of appearance:

- Code version: the version of the code
- **Parallelization**: information about number of MPI ranks being used, blocking information of OpenMP chunks and processor load balancing
- Namelists: displays values of all namelist variables. The ones input by the user should have the input values while the rest of them are set to their default values.
- Mode The mode of the run self-consistent/kinematic dynamo, convection, couette flow etc. See the control
  namelist for more information about mode.
- **Grid parameters**: information about the grid sizes and truncation being used. More information about this in the *grid namelist*. If a new grid, different from that in the restart file is used, then a comparison is shown between old and new grid parameters and the user is informed that the data is being mapped from the old to the new grid.
- **Progress**: information about the progress of the run for every 10% of the run and the mean wall time for time step.
- Writing of graphic, movie, restart and spectra files: displays the time step and tells the user whenever a *G\_#.TAG*, *checkpoint\_#.TAG* or *spectra* file or a *movie frame* is written disk.
- Energies: gives kinetic and magnetic energies (total, poloidal, toroidal, total density) at the end of the run.
- **Time averages**: this part gives time averaged kinetic and magnetic energies (total, poloidal, toroidal, total density) and time averaged parameters (Rm, Elsass, Rol etc.). If *l\_average=.true*., this section also provides information about average spectra and graphic files being written.
- Wall times: this is the last part of the log file and it provides information about the mean wall time for running different parts of the code. These values can be used to judge the speed and scaling capabilities of your computer.

Most of these informations can be parsed and stored into a python class using MagicSetup:

```
>>> # read log.N0m2
>>> stp = MagicSetup(nml='log.N0m2')
>>> print(stp.ek, stp.prmag) # print Ekman and magnetic Prandtl numbers
>>> print(stp.l_max) # print l_max
```

# 8.2 Default time-series outputs

#### 8.2.1 e\_kin.TAG

This file contains the kinetic energy of the outer core, defined by

$$E_{k} = \frac{1}{2} \int_{V} \tilde{\rho} u^{2} dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} \left[ \frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}} |Z_{\ell m}|^{2} dr$$
(8.1)

The detailed calculations are done in the subroutine get e k	<i>kin</i> . This file contains the following informations:
--	---

No. of column	Contents
1	time
2	poloidal energy
3	toroidal energy
4	axisymmetric poloidal energy
5	axisymmetric toroidal energy
6	equatorial symmetric poloidal energy
7	equatorial symmetric toroidal energy
8	equatorial symmetric and axisymmetric poloidal energy
9	equatorial symmetric and axisymmetric toroidal energy

```
>>> # To stack all the e_kin.TAG files of the current directory
>>> ts = MagicTs(field='e_kin', all=True)
>>> # To only read e_kin.N0m2
>>> ts = MagicTs(field='e_kin', tag='N0m2')
```

## 8.2.2 e\_mag\_oc.TAG

This file contains the magnetic energy of the outer core, defined by

$$E_{m} = \frac{1}{2} \int_{V} B^{2} dV = E_{pol} + E_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \left[ \frac{\ell(\ell+1)}{r^{2}} |b_{\ell m}|^{2} + \left| \frac{db_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} |j_{\ell m}|^{2} dr$$
(8.2)

The detailed calculations are done in the subroutine  $get\_e\_mag$ . This file contains the following informations:

No. of column	Contents
1	time
2	outer core poloidal energy
3	outer core toroidal energy
4	outer core axisymmetric poloidal energy
5	outer core axisymmetric toroidal energy
6	outside potential field energy
7	outside axisymmetric potential field energy
8	equatorial symmetric poloidal energy
9	equatorial symmetric toroidal energy
10	equatorial symmetric and axisymmetric poloidal energy
11	equatorial symmetric and axisymmetric toroidal energy
12	outside potential field energy
13	outside potential field axisymmetric energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_oc.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_oc', all=True)
>>> # To only read e_mag_oc.N0m2
>>> ts = MagicTs(field='e_mag_oc', tag='N0m2')
```

## 8.2.3 e\_mag\_ic.TAG

This file contains the magnetic energy of the inner core. The detailed calculations are done in the subroutine  $get\_e\_mag$ . This file contains the following informations:

No. of column	Contents
1	time
2	inner core poloidal energy
3	inner core toroidal energy
4	inner core axisymmetric poloidal energy
5	inner core axisymmetric toroidal energy

This file can be read using MagicTs with the following options:

```
>>> # To stack all the e_mag_ic.TAG files of the current directory
>>> ts = MagicTs(field='e_mag_ic', all=True)
>>> # To only read e_mag_ic.NOm2
>>> ts = MagicTs(field='e_mag_ic', tag='NOm2')
```

#### 8.2.4 rot. TAG

This files contains the rotation of the inner core and the mantle. Output concerning the rotation of inner core and mantle. This file is written by the subroutine write\_rot.

No. of column	Contents
1	time
2	Inner core rotation rate
3	Lorentz torque on inner core
4	viscous torque on inner core
5	mantle rotation rate
6	Lorentz torque on mantle
7	viscous torque on mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the rot.TAG files of the current directory
>>> ts = MagicTs(field='rot', iplot=False, all=True)
```

## 8.2.5 dipole. TAG

This file contains several informations about the magnetic dipole. This file is written by the subroutine  $get\_e\_mag$ .

No. of	Contents	
column		
1	time	
2	tilt angle (colatitude in degrees) of the dipole	
3	longitude (in degress) of dipole-pole	
4	relative energy of the axisymmetric dipole	
5	relative energy of the axisymmetric dipole at the CMB	
6	energy of the axisymmetric dipole at the CMB normalized with the total energy up to	
	spherical harmonic degree and order 11	
7	relative energy of the total (axisymmetric and equatorial) dipole	
8	relative energy of the total (axisymmetric and equatorial) dipole in the outer core	
9	relative energy of the total dipole (axisymmetric and equatorial) at the CMB	
10	energy of the total (axisymmetric and equatorial) dipole at the CMB	
11	energy of the axisymmetric dipole at the CMB	
12	energy of the dipole	
13	energy of the axisymmetric dipole	
14	magnetic energy at the CMB	
15	magnetic energy up to spherical harmonic degree and order 11	
16	ratio between equatorial dipole energy and equatorial poloidal energy	
17	difference between energy at the CMB and equatorial symmetric energy at the CMB,	
	normalized by energy at the CMB	
18	difference between energy at the CMB and axisymmetric energy at the CMB, normalized	
	by energy at the CMB	
19	difference between total energy and equatorial symmetric part of the total energy, nor-	
	malized by the total energy	
20	difference between total energy and axisymmetric part of the total energy, normalized	
	by the total energy	

```
>>> # To stack all the dipole.TAG files of the current directory
>>> ts = MagicTs(field='dipole', all=True)
```

# 8.2.6 par. TAG

This files contains the outputs of several parameters that describe flow and magnetic fields (Reynolds number, Elsasser number, flow lengthscales, etc.). This file is written by the subroutine output.

No. of column	Contents
1	time
2	(magnetic) Reynolds number
3	Elsasser number
4	Local Rossby number Rol
5	Realtive geostrophic kinetic energy
6	Total dipolarity
7	CMB dipolarity
8	Axial flow length scale dlV
9	Flow length scale dmV
10	Flow length scale dpV
11	Flow length scale dzV
12	Dissipation length scale lvDiss
13	Dissipation length scale lbDiss
14	Magnetic length scale dlB
15	Magnetic length scale dmB
16	Elsasser number at CMB
17	Local Rol based on non-ax. flow
18	Convective flow length scale dlVc
19	CMB zonal flow at the equator

```
>>> # To stack all the par.TAG files of the current directory
>>> ts = MagicTs(field='par', all=True)
```

# 8.3 Additional optional time-series outputs

## 8.3.1 heat.TAG

This files contains informations about the heat transfer (Nusselt number, entropy and temperature at both boundaries). This file is written by the subroutine outHeat.

No. of column	Contents
1	time
2	Nusselt number at the inner boundary
3	Nusselt number at the outer boundary
4	Nusselt number based on $\Delta T$ ratio
5	Temperature at the inner boundary
6	Temperature at the outer boundary
7	Entropy at the inner boundary
8	Entropy at the outer boundary
9	Heat flux at the inner boundary
10	Heat flux at the outer boundary
11	Pressure perturbation at the outer boundary
12	volume integrated mass perturbation
13	Sherwood number at the inner boundary
14	Sherwood number at the outer boundary
15	Sherwood number based on $\Delta \xi$ ratio
16	Chemical composition at the inner boundary
17	Chemical composition at the outer boundary

```
>>> # To stack all the heat.TAG files of the current directory
>>> ts = MagicTs(field='heat', all=True)
```

#### 8.3.2 AM. TAG

**Note:** This file is **only** written when  $l\_AM = .true$ .

This file contains the time series of the angular momentum of the inner core, the outer core and the mantle. This file is written by the subroutine  $write\_rot$ .

No. of column	Contents
1	time
2	angular momentum of the outer core
3	angular momentum of the inner core
4	angular momentum of the mantle
5	total angular momentum
6	relative in angular momentum, per time step
7	total kinetic angular momentum
8	relative change in kinetic energy, per time step
9	kinetic angular momentum of the inner core
10	kinetic angular momentum of the outer core
11	kinetic angular momentum of the mantle

This file can be read using MagicTs with the following options:

```
>>> # To stack all the AM.TAG files of the current directory
>>> ts = MagicTs(field='AM', all=True)
```

## 8.3.3 power.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the power budget diagnostic. This file is computed by the subroutine get\_power.

No. of column	Contents
1	time
2	Buoyancy power: $Ra g(r) \langle u_r T' \rangle_s$
3	Chemical power: $Ra_{\xi} g(r) \langle u_r \xi' \rangle_s$
4	Viscous power at the inner boundary (ICB)
5	Viscous power at the outer boundary (CMB)
6	Viscous dissipation: $\langle (\nabla \times u)^2 \rangle_s$
7	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$
8	Total power at the CMB (viscous + Lorentz)
9	Total power at the ICB (viscous + Lorentz)
10	Total power
11	Time variation of total power

This file can be read using MagicTs with the following options:

```
>>> # To stack the files that match the pattern ``power.N0m2*``
>>> ts = MagicTs(field='power', tags='N0m2*')
```

#### 8.3.4 dtE.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the time-derivatives of the total energy. It allows to accurately monitor how the total energy varies with time. This file is generated by the subroutine output.

No. of column	Contents
1	time
2	time-derivative of the total energy $\partial E/\partial t$
3	integrated time variation of the total energy
4	relative time variation of the total energy

## 8.3.5 earth\_like.TAG

This contains informations about the Earth-likeness of the CMB radial magnetic field. This file is written by the subroutine  $get\_e\_mag$ .

**Note:** This file is **only** calculated when  $l_{earth\_like} = .true$ ..

No. of column	Contents
1	time
2	Ratio of axial dipole to non-dipole component at the CMB
3	Equatorial symmetry of the CMB field (odd/even ratio)
4	Zonality: zonal to non-zonal ratio of the CMB field
5	Magnetic flux concentration at the CMB

The details of the calculations are given in (Christensen et al., 2010).

This file can be read using MagicTs with the following options:

```
>>> # To stack all the earth_like.TAG files of the current directory
>>> ts = MagicTs(field='earth_like', all=True)
```

## 8.3.6 geos. TAG

This file contains informations about the geostrophy of the flow. This file is written by the subroutine getEgeos.

**Note:** This file is **only** calculated when  $l\_par=.true$ ..

No. of column	Contents
1	time
2	Relative geostrophic kinetic energy
3	Relative kinetic energy in the northern part of the TC
4	Relative kinetic energy in the southern part of the TC
5	Kinetic energy (calculated on the cylindrical grid)
6	North/South correlation of Vz, outside the TC
7	North/South correlation of vorticity outside the TC
8	North/South correlation of helicity outside the TC

This file can be read using MagicTs with the following options:

```
>>> # To stack all the geos.TAG files of the current directory
>>> ts = MagicTs(field='geos', all=True)
```

## 8.3.7 helicity.TAG

This files contains informations about the kinetic helicity in both the Northern and the Southern hemispheres. This file is written by the subroutine <code>outHelicity</code>.

**Note:** This file is **only** calculated when  $l\_hel=.true$ ..

No. of column	Contents
1	time
2	Helicity (northern hemisphere)
3	Helicity (southern hemisphere)
4	RMS helicity (northern hemisphere)
5	RMS helicity (southern hemisphere)
6	Helicity (northern hemisphere, only non-axisym. flow)
6	Helicity (southern hemisphere, only non-axisym. flow)
8	RMS helicity (northern hemisphere, only non-axisym. flow)
9	RMS helicity (southern hemisphere, only non-axisym. flow)

```
>>> # To stack all the helicity.TAG files of the current directory
>>> ts = MagicTs(field='helicity', all=True)
```

## 8.3.8 u\_square.TAG

**Note:** This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior\_model/="None"* 

This file contains the square velocity of the outer core. It is actually very similar to the  $e\_kin.TAG$  file, except that the density background  $\tilde{\rho}$  is removed:

$$\mathcal{U} = \frac{1}{2} \int_{V} u^{2} \, dV = \mathcal{U}_{pol} + \mathcal{U}_{tor}$$

$$= \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} \left[ \frac{\ell(\ell+1)}{r^{2}} |W_{\ell m}|^{2} + \left| \frac{dW_{\ell m}}{dr} \right|^{2} \right] dr$$

$$+ \frac{1}{2} \sum_{\ell,m} \ell(\ell+1) \int_{r_{i}}^{r_{o}} \frac{1}{\tilde{\rho}^{2}} |Z_{\ell m}|^{2} dr$$

The detailed calculations are done in the subroutine get\_u\_square. This file contains the following informations:

No. of columns	Contents
1	time
2	poloidal part $\mathcal{U}_{pol}$
3	toroidal part $\mathcal{U}_{pol}$
4	axisymmetric contribution to the poloidal part
5	axisymmetric contribution to the toroidal part
6	Rossby number: $Ro = E\sqrt{\frac{2\mathcal{U}}{V}}$
7	Magnetic Reynolds number: $Rm = Pm \sqrt{\frac{2\mathcal{U}}{V}}$
8	local Rossby number: $Ro_l = Ro\frac{d}{l}$
9	average flow length scale: l
10	local Rossby number based on the non-axisymmetric components of the flow
11	average flow length scale based on the non-axisymmetric components of the flow

This file can be read using MagicTs with the following options:

```
>>> # To stack all the u_square.TAG files of the current directory
>>> ts = MagicTs(field='u_square', all=True)
```

## 8.3.9 drift[V|B][D|Q].TAG

**Note:** These files are **only** written when  $l\_drift = .true$ .

These files store spherical harmonic coefficients of the toroidal (poloidal) potential of the flow (magnetic) field, only for  $\ell=m$  or  $\ell=m+1$  depending on the symmetry - D for **D** ipolar and Q for **Q** uadrupolar. The coefficients are stored at different three different radial levels - n\_r1, nr\_2, n\_r3 for the velocity and two different radial levels - n\_r1 and n\_r2 - for the magnetic field.

The symmetries can be summarized below:

Field	Dipolar	Quadrupolar
Velocity	$\ell = m$	$\ell = m + 1$
Magnetic	$\ell = m + 1$	$\ell = m$

 $\ell+m=$  even for toroidal potential refers to an equatorially antisymmetric field (Dipolar), while the same for a poloidal potential is associated with an equatorially symmetric field (Quadrupolar). The sense is opposite when  $\ell+m=$  odd. This is the reason for the choice of selecting these specific coefficients.

The columns of the files look like follows:

For the flow field:

- $n_r1 = (1/3) * n_r_max-1$
- $n_r2 = (2/3) * n_r_max-1$
- $n_r3 = n_r_{max-1}$

Column no.	DriftVD.TAG	DriftVQ.TAG
1	Time	Time
2	z (minc, minc) at n_r1	$z (minc+1, minc)$ at n_r1
3	z (2*minc, 2*minc) at n_r1	z (2*minc+1, 2*minc) at n_r1
4	z (3*minc, 3*minc) at n_r1	z (3*minc+1, 3*minc) at n_r1
5	z (4*minc, 4*minc) at n_r1	z (4*minc+1, 4*minc) at n_r1
6	z (minc, minc) at n_r2	z (minc+1, minc) at n_r2
7	z (2*minc, 2*minc) at n_r2	z (2*minc+1, 2*minc) at n_r2
8	z (3*minc, 3*minc) at n_r2	z (3*minc+1, 3*minc) at n_r2
9	z (4*minc, 4*minc) at n_r2	z (4*minc+1, 4*minc) at n_r2
10	z (minc, minc) at n_r3	z (minc+1, minc) at n_r3
11	z (2*minc, 2*minc) at n_r3	z (2*minc+1, 2*minc) at n_r3
12	z (3*minc, 3*minc) at n_r3	z (3*minc+1, 3*minc) at n_r3
13	z (4*minc, 4*minc) at n_r3	z (4*minc+1, 4*minc) at n_r3

For the magnetic field:

92

•  $n_r1 = n_rICB$ 

• 
$$n_r^2 = n_r CMB$$

Column no.	DriftBD.TAG	DriftBQ.TAG
1	Time	Time
2	b (minc+1, minc) at n_r1	b (minc, minc) at n_r1
3	b (2*minc+1, 2*minc) at n_r1	b (2*minc, 2*minc) at n_r1
4	b (3*minc+1, 3*minc) at n_r1	b (3*minc, 3*minc) at n_r1
5	b (4*minc+1, 4*minc) at n_r1	b (4*minc, 4*minc) at n_r1
6	b (minc+1, minc) at n_r2	b (minc, minc) at n_r2
7	b (2*minc+1, 2*minc) at n_r2	b (2*minc, 2*minc) at n_r2
8	b (3*minc+1, 3*minc) at n_r2	b (3*minc, 3*minc) at n_r2
9	b (4*minc+1, 4*minc) at n_r2	b (4*minc, 4*minc) at n_r2

Analysis of these files can give you information about the drift frequency of the solution and it's symmetry.

## 8.3.10 iner[P|T].TAG

**Note:** These files are **only** written when  $l\_iner=.true$ . and minc = 1.

These files contain time series of spherical harmonic coefficients upto degree,  $\ell=6$  at a radius  $r=(r_{cmb}-r_{icb})/2$ . The inerp.TAG contains coefficients of the poloidal potential while the inerp.TAG contains coefficients of the toroidal potential. These files are written by the subroutine  $write\_rot$ . The oscillations of these coefficients can be analysed to look for inertial modes. The columns of the inerp.TAG look like follows:

No. of column	Coefficient
1	$w(\ell = 1, m = 1)$
2	$w(\ell=2, m=1)$
3	$w(\ell=2, m=2)$
4	$w(\ell=3, m=1)$
20	$w(\ell = 6, m = 5)$
21	$w(\ell=6, m=6)$

where  $w(\ell, m)$  is the poloidal potential with degree  $\ell$  and order m.

The columns of the inerT.TAG follow the following structure:

No. of column	Coefficient
1	$z(\ell=1, m=1)$
2	$z(\ell=2, m=1)$
3	$z(\ell=2, m=2)$
4	$z(\ell=3, m=1)$
20	$z(\ell=6, m=5)$
21	$z(\ell=6, m=6)$

where  $z(\ell, m)$  is the toroidal potential with degree  $\ell$  and order m.

## 8.3.11 SR[IC|MA].TAG

**Note:** These files are **only** written for nRotIc=-1 (for SRIC.TAG) or nRotMa=-1 (for SRMA.TAG). In other words, these outputs are produced **only** when one of the boundaries is made to rotate at a prescribed rotation rate.

These files contain information about power due to torque from viscous and Lorentz forces at the inner core boundary (SRIC.TAG) or core mantle boundary (SRMA.TAG). The columns look like follows:

No. of column	Contents
1	Time
2	$\Omega_{IC} \Omega_{MA}$
3	Total power = Lorentz + Viscous
4	Viscous power
5	Lorentz force power

#### 8.3.12 dtVrms.TAG

**Note:** This file is **only** written when  $l\_RMS=.true$ .

This files contains the RMS force balance of the Navier Stokes equation. This file is written by the subroutine dt Vrms.

No. of column	Contents
1	time
2	Flow changes: inertia-advection
3	Coriolis force
4	Lorentz force
5	Advection term
6	Diffusion term
7	Buoyancy term
8	Pressure gradient term
9	Sum of force terms: geostrophic balance
10	Sum of force terms: pressure, Coriolis and Lorentz
11	Sum of force terms: pressure, buoyancy and Coriolis
12	Sum of force terms: pressure, buoyancy, Coriolis and Lorentz
13	Sum of force terms: Lorentz/Coriolis
14	Sum of force terms: Pressure/Lorentz
15	Sum of force terms: Coriolis/Inertia/Archimedean

This file can be read using MagicTs with the following options:

```
>>> # To stack all the dtVrms.TAG files of the current directory
>>> ts = MagicTs(field='dtVrms', all=True)
```

## 8.3.13 dtBrms.TAG

**Note:** This file is **only** written when  $l\_RMS=.true$ .

No. of column	Contents
1	time
2	Changes in magnetic field (poloidal)
3	Changes in magnetic field (toroidal)
4	Poloidal induction term
5	Toroidal induction term
8	Poloidal diffusion term
9	Toroidal diffusion term
10	Omega effect / toroidal induction term
11	Omega effect
12	Production of the dipole field
13	Production of the axisymmetric dipole field

```
>>> # To stack all the dtBrms.TAG files of the current directory
>>> ts = MagicTs(field='dtBrms', all=True)
```

## 8.3.14 perpPar.TAG

**Note:** This file is **only** written when *l\_perpPar=.true*.

This file contains several time series that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	time
2	Total kinetic energy perpendicular to the rotation axis: $\frac{1}{2}\langle u_s^2 + u_\phi^2 \rangle_V$
3	Total kinetic energy parallel to the rotation axis: $\frac{1}{2}\langle u_z^2\rangle_V$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

This file can be read using MagicTs with the following options:

```
>>> # To stack all the perpPar.TAG files of the current directory
>>> ts = MagicTs(field='perpPar', all=True)
```

# 8.4 Time-averaged radial profiles

## 8.4.1 eKinR.TAG

This file contains the time and horizontally averaged outer core kinetic energy along the radius. This file is calculated by the subroutine  $get_e_kin$ .

No. of col-	Contents
umn	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this ra-
	dial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this radial
	level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level

```
>>> rad = MagicRadial(field='eKinR')
```

## 8.4.2 eMagR.TAG

This file contains the time and horizontally averaged outer core magnetic energy along the radius. This file is calculated by the subroutine  $get\_e\_mag$ .

No. of col-	Contents
umn	
1	radial level
2	time and horizontally averaged poloidal energy
3	time and horizontally averaged axisymmetric poloidal energy
4	time and horizontally averaged toroidal energy
5	time and horizontally averaged axisymmetric toroidal energy
6	time and horizontally averaged poloidal energy, normalized by surface area at this ra-
	dial level
7	time and horizontally averaged axisymmetric poloidal energy, normalized by surface
	area at this radial level
8	time and horizontally averaged toroidal energy, normalized by surface area at this radial
	level
9	time and horizontally averaged axisymmetric toroidal energy, normalized by surface
	area at this radial level
10	ratio between time-averaged dipole energy and time-averaged total energy

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='eMagR')
```

## 8.4.3 parR.TAG

This file contains several time and horizontally averaged flow properties (magnetic Reynolds number, Rossby number, etc.). This file is calculated by the subroutine outPar.

No. of col-	Contents
umn	
1	radial level
2	Magnetic Reynolds number
3	Local Rossby number (based on the mass-weighted velocity)
4	Local Rossby number (based on the RMS velocity)
5	Local flow length-scale (based on the mass-weighted velocity)
6	Local flow length-scale based on the non-axisymmetric flow components (based on the mass-weighted velocity)
7	Local flow length-scale (based on the RMS velocity)
8	Local flow length-scale based on the non-axisymmetric flow components (based on the
	RMS velocity)

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='parR')
```

#### 8.4.4 heatR.TAG

Note: This file is only written when an equation for the heat transport (temperature or entropy) is solved.

This file contains several time and horizontally averaged thermodynamic properties (temperature, pressure, entropy, etc.). This file is calculated by the subroutine <code>outHeat</code>.

No. of column	Contents
1	radial level
2	entropy (spherically-symetric contribution)
3	temperature (spherically-symetric contribution)
4	pressure (spherically-symetric contribution)
5	density (spherically-symetric contribution)
6	chemical composition (spherically-symetric contribution)

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='heatR')
```

## 8.4.5 powerR.TAG

**Note:** This file is **only** written when  $l\_power=.true$ .

This file contains the time and horizontally averaged power input (Buoyancy power) and outputs (viscous and Ohmic heating). This file is calculated by the subroutine *get\_power*.

No. of column	Contents
1	radial level
2	Buoyancy power: $Ra g(r) \langle u_r T' \rangle_s$
3	Chemical power: $Ra_{\xi} g(r) \langle u_r \xi' \rangle_s$
4	Viscous dissipation: $\langle (\nabla \times u)^2 \rangle_s$
5	Ohmic dissipation: $\langle (\nabla \times B)^2 \rangle_s$

```
>>> rad = MagicRadial(field='powerR')
```

## 8.4.6 fluxesR.TAG

**Note:** This file is **only** written when  $l\_fluxProfs=.true$ .

This file contains the time and horizontally averaged heat flux carried out by several physical processes: conductive flux, convective flux, kinetic flux, viscous flux, Poynting flux and resistive flux. This file is calculated by the subroutine outPar.

No. of column	Contents
1	radial level
2	conductive flux:
	$\mathcal{F}_{cond} = -rac{1}{Pr}\kappa ilde{ ho} ilde{T}rac{\partial\langle s angle_s}{\partial r}$
3	convective flux:
	$\mathcal{F}_{conv} = \tilde{\rho}\tilde{T}\langle s  u_r \rangle_s + rac{Pr  Di}{E  Ra} \langle p  u_r \rangle_s$
4	kinetic flux:
	$\mathcal{F}_{kin} = \frac{1}{2} \frac{Pr  Di}{Ra} \langle u_r(\tilde{\rho}u^2) \rangle_s$
5	viscous flux:
	$\mathcal{F}_{visc} = -rac{PrDi}{Ra}\langle m{u}\cdot S angle_s$
6	Poynting flux:
	$\mathcal{F}_{poyn} = -rac{PrDi}{RaEPm}\langle(oldsymbol{u} imesoldsymbol{B} angle_s$
7	resistive flux:
	$\mathcal{F}_{poyn} = \frac{Pr  Di}{Ra  E  Pm^2} \langle (\boldsymbol{\nabla} \times \boldsymbol{B}) \times \boldsymbol{B} \rangle_s$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='fluxesR')
```

## 8.4.7 bLayersR.TAG

**Note:** This file is **only** written when  $l\_viscBcCalc=.true$ .

This file contains several time and horizontally averaged profiles that can be further used to determine thermal and viscous boundary layers: entropy (or temperature), entropy variance, horizontal velocity, radial derivative of the horizontal velocity, thermal dissipation rate. This file is calculated by the subroutine <code>outPar</code>.

No. of column	Contents
1	radial level
2	entropy: $\langle s \rangle_s$
3	entropy variance:
	$\sqrt{\langle (s - \langle s \rangle_s)^2 \rangle_s}$
4	horizontal velocity:
	$u_h = \left\langle \sqrt{u_\theta^2 + u_\phi^2} \right\rangle_s$
5	radial derivative of the horizontal velocity:
	$\partial u_h/\partial r$
6	thermal dissipation rate:
	$\epsilon_T = \langle (\nabla T)^2 \rangle_s$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='bLayersR')
```

Additional analyses of the boundary layers can then be carried out using BLayers:

```
>>> bl = BLayers(iplot=True)
```

## 8.4.8 perpParR.TAG

**Note:** This file is **only** written when  $l\_perpPar=.true$ .

This file contains several time and horizontally averaged profiles that decompose the kinetic energy into components parallel and perpendicular to the rotation axis. This file is calculated by the subroutine <code>outPerpPar</code>.

No. of column	Contents
1	radial level
2	Total kinetic energy perpendicular to the rotation axis:
	$\frac{1}{2}\langle u_s^2 + u_\phi^2 \rangle_s$
3	Total kinetic energy parallel to the rotation axis:
	$rac{1}{2}\langle u_z^2 angle_s$
4	Axisymmetric kinetic energy perpendicular to the rotation axis
5	Axisymmetric kinetic energy parallel to the rotation axis

```
>>> rad = MagicRadial(field='perpParR')
```

# 8.5 Transport properties of the reference state

These files define the radial transport properties of the reference state. These arrays are calculated in the subroutines radial and transportProperties. The output files are written in the subroutine preCalc.

#### 8.5.1 anel. TAG

**Note:** This output is only calculated when an anelastic model is run, that is when <code>l\_anel=.true.</code> or <code>l\_anelastic\_liquid=.true.</code>.

This file contains the radial profiles of the reference state (density, temperature, gravity, etc.).

No. of column	Contents
1	radial level: r
2	temperature: $\tilde{T}(r)$
3	density: $\tilde{\rho}(r)$
4	radial derivative of the density: $\beta = d \ln \tilde{\rho}/dr$
5	radial derivative of $\beta$ : $d\beta/dr$
6	gravity: $g(r)$
7	entropy gradient: $ds_0/dr$
8	thermal diffusion operator: $\nabla \cdot (K(r)\tilde{T}(r)\nabla s_0)$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='anel')
>>> # print radius and density
>>> print(rad.radius, rad.rho0)
```

## 8.5.2 varCond.TAG

**Note:** This output is only calculated when the electrical conductivity varies with radius, i.e. when  $nVarCond \neq 0$ 

This file contains the radial profiles of the electrical conductivity, the electrical diffusivity and its radial derivative.

No. of column	Contents
1	radial level: r
2	electrical conductivity: $\sigma(r)$
3	electrical diffusivity: $\lambda(r) = 1/\sigma(r)$
4	radial derivative of the electrical diffusivity: $d \ln \lambda / dr$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varCond')
>>> print(rad.conduc) # Electrical conductivity
```

## 8.5.3 varDiff.TAG

**Note:** This output is only calculated when the thermal diffusivity varies with radius, i.e. when nVarDiff = 0

This file contains the radial profiles of the thermal conductivity, the thermal diffusivity and its radial derivative.

No. of column	Contents
1	radial level: $r$
2	thermal conductivity: $K(r)$
3	thermal diffusivity: $\kappa(r) = K(r)/\tilde{\rho}(r)$
4	radial derivative of the electrical diffusivity: $d \ln \kappa / dr$
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$

This file can be read using MagicRadial with the following options:

```
>>> rad = MagicRadial(field='varDiff')
>>> print(rad.kappa) # Thermal diffusivity
```

#### 8.5.4 varVisc.TAG

**Note:** This output is only calculated when the kinematic viscosity varies with radius, i.e. when  $nVarVisc \neq 0$ 

This file contains the radial profiles of the dynamic viscosity, the kinematic viscosity and its radial derivative.

No. of column	Contents
1	radial level: $r$
2	dynamic viscosity: $\mu(r)$
3	kinetmatic viscosity: $\nu(r) = \mu(r)/\tilde{\rho}(r)$
4	radial derivative of the kinematic viscosity: $d \ln \nu / dr$
5	Prandtl number: $Pr(r) = \nu(r)/\kappa(r)$
6	magnetic Prandtl number $Pm(r) = \nu(r)/\lambda(r)$

```
>>> rad = MagicRadial(field='varVisc')
>>> # print kinematic viscosity and Ekman
>>> print(rad.kinVisc, rad.ekman)
```

# 8.6 Nonlinear mapping of the Chebyshev grid

## 8.6.1 rNM. TAG

**Note:** This file is only written when  $l_newmap = .true$ .

This file contains the profile of the radial mapping and its derivatives:

No. of column	Contents
1	Grid point index
2	Radius of a grid point
3	First derivative of the mapping at a grid point
4	Second derivative of the mapping at a grid point
5	Third derivative of the mapping at a grid point

# 8.7 Spectra

## 8.7.1 kin\_spec\_#.TAG

This file contains the kinetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal kinetic energy versus degree
3	Poloidal kinetic energy versus order
4	Toroidal kinetic energy versus degree
5	Toroidal kinetic energy versus order

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='ekin')
```

# 8.7.2 mag\_spec\_#.TAG

This file contains the magnetic energy spectra. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal magnetic energy in the outer core versus degree
3	Poloidal magnetic energy in the outer core versus order
4	Toroidal magnetic energy in the outer core versus degree
5	Toroidal magnetic energy in the outer core versus order
6	Poloidal magnetic energy in the inner core versus degree
7	Poloidal magnetic energy in the inner core versus order
8	Toroidal magnetic energy in the inner core versus degree
9	Toroidal magnetic energy in the inner core versus order
10	Poloidal magnetic energy at the CMB versus degree
11	Poloidal magnetic energy at the CMB versus order
12	Poloidal magnetic energy at the CMB

This file can be read using MagicSpectrum with the following options:

```
>>> sp = MagicSpectrum(field='emag')
```

## 8.7.3 u2\_spec\_#.TAG

**Note:** This file is **only** written in an elastic models, i.e. either when *strat/=0* or when *interior\_model/="None"* 

This file contains the spectra of the square velocity. This file is written by the subroutine spectrum.

No. of column	Contents
1	degree / order
2	Poloidal contribution per degree in the outer core
3	Poloidal contribution per order in the outer core
4	Toroidal contribution per degree in the outer core
5	Toroidal contribution per order in the outer core

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``u2_spec_1.test``:
>>> sp = MagicSpectrum(field='u2', ispec=1, tag='test')
```

## 8.7.4 T\_spec\_#.TAG

This file contains the temperature/entropy spectra. It is written by the subroutine <code>spectrum\_temp</code>.

8.7. Spectra 103

No. of column	Contents
1	degree / order
2	RMS temperature/entropy versus degree
3	RMS temperature/entropy versus order
4	RMS temperature/entropy at the ICB versus degree
5	RMS temperature/entropy at the ICB versus order
6	RMS radial derivative of temperature/entropy at the ICB versus degree
7	RMS radial derivative of temperature/entropy at the ICB versus order

## 8.7.5 2D spectra [2D\_kin|mag|u2\_spec]\_#.TAG

Those files contain 2-D spectra in the  $(r,\ell)$  and in the (r,m) planes. In other words, the poloidal and toroidal energies versus degree  $\ell$  or versus order m are computed for all radii. There are three kinds of those files that correspond to the aforementioned spectra, namely  $2D_kin_spec_\#.TAG$ ,  $2D_mag_spec_\#.TAG$  and  $2D_u2_spec_\#.TAG$ . The calculations are done in the subroutine spectrum. The structure of the output files are same for these three outputs. They are stored as fortran unformatted files.

Unformatted files are not directly human readable, and are used to store binary data and move it around without changing the internal representation. In fortran, the open, read and write operations for these files are performed as follows:

```
open(unit=4, file='test', form='unformatted')
read(unit=4) readVar
write(unit=n_out, iostat=ios) writeVar !Unformatted write
```

The structure of the 2D spectra files are as follows:

```
! Line 1
1_____
time, n_r_max, l_max, minc ! Time, resolution, max(\ell), azimuthal symmetry
! Line 2
r(1), r(2), r(3), ..., r(n_r_max)
                                                 ! Radius
! Line 3
e_p_1(l=1,r=1), e_p_1(l=1,r=2), ..., e_p_1(l=1,r=n_r_max),
                                                              ! Poloidal
⇔energy
                                                              ! versus
→dearee
e_p_1(l=l_max,r=1), e_p_1(l=l_max,r=2), ..., e_p_1(l=l_max,r=n_r_max),
! Line 4
e_p_m(m=0,r=1), e_p_1(m=0,r=2), ..., e_p_1(m=1,r=n_r_max),
                                                              ! Poloidal
⊶energy
```

(continues on next page)

```
! versus.
. . .
→order
e_p_1(m=1_max,r=1), e_p_1(m=1_max,r=2), ..., e_p_1(m=1_max,r=n_r_max),
! Line 3
e_t_1(l=1,r=1), e_t_1(l=1,r=2), ..., e_t_1(l=1,r=n_r_max),
                                                               ! Toroidal_
⊶energy
                                                                 ! versus_
⇔degree
e_t_1(l=1_max,r=1), e_t_1(l=1_max,r=2), ..., e_t_1(l=1_max,r=n_r_max),
! Line 4
e_t_m(m=0,r=1), e_t_1(m=0,r=2), ..., e_t_1(m=1,r=n_r_max),
                                                                 ! Toroidal_
⇔energy
                                                                 ! versus
. . .
→order
e_t_1(m=1_max,r=1), e_t_1(m=1_max,r=2), ..., e_t_1(m=1_max,r=n_r_max),
```

Those files can be read using the python class MagicSpectrum2D with the following options:

```
>>> # Read the file 2D_mag_spec_3.ext
>>> sp = MagicRSpec(tag='ext', field=e_mag', ispec=3)
>>> # Print e_pol_1 and e_tor_m
>>> print(sp.e_pol_1, sp.e_tor_m)
```

## 8.7.6 kin\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average=.true$ .

This file contains the time-average kinetic energy spectra as well as squared quantities to allow a possible further reconstruction of the standard deviation. This file is written by the subroutine <code>spectrum\_average</code>.

No. of column	Contents	
1	degree / order	
2	Time-averaged poloidal kinetic energy versus degree	
3	Time-averaged poloidal kinetic energy versus order	
4	Time-averaged toroidal kinetic energy versus degree	
5	Time-averaged toroidal kinetic energy versus order	
6	Time-averaged poloidal kinetic energy square versus degree	
7	Time-averaged poloidal kinetic energy square versus order	
8	Time-averaged toroidal kinetic energy square versus degree	
9	Time-averaged toroidal kinetic energy square versus order	

This file can be read using MagicSpectrum with the following options:

8.7. Spectra 105

```
>>> # To read the file ``kin_spec_ave.test``:
>>> sp = MagicSpectrum(field='kin', ave=True, tag='test')
```

# 8.7.7 mag\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average=.true$ . and the run is magnetic

This file contains the time-average magnetic energy spectra. This file is written by the subroutine <code>spectrum\_average</code>.

No. of col-	Contents	
umn		
1	degree / order	
2	Time-averaged poloidal magnetic energy in the outer core versus degree	
3	Time-averaged poloidal magnetic energy in the outer core versus order	
4	Time-averaged toroidal magnetic energy in the outer core versus degree	
5	Time-averaged toroidal magnetic energy in the outer core versus order	
6	Time-averaged poloidal magnetic energy at the CMB versus degree	
7	Time-averaged poloidal magnetic energy at the CMB versus order	
8	Time-averaged poloidal magnetic energy in the outer core + its standard deviation	
	versus degree	
9	Time-averaged poloidal magnetic energy in the outer core - its standard deviation	
	versus degree	
10	Time-averaged poloidal magnetic energy in the outer core + its standard deviation	
	versus order	
11	Time-averaged poloidal magnetic energy in the outer core - its standard deviation	
	versus order	
12	Time-averaged toroidal magnetic energy in the outer core + its standard deviation	
	versus degree	
13	Time-averaged toroidal magnetic energy in the outer core - its standard deviation	
	versus degree	
14	Time-averaged toroidal magnetic energy in the outer core + its standard deviation	
	versus order	
15	Time-averaged toroidal magnetic energy in the outer core - its standard deviation	
	versus order	
16	Time-averaged poloidal magnetic energy at the CMB + its standard deviation versus	
	order	
17	Time-averaged poloidal magnetic energy at the CMB - its standard deviation versus	
	order	

This file can be read using MagicSpectrum with the following options:

```
>>> # To read the file ``mag_spec_ave.test``:
>>> sp = MagicSpectrum(field='mag', ave=True, tag='test')
```

## 8.7.8 T\_spec\_ave.TAG

**Note:** This file is **only** written when  $l\_average = .true$ .

This file contains the time-averaged temperature/entropy spectra and their standard deviation. It is written by the subroutine <code>spectrum\_temp\_average</code>.

No. of column	Contents
1	Spherical harmonic degree
2	Time-averaged RMS temperature/entropy versus degree
3	Standard deviation of the temperature/entropy versus degree
4	Time-averaged RMS temperature/entropy at the ICB versus degree
5	Standard deviation of the temperature/entropy at the ICB versus degree
6	Time-averaged temperature/entropy gradient at the ICB versus degree
7	Standard deviation of the temperature/entropy gradient at the ICB versus degree

## 8.7.9 2D spectra am\_[kin/mag]\_[pol/tor].TAG

Those files contain the time evolution of the poloidal and toroidal kinetic and magnetic spectra for a given range of spherical harmonic orders m. There are four kinds of those files that correspond to the aforementioned spectra, namely  $am_kin_pol.TAG$ ,  $am_kin_tor.TAG$ ,  $am_mag_pol.TAG$  and  $am_mag_tor.TAG$ . The calculations are done in the subroutine  $get_amplitude$ . The structure of the output files is the same for the four outputs (fortran unformatted files):

```
!-----
! Line 1
!-----
time(t=0), e_p_m(m=0,t=0), e_p_m(m=1,t=0), ..., e_p_m(m=m_max_modes,t=0)
...
!------
! Line N
!-----
time(t=N), e_p_m(m=0,t=N), e_p_m(m=1,t=N), ..., e_p_m(m=m_max_modes,t=N)
...
```

Those files can be read using the python class MagicTs with the following options:

```
>>> # Read the file am_mag_pol.ext
>>> ts = MagicTs(field='am_mag_pol', tag='ext')
>>> # Print the time
>>> print(ts.time)
>>> # Print the energy content in m=11 for all times
>>> print(ts.coeffs[:, 11])
```

# 8.8 Graphic files G\_#.TAG and G\_ave.TAG

These are fortran unformatted files containing 3D data (in the form vector\_array(phi, theta, r)) which can be used to visualize the solution. They are written after a fixed number of time steps as specified by the user in the *Output Control* 

namelist using the parameters listed in the section on output of graphic files. In case l\_average is set to .true., then an average graphic file, named G\_ave.TAG, containing time averaged values of 3D data, is also written at the end of the simulation.

These files are written in chunks of latitude for one radial level at a time by the subroutine <code>graphOut</code> or by <code>graphOut\_mpi</code> depending on whether <code>USE\_MPI</code> is set to Yes or No in the Makefile. The structure of the file looks like below:

```
! Line 1
         !Graphout_version_9 (using MPI without comp. without pressure)
version
         !Graphout_version_10 (using MPI, without comp. with pressure)
          !Graphout_version_11 (using MPI, with comp. without pressure)
          !Graphout_version_12 (using MPI, with comp. with pressure)
          !Graphout_version_5 (without MPI, with pressure and comp.)
          !Graphout_version_6 (without MPI, with comp. without pressure)
          !Graphout_version_7 (without MPI, without comp. without pressure)
          !Graphout_version_8 (without MPI, without comp. with pressure)
! Line 2
runid
! Line 3
!----
n_r_ic_max-1, minc, nThetasBs,
                                           ! (Simulation time),
ra, ek, pr, prmag,
                                           !nThetasBs = no. of
radratio, sigma_ratio
                                           !theta blocks
! Line 4
theta(1:n_theta_max)
!Graphout_version_[9/10/11/12]
! These versions are written when the code uses MPI (USE_MPI=yes). Parallel
! chunks of fields are written for different radial levels. Chunks in theta
! are written in parallel using OpenMP
1_____
! Data
1_____
! Block N
```

```
! Line 4 + N
1_____
n_r-1, r(n_r)/r(1), n_theta_start, n_theta_stop !Radial index, radius in_
→terms
                                              !of r_cmb, start and stop_
∽of
                                              !the theta block
1_____
! Line 4 + (N+1)
sr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Entropy
1_____
! Line 4 + (N+2)
vr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial velocity
! Line 4 + (N+3)
!----
vt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Theta component of_
→velocity
1______
! Line 4 + (N+4)
vp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component) of
                                              !velocity
if (l_chemical_conv):
                                              !If composition is stored
 !-----
 ! Line 4 + (N+5)
 xir(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !composition
if (l_PressGraph):
                                              !If pressure is stored
 !----
 ! Line 4 + (N+6/7)
 1-----
 pr(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !pressure
if (l_mag):
                                                !For a magnetic run
                                                          (continues on next page)
```

```
! Line 4 + (N+5/6/7)
  1______
 br(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Radial magnetic field
  ! Line 4 + (N+6/7/8)
 bt(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Theta component of
                                               !magnetic field
 ! Line 4 + (N+7/8/9)
 bp(1:n_phi_tot, n_theta_start:n_theta_stop, n_r) !Zonal (phi component)
                                               !of magnetic field
!-----
!Graphout_version_[5/6/7/8]
!This version is written when the code does not use MPI (USE_MPI=no).
!Chunks in theta are written in parallel with OpenMP.
! Data
1_____
1_____
! Block N
1-----
! Line 4 + (N+1)
n_r-1, r(n_r)/r(1), n_theta_start, n_theta_stop
! Each of the following data point is written in a new line
!----
! Entropy
1-----
sr(1,n_theta_start,n_r)
                         !n_phi = 1, n_theta = n_theta_start, n_r
sr(2,n_theta_start,n_r)
                              !n_phi = 2, n_theta = n_theta_start, n_r
                              !n_phi = n_phi_tot, n_theta = n_theta_
sr(n_phi_tot,n_theta_start,n_r)
⇔start, n_r
sr(1,n_theta_start+1,n_r)
                              !n_phi = 1, n_theta = n_theta_start+1, n_r
```

```
sr(n_phi_tot,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
sr(1,n_theta_stop,n_r)
sr(2,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
sr(n_phi_tot,n_theta_stop,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n r
! Radial velocity
vr(1,n_theta_start,n_r)
                                !n_phi = 1, n_theta = n_theta_start, n_r
vr(2,n_theta_start,n_r)
                                 !n_phi = 2, n_theta = n_theta_start, n_r
vr(n_phi_tot,n_theta_start,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
vr(1,n_theta_start+1,n_r)
                                !n_phi = 1, n_theta = n_theta_start+1, n_r
. . .
vr(n_phi_tot,n_theta_start+1,n_r)
. . .
vr(1,n_theta_stop,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
vr(2,n_theta_stop,n_r)
vr(n_phi_tot,n_theta_stop,n_r)
                                !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n r
! Theta component of velocity
1_____
vt(1,n_theta_start,n_r)
                                 !n_phi = 1, n_theta = n_theta_start, n_r
vt(2,n_theta_start,n_r)
                                 !n_phi = 2, n_theta = n_theta_start, n_r
vt(n_phi_tot,n_theta_start,n_r)
                                 !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
vt(1,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_start+1, n_r
vt(n_phi_tot,n_theta_start+1,n_r)
                                 !n_phi = 1, n_theta = n_theta_stop, n_r
vt(1,n_theta_stop,n_r)
                                 !n_phi = 2, n_theta = n_theta_stop, n_r
vt(2,n_theta_stop,n_r)
vt(n_phi_tot, n_theta_stop, n_r)   !n_phi = n_phi_tot, n_theta = n_theta_stop,
→ n_r
! Zonal (phi component) of velocity
vp(1,n_theta_start,n_r)
                                !n_phi = 1, n_theta = n_theta_start, n_r
vp(2,n_theta_start,n_r)
                                !n_phi = 2, n_theta = n_theta_start, n_r
vp(n_phi_tot,n_theta_start,n_r) !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
```

```
vp(1,n_theta_start+1,n_r)
                                   !n_phi = 1, n_theta = n_theta_start+1, n_r
vp(n_phi_tot,n_theta_start+1,n_r)
vp(1,n_theta_stop,n_r)
                                   !n_phi = 1, n_theta = n_theta_stop, n_r
vp(2,n_theta_stop,n_r)
                                   !n_phi = 2, n_theta = n_theta_stop, n_r
vp(n_phi_tot,n_theta_stop,n_r)
                                  !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
if (l_chemical_conv):
                                  !If chemical composition is stored
1_____
! Composition
xi(1,n_theta_start,n_r)
                                  !n_phi = 1, n_theta = n_theta_start, n_r
xi(2,n_theta_start,n_r)
                                   !n_phi = 2, n_theta = n_theta_start, n_r
xi(n_phi_tot,n_theta_start,n_r)
                                  !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
xi(1,n_theta_start+1,n_r)
                                  !n_phi = 1, n_theta = n_theta_start+1, n_r
xi(n_phi_tot,n_theta_start+1,n_r)
xi(1,n_theta_stop,n_r)
                                   !n_phi = 1, n_theta = n_theta_stop, n_r
xi(2,n_theta_stop,n_r)
                                  !n_phi = 2, n_theta = n_theta_stop, n_r
xi(n_phi_tot,n_theta_stop,n_r)
                                  !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n r
if (l_PressGraph):
                                   !If pressure is stored
! Pressure
pr(1, n_theta_start, n_r)
                                  !n_phi = 1, n_theta = n_theta_start, n_r
pr(2, n_theta_start, n_r)
                                  !n_phi = 2, n_theta = n_theta_start, n_r
                                  !n_phi = n_phi_tot, n_theta = n_theta_
pr(n_phi_tot,n_theta_start,n_r)
\hookrightarrowstart, n_r
                                  !n_phi = 1, n_theta = n_theta_start+1, n_r
pr(1,n_theta_start+1,n_r)
pr(n_phi_tot,n_theta_start+1,n_r)
. . .
pr(1, n_theta_stop, n_r)
                                   !n_phi = 1, n_theta = n_theta_stop, n_r
                                  !n_phi = 2, n_theta = n_theta_stop, n_r
pr(2,n_theta_stop,n_r)
pr(n_phi_tot,n_theta_stop,n_r)
                                  !n_phi = n_phi_tot, n_theta = n_theta_stop,
\hookrightarrow n_r
if (l_mag):
                                   !Only if it is a magnetic case
```

```
! Radial magnetic field
                                                                      !n_phi = 1, n_theta = n_theta_start, n_r
br(1,n_theta_start,n_r)
br(2,n_theta_start,n_r)
                                                                      !n_phi = 2, n_theta = n_theta_start, n_r
br(n_phi_tot,n_theta_start,n_r)
                                                                      !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n_r
br(1, n_theta_start+1, n_r)
                                                                      !n_phi = 1, n_theta = n_theta_start+1, n_r
br(n_phi_tot, n_theta_start+1, n_r)
br(1,n_theta_stop,n_r)
                                                                      !n_phi = 1, n_theta = n_theta_stop, n_r
br(2, n_theta_stop, n_r)
                                                                     !n_phi = 2, n_theta = n_theta_stop, n_r
\hookrightarrow n r
! Theta component of magnetic field
bt(1,n_theta_start,n_r)
                                                                    !n_phi = 1, n_theta = n_theta_start, n_r
bt(2,n_theta_start,n_r)
                                                                     !n_phi = 2, n_theta = n_theta_start, n_r
bt(n_phi_tot,n_theta_start,n_r)    !n_phi = n_phi_tot, n_theta = n_theta_
⇔start, n r
bt(1,n_theta_start+1,n_r)
                                                                     !n_phi = 1, n_theta = n_theta_start+1, n_r
bt(n_phi_tot, n_theta_start+1, n_r)
bt(1,n_theta_stop,n_r)
                                                                      !n_phi = 1, n_theta = n_theta_stop, n_r
                                                                      !n_phi = 2, n_theta = n_theta_stop, n_r
bt(2,n_theta_stop,n_r)
                                                                     !n_phi = n_phi_tot, n_theta = n_theta_stop,
bt(n_phi_tot,n_theta_stop,n_r)
\hookrightarrow n_r
1_____
! Zonal (phi component) of magnetic field
                                                                     !n_phi = 1, n_theta = n_theta_start, n_r
bp(1,n_theta_start,n_r)
                                                                      !n_phi = 2, n_theta = n_theta_start, n_r
bp(2,n_theta_start,n_r)
bp(n_phi_tot, n_theta_start, n_r)   !n_phi_tot, n_theta_tot, n_the
⇔start, n r
bp(1,n_theta_start+1,n_r)
                                                                     !n_phi = 1, n_theta = n_theta_start+1, n_r
bp (n_phi_tot, n_theta_start+1, n_r)
bp(1,n_theta_stop,n_r)
                                                                      !n_phi = 1, n_theta = n_theta_stop, n_r
bp(2,n_theta_stop,n_r)
                                                                      !n_phi = 2, n_theta = n_theta_stop, n_r
                                                                     !n_phi = n_phi_tot, n_theta = n_theta_stop,
bp(n_phi_tot,n_theta_stop,n_r)
\hookrightarrow n_r
```

```
!-----
!Subsequent blocks
!-----
!Block N+1 in both cases have data at the same radial level but the next
!theta chunk (n_theta_start + nThetaB, n_theta_stop + n_thetaB)
!After data for all the theta blocks have been written for one radial
!level, everything above is repeated for the next radial level
```

The graphic files can be read using the python class MagicGraph.

```
>>> gr = MagicGraph(ivar = 1, tag='TAG')
>>> # print radial velocity
>>> print(gr.vr)
```

They can be visualized using the *Surf* class:

```
>>> s = Surf(tag='TAG')
>>> # Surface map of radial velocity:
>>> s.surf(field = 'vr', r = 0.5, cm = 'jet', levels = 50)
>>> s.slice(field = 'br', lon_0 = [0]) # Longitudinal Slice of radial magnetic field
>>> s.equat(field = 'entropy') # Equatorial slice of entropy
```

## 8.9 Movie files \*\_mov.TAG

**Note:** These files are written **only** when  $l\_movie = .true$ . or when a finite number of movie frames are asked for using the input parameters described in the *standard inputs section* of the *output control namelist*.

These are unformatted fortran files containing time evolution of fields on different surfaces - constant radius, colatitude or azimuth or on the full 3D grid. The fields can be of various types like radial magnetic field or velocity, entropy, helicity etc. The type of field and the type of surface can be specified using a string that begins with the field name, followed by the surface type (or 'full 3D', when a 3D movie is desired). One such example is as follows:

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V all 3D",
movie(3) = "Hel Eq"
```

The code does not interpret any whitespaces and is not case-sensitive so there's no difference between, say, B r cmb and brcmb. For further details and a list of keywords for different fields and surfaces, please refer to the *movie* in the *output control namelist*.

These files are written by the subroutine write\_movie\_frame.

The movie files are suitably named to reflect the type of field and surface. Their names begin with the keyword for the type of movie asked for, followed by the type of surface, followed by the word 'mov'. Thus, a generic movie name looks like:

```
Keyword_SurType_mov.TAG
```

E.g. if one asks for the radial component of magnetic field on surface of CMB, the movie would be named as Br\_CMB\_mov.TAG.

When asks multiple movies for same surface types but different surface levels, the surfaces are numbered with integers. Thus, for the following namelist input,

```
l_movie = .true.,
n_movie_frames = 1000,
movie(1) = "B r r=0.5",
movie(2) = "V p r=0.5",
movie(3) = "V r r=0.8",
```

one would get the following movie files as output:

```
Br_R=C1_mov.TAG
Vp_R=C1_mov.TAG
Vr_R=C2_mov.TAG
```

The structure of a generic movie file is as follows:

```
! Line 1
1----
version
                                    !Movie version: 'JW_Movie_Version_2'
!----
! Line 2
!----
n_type, n_surface,
                                !Type of movie,
const, n_fields
                                    !Type of surface (r, theta, phi, CMB, Eq etc.)
!----
! Line 3
n_movie_field_type(1:n_fields, n_movie) !Type of fields (velocity,
                                               !mag field, vorticity etc.)
! Line 4
!----
runid
!----
! Line 5
n_r_mov_tot, n_r_max, !Total number of
n_theta_max, n_phi_max, !radial grid points (including IC),
minc, ra, ek, pr, prmag, !grid data, physical parameters
radratio, tScale
! Line 6
1_____
```

```
r_mov_tot(1:n_r_mov_tot)/r_cmb !All radii in terms of r_CMB
1_____
! Line 7
1_____
! Line 8
phi(1:n_phi_max)
                           !All phi points
!----
! Frame N
1_____
!----
! Line 8 + N
n_frame, t_movie(N), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+1)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                    !surface or 3D volume
                                    !n_start = start index of a field
                                    !n_stop = last index of a field
! Frame N+1
1-----
! Line 8 + (N+2)
n_frame, t_movie(N+1), omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 8 + (N+3)
frame_data(1:n_fields,n_start:n_stop) !Desired field data on a
                                   !surface or 3D volume
                                    !n_start = start index of a field
                                    !n_stop = last index of a field
                                                          (continues on next page)
```

The 2D movie files can be read and displayed using the python class Movie as follows:

```
>>> Movie() #Lists out available movie files to choose from
>>> M = Movie(file = 'Vr_R=C1_mov.TAG')
```

The 3D movie files can be read using the python class Movie3D:

```
>>> M = Movie3D(file = 'V_3D_mov.TAG')
```

# 8.10 Restart files checkpoint\_\*.TAG

**Note:** These frequency of writing these files are determined by the standard inputs mentioned in the section on *restart* files in the *output control namelist*. If nothing is specified then, by default one restart file is written at the end of the run.

**Note:** A restart file is read **only** when  $l\_start = .true$ .

These are unformatted fortran files containing a snapshot of information about spectral coefficients and physical and grid parameters. As the name suggests, these files are used to 'restart' a run from a specific time. One such file is read by the code at the beginning and are used as initial conditions for the run. These are very useful for continuing a simulation for a long time on computing clusters where the time for a single run is limited.

The file to be read at the beginning is specified by the input parameter *start\_file* which takes in a string providing path to the file.

These files are written by the subroutine *store*.

The following notations will be used for the coefficients of potentials (note that scalar fields like temperature and pressure do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	
Pressure	р	

Time derivatives are denoted with a self-explanatory notation. e.g, dbdt is the first derivative of b.

The word Last appended to a variable name denotes that the value is of the time-step previous to the one during which the file is being written. They are needed for the time-stepping schemes.

\_ic with a variable name says that it belongs to the Inner Core.

```
! Line 1
time*tScale, dt*tScale, ra, pr, prmag, ek, radratio, inform, n_r_max,
n_theta_max, n_phi_tot, minc, nalias, n_r_ic_max, sigma_ratio
if (l_heat):
                               !Run involving heat transport
                               ! (Convection)
! Line 2
1----
  w,z,p,s
! Line 3
!----
  dsdtLast, dwdtLast, dzdtLast, dpdtLast
else:
!----
! Line 2
  w,z,p
!----
! Line 3
 dwdtLast, dzdtLast, dpdtLast
if (l_mag):
                                              !If magnetic run
!----
! Line 4
```

# 8.11 Poloidal and toroidal potentials at given depths

These are fortran unformatted files which store time series of poloidal and toroidal coefficients of different fields (magnetic field, velocity and temperature) at specific depths.

In the following, time(j) is the time during the  $j^{th}$  time step, time(N) being the last step. real and imag denote real and imaginary parts, respectively, of spherical harmonic coefficients. Also, the following notations will be used for the coefficients of potentials (note that scalar fields like temperature do not have a poloidal/toroidal decomposition):

Field	Poloidal	Toroidal
Magnetic	b	aj
Velocity	W	Z
Temperature	S	

First and second derivatives are denoted with a differential notation. e.g.: dw is the first derivative of w, while ddb is the second derivative of b.

### 8.11.1 B\_coeff\_cmb.TAG

**Note:** This file is **only** written when  $l\_cmb\_field=.true$ .

This file contains time series of spherical harmonic coefficients for the poloidal potential of the magnetic field at the outer boundary (CMB) up to a spherical harmonic degree given by  $l\_max\_cmb$ . The detailed calculations are done in the subroutine  $write\_Bcmb$ . The contents of the file look as follows:

- **Header** The file header consists of the information:  $l\_max\_cmb$ , minc and the number of data points  $n\_data$ .
- Data Each chunk of data after the header has the same pattern of time followed by a list of real and imaginary values of coefficients.

Thus, on a whole, the structure of the file looks like follows:

This file can be read using MagicCoeffCmb with the following options:

```
>>> # To stack the files B_cmb_coeff.testc to B_cmb_coeff.testf
>>> cmb = MagicCoeffCmb(tag='test[c-f]')
>>> # print Gauss coefficient for (\ell=10, m=3)
>>> print(cmb.glm[:, 10, 3])
```

### 8.11.2 Coefficients at desired radii

The following files [B|V|T]\_coeff\_r#.TAG save coefficients at specified depths and are written by the subroutine  $write\_coeff\_r$ . See the section on *CMB* and radial coefficients in the ouput control namelist for details of specifying depth, using  $n\_r\_step$  or  $n\_r\_array$  and desired maximum degree of output  $l\_max\_r$ . A separate file for each desired radius is written, numbered suitably as  $[B|V|T]\_coeff\_r1.TAG$ ,  $[B|V|T]\_coeff\_r2.TAG$  etc.

## 8.11.3 B\_coeff\_r#.TAG

**Note:** This file is **only** written when  $l_r_{field}$ =.true..

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal magnetic field potentials and the first and second derivatives of the poloidal potential coefficients in the order b, db, aj and ddb. The output is for a specific radius, r up to degree  $l\_max\_r$ .

- **Header** The file header consists of the information:  $l_max_r$ , minc, the number of data points  $n_data$  and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient b, it's first derivative db, the toroidal coefficient aj and the second derivative of the poloidal coefficient ddb.

The complete structure of the file looks like follows:

```
! Line 1
l_max_r, minc, n_data, r
. . .
!----
! Line j + 1
time(j),
real (b(l=1, m=0)), imag(b(l=1, m=0)),
real (b (1=2, m=0)), imag (b (1=2, m=0)),
real (db(l=1, m=0)), imag(db(l=1, m=0)),
real (db(1=2, m=0)), imag(db(1=2, m=0)),
real (db(1=1_max_cmb, m=1_max_cmb)), imag(db(1=1_max_cmb, m=1_max_cmb)),
real (aj(l=1, m=0)), imag(aj(l=1, m=0)),
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
real(aj(l=1_max_cmb, m=1_max_cmb)), imag(aj(l=1_max_cmb, m=1_max_cmb)),
real (ddb(1=1, m=0)), imag(ddb(1=1, m=0)),
real (ddb (l=1, m=0)), imag (ddb (l=1, m=0)),
/____
! Line N + 1
time(N),
real (b(1=1, m=0)), imag(b(1=1, m=0)),
real (b(1=2, m=0)), imag(b(1=2, m=0)),
real(b(l=1_max_cmb, m=1_max_cmb)), imag(b(l=1_max_cmb, m=1_max_cmb)),
real (db (l=1, m=0)), imag (db (l=1, m=0)),
real (db(1=2, m=0)), imag(db(1=2, m=0)),
real (db(l=1_max_cmb, m=1_max_cmb)), imag(db(l=1_max_cmb, m=1_max_cmb)),
real(aj(l=1, m=0)), imag(aj(l=1, m=0)),
real (aj(1=2, m=0)), imag(aj(1=2, m=0)),
. . .
```

```
real (aj(l=l_max_cmb, m=l_max_cmb)), imag(aj(l=l_max_cmb, m=l_max_cmb)),
real (ddb(l=0, m=0)), imag(ddb(l=0, m=0)),
real (ddb(l=1, m=0)), imag(ddb(l=1, m=0)),
...
real (ddb(l=l_max_cmb, m=l_max_cmb)), imag(ddb(l=l_max_cmb, m=l_max_cmb))
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files B_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='B', r=3)
>>> # print the time and the poloidal potential for (\ell=3, m=3)
>>> print(cr.time, cr.wlm[:, 3, 3])
```

### 8.11.4 V\_coeff\_r#.TAG

**Note:** This file is **only** written when  $l_r_{field} = .true$ .

This file contains output of time series of the spherical harmonic coefficients of the poloidal and toroidal velocity field potentials and the first derivatives of the poloidal potential coefficients in the order w, dw, and z. The output is for a specific radius, r up to degree  $l\_max\_r$ .

- **Header** The file header consists of the information:  $l_max_r$ , minc, the number of data points  $n_data$  and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of: the poloidal coefficient w, it's first derivative dw and the toroidal coefficient z.

The complete structure of the file looks like follows:

```
!------
! Line 1
!------

l_max_r, minc, n_data, r
!------
! Line j + 1
!-----

time(j),
real(w(l=1,m=0)), imag(w(l=1,m=0)),
real(w(l=2,m=0)), imag(w(l=2,m=0)),
...
real(w(l=1_max_cmb,m=l_max_cmb)), imag(w(l=l_max_cmb,m=l_max_cmb)),
real(dw(l=1,m=0)), imag(dw(l=1,m=0)),
real(dw(l=2,m=0)), imag(dw(l=2,m=0)),
...
real(dw(l=1_max_cmb,m=l_max_cmb)), imag(dw(l=l_max_cmb,m=l_max_cmb)),
real(dw(l=1_max_cmb,m=l_max_cmb)), imag(dw(l=1_max_cmb,m=l_max_cmb)),
real(z(l=1,m=0)), imag(z(l=1,m=0)),
real(z(l=2,m=0)), imag(z(l=2,m=0)),
...
```

This file can be read using MagicCoeffR with the following options:

```
>>> # To stack the files V_coeff_r3.test* from the working directory
>>> cr = MagicCoeffR(tag='test*', field='V', r=3)
>>> # print the poloidal and toroidal potentials for (\ell=6, m=0)
>>> print(cr.wlm[:, 6, 0], cr.zlm[:, 6, 0])
```

### 8.11.5 T coeff r#.TAG

**Note:** This file is **only** written when  $l_r_{field}T = .true$ .

This file contains output of time series of the spherical harmonic coefficients of the temperature (or entropy) field. The output is for a specific radius, r up to degree  $l\_max\_r$ .

- **Header** The file header consists of the information:  $l\_max\_r$ , minc, the number of data points  $n\_data$  and the radius, r.
- Data Each chunk of data after the header contains the time at which the coefficients are stored, followed by the real and imaginary parts of the coefficient s.

The complete structure of the file looks like follows:

# 8.12 TO outputs

**Note:** These output files are **only** written when  $l\_TO=.true$ .

### 8.12.1 TOZ\_#.TAG and TOZM.TAG

### 8.12.2 TO mov. TAG files

**Note:** This file is **only** written when  $l\_TOmovie = .true$ .

This file contains the time evolution of the different forces that enter the phi-average of the azimuthal component of the Navier-Stokes equation. This is a special kind of *movie file* that contains seven different azimuthally-averaged fields in a  $(r, \theta)$  plane: the axisymmetric zonal flow component, the azimuthal component of the Reynolds stresses, the azimuthal component of advection, the azimuthal component of viscosity, the azimuthal component of Lorentz force, the azimuthal component of Coriolis force and the azimuthal component of the time-derivative. The structure of the file is similar to a *movie file*, i.e. an unformatted fortran binary file with a header that describes the type of the movie file. The detailed calculations can be found in the subroutine out TO.

On a whole, the structure of the file looks like follows:

```
!------
! Line 1
!-----
version
```

```
!----
! Line 2
!-----
n_type, n_surface, const, n_fields
! Line 3
runid
!----
! Line 4
n_r_movie_max, n_r_max, n_theta_max, n_phi_tot, minc, ra, ek, pr,
prmag, radratio, tScale
!----
! Line 5
r(1), r(2), ..., r(n_r_movie_max)
!----
! Line 6
theta(1), theta(2), ..., theta(n_theta_max)
1_____
! Line 7
phi(1), phi(2), ..., phi(n_theta_max)
!----
! Line 7+N
\verb|n_frame|, t_movie(N)|, omega_ic, omega_ma, dipLat, dipLon, dipStr, dipStrGeo
! Line 7+(N+1)
vphi(t=t_movie(N),phi=1,theta=1),
vphi(t=t_movie(N),phi=1,theta=2),
vphi(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)
! Line 7+(N+2)
                                                              (continues on next page)
```

(continues on next page)

8.12. TO outputs 125

```
rey(t=t_movie(N),phi=1,theta=1),
rey(t=t_movie(N),phi=1,theta=2),
...,
rey(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)

...
!-------
! Line 7+(N+7)
!------
dtVphi(t=t_movie(N),phi=1,theta=1),
dtVphi(t=t_movie(N),phi=1,theta=2),
...,
dtVphi(t=t_movie(N),phi=n_phi_max,theta=n_theta_max)
```

This file can be read using TOMovie with the following options:

```
>>> # To load 'TO_mov.test' and time-average it:
>>> to = TOMOvie(file='TO_mov.test', avg=True, levels=65, cm='seismic')
```

# 8.13 Radial spectra rB[r|p]Spec.TAG

**Note:** This files are **only** written when  $l\_rMagSpec=.true$ .

Those files contain the time-evolution of the poloidal (**rBrSpec.TAG**) and the toroidal (**rBpSpec.TAG**) magnetic energies for all radii including the inner core and for spherical harmonic degrees from  $\ell=1$  to  $\ell=6$ . The calculations are done in the subroutines rBrSpec and rBpSpec, respectively. The outputs are stored as a fortran unformatted file which follows the following structure for rBrSpec.TAG:

```
!-----
! Line N+2
!-----
time[N+1]
...
```

The rBpSpec. TAG files have exactly the same structure (just replacing the poloidal energy by its toroidal counterpart).

**Warning:** Be careful that in this file,  $n\_r\_tot$  is the **total** number of grid points (thus including the inner core).

Those files can be read using the python class MagicRSpec with the following options:

```
>>> # Read the files BrSpec.testa, BrSpec.testb and BrSpec.testc and stack them
>>> rsp = MagicRSpec(tag='test[a-c]', field='Br')
>>> # Print time and the time evolution of e_pol(\ell=4) at the 10th radial grid point
>>> print(rsp.time, rsp.e_pol[:, 10, 3])
```

## 8.14 Potential files [V|B|T] lmr #.TAG

### 8.14.1 V\_lmr\_#.TAG and V\_lmr\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeVpot=.true$ .

These files contain a snapshot of the poloidal and toroidal flow potentials w and z in the radial space for all spherical harmonic degrees and orders. They basically contain two arrays of dimension  $(1m_max, n_r_max)$ . The detailed calculations are done in the subroutine  $write_Pot$ . The outputs are stored as a fortran unformatted file which follows the following structure:

The potential files that contain the poloidal and toroidal potentials for the momentum can be read and transformed to the physical space using the python class MagicPotential.

```
>>> p = MagicPotential(field='V')
>>> print(p.pol[p.idex[3,2], 32]) # print w(1=3, m=2, n_r=32)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='vr', cm='jet', levels=50) # Equatorial cut of vr
>>> p.avg(field='vp') # Azimuthal average of vphi
>>> p.surf(field='vt', r=0.8) # Radial cut of vtheta at r=0.8r_o
```

## 8.14.2 B\_lmr\_#.TAG, B\_lmr\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeBpot=.true$ .

These files contain a snapshot of the poloidal and toroidal magnetic potentials b and a j in the radial space for all spherical harmonic degrees and orders. The detailed calculations are done in the subroutine  $write_Pot$ . The outputs are stored as a fortran unformatted file which follows the following structure:

```
ra, ek, pr, prmag, sigma_ratio, omega_ma, omega_ic ! Header (physics)
1_____
! Line 3
1-----
time
                                           ! Header (time)
! Line 4
r(1), ..., r(n_r_max), rho0(1), ..., rho0(n_r_max) ! Radius, Density
! Line 5
!----
                                           ! Poloidal potential
b(lm=1, n_r=1), b(lm=2, n_r=1), ..., b(lm=lm_max, n_r=1),
b(lm=1, n_r=n_r_max), \ldots, b(lm=lm_max, n_r=n_r_max)
1_____
! Line 6
1_____
                                           ! Toroidal potential
aj(lm=1, n_r=1), aj(lm=2, n_r=1), ..., aj(lm=lm_max, n_r=1),
aj(lm=1, n_r=n_r_max), ..., aj(lm=lm_max, n_r=n_r_max)
! The two following lines are optional and are only written when there is !
! an electrically-conducting inner-core
! Line 7
!----
                                           ! Time and poloidal ...
time.
→potential
b_ic(lm=1, n_r=1), b_ic(lm=2, n_r=1), ..., b_ic(lm=1m_max, n_r=1),
b_ic(lm=1, n_r=n_r_max), ..., b_ic(lm=lm_max, n_r=n_r_max)
! Line 8
1-----
time,
                                           ! Time and toroidal .
→potential
aj_ic(lm=1, n_r=1), aj_ic(lm=2, n_r=1), ..., aj_ic(lm=lm_max, n_r=1),
aj_ic(lm=1,n_r=n_r_max), ..., aj_ic(lm=lm_max,n_r=n_r_max)
```

The potential files that contain the poloidal and toroidal potentials for the magnetic field can be read and transformed to the physical space using the python class MagicPotential.

```
>>> p = MagicPotential(field='B')
>>> print(p.tor[p.idex[3,2], 32]) # print aj(1=3, m=2, n_r=32)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='Br', cm='jet', levels=50) # Equatorial cut of Br
>>> p.avg(field='Bp') # Azimuthal average of Bphi
>>> p.surf(field='Bt', r=0.8) # Radial cut of Btheta at r=0.8r_o
```

### 8.14.3 T\_lmr\_#.TAG, T\_lmr\_ave.TAG

**Note:** These output files are **only** written when either when  $l\_storePot=.true$ . or when  $l\_storeTpot=.true$ .

These files contain a snapshot of the temperature/entropy s in the spectral and radial spaces for all spherical harmonic degrees and orders. They basically contain one array of dimension ( $lm_max$ ,  $n_r_max$ ). The detailed calculations are done in the subroutine  $write_Pot$ . The outputs are stored as a fortran unformatted file which follows the following structure:

```
!-----
! Line 1
l_max, n_r_max, n_r_ic_max, minc, lm_max
                                        ! Header (truncation)
! Line 2
ra, ek, pr, prmag, sigma_ratio, omega_ma, omega_ic ! Header (physics)
! Line 3
                                                 ! Header (time)
time
! Line 4
r(1), ..., r(n_r_max), rho0(1), ..., rho0(n_r_max) ! Radius, Density
1_____
! Line 5
                                                 ! Temperature/entropy
s(lm=1, n_r=1), s(lm=2, n_r=1), ..., s(lm=lm_max, n_r=1),
s(lm=1,n_r=n_r_max), ..., s(lm=lm_max,n_r=n_r_max)
```

The potential files that contain the temperature/entropy in the spectral space can be read and transformed to the physical space using the python class <code>MagicPotential</code>.

```
>>> p = MagicPotential(field='T')
>>> print(p.pol[p.idex[0,0], 10]) # print s(1=0, m=0, n_r=10)
```

Once transformed to the physical space using a Fourier and a Legendre transform, they can be displayed:

```
>>> p.equat(field='T', cm='jet', levels=50) # Equatorial cut of temperature/entropy
>>> p.avg(field='T') # Azimuthal average of temperature/entropy
```

## DATA VISUALISATION AND POST-PROCESSING

Most of the *output files* written during a run of MagIC can be treated with the python post-processing classes and functions present in the \$MAGIC\_HOME/python/magic directory. These classes depend on several python libraries that can be usually found in most of the Linux distributions.

# 9.1 Requirements

## 9.1.1 Hard dependencies

- python 2.7/3.3 or higher.
- matplotlib 1.0 or higher.
- scipy 0.10 or higher.

## 9.1.2 Optional dependencies

- Although entirely optional, the installation of ipython makes the interactive use of the post-processing python functions much more pleasant. Installing it is therefore recommanded for a smoother interactive usage of the python functions.
- The installation of the basemap toolkit is optional. If installed, additional projections for the magic.Surf (Aitoff, orthographic, Mollweide, etc.) class will be provided for 2-D surface plotting. Otherwise, the usage of magic.Surf is limited to the Hammer projection.

# 9.2 Configuration: magic.cfg file

A file named magic.cfg located in \$MAGIC\_HOME/python/magic/magic.cfg should have been created when you used the source path/sourceme.sh command for the first time on your machine. At that stage, it tried to automatically fill the best options that correspond to your setup. Although tested on several various machine configurations, the auto-configuration script might however fail on your setup. The paragraph below details the possible options that you may want to adjust in the magic.cfg file.

## 9.2.1 Detailed options

In case, the file magic.cfg doesn't exist in the directory \$MAGIC\_HOME/python/magic, you can easily copy it from the default configuration magic.cfg.default and then adjust the options manually:

```
$ cp $MAGIC_HOME/python/magic/magic.cfg.default $MAGIC_HOME/python/magic/magic.cfg
```

In that file, you can set up the default matplotlib rendering backend (among the possible options: TkAgg, GTKAgg, Qt4Agg,...). The default configuration is

```
backend = TkAgg
```

Note: This is usually the default configuration which is the most likely to work on supercomputing clusters.

If LaTeX is installed on your work station, you might also want to make use of the better looking LaTeX fonts for all your displayed matplotlib figures (labels, caption, ticks, etc.). Be careful though that most of the time LaTeX is **not installed** on supercomputers. The default configuration is thus:

```
labTex = False
```

You can change the default colormap that will be used in the plotting routines.

```
defaultCm = seismic
```

You cant change the default number of contours that will be used in the plotting routines.

```
defaultLevels = 65
```

If you want to enable all the features of the python functions (faster reading the  $G_{-}\#.TAG$ , conversion to the VTK/VTS file format, potential extrapolation of the field lines, etc.), some fortran libraries present in the  $$MAGIC\_HOME/python/magic/fortranLib$$  directory need to be built using the f2py, which should be available on your Linux workstation if all the required python libraries have been correctly installed. The boolean buildlib can control whether you want to try building the fortran libraries with f2py. The following configuration will try to build the libraries:

```
buildLib = True
```

The exact name of the executable f2py however varies from one Linux distribution to the other. Among possible options, one frequently finds: f2py, f2py2, f2py3. This can be set to your proper configuration using the f2pyexec option of the magic.cfg file. The default configuration is:

```
f2pyexec = f2py2
```

You can also choose the fortran compiler you want to use on your machine. A list of the installed compilers can be obtained by using (where f2py has to be replaced by your own executable):

```
$ f2py -c --help-fcompiler
```

The most frequent options are:

- qnu95 for the GNU gfortran compiler.
- intelem for the Intel ifort compiler.
- pg for the Portlang group pgf compiler.

Once you've decided the ideal configuration for your machine, set it up via the option fcompiler:

```
fcompiler = intelem
```

Finally, he same configuration procedure can be applied to the C compiler using the variable named ccompiler. The possible options are:

- unix for the GNU gcc compiler.
- intelem for the Intelicc compiler.

In most of the configurations, the default configuration should do a good job:

```
ccompiler = unix
```

If you encounter any problem during the building stage, you can try playing with this parameter though.

## 9.2.2 Ready?!

Once you think you set up your magic.cfg file correctly, you can test your configuration. If you decided to build the fortran libraries (i.e. buildLib=True), you can easily test it with any python shell by typing the following command:

```
>>> from magic import *
```

If the build was successful, it should display:

```
Please wait: building greader_single...
Please wait: building greader_double...
Please wait: building lmrreader_single...
Please wait: building Legendre transforms...
Please wait: building vtklib...
```

Once the libraries have been successfully installed, this message won't be displayed again, except if you remove the \*.so files that are now present in the \$MAGIC\_HOME/python/magic/directory.

# 9.3 Python functions and classes

Once the python environment is correctly configured you can use the available functions and classes to analyse and post-process your data. The following pages will give you the detailed API of the available classes, as well as some practical examples:

### **Python classes**

- 1. To read the **log.TAG** files , see *here*.
- 2. To read and analyse the time series, see *here*.
- 3. To read and analyse the radial profiles, see *here*.
- 4. To read and analyse spectra **\_spec\_#.TAG**, see *here*.
- 5. To read and analyse the **G\_#.TAG** files, see *here*.
- 6. To read and analyse movie files **mov.TAG**, see *here*.
- 7. To read and analyse coeff files [VIBIT]\_coeff.TAG, see here.
- 8. To read and analyse potential files [VIBIT]\_lmr\_#.TAG, see here.
- 9. To read and analyse radial spectra **B[rlp]Spec.TAG**, see *here*.

- 10. To read and analyse TO outputs, see *here*.
- 11. To compare several runs simultaneously, see *here*.
- 12. To transform the graphic files **G\_#.TAG** to a file format readable by paraview, VisIt or mayavi and do some fancy 3-D visualisation, see *here*.
- 13. For additional diagnostics (boundary layer, heat transport, interpolation on cylindrical grids, etc.), see *here*.
- 14. To take a look at the additional useful functions available (derivation, integration, interpolation, etc.), see *here*.

## 9.3.1 Support for the log. TAG files

```
class magic.MagicSetup(datadir='.', nml='input.nml', quiet=False)
```

This class allows to read the input namelist or the log file of a current job and creates an object that contains all the parameters found in the namelist/log file.

```
>>> stp = MagicSetup(nml='log.test', quiet=True)
>>> print(stp.ra) # print the Rayleigh number
>>> print(stp.n_r_max) # print n_r_max
```

```
__init__ (datadir='.', nml='input.nml', quiet=False)
```

### **Parameters**

- datadir (str) the working directory
- nml (str) name of the input namelist/ log file
- quiet (bool) when set to True, makes the output silent (default False)

## 9.3.2 Support for the time series

**class** magic.**MagicTs** (*datadir='.'*, *field='e\_kin'*, *iplot=True*, *all=False*, *tag=None*)

This python class is used to read and plot the different time series written by the code:

- Kinetic energy: *e\_kin.TAG*
- Magnetic energy of the outer core: e\_mag\_oc.TAG
- Magnetic energy of the inner core: e\_mag\_ic.TAG
- Dipole information: dipole.TAG
- Rotation: rot.TAG
- Diagnostic parameters: par.TAG
- Geostrophy: geos.TAG
- Heat transfer: heat.TAG
- Helicity: helicity.TAG
- Velocity square: *u\_square.TAG*
- Angular momentum: AM.TAG
- Power budget: power.TAG
- Earth-likeness of the CMB field: earth\_like.TAG

- Parallel and perpendicular decomposition: perpPar.TAG
- RMS force balance: dtVrms.TAG
- RMS induction terms: dtBrms.TAG
- Time-evolution of m-spectra: am\_[kin|mag]\_[pol|tor].TAG

Here are a couple of examples of how to use this function.

```
>>> # plot the most recent e_kin.TAG file found in the directoy
>>> MagicTs(field='e_kin')
>>>
>>> # stack **all** the power.TAG file found in the directory
>>> ts = MagicTs(field='power', all=True)
>>> print(ts.time, ts.buoPower) # print time and buoyancy power
>>>
>>> # If you only want to read the file ``heat.NOm2z``
>>> ts = MagicTs(field='heat', tag='NOm2z', iplot=False)
```

\_\_init\_\_ (datadir='.', field='e\_kin', iplot=True, all=False, tag=None)

#### **Parameters**

- datadir (str) working directory
- **field** (str) the file you want to plot
- **iplot** (bool) when set to True, display the plots (default True)
- **all** (bool) when set to True, the complete time series is reconstructed by stacking all the corresponding files from the working directory (default False)
- tag(str) read the time series that exactly corresponds to the specified tag

plot()

Plotting subroutines. Only called if 'iplot=True'

### 9.3.3 Averaging the time series

class magic.AvgField(tstart=None, tag=None, dipExtra=False, perpPar=False, std=False)

This class calculates the time-average properties from time series. It will store the input starting time in a small file named tInitAvg, such that the next time you use it you don't need to give tstart again.

```
>>> # Average from t=2.11 and also store the additional dipole.TAG informations
>>> a = AvgField(tstart=2.11, dipExtra=True)
>>> # Average only the files that match the pattern N0m2[a-c]
>>> a = AvgField(tstart=2.11, tag='N0m2[a-c]')
>>> # Average only the files that match the pattern N0m2Z*
>>> a = AvgField(tstart=2.11, tag='N0m2Z*')
>>> print(a) # print the formatted output
```

\_\_\_init\_\_ (tstart=None, tag=None, dipExtra=False, perpPar=False, std=False)

### **Parameters**

- tstart (float) the starting time for averaging
- **tag** (str) if you specify an input tag (generic regExp pattern), the averaging process will only happen on the time series that match this input pattern

- dipExtra (bool) if this parameter is set to True, then additional values extracted from dipole.TAG are also computed
- perpPar (bool) additional values extracted from perpPar.TAG are also computed

```
__str__()
```

Formatted output

## 9.3.4 Support for time-averaged radial profiles

class magic.MagicRadial(datadir='.', field='eKin', iplot=True, tag=None, tags=None, normalize\_radius=False)

This class can be used to read and display the time and horizontally averaged files:

- Kinetic energy: eKinR.TAG
- Magnetic energy: eMagR.TAG
- Anelastic reference state: anel.TAG
- Variable electrical conductivity: varCond.TAG
- Variable thermal diffusivity: varDiff.TAG
- Variable kinematic viscosity: varVisc.TAG
- Diagnostic parameters: parR.TAG
- Power budget: powerR.TAG
- Heat fluxes: fluxesR.TAG
- Mean entropy, temperature and pressure: heatR.TAG
- Radial profiles used for boundary layers: bLayersR.TAG
- Parallel/perpendicular decomposition: perpParR.TAG

```
>>> rad = MagicRadial(field='eKinR') # display the content of eKinR.tag
>>> print(rad.radius, rad.ekin_pol_axi) # print radius and poloidal energy
```

\_\_init\_\_ (datadir='.', field='eKin', iplot=True, tag=None, tags=None, normalize\_radius=False)

### **Parameters**

- datadir (str) working directory
- field(str) the field you want to plot
- iplot (bool) to plot the output, default is True
- tag(str) a specific tag, default is None
- tags (list) a list that contains multiple tags: useful to sum several radial files

plot()

Display the result when iplot=True

## 9.3.5 Support for the spectra files (kin|mag|u2)\_spec\_#.TAG

- Kinetic energy spectra: kin\_spec\_#.TAG
- Magnetic energy spectra: mag\_spec\_#.TAG
- Spectra of the velocity square: u2\_spec\_#.TAG

```
>>> # display the content of kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum(field='e_kin', ispec=1)
>>> # display the content of mag_spec_ave.test on one single figure
>>> sp = MagicSpectrum(field='e_mag', tag='test', ave=True, gather=True)
```

\_\_init\_\_ (datadir='.', field='e\_kin', iplot=True, ispec=None, ave=False, gather=False, tag=None)

#### **Parameters**

- **field** (str) the spectrum you want to plot, 'e\_kin' for kinetic energy, 'e\_mag' for magnetic
- **iplot** (bool) display the output plot when set to True (default is True)
- ispec (int) the number of the spectrum you want to plot
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **ave** (bool) plot a time-averaged spectrum when set to True
- **gather** (bool) gather the spectra on the same figure when set to True, display one figure per spectrum when set to False, (default is False)
- datadir (str) current working directory

plot()

Plotting function

## 9.3.6 Support for the 2-D spectra files

This class can be used to read and display 2-D spectra in the  $(r, \ell)$  and in the (r, m) planes

- Kinetic energy spectra: 2D\_kin\_spec\_#.TAG
- Velocity square spectra: 2D\_u2\_spec\_#.TAG
- Magnetic energy spectra: 2D\_mag\_spec\_#.TAG

```
>>> # display the content of 2D_kin_spec_1.tag
>>> # where tag is the most recent file in the current directory
>>> sp = MagicSpectrum2D(field='e_kin', ispec=1, levels=17, cm='seismic')
>>> # display the content of 2D_mag_spec_3.test
>>> sp = MagicSpectrum2D(field='e_mag', tag='test', ispec=3)
```

\_\_init\_\_ (datadir='.', field='e\_mag', iplot=True, ispec=None, tag=None, cm='jet', levels=33, precision='Float64')

### **Parameters**

- **field** (str) the spectrum you want to plot, 'e\_kin' for kinetic energy, 'e\_mag' for magnetic
- iplot (bool) display the output when set to True (default is True)

- **ispec** (*int*) the number of the spectrum you want to plot
- tag (str) file suffix (tag=, if not specified the most recent one in the current directory is chosen
- cm (str) name of the colormap (default='jet')
- **levels** (*int*) number of contour levels (default 33)
- **precision** (str) single or double precision
- datadir (str) current working directory

plot (*levels*, *cm*)
Plotting function

#### **Parameters**

- levels (int) number of contour levels
- cm(str) name of the colormap

## 9.3.7 Support for G\_#. TAG files

```
class magic.MagicGraph (ivar=None, datadir='.', quiet=True, ave=False, tag=None, precision='Float32')
```

This class allows to read the 3-D graphic outputs of the MagIC code (*G\_#.TAG* and *G\_*ave.TAG) files. Those are binary unformatted outputs, there are therefore two ways to load them:

- If buildLib=True in magic.cfg and the fortran libraries were correctly built, then the reader uses a fortran program that is expected to be much faster than the pure python routine.
- If buildLib=False, then a pure python program is used to read the G files.

```
>>> # Regular G files
>>> gr = MagicGraph(ivar=1, tag='N0m2a')
>>> print(gr.vr.shape) # shape of vr
>>> print(gr.ek) # print ekman number
>>> print(gr.minc) # azimuthal symmetry
>>> # Averaged G file with double precision
>>> gr = MagicGraph(ave=True, tag='N0m2', precision='Float64')
```

\_\_init\_\_ (ivar=None, datadir='.', quiet=True, ave=False, tag=None, precision='Float32')

### **Parameters**

- ave (bool) when set to True, it tries to find an average G file (G\_ave.TAG)
- ivar (int) the number of the G file
- tag (str) extension TAG of the G file. If not specified, the most recent G\_#.TAG file found in the directory will be selected.
- quiet (bool) when set to True, makes the output silent
- datadir (str) directory of the G file (default is.)
- **precision** (str) single or double precision (default 'Float32')

#### rearangeLat (field)

This function is used to unfold the colatitudes

**Parameters field** (numpy.ndarray) – input array with MagIC ordering of colatitudes (i.e. successively Northern Hemisphere and Southern Hemisphere)

**Returns** an array with the regular ordering of the colatitudes

Return type numpy.ndarray

**class** magic.**Surf** (*ivar=None*, *datadir='.'*, *vort=False*, *ave=False*, *tag=None*, *precision='Float32'*)

This class allows to display the content of a graphic file (*G\_#.TAG* or *G\_ave.TAG*). It allows to plot radial, azimuthal and equatorial cuts as well as phi-averages.

```
>>> # To read G_1.test
>>> s = Surf(ivar=1, ave=False, tag='test')
>>> # To read the latest G file in the working directory (double precision)
>>> s = Surf(precision='Float64')
```

```
>>> # Possible plots
>>> s.equat(field='vr')
>>> s.avg(field='vp')
>>> s.surf(field='entropy', r=0.8)
>>> s.slice(field='Br', lon_0=[0, 30])
```

\_\_init\_\_ (ivar=None, datadir='.', vort=False, ave=False, tag=None, precision='Float32')

## **Parameters**

- ivar (int) index of the graphic file
- ave (bool) when set to True, it tries to read a time-averaged graphic file
- tag (str) TAG suffix extension of the graphic file
- **vort** (bool) a boolean to specify whether one wants to compute the 3-D vorticity components (take care of the memory imprint)
- datadir (str) the working directory
- **precision** (*str*) the storage precision of the graphic file (single or double precision). Default is 'Float32' (single)

avg (field='vphi', levels=65, cm='seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, pol=False, tor=False, mer=False, merLevels=16, polLevels=16)
Plot the azimutal average of a given field.

```
>>> s = Surf()
>>> # Axisymmetric zonal flows, 65 contour levels
>>> s.avg(field='vp', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='Br', tit=False, cbar=False)
```

```
>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)
```

```
>>> # Omega-effect, contours truncated from -1e3 to 1e3
>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)
```

- **field** (str) the field you want to display
- levels (int) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)

- **tit** (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- pol (bool) diplay the poloidal field lines contours when set to True
- tor (bool) diplay the toroidal axisymmetric field contours when set to True
- mer (bool) display the meridional circulation contours when set to True
- merLevels (int) number of contour levels to display meridional circulation
- pollevels (int) number of contour levels to display poloidal field lines

equat (field='vr', levels=65, cm='seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, avg=False, normRad=False)
Plot the equatorial cut of a given field

```
>>> s = Surf()
>>> # Equatorial cut of the z-vorticity, 65 contour levels
>>> s.equat(field='vortz', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.equat(field='bphi', tit=False, cbar=False)
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.equat(field='vr', vmin=-1e3, vmax=1e3, levels=33)
```

```
>>> # Normalise the contour levels radius by radius
>>> s.equat(field='jphi', normRad=True)
```

- **field** (str) the name of the input physical quantity you want to display
- **avg** (bool) when set to True, an additional figure which shows the radial profile of the input physical quantity (azimuthal average) is also displayed
- **normRad** (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

slice (field='Bphi', lon\_0=0.0, levels=65, cm='seismic', normed=True, vmin=None, vmax=None, cbar=True, tit=True, grid=False, nGridLevs=16, normRad=False)

Plot an azimuthal slice of a given field.

```
>>> s = Surf()
>>> # vphi at 0, 30, 60 degrees in longitude
>>> s.slice(field='vp', lon_0=[0, 30, 60], levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.avg(field='vp', lon_0=32, tit=False, cbar=False)
```

```
>>> # Axisymmetric Bphi + poloidal field lines
>>> s.avg(field='Bp', pol=True, polLevels=8)
```

```
>>> # Omega-effect, contours truncated from -1e3 to 1e3
>>> s.avg(field='omeffect', vmax=1e3, vmin=-1e3)
```

### **Parameters**

- **field** (str) the field you want to display
- lon\_0 (float or list) the longitude of the slice in degrees, or a list of longitudes
- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- grid (bool) display or hide the grid
- nGridLevs (int) number of grid levels
- **normRad** (bool) when set to True, the contour levels are normalised radius by radius (default is False)

surf (field='Bphi', proj='hammer', lon\_0=0.0, r=0.85, vmax=None, vmin=None, lat\_0=30.0, levels=65, cm='seismic', lon\_shift=0, normed=True, cbar=True, tit=True, lines=False)
Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> s = Surf()
>>> # Radial flow component at ``r=0.95 r_o``, 65 contour levels
>>> s.surf(field='vr', r=0.95, levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> s.surf(field='entropyfluct', r=0.6, tit=False, cbar=False)
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> s.surf(field='vp', r=1., vmin=-1e3, vmax=1e3, levels=33)
```

```
>>> # If basemap is installed, additional projections are available
>>> s.surf(field='Br', r=0.95, proj='ortho', lat_0=45, lon_0=45)
```

### **Parameters**

- **field** (str) the name of the field you want to display
- **proj** (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **r** (*float*) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- lon\_shift (int) translate map in azimuth (in degrees)
- lon\_0 (float) central azimuth (only used with Basemap)
- lat\_0 (float) central latitude (only used with Basemap)
- tit (bool) display the title of the figure when set to True
- **tit** display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **lines** (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- **vmax** (float) maximum value of the contour levels
- **vmin** (*float*) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

# 9.3.8 Support for movie files \*\_mov.TAG

class magic.Movie (file=None, iplot=True, step=1, png=False, lastvar=None, nvar='all', levels=12, cm='RdYlBu\_r', cut=0.5, bgcolor=None, fluct=False, normed=False, avg=False, std=False, dpi=80, normRad=False, precision='Float32', deminc=True, ifield=0)

This class allows to read the movie files generated by the MagIC code.

```
>>> m = Movie()
>>> # This returns a list of the available movies in the directory
>>> # and lets you decide which one you want to read
```

```
>>> # Reads and display AV_mov.test
>>> m = Movie(filed='AV_mov.test')
>>> print(m.data) # access to the data
```

```
>>> # Read three movie files (no display)
>>> m1 = Movie(file='AV_mov.testa', iplot=False)
>>> m2 = Movie(file='AV_mov.testb', iplot=False)
>>> m3 = Movie(file='AV_mov.testc', iplot=False)
>>> # Stack them together
>>> m = m1+m2+m3
>>> # Display
>>> m.plot(levels=33, cm='seismic', cut=0.5)
```

```
>>> # Store the outputs in movie/img_#.png
>>> # Only from the timesteps 280 to 380
>>> m = Movie(file='AB_mov.test', png=True, nvar=100, lastvar=380)
```

```
___add___(new)
```

Built-in function to sum two movies

**Note:** So far this function only works for two movies with the same grid sizes. At some point, we might introduce grid extrapolation to allow any summation

\_\_init\_\_ (file=None, iplot=True, step=1, png=False, lastvar=None, nvar='all', levels=12, cm='RdYlBu\_r', cut=0.5, bgcolor=None, fluct=False, normed=False, avg=False, std=False, dpi=80, normRad=False, precision='Float32', deminc=True, ifield=0)

### **Parameters**

- nvar (int) the number of timesteps of the movie file we want to plot starting from the last line
- png (bool) if png=True, write the png files instead of display
- iplot (bool) if iplot=True, display otherwise just read
- lastvar (int) the number of the last timesteps to be read
- **step** (*int*) the stepping between two timesteps
- **levels** (*int*) the number of contour levels
- cm(str) the name of the color map
- **fluct** (bool) if fluct=True, substract the axisymmetric part
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- avg (bool) if avg=True, time-average is displayed
- **std** (bool) if std=True, standard deviation is displayed
- **dpi** (*int*) dot per inch when saving PNGs
- normRad (bool) if normRad=True, then we normalise for each radial level
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision
- **cut** (float) adjust the contour extrema to max(abs(data))\*cut
- **bgcolor** (str) background color of the figure
- deminc (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield

avgStd (*ifield=0*, *std=False*, *cut=0.5*, *levels=12*, *cmap='RdYlBu\_r'*)
Plot time-average or standard deviation

## **Parameters**

• **ifield** (*int*) – in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield

- **std** (bool) the standard deviation is computed instead the average when std is True
- **levels** (*int*) number of contour levels
- cmap(str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))\*cut

#### **Parameters**

- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield
- levels (int) number of contour levels
- cmap(str) name of the colormap
- **cut** (float) adjust the contour extrema to max(abs(data))\*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (int) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

timeLongitude (*ifield=0*, *removeMean=True*, *lat0=0.0*, *levels=12*, *cm='RdYlBu\_r'*, *deminc=True*) Plot the time-longitude diagram (input latitude can be chosen)

### **Parameters**

- **ifield** (*int*) in case of a multiple-field movie file, you can change the default field displayed using the parameter ifield
- lat0 (float) value of the latitude
- levels (int) number of contour levels
- cm(str) name of the colormap
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **removeMean** (bool) remove the time-averaged part when set to True

class magic.Movie3D (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio\_out=2.0, potExtra=False, precision='Float32')

This class allows to read the 3D movie files  $(B|V)_3D_-$ . TAG and transform them into a series of VTS files ./vtsFiles/B3D\_#. TAG that can be further read using paraview.

```
>>> Movie3D(file='B_3D.TAG')
```

\_\_init\_\_ (file=None, step=1, lastvar=None, nvar='all', nrout=48, ratio\_out=2.0, potExtra=False, precision='Float32')

- **file** (str) file name
- nvar (int) the number of timesteps of the movie file we want to plot starting from the last line
- lastvar (int) the number of the last timestep to be read
- **step** (*int*) the stepping between two timesteps
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision
- potExtra (bool) when set to True, potential extrapolation of the magnetic field outside the fluid domain is also computed
- ratio\_out (float) ratio of desired external radius to the CMB radius. This is is only used when potExtra=True
- **nrout** (*int*) number of additional radial grid points to compute the potential extrapolation. This is only used when potExtra=True

# 9.3.9 Support for B\_cmb\_coeff. TAG and (V|B)\_coeff\_r#. TAG files

This class allows to read the  $B\_coeff\_cmb.TAG$  files. It first read the poloidal potential at the CMB and then transform it to the Gauss coefficients  $g_{\ell m}$  and  $h_{\ell m}$  using the getGauss function.

```
>>> # Reads the files B_coeff_cmb.testa, B_coeff_cmb.testb
>>> # and B_coeff_cmb.testc and stack them in one single time series
>>> cmb = MagicCoeffCmb(tag='test[a-c]')
>>> print(cmb.ell, cmb.glm) # print \ell and g_{\ell m}
>>> print(cmb.glm[:, cmb.idx[1, 0]]) # time-series of the axisymmetric dipole
>>> plot(cmb.time, cmb.dglmdt[:, cmb.idx[2, 0]]) # Secular variation of the_
-quadrupole
>>> # Display the time-evolution of the CMB field
>>> cmb.movieCmb(levels=12, cm='seismic')
>>> # Save the time-evolution of the CMB field
>>> cmb.movieCmb(levels=12, cm='seismic', png=True)
```

\_\_add\_\_\_(new)

Built-in function to sum two cmb files

**Note:** So far this function only works for two cmb files with the same grid sizes. At some point, we might introduce grid extrapolation to allow any summation/

```
__init__(tag, ratio_cmb_surface=1, scale_b=1, iplot=True, lCut=None, precision='Float64', ave=False, sv=False, quiet=False)

A class to read the B_coeff_cmb files
```

- tag(str) if you specify a pattern, it tries to read the corresponding files
- ratio\_cmb\_surface (float) ratio of surface ratio to CMB radius (default is 1)
- scale\_b (float) magnetic field unit (default is 1)
- iplot (int) a logical to toggle the plot (default is True)

- **precision** (char) single or double precision
- ave (bool) load a time-averaged CMB file when set to True
- **sv** (bool) load a dt\_b CMB file when set to True
- quiet (bool) verbose when toggled to True (default is True)
- **1Cut** (*int*) reduce the spherical harmonic truncation to 1 <= 1Cut

movieCmb (cut=0.5, levels=12, cm='RdYlBu\_r', png=False, step=1, normed=False, dpi=80, bg-color=None, deminc=True, removeMean=False, precision='Float64', contour=False, mer=False)

Plotting function (it can also write the png files)

### **Parameters**

- levels (int) number of contour levels
- $\mathbf{cm}(str)$  name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))\*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (*int*) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure
- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- precision (char) single or double precision
- contour (bool) also display the solid contour levels when set to True
- mer (bool) display meridians and circles when set to True
- **removeMean** (bool) remove the time-averaged part when set to True

# plot()

Display some results when iplot is set to True

timeLongitude (removeMean=True, lat0=0.0, levels=12, cm='RdYlBu\_r', deminc=True, shtns\_lib='shtns')

Plot the time-longitude diagram of Br (input latitude can be chosen)

Warning: the python bindings of SHTns are mandatory to use this plotting function!

- lat0 (float) value of the latitude
- **levels** (*int*) number of contour levels
- $\mathbf{cm}(str)$  name of the colormap
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **shtns\_lib** (*char*) version of shtns library used: can be either 'shtns' or 'shtns-magic'

• **removeMean** (bool) – remove the time-averaged part when set to True

truncate (lCut)

**Parameters 1Cut** (*int*) – truncate to spherical harmonic degree lCut

This class allows to read the  $B\_coeff\_r\#.TAG$  and  $V\_coeff\_r\#.TAG$  files. It reads the poloidal and toroidal potentials and reconstruct the time series (or the energy) contained in any given mode.

```
>>> # Reads the files V_coeff_r2.test*
>>> cr = MagicCoeffR(tag='test*', field='V', r=2)
>>> print(cr.ell, cr.wlm) # print \ell and w_{\ell m}
>>> # Time-evolution of the poloidal energy in the (\ell=10, m=10) mode
>>> plot(cr.time, cr.epolLM[:, cr.idx[10, 10]])
```

\_\_init\_\_ (tag, ratio\_cmb\_surface=1, scale\_b=1, iplot=True, field='B', r=1, precision='Float64', lCut=None, quiet=False)

#### **Parameters**

- tag(str) if you specify a pattern, it tries to read the corresponding files
- ratio\_cmb\_surface (float) ratio of surface ratio to CMB radius (default is 1)
- scale\_b (float) magnetic field unit (default is 1)
- **iplot** (bool) a logical to toggle the plot (default is True)
- **field** (str) 'B', 'V' or 'T' (magnetic field, velocity field or temperature)
- r (int) an integer to characterise which file we want to plot
- **precision** (str) single or double precision
- **1Cut** (*int*) reduce the spherical harmonic truncation to l <= lCut
- quiet (bool) verbose when toggled to True (default is True)

fft()

Fourier transform of the poloidal energy

movieRad (cut=0.5, levels=12, cm='RdYlBu\_r', png=False, step=1, normed=False, dpi=80, bg-color=None, deminc=True, removeMean=False, precision='Float64', contour=False, mer=False)

Plotting function (it can also write the png files)

**Warning:** the python bindings of SHTns are mandatory to use this plotting function!

- levels (int) number of contour levels
- cm (str) name of the colormap
- cut (float) adjust the contour extrema to max(abs(data))\*cut
- png (bool) save the movie as a series of png files when set to True
- **dpi** (*int*) dot per inch when saving PNGs
- **bgcolor** (str) background color of the figure

- **normed** (bool) the colormap is rescaled every timestep when set to True, otherwise it is calculated from the global extrema
- **step** (*int*) the stepping between two timesteps
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- precision (char) single or double precision
- contour (bool) also display the solid contour levels when set to True
- mer (bool) display meridians and circles when set to True
- **removeMean** (bool) remove the time-averaged part when set to True

truncate (lCut, field='B')

### **Parameters**

- 1Cut (int) truncate to spherical harmonic degree lCut
- **field** (char) name of the field ('V', 'B' or 'T')

magic.coeff.deriv(x, y, axis=0)

This function is a simple second order derivative

#### **Parameters**

- x (numpy.ndarray) input x-axis
- y (numpy.ndarray) input array

**Returns** an array that contains the derivatives

Return type numpy.ndarray

magic.coeff.getGauss(alm, blm, ell, m, scale\_b, ratio\_cmb\_surface, rcmb)

Get the Gauss coefficients from the real and imaginary parts of the poloidal potential

### **Parameters**

- alm (numpy.ndarray) real part of the poloidal potential
- blm (numpy.ndarray) imaginary part of the poloidal potential
- **ell** (numpy.ndarray) spherical harmonic degree ell
- **scale\_b** (float) magnetic field unit (default is 1)
- ratio\_cmb\_surface (float) ratio of surface ratio to CMB radius (default is 1)
- rcmb (float) radius of the outer boundary

magic.coeff.rearangeLat (field)

This function is used to unfold the colatitudes

**Parameters field** (numpy.ndarray) – input array with MagIC ordering of colatitudes (i.e. successively Northern Hemisphere and Southern Hemisphere)

**Returns** an array with the regular ordering of the colatitudes

Return type numpy.ndarray

# 9.3.10 Support for B[rp]Spec.TAG

class magic.MagicRSpec (tag, field='Br', precision='Float32', avg=False)

This class allows to read the rB[r|p]Spec.TAG files. Those files contain the time-evolution of the poloidal/toroidal magnetic energy for all radii and for spherical harmonic degrees from 1 to 6. This is an unformatted fortran file.

```
>>> # Read all the `BrSpec.test*` files in the current working directory and
>>> # stack them.
>>> rsp = MagicRSpec(tag='test*', field='Br')
```

```
__init__ (tag, field='Br', precision='Float32', avg=False)
```

#### **Parameters**

- tag (str) if you specify a pattern, it tries to read the corresponding files and stack them
- **field** (str) nature of the radial spectra. Possible choices are 'Bt' or 'Bp'
- **precision** (str) single or double precision (default single, i.e. 'Float32')
- avg (bool) when set to True, display time averaged quantities

### plotAvg()

Plotting function for time-averaged profiles

# 9.3.11 Support for [V|B|T] lmr #.TAG

```
class magic.MagicPotential (field='V', datadir='.', tag=None, ave=False, ipot=None, preci-
sion='Float32')
```

This class allows to load and display the content of the potential files:  $V_{lmr.TAG}$ ,  $B_{lmr.TAG}$  and  $T_{lmr.TAG}$ . This class allows to transform the poloidal/toroidal potential in spectral space to the physical quantities in the physical space. It allows to plot radial and equatorial cuts as well as phi-averages.

```
>>> # To read T_lmr.test
>>> p = MagicPotential(field='T', ipot=1, tag='test')
>>> # To read the latest V_lmr file in the working directory
>>> p = MagicPotential(field='V')
>>> # Get the poloidal potential (lm, nR)
>>> wlm = p.pol
>>> # Obtain the value of w(l=12, m=12, nR=33)
>>> print( p.pol[p.idx[12,12], 32] )
```

```
>>> # Possible plots
>>> p.equat(field='vr')
>>> p.avg(field='vp')
>>> p.surf(field='vt', r=0.8)
```

\_\_init\_\_ (field='V', datadir='.', tag=None, ave=False, ipot=None, precision='Float32')

- **field** (str) 'B', 'V' or 'T' (magnetic field, velocity field or temperature)
- datadir (str) the working directory
- tag(str) if you specify a pattern, it tries to read the corresponding files
- **ave** (bool) plot a time-averaged spectrum when set to True

- ipot (int) the number of the lmr file you want to plot
- **precision** (str) single or double precision

Plot the azimutal average of a given field.

```
>>> p = MagicPotential(field='V')
>>> # Axisymmetric zonal flows, 65 contour levels
>>> p.avg(field='vp', levels=65, cm='seismic')
```

```
>>> # Minimal plot (no cbar, not title)
>>> p.avg(field='vr', tit=False, cbar=False)
```

#### **Parameters**

- **field** (str) the field you want to display
- **levels** (*int*) the number of levels in the contourf plot
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

equat (field='vr', levels=65, cm='seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, normRad=False)
Plot the equatorial cut of a given field

```
>>> p = MagicPotential(field='B')
>>> # Equatorial cut of the Br
>>> p.equat(field='Br')
```

```
>>> # Normalise the contour levels radius by radius
>>> p.equat(field='Bphi', normRad=True)
```

- **field** (str) the name of the input physical quantity you want to display
- normRad (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- **tit** (bool) display the title of the figure when set to True
- cbar(bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels

• **normed** (bool) – when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

```
>>> p = MagicPotential(field='V')
>>> # Radial flow component at ``r=0.95 r_o``, 65 contour levels
>>> p.surf(field='vr', r=0.95, levels=65, cm='seismic')
```

```
>>> # Control the limit of the colormap from -1e3 to 1e3
>>> p.surf(field='vp', r=1., vmin=-1e3, vmax=1e3, levels=33)
```

#### **Parameters**

- **field** (str) the name of the field you want to display
- proj (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- lon\_0 (float) central azimuth (only used with Basemap)
- lat\_0 (float) central latitude (only used with Basemap)
- **r** (float) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- lines (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero.

# 9.3.12 Support for TO outputs

class magic.TOMovie (file=None, iplot=True, cm='RdYlBu\_r', cut=0.8, levels=16, avg=True, precision='Float32')

This class allows to read and display the TO mov. TAG generated when l TOmovie=.true. is True.

```
>>> # This will allow you to pick up one TO_mov files among the existing ones
>>> t = TOMovie()
```

```
>>> # Read TO_mov.NOm2, time-averaged it and display it with 65 contour levels
>>> t = TOMovie(file='TO_mov.N0m2', avg=True, levels=65, cm='seismic')
```

\_\_init\_\_ (file=None, iplot=True, cm='RdYlBu\_r', cut=0.8, levels=16, avg=True, precision='Float32')

### **Parameters**

- **file** (*str*) the filename of the TO\_mov file
- **cmap** (str) the name of the color map
- **levels** (*int*) the number of contour levels
- **cut** (float) adjust the contour extrema to max(abs(data))\*cut
- iplot (bool) a boolean to specify if one wants to plot or not the results
- avg (bool) time average of the different forces
- **precision** (*str*) precision of the input file, Float32 for single precision, Float64 for double precision

```
plot (cut=0.8, levs=16, avg=True, cmap='RdYlBu_r')
    Plotting function
```

### **Parameters**

- cut (float) adjust the contour extrema to max(abs(data))\*cut
- **levs** (*int*) number of contour levels
- avg (bool) when set to True, quantities are time-averaged
- cmap(str) name of the colormap

**class** magic. **MagicTOZ** (*datadir='.'*, *itoz=None*, *tag=None*, *precision='Float32'*, *ave=False*)

This class can be used to read the TOZ.TAG files produced by the TO outputs

```
>>> # read the content of TOZ_1.tag
>>> # where tag is the most recent file in the current directory
>>> toz = MagicTOZ(itoz=1)
>>> # read the content of TOZ_ave.test
>>> toz = MagicTOZ(tag='test', ave=True)
```

```
__init__ (datadir='.', itoz=None, tag=None, precision='Float32', ave=False)
```

## **Parameters**

- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **precision** (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)
- ave (bool) plot a time-averaged TOZ file when set to True
- itoz (int) the number of the TOZ file you want to plot

**class** magic.MagicTOHemi (datadir='.', hemi='n', tag=None, precision='Float32', iplot=False)

This class can be used to read and display z-integrated quantities produced by the TO outputs. Those are basically the TO[sln]hn.TAG files

```
>>> to = MagicTOHemi(hemi='n', iplot=True) # For the Northern hemisphere
```

```
__init__ (datadir='.', hemi='n', tag=None, precision='Float32', iplot=False)
```

#### **Parameters**

• datadir (str) - current working directory

- hemi (str) Northern or Southern hemisphere ('n' or 's')
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- precision (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)

plot()

Plotting function

class magic.MagicTaySphere (datadir='.', tag=None, precision='Float32', iplot=False)

This class can be used to read and display quantities produced by the TO outputs. Those are basically the TaySphere.TAG files

```
>>> to = MagicTaySphere(iplot=True) # For the Northern hemisphere
>>> print(to.time, to.e_kin)
```

**\_\_init\_\_** (datadir='.', tag=None, precision='Float32', iplot=False)

#### **Parameters**

- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **precision** (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)

plot()

Plotting function

class magic.MagicPV (field='PVZ', datadir='.', tag=None, precision='Float32', iplot=False)

This class can be used to read and display quantities produced by the PV outputs. Those are basically the PVZ.TAG and the Vcy.TAG files

```
>>> # To plot the content of PVZ.test
>>> pv = MagicPV(field='PVZ', tag='test', iplot=True)
```

\_\_init\_\_ (field='PVZ', datadir='.', tag=None, precision='Float32', iplot=False)

# **Parameters**

- **field** (str) file prefix (either 'Vcy' or 'PVZ')
- datadir (str) current working directory
- tag (str) file suffix (tag), if not specified the most recent one in the current directory is chosen
- **precision** (str) single or double precision
- **iplot** (bool) display the output plot when set to True (default is True)

plot (field)

Plotting routine

**Parameters field** (str) – file prefix (either 'Vcy' or 'PVZ')

# 9.3.13 Run comparison

```
class magic.CompSims (file='liste', field='ts', ncol=4, cm='RdYlBu_r', dpi=96, normed=True, levels=16, type=None, r=0.9, bw=False, ave=False, cut=1)
```

This class allows to compare an analyse several DNS simultaneously. It is possible to compare time-series or *graphic files*. To set it up, you first need to create a file that contains the list of directories you want to analyse:

```
$ cat inputList
E3e4Eps5e3Q05
E3e4Eps2e3Q07
E3e4Eps2e3Q08
E3e4Eps2e3Q09
```

This list thus contains four directories (one run per directory) that can be further analysed:

```
>>> # Display the time-series of kinetic energy on 2 columns
>>> CompSims(file='inputList', field='ts', ncol=2)
>>> # Display the equatorial cuts of v_r
>>> CompSims(file='inputList', field='vr', type='equat', levels=65, cm='seismic')
>>> # Display the radial cuts of B_r at r=0.8 r_o
>>> CompSims(file='inputList', field='br', type='surf', r=0.8)
>>> # Display the average zonal flow
>>> CompSims(file='inputList', field='vp', type='avg')
```

\_\_init\_\_ (file='liste', field='ts', ncol=4, cm='RdYlBu\_r', dpi=96, normed=True, levels=16, type=None, r=0.9, bw=False, ave=False, cut=1)

#### **Parameters**

- **file** (str) the input file that contains the list of directories that one wants to analyse
- **field** (str) name of the input field. Possible options are: 'ts': displaye the time-series of kinetic energy; 'e\_mag': display the time-series of magnetic energy; 'flux': display the time-series of the Nusselt numbers; 'zonal': display the surface zonal flow; 'Anything else': try to interpret the field
- **type** (str) nature of the plot. Possible values are: 'avg' or 'slice': phi-average or phi-slice; 'equat': equatorial cut; 'surf': radial cut; 'ts\*: time series
- ncol (int) number of columns of the figure
- ave (bool) when set to True, it tries to read a time-averaged graphic file
- **r** (*float*) the radius at which you want to display the input data (in normalised units with the radius of the outer boundary)
- **levels** (*int*) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- **dpi** (*int*) dot per inch when saving PNGs
- **bw** (bool) when set to True, display grey-scaled contour levels
- **cut** (float) adjust the contour extrema to max(abs(data))\*cut

# plotAvg()

Plot azimutal averages in (theta, r) planes.

```
plotEmag()
    Plot time-series of the magnetic energy

plotEquat()
    Plot equatorial cuts in (phi, r) planes.

plotFlux()
    Plot time-series of the top and bottom Nusselt numbers

plotSurf()
    Plot radial cuts in (phi, theta) planes using the Hammer projection.

plotTs()
    Plot time-series of the kinetic energy

plotZonal()
    Plot surface zonal flow profiles.
```

# 9.3.14 Conversion of G\_#.TAG files to vts/vti files

This class allows to transform an input graphic file to a file format readable by paraview/visit or mayavi. It also allows to compute a possible potential extrapolation of the field lines in an arbitrary outer spherical shell domain

```
>>> # Load a graphic file
>>> gr = MagicGraph(ivar=1)
>>> # store myOut.vts
>>> Graph2Vtk(gr, 'myOut', outType='vts')
>>> # store u' and B for the vector fields and vortz and T for the scalars
>>> Graph2Vtk(gr, scals=['temp', 'vortz'], vecs=['ufluct', 'B'])
>>> # store only T'
>>> Graph2Vtk(gr, scals=['tempfluct'], vecs=[])
>>> # store only B with its potential extrapolation up to 3*r_cmb
>>> Graph2Vtk(gr, scals=[], vecs=['B'], potExtra=True, ratio_out=3)
>>> # Extrapolate on a cartesian grid of size 128^3
>>> Graph2Vtk(gr, outType='vti', nx=128, ny=128, nz=128)
```

\_\_init\_\_(gr, filename='out', scals=['vr', 'emag', 'tfluct'], vecs=['u', 'B'], potExtra=False, ratio\_out=2, nrout=32, deminc=True, outType='vts', nFiles=1, nx=96, ny=96, nz=96, labFrame=False)

- **filename** (str) the file name of the output (without extension)
- gr (magic.MagicGraph) the input graphic file one wants to transform to vts/vti
- **scals** (list (str)) a list that contains the possible input scalars: 'entropy', 'vr', 'vp', 'tfluct', 'vortz', 'vortzfluct', 'ekin', 'emag', 'vortr'
- **vecs** (list(str)) a list that contains the possible input vectors: 'u', 'b', 'ufluct', 'bfluct'
- **potExtra** (bool) when set to True, calculates the potential extrapolation of the magnetic field up to ratio out\*r cmb
- ratio\_out (float) in case of potential extrapolation, this is the ratio of the external outer radius to r\_cmb (rout/rcmb)

- **nrout** (*integer*) in case of potential extrapolation, this input allows to specify thenumber of radial grid points in the outer spherical envelope
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry
- **outType** (str) nature of the VTK file produced. This can be either 'vts' for the spherical grid or 'vti' for an extrapolation on a cartesian grid
- nFiles (int) number of output chunks in case of parallel vts file format (pvts)
- $\mathbf{nx}(int)$  number of grid points in the x direction
- ny (int) number of grid points in the x direction
- **nz** (*int*) number of grid points in the x direction
- labFrame  $(b \circ o 1)$  when set to True, transform the velocity to the lab frame

**writeVTI** (*filename*, *nx*=96, *ny*=96, *nz*=96)

In this case, the output is extrapolated on a cartesian grid and then written in a vti file.

#### **Parameters**

- **filename** (str) the file name of the output (without extension)
- **nx** (*int*) number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- nz (int) number of grid points in the x direction

writeVTS (filename, nFiles)

This function stores the output on a structured-grid vts file.

## **Parameters**

- **filename** (str) the file name of the output (without extension)
- **nFiles** (*int*) number of outpute files (in case of pvts)

magic.graph2vtk.sph2cart\_scal (scals, radius, nx=96, ny=96, nz=96, minc=1)

This function interpolates a series of scalar fields from the spherical coordinates to the cartesian coordinates.

## **Parameters**

- scals (numpy.ndarray[nscals, nphi, ntheta, nr]) an array that contains the different scalar quantities
- radius (numpy.ndarray) the input radius
- nx (int) number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- **nz** (*int*) number of grid points in the x direction
- minc (int) azimuthal symmetry

**Returns** a tuple that contains the scalars, the max of the grid and the grid spacing

**Return type** (numpy.ndarray[nscals,nz,ny,nx],float,float)

magic.graph2vtk.sph2cart\_vec (vecr, vect, vecp, radius, nx=96, ny=96, nz=96, minc=1)

This function interpolates a series of vector fields from the spherical coordinates to the cartesian coordinates.

- vecr (numpy.ndarray[nvecs, nphi, ntheta, nr]) the radial components of the different vector fields
- vect (numpy.ndarray[nvecs, nphi, ntheta, nr]) the latitudinal components of the different vector fields
- **vecp** (numpy.ndarray[nvecs,nphi,ntheta,nr]) the azimuthal components of the different vector fields
- radius (numpy.ndarray) the input radius
- **nx** (*int*) number of grid points in the x direction
- **ny** (*int*) number of grid points in the x direction
- **nz** (*int*) number of grid points in the x direction
- minc (int) azimuthal symmetry

**Returns** a tuple that contains the three vectors components

**Return type** (numpy.ndarray[nvecs,nz,ny,nx],..)

# 9.3.15 Potential extrapolation

deminc=True)
This class is used to compute the potential field extrapolation of the magnetic field in an arbitrary outer spherical shell domain. It takes as an input the magnetic field at the CMB.

\_\_init\_\_ (rcmb, brcmb, minc, ratio\_out=2.0, nrout=32, cutCMB=False, deminc=True)

#### **Parameters**

- bcmb (numpy.ndarary) the surface radial field, array of dimension [np, nt]
- rcmb (float) the value of the radius at the surface
- minc (int) azimuthal symmetry
- ratio\_out (float) the ratio of the outer sphere radius to the surface radius
- **nrout** (*int*) the number of radial point (linearly spaced) of the extrapolated field in the outer spherical domain
- **cutCMB** (bool) a logical if one wants to remove the first grid point (useful if one then wants to merge the graphic file with the extrapolation)
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

avg (field='br', levels=12, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None)
A small routine to plot the azimuthal averages of the extrapolated fields.

- **field** (str) the quantity you want to plot: 'br' or 'bp'
- **levels** (*int*) the number of contour levels
- $\mathbf{cm}(str)$  the name of the colormap
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels

• **normed** (bool) – when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

# 9.3.16 Additional possible analyses

```
class magic.bLayers.BLayers(iplot=False, quiet=False)
```

This class allows to determine the viscous and thermal boundary layers using several classical methods (slope method, peak values, dissipation rates, etc.). It uses the following files:

- Kinetic energy: eKinR.TAG
- Power budget: powerR.TAG
- Radial profiles used for boundary layers: bLayersR.TAG

This function can thus **only** be used when both *powerR.TAG* and *bLayersR.TAG* exist in the working directory.

**Warning:** This function works well as long as rigid boundaries and fixed temperature boundary conditions are employed. Other combination of boundary conditions (fixed fluxes and/or stress-free) might give wrong results, since boundary layers become awkward to define in that case.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using AvgField: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvg file exists, the boundary layer calculation can be done:

```
>>> bl = BLayers(iplot=True)
>>> # print the formatted output
>>> print(bl)
```

\_\_\_init\_\_\_(iplot=False, quiet=False)

## **Parameters**

- **iplot** (bool) display the result when set to True (default False)
- quiet (bool) less verbose when set to True (default is False)

```
__str__()
```

Formatted output

plot()

Plotting function

```
magic.bLayers.getAccuratePeaks(rad, uh, uhTop, uhBot, ri, ro)
```

This functions performs a spline extrapolation around the maxima of the input array uh to define a more accurate location of the boundary layer.

- rad (numpy.ndarray) radius
- **uh** (numpy.ndarray) the horizontal velocity profile
- **uhTop** (float) first peak value of uh close to the outer boundary
- **uhBot** (float) first peak value of uh close to the inner boundary

- ri (float) the inner core radius
- **ro** (*float*) the outer core radius

**Returns** four floats: thickness of the bottom boundary layer, thickness of the top boundary layer, extrapolated value of uh at the bottom boundary layer, extrapolated value of uh at the top boundary layer

# Return type list

# magic.bLayers.getMaxima(field)

This function determines the local maxima of the input array field

Parameters field (numpy.ndarray) - the input array

Returns a list containing the indices of the local maxima

## Return type list

magic.bLayers.integBotTop(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the bottom and top boundary layers separately.

#### **Parameters**

- rad (numpy.ndarray) radius
- field (numpy.ndarray) the input radial profile
- ri (float) the inner core radius
- ro (float) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer
- **normed** (bool) when set to True, the outputs are normalised by the volumes of the boundary layers. In that case, the outputs are volume-averaged quantities.

**Returns** two floats that contains the bottom and top boundary layers integrations (integBot, integTop)

## Return type list

magic.bLayers.integBulkBc(rad, field, ri, ro, lambdai, lambdao, normed=False)

This function evaluates the radial integral of the input array field in the boundary layer and in the bulk separately.

#### **Parameters**

- rad (numpy.ndarray) radius
- **field** (numpy.ndarray) the input radial profile
- ri (float) the inner core radius
- ro (float) the outer core radius
- lambdai (float) thickness of the inner boundary layer
- lambdao (float) thickness of the outer boundary layer
- **normed** (bool) when set to True, the outputs are normalised by the volumes of the boundary layers and the fluid bulk, respectively. In that case, the outputs are volume-averaged quantities.

**Returns** two floats that contains the boundary layer and the bulk integrations (integBc, integBulk)

## Return type list

```
class magic.ThetaHeat (iplot=False, angle=10, pickleName='thHeat.pickle')
```

This class allows to conduct some analysis of the latitudinal variation of the heat transfer. It relies on the movie files *ATmov.TAG* and *AHF\_mov.TAG*. As it's a bit time-consuming, the calculations are stored in a python.pickle file to quicken future usage of the data.

This function can **only** be used when *bLayersR.TAG* exist in the working directory.

Since this function is supposed to use time-averaged quantities, the usual procedure is first to define the initial averaging time using AvgField: (this needs to be done only once)

```
>>> a = AvgField(tstart=2.58)
```

Once the tInitAvg file exists, the latitudinal heat transfer analysis can be done using:

```
>>> # For chunk-averages over 10^\degree in the polar and equatorial regions.
>>> th = ThetaHeat(angle=10)
>>> # Formatted output
>>> print(th)
```

```
__init__ (iplot=False, angle=10, pickleName='thHeat.pickle')
```

### **Parameters**

- iplot (bool) a boolean to toggle the plots on/off
- angle (float) the integration angle in degrees

PickleName calculations a

```
str ()
```

Formatted outputs

```
>>> th = ThetaHeat()
>>> print(th)
```

```
plot()
```

Plotting function

```
class magic.cyl.Cyl(ivar=1, datadir='.', ns=None)
```

This class allows to extrapolate a given *graphic file* on a cylindrical grid. Once done, the extrapolated file is stored in a python.pickle file. It is then possible to display 2-D cuts of the extrapolated arrays (radial cuts, phi-averages, equatorial cuts, z-averages and phi-slices)

**Warning:** This process is actually **very demanding** and it might take a lot of time to extrapolate the G\_#.TAG file. Be careful when choosing the input value of ns!

```
>>> # Extrapolate the G file to the cylindrical grid (ns=128, nz=2*ns)
>>> c = Cyl(ivar=1, ns=128)
>>> # Radial cut of v_r
>>> c.surf(field='vr', r=0.8)
>>> # Vertical average of B_\phi
>>> c.avgz(field='Bphi', cm='seismic', levels=33)
>>> # Azimuthal average of v_\phi
>>> c.avg(field='Bphi')
>>> c.avg(field='Bphi')
>>> # Equatorial cut of of v_theta
>>> c.equat(field='vtheta')
```

```
___init___(ivar=1, datadir='.', ns=None)
```

#### **Parameters**

- ivar (int) the number of the Graphic file
- datadir (str) working directory
- **ns** (*int*) number of grid points in the radial direction

avg (field='Bphi', levels=16, cm='RdYlBu\_r', normed=True, vmax=None, vmin=None)
Plot the azimutal average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Azimuthal average of B_r
>>> c.avg(field='Br', cm='seismic', levels=33)
```

#### **Parameters**

- **field** (str) name of the input field
- **levels** (*int*) number of contour levels
- cm (str) name of the color map
- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- **vmax** (float) truncate the contour levels to values < vmax

avgz (field='vs', levels=16, cm='RdYlBu\_r', normed=True, vmin=None, vmax=None, avg=False)
Plot the vertical average of a given field.

```
>>> c = Cyl(ns=65)
>>> # Vertical average of v_s
>>> c.avg(field='vs', cm='seismic', levels=33)
```

#### **Parameters**

- **field** (str) name of the input field
- levels (int) number of contour levels
- cm(str) name of the color map
- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- vmin (float) truncate the contour levels to values > vmin
- **vmax** (float) truncate the contour levels to values < vmax
- avg (bool) when set to True, an additional figure with the phi-average profile is also displayed

**equat** (*field='vs'*, *levels=16*, *cm='RdYlBu\_r'*, *normed=True*, *vmax=None*, *vmin=None*) Plot an input field in the equatorial plane.

```
>>> c = Cyl(ns=65)
>>> # Equatorial cut of v_\phi
>>> c.equat(field='vphi', cm='seismic', levels=33)
```

### **Parameters**

- **field** (str) name of the input field
- levels (int) number of contour levels
- cm(str) name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- vmax (float) truncate the contour levels to values < vmax

**slice** (*field='Bphi'*, *lon\_0=0.0*, *levels=16*, *cm='RdYlBu\_r'*, *normed=True*) Plot an azimuthal slice of a given field.

```
>>> c = Cyl(ns=65)
>>> # Slices of v_r at 30 and 60 degrees
>>> c.slice(field='vr', lon_0=[30, 60])
```

#### **Parameters**

- **field** (str) name of the input field
- lon\_0 (float or list) the longitude of the slice in degrees, or a list of longitudes
- **levels** (*int*) number of contour levels
- cm(str) name of the color map
- normed (bool) when set to True, the contours are normalised fro -max(field), max(field)

surf (field='Bphi', r=0.85, vmin=None, vmax=None, levels=16, cm='RdYlBu\_r', normed=True, figsize=None)

Plot the surface distribution of an input field at a given input radius (normalised by the outer boundary radius).

```
>>> c = Cyl(ns=65)
>>> # Surface plot of B_\phi from -10 to 10
>>> c.surf(field='Bphi', r=0.6, vmin=-10, vmax=10, levels=65)
```

- **field** (str) name of the input field
- **r** (float) radial level (normalised to the outer boundary radius)
- **levels** (*int*) number of contour levels
- cm(str) name of the color map
- **normed** (bool) when set to True, the contours are normalised fro -max(field), max(field)
- **vmin** (float) truncate the contour levels to values > vmin
- **vmax** (*float*) truncate the contour levels to values < vmax

```
magic.cyl.sph2cyl(g, ns=None, nz=None)
```

This function interpolates the three flow (or magnetic field) component of a  $G_{\#}.TAG$  file on a cylindrical grid of size (ns, nz).

Warning: This might be really slow!

#### **Parameters**

- g (magic.MagicGraph) input graphic output file
- **ns** (int) number of grid points in the radial direction
- nz (int) number of grid points in the vertical direction

**Returns** a python tuple of five numpy.ndarray (S,Z,vs,vp\_cyl,vz). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. vs[nz,ns] is the radial component of the velocity (or magnetic field), vp\_cyl[nz,ns] the azimuthal component and vz[nz,ns] the vertical component.

Return type tuple

# magic.cyl.sph2cyl\_plane(data, rad, ns, nz)

This function extrapolates a phi-slice of a spherical shell on a cylindrical grid

```
>>> # Read G_1.test
>>> gr = MagicGraph(ivar=1, tag='test')
>>> # phi-average v_\phi and s
>>> vpm = gr.vphi.mean(axis=0)
>>> sm = gr.entropy.mean(axis=0)
>>> # Interpolate on a cylindrical grid
>>> Z, S, outputs = sph2cyl_plane([vpm, sm], gr.radius, 512, 1024)
>>> vpm_cyl, sm_cyl = outputs
```

## **Parameters**

- data (list (numpy.ndarray)) a list of 2-D arrays [(ntheta, nr), (ntheta, nr), ...]
- rad (numpy.ndarray) radius
- **ns** (*int*) number of grid points in s direction
- **nz** (*int*) number of grid points in z direction

**Returns** a python tuple that contains two numpy.ndarray and a list (S,Z,output). S[nz,ns] is a meshgrid that contains the radial coordinate. Z[nz,ns] is a meshgrid that contains the vertical coordinate. output=[arr1[nz,ns], ..., arrN[nz,ns]] is a list of the interpolated array on the cylindrical grid.

## Return type tuple

magic.cyl.zavg(input, radius, ns, minc, save=True, filename='vp.pickle', normed=True)

This function computes a z-integration of a list of input arrays (on the spherical grid). This works well for 2-D (phi-slice) arrays. In case of 3-D arrays, only one element is allowed (too demanding otherwise).

- input (list (numpy.ndarray)) a list of 2-D or 3-D arrays
- radius (numpy.ndarray) spherical radius

- **ns** (*int*) radial resolution of the cylindrical grid (nz=2\*ns)
- minc (int) azimuthal symmetry
- **save** (bool) a boolean to specify if one wants to save the outputs into a pickle (default is True)
- **filename** (str) name of the output pickle when save=True
- normed (bool) a boolean to specify if ones wants to simply integrate over z or compute a z-average (default is True: average)

**Returns** a python tuple that contains two numpy.ndarray and a list (height,cylRad,output) height[ns] is the height of the spherical shell for all radii. cylRad[ns] is the cylindrical radius. output=[arr1[ns],..., arrN[ns]] contains the z-integrated output arrays.

## Return type tuple

This class can be used to display the time evolution of the magnetic field for various latitudes (i.e. the well-known butterfly diagrams). These diagrams are usually constructed using MagIC's *movie files*: either radial cuts (like Br\_CMB\_mov.TAG) or azimuthal-average (like AB\_mov.TAG).

## \_\_\_add\_\_\_(new)

Overload of the addition operator

```
>>> # Read 2 files
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> b2 = Butterfly(file='AB_mov.test2', iplot=False)
>>> # Stack them and display the whole thing
>>> b = b1+b2
>>> b.plot(levels=33, contour=True, cut=0.8, cm='seismic')
```

\_\_init\_\_(file=None, step=1, iplot=True, rad=0.8, lastvar=None, nvar='all', levels=20, cm='RdYlBu\_r', precision='Float32', cut=0.8)

- **file** (str) when specified, the constructor reads this file, otherwise a list with the possible options is displayed
- rad (float) radial level (normalised to the outer boundary radius)
- **iplot** (bool) display/hide the plots (default is True)
- **nvar** (*int*) the number of time steps (lines) of the movie file we want to plot starting from the last line
- lastvar (int) the number of the last time step to be read
- **step** (*int*) the stepping between two lines
- **levels** (*int*) the number of contour levels
- $\mathbf{cm}(str)$  the name of the color map
- **cut** (float) adjust the contour extrema to max(abs(data))\*cut

• **precision** (bool) – precision of the input file, Float32 for single precision, Float64 for double precision

### fourier2D (renorm=False)

This function allows to conduct some basic Fourier analysis on the data. It displays two figures: the first one is a contour levels in the (Frequency, Latitude) plane, the second one is integrated over latitudes (thus a simple, power vs Frequency plot)

```
>>> # Load the data without plotting
>>> b1 = Butterfly(file='AB_mov.test1', iplot=False)
>>> # Fourier analysis
>>> b1.fourier2D()
```

Parameters renorm (bool) – when set to True, it rebins the time series in case of irregularly spaced data

plot (levels=12, contour=False, renorm=False, cut=0.5, mesh=3, cm='RdYlBu\_R')
 Plotting function

#### **Parameters**

- cm (str) name of the colormap
- **levels** (*int*) the number of contour levels (only used when iplot=True and contour=True)
- **contour** (bool) when set to True, display contour levels (pylab.contourf), when set to False, display an image (pylab.imshow)
- renorm (bool) when set to True, it re-bins the time series in case of irregularly time-spaced data
- **mesh** (*int*) when renorm=True, factor of regriding: NewTime = mesh\*OldTime
- cut (float) adjust the contour extrema to max(abs(data))\*cut

# 9.3.17 Spectral tansforms

This python class is used to compute Legendre and Fourier transforms from spectral to physical space. It works in two steps: one first needs to initialize the transform

```
>>> sh = SpectralTransforms( l_max=256, lm_max=33153, n_theta_max=384)
>>> print(Tlm[:, 10].shape) # lm_max (Temperature at ir=10)
>>> T = sh.spec_spat(Tlm) # T[n_phi_max, n_theta_max]
```

## spat\_spec(input)

This subroutine computes a transfrom from spatial representation (n\_phi,n\_theta) to spectral representation (lm\_max). It returns one complex 1-D array (dimension(n\_phi\_max))

```
>>> gr = MagicGraph()
>>> sh = SpectralTransforms(gr.l_max, gr.minc, gr.lm_max, gr.n_theta_max)
>>> vr = gr.vr[:,:,30] # Radius ir=30
>>> vrlm = sh.spat_spec(vr) # vrlm is a complex array (lm_max)
>>> # Caculation of the poloidal potential from vr:
>>> wlm = np.zeros_like(vrlm)
>>> wlm[1:] = vrlm[1:]/(sh.ell[1:]*(sh.ell[1:]+1))*gr.radius[30]**2
```

**Parameters input** (numpy.ndarray) – input array in the physical space (n\_phi,n\_theta)

**Returns** output array in the spectral space (lm\_max)

Return type numpy.ndarray

```
spec_spat (*args, **kwargs)
```

This subroutine computes a transfrom from spectral to spatial for all latitudes. It returns either one or two 2-D arrays (dimension(n\_phi\_max,n\_theta\_max)) depending if only the poloidal or both the poloidal and the toroidal potentials are given as input quantities.

```
>>> print(wlmr.shape) # lm_max
>>> vr = spec_spat_equat(wlmr)
>>> print(vr.shape) # n_phi, n_theta
>>> vt, vp = spec_spat_equat(dwdrlmr, zlmr)
```

## spec\_spat\_dphi (polo)

This routine computes the phi-derivative and the transform from spectral to spatrial spaces. It returns a 2-D array of dimension (n\_phi,n\_theta)

```
>>> p = MagicPotential('V')
>>> vrlm = p.pol*p.ell*(p.ell+1)/p.radius[ir]**2/p.rho0[ir] # vr at r=ir
>>> dvrdp = p.sh.spec_spat_dphi(vrlm) # phi-derivative of vr
```

**Parameters** polo (numpy.ndarray) – the input array(lm\_max) in spectral space

**Returns** the phi derivative in the physical space (n\_phi, n\_theta)

Return type numpy.ndarray

```
spec_spat_dtheta (polo, l_axi=False)
```

This routine computes the theta-derivative and the transform from spectral to spatrial spaces. It returns a 2-D array of dimension (n\_phi,n\_theta)

```
>>> p = MagicPotential('V')
>>> vrlm = p.pol*p.ell*(p.ell+1)/p.radius[ir]**2/p.rho0[ir] # vr at r=ir
>>> dvrdt = p.sh.spec_spat_dtheta(vrlm) # theta-derivative of vr
```

### **Parameters**

- polo (numpy.ndarray) the input array(lm\_max) in spectral space
- **1\_axi** (bool) switch to True, if only the axisymmetric field is needed

**Returns** the theta derivative in the physical space (n\_phi, n\_theta)

Return type numpy.ndarray

```
spec_spat_equat (*args)
```

This subroutine computes a transfrom from spectral to spatial at the equator. It returns either one or two 1-D arrays (dimension(n\_phi\_max)) depending if only the poloidal or both the poloidal and the toroidal potentials are given as input quantities.

```
>>> print(wlmr.shape) # lm_max
>>> vr = spec_spat_equat(wlmr)
>>> print(vr.shape) # n_phi
>>> vt, vp = spec_spat_equat(dwdrlmr, zlmr)
```

# 9.3.18 Plotting functions

magic.plotlib.cut (dat, vmax=None, vmin=None)

This functions truncates the values of an input array that are beyond vmax or below vmin and replace them by vmax and vmin, respectively.

```
>>> # Keep only values between -1e3 and 1e3
>>> datNew = cut(dat, vmin=-1e3, vmax=1e3)
```

#### **Parameters**

- dat (numpy.ndarray) an input array
- vmax (float) maximum upper bound
- vmin (float) minimum lower bound

**Returns** an array where the values >=vmax have been replaced by vmax and the values <=vmin have been replaced by vmin

Return type numpy.ndarray

magic.plotlib.equatContour(data, radius, minc=1, label=None, levels=65, cm='seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True, norm-Rad=False.deminc=True)

Plot the equatorial cut of a given field

#### **Parameters**

- data (numpy.ndarray) the input data (an array of size (nphi,nr))
- radius (numpy.ndarray) the input radius
- minc (int) azimuthal symmetry
- label (str) the name of the input physical quantity you want to display
- normRad (bool) when set to True, the contour levels are normalised radius by radius (default is False)
- **levels** (int) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.
- **deminc** (bool) a logical to indicate if one wants do get rid of the possible azimuthal symmetry

```
magic.plotlib.hammer2cart (ttheta, pphi, colat=False)
```

This function is used to define the Hammer projection used when plotting surface contours in magic. Surf

```
>>> # Load Graphic file
>>> gr = MagicGraph()
>>> # Meshgrid
>>> pphi, ttheta = mgrid[-np.pi:np.pi:gr.nphi*1j, np.pi/2.:-np.pi/2.:gr.ntheta*1j]
>>> x,y = hammer2cart(ttheta, pphi)
>>> # Contour plots
>>> contourf(x, y, gr.vphi)
```

#### **Parameters**

- ttheta (numpy.ndarray) meshgrid [nphi, ntheta] for the latitudinal direction
- pphi meshgrid [nphi, ntheta] for the azimuthal direction
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** a tuple that contains two [nphi, ntheta] arrays: the x, y meshgrid used in contour plots **Return type** (numpy.ndarray, numpy.ndarray)

magic.plotlib.merContour(data, radius, label=None, levels=65, cm='seismic', normed=True, vmax=None, vmin=None, cbar=True, tit=True)

Plot a meridional cut of a given field

#### **Parameters**

- data (numpy.ndarray) the input data (an array of size (ntheta,nr))
- radius (numpy.ndarray) the input radius
- label (str) the name of the input physical quantity you want to display
- levels (int) the number of levels in the contour
- cm (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)
- tit (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **vmax** (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

```
magic.plotlib.radialContour(data, rad=0.85, label=None, proj='hammer', lon_0=0.0, vmax=None, vmin=None, lat_0=30.0, levels=65, cm='seismic', normed=True, cbar=True, tit=True, lines=False)
```

Plot the radial cut of a given field

- data (numpy.ndarray) the input data (an array of size (nphi,ntheta))
- rad (float) the value of the selected radius
- label (str) the name of the input physical quantity you want to display
- **proj** (str) the type of projection. Default is Hammer, in case you want to use 'ortho' or 'moll', then Basemap is required.
- **levels** (*int*) the number of levels in the contour
- $\mathbf{cm}$  (str) name of the colormap ('jet', 'seismic', 'RdYlBu\_r', etc.)

- **tit** (bool) display the title of the figure when set to True
- cbar (bool) display the colorbar when set to True
- **lines** (bool) when set to True, over-plot solid lines to highlight the limits between two adjacent contour levels
- vmax (float) maximum value of the contour levels
- **vmin** (float) minimum value of the contour levels
- **normed** (bool) when set to True, the colormap is centered around zero. Default is True, except for entropy/temperature plots.

# 9.3.19 Various useful functions

magic.libmagic.anelprof (radius, strat, polind, g0=0.0, g1=0.0, g2=1.0)

This functions calculates the reference temperature and density profiles of an anelastic model.

```
>>> rad = chebgrid(65, 1.5, 2.5)
>>> temp, rho, beta = anelprof(rad, strat=5., polind=2.)
```

### **Parameters**

- radius (numpy.ndarray) the radial gridpoints
- **polind** (float) the polytropic index
- **strat** (*float*) the number of the density scale heights between the inner and the outer boundary
- **g0** (float) gravity profile: g=g0
- **g1** (float) gravity profile: g=g1\*r/r\_o
- **g2** (float) gravity profile: g=g2\*(r\_o/r)\*\*2

**Returns** a tuple that contains the temperature profile, the density profile and the log-derivative of the density profile versus radius

**Return type** (numpy.ndarray, numpy.ndarray, numpy.ndarray)

magic.libmagic.avgField(time, field, tstart=None, std=False)

This subroutine computes the time-average (and the std) of a time series

```
>>> ts = MagicTs(field='misc', iplot=False, all=True)
>>> nuavg = avgField(ts.time, ts.topnuss, 0.35)
>>> print(nuavg)
```

# **Parameters**

- time (numpy.ndarray) time
- field (numpy.ndarray) the time series of a given field
- tstart (float) the starting time of the averaging
- std (bool) when set to True, the standard deviation is also calculated

**Returns** the time-averaged quantity

**Return type** float

```
magic.libmagic.chebgrid (nr, a, b)
```

This function defines a Gauss-Lobatto grid from a to b.

```
>>> r_icb = 0.5; r_cmb = 1.5; n_r_max=65
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
```

### **Parameters**

- nr (int) number of radial grid points
- a (float) lower limit of the Gauss-Lobatto grid
- **b** (float) upper limit of the Gauss-Lobatto grid

Returns the Gauss-Lobatto grid

Return type numpy.ndarray

```
magic.libmagic.cylSder(radius, data, order=4)
```

This function computes the s derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> s = linspace(0., 1., 129; dat = cos(s)
>>> ddatds = cylSder(s, dat)
```

#### **Parameters**

- radius (numpy.ndarray) cylindrical radius
- data (numpy.ndarray) input data
- order (int) order of the finite-difference scheme (possible values are 2 or 4)

Returns s derivative

Return type numpy.ndarray

```
magic.libmagic.cylZder(z, data)
```

This function computes the z derivative of an input array defined on a regularly-spaced cylindrical grid.

```
>>> z = linspace(-1., 1., 129; dat = cos(z)
>>> ddatdz = cylZder(z, dat)
```

#### **Parameters**

- z (numpy.ndarray) height of the cylinder
- data (numpy.ndarray) input data

Returns z derivative

Return type numpy.ndarray

magic.libmagic.fast\_read (file, skiplines=0, binary=False, precision='Float64')

This function reads an input ascii table (can read both formatted or unformatted fortran)

```
>>> # Read 'e_kin.test', skip the first 10 lines
>>> data = fast_read('e_kin.test', skiplines=10)
```

#### **Parameters**

• **file** (str) – name of the input file

- **skiplines** (*int*) number of header lines to be skept during reading
- **binary** (bool) when set to True, try to read an unformatted binray Fortran file (default is False)
- **precision** (str) single ('Float32') or double precision ('Float64')

**Returns** an array[nlines, ncols] that contains the data of the ascii file

Return type numpy.ndarray

```
magic.libmagic.getCpuTime (file)
```

This function calculates the CPU time from one given log file

**Parameters file** (file) – the log file you want to analyze

**Returns** the total CPU time

Return type float

```
magic.libmagic.getTotalRunTime()
```

This function calculates the total CPU time of one run directory

Returns the total RUN time

Return type float

```
magic.libmagic.intcheb (f, nr, z1, z2)
```

This function integrates an input function f defined on the Gauss-Lobatto grid.

```
>>> print(intcheb(f, 65, 0.5, 1.5))
```

## **Parameters**

- **f** an input array
- **nr** (*int*) number of radial grid points
- **z1** (float) lower limit of the Gauss-Lobatto grid
- **z2** (float) upper limit of the Gauss-Lobatto grid

**Type** numpy.ndarray

Returns the integrated quantity

Return type float

```
magic.libmagic.matder (nr, z1, z2)
```

This function calculates the derivative in Chebyshev space.

```
>>> r_icb = 0.5; r_cmb = 1.5; n_r_max=65
>>> d1 = matder(n_r_max, r_icb, r_cmb)
>>> # Chebyshev grid and data
>>> rr = chebgrid(n_r_max, r_icb, r_cmb)
>>> f = sin(rr)
>>> # Radial derivative
>>> df = dot(d1, f)
```

- nr (int) number of radial grid points
- **z1** (*float*) lower limit of the Gauss-Lobatto grid

• **z2** (float) – upper limit of the Gauss-Lobatto grid

**Returns** a matrix of dimension (nr,nr) to calculate the derivatives

Return type numpy.ndarray

magic.libmagic.phideravg(data, minc=1, order=4)

phi-derivative of an input array

```
>>> gr = MagicGraph()
>>> dvphidp = phideravg(gr.vphi, minc=gr.minc)
```

#### **Parameters**

- data (numpy.ndarray) input array
- minc (int) azimuthal symmetry
- **order** (*int*) order of the finite-difference scheme (possible values are 2 or 4)

Returns the phi-derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.progressbar(it, prefix=", size=60)
```

Fancy progress-bar for loops

```
for i in progressbar(range(1000000)):
    x = i
```

## **Parameters**

- **prefix** (str) prefix string before progress bar
- size (int) width of the progress bar (in points of xterm width)

magic.libmagic.rderavg(data, eta=0.35, spectral=True, exclude=False)

Radial derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdr = rderavg(gr.vr, eta=gr.radratio)
```

### **Parameters**

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)

**Returns** the radial derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.scanDir(pattern, tfix=None)
```

This function sorts the files which match a given input pattern from the oldest to the most recent one (in the current working directory)

```
>>> dat = scanDir('log.*')
>>> print(log)
```

### **Parameters**

- pattern (str) a classical regexp pattern
- **tfix** (float) in case you want to add only the files that are more recent than a certain date, use tfix (computer 1970 format!!)

**Returns** a list of files that match the input pattern

Return type list

magic.libmagic.sderavg(data, eta=0.35, spectral=True, colat=None, exclude=False) s derivative of an input array

```
>>> gr = MagiGraph()
>>> dvpds = sderavg(gr.vphi, eta=gr.radratio, colat=gr.colatitude)
```

#### **Parameters**

- data (numpy.ndarray) input array
- eta (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** the s derivative of the input array

Return type numpy.ndarray

```
magic.libmagic.selectField(obj, field, labTex=True)
```

This function selects for you which field you want to display. It actually allows to avoid possible variables miss-spelling: i.e. 'Bphi'='bp'='Bp'='bphi'

## **Parameters**

- **obj** (magic.MagicGraph) a graphic output file
- **field** (str) the name of the field one wants to select
- labTex (bool) when set to True, format the labels using LaTeX fonts

Returns a tuple that contains the selected physical field and its label

Return type (numpy.ndarray, str)

magic.libmagic.symmetrize(data, ms, reversed=False)

Symmetrise an array which is defined only with an azimuthal symmetry minc=ms

- data (numpy.ndarray) the input array
- ms (int) the azimuthal symmetry
- reversed (bool) set to True, in case the array is reversed (i.e. n\_phi is the last column)

**Returns** an output array of dimension (data.shape[0]\*ms+1)

**Return type** numpy.ndarray

magic.libmagic.thetaderavg(data, order=4)

Theta-derivative of an input array (finite differences)

```
>>> gr = MagiGraph()
>>> dvtdt = thetaderavg(gr.vtheta)
```

### **Parameters**

- data (numpy.ndarray) input array
- order (int) order of the finite-difference scheme (possible values are 2 or 4)

**Returns** the theta-derivative of the input array

Return type numpy.ndarray

magic.libmagic.writeVpEq(par, tstart)

This function computes the time-averaged surface zonal flow (and Rolc) and format the output

```
>>> # Reads all the par.* files from the current directory
>>> par = MagicTs(field='par', iplot=False, all=True)
>>> # Time-average
>>> st = writeVpEq(par, tstart=2.1)
>>> print(st)
```

## **Parameters**

- par (magic.MagicTs) a MagicTs object containing the par file
- **tstart** (float) the starting time of the averaging

**Returns** a formatted string

Return type str

magic.libmagic.zderavg (*data*, *eta=0.35*, *spectral=True*, *colat=None*, *exclude=False*) z derivative of an input array

```
>>> gr = MagiGraph()
>>> dvrdz = zderavg(gr.vr, eta=gr.radratio, colat=gr.colatitude)
```

# Parameters

- data (numpy.ndarray) input array
- **eta** (float) aspect ratio of the spherical shell
- **spectral** (bool) when set to True use Chebyshev derivatives, otherwise use finite differences (default is True)
- **exclude** (bool) when set to True, exclude the first and last radial grid points and replace them by a spline extrapolation (default is False)
- colat (numpy.ndarray) colatitudes (when not specified a regular grid is assumed)

**Returns** the z derivative of the input array

Return type numpy.ndarray

# DESCRIPTION OF THE FORTRAN MODULES

The following pages contain an exhaustive description of the different variables, subroutines and modules used in MagIC. This documentation is automatically generated from the source code docstrings using the Sphinx extention for the Fortran domain.

### Fortran modules

- 1. For the main program file magic.f90, see here.
- 2. For the core modules that contain most of the global variables, see *here*.
- 3. For the MPI related modules, see *here*.
- 4. For the code initialization and the pre-calculations done in the initial stage of the computation (before the time-stepping loop), see *here* and *there*.
- 5. For the time-stepping loop, see *here*.
- 6. For the calculation of the non-linear terms (in the physical space) and their time-advance, see here.
- 7. For the calculation of the linear terms (in spectral space) and their time-advance, see *here*.
- 8. For the Chebyshev, Fourier and Legendre transforms, see *here*.
- 9. For the computation of the radial derivatives (Chebyshev) and the integration, see *here*.
- 10. For the definition of the blocking, see *here*.
- 11. For the calculation of the standard outputs (time-series, spectra and radial files), see *here*.
- 12. For the calculation of binary outputs (graphic files, movie files, potential and coeff files), see here.
- 13. For the additional calculations of specific outputs (torsional oscillations, RMS force balance, etc.), see here.
- 14. For reading and writing the check points (restart files), see *here*.
- 15. For additional useful functions (string manipulation, etc.), see *here*.

# 10.1 Main program magic.f90

### program magic

A dynamic dynamo model driven by thermal convection in a rotating spherical fluid shell. This version can solve for both Boussinesq and anelastic fluids and non-dimensional variables are used throughout the whole code.

In the Boussinesq limit, the following set of equations is solved:

```
\label{eq:continuous} $``E \{dv/dt + v.grad(v)\} = -grad(p) - 2e_z x v + 1/Pm \ rot(B) x B + RaE/Pr \ g/g_o T dB/dt = rot(v x B) + 1/Pm \ Lapl(B) $$ dT/dt + v.grad(T) = 1/Pr \ Lapl(T) + epsc0 $$ div(v)=0 \ div(B)=0 $``$
```

List of symbols:

v: velocity p: pressure B: magnetic field g: gravity g\_o: reference value at outer radius T: temperature epsc0: rate of internal heating e\_z: unit vector parallel to the rotation axis d/dt: partial time derivative Lapl: Laplace operator

Scaling properties:

nu: kinematic viscosity d: shell width omega: angular frequency alpha: thermal expansion coeff delta\_T: temperature contrast kappa: thermal diffusivity eta: magnetic diffusivity rho: density mu\_o: magnetic permeability

# Scaling:

Length: d time: d^2/nu Velocity: nu/d pressure: rho\*nu\*omega Temperature: delta\_T mag.field: sqrt(rho\*mu o\*eta\*omega)

Non-dimensional numbers:

E: Ekman number  $E = nu*d^2/omega$  Ra: Rayleigh number  $Ra = alpha*g_o*delta_T*d^3/(kappa*nu)$  Pr: Prandtl number Pr = nu/kappa Pm: Magnetic Prandtl number Pm=nu/eta

Numerical simulations via a nonlinear, multimode, initial-boundary value problem.

• entropy boundary conditions (tops and bots on input)

if ktops = 1, entropy specified on outer boundary if ktops = 2, radial heat flux specified on outer boundary if kbots = 1, entropy specified on inner boundary if kbots = 2, radial heat flux specified on inner boundary for example: ktops=1, the spherically-symmetric temperature on the outer boundary relative to the reference state

· velocity boundary condtions

if ktopv = 1, stress-free outer boundary if ktopv = 2, non-slip outer boundary if kbotv = 1, stress-free inner boundary if kbotv = 2, non-slip inner boundary

· magnetic boundary condtions

if ktopb = 1, insulating outer boundary (mantle) if kbotb = 1, insulating inner boundary (core) if ktopb = 2, not implemented if kbotb = 2, perfectly conducting inner boundary if ktopb = 3, finitely conducting mantle if kbotb = 3, finitely conducting inner core if ktopb = 4, pseudo vacuum outer boundary (B=Br) if kbotb = 4, pseudo vacuum inner boundary (B=Br)

· magneto-convection

amp\_b1 = max amplitude of imposed magnetic field if imagcon == 1, imposed toroidal field via inner bc on J(l=2,m=0) if imagcon == 10, imposed tor. field on both icb and cmb J(l=2,m=0) if imagcon == 11, imposed tor. field on both icb and cmb J(l=2,m=0) opposite sign if imagcon == 12, imposed tor. field on both icb and cmb J(l=1,m=0) if imagcon < 0, imposed poloidal field via inner bc on B(l=1,m=0)

```
Use horizontal_data,
                     rms
                            (finalize_rms(),
                                               initialize_rms()),
  output_mod (finalize_output(), initialize_output()), probe_mod
  (initialize_probes(),
                            finalize\_probes()),
                                                 movie data
  (finalize_movie_data(),
                           initialize_movie_data()),
                                                      lmloop_mod
  (finalize_lmloop(),
                          initialize_lmloop()),
                                                     lmloop_data
  (initialize_lmloop_data()), mem_alloc, init_fields, radial_der
  (finalize der arrays(), initialize der arrays()),
                                                          useful
  (abortrun()), precision mod, special (initialize grenoble(),
```

magnetic\_energy,

```
step time mod
                       (step_time(),
                                            initialize_step_time(),
   finalize step time()), communications (finalize communications(),
   initialize_communications()), parallel_mod, precalculations,
   num param,
                     physical_parameters,
                                                   radial functions
   (initialize radial functions(), finalize radial functions()),
   output data (n log file(), tag(), log file()),
                                                             power
   (initialize_output_power(), finalize_output_power()), namelists,
   outto mod
                (initialize outto mod(),
                                             finalize outto mod()),
   torsional_oscillations,
                            timing
                                      (writetime(), walltime()),
   kinetic_energy, out_coeff (finalize_coeffs(), initialize_coeffs()),
   blocking (finalize_blocking(), initialize_blocking()), constants
   (codeversion()), truncation, fieldslast, outrot (finalize_outrot(),
   initialize_outrot()),
                                geos_mod (finalize_geos_mod(),
   initialize_geos_mod()),
                            fields, spectra (finalize_spectra(),
   initialize_spectra()),
                                dtb_mod
                                            (initialize_dtb_mod(),
   finalize_dtb_mod()),
                          outmisc_mod
                                           (finalize_outmisc_mod(),
   initialize_outmisc_mod()), radial_data (initialize_radial_data()),
   radialloop (finalize_radialloop(), initialize_radialloop()),
   outpar_mod (initialize_outpar_mod(), finalize_outpar_mod()), logic,
   start_fields(getstartfields())
Call to parallel(), walltime(), readnamelists(), initialize_output(),
   checktruncation(),
                                       initialize memory counter(),
   initialize blocking(),
                                          initialize_radial_data(),
   initialize lmloop data(),
                                    initialize radial functions(),
   initialize_horizontal_data(), memwrite(), initialize_radialloop(),
   initialize_lmloop(),
                                            initialize_num_param(),
   initialize_init_fields(),
                                             initialize_grenoble(),
   initialize fields(),
                                           initialize fieldslast().
   initialize_step_time(),
                                       initialize_communications(),
   initialize_der_arrays(),
                                       initialize_kinetic_energy(),
   initialize_magnetic_energy(),
                                              initialize_spectra(),
   initialize_outpar_mod(),
                                          initialize_outmisc_mod(),
   initialize_outrot(),
                                         initialize_output_power(),
   initialize coeffs(),
                                   initialize_fields_average_mod(),
   initialize to(),
                                             initialize_geos_mod(),
                          precalc(),
   initialize_outto_mod(),
                                           initialize_movie_data(),
   initialize_dtb_mod(),
                                                  initialize_rms(),
                           initialize_probes(),
   finalize_memory_counter(),
                                                  writenamelists(),
   getstartfields(), precalctimes(),
                                      writeinfo(), step time(),
                      finalize_movie_data(),
   writetime(),
                                                    finalize rms(),
   finalize outto mod(),
                          finalize to(),
                                               finalize geos mod(),
   finalize_dtb_mod(),
                                     finalize_fields_average_mod(),
   finalize_coeffs(), finalize_output_power(), finalize_outrot(),
   finalize_outmisc_mod(), finalize_outpar_mod(), finalize_spectra(),
   finalize_magnetic_energy(),
                                         finalize_kinetic_energy(),
   finalize_probes(),
                                         finalize_communications(),
   finalize_step_time(), finalize_fieldslast(), finalize_fields(),
   finalize_grenoble(), finalize_init_fields(), finalize_num_param(),
   finalize_lmloop(), finalize_radialloop(), finalize_der_arrays(),
   finalize_horizontal_data(),
                                       finalize_radial_functions(),
   finalize_blocking(), finalize_output()
```

fields\_average\_mod,

finalize grenoble()),

# 10.2 Base modules

# **10.2.1** precision.f90

# **Description**

This module controls the precision used in MagIC

#### **Quick access**

```
Variables sizeof_character, sizeof_logical, sizeof_integer, mpi_def_complex, mpi_out_real, mpi_def_real, lip, cp, outp, sizeof_def_complex, sizeof_out_real, sizeof_def_real
```

#### **Needed modules**

• mpi

### **Variables**

- precision\_mod/outp [integer,parameter=selected\_real\_kind(6)/public]
- precision\_mod/mpi\_out\_real [integer,parameter=mpi\_real4/public]
- precision\_mod/sizeof\_integer [integer,parameter=4/public]
- precision\_mod/sizeof\_character[integer,parameter=1/public]
- precision\_mod/mpi\_def\_complex [integer,parameter=mpi\_complex16/public]
- precision\_mod/mpi\_def\_real [integer,parameter=mpi\_real8/public]
- precision\_mod/sizeof\_def\_real [integer,parameter=8/public]
- precision\_mod/sizeof\_logical[integer,parameter=2/public]
- precision\_mod/sizeof\_out\_real [integer,parameter=4/public]
- precision\_mod/lip[integer,parameter=selected\_int\_kind(12)/public]
- precision\_mod/cp [integer,parameter=selected\_real\_kind(15)/public]
- precision\_mod/sizeof\_def\_complex [integer,parameter=16/public]

### 10.2.2 truncation.f90

# **Description**

This module defines the grid points and the truncation

### **Quick access**

Variables ncp, fd\_order, fd\_order\_bound, l\_maxmag, lm\_maxmag, lmagmem, ldtbmem, lmoviemem, lstressmem, n\_r\_ic\_max\_dtb, lm\_max\_dtb, lmp\_max\_dtb, n\_phi\_maxstr, n\_r\_max\_dtb, n\_r\_maxstr, n\_r\_ic\_maxmag, n\_theta\_maxstr, n\_phi\_max, minc, nalias, nrp, l\_axi, l\_max, n\_cheb\_max, n\_m\_max, m\_max, n\_r\_totmag, n\_cheb\_ic\_max, n\_r\_ic\_max, lm\_max\_real, lmp\_max, lm\_max, n\_phi\_tot, n\_r\_max, n\_theta\_max, n\_theta\_axi, n\_r\_tot, radial\_scheme, fd\_ratio, fd\_stretch

**Routines** checktruncation(), initialize\_truncation()

### **Needed modules**

- precision\_mod (cp ()): This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- logic (l\_finite\_diff()): Module containing the logicals that control the run

#### **Variables**

- truncation/n\_r\_ic\_max [integer]
   number of grid points in inner core
- truncation/1\_max [integer] max degree of Plms
- truncation/minc[integer]
  basic wavenumber, longitude symmetry
- truncation/n\_cheb\_ic\_max[integer] number of chebs in inner core
- truncation/lstressmem [integer]

  Memory for stress output
- truncation/l\_axi [logical] logical for axisymmetric calculations
- truncation/n\_r\_maxmag [integer]
   Number of radial points to calculate magnetic field
- truncation/n\_phi\_maxstr [integer]

  Number of phi points for stress output
- truncation/n\_theta\_max [integer] number of theta grid-points
- truncation/lm\_maxmag[integer]

  Max. number of l/m combinations for magnetic field calculation
- truncation/n\_r\_ic\_max\_dtb [integer]

  Number of IC radial points for movie output
- truncation/ldtbmem[integer]

  Memory for movie output

- truncation/fd\_order[integer]
  Finite difference order (for now only 2 and 4 are safe)
- truncation/radial\_scheme [character] radial scheme (either Cheybev of FD)
- truncation/n\_r\_max [integer] number of radial grid points
- truncation/n\_theta\_maxstr [integer]

  Number of theta points for stress output
- truncation/**lmoviemem** [integer]

  Memory for movies
- truncation/nalias [integer] controls dealiasing in latitude
- truncation/n\_phi\_tot [integer] number of longitude grid points
- truncation/**fd\_ratio** [real] drMin over drMax (only when FD are used)
- truncation/n\_r\_tot [integer] total number of radial grid points
- truncation/ncp [integer]
- truncation/lmp\_max\_dtb [integer]

  Number of I/m combinations for movie output if I runs to I max+1
- truncation/fd\_order\_bound [integer]
  Finite difference order on the boundaries
- truncation/lmp\_max[integer]
  number of l/m combination if l runs to l\_max+1
- truncation/n\_m\_max [integer]
   max number of ms (different oders)
- truncation/m\_max [integer] max order of Plms
- truncation/lm\_max[integer]
  number of l/m combinations
- truncation/n\_theta\_axi [integer]
   number of theta grid-points (axisymmetric models)
- truncation/**nrp** [integer] dimension of phi points in for real/complex arrays
- truncation/**lmagmem** [integer]

  Memory for magnetic field calculation
- truncation/lm\_max\_real [integer]
  number of l/m combination for real representation (cos/sin)
- truncation/n\_r\_ic\_maxmag [integer]

  Number of radial points to calculate IC magnetic field
- truncation/n\_r\_maxstr[integer]

  Number of radial points for stress output

- truncation/n\_phi\_max [integer]
   absolute number of phi grid-points
- truncation/n\_r\_max\_dtb [integer]

  Number of radial points for movie output
- truncation/**1\_maxmag** [integer]

  Max. degree for magnetic field calculation
- truncation/fd\_stretch [real] regular intervals over irregular intervals
- truncation/lm\_max\_dtb [integer]

  Number of l/m combinations for movie output
- truncation/n\_r\_totmag[integer]n\_r\_maxMag + n\_r\_ic\_maxMag
- truncation/n\_cheb\_max [integer] max degree-1 of cheb polynomia

This function checks truncations and writes it into STDOUT and the log-file. MPI: called only by the processor responsible for output!

```
Called from magic

Call to abortrun()
```

### 10.2.3 num param.f90

### **Description**

Module containing numerical and control parameters

### **Quick access**

```
Variables n_lscale, n_tscale, ldif, ldifexp, n_cour_step, n_time_steps, istop, map_function, polo_flow_eq, thermo_variable, anelastic_flavour, amstart, pscale, difchem, difeta, difkap, difnu, enscale, escale, dtstart, alph2, alph1, lscale, dtmax, runtimelimit, dtmin, tend, timestart, runtime, tscale, intfac, alffac, courfac, vscale, runtimestart, alpha, delxh2, delxr2
```

Routines finalize\_num\_param(), initialize\_num\_param()

# **Needed modules**

• mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC

- precision\_mod: This module controls the precision used in MagIC
- truncation (n\_r\_max()): This module defines the grid points and the truncation

- num\_param/amstart [real,public]
- num\_param/n\_cour\_step [integer,public]
  Step for controlling Courant criteria
- num\_param/alph1 [real,public]
  Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- num\_param/alph2 [real,public]
   Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- num\_param/n\_time\_steps [integer,public]

  Total number of time steps requested in the name list
- num\_param/difnu [real,public]
  Amplitude of viscous hyperdiffusion
- num\_param/timestart [real,public]

  Numerical time where run should start
- num\_param/dtmin [real,public]
   Minimum allowed time step
- num\_param/thermo\_variable [character,public] thermodynamic variable: S or T
- num\_param/delxr2 (:) [real,allocatable/public]
- num\_param/ldifexp[integer,public]
  Exponent for hyperdiffusion function
- num\_param/difkap [real,public]
  Amplitude of thermal hyperdiffusion
- num\_param/dtstart [real,public]
   Initial time step if start solution is initialized
- num\_param/difchem[real,public]
  Amplitude of chemical hyperdiffusion
- num\_param/n\_lscale [integer,public]
  Control length scale
- num\_param/tend[real,public]

  Numerical time where run should end
- num\_param/polo\_flow\_eq[character,public] form of the poloidal flow equation: Pressure or Double Curl
- num\_param/runtimelimit (4) [integer,public]

  Maximum running time
- num\_param/istop [integer,public]
  Variable used in FFT soubroutine
- num\_param/ldif [integer,public]

  Degree where hyperdiffusion starts to act

- num\_param/alffac [real,public]
   Value to scale Alfen-velocity in courant criteria
- num\_param/anelastic\_flavour [character,public] version of the anelastic approximation
- num\_param/vscale [real,public]
  Velocity scale
- num\_param/escale [real,public]
  Energy scale
- num\_param/delxh2 (:) [real,allocatable/public]
- num\_param/courfac [real,public]

  Value to scale velocity in courant criteria
- num\_param/tscale [real,public]
  Time scale
- num\_param/dtmax [real,public]

  Maximum allowed time step
- num\_param/alpha [real,public]
   Weight for implicit time step
- num\_param/n\_tscale [integer,public]
  Control time scale
- num\_param/pscale [real,public]
- num\_param/runtimestart (4) [integer,public] Wall clock time of start of the run
- num\_param/map\_function [character,public]

  Mapping family: either tangent or arcsin
- num\_param/difeta[real,public]
  Amplitude of magnetic hyperdiffusion
- num\_param/enscale [real,public]
  Energies scale
- num\_param/intfac [real,public]
   Value to re-scale dtMax during simulation
- num\_param/runtime (4) [integer,public]
  Running time
- num\_param/lscale [real,public]
  Length scale

# 10.2.4 phys\_param.f90

# **Description**

Module containing the physical parameters

#### **Quick access**

Variables impxi, kbotb, kbots, kbotv, kbotxi, n\_impxi, ktopp, ktopxi, ktops, imps, n\_imps, imagcon, ktopb, mode, n\_r\_lcr, nvareps, nvarcond, nvardiff, nvarvisc, ktopv, nvarentropygrad, interior\_model, ekscaled, rascaled, raxi, epss, dissnb, ek, con\_lambdamatch, grunnb, epscxi0, epsc0, lffac, opr, osc, corfac, opm, o\_sr, oek, conductance\_ma, r\_cut\_model, po, po\_diff, pr, prec\_angle, diff\_prec\_angle, ohmlossfac, vischeatfac, r\_lcr, buofac, chemfac, ra, epsc, epscxi, rho\_ratio\_ic, rho\_ratio\_ma, sc, g2, g0, g1, con\_decrate, difexp, thexpnb, tmagcon, con\_radratio, sigma\_ratio, radratio, prmag, con\_funcwidth, con\_lambdaout, strat, polind, ampstrat, cmbhflux, rstrat, slopestrat, thickstrat, n\_impxi\_max, n\_imps\_max, peaks, peakxi, phis, phixi, thetas, thetaxi, widths, widthxi

#### **Needed modules**

• precision mod: This module controls the precision used in MagIC

- physical\_parameters/n\_impxi[integer]
- physical\_parameters/sigma\_ratio [real]
   Value of IC rotation
- physical\_parameters/ktopb [integer]
   Magnetic boundary condition
- physical\_parameters/**strat** [real] number of density scale heights
- physical\_parameters/ampstrat [real] stratified Layer
- physical\_parameters/ekscaled[real]  $E\,l^2$
- physical\_parameters/n\_imps [integer] Heat boundary condition
- physical\_parameters/difexp[real]
   Thermal diffusivity variation
- physical\_parameters/ktopv [integer]
   Velocity boundary condition
- physical\_parameters/**chemfac** [real]

  Ratio of comp. Rayleigh number over Schmidt number

```
• physical parameters/ktopp[integer]
      Boundary condition for spherically-symmetric pressure
• physical_parameters/ktops [integer]
      Entropy boundary condition
• physical_parameters/con_radratio [real]
      Transition between branches of electrical conductivity profile (nVarCond=1,2)
• physical_parameters/rho_ratio_ic [real]
      Same density as outer core
• physical_parameters/osc[real]
      Inverse of Schmidt number (i.e. chemical Prandtl number)
• physical_parameters/pr[real]
      Prandtl number
• physical_parameters/rho_ratio_ma [real]
      Same density as outer core
• physical parameters/ktopxi[integer]
      Boundary conditions for chemical composition
• physical_parameters/rstrat [real]
      stratified Layer
• physical parameters/epsc/real]
      Renormalisation of epsc0
• physical_parameters/kbotxi[integer]
• physical_parameters/ohmlossfac[real]
      Prefactor for Ohmic heating: Di Pr/(Ra E Pm^2)
• physical_parameters/thetas(20)[real]
• physical_parameters/kbots[integer]
• physical_parameters/g2 [real]
      Set to 1.0 for 1/r^2 gravity
• physical parameters/q1 [real]
      Set to 1.0 for linear gravity
• physical_parameters/g0 [real]
      Set to 1.0 for constant gravity
• physical parameters/radratio [real]
      aspect ratio
• physical_parameters/nvarentropygrad[integer]
      stratified Layer
• physical_parameters/peakxi (20) [real]
```

• physical\_parameters/con\_funcwidth [real]

physical\_parameters/kbotb [integer]
 physical\_parameters/nvareps [integer]
 Selection of internal heating profile

nVarCond=1

- physical\_parameters/**opm** [real]
  Inverse of magnetic Prandtl number
- physical\_parameters/**slopestrat** [real] stratified Layer
- physical\_parameters/nvarvisc[integer]
  Selection of variable viscosity profile
- physical\_parameters/prec\_angle [real]
  Precession angle
- physical\_parameters/r\_lcr[real]

  Radius beyond which conductivity is zero
- physical\_parameters/**po\_diff** [real]
  Poincaré number for differential precession
- physical\_parameters/imps [integer]

  Heat boundary condition
- physical\_parameters/prmag[real] magnetic Prandtl number
- physical\_parameters/n\_imps\_max [integer,parameter=20] Heat boundary condition
- physical\_parameters/**epscxi** [real]
  Renormalisation of epsc0Xi
- physical\_parameters/corfac[real]
  Inverse of ekScaled
- physical\_parameters/**po** [real]
  Poincaré number
- physical\_parameters/mode [integer]
   Mode of calculation
- physical\_parameters/interior\_model [character] name of the interior model
- physical\_parameters/tmagcon[real]
  Time for magnetoconvection calculation
- physical\_parameters/raxi[real]
  Chemical composition-based Rayleigh number
- ullet physical\_parameters/rascaled[real]  $Ra\,l^3$
- physical\_parameters/**dissnb** [real]
  Dissipation number
- physical\_parameters/**polind** [real] polytropic index
- physical\_parameters/lffac[real]
  Inverse of Pr\*Ekman
- physical\_parameters/**ek** [real] Ekman number
- physical\_parameters/kbotv[integer]

- physical\_parameters/thetaxi(20)[real]
- physical\_parameters/epscxi0 [real]
   Internal chemical heat source magnitude
- physical\_parameters/widthxi(20)[real]
- physical\_parameters/**epsc0** [real]
  Internal heat source magnitude
- physical\_parameters/ ${\bf vischeatfac}$  [real] Prefactor for viscous heating: Di Pr/Ra
- physical\_parameters/thickstrat [real] stratified Layer
- physical\_parameters/con\_decrate [real]

  Slope of electrical conductivity profile (nVarCond=2)
- physical\_parameters/conductance\_ma [real] OC conductivity
- physical\_parameters/con\_lambdamatch [real] Electrical conductivity at con\_RadRatio (nVarCond=2)
- physical\_parameters/cmbhflux [real] stratified Layer
- physical\_parameters/opr [real]
   Inverse of Prandtl number
- physical\_parameters/impxi [integer]
- physical\_parameters/**grunnb** [real]
  Grüneisen paramater:math:'Gamma=(gamma-1)/alpha T\$
- physical\_parameters/ra[real]
  Rayleigh number
- physical\_parameters/n\_r\_lcr [integer]

  Number of radial points where conductivity is zero
- physical\_parameters/o\_sr[real]
  Inverse of sigma\_ratio
- physical\_parameters/nvardiff [integer]
  Selection of variable diffusivity profile
- physical\_parameters/diff\_prec\_angle [real]
   Precession angle for differential precession
- physical\_parameters/buofac [real]
   Ratio of Rayleigh number over Prandtl number
- physical\_parameters/peaks (20) [real]
- physical\_parameters/**oek** [real]
  Inverse of the Ekman number
- physical\_parameters/**sc** [real]
  Schmidt number (i.e. chemical Prandtl number)
- physical\_parameters/nvarcond[integer]
  Selection of variable conductivity profile

- physical\_parameters/phixi(20)[real]
- physical\_parameters/n\_impxi\_max [integer,parameter=20]
- physical\_parameters/widths (20) [real]
- physical\_parameters/con\_lambdaout [real] nVarCond=1
- physical\_parameters/**r\_cut\_model** [real]

  Percentage on the inner part of the interior model to be used
- physical\_parameters/**phis** (20) [real]
- physical\_parameters/imagcon [integer]
  Imposed magnetic field for magnetoconvection, at the boundaries
- physical\_parameters/thexpnb [real] Thermal expansion \* temperature  $\alpha_0 T_0$
- physical\_parameters/**epss** [real]

  Deviation from the adiabat

# 10.2.5 logic.f90

# **Description**

Module containing the logicals that control the run

### **Quick access**

Variables 1\_ab1, 1\_earth\_likeness, 1\_single\_matrix, 1\_cour\_alf\_damp, 1 pressgraph, 1 cmb field, 1 dt cmb field, 1 corrmov, l rms, l\_tomovie, l\_to, l\_runtimelimit, l\_par, l\_anel, l\_anelastic\_liquid, 1\_am, l\_probe, l\_energy\_modes, l\_perppar, l\_fluxprofs, l\_average, 1\_chemical\_conv, 1\_cond\_ic, 1\_cond\_ma, 1\_correct\_amz, 1\_correct\_ame, lverbose, l\_viscbccalc, l\_drift, l\_dtbmovie, l\_ht, l\_htmovie, l\_hel, l\_iner, l\_isothermal, l\_rmagspec, l\_dtrmagspec, l\_b\_nl\_icb, 1\_b\_nl\_cmb, 1\_newmap, 1\_pv, 1\_power, 1\_r\_fieldt, 1\_r\_field, 1\_movie, 1\_movie\_ic, 1\_movie\_oc, 1\_z10mat, 1\_storepot, 1\_storetpot, 1\_storebpot, 1\_store\_frame, l\_storevpot, l\_time\_hits, l\_true\_time, l\_non\_adia, l\_rot\_ic, l\_mag\_lf, l\_rot\_ma, l\_conv, l\_update\_s, l\_heat, l\_update\_b, l\_mag, l\_conv\_nl, l\_heat\_nl, l\_mag\_nl, l\_save\_out, l\_corr, l\_update\_xi, l\_update\_v, l\_mag\_kin, l\_non\_rot, l\_dtb, l\_sric, l\_srma, 1 diff prec, 1 finite diff, 1 precession, 1 tp form, 1 double curl, l\_temperature\_diff

- logic/l\_time\_hits [logical]
  Switch for time for outputs
- logic/l\_to [logical]
  Switch for TO output in TOnhs.TAG, TOshs.TAG

• logic/l\_dtrmagspec[logical]

Switch for magnetic spectra at different depths at movie output times

• logic/l\_lcr [logical]

Switch for zero electrical conductivity beyond r\_LCR

• logic/l\_dtbmovie [logical]

Switch for dtB movie

• logic/lverbose [logical]

Switch for detailed information about run progress

• logic/l\_correct\_amz [logical]

Switch for correction of axial angular momentum

• logic/l\_correct\_ame [logical]

Switch for correction of equatorial angular mom.

• logic/l\_pv [logical]

Switch for potential vorticity calculation

• logic/l heat [logical]

Switch off heat terms calculation

• logic/l\_srma [logical]

Switch to rotating OC with prescribed rot. rate

• logic/l mag lf [logical]

Switch off Lorentz force term

• logic/l\_perppar [logical]

Switch for calculation of of kinetic energy perpendicular+parallel to the rotation axis

• logic/l\_sric[logical]

Switch to rotating IC with prescribed rot. rate

• logic/l\_mag[logical]

Switch off magnetic terms calculation

• logic/**l\_ab1** [logical]

1st order Adams Bashforth

• logic/l\_non\_rot [logical]

Switch to non-rotating

• logic/l\_update\_b [logical]

Switch off magnetic field update

• logic/l r fieldt [logical]

Switch for radial T coefficients

• logic/l\_average [logical]

Switch for calculation of time-averages

• logic/l\_update\_v[logical]

Switch off velocity field update

• logic/l\_cond\_ic [logical]

Switch for conducting IC

• logic/l\_update\_s [logical]

Switch off entropy update

### • logic/l\_storevpot [logical]

Switch for storing velocity field potentials

### • logic/l\_non\_adia [logical]

Switch in case the reference state is non-adiabatic

#### • logic/**l\_am** [logical]

Switch for angular momentum calculation

# • logic/l\_storebpot [logical]

Switch for storing magnetic field potentials

# • logic/l\_viscbccalc[logical]

Switch for dissipation layer for stress-free BCs plots

### • logic/l\_conv[logical]

Switch off convection

### • logic/l\_pressgraph [logical]

Store pressure in graphic files

### • logic/l\_true\_time [logical]

Switch for times of outputs

### • logic/l\_chemical\_conv [logical]

Switch for chemical convection

### • logic/l\_movie\_ic[logical]

Switch for recording of movie files for IC

# • logic/l\_store\_frame [logical]

Switch for storing movie frames

### • logic/l\_single\_matrix [logical]

In case entropy, w and P are solved at once implicitely

### • logic/l\_isothermal[logical]

Switch for isothermal calculation

### • logic/l\_mag\_nl [logical]

Switch off non-linear magnetic terms calculation

# • logic/l\_z10mat [logical]

Switch for solid body rotation

### • logic/l\_cour\_alf\_damp [logical]

Modify Alven Courant condition based on Christensen et al., GJI, 1999 (.true. by default)

#### • logic/l rmagspec[logical]

Switch for magnetic spectra at different depths at log times

# • logic/l\_drift [logical]

Switch for drift rates calculation

# • logic/l\_dt\_cmb\_field[logical]

Switch for Bcoef files for secular variation of gauss coefs.

# • logic/l\_probe [logical]

Switch for artifical sensors

### • logic/l\_hel [logical]

Switch for helicity calculation, output in misc.TAG

#### • logic/l\_corrmov[logical]

Switch for North/south correlation movie (see s\_getEgeos.f)

### • logic/l\_finite\_diff [logical]

Use finite differences for the radial scheme

### • logic/l\_newmap [logical]

Switch for non-linear mapping (see Bayliss and Turkel, 1990)

### • logic/l\_storetpot [logical]

Switch for storing entropy field potentials

# • logic/l\_cond\_ma [logical]

Switch for conducting OC

# • logic/l\_save\_out [logical]

Switch off outputs

### • logic/l\_rot\_ic [logical]

Switch off IC rotation

### • logic/l\_anelastic\_liquid[logical]

Switch for anelastic liquid calculation

### • logic/l\_double\_curl [logical]

Use the double-curl of the NS equation to get the poloidal equation

#### • logic/l\_b\_nl\_icb [logical]

Switch for non-linear magnetic field at IC

# • logic/l\_conv\_nl [logical]

Switch off non-linear convection terms

### • logic/l\_htmovie [logical]

Switch for heat flux movie output

### • logic/l\_movie [logical]

Switch for recording of movie files

### • logic/l\_anel [logical]

Switch for anelastic calculation

# • logic/l\_runtimelimit [logical]

Switch for absolute time limit of the run

### • logic/l\_fluxprofs [logical]

Switch for calculation of radial profiles of flux contributions

### • logic/l\_update\_xi [logical]

Switch off update of chemical composition

### • logic/l\_earth\_likeness [logical]

Compute the Earth-likeness of the CMB field following Christensen et al., EPSL, 2010

# • logic/l\_movie\_oc[logical]

Switch for recording of movie files for OC

#### • logic/l\_cmb\_field[logical]

Switch for Bcoef files for gauss coefficients

# • logic/l\_temperature\_diff[logical]

diffusion of temperature instead of entropy

# • logic/l\_precession[logical]

Use precession

# • logic/l\_heat\_nl [logical]

Switch off non-linear heat terms calculation

# • logic/l\_iner[logical]

Switch for inertial modes calculation

### • logic/l\_mag\_kin [logical]

Switch related for kinematic dynamo

# • logic/l\_rot\_ma [logical]

Switch off OC rotation

### • logic/l\_ht [logical]

Switch for heat flux movie frame output

# • logic/l\_storepot [logical]

Switch for storing all field potentials

### • logic/l tomovie [logical]

Switch for TO movie output

# • logic/l\_power[logical]

Switch for power budget terms calculation

# • logic/l\_diff\_prec [logical]

Use differential precession

### • logic/l\_dtb [logical]

Switch to reserve memory for dtB movie

### • logic/l\_par [logical]

Switch for additional parameters calculation in s\_getEgeos.f

### • logic/l\_b\_nl\_cmb [logical]

Switch for non-linear magnetic field at OC

# • logic/l\_tp\_form[logical]

Use temperature and pressure instead of entropy and pressure

# • logic/l\_rms [logical]

Switch for RMS force balances calculation

### • logic/l\_r\_field[logical]

Switch for radial coefficients

### • logic/l\_energy\_modes [logical]

Switch for calculation of distribution of energies over m's

# • logic/l\_corr[logical]

Switch off rotation

### 10.2.6 fields.f90

# **Description**

This module contains the potential fields and their radial derivatives

#### **Quick access**

Variables omega\_ic, omega\_ma, aj\_ic, aj\_ic\_lmloc, b, b\_ic, b\_ic\_lmloc, db\_ic, db\_ic\_lmloc, ddb\_ic, ddb\_ic\_lmloc, ddb\_ic\_lmloc, ddj\_ic, ddj\_ic\_lmloc, dj\_ic, dj\_ic\_lmloc, work\_lmloc, aj\_lmloc, aj\_rloc, b\_lmloc, b\_rloc, db\_lmloc, ddb\_rloc, ddb\_rloc, ddb\_rloc, ddb\_lmloc, ddb\_rloc, ddj\_lmloc, ddw\_lmloc, ddw\_rloc, dj\_lmloc, dj\_rloc, dp\_lmloc, dp\_rloc, ds\_lmloc, ds\_rloc, dw\_lmloc, dw\_rloc, dxi\_lmloc, dxi\_rloc, dz\_lmloc, dz\_rloc, p\_lmloc, p\_rloc, s\_lmloc, s\_rloc, w\_lmloc, w\_rloc, xi\_lmloc, xi\_rloc, z\_lmloc, z\_rloc, field\_lmloc\_container, field\_rloc\_container, flow\_lmloc\_container, xi\_lmloc\_container, s\_rloc\_container, xi\_lmloc\_container, xi\_rloc\_container

Routines finalize\_fields(), initialize\_fields()

#### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- parallel\_mod (rank ()): This module contains the blocking information
- logic(l\_chemical\_conv()): Module containing the logicals that control the run
- truncation (lm\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation

# **Variables**

- fields/aj\_lmloc(:,:) [complex,pointer/public]
- fields/s\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/b\_rloc(:,:) [complex,pointer/public]
- fields/ddw\_rloc(:,:) [complex,pointer/public]
- fields/dxi\_rloc(:,:) [complex,pointer/public]
- fields/aj\_ic(:,:) [complex,allocatable/public]
- fields/ddw\_lmloc(:,:) [complex,pointer/public]
- fields/xi\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/xi\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/dj\_lmloc(:,:) [complex,pointer/public]
- fields/dw\_rloc(:,:) [complex,pointer/public]
- fields/p\_rloc(:,:) [complex,pointer/public]
- fields/dp\_rloc(:,:) [complex,pointer/public]

- fields/field\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/db\_lmloc(:,:) [complex,pointer/public]
- fields/s\_lmloc(:,:) [complex,pointer/public]
- fields/**s\_rloc**(:,:) [complex,pointer/public]
- fields/ddb lmloc(:,:) [complex,pointer/public]
- fields/b\_ic(:,:) [complex,allocatable/public]
- fields/ds\_lmloc(:,:) [complex,pointer/public]
- fields/dj\_rloc(:,:) [complex,pointer/public]
- fields/ddb\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/p\_lmloc(:,:) [complex,pointer/public]
- fields/dxi\_lmloc(:,:) [complex,pointer/public]
- fields/db\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/xi\_rloc(:,:) [complex,pointer/public]
- fields/dw\_lmloc(:,:) [complex,pointer/public]
- fields/dp\_lmloc(:,:) [complex,pointer/public]
- fields/dj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/ddb\_ic(:,:) [complex,allocatable/public]
- fields/db\_ic(:,:) [complex,allocatable/public]
- fields/s\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/flow\_lmloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/work\_lmloc(:,:) [complex,allocatable/public]
- fields/dj\_ic(:,:) [complex,allocatable/public]
- fields/b\_lmloc(:,:) [complex,pointer/public]
- fields/**z\_rloc**(:,:) [complex,pointer/public]
- fields/flow\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/**z\_lmloc**(:,:) [complex,pointer/public]
- fields/dz\_rloc(:,:) [complex,pointer/public]
- fields/field\_rloc\_container(:,:,:) [complex,target/allocatable/public]
- fields/**ds\_rloc**(:,:) [complex,pointer/public]
- fields/omega\_ma[real,public]
- fields/w\_lmloc(:,:) [complex,pointer/public]
- fields/aj\_rloc(:,:) [complex,pointer/public]
- fields/b(:,:) [complex,allocatable/public]
- fields/ddj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/ddj\_ic(:,:) [complex,allocatable/public]
- fields/b\_ic\_lmloc(:,:) [complex,allocatable/public]

```
• fields/ddb_rloc(:,:) [complex,pointer/public]
```

- fields/db\_rloc(:,:) [complex,pointer/public]
- fields/w\_rloc(:,:) [complex,pointer/public]
- fields/aj\_ic\_lmloc(:,:) [complex,allocatable/public]
- fields/xi lmloc(:,:) [complex,pointer/public]
- fields/omega ic/real, public/
- fields/ddj\_lmloc(:,:) [complex,pointer/public]
- fields/dz\_lmloc(:,:) [complex,pointer/public]

# 10.2.7 dt fieldsLast.f90

# **Description**

This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

The variables labeled with a suffix 'Last' are provided by the restart file for the first time step or calculated here or by the update routines for the following time step. These fields remain in the LM-distributed space

# **Quick access**

```
Variables d_omega_ic_dtlast, d_omega_ma_dtlast, lorentz_torque_iclast,
    lorentz_torque_malast, dbdt_iclast_lmloc, dbdtlast_lmloc,
    djdt_iclast_lmloc, djdtlast_lmloc, dpdtlast_lmloc, dsdtlast_lmloc,
    dwdtlast_lmloc, dxidtlast_lmloc, dzdtlast_lo
Routines finalize_fieldslast(), initialize_fieldslast()
```

#### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- precision\_mod: This module controls the precision used in MagIC
- logic (l\_chemical\_conv()): Module containing the logicals that control the run
- truncation(lm\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation

• parallel\_mod (rank ()): This module contains the blocking information

#### **Variables**

- fieldslast/dbdt\_iclast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/djdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dpdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/lorentz\_torque\_malast[real,public]
- fieldslast/dwdtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dzdtlast\_lo(:,:) [complex,allocatable/public]
- fieldslast/lorentz\_torque\_iclast [real,public]
- fieldslast/djdt\_iclast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/d\_omega\_ma\_dtlast [real, public]
- fieldslast/d\_omega\_ic\_dtlast [real,public]
- fieldslast/dxidtlast\_lmloc(:,:) [complex,allocatable/public]
- fieldslast/dsdtlast\_lmloc(:,;) [complex,allocatable/public]
- fieldslast/dbdtlast\_lmloc(:,:) [complex,allocatable/public]

### Subroutines and functions

# 10.2.8 output\_data.f90

### **Description**

This module contains the parameters for output control

#### Quick access

Variables graph\_mpi\_fh, l\_graph\_time, l\_max\_cmb, l\_max\_r, m\_max\_modes, n\_bpot\_step, n\_bpots, n\_cmb\_step, n\_cmbs, n\_coeff\_r\_max, n\_graph\_file, n\_graph\_step, n\_graphs, n\_log\_file, n\_log\_step, n\_logs, n\_movie\_frames, n\_movie\_step, n\_pot\_step, n\_pots, n\_probe\_out, n\_probe\_step, n\_r\_field\_step, n\_r\_fields, n\_r\_step, n\_rst\_step, n\_rsts, n\_spec\_step, n\_specs, n\_stores, n\_t\_bpot, n\_t\_cmb, n\_t\_graph, n\_t\_log, n\_t\_movie, n\_t\_pot, n\_t\_probe, n\_t\_r\_field, n\_t\_rst, n\_t\_spec, n\_t\_to, n\_t\_tomovie, n\_t\_toz, n\_t\_tpot, n\_t\_vpot, n\_to\_step, n\_tomovie\_frames, n\_tomovie\_step, n\_tos, n\_toz\_step, n\_tozs, n\_tpot\_step, n\_tpots, n\_vpot\_step, n\_vpots,

l\_max\_comp, n\_time\_hits, n\_coeff\_r, tag, runid, graph\_file, log\_file,
lp\_file, n\_r\_array, dt\_bpot, dt\_cmb, dt\_graph, dt\_log, dt\_movie, dt\_pot,
dt\_probe, dt\_r\_field, dt\_rst, dt\_spec, dt\_to, dt\_tomovie, dt\_toz, dt\_tpot,
dt\_vpot, rcut, rdea, sdens, t\_bpot\_start, t\_bpot\_stop, t\_cmb\_start,
t\_cmb\_stop, t\_graph\_start, t\_graph\_stop, t\_log\_start, t\_log\_stop,
t\_movie\_start, t\_movie\_stop, t\_pot\_start, t\_pot\_stop, t\_probe\_start,
t\_probe\_stop, t\_r\_field\_start, t\_r\_field\_stop, t\_rst\_start, t\_rst\_stop,
t\_spec\_start, t\_spec\_stop, t\_to\_start, t\_to\_stop, t\_tomovie\_start,
t\_tomovie\_stop, t\_toz\_start, t\_toz\_stop, t\_tpot\_start, t\_tpot\_stop,
t\_vpot\_start, t\_vpot\_stop, zdens, t\_bpot, t\_cmb, t\_graph, t\_log, t\_movie,
t\_pot, t\_probe, t\_r\_field, t\_rst, t\_spec, t\_to, t\_tomovie, t\_toz, t\_tpot,

### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

#### **Variables**

- output\_data/n\_tozs[integer,public]
- output\_data/n\_graphs [integer,public]
- output\_data/t\_toz\_start [real,public]
- output\_data/n\_tpots[integer,public]
- output\_data/runid[character,public]
- output\_data/dt\_spec [real,public]
- output\_data/dt\_tpot [real,public]
- output\_data/dt\_probe [real,public]
- output\_data/n\_r\_step[integer,public]
- output\_data/t\_movie\_start [real,public]
- output\_data/n\_t\_toz [integer,public]
- output\_data/n\_t\_cmb [integer,public]
- output\_data/sdens [real,public]
- output\_data/n\_tpot\_step[integer,public]
- output\_data/n\_t\_spec [integer,public]
- output\_data/t\_rst\_start [real,public]
- output\_data/n\_time\_hits [integer,parameter=5000/public]
- output\_data/t\_bpot\_start [real,public]
- output\_data/dt\_graph [real,public]
- output\_data/dt\_tomovie [real,public]
- output\_data/t\_rst\_stop [real,public]
- output\_data/t\_vpot\_start [real,public]

- output\_data/n\_r\_array (100) [integer,public]
- output\_data/n\_t\_tomovie [integer,public]
- output\_data/l\_max\_cmb [integer,public]
- output\_data/n\_to\_step[integer,public]
- output\_data/n\_log\_step[integer,public]
- output\_data/t\_to\_stop [real,public]
- output\_data/t\_rst (5000) [real,public]
- output\_data/t\_log\_stop [real,public]
- output\_data/dt\_cmb [real,public]
- output\_data/n\_cmb\_step[integer,public]
- output\_data/l\_graph\_time [logical,public]
- output\_data/dt\_r\_field[real,public]
- output\_data/t\_probe (5000) [real,public]
- output\_data/t\_graph\_start [real,public]
- output\_data/dt\_vpot [real,public]
- output\_data/l\_max\_comp [integer,public]
   Maximum spherical harmonic degree to estimate Earth-likeness
- output\_data/dt\_log[real,public]
- output\_data/t\_cmb (5000) [real,public]
- output\_data/t\_probe\_start [real,public]
- output\_data/n\_t\_pot [integer,public]
- output\_data/n\_graph\_step[integer,public]
- output\_data/n\_t\_bpot [integer,public]
- output\_data/zdens[real,public]
- output\_data/t\_graph (5000) [real,public]
- output\_data/t\_to\_start [real,public]
- output\_data/dt\_toz [real,public]
- output\_data/n\_bpots [integer,public]
- output\_data/**dt\_movie** [real,public]
- output\_data/graph\_mpi\_fh [integer,public]
- output\_data/t\_r\_field\_stop [real,public]
- output\_data/n\_log\_file [integer,public]
- output\_data/n\_movie\_frames [integer, public]
- output\_data/n\_specs [integer,public]
- output\_data/t\_cmb\_start [real,public]
- output\_data/t\_tomovie\_stop [real,public]

- output\_data/t\_r\_field\_start [real,public]
- output\_data/n\_probe\_step[integer,public]
- output\_data/n\_tos[integer,public]
- output\_data/n\_rst\_step [integer,public]
- output\_data/dt\_pot [real,public]
- output data/t vpot (5000) [real, public]
- output\_data/n\_graph\_file [integer,public]
- output\_data/n\_vpot\_step[integer,public]
- output\_data/t\_spec\_stop [real,public]
- output\_data/t\_tpot\_start [real,public]
- output\_data/n\_t\_movie [integer,public]
- output\_data/n\_t\_to[integer,public]
- output\_data/n\_t\_probe [integer,public]
- output\_data/n\_tomovie\_step [integer,public]
- output\_data/t\_cmb\_stop [real,public]
- output\_data/n\_vpots [integer,public]
- output\_data/t\_log\_start [real,public]
- output\_data/t\_toz\_stop [real,public]
- output\_data/t\_to (5000) [real,public]
- output\_data/n\_tomovie\_frames [integer,public]
- output\_data/n\_pots[integer,public]
- output\_data/t\_tpot (5000) [real,public]
- output\_data/n\_rsts[integer,public]
- output\_data/n\_cmbs [integer,public]
- output\_data/n\_t\_graph [integer,public]
- output\_data/dt\_rst [real,public]
- output\_data/t\_tomovie\_start [real,public]
- output\_data/t\_toz (5000) [real,public]
- output\_data/dt\_to [real,public]
- output\_data/n\_stores [integer,public]
- output\_data/n\_t\_vpot [integer,public]
- output\_data/t\_pot\_start [real,public]
- output\_data/m\_max\_modes [integer,public]
- output\_data/n\_coeff\_r(:) [integer,allocatable/public]
- output\_data/t\_spec (5000) [real,public]
- output\_data/n\_logs [integer,public]

- output\_data/t\_movie (5000) [real, public]
- output\_data/n\_t\_tpot [integer,public]
- output\_data/t\_tpot\_stop [real,public]
- output\_data/n\_t\_log[integer,public]
- output\_data/l\_max\_r [integer,public]
- output\_data/n\_r\_fields [integer,public]
- output\_data/n\_movie\_step[integer,public]
- output\_data/ $t_r_field(5000)$  [real,public]
- output\_data/n\_t\_r\_field[integer,public]
- output\_data/n\_pot\_step[integer,public]
- output\_data/n\_probe\_out [integer,public]
- output\_data/t\_pot (5000) [real,public]
- output\_data/t\_graph\_stop [real,public]
- output\_data/t\_probe\_stop [real,public]
- output\_data/n\_r\_field\_step [integer,public]
- output\_data/rcut [real,public]
- output\_data/t\_movie\_stop [real,public]
- output\_data/tag[character,public]
- output\_data/n\_toz\_step[integer,public]
- output\_data/n\_coeff\_r\_max [integer,public]
- output\_data/n\_bpot\_step[integer,public]
- output\_data/lp\_file [character,public]
- output\_data/t\_log(5000)[real,public]
- output\_data/t\_spec\_start [real,public]
- output\_data/n\_t\_rst [integer,public]
- output\_data/graph\_file [character,public]
- output\_data/n\_spec\_step [integer,public]
- output\_data/t\_bpot\_stop [real,public]
- output\_data/t\_bpot (5000) [real,public]
- output\_data/t\_tomovie (5000) [real,public]
- output\_data/dt\_bpot [real,public]
- output\_data/t\_pot\_stop [real, public]
- output\_data/t\_vpot\_stop [real,public]
- output\_data/log\_file [character,public]
- output\_data/rdea [real,public]

# 10.2.9 constants.f90

# **Description**

module containing constants and parameters used in the code.

### **Quick access**

```
Variables c_dt_z10_ic, c_dt_z10_ma, c_lorentz_ic, c_lorentz_ma, c_z10_omega_ic, c_z10_omega_ma, y10_norm, y11_norm, mass, c_moi_ic, c_moi_ma, c_moi_oc, surf_cmb, vol_ic, vol_oc, codeversion, zero, ci, half, sin60, one, two, three, four, pi, third, osq4pi, cos36, cos72, sin36, sin72, sq4pi
```

#### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

#### **Variables**

- constants/ci [complex,parameter=(0.0\_cp,1.0\_cp)]
- constants/c\_z10\_omega\_ma [real]
- constants/c\_lorentz\_ic[real]
- constants/one [real,parameter=1.0\_cp]
- constants/**four** [real,parameter=4.0\_cp]
- constants/sin60 [real,parameter=0.5\_cp\*sqrt(3.0\_cp)]
- constants/**zero** [complex,parameter=(0.0\_cp,0.0\_cp)]
- constants/**surf\_cmb** [real]

  Outer boundary surface
- constants/c\_moi\_oc [real]

  Moment of inertia of the outer core
- constants/three [real,parameter=3.0\_cp]
- constants/c\_dt\_z10\_ic [real]
- constants/c\_z10\_omega\_ic[real]
- constants/**c\_moi\_ic** [real]

  Moment of inertia of the inner core
- constants/c\_moi\_ma [real]

  Moment of inertia of the mantle
- constants/pi [real,parameter=4.0\_cp\*atan(1.0\_cp)]
- constants/osq4pi [real,parameter=1.0\_cp/sq4pi]
- constants/cos36 [real,parameter=cos(36.0 cp\*pi/180.0 cp)]
- constants/y10\_norm[real]

- constants/cos72 [real,parameter=cos(72.0\_cp\*pi/180.0\_cp)]
- constants/sin72 [real,parameter=sin(72.0\_cp\*pi/180.0\_cp)]
- constants/c\_dt\_z10\_ma [real]
- constants/**two** [real,parameter=2.0\_cp]
- constants/half [real,parameter=0.5 cp]
- constants/vol\_oc [real]
  Volume of the outer core
- constants/vol\_ic [real]

  Volume of the inner core
- constants/y11\_norm[real]
- constants/**sq4pi** [real,parameter=sqrt(4.0\_cp\*pi)]
- constants/c\_lorentz\_ma [real]
- constants/third[real,parameter=0.333333333333]
- constants/codeversion[character,parameter='5.6']
- constants/sin36 [real,parameter=sin(36.0\_cp\*pi/180.0\_cp)]
- constants/mass [real]

  Mass of the outer core

# 10.2.10 special.f90

# **Description**

This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes

# **Quick access**

```
Variables lgrenoble, n_imp, l_ri, l_imp, m_riicasym, m_riicsym, m_rimaasym, m_rimasym, l_curr, bic, amp_riicasym, amp_riicsym, amp_rimasym, amp_rimasym, amp_curr, amp_imp, expo_imp, omega_riicasym, omega_riicsym, omega_rimaasym, omega_rimasym, bmax_imp, rrmp, b0, db0, ddb0, fac_loop
```

**Routines** finalize\_grenoble(), initialize\_grenoble()

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- truncation (n\_r\_maxmag()): This module defines the grid points and the truncation

### **Variables**

- special/amp\_rimaasym [real,public]
  Amplitude of forcing at the outer boundary (eq anti symm)
- special/l\_ri[logical,public]

  Decide whether to use inertial-mode forcing
- special/amp\_riicsym[real,public]
  Amplitude of forcing at the inner boundary (eq symm)
- special/lgrenoble [logical, public]
- special/m\_riicasym[integer,public]
   Order of forcing at the inner boundary (eq anti symm)
- special/amp\_curr [real,public]
  Amplitude of magnetic field of current loop
- special/m\_rimaasym[integer,public]

  Order of forcing at the outer boundary (eq anti symm)
- special/fac\_loop(:) [real, allocatable/public]
- special/b0(:)[real,allocatable/public]
- special/amp\_riicasym [real,public]
  Amplitude of forcing at the inner boundary (eq anti symm)
- special/db0 (:) [real,allocatable/public]
- special/ddb0 (:) [real, allocatable/public]
- special/expo\_imp [real,public]
  Exponent for decay
- special/amp\_imp [real,public]
  Amplitude of the time varying osc
- special/omega\_riicsym[real,public]
  Frequency of forcing at the inner boundary (eq symm)
- special/bmax\_imp [real,public]
   Location of maximum in g\_ext/g\_int
- special/**1\_curr** [logical,public]
  Switch for current loop at the equator
- special/m\_rimasym[integer,public]

  Order of forcing at the outer boundary (eq symm)
- special/omega\_riicasym [real,public]
   Frequency of forcing at the inner boundary (eq anti symm)
- special/bic[real,public]
- special/omega\_rimaasym [real,public]
  Frequency of forcing at the outer boundary (eq anti symm)
- special/omega\_rimasym[real,public]
  Frequency of forcing at the outer boundary (eq symm)
- special/m\_riicsym [integer, public]
  Order of forcing at the inner boundary (eq symm)

- special/**rrmp** [real,public]
  Magnetopause radius
- special/n\_imp [integer,public]
   Controls external field model
- special/l\_imp [integer,public]

  Mode of external field (dipole,quadrupole etc.)
- special/amp\_rimasym[real,public]
  Amplitude of forcing at the outer boundary (eq symm)

# 10.3 MPI related modules

# 10.3.1 parallel.f90

### **Description**

This module contains the blocking information

### **Quick access**

### **Needed modules**

- omp\_lib
- mpi

- parallel\_mod/nr\_on\_last\_rank [integer]
- parallel\_mod/rank\_with\_l1m0 [integer]
- parallel\_mod/nthreads [integer]
- parallel\_mod/rank\_bn [integer]
- parallel\_mod/n\_procs [integer]

- parallel\_mod/nlmbs\_per\_rank [integer]
- parallel\_mod/ierr[integer]
- parallel\_mod/nr\_per\_rank [integer]
- parallel\_mod/chunksize [integer]

# **10.3.2** radial\_data.f90

# **Description**

This module defines the MPI decomposition in the radial direction.

#### **Quick access**

```
Variables n_r_cmb, n_r_icb, nrstart, nrstartmag, nrstop, nrstopmag

Routines initialize_radial_data()
```

# Needed modules

- parallel\_mod (nr\_on\_last\_rank(), nr\_per\_rank(), n\_procs(), rank()): This module contains the blocking information
- logic (l\_finite\_diff(), l\_mag(), lverbose()): Module containing the logicals that control the run
- truncation (n\_r\_max()): This module defines the grid points and the truncation

- radial\_data/n\_r\_cmb [integer,public]
- radial\_data/n\_r\_icb [integer,public]
- radial\_data/nrstopmag[integer,public]
- radial\_data/nrstartmag[integer,public]
- radial\_data/nrstop[integer,public]
- radial\_data/nrstart[integer,public]

```
subroutine radial_data/initialize_radial_data()
```

This subroutine is used to set up the MPI decomposition in the radial direction

- Local variable:

Called from magic

# 10.3.3 LMLoop\_data.f90

### **Quick access**

```
Variables 11m, 11mmag, 1m_on_last_rank, 1m_per_rank, ulm, ulmmag
Routines initialize 1mloop data()
```

### **Needed modules**

- parallel\_mod(n\_procs(), nlmbs\_per\_rank(), rank()): This module contains the blocking information
- blocking (sizelmb(), nlmbs(), lmstartb(), lmstopb()): Module containing blocking information
- logic(l\_mag()): Module containing the logicals that control the run

### **Variables**

- lmloop\_data/llmmag[integer,public]
- lmloop\_data/lm\_per\_rank [integer,public]
- lmloop\_data/lm\_on\_last\_rank [integer,public]
- lmloop\_data/ulmmag [integer,public]
- lmloop\_data/llm[integer,public]
- lmloop\_data/ulm [integer, public]

### **Subroutines and functions**

# 10.3.4 communications.f90

#### **Quick access**

```
Variables get_global_sum,
                       r_lm_gather_type, r_lm_gather_type_lm_end,
   final wait array,
                     r_request, s_request, array_of_statuses,
   r_transfer_type,
                      r_transfer_type_nr_end,
                                                 s_transfer_type,
   s_transfer_type_nr_end,
                                              r_transfer_type_cont,
                                              s_transfer_type_cont,
   r_transfer_type_nr_end_cont,
   s_transfer_type_nr_end_cont, gt_cheb, gt_ic, gt_oc, lo2r_field,
   102r_flow, 102r_s, 102r_xi, r210_b, r210_flow, r210_s, r210_xi,
   temp gather lo, temp r2lo
Routines initialize_communications(),
                                         finalize_communications(),
   scatter_from_rank0_to_lo(), lm2lo_redist(), gather_from_lo_to_rank0(),
   1021m_redist(), destroy_gather_type(), destroy_r21m_type(),
                                              r2lm_redist_wait(),
   destroy_lm2r_type(), lm2r_redist_wait(),
                        r2lo_redist_wait(),
   lo2r redist wait().
                                             lm2r redist start().
   gather_all_from_lo_to_rank0(),
                                              lo2r_redist_start(),
                                              create_lm2r_type(),
   r2lm_redist_start(), r2lo_redist_start(),
   myallgather(),
                                         get_global_sum_cmplx_2d(),
   get_global_sum_cmplx_1d(),
   get_global_sum_real_2d()
```

#### **Needed modules**

- mem\_alloc (memwrite(), bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- mpi
- precision\_mod: This module controls the precision used in MagIC
- parallel\_mod (nr\_on\_last\_rank(), nr\_per\_rank(), n\_procs(), ierr(), rank()): This module contains the blocking information
- logic (l\_double\_curl(), l\_chemical\_conv(), l\_mag\_kin(), l\_heat(), l\_tp\_form(), l\_mag(), l\_conv()): Module containing the logicals that control the run
- radial\_data (nrstart (), nrstop ()): This module defines the MPI decomposition in the radial direction.
- blocking (lo\_map(), lmstartb(), st\_map(), lmstopb()): Module containing blocking information
- truncation(n\_r\_ic\_max(), l\_max(), minc(), l\_axi(), n\_r\_max(), lm\_max()): This module defines the grid points and the truncation

# **Types**

• type communications/unknown type

Type fields

- % count [integer]
   % temp\_rloc(,,\*) [complex,pointer]
   % r\_request(\*) [integer,allocatable]
   % arr\_rloc(,,\*) [complex,pointer]
   % final\_wait\_array(\*) [integer,allocatable]
- % s\_request (\*) [integer,allocatable]
- type communications/unknown\_type

# Type fields

- % count [integer]
- % s\_request (\*) [integer,allocatable]
- % final\_wait\_array (\*) [integer,allocatable]
- % temp\_rloc(,,\*)[complex,pointer]
- % r\_request (\*) [integer,allocatable]
- type communications/unknown\_type

#### Type fields

- % dim2 [integer]
- % gather\_mpi\_type (\*) [integer,allocatable]

- communications/r2lo\_xi[r2lm\_type,public]
- communications/s\_transfer\_type\_cont(:,:) [integer,private/allocatable/save]
- communications/r2lo\_flow[r2lm\_type,public]
- communications/**gt\_ic**[gather\_type,public]
- communications/**gt\_oc** [gather\_type,public]
- communications/**get\_global\_sum** [public]
- $\bullet \verb| communications/s_transfer_type| (:) [integer, private/allocatable/save] \\$
- communications/array\_of\_statuses(:,:) [integer,private/allocatable]
- communications/r\_lm\_gather\_type [integer,private]
- communications/s\_transfer\_type\_nr\_end\_cont (:,:) [integer,private/allocatable/save]
- communications/r\_request (:) [integer,private/allocatable]
- communications/r\_transfer\_type (:) [integer,private/allocatable/save]
- communications/final\_wait\_array (:) [integer,private/allocatable]
- communications/s\_request(:) [integer,private/allocatable]
- communications/r\_transfer\_type\_cont(:,:) [integer,private/allocatable/save]
- communications/r2lo\_s [r2lm\_type,public]
- communications/r\_transfer\_type\_nr\_end\_cont (:,:) [integer,private/allocatable/save]

```
• communications/lo2r_xi[lm2r_type,public]
```

- communications/lo2r\_flow [lm2r\_type,public]
- communications/lo2r\_field[lm2r\_type,public]
- communications/r2lo\_b [r2lm\_type,public]
- communications/r\_transfer\_type\_nr\_end(:) [integer,private/allocatable/save]
- communications/s\_transfer\_type\_nr\_end(:) [integer,private/allocatable/save]
- communications/**gt\_cheb** [gather\_type,public]
- communications/r\_lm\_gather\_type\_lm\_end[integer,private]
- communications/lo2r\_s [lm2r\_type,public]
- communications/temp\_r2lo(:,:) [complex,private/allocatable]
- communications/temp\_gather\_lo(:) [complex,private/allocatable]

```
subroutine communications/initialize_communications()
         Called from magic
         Call to create_gather_type(), create_lm2r_type(), create_r2lm_type(),
             memwrite()
subroutine communications/finalize_communications()
         Called from magic
         Call to destroy_gather_type(), destroy_lm2r_type(), destroy_r2lm_type()
function communications/get_global_sum_cmplx_2d(dwdt_local)
         Parameters dwdt_local (,) [complex,in]
         Return global_sum [real]
function communications/get_global_sum_real_2d(dwdt_local)
         Parameters dwdt local (,) [real,in]
         Return global_sum [real]
function communications/get_global_sum_cmplx_1d(arr_local)
         Kahan summation algorithm
         function KahanSum(input) var sum = 0.0 var c = 0.0 for i = 1 to input.length do y = input[i] - c t =
         sum + y
         c = (t - sum) - y
         sum = t
         return sum
         Parameters arr_local (*) [complex,in]
         Return global_sum [real]
```

```
subroutine communications/gather_all_from_lo_to_rank0 (self, arr_lo, arr_full)
         Parameters
              • self [gather_type]
              • arr_lo (ulm-(llm)+1,self%dim2) [complex]
              • arr full (lm max,self%dim2) [complex]
         Called from fields_average(), store(), write_movie_frame(), output(),
             dtb_gather_lo_on_rank0(), costf_arrays()
subroutine communications/create_gather_type (self, dim2)
         Define the datatypes for gather_all_from_lo_to_rank0 the sending array has dimension
         (llm:ulm,1:dim2) receiving array has dimension (1:lm_max,1:dim2)
         Parameters
              • self [gather_type]
              • dim2 [integer]
         Called from initialize communications ()
subroutine communications/destroy_gather_type(self)
         Parameters self [gather type]
         Called from finalize communications ()
subroutine communications/gather_from_lo_to_rank0 (arr_lo, arr_full)
         Parameters
              • arr lo (ulm-(llm)+1) [complex]
              • arr_full (lm_max) [complex]
         Called from fields_average(), write_pot(), get_e_mag(), write_coeff_r(),
             output(), write_bcmb()
subroutine communications/scatter_from_rank0_to_lo(arr_full, arr_lo)
         Parameters
              • arr_full (lm_max) [complex]
              • arr_lo (ulm-(llm)+1) [complex]
         Called from step time(), readstartfields old(), readstartfields()
subroutine communications/create lm2r type(self[, count])
         Parameters self [lm2r_type]
         Options count [integer,in,optional]
         Called from initv(), initialize communications()
subroutine communications/destroy_lm2r_type (self)
         Parameters self [lm2r_type]
         Called from initv(), finalize_communications()
subroutine communications/create r2lm type(self | , count |)
```

```
Parameters self [r2lm_type]
         Options count [integer,in,optional]
         Called from initv(), initialize_dtb_mod(), initialize_communications()
subroutine communications/destroy_r2lm_type(self)
         Parameters self [r2lm type]
         Called from finalize dtb mod(), initv(), finalize communications()
subroutine communications/lm2r_redist_start (self, arr_lmloc, arr_rloc)
         Parameters
               • self [lm2r_type]
               • arr_lmloc (ulm-(llm)+1,n_r_max,*) [complex,in]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out]
         Called from lo2r_redist_start()
subroutine communications/lm2r_redist_wait (self)
         Parameters self [lm2r type]
         Called from 102r redist wait()
subroutine communications/lo2r redist start(self, arr lo, arr rloc)
         Parameters
               • self [lm2r_type]
               • arr_lo (ulm-(llm)+1,n_r_max,*) [complex,in]
               • arr rloc (lm_max,nrstop-(nrstart)+1,*) [complex,out,target]
         Called from getstartfields(), initv(), lmloop()
         Call to lm2r_redist_start()
subroutine communications/lo2r_redist_wait(self)
         Parameters self [lm2r type]
         Called from step time(), initv()
         Call to lm2r_redist_wait()
subroutine communications/r2lm_redist_start(self, arr_rloc, arr_lmloc)
         Parameters
               • self [r2lm_type]
               • arr_rloc (lm_max,nrstop-(nrstart)+1,*) [complex,in]
               • arr_lmloc (ulm-(llm)+1,n_r_max,*) [complex,out]
         Called from r2lo_redist_start()
subroutine communications/r2lm_redist_wait (self)
         Parameters self [r2lm_type]
         Called from r2lo redist wait()
subroutine communications/r2lo_redist_start (self, arr_rloc, arr_lo)
```

### **Parameters**

- **self** [r2lm\_type]
- arr\_rloc (lm\_max,nrstop-(nrstart)+1,\*) [complex,in]
- arr\_lo (ulm-(llm)+1,n\_r\_max,\*) [complex,out]

Called from step\_time(), initv(), dtb\_from\_rloc\_to\_lo()

Call to r2lm redist start()

subroutine communications/r2lo\_redist\_wait(self)

**Parameters self** [r2lm\_type]

Called from step\_time(), initv(), dtb\_from\_rloc\_to\_lo()

Call to r2lm\_redist\_wait()

subroutine communications/lm2lo\_redist(arr\_lmloc, arr\_lo)

### **Parameters**

- arr\_lmloc (ulm-(llm)+1,n\_r\_max) [complex,in]
- arr\_lo (ulm-(llm)+1,n\_r\_max) [complex,out]

Call to abortrun()

subroutine communications/lo21m\_redist(arr\_lo, arr\_lmloc)

#### **Parameters**

- arr\_lo (ulm-(llm)+1,n\_r\_max) [complex,in]
- arr\_lmloc (ulm-(llm)+1,n\_r\_max) [complex,out]

Call to abortrun()

subroutine communications/myallgather(arr, dim1, dim2)

### **Parameters**

- arr (dim1,dim2) [complex,inout]
- dim1 [integer,in,]
- dim2 [integer,in,]

Use parallel\_mod, blocking

### 10.4 Code initialization

### 10.4.1 Namelists.f90

### **Description**

Read and print the input namelist

### **Quick access**

Routines readnamelists(), defaultnamelists(), writenamelists()

### **Needed modules**

- torsional\_oscillations: This module contains information for TO calculation and output
- useful (abortrun ()): library with several useful subroutines
- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- probe\_mod: Module for artificial sensors to compare time series of physical data with experiments. Probes are located in a radially symmetrical way
- movie\_data(movie(), n\_movies(), n\_movies\_max())
- output\_data: This module contains the parameters for output control
- logic: Module containing the logicals that control the run
- precision\_mod: This module controls the precision used in MagIC
- init\_fields: This module is used to construct the initial solution.
- parallel\_mod: This module contains the blocking information
- num\_param: Module containing numerical and control parameters
- physical\_parameters: Module containing the physical parameters
- charmanip (capitalize(), length\_to\_blank()): This module contains several useful routines to manipule character strings
- truncation: This module defines the grid points and the truncation
- blocking (cacheblock\_size\_in\_b()): Module containing blocking information
- constants: module containing constants and parameters used in the code.
- radial\_functions: This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

### **Subroutines and functions**

```
subroutine namelists/readnamelists()
```

Purpose of this subroutine is to read the input namelists. This program also determins logical parameters that are stored in logic.f90.

- Local stuff

```
Called from magic
```

```
Call to defaultnamelists(), abortrun(), length_to_blank(), capitalize(),
   initialize_truncation()
```

```
subroutine namelists/writenamelists(n_out)
```

Purpose of this subroutine is to write the namelist to file unit n\_out. This file has to be open before calling this routine.

– Input variable:

Parameters n\_out [integer,in]

```
Called from magic
```

Call to length\_to\_blank()

### subroutine namelists/defaultnamelists()

Purpose of this subroutine is to set default parameters for the namelists.

– Local variable:

**Called from** readnamelists()

### 10.4.2 startFiels.f90

#### **Quick access**

```
Variables deltaxicond, botcond, topcond, botxicond, topxicond, deltacond Routines getstartfields()
```

- readcheckpoints (readstartfields(), readstartfields\_old()): This module contains the functions that can help reading and mapping of the restart files
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- useful (logwrite(), cc2real()): library with several useful subroutines
- parallel\_mod(n\_procs(), nlmbs\_per\_rank(), rank()): This module contains the blocking information
- communications (lo2r\_field(), lo2r\_xi(), lo2r\_flow(), lo2r\_redist\_start(), lo2r\_s())
- fields: This module contains the potential fields and their radial derivatives
- mpi
- logic (l\_rot\_ic(), l\_chemical\_conv(), l\_anelastic\_liquid(), l\_tp\_form(), l\_z10mat(), l\_lcr(), l\_mag\_kin(), l\_mag(), l\_heat(), l\_srma(), l\_mag\_lf(), l\_single\_matrix(), l\_rot\_ma(), l\_temperature\_diff(), l\_sric(), l\_cond\_ic(), l\_conv()): Module containing the logicals that control the run
- lmloop\_data(llmmag(), lm\_per\_rank(), lm\_on\_last\_rank(), ulm(), llm(), ulmmag())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- init\_fields (initxi(), pt\_cond(), initb(), init\_b1(), l\_start\_file(), tops(), start\_file(), initv(), xi\_cond(), inits(), init\_xi1(), init\_s1(), ps\_cond(), topxi()): This module is used to construct the initial solution.
- radial\_der\_even(get\_ddr\_even())
- constants (one (), osq4pi(), c\_lorentz\_ic(), two(), zero(), c\_lorentz\_ma()): module containing constants and parameters used in the code.
- num\_param(alpha(), dtmax()): Module containing numerical and control parameters

- radial\_der (get\_dr(), get\_ddr()): Radial derivatives functions
- physical\_parameters(imps(), lffac(), impxi(), kbotv(), vischeatfac(), n\_r\_lcr(), ktopv(), imagcon(), interior\_model(), thexpnb(), epss()): Module containing the physical parameters
- radial\_functions (rscheme\_oc(), orhol(), dr\_fac\_ic(), rhol(), dlalphal(), alphal(), orl(), dltempl(), beta(), r(), templ(), chebt\_ic\_even(), otempl(), ogrun(), chebt\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (nlmbs(), lmstartb(), lo\_map(), lmstopb()): Module containing blocking information
- special (lgrenoble()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- truncation: This module defines the grid points and the truncation

- start\_fields/botcond [real,public]
  Conducting heat flux at the inner boundary
- start\_fields/topcond [real,public]
   Conducting heat flux at the outer boundary
- start\_fields/botxicond [real,public]
  Conducting mass flux at the inner boundary
- start\_fields/**deltacond** [real,public]
  Temperature or entropy difference between boundaries
- start\_fields/**deltaxicond** [real,public]
  Composition difference between boundaries
- start\_fields/topxicond [real,public]
  Conducting mass flux at the outer boundary

### Subroutines and functions

```
subroutine start_fields/getstartfields(time, dt, dtnew, n_time_step)
```

Purpose of this subroutine is to initialize the fields and other auxiliary parameters.

— Output variables:

### **Parameters**

- time [real,out]
- **dt** [real,out]
- dtnew [real,out]
- **n\_time\_step** [integer,out]

### Called from magic

### 10.4.3 init fields.f90

### **Description**

This module is used to construct the initial solution.

### **Quick access**

Variables init\_b1, init\_s1, init\_s2, init\_v1, init\_xi1, init\_xi2, nrotic, nrotma, inform, l\_reset\_t, l\_start\_file, n\_s\_bounds, n\_xi\_bounds, start\_file, amp\_b1, amp\_s1, amp\_s2, amp\_v1, amp\_xi1, amp\_xi2, bpeakbot, bpeaktop, omega\_diff, omega\_ic1, omega\_ic2, omega\_ma1, omega\_ma2, omegaosz\_ic1, omegaosz\_ic2, omegaosz\_ma1, omegaosz\_ma2, scale\_b, scale\_s, scale\_v, scale\_xi, tomega\_ic1, tomega\_ic2, tomega\_ma1, tomega\_ma2, tshift\_ic1, tshift\_ic2, tshift\_ma1, tshift\_ma2, tipdipole, bots, botxi, tops, topxi, s\_top, xi\_top, s\_bot, xi\_bot

Routines initialize\_init\_fields(), finalize\_init\_fields(), initb(),
j\_cond(),inits(),ps\_cond(),pt\_cond(),initv(),initxi(),xi\_cond()

- horizontal\_data (hdif\_b(), phi(), dthetala(), dlh(), dthetals(), d\_lp1(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod: This module contains the blocking information
- cosine\_transform\_odd
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- algebra (sgesl(), sgefa(), cgesl())
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- physical\_parameters (n\_imps(), n\_impxi(), sigma\_ratio(), diff\_prec\_angle(), thetaxi(), buofac(), vischeatfac(), ktopp(), ktops(), osc(), impxi(), ktopxi(), epsc(), kbotxi(), o\_sr(), thetas(), widthxi(), kbots(), peaks(), opr(), radratio(), peakxi(), oek(), opm(), phixi(), imps(), n\_impxi\_max(), n\_imps\_max(), epscxi(), widths(), phis(), imagcon(), thexpnb()): Module containing the physical parameters
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(n\_r\_cmb(), nrstart(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- communications (r2lo\_redist\_start(), lo2r\_redist\_wait(), create\_lm2r\_type(), r2lm\_type(), destroy\_r2lm\_type(), lm2r\_type(), destroy\_lm2r\_type(), create\_r2lm\_type(), lo2r\_redist\_start(), r2lo\_redist\_wait())
- legendre\_grid\_to\_spec(legtf1())

- logic (l\_rot\_ic(), l\_anelastic\_liquid(), l\_tp\_form(), l\_chemical\_conv(), l\_cond\_ic(), l\_srma(), l\_rot\_ma(), l\_non\_adia(), l\_temperature\_diff(), l\_sric(), l\_diff\_prec()): Module containing the logicals that control the run
- useful (abortrun (), random ()): library with several useful subroutines
- radial\_functions (jvarcon(), rho0(), or2(), or3(), or1(), ogrun(), temp0(), otemp1(), d2cheb\_ic(), ddltemp0(), dlalpha0(), dlkappa(), cheb\_norm\_ic(), dllambda(), dcheb\_ic(), rgrav(), orho1(), cheb\_ic(), alpha0(), dltemp0(), beta(), chebt\_ic(), kappa(), r\_cmb(), epscprof(), dbeta(), r\_ic(), r(), rscheme\_oc(), r\_icb(), ddlalpha0(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lmstartb(), nthetabs(), sizethetab(), nfs(), lmstopb(), lo\_map(), st\_map()): Module containing blocking information
- constants (osq4pi(), third(), y10\_norm(), c\_z10\_omega\_ma(), two(), one(), four(), zero(), c\_z10\_omega\_ic(), three(), half(), pi()): module containing constants and parameters used in the code.
- truncation (n\_r\_ic\_max(), n\_r\_tot(), n\_cheb\_ic\_max(), minc(), n\_phi\_max(), l\_max(), lmp\_max(), l\_axi(), n\_r\_max(), m\_max(), lm\_max(), nrp(), n\_r\_maxmag(), n\_theta\_max()): This module defines the grid points and the truncation

- init fields/tshift mal[real,public]
- init\_fields/tshift\_ma2 [real,public]
- init\_fields/amp\_b1 [real,public]
- init\_fields/scale\_s [real, public]
- init\_fields/**s\_bot** (80) [real,public] input variables for tops,bots
- init\_fields/init\_b1 [integer,public]
- init\_fields/omegaosz\_ic2 [real,public]
- init\_fields/n\_s\_bounds [integer,parameter=20/public]
- init\_fields/omegaosz\_ic1 [real,public]
- init\_fields/l\_reset\_t [logical,public] reset time from startfile?
- init\_fields/tomega\_ma1 [real, public]
- init\_fields/tomega\_ma2 [real,public]
- init\_fields/xi\_top(80)[real,public]
- init\_fields/scale\_xi[real,public]
- init\_fields/scale\_b[real,public]
- init\_fields/omega\_diff[real,public]
- init\_fields/**1\_start\_file** [logical,public] taking fields from startfile ?
- init\_fields/omega\_ic1 [real,public]

- init\_fields/omega\_ic2 [real, public]
- init\_fields/init\_v1[integer,public]
- init\_fields/scale\_v [real, public]
- init\_fields/amp\_v1 [real, public]
- init fields/init s1[integer,public]
- init\_fields/**tipdipole** [real,public] adding to symetric field
- init\_fields/init\_xi1 [integer,public]
- init\_fields/tomega\_ic2 [real,public]
- init\_fields/tomega\_ic1 [real,public]
- init\_fields/init\_xi2 [integer,public]
- init\_fields/tops(:,:) [complex,allocatable/public]
- init\_fields/nrotma[integer,public]
- init\_fields/omega\_ma1 [real,public]
- init\_fields/omega\_ma2 [real,public]
- init\_fields/**xi\_bot** (80) [real,public] input variables for topxi,botxi
- init\_fields/bpeaktop[real,public]
- init\_fields/tshift\_ic2 [real,public]
- init\_fields/tshift\_ic1 [real,public]
- init\_fields/**s\_top** (80) [real,public]
- init\_fields/amp\_xi2 [real,public]
- init\_fields/topxi(:,:) [complex,allocatable/public]
- init\_fields/n\_xi\_bounds [integer,parameter=20/public]
- init\_fields/amp\_xi1 [real,public]
- init\_fields/inform[integer,public] format of start file
- init\_fields/bpeakbot [real,public]
- init\_fields/botxi(:,:) [complex,allocatable/public]
- init\_fields/amp\_s2 [real,public]
- init\_fields/omegaosz\_ma1 [real,public]
- init\_fields/omegaosz\_ma2 [real,public]
- init\_fields/amp\_s1 [real, public]
- init\_fields/init\_s2 [integer,public]
- init\_fields/bots(:,:) [complex,allocatable/public]
- init\_fields/nrotic[integer,public]

init\_fields/start\_file [character,public]
 name of start file

### Subroutines and functions

subroutine init\_fields/initv(w, z, omega\_ic, omega\_ma)

Purpose of this subroutine is to initialize the velocity field So far it is only rudimentary and will be expanded later. Because s is needed for dwdt init\_s has to be called before.

- Output variables

#### **Parameters**

- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,inout]
- omega\_ic [real,out]
- omega\_ma [real,out]

Called from getstartfields()

```
Call to create_r2lm_type(), create_lm2r_type(), lo2r_redist_start(),
    lo2r_redist_wait(), fft_thetab(), legtf1(), r2lo_redist_start(),
    r2lo_redist_wait(), destroy_r2lm_type(), destroy_lm2r_type(),
    random()
```

```
subroutine init_fields/inits(s, p)
```

Purpose of this subroutine is to initialize the entropy field according to the input control parameters.

- Output variables:

### **Parameters**

- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]

Called from getstartfields()

```
subroutine init_fields/initxi(xi)
```

Purpose of this subroutine is to initialize the chemical composition according to the input control parameters.

- Output variables:

```
Parameters xi (ulm-(llm)+1,n_r_max) [complex,inout]

Called from getstartfields()
```

```
subroutine init_fields/initb(b, aj, b_ic, aj_ic, lorentz_torque_ic, lorentz_torque_ma)
```

Purpose of this subroutine is to initialize the magnetic field according to the control parameters imageon and init\_b1/2. In addition CMB and ICB peak values are calculated for magneto convection.

- Output variables:

#### **Parameters**

- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_max*) [*complex,inout*]
- $aj\_ic$  (ulmmag-(llmmag)+1, $n\_r\_ic\_max$ ) [complex,inout]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]

```
Called from getstartfields()
```

```
Call to j_cond(), abortrun(), random()
```

```
subroutine init_fields/j_cond(lm0, aj0, aj0_ic)
```

Purpose of this subroutine is to solve the diffusion equation for an initial toroidal magnetic field.

– Input variable:

### **Parameters**

- lm0 [integer,in]
- **ai0** (\*) [complex,out]
- **aj0\_ic** (\*) [complex,out]

Called from initb()

```
Call to sgefa(), abortrun(), cgesl()
```

```
subroutine init_fields/xi_cond(xi0)
```

Purpose of this subroutine is to solve the chemical composition equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in s0.

```
Parameters xi0 (*) [real,out]
```

```
Called from getstartfields(), initxi()
```

```
Call to sgefa(), abortrun(), sgesl()
```

```
\verb"subroutine" init\_fields/pt\_cond" (\it{t0}, \it{p0})
```

Purpose of this subroutine is to solve the entropy equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in t0 and p0.

### **Parameters**

- **t0** (\*) [real,out]
- **p0** (\*) [real,out]

```
Called from getstartfields(), inits()
Call to sgefa(), abortrun(), sgesl()
```

**subroutine** init\_fields/**ps\_cond**(s0, p0)

Purpose of this subroutine is to solve the entropy equation for an the conductive (l=0,m=0)-mode. Output is the radial dependence of the solution in s0 and p0.

#### **Parameters**

- **s0** (\*) [real,out]
- **p0** (\*) [real,out]

Called from getstartfields(), inits()

Call to sgefa(), abortrun(), sgesl()

### 10.5 Pre-calculations

### 10.5.1 preCalc.f90

### **Quick access**

```
Routines precalc(), writeinfo(), get_hit_times(), precalctimes()
```

### **Needed modules**

- horizontal\_data (horizontal()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod (rank ()): This module contains the blocking information
- useful (abortrun(), logwrite()): library with several useful subroutines
- output\_data: This module contains the parameters for output control
- logic (l\_time\_hits(), l\_to(), l\_newmap(), l\_storetpot(), l\_heat(), l\_mag\_lf(), l\_mag(), l\_non\_rot(), l\_anelastic\_liquid(), l\_tomovie(), l\_cond\_ic(), l\_storevpot(), l\_anel(), l\_non\_adia(), l\_storevpot(), l\_probe(), l\_lcr(), l\_movie(), l\_cmb\_field(), l\_chemical\_conv(), l\_precession(), l\_storepot(), l\_r\_field(), l\_diff\_prec(), l\_save\_out(), l\_temperature\_diff(), l\_dt\_cmb\_field()): Module containing the logicals that control the run
- integration (rint\_r()): Radial integration functions
- precision\_mod: This module controls the precision used in MagIC
- init\_fields (s\_top(), omega\_diff(), topxi(), n\_xi\_bounds(), tops(), s\_bot(), botxi(), l\_reset\_t(), xi\_bot(), n\_s\_bounds(), bots(), xi\_top()): This module is used to construct the initial solution.
- special (fac\_loop(), l\_curr()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num param: Module containing numerical and control parameters

10.5. Pre-calculations 223

- physical\_parameters (polind(), lffac(), ek(), epsc0(), tmagcon(), ktops(), epscxi0(), rho\_ratio\_ic(), osc(), pr(), sigma\_ratio(), ktopxi(), grunnb(), epsc(), chemfac(), kbotxi(), ra(), n\_r\_lcr(), o\_sr(), rho\_ratio\_ma(), nvardiff(), po(), diff\_prec\_angle(), buofac(), kbots(), opr(), radratio(), oek(), sc(), nvareps(), opm(), nvarvisc(), raxi(), prmag(), r\_lcr(), epscxi(), corfac(), mode(), interior\_model(), nvarcond(), ekscaled(), prec\_angle(), rascaled()): Module containing the physical parameters
- radial\_functions(rho0(), dlvisc(), dentropy0(), ogrun(), rscheme\_oc(), dlkappa(), transportproperties(), dllambda(), r(), rgrav(), r\_surface(), alpha0(), visc(), beta(), divktemp0(), kappa(), r\_cmb(), dbeta(), temp0(), radial(), r\_icb(), sigma(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- constants: module containing constants and parameters used in the code.
- truncation(n\_r\_ic\_max(), n\_cheb\_ic\_max(), minc(), n\_phi\_max(), l\_max(), nalias(), n\_r\_max(), m\_max(), lm\_max(), n\_cheb\_max(), n\_theta\_max()): This module defines the grid points and the truncation

### Subroutines and functions

```
subroutine precalculations/precalc()
```

Purpose of this subroutine is to initialize the calc values, arrays, constants that are used all over the code. The stuff is stored in the common blocks. MPI: This is called by every processors.

—- Local variables:

```
Called from magic
```

```
Call to radial(), transportproperties(), horizontal(), rint_r(),
    abortrun(), logwrite()
```

subroutine precalculations/precalctimes (time, n\_time\_step)

Precalc. after time, time and dthas been read from startfile.

- Output variables

### **Parameters**

- time [real,out]
- **n\_time\_step** [integer,out]

Called from magic

```
Call to get_hit_times()
```

**subroutine** precalculations/**get\_hit\_times** (t,  $n\_t\_max$ ,  $n\_t$ ,  $l\_t$ ,  $t\_start$ ,  $t\_stop$ , dt,  $n\_tot$ ,  $n\_step$ ,  $string\_bn$ , time, tscale)

### **Parameters**

- $t (n_t_max) [real,inout] :: Times for output$
- **n t max** [integer,in,] :: Dimension of t(\*)
- **n\_t** [integer,out] :: No. of output times

```
• l_t [logical,out] :: =.true. if output times are defined
```

- t\_start [real,inout] :: Starting time for output
- **t\_stop** [real,inout] :: Stop time for output
- **dt** [real,inout] :: Time step for output
- **n** tot [integer,inout]:: No. of output (times) if no times defined
- n step [integer,inout] :: Ouput step in no. of time steps
- **string\_bn** [character,in]
- **time** [real,in] :: Time of start file
- tscale [real,in]

```
Called from precalctimes ()
```

Call to abortrun()

```
subroutine precalculations/writeinfo(n_out)
```

Purpose of this subroutine is to write the namelist to file unit n\_out. This file has to be open before calling this routine.

- Input variable:

```
Parameters n_out [integer,in]
Called from magic
```

Call to abortrun()

### 10.5.2 radial.f90

### **Description**

This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Quick access**

```
Variables ndd_costf1, ndd_costf1_ic, ndd_costf2_ic, ndi_costf1_ic, ndi_costf2_ic, chebt_ic, chebt_ic_even, cheb_norm_ic, dr_fac_ic, r_icb, alpha2, alpha1, r_cmb, r_surface, d2temp0, alpha0, beta, cheb_int, cheb_int_ic, dbeta, ddbeta, ddlalpha0, ddltemp0, ddlvisc, dentropy0, divktemp0, dlalpha0, dlkappa, dllambda, dltemp0, dlvisc, epscprof, jvarcon, kappa, lambda, o_r_ic, o_r_ic2, ogrun, or1, or2, or3, or4, orho1, orho2, otemp1, r, r_ic, rgrav, rho0, sigma, temp0, visc, cheb_ic, d2cheb_ic, dcheb_ic
```

```
Routines finalize_radial_functions(), initialize_radial_functions(), transportproperties(), radial(), getentropygradient(), polynomialbackground(), getbackground()
```

### **Needed modules**

- chebyshev (type\_cheb\_odd())
- parallel\_mod (rank ()): This module contains the blocking information

10.5. Pre-calculations 225

- cosine transform odd
- useful (abortrun(), logwrite()): library with several useful subroutines
- algebra (sgesl(), sgefa())
- output\_data(tag()): This module contains the parameters for output control
- finite\_differences (type\_fd()): This module is used to calculate the radial grid when finite differences are requested
- radial\_der (get\_dr()): Radial derivatives functions
- radial\_scheme (type\_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- num\_param (alph1(), alph2()): Module containing numerical and control parameters
- cosine\_transform\_even
- logic(l\_newmap(), l\_anelastic\_liquid(), l\_finite\_diff(), l\_temperature\_diff(), l\_mag(), l\_heat(), l\_single\_matrix(), l\_anel(), l\_non\_adia(), l\_tp\_form(), l\_cond\_ic(), l\_isothermal()): Module containing the logicals that control the run
- chebyshev\_polynoms\_mod
- physical\_parameters: Module containing the physical parameters
- constants (four (), three (), two (), sq4pi (), half (), one ()): module containing constants and parameters used in the code.
- truncation (n\_r\_ic\_max(), fd\_order(), n\_r\_max(), fd\_stretch(), fd\_order\_bound(), n\_cheb\_max(), fd\_ratio()): This module defines the grid points and the truncation

- radial\_functions/**r**(:) [real,allocatable/public]
- radial\_functions/cheb\_norm\_ic [real,public]
   Chebyshev normalisation for IC
- radial\_functions/or4 (:) [real,allocatable/public]
- radial\_functions/rho0 (:) [real,allocatable/public]
- radial\_functions/or2 (:) [real,allocatable/public]
- radial\_functions/or3(:)[real,allocatable/public]
- radial\_functions/or1 (:) [real,allocatable/public]
- radial\_functions/otemp1 (:) [real,allocatable/public]
- radial\_functions/temp0 (:) [real,allocatable/public]
- radial\_functions/dentropy0(:)[real,allocatable/public]
- radial\_functions/o\_r\_ic(:) [real,allocatable/public]
- radial\_functions/ogrun (:) [real,allocatable/public]
- radial\_functions/**dbeta**(:)[real,allocatable/public]

- radial\_functions/alpha2 [real,public]
  Input parameter for non-linear map to define central point of different spacing (-1.0:1.0)
- radial\_functions/ddltemp0(:)[real,allocatable/public]
- radial\_functions/alpha1 [real,public]
  Input parameter for non-linear map to define degree of spacing (0.0:2.0)
- radial\_functions/dlalpha0(:) [real,allocatable/public]
- radial\_functions/dlkappa (:) [real,allocatable/public]
- radial\_functions/ndd\_costf1 [integer,public]
   Radii for transform
- radial\_functions/jvarcon(:) [real,allocatable/public]
- radial\_functions/ndi\_costf2\_ic [integer,public]
  Radii for transform
- radial\_functions/**dllambda**(:)[real,allocatable/public]
- radial\_functions/dcheb\_ic(:,:) [real,allocatable/public]
- radial\_functions/rgrav(:) [real,allocatable/public]
- radial\_functions/cheb\_int (:) [real,allocatable/public]
- radial\_functions/**r\_surface** [real,public]
  Surface radius for extrapolation
- radial\_functions/cheb\_int\_ic(:) [real,allocatable/public]
- radial\_functions/**d2cheb\_ic**(:,:) [real,allocatable/public]
- radial\_functions/orho1 (:) [real,allocatable/public]
- radial\_functions/**ddlvisc**(:) [real,allocatable/public]
- radial\_functions/d2temp0 (:) [real,allocatable/private]
- radial\_functions/cheb\_ic(:,:) [real,allocatable/public]
- radial\_functions/ $dr_fac_ic[real,public]$ For IC:  $2/(2r_i)$
- radial\_functions/ndi\_costfl\_ic [integer,public]
   Radii for transform
- radial\_functions/alpha0(:) [real,allocatable/public]
- radial functions/dltemp0(:) [real, allocatable/public]
- radial\_functions/**beta**(:)[real,allocatable/public]
- radial\_functions/chebt\_ic\_even[costf\_even\_t,public]
- radial\_functions/**ddbeta**(:)[real,allocatable/public]
- radial\_functions/ddlalpha0(:) [real,allocatable/public]
- radial\_functions/chebt\_ic[costf\_odd\_t,public]
- radial\_functions/divktemp0 (:) [real,allocatable/public]
- radial\_functions/r\_ic(:) [real,allocatable/public]
- radial\_functions/kappa (:) [real,allocatable/public]

10.5. Pre-calculations 227

• radial\_functions/r\_cmb [real,public]

```
OC radius
   • radial_functions/visc(:) [real,allocatable/public]
   • radial_functions/o_r_ic2 (:) [real,allocatable/public]
   • radial functions/epscprof(:) [real, allocatable/public]
   • radial_functions/ndd_costf2_ic[integer,public]
         Radii for transform
   • radial_functions/orho2 (:) [real,allocatable/public]
   • radial_functions/dlvisc(:) [real,allocatable/public]
   • radial_functions/r_icb [real, public]
         IC radius
   • radial_functions/ndd_costf1_ic[integer,public]
         Radii for transform
   • radial functions/sigma(:) [real, allocatable/public]
   • radial functions/lambda (:) [real, allocatable/public]
Subroutines and functions
subroutine radial_functions/initialize_radial_functions()
     Initial memory allocation
         Called from magic
subroutine radial_functions/finalize_radial_functions()
         Called from magic
subroutine radial_functions/radial()
         Calculates everything needed for radial functions, transforms etc.
     - Local variables:
         Called from precalc()
         Call to getentropygradient(), getbackground(), polynomialbackground(),
             logwrite(), cheb_grid(), get_chebs_even()
subroutine radial functions/transportproperties()
     Calculates the transport properties: electrical conductivity, kinematic viscosity and thermal conductivity.
         Called from precalc()
         Call to abortrun()
subroutine radial_functions/getentropygradient()
     This subroutine allows to calculate the background entropy gradient in case stable stratification is required
         Called from radial()
subroutine radial_functions/getbackground(input, boundaryval, output |, coeff |)
         Linear solver of the form: df/dx +coeff*f= input with f(1)=boundaryVal
     - Input variables:
```

### **Parameters**

```
• input (n_r_max) [real,in]
```

• boundaryval [real,in]

• **output** (*n*\_*r*\_*max*) [*real*,*out*]

**Options coeff**  $(n\_r\_max)$  [real,in,optional]

Called from radial()

Call to sgefa(), abortrun(), sgesl()

**subroutine** radial\_functions/**polynomialbackground**(coeffdens, coefftemp)

This subroutine allows to calculate a reference state based on an input polynomial function.

- Input variables

### **Parameters**

- coeffdens (\*) [real,in]
- coefftemp (\*) [real,in]

Called from radial()

### 10.5.3 horizontal.f90

### **Description**

Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

### **Quick access**

```
Variables lmodd, lmoddp, lstart, lstartp, lstop, lstopp, n_theta_cal2ord, cosn2, costheta, d_l, d_lpl, d_m, d_mc2m, dlh, dphi, dphi0, dphi02, dpl0eq, dthetala, dthetals, dtheta2a, dtheta2s, dtheta3a, dtheta3s, dtheta4a, dtheta4s, gauss, hdif_b, hdif_s, hdif_v, hdif_xi, o_sin_theta, o_sin_theta_e2, osn1, osn2, phi, sintheta, sn2, theta, theta_ord, dplm, plm, wdplm, wplm
```

```
Routines initialize_horizontal_data(), finalize_horizontal_data(), horizontal(), gauleg()
```

### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- num\_param (difchem(), difeta(), difnu(), ldif(), ldifexp(), difkap()): Module containing numerical and control parameters
- precision\_mod: This module controls the precision used in MagIC
- plms\_theta(plm\_theta())
- logic(l\_rms(), l\_non\_rot()): Module containing the logicals that control the run

10.5. Pre-calculations 229

- physical\_parameters (ek ()): Module containing the physical parameters
- truncation (l\_max(), minc(), n\_phi\_max(), lmp\_max(), l\_axi(), n\_m\_max(), m\_max(), lm\_max(), n\_theta\_max()): This module defines the grid points and the truncation
- blocking (1mp21(), 1m2m(), 1m21(), 1mp21m()): Module containing blocking information
- constants (zero(), pi(), two(), half(), one()): module containing constants and parameters used in the code.
- radial\_functions (r\_cmb()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- horizontal\_data/dplm(:,:) [real,allocatable/public]
- horizontal\_data/dphi02(:)[complex,allocatable/public]
- horizontal\_data/osn1 (:) [real,allocatable/public]
- horizontal\_data/osn2 (:) [real,allocatable/public]
- horizontal\_data/sn2(:)[real,allocatable/public]
- horizontal\_data/o\_sin\_theta(:)[real,allocatable/public]
- horizontal\_data/dphi(:)[complex,allocatable/public]
- horizontal\_data/lstopp (:) [integer,allocatable/public]
- horizontal\_data/hdif\_xi(:) [real,allocatable/public]
- horizontal\_data/costheta(:)[real,allocatable/public]
- horizontal\_data/hdif\_b(:) [real,allocatable/public]
- horizontal\_data/lstop(:)[integer,allocatable/public]
- horizontal\_data/dphi0(:)[complex,allocatable/public]
- horizontal\_data/dtheta4a(:)[real,allocatable/public]
- horizontal\_data/lmodd(:)[logical,allocatable/public]
- horizontal\_data/dlh(:) [real,allocatable/public]
- horizontal\_data/dtheta3s(:)[real,allocatable/public]
- horizontal data/dtheta2a(:)[real,allocatable/public]
- horizontal\_data/hdif\_s (:) [real,allocatable/public]
- horizontal\_data/hdif\_v(:) [real,allocatable/public]
- horizontal\_data/dtheta4s(:)[real,allocatable/public]
- horizontal\_data/theta(:)[real,allocatable/public]
- horizontal\_data/dtheta2s(:)[real,allocatable/public]
- horizontal\_data/lstart (:) [integer,allocatable/public]
- horizontal\_data/**phi** (:) [real,allocatable/public]
- horizontal\_data/theta\_ord(:) [real,allocatable/public]
- horizontal data/d mc2m(:) [real, allocatable/public]

- horizontal\_data/plm(:,:) [real,allocatable/public]
- horizontal\_data/o\_sin\_theta\_e2 (:) [real,allocatable/public]
- horizontal\_data/gauss(:) [real,allocatable/public]
- horizontal\_data/wplm(:,:) [real,allocatable/public]
- horizontal\_data/d\_lp1(:) [real,allocatable/public]
- horizontal\_data/lstartp(:) [integer,allocatable/public]
- horizontal\_data/dtheta3a(:)[real,allocatable/public]
- horizontal\_data/cosn2 (:) [real,allocatable/public]
- horizontal\_data/dthetala(:)[real,allocatable/public]
- horizontal\_data/dpl0eq(:) [real,allocatable/public]
- horizontal\_data/lmoddp (:) [logical,allocatable/public]
- horizontal\_data/**d\_1**(:) [real,allocatable/public]
- horizontal\_data/wdplm(:,:) [real,allocatable/public]
- horizontal\_data/dthetals(:)[real,allocatable/public]
- horizontal\_data/n\_theta\_cal2ord(:) [integer,allocatable/public]
- horizontal\_data/d\_m(:) [real,allocatable/public]
- horizontal\_data/sintheta(:)[real,allocatable/public]

### Subroutines and functions

Calculates functions of theta and phi, for exmample the Legendre functions, and functions of degree l and order m of the legendres.

- Local variables:

Subroutine is based on a NR code. Calculates N zeros of legendre polynomial P(l=N) in the interval [sinThMin,sinThMax]. Zeros are returned in radiants theta\_ord(i) The respective weights for Gauss-integration are given in gauss(i).

- Input variables:

#### **Parameters**

• **sinthmin** [real,in] :: lower bound in radiants

10.5. Pre-calculations 231

- **sinthmax** [real,in] :: upper bound in radiants
- **theta\_ord** (n\_th\_max) [real,out] :: zeros cos(theta)
- gauss (n\_th\_max) [real,out] :: associated Gauss-Legendre weights
- n\_th\_max [integer,in] :: desired maximum degree

Called from horizontal()

## 10.6 Time stepping

### 10.6.1 step\_time.f90

### **Quick access**

Variables sigfile, dbdt\_cmb\_lmloc, dbdt\_lmloc, dbdt\_rloc, djdt\_lmloc, djdt\_rloc, dpdt\_lmloc, dpdt\_rloc, dsdt\_lmloc, dsdt\_rloc, dvprlm\_lmloc, dvprlm\_rloc, dvsrlm\_rloc, dvsrlm\_rloc, dvxbhlm\_lmloc, dvxbhlm\_rloc, dvxirlm\_lmloc, dvxirlm\_lmloc, dvxvhlm\_lmloc, dvxvhlm\_rloc, dwdt\_lmloc, dwdt\_lmloc, dxidt\_lmloc, dxidt\_rloc, dzdt\_lmloc, dzdt\_rloc, dbdt\_lmloc\_container, dbdt\_rloc\_container, dflowdt\_lmloc\_container, dsdt\_lmloc\_container, dxidt\_lmloc\_container, dxidt\_lmloc\_container, dxidt\_rloc\_container

Routines finalize\_step\_time(), initialize\_step\_time(), check\_time\_hits(),
 step\_time()

- movie\_data(t\_movies())
- useful (abortrun(), 1\_correct\_step(), logwrite()): library with several useful subroutines
- probe\_mod: Module for artificial sensors to compare time series of physical data with experiments. Probes are located in a radially symmetrical way
- lmloop mod(lmloop())
- lmloop\_data(llmmag(), lm\_per\_rank(), lm\_on\_last\_rank(), ulm(), llm(), ulmmag())
- timing: Useful functions for time-stepping
- output\_mod(output())
- radialloop(radialloopg())
- parallel\_mod: This module contains the blocking information
- constants (zero(), half(), one()): module containing constants and parameters used in the code.
- num\_param (tscale(), n\_time\_steps(), tend(), runtimelimit(), alpha(), dtmax(), dtmin(), runtime()): Module containing numerical and control parameters
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.

- logic (l\_probe(), l\_time\_hits(), l\_hel(), l\_to(), l\_dtrmagspec(), l\_storetpot(), lverbose(), l\_heat(), l\_mag\_lf(), l\_perppar(), l\_b\_nl\_icb(), l\_abl(), l\_tomovie(), l\_double\_curl(), l\_mag(), l\_dtbmovie(), l\_htmovie(), l\_storevpot(), l\_runtimelimit(), l\_fluxprofs(), l\_storebpot(), l\_viscbccalc(), l\_conv(), l\_pressgraph(), l\_movie(), l\_cmb\_field(), l\_true\_time(), l\_chemical\_conv(), l\_mag\_kin(), l\_ht(), l\_power(), l\_dt\_cmb\_field(), l\_dtb(), l\_save\_out(), l\_b\_nl\_cmb(), l\_tp\_form(), l\_rms(), l\_r\_field()): Module containing the logicals that control the run
- precision\_mod: This module controls the precision used in MagIC
- courant\_mod(dt\_courant())
- charmanip (dble2str(), capitalize()): This module contains several useful routines to manipule character strings
- blocking (nlmbs(), lmstartb(), lmstopb()): Module containing blocking information
- nonlinear\_bcs(get\_b\_nl\_bcs())
- truncation (1\_max(), 1m\_maxmag(), 1mp\_max(), 1\_maxmag(), n\_r\_max(), 1m\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- mem\_alloc(bytes\_allocated(), memwrite()): This little module is used to estimate the global memory allocation used in MagIC
- radial\_data (n\_r\_cmb(), n\_r\_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- communications (lo2r\_field(), r2lo\_redist\_start(), lo2r\_redist\_wait(), r2lo\_xi(), lm2r\_type(), lo2r\_xi(), r2lm\_type(), lo2r\_flow(), scatter\_from\_rank0\_to\_lo(), r2lo\_flow(), r2lo\_b(), r2lo\_s(), get\_global\_sum(), lo2r s(), r2lo redist wait())
- fields: This module contains the potential fields and their radial derivatives

- step\_time\_mod/dvxirlm\_lmloc(:,:) [complex,private/pointer]
- step\_time\_mod/dzdt\_lmloc(:,:) [complex,private/pointer]
- step\_time\_mod/dsdt\_lmloc\_container (:,:,:) [complex,private/target/allocatable]
- step\_time\_mod/**djdt\_rloc** (:,:) [complex,private/pointer]
- step\_time\_mod/**dpdt\_rloc** (:,:) [complex,private/pointer]

- step\_time\_mod/dsdt\_rloc(:,:) [complex,private/pointer] step\_time\_mod/dbdt\_lmloc\_container (:,:,:) [complex,private/target/allocatable] • step\_time\_mod/**dbdt\_rloc\_container** (:,;,:) [complex,private/target/allocatable] • step\_time\_mod/dxidt\_lmloc(:,:) [complex,private/pointer] • step time mod/dflowdt lmloc container (:,;;) [complex,private/target/allocatable] • step time mod/dzdt rloc(:,:) [complex,private/pointer] • step\_time\_mod/**dpdt\_lmloc** (:,:) [complex,private/pointer] • step\_time\_mod/dwdt\_lmloc(:,:) [complex,private/pointer] • step\_time\_mod/dvsrlm\_rloc(:,:) [complex,private/pointer] step\_time\_mod/dxidt\_rloc\_container(:,:,:) [complex,private/target/allocatable] • step\_time\_mod/dxidt\_rloc(:,:) [complex,private/pointer] • step\_time\_mod/dvxbhlm\_rloc(:,:) [complex,private/pointer] • step\_time\_mod/dbdt\_lmloc(:,:) [complex,private/pointer] • step\_time\_mod/sigfile [integer,private] • step\_time\_mod/dvprlm\_rloc(:,:) [complex,private/pointer] • step time mod/dvsrlm lmloc(:,:) [complex,private/pointer] • step\_time\_mod/dvprlm\_lmloc(:,:) [complex,private/pointer] • step\_time\_mod/**dbdt\_rloc** (:,:) [complex,private/pointer] • step\_time\_mod/dwdt\_rloc(:,:) [complex,private/pointer] • step\_time\_mod/dvxvhlm\_lmloc(:,:) [complex,private/pointer] • step\_time\_mod/dsdt\_lmloc(:,:) [complex,private/pointer] • step\_time\_mod/dflowdt\_rloc\_container(:,;,;) [complex,private/target/allocatable] • step\_time\_mod/dxidt\_lmloc\_container(:,:,:) [complex,private/target/allocatable] • step time mod/dvxvhlm rloc(:,:) [complex,private/pointer]
- step\_time\_mod/dvxbhlm\_lmloc(:,:) [complex,private/pointer]
- step\_time\_mod/dsdt\_rloc\_container(:,:,;) [complex,private/target/allocatable]
- step\_time\_mod/dvxirlm\_rloc(:,:) [complex,private/pointer]
- step\_time\_mod/dbdt\_cmb\_lmloc(:) [complex,private/allocatable]
- step\_time\_mod/djdt\_lmloc(:,:) [complex,private/pointer]

### Subroutines and functions

#### Called from magic

```
subroutine step_time_mod/step_time(time, dt, dtnew, n_time_step)
```

This subroutine performs the actual time-stepping.

- Input from initialization: time and n\_time\_step updated and returned to magic.f

#### **Parameters**

- time [real,inout]
- **dt** [real,inout]
- dtnew [real,inout]
- n\_time\_step [integer,inout]

### Called from magic

```
Call to walltime(), lo2r_redist_wait(), capitalize(), time2ms(),
    ms2time(), ltimelimit(), logwrite(), l_correct_step(), dble2str(),
    radialloopg(), lnegtime(), subtime(), addtime(), r2lo_redist_start(),
    r2lo_redist_wait(), scatter_from_rank0_to_lo(), output(),
    get_b_nl_bcs(), dt_courant(), check_time_hits(), abortrun(),
    lmloop(), meantime(), writetime()
```

**subroutine** step\_time\_mod/**check\_time\_hits**(*l\_new\_dt*, *time*, *dt*, *dt\_new*)

Checks whether a certain dt is required to hit a specific output-time.

- Output: ev. modified dt

### **Parameters**

- l\_new\_dt [logical,out] :: signfies change of dt !
- time [real,inout]
- **dt** [real,inout]
- dt\_new [real,inout]

Called from step\_time()

### 10.6.2 courant.f90

### **Quick access**

```
Routines dt courant(), courant()
```

- horizontal\_data(osn2()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- useful (logwrite()): library with several useful subroutines

- logic(l\_cour\_alf\_damp(), l\_mag(), l\_mag\_kin(), l\_mag\_lf()): Module containing the logicals that control the run
- radial\_data (nrstart (), nrstop ()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- num\_param(delxh2(), delxr2(), courfac(), alffac()): Module containing numerical and control parameters
- physical\_parameters (opm(), 1ffac()): Module containing the physical parameters
- truncation (nrp(), n\_phi\_max()): This module defines the grid points and the truncation
- blocking (nfs ()): Module containing blocking information
- constants (one (), two (), half ()): module containing constants and parameters used in the code.
- radial\_functions (or2(), or4(), orho1(), orho2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### Subroutines and functions

**subroutine** courant\_mod/**courant**( $n_r$ , dtrkc, dthkc, vr, vt, vp, br, bt, bp,  $n_theta_min$ ,  $n_theta_block$ )

### **Parameters**

- **n r** [integer,in] :: radial level
- **dtrkc** [real,inout] :: Courant step (based on radial advection)
- dthkc [real,inout] :: Courant step based on horizontal advection
- vr (nrp,nfs) [real,in] :: radial velocity
- vt (nrp,nfs) [real,in] :: longitudinal velocity
- **vp** (*nrp*,*nfs*) [*real*,*in*] :: azimuthal velocity
- **br** (*nrp*,*nfs*) [real,in] :: radial magnetic field
- **bt** (*nrp*,*nfs*) [*real*,*in*] :: longitudinal magnetic field
- **bp** (nrp,nfs) [real,in] :: azimuthal magnetic field
- n\_theta\_min [integer,in] :: first theta in block stored in fields
- n\_theta\_block [integer,in] :: size of theta block

Called from do\_iteration\_thetablocking\_openmp(), do\_iteration\_thetablocking\_seq(),
 do iteration thetablocking shtns()

**subroutine** courant\_mod/**dt\_courant**( $dt_r$ ,  $dt_h$ ,  $l_new_dt$ , dt,  $dt_new$ , dtmax, dtrkc, dthkc)

Check if Courant criterion based on combined fluid and Alfven velocity is satisfied Returns new value of time step dtnew

dtr,dth: (output) radial/horizontal Courant time step n\_time\_step: (input) time step number l\_new\_dt: (output) flag indicating that time step is changed (=1) or not (=0) dt: (input) old time step dtnew: (output) new time step dtMin: (input) lower limit for time step (termination if dtnew < dtMin) dtMax:

(input) upper limit for time step dtrkc: (input) radial Courant time step as function of radial level dthkc: (input) horizontal Courant time step as function of radial level

### - Input variables:

### **Parameters**

- **dt r** [real,out]
- **dt\_h** [real,out]
- l\_new\_dt [logical,out]
- dt [real,in]
- dt\_new [real,out]
- dtmax [real,in]
- dtrkc (nrstop-(nrstart)+1) [real,in]
- **dthkc** (*nrstop*-(*nrstart*)+1) [real,in]

```
Called from step_time()
Call to logwrite()
```

### 10.6.3 timing.f90

### **Description**

Useful functions for time-stepping

### **Quick access**

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- parallel\_mod (rank ()): This module contains the blocking information
- mpi

### **Variables**

- timing/msechour [integer,private/parameter=3600000]
- timing/msecsecond [integer, private/parameter=1000]
- timing/msecminute[integer,private/parameter=60000]

### Subroutines and functions

```
subroutine timing/walltime(time)
```

This routine returns the wallclock time in four integer arguments.

- Output variables

```
Parameters time (4) [integer,out]
Called from step_time(), lmloop(), magic
Call to ms2time()
```

```
subroutine timing/ms2time(ms, time)
```

Transforms accumulated milliseconds ms into an four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4).

- Input variables:

### **Parameters**

- ms [integer,in]
- **time** (4) [integer,out]

```
Called from subtime(), walltime(), step_time(), meantime(), addtime()
```

```
function timing/time2ms(time)
```

Transforms a four-element integer arrays time(4) containing the time in hours=time(1), minutes=time(2), seconds=time(3), and milliseconds=time(4) into accumulated milliseconds.

– Input variable:

```
Parameters time (4) [integer,in]
Return time2ms [integer]
Called from subtime(), lnegtime(), step_time(), meantime(), addtime()
```

Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeStart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter

as reset every day at midnight.

- Input variables:

### **Parameters**

• timestart (4) [integer,in]

subroutine timing/subtime(timestart, timestop, timed)

- **timestop** (4) [integer,in]
- **timed** (4) [integer,out]

```
Called from step_time(), lmloop()
Call to time2ms(), ms2time()
```

function timing/ltimelimit(time, timemax)

True when time exeeds timeMax

- Input variables

**Parameters** 

```
• time (4) [integer,in]
• timemax (4) [integer,in]

Return ltimelimit [logical]

Called from step_time()

subroutine timing/addtime (time1, time2)

- Input variables

Parameters
• time1 (4) [integer]
• time2 (4) [integer]

Called from step_time()

Call to time2ms(), ms2time()

subroutine timing/meantime (time, n)

- Input variables

Parameters
```

- time (4) [integer]
- **n** [integer,in]

```
Called from step time()
```

Call to time2ms(), ms2time()

function timing/lnegtime(time1, time2)

Negative passed time? Means we have passed midnight. The wallclock time is reset to zero on some computers at midnight.

- Input variables

### **Parameters**

- **time1** (4) [integer,in]
- **time2** (4) [integer,in]

**Return Inegtime** [logical]

Called from step\_time()

Call to time2ms()

subroutine timing/writetime(nout, text, time)

Returns time passed between timeStop and timeStart. Note timeStop has to be younger than timeStart, otherwise 24 hours are added. This is necessary on systems like the IBM where the time counter are reset every day at midnight.

- Input variables:

#### **Parameters**

- nout [integer,in]
- text [character,in]
- **time** (4) [integer,in]

Called from step\_time(), lmloop(), magic

# 10.7 Linear calculation part of the time stepping (LMLoop)

### 10.7.1 LMLoop.f90

### **Quick access**

Routines finalize\_lmloop(), initialize\_lmloop(), lmloop()

- debugging (debug\_write())
- updatez\_mod
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- precision\_mod: This module controls the precision used in MagIC
- updatewps\_mod
- parallel\_mod: This module contains the blocking information
- updatexi\_mod
- updateb\_mod
- logic (l\_anelastic\_liquid(), l\_chemical\_conv(), lverbose(), l\_heat(), l\_single\_matrix(), l\_tp\_form(), l\_save\_out(), l\_mag(), l\_conv()): Module containing the logicals that control the run
- updatewp\_mod
- mem\_alloc (memwrite(), bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- timing (writetime(), subtime(), walltime()): Useful functions for time-stepping
- blocking (lo\_map(), lmstartb(), lmstopb()): Module containing blocking information
- updatewpt\_mod
- truncation(lm\_max(), l\_max(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- fieldslast: This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- omp\_lib
- · updates mod
- output\_data (n\_log\_file(), log\_file()): This module contains the parameters for output control
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications (lo2r\_field(), lo2r\_xi(), lo2r\_flow(), lo2r\_s(), get\_global\_sum(), lo2r\_redist\_start())
- fields: This module contains the potential fields and their radial derivatives

### Subroutines and functions

```
subroutine lmloop_mod/initialize_lmloop()
         Called from magic
         Call to initialize_updatewpt(),
                                                                 initialize_updatewps(),
             initialize_updates(),
                                                                  initialize_updatewp(),
             initialize_updatexi(), initialize_updatez(), initialize_updateb(),
             memwrite()
subroutine lmloop_mod/finalize_lmloop()
         Called from magic
         Call to finalize_updatewpt(), finalize_updatewps(), finalize_updates(),
              finalize_updatewp(), finalize_updatexi(), finalize_updatez(),
             finalize_updateb()
subroutine lmloop_mod/lmloop(w1, coex, time, dt, lmat, lrmsnext, lpressnext, dvxvhlm, dvxbhlm,
                                    dvsrlm, dvprlm, dvxirlm, dsdt, dwdt, dzdt, dpdt, dxidt, dbdt,
                                    djdt, lorentz_torque_ma, lorentz_torque_ic, b_nl_cmb, aj_nl_cmb,
                                    aj_nl_icb
         This subroutine performs the actual time-stepping.
     – Input of variables:
         Parameters
               • w1 [real,in]
               • coex [real,in]
               • time [real,in]
               • dt [real,in]
               • lmat [logical,in]
               • Irmsnext [logical,in]
               • lpressnext [logical,in]
               • dvxvhlm (ulm-(llm)+1,n_r_max) [complex,inout]
               • dvxbhlm (ulmmag-(llmmag)+1,n_r_maxmag) [complex,inout]
               • dvsrlm (ulm-(llm)+1,n_r_max) [complex,inout]
               • dvprlm (ulm-(llm)+1,n_r_max) [complex,inout]
               • dvxirlm (ulm-(llm)+1,n_r_max) [complex,inout]
               • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
               • dwdt (ulm-(llm)+1,n_r_max) [complex,inout]
               • dzdt (ulm-(llm)+1,n_r_max) [complex,in]
               • dpdt (ulm-(llm)+1,n_r_max) [complex,in]
               • dxidt (ulm-(llm)+1,n_r_max) [complex, inout]
               • dbdt (ulmmag-(llmmag)+1,n r maxmag) [complex,in]
```

- **djdt** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [complex,inout]
- lorentz\_torque\_ma [real,in]
- lorentz\_torque\_ic [real,in]
- **b\_nl\_cmb** (*lm\_max*) [complex,in] :: nonlinear bc for b at CMB
- aj\_nl\_cmb (lm\_max) [complex,in] :: nonlinear bc for aj at CMB
- aj nl icb (lm max) [complex,in] :: nonlinear bc for dr aj at ICB

```
Called from step_time()
```

```
Call to walltime(), updates_ala(), updates(), lo2r_redist_start(),
    updatexi(), updatewpt(), updatewps(), updatewp(), updateb(),
    subtime(), writetime()
```

### 10.7.2 updateWPS.f90

#### **Quick access**

- horizontal\_data (hdif\_s(), dlh(), hdif\_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- init\_fields (bots (), tops ()): This module is used to construct the initial solution.
- radial\_der (get\_dr(), get\_ddr(), get\_dddr()): Radial derivatives functions
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- num\_param(alpha()): Module containing numerical and control parameters
- physical\_parameters (kbotv(), buofac(), kbots(), opr(), vischeatfac(), ktopv(), ra(), ktops(), thexpnb(), corfac(), ktopp()): Module containing the physical parameters
- omp\_lib
- radial\_functions (rscheme\_oc(), kappa(), temp0(), dlkappa(), dltemp0(), dlvisc(), dlalpha0(), rho0(), or2(), ddltemp0(), or1(), visc(), beta(), r(), dentropy0(), rgrav(), alpha0(), ogrun(), ddlalpha0(), dbeta(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (sgesl(), sgefa(), cgeslml())
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC

- rms\_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map(), st\_sub\_map()): Module containing blocking information
- constants (osq4pi(), pi(), third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- precision\_mod: This module controls the precision used in MagIC
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications(get\_global\_sum())
- logic (l\_update\_v(), l\_rms(), l\_temperature\_diff()): Module containing the logicals that control the run

- updatewps\_mod/**pre**(:) [complex,private/allocatable]
- updatewps\_mod/ps0pivot (:) [integer,private/allocatable]
- updatewps\_mod/ps0mat\_fac(:,:) [real,private/allocatable]
- updatewps\_mod/lwpsmat (:) [logical,allocatable/public]
- updatewps\_mod/ps0mat (:,:) [real,private/allocatable]
- updatewps\_mod/buo(:) [complex,private/allocatable]
- updatewps\_mod/cor00\_fac [real,private]
- updatewps\_mod/wpsmat (:,:,:) [real,private/allocatable]
- updatewps\_mod/wpspivot (:,:) [integer,private/allocatable]
- updatewps\_mod/maxthreads [integer,private]
- updatewps\_mod/workb(:,:) [complex,private/allocatable]
- updatewps\_mod/workc(:,:) [complex,private/allocatable]
- updatewps\_mod/workd(:,:) [complex,private/allocatable]
- updatewps\_mod/rhs1(:,:,:) [complex,private/allocatable]
- updatewps\_mod/wpsmat\_fac(:,:,:) [real,private/allocatable]
- updatewps\_mod/dif(:)[complex,private/allocatable]
- updatewps\_mod/dtv(:) [complex,private/allocatable]

### **Subroutines and functions**

```
subroutine updatewps_mod/initialize_updatewps()
Called from initialize lmloop()
```

```
subroutine updatewps_mod/finalize_updatewps()
          Called from finalize_lmloop()
subroutine updatewps_mod/updatewps (w, dw, ddw, z10, dwdt, dwdtlast, p, dp, dpdt, dpdtlast, s, ds,
                                                dvsrlm, dsdt, dsdtlast, w1, coex, dt, nlmb, lrmsnext)
          updates the poloidal velocity potential w, the pressure p, and their derivatives adds explicit part to
          time derivatives of w and p
     - Input/output of scalar fields:
          Parameters
                • w (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dw (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ddw (ulm-(llm)+1,n_r_max) [complex,out]
                • z10 (n_r_max) [real,in]
                 • dwdt (ulm-(llm)+1,n_r_max) [complex,in]
                 • dwdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • p (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dp (ulm-(llm)+1,n_r_max) [complex, out]
                 • dpdt (ulm-(llm)+1,n_r_max) [complex,in]
                 • dpdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                • s (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ds (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dvsrlm (ulm-(llm)+1,n_r_max) [complex,inout]
                • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • w1 [real,in] :: weight for time step!
                • coex [real,in] :: factor depending on alpha
                • dt [real,in] :: time step
                 • nlmb [integer,in] :: block number
                 • lrmsnext [logical,in]
          Called from lmloop()
          Call to get_ps0mat(), get_wpsmat(), sges1(), cges1ml(), get_dddr(),
               get ddr(), hint2pol()
subroutine updatewps_mod/get_wpsmat (dt, l, hdif_vel, hdif_s, wpsmat, wpspivot, wpsmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.
     - Input variables:
          Parameters
                 • dt [real,in]
                 • I [integer,in]
```

```
hdif_vel [real,in]
hdif_s [real,in]
wpsmat (3*n_r_max,3*n_r_max) [real,out]
wpspivot (3*n_r_max) [integer,out]
wpsmat_fac (3*n_r_max,2) [real,out]
Called from updatewps()
Call to sgefa(), abortrun()
subroutine updatewps_mod/get_ps0mat(dt, psmat, pspivot, psmat_fac)
Input variables
Parameters
dt [real,in]
psmat (2*n_r_max,2*n_r_max) [real,out]
pspivot (2*n r max) [integer,out]
```

• psmat fac (2\*n r max,2) [real,out]

# Called from updatewps()

### Call to sgefa(), abortrun()

### 10.7.3 updateWPT.f90

### **Quick access**

- horizontal\_data (hdif\_s(), dlh(), hdif\_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- init\_fields (bots (), tops ()): This module is used to construct the initial solution.
- radial\_der(get\_dr(), get\_ddr(), get\_dddr()): Radial derivatives functions
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- num\_param(alpha()): Module containing numerical and control parameters
- physical\_parameters (kbotv(), buofac(), kbots(), opr(), vischeatfac(), ktopv(), ra(), ktops(), thexpnb(), corfac(), ktopp(): Module containing the physical parameters

- omp lib
- radial\_functions (rho0(), or2(), or1(), ogrun(), temp0(), dentropy0(), otemp1(), rscheme\_oc(), dlkappa(), rgrav(), orho1(), orho2(), dlvisc(), ddltemp0(), dltemp0(), beta(), alpha0(), kappa(), visc(), dlalpha0(), dbeta(), r(), ddlalpha0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (sgesl(), sgefa(), cgeslml())
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms\_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map(), st\_sub\_map()): Module containing blocking information
- constants (osq4pi(), pi(), third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- precision\_mod: This module controls the precision used in MagIC
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get global sum())
- logic (l\_update\_v(), l\_rms(), l\_temperature\_diff()): Module containing the logicals that control the run

- updatewpt\_mod/pre (:) [complex,private/allocatable]
- updatewpt\_mod/workc(:,:) [complex,private/allocatable]
- updatewpt\_mod/wptmat\_fac(:,:,:) [real,private/allocatable]
- updatewpt\_mod/workd(:,:) [complex,private/allocatable]
- updatewpt\_mod/lwptmat(:)[logical,allocatable/public]
- updatewpt mod/maxthreads[integer,private]
- updatewpt\_mod/buo(:) [complex,private/allocatable]
- updatewpt\_mod/cor00\_fac [real,private]
- updatewpt\_mod/pt0mat\_fac(:,:) [real,private/allocatable]
- updatewpt\_mod/wptpivot (:,:) [integer,private/allocatable]
- updatewpt\_mod/workb (:,:) [complex,private/allocatable]
- updatewpt\_mod/pt0mat(:,:) [real,private/allocatable]
- updatewpt\_mod/rhs1(:,:,:) [complex,private/allocatable]
- updatewpt\_mod/wptmat(:,:,:) [real,private/allocatable]
- updatewpt\_mod/**pt0pivot** (:) [integer,private/allocatable]

- updatewpt\_mod/dif(:) [complex,private/allocatable]
- updatewpt\_mod/dtv(:) [complex,private/allocatable]

### Subroutines and functions

```
subroutine updatewpt_mod/initialize_updatewpt()
          Called from initialize Imloop()
subroutine updatewpt_mod/finalize_updatewpt()
          Called from finalize_lmloop()
subroutine updatewpt_mod/updatewpt (w, dw, ddw, z10, dwdt, dwdtlast, p, dp, dpdt, dpdtlast, tt,
                                                dtt, dvtrlm, dvprlm, dttdt, dttdtlast, w1, coex, dt, nlmb, lrm-
                                                snext)
          updates the poloidal velocity potential w, the pressure p, and their derivatives adds explicit part to
          time derivatives of w and p
     - Input/output of scalar fields:
          Parameters
                 • w (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dw (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ddw (ulm-(llm)+1,n_r_max) [complex,out]
                 • z10 (n_r_max) [real,in]
                 • dwdt (ulm-(llm)+1,n_r_max) [complex,in]
                 • dwdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • p (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dp (ulm-(llm)+1,n_r_max) [complex,out]
                 • dpdt (ulm-(llm)+1,n_r_max) [complex,in]
                 • dpdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • tt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dtt (ulm-(llm)+1, n r max) [complex, inout]
                 • dvtrlm (ulm-(llm)+1,n_r_max) [complex, inout]
                 • dvprlm (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dttdt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dttdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • w1 [real,in] :: weight for time step!
                 • coex [real,in] :: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in] :: block number
                 • Irmsnext [logical,in]
```

Called from lmloop()

10.7. Linear calculation part of the time stepping (LMLoop)

```
Call to get_pt0mat(), get_wptmat(), sges1(), cges1ml(), get_dddr(),
              get_ddr(), hint2pol()
subroutine updatewpt_mod/get_wptmat (dt, l, hdif_vel, hdif_t, wptmat, wptpivot, wptmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.
     - Input variables:
          Parameters
               • dt [real,in]
               • 1 [integer,in]
               • hdif vel [real,in]
               • hdif_t [real,in]
               • wptmat (3*n_r_max,3*n_r_max) [real,out]
               • wptpivot (3*n_r_max) [integer,out]
                • wptmat fac (3*n r max, 2) [real, out]
          Called from updatewpt()
          Call to sgefa(), abortrun()
subroutine updatewpt_mod/get_pt0mat (dt, ptmat, ptpivot, ptmat_fac)
     - Input variables
          Parameters
               • dt [real,in]
                • ptmat (2*n_r_max,2*n_r_max) [real,out]
                • ptpivot (2*n_r_max) [integer,out]
                • ptmat_fac (2*n_r_max,2) [real,out]
          Called from updatewpt()
          Call to sgefa(), abortrun()
10.7.4 updateWP.f90
Quick access
     Variables p0pivot, wppivot, lwpmat, work, ddddw, dwold, p0mat, wpmat, wpmat_fac
```

# Needed modules

- horizontal\_data(dlh(), hdif\_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (difpol2hint(), dtvpol1mr(), dtvpol2hint(), difpol1mr()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun()): library with several useful subroutines

get\_wpmat(), get\_p0mat(), updatewp()

**Routines** finalize updatewp(),

- lmloop\_data(llm(), ulm())
- radial\_der (get\_dr(), get\_ddr(), get\_dddr()): Radial derivatives functions
- integration (rint\_r()): Radial integration functions
- parallel\_mod (chunksize()): This module contains the blocking information
- num\_param(alpha()): Module containing numerical and control parameters
- physical\_parameters (kbotv(), buofac(), vischeatfac(), ktopv(), chemfac(), ra(), thexpnb(), ktopp()): Module containing the physical parameters
- omp\_lib
- radial\_functions(alpha0(), orho1(), ddlvisc(), rho0(), or2(), rscheme\_oc(), or1(), ddbeta(), visc(), beta(), dlvisc(), temp0(), rgrav(), ogrun(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (sqesl(), sqefa(), cqeslml())
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms\_helpers (hint2pol()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map(), st\_sub\_map()): Module containing blocking information
- constants (third(), three(), two(), four(), zero(), half(), one()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- precision\_mod: This module controls the precision used in MagIC
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get\_global\_sum())
- logic(l\_double\_curl(), l\_update\_v(), l\_rms(), l\_chemical\_conv(), l\_fluxprofs()): Module containing the logicals that control the run

## **Variables**

- updatewp\_mod/**pre** (:) [complex,private/allocatable]
- updatewp\_mod/**ddddw** (:,:) [complex,private/allocatable]
- updatewp\_mod/maxthreads[integer,private]
- updatewp\_mod/buo(:) [complex,private/allocatable]
- updatewp\_mod/lwpmat(:)[logical,allocatable/public]
- updatewp\_mod/wpmat\_fac(:,:,:) [real,private/allocatable]
- updatewp\_mod/p0mat (:,:) [real,private/allocatable]
- updatewp\_mod/dwold(:,:) [complex,private/allocatable]
- updatewp\_mod/workb (:,:) [complex,private/allocatable]

- updatewp\_mod/work (:) [real,private/allocatable]
- updatewp\_mod/rhs1 (:,:,:) [complex,private/allocatable]
- updatewp\_mod/wppivot (:,:) [integer,private/allocatable]
- updatewp\_mod/wpmat(:,:,:) [real,private/allocatable]
- updatewp\_mod/dif(:)[complex,private/allocatable]
- updatewp\_mod/**p0pivot** (:) [integer,private/allocatable]
- updatewp\_mod/dtv(:) [complex,private/allocatable]

#### Subroutines and functions

- Input/output of scalar fields:

time derivatives of w and p

- w (ulm-(llm)+1,n\_r\_max) [complex,inout]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [complex,inout]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,inout]
- **dvxvhlm** (*ulm*-(*llm*)+1,*n\_r\_max*) [complex,inout]
- **dwdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *inout*]
- **dwdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,inout]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **dp** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dpdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dpdtlast** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*, *inout*]
- $\mathbf{s}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- **xi** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- w1 [real,in] :: weight for time step!
- coex [real,in] :: factor depending on alpha
- **dt** [real,in] :: time step
- **nlmb** [integer,in] :: block number
- **lrmsnext** [logical,in]
- **lpressnext** [logical,in]

```
Called from Imloop()
          Call to get_p0mat(), get_wmat(), get_wpmat(), rint_r(), sges1(), cges1m1(),
              get_ddr(), get_dddr(), hint2pol()
subroutine updatewp_mod/get_wpmat (dt, l, hdif, wpmat, wppivot, wpmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation.
     - Input variables:
          Parameters
                • dt [real,in]
                • I [integer,in]
                • hdif [real,in]
                • wpmat (2*n_r_max,2*n_r_max) [real,out]
                • wppivot (2*n_r_max) [integer,out]
                • wpmat fac (2*n \ r \ max, 2) [real,out]
          Called from updatewp()
          Call to sgefa(), abortrun()
subroutine updatewp_mod/get_wmat (dt, l, hdif, wmat, wpivot, wmat_fac)
          Purpose of this subroutine is to contruct the time step matrix wpmat for the NS equation. This matrix
          corresponds here to the radial component of the double-curl of the Navier-Stokes equation.
     - Input variables:
          Parameters
                • dt [real,in]
                • I [integer,in]
                • hdif [real,in]
                • wmat (2*n_r_max,2*n_r_max) [real,out]
                • wpivot (2*n_r_max) [integer,out]
                • wmat_fac (2*n_r_max,2) [real,out]
          Called from updatewp()
          Call to sgefa(), abortrun()
subroutine updatewp_mod/get_p0mat (pmat, ppivot)
     - Output variables:
          Parameters
                • pmat (n_r_max,n_r_max) [real,out]
                • ppivot (n_r_max) [integer,out]
          Called from updatewp()
```

Call to sgefa(), abortrun()

## 10.7.5 updateZ.f90

#### **Quick access**

- horizontal\_data(dlh(), hdif\_v()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (dtvtor2hint (), diftor2hint ()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun ()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- *init\_fields*: This module is used to construct the initial solution.
- radial\_der (get\_ddr ()): Radial derivatives functions
- precision mod: This module controls the precision used in MagIC
- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- parallel\_mod: This module contains the blocking information
- num\_param (alpha(), amstart()): Module containing numerical and control parameters
- physical\_parameters (po\_diff(), kbotv(), lffac(), diff\_prec\_angle(), oek(), ktopv(), prec\_angle(), po()): Module containing the physical parameters
- omp\_lib
- algebra(cgesl(), sgefa(), cgeslml())
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms\_helpers (hint2tor()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map(), st\_sub\_map()): Module containing blocking information
- constants (c\_moi\_oc(), y11\_norm(), pi(), third(), y10\_norm(), c\_z10\_omega\_ma(), c\_lorentz\_ic(), c\_dt\_z10\_ic(), one(), four(), c\_moi\_ma(), zero(), c\_z10\_omega\_ic(), two(), c\_moi\_ic(), c\_dt\_z10\_ma(), c\_lorentz\_ma()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), r\_cmb(), rho0(), or2(), or1(), visc(), beta(), dlvisc(), r\_icb(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

- torsional\_oscillations (ddzasl()): This module contains information for TO calculation and output
- outrot(get\_angular\_moment())
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get\_global\_sum())
- logic (l\_rot\_ic(), l\_diff\_prec(), l\_precession(), l\_correct\_amz(), l\_correct\_ame(), l\_update\_v(), l\_srma(), l\_z10mat(), l\_rot\_ma(), l\_to(), l\_sric(), l\_rms()): Module containing the logicals that control the run

## **Variables**

- updatez\_mod/lz10mat [logical,public]
- updatez\_mod/zmat\_fac(:,:) [real,private/allocatable]
- updatez\_mod/**zmat** (:,:,:) [real,private/allocatable]
- updatez\_mod/**z10mat\_fac**(:) [real,private/allocatable]
- updatez\_mod/lzmat(:) [logical,allocatable/public]
- updatez\_mod/maxthreads [integer,private]
- updatez\_mod/workb (:,:) [complex,private/allocatable]
- updatez\_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updatez\_mod/**z10mat** (:,:) [real,private/allocatable]
- updatez\_mod/dif(:) [complex,private/allocatable]
- updatez\_mod/**z10pivot** (:) [integer,private/allocatable]
- updatez\_mod/**zpivot** (:,:) [integer,private/allocatable]
- updatez\_mod/dtv(:) [complex,private/allocatable]

## **Subroutines and functions**

updates the toroidal potential z and its radial derivatives adds explicit part to time derivatives of z

- Input/output of scalar fields:

- $\mathbf{z}$  (ulm-(llm)+1,n\_r\_max) [complex,inout]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dzdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dzdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **time** [real,in] :: Current time
- omega ma [real,out] :: Calculated OC rotation
- **d\_omega\_ma\_dtlast** [real,inout] :: Time derivative of OC rotation of previous step
- omega\_ic [real,out] :: Calculated IC rotation
- **d\_omega\_ic\_dtlast** [real,inout] :: Time derivative of IC rotation of previous step
- **lorentz\_torque\_ma** [real,in] :: Lorentz torque (for OC rotation)
- lorentz\_torque\_malast [real,in] :: Lorentz torque (for OC rotation) of previous step
- **lorentz\_torque\_ic** [real,in] :: Lorentz torque (for IC rotation)
- lorentz\_torque\_iclast [real,in] :: Lorentz torque (for IC rotation) of previous step
- w1 [real,in] :: Weight for time step
- coex [real,in] :: Factor depending on alpha
- **dt** [real,in] :: Time step interval
- **Irmsnext** [logical,in] :: Logical for storing update if (l\_RMS.and.l\_logNext)

```
Call to get_zmat(), get_z10mat(), cgesl(), cgeslml(), get_ddr(),
    get_angular_moment(), hint2tor()
```

```
subroutine updatez_mod/get_z10mat (dt, l, hdif, zmat, zpivot, zmat_fac)
```

Purpose of this subroutine is to construct and LU-decompose the inversion matrix z10mat for the implicit time step of the toroidal velocity potential z of degree l=1 and order m=0. This differs from the the normal zmat only if either the ICB or CMB have no-slip boundary condition and inner core or mantle are chosen to rotate freely (either kbotv=1 and/or ktopv=1).

## **Parameters**

- **dt** [real,in] :: Time step internal
- I [integer,in] :: Variable to loop over l's
- hdif [real,in] :: Value of hyperdiffusivity in zMat terms
- **zmat** (n\_r\_max,n\_r\_max) [real,out] :: LHS matrix to calculate z
- **zpivot** (*n\_r\_max*) [integer,out] :: Pivot to invert zMat
- **zmat\_fac** (*n\_r\_max*) [*real,out*] :: Inverse of max(zMat) for inversion

```
Called from updatez()
```

```
Call to sgefa(), abortrun()
```

subroutine updatez\_mod/get\_zmat (dt, l, hdif, zmat, zpivot, zmat\_fac)

Purpose of this subroutine is to contruct the time step matricies zmat(i,j) for the NS equation.

- Input variables:

```
• dt [real,in] :: Time interval
```

- 1 [integer,in] :: Variable to loop over degrees
- hdif [real,in] :: Hyperdiffusivity
- **zmat** (*n\_r\_max,n\_r\_max*) [*real,out*] :: Matrix with LHS of z equation
- **zpivot** (*n r max*) [integer, out] :: Pivot for zMat inversion
- **zmat** fac (n r max) [real,out] :: Inverse of max(zMat) for the inversion

```
Called from updatez()
Call to sgefa(), abortrun()
```

## 10.7.6 updateS.f90

#### **Quick access**

- horizontal\_data(hdif\_s(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- useful (abortrun ()): library with several useful subroutines
- algebra (sgesl(), sgefa(), cgeslml())
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- logic(l\_anelastic\_liquid(), l\_update\_s()): Module containing the logicals that control the run
- lmloop\_data(llm(), ulm())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision mod: This module controls the precision used in MagIC
- init\_fields (bots (), tops ()): This module is used to construct the initial solution.
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- num\_param (alpha()): Module containing numerical and control parameters
- radial der (get dr(), get ddr()): Radial derivatives functions
- physical\_parameters (kbots(), ktops(), opr()): Module containing the physical parameters
- omp\_lib
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map()): Module containing blocking information

- constants (zero (), two (), one ()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), orho1(), dlkappa(), or2(), or1(), dltemp0(), beta(), temp0(), dentropy0(), kappa()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

- updates\_mod/maxthreads [integer,private]
- updates\_mod/**spivot** (:,:) [integer,private/allocatable]
- updates\_mod/**smat** (:,:,:) [real,private/allocatable]
- updates\_mod/smat\_fac(:,:) [real,private/allocatable]
- updates\_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updates\_mod/s0mat\_fac(:)[real,private/allocatable]
- updates\_mod/s0mat(:,:) [real,private/allocatable]
- updates\_mod/lsmat(:) [logical,allocatable/public]
- updates\_mod/s0pivot (:) [integer,private/allocatable]

## **Subroutines and functions**

## **Parameters**

- $s(ulm-(llm)+1,n\_r\_max)[complex,inout]$
- **ds** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*out*]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dvsrlm** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*inout*]
- **dsdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*inout*]
- **dsdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,inout]
- w1 [real,in] :: weight for time step!
- **coex** [real,in] :: factor depending on alpha
- **dt** [real,in] :: time step
- nlmb [integer,in]

Called from lmloop()

```
Call to get_s0mat(), get_smat(), sgesl(), cgeslml(), get_ddr()
subroutine updates_mod/updates_ala (s, ds, w, dvsrlm, dsdt, dsdtlast, w1, coex, dt, nlmb)
          updates the entropy field s and its radial derivatives adds explicit part to time derivatives of s
     - Input of variables:
          Parameters
                 • s (ulm-(llm)+1,n_r_max) [complex,inout]
                 • ds (ulm-(llm)+1,n_r_max) [complex,out]
                 • w (ulm-(llm)+1,n_r_max) [complex,in]
                 • dvsrlm (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdt (ulm-(llm)+1,n_r_max) [complex,inout]
                 • dsdtlast (ulm-(llm)+1,n_r_max) [complex,inout]
                 • w1 [real,in] :: weight for time step!
                 • coex [real,in] :: factor depending on alpha
                 • dt [real,in] :: time step
                 • nlmb [integer,in]
          Called from Imloop()
          Call to get_s0mat(), get_smat(), sgesl(), cgeslml(), get_ddr()
subroutine updates_mod/get_s0mat (dt, smat, spivot, smat_fac)
          Purpose of this subroutine is to contruct the time step matrix sMat0
     - Input variables
          Parameters
                 • dt [real,in]
                 • smat (n_r_max,n_r_max) [real,out]
                 • spivot (n_r_max) [integer,out]
                 • smat fac (n r max) [real,out]
          Called from updates(), updates_ala()
          Call to sgefa(), abortrun()
subroutine updates_mod/get_smat(dt, l, hdif, smat, spivot, smat_fac)
          Purpose of this subroutine is to contruct the time step matricies sMat(i,j) and s0mat for the entropy
          equation.
     - Input variables
          Parameters
                 • dt [real,in]
                 • I [integer,in]
                 • hdif [real,in]
                 • smat (n_r_max,n_r_max) [real,out]
```

```
spivot (n_r_max) [integer,out]
smat_fac (n_r_max) [real,out]
Called from updates(), updates_ala()
Call to sgefa(), abortrun()
```

## 10.7.7 updateXI.f90

#### **Quick access**

- horizontal\_data (hdif\_xi(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun ()): library with several useful subroutines
- algebra (sgesl(), sgefa(), cgeslml())
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- logic (l\_update\_xi()): Module containing the logicals that control the run
- lmloop\_data(llm(), ulm())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- init\_fields (botxi(), topxi()): This module is used to construct the initial solution.
- num\_param (alpha()): Module containing numerical and control parameters
- radial\_der(get\_dr(), get\_ddr()): Radial derivatives functions
- physical\_parameters (kbotxi(), osc(), ktopxi()): Module containing the physical parameters
- omp\_lib
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map()): Module containing blocking information
- constants (zero (), two (), one ()): module containing constants and parameters used in the code.
- radial\_functions (or2(), beta(), orho1(), rscheme\_oc(), or1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

```
updatexi_mod/maxthreads [integer,private]updatexi_mod/xipivot (:,:) [integer,private/allocatable]
```

• updatexi\_mod/xi0mat(:,:) [real,private/allocatable]

• updatexi\_mod/rhs1(:,:,:) [complex,private/allocatable]

• updatexi\_mod/ximat(:,:,:) [real,private/allocatable]

• updatexi\_mod/xi0pivot (:) [integer,private/allocatable]

• updatexi\_mod/ximat\_fac(:,:) [real,private/allocatable]

• updatexi\_mod/xi0mat\_fac(:) [real,private/allocatable]

• updatexi\_mod/lximat (:) [logical,allocatable/public]

subroutine updatexi\_mod/initialize\_updatexi()

## **Subroutines and functions**

```
Called from initialize_lmloop()
subroutine updatexi_mod/finalize_updatexi()
          Called from finalize_lmloop()
subroutine updatexi_mod/updatexi(xi, dxi, dvxirlm, dxidt, dxidtlast, w1, coex, dt, nlmb)
          updates the entropy field s and its radial derivatives adds explicit part to time derivatives of s
     - Input of variables:
          Parameters
                • xi (ulm-(llm)+1,n_r_max) [complex,inout]
                • dxi (ulm-(llm)+1,n_r_max) [complex,out]
                • dvxirlm (ulm-(llm)+1,n_r_max) [complex,inout]
                • dxidt (ulm-(llm)+1,n_r_max) [complex,inout]
                • dxidtlast (ulm-(llm)+1,n_r_max) [complex, inout]
                • w1 [real,in] :: weight for time step!
                • coex [real,in] :: factor depending on alpha
                • dt [real,in] :: time step
                • nlmb [integer,in]
          Called from lmloop()
          Call to get_xi0mat(), get_ximat(), sgesl(), cgeslml(), get_ddr()
subroutine updatexi_mod/get_xiOmat(dt, ximat, xipivot, ximat_fac)
          Purpose of this subroutine is to contruct the time step matrix xiMat0
     - Input variables
```

- **dt** [real,in]
- ximat (n\_r\_max,n\_r\_max) [real,out]
- **xipivot** (*n\_r\_max*) [integer,out]
- ximat\_fac (n\_r\_max) [real,out]

Called from updatexi()

Call to sgefa(), abortrun()

subroutine updatexi\_mod/get\_ximat (dt, l, hdif, ximat, xipivot, ximat\_fac)

Purpose of this subroutine is to contruct the time step matricies xiMat(i,j) for the equation for the chemical composition.

- Input variables

#### **Parameters**

- **dt** [real,in]
- I [integer,in]
- hdif [real,in]
- ximat (n\_r\_max,n\_r\_max) [real,out]
- **xipivot** (*n\_r\_max*) [integer,out]
- ximat\_fac (n\_r\_max) [real,out]

Called from updatexi()

Call to sgefa(), abortrun()

# 10.7.8 updateB.f90

#### **Quick access**

```
Variables bpivot, jpivot, lbmat, dtp, dtt, bmat_fac, jmat_fac, bmat, jmat, rhs2

Routines finalize_updateb(), initialize_updateb(), updateb(), get_bmat()
```

- horizontal\_data (hdif\_b(), dphi(), dlh(), d\_l(), d\_lp1()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- rms (dtbtor2hint(), dtbpollmr(), dtbpol2hint()): This module contains the calculation of thr RMS force balance and induction terms.
- useful (abortrun()): library with several useful subroutines
- lmloop\_data(llmmag(), ulmmag())
- init fields (bpeakbot (), bpeaktop ()): This module is used to construct the initial solution.
- radial\_der\_even(get\_ddr\_even())
- radial\_der (get\_dr(), get\_ddr()): Radial derivatives functions

- special: This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- parallel\_mod (chunksize(), rank()): This module contains the blocking information
- num\_param(alpha()): Module containing numerical and control parameters
- physical\_parameters (sigma\_ratio(), ktopb(), tmagcon(), imagcon(), o\_sr(), n\_r\_lcr(), opm(), conductance\_ma(), kbotb()): Module containing the physical parameters
- omp\_lib
- radial\_functions (d2cheb\_ic(), rscheme\_oc(), dcheb\_ic(), r\_cmb(), cheb\_norm\_ic(), or2(), dr\_fac\_ic(), or1(), dllambda(), r(), o\_r\_ic(), chebt\_ic\_even(), chebt\_ic(), cheb\_ic(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- algebra (sgefa(), cgeslml())
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms\_helpers (hint2torlm(), hint2pollm()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lo\_sub\_map(), lmstartb(), nlmbs(), lmstopb(), lo\_map(), st\_map(), st\_sub\_map()): Module containing blocking information
- constants (one (), three (), two (), zero (), half (), pi ()): module containing constants and parameters used in the code.
- truncation(n\_r\_ic\_max(), n\_cheb\_ic\_max(), n\_r\_ic\_maxmag(), n\_r\_tot(), lm\_max(), l\_maxmag(), n\_r\_max(), n\_r\_totmag(), n\_r\_maxmag()): This module defines the grid points and the truncation
- precision\_mod: This module controls the precision used in MagIC
- fields (work\_lmloc()): This module contains the potential fields and their radial derivatives
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- logic (l\_rot\_ic(), l\_mag\_nl(), l\_lcr(), l\_cond\_ic(), l\_b\_nl\_cmb(), l\_rms(), l\_b\_nl\_icb(), l\_update\_b()): Module containing the logicals that control the run

## **Variables**

- updateb\_mod/jpivot(:,:) [integer,private/allocatable]
- updateb\_mod/lbmat(:)[logical,allocatable/public]
- updateb\_mod/jmat\_fac(:,:) [real,private/allocatable]
- updateb\_mod/maxthreads [integer,private]
- updateb\_mod/workb (:,:) [complex,private/allocatable]
- updateb\_mod/**bpivot** (:,:) [integer,private/allocatable]
- updateb\_mod/rhs2 (:,:,:) [complex,private/allocatable]
- updateb\_mod/**rhs1** (:,:,:) [complex,private/allocatable]
- updateb\_mod/bmat\_fac(:,:) [real,private/allocatable]

- updateb\_mod/bmat (:,:,:) [real,private/allocatable]
- updateb\_mod/jmat(:,:,:) [real,private/allocatable]
- updateb\_mod/dtp(:)[complex,private/allocatable]
- updateb\_mod/dtt(:)[complex,private/allocatable]

## Subroutines and functions

**subroutine** updateb\_mod/**updateb**(b, db, ddb, aj, dj, ddj, dvxbhlm, dbdt, dbdtlast, djdt, djdtlast, b\_ic, db\_ic, ddb\_ic, aj\_ic, dj\_ic, ddj\_ic, dbdt\_iclast, djdt\_iclast, b\_nl\_cmb, aj\_nl\_icb, omega\_ic, w1, coex, dt, time, nlmb, lrmsnext)

Calculated update of magnetic field potential and the time stepping arrays dbdtLast, ...

updates the magnetic field potentials b, aj and their derivatives, adds explicit part to time derivatives of b and j input: w1 - weight for dbdt-contribution from current time step (w2=1-w1: weight for contrib. from previous step) coex - factor depending on weighting alpha of implicit contribution mc\_min,mc\_max - range of mca-indices in which field is updated (harmonic order m=(mca-1)\*minc) b\_nl\_cmb = RHS of nonlinear BC for poloidal magnetic field potential in the case of stress free CMB aj\_nl\_cmb = RHS of nonlinear BC for toroidal magnetic field potential in the case of stress free CMB aj\_nl\_icb = RHS of nonlinear BC for radial derivative of toroidal magnetic field potential in the case of stress free ICB

## - Input variables:

- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **db** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [complex,out]
- **ddb** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,out]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **dj** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*, *out*]
- **ddj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,out]
- **dvxbhlm** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [complex,inout]
- **dbdt** (*ulmmag-(llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **dbdtlast** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **djdt** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,inout]
- **djdtlast** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*, *inout*]
- **b\_ic** (*ulmmag-(llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex,inout*]
- **db\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,out*]
- **ddb\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,out]

```
• aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
                • dj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                • ddj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                • dbdt_iclast (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,inout]
                • djdt iclast (ulmmag-(llmmag)+1,n r ic maxmag) [complex,inout]
                • b_nl_cmb (*) [complex,in]
                • aj_nl_cmb (*) [complex,in]
                • aj_nl_icb (*) [complex,in]
                • omega_ic [real,in]
                • w1 [real,in] :: weight for time step!
                • coex [real,in] :: factor depending on alpha
                • dt [real,in]
                • time [real,in]
                • nlmb [integer,in]
                • lrmsnext [logical,in]
          Called from Imloop()
          Call to get_bmat(), abortrun(), cgeslml(), get_ddr(), get_ddr_even(),
               hint2pollm(), hint2torlm()
subroutine updateb_mod/get_bmat (dt, l, hdif, bmat, bpivot, bmat_fac, jmat, jpivot, jmat_fac)
          Purpose of this subroutine is to contruct the time step matrices bmat(i,j) and ajmat for the dynamo
          equations.
     - Input variables:
          Parameters
```

- dt [real,in]
- **l** [integer,in]
- hdif [real,in]
- **bmat** (*n\_r\_totmag*,*n\_r\_totmag*) [real,out]
- **bpivot** (*n r totmag*) [integer,out]
- bmat\_fac (n\_r\_totmag) [real,out]
- **jmat** (*n\_r\_totmag*,*n\_r\_totmag*) [real,out]
- **jpivot** (*n\_r\_totmag*) [integer,out]
- jmat\_fac (n\_r\_totmag) [real,out]

Called from updateb()

Call to abortrun(), sgefa()

# 10.8 Non-linear part of the time stepping (radial loop)

# 10.8.1 radialLoop.f90

## **Quick access**

**Routines** finalize\_radialloop(), initialize\_radialloop(), radialloopg()

#### **Needed modules**

- mem\_alloc (memwrite(), bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- graphout\_mod (graphout\_mpi\_header()): This module contains the subroutines that store the 3-D graphic files.
- riterthetablocking\_mod(riterthetablocking\_t())
- radial\_data (n\_r\_cmb(), n\_r\_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- parallel\_mod (n\_procs(), rank()): This module contains the blocking information
- logic (l\_rot\_ic(), l\_mag\_nl(), l\_dtb(), l\_double\_curl(), l\_chemical\_conv(), l\_cond\_ma(), lverbose(), l\_mag\_kin(), l\_cond\_ic(), l\_mag\_lf(), l\_single\_matrix(), l\_rot\_ma(), l\_mag()): Module containing the logicals that control the run
- riteration\_mod(riteration\_t())
- physical\_parameters (kbotv(), ktopv()): Module containing the physical parameters
- riterthetablocking\_seq\_mod(riterthetablocking\_seq\_t())
- blocking (nthetabs(), sizethetab()): Module containing blocking information
- constants (zero ()): module containing constants and parameters used in the code.
- truncation(lm\_max(), lm\_maxmag(), lmp\_max(), l\_maxmag(), l\_max()): This module defines the grid points and the truncation

## **Variables**

## Subroutines and functions

subroutine radialloop/radialloopg (l\_graph, l\_cour, l\_frame, time, dt, dtlast, ltocalc, ltonext, ltonext2, lhelcalc, lpowercalc, lrmscalc, lpresscalc, lviscbccalc, lfluxprofcalc, lperpparcalc, l\_probe\_out, dsdt, dwdt, dzdt, dpdt, dxidt, dbdt, djdt, dvxvhlm, dvxbhlm, dvsrlm, dvprlm, dvxirlm, lorentz\_torque\_ic, lorentz\_torque\_ma, br\_vt\_lm\_cmb, br\_vp\_lm\_cmb, br\_vt\_lm\_icb, br\_vp\_lm\_icb, hellmr, helnalmr, helna2lmr, visclmr, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr,

*eperpaxilmr*, *eparaxilmr*, *dtrkc*, *dthkc*)

This subroutine performs the actual time-stepping.

## — Input of variables:

- l\_graph [logical,in]
- l\_cour [logical,in]
- **l\_frame** [logical,in]
- **time** [real,in]
- dt [real,in]
- dtlast [real,in]
- **Itocalc** [logical,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **lhelcalc** [logical,in]
- **lpowercalc** [logical,in]
- **lrmscalc** [logical,in]
- **lpresscalc** [logical,in]
- lviscbccalc [logical,in]
- Ifluxprofcalc [logical,in]
- **lperpparcalc** [logical,in]
- l\_probe\_out [logical,in]
- **dsdt** (*lm\_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dwdt** (*lm max,nrstop-(nrstart)*+1) [*complex,out*]
- **dzdt** (*lm\_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dpdt** (*lm\_max,nrstop-(nrstart*)+1) [*complex,out*]
- **dxidt** (lm\_max,nrstop-(nrstart)+1) [complex,out]
- **dbdt** (*lm\_maxmag,nrstopmag-*(*nrstartmag*)+1) [*complex,out*]
- **djdt** (lm\_maxmag,nrstopmag-(nrstartmag)+1) [complex,out]
- **dvxvhlm** (*lm\_max,nrstop-(nrstart)*+1) [*complex,out*]
- **dvxbhlm** (*lm\_maxmag,nrstopmag-(nrstartmag)*+1) [*complex,out*]

```
• dvprlm (lm_max,nrstop-(nrstart)+1) [complex,out]
                 • dvxirlm (lm_max,nrstop-(nrstart)+1) [complex,out]
                 • lorentz_torque_ic [real,out]
                 • lorentz torque ma [real,out]
                 • br_vt_lm_cmb (lmp_max) [complex,out] :: product br*vt at CMB
                 • br_vp_lm_cmb (lmp_max) [complex,out] :: product br*vp at CMB
                 • br_vt_lm_icb (lmp_max) [complex,out] :: product br*vt at ICB
                 • br_vp_lm_icb (lmp_max) [complex,out] :: product br*vp at ICB
                 • hellmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • hel2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • helnalmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • helna2lmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • visclmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • uhlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • duhlmr (l max+1,nrstop-(nrstart)+1) [real,out]
                 • gradslmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • fconvlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • fkinlmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • fvisclmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • fpoynlmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
                 • freslmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,out]
                 • eperplmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • eparlmr (l max+1,nrstop-(nrstart)+1) [real,out]
                 • eperpaxilmr (l max+1,nrstop-(nrstart)+1) [real,out]
                 • eparaxilmr (l_max+1,nrstop-(nrstart)+1) [real,out]
                 • dtrkc (nrstop-(nrstart)+1) [real, out]
                 • dthkc (nrstop-(nrstart)+1) [real, out]
           Called from step time()
           Call to graphout_mpi_header()
10.8.2 rIteration.f90
```

• **dvsrlm** (*lm\_max,nrstop-(nrstart)*+1) [*complex,out*]

## **Quick access**

**Routines** set\_steering\_variables()

## **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

## **Types**

```
• type riteration_mod/unknown_type
```

## Type fields

- % lfluxprofcalc [logical]
- % dthkc[real]
- % lhelcalc[logical]
- % lpresscalc [logical]
- % l\_probe\_out [logical]
- % isradialboundarypoint [logical]
- % nbc[integer]
- % lderiv[logical]
- % nr [integer]
- % 1\_frame [logical]
- % l\_graph [logical]
- % lperpparcalc [logical]
- % dtrkc[real]
- % ltonext2 [logical]
- % 1\_cour [logical]
- % ltocalc [logical]
- % ltonext [logical]
- % lmagnlbc [logical]
- % lviscbccalc [logical]
- % lrmscalc[logical]
- % lpowercalc[logical]

#### Subroutines and functions

## **Parameters**

• this [real]

- **l\_cour** [logical,in]
- **Itocalc** [logical,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- **Ideriv** [logical,in]
- **Irmscalc** [logical,in]
- **lhelcalc** [logical,in]
- **lpowercalc** [logical,in]
- l\_frame [logical,in]
- **lmagnlbc** [logical,in]
- l\_graph [logical,in]
- lviscbccalc [logical,in]
- **Ifluxprofcalc** [logical,in]
- **lperpparcalc** [logical,in]
- **lpresscalc** [logical,in]
- l\_probe\_out [logical,in]

# 10.8.3 rIterThetaBlocking.f90

## **Quick access**

```
Routines allocate_common_arrays(),
    set_thetablocking(),
    transform_to_grid_space()
deallocate_common_arrays(),
    transform_to_lm_space()
```

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- grid\_space\_arrays\_mod(grid\_space\_arrays\_t())
- nonlinear\_lm\_mod(nonlinear\_lm\_t())
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_spec\_to\_grid (leg\_scal\_to\_spat(), legtfgnomag(), legtfg(), leg\_scal\_to\_grad\_spat())
- radial\_data(n\_r\_cmb(), nrstart(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- legendre\_grid\_to\_spec

- logic (l\_rot\_ic(), l\_chemical\_conv(), l\_b\_nl\_icb(), l\_mag\_nl(), l\_dtb(), l\_movie\_oc(), l\_precession(), l\_rot\_ma(), l\_cond\_ic(), l\_cond\_ma(), l\_mag\_kin(), l\_conv\_nl(), l\_b\_nl\_cmb(), l\_store\_frame(), l\_heat(), l\_mag\_lf(), l\_anel(), l\_tp\_form(), l\_ht(), l\_mag(), l\_conv()): Module containing the logicals that control the run
- riteration\_mod(riteration\_t())
- physical\_parameters (n\_r\_lcr(), kbots(), ktops()): Module containing the physical parameters
- radial\_functions (orho1(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- leg\_helper\_mod(leg\_helper\_t())
- blocking (nfs ()): Module containing blocking information
- nonlinear\_bcs(v\_rigid\_boundary())
- truncation(l\_max(), n\_r\_maxstr(), lm\_maxmag(), lmp\_max\_dtb(), lmp\_max(), l\_axi(), n\_theta\_maxstr(), lm\_max(), nrp(), n\_phi\_maxstr()): This module defines the grid points and the truncation

# **Types**

• type riterthetablocking\_mod/unknown\_type

# Type fields

- % bslast (,,\*) [real,allocatable]
- % bplast (,,\*) [real,allocatable]
- % leg\_helper [leg\_helper\_t]
- % bzlast (,,\*) [real,allocatable]
- % nthetabs [integer]
- % sizethetab [integer]

#### **Subroutines and functions**

```
subroutine riterthetablocking_mod/allocate_common_arrays(this)
```

#### **Parameters this** [real]

subroutine riterthetablocking\_mod/deallocate\_common\_arrays(this)

## Parameters this [real]

subroutine riterthetablocking\_mod/set\_thetablocking(this, nthetabs, sizethetab)

#### **Parameters**

- this [real]
- nthetabs [integer,in]
- **sizethetab** [integer,in]

#### **Parameters**

- this [real]
- nthetastart [integer,in]
- **nthetastop** [integer,in]
- **gsa** [grid\_space\_arrays\_t]
- time [real,in]

```
Call to legtfg(), legtfgnomag(), leg_scal_to_spat(),
leg_scal_to_grad_spat(), fft_thetab(), v_rigid_boundary()
```

#### **Parameters**

- this [real]
- nthetastart [integer,in]
- **nthetastop** [integer,in]
- **gsa** [grid\_space\_arrays\_t]
- **nl\_lm** [nonlinear\_lm\_t]

Call to fft\_thetab(), legtf3(), legtf2(), legtf1(), legtf\_spher\_tor()

# 10.8.4 rIterThetaBlocking\_OpenMP.f90

## **Quick access**

**Routines** finalize\_riterthetablocking\_openmp(), initialize\_riterthetablocking\_openmp(), do\_iteration\_thetablocking\_openmp()

- probe\_mod: Module for artificial sensors to compare time series of physical data with experiments. Probes are located in a radially symmetrical way
- nonlinear\_lm\_mod(nonlinear\_lm\_t())
- grid\_space\_arrays\_mod(grid\_space\_arrays\_t())
- graphout\_mod (graphout\_mpi ()): This module contains the subroutines that store the 3-D graphic files.
- constants (zero()): module containing constants and parameters used in the code.
- nl\_special\_calc: This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)
- truncation (l\_max(), n\_r\_maxstr(), lmp\_max\_dtb(), lmp\_max(), n\_theta\_maxstr(), lm\_max(), nrp(), n\_phi\_maxstr()): This module defines the grid points and the truncation
- leg\_helper\_mod(leg\_helper\_t())
- dtb\_arrays\_mod(dtb\_arrays\_t())

- torsional\_oscillations (gettonext(), getto(), gettofinish()): This module contains information for TO calculation and output
- to\_arrays\_mod(to\_arrays\_t())
- courant\_mod(courant())
- blocking (nfs ()): Module containing blocking information
- nonlinear\_bcs(get\_br\_v\_bcs())
- radial\_functions (orho1(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- precision\_mod: This module controls the precision used in MagIC
- outrot (get\_lorentz\_torque())
- riterthetablocking\_mod(riterthetablocking\_t())
- out\_movie(store\_movie\_frame())
- dtb\_mod (get\_dh\_dtblm(), get\_dtblm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- logic (l\_to(), l\_cond\_ma(), l\_heat(), l\_mag\_lf(), l\_b\_nl\_icb(), l\_rot\_ic(), l\_mag(), l\_cond\_ic(), l\_anel(), l\_conv\_nl(), l\_conv(), l\_probe(), l\_movie\_oc(), l\_chemical\_conv(), l\_mag\_kin(), l\_store\_frame(), l\_rot\_ma(), l\_ht(), l\_mag\_nl(), l\_dtb(), l\_b\_nl\_cmb(), l\_tp\_form()): Module containing the logicals that control the run

## **Types**

type riterthetablocking\_openmp\_mod/unknown\_type

## Type fields

- % gsa (\*) [grid\_space\_arrays\_t,allocatable]
- % lorentz\_torque\_ic (\*) [real,allocatable]
- % nthreads [integer]
- % dtb\_arrays (\*) [dtb\_arrays\_t,allocatable]
- % nl\_lm (\*) [nonlinear\_lm\_t,allocatable]
- % to\_arrays(\*)[to\_arrays\_t,allocatable]
- % lorentz\_torque\_ma (\*) [real,allocatable]

## **Subroutines and functions**

```
function riterthetablocking_openmp_mod/getthistype (this)
```

**Parameters this** [real]

**Return getthistype** [character]

 $\textbf{subroutine} \ \ \texttt{riterthetablocking\_openmp\_mod/initialize\_riterthetablocking\_openmp} \ (\textit{this})$ 

**Parameters this** [real]

```
subroutine riterthetablocking_openmp_mod/do_iteration_thetablocking_openmp (this,
                                                                                                      nr,
                                                                                                      nbc,
                                                                                                      time,
                                                                                                      dt,
                                                                                                      dt-
                                                                                                      last.
                                                                                                      dsdt,
                                                                                                      dwdt,
                                                                                                      dzdt,
                                                                                                      dpdt,
                                                                                                      dx-
                                                                                                      idt,
                                                                                                      dbdt,
                                                                                                      djdt,
                                                                                                      dvxvhlm,
                                                                                                      dvxbhlm,
                                                                                                      dvs-
                                                                                                      rlm,
                                                                                                      dvprlm,
                                                                                                      dvxirlm,
                                                                                                      br_vt_lm_cmb,
                                                                                                      br_vp_lm_cmb,
                                                                                                      br\_vt\_lm\_icb,
                                                                                                      br_vp_lm_icb,
                                                                                                      lorentz_torque_ic,
                                                                                                      lorentz_torque_ma,
                                                                                                      hellmr,
                                                                                                      hel2lmr,
                                                                                                      hel-
                                                                                                      nalmr,
                                                                                                      helna2lmr,
                                                                                                      vis-
                                                                                                      clmr,
                                                                                                      uhlmr,
                                                                                                      duhlmr,
                                                                                                      grad-
                                                                                                      slmr,
                                                                                                      fcon-
                                                                                                      vlmr,
                                                                                                      fkinlmr,
                                                                                                      fvis-
                                                                                                      clmr,
                                                                                                      fpoynlmr,
                                                                                                      freslmr,
                                                                                                      eper-
                                                                                                      plmr,
                                                                                                      eparlmr,
                                                                                                      eper-
                                                                                                      рах-
                                                                                                      ilmr,
                                                                                                      eparax-
```

**Parameters** 

ilmr)

- this [real]
- **nr** [integer,in]
- **nbc** [integer,in]
- time [real,in]
- **dt** [real,in]
- dtlast [real,in]
- **dsdt** (\*) [complex,out]
- **dwdt** (\*) [complex,out]
- **dzdt** (\*) [complex,out]
- **dpdt** (\*) [complex,out]
- dxidt (\*) [complex,out]
- **dbdt** (\*) [complex,out]
- **djdt** (\*) [complex,out]
- **dvxvhlm** (\*) [complex,out]
- dvxbhlm (\*) [complex,out]
- dvsrlm (\*) [complex,out]
- **dvprlm** (\*) [complex,out]
- dvxirlm (\*) [complex,out]
- br\_vt\_lm\_cmb (\*) [complex,out]
- br\_vp\_lm\_cmb (\*) [complex,out]
- **br\_vt\_lm\_icb** (\*) [complex,out]
- br\_vp\_lm\_icb (\*) [complex,out]
- lorentz\_torque\_ic [real,out]
- lorentz\_torque\_ma [real,out]
- hellmr (\*) [real,out]
- **hel2lmr** (\*) [real,out]
- helnalmr (\*) [real,out]
- helna2lmr (\*) [real,out]
- visclmr (\*) [real,out]
- uhlmr (\*) [real,out]
- **duhlmr** (\*) [real,out]
- gradslmr (\*) [real,out]
- fconvlmr (\*) [real,out]
- **fkinlmr** (\*) [real,out]
- **fvisclmr** (\*) [real,out]
- **fpoynlmr** (\*) [real,out]

Chapter 10. Description of the Fortran modules

- freslmr (\*) [real,out]
- **eperplmr** (\*) [real,out]
- eparlmr (\*) [real,out]
- eperpaxilmr (\*) [real,out]
- eparaxilmr (\*) [real,out]

```
Call to get_br_v_bcs(), get_lorentz_torque(), courant(), graphout_mpi(),
    probe_out(),    get_helicity(),    get_visc_heat(),    get_fluxes(),
    get_perppar(),    store_movie_frame(),    get_dtblm(),    gettonext(),
    getto(), gettofinish(), get_dh_dtblm()
```

# 10.8.5 get\_nl.f90

## **Types**

• type general\_arrays\_mod/unknown\_type

## 10.8.6 get td.f90

## **Quick access**

```
Routines set_zero(), get_td()
```

- horizontal\_data (dtheta3a(), hdif\_b(), dphi0(), dtheta4a(), dtheta1a(), dlh(), dtheta2a(), dtheta3s(), hdif\_v(), dtheta4s(), dtheta1s(), dphi(), dtheta2s()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- rms (lf2hint(), pre2hint(), clf2hint(), geo2hint(), arcmag2hint(), arc2hint(), cia2hint(), cor2hint(), adv2hint(), mag2hint(), buo2hint(), plf2hint()): This module contains the calculation of thr RMS force balance and induction terms.
- fields (w\_rloc(), z\_rloc(), dz\_rloc(), dw\_rloc(), ddw\_rloc()): This module contains the potential fields and their radial derivatives
- rms\_helpers (hintrms ()): This module contains several useful subroutines required to compute RMS diagnostics
- precision\_mod: This module controls the precision used in MagIC
- logic (l\_anelastic\_liquid(), l\_mag\_nl(), l\_double\_curl(), l\_chemical\_conv(), l\_mag\_kin(), l\_conv\_nl(), l\_mag\_lf(), l\_single\_matrix(), l\_anel(), l\_heat(), l\_tp\_form(), l\_rms(), l\_conv(), l\_mag(), l\_corr()): Module containing the logicals that control the run
- physical\_parameters (buofac(), epscxi(), epsc(), vischeatfac(), ra(), n\_r\_lcr(), thexpnb(), corfac(), ohmlossfac()): Module containing the physical parameters

- truncation (lm\_max(), l\_max(), lmp\_max(), lm\_maxmag()): This module defines the grid points and the truncation
- leg\_helper\_mod(leg\_helper\_t())
- blocking (lmp2lmps(), lm2lms(), lm2lmp(), lm2m(), lm2l(), lmp2lmpa(), st\_map(), lm2lma()): Module containing blocking information
- constants (zero(), two()): module containing constants and parameters used in the code.
- radial\_functions (alpha0(), orho1(), epscprof(), or4(), rho0(), or2(), or1(), beta(), r(), temp0(), rgrav(), ogrun()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

# **Types**

• type nonlinear\_lm\_mod/unknown\_type

## Type fields

- % vxirlm(\*)[complex,allocatable]
- % vxbrlm(\*)[complex,allocatable]
- % vxiplm(\*)[complex,allocatable]
- % vstlm(\*)[complex,allocatable]
- % ohmlosslm(\*)[complex,allocatable]
- % vsplm(\*)[complex,allocatable]
- % vprlm(\*)[complex,allocatable]
- % pfp2lm (\*) [complex, allocatable]
- % lfplm(\*)[complex,allocatable]
- % lfrlm (\*) [complex,allocatable]
- % lftlm(\*)[complex,allocatable]
- % advtlm (\*) [complex,allocatable]
- % advrlm (\*) [complex, allocatable]
- % advplm (\*) [complex,allocatable]
- % pft2lm (\*) [complex,allocatable]
- % cfp2lm(\*)[complex,allocatable]
- % advt2lm(\*)[complex,allocatable]
- % vsrlm(\*)[complex,allocatable]
- % lfp2lm(\*)[complex,allocatable]
- % vxbplm (\*) [complex,allocatable]
- % vxitlm(\*)[complex,allocatable]
- % lft2lm(\*)[complex,allocatable]
- % vxbtlm(\*)[complex,allocatable]
- % vischeatlm(\*)[complex,allocatable]

- % cft2lm(\*)[complex,allocatable]
- % advp2lm(\*)[complex,allocatable]

#### Subroutines and functions

subroutine nonlinear\_lm\_mod/initialize(this, lmp\_max)

#### **Parameters**

- this [real]
- lmp\_max [integer,in]

subroutine nonlinear\_lm\_mod/finalize(this)

## **Parameters this** [real]

subroutine nonlinear\_lm\_mod/set\_zero(this)

## **Parameters this** [real]

subroutine nonlinear\_lm\_mod/output (this)

## **Parameters this** [real]

Purpose of this to calculate time derivatives dwdt,dzdt,dpdt,dsdt,dxidt,dbdt,djdt and auxiliary arrays dVSrLM, dVXirLM and dVxBhLM, dVxVhLM from non-linear terms in spectral form, contained in flmw1-3,flms1-3, flmb1-3 (input)

- Input of variables:

- this [real]
- **nr** [integer,in]
- **nbc** [integer,in] :: signifies boundary conditions
- **lrmscalc** [logical,in]
- **lpresscalc** [logical,in]
- **dvsrlm** (\*) [complex,out]
- **dvprlm** (\*) [complex,out]
- $\bullet \ \ dvxirlm \ (*) \ [\mathit{complex}, \mathit{out}]$
- **dvxvhlm** (\*) [complex,out]
- dvxbhlm (\*) [complex,out]
- **dwdt** (\*) [complex,out]
- **dzdt** (\*) [complex,out]
- **dpdt** (\*) [complex,out]
- **dsdt** (\*) [complex,out]
- dxidt (\*) [complex,out]

- **dbdt** (\*) [complex,out]
- **djdt** (\*) [complex,out]
- **leg\_helper** [leg\_helper\_t,in]

Call to hintrms()

## 10.8.7 nonlinear bcs.f90

#### **Quick access**

```
Routines get_b_nl_bcs(), get_br_v_bcs(), v_rigid_boundary()
```

#### **Needed modules**

- horizontal\_data (phi(), dthetala(), dlh(), sn2(), o\_sin\_theta(), dthetals(), dphi(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- legendre\_grid\_to\_spec(legtf2())
- useful (abortrun ()): library with several useful subroutines
- fft (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- logic (l\_diff\_prec()): Module containing the logicals that control the run
- physical\_parameters (po\_diff(), diff\_prec\_angle(), prmag(), sigma\_ratio(), oek(), conductance\_ma()): Module containing the physical parameters
- truncation (1\_axi(), nrp(), n\_phi\_max(), lmp\_max()): This module defines the grid points and the truncation
- blocking (lmp2lmps(), lm2lmp(), sizethetab(), lm2m(), lm2l(), nfs(), lmp2lmpa()): Module containing blocking information
- constants (two ()): module containing constants and parameters used in the code.
- radial\_functions (r\_cmb(), r\_icb(), rho0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

## Subroutines and functions

Purpose of this subroutine is to calculate the nonlinear term of the magnetic boundary condition for a conducting mantle or inner core in space (r,lm). Calculation is performed for the theta block:

```
n_theta_min<=n_theta<=n_theta_min+n_theta_block-1
```

On input br, vt and vp are given on all phi points and thetas in the specific block. On output the contribution of these grid points to all degree and orders is stored in br\_vt\_lm and br\_vp\_lm. Output is [r/sin(theta)\*Br\*U]=[(0,br\_vt\_lm,br\_vp\_lm)]

- input:

## **Parameters**

- **br** (nrp,\*) [real,in] ::  $r**2*B_r$
- vt (nrp,\*) [real,in] :: r\*sin(theta) U\_theta
- **vp** (*nrp*,\*) [real,in] :: r\*sin(theta) U phi
- omega [real,in] :: rotation rate of mantle or IC
- **o\_r\_e\_2** [real,in] :: 1/r\*\*2
- **o\_rho** [real,in] :: 1/rho0 (anelastic)
- n\_theta\_min [integer,in] :: start of theta block
- n\_theta\_block [integer,in] :: size of theta\_block
- **br\_vt\_lm** (*lmp\_max*) [complex,inout]
- **br\_vp\_lm** (*lmp\_max*) [complex,inout]

```
Call to fft_thetab(), legtf2()
```

#### **Parameters**

- **bc** [character,in] :: Distinguishes 'CMB' and 'ICB'
- **br\_vt\_lm** (*lmp\_max*) [*complex,in*] :: [br\*vt/(r\*\*2\*sin(theta)\*\*2)]
- **br\_vp\_lm** (*lmp\_max*) [*complex,in*] :: [br\*vp/(r\*\*2\*sin(theta)\*\*2)
- **lm min b** [integer,in] :: limits of lm-block
- **Im max b** [integer,in] :: nonlinear bc for a
- **b\_nl\_bc** (lm\_max\_b-lm\_min\_b+1) [complex,out]
- aj\_nl\_bc (lm\_max\_b-lm\_min\_b+1) [complex,out]

Called from step\_time()

Call to abortrun()

Purpose of this subroutine is to set the velocities and their derivatives at a fixed boundary. While vt is zero, since we only allow for rotation about the z-axix, vp=  $r \sin(theta)$  v\_phi =  $r^**2 \sin(theta)^**2$  omega cvr=  $r^**2$  radial component of (curl v) =  $r^**2$  2 cos(theta) omega

- Input of variables:

#### **Parameters**

```
• nr [integer,in] :: no of radial grid point
```

- omega [real,in]
- **Ideriv** [logical,in] :: derivatives required?
- **vrr** (*nrp*,*nfs*) [real,out]
- **vtr** (*nrp*,*nfs*) [real,out]
- **vpr** (*nrp*,*nfs*) [real,out]
- **cvrr** (*nrp*,*nfs*) [real,out]
- **dvrdtr** (*nrp*,*nfs*) [real,out]
- **dvrdpr** (*nrp*,*nfs*) [real,out]
- **dvtdpr** (*nrp*,*nfs*) [real,out]
- **dvpdpr** (*nrp*,*nfs*) [real,out]
- **nthetastart** [integer,in] :: no of theta to start with
- time [real,in]

Called from transform\_to\_grid\_space(), transform\_to\_grid\_space\_shtns()

# 10.9 Chebyshev polynomials and cosine transforms

# 10.9.1 chebyshev\_polynoms.f90

## Quick access

```
Routines cheb_grid(), get_chebs_even()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- num\_param (map\_function ()): Module containing numerical and control parameters
- constants (one (), four (), pi (), two (), half ()): module containing constants and parameters used in the code.
- logic (l\_newmap()): Module containing the logicals that control the run

# **Variables**

# **Subroutines and functions**

Construct even Chebychev polynomials and their first, second and third derivative up to degree  $2*(n_r/2)$  at  $(n_r/2)$  points x in the interval [a,b]. Since the Chebs are only defined in [-1,1] we have to map the points x in [a,b] onto points y in the interval [-1,1]. This map is contructed by the subroutine cheb\_x\_map\_e.f which must be called before entering this subroutine. For even Chebs we need only half the point of the map, these  $(n_r/2)$  points are in the interval [1,0]. NOTE the reversed order in the points: y(1)=-1,  $y(n_r)=1$ . y=0 is not used, which helps to avoid singularities.

## - Input variables:

#### **Parameters**

- n\_r [integer,in] :: number of grid points
- a [real,in] :: interval boundaries [a,b]
- **b** [real,in]
- y (n\_r\_max) [real,in] :: n\_r grid points in interval [a,b]
- n\_r\_max [integer,in,] :: max number of radial points, dims of y
- **cheb** (dim1,dim2) [real,out] :: cheb(i,j) is Chebychev pol.
- **dcheb** (dim1,dim2) [real,out] :: first derivative of cheb
- **d2cheb** (dim1,dim2) [real,out] :: second derivative o cheb
- **dim1** [integer,in] :: dimensions of cheb,dcheb,.....
- dim2 [integer,in]

Called from radial()

```
subroutine chebyshev_polynoms_mod/cheb_grid(a, b, n, x, y, a1, a2, x0, lbd, l_map)
```

Given the interval [a,b] the routine returns the n+1 points that should be used to support a Chebychev expansion. These are the n+1 extrema y(i) of the Chebychev polynomial of degree n in the interval [-1,1]. The respective points mapped into the interval of question [a,b] are the x(i).

**Note:** x(i) and y(i) are stored in the reversed order:

```
x(1)=b, x(n+1)=a, y(1)=1, y(n+1)=-1
```

## - Input variables

- a [real,in] :: interval boundaries
- **b** [real,in]
- **n** [integer,in] :: degree of Cheb polynomial to be represented by the grid points
- $\mathbf{x}$  (\*) [real,out] :: grid points in interval [a,b]
- y (\*) [real,out] :: grid points in interval [-1,1]
- **a1** [real,in]
- **a2** [real,in]
- **x0** [real,in]
- **lbd** [real,in]
- **l\_map** [logical,in] :: Chebyshev mapping

Called from initialize\_mapping(), chebintinit(), radial()

## 10.9.2 cosine\_transform\_odd.f90

## **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), factorise()): library with several useful subroutines
- precision\_mod: This module controls the precision used in MagIC
- fft\_fac\_mod(fft\_fac\_complex(), fft\_fac\_real())
- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.
- truncation (1m\_max(), 1m\_max\_real()): This module defines the grid points and the truncation

# **Types**

• type cosine\_transform\_odd/unknown\_type

# Type fields

- % i\_costf\_init (\*) [integer,allocatable]
- % d\_costf\_init (\*) [real,allocatable]

## Subroutines and functions

```
subroutine cosine transform odd/initialize(this, n, ni, nd)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast cosine transform of the first kind. The actual transform is performed by the subroutine costf1.

## **Parameters**

- this [real]
- **n** [integer,in]
- ni [integer,in]
- **nd** [integer,in]

Call to abortrun(), factorise()

```
subroutine cosine_transform_odd/finalize(this)
```

# **Parameters this** [real]

```
subroutine cosine transform odd/costf1 complex(this, f, n f max, n f start, n f stop, f2)
```

Purpose of this subroutine is to perform a multiple cosine transforms for n+1 datapoints on the columns numbered n\_f\_start to n\_f\_stop in the array f(n\_f\_max,n+1) Depending whether the input f contains data or coeff arrays coeffs or data are returned in f.

## **Parameters**

```
• this [real]
```

- **f** (n\_f\_max,\*) [complex,inout]
- n\_f\_max [integer,in,]
- **n\_f\_start** [integer,in]
- **n\_f\_stop** [integer,in]
- **f2** (n\_f\_max,\*) [complex,out]

Call to fft\_fac\_complex()

subroutine cosine\_transform\_odd/costf1\_complex\_1d(this, f, f2)

## **Parameters**

- this [real]
- **f** (\*) [complex,inout]
- **f2** (\*) [complex,out]

Call to fft\_fac\_complex()

subroutine cosine\_transform\_odd/costf1\_real (this, f, n\_f\_max, n\_f\_start, n\_f\_stop, f2)

#### **Parameters**

- this [real]
- **f** (n\_f\_max,\*) [real,inout]
- n\_f\_max [integer,in,]
- n\_f\_start [integer,in]
- n\_f\_stop [integer,in]
- **f2** (n\_f\_max,\*) [real,out]

Call to fft\_fac\_real()

subroutine cosine\_transform\_odd/costf1\_real\_1d(this, f, f2)

# **Parameters**

- this [real]
- **f** (\*) [real,inout]
- **f2** (\*) [real,out]

Call to fft\_fac\_real()

# 10.9.3 cosine\_transform\_even.f90

## **Quick access**

Routines costf2()

#### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), factorise()): library with several useful subroutines
- precision\_mod: This module controls the precision used in MagIC
- fft\_fac\_mod(fft\_fac\_complex())
- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.
- truncation (lm\_max()): This module defines the grid points and the truncation

## **Types**

• type cosine\_transform\_even/unknown\_type

## Type fields

- % i\_costf\_init(\*)[integer,allocatable]
- % d\_costf\_init (\*) [real,allocatable]

#### Subroutines and functions

```
subroutine cosine_transform_even/initialize(this, n, ni, nd)
```

Purpose of this subroutine is to calculate several things needed for the cheb transform. Prepares costf2 for even number of grid points.

## **Parameters**

- this [real]
- **n** [integer,in]
- **ni** [integer,in]
- **nd** [integer,in]

Call to abortrun(), factorise()

subroutine cosine\_transform\_even/finalize(this)

#### **Parameters this** [real]

```
subroutine cosine_transform_even/costf2 (this, f, n_f_max, n_f_start, n_f_stop, f2, isign)
```

Purpose of this subroutine is to perform a multiple cosine transforms for n+1 datapoints on the columns numbered  $n_f$ \_start to  $n_f$ \_stop in the array  $y(n_f_max,n+1)$  Depending whether the input y contains data or coeff arrays coeffs or data are returned in y.

- this [real]
- **f** (n\_f\_max,\*) [complex,inout] :: data/coeff input
- **n\_f\_max** [integer,in,] :: number of columns in y,y2

```
• n_f_start [integer,in] :: columns to be transformed
```

- **n\_f\_stop** [integer,in]
- **f2** (n\_f\_max,\*) [complex,out] :: work array of the same size as y
- **isign** [integer,in] :: = +1 (-1) for forward (backward) transform

Call to fft\_fac\_complex()

# 10.9.4 fft fac.f90

## **Quick access**

```
Routines fft_fac_real(), fft_fac_complex()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- constants (cos36(), sin36(), cos72(), sin72(), sin60(), half()): module containing constants and parameters used in the code.

## **Variables**

## **Subroutines and functions**

```
subroutine fft_fac_mod/fft_fac_real (a, b, c, d, trigs, nv, l1, l2, n, ifac, la)
    main part of Fourier / Chebychev transform called in costf1, costf2
    - Input variables:
```

## **Parameters**

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (2 \* n) [real,in]
- nv [integer,in]
- **l1** [integer,in]
- 12 [integer,in]
- **n** [integer,in,]
- ifac [integer,in]
- la [integer,in]

```
\textbf{subroutine} \ \texttt{fft\_fac\_mod/fft\_fac\_complex} \ (\textit{a,b,c,d,trigs,nv}, \textit{l1}, \textit{l2}, \textit{n}, \textit{ifac,la})
```

main part of Fourier / Chebychev transform called in costf1, costf2

## - Input variables:

## **Parameters**

- **a** (\*) [complex,in]
- **b** (\*) [complex,in]
- **c** (\*) [complex,out]
- **d** (\*) [complex,out]
- **trigs** (2 \* n) [real,in]
- **nv** [integer,in]
- **l1** [integer,in]
- **12** [integer,in]
- **n** [integer,in,]
- ifac [integer,in]
- la [integer,in]

Called from costf2()

# 10.10 Legendre transforms

10.10.1 plms.f90

## **Quick access**

Routines plm\_theta()

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- constants (osq4pi (), two (), one ()): module containing constants and parameters used in the code.

## **Variables**

#### Subroutines and functions

- theta [real,in] :: angle in degrees
- max\_degree [integer,in] :: required max degree of plm
- max\_order [integer,in] :: required max order of plm

- **m0** [integer,in] :: basic wave number
- **plma** (ndim\_plma) [real,out] :: ass. legendres at theta
- **dtheta\_plma** (ndim\_plma) [real,out] :: their theta derivative
- ndim\_plma [integer,in] :: dimension of plma and dtheta\_plma
- **norm** [integer,in] :: =0 fully normalised

```
Called from outto(), lnpas2tr(), horizontal(), outpv(), getegeos(),
   initialize_magnetic_energy()
Call to abortrun()
```

# 10.10.2 legendre\_helpers.f90

## **Quick access**

```
Routines finalize(), initialize(), legprepg(), legprep(), legprep_ic()
```

## **Needed modules**

- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fields(z\_rloc(), s\_rloc(), ddw\_rloc(), dj\_rloc(), b\_rloc(), ddb\_rloc(), db\_rloc(), dw\_rloc(), w\_rloc(), p\_rloc(), aj\_rloc(), dp\_rloc(), dz\_rloc(), ds\_rloc(), omega\_ma(), xi\_rloc(), omega\_ic()): This module contains the potential fields and their radial derivatives
- torsional\_oscillations (ddzasl()): This module contains information for TO calculation and output
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- constants (zero(), two(), one()): module containing constants and parameters used in the code.
- logic (l\_movie\_oc(), l\_chemical\_conv(), l\_mag\_kin(), l\_heat(), l\_mag\_lf(), l\_fluxprofs(), l\_mag(), l\_conv()): Module containing the logicals that control the run
- truncation (lm\_max(), l\_max(), l\_axi(), n\_m\_max()): This module defines the grid points and the truncation
- blocking (1m2m(), 1m21(), 1m2()): Module containing blocking information
- special (lgrenoble(), ddb0(), b0(), db0()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- radial\_functions (or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Types**

```
• type leg_helper_mod/unknown_type
           Type fields
              - % bcmb (*) [complex, allocatable]
               - % omegaic [real]
               - % dlhz (*) [complex,allocatable]
              - % bhc (*) [complex,allocatable]
              - % dlhw (*) [complex,allocatable]
               - % bhg (*) [complex,allocatable]
              - % omegama [real]
              - % dlhj(*) [complex,allocatable]
              - % dlhb (*) [complex,allocatable]
               - % zas (*) [real, allocatable]
              - % dzas (*) [real, allocatable]
               - % ddzas (*) [real,allocatable]
               - % dpr (*) [complex,allocatable]
              - % dlhdw (*) [complex, allocatable]
              - % sr (*) [complex,allocatable]
               - % dsr(*)[complex,allocatable]
              - % dvhdrg (*) [complex, allocatable]
              - % xir(*)[complex,allocatable]
               - % dvhdrc (*) [complex,allocatable]
               - % cbhg (*) [complex,allocatable]
               - % vhg (*) [complex,allocatable]
               - % cbhc (*) [complex,allocatable]
               - % vhc (*) [complex,allocatable]
              - % prer (*) [complex,allocatable]
```

## **Variables**

## **Subroutines and functions**

```
subroutine leg_helper_mod/initialize(this, lm_max, lm_maxmag, l_max)
```

- this [real]
- lm\_max [integer,in]
- lm\_maxmag [integer,in]

• l\_max [integer,in]

subroutine leg\_helper\_mod/finalize(this)

## Parameters this [real]

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dpdw,dpddw, ...... dLhj which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as the radial dependence:

- nBc =0 standard inner radial grid point
- nBc =1 radial velocity zero, spatial derivs not needed
- nBc =2 all velocity comp. zero, spatial derivs not needed

lDeriv=.true. field derivatives required

## **Parameters**

- this [real]
- nr [integer,in] :: radial level
- **nbc** [integer,in] :: boundary condition
- Ideriv [logical,in] :: get also field derivatives !
- **Irmscalc** [logical,in] :: Rms force balance?
- **lpresscalc** [logical,in] :: Pressure ?
- **l\_frame** [logical,in] :: Calculate movie frame?
- **Itonext** [logical,in] :: for TO output
- ltonext2 [logical,in]
- **Itocalc** [logical,in]

**subroutine** leg\_helper\_mod/**legprep** (w, dw, ddw, z, dz, dlh, lm\_max, l\_max, minc, r, lderiv, lhor, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays w, dw, ddw, ...... which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

1Deriv=.true. field derivatives required for curl of field

– Input variables:

- w (lm\_max) [complex,in]
- **dw** (*lm\_max*) [complex,in]
- **ddw** (*lm\_max*) [*complex*,*in*]
- **z** (lm\_max) [complex,in]
- **dz** (*lm\_max*) [*complex*, *in*]
- **dlh** (*lm\_max*) [*real*,*in*]
- lm\_max [integer,in,]

- l\_max [integer,in]
- minc [integer,in]
- **r** [real,in]
- Ideriv [logical,in]
- **lhor** [logical,in]
- **dlhw** (\*) [complex,out]
- **vhg** (\*) [complex,out]
- **vhc** (\*) [complex,out]
- **dlhz** (\*) [complex,out]
- cvhg (\*) [complex,out]
- cvhc (\*) [complex,out]

Called from fields\_average()

**subroutine** leg\_helper\_mod/**legprep\_ic**(w, dw, ddw, z, dz, dlh, lm\_max, l\_max, minc, r, r\_icb, lderiv, lhor, lcondic, dlhw, vhg, vhc, dlhz, cvhg, cvhc)

Purpose of this subroutine is to prepare Legendre transforms from (r,l,m) space to (r,theta,m) space by calculating auxiliary arrays dLhw,vhG, ....... which contain combinations of harmonic coeffs multiplied with (l,m)-dependend factors as well as possible the radial dependencies.

lDeriv=.true. field derivatives required for curl of field

Note: This routine is used for the inner core magnetic field which has a special radial function ansatz. It can also be used to prepare the calculation of a field in an insulating inner core for lCondIC=.false.. For this the w has to be the outer core poloidal field and nR is the grid point for the ICB. In any case legTF can be used for the following Legendre transform and fftJW for the Fourier transform.

## - Input variables:

- w (lm\_max) [complex,in]
- **dw** (*lm\_max*) [complex,in]
- **ddw** (*lm\_max*) [*complex*, *in*]
- **z** (lm\_max) [complex,in]
- **dz** (*lm\_max*) [*complex*,*in*]
- **dlh** (*lm\_max*) [*real*,*in*]
- lm max [integer,in,]
- l\_max [integer,in]
- minc [integer,in]
- **r** [real,in]
- **r\_icb** [real,in]
- **Ideriv** [logical,in]
- **lhor** [logical,in]
- lcondic [logical,in]

```
• dlhw (lm_max) [complex,out]
```

- **vhg** (*lm\_max*) [*complex,out*]
- **vhc** (*lm\_max*) [*complex,out*]
- **dlhz** (*lm\_max*) [*complex,out*]
- **cvhg** (*lm\_max*) [*complex,out*]
- cvhc (lm max) [complex,out]

Called from graphout\_ic(), store\_movie\_frame\_ic()

# 10.10.3 legendre\_spec\_to\_grid.f90

#### **Quick access**

```
Routines lmas2pt(), legtf(), legtfg(), legtfgnomag(), leg_scal_to_grad_spat(), leg_scal_to_spat()
```

## **Needed modules**

- horizontal\_data(dplm(), d\_mc2m(), lstop(), lmodd(), osn2(), plm(), lstart()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod (rank ()): This module contains the blocking information
- useful (abortrun ()): library with several useful subroutines
- precision mod: This module controls the precision used in MagIC
- leg\_helper\_mod(leg\_helper\_t())
- blocking (lm2mc(), lm2(), nfs(), sizethetab()): Module containing blocking information
- constants (zero(), one(), half()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), nrp(), l\_axi(), n\_m\_max()): This module defines the grid points and the truncation

### **Variables**

## Subroutines and functions

Legendre transform from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l is the degree of the spherical harmonic representation.

Transforms entropy, velocity and magnetic field components and terms involving spatial derivatives. The symmetry properties of the P\_lm with respect to the equator are used. The equatorially antisymmetric (EA) contribution is added to (subracted from ) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

• nBc: (input) accounts for special conditions on radial boundaries

-nBc=2: we are dealing with a no slip boundary, v\_r and v\_theta are zero and v\_phi=r sin(theta) omega, where omega is the rotation rate of the boundary (mantle of IC), only magn. field terms are calculated, v is set later.

-nBc=1: a free slip bounday: v\_r is zero, derivatives of v and B are not needed, only components of v,B and entropy are calculated

- -nBc=0: normal case, interior grid point
  - lDeriv=.true. : (input) calculate derivatives
  - nThetaStart: (input) transformation is done for the range of

points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB \* Plm : associated Legendre polynomials \* dPlm : sin(theta) d Plm / d theta \* osn2 : 1/sin(theta)^2 \* vrc, ...., : (output) components in (nTheta,m)-space \* dLhw,...,cbhC : (input) help arrays calculated in s\_legPrep.f

## - Input variables:

## **Parameters**

- **nbc** [integer,in]
- **Ideriv** [logical,in]
- **nthetastart** [integer,in]
- **vrc** (*nrp*,*nfs*) [real,out]
- **vtc** (*nrp*,*nfs*) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (nrp,nfs) [real,out]
- **dvtdrc** (nrp,nfs) [real,out]
- **dvpdrc** (*nrp*,*nfs*) [real,out]
- **cvrc** (nrp,nfs) [real,out]
- **dvrdtc** (nrp,nfs) [real,out]
- **dvrdpc** (*nrp*,*nfs*) [real,out]
- **dvtdpc** (*nrp*,*nfs*) [real,out]
- **dvpdpc** (*nrp*,*nfs*) [real,out]
- **brc** (*nrp*,*nfs*) [real,out]
- **btc** (*nrp*,*nfs*) [real,out]
- **bpc** (*nrp*,*nfs*) [real,out]
- **cbrc** (*nrp*,*nfs*) [real,out]
- **cbtc** (*nrp*,*nfs*) [real,out]
- **cbpc** (*nrp*,*nfs*) [real,out]
- leg\_helper [leg\_helper\_t]

Called from transform\_to\_grid\_space()

Same as legTFG for non-magnetic cases

## - Input:

#### **Parameters**

- **nbc** [integer,in]
- Ideriv [logical,in]
- nthetastart [integer,in]
- **vrc** (*nrp*,*nfs*) [real,out]
- vtc (nrp,nfs) [real,out]
- **vpc** (*nrp*,*nfs*) [real,out]
- **dvrdrc** (nrp,nfs) [real,out]
- **dvtdrc** (nrp,nfs) [real,out]
- **dvpdrc** (nrp,nfs) [real,out]
- **cvrc** (*nrp*,*nfs*) [real,out]
- **dvrdtc** (nrp,nfs) [real,out]
- **dvrdpc** (*nrp*,*nfs*) [real,out]
- **dvtdpc** (nrp,nfs) [real,out]
- **dvpdpc** (*nrp*,*nfs*) [real,out]
- leg\_helper [leg\_helper\_t]

Called from transform\_to\_grid\_space()

'Legendre transform' from (nR,l,m) to (nR,nTheta,m) [spectral to grid] where nTheta numbers the colatitudes and l and m are degree and order of the spherical harmonic representation.

Calculates all three spherical components vrc,vtc,vpc of a field as well as its curl (cvrc,cvtc,cvpc) that is given a spherical harmonis poloidal toroidal decomposition. s\_legPrep.f has to be called first and provides the input fields dLhW, ..... The symmetry properties of the P\_lm with respect to the equator are used. The equatorially anti-symmetric (EA) contribution is added to (subracted from ) the equatorially symmetric (ES) contribution in northern (southern) hemisphere.

Output is given for all sizeThetaB colatitudes in a colatitude block that starts with colatitude nThetaStart. At output, each component in the northern hemisphere is followed by the component in the southern hemisphere. The Plms and dPlms=sin(theta) d Plm / d theta are only given for the colatitudes in the northern hemisphere.

- dLhw,...,cvhC : (input) arrays provided by legendre\_helpers.f90
- 1\_max : (input) maximum spherical harmonic degree
- minc: (input) azimuthal symmetry
- nThetaStart : (input) transformation is done for the range of

points nThetaStart <= nTheta <= nThetaStart-1+sizeThetaB \* sizeThetaB : (input) size theta block \* Plm : (input) associated Legendre polynomials \* dPlm : (input) sin(theta) d Plm / d theta \* lHor=.true. : (input) calculate horizontal componenst \* lDeriv=.true. : (input) calculate curl of field \* vrc, ...,cvpc : (output) components in (nTheta,m)-space

– Input: — Stuff precomputed in legPrep:

```
Parameters
```

```
• dlhw (*) [complex,in]
                • vhg (*) [complex,in]
                • vhc (*) [complex,in]
                • dlhz (*) [complex,in]
                • cvhg (*) [complex,in]
                • cvhc (*) [complex,in]
                • l_max [integer,in]
                • minc [integer,in]
                • nthetastart [integer,in]
                • sizethetab [integer,in]
                • plm (lm_max,*) [real,in]
                • dplm (lm_max,*) [real,in]
                • lhor [logical,in]
                • Ideriv [logical,in]
                • vrc (nrp,*) [real,out]
                • vtc (nrp,*) [real,out]
                • vpc (nrp,*) [real,out]
                • cvrc (nrp,*) [real,out]
                • cvtc (nrp,*) [real,out]
                • cvpc (nrp,*) [real,out]
          Called from fields_average(), graphout_ic(), store_movie_frame_ic()
          Call to abortrun()
subroutine legendre_spec_to_grid/leg_scal_to_spat (nthetastart, slm, sc)
          Legendre transform from (1) to (theta) for a scalar input field
     - Input variable
          Parameters
                 • nthetastart [integer,in]
                 • slm (lm_max) [complex,in]
                 • sc (nrp,nfs) [real,out]
          Called from transform_to_grid_space()
subroutine legendre_spec_to_grid/leg_scal_to_grad_spat (nthetastart, slm, gradtc,
                                                                           gradpc)
          Transform s(l) into dsdt(theta) and dsdp(theta)
     - Input variable
          Parameters
                 • nthetastart [integer,in]
```

- slm (lm\_max) [complex,in]
- gradtc (nrp,nfs) [real,out]
- gradpc (nrp,nfs) [real,out]

Called from transform\_to\_grid\_space()

subroutine legendre\_spec\_to\_grid/lmas2pt (alm, aij, nthetastart, nthetablocksize)

Spherical harmonic transform from alm(l) to aij(theta) Done within the range [nThetaStart,n\_thetaStart+nThetaBlockSize-1] only considering axisymmetric contributions. alm contains only m=0 coefficients

- Input variables:

#### **Parameters**

- **alm** (\*) [real,in] :: field in (l,m)-space
- aij (\*) [real,out] :: field in (theta,phi)-space
- **nthetastart** [integer,in] :: first theta to be treated
- nthetablocksize [integer,in]

Called from get\_power(), outpar(), outhelicity(), outperppar()

# 10.10.4 legendre\_grid\_to\_spec.f90

#### **Quick access**

```
Routines legtfas2(), legtfas(), legtf1(), legtf2(), legtf_spher_tor(), legtf3()
```

#### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- horizontal\_data (d\_mc2m(), wplm(), lmoddp(), wdplm(), lstopp(), lstartp()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- blocking (nfs(), sizethetab()): Module containing blocking information
- constants (ci ()): module containing constants and parameters used in the code.
- truncation(n\_theta\_max(), nrp(), n\_m\_max(), lmp\_max()): This module defines the grid points and the truncation

## **Variables**

## Subroutines and functions

```
subroutine legendre_grid_to_spec/legtf1(nthetastart, fllm, fltm)
```

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays f1TM (input) to f1LM (output) One call to this routine does part of the transform by summation over theta points in one theta block: nThetaStart,..,nThetaStart+n theta block-1

## - Input variables:

## **Parameters**

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex*, *inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]

**Called from** initv(), inits(), initxi(), transform to lm space()

subroutine legendre\_grid\_to\_spec/legtf2 (nthetastart, fllm, f2lm, f2tm)

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays f1TM,f2TM (input) to f1LM,f2LM (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,..,nThetaStart+n\_theta\_block-1

- Input variables:

## **Parameters**

- **nthetastart** [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex*, *inout*]
- **f2lm** (*lmp\_max*) [*complex,inout*]
- fltm (nrp,nfs) [real,in]
- **f2tm** (*nrp*,*nfs*) [*real*,*in*]

**Called from** get\_br\_v\_bcs(), transform\_to\_lm\_space(), get\_dtblm()

subroutine legendre\_grid\_to\_spec/legtf3 (nthetastart, fllm, f2lm, f3lm, f1tm, f2tm, f3tm)

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2/3 (input) to flm1/2/3 (output) One call to this routine does part of the transform by summation over theta points in on theta block: nThetaStart,...,nThetaStart+n\_theta\_block-1

- Input variables:

## **Parameters**

- nthetastart [integer,in] :: First no of theta on block
- **f1lm** (*lmp\_max*) [*complex*, *inout*]
- **f2lm** (*lmp\_max*) [*complex*, *inout*]
- **f3lm** (*lmp\_max*) [*complex,inout*]
- **f1tm** (*nrp*,*nfs*) [real,in]
- **f2tm** (*nrp*,*nfs*) [real,in]
- **f3tm** (*nrp*,*nfs*) [*real*,*in*]

Called from transform\_to\_lm\_space(), get\_dtblm()

 $\textbf{subroutine} \ \texttt{legendre\_grid\_to\_spec/legtf\_spher\_tor} \ (\textit{nthetastart}, \textit{f1lm}, \textit{f2lm}, \textit{f1tm}, \textit{f2tm})$ 

Vector Legendre transform  $vt(n_r,n_t)$ ,  $vp(n_r,n_t)$  to Spheroidal $(n_r,l,m)$  and Toroidal $(n_r,l,m)$ 

- Input variables:

#### **Parameters**

• **nthetastart** [integer,in] :: First no of theta on block

- **f1lm** (*lmp\_max*) [*complex,inout*]
- **f2lm** (*lmp\_max*) [complex,inout]
- fltm (nrp,nfs) [real,in]
- **f2tm** (nrp,nfs) [real,in]

Called from transform to 1m space()

**subroutine** legendre grid to spec/**legtfas**(flm1, ft1, lmmax, nthetastart, sizethetab)

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n\_theta\_min,..,n\_theta\_min+n\_theta\_block-1

- Input variables:

## **Parameters**

- flm1 (\*) [real,out]
- ft1 (\*) [real,in]
- **Immax** [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- sizethetab [integer,in] :: Size of theta block

Called from outto(), get\_visc\_heat(), get\_nlblayers(), get\_fluxes()

subroutine legendre\_grid\_to\_spec/legtfas2(flm1, flm2, ft1, ft2, lmmax, nthetastart, sizethetab)

Legendre transform (n\_r,n\_theta,m) to (n\_r,l,m) [grid to spectral] for 2 arrays ancl1/2 (input) to flm1/2 (output) One call to this routine does part of the transform by summation over theta points in on theta block: n\_theta\_min,..,n\_theta\_min+n\_theta\_block-1

- Input variables

## **Parameters**

- **flm1** (\*) [real,out]
- flm2 (\*) [real,out]
- ft1 (\*) [real,in]
- ft2 (\*) [real,in]
- Immax [integer,in] :: Number of modes to be processed
- **nthetastart** [integer,in] :: First no of theta on block
- **sizethetab** [integer,in] :: Size of theta block

Called from get\_perppar(), outto(), get\_nlblayers(), get\_fluxes(),
 get\_helicity(), getto()

# 10.11 Fourier transforms

## 10.11.1 fft.f90

## **Description**

This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5

## **Quick access**

```
Variables nd, ni, i_fft_init, d_fft_init
Routines finalize_fft(), wpass3jw(), wpass4jw(), wpass5jw(), wpass2jw(),
    fftjw(), fft99ajw(), fft_thetab(), fft_to_real(), init_fft(), fft99bjw()
```

## **Needed modules**

- parallel\_mod: This module contains the blocking information
- useful (abortrun(), factorise()): library with several useful subroutines
- precision\_mod: This module controls the precision used in MagIC
- blocking: Module containing blocking information
- constants (cos36(), sin36(), cos72(), two(), one(), sin72(), sin60(), half(), pi()): module containing constants and parameters used in the code.
- truncation: This module defines the grid points and the truncation

## **Variables**

- fft/ni [integer,private/parameter=100]
- fft/nd[integer,private]
- fft/d\_fft\_init (:) [real,private/allocatable]
- fft/i\_fft\_init (100) [integer,private]

## Subroutines and functions

```
subroutine fft/init_fft(n)
```

Purpose of this subroutine is to calculate and store several values that will be needed for a fast fft transform. The actual transform is performed by the subroutine fftJW.

- Input variable:

```
Called from finalize_horizontal_data()
```

subroutine fft/fft\_to\_real(f, ld\_f, nrep)

## **Parameters**

- **f** (ld\_f,nrep) [real,inout]
- ld f [integer, in, ]
- **nrep** [integer,in,]

Called from getdvptr()

Call to fft jw()

subroutine fft/fft thetab(f, dir)

#### **Parameters**

- **f** (nrp,nfs) [real,inout]
- **dir** [integer,in] :: back or forth transform

```
Called from fields_average(), graphout_ic(), get_bpol(), initv(),
  inits(), get_btor(), initxi(), lm2pt(), get_br_v_bcs(),
  transform_to_grid_space(), transform_to_lm_space(), get_dtblm(),
  store movie frame ic(), get b surface()
```

Call to fft jw()

subroutine fft/fftjw(a, ld\_a, n, isign, nsize, wrk, wd1, wd2, i\_fft\_init, d\_fft\_init)

The routines has been adopted by Gary Glatzmaier and has subsequently been modified by Uli Christensen and Johannes Wicht

It performs a number of simultaneous real/half-complex periodic fast fourier transforms or corresponding inverse transforms, using ordinary spatial order of gridpoint values. given a set of real data vectors, the package returns a set of "half-complex" fourier coefficient vectors, or vice versa. the length of the transforms must be an even number that has no other factors except possibly powers of 2, 3, and 5. this version of fft991 is optimized for use on the cray-1.

on input a(ld\_a,\*) an array of length (ld\_a,nsize) containing the input data or coefficient vectors. This array is overwritten by the results.

n the length of each transform (see definition of transforms, below).

nsize the number of transforms to be done simultaneously.

isign = +1 for a transform from fourier coefficients to gridpoint values. = -1 for a transform from gridpoint values to fourier coefficients.

on output a if isign = +1, and n\_theta\_max coefficient vectors are supplied each containing the sequence

```
a(0),b(0),a(1),b(1),...,a(n/2),b(n/2) (n+2 values)
```

then the result consists of n\_theta\_max data vectors each containing the corresponding n+2 gridpoint values

```
for fft991, x(0), x(1), x(2),...,x(n-1),0,0. (n+2) real values with x(n)=x(n+1)=0
```

when isign = +1, the transform is defined by  $x(j)=sum(k=0,\ldots,n-1)(c(k)*exp(2*i*j*k*pi/n))$  where c(k)=a(k)+i\*b(k) and c(n-k)=a(k)-i\*b(k) and i=sqrt(-1) for  $k=0,\ldots,n/2$  i.e., (n/2+1) complex values with c(0)=c(n)=a(0) and c(n/2)=a(n/2)=0

if isign = -1, and n\_theta\_max data vectors are supplied each containing a sequence of gridpoint values x(j) as defined above, then the result consists of n\_theta\_max vectors each containing the corresponding fourier cofficients a(k), b(k),  $0 \le k$ . le n/2.

when isign = -1, the inverse transform is defined by c(k)=(1/n)\*sum(j=0,...,n-1)(x(j)\*exp(-2\*i\*j\*k\*pi/n)) where c(k)=a(k)+i\*b(k) and i=sqrt(-1) for k=0,...,n/2

a call with isign=+1 followed by a call with isign=-1 (or vice versa) returns the original data.

note the fact that the gridpoint values x(j) are real implies that b(0)=b(n/2)=0. for a call with isign=+1, it is not actually necessary to supply these zeros. note starting from grid with x(n)=x(n+1)=0 then transforming to spectral (sign=-1) then c(n/2)=a(n/2) is not necessarily 0 unless there is no aliasing.

# - Input variables:

#### **Parameters**

- $a (ld_a,*)$  [real,inout] :: fields to be transformed
- ld\_a [integer,in,] :: leading dimension of a
- **n** [integer,in] :: dimension of problem
- isign [integer,in] :: back/forth transform for isign=1/-1
- nsize [integer,in] :: number of fields for
- wrk (wd1,wd2) [real,inout] :: work array
- wd1 [integer,in,]
- wd2 [integer,in,]
- i\_fft\_init (\*) [integer,in] :: factorization information from init\_fft
- **d\_fft\_init** (\*) [real,in] :: trigonometric functions from init\_fft

```
Called from fft_thetab(), fft_to_real()
```

Call to abortrun(), fft99ajw(), wpass2jw(), wpass3jw(), wpass4jw(),
 wpass5jw(), fft99bjw()

subroutine fft/fft99ajw(a, work, trigs, nrp, nsize)

- Input/output:

## **Parameters**

- **a** (\*) [real,inout]
- work (\*) [real,inout]
- **trigs** (\*) [real,in]
- **nrp** [integer,in]
- nsize [integer,in]

Called from fftjw()

subroutine fft/fft99bjw(work, a, trigsf, nrp, nsize)

postprocessing step (isign=-1) (gridpoint to spectral transform)

– input/output:

## **Parameters**

work (\*) [real,inout]

```
• a (*) [real,inout]
                  • trigsf (*) [real,in]
                  • nrp [integer,in]
                  • nsize [integer,in]
           Called from fftjw()
subroutine fft/wpass2jw(a, b, c, d, trigs, nrp, nsize)
           reduction for factor 2
      – input/ouput:
           Parameters
                  • a (*) [real,in]
                  • b (*) [real,in]
                  • c (*) [real,out]
                  • d (*) [real,out]
                  • trigs (*) [real,in]
                  • nrp [integer,in]
                  • nsize [integer,in]
           Called from fftjw()
\verb|subroutine| fft/wpass3jw| (a, b, c, d, trigs, nrp, la, nsize)|
           called in fftJW
      – input/output:
           Parameters
                  • a (*) [real,in]
                  • b (*) [real,in]
                  • c (*) [real,out]
                  • d (*) [real,out]
                  • trigs (*) [real,in]
                  • nrp [integer,in]
                  • la [integer,in]
                  • nsize [integer,in]
           Called from fft jw()
           Call to abortrun()
subroutine fft/wpass4jw(a, b, c, d, trigs, nrp, la, nsize)
           called in fftJW reduction for factor 4
      – input/output:
           Parameters
                  • a (*) [real,in]
```

```
b (*) [real,in]
c (*) [real,out]
d (*) [real,out]
trigs (*) [real,in]
nrp [integer,in]
la [integer,in]
nsize [integer,in]
Called from fftjw()
Call to abortrun()
subroutine fft/wpass5jw(a, b, c, d, trigs, nrp, la, nsize)
called in fftJW reduction for factor 5
input/output:
Parameters
```

- **a** (\*) [real,in]
- **b** (\*) [real,in]
- **c** (\*) [real,out]
- **d** (\*) [real,out]
- **trigs** (\*) [real,in]
- **nrp** [integer,in]
- la [integer,in]
- nsize [integer,in]

Called from fftjw()

Call to abortrun()

# 10.12 Linear algebra

# 10.12.1 algebra.f90

## **Quick access**

```
Variables zero_tolerance
Routines sgesl(), cgeslml(), cgesl(), sgefa()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- omp\_lib
- useful (abortrun()): library with several useful subroutines

• constants (one ()): module containing constants and parameters used in the code.

## **Variables**

• algebra/zero\_tolerance [real,private/parameter=1.0e-15\_cp]

## Subroutines and functions

```
subroutine algebra/cgesl(a, ia, n, ip, bcl)
```

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a \* x = bc1) were bc1 is the right hand side vector. On return x is stored in bc1.

- Input variables:

## **Parameters**

- a (ia,\*) [real,in] :: real n X n matrix
- ia [integer,in,] :: first dim of a
- **n** [integer,in] :: dimension of problem
- ip (\*) [integer,in] :: pivot pointer of legth n
- **bc1** (\*) [complex,inout] :: on input RHS of problem

Called from updatez(), j\_cond()

```
subroutine algebra/cgeslml (a, ia, n, ip, bc, nrhss)
```

This routine does the backward substitution into a lu-decomposed real matrix a (to solve a \* x = bc) simultaneously for nRHSs complex vectors bc. On return the results are stored in the bc.

- Input variables:

## **Parameters**

- a (ia,n) [real,in] :: real n X n matrix
- ia [integer,in,] :: leading dimension of a
- **n** [integer,in,] :: dimension of problem
- ip (n) [integer,in] :: pivot pointer of length n
- **bc** (,) [complex,inout]
- **nrhss** [integer,in] :: number of right-hand sides

Called from updateb(), updates(), updatexi(), updatewpt(), updatewps(),
 updatez(), updatewp(), updates\_ala()

```
subroutine algebra/sgesl(a, ia, n, ip, b)
```

like the linpack routine backward substitution of vector b into lu-decomposed matrix a to solve a \* x = b for a single real vector b

sub sgefa must be called once first to initialize a and ip

- a: (input) nxn real matrix n: (input) size of a and b ip: (input) pivot pointer array of length n b: (in/output) rhs-vector on input, solution on output
- Input variables:

## **Parameters**

```
• a (ia,*) [real,in]
```

• ia [integer,in,] :: first dim of a

• **n** [integer,in] :: dim of problem

• **ip** (\*) [integer,in] :: pivot information

• **b** (\*) [real,inout]

Called from updates(), updatexi(), updatewpt(), updatewps(), inits(),
 updatewp(), initxi(), updates\_ala(), pt\_cond(), xi\_cond(), ps\_cond(),
 getbackground()

subroutine algebra/sgefa(a, ia, n, ip, info)

like the linpack routine

lu decomposes the real matrix a(n,n) via gaussian elimination

a: (in/output) real nxn matrix on input, lu-decomposed matrix on output ia: (input) first dimension of a (must be >= n) n: (input) 2nd dimension and rank of a ip: (output) pivot pointer array info: (output) error message when /= 0

- Input variables:

#### **Parameters**

- **a** (ia,\*) [real,inout]
- ia [integer,in,]
- **n** [integer,in]
- **ip** (\*) [integer,out] :: pivoting information
- info [integer,out]

```
Called from get_p0mat(), get_s0mat(), inits(), initxi(), get_wpsmat(),
    get_zmat(), pt_cond(), get_wptmat(), get_wmat(), get_ps0mat(),
    xi_cond(), get_pt0mat(), ps_cond(), get_wpmat(), j_cond(), get_bmat(),
    get_smat(), getbackground(), get_ximat(), get_xi0mat(), get_z10mat()
```

Call to abortrun()

# 10.13 Radial derivatives and integration

## 10.13.1 radial derivatives.f90

## **Description**

Radial derivatives functions

## **Quick access**

Variables get\_dcheb, get\_dr, work\_1d\_real

```
Routines finalize_der_arrays(), get_dddcheb(), get_dddr(), get_ddcheb(),
    get_ddr(), get_dcheb_complex(), get_dr_complex(), get_dcheb_real_1d(),
    get_dr_real_1d(), initialize_der_arrays()
```

## **Needed modules**

- mem\_alloc: This little module is used to estimate the global memory allocation used in MagIC
- cosine\_transform\_odd
- radial\_scheme (type\_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- precision\_mod: This module controls the precision used in MagIC
- logic (l\_finite\_diff()): Module containing the logicals that control the run
- constants (zero(), three(), one()): module containing constants and parameters used in the code.

## **Variables**

- radial\_der/get\_dcheb [public]
- radial\_der/get\_dr [public]
- radial\_der/work (:,:) [complex,private/allocatable]
- radial\_der/work\_1d\_real (:) [real,private/allocatable]

## **Subroutines and functions**

```
subroutine radial_der/initialize_der_arrays(n_r_max, llm, ulm)
```

Allocate work arrays to compute derivatives

## **Parameters**

- n\_r\_max [integer,in]
- **llm** [integer,in]
- **ulm** [integer,in]

Called from magic

```
subroutine radial_der/finalize_der_arrays()
```

Deallocate work arrays

Called from magic

```
subroutine radial_der/get_dcheb_complex(f, df, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, n\_cheb\_max, d\_fac)
```

Returns chebychev coeffitiens of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n\_f\_max,n\_r\_max).

– Input variables:

## **Parameters**

• **f** (n\_f\_max,n\_r\_max) [complex,in]

- **df**  $(n_f_{max}, n_r_{max})$  [complex, out]
- n\_f\_max [integer,in,] :: Max no of functions
- n\_f\_start [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n r max [integer, in, ] :: second dimension of f,df,ddf
- n cheb max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

#### **Parameters**

- **f** (*n*\_*r*\_*max*) [real,in]
- **df** (*n\_r\_max*) [real,out]
- n r max [integer, in, ] :: Dimension of f,df,ddf
- n cheb max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

**subroutine** radial\_der/**get\_ddcheb**  $(f, df, ddf, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, n cheb max, d fac)$ 

Returns chebychev coefficients of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n\_c\_tot,n\_r\_max).

- Input variables:

## **Parameters**

- **f** (n\_f\_max,n\_r\_max) [complex,in]
- **df** (n\_f\_max,n\_r\_max) [complex,out]
- **ddf** (n\_f\_max,n\_r\_max) [complex,out]
- n\_f\_max [integer,in,] :: First dimension of f,df,ddf
- **n\_f\_start** [integer,in] :: No of column to start with
- **n\_f\_stop** [integer,in] :: No of column to stop with
- **n\_r\_max** [integer,in,] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- d fac [real,in]:: factor for interval mapping

Called from get\_ddr()

Returns chebychev coeffitiens of first derivative df and second derivative ddf for a function whose cheb-coeff. are given as columns in array f(n\_c\_tot,n\_r\_max).

- Input variables:

#### **Parameters**

• **f** (n\_f\_max,n\_r\_max) [complex,in]

- **df** (n\_f\_max,n\_r\_max) [complex,out]
- $\mathbf{ddf}$  (n f max, n r max) [complex, out]
- **dddf** (n\_f\_max,n\_r\_max) [complex,out]
- **n\_f\_max** [integer,in,] :: First dimension of f,df,ddf
- n\_f\_start [integer,in] :: No of column to start with
- **n f stop** [integer,in] :: No of column to stop with
- n\_r\_max [integer,in,] :: second dimension of f,df,ddf
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

**Called from** get\_dddr()

## **Parameters**

- $\mathbf{f}(n \ r \ max)[real,in]$
- **df** (*n\_r\_max*) [real,out] :: first derivative of f
- n\_r\_max [integer,in,] :: number of radial grid points
- r scheme [real]

```
subroutine radial_der/get_dr_complex(f, df, n\_f\_max, n\_f\_start, n\_f\_stop, n\_r\_max, r\_scheme[,nocopy])
```

Returns first radial derivative df of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions  $f(n_f_start,^*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points .

## - Input variables:

## **Parameters**

- **f** (n\_f\_max,n\_r\_max) [complex,inout]
- **df** (n\_f\_max,n\_r\_max) [complex,out] :: first derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- **n r max** [integer, in, ] :: number of radial grid points
- r\_scheme [real]

**Options nocopy** [logical,in,optional]

```
subroutine radial_der/get_ddr(f, df, ddf, n_f_max, n_f_start, n_f_stop, n_r_max, r_scheme)
```

Returns first radial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points.

- Input variables:

## **Parameters**

```
• \mathbf{f} (n_f_max,n_r_max) [complex,in]
```

- **df** (n\_f\_max,n\_r\_max) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,n\_r\_max) [complex,out] :: second derivative of f
- **n f max** [integer,in,] :: first dim of f
- **n f start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- n\_r\_max [integer,in,] :: number of radial grid points
- r scheme [real]

```
Called from getstartfields(), updateb(), updates(), updatexi(),
    updatewpt(), updatewps(), updatez(), updatewp(), updates_ala()
```

Call to get\_ddcheb()

Returns first radial derivative df, the second radial deriv. ddf, and the third radial derivative dddf of the input function f. Array  $f(n_f_max,^*)$  may contain several functions numbered by the first index. The subroutine calculates the derivative of the functions  $f(n_f_start,^*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points.

## - Input variables:

## **Parameters**

- $\mathbf{f}$  (n\_f\_max,n\_r\_max) [complex,in]
- **df** (n\_f\_max,n\_r\_max) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,n\_r\_max) [complex,out] :: second derivative of f
- **dddf** (n\_f\_max,n\_r\_max) [complex,out] :: third derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- **n r max** [integer, in, ] :: number of radial grid points
- r scheme [real]

```
Called from updatewpt(), updatewps(), updatewp()
```

Call to get\_dddcheb()

## 10.13.2 radial derivatives even.f90

## **Quick access**

```
Routines get_ddcheb_even(), get_ddrns_even(), get_dcheb_even(), get_drns_even()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- cosine\_transform\_odd
- cosine\_transform\_even
- constants (zero ()): module containing constants and parameters used in the code.

## **Variables**

## Subroutines and functions

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init\_costf1 and init\_costf2.

- Input variables:

```
• f (n_f_max,n_r_max) [complex,in]
```

```
• df (n_f_max,n_r_max) [complex,out] :: first derivative of f
```

- **ddf** (n\_f\_max,n\_r\_max) [complex,out] :: second derivative of f
- **n\_f\_max** [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- **n\_r\_max** [integer,in,] :: number of radial grid points
- n cheb max [integer,in] :: number of cheb modes
- **dr\_fac** [real,in] :: mapping factor
- work1 (n\_f\_max,n\_r\_max) [complex,out] :: work array needed for costf
- work2 (n\_f\_max,n\_r\_max) [complex,out] :: work array needed for costf
- **chebt\_odd** [costf\_odd\_t,in]
- **chebt\_even** [costf\_even\_t,in]

```
Called from getstartfields(), updateb()
```

```
Call to get_ddcheb_even()
```

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivatives of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init costf1 and init costf2.

## - Input variables:

## **Parameters**

- **f** (n\_f\_max,n\_r\_max) [complex,inout]
- **df** (n\_f\_max,n\_r\_max) [complex,out] :: first derivative of f
- **n f max** [integer,in,] :: first dim of f
- **n\_f\_start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- n\_r\_max [integer,in,] :: number of radial grid points
- n\_cheb\_max [integer,in] :: number of cheb modes
- **dr\_fac** [real,in] :: mapping factor
- work1 (n\_f\_max,n\_r\_max) [complex,out] :: work array needed for costf
- **chebt\_odd** [costf\_odd\_t,in]
- chebt even [costf even t,in]

```
Called from fields_average(), write_dtb_frame()
```

Call to get\_dcheb\_even()

Returns first rarial derivative df and second radial derivative ddf of the input function f. Array  $f(n_f_max,*)$  may contain several functions numbered by the first index. The subroutine calculates the derivaties of the functions  $f(n_f_start,*)$  to  $f(n_f_stop)$  by transforming to a Chebychev representation using  $n_r_max$  radial grid points. The cheb transforms have to be initialized by calling init\_costf1 and init\_costf2.

## – Input variables:

- **f** (n\_f\_max,n\_r\_max) [complex,inout]
- **df** (n\_f\_max,n\_r\_max) [complex,out] :: first derivative of f
- **ddf** (n\_f\_max,n\_r\_max) [complex,out] :: second derivative of f
- n\_f\_max [integer,in,] :: first dim of f
- **n f start** [integer,in] :: first function to be treated
- **n\_f\_stop** [integer,in] :: last function to be treated
- **n\_r\_max** [integer, in, ] :: number of radial grid points
- **n\_cheb\_max** [integer,in] :: number of cheb modes
- dr\_fac [real,in] :: mapping factor
- work1 (n\_f\_max,n\_r\_max) [complex,out] :: work array needed for costf

```
• chebt_odd [costf_odd_t,in]
```

• **chebt\_even** [costf\_even\_t,in]

Called from fields\_average()

Call to get\_ddcheb\_even()

## **Parameters**

- $\mathbf{f}$  (n\_f\_max,n\_r\_max) [complex,in]
- **df** (n\_f\_max,n\_r\_max) [complex,out]
- **n\_f\_max** [integer,in,] :: First dimension of f,df
- n\_f\_start [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n\_r\_max [integer,in,] :: second dimension of f,df
- n\_cheb\_max [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

Called from get\_drns\_even()

**subroutine** radial\_der\_even/get\_ddcheb\_even(f, df, ddf,  $n\_f\_max$ ,  $n\_f\_start$ ,  $n\_f\_stop$ ,  $n\_r\_max$ ,  $n\_cheb\_max$ ,  $d\_fac$ )

## **Parameters**

- $\mathbf{f}$  (n f max, n r max) [complex, in]
- **df** (n\_f\_max,n\_r\_max) [complex,out]
- **ddf** (n\_f\_max,n\_r\_max) [complex,out]
- n\_f\_max [integer,in,] :: First dimension of f,df,ddf
- **n\_f\_start** [integer,in] :: No of function to start with
- **n\_f\_stop** [integer,in] :: No of function to stop with
- n\_r\_max [integer,in,] :: second dimension of f,df,ddf
- **n\_cheb\_max** [integer,in] :: Number of cheb modes
- **d\_fac** [real,in] :: factor for interval mapping

Called from get\_ddr\_even(), get\_ddrns\_even()

## **10.13.3** integration.f90

## **Description**

Radial integration functions

## **Quick access**

**Routines** rintic(), rint r()

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- cosine\_transform\_odd
- radial\_scheme (type\_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- constants (one (), two (), half ()): module containing constants and parameters used in the code.

## **Variables**

## **Subroutines and functions**

```
function integration/rintic(f, nrmax, drfac, chebt)
```

This function performs the radial integral over a function f that is given on the appropriate nRmax radial Chebychev grid points.

- Input variables:

#### **Parameters**

- **f** (nrmax) [real,inout]
- **nrmax** [integer,in,]
- **drfac** [real,in]
- **chebt** [costf\_odd\_t,in]

**Return rintic** [real]

```
Called from get_power(), get_e_mag(), spectrum()
```

**function** integration/**rint\_r**(*f*, *r*, *r\_scheme*)

Same as function rInt but for a radial dependent mapping function dr\_fac2.

- Input variables:

#### **Parameters**

- **f** (\*) [real,in]
- **r** (\*) [real,in]
- **r\_scheme** [real] :: Radial scheme (FD or Cheb)

## **Return rint** [real]

```
Called from dtvrms(), outto(), get_angular_moment(), get_power(),
  outheat(), get_amplitude(), get_poltorrms(), get_e_mag(), updatewp(),
  dtbrms(), get_u_square(), spectrum(), getdlm(), outhelicity(),
  get_e_kin(), output(), spectrum_average(), outperppar(),
  spectrum_temp_average(), precalc(), spectrum_temp()
```

# 10.14 Blocking and LM mapping

## 10.14.1 blocking.f90

## **Description**

Module containing blocking information

## **Quick access**

```
Variables get_theta_blocking, nfs, nlmbs, nthetabs, sizelmb, sizethetab, nbsave,
    sizethetabi, cacheblock_size_in_b, nbdown, lmstartb, lmstopb, 12lmas,
    lm21, lm2lma, lm2lmp, lm2lms, lm2m, lm2mc, lmp2l, lmp2lm, lmp2lmpa, lmp2lmps,
    nlmbs2, lm2, lmp2, sizelmb2, lm22l, lm22lm, lm22m, lo_map, lo_sub_map,
    sn_sub_map, st_map, st_sub_map
Routines initialize_blocking(),
    get_lorder_lm_blocking(),
    get_snake_lm_blocking(),
```

get\_standard\_lm\_blocking(), get\_subblocks(), get\_theta\_blocking\_cache(),

#### **Needed modules**

- mem\_alloc (memwrite(), bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), logwrite()): library with several useful subroutines
- output\_data (n\_log\_file(), log\_file()): This module contains the parameters for output control
- precision\_mod: This module controls the precision used in MagIC

get\_theta\_blocking\_openmp()

- parallel\_mod(n\_procs(), rank\_with\_l1m0(), nthreads(), rank(), nlmbs\_per\_rank()): This module contains the blocking information
- logic(l\_finite\_diff(), l\_save\_out()): Module containing the logicals that control the run
- lmmapping (mappings(), deallocate\_mappings(), subblocks\_mappings(), deallocate\_subblocks\_mappings(), allocate\_subblocks\_mappings())
- constants (one ()): module containing constants and parameters used in the code.
- truncation (l\_max(), minc(), lmp\_max(), l\_axi(), n\_r\_max(), m\_max(), lm\_max(), nrp(), n theta max()): This module defines the grid points and the truncation

## **Variables**

- blocking/nbsave[integer,private/parameter=16]
- blocking/lmstartb(:)[integer,allocatable/public]
- blocking/lm2 (:,:) [integer,pointer/public]
- blocking/lmp2 (:,:) [integer, pointer/public]

- blocking/lm2lms (:) [integer, pointer/public]
- blocking/lmp21 (:) [integer, pointer/public]
- blocking/lm221 (:,:,:) [integer,pointer/public]
- blocking/lm22m(:,:,:) [integer,pointer/public]
- blocking/lmp2lm(:)[integer,pointer/public]
- blocking/lm2lmp (:) [integer, pointer/public]
- blocking/get\_theta\_blocking[public]
- blocking/lo\_sub\_map [subblocks\_mappings,target/public]
- blocking/lmp2lmps (:) [integer,pointer/public]
- blocking/nthetabs [integer, public]
- blocking/sn\_sub\_map[subblocks\_mappings,target/public]
- blocking/lm2m(:) [integer,pointer/public]
- blocking/lm21(:)[integer,pointer/public]
- blocking/lmp2lmpa (:) [integer, pointer/public]
- blocking/lm2mc(:)[integer,pointer/public]
- blocking/nlmbs [integer, public]
- blocking/sizethetab[integer,public]
- blocking/st\_map [mappings,target/public]
- blocking/lo\_map [mappings,target/public]
- blocking/nlmbs2 (:) [integer,pointer/public]
- blocking/sizelmb [integer, public]
- blocking/sizethetabi[integer,private/parameter=284]
- blocking/lm22lm(:,:,:) [integer,pointer/public]
- blocking/nfs [integer, public]
- blocking/lmstopb(:)[integer,allocatable/public]
- blocking/121mas (:) [integer,pointer/public]
- blocking/cacheblock\_size\_in\_b[integer,public]
- blocking/nbdown [integer,private/parameter=8]
- blocking/lm2lma(:)[integer,pointer/public]
- blocking/sizelmb2 (:,:) [integer,pointer/public]
- blocking/st\_sub\_map[subblocks\_mappings,target/public]

## **Subroutines and functions**

subroutine blocking/initialize\_blocking()

Called from magic

```
Call to allocate_mappings(),
                                                 logwrite().
                                                                         abortrun().
            get_standard_lm_blocking(),
                                                          get_snake_lm_blocking(),
            get_lorder_lm_blocking(),
                                                  allocate subblocks mappings(),
            get_subblocks(),
                                                      get_theta_blocking_cache(),
            get_theta_blocking_openmp(), memwrite()
subroutine blocking/finalize blocking()
         Called from magic
         Call to deallocate_mappings(), deallocate_subblocks_mappings()
subroutine blocking/get_subblocks (map, sub_map)
    - Input variables:
         Parameters
              • map [mappings,in]
              • sub_map [subblocks_mappings,inout]
         Called from initialize blocking()
         Call to abortrun()
subroutine blocking/get_standard_lm_blocking(map, minc)
         Parameters
              • map [mappings,inout]
              • minc [integer,in]
         Called from initialize_blocking()
         Call to abortrun()
subroutine blocking/get_lorder_lm_blocking(map, minc)
         Parameters
              • map [mappings,inout]
              • minc [integer,in]
         Called from initialize blocking()
         Call to abortrun()
subroutine blocking/get_snake_lm_blocking(map, minc)
         Parameters
              • map [mappings,inout]
              • minc [integer,in]
         Called from initialize blocking()
         Call to abortrun()
subroutine blocking/get_theta_blocking_cache (n_theta_max, nrp, cacheblock_size_in_b,
                                                   nthetabs, sizethetab)
         Parameters
              • n_theta_max [integer,in]
```

• **nrp** [integer,in]

- cacheblock\_size\_in\_b [integer,in]
- **nthetabs** [integer,out]
- sizethetab [integer,out]

Called from initialize\_blocking()

subroutine blocking/get\_theta\_blocking\_openmp(n\_theta\_max, nthreads, nthetabs, sizethetab)

This routine determines the number of theta blocks and the blocksize with respect to the number of threads.

## **Parameters**

- n\_theta\_max [integer,in]
- **nthreads** [integer,in]
- **nthetabs** [integer,out]
- sizethetab [integer,out]

Called from initialize\_blocking()

## 10.14.2 LMmapping.f90

## Quick access

```
Routines deallocate_mappings(), deallocate_subblocks_mappings(), allocate_mappings(), allocate_subblocks_mappings()
```

## **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- truncation (1\_axi()): This module defines the grid points and the truncation

## **Types**

• type lmmapping/unknown\_type

## Type fields

- % 1\_max [integer]
- % lm2mc (\*) [integer,allocatable]
- % lm2 (,) [integer, allocatable]
- % m\_max [integer]
- % lmp21 (\*) [integer, allocatable]
- % lmp2m (\*) [integer, allocatable]
- % lmp\_max [integer]

```
- % lmp2lm (*) [integer, allocatable]
              - % lmp2 (,) [integer, allocatable]
              - % lm_max [integer]
              - % lmp2lmps (*) [integer, allocatable]
              - % lm2lms (*) [integer, allocatable]
              - % lm2lmp (*) [integer, allocatable]
              - % lm2m(*)[integer,allocatable]
              - % lm21 (*) [integer, allocatable]
              - % 121mas (*) [integer, allocatable]
              - % lmp2lmpa (*) [integer, allocatable]
              - % lm2lma (*) [integer,allocatable]
• type lmmapping/unknown_type
           Type fields
              - % 1_max [integer]
              - % sizelmb2max [integer]
              - % nlmbs [integer]
```

- % lm22lm (,,\*) [integer, allocatable]
- % lm221 (,,\*) [integer, allocatable]
- % lm22m (,,\*) [integer, allocatable]
- % sizelmb2(,)[integer,allocatable]
- % m\_max [integer]
- % nlmbs2 (\*) [integer,allocatable]

#### **Variables**

### Subroutines and functions

```
subroutine lmmapping/allocate_mappings (self, l_max, lm_max, lmp_max)
```

## **Parameters**

- **self** [mappings]
- l\_max [integer,in]
- lm\_max [integer,in]
- lmp\_max [integer,in]

Called from initialize\_blocking()

subroutine lmmapping/deallocate\_mappings(self)

**Parameters self** [mappings]

Called from finalize\_blocking()

subroutine lmmapping/allocate\_subblocks\_mappings (self, map, nlmbs, l\_max, lmstartb, lmstopb)

- Input variables

#### **Parameters**

- **self** [subblocks\_mappings]
- map [mappings,in]
- nlmbs [integer,in,]
- 1 max [integer,in]
- **Imstartb** (*nlmbs*) [integer,in]
- **lmstopb** (*nlmbs*) [integer,in]

Called from initialize\_blocking()

subroutine lmmapping/deallocate\_subblocks\_mappings (self)

Parameters self [subblocks\_mappings]

Called from finalize\_blocking()

# 10.15 IO: time series, radial profiles and spectra

# 10.15.1 output.f90

#### **Quick access**

Variables n\_cmb\_file, n\_cmb\_setsmov, n\_cmbmov\_file, n\_dt\_cmb\_file, n\_dt\_cmb\_sets, n\_dte\_file, n\_e\_sets, n\_par\_file, n\_spec, nbpotsets, nlogs, npvsets, nrms\_sets, ntomovsets, ntormssets, ntosets, ntpotsets, nvpotsets, cmb\_file, cmbmov\_file, dt\_cmb\_file, dte\_file, par\_file, dteint, e\_kin\_pmean, e\_kin\_tmean, e\_mag\_pmean, e\_mag\_tmean, etot, etotold, timenormlog, timenormrms, timepassedlog, timepassedrms, n\_b\_r\_file, n\_b\_r\_sets, n\_t\_r\_file, n\_t\_r\_sets, n\_v\_r\_file, n\_v\_r\_sets, dipcmbmean, dipmean, dlbmean, dlvcmean, dlvmean, dmbmean, dmvmean, dpvmean, dzvmean, elcmbmean, elmean, geosmean, lbdissmean, lvdissmean, rmmean, rolmean, b\_r\_file, t\_r\_file, v\_r\_file, bicb

**Routines** finalize\_output(), initialize\_output(), output()

## **Needed modules**

- horizontal\_data (hdif\_b(), dpl0eq(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie\_data(movie\_gather\_frames\_to\_rank0())
- useful (logwrite()): library with several useful subroutines
- rms (dtvrms (), zerorms (), dtbrms ()): This module contains the calculation of thr RMS force balance and induction terms.
- $\bullet \ lmloop\_data(llmmag(), lm\_per\_rank(), lm\_on\_last\_rank(), ulm(), llm(), ulmmag())\\$

- radial spectra
- getdlm\_mod (getdlm()): This module is used to calculate the lengthscales
- precision\_mod: This module controls the precision used in MagIC
- graphout\_mod (graphout\_ic()): This module contains the subroutines that store the 3-D graphic files.
- magnetic\_energy (get\_e\_mag())
- integration (rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- num\_param (escale (), tscale ()): Module containing numerical and control parameters
- out\_movie\_ic(store\_movie\_frame\_ic())
- physical\_parameters (prmag(), lffac(), ek(), ktopv(), nvarcond(), opm(), ekscaled()): Module containing the physical parameters
- radial\_functions (rscheme\_oc(), orho1(), r\_cmb(), or2(), or1(), r(), r\_icb(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- output\_data(l\_max\_cmb(), n\_r\_step(), n\_log\_file(), l\_max\_r(), n\_coeff\_r(), tag(), log\_file(), n\_coeff\_r\_max(), n\_r\_array()): This module contains the parameters for output control
- power (get\_power())
- logic (l\_hel(), lverbose(), l\_pv(), l\_rmagspec(), l\_mag\_lf(), l\_perppar(), l\_sric(), l\_mag(), l\_non\_rot(), l\_r\_fieldt(), l\_average(), l\_cond\_ic(), l\_movie(), l\_anel(), l\_heat(), l\_cmb\_field(), l\_chemical\_conv(), l\_movie\_ic(), l\_store\_frame(), l\_power(), l\_r\_field(), l\_dtb(), l\_par(), l\_save\_out(), l\_rms(), l\_dt\_cmb\_field(), l\_energy\_modes()): Module containing the logicals that control the run
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- storecheckpoints: This module contains several subroutines that can be used to store the checkpoint\_#.tag
  files
- kinetic\_energy (get\_e\_kin(), get\_u\_square())
- out\_coeff (write\_pot(), write\_coeff\_r(), write\_bcmb()): This module contains the subroutines that calculate the Bcmb files, the [BIVIT]\_coeff\_r files and the [BIVIT]\_lmr files
- omega (outomega ()): This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By
- blocking (lm2(), st\_map(), lo\_map()): Module containing blocking information
- constants (surf\_cmb(), two(), three(), mass(), vol\_oc(), vol\_ic()): module containing constants and parameters used in the code.
- truncation (n\_r\_ic\_max(), l\_max(), minc(), l\_maxmag(), n\_r\_max(), lm\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- fieldslast (dbdt\_iclast\_lmloc(), dzdtlast\_lo(), djdtlast\_lmloc(), djdt\_iclast\_lmloc(), dpdtlast\_lmloc(), dxidtlast\_lmloc(), dwdtlast\_lmloc(), dsdtlast\_lmloc(), dbdtlast\_lmloc()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- outrot (write rot())

- geos\_mod (outpv(), getegeos()): This module is used to calculate the outputs when either l\_par or 1 PV are set to .true.
- out\_movie(write\_movie\_frame())
- fields (aj\_lmloc(), ddj\_ic(), aj\_ic(), ddw\_lmloc(), ddb\_ic(), b\_lmloc(), dj\_lmloc(), ddj\_ic\_lmloc(), db\_lmloc(), s\_lmloc(), ddb\_lmloc(), b\_ic(), ds\_lmloc(), ddb\_ic\_lmloc(), p\_lmloc(), dxi\_lmloc(), db\_ic\_lmloc(), dw\_lmloc(), dp\_lmloc(), dj\_ic\_lmloc(), dj\_ic\_lmloc(), dj\_ic\_lmloc(), aj\_ic\_lmloc(), omega\_ic(), z\_lmloc(), omega\_ma(), w\_lmloc(), b\_ic\_lmloc(), ddj\_lmloc(), xi\_lmloc(), dz\_lmloc()): This module contains the potential fields and their radial derivatives
- spectra (get\_amplitude(), spectrum\_temp(), spectrum\_average(), spectrum\_temp\_average(), spectrum())
- dtb\_mod (get\_dtblmfinish()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- outmisc\_mod (outhelicity(), outheat()): This module contains several subroutines that can compute and store various informations: helicity, heat transfer.
- radial\_data (n\_r\_cmb(), n\_r\_icb(), nrstopmag(), nrstartmag(), nrstop(), nrstart()): This module defines the MPI decomposition in the radial direction.
- communications (gather\_all\_from\_lo\_to\_rank0(), gt\_ic(), gather\_from\_lo\_to\_rank0(), gt\_oc())
- outpar\_mod (outpar(), outperppar()): This module is used to compute several time-averaged radial profiles: fluxes, boundary layers, etc.
- outto\_mod(outto())
- fields\_average\_mod (fields\_average()): This module is used when one wants to store time-averaged quantities

## **Variables**

- output\_mod/dlvmean [real,private/save]
- output\_mod/nbpotsets[integer,private]
- output\_mod/ntpotsets [integer,private]
- output\_mod/etot [real,private]
- output\_mod/bicb (:) [complex,private/allocatable]
- output\_mod/ntosets[integer,private]
- output\_mod/n\_dte\_file [integer,private]
- output\_mod/timepassedlog[real,private]
- output\_mod/n\_par\_file [integer,private]
- output\_mod/n\_cmbmov\_file [integer,private]
- output\_mod/t\_r\_file (:) [character,private/allocatable]
- output\_mod/**dpvmean** [real,private/save]
- output\_mod/dipmean [real,private/save]
- output\_mod/rolmean [real,private/save]

- output\_mod/etotold[real,private]
- output\_mod/n\_v\_r\_file (:) [integer,private/allocatable]
- output\_mod/elmean [real,private/save]
- output\_mod/ntomovsets[integer,private]
- output mod/geosmean [real, private/save]
- output\_mod/timenormrms [real,private]
- output\_mod/dt\_cmb\_file [character,private]
- output\_mod/dte\_file [character,private]
- output\_mod/v\_r\_file (:) [character,private/allocatable]
- output\_mod/npvsets[integer,private]
- output\_mod/dlbmean [real,private/save]
- output\_mod/e\_kin\_tmean [real,private]
- output\_mod/lbdissmean [real,private/save]
- output\_mod/n\_t\_r\_sets(:)[integer,private/allocatable]
- output\_mod/rmmean [real,private/save]
- output\_mod/n\_dt\_cmb\_file [integer,private]
- output\_mod/n\_v\_r\_sets(:) [integer,private/allocatable]
- output\_mod/dmbmean [real,private/save]
- output\_mod/n\_cmb\_setsmov [integer,private]
- output\_mod/n\_b\_r\_sets (:) [integer,private/allocatable]
- output\_mod/n\_t\_r\_file (:) [integer,private/allocatable]
- output\_mod/ntormssets[integer,private]
- output\_mod/n\_e\_sets[integer,private]
- output\_mod/nlogs [integer,private]
- output\_mod/e\_kin\_pmean [real,private]
- output\_mod/cmb\_file [character,private]
- output\_mod/dteint [real,private]
- output\_mod/nvpotsets [integer,private]
- output\_mod/par\_file [character,private]
- output\_mod/dmvmean [real,private/save]
- output\_mod/lvdissmean [real,private/save]
- output\_mod/cmbmov\_file [character,private]
- output\_mod/n\_dt\_cmb\_sets[integer,private]
- output\_mod/e\_mag\_pmean [real,private]
- output\_mod/elcmbmean [real,private/save]
- output\_mod/timenormlog [real,private]

- output\_mod/n\_cmb\_file [integer,private]
- output\_mod/e\_mag\_tmean [real,private]
- output\_mod/timepassedrms [real,private]
- output\_mod/dzvmean [real,private/save]
- output mod/dlvcmean [real,private/save]
- output\_mod/b\_r\_file (:) [character,private/allocatable]
- output\_mod/n\_spec [integer,private]
- output\_mod/n\_b\_r\_file (:) [integer, private/allocatable]
- output\_mod/dipcmbmean [real,private/save]
- output\_mod/nrms\_sets[integer,private]

#### Subroutines and functions

subroutine output\_mod/output (time, dt, dtnew, n\_time\_step, l\_stop\_time, l\_bpot, l\_vpot, l\_tpot, l\_log, l\_graph, lrmscalc, l\_store, l\_new\_rst\_file, l\_spectrum, ltocalc, ltoframe, ltozwrite, l\_frame, n\_frame, l\_cmb, n\_cmb\_sets, l\_r, lorentz\_torque\_ic, lorentz\_torque\_ma, dbdt\_cmb\_lmloc, hellmr, hel2lmr, helnalmr, helna2lmr, visclmr, uhlmr, duhlmr, gradslmr, fconvlmr, fkinlmr, fvisclmr, fpoynlmr, freslmr, eperplmr, eparlmr, eperpaxilmr, eparaxilmr)

This subroutine controls most of the output.

— Input of variables

- time [real,in]
- dt [real,in]
- dtnew [real,in]
- n\_time\_step [integer,in]
- l\_stop\_time [logical,in]
- **l\_bpot** [logical,in]
- **l\_vpot** [logical,in]
- l\_tpot [logical,in]
- l\_log [logical,in]
- l\_graph [logical,in]
- **lrmscalc** [logical,in]
- **l\_store** [logical,in]

- l\_new\_rst\_file [logical,in]
- l\_spectrum [logical,in]
- **ltocalc** [logical,in]
- **Itoframe** [logical,in]
- **Itozwrite** [logical,inout]
- **l\_frame** [logical,in]
- **n\_frame** [integer,inout]
- **l\_cmb** [logical,in]
- n\_cmb\_sets [integer,inout]
- l\_r [logical,in]
- lorentz\_torque\_ic [real,in]
- lorentz\_torque\_ma [real,in]
- **dbdt\_cmb\_lmloc** (*ulmmag-*(*llmmag*)+1) [*complex*,*in*]
- **hellmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **hel2lmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **helnalmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **helna2lmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **visclmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **uhlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **duhlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **gradslmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fconvlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [real,in]
- **fkinlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fvisclmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **fpoynlmr** (*l\_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **freslmr** (*l\_maxmag+1,nrstopmag-(nrstartmag)+1*) [real,in]
- **eperplmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparlmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eperpaxilmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]
- **eparaxilmr** (*l\_max*+1,*nrstop*-(*nrstart*)+1) [*real*,*in*]

## Called from step\_time()

```
Call to write_rot(), get_e_kin(), get_e_mag(), get_amplitude(),
    spectrum_average(), spectrum_temp_average(), fields_average(),
    get_power(), get_u_square(), outperppar(), getdlm(), outpar(),
    outheat(), outhelicity(), getegeos(), spectrum(), spectrum_temp(),
    outto(), get_dtblmfinish(), zerorms(), dtvrms(), dtbrms(),
    write_bcmb(), write_coeff_r(), write_pot(), rbrspec(), rbpspec(),
    store(), gather_from_lo_to_rank0(), gather_all_from_lo_to_rank0(),
```

# 10.15.2 kinetic\_energy.f90

#### Quick access

#### **Needed modules**

- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- output\_data(tag()): This module contains the parameters for output control
- logic(l\_non\_rot(), l\_save\_out(), l\_anel()): Module containing the logicals that control the run
- lmloop data(llm(), ulm())
- integration (rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- communications (get\_global\_sum())
- num\_param (escale (), tscale ()): Module containing numerical and control parameters
- physical\_parameters (nvarcond(), prmaq(), ek()): Module containing the physical parameters
- truncation (1\_max(), n\_r\_max()): This module defines the grid points and the truncation
- blocking (lo\_map(), st\_map()): Module containing blocking information
- constants (one(), osq4pi(), three(), two(), four(), half(), vol\_oc(), pi()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), orho1(), orho2(), r\_cmb(), or2(), or1(), r(), r\_icb(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

- kinetic\_energy/e\_pa(:)[real,private/allocatable]
- kinetic\_energy/n\_e\_kin\_file [integer,private]
- kinetic\_energy/e\_ta(:)[real,private/allocatable]

- kinetic\_energy/n\_u\_square\_file [integer,private]
- kinetic\_energy/u\_square\_file [character,private]
- kinetic\_energy/e\_p\_asa(:)[real,private/allocatable]
- kinetic\_energy/e\_t\_asa(:)[real,private/allocatable]
- kinetic energy/e kin file[character,private]

## Subroutines and functions

calculates kinetic energy = 1/2 Integral ( $v^2$  dV) integration in theta,phi by summation of spherical harmonics integration in r by using Chebycheff integrals

Output: e\_p: Total poloidal e\_t: Total toroidal e\_p\_as: Axisym. poloidal e\_t\_as: Axisym. toroidal - Input variables:

#### **Parameters**

- **time** [real,in] :: Current time
- 1 write [logical,in] :: Switch to write output
- **l\_stop\_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n e sets [integer,in] :: Switch for time-average and to determine first time step
- $\mathbf{w} (ulm (llm) + 1, n_r max) [complex, in]$
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **e\_p** [real,out] :: poloidal energy
- **e\_t** [real,out] :: toroidal energy
- **e\_p\_as** [real,out] :: axisymmetric poloidal energy
- e t as [real,out] :: axisymmetric toroidal energy

**Options ekinr**  $(n\_r\_max)$  [real,out,optional] :: Radial profile of kinetic energy

```
Called from fields_average(), output()
Call to cc2real(), rint_r()
```

subroutine kinetic energy/get u square (time, w, dw, z, rolr, dlr, dlrc)

calculates square velocity = 1/2 Integral ( $v^2 dV$ ) integration in theta,phi by summation of spherical harmonics integration in r by using Chebychef integrals

Write the different contributions in u\_square.TAG file

- Input of scalar fields:

#### **Parameters**

```
• time [real,in] :: Current time
```

```
• w (ulm-(llm)+1,n_r_max) [complex,in]
```

- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- rolr (n\_r\_max) [real,out] :: local Rossby number
- **dlr** (*n\_r\_max*) [real,out] :: Length scale
- **dlrc** (*n\_r\_max*) [*real,out*] :: Convective length scale

```
Called from output ()
```

```
Call to cc2real(), rint_r()
```

# 10.15.3 magnetic\_energy.f90

#### **Quick access**

```
Variables lm_max_comp, n_compliance_file, n_dipole_file, n_e_mag_ic_file,
    n_e_mag_oc_file, n_phi_max_comp, n_theta_max_comp, dipole_file,
    e_mag_ic_file, e_mag_oc_file, earth_compliance_file, bcmb, e_dipa,
    e_p_asa, e_pa, e_t_asa, e_ta, plm_comp
Routines finalize_magnetic_energy(), initialize_magnetic_energy(),
    get_br_skew(), get_e_mag()
```

#### **Needed modules**

- horizontal\_data(dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc22real (), cc2real ()): library with several useful subroutines
- movie\_data (moviedipstrengthgeo(), moviedipstrength(), moviedipcolat(), moviediplon())
- output\_data(tag(), 1\_max\_comp()): This module contains the parameters for output control
- communications (gather\_from\_lo\_to\_rank0())
- logic(l\_save\_out(), l\_earth\_likeness(), l\_cond\_ic(), l\_mag(), l\_mag\_lf()): Module containing the logicals that control the run
- !mloop\_data(llmmag(), ulmmag())
- radial\_data(n\_r\_cmb()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- integration(rint\_r(), rintic()): Radial integration functions

- plms theta(plm theta())
- special (n\_imp(), rrmp()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num\_param(escale(), tscale()): Module containing numerical and control parameters
- physical\_parameters (ktopb(), lffac(), kbotb()): Module containing the physical parameters
- truncation (n\_r\_ic\_max(), n\_r\_ic\_maxmag(), minc(), n\_r\_max(), lm\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- blocking (lo\_map(), lmstartb(), st\_map(), lmstopb()): Module containing blocking information
- constants (osq4pi(), two(), one(), four(), zero(), half(), pi()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), orhol(), r\_cmb(), dr\_fac\_ic(), or2(), r\_ic(), r(), r\_icb(), chebt\_ic(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

- magnetic\_energy/bcmb (:) [complex,private/allocatable]
- magnetic\_energy/e\_pa (:) [real,private/allocatable]
- magnetic\_energy/e\_ta(:) [real,private/allocatable]
- magnetic\_energy/e\_t\_asa(:) [real,private/allocatable]
- magnetic\_energy/n\_phi\_max\_comp [integer,private]
- magnetic\_energy/n\_theta\_max\_comp [integer,private]
- magnetic\_energy/e\_mag\_ic\_file [character,private]
- magnetic\_energy/earth\_compliance\_file [character,private]
- magnetic\_energy/dipole\_file [character,private]
- magnetic\_energy/n\_e\_mag\_ic\_file [integer,private]
- magnetic\_energy/e\_mag\_oc\_file [character,private]
- magnetic\_energy/e\_dipa (:) [real,private/allocatable]
- magnetic energy/n compliance file [integer, private]
- magnetic\_energy/e\_p\_asa(:) [real,private/allocatable]
- magnetic\_energy/n\_dipole\_file [integer,private]
- magnetic\_energy/plm\_comp (:,:) [real,private/allocatable]
- magnetic\_energy/n\_e\_mag\_oc\_file[integer,private]
- magnetic\_energy/lm\_max\_comp [integer,private]

## **Subroutines and functions**

```
subroutine magnetic_energy/initialize_magnetic_energy()
          Open diagnostic files and allocate memory
- Local variables
          Called from magic
          Call to plm_theta()
subroutine magnetic_energy/finalize_magnetic_energy()
          Close file and deallocates global arrays
```

Called from magic

calculates magnetic energy = 1/2 Integral(B<sup>2</sup> dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebyshev integrals or Simpson rule depending whether FD or Cheb is used.

- Input of variables:

- **time** [real,in] :: Current time
- **l\_write** [logical,in] :: Switch to write output
- **l\_stop\_time** [logical,in] :: Indicates when last time step of the run is reached for radial output
- n\_e\_sets [integer,in] :: Switch for time-average and to determine first time step
- **b** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **db** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- aj (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **b\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **aj\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **e\_p** [real,out] :: Volume averaged poloidal magnetic energy
- **e\_t** [real,out] :: Volume averaged toroidal magnetic energy
- e p as [real,out]:: Volume averaged axisymmetric poloidal magnetic energy
- e\_t\_as [real,out] :: Volume averaged axisymmetric toroidal magnetic energy
- **e\_p\_ic** [real,out] :: IC poloidal magnetic energy
- e\_t\_ic [real,out] :: IC toroidal magnetic energy
- e\_p\_as\_ic [real,out] :: IC axisymmetric poloidal magnetic energy
- e\_t\_as\_ic [real,out] :: IC axisymmetric toroidal magnetic energy
- e\_p\_os [real,out] :: Outside poloidal magnetic energy

- e\_p\_as\_os [real,out] :: Outside axisymmetric poloidal magnetic energy
- e\_cmb [real,out] :: Magnetic energy at the CMB
- **dip** [real,out] :: Relative magnetic energy of axial dipole
- dipcmb [real,out] :: Relative magnetic energy of axial dipole at the CMB
- elsanel [real, out] :: Radially averaged Elsasser number

```
Called from fields average(), output()
```

```
Call to cc2real(), gather_from_lo_to_rank0(), rint_r(), cc22real(),
    rintic(), get_br_skew()
```

subroutine magnetic\_energy/get\_br\_skew(bcmb, br\_skew)

This subroutine calculates the skewness of the radial magnetic field at the outer boundary. bskew :=  $\langle B^4 \rangle / \langle B^2 \rangle^2$  where  $\langle ... \rangle$  is average over the surface

- Input variable

#### **Parameters**

- **bcmb** (*lm\_max*) [*complex*,*in*]
- **br\_skew** [real,out]

Called from get\_e\_mag()

# 10.15.4 getDlm.f90

# **Description**

This module is used to calculate the lengthscales

#### **Quick access**

Routines getdlm()

#### **Needed modules**

- horizontal\_data (dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- integration(rint\_r()): Radial integration functions
- parallel mod: This module contains the blocking information
- num\_param(escale()): Module containing numerical and control parameters
- truncation (1\_max(), minc(), n\_r\_max(), m\_max()): This module defines the grid points and the truncation
- blocking (lo\_map(), st\_map()): Module containing blocking information

- constants (pi (), half ()): module containing constants and parameters used in the code.
- radial\_functions (orho1 (), rscheme\_oc(), r(), or2 ()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

#### Subroutines and functions

```
subroutine getdlm_mod/getdlm(w, dw, z, dl, dlr, dm, dlc, dlrc, switch_bn)
```

calculates energy = 1/2 Integral(B<sup>2</sup> dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal – Input variables:

#### **Parameters**

- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- $\mathbf{dw}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dl** [real,out]
- **dlr** (*n\_r\_max*) [*real,out*]
- **dm** [real,out]
- dlc [real,out]
- **dlrc** (*n\_r\_max*) [*real,out*]
- switch\_bn [character,in]

Called from output ()

Call to cc2real(), abortrun(), rint\_r()

## 10.15.5 outMisc.f90

# **Description**

This module contains several subroutines that can compute and store various informations: helicity, heat transfer.

## **Quick access**

## **Needed modules**

- horizontal\_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- output\_data(tag()): This module contains the parameters for output control
- logic (l\_hel(), l\_anelastic\_liquid(), l\_chemical\_conv(), l\_heat(), l\_tp\_form(), l\_temperature\_diff(), l\_save\_out()): Module containing the logicals that control the run
- legendre\_spec\_to\_grid(lmas2pt())
- integration (rint\_r()): Radial integration functions
- radial\_data(n\_r\_cmb(), nrstart(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- num\_param (1scale ()): Module containing numerical and control parameters
- lmloop\_data(llm(), ulm())
- physical\_parameters (vischeatfac(), thexpnb()): Module containing the physical parameters
- truncation (lm\_max(), l\_max(), n\_r\_max()): This module defines the grid points and the truncation
- start\_fields (botcond(), topcond(), botxicond(), deltacond(), deltaxicond(), topxicond())
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- constants (four (), osq4pi (), two (), one (), sq4pi (), vol\_oc(), pi ()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), kappa(), r\_cmb(), rho0(), dlalpha0(), alpha0(), ogrun(), dltemp0(), beta(), temp0(), r\_icb(), orho1(), r(), otemp1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

- outmisc\_mod/tmeanr(:) [real,private/allocatable]
- outmisc\_mod/smeanr(:) [real,private/allocatable]
- outmisc\_mod/ximeanr(:) [real,private/allocatable]
- outmisc\_mod/n\_heat\_file [integer,private]
- outmisc\_mod/pmeanr(:) [real,private/allocatable]
- outmisc\_mod/helicity\_file [character,private]
- outmisc\_mod/heat\_file [character,private]
- outmisc\_mod/n\_helicity\_file [integer,private]

## **Subroutines and functions**

```
subroutine outmisc_mod/initialize_outmisc_mod()
          Called from magic
subroutine outmisc_mod/finalize_outmisc_mod()
          Called from magic
subroutine outmisc_mod/outhelicity (timescaled, hellmr, hel2lmr, helnalmr, helna2lmr)
          This subroutine is used to store informations about kinetic helicity
     - Input of variables:
          Parameters
                • timescaled [real,in]
                • hellmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • hel2lmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • helnalmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • helna2lmr (l_max+1,nrstop-(nrstart)+1) [real,in]
          Called from output ()
          Call to lmas2pt(), rint_r()
subroutine outmisc_mod/outheat (time, timepassed, timenorm, l_stop_time, s, ds, p, dp, xi, dxi)
          This subroutine is used to store informations about heat transfer (i.e. Nusselt number, temperature,
          entropy, ...)
     - Input of variables:
          Parameters
                • time [real,in]
                • timepassed [real,in]
                • timenorm [real,in]
                • l_stop_time [logical,in]
                • s(ulm-(llm)+1,n_r_max)[complex,in]
                • ds (ulm-(llm)+1,n_r_max) [complex,in]
                • p (ulm-(llm)+1,n_r_max) [complex,in]
                • dp (ulm-(llm)+1,n_r_max) [complex,in]
                • xi (ulm-(llm)+1,n_r_max) [complex,in]
                • dxi (ulm-(llm)+1,n_r_max) [complex,in]
          Called from output()
          Call to rint_r()
```

# 10.15.6 outRot.f90

#### **Quick access**

# Needed modules

• horizontal\_data (gauss (), costheta ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

get\_lorentz\_torque(), write\_rot(), get\_viscous\_torque\_complex(),

- precision\_mod: This module controls the precision used in MagIC
- useful (abortrun ()): library with several useful subroutines
- output\_data(tag()): This module contains the parameters for output control

get\_viscous\_torque\_real(), get\_angular\_moment()

- logic (l\_rot\_ic(), l\_finite\_diff(), l\_drift(), l\_iner(), l\_save\_out(), l\_srma(), l\_mag\_lf(), l\_rot\_ma(), l\_am(), l\_sric(), l\_mag()): Module containing the logicals that control the run
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction
- parallel\_mod: This module contains the blocking information
- integration (rint\_r()): Radial integration functions
- special (lgrenoble(), bic()): This module contains all variables for the case of an imposed IC dipole, an imposed external magnetic field and a special boundary forcing to excite inertial modes
- num\_param(tscale(), lscale(), vscale()): Module containing numerical and control parameters
- $physical\_parameters$  (kbotv(), ktopv()): Module containing the physical parameters
- truncation (nrp(), minc(), n\_phi\_max(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- blocking (lo\_map(), lmstartb(), st\_map(), lm2(), lmstopb()): Module containing blocking information
- constants (c\_moi\_oc(), y11\_norm(), third(), y10\_norm(), two(), four(), zero(), c\_moi\_ic(), half(), c\_moi\_ma(), pi()): module containing constants and parameters used in the code.
- radial\_functions (r\_icb(), r\_cmb(), rscheme\_oc(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

```
    outrot/n_inerp_file [integer,private]
    outrot/inert_file [character,private]
    outrot/rot_file [character,private]
```

- outrot/driftvd\_file [character,private]
- outrot/srma\_file [character,private]
- outrot/sric\_file [character,private]
- outrot/driftvq\_file [character,private]
- outrot/n\_driftvq\_file [integer,private]
- outrot/n\_driftvd\_file [integer,private]
- outrot/get\_viscous\_torque [public]
- outrot/driftbq\_file [character,private]
- outrot/n\_inert\_file [integer, private]
- outrot/angular\_file [character,private]
- outrot/n\_angular\_file [integer,private]
- outrot/driftbd\_file [character,private]
- outrot/n\_srma\_file [integer,private]
- outrot/n\_rot\_file [integer,private]
- outrot/n\_driftbq\_file [integer,private]
- outrot/inerp\_file [character,private]
- outrot/n\_sric\_file [integer,private]
- outrot/n\_driftbd\_file [integer,private]

## Subroutines and functions

- time [real,in]
- **dt** [real,in]
- ekinic [real,out]
- ekinma [real,out]

```
• w (ulm-(llm)+1,n_r_max) [complex,in]
```

- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- omega\_ic [real,in]
- omega ma [real,in]
- lorentz\_torque\_ic [real,in]
- lorentz\_torque\_ma [real,in]

## Called from output ()

Call to sendvals\_to\_rank0(), get\_angular\_moment()

# subroutine outrot/get\_viscous\_torque\_real (viscous\_torque, z10, dz10, r)

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

- Input:

#### **Parameters**

- viscous\_torque [real,out]
- **z10** [real,in] :: z10 coefficient and its radial deriv.
- **dz10** [real,in]
- **r** [real,in] :: radius (ICB or CMB)

# subroutine outrot/get\_viscous\_torque\_complex(viscous\_torque, z10, dz10, r)

Purpose of this subroutine is to calculate the viscous torque on mantle or inner core respectively. NOTE: sign is wrong for torque on mantle!

- Input:

#### **Parameters**

- viscous\_torque [real,out]
- **z10** [complex,in] :: z10 coefficient and its radial deriv.
- dz10 [complex,in]
- r [real,in] :: radius (ICB or CMB)

**subroutine** outrot/**get\_lorentz\_torque**(lorentz\_torque, nthetastart, sizethetab, br, bp, nr)

- **lorentz\_torque** [real,inout] :: lorentz\_torque for theta(1:n\_theta)
- nthetastart [integer,in] :: first number of theta in block
- **sizethetab** [integer,in] :: size of theta bloching
- **br** (*nrp*,\*) [*real,in*] :: array containing
- **bp** (*nrp*,\*) [*real,in*] :: array containing
- **nr** [integer,in]

```
Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
             do_iteration_thetablocking_shtns()
subroutine outrot/get_angular_moment(z10, z11, omega_ic, omega_ma, angular_moment_oc,
                                              angular_moment_ic, angular_moment_ma)
         Parameters
               • z10 (n_r_max) [complex,in]
               • z11 (n_r_max) [complex,in]
               • omega ic [real,in]
               • omega_ma [real,in]
               • angular_moment_oc (*) [real,out]
               • angular_moment_ic (*) [real,out]
               • angular_moment_ma (*) [real,out]
         Called from write_rot(), updatez()
         Call to rint_r()
subroutine outrot/sendvals_to_rank0 (field, n_r, lm_vals, vals_on_rank0)
     - Input variables:
         Parameters
               • field (ulm-(llm)+1,n_r_max) [complex,in]
               • n_r [integer,in]
               • lm_vals (*) [integer,in]
               • vals_on_rank0 (*) [complex,out]
         Called from write_rot()
         Call to abortrun()
10.15.7 outPar.f90
```

# **Description**

This module is used to compute several time-averaged radial profiles: fluxes, boundary layers, etc.

## **Quick access**

```
Variables n_perppar_file, perppar_file, dlvcmeanr, dlvmeanr, dlvu2cmeanr,
    dlvu2meanr, duhmeanr, eparaximeanr, eparmeanr, eperpaximeanr,
    eperpmeanr, fcondmeanr, fconvmeanr, fkinmeanr, fpoynmeanr, fresmeanr,
    fviscmeanr, gradt2meanr, mvar, rmmeanr, rolmeanr, rolmeanru2, smeanr,
    svar, uhmeanr
Routines finalize_outpar_mod(), initialize_outpar_mod(), outperppar(),
    outpar()
```

## **Needed modules**

- horizontal\_data(gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- output\_data(tag()): This module contains the parameters for output control
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (cc2real ()): library with several useful subroutines
- fields (ds\_rloc(), dp\_rloc(), s\_rloc(), p\_rloc()): This module contains the potential fields and their radial derivatives
- num\_param(tscale()): Module containing numerical and control parameters
- legendre\_spec\_to\_grid(lmas2pt())
- integration (rint\_r()): Radial integration functions
- radial\_data(nrstartmag(), nrstart(), nrstopmag(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- logic (l\_anelastic\_liquid(), l\_mag\_nl(), l\_tp\_form(), l\_temperature\_diff(), l\_save\_out(), l\_anel(), l\_perppar(), l\_fluxprofs(), l\_viscbccalc()): Module containing the logicals that control the run
- physical\_parameters (prmag(), kbots(), ek(), opr(), ekscaled(), vischeatfac(), ktops(), thexpnb(), ohmlossfac()): Module containing the physical parameters
- radial\_functions (rscheme\_oc(), kappa(), dlalpha0(), rho0(), or2(), alpha0(), dltemp0(), beta(), temp0(), orho1(), r(), sigma()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lm2m(), nthetabs(), nfs(), sizethetab()): Module containing blocking information
- constants (four (), osq4pi (), two (), sq4pi (), mass (), half (), pi ()): module containing constants and parameters used in the code.
- truncation (lm\_max(), l\_max(), l\_maxmag(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation

## **Variables**

- outpar\_mod/fconvmeanr (:) [real,private/allocatable]
- outpar\_mod/eparmeanr (:) [real,private/allocatable]
- outpar\_mod/dlvcmeanr (:) [real,private/allocatable]
- outpar\_mod/dlvu2cmeanr (:) [real,private/allocatable]
- outpar\_mod/fcondmeanr (:) [real,private/allocatable]
- outpar\_mod/rolmeanru2 (:) [real,private/allocatable]
- outpar\_mod/eparaximeanr (:) [real,private/allocatable]
- outpar\_mod/fpoynmeanr (:) [real,private/allocatable]

- outpar\_mod/rolmeanr(:) [real, private/allocatable]
- outpar\_mod/fresmeanr (:) [real,private/allocatable]
- outpar\_mod/fviscmeanr(:) [real,private/allocatable]
- outpar\_mod/duhmeanr (:) [real,private/allocatable]
- outpar\_mod/rmmeanr(:) [real,private/allocatable]
- outpar\_mod/mvar (:) [real,private/allocatable]
- outpar\_mod/smeanr (:) [real,private/allocatable]
- outpar\_mod/gradt2meanr(:) [real,private/allocatable]
- outpar\_mod/dlvu2meanr(:) [real,private/allocatable]
- outpar\_mod/**fkinmeanr** (:) [real,private/allocatable]
- outpar\_mod/n\_perppar\_file [integer,private]
- outpar\_mod/uhmeanr(:) [real,private/allocatable]
- outpar\_mod/svar (:) [real,private/allocatable]
- outpar\_mod/eperpaximeanr (:) [real,private/allocatable]
- outpar\_mod/dlvmeanr(:) [real,private/allocatable]
- outpar\_mod/perppar\_file [character,private]
- outpar\_mod/eperpmeanr (:) [real,private/allocatable]

## Subroutines and functions

- timepassed [real,in]
- **timenorm** [real,in]
- **nlogs** [integer,in]
- l\_stop\_time [logical,in]
- **ekinr** (*n\_r\_max*) [*real,in*] :: kinetic energy w radius
- **rolru2** (*n\_r\_max*) [real,in]
- **dlvr** (*n\_r\_max*) [*real,in*]
- **dlvrc** (*n\_r\_max*) [real,in]
- **dlvru2** (*n\_r\_max*) [*real,in*]

```
• dlvru2c (n_r_max) [real,in]
                • uhlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • duhlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • gradslmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fconvlmr (l max+1,nrstop-(nrstart)+1) [real,in]
                • fkinlmr (l max+1,nrstop-(nrstart)+1) [real,in]
                • fvisclmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • fpoynlmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,in]
                • freslmr (l_maxmag+1,nrstopmag-(nrstartmag)+1) [real,in]
                • rmr (n_r_max) [real,out]
          Called from output ()
          Call to cc2real(), lmas2pt()
subroutine outpar_mod/outperppar(time, timepassed, timenorm, l_stop_time, eperplmr, eparlmr,
                                           eperpaxilmr, eparaxilmr)
     — Input of variables
          Parameters
                • time [real,in]
                • timepassed [real,in]
                • timenorm [real,in]
                • l_stop_time [logical,in]
                • eperplmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • eparlmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • eperpaxilmr (l_max+1,nrstop-(nrstart)+1) [real,in]
                • eparaxilmr (l_max+1,nrstop-(nrstart)+1) [real,in]
          Called from output ()
          Call to Imas2pt(), rint_r()
10.15.8 power.f90
Quick access
     Variables n power file, power file, buo chem meanr, buomeanr, ohmdissr,
          vischeatmeanr
     Routines finalize output power(), initialize output power(), get power()
```

## **Needed modules**

• horizontal\_data(dlh(), gauss()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order

- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- outrot(get\_viscous\_torque())
- useful (cc22real (), cc2real ()): library with several useful subroutines
- output data (tag()): This module contains the parameters for output control
- logic (l\_rot\_ic(), l\_anelastic\_liquid(), l\_chemical\_conv(), l\_mag(), l\_save\_out(), l\_srma(), l\_rot\_ma(), l\_heat(), l\_tp\_form(), l\_sric(), l\_cond\_ic(), l\_conv()): Module containing the logicals that control the run
- legendre\_spec\_to\_grid(lmas2pt())
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(n\_r\_cmb(), nrstart(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- integration(rint\_r(), rintic()): Radial integration functions
- num\_param (escale (), tscale ()): Module containing numerical and control parameters
- physical\_parameters (kbotv(), buofac(), lffac(), vischeatfac(), ktopv(), chemfac(), opm(), thexpnb()): Module containing the physical parameters
- truncation (n\_r\_ic\_max(), 1\_max(), n\_r\_maxmag(), n\_r\_ic\_maxmag(), n\_r\_max()): This module defines the grid points and the truncation
- blocking (lmstartb(), nthetabs(), sizethetab(), nfs(), lmstopb(), lo\_map(), st\_map()): Module containing blocking information
- constants (half(), two(), one()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), orhol(), r\_ic(), r\_cmb(), o\_r\_ic2(), or2(), alpha0(), rgrav(), r(), temp0(), o\_r\_ic(), dr\_fac\_ic(), r\_icb(), chebt\_ic(), otemp1(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

- power/ohmdissr(:) [real,private/allocatable]
- power/buo chem meanr (:) [real,private/allocatable]
- power\_file [character,private]
- power/buomeanr (:) [real,private/allocatable]
- power/vischeatmeanr(:) [real,private/allocatable]
- power/n\_power\_file [integer, private]

## Subroutines and functions

#### Called from magic

subroutine power/finalize\_output\_power()

Called from magic

This subroutine calculates power and dissipation of the core/mantle system. Energy input into the outer core is by buoyancy and possibly viscous accelarations at the boundaries if the rotation rates of inner core or mantle are prescribed and kept fixed. The losses are due to Ohmic and viscous dissipation. If inner core and mantel are allowed to change their rotation rates due to viscous forces this power is not lost from the system and has to be respected.

The output is written into a file power.TAG.

## - Input of variables:

- time [real,in]
- timepassed [real,in]
- **timenorm** [real,in]
- l\_stop\_time [logical,in]
- omega\_ic [real,in]
- omega\_ma [real,in]
- lorentz\_torque\_ic [real,in]
- lorentz\_torque\_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **xi** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **ddb** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **aj** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **dj** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [complex,in]
- **db\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **ddb\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- visclmr (l\_max+1,nrstop-(nrstart)+1) [real,in]
- viscdiss [real,out]

• **ohmdiss** [real,out]

```
Called from output()
Call to lmas2pt(), cc2real(), cc22real(), rint_r(), rintic()
```

# 10.15.9 spectra.f90

#### Quick access

```
Variables n_am_kpol_file, n_am_ktor_file, n_am_mpol_file, n_am_mtor_file, n_kin_spec_file, n_mag_spec_file, n_temp_spec_file, n_u2_spec_file, am_kpol_file, am_ktor_file, am_mpol_file, am_mtor_file, dt_icb2_ave, dt_icb_ave, e_cmb2_l_ave, e_cmb2_m_ave, e_cmb_l_ave, e_cmb_m_ave, e_p2_l_ave, e_p2_m_ave, e_p1_ave, e_p_m_ave, e_t2_l_ave, e_t2_m_ave, e_t1_ave, ek_p2_l_ave, ek_p2_m_ave, ek_p1_ave, ek_p1_ave, ek_t2_l_ave, ek_t2_l_ave, t_ave, t_icb2_ave, t_icb_ave
```

Routines finalize\_spectra(), initialize\_spectra(), spectrum\_average(), spectrum\_temp\_average(), spectrum\_temp(), spectrum(), get\_amplitude(), get\_standard\_deviation()

#### **Needed modules**

- horizontal\_data (dlh ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- useful (abortrun(), cc22real(), cc2real()): library with several useful subroutines
- output\_data (n\_log\_file(), tag(), m\_max\_modes(), log\_file()): This module contains the parameters for output control
- logic (l\_mag(), l\_heat(), l\_anel(), l\_save\_out(), l\_energy\_modes(), l\_cond\_ic()): Module containing the logicals that control the run
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- integration(rint\_r(), rintic()): Radial integration functions
- num\_param (escale(), tscale()): Module containing numerical and control parameters
- physical\_parameters (lffac()): Module containing the physical parameters
- truncation (n\_r\_ic\_max(), l\_max(), n\_r\_ic\_maxmag(), minc(), n\_r\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation
- blocking (lo\_map(), st\_map()): Module containing blocking information

- constants (one (), four (), vol\_oc(), pi(), half()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), orho1(), orho2(), dr\_fac\_ic(), or2(), r\_ic(), r(), r\_icb(), chebt\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

- spectra/n\_am\_mtor\_file [integer,private]
- spectra/e\_cmb2\_m\_ave (:) [real,private/allocatable]
- spectra/ek\_p\_l\_ave(:) [real,private/allocatable]
- spectra/e\_t2\_m\_ave(:) [real,private/allocatable]
- spectra/e\_t2\_1\_ave(:) [real,private/allocatable]
- spectra/ek\_t\_l\_ave(:)[real,private/allocatable]
- spectra/ek\_p2\_m\_ave(:) [real,private/allocatable]
- spectra/t\_icb2\_ave(:) [real,private/allocatable]
- spectra/n\_kin\_spec\_file [integer,private]
- spectra/e\_p\_l\_ave (:) [real,private/allocatable]
- spectra/e\_cmb2\_1\_ave (:) [real,private/allocatable]
- spectra/n\_u2\_spec\_file [integer,private]
- spectra/n\_temp\_spec\_file [integer,private]
- spectra/am\_mtor\_file [character,private]
- spectra/e\_cmb\_l\_ave(:) [real,private/allocatable]
- spectra/ek\_p\_m\_ave(:)[real,private/allocatable]
- spectra/e\_p2\_1\_ave(:) [real,private/allocatable]
- spectra/t\_icb\_ave (:) [real,private/allocatable]
- spectra/**e\_p\_m\_ave** (:) [real,private/allocatable]
- spectra/**e\_t\_l\_ave** (:) [real,private/allocatable]
- spectra/dt icb2 ave(:) [real,private/allocatable]
- spectra/**e\_t\_m\_ave** (:) [real,private/allocatable]
- spectra/t\_ave(:) [real,private/allocatable]
- spectra/n\_am\_mpol\_file[integer,private]
- spectra/am\_ktor\_file [character,private]
- spectra/dt\_icb\_ave(:) [real,private/allocatable]
- spectra/ek\_t\_m\_ave(:) [real,private/allocatable]
- spectra/n\_am\_kpol\_file [integer,private]
- spectra/am\_kpol\_file [character,private]
- spectra/am\_mpol\_file [character,private]

```
• spectra/ek_t2_m_ave(:) [real,private/allocatable]
   • spectra/t2_ave (:) [real,private/allocatable]
   • spectra/ek_p2_1_ave (:) [real,private/allocatable]
   • spectra/e_p2_m_ave(:) [real,private/allocatable]
   • spectra/e_cmb_m_ave(:) [real,private/allocatable]
   • spectra/n_mag_spec_file [integer,private]
   • spectra/n_am_ktor_file [integer,private]
   • spectra/ek_t2_1_ave(:) [real,private/allocatable]
Subroutines and functions
subroutine spectra/initialize_spectra()
         Called from magic
subroutine spectra/finalize_spectra()
         Called from magic
subroutine spectra/spectrum_average(n_time_ave, l_stop_time, time_passed, time_norm, b, aj,
                                             db, bv)
     - Input variables:
         Parameters
               • n time ave [integer,in]
               • l_stop_time [logical,in]
               • time_passed [real,in]
               • time_norm [real,in]
               • b (ulm-(llm)+1,n_r_max) [complex,in]
               • aj(ulm-(llm)+1,n_r_max)[complex,in]
               • db (ulm-(llm)+1,n_r_max) [complex,in]
               • bv [character,in]
         Called from output ()
         Call to cc2real(), rint_r(), abortrun(), get_standard_deviation()
function spectra/get_standard_deviation(dt_norm, mean, sum_of_squares)
         Parameters
               • dt_norm [real,in]
               • mean [real,in]
               • sum_of_squares [real,in]
         Return stdev [real]
         Called from spectrum_average(), spectrum_temp_average()
subroutine spectra/spectrum(time, n_spec, w, dw, z, b, db, aj, b_ic, db_ic, aj_ic)
```

calculates magnetic energy = 1/2 Integral(B^2 dV) integration in theta,phi by summation over harmonic coeffs. integration in r by Chebycheff integrals

Output: enbp: Total poloidal enbt: Total toroidal apome: Axisym. poloidal atome: Axisym. toroidal – Input of variables:

#### **Parameters**

- time [real,in]
- **n\_spec** [integer,in] :: number of spectrum/call, file
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **db** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **db\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]

```
Called from fields_average(), output()
```

Call to cc2real(), rint\_r(), cc22real(), rintic()

- Direct input:

## **Parameters**

- n\_time\_ave [integer,in]
- l\_stop\_time [logical,in]
- time\_passed [real,in]
- time\_norm [real,in]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- ds (ulm-(llm)+1, $n_r_max$ ) [complex,in]

Called from output ()

Call to cc2real(), rint\_r(), get\_standard\_deviation()

subroutine spectra/spectrum\_temp (time, n\_spec, s, ds)

calculates spectra of temperature and composition

- Input variables:

- time [real,in]
- **n\_spec** [integer,in] :: number of spectrum/call, file
- $\mathbf{s}$  (ulm-(llm)+1,n\_r\_max) [complex,in]

```
• ds (ulm-(llm)+1,n_r_max) [complex,in]
Called from fields_average(), output()
Call to cc2real(), rint_r()
subroutine spectra/get_amplitude(time, w, dw, z, b, db, aj)
- Input of variables:
Parameters
• time [real,in]
• w (ulm-(llm)+1,n_r_max) [complex,in]
• dw (ulm-(llm)+1,n_r_max) [complex,in]
• z (ulm-(llm)+1,n_r_max) [complex,in]
• b (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
• db (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
• aj (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
Called from output()
Call to cc2real(), rint_r()
```

# 10.16 IO: graphic files, movie files, coeff files and potential files

# 10.16.1 out\_graph\_file.f90

## **Description**

This module contains the subroutines that store the 3-D graphic files.

#### **Quick access**

```
Routines graphout_ic(), graph_write_mpi(), graph_write(), graphout_header(), graphout_mpi_header(), graphout_mpi(), graphout()
```

#### **Needed modules**

- horizontal\_data(dplm(), plm(), dlh(), theta\_ord(), o\_sin\_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- output\_data(n\_graph\_file(), runid(), graph\_mpi\_fh()): This module contains the parameters for output control
- logic(l\_pressgraph(), l\_chemical\_conv(), l\_cond\_ic(), l\_mag()): Module containing the logicals that control the run
- legendre\_spec\_to\_grid(legtf())

- radial\_data (n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- num\_param (vscale()): Module containing numerical and control parameters
- physical\_parameters (pr(), prmag(), ek(), sigma\_ratio(), radratio(), ra()): Module containing the physical parameters
- truncation (n\_r\_ic\_max(), lm\_maxmag(), nrp(), n\_r\_ic\_maxmag(), minc(), n\_phi\_max(), l\_max(), l\_axi(), n\_r\_max(), lm\_max(), n\_theta\_max(), n\_r\_maxmag(), n\_phi\_tot()): This module defines the grid points and the truncation
- leg\_helper\_mod(legprep\_ic())
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- radial\_functions (orho1(), r\_cmb(), o\_r\_ic2(), or2(), or1(), r\_ic(), r(), o\_r\_ic(), r\_icb()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

## Subroutines and functions

**subroutine** graphout\_mod/**graphout** (time,  $n_-r$ , vr, vt, vp, br, bt, bp, sr, prer, xir,  $n_\_theta\_start$ ,  $n_\_theta\_block\_size$ , lgraphheader)

Output of components of velocity, magnetic field vector and entropy for graphics.

• n r: (input) for n r = 0 a header is written.

for n > 0 values at radial level n = r are written

- vr...sr: (input) arrays with grid-point values
- n\_theta\_start : (input) values are written for theta-points :

```
n_theta_start <= n_theta <= n_theta_start-1+n_theta_block
```

- Input variables

- time [real,in]
- **n\_r** [integer,in] :: radial grod point no.
- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [real,in]
- **bt** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [*real*,*in*]
- **sr** (*nrp*,\*) [*real*,*in*]
- **prer** (*nrp*,\*) [real,in]
- **xir** (*nrp*,\*) [real,in]

```
• n_theta_start [integer,in] :: start theta no.
                 • n_theta_block_size [integer,in] :: size of theta block
                • lgraphheader [logical,inout]
          Called from fields_average()
          Call to graph_write()
subroutine graphout_mod/graphout_header(time)

    Input variables

          Parameters time [real,in]
subroutine graphout_mod/graphout_mpi(time, n_r, vr, vt, vp, br, bt, bp, sr, prer, xir,
                                                  n\_theta\_start, n\_theta\_block\_size, lgraphheader)
          MPI version of the graphOut subroutine (use of MPI_IO)
     - Input variables:
          Parameters
                • time [real,in]
                • n_r [integer,in] :: radial grod point no.
                • vr (nrp,*) [real,in]
                • vt (nrp,*) [real,in]
                 • vp (nrp,*) [real,in]
                • br (nrp,*) [real,in]
                • bt (nrp,*) [real,in]
                • bp (nrp,*) [real,in]
                • sr (nrp,*) [real,in]
                • prer (nrp,*) [real,in]
                • xir (nrp,*) [real,in]
                • n_theta_start [integer,in] :: start theta no.
                • n_theta_block_size [integer,in] :: size of theta block
                • lgraphheader [logical,inout]
          Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
               do_iteration_thetablocking_shtns()
          Call to graph_write_mpi()
subroutine graphout_mod/graphout_mpi_header (time, n_r, n_theta_start, n_theta_block_size)
          Writes the header (MPI version)
     - Input variables:
          Parameters
                 • time [real,in]
                 • n_r [integer,in] :: radial grod point no.
```

• n\_theta\_start [integer,in] :: start theta no.

• n\_theta\_block\_size [integer,in] :: size of theta block

Called from radialloopg()

```
subroutine graphout_mod/graphout_ic(b_ic, db_ic, ddb_ic, aj_ic, dj_ic, bicb)
```

Purpose of this subroutine is to write inner core magnetic field onto graphic output file. If the inner core is insulating (l\_cond\_ic=false) the potential field is calculated from the outer core field at r=r\_cmb. This version assumes that the fields are fully local on the rank which is calling this routine (usually rank 0).

- Input variables:

## **Parameters**

- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- ddb\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **bicb** (*lm\_maxmag*) [*complex*,*in*]

```
Called from fields_average(), output()
```

```
Call to legprep_ic(), legtf(), fft_thetab(), graph_write_mpi()
```

**subroutine** graphout\_mod/**graph\_write** (*n\_phis*, *n\_thetas*, *dummy*, *n\_graph\_file*)

This subroutine writes the data for one theta-band (stored in 'dummy'). Version May, 5, 2000.

- Input variables:

## **Parameters**

- **n\_phis** [integer,in] :: number of logitudes to be printed
- **n\_thetas** [integer,in] :: number of first colatitude value
- **dummy** (*n\_phi\_max*,\*) [*real,in*] :: data
- n\_graph\_file [integer,in] :: output unit

Called from graphout ()

## **Parameters**

- **n\_phis** [integer,in] :: number of logitudes to be printed
- n\_thetas [integer,in] :: number of first colatitude value
- **dummy** (n\_phi\_max,\*) [real,in] :: data
- graph\_mpi\_fh [integer,in] :: mpi handle of the mpi file

Called from graphout\_ic(), graphout\_mpi()

## 10.16.2 movie.f90

#### **Quick access**

Variables n\_frame\_work, n\_md, n\_movies, n\_movies\_max, n\_movie\_fields\_max, licfield, lstoremov, n\_movie\_const, n\_movie\_fields, n\_movie\_fields\_ic, n\_movie\_file, n\_movie\_surface, n\_movie\_type, n\_movie\_field\_start, n\_movie\_field\_stop, n\_movie\_field\_type, moviedipcolat, moviediplon, moviedipstrength, moviedipstrengthgeo, frames, movie\_file, movie, t movies, movie const

**Routines** get\_movie\_type(), finalize\_movie\_data(), initialize\_movie\_data(), movie\_gather\_frames\_to\_rank0()

#### **Needed modules**

- horizontal\_data(theta(), phi()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- useful (abortrun(), logwrite()): library with several useful subroutines
- output\_data(n\_log\_file(), log\_file(), tag()): This module contains the parameters for output control
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- radial\_data(n\_r\_cmb(), nrstart(), n\_r\_icb(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod: This module contains the blocking information
- logic (l\_movie\_oc(), l\_dtbmovie(), l\_movie\_ic(), l\_store\_frame(), l\_save\_out(), l\_htmovie(), l\_movie()): Module containing the logicals that control the run
- charmanip (length\_to\_blank(), delete\_string(), capitalize(), str2dble()): This module contains several useful routines to manipule character strings
- truncation (n\_r\_ic\_max(), lmoviemem(), ldtbmem(), minc(), n\_phi\_max(), n\_r\_tot(), n\_r\_max(), n\_theta\_max()): This module defines the grid points and the truncation
- constants (pi (), one ()): module containing constants and parameters used in the code.
- radial\_functions (r\_cmb(), r\_icb(), r(), r\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

## **Variables**

- movie\_data/n\_frame\_work [integer, public]
- movie\_data/n\_movies[integer,public]
- movie\_data/n\_movie\_field\_stop (6,30) [integer,public]
- movie\_data/n\_movie\_surface (30) [integer,public]
- movie\_data/n\_movie\_field\_start (6,30) [integer,public]

- movie\_data/movie\_const (30) [real, public]
- movie\_data/n\_movies\_max [integer,parameter=30/public]
   Max no. of different movies
- movie\_data/n\_movie\_fields\_max [integer,parameter=6/public]
   Max no. of fields per movie
- movie\_data/n\_md [integer,public]
- movie\_data/frames (:) [real,allocatable/public]
- movie\_data/moviediplon [real,public]
- movie\_data/n\_movie\_fields\_ic (30) [integer, public]
- movie\_data/moviedipstrengthgeo [real,public]
- movie\_data/n\_movie\_field\_type (6,30) [integer,public]
- movie\_data/licfield(30)[logical,public]
- movie\_data/movie (30) [character,public]
  Only for input
- movie\_data/n\_movie\_file (30) [integer,public]
- movie\_data/n\_movie\_fields (30) [integer,public]
- movie\_data/t\_movies (10000) [real, public]
- movie\_data/n\_movie\_const (30) [integer,public]
- movie\_data/moviedipcolat [real,public]
- movie\_data/movie\_file (30) [character,public]
- movie\_data/lstoremov(30)[logical,public]
- movie\_data/moviedipstrength [real,public]
- movie\_data/n\_movie\_type (30) [integer,public]

#### Subroutines and functions

```
subroutine movie_data/initialize_movie_data()
```

This routine is called during the initialization of the code. It allows to:

• Estimate the required memory imprint and allocate the arrays

accordingly \* Open the requested movie files

```
Called from magic
```

Call to get\_movie\_type()

subroutine movie\_data/finalize\_movie\_data()

Close movie files

Called from magic

```
subroutine movie_data/get_movie_type()
```

Purpose of this subroutine is to identify the different movie types from the input string movies(\*). Note that generally blanks are not interpreted and that the interpretation is not case sensitive. In general two informations are needed:

- 1. A word FIELDINFO that identifies the field to be plotted (e.g. Br for radial magnetic field, see list below) Possible keywords are (optional text in brackets):
  - B r[adial] : radial magnetic field
  - B t[heta]: theta component
  - B p[hi]: azimuthal component
  - B h[orizontal]: the two horizontal components
  - B a[ll]: all three components
  - FIELDLINE[S]: field lines of axisymmetric

or FL poloidal field for phi=constant - AX[ISYMMETRIC] B or AB: axisymmetric phi component of the magnetic field for phi=constant - V r[adial]: radial velocity field - V t[heta]: theta component - V p[hi]: azimuthal component - V h[orizontal]: the two horizontal components - V a[ll]: all three components - STREAMLINE[S]: field lines of axisymmetric or SL: poloidal field for phi=constant - AX[ISYMMETRIC] V or AV: axisymmetric phi component of the velocity field for phi=constant - V z : z component of velocity at equator and z component of the vorticity at the equator (closest point to equator) - Vo z: z-component of vorticity - Vo r: r-component of vorticity - Vo p: phicomponent of vorticity - T[emperature] : sic - AX[ISYMMETRIC] T or AT : axisymmetric T field for phi=constant - Heat t[ransport]: radial derivative of T - FL Pro: axisymmetric field line stretching - FL Adv: axisymmetric field line advection - FL Dif: axisymmetric field line diffusion - AB Pro : axisymmetric (tor.) Bphi production - AB Dif : axisymmetric (tor.) Bphi diffusion - Br Pro : Br production - Br Adv: Br advection - Br Dif: Br diffusion - Jr: Jr production - Jr Pro: Jr production + omega effects - Jr Adv : Jr advection - Jr Dif : Jr diffusion - Bz Pol : poloidal Bz - Bz Pol Pro : poloidal Bz production - Bz Pol Adv: poloidal Bz advection - Bz Pol Dif: poloidal Bz diffusion -Jz Tor: poloidal Jz - Jz Tor Pro: poloidal Jz production - Jz Tor Adv: poloidal Jz advection - Jz Tor Dif: poloidal Jz diffusion - Bp Tor: toriodal Bphi - Bp Tor Pro: toriodal Bphi production -Bp Tor Adv: toriodal Bphi advection - Bp Tor Dif: toriodal Bphi diffusion - HEL[ICITY]: sic -AX[ISYMMETRIC HELICITY] or AHEL: axisymmetric helicity - Bt Tor: toroidal Btheta - Pot Tor: toroidal Potential - Pol Fieldlines: toroidal Potential - Br Shear: azimuthal Shear of Br -Lorentz[force]: Lorentz force (only phi component) - Br Inv: Inverse field apperance at CMB

- 2. A second information that identifies the coordinate to be kept constant (surface). E.g. r=number for surface r=constant with number given in units of the total core radius or theta/phi=number with number given in degrees Four keywords are also possible:
  - CMB : core mantle boundary
  - EQ[UATOR] : equatorial plane
  - SUR[FACE] : Earth surface (only magnetic field)
  - 3[D]: 3D field throughout the OC [and IC for B]

On output the necessary information is coded into integers and is used in this form by further sub-routines:

- n\_movies = total number of movies
- n\_type(n\_movie) = movie type:
- = 1 : Radial magnetic field
- = 2 : Theta component of magnetic field
- = 3 : Azimuthal magnetic field
- = 4 : Horizontal magnetic field

- = 5 : Total magnetic field (all compnents)
- = 8 : Axisymmetric azimuthal

magnetic field (phi=constant) - = 9 : 3d magnetic field - = 11 : Radial velocity field - = 12 : Theta component of velocity field - = 13: Azimuthal velocity field - = 14: Horizontal velocity field - = 15: Total velocity field (all compnets) - = 17: Scalar field whose contours are the stream lines of the axisymm. poloidal velocity field (phi=constant) - = 18: Axisymmetric azimuthal velocity field (phi=constant) - = 19: 3d velocity field - = 20: z component of vorticity - = 21: Temperature field - = 22 : radial conv. heat transport - = 23 : helicity - = 24 : axisymmetric helicity - = 25 : phi component of vorticity - = 26: radial component of vorticity - = 28: axisymmetric Temperature field for phi=const. - = 29: 3d temperature field - = 30: Scalar field whose contours are the fieldlines of the axisymm. poloidal magnetic field (phi=constant) - = 31: field line production - = 32: field line advection - = 33: field line diffusion - = 40: Axisymmetric azimuthal magnetic field (phi=constant) -= 41 : Axis, Bphi production + omega eff. - = 42 : Axis, Bphi advection - = 43 : Axis, Bphi diffusion - = 44 : Axis. Bphi str.,dyn.,omega,diff. - = 50 : Bz - = 51 : Bz production - = 52 : Bz advection - = 53 : Bz diffusion - = 60 : toroidal Bphi - = 61 : toroidal Bphi production + omega eff. - = 62 : toroidal Bphi advection - = 63: toroidal Bphi diffusion - = 71: Br production - = 72: Br advection - = 73 : Br diffusion - = 80 : Jr - = 81 : Jr production - = 82 : Jr advection - = 83 : Jr diffusion - = 90 : poloidal Jz pol. - = 91 : poloidal Jz pol. production - = 92 : poloidal Jz advection - = 93 : poloidal Jz diffusion - = 94 : z component of velovity - = 95 : toroidal Btheta - = 96 : toroidal Potential - = 97 : Function for Poloidal Fieldlines - = 98 : azimuthal shear of Br - = 99 : phi component of Lorentz force - =101 : Stress fields - =102 : Force fields - =103 : Br Inverse appearence at CMB - =110 : radial heat flow -=111: Vz and Vorz north/south correlation -=112: axisymm dtB tersm for Br and Bp - =113: axisymm dSdr - =114: Cylindrically radial magnetic field

- n movie surface(n movie) = defines surface
- n\_movie\_surface = 1 : r=constant:
- 2 : theta=constant
- 3 : phi=constant
- -1 : r=constant, Earth surface
- 0: 3d volume
- n\_movie\_fields(n\_movie) = no. of fields for outer core
- n\_movie\_fields\_ic(n\_movie) = no. of fields for inner core
- n\_movie\_field\_type(n\_field,n\_movie) = defines field
- n movie field type:
- = 1 : radial magnetic field
- = 2: theta comp. of the magnetic field
- = 3 : azimuthal magnetic field
- = 4 : radial velocity field
- = 5: theta comp. of the velocity field
- = 6 : azimuthal velocity field
- = 7: temperature field
- = 8 : scalar field for field lines

- = 9 : axisymm. toroidal mag. field
- =10 : scalar field for stream lines
- =11 : axisymm. v\_phi
- =12 : axisymm. T
- =13 : z-comp. of poloidal Bz
- =14 : z-comp. of poloidal Jz
- =15 : z-comp. of velocity
- =16 : z-comp. of vorticity
- =17 : radial derivative of T \* vr
- =18 : helicity
- =19 : axisymmetric helicity
- =20 : axisymm field-line production
- =21 : axisymm field-line advection
- =22 : axisymm field-line diffusion
- =23 : axisymm Bphi production
- =24 : axisymm Bphi omega effect
- =25 : axisymm Bphi advection
- =26 : axisymm Bphi diffusion
- =27 : Br production
- =28 : Br advection
- =29 : Br diffusion
- =30 : Jr
- =31 : Jr production
- =32 : Jr omega effect
- =33 : Jr advection
- =34: Jr diffusion
- =35 : poloidal Bz production
- =36 : poloidal Bz advection
- =37 : poloidal Bz diffusion
- =38 : poloidal Jz production
- =39 : poloidal Jz omega effect
- =40 : poloidal Jz advection
- =41 : poloidal Jz diffusion
- =42 : toroidal Bp
- =43 : toroidal Bp production
- =44 : toroidal Bp omega effect

- =45 : toroidal Bp advection
- =46: toroidal Bp diffusion
- =47 : phi-comp. of vorticity
- =48 : r-comp. of vorticity
- =49 : toroidal Bp omega effect
- =50: toroidal Bt
- =51 : toroidal Potential
- =52 : poloidal Fieldlines in theta=const
- =53 : Br dr ( $vp/(r \sin(theta))$
- =54 : phi Lorentz force
- =61 : AS phi reynolds stress force
- =62 : AS phi advective stress force
- =63 : AS phi viscous stress force
- =64 : AS phi Lorentz force
- =66: time derivative of axisym. v phi
- =67 : relative strength of axisym. v phi
- =81 : Br inverse appearence at CMB
- =91 : radial derivative of T
- =92 : Vz north/south correlation
- =93 : Vorz north/south correlation
- =94 : Hel north/south correlation
- =101: AS poloidal Br production
- =102: AS poloidal Br dynamo term
- =103: AS poloidal Br diffusion
- =104: AS toroidal Bp production
- =105: AS toroidal Bp dynamo term
- =106: AS toroidal Bp omega effect
- =107: AS toroidal Bp diffusion
- =108: Bs
- n\_movie\_field\_start(n\_field,n\_movie) = defines where first

element of a field is stored in frames (\*) \* n\_movie\_field\_stop(n\_field,n\_movie) = defines where last element of a field is stored in frames (\*)

· The subroutine also defines appropriate file names for

the movie files. These generally have the form TYPE\_mov.TAG

## - Local variables:

Called from initialize movie data()

```
Called from output()
Call to abortrun()
```

# 10.16.3 out movie file.f90

#### **Quick access**

```
Routines get_b_surface(), get_fl(), write_movie_frame(), store_movie_frame(), store_fields_sur(), get_sl(), store_fields_p(), store_fields_sur()
```

## **Needed modules**

- horizontal\_data (dplm(), phi(), dlh(), d\_l(), theta\_ord(), osnl(), o\_sin\_theta\_e2(), o\_sin\_theta(), dphi(), plm(), n\_theta\_cal2ord(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod (rank ()): This module contains the blocking information
- output data (runid()): This module contains the parameters for output control
- useful (abortrun()): library with several useful subroutines
- fields (w\_rloc(), b\_ic(), b\_rloc(), b()): This module contains the potential fields and their radial derivatives
- fft (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- out\_dtb\_frame(write\_dtb\_frame())
- !mloop data(llmmag(), ulmmag())
- radial\_data (n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- communications(gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- constants (zero(), two(), one()): module containing constants and parameters used in the code.
- num\_param(tscale(), vscale()): Module containing numerical and control parameters
- physical\_parameters (pr(), prmag(), lffac(), ek(), radratio(), ra()): Module containing the physical parameters

- radial\_functions (orho1(), orho2(), r\_cmb(), or4(), or2(), or3(), or1(), r\_ic(), beta(), r(), r\_surface()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (1m2(), 1m21(), nfs()): Module containing blocking information
- logic(l\_save\_out(), l\_cond\_ic()): Module containing the logicals that control the run
- truncation (n\_r\_ic\_max(), l\_max(), n\_r\_ic\_maxmag(), minc(), n\_phi\_max(), lm\_maxmag(), l\_axi(), n\_r\_max(), n\_m\_max(), lm\_max(), nrp(), n\_r\_maxmag(), n\_theta\_max()): This module defines the grid points and the truncation

#### **Variables**

# **Subroutines and functions**

```
subroutine out_movie/store_movie_frame (n_r, vr, vt, vp, br, bt, bp, sr, drsr, dvrdp, dvpdr, dvtdr, dvrdt, cvr, cbr, cbt, n_theta_start, n_theta_block, bcmb)
```

Controls output of movie frames. Usually called from radialLoop.

- Input variables:

### **Parameters**

- **n\_r** [integer,in] :: radial grid point no.
- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [real,in]
- **drsr** (*nrp*,\*) [real,in]
- **dvrdp** (*nrp*,\*) [*real*,*in*]
- dvpdr (nrp,\*) [real,in]
- **dvtdr** (*nrp*,\*) [real,in]
- **dvrdt** (*nrp*,\*) [*real*,*in*]
- **cvr** (*nrp*,\*) [real,in]
- **cbr** (*nrp*,\*) [*real*,*in*]
- **cbt** (*nrp*,\*) [real,in]
- n\_theta\_start [integer,in] :: start theta no.
- n\_theta\_block [integer,in] :: size of theta block
- **bcmb** (*lm\_max*) [*complex*, *in*]

```
Call to store_fields_sur(),
                                             store fields 3d(), store fields r(),
              store fields t(), store fields p()
subroutine out_movie/write_movie_frame(n_frame, time, b_lmloc, db_lmloc, aj_lmloc,
                                                   dj_lmloc, b_ic, db_ic, aj_ic, dj_ic, omega_ic,
                                                   omega_ma)
          Writes different movie frames into respective output files. Called from rank 0 with full arrays in
          standard LM order.
     – Input of variables:
          Parameters
                • n_frame [integer,in]
                • time [real,in]
                • b_lmloc (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
                • db_lmloc (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
                • aj_lmloc (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
                • dj_lmloc (ulmmag-(llmmag)+1,n_r_maxmag) [complex,in]
                • b_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
                • db_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
                • aj_ic (lm_maxmag,n_r_ic_maxmag) [complex,in]
                • dj ic (lm maxmag,n r ic maxmag) [complex,in]
                • omega ic [real,in]
                • omega_ma [real,in]
          Called from output ()
          Call to gather_all_from_lo_to_rank0(), abortrun(), write_dtb_frame()
subroutine out_movie/store_fields_sur(n_store_last,
                                                                   n_field_type,
                                                                                     n_theta_start,
                                                 n_theta_block, bcmb)
          Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)
     - Input variables:
          Parameters
                • n store last [integer,in] :: Start position for storing -1
                • n_field_type [integer,in] :: Defines field type
                • n_theta_start [integer,in] :: Beginning of theta block
                • n_theta_block [integer,in] :: Size of theta block
                • bcmb (lm max) [complex,in]
          Called from store movie frame()
          Call to get_b_surface()
```

 $n\_theta\_block$ )

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

subroutine out\_movie/store\_fields\_r(vr, vt, vp, br, bt, bp, sr, drsr, dvrdp, dvpdr, dvtdr,

*dvrdt*, *cvr*, *n\_r*, *n\_store\_last*, *n\_field\_type*, *n\_theta\_start*,

# - Input variables:

### **Parameters**

- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [*real*,*in*]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real*,*in*]
- **dvpdr** (*nrp*,\*) [*real*,*in*]
- **dvtdr** (*nrp*,\*) [*real,in*]
- **dvrdt** (*nrp*,\*) [*real*,*in*]
- **cvr** (*nrp*,\*) [real,in]
- **n\_r** [integer,in]
- **n\_store\_last** [integer,in] :: Start position in frame(\*)-1
- n\_field\_type [integer,in] :: Defines field type
- n\_theta\_start [integer,in] :: Beginning of theta block
- n\_theta\_block [integer,in] :: Size of theta block

Called from store\_movie\_frame()

Purpose of this subroutine is to store movie frames for surfaces phi=const. into array frames(,)

# - Input variables:

- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bp** (*nrp*,\*) [real,in]
- **bt** (*nrp*,\*) [*real*,*in*]
- **sr** (*nrp*,\*) [real,in]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real,in*]
- **dvpdr** (*nrp*,\*) [*real*,*in*]

```
• dvtdr (nrp,*) [real,in]
                  • dvrdt (nrp,*) [real,in]
                  • cvr (nrp,*) [real,in]
                  • cbr (nrp,*) [real,in]
                  • cbt (nrp,*) [real,in]
                  • n_r [integer,in] :: No. of radial point
                  • n_store_last [integer,in] :: Start position in frame(*)-1
                  • n_field_type [integer,in] :: Defines field type
                  • n_phi_const [integer,in] :: No. of surface phi
                  • n_field_size [integer,in] :: Size of field
                  • n_theta_start [integer,in] :: Beginning of theta block
                  • n_theta_block [integer,in] :: Size of theta block
           Called from store_movie_frame()
           Call to get_fl(), get_sl()
subroutine out_movie/store_fields_t (vr, vt, vp, br, bt, bp, sr, drsr, dvrdp, dvpdr, dvtdr, dvrdt,
                                                     cvr, cbt, n_r, n_store_last, n_field_type, n_theta_const,
                                                     n theta)
           Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)
      - Input variables:
           Parameters
                  • vr (nrp,*) [real,in]
                  • vt (nrp,*) [real,in]
                  • vp (nrp,*) [real,in]
                  • br (nrp,*) [real,in]
                  • bt (nrp,*) [real,in]
                  • bp (nrp,*) [real,in]
                  • sr (nrp,*) [real,in]
                  • drsr (nrp,*) [real,in]
                  • dvrdp (nrp,*) [real,in]
```

cbt (nrp,\*) [real,in]
n\_r [integer,in] :: No. of radial grid point

dvpdr (nrp,\*) [real,in]
dvtdr (nrp,\*) [real,in]
dvrdt (nrp,\*) [real,in]
cvr (nrp,\*) [real,in]

• **n\_store\_last** [integer,in] :: Position in frame(\*)-1

• n\_field\_type [integer,in] :: Defines field

- n\_theta\_const [integer,in] :: No. of theta to be stored
- n\_theta [integer,in] :: No. of theta in block

Called from store\_movie\_frame()

Purpose of this subroutine is to store movie frames for surfaces r=const. into array frame(,)

### - Input variables:

### **Parameters**

- **vr** (*nrp*,\*) [real,in]
- **vt** (*nrp*,\*) [real,in]
- **vp** (*nrp*,\*) [real,in]
- **br** (*nrp*,\*) [*real*,*in*]
- **bt** (*nrp*,\*) [real,in]
- **bp** (*nrp*,\*) [real,in]
- **sr** (*nrp*,\*) [*real*,*in*]
- **drsr** (*nrp*,\*) [*real*,*in*]
- **dvrdp** (*nrp*,\*) [*real*,*in*]
- **dvpdr** (*nrp*,\*) [*real*,*in*]
- **dvtdr** (*nrp*,\*) [*real*,*in*]
- **dvrdt** (*nrp*,\*) [*real*,*in*]
- **cvr** (*nrp*,\*) [real,in]
- **cbr** (*nrp*,\*) [real,in]
- **cbt** (*nrp*,\*) [real,in]
- n\_r [integer,in] :: No. of radial grid point
- **n\_store\_last** [integer,in] :: Position in frame(\*)-1
- n\_field\_type [integer,in] :: Defines field
- n\_theta\_start [integer,in] :: No. of first theta to block
- n\_theta\_block [integer,in] :: Size of theta block

Called from store\_movie\_frame()

subroutine out\_movie/get\_sl(sl, n\_r, n\_theta\_start, n\_theta\_block)

Return field sl whose contourlines are the stream lines of the axisymmetric poloidal velocity field.  $sl(r,theta)=d_theta v(r,theta,m=0)/r$ 

- Input variables:

- sl (\*) [real,out] :: Field for field lines
- n\_r [integer,in] :: No. of radial grid point

- **n\_theta\_start** [integer,in] :: No. of theta to start with
- n theta block [integer,in] :: Size of theta block

```
Called from store_fields_p()
```

```
subroutine out_movie/get_fl(fl, n_r, n_theta_start, n_theta_block, l_ic)
```

Return field fl whose contourlines are the fields lines of the axisymmetric poloidal mangetic field. fl(r,theta)=d theta b(r,theta,m=0)/r

This routine is called for l\_ic=.true. only from rank 0 with full field b\_ic in standard lm ordering available. The case l\_ic=.false. is called from all ranks and uses b\_Rloc.

- Input variables:

### **Parameters**

- fl (\*) [real,out] :: Field for field lines
- **n\_r** [integer,in] :: No. of radial grid point
- n\_theta\_start [integer,in] :: No. of theta to start with
- n\_theta\_block [integer,in] :: Size of theta block
- l\_ic [logical,in] :: =true if inner core field

```
Called from store_fields_p(), store_movie_frame_ic()
```

```
subroutine out_movie/get_b_surface(b_r, b_t, b_p, bcmb, n_theta_start, n_theta_block)
```

Upward continuation of laplacian field to Earths surface. Field is given by poloidal harmonic coefficients b at CMB. Spherical harmonic transforms of upward continued field to r/theta/phi vector components for all logitudes and latitude are returned in br/bt/bp. Note that this routine given the real components of the magnetic fields while other transforms in the code provide only: r\*\*2 br, r\*\*2 sin(theta) bt, r\*\*2 sin(theta) bp

– Input of variables:

### **Parameters**

- **b\_r** (*nrp*,\*) [real,out] :: Radial magnetic field in (phi,theta)-space
- **b\_t** (*nrp*,\*) [real,out] :: Latitudinal magnetic field
- **b\_p** (*nrp*,\*) [real,out] :: Azimuthal magnetic field.
- bcmb (lm\_max) [complex,in]
- n\_theta\_start [integer,in] :: No. of theta to start with
- n theta block [integer,in] :: Size of theta block

```
Called from store_fields_sur()
Call to fft_thetab()
```

# 10.16.4 store movie IC.f90

# Quick access

```
Routines store_movie_frame_ic()
```

# **Needed modules**

- horizontal\_data (dplm(), plm(), dlh(), n\_theta\_cal2ord(), o\_sin\_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie\_data (n\_movie\_fields\_ic(), n\_movies(), n\_movie\_field\_stop(), n\_movie\_surface(), n\_movie\_field\_type(), n\_movie\_field\_start(), n\_movie\_fields(), n\_movie\_const(), frames(), n\_movie\_type())
- out\_movie(get\_fl())
- fft (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- legendre\_spec\_to\_grid(legtf())
- radial\_data (n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- logic(l\_cond\_ic()): Module containing the logicals that control the run
- physical\_parameters (lffac()): Module containing the physical parameters
- truncation (n\_r\_ic\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), minc(), n\_phi\_max(), l\_max(), l\_axi(), lm\_max(), nrp(), n\_r\_maxmag(), n\_theta\_max()): This module defines the grid points and the truncation
- leg\_helper\_mod(legprep\_ic())
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- constants (one ()): module containing constants and parameters used in the code.
- radial\_functions (r\_icb(), r\_ic(), o\_r\_ic2(), o\_r\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

### Subroutines and functions

```
\verb|subroutine| \verb|out_movie_ic/store_movie_frame_ic| (bicb, b\_ic, db\_ic, db\_ic, ddb\_ic, aj\_ic, dj\_ic)|
```

Controls storage of IC magnetic field in movie frame.

- Input of scalar fields:

### **Parameters**

- **bicb** (*lm\_maxmag*) [*complex*,*in*]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **ddb\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]

#### Called from output ()

Call to legprep\_ic(), legtf(), fft\_thetab(), get\_fl()

# 10.16.5 out coeff.f90

# **Description**

This module contains the subroutines that calculate the Bcmb files, the [BIVIT]\_coeff\_r files and the [BIVIT]\_lmr files

### **Quick access**

```
Routines finalize_coeffs(), initialize_coeffs(), write_pot(), write_bcmb(),
    write_coeff_r()
```

#### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output\_data(tag()): This module contains the parameters for output control
- lmloop\_data(llm(), ulm())
- precision\_mod: This module controls the precision used in MagIC
- communications (gather\_from\_lo\_to\_rank0())
- parallel\_mod (rank ()): This module contains the blocking information
- logic(l\_save\_out(), l\_cmb\_field(), l\_r\_field(), l\_average(), l\_cond\_ic()): Module containing the logicals that control the run
- physical\_parameters (pr(), prmag(), ek(), sigma\_ratio(), radratio(), ra()): Module containing the physical parameters
- truncation (lm\_max(), n\_r\_ic\_max(), l\_max(), minc(), n\_r\_max()): This module defines the grid points and the truncation
- blocking (1m2()): Module containing blocking information
- constants (two (), half ()): module containing constants and parameters used in the code.
- radial\_functions (r(), rho0()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

- out\_coeff/work (:) [complex,private/allocatable]
- out\_coeff/filehandle [integer,private]

# Subroutines and functions

**subroutine** out\_coeff/write\_bcmb (time, b\_lmloc, l\_max\_cmb, n\_cmb\_sets, cmb\_file, n\_cmb\_file)

Each call of this subroutine writes time and the poloidal magnetic potential coefficients b at the CMB up to degree and order l\_max\_cmb at the end of output file \$cmb\_file. The parameters l\_max\_cmb, minc and the number of stored coeffs. are written into the first line of \$cmb\_file. Each further set contains:

 $time, \ real(b(l=0,m=0)), imag(b(l=0,m=0)), \ real(b(l=1,m=0)), imag(b(l=1,m=0)), \\$ 

Real and imaginary part of b(\*) for all orders m<=l are written for a specific degree l, then for the degrees l+1, l+2, l\_max\_cmb.

- Input variables:

### **Parameters**

- **time** [real,in] :: Time
- **b\_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]
- l\_max\_cmb [integer,inout] :: Max degree of output
- n cmb sets [integer,inout] :: Total no. of cmb sets,
- cmb\_file [character,in] :: Name of output file
- n\_cmb\_file [integer,inout] :: Output unit for \$cmb\_file

Called from fields\_average(), output()

Call to gather\_from\_lo\_to\_rank0()

Each call of this subroutine writes time and the poloidal and toroidal coeffitients w,dw,z at a specific radius up to degree and order l\_max\_r at the end of output file \$file. If the input is magnetic field (nVBS=2) ddw is stored as well. If the input is entropy field (nVBS=3) only ddw=s is stored. The parameters l\_max\_r, minc, the number of stored coeffs and radius in the outer core are written into the first line of \$file. Each further set contains:

```
\begin{array}{lll} time, & real(w(l=0,m=0)), imag(w(l=0,m=0)), & real(w(l=1,m=0)), imag(w(l=1,m=0)), \\ \dots & real(dw(l=0,m=0)), imag(dw(l=0,m=0)), & real(dw(l=1,m=0)), imag(dw(l=1,m=0)), \\ \dots & real(z(l=0,m=0)), imag(z(l=0,m=0)), & real(z(l=1,m=0)), imag(z(l=1,m=0)), \\ \dots & real(ddw(l=0,m=0)), imag(ddw(l=0,m=0)), real(ddw(l=1,m=0)), \\ \end{array}
```

Real and imaginary part of w(\*) for all orders  $m \le 1$  are written for a specific degree 1, then for the degrees 1+1, 1+2,  $1_max_r$ .

- Input variables:

- **time** [real,in] :: Time
- w lmloc (ulm-(llm)+1) [complex,in]
- dw\_lmloc (ulm-(llm)+1) [complex,in]
- **ddw\_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]
- **z\_lmloc** (*ulm*-(*llm*)+1) [*complex*,*in*]

```
• r [real,in] :: radius of coeffs
```

- l\_max\_r [integer,inout] :: Max degree of output
- **n\_sets** [integer,inout] :: Total no. of cmb sets,
- file [character,in] :: Name of output file
- **n** file [integer,inout] :: Output unit for \$file
- **nvbs** [integer,in] :: True if output is flow

```
Called from output ()
```

```
Call to gather_from_lo_to_rank0()
```

subroutine out\_coeff/write\_pot(time, b, aj, b\_ic, aj\_ic, npotsets, root, omega\_ma, omega\_ic)

This routine stores the fields in spectral and radial space

- Input of variables:

### **Parameters**

- time [real,in]
- **b** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **aj** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b\_ic** (*ulm*-(*llm*)+1,*n\_r\_ic\_max*) [*complex*,*in*]
- **aj\_ic** (*ulm*-(*llm*)+1,*n\_r\_ic\_max*) [*complex*,*in*]
- **npotsets** [integer,inout]
- root [character,in]
- omega\_ma [real,in]
- omega\_ic [real,in]

```
Called from fields_average(), output()
```

Call to gather\_from\_lo\_to\_rank0()

# 10.16.6 field\_average.f90

# **Description**

This module is used when one wants to store time-averaged quantities

### **Quick access**

```
Variables aj_ave_global, b_ave_global, db_ave_global, dw_ave_global, p_ave_global, s_ave_global, w_ave_global, xi_ave_global, z_ave_global, aj_ave, aj_ic_ave, b_ave, b_ic_ave, p_ave, s_ave, w_ave, xi_ave, z_ave
```

Routines finalize\_fields\_average\_mod(), initialize\_fields\_average\_mod(),
 fields\_average()

# **Needed modules**

- horizontal\_data(dplm(), plm(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- fft (fft\_thetab()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_der\_even(get\_drns\_even(), get\_ddrns\_even())
- radial\_der (get\_dr()): Radial derivatives functions
- graphout\_mod (graphout (), graphout\_ic()): This module contains the subroutines that store the 3-D graphic files.
- magnetic\_energy (get\_e\_mag())
- parallel\_mod (rank ()): This module contains the blocking information
- radial\_functions (dr\_fac\_ic(), r(), chebt\_ic(), rscheme\_oc(), chebt\_ic\_even()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- leg\_helper\_mod(legprep())
- fieldslast (dbdt\_iclast\_lmloc(), dzdtlast\_lo(), djdtlast\_lmloc(), djdt\_iclast\_lmloc(), dpdtlast\_lmloc(), dxidtlast\_lmloc(), dwdtlast\_lmloc(), dsdtlast\_lmloc(), dbdtlast\_lmloc()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- storecheckpoints (store()): This module contains several subroutines that can be used to store the checkpoint\_#.tag files
- kinetic\_energy (get\_e\_kin())
- out\_coeff (write\_pot(), write\_bcmb()): This module contains the subroutines that calculate the Bcmb files , the [BIVIT]\_coeff\_r files and the [BIVIT]\_lmr files
- blocking (lmstartb(), lm2(), nthetabs(), sizethetab(), nfs(), lmstopb()): Module containing blocking information
- constants (zero(), vol\_ic(), vol\_oc(), one()): module containing constants and parameters used in the code.
- truncation: This module defines the grid points and the truncation
- precision\_mod: This module controls the precision used in MagIC
- output\_data (l\_max\_cmb(), n\_graphs(), n\_log\_file(), n\_graph\_file(), tag(), graph\_file(), log\_file()): This module contains the parameters for output control
- spectra(spectrum(), spectrum\_temp())
- legendre\_spec\_to\_grid(legtf())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- communications (get\_global\_sum(), gather\_from\_lo\_to\_rank0(), gather\_all\_from\_lo\_to\_rank0(), gt\_ic(), gt\_oc())

• logic(l\_chemical\_conv(), l\_mag(), l\_heat(), l\_save\_out(), l\_cond\_ic(), l\_conv()): Module containing the logicals that control the run

# **Variables**

- fields\_average\_mod/**z\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/**b\_ic\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/**db\_ave\_global** (:) [complex,private/allocatable]
- fields\_average\_mod/s\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/bicb(:) [complex,private/allocatable]
- fields\_average\_mod/**p\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/**b\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/w\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/w\_ave(:,:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ave (:,:) [complex,private/allocatable]
- fields\_average\_mod/**p\_ave\_global** (:) [complex,private/allocatable]
- fields\_average\_mod/**z\_ave\_global** (:) [complex,private/allocatable]
- fields\_average\_mod/b\_ave\_global (:) [complex,private/allocatable]
- fields\_average\_mod/**s\_ave** (:,:) [complex,private/allocatable]
- fields\_average\_mod/xi\_ave(:,:) [complex,private/allocatable]
- fields\_average\_mod/xi\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ave\_global(:) [complex,private/allocatable]
- fields\_average\_mod/aj\_ic\_ave (:,:) [complex,private/allocatable]
- fields\_average\_mod/dw\_ave\_global(:) [complex,private/allocatable]

### Subroutines and functions

This subroutine averages fields b and v over time.

– Input of variables:

- simtime [real,in]
- **dt** [real,in]

- dtnew [real,in]
- nave [integer,in] :: number for averaged time steps
- **l\_stop\_time** [logical,in] :: true if this is the last time step
- time\_passed [real,in] :: time passed since last log
- time norm [real,in]:: time passed since start of time loop
- omega ic [real,in]
- omega\_ma [real,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **xi** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,in*]
- **aj** (*ulmmag-(llmmag)*+1,*n\_r\_maxmag*) [*complex*,*in*]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]

### Called from output ()

```
Call to get_ddrns_even(), get_drns_even(), spectrum(), spectrum_temp(),
    get_e_kin(), get_e_mag(), graphout(), gather_from_lo_to_rank0(),
    legprep(), legtf(), fft_thetab(), gather_all_from_lo_to_rank0(),
    graphout_ic(), write_bcmb(), write_pot(), store()
```

# 10.17 IO: RMS force balance, torsional oscillations, misc

# 10.17.1 RMS. £90

# **Description**

This module contains the calculation of thr RMS force balance and induction terms.

### **Quick access**

Variables n\_dtbrms\_file, n\_dtvrms\_file, n\_cheb\_maxc, ncut, n\_r\_maxc, dtbrms\_file, dtvrms\_file, advrmsl\_sd, advrmsl\_ta, advrmssd, arcmagrmsl\_sd, arcmagrmsl\_ta, arcmagrmssd, arcrmsl\_sd, arcrmsl\_ta, arcrmssd, buormsl\_sd, buormsl\_ta, buormssd, ciarmsl\_sd, ciarmsl\_ta, ciarmssd, clfrmsl\_sd, clfrmsl\_ta, clfrmssd, corrmsl\_sd, corrmsl\_ta, corrmssd, difrmsl\_sd, difrmsl\_ta, difrmssd, dtvrmsl\_sd, dtvrmsl\_ta, dtvrmssd, geormsl\_sd, geormsl\_ta, geormssd, lfrmsl\_sd, lfrmsl\_ta, lfrmssd, magrmsl\_sd, magrmsl\_ta, magrmssd, plfrmsl\_sd, plfrmsl\_ta, plfrmssd, prermsl\_sd, prermsl\_ta, prermssd, rc, dr\_facc, adv2hint, arc2hint, arcmag2hint, buo2hint, cia2hint, clf2hint, cor2hint, difpollmr, dtbpollmr,

```
dtvpollmr, geo2hint, 1f2hint, mag2hint, plf2hint, pre2hint, difpol2hint, diftor2hint, dtbpol2hint, dtbtor2hint, dtvpol2hint, dtvtor2hint
```

### **Needed modules**

- chebyshev(type\_cheb\_odd())
- horizontal\_data (phi (), theta\_ord ()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- useful (getmsd2(), abortrun()): library with several useful subroutines
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_der (get\_dr()): Radial derivatives functions
- cosine\_transform\_odd
- radial\_scheme (type\_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- integration(rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- num\_param (alph1(), alph2(), tscale()): Module containing numerical and control parameters
- physical\_parameters(pr(), prmag(), radratio(), ra(), ek()): Module containing the physical parameters
- truncation (l\_max(), minc(), n\_phi\_max(), lm\_maxmag(), n\_r\_max\_dtb(), n\_r\_max(), fd\_stretch(), lm\_max\_dtb(), lm\_max(), n\_cheb\_max(), n\_r\_maxmag(), fd\_ratio(), n\_theta\_max()): This module defines the grid points and the truncation
- finite\_differences (type\_fd()): This module is used to calculate the radial grid when finite differences are requested
- precision\_mod: This module controls the precision used in MagIC
- rms\_helpers (hint2dpollm(), get\_poltorrms(), hint2dpol(), get\_ras(), get\_paslm()): This module contains several useful subroutines required to compute RMS diagnostics
- blocking (lm2(), nthetabs(), sizethetab(), lm2m(), nfs(), lo\_map(), st\_map()): Module containing blocking information
- constants (third(), one(), four(), zero(), half(), vol\_oc(), pi()): module containing constants and parameters used in the code.
- radial\_functions (r\_cmb(), r\_icb(), rscheme\_oc(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output\_data (tag(), rdea(), runid(), rcut()): This module contains the parameters for output control
- dtb\_mod (pdiflm\_lmloc(), tstrlm\_lmloc(), tdiflm\_lmloc(), pstrlm\_lmloc(), tadvlm\_lmloc(), tomelm\_lmloc(), padvlm\_lmloc()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....

- radial\_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- logic(l\_finite\_diff(), l\_newmap(), l\_corr(), l\_heat(), l\_mag\_lf(), l\_save\_out(), l\_mag(), l\_conv\_nl(), l\_conv()): Module containing the logicals that control the run

#### **Variables**

- rms/buormsl\_sd(:) [real,private/allocatable]
- rms/dtbpol2hint (:,:,:) [real,allocatable/public]
- rms/geo2hint (:,:) [real,allocatable/public]
- rms/dtvrmssd(:) [real,private/allocatable]
- rms/corrmsl\_ta(:) [real,private/allocatable]
- rms/dtvtor2hint (:,:,:) [real,allocatable/public]
- rms/advrmsl\_ta(:) [real,private/allocatable]
- rms/cia2hint (:,:) [real,allocatable/public]
- rms/plfrmsl\_sd(:) [real,private/allocatable]
- rms/ncut [integer,public]

  Number of points for the cut-off
- rms/arcmagrmsl\_sd(:) [real,private/allocatable]
- rms/advrmsl\_sd(:) [real,private/allocatable]
- rms/dtbpollmr(:,:) [complex,allocatable/public]
- rms/diftor2hint (:,:,:) [real,allocatable/public]
- rms/lfrmssd(:) [real,private/allocatable]
- rms/dtvrmsl\_sd(:) [real,private/allocatable]
- rms/prermssd(:) [real,private/allocatable]
- rms/lf2hint (:,:) [real,allocatable/public]
- rms/ciarmsl\_ta(:)[real,private/allocatable]
- rms/buormssd(:) [real,private/allocatable]
- rms/corrmssd(:) [real,private/allocatable]
- rms/plfrmsl\_ta(:) [real,private/allocatable]
- rms/magrmsl\_sd(:) [real,private/allocatable]
- rms/geormsl\_ta(:)[real,private/allocatable]
- rms/dtbrms\_file [character, private]
- rms/advrmssd(:) [real,private/allocatable]
- rms/dtvpollmr (:,:) [complex,allocatable/public]
- rms/n\_dtvrms\_file[integer,private]
- rms/plfrmssd(:) [real,private/allocatable]
- rms/dtvrmsl\_ta(:) [real,private/allocatable]

- rms/arc2hint (:,:) [real,allocatable/public]
- rms/clfrmssd(:) [real,private/allocatable]
- rms/dtbtor2hint (:,:,:) [real,allocatable/public]
- rms/buormsl\_ta(:) [real,private/allocatable]
- rms/arcmag2hint (:,:) [real,allocatable/public]
- rms/clfrmsl\_ta(:) [real,private/allocatable]
- rms/arcrmssd(:) [real,private/allocatable]
- rms/adv2hint (:,:) [real,allocatable/public]
- rms/clf2hint (:,:) [real,allocatable/public]
- rms/difpol2hint (:,:,:) [real,allocatable/public]
- rms/n\_cheb\_maxc [integer,public]
   Number of Chebyshevs
- rms/lfrmsl\_sd(:) [real,private/allocatable]
- rms/arcrmsl\_sd(:) [real,private/allocatable]
- rms/geormsl\_sd(:) [real,private/allocatable]
- rms/ciarmsl\_sd(:) [real,private/allocatable]
- rms/dr\_facc(:) [real,allocatable/public]
- rms/dtvpol2hint (:,:,:) [real,allocatable/public]
- rms/difrmssd(:) [real,private/allocatable]
- rms/n\_dtbrms\_file [integer,private]
- rms/clfrmsl\_sd(:) [real,private/allocatable]
- rms/prermsl\_ta(:)[real,private/allocatable]
- rms/ciarmssd(:) [real,private/allocatable]
- rms/rc(:) [real,private/allocatable]
- rms/buo2hint (:,:) [real,allocatable/public]
- rms/difrmsl\_ta(:)[real,private/allocatable]
- rms/difpollmr(:,:) [complex,allocatable/public]
- rms/prermsl\_sd(:) [real,private/allocatable]
- rms/arcmagrmsl\_ta(:) [real,private/allocatable]
- rms/lfrmsl\_ta(:) [real,private/allocatable]
- rms/arcmagrmssd(:) [real,private/allocatable]
- rms/cor2hint (:,:) [real,allocatable/public]
- rms/mag2hint (:,:) [real,allocatable/public]
- rms/arcrmsl\_ta(:) [real,private/allocatable]
- rms/plf2hint (:,:) [real,allocatable/public]
- rms/magrmsl\_ta(:)[real,private/allocatable]

- rms/pre2hint (:,:) [real,allocatable/public]
- rms/eps[real,private/parameter=10.0\_cp\*epsilon(one)]
- rms/magrmssd(:) [real,private/allocatable]
- rms/difrmsl\_sd(:) [real,private/allocatable]
- rms/geormssd(:) [real,private/allocatable]
- rms/dtvrms file [character, private]
- rms/n\_r\_maxc [integer,public]
  Number of radial points
- rms/corrmsl\_sd(:) [real,private/allocatable]

### **Subroutines and functions**

```
subroutine rms/initialize_rms()
    Memory allocation
    Called from magic
    Call to init_rnb()
subroutine rms/finalize_rms()
    Called from magic
subroutine rms/zerorms()
    Zeros integrals that are set in get_td, update_z, update_wp, update_b, dtVrms and dtBrms
- Local variables
    Called from output()
subroutine rms/init_rnb(r, rcut, rdea, r2, n_r_max2, n_cheb_max2, ns, rscheme_rms)
```

Prepares the usage of a cut back radial grid where nS points on both boundaries are discarded. The aim actually is to discard boundary effects, but just not considering the boundary grid points does not work when you also want radial derivatives and integrals. For these we use the Chebychev transform which needs are particular number of grid points so that the fast cosine transform can be applied. Therefor more than just 2 points have to be thrown away, which may make sense anyway.

- Input variables:

### **Parameters**

- **r** (*n*\_*r*\_*max*) [real,in]
- rcut [real,in]
- rdea [real,in]
- r2 (\*) [real,out,allocatable]
- n\_r\_max2 [integer,out]
- n\_cheb\_max2 [integer,out]
- **ns** [integer,out]
- rscheme rms [real]

Called from initialize rms()

```
Call to abortrun()
subroutine rms/dtvrms (time, nrms_sets, timepassed, timenorm)
          This routine calculates and stores the different contributions of the forces entering the Navier-Stokes
          equation.
     - Input variables:
          Parameters
                • time [real,in]
                • nrms_sets [integer,inout]
                • timepassed [real,in]
                • timenorm [real,in]
          Called from output ()
          Call to hint2dpol(), rint_r(), getmsd2()
subroutine rms/dtbrms(time)
     - Input of variables:
          Parameters time [real,in]
          Called from output ()
          Call to get poltorrms(), hint2dpollm(), rint r()
```

# 10.17.2 RMS\_helpers.f90

# **Description**

This module contains several useful subroutines required to compute RMS diagnostics

# **Quick access**

```
Routines get_ras(), hint2dpollm(), hint2dpol(), hintrms(), get_poltorrms(),
    hint2pollm(), hint2pol(), get_paslm(), hint2torlm(), hint2tor()
```

# **Needed modules**

- horizontal\_data(osn1(), plm(), dlh(), dplm()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod: This module contains the blocking information
- useful (cc2real ()): library with several useful subroutines
- integration(rint\_r()): Radial integration functions
- precision mod: This module controls the precision used in MagIC
- truncation(lm\_max(), l\_max(), n\_r\_max(), lm\_max\_dtb()): This module defines the grid points and the truncation
- lmmapping (mappings())

- blocking (1m2(), st\_map()): Module containing blocking information
- constants (vol\_oc(), one()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), r(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

#### Subroutines and functions

```
subroutine rms_helpers/get_paslm(tlm, bp, rt, nthetastart, sizethetablock)
```

Purpose of this subroutine is to calculated the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (l,m=0).

- Input variables:

### **Parameters**

- tlm (lm\_max\_dtb) [complex,in] :: field in (l,m)-space for rT
- **bp** (\*) [real,out]
- rt [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- sizethetablock [integer,in] :: size of theta block

calculates integral PolRms=sqrt( Integral (pol^2 dV) ) calculates integral TorRms=sqrt( Integral (tor^2 dV) ) plus axisymmetric parts. integration in theta,phi by summation of spherical harmonics integration in r by using Chebycheff integrals The mapping map gives the mapping lm to l,m for the input arrays Pol,drPol and Tor Output: PolRms,TorRms,PolAsRms,TorAsRms

– Input variables:

#### **Parameters**

- **pol** (*ulm-llm*+1,*n\_r\_max*) [*complex*,*in*]
- **drpol** (*ulm-llm*+1,*n\_r\_max*) [*complex*,*in*]
- **tor** (*ulm-llm*+1,*n\_r\_max*) [*complex*,*in*]
- **llm** [integer,in]
- **ulm** [integer,in] :: Toroidal field Potential
- polrms [real,out]
- **torrms** [real,out]
- polasrms [real,out]
- torasrms [real,out]
- map [mappings,in]

Called from dtbrms()

Call to cc2real(), rint\_r()

```
subroutine rms_helpers/hint2dpol(dpol, lmstart, lmstop, pol2hint, map)
     - Input variables:
          Parameters
                • dpol (lmstop-lmstart+1) [complex,in]
                • Imstart [integer,in]
                • Imstop [integer,in] :: Toroidal field Potential
                • pol2hint (l_max)+1) [real,inout]
                • map [mappings,in]
          Called from dtvrms()
          Call to cc2real()
subroutine rms_helpers/hint2dpollm(dpol, lmstart, lmstop, pol2hint, map)
     - Input variables
          Parameters
                • dpol (lmstop-lmstart+1) [complex,in]
                • Imstart [integer,in]
                • Imstop [integer,in]
                • pol2hint (lmstop-lmstart+1) [real,inout]
                • map [mappings,in]
          Called from dtbrms()
          Call to cc2real()
subroutine rms_helpers/hint2pol(pol, lb, ub, nr, lmstart, lmstop, pollmr, pol2hint, map)
     - Input variables:
          Parameters
                • pol (ub-lb+1) [complex,in]
                • lb [integer,in]
                • ub [integer,in] :: Poloidal field Potential
                • nr [integer,in]
                • Imstart [integer,in]
                • lmstop [integer,in]
                • pollmr (ub-lb+1) [complex,out]
                • pol2hint (l_max)+1) [real,inout]
                • map [mappings,in]
          Called from updatewpt(), updatewps(), updatewp()
          Call to cc2real()
subroutine rms_helpers/hint2pollm(pol, lb, ub, nr, lmstart, lmstop, pollmr, pol2hint, map)
     - Input variables:
          Parameters
```

```
• pol (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Poloidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • pollmr (ub-lb+1) [complex,out]
                 • pol2hint (ub-lb+1) [real,inout]
                 • map [mappings,in]
           Called from updateb()
           Call to cc2real()
subroutine rms_helpers/hintrms(f, nr, lmstart, lmstop, lmp, f2hint, map, sphertor)

    Input variables

           Parameters
                 • f (*) [complex,in]
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • lmp [integer,in]
                 • f2hint (l_max)+1) [real,inout]
                 • map [mappings,in]
                 • sphertor [logical,in]
           Called from get_td()
           Call to cc2real()
subroutine rms_helpers/hint2tor(tor, lb, ub, nr, lmstart, lmstop, tor2hint, map)
     - Input variables:
           Parameters
                 • tor (ub-lb+1) [complex,in]
                 • lb [integer,in]
                 • ub [integer,in] :: Toroidal field Potential
                 • nr [integer,in]
                 • Imstart [integer,in]
                 • lmstop [integer,in]
                 • tor2hint (l_max)+1) [real,inout]
                 • map [mappings,in]
           Called from updatez()
           Call to cc2real()
```

**subroutine** rms\_helpers/hint2torlm(tor, lb, ub, nr, lmstart, lmstop, tor2hint, map) - Input variables:

#### **Parameters**

- **tor** (ub-lb+1) [complex,in]
- **lb** [integer,in]
- **ub** [integer,in] :: Toroidal field Potential
- **nr** [integer,in]
- **Imstart** [integer,in]
- **Imstop** [integer,in]
- **tor2hint** (ub-lb+1) [real,inout]
- map [mappings,in]

Called from updateb()

Call to cc2real()

subroutine rms helpers/get ras(blm, br, rt, nthetastart, sizethetablock)

Purpose of this subroutine is to calculate the axisymmetric radial component Br of an axisymmetric ploidal field Blm given in spherical harmonic space (l,m=0).

- Input variables:

### **Parameters**

- **blm** (*lm\_max\_dtb*) [*complex,in*] :: field in (l,m)-space for rT
- **br** (\*) [real,out]
- **rt** [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- sizethetablock [integer,in] :: last theta

# 10.17.3 dtB.f90

### **Description**

This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output.

### **Quick access**

Variables r2lo\_dtb, padvlm, padvlmic, padvlmic\_lmloc, pdiflm, pdiflm\_lmloc, pdiflmic, pdiflmic\_lmloc, pstrlm, tadvlm, tadvlmic, tadvlmic\_lmloc, tdiflm, tdiflm\_lmloc, tdiflmic, tdiflmic\_lmloc, tomelm, tstrlm, padvlm\_rloc, pstrlm\_rloc, tadvlm\_rloc, tadvrlm\_rloc, tomelm\_rloc, tomerlm\_rloc, tstrlm\_rloc, tstrrlm\_rloc, padvlm\_lmloc, pstrlm\_lmloc, tadvlm\_lmloc, tadvrlm\_lmloc, tomelm\_lmloc, tomerlm\_lmloc, tstrrlm\_lmloc, tstrrlm\_lmloc, tstrrlm\_lmloc, tstrrlm\_lmloc, dtb\_lmloc\_container, dtb\_rloc\_container

```
Routines dtb_gather_lo_on_rank0(), dtb_from_rloc_to_lo(), initialize_dtb_mod(), finalize_dtb_mod(), get_dh_dtblm(), get_dtblm(), get_dtblmfinish()
```

#### **Needed modules**

- horizontal\_data (hdif\_b(), osn1(), osn2(), dlh(), cosn2(), d\_lp1(), dtheta1s(), dphi(), dtheta1a()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod: This module contains the blocking information
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- lmloop\_data(ulm(), llmmag(), llm(), ulmmag())
- radial\_spectra
- radial\_data (nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- communications (gather\_all\_from\_lo\_to\_rank0(), r2lo\_redist\_start(), create\_r2lm\_type(), destroy\_r2lm\_type(), gt\_oc(), gt\_ic(), r2lm\_type(), r2lo\_redist\_wait())
- legendre\_grid\_to\_spec(legtf2(), legtf3())
- logic(l\_dtbmovie(), l\_cond\_ic(), l\_dtrmagspec()): Module containing the logicals that control the run
- radial der (get dr ()): Radial derivatives functions
- physical\_parameters (opm(), o\_sr()): Module containing the physical parameters
- radial\_functions (rscheme\_oc(), orhol(), or2(), orl(), dllambda(), o\_r\_ic(), lambda()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (121mas(), 1m21mp(), 1m2m(), 1m21(), nfs(), 1mp21mps(), 1o\_map(), 1mp21mpa(), st map()): Module containing blocking information
- constants (two ()): module containing constants and parameters used in the code.
- truncation(n\_r\_ic\_max(), l\_max(), n\_r\_ic\_maxmag(), n\_r\_ic\_max\_dtb(), ldtbmem(), n\_phi\_max(), n\_r\_max\_dtb(), l\_axi(), n\_r\_max(), lm\_max\_dtb(), lm\_max(), nrp(), n\_cheb\_max(), n\_r\_maxmag()): This module defines the grid points and the truncation

### Variables

- dtb\_mod/tstrlm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/tadvlmic(:,:) [complex,allocatable/public]
- dtb\_mod/tomerlm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/pstrlm\_lmloc(:,:) [complex,pointer/public]

- dtb\_mod/tadvlmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tadvlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/padvlm(:,:) [complex,allocatable/public]
- dtb\_mod/padvlm\_lmloc(:,:) [complex,pointer/public]
- dtb mod/pdiflmic(:,:) [complex,allocatable/public]
- dtb mod/tstrlm(:,:) [complex,allocatable/public]
- dtb\_mod/tomelm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/dtb\_lmloc\_container(:,:,:) [complex,private/target/allocatable]
- dtb\_mod/tdiflm(:,:) [complex,allocatable/public]
- dtb\_mod/tadvrlm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/tdiflmic(:,:) [complex,allocatable/public]
- dtb\_mod/tadvlm(:,:) [complex,allocatable/public]
- dtb\_mod/tdiflm\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tadvlm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/tstrlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/tadvrlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/padvlmic(:,:) [complex,allocatable/public]
- dtb\_mod/dtb\_rloc\_container (:,:,:) [complex,private/target/allocatable]
- dtb\_mod/pdiflm\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tdiflmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/tstrrlm\_lmloc(:,:) [complex,pointer/public]
- dtb\_mod/pdiflmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/pstrlm(:,:) [complex,allocatable/public]
- dtb\_mod/pstrlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/tstrrlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/tomelm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/padvlmic\_lmloc(:,:) [complex,allocatable/public]
- dtb\_mod/r2lo\_dtb [r2lm\_type,private]
- dtb\_mod/tomerlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/**pdiflm**(:,:) [complex,allocatable/public]
- dtb\_mod/padvlm\_rloc(:,:) [complex,private/pointer]
- dtb\_mod/tomelm(:,:) [complex,allocatable/public]

# **Subroutines and functions**

```
subroutine dtb_mod/initialize_dtb_mod()
     Memory allocation
     The remaining global arrays should be suppressed, they are only needed because of some movie outputs
         Called from magic
         Call to create_r2lm_type()
subroutine dtb mod/finalize dtb mod()
         Called from magic
         Call to destroy r2lm type()
subroutine dtb_mod/dtb_from_rloc_to_lo()
         MPI transpose (from LM to R) for dtB calculations
     - Redistribute from r-distrubuted arrays to LM-distributed arrays
         Called from get_dtblmfinish()
         Call to r2lo_redist_start(), r2lo_redist_wait()
subroutine dtb_mod/dtb_gather_lo_on_rank0()
     MPI gather on rank0 for dtBmovie outputs. This routine should really be suppressed once the movie outputs
     have been improved
         Called from get dtblmfinish()
         Call to gather_all_from_lo_to_rank()()
subroutine dtb_mod/get_dtblm(nr, vr, vt, vp, br, bt, bp, n_theta_start, n_theta_block, btvrlm,
                                    bpvrlm, brvtlm, brvplm, btvplm, bpvtlm, brvzlm, btvzlm, btvpcotlm,
                                    bpvtcotlm, btvzcotlm, btvpsn2lm, bpvtsn2lm, btvzsn2lm)
```

This subroutine calculates non-linear products in grid-space for radial level n\_r and returns them in arrays wnlr1-3, snlr1-3, bnlr1-3

if Ivelo >0 velocities are zero only the (vxB) contributions to bnlr2-3 need to be calculated

vr...sr: (input) velocity, magnetic field comp. and derivs, entropy on grid points i1: (input) range of points in theta for which calculation is done

- Input variables:

- **nr** [integer,in]
- **vr** (*nrp*,*nfs*) [*real*,*in*]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [real,in]
- **bp** (*nrp*,*nfs*) [*real*,*in*]
- n\_theta\_start [integer,in]
- n\_theta\_block [integer,in]

- **btvrlm** (\*) [complex,out]
- **bpvrlm** (\*) [complex,out]
- **brvtlm** (\*) [complex,out]
- **brvplm** (\*) [complex,out]
- **btvplm** (\*) [complex,out]
- **bpvtlm** (\*) [complex,out]
- brvzlm (\*) [complex,out]
- **btvzlm** (\*) [complex,out]
- **btvpcotlm** (\*) [complex,out]
- **bpvtcotlm** (\*) [complex,out]
- btvzcotlm (\*) [complex,out]
- btvpsn2lm (\*) [complex,out]
- **bpvtsn2lm** (\*) [complex,out]
- btvzsn2lm (\*) [complex,out]

```
Call to fft_thetab(), legtf3(), legtf2()
```

**subroutine** dtb\_mod/**get\_dh\_dtblm** (*nr*, *btvrlm*, *bpvrlm*, *brvtlm*, *brvplm*, *btvplm*, *bpvtlm*, *bpvtsn2lm*) *zlm*, *btvpcotlm*, *bpvtcotlm*, *btvpsn2lm*)

Purpose of this routine is to calculate theta and phi derivative related terms of the magnetic production and advection terms and store them.

- Input variables:

### **Parameters**

- **nr** [integer,in]
- **btvrlm** (\*) [complex,in]
- **bpvrlm** (\*) [complex,in]
- **brvtlm** (\*) [complex,in]
- brvplm (\*) [complex,in]
- btvplm (\*) [complex,in]
- **bpvtlm** (\*) [complex,in]
- brvzlm (\*) [complex,in]
- btvzlm (\*) [complex,in]
- btvpcotlm (\*) [complex,in]
- **bpvtcotlm** (\*) [complex,in]
- btvpsn2lm (\*) [complex,in]
- **bpvtsn2lm** (\*) [complex,in]

### **Parameters**

- time [real,in]
- n\_time\_step [integer,in]
- omega\_ic [real,in]
- **b** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **ddb** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **dj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **ddj** (*ulmmag-*(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **db\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **ddb\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **aj\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- **dj\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **ddj\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- 1 frame [logical,in]

```
Called from output ()
```

```
Call to dtb_from_rloc_to_lo(),
    dtb_gather_lo_on_rank0()
rbrspec(),
    rbpspec(),
```

# 10.17.4 dtB arrays.f90

# **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- precision\_mod: This module controls the precision used in MagIC
- constants (zero ()): module containing constants and parameters used in the code.
- truncation (1mp\_max\_dtb()): This module defines the grid points and the truncation

# **Types**

• type dtb\_arrays\_mod/unknown\_type

# Type fields

- % bpvtsn2lm(\*)[complex,allocatable]
- % btvrlm(\*)[complex,allocatable]

```
- % brvzlm(*)[complex,allocatable]
```

- % btvzlm(\*)[complex,allocatable]
- % btvpcotlm(\*)[complex,allocatable]
- % btvpsn2lm(\*)[complex,allocatable]
- % btvzsn2lm(\*)[complex,allocatable]
- % bpvtcotlm(\*)[complex,allocatable]
- % bpvtlm(\*)[complex,allocatable]
- % brvplm(\*)[complex,allocatable]
- % bpvrlm(\*)[complex,allocatable]
- % btvzcotlm(\*)[complex,allocatable]
- % brvtlm (\*) [complex,allocatable]
- % btvplm(\*)[complex,allocatable]

# **Subroutines and functions**

```
Parameters this [real]

subroutine dtb_arrays_mod/finalize(this)

Parameters this [real]

subroutine dtb_arrays_mod/set_zero(this)

Parameters this [real]
```

# 10.17.5 out dtB frame.f90

# **Quick access**

```
Routines 1m2pt(), get_dtb(), write_dtb_frame(), get_bpol(), get_btor()
```

# **Needed modules**

- horizontal\_data(dplm(), osn1(), dlh(), d\_lp1(), dphi(), n\_theta\_cal2ord(), plm(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- movie\_data (n\_movie\_fields\_ic(), n\_movie\_field\_type(), n\_movie\_surface(), movie\_const(), n\_movie\_file(), n\_movie\_fields(), n\_movie\_const(), n\_movie\_type())
- fft: This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- dtb\_mod (pstrlm(), tdiflmic(), tadvlm(), tomelm(), tadvlmic(), tdiflm(), pdiflmic(), padvlm(), pdiflm(), padvlmic(), tstrlm()): This module contains magnetic field stretching and advection terms plus a separate omega-effect. It is used for movie output....
- precision\_mod: This module controls the precision used in MagIC

- radial\_der\_even(get\_drns\_even())
- logic(l\_cond\_ic()): Module containing the logicals that control the run
- radial\_der (get\_dr()): Radial derivatives functions
- truncation: This module defines the grid points and the truncation
- blocking (lm2(), nthetabs(), sizethetab(), lm2m(), lm2l(), nfs()): Module containing blocking information
- constants (zero(), ci(), one()): module containing constants and parameters used in the code.
- radial\_functions (rscheme\_oc(), dr\_fac\_ic(), or1(), r\_ic(), r(), chebt\_ic\_even(), r\_icb(), chebt\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

### Subroutines and functions

```
\verb|subroutine| | \texttt{out\_dtb\_frame} / \verb|write\_dtb\_frame| (n\_movie, b, db, aj, dj, b\_ic, db\_ic, aj\_ic, dj\_ic) | \\
```

Controls output of specific movie frames related to magnetic field production and diffusion.

- Input of variables:

### **Parameters**

- **n\_movie** [integer,in]
- **b** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **db** (*lm\_maxmag*,*n\_r\_maxmag*) [*complex*,*in*]
- **aj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **dj** (lm\_maxmag,n\_r\_maxmag) [complex,in]
- **b\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **db\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- aj\_ic (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]
- **dj\_ic** (lm\_maxmag,n\_r\_ic\_maxmag) [complex,in]

Called from write\_movie\_frame()

```
Call to get_dtb(), get_bpol(), get_btor(), lm2pt(), get_drns_even()
```

- Input variables:

- **dtb** (\*) [real,out]
- **dtblm** (dimb1,dimb2) [complex,in]
- dimb1 [integer,in,]
- dimb2 [integer,in,]
- **n\_r** [integer,in] :: No. of radial grid point

- **n\_theta\_start** [integer,in] :: No. of theta to start with
- n\_theta\_block [integer,in] :: Size of theta block
- **l\_ic** [logical,in] :: =true if inner core field

Called from write\_dtb\_frame()

subroutine out\_dtb\_frame/get\_bpol (pollm, dpollm, br, bt, bp, rt, n\_theta\_start, n\_theta\_block,
lic)

Purpose of this subroutine is to calculate the components Br, Bt, and Bp of the poloidal magnetic field PolLM (l,m space) at the radial grid point r=rT and the block of theta grid points from n\_theta=n\_theta\_start to n\_theta=n\_theta\_start+n\_theta\_block-1 and for all phis. For IIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core PolLM has to be the poloidal field at the ICB.

# - Input variables

#### **Parameters**

- pollm (lm\_max) [complex,in] :: field in (l,m)-space for rT
- **dpollm** (*lm\_max*) [*complex,in*] :: dr field in (l,m)-space for rT
- **br** (*nrp*,\*) [*real*, *out*]
- **bt** (*nrp*,\*) [*real*,*out*]
- **bp** (*nrp*,\*) [*real*,*out*]
- rt [real,in] :: radius
- n\_theta\_start [integer,in] :: first theta to be treated
- n\_theta\_block [integer,in] :: last theta
- lic [logical,in] :: true for inner core, special rDep!

Called from write\_dtb\_frame()

Call to fft thetab()

**subroutine** out\_dtb\_frame/**get\_btor**(*tlm*, *bt*, *bp*, *rt*, *n\_theta\_start*, *n\_theta\_block*, *lic*)

Purpose of this subroutine is to calculate the components Bt and Bp of the toroidal magnetic field Tlm (in l,m space) at the radial grid point r=rT and the block of theta grid points from n\_theta=n\_theta\_start to n\_theta=n\_theta\_start+n\_theta\_block-1 and for all phis. For IIC=.true. the inner core field is calculated, to get the IC field for a conducting inner core Plm has to be the toroidal field at the ICB.

# - Input variables:

- tlm (lm\_max) [complex,in] :: field in (l,m)-space for rT
- **bt** (*nrp*,\*) [*real*,*out*]
- **bp** (*nrp*,\*) [real,out]
- **rt** [real,in] :: radius
- n\_theta\_start [integer,in] :: first theta to be treated
- n\_theta\_block [integer,in] :: last theta
- lic [logical,in] :: true for inner core, special rDep!

```
Called from write_dtb_frame()
Call to fft_thetab()
```

subroutine out\_dtb\_frame/lm2pt (alm, aij, rt, nthetastart, lic, lrcomp)

Spherical harmonic transform from alm(l,m) to aij(phi,theta) Radial field components are calculated for lrComp=.true. Done within the range [n\_theta\_min,n\_theta\_min+n\_theta\_block-1] Used only for graphic output.

- Input variables:

#### **Parameters**

- alm (\*) [complex,in] :: field in (l,m)-space
- aij (nrp,\*) [real,out] :: field in (theta,phi)-space
- **rt** [real,in]
- **nthetastart** [integer,in] :: first theta to be treated
- **lic** [logical,in] :: true for inner core, extra factor!
- **lrcomp** [logical,in] :: true for radial field components

```
Called from write_dtb_frame()
Call to fft_thetab()
```

# 10.17.6 TO. £90

# **Description**

This module contains information for TO calculation and output

### **Quick access**

```
Variables bpsdas_rloc, bpzas_rloc, bpzdas_rloc, bs2as_rloc, bspas_rloc, bspdas_rloc, bszas_rloc, bzpdas_rloc, ddzasl, dzastrlmr, dzastrlmr_rloc, dzcorlmr, dzcorlmr_rloc, dzddvplmr, dzddvplmr_rloc, dzdvplmr, dzdvplmr_rloc, dzlflmr, dzlflmr_rloc, dzrstrlmr, dzrstrlmr_rloc, dzstrlmr, dzstrlmr_rloc, v2as_rloc
```

Routines initialize\_to(), finalize\_to(), gettofinish(), getto(), gettonext()

# **Needed modules**

- horizontal\_data(dthetala(), dlh(), hdif\_v(), dthetals(), sintheta(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- !mloop\_data(llmmag(), ulmmag())
- radial\_data (n\_r\_cmb(), nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.

- precision\_mod: This module controls the precision used in MagIC
- legendre\_grid\_to\_spec(legtfas2())
- logic(l\_mag(), lverbose()): Module containing the logicals that control the run
- physical\_parameters (kbotv(), ktopv(), corfac()): Module containing the physical parameters
- truncation (n\_r\_maxstr(), l\_max(), nrp(), n\_phi\_maxstr(), n\_theta\_maxstr()): This module defines the grid points and the truncation
- blocking (1m2(), nfs()): Module containing blocking information
- constants (two (), one ()): module containing constants and parameters used in the code.
- radial\_functions (orho1(), or4(), or2(), or3(), or1(), beta(), r(), dbeta()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

- torsional\_oscillations/dzlflmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzddvplmr(:,:) [real,allocatable/public]
- torsional\_oscillations/dzastrlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzlflmr(:,:) [real,allocatable/public]
- torsional\_oscillations/dzrstrlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/v2as\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzcorlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/dzdvplmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bs2as\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzrstrlmr(:,:) [real, allocatable/public]
- torsional\_oscillations/ddzasl(:,:) [real,allocatable/public]
- torsional\_oscillations/bspas\_rloc(:,:) [real, allocatable/public]
- torsional\_oscillations/**bspdas\_rloc**(:,:) [real,allocatable/public]
- torsional\_oscillations/dzdvplmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzstrlmr(:,:) [real,allocatable/public]
- torsional oscillations/bpzas rloc(:,:) [real, allocatable/public]
- torsional\_oscillations/dzstrlmr\_rloc(:,:) [real, allocatable/public]
- torsional\_oscillations/dzcorlmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bzpdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bpsdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzddvplmr\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/bpzdas\_rloc(:,:) [real,allocatable/public]
- torsional\_oscillations/dzastrlmr(:,:) [real,allocatable/public]
- torsional\_oscillations/bszas\_rloc(:,:) [real,allocatable/public]

# **Subroutines and functions**

This program calculates various axisymmetric linear and nonlinear variables for a radial grid point nR and a theta-block. Input are the fields vr,vt,vp,cvr,dvpdr Output are linear azimuthally averaged field VpAS (flow phi component), VpAS2 (square of flow phi component), V2AS (V\*V), and Coriolis force Cor. These are give in (r,theta)-space. Also in (r,theta)-space are azimuthally averaged correlations of non-axisymmetric flow components and the respective squares: Vsp=Vs\*Vp,Vzp,Vsz,VspC,VzpC,VzsC. These are used to calulcate the respective correlations and Reynolds stress. In addition three output field are given in (lm,r) space: dzRstrLMr,dzAstrLMr,dzCorLM,dzLFLM.

These are used to calculate the total Reynolds stress, advection and viscous stress later. Their calculation retraces the calculations done in the time-stepping part of the code.

### - Input of variables

- **vr** (*nrp*,*nfs*) [*real*,*in*]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- cvr (nrp,nfs) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (nrp,nfs) [real,in]
- **bp** (*nrp*,*nfs*) [real,in]
- **cbr** (*nrp*,*nfs*) [real,in]
- **cbt** (*nrp*,*nfs*) [real,in]
- **bslast** (n\_phi\_maxstr,n\_theta\_maxstr,nrstop-(nrstart)+1) [real,in]
- **bplast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,in]
- **bzlast** (n\_phi\_maxstr,n\_theta\_maxstr,nrstop-(nrstart)+1) [real,in]
- **dzrstrlm** (*l max*+2) [real,out]
- **dzastrlm** (*l\_max*+2) [real,out]
- dzcorlm (l max+2) [real,out]
- **dzlflm** (*l\_max*+2) [real,out]
- **dtlast** [real,in] :: last time step

```
• nr [integer,in] :: radial grid point
```

- **nthetastart** [integer,in] :: theta block
- nthetablocksize [integer,in]

Called from do\_iteration\_thetablocking\_openmp(), do\_iteration\_thetablocking\_seq(),
 do\_iteration\_thetablocking\_shtns()

Call to legtfas2()

Preparing TO calculation by storing flow and magnetic field contribution to build time derivative.

- Input of variables:

#### **Parameters**

- **zas** (*l\_max*+1) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [real,in]
- **bp** (*nrp*,*nfs*) [real,in]
- **ltonext** [logical,in]
- ltonext2 [logical,in]
- dt [real,in]
- dtlast [real,in]
- **nr** [integer,in]
- nthetastart [integer,in]
- **nthetablocksize** [integer,in]
- **bslast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]
- **bplast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]
- **bzlast** (*n\_phi\_maxstr*,*n\_theta\_maxstr*,*nrstop-*(*nrstart*)+1) [real,out]

Called from do\_iteration\_thetablocking\_openmp(), do\_iteration\_thetablocking\_seq(),
 do iteration thetablocking shtns()

> This program was previously part of getTO(...) It has now been separated to get it out of the thetablock loop.

- Input of variables:

- **nr** [integer,in]
- dtlast [real,in]
- **zas** (*l\_max*+1) [real,in]
- **dzas** (*l max*+1) [real,in]

```
• ddzas (l_max+1) [real,in]
```

- dzrstrlm (l\_max+2) [real,in]
- **dzastrlm** (*l\_max*+2) [real,in]
- **dzcorlm** (*l\_max*+2) [*real,in*]
- **dzlflm** (*l* max+2) [real,in]

# 10.17.7 TO\_helpers.f90

# **Description**

This module contains several helpful subroutines used in the TO calculations

#### **Quick access**

```
Routines getpastr(), getastr(), get_pas()
```

### **Needed modules**

- precision mod: This module controls the precision used in MagIC
- horizontal\_data(dplm(), osn1()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- blocking (1m2()): Module containing blocking information
- constants (half(), two(), one()): module containing constants and parameters used in the code.
- truncation (1\_max()): This module defines the grid points and the truncation

#### **Variables**

### Subroutines and functions

Calculates axisymmetric phi component for a given toroidal potential flmn in spherical harmonic/Cheb space. This is calculated at radii rZ(nZmax) and matching colatitutes theta(nZmax) for which dPlm(theta) and OsinTS(theta) are provided for the south hemisphere. Points in the northern hemipshere use Plm symmetries.

- Input variables:

- **fz** (\*) [real,out]
- **flmn** (lmax + 1,\*) [real,in]
- nzmax [integer,in]

- nzmaxa [integer,in,]
- lmax [integer,in,]
- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- rz (0.5 \* nzmaxa + 1.0) [real, in]
- **dplm** (lmax + 1,0.5 \* nzmaxa + 1.0) [real,in]
- **osints** (0.5 \* *nzmaxa* + 1.0) [*real,in*]

Called from outto(), outpv()

subroutine to\_helpers/get\_pas(tlm, bp, rt, nthetastart, sizethetablock)

Purpose of this subroutine is to calculate the axisymmetric phi component Bp of an axisymmetric toroidal field Tlm given in spherical harmonic space (1,m=0).

- Input variables

### **Parameters**

- tlm (\*) [real,in] :: field in (l,m)-space for rT
- **bp** (\*) [real,out]
- rt [real,in] :: radius
- **nthetastart** [integer,in] :: first theta to be treated
- **sizethetablock** [integer,in] :: size of theta block

Called from outto()

subroutine to\_helpers/getastr(fz,flmn, nzmax, nzmaxa, lmax, rmin, rmax, nchebmax, rz, plm)

Calculates function value at radii rZ(nZmax) and colatitudes for which Plm(theta) is given from the spherical harmonic/Chebychev coefficients of an axisymmetric function (order=0).

- Input variables:

# **Parameters**

- **fz** (\*) [real,out]
- flmn (lmax + 1,\*) [real,in]
- nzmax [integer,in]
- nzmaxa [integer,in,]
- lmax [integer,in,]
- rmin [real,in]
- rmax [real,in]
- nchebmax [integer,in]
- **rz** (0.5 \* *nzmaxa* + 1.0) [*real,in*]
- **plm** (lmax + 1,0.5 \* nzmaxa + 1.0) [real,in]

Called from outto()

## 10.17.8 TO\_arrays.f90

### **Needed modules**

- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- precision\_mod: This module controls the precision used in MagIC
- truncation (1\_max()): This module defines the grid points and the truncation

### **Types**

```
• type to_arrays_mod/unknown_type
```

### Type fields

- % dzcorlm(\*)[real,allocatable]
- % dzlflm(\*)[real,allocatable]
- % dzrstrlm(\*)[real,allocatable]
- % dzastrlm(\*)[real,allocatable]

### **Subroutines and functions**

**Parameters this** [real]

10.17.9 out TO.f90

### **Quick access**

Variables ns\_on\_last\_rank, ns\_per\_rank, nsmax, nsstart, nsstop, ntozfile, nzmaxa, movfile, tofilenhs, tofileshs, tayfile, timeave, timelast, nzmaxs, nzmaxs\_sloc, chebt\_z, bpsdlmr, bpsdlmr\_rloc, bpzdlmr, bpzdlmr\_rloc, bsplmr, bpzlmr\_rloc, bs2lmr, bs2lmr\_rloc, bspdlmr, bspdlmr\_rloc, bsplmr, bsplmr\_rloc, bszlmr, bszlmr\_rloc, bzpdlmr, bzpdlmr\_rloc, dzvplmr, dzvplmr\_loc, osints, rz, v2lmr, v2lmr\_rloc, zz, zz\_sloc, astrm, astrm\_sloc, clm, clm\_sloc, corm, corm\_sloc, dvpm, dvpm\_sloc, lfm, lfm\_sloc, rstrm, rstrm\_sloc, strm, strm\_sloc, vpm, vpm\_sloc, dplms, plms

### **Needed modules**

- horizontal\_data (phi(), gauss(), theta\_ord(), sintheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- chebint\_mod(chebint(), chebintinit())
- useful (abortrun (), logwrite ()): library with several useful subroutines
- lmloop\_data(llm(), ulm())
- to\_helpers(getpastr(), get\_pas(), getastr()): This module contains several helpful subroutines used in the TO calculations
- legendre\_grid\_to\_spec(legtfas2(), legtfas())
- cosine transform odd
- integration (rint\_r()): Radial integration functions
- parallel\_mod: This module contains the blocking information
- num\_param(tscale()): Module containing numerical and control parameters
- physical\_parameters(pr(), prmag(), lffac(), ek(), radratio(), ra()): Module containing the physical parameters
- radial\_functions (r\_icb(), r\_cmb(), rscheme\_oc(), r(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- precision\_mod: This module controls the precision used in MagIC
- plms\_theta(plm\_theta())
- blocking (lo\_map(), nthetabs(), nfs(), sizethetab()): Module containing blocking information
- constants (two(), one(), four(), half(), vol\_oc(), pi()): module containing constants and parameters used in the code.
- truncation (l\_max(), n\_r\_maxstr(), minc(), n\_phi\_max(), lstressmem(), n\_r\_max(), n\_theta\_maxstr(), lm\_max(), n\_theta\_max()): This module defines the grid points and the truncation
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- output\_data(n\_log\_file(), zdens(), tag(), runid(), log\_file(), sdens()): This module contains the parameters for output control
- torsional\_oscillations (dzastrlmr(), dzastrlmr\_rloc(), dzrstrlmr(), v2as\_rloc(), dzdvplmr(), bspdas\_rloc(), bpzas\_rloc(), dzstrlmr\_rloc(), dzcorlmr\_rloc(), dzlflmr\_rloc(), dzddvplmr\_rloc(), bzpdas\_rloc(), dzddvplmr(), dzlflmr(), dzcorlmr(), bs2as\_rloc(), dzrstrlmr\_rloc(), bspas\_rloc(), dzdvplmr\_rloc(), dzstrlmr(), bpsdas\_rloc(), bpzdas\_rloc(), bszas\_rloc(): This module contains information for TO calculation and output
- radial\_data (nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- logic (l\_save\_out (), lverbose ()): Module containing the logicals that control the run

### **Variables**

- outto\_mod/dzvplmr\_loc(:,:) [real,private/allocatable]
- outto\_mod/rstrm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/tayfile [character,private]
- outto\_mod/chebt\_z (:) [costf\_odd\_t,private/allocatable]
- outto\_mod/lfm(:,:) [real,private/allocatable]
- outto\_mod/nzmaxa [integer,private]
- outto\_mod/bpzlmr (:,:) [real,private/allocatable]
- outto\_mod/osints(:,:) [real,private/allocatable]
- outto\_mod/nzmaxs\_sloc(:) [integer,private/allocatable]
- outto\_mod/ns\_on\_last\_rank [integer,private]
- outto\_mod/astrm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/bsplmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/ns\_per\_rank [integer,private]
- outto\_mod/zz(:,:) [real,private/allocatable]
- outto\_mod/bpsdlmr (:,:) [real,private/allocatable]
- outto\_mod/nzmaxs (:) [integer,private/allocatable]
- outto\_mod/v2lmr(:,:) [real,private/allocatable]
- outto\_mod/v21mr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/clm(:,:) [real,private/allocatable]
- outto\_mod/clm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/timelast [real,private] ,tNorm
- outto\_mod/nsstop [integer,private]
- outto\_mod/bpzdlmr (:,:) [real,private/allocatable]
- outto\_mod/bspdlmr (:,:) [real,private/allocatable]
- outto\_mod/rz(:,:) [real,private/allocatable]
- outto\_mod/bszlmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/lfm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/**timeave** [real,private]
- outto\_mod/**dplms** (:,:,:) [real,private/allocatable]
- outto\_mod/plms (:,:,:) [real,private/allocatable]
- outto\_mod/bsplmr(:,:) [real,private/allocatable]
- outto\_mod/zz\_sloc(:,:) [real,private/allocatable]
- outto\_mod/rstrm(:,:) [real,private/allocatable]
- outto\_mod/movfile [character,private]

- outto\_mod/corm(:,:) [real,private/allocatable]
- outto\_mod/dzvplmr (:,:) [real,private/allocatable]
- outto\_mod/bs21mr (:,:) [real,private/allocatable]
- outto\_mod/astrm(:,:) [real,private/allocatable]
- outto\_mod/strm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/bpzdlmr\_rloc (:,:) [real,private/allocatable]
- outto\_mod/bspdlmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/vpm(:,:) [real,private/allocatable]
- outto\_mod/nsmax [integer,private]
- outto\_mod/bs2lmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/dvpm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/corm\_sloc(:,:) [real,private/allocatable]
- outto\_mod/ntozfile [integer,private]
- outto\_mod/bzpdlmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/**vpm\_sloc** (:,:) [real,private/allocatable]
- outto\_mod/bzpdlmr (:,:) [real,private/allocatable]
- outto\_mod/bpzlmr\_rloc(:,:) [real,private/allocatable]
- outto\_mod/tofilenhs [character,private]
- outto\_mod/dvpm (:,:) [real,private/allocatable]
- outto\_mod/strm(:,:) [real,private/allocatable]
- outto\_mod/bszlmr (:,:) [real,private/allocatable]
- outto\_mod/nsstart [integer,private]
- outto\_mod/tofileshs[character,private]
- outto\_mod/bpsdlmr\_rloc(:,:) [real,private/allocatable]

### **Subroutines and functions**

**subroutine** outto\_mod/outto (time, n\_time\_step, ekin, ekintas, ntosets, ntomovsets, ntormssets, lto-mov, ltorms, ltozwrite, z, omega\_ic, omega\_ma)

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repetitious calculation of plms by subroutine plm\_theta. They are needed in getAStr and getPAStr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use!

- Input of variables:

### **Parameters**

```
• time [real,in]
```

- n\_time\_step [integer,in]
- ekin [real,in]
- ekintas [real,in]
- **ntosets** [integer,inout]
- ntomovsets [integer,inout]
- **ntormssets** [integer,inout]
- **Itomov** [logical,in]
- **Itorms** [logical,inout]
- **ltozwrite** [logical,inout]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- omega\_ic [real,in]
- omega\_ma [real,in]

### Called from output ()

```
Call to legtfas(), legtfas2(), outto_allgather_rloc(), chebintinit(),
    plm_theta(), getpastr(), getastr(), chebint(), abortrun(), logwrite(),
    get_pas(), rint_r()
```

### subroutine outto\_mod/outto\_allgather\_rloc()

MPI communicators for TO outputs

- Local variables:

Called from outto()

### 10.17.10 radial\_spectra.f90

#### Quick access

```
Variables filehandle
```

Routines rbrspec(), rbpspec()

### **Needed modules**

- horizontal\_data(dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod: This module contains the blocking information
- useful (cc2real ()): library with several useful subroutines
- output\_data(tag()): This module contains the parameters for output control
- logic(l\_cond\_ic()): Module containing the logicals that control the run
- lmloop\_data(llm(), ulm())

- radial\_data (n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- num\_param (escale()): Module containing numerical and control parameters
- truncation(lm\_max(), n\_r\_ic\_max(), l\_max(), n\_r\_tot(), n\_r\_max()): This module defines the grid points and the truncation
- *lmmapping* (mappings())
- blocking (st\_map()): Module containing blocking information
- constants (four(), half(), pi(), one()): module containing constants and parameters used in the code.
- radial\_functions (r\_icb(), r\_ic(), or2()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

#### **Variables**

• radial\_spectra/filehandle [integer,private]

### **Subroutines and functions**

### **Parameters**

- time [real,in]
- **pol** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **polic** (*ulm*-(*llm*)+1,*n\_r\_ic\_max*) [*complex*,*in*]
- **fileroot** [character,in]
- **lic** [logical,in]
- map [mappings,in]

```
\textbf{Called from} \ \textit{get\_dtblmfinish(),output()}
```

Call to cc2real()

**subroutine** radial spectra/**rbpspec** (time, tor, toric, fileroot, lic, map)

Called from rank0, map gives the lm order of Tor and TorIC

- Input variables:

- time [real,in]
- tor  $(ulm-(llm)+1,n_r_max)$  [complex,in]
- **toric** (*ulm*-(*llm*)+1,*n*\_*r*\_*ic*\_*max*) [*complex*,*in*]
- fileroot [character,in]
- lic [logical,in]
- map [mappings,in]

```
Called from get_dtblmfinish(), output()
Call to cc2real()
```

### 10.17.11 outGeos.f90

### **Description**

This module is used to calculate the outputs when either l\_par or l\_PV are set to .true.

### **Quick access**

```
Variables n_geos_file, geos_file, timeold, nzc, nzc_sloc, nz2, eps, ddws_global,
    dws_global, dzs_global, osintspv, rzpv, ws_global, zs_global, dplmspv,
    dplmz, plmspv, plmz, vorold
Routines initialize_geos_mod(), finalize_geos_mod(), outpv(), getegeos(),
    costf_arrays(), getdvptr()
```

### **Needed modules**

- horizontal\_data(dphi(), phi(), dlh()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- parallel\_mod: This module contains the blocking information
- cosine\_transform\_odd(costf\_odd\_t())
- fft (fft\_to\_real()): This file contains the subroutines called by fftJW: fft99a, fft99b, wpass2, wpass3, wpass4 and wpass5
- mem\_alloc (bytes\_allocated()): This little module is used to estimate the global memory allocation used in MagIC
- chebint\_mod
- output\_data(zdens(), tag(), runid(), sdens()): This module contains the parameters for output control
- logic (l\_corrmov(), l\_sric(), l\_save\_out(), lverbose(), l\_anel()): Module containing the logicals that control the run
- lmloop\_data(llm(), ulm())
- to helpers (getpastr()): This module contains several helpful subroutines used in the TO calculations
- precision\_mod: This module controls the precision used in MagIC
- communications (gather\_all\_from\_lo\_to\_rank0(), gt\_oc())
- plms\_theta(plm\_theta())
- num param(tscale()): Module containing numerical and control parameters
- physical\_parameters(pr(), prmag(), radratio(), ra(), ek()): Module containing the physical parameters
- truncation (l\_max(), minc(), n\_phi\_max(), l\_axi(), n\_r\_max(), n\_m\_max(), m\_max(), lm\_max(), nrp()): This module defines the grid points and the truncation

- blocking (st\_map(), lm2m(), lm2l(), lm2mc(), lo\_map()): Module containing blocking information
- constants (ci(), two(), one(), zero(), half(), pi()): module containing constants and parameters used in the code.
- radial\_functions (r\_icb(), r\_cmb(), rscheme\_oc(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

- geos\_mod/chebt\_z (:) [costf\_odd\_t,private/allocatable]
- geos\_mod/nzmaxa [integer,private]
- geos\_mod/ws\_global(:,:) [complex,private/allocatable]
- geos\_mod/osintspv(:,:) [real,private/allocatable]
- geos\_mod/zz(:,:) [real,private/allocatable]
- geos\_mod/ns\_per\_rank [integer,private]
- geos\_mod/nzmaxs (:) [integer,private/allocatable]
- geos\_mod/nz2 (:,:) [integer,private/allocatable]
- geos\_mod/nsstop[integer,private]
- geos mod/nzc sloc(:) [integer,private/allocatable]
- geos\_mod/rzpv(:,:) [real,private/allocatable]
- geos\_mod/dplmz (:,:,:) [real,private/allocatable]
- geos\_mod/dzs\_global (:,:) [complex,private/allocatable]
- geos\_mod/plmz (:,:,:) [real,private/allocatable]
- geos\_mod/**dplms** (:,:,:) [real,private/allocatable]
- geos\_mod/plms (:,:,:) [real,private/allocatable]
- geos\_mod/**dplmspv** (:,:,:) [real,private/allocatable]
- geos\_mod/n\_geos\_file [integer,private]
- geos\_mod/timeold[real,private]
- geos mod/**nsstart** [integer,private]
- geos\_mod/ddws\_global (:,:) [complex,private/allocatable]
- geos\_mod/ns\_on\_last\_rank [integer,private]
- geos\_mod/nsmax [integer,private]
- geos\_mod/osints(:,:) [real,private/allocatable]
- geos\_mod/zs\_global(:,:) [complex,private/allocatable]
- geos\_mod/**eps** [real,private/parameter=10.0\_cp\*epsilon(one)]
- geos\_mod/nzc(:)[integer,private/allocatable]
- geos\_mod/geos\_file [character,private]
- geos mod/vorold(:,:,:) [real,private/allocatable]

- geos\_mod/plmspv (:,:,:) [real,private/allocatable]
- geos\_mod/dws\_global(:,:) [complex,private/allocatable]
- geos\_mod/rz(:,:) [real,private/allocatable]

### **Subroutines and functions**

```
subroutine geos_mod/initialize_geos_mod(l_geos, l_pv)
```

Memory allocation in Egeos

### **Parameters**

- l\_geos [logical,in]
- l\_pv [logical,in]

Called from magic

```
subroutine geos_mod/finalize_geos_mod(l_geos, l_pv)
```

Memory deallocation

### **Parameters**

- l\_geos [logical,in]
- l\_pv [logical,in]

Called from magic

```
subroutine geos_mod/getegeos(time, ngeossets, w, dw, ddw, z, dz, geos, dpflow, dzflow)
```

Output of axisymmetric zonal flow, its relative strength, its time variation, and all forces acting on it. The slowest part in the TO process is the repitions calculation of Plms by subroutine plm\_theta. They are needed in getDVptr when I transform on the cylindrical grid. The necessary plms could simply be calculated one and then be stored for later use! See s\_outTOnew.f.

- Input of variables:

### **Parameters**

- time [real,in]
- **ngeossets** [integer,in]
- $\mathbf{w}$  (ulm-(llm)+1,n r max) [complex,in]
- **dw** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- dz (ulm-(llm)+1,n\_r\_max) [complex,in]
- **geos** [real,out] :: Degree of geostrophy
- **dpflow** [real,out] :: RMS lengths scale
- **dzflow** [real,out] :: RMS lengths scale

Called from output ()

**subroutine** geos\_mod/**outpv** (time, l\_stop\_time, npvsets, w, dw, ddw, z, dz, omega\_ic, omega\_ma)

Output of z-integrated axisymmetric rotation rate Vp/s and s derivatives

– Input of variables:

#### **Parameters**

- time [real,in]
- l\_stop\_time [logical,in]
- **npvsets** [integer,inout]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- $\mathbf{z}$  (ulm-(llm)+1,n r max) [complex,in]
- dz (ulm-(llm)+1,n r max) [complex,in]
- omega\_ic [real,in]
- omega\_ma [real,in]

Called from output ()

```
Call to costf_arrays(), plm_theta(), getpastr(), getdvptr()
```

This subroutine calculates the three flow components VrS,VtS,VpS at a (r,theta,all phis) and (t,pi=theta, all phis). Here r=rS, PlmS=Plm(theta), dPlmS=sin(theta)\*dTheta Plm(theta), and OsinTS=1/sin(theta). The flow is calculated for all n\_phi\_max azimuthal points used in the code, and for corresponding latitudes north and south of the equator. When kindCalc=1, the subroutine also calculates dpEk and dzEk which are phi averages of (d Vr/d phi)\*\*2 + (d Vtheta/d phi)\*\*2 + (d Vphi/d phi)\*\*2 and (d Vr/d z)\*\*2 + (d Vtheta/d z)\*\*2 + (d Vphi/d z)\*\*2, respectively.

**Note:** on input wS=w/r^2, dwS=dw/r, ddwS=ddw/r, zS=z/r

### - Input variables:

- $\mathbf{w}$  ( $lm \ max, n \ r \ max$ ) [complex, in]
- **dw** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **ddw** (*lm\_max*,*n\_r\_max*) [*complex*,*in*]
- **z** (lm\_max,n\_r\_max) [complex,in]
- dz (lm max, n r max) [complex, in]
- **rmin** [real,in] :: radial bounds
- rmax [real,in]
- **rs** (nzmaxa) [real,in]

```
• nzmax [integer,in] :: number of (r,theta) points
```

```
• nzmaxa [integer,in,]
```

- plms  $(lm_max, 0.5 * nzmaxa + 1.0)$  [real,in]
- **dplms** (*lm\_max*,0.5 \* *nzmaxa* + 1.0) [*real,in*]
- osints (0.5 \* nzmaxa + 1.0) [real,in]
- **kindcalc** [integer,in]
- vrs (nrp,nzmaxa) [real,out]
- vts (nrp,nzmaxa) [real,out]
- **vps** (*nrp*,*nzmaxa*) [real,out]
- **vors** (*nrp*,*nzmaxa*) [real,out]

Options dpek (nzmaxa) [real,out,optional]

Called from outpv(), getegeos()

Call to fft\_to\_real()

### subroutine geos\_mod/costf\_arrays (w, dw, ddw, z, dz)

This subroutine performs local copy of LM-distributed arrays, do a cosine transform and then all-gather them

- Input variables

#### **Parameters**

- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **ddw** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [complex,in]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dz** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]

Called from outpv(), getegeos()

Call to gather\_all\_from\_lo\_to\_rank0()

### 10.17.12 chebInt.f90

### **Quick access**

**Routines** chebintinit(), chebintd(), chebint()

### **Needed modules**

- parallel\_mod: This module contains the blocking information
- cosine\_transform\_odd
- useful (abortrun()): library with several useful subroutines
- precision\_mod: This module controls the precision used in MagIC

- radial\_der (get\_dcheb ()): Radial derivatives functions
- chebyshev\_polynoms\_mod(cheb\_grid())
- constants (four (), two (), half ()): module containing constants and parameters used in the code.

#### **Variables**

#### Subroutines and functions

### **Parameters**

- **zmin** [real,in] :: integration interval!
- **zmax** [real,in]
- **znorm** [real,in] :: norm interval length
- nnorm [integer,in] :: suggested number of grid points for norm length
- ngridpointsmax [integer,in] :: dimension of z on input
- **z** (ngridpointsmax) [real,out] :: grid points, dimension at >= nGridPointsMax
- ngridpoints [integer,out] :: number of used grid points
- chebt [costf\_odd\_t,out]

```
Called from outto(), getegeos()
Call to abortrun(), cheb_grid()
```

**function** chebint\_mod/**chebint** (*f*, *zmin*, *zmax*, *ngridpoints*, *ngridpointsmax*, *chebt*) – Input variables:

### **Parameters**

- **f** (ngridpointsmax) [real,in] :: function on grid points
- **zmin** [real,in] :: integration boundaries
- **zmax** [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- ngridpointsmax [integer,in,] :: No of max grid points
- **chebt** [costf\_odd\_t,in]

### Return chebint [real]

```
Called from outto(), getegeos()
```

**function** chebint\_mod/**chebintd**(*f*, *lderiv*, *zmin*, *zmax*, *ngridpoints*, *ngridpointsmax*, *chebt*) – Input variables:

- **f** (ngridpointsmax) [real,inout] :: function on grid points
- **Ideriv** [logical,in]
- **zmin** [real,in] :: integration boundaries

- zmax [real,in]
- **ngridpoints** [integer,in] :: No of grid points
- ngridpointsmax [integer,in,] :: No of max grid points
- **chebt** [costf\_odd\_t,in]

**Return chebintd** [real]

Called from getegeos ()

### 10.17.13 outOmega.f90

### **Description**

This module allows to compute the axisymmetric zonal flow versus the cylindrical radius s. By

#### **Quick access**

```
Routines outomega(), lnpas2tr()
```

### **Needed modules**

- parallel\_mod: This module contains the blocking information
- cosine transform odd
- useful (abortrun()): library with several useful subroutines
- output\_data(tag()): This module contains the parameters for output control
- lmloop\_data(llm(), ulm())
- precision\_mod: This module controls the precision used in MagIC
- plms\_theta(plm\_theta())
- logic (lverbose ()): Module containing the logicals that control the run
- truncation (lm\_max(), l\_max(), minc(), n\_r\_max()): This module defines the grid points and the truncation
- blocking (lo\_map()): Module containing blocking information
- constants (half(), two(), one()): module containing constants and parameters used in the code.
- radial\_functions (r\_cmb(), r\_icb(), rscheme\_oc(), orho1()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

omega/nsmax [integer,private/parameter=300]
 Number of cylindrical radial grid points

### Subroutines and functions

Call to Inpas2tr()

Called from output ()

**function** omega/lnpas2tr(f, lmmax, a, b, lmax, minc, nchebmax, theta, r) — Input variables

### **Parameters**

- f (lmmax,\*) [real,in]
- **lmmax** [integer,in,]
- **a** [real,in]
- **b** [real,in]
- lmax [integer,in]
- minc [integer,in]
- nchebmax [integer,in]
- theta [real,in]
- **r** [real,in]

### **Return Inpas2tr** [real]

Called from outomega()

Call to plm\_theta(), abortrun()

### 10.17.14 nl\_special\_calc.f90

### **Description**

This module allows to calculcate several diagnostics that need to be computed in the physical space (non-linear quantities)

### **Quick access**

### **Needed modules**

- horizontal\_data(cosn2(), osn2(), o\_sin\_theta\_e2(), sn2(), costheta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- legendre\_grid\_to\_spec(legtfas2(), legtfas())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- logic(l\_tp\_form(), l\_anelastic\_liquid(), l\_mag\_nl()): Module containing the logicals that control the run
- physical\_parameters (vischeatfac(), thexpnb(), ek()): Module containing the physical parameters
- radial\_functions (alpha0(), orho1(), orho2(), or4(), or2(), or1(), visc(), beta(), temp0(), r()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (nfs(), sizethetab()): Module containing blocking information
- constants (half(), pi(), two(), third(), one()): module containing constants and parameters used in the code.
- truncation (1\_maxmag(), 1\_max(), nrp(), n\_phi\_max()): This module defines the grid points and the truncation

### **Variables**

### Subroutines and functions

Calculates axisymmetric contributions of:

- the horizontal velocity  $u_h = \sqrt{u_\theta^2 + u_\phi^2}$
- its radial derivative  $|\partial u_h/\partial r|$
- The thermal dissipation rate  $(\nabla T)^2$

This subroutine is used when one wants to evaluate viscous and thermal dissipation layers

- Input of variables

- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [real,in]
- **dvtdr** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dsdr** (*nrp*,*nfs*) [real,in]
- **dsdt** (nrp,nfs) [real,in]

```
• dsdp (nrp,nfs) [real,in]
```

- **nr** [integer,in]
- nthetastart [integer,in]

Called from do\_iteration\_thetablocking\_seq(), do\_iteration\_thetablocking\_shtns()

Call to legtfas2(), legtfas()

**subroutine** nl\_special\_calc/**get\_perppar**(*vr*, *vt*, *vp*, *eperplmr*, *eparlmr*, *eparamr*, *eparaxilmr*, *nr*, *nthetastart*)

Calculates the energies parallel and perpendicular to the rotation axis

• 
$$E_{\perp} = 0.5(v_s^2 + v_{\phi}^2)$$
 with

$$v_s = v_r \sin \theta + v_\theta \cos \theta * E_{\parallel} = 0.5 v_z^2 \text{ with } v_z = v_r \cos \theta - v_\theta * \sin \theta$$

- Input of variables

#### **Parameters**

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **eperplmr** (*l\_max*+1) [real,out]
- **eparlmr** (*l\_max*+1) [real,out]
- **eperpaxilmr** (*l\_max*+1) [real,out]
- **eparaxilmr** (*l\_max*+1) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Call to legtfas2()

Calculates the fluxes:

- Convective flux:  $F_c = \rho T(u_r s)$
- Kinetic flux:  $F_k = 1/2 \rho u_r (u_r^2 + u_\theta^2 + u_\phi^2)$
- Viscous flux:  $F_{=} (u \cdot S)_r$

If the run is magnetic, then this routine also computes:

- · Poynting flux
- · resistive flux
- Input of variables

### **Parameters**

```
• vr (nrp,nfs) [real,in]
```

- **vt** (nrp,nfs) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **dvrdr** (*nrp*,*nfs*) [real,in]
- **dvtdr** (*nrp*,*nfs*) [real,in]
- **dvpdr** (*nrp*,*nfs*) [real,in]
- **dvrdt** (nrp,nfs) [real,in]
- **dvrdp** (*nrp*,*nfs*) [real,in]
- **sr** (*nrp*,*nfs*) [real,in]
- **pr** (*nrp*,*nfs*) [real,in]
- **br** (*nrp*,*nfs*) [real,in]
- **bt** (*nrp*,*nfs*) [*real*,*in*]
- **bp** (*nrp*,*nfs*) [real,in]
- **cbt** (*nrp*,*nfs*) [real,in]
- **cbp** (*nrp*,*nfs*) [real,in]
- **fconvlmr** (*l\_max*+1) [real,out]
- **fkinlmr** (*l\_max*+1) [real,out]
- **fvisclmr** (*l\_max*+1) [real,out]
- **fpoynlmr** (*l\_maxmag+1*) [real,out]
- **freslmr** (*l\_maxmag+1*) [real,out]
- **nr** [integer,in]
- nthetastart [integer,in]

Called from do\_iteration\_thetablocking\_openmp(), do\_iteration\_thetablocking\_seq(),
 do\_iteration\_thetablocking\_shtns()

Call to legtfas2(), legtfas()

Calculates axisymmetric contributions of helicity HelLMr and helicity\*\*2 Hel2LMr in (l,m=0,r) space.

- Input of variables

- **vr** (*nrp*,*nfs*) [real,in]
- **vt** (*nrp*,*nfs*) [real,in]
- **vp** (*nrp*,*nfs*) [*real*,*in*]
- **cvr** (*nrp*,*nfs*) [real,in]
- **dvrdt** (nrp,nfs) [real,in]

```
• dvrdp (nrp,nfs) [real,in]
                 • dvtdr (nrp,nfs) [real,in]
                 • dvpdr (nrp,nfs) [real,in]
                 • hellmr (l_max+1) [real,out]
                 • hel2lmr (l_max+1) [real,out]
                 • helnalmr (l max+1) [real,out]
                 • helna2lmr (l_max+1) [real,out]
                 • nr [integer,in]
                 • nthetastart [integer,in]
           Called from do_iteration_thetablocking_openmp(), do_iteration_thetablocking_seq(),
               do_iteration_thetablocking_shtns()
           Call to legtfas2()
subroutine nl_special_calc/get_visc_heat (vr, vt, vp, cvr, dvrdr, dvrdt, dvrdp, dvtdr, dvtdp,
                                                         dvpdr, dvpdp, visclmr, nr, nthetastart)
           Calculates axisymmetric contributions of the viscous heating
     - Input of variables
           Parameters
                 • vr (nrp,nfs) [real,in]
                 • vt (nrp,nfs) [real,in]
                 • vp (nrp,nfs) [real,in]
                 • cvr (nrp,nfs) [real,in]
                 • dvrdr (nrp,nfs) [real,in]
                 • dvrdt (nrp,nfs) [real,in]
                 • dvrdp (nrp,nfs) [real,in]
                 • dvtdr (nrp,nfs) [real,in]
                 • dvtdp (nrp,nfs) [real,in]
                 • dvpdr (nrp,nfs) [real,in]
                 • dvpdp (nrp,nfs) [real,in]
                 • visclmr (l_max+1) [real,out]
                 • nr [integer,in]
                 • nthetastart [integer,in]
           \textbf{Called from} \ \textit{do\_iteration\_thetablocking\_openmp()}, \\ \textit{do\_iteration\_thetablocking\_seq()}, \\
               do_iteration_thetablocking_shtns()
           Call to legtfas()
```

### 10.17.15 probes.f90

### **Description**

Module for artificial sensors to compare time series of physical data with experiments. Probes are located in a radially symmetrical way on a radial surface given by r\_probe (in terms of r\_cmb), theta\_probe in degrees between 0 and 90 and n\_phi\_probes denoting the number of probes in phi. Probes will be located at 'n\_phi\_probes' points at two equatorially symmetric latitudes - theta\_probe and (180 - theta\_probe) on  $r = r_p$ .

version 1.0: Works only for v\_phi, for now. Will be extended for other data later.

### **Quick access**

```
Variables n_out_probes, n_theta_usr, rad_rank, rad_usr, n_phi_probes,
    probe_file, theta_probe, r_probe
Routines finalize_probes(), initialize_probes(), probe_out()
```

### **Needed modules**

- horizontal\_data (theta(), o\_sin\_theta()): Module containing functions depending on longitude and latitude plus help arrays depending on degree and order
- precision\_mod: This module controls the precision used in MagIC
- output\_data(tag()): This module contains the parameters for output control
- logic (l\_save\_out ()): Module containing the logicals that control the run
- radial\_data(nrstart(), nrstop()): This module defines the MPI decomposition in the radial direction.
- parallel\_mod (rank ()): This module contains the blocking information
- num\_param (vscale ()): Module containing numerical and control parameters
- truncation(nrp(), n\_phi\_max(), n\_r\_max()): This module defines the grid points and the truncation
- blocking (nthetabs (), nfs (), sizethetab ()): Module containing blocking information
- constants (pi ()): module containing constants and parameters used in the code.
- radial\_functions (orho1(), r\_cmb(), or2(), or1(), r(), r\_icb()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)

### **Variables**

- probe\_mod/r\_probe [real,public] probe locations, r\_probe in terms of r\_cmb and theta in degrees
- probe\_mod/n\_theta\_usr [integer,private]
- probe\_mod/rad\_usr [integer,private]
- probe\_mod/rad\_rank [integer,private]
- probe mod/n out probes [integer, private]

- probe\_mod/n\_phi\_probes [integer,public] number of probes in phi symmetrically distributed
- probe\_mod/probe\_file [character,private]
- probe\_mod/theta\_probe [real,public]

#### Subroutines and functions

#### **Parameters**

- time [real,in]
- **n\_r** [integer,in] :: radial grod point no.
- **vp** (*nrp*,\*) [real,in]
- **n\_theta\_start** [integer,in] :: start theta no.
- n\_theta\_block\_size [integer,in] :: size of theta block

# 10.18 Reading and storing check points (restart files)

### 10.18.1 readCheckPoints.f90

### **Description**

This module contains the functions that can help reading and mapping of the restart files

#### **Quick access**

### **Needed modules**

- chebyshev(type\_cheb\_odd())
- parallel\_mod: This module contains the blocking information
- cosine\_transform\_odd(costf\_odd\_t())

- useful (polynomial\_interpolation(), abortrun()): library with several useful subroutines
- init\_fields (tshift\_ma1(), tshift\_ma2(), omegaosz\_ic2(), omegaosz\_ic1(), tomega\_ma1(), tomega\_ma2(), start\_file(), scale\_xi(), scale\_b(), omega\_ic1(), omega\_ic2(), scale\_s(), scale\_v(), tipdipole(), tomega\_ic2(), tomega\_ic1(), omega\_ma2(), omega\_ma1(), tshift\_ic2(), tshift\_ic1(), inform(), omegaosz\_ma1(), omegaosz\_ma2()): This module is used to construct the initial solution.
- finite\_differences (type\_fd()): This module is used to calculate the radial grid when finite differences are requested
- radial\_scheme (type\_rscheme()): This is an abstract type that defines the radial scheme used in MagIC
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- radial\_data(n\_r\_cmb(), n\_r\_icb()): This module defines the MPI decomposition in the radial direction.
- precision\_mod: This module controls the precision used in MagIC
- communications (scatter\_from\_rank0\_to\_lo())
- logic (l\_rot\_ic(), l\_ab1(), l\_chemical\_conv(), l\_mag(), l\_heat(), l\_srma(), l\_mag\_lf(), l\_rot\_ma(), l\_sric(), l\_cond\_ic()): Module containing the logicals that control the run
- physical\_parameters (pr(), kbotv(), prmag(), ek(), sigma\_ratio(), radratio(), ktopv(), ra(), sc(), raxi(): Module containing the physical parameters
- radial\_functions (r(), rscheme\_oc(), chebt\_ic(), cheb\_norm\_ic()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- blocking (lmstartb(), nlmbs(), lm2m(), lm2l(), lmstopb(), lo\_map()): Module containing blocking information
- constants (one ()): module containing constants and parameters used in the code.
- truncation(n\_r\_ic\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), minc(), l\_max(), nalias(), n\_r\_max(), m\_max(), lm\_max(), lmagmem(), n\_r\_maxmag(), n\_phi\_tot()): This module defines the grid points and the truncation

#### **Variables**

- readcheckpoints/l\_axi\_old[logical,private]
- readcheckpoints/lreads [logical,private]
- readcheckpoints/bytes\_allocated[integer,private]
- readcheckpoints/n\_start\_file [integer,private]
- readcheckpoints/lreadr[logical,private]
- readcheckpoints/lreadxi[logical,private]

### **Subroutines and functions**

This subroutine is used to read the old restart files produced by MagIC. This is now deprecated with the change of the file format. This is still needed to read old files.

### - Output:

### **Parameters**

- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dwdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dzdt** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*, *out*]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*out*]
- **dpdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*out*]
- **s** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*out*]
- **dsdt** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **xi** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*, *out*]
- **dxidt** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*out*]
- $\mathbf{b}$  (ulmmag-(llmmag)+1, $n_r$ \_maxmag) [complex,out]
- **dbdt** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [*complex,out*]
- **aj** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*, *out*]
- **djdt** (*ulmmag-*(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*out*]
- **b\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,out]
- **dbdt\_ic** (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,out]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,out]
- **djdt\_ic** (*ulmmag-*(*llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex*, *out*]
- omega\_ic [real,out]
- omega\_ma [real,out]
- lorentz\_torque\_ic [real,out]
- lorentz torque ma [real,out]
- **time** [real,out]
- dt\_old [real,out]
- dt\_new [real,out]
- n\_time\_step [integer,out]

Called from getstartfields()

```
Call to abortrun(),
                                                 get1m21mo().
                                                                                  mapdatahydro(),
               scatter_from_rank0_to_lo(), mapdatamag()
subroutine readcheckpoints/readstartfields(w, dwdt, z, dzdt, p, dpdt, s, dsdt, xi, dxidt, b,
                                                          dbdt, aj, djdt, b_ic, dbdt_ic, aj_ic, djdt_ic,
                                                           omega_ic, omega_ma, lorentz_torque_ic,
                                                           lorentz torque ma, time, dt old, dt new,
                                                          n_time_step)
          This subroutine is used to read the restart files produced by MagIC.
     - Output:
          Parameters
                 • \mathbf{w} (ulm-(llm)+1, n\_r\_max) [complex, out]
                 • dwdt (ulm-(llm)+1,n_r_max) [complex, out]
                 • z (ulm-(llm)+1,n_r_max) [complex, out]
                 • dzdt (ulm-(llm)+1,n_r_max) [complex,out]
                 • p (ulm-(llm)+1,n_r_max) [complex, out]
                 • dpdt (ulm-(llm)+1,n_r_max) [complex, out]
                • \mathbf{s} (ulm-(llm)+1,n_r_max) [complex, out]
                 • dsdt (ulm-(llm)+1,n_r_max) [complex, out]
                 • xi (ulm-(llm)+1,n r max) [complex,out]
                • dxidt (ulm-(llm)+1, n r max) [complex, out]
                 • b (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
                 • dbdt (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
                 • aj (ulmmag-(llmmag)+1,n_r_maxmag) [complex, out]
                 • djdt (ulmmag-(llmmag)+1,n_r_maxmag) [complex,out]
                 • b_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                • dbdt_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                • aj_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                 • djdt_ic (ulmmag-(llmmag)+1,n_r_ic_maxmag) [complex,out]
                 • omega_ic [real,out]
                • omega_ma [real,out]
                 • lorentz_torque_ic [real,out]
                 • lorentz_torque_ma [real,out]
                 • time [real,out]
                 • dt_old [real,out]
                 • dt_new [real,out]
                 • n_time_step [integer,out]
          Called from getstartfields()
```

Call to abortrun(), getlm2lmo(), maponefield(), scatter\_from\_rank0\_to\_lo()

```
subroutine readcheckpoints/getlm2lmo(n_r_max, n_r_max_old, l_max, l_max_old, m_max,
                                                minc, minc_old, inform, lm_max, lm_max_old,
                                                n data oldp, lm2lmo)
     - Input variables
          Parameters
                • n_r_max [integer,in]
                • n_r_max_old [integer,in]
                • 1 max [integer,in]
                • l_max_old [integer,in]
                • m_max [integer,in]
                • minc [integer,in]
                • minc_old [integer,in]
                • inform [integer,in]
                • lm_max [integer,in]
                • lm_max_old [integer,out]
                • n_data_oldp [integer,out]
                • lm2lmo (lm_max) [integer,out]
          Called from readstartfields_old(), readstartfields()
subroutine readcheckpoints/maponefield(wo, scale_w, r_old, lm2lmo, n_r_max_old,
                                                   lm_max_old, n_r_maxl, dim1, lbc1, l_ic, w)
     - Input variables
          Parameters
                • wo (*) [complex,in]
                • scale_w [real,in]
                • r_old (*) [real,in]
                • lm2lmo (lm_max) [integer,in]
                • n_r_max_old [integer,in]
                • lm_max_old [integer,in]
                • n_r_maxl [integer,in]
                • dim1 [integer,in]
                • lbc1 [logical,in]
                • l_ic [logical,in]
                • w (lm max,dim1) [complex,out]
          Called from readstartfields()
          Call to mapdatar()
subroutine readcheckpoints/mapdatahydro(wo, zo, po, so, xio, r_old, lm2lmo, n_r_max_old,
                                                    lm_max_old, n_r_maxl, lbc1, lbc2, lbc3, lbc4, lbc5,
                                                    w, z, p, s, xi
     - Input variables
```

### **Parameters**

- **wo** (\*) [complex,in]
- **zo** (\*) [complex,in]
- **po** (\*) [complex,in]
- **so** (\*) [complex,in]
- **xio** (\*) [complex,in]
- **r\_old** (\*) [real,in]
- lm2lmo (lm\_max) [integer,in]
- n\_r\_max\_old [integer,in]
- lm\_max\_old [integer,in]
- n\_r\_maxl [integer,in]
- **lbc1** [logical,in]
- lbc2 [logical,in]
- **lbc3** [logical,in]
- **lbc4** [logical,in]
- **lbc5** [logical,in]
- w (lm\_max,n\_r\_max) [complex,out]
- **z** (lm\_max,n\_r\_max) [complex,out]
- **p** (lm\_max,n\_r\_max) [complex,out]
- **s** (*lm\_max*,*n\_r\_max*) [*complex*,*out*]
- **xi** (lm\_max,n\_r\_max) [complex,out]

Called from readstartfields\_old()

Call to mapdatar()

### - Input variables

- wo (n\_data\_oldp) [complex,in]
- **zo** (n\_data\_oldp) [complex,in]
- **po** (n\_data\_oldp) [complex,in]
- so (n\_data\_oldp) [complex,in]
- **r\_old** (\*) [real,in]
- n\_data\_oldp [integer,in,]
- n\_rad\_tot [integer,in]
- n\_r\_max\_old [integer,in]
- lm\_max\_old [integer,in]

```
• n_r_maxl [integer,in]
                 • lm2lmo (lm_max) [integer,in]
                 • dim1 [integer,in]
                 • l_ic [logical,in]
                 • w (lm_maxmag,dim1) [complex,out]
                 • z (lm_maxmag,dim1) [complex, out]
                 • p (lm_maxmag,dim1) [complex,out]
                 • s (lm_maxmag,dim1) [complex,out]
           Called from readstartfields_old()
           Call to mapdatar()
subroutine readcheckpoints/mapdatar(datar, r_old, n_rad_tot, n_r_max_old, n_r_maxl, lbc,
                                                  l_{\perp}ic)
           Copy (interpolate) data (read from disc file) from old grid structure to new grid. Linear interploation
           is used in r if the radial grid structure differs
           called in mapdata
     — Input variables
           Parameters
                 • datar (*) [complex,inout]
                 • r_old (*) [real,in]
                 • n_rad_tot [integer,in]
                 • n_r_max_old [integer,in]
                 • n_r_maxl [integer,in]
                 • lbc [logical,in]
                 • l_ic [logical,in]
```

### 10.18.2 storeCheckPoints.f90

Call to polynomial\_interpolation()

### **Description**

This module contains several subroutines that can be used to store the checkpoint\_#.tag files

Called from mapdatahydro(), maponefield(), mapdatamag()

### **Quick access**

Routines store()

### **Needed modules**

- parallel\_mod (rank ()): This module contains the blocking information
- init\_fields (tomega\_ic2(), tomega\_ic1(), omegaosz\_ic2(), omega\_ic1(), omega\_ma2(), omega\_ma1(), omega\_ic2(), inform(), omegaosz\_ma1(), omegaosz\_ma2(), tomega\_ma1(), tomega\_ma2(), omegaosz\_ic1()): This module is used to construct the initial solution.
- fieldslast (d\_omega\_ma\_dtlast(), d\_omega\_ic\_dtlast(), lorentz\_torque\_iclast(), lorentz\_torque\_malast()): This module contains time-derivaties array of the previous time-step They are needed in the time-stepping scheme.
- output\_data (n\_log\_file(), tag(), log\_file()): This module contains the parameters for output control
- logic(l\_save\_out(), l\_chemical\_conv(), l\_heat(), l\_mag(), l\_cond\_ic()): Module containing the logicals that control the run
- lmloop\_data(ulmmag(), llmmag(), llm(), ulm())
- precision\_mod: This module controls the precision used in MagIC
- communications(gather\_all\_from\_lo\_to\_rank0(), gt\_ic(), gt\_oc())
- num\_param (alph1(), alph2(), tscale()): Module containing numerical and control parameters
- physical\_parameters (pr(), prmag(), ek(), sigma\_ratio(), radratio(), ra(), sc(), raxi()): Module containing the physical parameters
- charmanip (dble2str()): This module contains several useful routines to manipule character strings
- radial\_functions (rscheme\_oc()): This module initiates all the radial functions (transport properties, density, temperature, cheb transforms, etc.)
- truncation(n\_r\_ic\_max(), lm\_maxmag(), n\_r\_ic\_maxmag(), minc(), l\_max(), nalias(), n\_r\_max(), fd\_stretch(), lm\_max(), n\_theta\_max(), n\_r\_maxmag(), fd\_ratio(), n\_phi\_tot()): This module defines the grid points and the truncation

### **Variables**

### Subroutines and functions

This subroutine stores the results in a checkpoint file. In addition to the magnetic field and velocity potentials we also store the time derivative terms djdt(lm,nR),dbdt(lm,nR),... to allow to restart with 2nd order Adams-Bashforth scheme. To minimize the memory imprint, a gater/write strategy has been adopted here. This implies that only one global array dimension(lm\_max,n\_r\_max) is required.

- Input of variables:

- time [real,in]
- **dt** [real,in]

- dtnew [real,in]
- n\_time\_step [integer,in]
- l\_stop\_time [logical,in]
- l\_new\_rst\_file [logical,in]
- l\_ave\_file [logical,in]
- **w** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **z** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **p** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- $\mathbf{s}$  (ulm-(llm)+1,n\_r\_max) [complex,in]
- **xi** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **b** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **aj** (ulmmag-(llmmag)+1,n\_r\_maxmag) [complex,in]
- **b\_ic** (*ulmmag-(llmmag)+1,n\_r\_ic\_maxmag*) [*complex,in*]
- aj\_ic (ulmmag-(llmmag)+1,n\_r\_ic\_maxmag) [complex,in]
- **dwdtlast** (*ulm*-(*llm*)+1,*n\_r\_max*) [*complex*,*in*]
- **dzdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dpdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dsdtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dxidtlast** (*ulm*-(*llm*)+1,*n*\_*r*\_*max*) [*complex*,*in*]
- **dbdtlast** (*ulmmag*-(*llmmag*)+1,*n\_r\_maxmag*) [*complex*,*in*]
- **djdtlast** (*ulmmag-(llmmag)+1,n\_r\_maxmag*) [complex,in]
- **dbdt\_iclast** (*ulmmag-*(*llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex*,*in*]
- **djdt\_iclast** (*ulmmag-*(*llmmag*)+1,*n\_r\_ic\_maxmag*) [*complex*,*in*]

Called from fields average(), output()

Call to dble2str(), gather all from lo to rank0()

### 10.19 Useful additional libraries

### 10.19.1 useful.f90

### **Description**

library with several useful subroutines

### **Quick access**

```
Routines getmsd2(), logwrite(), abortrun(), factorise(),
    polynomial_interpolation(), polynomial_interpolation_real(),
    cc2real(), cc22real(), l_correct_step(), random()
```

### **Needed modules**

- precision\_mod: This module controls the precision used in MagIC
- parallel\_mod: This module contains the blocking information
- logic (l\_save\_out ()): Module containing the logicals that control the run
- constants (one (), two (), half ()): module containing constants and parameters used in the code.
- output\_data (n\_log\_file(), log\_file()): This module contains the parameters for output control

### **Variables**

### Subroutines and functions

#### **Parameters**

```
• n [integer,in] :: current step
```

• t [real,in] :: time at current step

• t\_last [real,in] :: last time at current step

• n\_max [integer,in] :: max number of steps

• **n\_step** [integer,in] :: action interval

• **n intervals** [integer,in] :: number of actions

• **n\_ts** [integer,in] :: number of times t

• **times** (\*) [real,in] :: times where l\_correct\_step == true

• **n\_eo** [integer,in] :: even/odd controller

### Return l\_correct\_step [logical]

```
Called from step_time()
```

Call to abortrun()

### function useful/random(r)

random number generator

if ( r == 0 ) then random(r) = next random number (between 0. and 1.) if ( r < 0 ) then random(r) = previous random number if ( r > 0 ) then random(r) = a new sequence of random numbers is started with seed r mod 1 note: r must be a non-integer to get a different seq

called in sinit

- Input variables:

**Parameters** r [real,in]

```
Return random [real]
         Called from initb(), initv(), inits(), initxi()
subroutine useful/factorise(n, n_facs, fac, n_factors, factor)
         Purpose of this subroutine is factorize n into a number of given factors fac(i).
     - Input variables:
         Parameters
               • n [integer,in] :: number to be factorised!
               • n_facs [integer,in] :: number of facs to be tried!
               • fac (*) [integer,in] :: list of fators to be tried!
               • n_factors [integer,out] :: number of factors used
               • factor (*) [integer,out] :: list of factors used
         Called from init_fft()
         Call to abortrun()
function useful/cc2real (c, m)
     - Input variables:
         Parameters
               • c [complex,in]
               • m [integer,in]
         Return cc2real [real]
         Called from getstartfields(), get_power(),
                                                             hintrms(),
             get_amplitude(), hint2dpollm(), hint2pollm(), get_poltorrms(),
             get_e_mag(), outpar(), hint2dpol(), get_u_square(), spectrum(),
             hint2torlm(), hint2pol(), hint2tor(), rbpspec(),
                                                                                getdlm(),
             get_e_kin(),
                                 spectrum_average(),
                                                             spectrum_temp_average(),
             spectrum_temp()
function useful/cc22real (c1, c2, m)
     - Input variables:
         Parameters
               • c1 [complex,in]
               • c2 [complex,in]
               • m [integer,in]
         Return cc22real [real]
         Called from get_power(), get_e_mag(), spectrum()
subroutine useful/logwrite(message)
     - Input variable:
         Parameters message [character,in]
         Called from getstartfields(), outto(), get_fd_grid(), step_time(),
             output(), radial(), initialize_blocking(), precalc(), dt_courant()
```

```
subroutine useful/getmsd2 (mean, sd, x, n, dt, totaltime)
```

This subroutine computes the mean and standard deviation according to a method introduced by Donald Knuth (1962). I rederived his formulas for a variable time step. On output SD still needs to be normalized with the totalTime and then you have to take the square root!! The input integer counts the number of calls. For n=1 initialisation is necessary. – Input variables:

#### **Parameters**

```
• mean [real,out] :: Time-average
```

- sd [real,out] :: Standard-deviation
- x [real,in] :: quantity to be averaged
- **n** [integer,in] :: number of calls( only n=1 needed)
- **dt** [real,in] :: time since last averaging step
- totaltime [real,in]:: total averaging time up to now

Called from dtvrms()

## Parameters

- **xold** (4) [real,in]
- yold (4) [complex,in]
- xnew [real,in]
- ynew [complex,out]

Called from mapdatar()

Call to polynomial\_interpolation\_real()

### Parameters

- **xold** (\*) [real,in]
- **yold** (\*) [real,in]
- xnew [real,in]
- ynew [real,out]

**Called from** polynomial interpolation()

Call to abortrun()

subroutine useful/abortrum(message)

This routine properly terminates a run

- Input variable

### Parameters message [character,in]

```
Called from l_correct_step(), transportproperties(), updateb(),
    get_lorder_lm_blocking(), get_b_nl_bcs(), outto(), get_p0mat(),
    get_fd_grid(), wpass4jw(), get_s0mat(), readnamelists(), sgefa(),
    fftjw(), factorise(), init_fft(), lnpas2tr(), get_hit_times(),
```

```
get_standard_lm_blocking(), step_time(), wpass3jw(), initb(),
inits(), get_subblocks(), polynomial_interpolation_real(),
readstartfields_old(), initxi(), get_snake_lm_blocking(),
get_wpsmat(), init_rnb(), get_zmat(), pt_cond(), checktruncation(),
get_wptmat(), get_wmat(), wpass5jw(), get_ps0mat(),
xi_cond(), getdlm(), lo2lm_redist(), readstartfields(),
writeinfo(), plm_theta(), get_pt0mat(), ps_cond(), get_wpmat(),
j_cond(), chebintinit(), get_bmat(), sendvals_to_rank0(),
movie_gather_frames_to_rank0(), write_movie_frame(),
spectrum_average(), get_smat(), getbackground(), lm2lo_redist(),
get_ximat(), get_xi0mat(), get_movie_type(), initialize_blocking(),
get_zl0mat(), precalc(), legtf()
```

### 10.19.2 mem alloc.f90

### **Description**

This little module is used to estimate the global memory allocation used in MagIC

### **Quick access**

### **Needed modules**

- parallel\_mod: This module contains the blocking information
- precision\_mod(cp(), lip()): This module controls the precision used in MagIC
- output\_data(tag()): This module contains the parameters for output control

#### **Variables**

- mem\_alloc/bytes\_allocated[integer,public]
- mem\_alloc/ranks\_selected(:)[integer,private/allocatable]
- mem\_alloc/n\_memory\_file [integer,private]
- mem\_alloc/memory\_file [character,private]
- mem\_alloc/n\_ranks\_print [integer,private]

### **Subroutines and functions**

```
subroutine mem_alloc/initialize_memory_counter()
Called from magic
```

```
subroutine mem_alloc/memwrite(origin, bytes_alloc)

    Input variables

         Parameters
              • origin [character,in]
              • bytes alloc [integer,in]
         Called from initialize_radialloop(),
                                                                 initialize_lmloop(),
             initialize_step_time(),
                                                       initialize communications(),
             initialize_blocking(), magic
         Call to human_readable_size()
subroutine mem_alloc/finalize_memory_counter()

    Local variables

         Called from magic
         Call to human_readable_size()
function mem alloc/human readable size(bytes)
         Parameters bytes [integer,in]
         Return st [real]
         Called from memwrite(), finalize_memory_counter()
```

## 10.19.3 char\_manip.f90

### **Description**

This module contains several useful routines to manipule character strings

### **Quick access**

```
Routines dble2str(), capitalize(), str2dble(), delete_string(), length_to_blank(), length_to_char()
```

### **Needed modules**

• precision\_mod: This module controls the precision used in MagIC

### Subroutines and functions

```
Deletes string_del from string and returns new length of string.

    Input variables

          Parameters
                • string_bn [character,inout]
                • string del [character,in]
                • length [integer,out]
          Called from get_movie_type()
subroutine charmanip/str2dble(string_bn, num)
          interprets next word in string as an 1 real number deletes leading blanks and next_word from string
     - Input variable:
          Parameters
                • string_bn [character,in]
                • num [real,out] :: output
          Called from get_movie_type()
function charmanip/length_to_blank(string_bn)
          determines number of characters before first blank in string
     - Input variable
          Parameters string_bn [character,in]
          Return length_to_blank [integer]
          Called from readnamelists(), writenamelists(), get_movie_type()
function charmanip/length_to_char(string_bn, char_bn)
     - Input variables:
          Parameters
                • string_bn [character,in]
                • char_bn [character,in]
          Return length_to_char [integer]
subroutine charmanip/dble2str(num, str)
          converts a 1 number num into a character str
     - Input variable
          Parameters
                • num [real,in]
                • str [character,out]
          Called from step_time(), store()
```

# **FORTRAN MODULE INDEX**

а	1
algebra, 302	leg_helper_mod, 287
b	legendre_grid_to_spec,295
	legendre_spec_to_grid, 291
blocking, 313	<pre>lmloop_data, 208 lmloop_mod, 240</pre>
C	lmmapping, 316
charmanip, 425	logic, 190
chebint_mod, 403	m
chebyshev_polynoms_mod, 280 communications, 209	magnetic_energy, 326
constants, 203	mem_alloc, 424
cosine_transform_even, 283	movie_data,350
cosine_transform_odd, 282	n
courant_mod, 235	
d	namelists, 214 nl_special_calc, 406
dtb_arrays_mod,383	nonlinear_bcs, 278
dtb_mod, 378	nonlinear_lm_mod, 275
f	num_param, 183
I and the second	
EEF 300	0
fft, 298 fft fac mod 285	O omega 405
fft_fac_mod, 285	omega, 405
fft_fac_mod, 285 fields, 194	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356
fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197</pre> <pre>g</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197  general_arrays_mod, 275</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197  g general_arrays_mod, 275 geos_mod, 399</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197  general_arrays_mod, 275</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197  general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197   g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197  g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346 h</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333 outto_mod, 393  p parallel_mod, 206
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197   g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346  h horizontal_data, 229 i</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333 outto_mod, 393  p parallel_mod, 206 physical_parameters, 186
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197   g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346  h horizontal_data, 229 i init_fields, 218</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333 outto_mod, 393  p parallel_mod, 206 physical_parameters, 186 plms_theta, 286
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197   g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346  h horizontal_data, 229 i</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333 outto_mod, 393  p parallel_mod, 206 physical_parameters, 186 plms_theta, 286 power, 339
<pre>fft_fac_mod, 285 fields, 194 fields_average_mod, 366 fieldslast, 197   g general_arrays_mod, 275 geos_mod, 399 getdlm_mod, 329 graphout_mod, 346  h horizontal_data, 229 i init_fields, 218</pre>	omega, 405 out_coeff, 364 out_dtb_frame, 384 out_movie, 356 out_movie_ic, 362 outmisc_mod, 330 outpar_mod, 336 output_data, 198 output_mod, 318 outrot, 333 outto_mod, 393  p parallel_mod, 206 physical_parameters, 186 plms_theta, 286

```
r
radial_data, 207
radial_der, 304
radial_der_even, 308
radial_functions, 225
radial_spectra, 397
radialloop, 264
readcheckpoints, 412
riteration_mod, 266
riterthetablocking_mod, 268
riterthetablocking_openmp_mod, 270
rms, 369
rms_helpers, 374
S
special, 204
spectra, 342
start_fields, 216
step_time_mod, 232
storecheckpoints, 418
t
timing, 237
to_arrays_mod, 393
to_helpers, 391
torsional_oscillations, 387
truncation, 180
u
updateb_mod, 260
updates_mod, 255
updatewp_mod, 248
updatewps_mod, 242
updatewpt_mod, 245
updatexi_mod, 258
updatez_mod, 252
useful, 420
```

428 Fortran Module Index

# **PYTHON MODULE INDEX**

### m

```
magic.bLayers, 160
magic.coeff, 147
magic.cyl, 162
magic.graph2vtk, 157
magic.libmagic, 171
magic.plotlib, 169
magic.potExtra, 159
magic.spectralTransforms, 167
```

430 Python Module Index

# **INDEX**

Symbols	advrmssd (fortran variable in module rms), 371
('general_arrays_mod/unknown_type', None) (fortran	aj_ave (fortran variable in module fields_average_mod),
type in module general_arrays_mod), 275	368
add() (magic.Butterfly method), 166	aj_ave_global (fortran variable in module
add() (magic.Movie method), 145	fields_average_mod), 368
add() (magic.coeff.MagicCoeffCmb method), 147	aj_ic (fortran variable in module fields), 195
init() (magic.AvgField method), 137	aj_ic_ave (fortran variable in module
init() (magic.Butterfly method), 166	fields_average_mod), 368
init() (magic.CompSims method), 156	aj_ic_lmloc (fortran variable in module fields), 197
init() (magic.MagicGraph method), 140	aj_lmloc (fortran variable in module fields), 195
init() (magic.MagicPV method), 155	aj_rloc (fortran variable in module fields), 196
init() (magic.MagicPotential method), 151	alffac (fortran variable in module num_param), 185
init() (magic.MagicRSpec method), 151	algebra (module), 302
init() (magic.MagicRadial method), 138	allocate_common_arrays() (fortran subroutine in module
init() (magic.MagicSetup method), 136	riterthetablocking_mod), 269
init() (magic.MagicSpectrum method), 139	allocate_mappings() (fortran subroutine in module
init() (magic.MagicSpectrum2D method), 139	lmmapping), 317
init() (magic.MagicTOHemi method), 154	allocate_subblocks_mappings() (fortran subroutine in
init() (magic.MagicTOZ method), 154	module Immapping), 317
init() (magic.MagicTaySphere method), 155	alph1 (fortran variable in module num_param), 184
init() (magic.MagicTs method), 137	alph2 (fortran variable in module num_param), 184
init() (magic.Movie method), 145	alpha (fortran variable in module num_param), 185
init() (magic.Movie3D method), 146	alpha0 (fortran variable in module radial_functions), 227
init() (magic.Surf method), 141	alpha1 (fortran variable in module radial_functions), 227
init() (magic.TOMovie method), 153	alpha2 (fortran variable in module radial_functions), 227
init() (magic.ThetaHeat method), 162	am_kpol_file (fortran variable in module spectra), 343
init() (magic.bLayers.BLayers method), 160	am_ktor_file (fortran variable in module spectra), 343
init() (magic.coeff.MagicCoeffCmb method), 147	am_mpol_file (fortran variable in module spectra), 343
init() (magic.coeff.MagicCoeffR method), 149	am_mtor_file (fortran variable in module spectra), 343 amp_b1 (fortran variable in module init_fields), 219
init() (magic.cyl.Cyl method), 162	amp_curr (fortran variable in module special), 205
init() (magic.graph2vtk.Graph2Vtk method), 157	amp_imp (fortran variable in module special), 205
init() (magic.potExtra.ExtraPot method), 159	amp_riicasym (fortran variable in module special), 205
str() (magic.AvgField method), 138	amp_riicsym (fortran variable in module special), 205
str() (magic.ThetaHeat method), 162	amp_rimasym (fortran variable in module special), 205
str() (magic.bLayers.BLayers method), 160	amp_rimasym (fortran variable in module special), 206
Α	amp_s1 (fortran variable in module init_fields), 220
	amp_s2 (fortran variable in module init_fields), 220
abortrun() (fortran subroutine in module useful), 423	amp_v1 (fortran variable in module init_fields), 220
addtime() (fortran subroutine in module timing), 239	amp_xi1 (fortran variable in module init_fields), 220
adv2hint (fortran variable in module rms), 372	amp_xi2 (fortran variable in module init_fields), 220
advrmsl_sd (fortran variable in module rms), 371	ampstrat (fortran variable in module physi-
advrmsl_ta (fortran variable in module rms), 371	amporar (torum variable in module physi-

cal_parameters), 186	botxi (fortran variable in module init_fields), 220
amstart (fortran variable in module num_param), 184	botxicond (fortran variable in module start_fields), 217
anelastic_flavour (fortran variable in module	bpeakbot (fortran variable in module init_fields), 220
num_param), 185	bpeaktop (fortran variable in module init_fields), 220
anelprof() (in module magic.libmagic), 171	bpivot (fortran variable in module updateb_mod), <b>261</b>
angular_file (fortran variable in module outrot), 334 arc2hint (fortran variable in module rms), 372	bpsdas_rloc (fortran variable in module torsional_oscillations), 388
arcmag2hint (fortran variable in module rms), 372	bpsdlmr (fortran variable in module outto_mod), 395
arcmagrmsl_sd (fortran variable in module rms), 371	bpsdlmr_rloc (fortran variable in module outto_mod), 396
arcmagrmsl_ta (fortran variable in module rms), 372	bpzas_rloc (fortran variable in module tor-
arcmagrmssd (fortran variable in module rms), 372	sional_oscillations), 388
arcrmsl_sd (fortran variable in module rms), 372	bpzdas_rloc (fortran variable in module tor-
arcrmsl_ta (fortran variable in module rms), 372	sional_oscillations), 388
arcrmssd (fortran variable in module rms), 372	bpzdlmr (fortran variable in module outto_mod), 395
array_of_statuses (fortran variable in module communi-	bpzdlmr_rloc (fortran variable in module outto_mod), 396
cations), 210	bpzlmr (fortran variable in module outto_mod), 395
astrm (fortran variable in module outto_mod), 396	bpzlmr_rloc (fortran variable in module outto_mod), 396
astrm_sloc (fortran variable in module outto_mod), 395	bs2as_rloc (fortran variable in module tor-
avg() (magic.cyl.Cyl method), 163	sional_oscillations), 388
avg() (magic.MagicPotential method), 152	bs2lmr (fortran variable in module outto_mod), 396
avg() (magic.potExtra.ExtraPot method), 159	bs2lmr_rloc (fortran variable in module outto_mod), 396
avg() (magic.Surf method), 141	bspas_rloc (fortran variable in module tor-
AvgField (class in magic), 137	sional_oscillations), 388
avgField() (in module magic.libmagic), 171	bspdas_rloc (fortran variable in module tor-
avgStd() (magic.Movie method), 145	sional_oscillations), 388
avgz() (magic.cyl.Cyl method), 163	bspdlmr (fortran variable in module outto_mod), 395 bspdlmr_rloc (fortran variable in module outto_mod), 396
В	bsplmr (fortran variable in module outto_mod), 395
	bsplmr_rloc (fortran variable in module outto_mod), 395
b (fortran variable in module fields), 196 b0 (fortran variable in module special), 205	bszas_rloc (fortran variable in module tor-
b_ave (fortran variable in module fields_average_mod),	sional_oscillations), 388
368	bszlmr (fortran variable in module outto_mod), 396
b_ave_global (fortran variable in module	bszlmr_rloc (fortran variable in module outto_mod), 395
fields_average_mod), 368	buo (fortran variable in module updatewp_mod), 249
b_ic (fortran variable in module fields), 196	buo (fortran variable in module updatewps_mod), 243
b_ic_ave (fortran variable in module	buo (fortran variable in module updatewpt_mod), 246
fields_average_mod), 368	buo2hint (fortran variable in module rms), 372
b_ic_lmloc (fortran variable in module fields), 196	buo_chem_meanr (fortran variable in module power), 340
b_lmloc (fortran variable in module fields), 196	buofac (fortran variable in module physical_parameters),
b_r_file (fortran variable in module output_mod), 322	189
b_rloc (fortran variable in module fields), 195	buomeanr (fortran variable in module power), 340
bcmb (fortran variable in module magnetic_energy), 327	buormsl_sd (fortran variable in module rms), 371
beta (fortran variable in module radial_functions), 227	buormsl_ta (fortran variable in module rms), 372 buormssd (fortran variable in module rms), 371
bic (fortran variable in module special), 205	Butterfly (class in magic), 166
bicb (fortran variable in module fields_average_mod), 368	bytes_allocated (fortran variable in module mem_alloc),
bicb (fortran variable in module output_mod), 320	424
BLayers (class in magic.bLayers), 160	bytes_allocated (fortran variable in module readcheck-
blocking (module), 313	points), 413
bmat (fortran variable in module updateb_mod), 262	bzpdas_rloc (fortran variable in module tor-
bmat_fac (fortran variable in module updateb_mod), 261	sional_oscillations), 388
bmax_imp (fortran variable in module special), 205	bzpdlmr (fortran variable in module outto_mod), 396
botcond (fortran variable in module start_fields), 217	bzpdlmr_rloc (fortran variable in module outto_mod), 396

C
c_dt_z10_ic (fortran variable in module constants), 203
c_dt_z10_ma (fortran variable in module constants), 204
c_lorentz_ic (fortran variable in module constants), 203
c_lorentz_ma (fortran variable in module constants), <b>204</b>
c_moi_ic (fortran variable in module constants), 203
c_moi_ma (fortran variable in module constants), 203
c_moi_oc (fortran variable in module constants), 203
c_z10_omega_ic (fortran variable in module constants),
203
c_z10_omega_ma (fortran variable in module constants), 203
cacheblock_size_in_b (fortran variable in module block-
ing), 314
capitalize() (fortran subroutine in module charmanip), 425
cc22real() (fortran function in module useful), 422
cc2real() (fortran function in module useful), 422
cgesl() (fortran subroutine in module algebra), 303
cgeslml() (fortran subroutine in module algebra), 303
charmanip (module), 425
cheb_grid() (fortran subroutine in module cheby-
shev_polynoms_mod), 281
cheb_ic (fortran variable in module radial_functions), 227
cheb_int (fortran variable in module radial_functions),
cheb_int_ic (fortran variable in module radial_functions),
227
cheb_norm_ic (fortran variable in module ra-
dial_functions), 226
chebgrid() (in module magic.libmagic), 171
chebint() (fortran function in module chebint_mod), 404
chebint_mod (module), 403
chebintd() (fortran function in module chebint_mod), 404
chebintinit() (fortran subroutine in module chebint_mod),
404
chebt_ic (fortran variable in module radial_functions), 227
chebt_ic_even (fortran variable in module ra-
dial_functions), 227
chebt_z (fortran variable in module geos_mod), <b>400</b>
chebt_z (fortran variable in module outto_mod), 395
chebyshev_polynoms_mod (module), 280
check_mpi_error() (fortran subroutine in module paral-
lel_mod), 207
check_time_hits() (fortran subroutine in module
step_time_mod), 235
checktruncation() (fortran subroutine in module trunca-
tion), <b>183</b>

(fortran

cal parameters), 186

ci (fortran variable in module constants), 203 cia2hint (fortran variable in module rms), 371

chemfac

variable

chunksize (fortran variable in module parallel mod), 207

in

module

ciarmsl sd (fortran variable in module rms), 372 ciarmsl ta (fortran variable in module rms), 371 ciarmssd (fortran variable in module rms), 372 clf2hint (fortran variable in module rms), 372 clfrmsl sd (fortran variable in module rms), 372 clfrmsl ta (fortran variable in module rms), 372 clfrmssd (fortran variable in module rms), 372 clm (fortran variable in module outto mod), 395 clm sloc (fortran variable in module outto mod), 395 cmb\_file (fortran variable in module output\_mod), 321 cmbhflux (fortran variable in module physical\_parameters), 189 cmbmov file (fortran variable in module output mod), 321 codeversion (fortran variable in module constants), 204 communications (module), 209 CompSims (class in magic), 156 con decrate (fortran variable in module physical parameters), 189 con funcwidth (fortran variable in module physical parameters), 187 con lambdamatch (fortran variable in module physical\_parameters), 189 con lambdaout (fortran variable in module physical parameters), 190 con radratio (fortran variable in module physical\_parameters), 187 conductance\_ma (fortran variable in module physical\_parameters), 189 constants (module), 203 cor00\_fac (fortran variable in module updatewps\_mod), cor00\_fac (fortran variable in module updatewpt\_mod), cor2hint (fortran variable in module rms), 372 corfac (fortran variable in module physical parameters), corm (fortran variable in module outto\_mod), 396 corm sloc (fortran variable in module outto mod), 396 corrmsl\_sd (fortran variable in module rms), 373 corrmsl ta (fortran variable in module rms), 371 corrmssd (fortran variable in module rms), 371 cos36 (fortran variable in module constants), 203 cos72 (fortran variable in module constants), 204 cosine\_transform\_even (module), 283 cosine\_transform\_odd (module), 282 cosn2 (fortran variable in module horizontal data), 231 costf1\_complex() (fortran subroutine in module cosine\_transform\_odd), 282 costf1\_complex\_1d() (fortran subroutine in module cosine\_transform\_odd), 283 costf1\_real() (fortran subroutine in module co-

sine transform odd), 283

Index 433

physi-

costf1_real_1d() (fortran subroutine in module co-	dbdt_rloc_container (fortran variable in module step_time_mod), 234
sine_transform_odd), 283 costf2() (fortran subroutine in module co-	dbdtlast_lmloc (fortran variable in module fieldslast), 198
sine_transform_even), 284	dbeta (fortran variable in module radial_functions), 226
costf_arrays() (fortran subroutine in module geos_mod),	dble2str() (fortran subroutine in module charmanip), 426
403	dcheb_ic (fortran variable in module radial_functions),
costheta (fortran variable in module horizontal_data), 230	227
courant() (fortran subroutine in module courant_mod),	ddb0 (fortran variable in module special), 205
236	ddb_ic (fortran variable in module fields), 196
courant_mod (module), 235	ddb_ic_lmloc (fortran variable in module fields), 196
courfac (fortran variable in module num_param), 185	ddb_lmloc (fortran variable in module fields), 196
cp (fortran variable in module precision_mod), 180	ddb_rloc (fortran variable in module fields), 197
create_gather_type() (fortran subroutine in module communications), 212	ddbeta (fortran variable in module radial_functions), 227 ddddw (fortran variable in module updatewp_mod), 249
create_lm2r_type() (fortran subroutine in module com-	ddj_ic (fortran variable in module tipdatewp_inod), 249
munications), 212	ddj_ic_lmloc (fortran variable in module fields), 196
create_r2lm_type() (fortran subroutine in module com-	ddj_lmloc (fortran variable in module fields), 197
munications), 212	ddlalpha0 (fortran variable in module radial_functions),
cut() (in module magic.plotlib), 169	227
Cyl (class in magic.cyl), 162	ddltemp0 (fortran variable in module radial_functions),
cylSder() (in module magic.libmagic), 172	227
cylZder() (in module magic.libmagic), 172	ddlvisc (fortran variable in module radial_functions), 227
D	ddw_lmloc (fortran variable in module fields), 195
_	ddw_rloc (fortran variable in module fields), 195 ddws_global (fortran variable in module geos_mod), 400
d2cheb_ic (fortran variable in module radial_functions),	ddzasl (fortran variable in module torsional_oscillations),
d2temp0 (fortran variable in module radial_functions),	388
227	deallocate_common_arrays() (fortran subroutine in mod-
d_fft_init (fortran variable in module fft), 298	ule riterthetablocking_mod), 269
d_l (fortran variable in module horizontal_data), 231	deallocate_mappings() (fortran subroutine in module
d_lp1 (fortran variable in module horizontal_data), 231	lmmapping), 317
d_m (fortran variable in module horizontal_data), 231	deallocate_subblocks_mappings() (fortran subroutine in
d_mc2m (fortran variable in module horizontal_data), 230	module Immapping), 318
d_omega_ic_dtlast (fortran variable in module fieldslast),	defaultnamelists() (fortran subroutine in module
198	namelists), <b>216</b> delete_string() (fortran subroutine in module charmanip),
d_omega_ma_dtlast (fortran variable in module field-	425
slast), 198 db0 (fortran variable in module special), 205	deltacond (fortran variable in module start_fields), 217
db_ave_global (fortran variable in module	deltaxicond (fortran variable in module start_fields), 217
fields_average_mod), 368	delxh2 (fortran variable in module num_param), 185
db_ic (fortran variable in module fields), 196	delxr2 (fortran variable in module num_param), 184
db_ic_lmloc (fortran variable in module fields), 196	dentropy0 (fortran variable in module radial_functions),
db_lmloc (fortran variable in module fields), 196	226
db_rloc (fortran variable in module fields), 197	deriv() (in module magic.coeff), 150
dbdt_cmb_lmloc (fortran variable in module	destroy_gather_type() (fortran subroutine in module communications), 212
step_time_mod), 234	destroy_lm2r_type() (fortran subroutine in module com-
dbdt_iclast_lmloc (fortran variable in module fieldslast),  198	munications), 212
dbdt_lmloc (fortran variable in module step_time_mod),	destroy_r2lm_type() (fortran subroutine in module com-
234	munications), 213
dbdt_lmloc_container (fortran variable in module	dflowdt_lmloc_container (fortran variable in module
step_time_mod), 234	step_time_mod), 234
dbdt_rloc (fortran variable in module step_time_mod),	dflowdt_rloc_container (fortran variable in module
234	step_time_mod), 234

dif (fortran variable in module updatewp_mod), 250	dlvu2meanr (fortran variable in module outpar_mod), 338
dif (fortran variable in module updatewps_mod), 243	dmbmean (fortran variable in module output_mod), 321
dif (fortran variable in module updatewpt_mod), 247	dmvmean (fortran variable in module output_mod), 321
dif (fortran variable in module updatez_mod), 253	do_iteration_thetablocking_openmp() (fortran subroutine
difchem (fortran variable in module num_param), 184	in module riterthetablocking_openmp_mod),
difeta (fortran variable in module num_param), 185	272
difexp (fortran variable in module physical_parameters),	dp_lmloc (fortran variable in module fields), 196
186	dp_rloc (fortran variable in module fields), 195
diff_prec_angle (fortran variable in module physi-	dpdt_lmloc (fortran variable in module step_time_mod),
cal_parameters), 189	234
difkap (fortran variable in module num_param), 184	dpdt_rloc (fortran variable in module step_time_mod),
difnu (fortran variable in module num_param), 184	233
difpol2hint (fortran variable in module rms), 372	dpdtlast_lmloc (fortran variable in module fieldslast), 198
difpollmr (fortran variable in module rms), 372	dphi (fortran variable in module horizontal_data), 230
difrmsl_sd (fortran variable in module rms), 373	dphi0 (fortran variable in module horizontal_data), 230
difrmsl_ta (fortran variable in module rms), 372	dphi02 (fortran variable in module horizontal_data), 230
difrmssd (fortran variable in module rms), 372	dpl0eq (fortran variable in module horizontal_data), 231
diftor2hint (fortran variable in module rms), 371	dplm (fortran variable in module horizontal_data), 230
dipcmbmean (fortran variable in module output_mod),	dplms (fortran variable in module geos_mod), 400
322	dplms (fortran variable in module outto_mod), 395
dipmean (fortran variable in module output_mod), 320	dplmspv (fortran variable in module geos_mod), 400
dipole_file (fortran variable in module magnetic_energy),	dplmz (fortran variable in module geos_mod), 400
327	dpvmean (fortran variable in module output_mod), 320
dissnb (fortran variable in module physical_parameters), 188	dr_fac_ic (fortran variable in module radial_functions),
divktemp0 (fortran variable in module radial_functions),	dr_facc (fortran variable in module rms), 372
227	driftbd_file (fortran variable in module outrot), 334
dj_ic (fortran variable in module fields), 196	driftbq_file (fortran variable in module outrot), 334
dj_ic_lmloc (fortran variable in module fields), 196	driftvd_file (fortran variable in module outrot), 334
dj_lmloc (fortran variable in module fields), 195	driftvq_file (fortran variable in module outrot), 334
dj_rloc (fortran variable in module fields), 196	ds_lmloc (fortran variable in module fields), 196
djdt_iclast_lmloc (fortran variable in module fieldslast),	ds_rloc (fortran variable in module fields), 196
198	dsdt_lmloc (fortran variable in module step_time_mod),
	234
djdt_lmloc (fortran variable in module step_time_mod), 234	
201	dsdt_lmloc_container (fortran variable in module
djdt_rloc (fortran variable in module step_time_mod),	step_time_mod), 233
233	dsdt_rloc (fortran variable in module step_time_mod),
djdtlast_lmloc (fortran variable in module fieldslast), 198	234
dlalpha0 (fortran variable in module radial_functions), 227	dsdt_rloc_container (fortran variable in module step_time_mod), 234
dlbmean (fortran variable in module output_mod), 321	dsdtlast_lmloc (fortran variable in module fieldslast), 198
dlh (fortran variable in module horizontal_data), 230	dt_bpot (fortran variable in module output_data), 202
dlkappa (fortran variable in module radial_functions), 227	dt_cmb (fortran variable in module output_data), 200
dllambda (fortran variable in module radial_functions),	dt_cmb_file (fortran variable in module output_mod), 321
227	dt_courant() (fortran subroutine in module courant_mod),
dltemp0 (fortran variable in module radial_functions),	236
227	dt_graph (fortran variable in module output_data), 199
dlvcmean (fortran variable in module output_mod), 322	dt_icb2_ave (fortran variable in module spectra), 343
dlycmeanr (fortran variable in module outpar_mod), 337	dt_icb_ave (fortran variable in module spectra), 343
dlvisc (fortran variable in module radial_functions), 228	dt_log (fortran variable in module output_data), 200
dlymean (fortran variable in module output_mod), 320	dt_movie (fortran variable in module output_data), 200
dlymeanr (fortran variable in module outpar_mod), 338	dt_pot (fortran variable in module output_data), 201
dlvu2cmeanr (fortran variable in module outpar_mod),	dt_probe (fortran variable in module output_data), 199
337	dt_r_field (fortran variable in module output_data), 200
**:	(

dt_rst (fortran variable in module output_data), 201 dt_spec (fortran variable in module output_data), 199	dvprlm_rloc (fortran variable in module step_time_mod), 234
dt_to (fortran variable in module output_data), 201 dt_tomovie (fortran variable in module output_data), 199	dvsrlm_lmloc (fortran variable in module step_time_mod), 234
	dvsrlm_rloc (fortran variable in module step_time_mod),
dt_toz (fortran variable in module output_data), 200	dvsriii_floc (fortiali variable ili filodule step_tlifie_filod),
dt_tpot (fortran variable in module output_data), 199	
dt_vpot (fortran variable in module output_data), 200	dvxbhlm_lmloc (fortran variable in module
dtb_arrays_mod (module), 383	step_time_mod), 234
dtb_from_rloc_to_lo() (fortran subroutine in module dtb_mod), 381	dvxbhlm_rloc (fortran variable in module step_time_mod), 234
dtb_gather_lo_on_rank0() (fortran subroutine in module dtb_mod), 381	dvxirlm_lmloc (fortran variable in module step_time_mod), 233
dtb_lmloc_container (fortran variable in module	dvxirlm_rloc (fortran variable in module step_time_mod),
dtb_mod), 380	234
dtb_mod (module), 378	dvxvhlm_lmloc (fortran variable in module
dtb_rloc_container (fortran variable in module dtb_mod),	step_time_mod), 234
380	dvxvhlm_rloc (fortran variable in module
dtbpol2hint (fortran variable in module rms), 371	step_time_mod), 234
dtbpollmr (fortran variable in module rms), 371	dw_ave_global (fortran variable in module
dtbrms() (fortran subroutine in module rms), 374	fields_average_mod), 368
dtbrms_file (fortran variable in module rms), 371	dw_lmloc (fortran variable in module fields), 196
dtbtor2hint (fortran variable in module rms), 372	dw_rloc (fortran variable in module fields), 195
dte_file (fortran variable in module output_mod), 321	dwdt_lmloc (fortran variable in module step_time_mod),
dteint (fortran variable in module output_mod), 321	234
dtheta1a (fortran variable in module horizontal_data), 231	<pre>dwdt_rloc (fortran variable in module step_time_mod),</pre>
dtheta1s (fortran variable in module horizontal_data), 231	234
dtheta2a (fortran variable in module horizontal_data), 230	dwdtlast_lmloc (fortran variable in module fieldslast), 198
dtheta2s (fortran variable in module horizontal_data), 230	dwold (fortran variable in module updatewp_mod), 249
dtheta3a (fortran variable in module horizontal_data), 231	dws_global (fortran variable in module geos_mod), 401
dtheta3s (fortran variable in module horizontal_data), 230	dxi_lmloc (fortran variable in module fields), 196
dtheta4a (fortran variable in module horizontal_data), 230	dxi_rloc (fortran variable in module fields), 195
dtheta4s (fortran variable in module horizontal_data), 230	dxidt_lmloc (fortran variable in module step_time_mod),
dtmax (fortran variable in module num_param), 185	234
dtmin (fortran variable in module num_param), 184	dxidt_lmloc_container (fortran variable in module
dtp (fortran variable in module updateb_mod), 262	step_time_mod), 234
dtstart (fortran variable in module num_param), 184	dxidt_rloc (fortran variable in module step_time_mod),
dtt (fortran variable in module updateb_mod), 262	234
dtv (fortran variable in module updatewp_mod), 250	dxidt_rloc_container (fortran variable in module
dtv (fortran variable in module updatewps_mod), 243	step_time_mod), 234
dtv (fortran variable in module updatewpt_mod), 247	dxidtlast_lmloc (fortran variable in module fieldslast),
dtv (fortran variable in module updatez_mod), 253	198
dtvpol2hint (fortran variable in module rms), 372	dz_lmloc (fortran variable in module fields), 197
dtvpollmr (fortran variable in module rms), 371	dz_rloc (fortran variable in module fields), 196
dtvrms() (fortran subroutine in module rms), 374	dzastrlmr (fortran variable in module tor-
dtvrms_file (fortran variable in module rms), 373	sional_oscillations), 388
dtvrmsl_sd (fortran variable in module rms), 371	dzastrlmr_rloc (fortran variable in module tor-
dtvrmsl_ta (fortran variable in module rms), 371	sional_oscillations), 388
dtvrmssd (fortran variable in module rms), 371	dzcorlmr (fortran variable in module tor-
dtvtor2hint (fortran variable in module rms), 371	sional_oscillations), 388
duhmeanr (fortran variable in module outpar_mod), 338	dzcorlmr_rloc (fortran variable in module tor-
dvpm (fortran variable in module outto_mod), 396	sional_oscillations), 388
dvpm_sloc (fortran variable in module outto_mod), 396	dzddvplmr (fortran variable in module tor-
dvprlm_lmloc (fortran variable in module	sional_oscillations), 388
step_time_mod), 234	dzddvplmr_rloc (fortran variable in module tor-

sional_oscillations), 388	e_pa (fortran variable in module kinetic_energy), 324
dzdt_lmloc (fortran variable in module step_time_mod),	e_pa (fortran variable in module magnetic_energy), 327
233	e_t2_l_ave (fortran variable in module spectra), 343
dzdt_rloc (fortran variable in module step_time_mod),	e_t2_m_ave (fortran variable in module spectra), 343
234	e_t_asa (fortran variable in module kinetic_energy), 325
dzdtlast_lo (fortran variable in module fieldslast), 198	e_t_asa (fortran variable in module magnetic_energy),
dzdvplmr (fortran variable in module tor-	327
sional_oscillations), 388	e_t_l_ave (fortran variable in module spectra), 343
dzdvplmr_rloc (fortran variable in module tor-	e_t_m_ave (fortran variable in module spectra), 343
sional_oscillations), 388	e_ta (fortran variable in module kinetic_energy), 324
dzlflmr (fortran variable in module tor-	e_ta (fortran variable in module magnetic_energy), 327
sional_oscillations), 388	earth_compliance_file (fortran variable in module mag-
dzlflmr_rloc (fortran variable in module tor-	netic_energy), 327
sional_oscillations), 388	ek (fortran variable in module physical_parameters), 188
dzrstrlmr (fortran variable in module tor-	ek_p2_l_ave (fortran variable in module spectra), 344
sional_oscillations), 388	ek_p2_m_ave (fortran variable in module spectra), 343
dzrstrlmr_rloc (fortran variable in module tor-	ek_p_l_ave (fortran variable in module spectra), 343
sional_oscillations), 388	ek_p_m_ave (fortran variable in module spectra), 343
dzs_global (fortran variable in module geos_mod), 400	ek_t2_l_ave (fortran variable in module spectra), 344
dzstrlmr (fortran variable in module tor-	ek_t2_m_ave (fortran variable in module spectra), 344
sional_oscillations), 388	ek_t_l_ave (fortran variable in module spectra), 343
dzstrlmr_rloc (fortran variable in module torsional_oscillations), 388	ek_t_m_ave (fortran variable in module spectra), 343 ekscaled (fortran variable in module physi-
dzymean (fortran variable in module output_mod), 322	ekscaled (fortran variable in module physical_parameters), <b>186</b>
dzyniean (fortran variable in module output_mod), 322 dzyplmr (fortran variable in module outto_mod), 396	elcmbmean (fortran variable in module output_mod), 321
dzvplmr_loc (fortran variable in module outto_mod), 395	elmean (fortran variable in module output_mod), 321
dzypinii_ioe (fortraii variable iii inoddie outto_inod), 373	enscale (fortran variable in module num_param), 185
E	eparaximeanr (fortran variable in module outpar_mod),
a amb? 1 ava (fartran variable in madule spectra) 2/2	
e_cmb2_l_ave (fortran variable in module spectra), 343	337
e_cmb2_m_ave (fortran variable in module spectra), 343	337 eparmeanr (fortran variable in module outpar_mod), 337
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343	337
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344	<ul><li>337</li><li>eparmeanr (fortran variable in module outpar_mod), 337</li><li>eperpaximeanr (fortran variable in module outpar_mod), 338</li></ul>
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters),
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions),
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module mag-	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters),
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters),
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 322 e_p2_l_ave (fortran variable in module spectra), 343 e_p2_m_ave (fortran variable in module spectra), 344	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163 equat() (magic.MagicPotential method), 152
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 343 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 322 e_p2_l_ave (fortran variable in module spectra), 343 e_p2_m_ave (fortran variable in module kinetic_energy), 325	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163 equat() (magic.MagicPotential method), 152 equat() (magic.Surf method), 142
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 344 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 322 e_p2_l_ave (fortran variable in module spectra), 343 e_p2_m_ave (fortran variable in module spectra), 344 e_p_asa (fortran variable in module magnetic_energy), 325 e_p_asa (fortran variable in module magnetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163 equat() (magic.MagicPotential method), 152 equat() (magic.Surf method), 142 equatContour() (in module magic.plotlib), 169
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 344 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 322 e_p2_l_ave (fortran variable in module spectra), 343 e_p2_m_ave (fortran variable in module spectra), 344 e_p_asa (fortran variable in module kinetic_energy), 325 e_p_asa (fortran variable in module magnetic_energy), 327	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163 equat() (magic.MagicPotential method), 152 equat() (magic.Surf method), 142 equatContour() (in module magic.plotlib), 169 escale (fortran variable in module num_param), 185
e_cmb2_m_ave (fortran variable in module spectra), 343 e_cmb_l_ave (fortran variable in module spectra), 344 e_cmb_m_ave (fortran variable in module spectra), 344 e_dipa (fortran variable in module magnetic_energy), 327 e_kin_file (fortran variable in module kinetic_energy), 325 e_kin_pmean (fortran variable in module output_mod), 321 e_kin_tmean (fortran variable in module output_mod), 321 e_mag_ic_file (fortran variable in module magnetic_energy), 327 e_mag_oc_file (fortran variable in module magnetic_energy), 327 e_mag_pmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 321 e_mag_tmean (fortran variable in module output_mod), 322 e_p2_l_ave (fortran variable in module spectra), 343 e_p2_m_ave (fortran variable in module spectra), 344 e_p_asa (fortran variable in module magnetic_energy), 325 e_p_asa (fortran variable in module magnetic_energy),	eparmeanr (fortran variable in module outpar_mod), 337 eperpaximeanr (fortran variable in module outpar_mod), 338 eperpmeanr (fortran variable in module outpar_mod), 338 eps (fortran variable in module geos_mod), 400 eps (fortran variable in module rms), 373 epsc (fortran variable in module physical_parameters), 187 epsc0 (fortran variable in module physical_parameters), 189 epscprof (fortran variable in module radial_functions), 228 epscxi (fortran variable in module physical_parameters), 188 epscxi0 (fortran variable in module physical_parameters), 189 epss (fortran variable in module physical_parameters), 190 equat() (magic.cyl.Cyl method), 163 equat() (magic.MagicPotential method), 152 equat() (magic.Surf method), 142 equatContour() (in module magic.plotlib), 169

expo imp (fortran variable in module special), 205 ExtraPot (class in magic.potExtra), 159 fac loop (fortran variable in module special), 205 factorise() (fortran subroutine in module useful), 422 fast read() (in module magic.libmagic), 172 fcondmeanr (fortran variable in module outpar mod), 337 fconvmeanr (fortran variable in module outpar mod), 337 fd order (fortran variable in module truncation), 182 fd order bound (fortran variable in module truncation), 182 fd ratio (fortran variable in module truncation), 182 fd\_stretch (fortran variable in module truncation), 183 fft (module), 298 fft() (magic.coeff.MagicCoeffR method), 149 fft99ajw() (fortran subroutine in module fft), 300 fft99bjw() (fortran subroutine in module fft), 300 fft\_fac\_complex() (fortran subroutine in module fft fac mod), 285 fft fac mod (module), 285 fft fac real() (fortran subroutine in module fft fac mod), fft thetab() (fortran subroutine in module fft), 299 fft to real() (fortran subroutine in module fft), 299 fftjw() (fortran subroutine in module fft), 299 field lmloc container (fortran variable in module fields), 196 field\_rloc\_container (fortran variable in module fields), fields (module), 194 fields\_average() (fortran subroutine module in fields average mod), 368 fields average mod (module), 366 fieldslast (module), 197 filehandle (fortran variable in module out coeff), 364 filehandle (fortran variable in module radial spectra), 398 final wait array (fortran variable in module communications), 210 finalize() (fortran subroutine in module cosine transform even), 284 (fortran subroutine finalize() in module cosine transform odd), 282 finalize() (fortran subroutine in module dtb\_arrays\_mod), finalize() (fortran subroutine in module leg\_helper\_mod), 289

finalize() (fortran subroutine in module nonlin-

finalize() (fortran subroutine in module to arrays mod),

finalize\_blocking() (fortran subroutine in module block-

ear\_lm\_mod), 277

ing), 315

 $\begin{array}{c} \text{finalize\_coeffs() (fortran subroutine in module out\_coeff),} \\ \textbf{364} \end{array}$ 

finalize\_communications() (fortran subroutine in module communications), 211

finalize\_der\_arrays() (fortran subroutine in module radial\_der), 305

finalize\_dtb\_mod() (fortran subroutine in module dtb\_mod), 381

finalize fft() (fortran subroutine in module fft), 298

finalize\_fields() (fortran subroutine in module fields), 197 finalize\_fields\_average\_mod() (fortran subroutine in module fields\_average\_mod), 368

finalize\_fieldslast() (fortran subroutine in module fieldslast), 198

finalize\_geos\_mod() (fortran subroutine in module geos\_mod), 401

 $\begin{array}{c} \text{finalize\_grenoble() (fortran subroutine in module special),} \\ \textbf{206} \end{array}$ 

finalize\_horizontal\_data() (fortran subroutine in module horizontal\_data), 231

 $\begin{array}{cccc} finalize\_init\_fields() & (fortran & subroutine & in & module \\ & & init\_fields), \\ \textbf{221} & \end{array}$ 

finalize\_kinetic\_energy() (fortran subroutine in module kinetic\_energy), 325

finalize\_lmloop() (fortran subroutine in module lm-loop\_mod), 241

finalize\_magnetic\_energy() (fortran subroutine in module magnetic\_energy), 328

finalize\_memory\_counter() (fortran subroutine in module mem\_alloc), 425

finalize\_movie\_data() (fortran subroutine in module movie\_data), 351

finalize\_num\_param() (fortran subroutine in module num\_param), 185

finalize\_outmisc\_mod() (fortran subroutine in module outmisc\_mod), 332

finalize\_outpar\_mod() (fortran subroutine in module outpar\_mod), 338

finalize\_output() (fortran subroutine in module out-put\_mod), 322

finalize\_output\_power() (fortran subroutine in module power), 341

finalize\_outrot() (fortran subroutine in module outrot), 334

finalize\_outto\_mod() (fortran subroutine in module outto\_mod), 396

finalize\_probes() (fortran subroutine in module probe\_mod), 412

finalize\_radial\_functions() (fortran subroutine in module radial\_functions), 228

finalize\_radialloop() (fortran subroutine in module radialloop), **264** 

 $\begin{array}{ccc} finalize\_riter the tablocking\_openmp() \ (for tran \ subroutine \\ in \ module \ riter the tablocking\_openmp\_mod), \end{array}$ 

### 271 get amplitude() (fortran subroutine in module spectra), finalize rms() (fortran subroutine in module rms), 373 finalize spectra() (fortran subroutine in module spectra), get angular moment() (fortran subroutine in module outrot), 336 finalize step time() (fortran subroutine in module get b nl bcs() (fortran subroutine in module nonlinstep time mod), 234 ear bcs), 279 finalize to() (fortran subroutine in module get b surface() (fortran subroutine module sional oscillations), 389 out movie), 362 get\_bmat() (fortran subroutine in module updateb\_mod), finalize updateb() (fortran subroutine in module updateb\_mod), 262 finalize\_updates() (fortran subroutine in module upget\_bpol() (fortran subroutine in module out\_dtb\_frame), dates\_mod), 256 386 finalize\_updatewp() (fortran subroutine in module upget\_br\_skew() (fortran subroutine in module magdatewp\_mod), 250 netic\_energy), 329 finalize\_updatewps() (fortran subroutine in module upget\_br\_v\_bcs() (fortran subroutine in module nonlindatewps\_mod), 243 ear\_bcs), 278 finalize\_updatewpt() (fortran subroutine in module upget\_btor() (fortran subroutine in module out\_dtb\_frame), datewpt mod), 247 finalize updatexi() (fortran subroutine in module updaget chebs even() (fortran subroutine in module chebytexi mod), 259 shev polynoms mod), 280 get dcheb (fortran variable in module radial der), 305 finalize\_updatez() (fortran subroutine in module upget dcheb complex() (fortran subroutine in module radatez mod), 253 fkinmeanr (fortran variable in module outpar\_mod), 338 dial der), 305 get\_dcheb\_even() (fortran subroutine in module raflow Imloc container (fortran variable in module fields). dial der even), 311 flow rloc container (fortran variable in module fields), get dcheb real 1d() (fortran subroutine in module ra-196 dial\_der), 306 four (fortran variable in module constants), 203 get\_ddcheb() (fortran subroutine in module radial\_der), fourier2D() (magic.Butterfly method), 167 fpoynmeanr (fortran variable in module outpar mod), 337 get\_ddcheb\_even() (fortran subroutine in module raframes (fortran variable in module movie data), 351 dial\_der\_even), 311 fresmeanr (fortran variable in module outpar mod), 338 get\_dddcheb() (fortran subroutine in module radial\_der), fviscmeanr (fortran variable in module outpar\_mod), 338 get\_dddr() (fortran subroutine in module radial\_der), 308 G get ddr() (fortran subroutine in module radial der), 307 get ddr even() (fortran subroutine in module rag0 (fortran variable in module physical\_parameters), 187 dial der even), 309 g1 (fortran variable in module physical\_parameters), 187 get\_ddrns\_even() (fortran subroutine in module rag2 (fortran variable in module physical\_parameters), 187 dial der even), 310 gather all from lo to rank0() (fortran subroutine in get\_dh\_dtblm() (fortran subroutine in module dtb\_mod), module communications), 212 gather\_from\_lo\_to\_rank0() (fortran subroutine in module get dr (fortran variable in module radial der), 305 communications), 212 get\_dr\_complex() (fortran subroutine in module ragauleg() (fortran subroutine in module horizontal data), dial\_der), 307 get\_dr\_real\_1d() (fortran subroutine in module ragauss (fortran variable in module horizontal data), 231 dial\_der), 307 general arrays mod (module), 275 get\_drns\_even() (fortran subroutine in module rageo2hint (fortran variable in module rms), 371 dial der even), 309 geormsl sd (fortran variable in module rms), 372 get\_dtb() (fortran subroutine in module out dtb frame), geormsl\_ta (fortran variable in module rms), 371 385 geormssd (fortran variable in module rms), 373 get\_dtblm() (fortran subroutine in module dtb\_mod), 381 geos file (fortran variable in module geos mod), 400 subroutine in get\_dtblmfinish() (fortran module geos\_mod (module), 399

Index 439

get e kin()

geosmean (fortran variable in module output\_mod), 321

dtb mod), 383

(fortran subroutine

in

module

ki-

netic energy), 325 get\_e\_mag() (fortran subroutine in module magnetic energy), 328 get fl() (fortran subroutine in module out movie), 362 get fluxes() (fortran subroutine in module nl special calc), 408 get\_global\_sum (fortran variable in module communications), 210 get\_global\_sum\_cmplx\_1d() (fortran function in module communications), 211 get\_global\_sum\_cmplx\_2d() (fortran function in module communications), 211 get\_global\_sum\_real\_2d() (fortran function in module communications), 211 get\_helicity() (fortran subroutine in module nl\_special\_calc), 409 get\_hit\_times() (fortran subroutine in module precalculations), 224 get lorder lm blocking() (fortran subroutine in module blocking), 315 get lorentz torque() (fortran subroutine in module outrot), 335 get\_movie\_type() (fortran subroutine module movie data), 351 get\_nlblayers() subroutine (fortran in module nl special calc), 407 get\_p0mat() (fortran subroutine in module updatewp\_mod), 251 get\_pas() (fortran subroutine in module to\_helpers), 392 get\_paslm() (fortran subroutine in module rms\_helpers), 375 get\_perppar() (fortran subroutine in module nl\_special\_calc), 408 get\_poltorrms() (fortran subroutine module in rms helpers), 375 get power() (fortran subroutine in module power), 341 get ps0mat() (fortran subroutine in module datewps mod), 245 get\_pt0mat() (fortran subroutine in module datewpt\_mod), 248 get ras() (fortran subroutine in module rms helpers), 378 get s0mat() (fortran subroutine in module updates mod), get\_sl() (fortran subroutine in module out\_movie), 361 get\_smat() (fortran subroutine in module updates\_mod), get\_snake\_lm\_blocking() (fortran subroutine in module blocking), 315 get\_standard\_deviation() (fortran function in module spectra), 344

get\_standard\_lm\_blocking() (fortran subroutine in mod-

get subblocks() (fortran subroutine in module blocking),

ule blocking), 315

315

get td() (fortran subroutine in module nonlinear lm mod), 277 get theta blocking (fortran variable in module blocking), get\_theta\_blocking\_cache() (fortran subroutine in module blocking), 315 get theta blocking openmp() (fortran subroutine in module blocking), 316 get\_u\_square() (fortran subroutine in module kinetic\_energy), 325 get\_visc\_heat() (fortran subroutine in module nl\_special\_calc), 410 get\_viscous\_torque (fortran variable in module outrot), 334 get\_viscous\_torque\_complex() (fortran subroutine in module outrot), 335 get\_viscous\_torque\_real() (fortran subroutine in module outrot), 335 get wmat() (fortran subroutine module datewp mod), 251 get\_wpmat() (fortran subroutine module updatewp mod), 251 get\_wpsmat() (fortran subroutine in module updatewps mod), 244 get wptmat() (fortran subroutine in module updatewpt mod), 248 get\_xi0mat() (fortran subroutine in module updatexi\_mod), 259 get\_ximat() (fortran subroutine in module updatexi\_mod), **260** get\_z10mat() (fortran subroutine in module updatez\_mod), 254 get\_zmat() (fortran subroutine in module updatez\_mod), getAccuratePeaks() (in module magic.bLayers), 160 getastr() (fortran subroutine in module to\_helpers), 392 getbackground() (fortran subroutine in module radial functions), 228 getCpuTime() (in module magic.libmagic), 173 getdlm() (fortran subroutine in module getdlm\_mod), 330 getdlm mod (module), 329 getdvptr() (fortran subroutine in module geos mod), 402 getegeos() (fortran subroutine in module geos mod), 401 getentropygradient() (fortran subroutine in module radial\_functions), 228 getGauss() (in module magic.coeff), 150 getlm2lmo() (fortran subroutine in module readcheckpoints), **415** getMaxima() (in module magic.bLayers), 161 getmsd2() (fortran subroutine in module useful), 422 getpastr() (fortran subroutine in module to\_helpers), 391 getstartfields() (fortran subroutine in module start fields),

getthistype() (fortran function in module riterthetablock-

ing_openmp_mod), <b>271</b> getto() (fortran subroutine in module tor-	hint2tor() (fortran subroutine in module rms_helpers), 377
sional_oscillations), 389	hint2torlm() (fortran subroutine in module rms_helpers),
gettofinish() (fortran subroutine in module tor-	377
sional_oscillations), 390 gettonext() (fortran subroutine in module tor-	hintrms() (fortran subroutine in module rms_helpers), 377 horizontal() (fortran subroutine in module horizon-
sional_oscillations), 390	tal_data), 231
getTotalRunTime() (in module magic.libmagic), 173	horizontal_data (module), 229
gradt2meanr (fortran variable in module outpar_mod), 338	human_readable_size() (fortran function in module mem_alloc), 425
Graph2Vtk (class in magic.graph2vtk), 157	
graph_file (fortran variable in module output_data), 202	I
graph_mpi_fh (fortran variable in module output_data), 200	i_fft_init (fortran variable in module fft), 298 ierr (fortran variable in module parallel_mod), 207
<pre>graph_write() (fortran subroutine in module     graphout_mod), 349</pre>	imageon (fortran variable in module physical_parameters), 190
graph_write_mpi() (fortran subroutine in module graphout_mod), 349	imps (fortran variable in module physical_parameters), 188
graphout() (fortran subroutine in module graphout_mod),  347	impxi (fortran variable in module physical_parameters),
graphout_header() (fortran subroutine in module	inerp_file (fortran variable in module outrot), 334
graphout_mod), 348	inert_file (fortran variable in module outrot), 334
graphout_ic() (fortran subroutine in module	inform (fortran variable in module init_fields), 220
graphout_mod), 349	init_b1 (fortran variable in module init_fields), 219
graphout_mod (module), 346	<pre>init_fft() (fortran subroutine in module fft), 298</pre>
graphout_mpi() (fortran subroutine in module	init_fields (module), 218
graphout_mod), 348	init_rnb() (fortran subroutine in module rms), 373
graphout_mpi_header() (fortran subroutine in module	init_s1 (fortran variable in module init_fields), 220
graphout_mod), 348 grunnb (fortran variable in module physical_parameters),	init_s2 (fortran variable in module init_fields), 220
189	init_v1 (fortran variable in module init_fields), 220 init_xi1 (fortran variable in module init_fields), 220
gt_cheb (fortran variable in module communications),	init_xi2 (fortran variable in module init_fields), 220
211	initb() (fortran subroutine in module init_fields), 222
gt_ic (fortran variable in module communications), 210 gt_oc (fortran variable in module communications), 210	initialize() (fortran subroutine in module co- sine_transform_even), <b>284</b>
Н	initialize() (fortran subroutine in module co- sine_transform_odd), 282
half (fortran variable in module constants), 204	initialize() (fortran subroutine in module
hammer2cart() (in module magic.plotlib), 169	dtb_arrays_mod), 384
hdif_b (fortran variable in module horizontal_data), 230	initialize() (fortran subroutine in module
hdif_s (fortran variable in module horizontal_data), 230	leg_helper_mod), 288
hdif_v (fortran variable in module horizontal_data), 230	initialize() (fortran subroutine in module nonlin-
hdif_xi (fortran variable in module horizontal_data), 230	ear_lm_mod), 277
heat_file (fortran variable in module outmisc_mod), 331	initialize() (fortran subroutine in module to_arrays_mod), 393
helicity_file (fortran variable in module outmisc_mod), 331	initialize_blocking() (fortran subroutine in module block-
hint2dpol() (fortran subroutine in module rms_helpers),	ing), 314
375	initialize_coeffs() (fortran subroutine in module
hint2dpollm() (fortran subroutine in module	out_coeff), 364
rms_helpers), 376	initialize_communications() (fortran subroutine in mod-
hint2pol() (fortran subroutine in module rms_helpers),	ule communications), 211
376	initialize_der_arrays() (fortran subroutine in module ra-
hint2pollm() (fortran subroutine in module rms_helpers),	dial_der), 305

**376** 

- dtb mod), 381
- initialize fields() (fortran subroutine in module fields),
- initialize fields average mod() (fortran subroutine in module fields average mod), 368
- initialize fieldslast() (fortran subroutine in module fieldslast), 198
- initialize\_geos\_mod() (fortran subroutine in module geos\_mod), 401
- initialize\_grenoble() (fortran subroutine in module special), 206
- initialize horizontal data() (fortran subroutine in module horizontal data), 231
- initialize\_init\_fields() (fortran subroutine in module init\_fields), 221
- initialize\_kinetic\_energy() (fortran subroutine in module kinetic energy), 325
- initialize\_lmloop() (fortran subroutine in module lmloop mod), 241
- initialize\_lmloop\_data() (fortran subroutine in module Imloop data), 208
- initialize\_magnetic\_energy() (fortran subroutine in module magnetic energy), 328
- initialize memory counter() (fortran subroutine in module mem alloc), 424
- initialize\_movie\_data() (fortran subroutine in module movie\_data), 351
- initialize\_num\_param() (fortran subroutine in module num param), 185
- initialize\_outmisc\_mod() (fortran subroutine in module outmisc\_mod), 332
- initialize\_outpar\_mod() (fortran subroutine in module outpar\_mod), 338
- initialize output() (fortran subroutine in module output mod), 322
- initialize output power() (fortran subroutine in module power), 340
- initialize outrot() (fortran subroutine in module outrot),
- initialize outto mod() (fortran subroutine in module outto\_mod), 396
- initialize probes() (fortran subroutine module probe\_mod), 412
- initialize\_radial\_data() (fortran subroutine in module radial\_data), 208
- initialize radial functions() (fortran subroutine in module radial\_functions), 228
- initialize\_radialloop() (fortran subroutine in module radialloop), 264
- initialize\_riterthetablocking\_openmp() (fortran subroutine in module riterthetablocking openmp mod), 271
- initialize rms() (fortran subroutine in module rms), 373

- initialize dtb mod() (fortran subroutine in module initialize spectra() (fortran subroutine in module spectra),
  - initialize step time() (fortran subroutine in module step\_time\_mod), 234
  - initialize to() (fortran subroutine in module sional oscillations), 389
  - initialize truncation() (fortran subroutine in module truncation), 183
  - initialize updateb() (fortran subroutine in module updateb\_mod), 262
  - initialize\_updates() (fortran subroutine in module updates\_mod), 256
  - initialize updatewp() (fortran subroutine in module updatewp\_mod), 250
  - initialize\_updatewps() (fortran subroutine in module updatewps\_mod), 243
  - initialize\_updatewpt() (fortran subroutine in module updatewpt mod), 247
  - initialize updatexi() (fortran subroutine in module updatexi mod), 259
  - initialize updatez() (fortran subroutine in module updatez mod), 253
  - inits() (fortran subroutine in module init\_fields), 221
  - inity() (fortran subroutine in module init fields), 221
  - initxi() (fortran subroutine in module init fields), 221
  - intcheb() (in module magic.libmagic), 173
  - integBotTop() (in module magic.bLayers), 161
  - integBulkBc() (in module magic.bLayers), 161
  - integration (module), 311
  - interior model (fortran variable in module physical\_parameters), 188
  - intfac (fortran variable in module num\_param), 185 istop (fortran variable in module num\_param), 184

j\_cond() (fortran subroutine in module init\_fields), 222 jmat (fortran variable in module updateb mod), 262 jmat fac (fortran variable in module updateb mod), 261 ipivot (fortran variable in module updateb mod), 261 jvarcon (fortran variable in module radial functions), 227

## K

- kappa (fortran variable in module radial\_functions), 227 kbotb (fortran variable in module physical\_parameters), 187
- kbots (fortran variable in module physical\_parameters), 187
- kbotv (fortran variable in module physical\_parameters),
- kbotxi (fortran variable in module physical\_parameters), 187
- kinetic\_energy (module), 324
- ktopb (fortran variable in module physical parameters), 186

ktopp (fortran variable in module physical_parameters), $187$	l_isothermal (fortran variable in module logic), 192 l_lcr (fortran variable in module logic), 191
ktops (fortran variable in module physical_parameters), 187	l_mag (fortran variable in module logic), 191 l_mag_kin (fortran variable in module logic), 194
ktopv (fortran variable in module physical_parameters), 186	l_mag_lf (fortran variable in module logic), 191 l_mag_nl (fortran variable in module logic), 192
ktopxi (fortran variable in module physical_parameters),	l_max (fortran variable in module truncation), <b>181</b>
187	l_max_cmb (fortran variable in module output_data), 200
1	l_max_comp (fortran variable in module output_data),
L	200
12lmas (fortran variable in module blocking), 314	l_max_r (fortran variable in module output_data), 202
l_ab1 (fortran variable in module logic), 191	l_maxmag (fortran variable in module truncation), 183
l_am (fortran variable in module logic), 192	l_movie (fortran variable in module logic), 193
l_anel (fortran variable in module logic), 193	l_movie_ic (fortran variable in module logic), 192
l_anelastic_liquid (fortran variable in module logic), 193	l_movie_oc (fortran variable in module logic), 193
l_average (fortran variable in module logic), 191	l_newmap (fortran variable in module logic), 193
l_axi (fortran variable in module truncation), 181	l_non_adia (fortran variable in module logic), 192
l_axi_old (fortran variable in module readcheckpoints),	l_non_rot (fortran variable in module logic), 191
413	l_par (fortran variable in module logic), 194
l_b_nl_cmb (fortran variable in module logic), 194	l_perppar (fortran variable in module logic), 191
l_b_nl_icb (fortran variable in module logic), 193	1_power (fortran variable in module logic), 194
l_chemical_conv (fortran variable in module logic), 192	l_precession (fortran variable in module logic), 194 l_pressgraph (fortran variable in module logic), 192
l_cmb_field (fortran variable in module logic), 193	
l_cond_ic (fortran variable in module logic), 191	l_probe (fortran variable in module logic), 192 l_pv (fortran variable in module logic), 191
l_cond_ma (fortran variable in module logic), 193 l_conv (fortran variable in module logic), 192	l_r_field (fortran variable in module logic), 194
l_conv_nl (fortran variable in module logic), 192	l_r_field (fortran variable in module logic), 191
l_corr (fortran variable in module logic), 194	l_reset_t (fortran variable in module init_fields), 219
l_correct_ame (fortran variable in module logic), 191	l_ri (fortran variable in module special), <b>205</b>
l_correct_amz (fortran variable in module logic), 191	l_rmagspec (fortran variable in module logic), 192
l_correct_step() (fortran function in module useful), 421	l_rms (fortran variable in module logic), 194
l_corrmov (fortran variable in module logic), 193	l_rot_ic (fortran variable in module logic), 193
l_cour_alf_damp (fortran variable in module logic), 192	l_rot_ma (fortran variable in module logic), 194
l_curr (fortran variable in module special), 205	l_runtimelimit (fortran variable in module logic), 193
l_diff_prec (fortran variable in module logic), 194	l_save_out (fortran variable in module logic), 193
l_double_curl (fortran variable in module logic), 193	l_single_matrix (fortran variable in module logic), 192
l_drift (fortran variable in module logic), 192	l_sric (fortran variable in module logic), 191
l_dt_cmb_field (fortran variable in module logic), 192	l_srma (fortran variable in module logic), 191
l_dtb (fortran variable in module logic), 194	l_start_file (fortran variable in module init_fields), 219
l_dtbmovie (fortran variable in module logic), 191	l_store_frame (fortran variable in module logic), 192
l_dtrmagspec (fortran variable in module logic), 191	l_storebpot (fortran variable in module logic), 192
l_earth_likeness (fortran variable in module logic), 193	l_storepot (fortran variable in module logic), 194
l_energy_modes (fortran variable in module logic), 194	l_storetpot (fortran variable in module logic), 193
l_finite_diff (fortran variable in module logic), 193	l_storevpot (fortran variable in module logic), 192
l_fluxprofs (fortran variable in module logic), 193	l_temperature_diff (fortran variable in module logic), 193
l_graph_time (fortran variable in module output_data),	l_time_hits (fortran variable in module logic), 190
200	l_to (fortran variable in module logic), 190
l_heat (fortran variable in module logic), 191	1_tomovie (fortran variable in module logic), 194
l_heat_nl (fortran variable in module logic), 194	l_tp_form (fortran variable in module logic), 194 l_true_time (fortran variable in module logic), 192
l_hel (fortran variable in module logic), 192 l_ht (fortran variable in module logic), 194	l_update_b (fortran variable in module logic), 191
l_htmovie (fortran variable in module logic), 194	l_update_s (fortran variable in module logic), 191
l_imp (fortran variable in module special), 206	l_update_v (fortran variable in module logic), 191
l iner (fortran variable in module logic) 194	1 update_xi (fortran variable in module logic), 193

l_viscbccalc (fortran variable in module logic), 192 l_z10mat (fortran variable in module logic), 192 lambda (fortran variable in module radial_functions), 228 lbdissmean (fortran variable in module output_mod), 321 lbmat (fortran variable in module updateb_mod), 261 ldif (fortran variable in module num_param), 184 ldifexp (fortran variable in module num_param), 184 ldtbmem (fortran variable in module truncation), 181 leg_helper_mod (module), 287 leg_scal_to_grad_spat() (fortran subroutine in module	llm (fortran variable in module lmloop_data), 208 llmmag (fortran variable in module lmloop_data), 208 lm2 (fortran variable in module blocking), 313 lm22l (fortran variable in module blocking), 314 lm22lm (fortran variable in module blocking), 314 lm22m (fortran variable in module blocking), 314 lm21 (fortran variable in module blocking), 314 lm2lma (fortran variable in module blocking), 314 lm2lmp (fortran variable in module blocking), 314 lm2lmp (fortran variable in module blocking), 314 lm2lms (fortran variable in module blocking), 314 lm2lo_redist() (fortran subroutine in module communications), 214 lm2m (fortran variable in module blocking), 314 lm2mc (fortran variable in module blocking), 314 lm2mc (fortran variable in module blocking), 314 lm2pt() (fortran subroutine in module out_dtb_frame),
legprep() (fortran subroutine in module leg_helper_mod),	387
289 legprep_ic() (fortran subroutine in module	lm2r_redist_start() (fortran subroutine in module communications), 213
leg_helper_mod), 290	lm2r_redist_wait() (fortran subroutine in module commu-
legprepg() (fortran subroutine in module	nications), 213
leg_helper_mod), 289	lm_max (fortran variable in module truncation), <b>182</b>
legtf() (fortran subroutine in module legen- dre_spec_to_grid), 293	lm_max_comp (fortran variable in module magnetic_energy), 327
legtf1() (fortran subroutine in module legen-	lm_max_dtb (fortran variable in module truncation), 183
dre_grid_to_spec), 295	lm_max_real (fortran variable in module truncation), 182
legtf2() (fortran subroutine in module legen-	lm_maxmag (fortran variable in module truncation), 181
dre_grid_to_spec), 296	lm_on_last_rank (fortran variable in module lm-
legtf3() (fortran subroutine in module legen-	loop_data), 208
dre_grid_to_spec), 296	lm_per_rank (fortran variable in module lmloop_data), 208
<pre>legtf_spher_tor() (fortran subroutine in module legen- dre_grid_to_spec), 296</pre>	lmagmem (fortran variable in module truncation), 182
legtfas() (fortran subroutine in module legen-	lmas2pt() (fortran subroutine in module legen-
dre_grid_to_spec), 297	dre_spec_to_grid), 295
legtfas2() (fortran subroutine in module legen-	lmloop() (fortran subroutine in module lmloop_mod), 241
dre_grid_to_spec), 297	lmloop_data (module), 208
legtfg() (fortran subroutine in module legen-	lmloop_mod (module), 240
dre_spec_to_grid), 291	Immapping (module), 316
legtfgnomag() (fortran subroutine in module legen-	lmodd (fortran variable in module horizontal_data), 230
dre_spec_to_grid), 292 length_to_blank() (fortran function in module charma-	lmoddp (fortran variable in module horizontal_data), 231
nip), 426	Imoviemem (fortran variable in module truncation), 182 Imp2 (fortran variable in module blocking), 313
length_to_char() (fortran function in module charmanip),	lmp2l (fortran variable in module blocking), 314
426	lmp2lm (fortran variable in module blocking), 314
lf2hint (fortran variable in module rms), 371	lmp2lmpa (fortran variable in module blocking), 314
lffac (fortran variable in module physical_parameters),	lmp2lmps (fortran variable in module blocking), 314
188	lmp_max (fortran variable in module truncation), 182
lfm (fortran variable in module outto_mod), 395	lmp_max_dtb (fortran variable in module truncation), 182
lfm_sloc (fortran variable in module outto_mod), 395	Imstartb (fortran variable in module blocking), 313
Ifrmsl_sd (fortran variable in module rms), 372	lmstopb (fortran variable in module blocking), 314
lfrmsl_ta (fortran variable in module rms), 372 lfrmssd (fortran variable in module rms), 371	lnegtime() (fortran function in module timing), 239 lnpas2tr() (fortran function in module omega), 406
Igrenoble (fortran variable in module special), 205	lo2lm_redist() (fortran subroutine in module communica-
licfield (fortran variable in module movie_data), 351	tions), 214
lip (fortran variable in module precision_mod), 180	

lo2r_field (fortran variable in module communications), 211	magic.cyl (module), 162 magic.graph2vtk (module), 157
lo2r_flow (fortran variable in module communications),	magic.libmagic (module), 171
211	magic.plotlib (module), 169
lo2r_redist_start() (fortran subroutine in module commu-	magic.potExtra (module), 159
nications), 213	magic.spectralTransforms (module), 167
lo2r_redist_wait() (fortran subroutine in module commu-	MagicCoeffCmb (class in magic.coeff), 147
nications), 213	MagicCoeffR (class in magic.coeff), 149
lo2r_s (fortran variable in module communications), 211	MagicGraph (class in magic), 140
lo2r_xi (fortran variable in module communications), 211	MagicPotential (class in magic), 151
lo_map (fortran variable in module blocking), 314	MagicPV (class in magic), 155
lo_sub_map (fortran variable in module blocking), 314	MagicRadial (class in magic), 138
	MagicRSpec (class in magic), 151
log_file (fortran variable in module output_data), 202	MagicSetup (class in magic), 136
logic (module), 190	
logwrite() (fortran subroutine in module useful), 422	MagicSpectrum (class in magic), 138
lorentz_torque_iclast (fortran variable in module field-	MagicSpectrum2D (class in magic), 139
slast), 198	MagicTaySphere (class in magic), 155
lorentz_torque_malast (fortran variable in module field-	MagicTOHemi (class in magic), 154
slast), 198	MagicTOZ (class in magic), 154
lp_file (fortran variable in module output_data), 202	MagicTs (class in magic), 136
lreadr (fortran variable in module readcheckpoints), 413	magnetic_energy (module), 326
lreads (fortran variable in module readcheckpoints), 413	magrmsl_sd (fortran variable in module rms), 371
lreadxi (fortran variable in module readcheckpoints), 413	magrmsl_ta (fortran variable in module rms), 372
lscale (fortran variable in module num_param), 185	magrmssd (fortran variable in module rms), 373
lsmat (fortran variable in module updates_mod), 256	map_function (fortran variable in module num_param),
lstart (fortran variable in module horizontal_data), 230	185
lstartp (fortran variable in module horizontal_data), 231	mapdatahydro() (fortran subroutine in module readcheck-
lstop (fortran variable in module horizontal_data), 230	points), <b>416</b>
lstopp (fortran variable in module horizontal_data), 230	mapdatamag() (fortran subroutine in module readcheck-
lstoremov (fortran variable in module movie_data), 351	points), <b>417</b>
lstressmem (fortran variable in module truncation), 181	mapdatar() (fortran subroutine in module readcheck-
ltimelimit() (fortran function in module timing), 238	points), <b>418</b>
lvdissmean (fortran variable in module output_mod), 321	maponefield() (fortran subroutine in module readcheck-
lverbose (fortran variable in module logic), 191	points), <b>416</b>
lwpmat (fortran variable in module updatewp_mod), 249 lwpsmat (fortran variable in module updatewps_mod),	mass (fortran variable in module constants), <b>204</b> matder() (in module magic.libmagic), 173
243	maxthreads (fortran variable in module updateb_mod),
lwptmat (fortran variable in module updatewpt_mod), 246	261
lximat (fortran variable in module updatexi_mod), 259	maxthreads (fortran variable in module updates_mod),
lz10mat (fortran variable in module updatez_mod), 253	256
lzmat (fortran variable in module updatez_mod), 253	maxthreads (fortran variable in module updatewp_mod), 249
M	maxthreads (fortran variable in module updatewps_mod),
m_max (fortran variable in module truncation), 182	243
m_max_modes (fortran variable in module output_data), 201	maxthreads (fortran variable in module updatewpt_mod), 246
m_riicasym (fortran variable in module special), 205	maxthreads (fortran variable in module updatexi_mod),
m_riicsym (fortran variable in module special), 205	259
m_rimaasym (fortran variable in module special), 205	maxthreads (fortran variable in module updatez_mod),
m_rimasym (fortran variable in module special), 205	253
mag2hint (fortran variable in module rms), 372	meantime() (fortran subroutine in module timing), 239
magic (fortran program), 177	mem_alloc (module), 424
magic.bLayers (module), 160	memory_file (fortran variable in module mem_alloc), 424
magic.coeff (module), 147	

memwrite() (fortran subroutine in module mem_alloc), 424	n_cmb_setsmov (fortran variable in module output_mod) 321
merContour() (in module magic.plotlib), 170 minc (fortran variable in module truncation), <b>181</b> mode (fortran variable in module physical_parameters),	n_cmb_step (fortran variable in module output_data), 200 n_cmbmov_file (fortran variable in module output_mod) 320
movfile (fortran variable in module outto_mod), 395	n_cmbs (fortran variable in module output_data), 201 n_coeff_r (fortran variable in module output_data), 201
Movie (class in magic), 144 movie (fortran variable in module movie_data), <b>351</b>	n_coeff_r_max (fortran variable in module output_data) 202
Movie3D (class in magic), 146 movie_const (fortran variable in module movie_data),	n_compliance_file (fortran variable in module magnetic_energy), 327
351	n_cour_step (fortran variable in module num_param), 184
movie_data (module), 350	n_dipole_file (fortran variable in module mag
movie_file (fortran variable in module movie_data), 351	netic_energy), 327
movie_gather_frames_to_rank0() (fortran subroutine in	n_driftbd_file (fortran variable in module outrot), 334
module movie_data), 356 movieCmb() (magic.coeff.MagicCoeffCmb method), 148	n_driftbq_file (fortran variable in module outrot), 334 n_driftvd_file (fortran variable in module outrot), 334
moviedipcolat (fortran variable in module movie_data),	n_driftvq_file (fortran variable in module outrot), 334
351	n_dt_cmb_file (fortran variable in module output_mod)
moviediplon (fortran variable in module movie_data), 351	321
moviedipstrength (fortran variable in module movie_data), 351	n_dt_cmb_sets (fortran variable in module output_mod) 321
moviedipstrengthgeo (fortran variable in module	n_dtbrms_file (fortran variable in module rms), 372
movie_data), <b>351</b> movieRad() (magic.coeff.MagicCoeffR method), 149	n_dte_file (fortran variable in module output_mod), 320
mpi_def_complex (fortran variable in module preci-	n_dtvrms_file (fortran variable in module rms), 371 n_e_kin_file (fortran variable in module kinetic_energy)
sion_mod), 180	324
mpi_def_real (fortran variable in module precision_mod),  180	n_e_mag_ic_file (fortran variable in module magnetic_energy), 327
mpi_out_real (fortran variable in module precision_mod),  180	n_e_mag_oc_file (fortran variable in module mag netic_energy), 327
ms2time() (fortran subroutine in module timing), 238	n_e_sets (fortran variable in module output_mod), 321
msechour (fortran variable in module timing), 237 msecminute (fortran variable in module timing), 237	n_frame_work (fortran variable in module movie_data) 350
msecsecond (fortran variable in module timing), 237	n_geos_file (fortran variable in module geos_mod), 400
mvar (fortran variable in module outpar_mod), 338	n_graph_file (fortran variable in module output_data)
myallgather() (fortran subroutine in module communica-	201
tions), <b>214</b>	n_graph_step (fortran variable in module output_data) 200
N	n_graphs (fortran variable in module output_data), 199
n_am_kpol_file (fortran variable in module spectra), 343	n_heat_file (fortran variable in module outmisc_mod)
n_am_ktor_file (fortran variable in module spectra), 344	331
n_am_mpol_file (fortran variable in module spectra), 343	n_helicity_file (fortran variable in module outmisc_mod) 331
n_am_mtor_file (fortran variable in module spectra), 343	n_imp (fortran variable in module special), 206
n_angular_file (fortran variable in module outrot), 334 n_b_r_file (fortran variable in module output_mod), 322	n_imps (fortran variable in module physical_parameters)
n_b_r_sets (fortran variable in module output_mod), 321	186
n_bpot_step (fortran variable in module output_data), 202	n_imps_max (fortran variable in module physi-
n_bpots (fortran variable in module output_data), 200	cal_parameters), 188
n_cheb_ic_max (fortran variable in module truncation),	n_impxi (fortran variable in module physi-
181	cal_parameters), 186
n_cheb_max (fortran variable in module truncation), 183	n_impxi_max (fortran variable in module physi-
n_cheb_maxc (fortran variable in module rms), 372	cal_parameters), 190 n inerp file (fortran variable in module outrot), 334
n com the corran variable in modille ollinit mod) 422	ii merp ine (101tran variable in mount outlot). 334

n_inert_file (fortran variable in module outrot), 334	202
n_kin_spec_file (fortran variable in module spectra), 343	n_probe_step (fortran variable in module output_data),
n_log_file (fortran variable in module output_data), 200	201
n_log_step (fortran variable in module output_data), 200	n_procs (fortran variable in module parallel_mod), 206
n_logs (fortran variable in module output_data), 201	n_r_array (fortran variable in module output_data), 200
n_lscale (fortran variable in module num_param), 184	n_r_cmb (fortran variable in module radial_data), 207
n_m_max (fortran variable in module truncation), 182	n_r_field_step (fortran variable in module output_data),
n_mag_spec_file (fortran variable in module spectra), 344	202
n_md (fortran variable in module movie_data), 351	n_r_fields (fortran variable in module output_data), 202
n_memory_file (fortran variable in module mem_alloc),	n_r_ic_max (fortran variable in module truncation), <b>181</b>
424	n_r_ic_max_dtb (fortran variable in module truncation),
n_movie_const (fortran variable in module movie_data),	181
351	n_r_ic_maxmag (fortran variable in module truncation),
n_movie_field_start (fortran variable in module	182
movie_data), 350	n_r_icb (fortran variable in module radial_data), 207
n_movie_field_stop (fortran variable in module	n_r_ler (fortran variable in module physical_parameters),
movie_data), 350	189
n_movie_field_type (fortran variable in module	n_r_max (fortran variable in module truncation), 182
movie_data), 351	n_r_max_dtb (fortran variable in module truncation), 183
n_movie_fields (fortran variable in module movie_data),	n_r_maxc (fortran variable in module rms), 373
351	n_r_maxmag (fortran variable in module truncation), <b>181</b>
n_movie_fields_ic (fortran variable in module	n_r_maxstr (fortran variable in module truncation), 182
movie_data), 351	n_r_step (fortran variable in module output_data), 199
n_movie_fields_max (fortran variable in module	n_r_tot (fortran variable in module truncation), <b>182</b>
movie_data), 351	n_r_totmag (fortran variable in module truncation), 183
n_movie_file (fortran variable in module movie_data),	n_ranks_print (fortran variable in module mem_alloc),
351	424
n_movie_frames (fortran variable in module out-	n_rot_file (fortran variable in module outrot), 334
put_data), <b>200</b>	n_rst_step (fortran variable in module output_data), 201
n_movie_step (fortran variable in module output_data),	n_rsts (fortran variable in module output_data), 201
202	n_s_bounds (fortran variable in module init_fields), 219
n_movie_surface (fortran variable in module	n_spec (fortran variable in module output_mod), 322
in_movie_surface (fortial) variable in module	ii_spec (fortrail variable in module output_mod), 322
movie_data), 350	n_spec_step (fortran variable in module output_mod), 322  n_spec_step (fortran variable in module output_data), 202
movie_data), 350	n_spec_step (fortran variable in module output_data), 202
movie_data), 350 n_movie_type (fortran variable in module movie_data),	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200
movie_data), 350 n_movie_type (fortran variable in module movie_data), 351	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334
movie_data), <b>350</b> n_movie_type (fortran variable in module movie_data), <b>351</b> n_movies (fortran variable in module movie_data), <b>350</b> n_movies_max (fortran variable in module movie_data),	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints),
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod),	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod),	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 201
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 202 n_t_movie (fortran variable in module output_data), 201
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module mag-	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 202 n_t_movie (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module mag-netic_energy), 327	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 202 n_t_movie (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 200 n_t_probe (fortran variable in module output_data), 200
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module magnetic_energy), 327  n_phi_maxstr (fortran variable in module truncation), 181	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 201 n_t_movie (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_r_field (fortran variable in module output_data), 201
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module magnetic_energy), 327  n_phi_maxstr (fortran variable in module truncation), 181  n_phi_probes (fortran variable in module probe_mod),	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_r_field (fortran variable in module output_data), 201 n_t_r_field (fortran variable in module output_data), 202 n_t_r_file (fortran variable in module output_mod), 321
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module magnetic_energy), 327  n_phi_maxstr (fortran variable in module truncation), 181  n_phi_probes (fortran variable in module probe_mod), 412	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_r_field (fortran variable in module output_data), 202 n_t_r_file (fortran variable in module output_mod), 321 n_t_r_sets (fortran variable in module output_mod), 321
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module magnetic_energy), 327  n_phi_maxstr (fortran variable in module truncation), 181  n_phi_probes (fortran variable in module probe_mod), 412  n_phi_tot (fortran variable in module truncation), 182	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 202 n_t_movie (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_r_file (fortran variable in module output_data), 202 n_t_r_file (fortran variable in module output_mod), 321 n_t_r_sets (fortran variable in module output_data), 202
movie_data), 350  n_movie_type (fortran variable in module movie_data), 351  n_movies (fortran variable in module movie_data), 350  n_movies_max (fortran variable in module movie_data), 351  n_out_probes (fortran variable in module probe_mod), 411  n_par_file (fortran variable in module output_mod), 320  n_perppar_file (fortran variable in module outpar_mod), 338  n_phi_max (fortran variable in module truncation), 183  n_phi_max_comp (fortran variable in module magnetic_energy), 327  n_phi_maxstr (fortran variable in module truncation), 181  n_phi_probes (fortran variable in module probe_mod), 412  n_phi_tot (fortran variable in module truncation), 182  n_pot_step (fortran variable in module output_data), 202	n_spec_step (fortran variable in module output_data), 202 n_specs (fortran variable in module output_data), 200 n_sric_file (fortran variable in module outrot), 334 n_srma_file (fortran variable in module outrot), 334 n_start_file (fortran variable in module readcheckpoints), 413 n_stores (fortran variable in module output_data), 201 n_t_bpot (fortran variable in module output_data), 200 n_t_cmb (fortran variable in module output_data), 199 n_t_graph (fortran variable in module output_data), 201 n_t_log (fortran variable in module output_data), 202 n_t_movie (fortran variable in module output_data), 201 n_t_pot (fortran variable in module output_data), 201 n_t_probe (fortran variable in module output_data), 201 n_t_r_field (fortran variable in module output_data), 202 n_t_r_sets (fortran variable in module output_mod), 321 n_t_rsets (fortran variable in module output_data), 202 n_t_spec (fortran variable in module output_data), 202

n_t_toz (fortran variable in module output_data), 199	nfs (fortran variable in module blocking), 314
n_t_tpot (fortran variable in module output_data), 202	ni (fortran variable in module fft), 298
n_t_vpot (fortran variable in module output_data), 201	nl_special_calc (module), 406
n_temp_spec_file (fortran variable in module spectra),	nlmbs (fortran variable in module blocking), 314
343	nlmbs2 (fortran variable in module blocking), 314
n_theta_axi (fortran variable in module truncation), 182	nlmbs_per_rank (fortran variable in module paral-
n_theta_cal2ord (fortran variable in module horizon-	lel_mod), 207
tal_data), 231	nlogs (fortran variable in module output_mod), 321
n_theta_max (fortran variable in module truncation), 181	nonlinear_bcs (module), 278
n_theta_max_comp (fortran variable in module mag-	nonlinear_lm_mod (module), 275
netic_energy), 327	npvsets (fortran variable in module output_mod), 321
n_theta_maxstr (fortran variable in module truncation), 182	nr_on_last_rank (fortran variable in module paral- lel_mod), <b>206</b>
n_theta_usr (fortran variable in module probe_mod), 411	nr_per_rank (fortran variable in module parallel_mod),
n_time_hits (fortran variable in module output_data), 199	207
n_time_steps (fortran variable in module num_param),	nrms_sets (fortran variable in module output_mod), 322
184	nrotic (fortran variable in module init_fields), 220
n_to_step (fortran variable in module output_data), 200	nrotma (fortran variable in module init_fields), 220
n_tomovie_frames (fortran variable in module out-	nrp (fortran variable in module truncation), 182
put_data), <b>201</b>	nrstart (fortran variable in module radial_data), 207
n_tomovie_step (fortran variable in module output_data),	nrstartmag (fortran variable in module radial_data), 207
201	nrstop (fortran variable in module radial_data), 207
n_tos (fortran variable in module output_data), 201	nrstopmag (fortran variable in module radial_data), 207
n_toz_step (fortran variable in module output_data), 202	ns_on_last_rank (fortran variable in module geos_mod),
n_tozs (fortran variable in module output_data), 199	400
n_tpot_step (fortran variable in module output_data), 199	ns_on_last_rank (fortran variable in module outto_mod),
n_tpots (fortran variable in module output_data), 199	395
n_tscale (fortran variable in module num_param), 185	ns_per_rank (fortran variable in module geos_mod), 400
n_u2_spec_file (fortran variable in module spectra), 343	ns_per_rank (fortran variable in module outto_mod), 395
n_u_square_file (fortran variable in module ki-	nsmax (fortran variable in module geos_mod), 400
netic_energy), 325	nsmax (fortran variable in module omega), 405
n_v_r_file (fortran variable in module output_mod), 321	nsmax (fortran variable in module outto_mod), 396
n_v_r_sets (fortran variable in module output_mod), 321	nsstart (fortran variable in module geos_mod), 400
n_vpot_step (fortran variable in module output_data), 201	nsstart (fortran variable in module outto_mod), 396
n_vpots (fortran variable in module output_data), 201	nsstop (fortran variable in module geos_mod), 400
n_xi_bounds (fortran variable in module init_fields), 220	nsstop (fortran variable in module outto_mod), 395
nalias (fortran variable in module truncation), 182	nthetabs (fortran variable in module blocking), 314
namelists (module), 214	nthreads (fortran variable in module parallel_mod), 206
nbdown (fortran variable in module blocking), 314	ntomovsets (fortran variable in module output_mod), 321
nbpotsets (fortran variable in module output_mod), 320	ntormssets (fortran variable in module output_mod), 321
nbsave (fortran variable in module blocking), 313	ntosets (fortran variable in module output_mod), 320
ncp (fortran variable in module truncation), 182	ntozfile (fortran variable in module outto_mod), 396
ncut (fortran variable in module rms), 371	ntpotsets (fortran variable in module output_mod), 320
nd (fortran variable in module fft), 298	num_param (module), 183
ndd_costf1 (fortran variable in module radial_functions),	nvarcond (fortran variable in module physi-
227	cal_parameters), 189
ndd_costf1_ic (fortran variable in module ra- dial_functions), 228	nvardiff (fortran variable in module physical_parameters), 189
ndd_costf2_ic (fortran variable in module ra-	nvarentropygrad (fortran variable in module physi-
dial_functions), 228	cal_parameters), 187
ndi_costf1_ic (fortran variable in module ra-	nvareps (fortran variable in module physical_parameters),
dial_functions), 227	187
ndi_costf2_ic (fortran variable in module ra-	nvarvisc (fortran variable in module physi-
dial functions), 227	cal parameters), 188

nvpotsets (fortran variable in module output_mod), 321 nz2 (fortran variable in module geos_mod), 400 nzc (fortran variable in module geos_mod), 400 nzc_sloc (fortran variable in module geos_mod), 400 nzmaxa (fortran variable in module geos_mod), 400 nzmaxa (fortran variable in module outto_mod), 395 nzmaxs (fortran variable in module outto_mod), 395 nzmaxs (fortran variable in module outto_mod), 395 nzmaxs_sloc (fortran variable in module outto_mod), 395	osints (fortran variable in module geos_mod), 400 osints (fortran variable in module outto_mod), 395 osintspv (fortran variable in module geos_mod), 400 osn1 (fortran variable in module horizontal_data), 230 osn2 (fortran variable in module horizontal_data), 230 osq4pi (fortran variable in module constants), 203 otemp1 (fortran variable in module radial_functions), 226 out_coeff (module), 364 out_dtb_frame (module), 384
Ο	out_movie (module), 356 out_movie_ic (module), 362
o_r_ic (fortran variable in module radial_functions), 226 o_r_ic2 (fortran variable in module radial_functions), 228 o_sin_theta (fortran variable in module horizontal_data), 230	outheat() (fortran subroutine in module outmisc_mod), 332 outhelicity() (fortran subroutine in module outmisc_mod), 332
o_sin_theta_e2 (fortran variable in module horizon-	outmisc_mod (module), 330
tal_data), 231 o_sr (fortran variable in module physical_parameters), 189	outomega() (fortran subroutine in module omega), 406 outp (fortran variable in module precision_mod), 180 outpar() (fortran subroutine in module outpar_mod), 338
oek (fortran variable in module physical_parameters), 189 ogrun (fortran variable in module radial_functions), 226 ohmdissr (fortran variable in module power), 340	outpar_mod (module), 336 outperppar() (fortran subroutine in module outpar_mod), 339
ohmlossfac (fortran variable in module physi-	output() (fortran subroutine in module nonlinear_lm_mod), 277
cal_parameters), 187 omega (module), 405	output() (fortran subroutine in module output_mod), 322
omega_diff (fortran variable in module init_fields), 219	output_data (module), 198
omega_ic (fortran variable in module fields), 197	output_mod (module), 318
omega_ic1 (fortran variable in module init_fields), 219	outpv() (fortran subroutine in module geos_mod), 402
omega_ic2 (fortran variable in module init_fields), 220	outrot (module), 333
omega_ma (fortran variable in module fields), 196	outto() (fortran subroutine in module outto_mod), 396
omega_ma1 (fortran variable in module init_fields), 220	outto_allgather_rloc() (fortran subroutine in module
omega_ma2 (fortran variable in module init_fields), 220	outto_mod), 397
omega_riicasym (fortran variable in module special), 205	outto_mod (module), 393
omega_riicsym (fortran variable in module special), 205	P
omega_rimaasym (fortran variable in module special),	
205 omega_rimasym (fortran variable in module special), 205	p0mat (fortran variable in module updatewp_mod), 249 p0pivot (fortran variable in module updatewp_mod), 250
omegaosz_ic1 (fortran variable in module init_fields), 219 omegaosz_ic2 (fortran variable in module init_fields), 219	p_ave (fortran variable in module fields_average_mod),  368
omegaosz_ma1 (fortran variable in module init_fields),	p_ave_global (fortran variable in module
220	fields_average_mod), 368
omegaosz_ma2 (fortran variable in module init_fields),	p_lmloc (fortran variable in module fields), 196
220	p_rloc (fortran variable in module fields), 195
one (fortran variable in module constants), 203	padvlm (fortran variable in module dtb_mod), 380
opm (fortran variable in module physical_parameters),	padvlm_lmloc (fortran variable in module dtb_mod), 380
188	padvlm_rloc (fortran variable in module dtb_mod), 380
opr (fortran variable in module physical_parameters), <b>189</b> or1 (fortran variable in module radial_functions), <b>226</b>	padvlmic (fortran variable in module dtb_mod), 380 padvlmic_lmloc (fortran variable in module dtb_mod),
or2 (fortran variable in module radial_functions), 226	380
or3 (fortran variable in module radial_functions), 226	par_file (fortran variable in module output_mod), 321
or4 (fortran variable in module radial_functions), 226	parallel() (fortran subroutine in module parallel_mod),
orho1 (fortran variable in module radial_functions), 227	207
orho2 (fortran variable in module radial_functions), 228	parallel_mod (module), 206
osc (fortran variable in module physical_parameters), 187	pdiflm (fortran variable in module dtb_mod), 380

pdiflm_lmloc (fortran variable in module dtb_mod), 380 pdiflmic (fortran variable in module dtb_mod), 380	po_diff (fortran variable in module physical_parameters), 188
pdiflmic_lmloc (fortran variable in module dtb_mod), 380 peaks (fortran variable in module physical_parameters),	polind (fortran variable in module physical_parameters), 188
189	polo_flow_eq (fortran variable in module num_param),
peakxi (fortran variable in module physical_parameters), 187	184 polynomial_interpolation() (fortran subroutine in module
perppar_file (fortran variable in module outpar_mod), 338	useful), 423
phi (fortran variable in module horizontal_data), 230	polynomial_interpolation_real() (fortran subroutine in
phideravg() (in module magic.libmagic), 174	module useful), 423
phis (fortran variable in module physical_parameters), 190	polynomialbackground() (fortran subroutine in module radial_functions), 229
phixi (fortran variable in module physical_parameters),	power (module), 339
190	power_file (fortran variable in module power), 340
physical_parameters (module), 186	pr (fortran variable in module physical_parameters), 187
pi (fortran variable in module constants), 203	pre (fortran variable in module updatewp_mod), 249
plf2hint (fortran variable in module rms), 372	pre (fortran variable in module updatewps_mod), 243
plfrmsl_sd (fortran variable in module rms), 371	pre (fortran variable in module updatewpt_mod), 246
plfrmsl_ta (fortran variable in module rms), 371	pre2hint (fortran variable in module rms), 373
plfrmssd (fortran variable in module rms), 371	prec_angle (fortran variable in module physi-
plm (fortran variable in module horizontal_data), 231	cal_parameters), 188
plm_comp (fortran variable in module magnetic_energy),	precalc() (fortran subroutine in module precalculations),
327	224
$\begin{array}{c} plm\_theta() \ (fortran \ subroutine \ in \ module \ plms\_theta), \\ \hline 286 \end{array}$	precalctimes() (fortran subroutine in module precalculations), 224
plms (fortran variable in module geos_mod), 400	precalculations (module), 223
plms (fortran variable in module outto_mod), 395	precision_mod (module), 180
plms_theta (module), 286	prermsl_sd (fortran variable in module rms), 372
plmspv (fortran variable in module geos_mod), 401	prermsl_ta (fortran variable in module rms), 372
plmz (fortran variable in module geos_mod), 400	prermssd (fortran variable in module rms), 371
plot() (magic.bLayers.BLayers method), 160	prmag (fortran variable in module physical_parameters),
plot() (magic.Butterfly method), 167	188
plot() (magic.coeff.MagicCoeffCmb method), 148	probe_file (fortran variable in module probe_mod), 412
plot() (magic.MagicPV method), 155	probe_mod (module), 411
plot() (magic.MagicRadial method), 138	<pre>probe_out() (fortran subroutine in module probe_mod),</pre>
plot() (magic.MagicSpectrum method), 139	412
plot() (magic.MagicSpectrum2D method), 140	progressbar() (in module magic.libmagic), 174
plot() (magic.MagicTaySphere method), 155	ps0mat (fortran variable in module updatewps_mod), 243
plot() (magic.MagicTOHemi method), 155	ps0mat_fac (fortran variable in module updatewps_mod),
plot() (magic.MagicTs method), 137	243
plot() (magic.Movie method), 146	ps0pivot (fortran variable in module updatewps_mod),
plot() (magic.ThetaHeat method), 162	243
plot() (magic.TOMovie method), 154	ps_cond() (fortran subroutine in module init_fields), 223
plotAvg() (magic.CompSims method), 156	pscale (fortran variable in module num_param), 185
plotAvg() (magic.MagicRSpec method), 151	pstrlm (fortran variable in module dtb_mod), 380
plotEmag() (magic.CompSims method), 156	pstrlm_lmloc (fortran variable in module dtb_mod), 379
plotEquat() (magic.CompSims method), 157	pstrlm_rloc (fortran variable in module dtb_mod), 380
plotFlux() (magic.CompSims method), 157	pt0mat (fortran variable in module updatewpt_mod), 246
plotSurf() (magic.CompSims method), 157	pt0mat_fac (fortran variable in module updatewpt_mod),
plotTs() (magic.CompSims method), 157	246
plotZonal() (magic.CompSims method), 157	pt0pivot (fortran variable in module updatewpt_mod), 246
pmeanr (fortran variable in module outmisc_mod), 331	pt_cond() (fortran subroutine in module init_fields), 222
po (fortran variable in module physical_parameters), 188	

R	radialloopg() (fortran subroutine in module radialloop)
r (fortran variable in module radial_functions), <b>226</b> r2lm_redist_start() (fortran subroutine in module commu-	264 radratio (fortran variable in module physical_parameters)
nications), 213	187
r2lm_redist_wait() (fortran subroutine in module communications), 213	random() (fortran function in module useful), <b>421</b> rank_bn (fortran variable in module parallel_mod), <b>206</b>
r2lo_b (fortran variable in module communications), <b>211</b> r2lo_dtb (fortran variable in module dtb_mod), <b>380</b>	rank_with_11m0 (fortran variable in module paral- lel_mod), <b>206</b>
r2lo_flow (fortran variable in module communications), 210	ranks_selected (fortran variable in module mem_alloc) 424
r2lo_redist_start() (fortran subroutine in module communications), 213	rascaled (fortran variable in module physical_parameters), 188
r2lo_redist_wait() (fortran subroutine in module communications), 214	raxi (fortran variable in module physical_parameters)  188
r2lo_s (fortran variable in module communications), 210	rbpspec() (fortran subroutine in module radial_spectra) 398
r2lo_xi (fortran variable in module communications), 210 r_cmb (fortran variable in module radial_functions), 228	rbrspec() (fortran subroutine in module radial_spectra)
r_cut_model (fortran variable in module physi-	398
cal_parameters), 190	rc (fortran variable in module rms), 372
r_ic (fortran variable in module radial_functions), 227	rcut (fortran variable in module output_data), 202 rdea (fortran variable in module output_data), 202
r_icb (fortran variable in module radial_functions), 228	rderavg() (in module magic.libmagic), 174
r_lcr (fortran variable in module physical_parameters), 188	readcheckpoints (module), 412
r_lm_gather_type (fortran variable in module communications), 210	readnamelists() (fortran subroutine in module namelists) 215
r_lm_gather_type_lm_end (fortran variable in module	readstartfields() (fortran subroutine in module readcheck
communications), 211	points), <b>415</b>
r_probe (fortran variable in module probe_mod), 411	readstartfields_old() (fortran subroutine in module read-
r_request (fortran variable in module communications),	checkpoints), 414 rearangeLat() (in module magic.coeff), 150
210	rearangeLat() (magic.MagicGraph method), 140
r_surface (fortran variable in module radial_functions), 227	rgrav (fortran variable in module radial_functions), 227
r_transfer_type (fortran variable in module communications), $210$	rho0 (fortran variable in module radial_functions), 226 rho_ratio_ic (fortran variable in module physi-
r_transfer_type_cont (fortran variable in module communications), <b>210</b>	cal_parameters), 187 rho_ratio_ma (fortran variable in module physi-
r_transfer_type_nr_end (fortran variable in module com-	cal_parameters), 187 rhs1 (fortran variable in module updateb_mod), 261
munications), 211	rhs1 (fortran variable in module updates_mod), 256
r_transfer_type_nr_end_cont (fortran variable in module communications), 210	rhs1 (fortran variable in module updatewp_mod), 250
ra (fortran variable in module physical_parameters), 189	rhs1 (fortran variable in module updatewps_mod), 243
rad_rank (fortran variable in module probe_mod), 411	rhs1 (fortran variable in module updatewpt_mod), 246
rad_usr (fortran variable in module probe_mod), 411	rhs1 (fortran variable in module updatexi_mod), 259
radial() (fortran subroutine in module radial_functions),	rhs1 (fortran variable in module updatez_mod), 253
228	rhs2 (fortran variable in module updateb_mod), 261
radial_data (module), 207	rint_r() (fortran function in module integration), 312
radial_der (module), 304	rintic() (fortran function in module integration), 312
radial_der_even (module), 308	riteration_mod (module), 266
radial_functions (module), 225	riterthetablocking_mod (module), 268 riterthetablocking_openmp_mod (module), 270
radial_scheme (fortran variable in module truncation),	rmmean (fortran variable in module output_mod), 321
182	rmmeanr (fortran variable in module output_mod), 321
radial_spectra (module), 397	rms (module), 369
radialContour() (in module magic.plotlib), 170 radialloop (module), <b>264</b>	rms_helpers (module), 374
	=

rolmean (fortran variable in module output_mod), 320 rolmeanr (fortran variable in module outpar_mod), 338	sendvals_to_rank0() (fortran subroutine in module outrot), 336
rolmeanru2 (fortran variable in module outpar_mod), 337 rot_file (fortran variable in module outrot), 334	set_steering_variables() (fortran subroutine in module riteration_mod), <b>267</b>
rrmp (fortran variable in module special), <b>206</b> rstrat (fortran variable in module physical_parameters),	set_thetablocking() (fortran subroutine in module riter-thetablocking_mod), 269
187	set_zero() (fortran subroutine in module
rstrm (fortran variable in module outto_mod), 395	dtb_arrays_mod), 384
rstrm_sloc (fortran variable in module outto_mod), 395	set_zero() (fortran subroutine in module nonlin-
runid (fortran variable in module output_data), 199	ear_lm_mod), 277
runtime (fortran variable in module num_param), 185 runtimelimit (fortran variable in module num_param),	set_zero() (fortran subroutine in module to_arrays_mod), 393
184	sgefa() (fortran subroutine in module algebra), 304
runtimestart (fortran variable in module num_param), 185	sgesl() (fortran subroutine in module algebra), 303
rz (fortran variable in module geos_mod), 401	sigfile (fortran variable in module step_time_mod), 234
rz (fortran variable in module outto_mod), 395	sigma (fortran variable in module radial_functions), 228
rzpv (fortran variable in module geos_mod), 400	sigma_ratio (fortran variable in module physi-
S	cal_parameters), 186
	sin36 (fortran variable in module constants), 204 sin60 (fortran variable in module constants), 203
s0mat (fortran variable in module updates_mod), 256	sin72 (fortran variable in module constants), 203
s0mat_fac (fortran variable in module updates_mod), 256	sintheta (fortran variable in module horizontal_data), 231
sOpivot (fortran variable in module updates_mod), 256	sizelmb (fortran variable in module blocking), 314
s_ave (fortran variable in module fields_average_mod), 368	sizelmb2 (fortran variable in module blocking), 314
s_ave_global (fortran variable in module	sizeof_character (fortran variable in module preci-
fields_average_mod), 368	sion_mod), 180
s_bot (fortran variable in module init_fields), 219	sizeof_def_complex (fortran variable in module preci-
s_lmloc (fortran variable in module fields), 196	sion_mod), 180
s_lmloc_container (fortran variable in module fields), 196	sizeof_def_real (fortran variable in module preci-
s_request (fortran variable in module communications),	sion_mod), 180
210	sizeof_integer (fortran variable in module preci-
s_rloc (fortran variable in module fields), 196	sion_mod), 180
s_rloc_container (fortran variable in module fields), 195	sizeof_logical (fortran variable in module preci-
s_top (fortran variable in module init_fields), 220	sion_mod), 180
s_transfer_type (fortran variable in module communications), 210	sizeof_out_real (fortran variable in module precision_mod), 180
s_transfer_type_cont (fortran variable in module communications), 210	sizethetab (fortran variable in module blocking), 314 sizethetabi (fortran variable in module blocking), 314
s_transfer_type_nr_end (fortran variable in module com- munications), 211	slice() (magic.cyl.Cyl method), 164 slice() (magic.Surf method), 142
s_transfer_type_nr_end_cont (fortran variable in module	slopestrat (fortran variable in module physi-
communications), 210	cal_parameters), 188
sc (fortran variable in module physical_parameters), 189	smat (fortran variable in module updates_mod), 256 smat_fac (fortran variable in module updates_mod), 256
scale_b (fortran variable in module init_fields), 219	smeanr (fortran variable in module outmisc_mod), 331
scale_s (fortran variable in module init_fields), 219	smeanr (fortran variable in module outpar_mod), 338
scale_v (fortran variable in module init_fields), 220	sn2 (fortran variable in module horizontal_data), 230
scale_xi (fortran variable in module init_fields), <b>219</b> scanDir() (in module magic.libmagic), 174	sn_sub_map (fortran variable in module blocking), 314
scatter_from_rank0_to_lo() (fortran subroutine in module	spat_spec() (magic.spectralTransforms.SpectralTransforms
communications), 212	method), 167
sdens (fortran variable in module output_data), 199	$spec\_spat()  (magic.spectral Transforms. Spectral Transforms$
sderavg() (in module magic.libmagic), 175	method), 168
selectField() (in module magic.libmagic), 175	spec_spat_dphi() (magic.spectralTransforms.SpectralTransforms method), 168

spec_spat_dtheta() (magic.spectralTransforms.SpectralTransforms.	
method), 168	surf() (magic.MagicPotential method), 153
spec_spat_equat() (magic.spectralTransforms.SpectralTransforms.	
method), 168	surf_cmb (fortran variable in module constants), 203 svar (fortran variable in module outpar_mod), 338
special (module), 204	
spectra (module), 342 SpectralTransforms (class in magic.spectralTransforms),	symmetrize() (in module magic.libmagic), 175
167	T
spectrum() (fortran subroutine in module spectra), 344	
spectrum_average() (fortran subroutine in module spec-	t2_ave (fortran variable in module spectra), 344
tra), 344	t_ave (fortran variable in module spectra), 343
spectrum_temp() (fortran subroutine in module spectra),	t_bpot (fortran variable in module output_data), 202 t_bpot_start (fortran variable in module output_data), 199
345	t_bpot_stop (fortran variable in module output_data), 202
spectrum_temp_average() (fortran subroutine in module	t_cmb (fortran variable in module output_data), 200
spectra), 345	t_cmb_start (fortran variable in module output_data), 200
sph2cart_scal() (in module magic.graph2vtk), 158	t_cmb_stop (fortran variable in module output_data), 201
sph2cart_vec() (in module magic.graph2vtk), 158	t_graph (fortran variable in module output_data), 200
sph2cyl() (in module magic.cyl), 164	t_graph_start (fortran variable in module output_data),
sph2cyl_plane() (in module magic.cyl), 165	200
spivot (fortran variable in module updates_mod), 256	t_graph_stop (fortran variable in module output_data),
sq4pi (fortran variable in module constants), 204	202
sric_file (fortran variable in module outrot), 334	t_icb2_ave (fortran variable in module spectra), 343
srma_file (fortran variable in module outrot), 334	t_icb_ave (fortran variable in module spectra), 343
st_map (fortran variable in module blocking), 314	t_log (fortran variable in module output_data), 202
st_sub_map (fortran variable in module blocking), 314	t_log_start (fortran variable in module output_data), 201
start_fields (module), 216	t_log_stop (fortran variable in module output_data), 200
start_file (fortran variable in module init_fields), 221	t_movie (fortran variable in module output_data), 202
step_time() (fortran subroutine in module	t_movie_start (fortran variable in module output_data),
step_time_mod), 235	199
step_time_mod (module), 232	t_movie_stop (fortran variable in module output_data),
store() (fortran subroutine in module storecheckpoints),	202
419	t_movies (fortran variable in module movie_data), 351
store_fields_3d() (fortran subroutine in module	t_pot (fortran variable in module output_data), 202
out_movie), 361 store_fields_p() (fortran subroutine in module	t_pot_start (fortran variable in module output_data), 201
store_fields_p() (fortran subroutine in module out_movie), 359	t_pot_stop (fortran variable in module output_data), 202
store_fields_r() (fortran subroutine in module out_movie),	t_probe (fortran variable in module output_data), 200
358	t_probe_start (fortran variable in module output_data), 200
store_fields_sur() (fortran subroutine in module	t_probe_stop (fortran variable in module output_data),
out_movie), <b>358</b>	202
store_fields_t() (fortran subroutine in module out_movie),	t_r_field (fortran variable in module output_data), 202
360	t_r_field_start (fortran variable in module output_data),
store_movie_frame() (fortran subroutine in module	201
out_movie), 357	t_r_field_stop (fortran variable in module output_data),
store_movie_frame_ic() (fortran subroutine in module	200
out_movie_ic), 363	t_r_file (fortran variable in module output_mod), 320
storecheckpoints (module), 418	t_rst (fortran variable in module output_data), 200
str2dble() (fortran subroutine in module charmanip), 426	t_rst_start (fortran variable in module output_data), 199
strat (fortran variable in module physical_parameters), 186	t_rst_stop (fortran variable in module output_data), 199
strm (fortran variable in module outto_mod), 396	t_spec (fortran variable in module output_data), 201
strm_sloc (fortran variable in module outto_mod), 396	t_spec_start (fortran variable in module output_data), 202
subtime() (fortran subroutine in module timing), 238	t_spec_stop (fortran variable in module output_data), 201
Surf (class in magic), 141	t_to (fortran variable in module output_data), 201 t to start (fortran variable in module output_data), 200

timeave (fortran variable in module outto_mod), 395 timelast (fortran variable in module outto_mod), 395
timeLongitude() (magic.coeff.MagicCoeffCmb method) 148
timeLongitude() (magic.Movie method), 146
timenormlog (fortran variable in module output_mod) 321
timenormrms (fortran variable in module output_mod) 321
timeold (fortran variable in module geos_mod), 400
timepassedlog (fortran variable in module output_mod)
320
timepassedrms (fortran variable in module output_mod)
322
timestart (fortran variable in module num_param), 184
timing (module), 237
tipdipole (fortran variable in module init_fields), 220
tmagcon (fortran variable in module physical_parameters), 188
tmeanr (fortran variable in module outmisc_mod), 331
to_arrays_mod (module), 393
to_helpers (module), 391
tofilenhs (fortran variable in module outto_mod), 396
tofileshs (fortran variable in module outto_mod), 396
tomega_ic1 (fortran variable in module init_fields), 220
tomega_ic2 (fortran variable in module init_fields), 220
tomega_ma1 (fortran variable in module init_fields), 219
tomega_ma2 (fortran variable in module init_fields), 219
tomelm (fortran variable in module dtb_mod), 380
tomelm_lmloc (fortran variable in module dtb_mod), 380
tomelm_rloc (fortran variable in module dtb_mod), 380
tomerlm_lmloc (fortran variable in module dtb_mod), 379
tomerlm_rloc (fortran variable in module dtb_mod), 380
TOMovie (class in magic), 153
topcond (fortran variable in module start_fields), 217
tops (fortran variable in module init_fields), 220
topxi (fortran variable in module init_fields), 220
topxicond (fortran variable in module start_fields), 217
torsional_oscillations (module), 387
transform_to_grid_space() (fortran subroutine in module
riterthetablocking_mod), 269
transform_to_lm_space() (fortran subroutine in module
riterthetablocking_mod), 270
transportproperties() (fortran subroutine in module ra- dial_functions), 228
truncate() (magic.coeff.MagicCoeffCmb method), 149
truncate() (magic.coeff.MagicCoeffR method), 150
truncation (module), 180
tscale (fortran variable in module num_param), 185
tshift_ic1 (fortran variable in module init_fields), 220
tshift_ic2 (fortran variable in module init_fields), 220
tshift_ma1 (fortran variable in module init_fields), 219
tshift_ma2 (fortran variable in module init_fields), 219
tstrlm (fortran variable in module dtb_mod), 380

tstrlm_lmloc (fortran variable in module dtb_mod), 379 tstrlm_rloc (fortran variable in module dtb_mod), 380 tstrrlm_lmloc (fortran variable in module dtb_mod), 380 tstrrlm_rloc (fortran variable in module dtb_mod), 380 two (fortran variable in module constants), 204	updatez() (fortran subroutine in module updatez_mod), 253 updatez_mod (module), 252 useful (module), 420
U	V
u_square_file (fortran variable in module kinetic_energy), 325	v2as_rloc (fortran variable in module tor- sional_oscillations), 388 v2lmr (fortran variable in module outto_mod), 395
uhmeanr (fortran variable in module outpar_mod), 338 ulm (fortran variable in module lmloop_data), 208 ulmmag (fortran variable in module lmloop_data), 208 unknown_type (fortran type in module communications),	v2lmr_rloc (fortran variable in module outto_mod), 395 v_r_file (fortran variable in module output_mod), 321 v_rigid_boundary() (fortran subroutine in module nonlinear_bcs), 279
209, 210	visc (fortran variable in module radial_functions), 228
unknown_type (fortran type in module co- sine_transform_even), 284	cal_parameters), 189
unknown_type (fortran type in module co- sine_transform_odd), 282	vischeatmeanr (fortran variable in module power), 340 vol_ic (fortran variable in module constants), 204
unknown_type (fortran type in module dtb_arrays_mod), 383	vol_oc (fortran variable in module constants), 204 vorold (fortran variable in module geos_mod), 400
unknown_type (fortran type in module leg_helper_mod), 288	vpm (fortran variable in module outto_mod), 396 vpm_sloc (fortran variable in module outto_mod), 396
unknown_type (fortran type in module lmmapping), 316, 317	vscale (fortran variable in module num_param), 185
unknown_type (fortran type in module nonlin-	W
ear_lm_mod), 276 unknown_type (fortran type in module riteration_mod), 267	w_ave (fortran variable in module fields_average_mod),  368  w_ave_global (fortran variable in module
unknown_type (fortran type in module riterthetablock-ing_mod), 269	w_ave_global (fortran variable in module fields_average_mod), 368 w_lmloc (fortran variable in module fields), 196
unknown_type (fortran type in module riterthetablock-ing_openmp_mod), 271	w_rloc (fortran variable in module fields), 197
unknown_type (fortran type in module to_arrays_mod), 393	walltime() (fortran subroutine in module timing), 238 wdplm (fortran variable in module horizontal_data), 231 widths (fortran variable in module physical_parameters),
updateb() (fortran subroutine in module updateb_mod),  262	<ul><li>190</li><li>widthxi (fortran variable in module physical_parameters),</li></ul>
updateb_mod (module), 260 updates() (fortran subroutine in module updates_mod),	work (fortran variable in module out_coeff), 364
256	work (fortran variable in module radial_der), 305
updates_ala() (fortran subroutine in module updates_mod), 257	work (fortran variable in module updatewp_mod), 250 work_1d_real (fortran variable in module radial_der), 305
updates_mod (module), 255 updatewp() (fortran subroutine in module up-	work_lmloc (fortran variable in module fields), 196
updatewp() (fortran subroutine in module updatewp_mod), 250	workb (fortran variable in module updateb_mod), 261 workb (fortran variable in module updatewp_mod), 249
updatewp_mod (module), 248	workb (fortran variable in module updatewp_mod), 243 workb (fortran variable in module updatewps_mod), 243
updatewps() (fortran subroutine in module up-	workb (fortran variable in module updatewpt_mod), 246
datewps_mod), 244	workb (fortran variable in module updatez_mod), 253
updatewps_mod (module), 242 updatewpt() (fortran subroutine in module up-	workc (fortran variable in module updatewps_mod), 243
updatewpt() (fortran subroutine in module updatewpt_mod), 247	workc (fortran variable in module updatewpt_mod), 246 workd (fortran variable in module updatewps_mod), 243
updatewpt_mod (module), 245	workd (fortran variable in module updatewps_mod), 243 workd (fortran variable in module updatewpt_mod), 246
updatexi() (fortran subroutine in module updatexi_mod),	wpass2jw() (fortran subroutine in module fft), 301
259	wpass3jw() (fortran subroutine in module fft), 301
updatexi_mod (module), 258	wpass4iw() (fortran subroutine in module fft), 301

wpass5jw() (fortran subroutine in module fft), 302 wplm (fortran variable in module horizontal_data), 231 wpmat (fortran variable in module updatewp_mod), 250 wpmat_fac (fortran variable in module updatewp_mod), 249	ximat_fac (fortran variable in module updatexi_mod), 259 ximeanr (fortran variable in module outmisc_mod), 331 xipivot (fortran variable in module updatexi_mod), 259
wppivot (fortran variable in module updatewp_mod), 250 wpsmat (fortran variable in module updatewps_mod), 243 wpsmat_fac (fortran variable in module updatewps_mod), 243	y10_norm (fortran variable in module constants), 203 y11_norm (fortran variable in module constants), 204 Z
wpspivot (fortran variable in module updatewps_mod), 243  wptmat (fortran variable in module updatewpt_mod), 246  wptmat_fac (fortran variable in module updatewpt_mod), 246  wptpivot (fortran variable in module updatewpt_mod), 246  write_bcmb() (fortran subroutine in module out_coeff), 364  write_coeff_r() (fortran subroutine in module out_coeff), 365  write_dtb_frame() (fortran subroutine in module out_dtb_frame), 385  write_movie_frame() (fortran subroutine in module out_movie), 358  write_pot() (fortran subroutine in module out_coeff), 366  write_rot() (fortran subroutine in module outrot), 334  writeinfo() (fortran subroutine in module precalculations), 225  writenamelists() (fortran subroutine in module namelists), 215  writetime() (fortran subroutine in module timing), 239  writeVPEq() (in module magic.libmagic), 176  writeVTI() (magic.graph2vtk.Graph2Vtk method), 158  writeVTS() (magic.graph2vtk.Graph2Vtk method), 158  ws_global (fortran variable in module geos_mod), 400	z10mat (fortran variable in module updatez_mod), 253 z10mat_fac (fortran variable in module updatez_mod), 253 z10pivot (fortran variable in module updatez_mod), 253 z_ave (fortran variable in module fields_average_mod), 368 z_ave_global (fortran variable in module fields), 196 z_rloc (fortran variable in module fields), 196 z_rloc (fortran variable in module fields), 196 zavg() (in module magic.cyl), 165 zdens (fortran variable in module output_data), 200 zderavg() (in module magic.libmagic), 176 zero (fortran variable in module constants), 203 zero_tolerance (fortran variable in module rms), 373 zmat (fortran variable in module updatez_mod), 253 zmat_fac (fortran variable in module updatez_mod), 253 zs_global (fortran variable in module geos_mod), 400 zz (fortran variable in module outto_mod), 395 zz_sloc (fortran variable in module outto_mod), 395 zz_sloc (fortran variable in module outto_mod), 395
X	
xi0mat (fortran variable in module updatexi_mod), 259 xi0mat_fac (fortran variable in module updatexi_mod), 259 xi0pivot (fortran variable in module updatexi_mod), 259 xi_ave (fortran variable in module fields_average_mod),	
xi_ave_global (fortran variable in module fields_average_mod), 368 xi_bot (fortran variable in module init_fields), 220 xi_cond() (fortran subroutine in module init_fields), 222 xi_lmloc (fortran variable in module fields), 197 xi_lmloc_container (fortran variable in module fields), 195 xi_rloc (fortran variable in module fields), 196 xi_rloc_container (fortran variable in module fields), 195 xi_top (fortran variable in module init_fields), 219 ximat (fortran variable in module updatexi_mod), 259	