PyReMoto

Generated by Doxygen 1.8.6

Mon Jun 20 2016 18:14:00

Contents

1	ReM	loto in Python	1
2	Nam	nespace Index	3
	2.1	Packages	3
3	Hiera	rarchical Index	5
	3.1	Class Hierarchy	5
4	Clas	ss Index	7
	4.1	Class List	7
5	File	Index	9
	5.1	File List	9
6	Nam	nespace Documentation	11
	6.1	AxonDelay Namespace Reference	11
	6.2	ChannelConductance Namespace Reference	11
	6.3	Compartment Namespace Reference	11
		6.3.1 Function Documentation	11
		6.3.1.1 calcGLeak	11
	6.4	Configuration Namespace Reference	12
	6.5	MotorUnit Namespace Reference	12
		6.5.1 Function Documentation	12
		6.5.1.1 calcGCoupling	12
		6.5.1.2 compGCouplingMatrix	13
		6.5.1.3 runge_kutta	13
	6.6	MotorUnitPool Namespace Reference	14
		6.6.1 Function Documentation	14
		6.6.1.1 twitchSaturation	14
	6.7	NeuralTract Namespace Reference	15
	6.8	NeuralTractUnit Namespace Reference	15
	6.9	PointProcessGenerator Namespace Reference	15
		6.9.1 Function Documentation	15

iv CONTENTS

			6.9.1.1	gammaPoint	15
	6.10	PulseC	onductance	eState Namespace Reference	16
		6.10.1	Function D	Occumentation	16
			6.10.1.1	compValOff	16
			6.10.1.2	compValOn	17
	6.11	simulat	ion Names	pace Reference	17
		6.11.1	Function D	Occumentation	17
			6.11.1.1	simulador	17
	6.12	Synaps	se Namespa	ace Reference	17
		6.12.1	Function D	Occumentation	18
			6.12.1.1	compRiStart	18
			6.12.1.2	compRiStop	18
			6.12.1.3	compRoff	19
			6.12.1.4	compRoffStart	19
			6.12.1.5	compRoffStop	19
			6.12.1.6	compRon	20
			6.12.1.7	compRonStart	20
			6.12.1.8	compRonStop	21
			6.12.1.9	compSynapCond	21
	0.40	Cynon		Namespace Reference	00
	6.13	Syriaps	sesFactory I	Namespace Reference	22
7				Namespace Reference	
7		s Docui	mentation		22 23
7	Clas	s Docui	mentation elay.AxonDe	elay Class Reference	23
7	Clas	s Docu i AxonD	mentation elay.AxonDe Detailed D		23
7	Clas	S Docui AxonD 7.1.1	mentation elay.AxonDe Detailed D	elay Class Reference	23 23 24
7	Clas	S Docui AxonD 7.1.1	mentation elay.AxonDe Detailed D Constructo 7.1.2.1	elay Class Reference	23 23 24 24
7	Clas	AxonD 7.1.1 7.1.2	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F	elay Class Reference	23 23 24 24 24
7	Clas	AxonD 7.1.1 7.1.2	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1	elay Class Reference	23 24 24 24 24 24
7	Clas	AxonD 7.1.1 7.1.2	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2	elay Class Reference	23 24 24 24 24 24 24
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D	elay Class Reference	23 24 24 24 24 24 24
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1	elay Class Reference	23 24 24 24 24 24 24 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2	elay Class Reference	23 24 24 24 24 24 24 25 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3	elay Class Reference rescription or & Destructor Documentation init unction Documentation addSpinalSpike addTerminalSpike rata Documentation index latencySpinalTerminal_ms	23 24 24 24 24 24 24 25 25 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3 7.1.4.4	elay Class Reference description or & Destructor Documentation init unction Documentation addSpinalSpike addTerminalSpike ata Documentation index latencySpinalTerminal_ms latencyStimulusSpinal_ms	23 24 24 24 24 24 25 25 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3 7.1.4.5	elay Class Reference	23 24 24 24 24 24 25 25 25 25 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3 7.1.4.4 7.1.4.5 7.1.4.6	elay Class Reference rescription or & Destructor Documentation init unction Documentation addSpinalSpike ata Documentation index latencySpinalTerminal_ms latencyStimulusSpinal_ms latencyStimulusTerminal_ms length_m	23 24 24 24 24 24 25 25 25 25 25 25
7	Clas	AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3 7.1.4.4 7.1.4.5 7.1.4.6 7.1.4.7	elay Class Reference rescription or & Destructor Documentation init unction Documentation addSpinalSpike addTerminalSpike rata Documentation index latencySpinalTerminal_ms latencyStimulusSpinal_ms latencyStimulusTerminal_ms length_m stimulusPositiontoTerminal	23 24 24 24 24 25 25 25 25 25 25 25
7	Clas	s Docui AxonD 7.1.1 7.1.2 7.1.3	mentation elay.AxonDe Detailed D Constructo 7.1.2.1 Member F 7.1.3.1 7.1.3.2 Member D 7.1.4.1 7.1.4.2 7.1.4.3 7.1.4.4 7.1.4.5 7.1.4.6 7.1.4.7 7.1.4.8	elay Class Reference rescription or & Destructor Documentation init unction Documentation addSpinalSpike addTerminalSpike rata Documentation index latencySpinalTerminal_ms latencyStimulusSpinal_ms latencyStimulusTerminal_ms length_m stimulusPositiontoTerminal terminalSpikeTrain	23 24 24 24 24 25 25 25 25 25 25 25 25

CONTENTS

	7.2.2	Construc	tor & Destructor Documentation	27
		7.2.2.1	init	27
	7.2.3	Member	Function Documentation	27
		7.2.3.1	compCondKf	27
		7.2.3.2	compCondKs	27
		7.2.3.3	compCondNa	28
		7.2.3.4	computeCurrent	28
	7.2.4	Member	Data Documentation	28
		7.2.4.1	compCond	28
		7.2.4.2	condState	29
		7.2.4.3	EqPot_mV	29
		7.2.4.4	gmax_muS	29
		7.2.4.5	kind	29
		7.2.4.6	lenStates	29
		7.2.4.7	stateType	29
7.3	Compa	artment.Co	empartment Class Reference	29
	7.3.1	Detailed	Description	30
	7.3.2	Construc	tor & Destructor Documentation	30
		7.3.2.1	init	30
	7.3.3	Member	Function Documentation	31
		7.3.3.1	computeCurrent	31
	7.3.4	Member	Data Documentation	31
		7.3.4.1	capacitance_nF	31
		7.3.4.2	Channels	31
		7.3.4.3	diameter_mum	31
		7.3.4.4	gLeak	31
		7.3.4.5	index	31
		7.3.4.6	kind	31
		7.3.4.7	length_mum	32
		7.3.4.8	neuronKind	32
		7.3.4.9	numberChannels	32
		7.3.4.10	SynapsesIn	32
		7.3.4.11	SynapsesOut	32
7.4	Config	uration.Co	nfiguration Class Reference	32
	7.4.1	Detailed	Description	33
	7.4.2	Construc	tor & Destructor Documentation	33
		7.4.2.1	init	33
	7.4.3	Member	Function Documentation	33
		7.4.3.1	determineSynapses	33
		7.4.3.2	inputFunctionGet	34

vi CONTENTS

		7.4.3.3	parameterSet	34
	7.4.4	Member	Data Documentation	34
		7.4.4.1	confArray	34
		7.4.4.2	simDuration_ms	34
		7.4.4.3	timeStep_ms	34
		7.4.4.4	timeStepBySix_ms	34
		7.4.4.5	timeStepByTwo_ms	35
7.5	MotorL	Jnit.Motorl	Unit Class Reference	35
	7.5.1	Detailed	Description	36
	7.5.2	Construc	ctor & Destructor Documentation	36
		7.5.2.1	init	36
	7.5.3	Member	Function Documentation	37
		7.5.3.1	addSomaSpike	37
		7.5.3.2	atualizeCompartments	37
		7.5.3.3	atualizeDelay	38
		7.5.3.4	atualizeMotorUnit	38
		7.5.3.5	dVdt	39
	7.5.4	Member	Data Documentation	39
		7.5.4.1	bSat	39
		7.5.4.2	capacitanceInv	39
		7.5.4.3	compartment	39
		7.5.4.4	compNumber	39
		7.5.4.5	conf	39
		7.5.4.6	Delay	39
		7.5.4.7	G	40
		7.5.4.8	ilnjected	40
		7.5.4.9	ilonic	40
		7.5.4.10	index	40
		7.5.4.11	kind	40
		7.5.4.12	MNRefPer_ms	40
		7.5.4.13	nerve	40
		7.5.4.14	somaIndex	40
		7.5.4.15	somaSpikeTrain	41
		7.5.4.16	terminalSpikeTrain	41
		7.5.4.17	threshold_mV	41
		7.5.4.18	tSomaSpike	41
		7.5.4.19	TwitchAmp_N	41
		7.5.4.20	TwitchTc_ms	41
		7.5.4.21	twTet	41
		7.5.4.22	v_mV	41

CONTENTS vii

7.6	MotorU	InitPool.MotorUnitPool Class Reference 41
	7.6.1	Detailed Description
	7.6.2	Constructor & Destructor Documentation
		7.6.2.1init
	7.6.3	Member Function Documentation
		7.6.3.1 atualizeActivationSignal
		7.6.3.2 atualizeForceNoHill
		7.6.3.3 atualizeMotorUnitPool
		7.6.3.4 listSpikes
	7.6.4	Member Data Documentation
		7.6.4.1 activation_nonSat
		7.6.4.2 activation_Sat
		7.6.4.3 activationModel
		7.6.4.4 ActMatrix
		7.6.4.5 an
		7.6.4.6 atualizeForce
		7.6.4.7 bSat
		7.6.4.8 conf
		7.6.4.9 diracDeltaValue
		7.6.4.10 force
		7.6.4.11 hillModel
		7.6.4.12 kind
		7.6.4.13 MUnumber
		7.6.4.14 pool
		7.6.4.15 poolSomaSpikes
		7.6.4.16 poolTerminalSpikes
		7.6.4.17 timeIndex
		7.6.4.18 twitchAmp_N
		7.6.4.19 twTet
		7.6.4.20 unit
7.7	Neural	Tract.NeuralTract Class Reference
	7.7.1	Detailed Description
	7.7.2	Constructor & Destructor Documentation
		7.7.2.1init
	7.7.3	Member Function Documentation
		7.7.3.1 atualizePool
		7.7.3.2 listSpikes
	7.7.4	Member Data Documentation
		7.7.4.1 FR
		7.7.4.2 kind

viii CONTENTS

		7.7.4.3	Number	47
		7.7.4.4	pool	47
		7.7.4.5	poolTerminalSpikes	47
		7.7.4.6	target	47
		7.7.4.7	timeIndex	47
		7.7.4.8	unit	47
7.8	Neural	TractUnit.N	NeuralTractUnit Class Reference	48
	7.8.1	Detailed	Description	48
	7.8.2	Construc	tor & Destructor Documentation	48
		7.8.2.1	init	48
	7.8.3	Member	Function Documentation	48
		7.8.3.1	atualizeNeuralTractUnit	48
		7.8.3.2	transmitSpikes	49
	7.8.4	Member	Data Documentation	49
		7.8.4.1	GammaOrder	49
		7.8.4.2	indicesOfSynapsesOnTarget	49
		7.8.4.3	spikesGenerator	49
		7.8.4.4	SynapsesOut	49
		7.8.4.5	terminalSpikeTrain	49
		7.8.4.6	transmitSpikesThroughSynapses	49
7.9	PointPr	rocessGen	nerator.PointProcessGenerator Class Reference	49
	7.9.1	Detailed	Description	50
	7.9.2	Construc	tor & Destructor Documentation	50
		7.9.2.1	init	50
	7.9.3	Member	Function Documentation	50
		7.9.3.1	atualizeGenerator	50
	7.9.4	Member	Data Documentation	51
		7.9.4.1	GammaOrder	51
		7.9.4.2	GammaOrderInv	51
		7.9.4.3	index	51
		7.9.4.4	points	51
		7.9.4.5	threshold	51
		7.9.4.6	$y \ \dots $	51
7.10	PulseC	onductand	ceState.PulseConductanceState Class Reference	52
	7.10.1	Detailed	Description	52
	7.10.2	Construc	tor & Destructor Documentation	52
		7.10.2.1	init	52
	7.10.3	Member	Function Documentation	53
		7.10.3.1	changeState	53
		7.10.3.2	computeStateValue	53

CONTENTS

	7.10.4	Member Data Documentation	53
		7.10.4.1 actType	53
		7.10.4.2 alpha_ms1	53
		7.10.4.3 beta_ms1	54
		7.10.4.4 computeValueOff	54
		7.10.4.5 computeValueOn	54
		7.10.4.6 kind	54
		7.10.4.7 PulseDur_ms	54
		7.10.4.8 state	54
		7.10.4.9 t0	54
		7.10.4.10 v0	54
		7.10.4.11 value	54
7.11	Synaps	se.Synapse Class Reference	54
	7.11.1	Detailed Description	55
	7.11.2	Constructor & Destructor Documentation	56
		7.11.2.1init	56
	7.11.3	Member Data Documentation	56
		7.11.3.1 alpha_ms1	56
		7.11.3.2 beta_ms1	56
		7.11.3.3 conductanceState	56
		7.11.3.4 delay_ms	56
		7.11.3.5 dynamics	56
		7.11.3.6 EqPot_mV	56
		7.11.3.7 expFinish	56
		7.11.3.8 gmax_muS	57
		7.11.3.9 gMaxTot_muS	57
		7.11.3.10 kind	57
		7.11.3.11 neuronKind	57
		7.11.3.12 Non	57
		7.11.3.13 numberOfIncomingSynapses	57
		7.11.3.14 pool	57
		7.11.3.15 ri	57
		7.11.3.16 rlnf	57
		7.11.3.17 Roff	57
		7.11.3.18 Ron	58
		7.11.3.19 t0	58
		7.11.3.20 tauOff	58
		7.11.3.21 tauOn	58
		7.11.3.22 tBeginOfPulse	58
		7.11.3.23 tEndOfPulse	58

X CONTENTS

		7.11.3.24 ti	58
		7.11.3.25 Tmax_mM	58
		7.11.3.26 tPeak_ms	58
	7.12	SynapsesFactory.SynapsesFactory Class Reference	59
		7.12.1 Detailed Description	59
		7.12.2 Constructor & Destructor Documentation	59
		7.12.2.1init	59
		7.12.3 Member Data Documentation	59
		7.12.3.1 numberOfSynapses	59
	Ette F		~4
8		Documentation	61
	8.1	AxonDelay.py File Reference	61
	8.2	ChannelConductance.py File Reference	61
	8.3	Compartment.py File Reference	61
	8.4	Configuration.py File Reference	62
	8.5	MotorUnit.py File Reference	62
	8.6	MotorUnitPool.py File Reference	62
	8.7	NeuralTract.py File Reference	63
	8.8	NeuralTractUnit.py File Reference	63
	8.9	PointProcessGenerator.py File Reference	63
	8.10	PulseConductanceState.py File Reference	64
	8.11	simulation.py File Reference	64
	8.12	Synapse.py File Reference	64
	8.13	SynapsesFactory.py File Reference	65
			00
Inc	ıex		66

ReMoto in Python

This program is a neuronal simulation system, intended for studying spinal cord neuronal networks responsible for muscle control. These networks are affected by descending drive, afferent drive, and electrical nerve stimulation. The simulator may be used to investigate phenomena at several levels of organization, e.g., at the neuronal membrane level or at the whole muscle behavior level (e.g., muscle force generation). This versatility is due to the fact that each element (neurons, synapses, muscle fibers) has its own specific mathematical model, usually involving the action of voltage- or neurotransmitter-dependent ionic channels. The simulator should be helpful in activities such as interpretation of results obtained from neurophysiological experiments in humans or mammals, proposal of hypothesis or testing models or theories on neuronal dynamics or neuronal network processing, validation of experimental protocols, and teaching neurophysiology.

The elements that take part in the system belong to the following classes: motoneurons, muscle fibers (electrical activity and force generation), Renshaw cells, la inhibitory interneurons, lb inhibitory interneurons, la and lb afferents. The neurons are interconnected by chemical synapses, which can be exhibit depression or facilitation.

The system simulates the following nuclei involved in flexion and extension of the human or cat ankle: Medial Gastrocnemius (MG), Lateral Gastrocnemius (LG), Soleus (SOL), and Tibialis Anterior (TA).

A web-based version can be found in remoto.leb.usp.br. The version to which this documentation refers is from a Python program that can be found in github.com/rnwatanabe/projectPR.

ReMoto in Python

Namespace Index

2.1 Packages

Here are the packages with brief descriptions (if available):

AxonDelay	. 11
ChannelConductance	
Compartment	
Configuration	
MotorUnit	
MotorUnitPool	
NeuralTract	
NeuralTractUnit	
PointProcessGenerator	
PulseConductanceState	
simulation	
Synapse	
SynapsesFactory	22

Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

object	
AxonDelay.AxonDelay	23
ChannelConductance.ChannelConductance	26
Compartment.Compartment	29
Configuration.Configuration	32
MotorUnit.MotorUnit	35
MotorUnitPool.MotorUnitPool	41
NeuralTract.NeuralTract	46
NeuralTractUnit.NeuralTractUnit	48
PointProcessGenerator.PointProcessGenerator	49
PulseConductanceState.PulseConductanceState	52
Synapse.Synapse	54
SynapsesFactory.SynapsesFactory	59

6 **Hierarchical Index**

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

AxonDelay.	
Class that implements a delay correspondent to the nerve	23
ChannelConductance.ChannelConductance	
Class that implements a model of the ionic Channels in a compartment	26
Compartment.Compartment	
Class that implements a neural compartment	29
Configuration. Configuration	
Class that builds an object of Configuration, based on a configuration file	32
MotorUnit.MotorUnit	
Class that implements a motor unit model	35
MotorUnitPool.MotorUnitPool	
Class that implements a motor unit pool	41
NeuralTract.NeuralTract	
Classdocs	46
NeuralTractUnit.NeuralTractUnit	
Classdocs	48
PointProcessGenerator.PointProcessGenerator	
Generator of point processes	49
PulseConductanceState.PulseConductanceState	
Implements the Destexhe pulse approximation of the solution of the states of the Hodgkin-Huxley	
neuron model	52
Synapse. Synapse	
Implements the synapse model from Destexhe (1994) using the computational method from	
Lytton (1996)	54
SynapsesFactory.SynapsesFactory	
Class to build all the synapses in the system	59

8 Class Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

ıxonDelay.py	61
ChannelConductance.py	61
Compartment.py	61
Configuration.py	62
NotorUnit.py	
NotorUnitPool.py	62
leuralTract.py	63
leuralTractUnit.py	63
ointProcessGenerator.py	63
PulseConductanceState.py	64
imulation.py	64
Synapse.py	64
Synapses Factory by	65

10 File Index

Namespace Documentation

6.1 AxonDelay Namespace Reference

Classes

· class AxonDelay

Class that implements a delay correspondent to the nerve.

6.2 ChannelConductance Namespace Reference

Classes

· class ChannelConductance

Class that implements a model of the ionic Channels in a compartment.

6.3 Compartment Namespace Reference

Classes

class Compartment

Class that implements a neural compartment.

Functions

• def calcGLeak

Computes the leak conductance of the compartment.

6.3.1 Function Documentation

6.3.1.1 def Compartment.calcGLeak (area, specificRes)

Computes the leak conductance of the compartment.

- · Input:
 - area: area of the compartment in cm².

- **specificRes**: specific resistance of the compartment in $\Omega.cm^2$.
- · Output:
 - Leak conductance in MS.

It is compute according to the following formula:

$$g = 10^6 \cdot \frac{A}{\rho} \tag{6.1}$$

where A is the compartment area [cm 2], ρ is the specific resistance [$\Omega.cm^2$] and g is the compartment conductance [MS].

Definition at line 32 of file Compartment.py.

6.4 Configuration Namespace Reference

Classes

· class Configuration

Class that builds an object of Configuration, based on a configuration file.

6.5 MotorUnit Namespace Reference

Classes

· class MotorUnit

Class that implements a motor unit model.

Functions

· def calcGCoupling

Calculates the coupling conductance between two compartments.

· def compGCouplingMatrix

Computes the Coupling Matrix to be used in the dVdt function of the N compartments of the motor unit.

• def runge_kutta

Function to implement the fourth order Runge-Kutta Method to solve numerically a differential equation.

6.5.1 Function Documentation

6.5.1.1 def MotorUnit.calcGCoupling (cytR, IComp1, IComp2, dComp1, dComp2)

Calculates the coupling conductance between two compartments.

- · Inputs:
 - cytR: Cytoplasmatic resistivity in Ω .cm.
 - IComp1, IComp2: length of the compartments in μ m.
 - dComp1, dComp2: diameter of the compartments in μ m.
- Output:

- coupling conductance in MS.

The coupling conductance between compartment 1 and 2 is computed by the following equation:

$$g_c = \frac{2.10^2}{\frac{R_{cyt}l_1}{\pi r_1^2} + \frac{R_{cyt}l_2}{\pi r_2^2}}$$
(6.2)

where g_c is the coupling conductance [MS], R_{cyl} is the cytoplasmatic resistivity [Ω .cm], l_1 and l_2 are the lengths [μ m] of compartments 1 and 2, respectively and r_1 and r_2 are the radius [μ m] of compartments 1 and 2, respectively. Definition at line 46 of file MotorUnit.py.

6.5.1.2 def MotorUnit.compGCouplingMatrix (gc)

Computes the Coupling Matrix to be used in the dVdt function of the N compartments of the motor unit.

The Matrix uses the values obtained with the function calcGcoupling.

- · Inputs:
 - gc: the vector with N elements, with the coupling conductance of each compartment of the Motor Unit.
- · Output:
 - the GC matrix

$$GC = \begin{bmatrix} -g_c[0] & g_c[0] & 0 & \dots & \dots & 0 & 0 & 0 \\ g_c[0] & -g_c[0] - g_c[1] & g_c[1] & 0 & \dots & \dots & 0 & 0 \\ \vdots & & \ddots & & \dots & & 0 & 0 \\ 0 & \dots & g_c[i-1] & -g_c[i-1] - g_c[i] & g_c[i] & 0 & \dots & 0 \\ 0 & 0 & 0 & \dots & \dots & \dots & 0 \\ 0 & & \dots & g_c[N-2] & -g_c[N-2] - g_c[N-1] & g_c[N-1] & 0 \\ 0 & \dots & 0 & g_c[N-1] & -g_c[N-1] \end{bmatrix}$$

Definition at line 78 of file MotorUnit.py.

6.5.1.3 def MotorUnit.runge_kutta (derivativeFunction, t, x, timeStep, timeStepByTwo, timeStepBySix)

Function to implement the fourth order Runge-Kutta Method to solve numerically a differential equation.

- Inputs:
 - derivativeFunction: function that corresponds to the derivative of the differential equation.
 - t: current instant.
 - x: current state value.
 - timeStep: time step of the solution of the differential equation, in the same unit of t.
 - timeStepByTwo: timeStep divided by two, for computational efficiency.
 - timeStepBySix: timeStep divided by six, for computational efficiency.

This method is intended to solve the following differential equation:

$$\frac{dx(t)}{dt} = f(t, x(t)) \tag{6.4}$$

First, four derivatives are computed:

$$k_1 = f(t, x(t))$$

$$\begin{array}{l} \mathbf{k}_1 = f(t, \mathbf{x}(t)) \\ k_2 = f(t + \frac{\Delta t}{2}, \mathbf{x}(t) + \frac{\Delta t}{2}.k_1) \end{array}$$

$$k_3 = f(t + \frac{\Delta t}{2}, x(t) + \frac{\Delta t}{2}.k_2$$

 $k_3 = f(t + \frac{\Delta t}{2}, x(t) + \frac{\Delta t}{2}.k_2)$ $k_4 = f(t + \Delta t, x(t) + \Delta t.k_3)$ where Δt is the time step of the numerical solution of the differential equation.

Then the value of $x(t + \Delta t)$ is computed with:

$$x(t + \Delta t) = x(t) + \frac{\Delta t}{6}(k_1 + 2k_2 + 2k_3 + k_4)$$
(6.5)

Definition at line 133 of file MotorUnit.py.

Here is the caller graph for this function:



MotorUnitPool Namespace Reference

Classes

· class MotorUnitPool

Class that implements a motor unit pool.

Functions

· def twitchSaturation

Computes the muscle unit force after the nonlinear saturation.

6.6.1 Function Documentation

6.6.1.1 def MotorUnitPool.twitchSaturation (force, b)

Computes the muscle unit force after the nonlinear saturation.

$$F_{sat} = \frac{1 - e^{-b.force}}{1 + e^{-b.force}} \tag{6.6}$$

- · Inputs:
 - force: force before the saturation.
 - b: saturation function parameter.
- · Outputs:
 - Saturated force.

Definition at line 31 of file MotorUnitPool.py.

Here is the caller graph for this function:



6.7 NeuralTract Namespace Reference

Classes

class NeuralTract

classdocs

6.8 NeuralTractUnit Namespace Reference

Classes

· class NeuralTractUnit

classdocs

6.9 PointProcessGenerator Namespace Reference

Classes

• class PointProcessGenerator

Generator of point processes.

Functions

· def gammaPoint

Generates a number according to a Gamma Distribution with an integer order GammaOrder.

6.9.1 Function Documentation

6.9.1.1 def PointProcessGenerator.gammaPoint (GammaOrder, GammaOrderInv)

Generates a number according to a Gamma Distribution with an integer order GammaOrder.

- · Inputs:
 - **GammaOrder**: integer order of the Gamma distribution.
 - GammaOrderInv: inverse of the GammaOrder. This is necessary for computational efficiency.
- · Outputs:
 - The number generated from the Gamma distribution.

The number is generated according to:

$$\Gamma = -\frac{1}{\lambda} \ln(\prod_{i=1}^{\lambda} U(0,1)) \tag{6.7}$$

where λ is the order of the Gamma distribution and U(a,b) is a uniform distribution from a to b.

Definition at line 37 of file PointProcessGenerator.py.

Here is the caller graph for this function:



6.10 PulseConductanceState Namespace Reference

Classes

· class PulseConductanceState

Implements the Destexhe pulse approximation of the solution of the states of the Hodgkin-Huxley neuron model.

Functions

def compValOn

Time course of the state during the pulse for the inactivation states and before and after the pulse for the activation states.

def compValOff

Time course of the state during the pulse for the activation states and before and after the pulse for the inactivation states.

6.10.1 Function Documentation

6.10.1.1 def PulseConductanceState.compValOff (v0, alpha, beta, t, t0)

Time course of the state during the pulse for the *activation* states and before and after the pulse for the *inactivation* states

The value of the state ν is computed according to the following equation:

$$v(t) = 1 + (v_0 - 1) \exp[-\alpha(t - t_0)]$$
(6.8)

where t_0 is the time at which the pulse changed the value (on to off or off to on) and v_0 is value of the state at that time.

Definition at line 46 of file PulseConductanceState.py.

6.10.1.2 def PulseConductanceState.compValOn (v0, alpha, beta, t, t0)

Time course of the state during the pulse for the *inactivation* states and before and after the pulse for the *activation* states.

The value of the state v is computed according to the following equation:

$$v(t) = v_0 \exp[-\beta (t - t_0)] \tag{6.9}$$

where t_0 is the time at which the pulse changed the value (on to off or off to on) and v_0 is value of the state at that time.

Definition at line 28 of file PulseConductanceState.py.

6.11 simulation Namespace Reference

Functions

· def simulador

6.11.1 Function Documentation

6.11.1.1 def simulation.simulador ()

Definition at line 21 of file simulation.py.

6.12 Synapse Namespace Reference

Classes

class Synapse

Implements the synapse model from Destexhe (1994) using the computational method from Lytton (1996).

Functions

· def compSynapCond

Computes the synaptic conductance.

def compRon

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).

def compRoff

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

· def compRiStart

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter begin (begin of the pulse).

def compRiStop

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter release stops (the pulse ends).

def compRonStart

Incorporates a new conductance to the set of conductances during a pulse.

def compRoffStart

Incorporates a new conductance to the set of conductances that are not during a pulse.

def compRonStop

Removes a conductance from the set of conductances during a pulse.

def compRoffStop

Removes a conductance from the set of conductances that are not during a pulse.

6.12.1 Function Documentation

6.12.1.1 def Synapse.compRiStart (ri, t, ti, tPeak, tauOff)

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter begin (begin of the pulse).

- · Inputs:
 - ri: the fraction of postsynaptic receptors that were bound to neurotransmitters at the last state change.
 - t: current instant, in ms.
 - ti: The instant that the last pulse began.
 - tPeak: The duration of the pulse.
 - tauOff: Time constant after a pulse, in ms.
- · Output:
 - individual synapse state value.

It is computed by the following equation:

$$r_{i_{newValue}} = r_{i_{oldValue}} \exp\left(\frac{t_i + T_{dur} - t}{\tau_{off}}\right)$$
(6.10)

Definition at line 142 of file Synapse.py.

6.12.1.2 def Synapse.compRiStop (rInf, ri, expFinish)

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter release stops (the pulse ends).

- · Inputs:
 - rInf: the fraction of postsynaptic receptors that would be bound to neurotransmitters after an infinite amount of time with neurotransmitter being released.
 - ri: the fraction of postsynaptic receptors that were bound to neurotransmitters at the last state change.
 - **expFinish**: Is the value of the exponential at the end of the pulse ($\exp(T_{dur}/\tau_{on})$). It is is computed before for computational efficiency.
- Output:
 - individual synapse state value.

It is computed by the following equation:

$$r_{i_{newValue}} = r_{\infty} + (r_{i_{oldValue}} - r_{\infty}) \exp\left(\frac{T_{dur}}{\tau_{on}}\right)$$
(6.11)

Definition at line 173 of file Synapse.py.

6.12.1.3 def Synapse.compRoff (Roff, t0, t, tauOff)

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

- · Inputs:
 - Roff: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).
 - t0: instant that the last spike arrived to the compartment.
 - t: current instant, in ms.
 - tauOff: time constant after a pulse, in ms.
- · Output:
 - The fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released.

It is computed by the following formula:

$$R_{off_{newValue}} = R_{off_{oldValue}} \exp\left(-\frac{t - t0}{\tau_{off}}\right)$$
(6.12)

Definition at line 112 of file Synapse.py.

6.12.1.4 def Synapse.compRoffStart (Roff, ri, synContrib)

Incorporates a new conductance to the set of conductances that are not during a pulse.

- · Inputs:
 - **Roff**: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).
 - ri: fraction of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.
 - **synContrib**: individual conductance constribution to the global synaptic conductance.
- Output:
 - The new value of the sum of the fraction of postsynaptic receptors that are bound to neurotransmitters
 of all the individual synapses that do not have neurotransmitters being released (before and after the
 pulse).

It is computed as:

$$R_{off_{newValue}} = R_{off_{oldValue}} - r_i S_{indCont}$$
(6.13)

Definition at line 235 of file Synapse.py.

6.12.1.5 def Synapse.compRoffStop (Roff, ri, synContrib)

Removes a conductance from the set of conductances that are not during a pulse.

- · Inputs:
 - Roff: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

- ri: fraction of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.
- synContrib: individual conductance constribution to the global synaptic conductance.
- · Output:
 - The new value of the sum of the fraction of postsynaptic receptors that are bound to neurotransmitters
 of all the individual synapses that do not have neurotransmitters being released (before and after the
 pulse).

It is computed as:

$$R_{off_{newValue}} = R_{off_{oldValue}} + r_i S_{indCont}$$
(6.14)

Definition at line 297 of file Synapse.py.

6.12.1.6 def Synapse.compRon (Non, rInf, Ron, t0, t, tauOn)

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).

- · Inputs:
 - **Non**: sum of the fractions of the individual conductances that are receiving neurotransmitter (during pulse) relative to the G_{max} ($N_{on} = \sum_{i=1} g_{i_{on}}/G_{max}$).
 - rInf: the fraction of postsynaptic receptors that would be bound to neurotransmitters after an infinite amount of time with neurotransmitter being released.
 - **Ron**: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).
 - t0: instant that the last spike arrived to the compartment.
 - t: current instant, in ms.
 - tauOn: Time constant during a pulse, in ms. $\tau_{on} = \frac{1}{\alpha.T_{max} + \beta}$.
- · Outputs:
 - The fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released

It is computed by the following equation:

$$R_{on_{newValue}} = N_{on} r_{\infty} \left[1 - \exp\left(-\frac{t - t_0}{\tau_{on}}\right) \right] + R_{on_{oldValue}} \exp\left(-\frac{t - t_0}{\tau_{on}}\right)$$
(6.15)

Definition at line 78 of file Synapse.py.

6.12.1.7 def Synapse.compRonStart (Ron, ri, synContrib)

Incorporates a new conductance to the set of conductances during a pulse.

- · Inputs:
 - Ron: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).
 - ri: fraction of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.
 - synContrib: individual conductance constribution to the global synaptic conductance.

- Output:
 - The new value of the sum of the fraction of postsynaptic receptors that are bound to neurotransmitters
 of all the individual synapses that have neurotransmitters being released (during the pulse).

It is computed as:

$$R_{on_{newValue}} = R_{on_{oldValue}} + r_i S_{indCont}$$
(6.16)

Definition at line 203 of file Synapse.py.

6.12.1.8 def Synapse.compRonStop (Ron, ri, synContrib)

Removes a conductance from the set of conductances during a pulse.

- · Inputs:
 - Ron: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).
 - ri: fraction of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.
 - synContrib: individual conductance constribution to the global synaptic conductance.
- · Output:
 - The new value of the sum of the fraction of postsynaptic receptors that are bound to neurotransmitters
 of all the individual synapses that have neurotransmitters being released (during the pulse).

It is computed as:

$$R_{on_{newValue}} = R_{on_{oldValue}} - r_i S_{indCont}$$
(6.17)

Definition at line 265 of file Synapse.py.

6.12.1.9 def Synapse.compSynapCond (Gmax, Ron, Roff)

Computes the synaptic conductance.

- · Input:
 - **Gmax**: the sum of individual conductances of all synapses in the compartment, in μ S.
 - Ron: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).
 - Roff: sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).
- · Output:
 - the synaptic conductance of all synapses in the compartment, in μ S.

It is computed by the following formula:

$$G = G_{max}(R_{on} + R_{off}) ag{6.18}$$

where G is the synaptic conductance of all synapses in the compartment.

Definition at line 39 of file Synapse.py.

6.13 SynapsesFactory Namespace Reference

Classes

class SynapsesFactory

Class to build all the synapses in the system.

Class Documentation

7.1 AxonDelay.AxonDelay Class Reference

Class that implements a delay correspondent to the nerve.

Public Member Functions

def __init__

Constructor.

def addTerminalSpike

Indicates to the AxonDelay object that a spike has occurred in the Terminal.

· def addSpinalSpike

Indicates to the AxonDelay object that a spike has occurred in the soma.

Public Attributes

• index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

length_m

Length, in m, of the part of the nerve that is not modelled as a delay.

· velocity_m_s

Velocity of conduction, in m/s, of the part of the nerve that is not modelled as a delay.

• stimulusPositiontoTerminal

Distance, in m, of the stimulus position to the terminal.

• latencyStimulusSpinal_ms

time, in ms, that the signal takes to travel between the stimulus and the spinal cord.

· latencySpinalTerminal ms

time, in ms, that the signal takes to travel between the spinal cord and the terminal.

• latencyStimulusTerminal_ms

time, in ms, tat the signal takes to travel between the stimulus and the terminal.

• terminalSpikeTrain

Float with instant, in ms, of the last spike in the terminal.

24 Class Documentation

7.1.1 Detailed Description

Class that implements a delay correspondent to the nerve.

This class corresponds to the part of the axon that is modeled with no dynamics. Ideally this class would not exist and all the axon would be modelled in the motor unit or sensory class with the proper dynamics.

Definition at line 16 of file AxonDelay.py.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 def AxonDelay.__init__ (self, conf, nerve, pool, index)

Constructor.

- · Inputs:
 - conf: Configuration object with the simulation parameters.
 - nerve: string with type of the nerve. It can be PTN (posterior tibial nerve) or CPN (common peroneal nerve).
 - pool: string with Motor unit pool to which the motor unit belongs.
 - index: integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

Definition at line 35 of file AxonDelay.py.

7.1.3 Member Function Documentation


7.1.3.1 def AxonDelay.AxonDelay.addSpinalSpike (self, t)

Indicates to the AxonDelay object that a spike has occurred in the soma.

- · Inputs:
 - t: current instant, in ms.

Definition at line 76 of file AxonDelay.py.

Here is the call graph for this function:



7.1.3.2 def AxonDelay.AxonDelay.addTerminalSpike (self, t)


Indicates to the AxonDelay object that a spike has occurred in the Terminal.

Inputs:

- t: current instant, in ms.

Definition at line 65 of file AxonDelay.py.

Here is the caller graph for this function:



7.1.4 Member Data Documentation

7.1.4.1 AxonDelay.AxonDelay.index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle). Definition at line 39 of file AxonDelay.py.

7.1.4.2 AxonDelay.AxonDelay.latencySpinalTerminal_ms

time, in ms, that the signal takes to travel between the spinal cord and the terminal.

Definition at line 50 of file AxonDelay.py.

7.1.4.3 AxonDelay.AxonDelay.latencyStimulusSpinal_ms

time, in ms, that the signal takes to travel between the stimulus and the spinal cord.

Definition at line 48 of file AxonDelay.py.

7.1.4.4 AxonDelay.AxonDelay.latencyStimulusTerminal_ms

time, in ms, tat the signal takes to travel between the stimulus and the terminal.

Definition at line 52 of file AxonDelay.py.

7.1.4.5 AxonDelay.AxonDelay.length_m

Length, in m, of the part of the nerve that is not modelled as a delay.

Definition at line 42 of file AxonDelay.py.

7.1.4.6 AxonDelay.AxonDelay.stimulusPositiontoTerminal

Distance, in m, of the stimulus position to the terminal.

Definition at line 46 of file AxonDelay.py.

26 Class Documentation

7.1.4.7 AxonDelay.AxonDelay.terminalSpikeTrain

Float with instant, in ms, of the last spike in the terminal.

Definition at line 55 of file AxonDelay.py.

7.1.4.8 AxonDelay.AxonDelay.velocity_m_s

Velocity of conduction, in m/s, of the part of the nerve that is not modelled as a delay.

Definition at line 44 of file AxonDelay.py.

The documentation for this class was generated from the following file:

AxonDelay.py

7.2 ChannelConductance.ChannelConductance Class Reference

Class that implements a model of the ionic Channels in a compartment.

Public Member Functions

def __init__

Constructor.

def computeCurrent

Computes the current genrated by the ionic Channel.

def compCondKf

Computes the conductance of a Kf Channel.

· def compCondKs

Computes the conductance of a slow potassium Channel.

· def compCondNa

Computes the conductance of a Na Channel.

Public Attributes

• kind

string with the type of the ionic channel.

condState

List of ConductanceState objects, representing each state of the ionic channel.

EqPot_mV

Equilibrium Potential of the ionic channel, mV.

• gmax_muS

Maximal conductance, in μ S, of the ionic channel.

stateType

String with type of dynamics of the states.

compCond

Function that computes the conductance dynamics.

lenStates

Integer with the number of states in the ionic channel.

7.2.1 Detailed Description

Class that implements a model of the ionic Channels in a compartment.

Definition at line 16 of file ChannelConductance.py.

7.2.2 Constructor & Destructor Documentation

7.2.2.1 def ChannelConductance.ChannelConductance.__init__ (self, kind, conf, compArea, pool, index)

Constructor.

Builds an ionic channel conductance.

-Inputs:

- **kind**: string with the type of the ionic channel. For now it can be *Na* (Sodium), *Ks* (slow Potassium), *Kf* (fast Potassium) or *Ca* (Calcium).
- conf: instance of the Configuration class (see Configuration file).
- **compArea**: float with the area of the compartment that the Channel belongs, in cm^2 .
- pool: the pool that this state belongs.
- index: the index of the unit that this state belongs.

Definition at line 38 of file ChannelConductance.py.

7.2.3 Member Function Documentation

7.2.3.1 def ChannelConductance.ChannelConductance.compCondKf (self, V_mV)

Computes the conductance of a Kf Channel.

This function is assigned as self.compCond to a Kf Channel at the class constructor.

- Input:
 - V_mV: membrane potential of the compartment in mV.

Output:

Conductance in μS.

It is computed as:

$$g = g_{max}n^4(E_0 - V) (7.1)$$

where E_0 is the equilibrium potential of the compartment, V is the membrane potential and n is the state of a fast potassium channel.

Definition at line 115 of file ChannelConductance.py.

7.2.3.2 def ChannelConductance.ChannelConductance.compCondKs (self, V_mV)

Computes the conductance of a slow potassium Channel.

This function is assigned as self.compCond to a Ks Channel at the class constructor.

- · Input:
 - V_mV: membrane potential of the compartment in mV.
- · Output:
 - Conductance in μ S.

It is computed as:

$$g = g_{max}q^2(E_0 - V) (7.2)$$

where E_0 is the equilibrium potential of the compartment, V is the membrane potential and q is the state of a slow potassium channel.

Definition at line 138 of file ChannelConductance.py.

7.2.3.3 def ChannelConductance.ChannelConductance.compCondNa (self, V_mV)

Computes the conductance of a Na Channel.

This function is assigned as self.compCond to a Na Channel at the class constructor. -Input:

• V_mV: membrane potential of the compartment in mV.

Output:

Conductance in μS.

It is computed as:

$$g = g_{max}m^3h(E_0 - V) (7.3)$$

where E_0 is the equilibrium potential of the compartment, V is the membrane potential and m and h are the states of a sodium channel..

Definition at line 159 of file ChannelConductance.py.

7.2.3.4 def ChannelConductance.ChannelConductance.computeCurrent (self, t, V_mV)

Computes the current genrated by the ionic Channel.

- · Inputs:
 - t: instant in ms.
 - V_mV: membrane potential of the compartment in mV.
- Outputs:
 - Ionic current, in nA

Definition at line 91 of file ChannelConductance.py.

7.2.4 Member Data Documentation

7.2.4.1 ChannelConductance.ChannelConductance.compCond

Function that computes the conductance dynamics.

Definition at line 60 of file ChannelConductance.py.

7.2.4.2 ChannelConductance.ChannelConductance.condState

List of ConductanceState objects, representing each state of the ionic channel.

Definition at line 44 of file ChannelConductance.py.

7.2.4.3 ChannelConductance.ChannelConductance.EqPot_mV

Equilibrium Potential of the ionic channel, mV.

Definition at line 47 of file ChannelConductance.py.

7.2.4.4 ChannelConductance.ChannelConductance.gmax_muS

Maximal conductance, in μ S, of the ionic channel.

Definition at line 49 of file ChannelConductance.py.

7.2.4.5 ChannelConductance.ChannelConductance.kind

string with the type of the ionic channel.

For now it can be Na (Sodium), Ks (slow Potassium), Kf (fast Potassium) or Ca (Calcium).

Definition at line 42 of file ChannelConductance.py.

7.2.4.6 ChannelConductance.ChannelConductance.lenStates

Integer with the number of states in the ionic channel.

Definition at line 74 of file ChannelConductance.py.

7.2.4.7 ChannelConductance.ChannelConductance.stateType

String with type of dynamics of the states.

For now it accepts the string pulse.

Definition at line 52 of file ChannelConductance.py.

The documentation for this class was generated from the following file:

ChannelConductance.py

7.3 Compartment.Compartment Class Reference

Class that implements a neural compartment.

Public Member Functions

def init

Constructor.

def computeCurrent

Computes the active currents of the compartment.

Public Attributes

Channels

List of ChannelConductance objects in the Compartment.

neuronKind

String with the type of the motor unit.

SynapsesOut

List of summed synapses (see Lytton, 1996) that the Compartment do with other neural components.

SynapsesIn

List of summed synapses (see Lytton, 1996) that the Compartment receive from other neural components.

• kind

The kind of compartment.

index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

• length_mum

Length of the compartment, in μ m.

diameter_mum

Diameter of the compartment, in μ m.

capacitance_nF

Capacitance of the compartment, in nF.

gLeak

Leak conductance of the compartment, in MS.

• numberChannels

Integer with the number of ionic channels.

7.3.1 Detailed Description

Class that implements a neural compartment.

For now it is implemented dendrite and soma.

Definition at line 40 of file Compartment.py.

7.3.2 Constructor & Destructor Documentation

7.3.2.1 def Compartment.Compartment.__init__ (self, kind, conf, pool, index, neuronKind)

Constructor.

- Inputs:
 - kind: The kind of compartment. For now, it can be soma or dendrite.
 - conf: Configuration object with the simulation parameters.
 - pool: string with Motor unit pool to which the motor unit belongs.
 - index: integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).
 - neuronKind: string with the type of the motor unit. It can be S (slow), FR (fast and resistant), and FF (fast and fatigable).

Definition at line 60 of file Compartment.py.

7.3.3 Member Function Documentation

7.3.3.1 def Compartment.Compartment.computeCurrent (self, t, V_mV)

Computes the active currents of the compartment.

Active currents are the currents from the ionic channels and from the synapses.

- Inputs:
 - t: current instant, in ms.
 - V_mV: membrane potential, in mV.

Definition at line 116 of file Compartment.py.

7.3.4 Member Data Documentation

7.3.4.1 Compartment.Compartment.capacitance_nF

Capacitance of the compartment, in nF.

Definition at line 89 of file Compartment.py.

7.3.4.2 Compartment.Compartment.Channels

List of ChannelConductance objects in the Compartment.

Definition at line 63 of file Compartment.py.

7.3.4.3 Compartment.Compartment.diameter_mum

Diameter of the compartment, in μ m.

Definition at line 85 of file Compartment.py.

7.3.4.4 Compartment.Compartment.gLeak

Leak conductance of the compartment, in MS.

Definition at line 91 of file Compartment.py.

7.3.4.5 Compartment.Compartment.index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

Definition at line 80 of file Compartment.py.

7.3.4.6 Compartment.Compartment.kind

The kind of compartment.

For now, it can be soma or dendrite.

Definition at line 76 of file Compartment.py.

7.3.4.7 Compartment.Compartment.length_mum

Length of the compartment, in μ m.

Definition at line 83 of file Compartment.py.

7.3.4.8 Compartment.Compartment.neuronKind

String with the type of the motor unit.

It can be S (slow), FR (fast and resistant), and FF (fast and fatigable).

Definition at line 66 of file Compartment.py.

7.3.4.9 Compartment.Compartment.numberChannels

Integer with the number of ionic channels.

Definition at line 102 of file Compartment.py.

7.3.4.10 Compartment.Compartment.SynapsesIn

List of summed synapses (see Lytton, 1996) that the Compartment receive from other neural components.

Definition at line 71 of file Compartment.py.

7.3.4.11 Compartment.Compartment.SynapsesOut

List of summed synapses (see Lytton, 1996) that the Compartment do with other neural components.

Definition at line 68 of file Compartment.py.

The documentation for this class was generated from the following file:

Compartment.py

7.4 Configuration.Configuration Class Reference

Class that builds an object of Configuration, based on a configuration file.

Public Member Functions

• def __init__

Constructor.

def parameterSet

Function that returns the value of wished parameter specified in the paramTag variable.

· def inputFunctionGet

Returns a numpy array with the values of the function for the whole simulation.

· def determineSynapses

Function used to determine all the synapses that a given pool makes.

Public Attributes

confArray

An array with all the simulation parameters.

timeStep_ms

Time step of the numerical solution of the differential equation.

· simDuration ms

Total length of the simulation in ms.

timeStepByTwo_ms

The variable timeStep divided by two, for computaional efficiency.

timeStepBySix_ms

The variable timeStep divided by six, for computaional efficiency.

7.4.1 Detailed Description

Class that builds an object of Configuration, based on a configuration file.

Definition at line 38 of file Configuration.py.

7.4.2 Constructor & Destructor Documentation

7.4.2.1 def Configuration.Configuration.__init__ (self, filename)

Constructor.

Builds the Configuration object. A Configuration object is responsible to set the variables that are used in the whole system, such as timeStep and simDuration.

- · Inputs:
 - filename: name of the file with the parameter values. The extension of the file should be .rmto.

Definition at line 52 of file Configuration.py.

7.4.3 Member Function Documentation

7.4.3.1 def Configuration.Configuration.determineSynapses (self, neuralSource)

Function used to determine all the synapses that a given pool makes.

It is used in the SynapsesFactory class.

- · Inputs:
 - neuralSource string with the pool name from which is desired to know what synapses it will make.
- · Outputs:
 - array of strings with all the synapses target that the neuralSource will make.

Definition at line 153 of file Configuration.py.

7.4.3.2 def Configuration.Configuration.inputFunctionGet (self, function)

Returns a numpy array with the values of the function for the whole simulation.

It is used to obtain before the simulation run all the values of the inputs.

- · Inputs:
 - function: function from which is desired to obtain its values during the simulation duration.
- · Output:
 - narray with the function values for each instant.

Definition at line 137 of file Configuration.py.

7.4.3.3 def Configuration.Configuration.parameterSet (self, paramTag, pool, index)

Function that returns the value of wished parameter specified in the paramTag variable.

In the case of min/max parameters, the value returned is the specific to the index of the unit that called the function.

- · Inputs:
 - paramTag: string with the name of the wished parameter as in the first column of the rmto file.
 - pool: pool from which the unit that will receive the parameter value belongs. For example SOL. It is
 used only in the parameters that have a range.
 - index: index of the unit. It is is an integer.
- · Outputs:
 - required parameter value

Definition at line 93 of file Configuration.py.

7.4.4 Member Data Documentation

7.4.4.1 Configuration.Configuration.confArray

An array with all the simulation parameters.

Definition at line 55 of file Configuration.py.

7.4.4.2 Configuration.Configuration.simDuration_ms

Total length of the simulation in ms.

Definition at line 65 of file Configuration.py.

7.4.4.3 Configuration.Configuration.timeStep_ms

Time step of the numerical solution of the differential equation.

Definition at line 62 of file Configuration.py.

7.4.4.4 Configuration.Configuration.timeStepBySix_ms

The variable timeStep divided by six, for computaional efficiency.

Definition at line 69 of file Configuration.py.

7.4.4.5 Configuration.Configuration.timeStepByTwo_ms

The variable timeStep divided by two, for computaional efficiency.

Definition at line 67 of file Configuration.py.

The documentation for this class was generated from the following file:

· Configuration.py

7.5 MotorUnit.MotorUnit Class Reference

Class that implements a motor unit model.

Public Member Functions

def init

Constructor.

· def atualizeMotorUnit

Atualize the dynamical and nondynamical (delay) parts of the motor unit.

· def atualizeCompartments

Atualize all neural compartments.

def dVdt

Compute the potential derivative of all compartments of the motor unit.

def addSomaSpike

When the soma potential is above the threshold a spike is added tom the soma.

def atualizeDelay

Atualize the terminal spike train, by considering the Delay of the nerve.

Public Attributes

· conf

Configuration object with the simulation parameters.

kind

String with the type of the motor unit.

tSomaSpike

The instant of the last spie of the Motor unit at the Soma compartment.

• somaSpikeTrain

Vector with the instants of spikes at the soma.

index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

· compartment

Vector of Compartment of the Motor Unit.

· threshold_mV

Value of the membrane potential, in mV, that is considered a spike.

compNumber

Number of compartments.

v_mV

Vector with membrane potential, in mV, of all compartments.

· capacitanceInv

Vector with the inverse of the capacitance of all compartments.

· ilonic

Vector with current, in nA, of each compartment coming from other elements of the model.

· ilnjected

Vector with the current, in nA, injected in each compartment.

• G

Matrix of the conductance of the motoneuron.

somaIndex

index of the soma compartment.

• MNRefPer_ms

Refractory period, in ms, of the motoneuron.

nerve

String with type of the nerve.

Delay

AxonDelay object of the motor unit.

· terminalSpikeTrain

Vector with the instants of spikes at the terminal.

TwitchTc_ms

Contraction time of the twitch muscle unit, in ms.

TwitchAmp_N

Amplutude of the muscle unit twitch, in N.

bSat

Parameter of the saturation.

twTet

Twitch- tetanus relationship.

7.5.1 Detailed Description

Class that implements a motor unit model.

Encompasses a motoneuron and a muscle unit.

Definition at line 147 of file MotorUnit.py.

7.5.2 Constructor & Destructor Documentation

7.5.2.1 def MotorUnit.MotorUnit.__init__ (self, conf, pool, index, kind)

Constructor.

- · Inputs:
 - conf: Configuration object with the simulation parameters.
 - **pool**: string with Motor unit pool to which the motor unit belongs.
 - index: integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).
 - kind: string with the type of the motor unit. It can be S (slow), FR (fast and resistant), and FF (fast and fatigable).

Definition at line 165 of file MotorUnit.py.

7.5.3 Member Function Documentation

7.5.3.1 def MotorUnit.MotorUnit.addSomaSpike (self, t)

When the soma potential is above the threshold a spike is added tom the soma.

- · Inputs:
 - t: current instant, in ms.

Definition at line 316 of file MotorUnit.py.

Here is the caller graph for this function:




7.5.3.2 def MotorUnit.MotorUnit.atualizeCompartments (self, t)

Atualize all neural compartments.

- · Inputs:
 - t: current instant, in ms.

Definition at line 286 of file MotorUnit.py.

Here is the call graph for this function:



Here is the caller graph for this function:



7.5.3.3 def MotorUnit.MotorUnit.atualizeDelay (self, t)

Atualize the terminal spike train, by considering the Delay of the nerve.

- · Inputs:
 - t: current instant, in ms.

Definition at line 332 of file MotorUnit.py.

Here is the caller graph for this function:




7.5.3.4 def MotorUnit.MotorUnit.atualizeMotorUnit (self, t)

Atualize the dynamical and nondynamical (delay) parts of the motor unit.

- · Inputs:
 - t: current instant, in ms.

Definition at line 274 of file MotorUnit.py.

Here is the call graph for this function:



7.5.3.5 def MotorUnit.MotorUnit.dVdt (self, t, V)

Compute the potential derivative of all compartments of the motor unit.

- · Inputs:
 - t: current instant, in ms.
 - V: Vector with the current potential value of all neural compartments of the motor unit.

Definition at line 301 of file MotorUnit.py.

Here is the caller graph for this function:



7.5.4 Member Data Documentation

7.5.4.1 MotorUnit.MotorUnit.bSat

Parameter of the saturation.

Definition at line 259 of file MotorUnit.py.

7.5.4.2 MotorUnit.MotorUnit.capacitanceInv

Vector with the inverse of the capacitance of all compartments.

Definition at line 211 of file MotorUnit.py.

7.5.4.3 MotorUnit.MotorUnit.compartment

Vector of Compartment of the Motor Unit.

Definition at line 182 of file MotorUnit.py.

7.5.4.4 MotorUnit.MotorUnit.compNumber

Number of compartments.

Definition at line 189 of file MotorUnit.py.

7.5.4.5 MotorUnit.MotorUnit.conf

Configuration object with the simulation parameters.

Definition at line 168 of file MotorUnit.py.

7.5.4.6 MotorUnit.MotorUnit.Delay

AxonDelay object of the motor unit.

Definition at line 244 of file MotorUnit.py.

7.5.4.7 MotorUnit.MotorUnit.G

Matrix of the conductance of the motoneuron.

Multiplied by the vector self.v_mV, results in the passive currents of each compartment.

Definition at line 226 of file MotorUnit.py.

7.5.4.8 MotorUnit.MotorUnit.ilnjected

Vector with the current, in nA, injected in each compartment.

Definition at line 217 of file MotorUnit.py.

7.5.4.9 MotorUnit.MotorUnit.ilonic

Vector with current, in nA, of each compartment coming from other elements of the model.

For example from ionic channels and synapses.

Definition at line 215 of file MotorUnit.py.

7.5.4.10 MotorUnit.MotorUnit.index

Integer corresponding to the motor unit order in the pool, according to the Henneman's principle (size principle).

Definition at line 180 of file MotorUnit.py.

7.5.4.11 MotorUnit.MotorUnit.kind

String with the type of the motor unit.

It can be S (slow), FR (fast and resistant) and FF (fast and fatigable).

Definition at line 171 of file MotorUnit.py.

7.5.4.12 MotorUnit.MotorUnit.MNRefPer_ms

Refractory period, in ms, of the motoneuron.

Definition at line 233 of file MotorUnit.py.

7.5.4.13 MotorUnit.MotorUnit.nerve

String with type of the nerve.

It can be PTN (posterior tibial nerve) or CPN (common peroneal nerve).

Definition at line 239 of file MotorUnit.py.

7.5.4.14 MotorUnit.MotorUnit.somaIndex

index of the soma compartment.

Definition at line 230 of file MotorUnit.py.

7.5.4.15 MotorUnit.MotorUnit.somaSpikeTrain

Vector with the instants of spikes at the soma.

Definition at line 178 of file MotorUnit.py.

7.5.4.16 MotorUnit.MotorUnit.terminalSpikeTrain

Vector with the instants of spikes at the terminal.

Definition at line 248 of file MotorUnit.py.

7.5.4.17 MotorUnit.MotorUnit.threshold_mV

Value of the membrane potential, in mV, that is considered a spike.

Definition at line 184 of file MotorUnit.py.

7.5.4.18 MotorUnit.MotorUnit.tSomaSpike

The instant of the last spie of the Motor unit at the Soma compartment.

Definition at line 175 of file MotorUnit.py.

7.5.4.19 MotorUnit.MotorUnit.TwitchAmp_N

Amplutude of the muscle unit twitch, in N.

Definition at line 257 of file MotorUnit.py.

7.5.4.20 MotorUnit.MotorUnit.TwitchTc_ms

Contraction time of the twitch muscle unit, in ms.

Definition at line 255 of file MotorUnit.py.

7.5.4.21 MotorUnit.MotorUnit.twTet

Twitch- tetanus relationship.

Definition at line 261 of file MotorUnit.py.

7.5.4.22 MotorUnit.MotorUnit.v_mV

Vector with membrane potential,in mV, of all compartments.

Definition at line 191 of file MotorUnit.py.

The documentation for this class was generated from the following file:

MotorUnit.py

7.6 MotorUnitPool.MotorUnitPool Class Reference

Class that implements a motor unit pool.

Public Member Functions

def __init__

Constructor.

- · def atualizeMotorUnitPool
- · def atualizeActivationSignal
- · def atualizeForceNoHill

Compute the muscle force when no muscle dynamics (Hill model) is used.

· def listSpikes

Public Attributes

kind

Indicates that is Motor Unit pool.

· conf

Configuration object with the simulation parameters.

pool

String with Motor unit pool to which the motor unit belongs.

MUnumber

Number of motor units.

unit

List of MotorUnit objects.

· poolSomaSpikes

Vector with the instants of spikes in the soma compartment, in ms.

• poolTerminalSpikes

Vector with the instants of spikes in the terminal, in ms.

activationModel

Model of the activation signal.

- ActMatrix
- an
- · activation_nonSat
- bSat
- twTet
- twitchAmp_N
- · activation_Sat
- diracDeltaValue
- force
- hillModel
- · atualizeForce
- timeIndex

7.6.1 Detailed Description

Class that implements a motor unit pool.

Encompasses a set of motor units that controls a single muscle.

Definition at line 40 of file MotorUnitPool.py.

7.6.2 Constructor & Destructor Documentation

7.6.2.1 def MotorUnitPool.MotorUnitPool.__init__ (self, conf, pool)

Constructor.

- · Inputs:
 - conf: Configuration object with the simulation parameters.
 - pool: string with Motor unit pool to which the motor unit belongs.

Definition at line 52 of file MotorUnitPool.py.

7.6.3 Member Function Documentation


7.6.3.1 def MotorUnitPool.MotorUnitPool.atualizeActivationSignal (self, t)

Definition at line 136 of file MotorUnitPool.py.

Here is the call graph for this function:



Here is the caller graph for this function:



7.6.3.2 def MotorUnitPool.MotorUnitPool.atualizeForceNoHill (self)

Compute the muscle force when no muscle dynamics (Hill model) is used.

Definition at line 152 of file MotorUnitPool.py.

7.6.3.3 def MotorUnitPool.MotorUnitPool.atualizeMotorUnitPool (self, t)

Definition at line 129 of file MotorUnitPool.py.

Here is the call graph for this function:



7.6.3.4 def MotorUnitPool.MotorUnitPool.listSpikes (self)

Definition at line 157 of file MotorUnitPool.py.

7.6.4 Member Data Documentation

7.6.4.1 MotorUnitPool.MotorUnitPool.activation_nonSat

Definition at line 105 of file MotorUnitPool.py.

7.6.4.2 MotorUnitPool.MotorUnitPool.activation_Sat

Definition at line 114 of file MotorUnitPool.py.

7.6.4.3 MotorUnitPool.MotorUnitPool.activationModel

Model of the activation signal.

For now, it can be SOCDS (second order critically damped system).

Definition at line 86 of file MotorUnitPool.py.

7.6.4.4 MotorUnitPool.MotorUnitPool.ActMatrix

Definition at line 94 of file MotorUnitPool.py.

7.6.4.5 MotorUnitPool.MotorUnitPool.an

Definition at line 103 of file MotorUnitPool.py.

7.6.4.6 MotorUnitPool.MotorUnitPool.atualizeForce

Definition at line 121 of file MotorUnitPool.py.

7.6.4.7 MotorUnitPool.MotorUnitPool.bSat

Definition at line 106 of file MotorUnitPool.py.

7.6.4.8 MotorUnitPool.MotorUnitPool.conf

Configuration object with the simulation parameters.

Definition at line 58 of file MotorUnitPool.py.

7.6.4.9 MotorUnitPool.MotorUnitPool.diracDeltaValue

Definition at line 116 of file MotorUnitPool.py.

7.6.4.10 MotorUnitPool.MotorUnitPool.force

Definition at line 119 of file MotorUnitPool.py.

7.6.4.11 MotorUnitPool.MotorUnitPool.hillModel

Definition at line 120 of file MotorUnitPool.py.

7.6.4.12 MotorUnitPool.MotorUnitPool.kind

Indicates that is Motor Unit pool.

Definition at line 55 of file MotorUnitPool.py.

7.6.4.13 MotorUnitPool.MotorUnitPool.MUnumber

Number of motor units.

Definition at line 65 of file MotorUnitPool.py.

7.6.4.14 MotorUnitPool.MotorUnitPool.pool

String with Motor unit pool to which the motor unit belongs.

Definition at line 60 of file MotorUnitPool.py.

7.6.4.15 MotorUnitPool.MotorUnitPool.poolSomaSpikes

Vector with the instants of spikes in the soma compartment, in ms.

Definition at line 80 of file MotorUnitPool.py.

7.6.4.16 MotorUnitPool.MotorUnitPool.poolTerminalSpikes

Vector with the instants of spikes in the terminal, in ms.

Definition at line 82 of file MotorUnitPool.py.

7.6.4.17 MotorUnitPool.MotorUnitPool.timeIndex

Definition at line 123 of file MotorUnitPool.py.

7.6.4.18 MotorUnitPool.MotorUnitPool.twitchAmp_N

Definition at line 108 of file MotorUnitPool.py.

7.6.4.19 MotorUnitPool.MotorUnitPool.twTet

Definition at line 107 of file MotorUnitPool.py.

7.6.4.20 MotorUnitPool.MotorUnitPool.unit

List of MotorUnit objects.

Definition at line 68 of file MotorUnitPool.py.

The documentation for this class was generated from the following file:

MotorUnitPool.py

7.7 NeuralTract.NeuralTract Class Reference

classdocs

Public Member Functions

def __init__

Constructor.

- · def atualizePool
- · def listSpikes

Public Attributes

- kind
- · pool
- Number
- unit
- poolTerminalSpikes
- target
- FR
- timeIndex

7.7.1 Detailed Description

classdocs

Definition at line 14 of file NeuralTract.py.

7.7.2 Constructor & Destructor Documentation

 $7.7.2.1 \quad def \ Neural Tract. \underline{\hspace{0.5cm}} nit \underline{\hspace{0.5cm}} (\quad \textit{self, conf, pool })$

Constructor.

- · Inputs:
 - conf:
 - pool:

Definition at line 26 of file NeuralTract.py.

7.7.3 Member Function Documentation

7.7.3.1 def NeuralTract.NeuralTract.atualizePool (self, t)

Definition at line 50 of file NeuralTract.py.

7.7.3.2 def NeuralTract.NeuralTract.listSpikes (self)

Definition at line 55 of file NeuralTract.py.

7.7.4 Member Data Documentation

7.7.4.1 NeuralTract.NeuralTract.FR

Definition at line 43 of file NeuralTract.py.

7.7.4.2 NeuralTract.NeuralTract.kind

Definition at line 27 of file NeuralTract.py.

7.7.4.3 NeuralTract.NeuralTract.Number

Definition at line 29 of file NeuralTract.py.

7.7.4.4 NeuralTract.NeuralTract.pool

Definition at line 28 of file NeuralTract.py.

7.7.4.5 NeuralTract.NeuralTract.poolTerminalSpikes

Definition at line 34 of file NeuralTract.py.

7.7.4.6 NeuralTract.NeuralTract.target

Definition at line 36 of file NeuralTract.py.

7.7.4.7 NeuralTract.NeuralTract.timeIndex

Definition at line 46 of file NeuralTract.py.

7.7.4.8 NeuralTract.NeuralTract.unit

Definition at line 31 of file NeuralTract.py.

The documentation for this class was generated from the following file:

NeuralTract.py

7.8 NeuralTractUnit.NeuralTractUnit Class Reference

classdocs

Public Member Functions

- def __init__
 - Constructor.
- · def atualizeNeuralTractUnit
- · def transmitSpikes

Public Attributes

- GammaOrder
- · spikesGenerator
- terminalSpikeTrain
- SynapsesOut
- transmitSpikesThroughSynapses
- indicesOfSynapsesOnTarget

7.8.1 Detailed Description

classdocs

Definition at line 20 of file NeuralTractUnit.py.

7.8.2 Constructor & Destructor Documentation

7.8.2.1 def NeuralTractUnit.NeuralTractUnit.__init__ (self, conf, pool, index)

Constructor.

Definition at line 27 of file NeuralTractUnit.py.

7.8.3 Member Function Documentation

7.8.3.1 def NeuralTractUnit.NeuralTractUnit.atualizeNeuralTractUnit (self, t, FR)

Definition at line 49 of file NeuralTractUnit.py.


Here is the call graph for this function:



7.8.3.2 def NeuralTractUnit.NeuralTractUnit.transmitSpikes (self, t)

Definition at line 59 of file NeuralTractUnit.py.

Here is the caller graph for this function:



7.8.4 Member Data Documentation

7.8.4.1 NeuralTractUnit.NeuralTractUnit.GammaOrder

Definition at line 29 of file NeuralTractUnit.py.

 $7.8.4.2 \quad Neural Tract Unit. Neural Tract Unit. indices Of Synapses On Target$

Definition at line 41 of file NeuralTractUnit.py.

7.8.4.3 NeuralTractUnit.NeuralTractUnit.spikesGenerator

Definition at line 32 of file NeuralTractUnit.py.

7.8.4.4 NeuralTractUnit.NeuralTractUnit.SynapsesOut

Definition at line 39 of file NeuralTractUnit.py.

7.8.4.5 NeuralTractUnit.NeuralTractUnit.terminalSpikeTrain

Definition at line 33 of file NeuralTractUnit.py.

7.8.4.6 NeuralTractUnit.NeuralTractUnit.transmitSpikesThroughSynapses

Definition at line 40 of file NeuralTractUnit.py.

The documentation for this class was generated from the following file:

NeuralTractUnit.py

7.9 PointProcessGenerator.PointProcessGenerator Class Reference

Generator of point processes.

Public Member Functions

def __init__

Constructor.

· def atualizeGenerator

Public Attributes

GammaOrder

Integer order of the Gamma distribution.

GammaOrderInv

Inverse of the GammaOrder.

• index

Integer corresponding to the unit order in the pool to which this generator is associated.

• y

Auxiliary variable cummulating a value that indicates whether there will be a new spike or not.

· threshold

Spike threshold.

points

List of spike instants of the generator.

7.9.1 Detailed Description

Generator of point processes.

Definition at line 46 of file PointProcessGenerator.py.

7.9.2 Constructor & Destructor Documentation

7.9.2.1 def PointProcessGenerator.PointProcessGenerator.__init__ (self, GammaOrder, index)

Constructor.

- Inputs:
 - GammaOrder: integer order of the Gamma distribution.
 - index: integer corresponding to the unit order in the pool.

Definition at line 57 of file PointProcessGenerator.py.

7.9.3 Member Function Documentation

7.9.3.1 def PointProcessGenerator.PointProcessGenerator.atualizeGenerator (self, t, firingRate)

- Inputs:
 - t: current instant, in ms.
 - firingRate: instant firing rate, in spikes/s.

Definition at line 86 of file PointProcessGenerator.py.

Here is the call graph for this function:



7.9.4 Member Data Documentation

7.9.4.1 PointProcessGenerator.PointProcessGenerator.GammaOrder

Integer order of the Gamma distribution.

Gamma order 1 is Poisson process and order 10 is a Gaussian process.

Definition at line 60 of file PointProcessGenerator.py.

7.9.4.2 PointProcessGenerator.PointProcessGenerator.GammaOrderInv

Inverse of the GammaOrder.

This is necessary for computational efficiency.

Definition at line 63 of file PointProcessGenerator.py.

7.9.4.3 PointProcessGenerator.PointProcessGenerator.index

Integer corresponding to the unit order in the pool to which this generator is associated.

Definition at line 66 of file PointProcessGenerator.py.

7.9.4.4 PointProcessGenerator.PointProcessGenerator.points

List of spike instants of the generator.

Definition at line 76 of file PointProcessGenerator.py.

7.9.4.5 PointProcessGenerator.PointProcessGenerator.threshold

Spike threshold.

When the auxiliary variable y reaches the value of threshold, there is a new spike.

Definition at line 74 of file PointProcessGenerator.py.

7.9.4.6 PointProcessGenerator.PointProcessGenerator.y

Auxiliary variable cummulating a value that indicates whether there will be a new spike or not.

Definition at line 70 of file PointProcessGenerator.py.

The documentation for this class was generated from the following file:

· PointProcessGenerator.py

7.10 PulseConductanceState.PulseConductanceState Class Reference

Implements the Destexhe pulse approximation of the solution of the states of the Hodgkin-Huxley neuron model.

Public Member Functions

def __init__

Initializes the pulse conductance state.

· def changeState

Void function that modify the current situation (true/false) of the state.

· def computeStateValue

Compute the state value by using the approximation of Destexhe (1997) to compute the Hodgkin-Huxley states.

Public Attributes

- kind
- value
- v0
- t0
- state
- beta_ms1
- alpha_ms1
- PulseDur_ms
- actType
- computeValueOn
- computeValueOff

7.10.1 Detailed Description

Implements the Destexhe pulse approximation of the solution of the states of the Hodgkin-Huxley neuron model. Definition at line 54 of file PulseConductanceState.py.

7.10.2 Constructor & Destructor Documentation

7.10.2.1 def PulseConductanceState.PulseConductanceState.__init__ (self, kind, conf, pool, index)

Initializes the pulse conductance state.

Variables: kind - type of the state(m, h, n, q). conf - an instance of the Configuration class with the functions to correctly parameterize the model. See the Configuration class. pool - the pool that this state belongs. index - the index of the unit that this state belongs.

Definition at line 65 of file PulseConductanceState.py.

7.10.3 Member Function Documentation

7.10.3.1 def PulseConductanceState.PulseConductanceState.changeState (self, t)

Void function that modify the current situation (true/false) of the state.

- · Inputs:
 - t: current instant, in ms.

Definition at line 104 of file PulseConductanceState.py.

Here is the caller graph for this function:




7.10.3.2 def PulseConductanceState.PulseConductanceState.computeStateValue (self, t)

Compute the state value by using the approximation of Destexhe (1997) to compute the Hodgkin-Huxley states.

- Input:
 - t: current instant, in ms.

Definition at line 116 of file PulseConductanceState.py.

Here is the call graph for this function:



7.10.4 Member Data Documentation

7.10.4.1 PulseConductanceState.PulseConductanceState.actType

Definition at line 80 of file PulseConductanceState.py.

7.10.4.2 PulseConductanceState.PulseConductanceState.alpha_ms1

Definition at line 76 of file PulseConductanceState.py.

7.10.4.3 PulseConductanceState.PulseConductanceState.beta_ms1

Definition at line 75 of file PulseConductanceState.py.

7.10.4.4 PulseConductanceState.PulseConductanceState.computeValueOff

Definition at line 90 of file PulseConductanceState.py.

7.10.4.5 PulseConductanceState.PulseConductanceState.computeValueOn

Definition at line 89 of file PulseConductanceState.py.

7.10.4.6 PulseConductanceState.PulseConductanceState.kind

Definition at line 66 of file PulseConductanceState.py.

7.10.4.7 PulseConductanceState.PulseConductanceState.PulseDur ms

Definition at line 77 of file PulseConductanceState.py.

7.10.4.8 PulseConductanceState.PulseConductanceState.state

Definition at line 73 of file PulseConductanceState.py.

7.10.4.9 PulseConductanceState.PulseConductanceState.t0

Definition at line 71 of file PulseConductanceState.py.

7.10.4.10 PulseConductanceState.PulseConductanceState.v0

Definition at line 70 of file PulseConductanceState.py.

7.10.4.11 PulseConductanceState.PulseConductanceState.value

Definition at line 67 of file PulseConductanceState.py.

The documentation for this class was generated from the following file:

PulseConductanceState.py

7.11 Synapse.Synapse Class Reference

Implements the synapse model from Destexhe (1994) using the computational method from Lytton (1996).

Public Member Functions

def init

Constructor.

Public Attributes

- pool
- kind
- neuronKind
- EqPot_mV
- alpha_ms1
- beta_ms1
- Tmax_mM
- tPeak_ms

Pulse duration, in ms.

- · gmax muS
- · delay_ms
- dynamics
- gMaxTot_muS

The sum of individual conductances of all synapses in the compartment, in μS ($G_{max} = \sum_{i=1}^{N} g_i$).

- numberOfIncomingSynapses
- · rInf

The fraction of postsynaptic receptors that would be bound to neurotransmitters after an infinite amount of time with neurotransmitter being released.

• tauOn

Time constant during a pulse, in ms.

tauOff

Time constant after a pulse, in ms.

expFinish

Is the value of the exponential at the end of the pulse.

• Non

Sum of the fractions of the individual conductances that are receiving neurotransmitter (during pulse) relative to the G_{max} .

• Ron

Sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).

Roff

Sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

• t0

Instant that the last spike arrived to the compartment.

- conductanceState
- tBeginOfPulse
- tEndOfPulse
- ri

List with the fractions of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.

• ti

List with the instants of spike arriving at each conductance, in ms.

7.11.1 Detailed Description

Implements the synapse model from Destexhe (1994) using the computational method from Lytton (1996). Definition at line 305 of file Synapse.py.

7.11.2 Constructor & Destructor Documentation 7.11.2.1 def Synapse.Synapse.__init__ (self, conf, pool, index, compartment, kind, neuronKind) Constructor. • Input: - conf: - pool: - index: - compartment: - kind: - neuronKind: Definition at line 323 of file Synapse.py. 7.11.3 Member Data Documentation 7.11.3.1 Synapse.Synapse.alpha_ms1 Definition at line 329 of file Synapse.py. 7.11.3.2 Synapse.Synapse.beta_ms1 Definition at line 330 of file Synapse.py. 7.11.3.3 Synapse.Synapse.conductanceState Definition at line 376 of file Synapse.py. 7.11.3.4 Synapse.Synapse.delay_ms Definition at line 336 of file Synapse.py. 7.11.3.5 Synapse.Synapse.dynamics Definition at line 337 of file Synapse.py. 7.11.3.6 Synapse.Synapse.EqPot_mV Definition at line 328 of file Synapse.py. 7.11.3.7 Synapse.Synapse.expFinish

Is the value of the exponential at the end of the pulse.

It is computed as $\exp(T_{dur}/\tau_{on})$.

Definition at line 358 of file Synapse.py.

7.11.3.8 Synapse.Synapse.gmax_muS

Definition at line 335 of file Synapse.py.

7.11.3.9 Synapse.Synapse.gMaxTot_muS

The sum of individual conductances of all synapses in the compartment, in μ S ($G_{max} = \sum_{i=1}^{N} g_i$).

Definition at line 341 of file Synapse.py.

7.11.3.10 Synapse.Synapse.kind

Definition at line 325 of file Synapse.py.

7.11.3.11 Synapse.Synapse.neuronKind

Definition at line 326 of file Synapse.py.

7.11.3.12 Synapse.Synapse.Non

Sum of the fractions of the individual conductances that are receiving neurotransmitter (during pulse) relative to the G_{max} .

Definition at line 363 of file Synapse.py.

7.11.3.13 Synapse.Synapse.numberOfIncomingSynapses

Definition at line 342 of file Synapse.py.

7.11.3.14 Synapse.Synapse.pool

Definition at line 324 of file Synapse.py.

7.11.3.15 Synapse.Synapse.ri

List with the fractions of postsynaptic receptors that are bound to neurotransmitters of the individual synapses.

Definition at line 382 of file Synapse.py.

7.11.3.16 Synapse.Synapse.rlnf

The fraction of postsynaptic receptors that would be bound to neurotransmitters after an infinite amount of time with neurotransmitter being released.

Definition at line 348 of file Synapse.py.

7.11.3.17 Synapse.Synapse.Roff

Sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

Definition at line 372 of file Synapse.py.

7.11.3.18 Synapse.Synapse.Ron

Sum of the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).

Definition at line 367 of file Synapse.py.

7.11.3.19 Synapse.Synapse.t0

Instant that the last spike arrived to the compartment.

Definition at line 374 of file Synapse.py.

7.11.3.20 Synapse.Synapse.tauOff

Time constant after a pulse, in ms.

$$\tau_{off} = \frac{1}{B}$$

Definition at line 354 of file Synapse.py.

7.11.3.21 Synapse.Synapse.tauOn

Time constant during a pulse, in ms.

$$\tau_{on} = \frac{1}{\alpha.T_{max} + \beta}$$

Definition at line 351 of file Synapse.py.

7.11.3.22 Synapse.Synapse.tBeginOfPulse

Definition at line 377 of file Synapse.py.

7.11.3.23 Synapse.Synapse.tEndOfPulse

Definition at line 378 of file Synapse.py.

7.11.3.24 Synapse.Synapse.ti

List with the instants of spike arriving at each conductance, in ms.

Definition at line 385 of file Synapse.py.

7.11.3.25 Synapse.Synapse.Tmax_mM

Definition at line 331 of file Synapse.py.

7.11.3.26 Synapse.Synapse.tPeak_ms

Pulse duration, in ms.

Definition at line 333 of file Synapse.py.

The documentation for this class was generated from the following file:

Synapse.py

7.12 SynapsesFactory.SynapsesFactory Class Reference

Class to build all the synapses in the system.

Public Member Functions

• def __init__ Constructor.

Public Attributes

numberOfSynapses

7.12.1 Detailed Description

Class to build all the synapses in the system.

Definition at line 15 of file SynapsesFactory.py.

7.12.2 Constructor & Destructor Documentation

7.12.2.1 def SynapsesFactory.SynapsesFactory.__init__ (self, conf, pools)

Constructor.

Definition at line 24 of file SynapsesFactory.py.

7.12.3 Member Data Documentation

 $7.12.3.1 \quad Synapses Factory. Synapses Factory. number Of Synapses$

Definition at line 26 of file SynapsesFactory.py.

The documentation for this class was generated from the following file:

SynapsesFactory.py

Chapter 8

File Documentation

8.1 AxonDelay.py File Reference

Classes

• class AxonDelay.AxonDelay

Class that implements a delay correspondent to the nerve.

Namespaces

AxonDelay

8.2 ChannelConductance.py File Reference

Classes

• class ChannelConductance.ChannelConductance

Class that implements a model of the ionic Channels in a compartment.

Namespaces

• ChannelConductance

8.3 Compartment.py File Reference

Classes

· class Compartment.Compartment

Class that implements a neural compartment.

Namespaces

Compartment

62 File Documentation

Functions

· def Compartment.calcGLeak

Computes the leak conductance of the compartment.

8.4 Configuration.py File Reference

Classes

· class Configuration. Configuration

Class that builds an object of Configuration, based on a configuration file.

Namespaces

Configuration

8.5 MotorUnit.py File Reference

Classes

· class MotorUnit.MotorUnit

Class that implements a motor unit model.

Namespaces

• MotorUnit

Functions

• def MotorUnit.calcGCoupling

Calculates the coupling conductance between two compartments.

• def MotorUnit.compGCouplingMatrix

Computes the Coupling Matrix to be used in the dVdt function of the N compartments of the motor unit.

· def MotorUnit.runge_kutta

Function to implement the fourth order Runge-Kutta Method to solve numerically a differential equation.

8.6 MotorUnitPool.py File Reference

Classes

· class MotorUnitPool.MotorUnitPool

Class that implements a motor unit pool.

Namespaces

MotorUnitPool

Functions

• def MotorUnitPool.twitchSaturation

Computes the muscle unit force after the nonlinear saturation.

8.7 NeuralTract.py File Reference

Classes

· class NeuralTract.NeuralTract

classdocs

Namespaces

NeuralTract

8.8 NeuralTractUnit.py File Reference

Classes

• class NeuralTractUnit.NeuralTractUnit

classdocs

Namespaces

NeuralTractUnit

8.9 PointProcessGenerator.py File Reference

Classes

· class PointProcessGenerator.PointProcessGenerator

Generator of point processes.

Namespaces

· PointProcessGenerator

Functions

• def PointProcessGenerator.gammaPoint

Generates a number according to a Gamma Distribution with an integer order GammaOrder.

64 File Documentation

8.10 PulseConductanceState.py File Reference

Classes

· class PulseConductanceState.PulseConductanceState

Implements the Destexhe pulse approximation of the solution of the states of the Hodgkin-Huxley neuron model.

Namespaces

• PulseConductanceState

Functions

• def PulseConductanceState.compValOn

Time course of the state during the pulse for the inactivation states and before and after the pulse for the activation states

• def PulseConductanceState.compValOff

Time course of the state during the pulse for the activation states and before and after the pulse for the inactivation states.

8.11 simulation.py File Reference

Namespaces

simulation

Functions

· def simulation.simulador

8.12 Synapse.py File Reference

Classes

• class Synapse.Synapse

Implements the synapse model from Destexhe (1994) using the computational method from Lytton (1996).

Namespaces

Synapse

Functions

· def Synapse.compSynapCond

Computes the synaptic conductance.

def Synapse.compRon

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that have neurotransmitters being released (during the pulse).

• def Synapse.compRoff

Computes the fraction of postsynaptic receptors that are bound to neurotransmitters of all the individual synapses that do not have neurotransmitters being released (before and after the pulse).

· def Synapse.compRiStart

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter begin (begin of the pulse).

· def Synapse.compRiStop

Computes the fraction of bound postsynaptic receptors to neurotransmitters in individual synapses when the neurotransmitter release stops (the pulse ends).

• def Synapse.compRonStart

Incorporates a new conductance to the set of conductances during a pulse.

def Synapse.compRoffStart

Incorporates a new conductance to the set of conductances that are not during a pulse.

def Synapse.compRonStop

Removes a conductance from the set of conductances during a pulse.

· def Synapse.compRoffStop

Removes a conductance from the set of conductances that are not during a pulse.

8.13 SynapsesFactory.py File Reference

Classes

· class SynapsesFactory.SynapsesFactory

Class to build all the synapses in the system.

Namespaces

SynapsesFactory

Index

init	MotorUnitPool::MotorUnitPool, 38
AxonDelay::AxonDelay, 20	atualizeForceNoHill
ChannelConductance::ChannelConductance, 23	MotorUnitPool::MotorUnitPool, 37
Compartment::Compartment, 25	atualizeGenerator
Configuration::Configuration, 27	PointProcessGenerator::PointProcessGenerator,
MotorUnit::MotorUnit, 31	44
MotorUnitPool::MotorUnitPool, 37	atualizeMotorUnit
NeuralTract::NeuralTract, 40	MotorUnit::MotorUnit, 32
NeuralTractUnit::NeuralTractUnit, 42	atualizeMotorUnitPool
PointProcessGenerator::PointProcessGenerator,	MotorUnitPool::MotorUnitPool, 37
44	atualizeNeuralTractUnit
PulseConductanceState::PulseConductanceState,	NeuralTractUnit::NeuralTractUnit, 42
45	atualizePool
Synapse::Synapse, 48	NeuralTract::NeuralTract, 40
SynapsesFactory::SynapsesFactory, 55	AxonDelay, 11
	AxonDelay, AxonDelay, 19
ActMatrix	AxonDelay.py, 57
MotorUnitPool::MotorUnitPool, 38	AxonDelay::AxonDelay
actType	init, 20
PulseConductanceState::PulseConductanceState,	addSpinalSpike, 20
46	addTerminalSpike, 20
activation_Sat	index, 21
MotorUnitPool::MotorUnitPool, 38	latencySpinalTerminal_ms, 21
activation_nonSat	latencyStimulusSpinal_ms, 21
MotorUnitPool::MotorUnitPool, 38	latencyStimulusTerminal ms, 21
activationModel	length_m, 21
MotorUnitPool::MotorUnitPool, 38	stimulusPositiontoTerminal, 21
addConductance	terminalSpikeTrain, 21
Synapse::Synapse, 48	velocity_m_s, 22
addSomaSpike	
MotorUnit::MotorUnit, 31	bSat
addSpinalSpike	MotorUnit::MotorUnit, 33
AxonDelay::AxonDelay, 20	MotorUnitPool::MotorUnitPool, 38
addTerminalSpike	beta ms1
AxonDelay::AxonDelay, 20	PulseConductanceState::PulseConductanceState,
alpha_ms1	46
PulseConductanceState::PulseConductanceState,	Synapse::Synapse, 51
46	
Synapse::Synapse, 51	calcGCoupling
an	MotorUnit, 12
MotorUnitPool::MotorUnitPool, 38	calcGLeak
area_cm2	Compartment, 11
Compartment::Compartment, 25	capacitance_nF
atualizeActivationSignal	Compartment::Compartment, 25
MotorUnitPool::MotorUnitPool, 37	capacitanceInv
atualizeCompartments	MotorUnit::MotorUnit, 33
MotorUnit::MotorUnit, 31	changeState
atualizeDelay	PulseConductanceState::PulseConductanceState,
MotorUnit::MotorUnit, 32	45
atualizeForce	ChannelConductance, 11

ChannelConductance.ChannelConductance, 22 ChannelConductance.py, 57 ChannelConductance::ChannelConductanceinit, 23	init, 25 area_cm2, 25 capacitance_nF, 25 Channels, 25
compCond, 24	computeCurrent, 25
compCondKf, 23	diameter_mum, 25
compCondKs, 23	gLeak, 26
•	index, 26
compCondNa, 23 computeCurrent, 23	kind, 26
condState, 24	length_mum, 26
	neuronKind, 26
EqPot_mV, 24 gmax muS, 24	numberChannels, 26
-	numberofMultiSynapses, 26
kind, 24	specifRes_Ohmcm2, 26
lenStates, 24	SynapsesIn, 26
stateType, 24	SynapsesOut, 26
Channels OF	computeConductance
Compartment::Compartment, 25	Synapse::Synapse, 48
compCond	computeCurrent
ChannelConductance::ChannelConductance, 24	ChannelConductance::ChannelConductance, 23
compCondKf	Compartment::Compartment, 25
ChannelConductance::ChannelConductance, 23	Synapse::Synapse, 49, 51
compCondKs	computeCurrent2
ChannelConductance::ChannelConductance, 23	Synapse::Synapse, 49
compCondNa	computeForce
ChannelConductance::ChannelConductance, 23	MotorUnitPool, 14
compGCouplingMatrix	computeStateValue
MotorUnit, 12	PulseConductanceState::PulseConductanceState,
compNumber	45
MotorUnit::MotorUnit, 34	
compRiStart	computeValueOff
Synapse, 16	PulseConductanceState::PulseConductanceState,
compRiStop	
Synapse, 16	computeValueOn
compRoff	PulseConductanceState::PulseConductanceState,
Synapse, 16	condState
compRoffStart	
Synapse, 17	ChannelConductance::ChannelConductance, 24 conductanceState
compRoffStop	
Synapse, 17	Synapse::Synapse, 52
compRon	conf MotorUnit::MotorUnit, 34
Synapse, 17	
compRonStart	MotorUnitPool::MotorUnitPool, 38
Synapse, 17	confArray
compRonStop	Configuration::Configuration, 28
Synapse, 18	Configuration, 12
compSynapCond	Configuration.Configuration, 27
Synapse, 18	Configuration.py, 58
compValOff	Configuration::Configuration
PulseConductanceState, 15	init, 27
compValOn	confArray, 28
PulseConductanceState, 15	determineSynapses, 28
Compartment, 11	inputFunctionGet, 28
calcGLeak, 11	parameterSet, 28
compartment	simDuration_ms, 28
MotorUnit::MotorUnit, 33	timeStep_ms, 29
Compartment.Compartment, 24	timeStepBySix_ms, 29
Compartment.compartment, 24 Compartment.py, 57	timeStepByTwo_ms, 29
Compartment::Compartment	dVdt
oompartmentoompartment	uvul

MotorUnit::MotorUnit, 33 Delay	inputFunctionGet Configuration::Configuration, 28
MotorUnit::MotorUnit, 34	
delay_ms	kind
Synapse::Synapse, 52	ChannelConductance::ChannelConductance, 24
determineSynapses	Compartment::Compartment, 26
Configuration::Configuration, 28	MotorUnit::MotorUnit, 34
diameter_mum	MotorUnitPool::MotorUnitPool, 39
Compartment::Compartment, 25	NeuralTract::NeuralTract, 40
diracDeltaValue	PulseConductanceState::PulseConductanceState
MotorUnitPool::MotorUnitPool, 38	46
dynamics	Synapse::Synapse, 52
Synapse::Synapse, 52	latanay Chinal Tarminal ma
· · · ·	latencySpinalTerminal_ms
EqPot_mV	AxonDelay::AxonDelay, 21
ChannelConductance::ChannelConductance, 24	latencyStimulusSpinal_ms
Synapse::Synapse, 52	AxonDelay::AxonDelay, 21
expFinish	latencyStimulusTerminal_ms
Synapse::Synapse, 52	AxonDelay::AxonDelay, 21 lenStates
5 D	
FR IT I I I	ChannelConductance::ChannelConductance, 24
NeuralTract::NeuralTract, 40	length_m
force	AxonDelay::AxonDelay, 21
MotorUnitPool::MotorUnitPool, 39	length_mum
6	Compartment::Compartment, 26
G	listSpikes
MotorUnit::MotorUnit, 34	MotorUnitPool::MotorUnitPool, 38
gLeak	NeuralTract::NeuralTract, 40
Compartment::Compartment, 26	MNRefPer_ms
gMaxTot_muS	MotorUnit::MotorUnit, 34
Synapse::Synapse, 52	MUnumber
GammaOrder	MotorUnitPool::MotorUnitPool, 39
NeuralTractUnit::NeuralTractUnit, 42	MotorUnit, 12
PointProcessGenerator::PointProcessGenerator,	calcGCoupling, 12
44 Commo Ordovinu	compGCouplingMatrix, 12
GammaOrderInv PointProcessGenerator::PointProcessGenerator,	runge_kutta, 13
	MotorUnit.MotorUnit, 29
44 commo Point	MotorUnit.py, 58
gammaPoint	MotorUnit::MotorUnit
PointProcessGenerator, 15	init, 31
gmax_muS ChannelConductance::ChannelConductance, 24	addSomaSpike, 31
Synapse::Synapse, 52	atualizeCompartments, 31
SynapseSynapse, 32	atualizeDelay, 32
hillModel	atualizeMotorUnit, 32
MotorUnitPool::MotorUnitPool, 39	bSat, 33
Wotor Gritti GoiWotor Gritti Goi, Go	capacitanceInv, 33
ilnjected	compNumber, 34
MotorUnit::MotorUnit, 34	compartment, 33
ilonic	conf, 34
MotorUnit::MotorUnit, 34	dVdt, 33
index	Delay, 34
AxonDelay::AxonDelay, 21	G, 34
Compartment::Compartment, 26	ilnjected, 34
MotorUnit::MotorUnit, 34	ilonic, 34
PointProcessGenerator::PointProcessGenerator,	index, 34
44	kind, 34
indicesOfSynapsesOnTarget	MNRefPer_ms, 34
NeuralTractUnit::NeuralTractUnit, 42	nerve, 35
····, ·—	•

somalndex, 35	NeuralTractUnit.NeuralTractUnit, 41
somaSpikeTrain, 35	NeuralTractUnit.py, 59
tSomaSpike, 35	NeuralTractUnit::NeuralTractUnit
terminalSpikeTrain, 35	init , 42
threshold_mV, 35	atualizeNeuralTractUnit, 42
twTet, 35	GammaOrder, 42
TwitchAmp_N, 35	indicesOfSynapsesOnTarget, 42
TwitchTc_ms, 35	spikesGenerator, 43
v mV, 36	SynapsesOut, 43
MotorUnitPool, 13	terminalSpikeTrain, 43
	•
computeForce, 14	transmitSpikes, 42
twitchSaturation, 14	transmitSpikesThroughSynapses, 43
MotorUnitPool, MotorUnitPool, 36	neuronKind
MotorUnitPool.py, 58	Compartment::Compartment, 26
MotorUnitPool::MotorUnitPool	Synapse::Synapse, 52
init, 37	Non
ActMatrix, 38	Synapse::Synapse, 52
activation_Sat, 38	Number
activation_nonSat, 38	NeuralTract::NeuralTract, 41
activationModel, 38	numberChannels
an, 38	Compartment::Compartment, 26
atualizeActivationSignal, 37	numberOfIncomingSynapses
atualizeForce, 38	Synapse::Synapse, 52
atualizeForceNoHill, 37	numberOfSynapses
atualizeMotorUnitPool, 37	SynapsesFactory::SynapsesFactory, 55
bSat, 38	numberofMultiSynapses
conf, 38	Compartment::Compartment, 26
diracDeltaValue, 38	CompartmentCompartment, 20
	parameterSet
force, 39	Configuration::Configuration, 28
hillModel, 39	PointProcessGenerator, 15
kind, 39	gammaPoint, 15
listSpikes, 38	PointProcessGenerator, 43
MUnumber, 39	PointProcessGenerator.py, 59
pool, 39	PointProcessGenerator::PointProcessGenerator
poolSomaSpikes, 39	init , 44
poolTerminalSpikes, 39	
timeIndex, 39	atualizeGenerator, 44
twTet, 39	GammaOrder, 44
twitchAmp_N, 39	GammaOrderInv, 44
unit, 39	index, 44
	points, 44
nerve	threshold, 44
MotorUnit::MotorUnit, 35	y, 44
NeuralTract, 14	points
NeuralTract.NeuralTract, 40	PointProcessGenerator::PointProcessGenerator,
NeuralTract.py, 59	44
NeuralTract::NeuralTract	pool
init, 40	MotorUnitPool::MotorUnitPool, 39
atualizePool, 40	NeuralTract::NeuralTract, 41
FR, 40	Synapse::Synapse, 52
kind, 40	poolSomaSpikes
listSpikes, 40	MotorUnitPool::MotorUnitPool, 39
Number, 41	poolTerminalSpikes
pool, 41	MotorUnitPool::MotorUnitPool, 39
poolTerminalSpikes, 41	NeuralTract::NeuralTract, 41
·	PulseConductanceState, 15
target, 41	
timeIndex, 41	compValOn, 15
unit, 41	compValOn, 15
NeuralTractUnit, 14	PulseConductanceState.PulseConductanceState, 44

PulseConductanceState.py, 59	Synapse::Synapse, 53
PulseConductanceState::PulseConductanceState	startEntrance
init, 45	Synapse::Synapse, 53
actType, 46	state
alpha_ms1, 46	PulseConductanceState::PulseConductanceState
beta_ms1, 46	46
changeState, 45	stateType
computeStateValue, 45	ChannelConductance::ChannelConductance, 24
computeValueOff, 46	stimulusPositiontoTerminal
computeValueOn, 46	AxonDelay::AxonDelay, 21
kind, 46	stopConductanceDynamics
PulseDur_ms, 46	Synapse::Synapse, 51
state, 46	stopConductanceNone
t0, 46	Synapse::Synapse, 51
v0, 47	stopDynamicFunction
value, 47	Synapse::Synapse, 53
PulseDur_ms	stopEntrance
PulseConductanceState::PulseConductanceState,	Synapse::Synapse, 53
46	synContrib
الماس	Synapse::Synapse, 53
rInf	Synapse, 16
Synapse::Synapse, 53	compRiStart, 16
receiveSpike	compRiStop, 16
Synapse::Synapse, 50	compRoff, 16
ri Synanao::Synanao E2	compRoffStart, 17
Synapse::Synapse, 53	compRoffStop, 17
Roff Synanco::Synanco 52	compRon, 17
Synapse::Synapse, 53 roff	compRonStart, 17
Synapse::Synapse, 53	compRonStop, 18
Ron	compSynapCond, 18
Synapse::Synapse, 53	Synapse.py, 60
ron	Synapse.Synapse, 47
Synapse::Synapse, 53	Synapse::Synapse
runge_kutta	init, 48
MotorUnit, 13	addConductance, 48
motorom, ro	alpha_ms1, 51
simDuration_ms	beta_ms1, 51
Configuration::Configuration, 28	computeConductance, 48
simulador	computeCurrent, 49, 51
simulation, 15	computeCurrent2, 49
simulation, 15	conductanceState, 52
simulador, 15	delay_ms, 52
simulation.py, 60	dynamics, 52
somaIndex	EqPot_mV, 52
MotorUnit::MotorUnit, 35	expFinish, 52
somaSpikeTrain	gMaxTot_muS, 52
MotorUnit::MotorUnit, 35	gmax_muS, 52
specifRes_Ohmcm2	kind, 52
Compartment::Compartment, 26	neuronKind, 52
spikesGenerator	Non, 52
NeuralTractUnit::NeuralTractUnit, 43	numberOfIncomingSynapses, 52
spikesReceived	pool, 52
Synapse::Synapse, 53	rlnf, 53
startConductanceDynamics	receiveSpike, 50
Synapse::Synapse, 50	ri, 53
startConductanceNone	Roff, 53
Synapse::Synapse, 50	roff, 53
startDynamicFunction	Ron, 53

ron, 53	Synapse::Synapse, 54
spikesReceived, 53	timeIndex
startConductanceDynamics, 50	MotorUnitPool::MotorUnitPool, 39
startConductanceNone, 50	NeuralTract::NeuralTract, 41
startDynamicFunction, 53	timeStep_ms
startEntrance, 53	Configuration::Configuration, 29
stopConductanceDynamics, 51	timeStepBySix_ms
stopConductanceNone, 51	Configuration::Configuration, 29
stopDynamicFunction, 53	timeStepByTwo_ms
stopEntrance, 53	Configuration::Configuration, 29
synContrib, 53	Tmax mM
·	Synapse::Synapse, 54
t0, 54	· · · · · · · · · · · · · · · · · · ·
tBeginOfPulse, 54	transmitSpikes
tEndOfPulse, 54	NeuralTractUnit::NeuralTractUnit, 42
tPeak_ms, 54	transmitSpikesThroughSynapses
tauOff, 54	NeuralTractUnit::NeuralTractUnit, 43
tauOn, 54	twTet
ti, 54	MotorUnit::MotorUnit, 35
Tmax_mM, 54	MotorUnitPool::MotorUnitPool, 39
SynapsesFactory, 18	TwitchAmp_N
SynapsesFactory.py, 60	MotorUnit::MotorUnit, 35
SynapsesFactory, 54	twitchAmp_N
SynapsesFactory::SynapsesFactory	MotorUnitPool::MotorUnitPool, 39
init, 55	twitchSaturation
numberOfSynapses, 55	MotorUnitPool, 14
SynapsesIn	TwitchTc_ms
Compartment::Compartment, 26	MotorUnit::MotorUnit, 35
SynapsesOut	
Compartment::Compartment, 26	unit
NeuralTractUnit::NeuralTractUnit, 43	MotorUnitPool::MotorUnitPool, 39
•	NeuralTract::NeuralTract, 41
t0	
PulseConductanceState::PulseConductanceState,	v0
46	PulseConductanceState::PulseConductanceState,
Synapse::Synapse, 54	47
tBeginOfPulse	v_mV
Synapse::Synapse, 54	MotorUnit::MotorUnit, 36
tEndOfPulse	value
Synapse::Synapse, 54	PulseConductanceState::PulseConductanceState,
tPeak ms	47
Synapse::Synapse, 54	velocity_m_s
tSomaSpike	AxonDelay::AxonDelay, 22
MotorUnit::MotorUnit, 35	•
target	у
NeuralTract::NeuralTract, 41	PointProcessGenerator::PointProcessGenerator,
tauOff	44
Synapse::Synapse, 54	
tauOn	
Synapse::Synapse, 54	
terminalSpikeTrain	
AxonDelay::AxonDelay, 21	
MotorUnit::MotorUnit, 35	
NeuralTractUnit::NeuralTractUnit, 43	
threshold	
PointProcessGenerator::PointProcessGenerator,	
44	
threshold_mV	
MotorUnit::MotorUnit, 35	
ti	