MY-BASIC Quick Reference

1. Introduction

MY-BASIC is a lightweight cross-platform easy extendable BASIC interpreter written in pure C with about 16,000 lines of source code. MY-BASIC is a dynamic typed programming language. It supports structured grammar, and implements a style of OOP called prototype-based programming paradigm, furthermore it implements a functional programming ability with Lambda. It is aimed to be either an embeddable scripting language or a standalone interpreter. The core is pretty light; all in a C source file and an associated header file; simpleness of source file layout and tightness dependency make it feels extraordinarily tough. You can combine MY-BASIC with an existing project in C, C++, Objective-C, etc. Scripting driven can make your projects more powerful, elegant and neat.

This manual is a quick reference on how to program with MY-BASIC, what it can do and what cannot, how to use it and extend it as a scripting programming language.

For the latest revision or information, see https://github.com/paladin-t/my_basic; or contact with the author through hellotony521@qq.com to get support.

2. Programming with BASIC

The well-known programming language BASIC is an acronym for Beginner's All-purpose Symbolic Instruction Code; when we mention BASIC today, we often refer to the BASIC family, not a specific one. The BASIC family has a long history since an original BASIC was designed in 1964 by John George Kemeny and Thomas Eugene Kurtz at Dartmouth College in New Hampshire; and BASIC is famous because it is easy to learn and use all the time. Thank you all BASIC dedicators and fanatics.

MY-BASIC has a structured BASIC like grammar. It would be familiar to you if you ever had programmed with another BASIC dialect.

Getting started

You can download the latest MY-BASIC package from https://github.com/paladin-t/my_basic/archive/master.zip_or_check out the git clone https://github.com/paladinsource use t/my basic.git first if you didn't have a standalone interpreter yet. It is recommended to get a latest MY-BASIC package and have a quick blast with it first.

In this part let's get start using the MY-BASIC command line interpreter, which comes as below:

The close square bracket is an input prompt. Let's begin rock it by typing a classical "hello world" tutorial as below:

```
' Hello world tutorial

a$ = "Hello"

a$ = a$ + "World"

PRINT a$
```

Like other BASIC dialects, MY-BASIC is case-insensitive; it means *PRINT A\$* or *Print a\$* will perform the same behavior. You would get the response text after giving it a *RUN* command and hinting the enter key. Any text begins with a single quote and end to that line wouldn't be parsed to interpretable structure because it is a comment which won't influence the logic; a comment does not perform anything, it's just a short explanation of statements. MY-BASIC also supports multi-line comment surrounded by *[*] and *[*], for example:

```
PRINT "Begin";

[
PRINT "Ignored";

]
PRINT "End";
```

This code won't print any ignored comments.

Keywords

There are forty keywords and forty four reserved function words in MY-BASIC as below:

Keywords		NIL, MOD, AND, OR, NOT, IS, LET, DIM, IF,
		THEN, ELSEIF, ELSE, ENDIF, FOR, IN, TO,
		STEP, NEXT, WHILE, WEND, DO, UNTIL,
		EXIT, GOTO, GOSUB, RETURN, CALL, DEF,
		ENDDEF, CLASS, ENDCLASS, ME, NEW,
		VAR, REFLECT, LAMBDA, MEM, TYPE,
		IMPORT, END
Reserved	Standard	ABS, SGN, SQR, FLOOR, CEIL, FIX, ROUND,
words	library	SRND, RND, SIN, COS, TAN, ASIN, ACOS,
		ATAN, EXP, LOG, ASC, CHR, LEFT, LEN,
		MID, RIGHT, STR, VAL, PRINT, INPUT
	Collection	LIST, DICT, PUSH, POP, PEEK, INSERT,
	library	SORT, EXIST, INDEX_OF, GET, SET,
		REMOVE, CLEAR, CLONE, TO_ARRAY,

	ITERATOR, MOVE_NEXT

It is not allowed to use these words for user-defined identifier; in addition there are two more *TRUE* and *FALSE* predefined symbols besides these words, which represent Boolean value true and false, it's able to re-define these two symbols but it's not recommended. Meaning of each keyword will be mentioned latter in this manual.

Operators

There are eleven operators in MY-BASIC as below:

All these operators could perform in calculation or comparison. Besides these operators, keywords *MOD*, *AND*, *OR*, *NOT*, *IS* are operators as well. An operator priority level shown in the table below indicates execution order in an expression:

Level	Operation
1	- (negative), NOT
2	٨
3	*, /, MOD
4	+, - (minus)
5	<, >, <=, >=, <>, = (equal comparison)
6	AND, OR, IS
7	= (assignment)

The priority of level 1 is the highest and level 7 is the lowest. Higher level operations are treated before the lower ones. An expression is

processed from left to right; operations in a same level are dealt in the same direction. Brackets "(" and ")" are used in pair to tell the interpreter to process expression between them before operations outer.

MOD means modulus; it is usually signified by percent symbol "%" in some other programming languages. The caret symbol stands for power operation thus 2 ^ 3 results 8.

Data and operation

There are eleven kinds of built-in data types in MY-BASIC: Nil, Integer, Real, Boolean, String, List, List Iterator, Dictionary, Dictionary Iterator, Usertype, Referenced Usertype. MY-BASIC supports user defined data types to let you to customize your own data structures, it will be explained later.

Nil is a special type which includes only one value: *NIL*. A *NIL* represents nothing, similar to null, none, etc. in other programming languages. Assigning a variable with a Nil value will release the previous value it holds.

Integer and Real are defined as *int* and *float* in C types which are 32bit size under most compiler architectures nowadays. And you could redefine them with other types like *long* and *double* by modifying a few lines of code according to your requirement. The only instances of Boolean are *TRUE* and *FALSE*, and can be assigned from a Boolean expression or an Integer expression. Actually Boolean is implemented and treated the same way as Integer; zero means

FALSE and non-zero means TRUE.

NIL, FALSE, and 0 all mean false in a Boolean expression; on the other hand all other value including a blank String "" mean true.

MY-BASIC accepts numbers in HEX and OCT representation. A hexadecimal number begins with a 0x prefix, and an octadic one begins with a 0. For instance 0x10 (HEX) equals to 020 (OCT) equals to 16 (DEC).

A variable identifier is formed with alphabet, underline and numbers, but it must begin with a letter or an underline. A variable does not require declaration before using, so pay attention to spelling mistakes to avoid unexpected behaviours. You don't need to take care of conversion between Integer/Float values, an Integer variable can be converted to a Float automatically if it's assigned with a Float value, and a Float value will be converted to an Integer if it doesn't has a real component. Notice that a String variable doesn't have to end with a dollar character \$, which maybe a little different from some early BASIC dialects. An assignment statement consists of a beginning keyword LET and a following assignment expression, practically the word LET is optional. See below:

LET a = 1 'Assignment statement begins with LET pi = 3.14 'Another assignment statement without LET

MY-BASIC supports array up to four dimensions by default (defined by a macro), without doubt you can redefine this limitation. Array is a kind of regular collection data structure in programming aspect. An array can store a set of data that each element can be accessed via the array name and subscript. A MY-BASIC array can hold either Real or String data; furthermore, it's able to store each type of data in an array by modifying a macro. An array must be declared by a *DIM* (short for dimension) statement before using like this:

DIM nums(10)
DIM strs\$(2, 5)

The naming rule for array identifiers is the same as variable naming rule. A dimension definition field followed an array identifier begins with an open bracket and ends with a close bracket. Dimensions are separated by commas. Array indexes begin from zero in MY-BASIC therefore *nums(0)* is the first element of array *nums*, note for this difference from other BASICs, but it's more common in most modern programming languages. An array index could be a non-negative Integer value formed as a constant, a variable of Integer or an expression which evaluation results an Integer; an invalid index would cause an out of bound error.

MY-BASIC allows you to concatenate two Strings together using operator plus "+" and get a concatenated String. So be aware of that each String concatenating operation would generate a new String object with memory allocation. Comparison operators can also apply to Strings. These operators start comparing the first character of each String, if they are equal to each other, it continues looking at the following ones until a difference or a terminating null-character "\0"

is reached; then return Integer values indicating the relationship between the Strings: a zero value if both Strings are equal, a positive value if the first is greater than the second one, a negative value if the first is less than the second one.

Structured sub routine

It is recommended to break a program into small sub routines. Sub routines can reduce duplicate and complicacy code. MY-BASIC supports both structured sub routine with *CALL/DEF/ENDDEF* and instructional sub routine with *GOSUB/RETURN*, but you cannot use them both in one program. It's recommended to use structured *CALL/DEF/ENDDEF* to write more elegant programs.

A sub routine begins with a *DEF* statement and ends with *ENDDEF*, you can add any numbers of parameters to a sub routine. It's quite similar to call a sub routine with calling a scripting interface, note you need to write an explicit *CALL* statement, if you were calling a sub routine which was defined after the calling statement. A sub routine returns the value of the last expression back to its caller, or you may use an explicit *RETURN* statement. See below for example:

```
a = 1
b = 0
DEF FUN(d)
  d = CALL BAR(d)
SIN(10)
  RETURN d' Try comment this line
ENDDEF
DEF FOO(b)
  a = 2
  RFTURN a + b
ENDDEF
DEF BAR(c)
  RETURN FOO(c)
ENDDEF
r = FUN(2 * 5)
PRINT r; a; b; c;
```

As you may see, a variable defined in a sub routine is only visible inside the local routine scope.

MY-BASIC supports recursive sub routines and tail recursion optimization.

Besides, the CALL statement is used to get a routine value itself as:

```
routine = CALL(FUN) ' Get a routine value.
routine() ' Invoke a routine value.
```

Be aware it requires a pair of brackets.

Instructional sub routine

Whatever, instructional sub routine is a valid option as well. A label is used to define the entry point of an instructional sub routine. You can use a *GOSUB* statement wherever in the program to call a labeled sub routine and transfer control to it. A *RETURN* statement is used to exit a sub routine and transfer control back to its caller.

Control structures

There are three kinds of control structure in common structured programming languages; MY-BASIC supports them as well.

Serial structure that executes statements one by one is the most fundamental structure. MY-BASIC supports *GOTO* statement that provides unconditional control transfer ability. You can execute it like *GOSUB* as *GOTO* label, note instructional sub routine control proprietary cannot be returned back from a callee but unconditional *GOTO* cannot. Also, you cannot user both structured sub routine and unconditional jumping in one program. An *END* statement can be placed anywhere in source code to terminate the whole execution of a program.

Conditional structure consists of some condition jump statements (such as *IF*, *THEN*, *ELSEIF*, *ELSE*, *ENDIF*). These statements check condition expressions then perform an action in a case of true condition branch and in a case of false it performs something else as

you wrote.

You can write conditional *IF* statements in two ways. The first is single line format which the whole conditional chunk is written in a single line:

```
IF n MOD 2 THEN PRINT "Even" ELSE PRINT "Odd"
```

The other way is multiple line statements:

```
INPUT n

IF n = 1 THEN

PRINT "One"

ELSEIF n = 2 THEN

PRINT "Two"

ELSEIF n = 3 THEN

PRINT "Three"

ELSE

PRINT "More than three"

ENDIF
```

It supports nested *IF* in multiple line conditional statements.

Loop structure statements check a loop condition and do the loop body in a case of true until it comes to a false case.

The *FOR TO STEP NEXT* loop statement is deemed as fixed step loop. See below that prints number one to ten:

```
FOR i = 1 TO 10 STEP 1
PRINT i
NEXT i
```

The *STEP* segment is optional if the increment is one. The loop variable after *NEXT* is optional if it is associated with the closest *FOR* segment.

MY-BASIC supports loop on collections by using *FOR IN* statement as well. It's able to iterate a list or a dictionary. The loop variable is assigned with the value of the element which an iterator is currently pointing to. For example:

```
FOR i IN LIST(1 TO 5)
PRINT i;
NEXT
```

Sometimes, we don't know how many steps a loop would repeat. For this reason, variable step loops are quite essential. There are two kinds of variable loops in MY-BASIC, *WHILE WEND* and *DO UNTIL* loops. See the code below:

```
a = 1

WHILE a <= 10

PRINT a

WEND
```

b = 1DO

PRINT b

UNTIL a > 10

Just as their names imply, *WHILE WEND* loop do the loop body while the condition is true, and *DO UNTIL* loop do that until the condition is false. A key difference is *WHILE WEND* checks the condition first before executing the loop body, however, *DO UNTIL* checks the condition after the loop body has been executed once.

EXIT statement in MY-BASIC is used to interrupt current loop and continue to execute the program after it. It is the same as "break" statement in some other programming languages.

Use a class

MY-BASIC supports prototype-based programming paradigm which is a style of OOP (Object-Oriented Programming) paradigm. When we say "class instance" or "prototype", them mean the same thing in MY-BASIC. Use a pair of CLASS/ENDCLASS statements to define a class (a prototype object). Use VAR to declare a member variable in a class. Use NEW to clone a new instance of a prototype See below for example to use a class in MY-BASIC:

```
CLASS Foo

VAR a = 1

DEF FUN(b)

RETURN a + b

ENDDEF

ENDCLASS

CLASS Bar(Foo) ' Use Foo as a meta class (inheriting).

VAR a = 2

ENDCLASS

inst = NEW(Bar) ' Create a new clone of Bar.

PRINT inst.FUN(3);
```

"Bar" will simply link "Foo" as a meta class. But "inst" will create a new clone of "Bar" and keep the "Foo" meta link.

MY-BASIC supports reflection on a class instance with the *REFLECT* statement. It iterates all variable fields and sub routines in a class and its meta class as well, and stores the *name/value* of a variable and the *name/type* of a sub routine to the dictionary *d*. You need to have a binary build with the collection library enabled to use reflection. Let's have a look at an example:

```
CLASS Base
     VAR b = "Base"
    DEF FUN()
         PRINT b:
     FNDDFF
ENDCLASS
CLASS Derived(Base)
     VAR d = "Derived"
    DEF FUN()
         PRINT d;
     ENDDEF
ENDCLASS
i = NEW(Derived)
i.FUN();
r = REFLECT(i)
f = ITERATOR(r)
WHILE MOVE_NEXT(f)
    k = GET(f)
    v = r(k)
    PRINT k, ": ", v;
WEND
g = GET(i, "FUN");
g()
```

Use Lambda

According to Wikipedia's description, a <u>Lambda</u> abstraction (aka. anonymous function or function literal) is a function definition that is not bound to an identifier. Lambda functions are often:

- 1. Arguments being passed to higher order functions, or
- 2. Used for constructing the result of a higher-order function that needs to return a function.

A Lambda becomes a <u>closure</u> after it captured some values in outer scope.

MY-BASIC has a full support for Lambda, including invokable as a value, higher order function, closure and currying, etc.

A Lambda abstraction begins with a *LAMBDA* keyword.

```
' Simple invoke.

f = LAMBDA (x, y) (RETURN x * x + y * y)

PRINT f(3, 4);
```

```
' Higher order function.

DEF FOO()

y = 1

RETURN LAMBDA (x, z) (RETURN x + y + z)

ENDDEF

I = FOO()

PRINT I(2, 3);
```

```
'Closure.

s = 0

DEF CREATE_LAMBDA()

v = 0

RETURN LAMBDA ()

(

v = v + 1

s = s + 1

PRINT v;

PRINT s;

)

ENDDEF

a = CREATE_LAMBDA()

b = CREATE_LAMBDA()

a()

b()
```

```
'Currying.

DEF DIVIDE(x, y)

RETURN x / y

ENDDEF

DEF DIVISOR(d)

RETURN LAMBDA (x) (RETURN DIVIDE(x, d))

ENDDEF

half = DIVISOR(2)

third = DIVISOR(3)

PRINT half(32); third(32);
```

Lambda enhanced MY-BASIC with functional programming abilities.

Check the type of a value

You can use *TYPE* statement to tell what the type of a value is, or use a predefined string argument to generate a type information. Eg:

```
PRINT TYPE(123); TYPE("Hi"); ' Get type of values.

PRINT TYPE("INT"); TYPE("REAL"); ' Get type objects.
```

It's also able to check whether a value match a specific type by using the *IS* operator as follow:

```
PRINT 123 IS TYPE("INT"); "Hi" IS TYPE("STRING");
PRINT inst is TYPE("CLASS");
```

You can also use *IS* to tell whether a class instance is inherited from another prototype:

```
PRINT inst is Foo;
```

Import another script file

It's necessary to separate modules to multiple files in large system. MY-BASIC provides an *IMPORT* statement to let a script import another script file. Eg. assuming we got a "a.bas" which is:

```
foo = 1
```

And another "b.bas" which is:

IMPORT a.bas

PRINT foo;

When MY-BASIC is parsing "b.bas", it will load "a.bas" as if it was written in "b.bas".

Import a module

It's able to put some symbols in a module (or called "namespace" in other programming languages) to avoid naming pollution.

Use *IMPORT "@xxx"* to import a module, and all symbols in that module could be used without the module prefix.

3. Core and Standard Libraries

MY-BASIC supplies a set of frequently used function libraries which provides some fundamental numeric and string functions. These function names couldn't be used as a user-defined variable identifier either. For details of these functions, see the figure bellow:

Туре	Name	Description
Numeric	ABS	Returns the absolute value of a number
	SGN	Returns the sign of a number
	SQR	Returns the arithmetic square root of a
		number
	FLOOR	Returns the greatest integer not greater

	1	
		than a number
	CEIL	Returns the least integer not less than a
		number
	FIX	Returns the integer trimmed format of a
		number
	ROUND	Returns the specified value to the nearest
		integer of a number
	SRND	Sets the seed of random number
	RND	Returns a random float number between
		0.0 and 1.0
	SIN	Returns the sine of a number
	cos	Returns the cosine of a number
	TAN	Returns the tangent of a number
	ASIN	Returns the arcsine of a number
	ACOS	Returns the arccosine of a number
	ATAN	Returns the arctangent of a number
	EXP	Returns the base-e exponential of a
		number
	LOG	Returns the base-e logarithm of a number
String	ASC	Returns the integer ASCII code of a
		character
	CHR	Returns the character of an integer ASCII
		code
	LEFT	Returns a given number of characters

		from the left of a string
	MID	Returns a given number of characters
		from a given position of a string
	RIGHT	Returns a given number of characters
		from the right of a string
	STR	Returns the string type value of a number
	VAL	Returns the number type value of a string
Common	LEN	Returns the length of a string or an array,
		or the element count of a LIST or a DICT
Input &	PRINT	Outputs number or string to the standard
Output		output stream, user redirectable
	INPUT	Inputs number or string from the
		standard input stream, user redirectable

Be aware that all those functions besides *PRINT* and *INPUT* require a pair of brackets to surround arguments.

4. Collection Libraries

MY-BASIC supplies a set of *LIST*, *DICT* manipulation function libraries which provide creation, accessing, iteration, etc. as below:

Name	Description
LIST	Creates a list
DICT	Creates a dictionary
PUSH	Pushes a value to the tail of a list

Pops a value from the tail of a list
Peeks the value of a tail of a list
Inserts a value at a specific position of a list
Sorts a list increasingly
Tells whether a list contains a specific value, or
whether a dictionary contains a specific key
Gets the index of a value in a list
Returns the value of a specific index in a list, or
the value of a specific key in a dictionary; or a
member of a class instance
Sets the value of a specific index in a list, or the
value of a specific key in a dictionary
Removes the element of a specific index in a list,
or the element of a specific key in a dictionary
Clears a list or a dictionary
Clones a collection
Copies all elements from a list to an array
Gets an iterator of a list or a dictionary
Moves an iterator to next position for a list or a
dictionary

For example:

```
I = LIST(1, 2, 3, 4)
SET(I, 1, "B")
PRINT EXIST(I, 2); POP(I); PEEK(I); LEN(I);

d = DICT(1, "One", 2, "Two")
SET(d, 3, "Three")
PRINT LEN(d)
it = ITERATOR(d)
WHILE MOVE_NEXT(it)
PRINT GET(it);
WEND
```

MY-BASIC supports accessing an element of a collection using brackets as well:

```
d = DICT()
d(1) = 2
PRINT d(1);
```

5. Application Programming Interface

There are a few but adequate exposed MY-BASIC APIs (Application Programming Interface) for C, C++, Objective-C, etc. programmers. MY-BASIC is written with pure C, what you need to do before scripting with MY-BASIC is just copy *my basic.h* and *my basic.c* to

the target project, then add them to the project build configuration; all interfaces are declared in *my_basic.h*. Most APIs return an *int* value, they should return *MB_FUNC_OK* if there was no execution error most time.

Interpreter structure

MY-BASIC uses an interpreter structure to store some necessary data structures during parsing and running period; like local, global function directory, variable scope dictionary, abstract syntax tree (list), parsing context, running context, error information, etc. An interpreter structure is a unit of MY-BASIC environment. Invoking between MY-BASIC script and host program also works through this structure.

Meta information

unsigned int mb_ver(void);

Returns the version number of current interpreter.

const char* mb_ver_string(void);

Returns the version number in text of current interpreter.

Initializing and disposing

int mb_init(void);

This function must and must only be called once before any other operations with MY-BASIC to initialize the entire system.

int mb_dispose(void);

This function must and must only be called once after operations with MY-BASIC to dispose the entire system.

```
int mb_open(struct mb_interpreter_t** s);
```

This function opens an interpreter structure to get ready for parsing and running.

Common usage of this function does like this:

```
struct mb_interpreter_t* bas = 0;
mb_open(&bas);
```

```
int mb_close(struct mb_interpreter_t** s);
```

This function closes an interpreter structure when it is no longer used. *mb_open* and *mb_close* must be matched in pair sequentially.

```
int mb_reset(struct mb_interpreter_t** s, bool_t clrf);
```

This function resets an interpreter structure to initialization as it was just opened. This function is optional, it will clear all variables, and also all registered global functions if *tclrf* is *true*.

Function registration/unregistration

These functions are called to register or remove extended functions.

This function registers a function pointer into an interpreter structure using a given name. The function to be registered must be a pointer of *int* (* mb_func_t)(struct mb_interpreter_t*, void**). A registered

function can be called in MY-BASIC script.

This function removes a registered function out of an interpreter structure by a given name the same as it was registered.

This function removes a reserved function out of an interpreter structure by a given name. Do not use this function unless you really need to.

```
int mb_begin_module(struct mb_interpreter_t* s, const char* n);
```

This function begins a module with a module name. All functions registered after a module began will be put in that module.

```
int mb_end_module(struct mb_interpreter_t* s);
```

This function ends the current module.

Invoking

These functions are utilities called in extended functions.

This function checks whether script is invoking an extended function in a legal begin format.

This function checks whether script is invoking an extended function

in a legal end format.

This function checks whether script is invoking an extended function in a legal format that begins with an open bracket before arguments list.

This function checks whether script is invoking an extended function in a legal format that ends with a close bracket after arguments list.

This function detects whether there is any more argument at current execution position in an interpreter structure. Use this function to implement a variable arguments interface function.

This function tries to pop an argument of *int_t* from an interpreter structure.

This function tries to pop an argument of *real_t* from an interpreter structure.

This function tries to pop an argument of *char** (String) from an interpreter structure.

This function tries to pop an argument of *void** (Usertype) from an interpreter structure.

This function tries to pop an argument of *mb_value_t* from an interpreter structure. Use this function instead of *mb_pop_int*, *mb_pop_real* and *mb_pop_string* if an extended function accepts arguments of generics types.

This function pushes an argument of int_t to an interpreter structure.

```
real_t val);
```

This function pushes an argument of real_t to an interpreter

structure.

This function pushes an argument of *char** (String) to an interpreter structure.

This function pushes an argument of *void** (Usertype) to an interpreter structure.

This function pushes an argument of <code>mb_value_t</code> to an interpreter structure. Use this function instead of <code>mb_push_int</code>, <code>mb_push_real</code> and <code>mb_push_string</code> if an extended function returns value of generics types.

Class definition

These functions are used to define a class manually in native side.

```
int c,
mb value t* out);
```

This function begins a class definition with a specific name.

This function ends a class definition.

This function gets the userdata of a class instance.

This function sets the userdata of a class instance.

Value manipulation

These functions manipulate values.

This function gets the value of an identifier with a specific name.

```
mb_value_t val,
bool_t force);
```

This function adds a variable with a specific identifier name and a value.

This function gets a token literally, store it in an argument if it's a variable.

This function gets the value of a variable.

This function sets the value of a variable.

This function initializes an array which MY-BASIC can use. The parameter *mb data e t* means what's the type of elements in the

array, you can pass MB_DT_REAL or MB_DT_STRING; you need to disable the MB_SIMPLE_ARRAY macro to use a complex array and pass MB_DT_NIL. The int* d and int c stand for ranks of dimensions and dimension count. The function will put a created array to void** a.

This function gets the length of an array. *int r* means which dimension you'd like to get.

This function gets the value of an element in an array.

This function sets the value of an element in an array.

This function initializes a collection; you need to pass a valid mb_value_t pointer with a specific collection type you'd like to initialize.

This function gets an element in a collection. You can pass *LIST* index or *DICT* key to *mb_value_t idx*.

This function sets an element in a collection. You can pass *LIST* index or *DICT* key to *mb* value t idx.

```
This function removes an element from a collection. You can pass LIST index or DICT key to mb_value_t idx.
```

This function returns the count of elements in a collection.

This function makes a Referenced Usertype mb_value_t object which holds void*val as userdata. Note you need to specify some functors.

This function gets the raw userdata from a Referenced Usertype.

This function increases the reference count of a Referenced Usertype.

This function decreases the reference count of a Referenced Usertype.

This function overrides a meta function of a Referenced Usertype.

This function disposes a value popped from an interpreter. Now used for strings only.

Sub routine manipulation

This function gets a sub routine object by its name.

```
const char* n,
mb_routine_func_t f,
bool_t force);
```

This function sets a sub routine with a specific name using a native functor.

This function evaluates a subroutine object. *mb_value_t* args* is a pointer of an argument array, *unsigned argc* is the count of arguments.

Parsing and running

This function loads a string into an interpreter structure; then parses script source to executable structures and appends them to the abstract syntax tree (list).

This function loads a string into an interpreter structure; then parses script source to executable structures and appends them to the abstract syntax tree (list).

int mb_run(struct mb_interpreter_t* s);

This function runs a parsed abstract syntax tree (list) in an interpreter structure.

This function suspends and saves current execution point. Some extended functions need this ability and resume that point after some other operations. Call *mb_run* again to resume a suspended point.

This function schedules a suspend event, and it will trigger the event after the active statement execution is done. It's useful to do so when you need to do something else during the whole execution.

A). mb_schedule_suspend(s, MB_FUNC_SUSPEND); It's re-enterable which means next mb_run will resume execution from where you suspended. B). mb_schedule_suspend(s, MB_FUNC_END); Terminate an execution normally, no error message. C). mb_schedule_suspend(s, MB_EXTENDED_ABORT); Or pass an argument greater than MB_EXTENDED_ABORT to terminate an execution and trigger an error message. You can call mb_schedule_suspend either in _on_stepped or in a scripting interface function. The difference between mb_schedule_suspend and mb_suspend is that mb_suspend can be called in a scripting interface only, and it cannot trap type B) and C) suspension.

Debugging

This function retrieves the value of a variable using the identifier in an interpreter structure.

This function sets a variable using the identifier with a given value in an interpreter structure.

This function gets current stack frame trace. It requires the MB_ENABLE_STACK_TRACE macro enabled to use this function.

This function sets a single step handler of an interpreter structure. The function to be set must be a pointer of *void* (* *mb_debug_stepped_handler_t*)(struct *mb_interpreter_t**, *char**, *int, unsigned short, unsigned short*). This function is useful for step by step debugging.

Type handling

```
const char* mb_get_type_string(mb_data_e t);
```

This function returns type information in string of a given type.

Error handling

This function raises an error manually.

```
mb_error_e mb_get_last_error(struct mb_interpreter_t* s);
```

This function returns the latest error information of an interpreter structure.

```
const char* mb_get_error_desc(mb_error_e err);
```

This function returns the description string of error information.

This function sets an error callback handler of an interpreter structure.

Stream redirection

This function sets a **PRINT** handler of an interpreter structure. Use

this to customize an output handler for the *PRINT* statement. The function to be set must be a pointer of *int* (* *mb_print_func_t*)(*const char**, ...). *printf* is set by default.

This function sets the *INPUT* handler of an interpreter structure. Use this to customize an input handler for the *INPUT* statement. The function to be set must be a pointer of *int* (* *mb_input_func_t*)(*char**, *int*). *mb_gets* is set by default.

Miscellaneous

This function tries to trigger a garbage collection.

This function gets the userdata of an interpreter instance.

This function sets the userdata of an interpreter instance.

This function sets a customized module importing handler.

A more safety evolvement of the standard *gets*.

This function duplicates a piece of memory to a MY-BASIC manageable buffer structure; use this to generate an argument for strings to be pushed. Note this function only copy bytes in given *size*, thus you have to add an extra byte to *size* for ending "\0".

This function sets a memory allocator and a freer globally to MY-BASIC.

6. Scripting with MY-BASIC

As to source code portability, the C programming language is most outstanding, because C compilers are available on almost every platform; that is why MY-BASIC is written in pure clean C so it can be compiled for PC, pad, tablet, mobile phone, PDA, video game console, Raspberry Pi and even MCU, with none or few porting modifications. It would be pretty easy to bind MY-BASIC in an existing project by just adding the MY-BASIC core which consists of a header declaration file and corresponding C implementation file into the target project.

First of all, you should recognize which parts in your project require execution speed and low level control, and which parts require flexibility and augmentability. It's not wise to code kernel

computation-intensive modules in script; script is appropriate for volatile parts of an entire program. There is no one fits all solution; scripting programming languages are not omnipotent.

If it is explicit to you that using a scripting language would benefit your project then you should make and expose some interfaces correctly. More details on how to create your own scripting interfaces will be dealt with in the next chapter. After that you may complete your program with MY-BASIC script, invoking those scripting interfaces and pack them together into a publishable version.

Besides the scripting benefits, play with a scripting language itself is a really enjoyable thing.

7. Customizing MY-BASIC

Redirect PRINT and INPUT

Include a header file to use variable argument list:

#include <stdarg.h>

Customizable print handler:

```
int my_print(const char* fmt, ...) {
    char buf[1024];
    va_list argptr;

    va_start(argptr, fmt);
    vsnprintf(buf, sizeof(buf), fmt, argptr);
    va_end(argptr);

    printf(buf); /* Change me. */

    return MB_FUNC_OK;
}
```

Customizable input handler:

```
int my_input(char* buf, int s) {
    int result = 0;
    if(fgets(buf, s, stdin) == 0) { /* Change me. */
        fprintf(stderr, "Error reading.\n");
        exit(1);
    }
    result = (int)strlen(buf);
    if(buf[result - 1] == '\n')
        buf[result - 1] = '\0';
    return result;
}
```

Register handlers to an interpreter:

```
mb_set_printer(bas, my_print);
mb_set_inputer(bas, my_input);
```

Now your printer and inputer would be invoked.

Write scripting APIs

MY-BASIC is free and open source software released under the MIT license which allows you to use, modify, extend and distribute the software for either commercial or noncommercialuses. You might need more scripting libraries according to your specific requirement though MY-BASIC has already provided some functions. It is really

simple in MY-BASIC to do so.

The first step is to define the function in your host program. All C, C++, Objective-C callee functions that will be invoked from MY-BASIC script is a pointer of type <code>int (* mb_func_t)(struct mb_interpreter_t*, void**)</code>. Since an interpreter structure is used as the first argument of an extended function, the function actually can pop any number of arguments from the interpreter structure and push none or one return value back into the structure. The <code>int</code> return value indicates an execution status of an extended function which always returns <code>MB_FUNC_OK</code> for no error. Let's make a <code>maximum</code> function that returns the maximum value of two integers as a tutorial; see code below:

```
int maximum(struct mb interpreter t* s, void** I) {
    int result = MB FUNC OK;
    int m = 0;
    int n = 0:
    int r = 0;
    mb assert(s && I);
    mb_check(mb_attempt_open_bracket(s, I));
    mb_check(mb_pop_int(s, I, &m));
    mb check(mb pop int(s, I, &n));
    mb check(mb attempt close bracket(s, I));
    r = m > n ? m : n:
    mb check(mb push int(s, l, r));
    return result;
}
```

Quite simple, isn't it.

The second step is to register defined functions like: $mb_reg_fun(bas, maximum)$ (assuming we already have $struct mb_interpreter_t* bas defined).$

After that you can use a registered function as any other scripting interfaces in MY-BASIC like:

```
i = MAXIMUM(1, 2)
PRINT i
```

To perform a user defined abort, just return an integer value greater equal than a macro <u>MB_EXTENDED_ABORT</u>. It is recommended to add an abort value like:

```
typedef enum mb_user_abort_e {
     MB_ABORT_FOO = MB_EXTENDED_ABORT + 1,
     /* more... */
};
```

Then write *return MB_ABORT_FOO*; in your customized function when something uncontainable happened.

Use usertype values

MY-BASIC build-in types maybe not enough for all purposes. It's easy to use Usertype in MY-BASIC. It can accept whatever type you give it. MY-BASIC doesn't care what a Usertype is; it just holds a Usertype value at a variable or an array element. Note *MB_SIMPLE_ARRAY* macro must be disabled when you wish to store Usertype in arrays.

There are only two essential interfaces to get or set a Usertype: $mb_pop_usertype$ and $mb_push_usertype$. You can push a void* to an interpreter and pop a value as void* as well. This is more flexible than using only build-in types.

Macros

Some features of MY-BASIC could be customized with macros.

MB SIMPLE ARRAY

Enabled by default. An entire array uses a unified type mark, which means there are only two kinds of array: *string* and *real_t*.

Disable this macro if you would like to store generic type values in an array including *int_t*, *real_t*, *usertype*. Besides, array of *string* is still another kind. Note non simple array requires extra memory to store type mark of each element.

MB_ENABLE_ARRAY_REF

Enabled by default. Compiles with referenced array if this macro defined, otherwise compiles as value type array.

MB_MAX_DIMENSION_COUNT

Defined as 4 by default. Change this to support arrays of bigger maximum dimensions.

MB_ENABLE_COLLECTION_LIB

Enabled by default. Compiles including *LIST* and *DICT* libraries if this macro is defined.

MB_GC_GARBAGE_THRESHOLD

Defined as 16 by default. It will trigger a sweep-collect GC cycle when such number of deallocation occurred.

MB_ENABLE_ALLOC_STAT

Enabled by default. Use *MEM* to tell how much memory in bytes is allocated by MY-BASIC. Note statistics of each allocation takes

sizeof(intptr_t) more bytes memory.

MB_ENABLE_SOURCE_TRACE

Enabled by default. MY-BASIC can tell where it goes in source code when an error occurs.

Disable this to reduce some memory occupation. Only do this on memory sensitive platforms.

MB_ENABLE_STACK_TRACE

Enabled by default. MY-BASIC will record stack frames including sub routines and native functions if this macro defined.

MB_ENABLE_UNICODE

Enabled by default. Compiles with UTF8 manipulation ability if this macro defined, to handle UTF8 string properly with functions such as *LEN*, *LEFT*, *RIGHT*, *MID*, etc.

MB_CONVERT_TO_INT_LEVEL

Describes how to deal with Real numbers after an expression is evaluated. lust leave it а Real if it's defined MB CONVERT TO INT LEVEL NONE; otherwise try to convert it to an Integer if it doesn't contains decimal part if it's defined as MB CONVERT TO INT LEVEL ALL. Also you could use the mb convert to int if posible macro to deal with an mb value t in your own scripting interface functions.

MB_ENABLE_MODULE

Enabled by default. Compiles with module (namespace) support if this macro defined. Use *IMPORT "@xxx"* to import a module, and all symbols in that module could be used without the module prefix.

MB_ENABLE_USERTYPE_REF

Enabled by default. Compiles with referenced usertype support if this macro defined.

MB_ENABLE_CLASS

Enabled by default. Compiles with class (prototype) support if this macro defined.

MB_ENABLE_LAMBDA

Enabled by default. Compiles with Lambda (anonymous function) support if this macro defined.

MB COMPACT MODE

Enabled by default. C struct may use a compact layout.

This might cause some strange pointer accessing bugs with some compilers (eg. Some embedded system compilers). Try disabling this if you met any strange bugs.

_WARNING_AS_ERROR

Defined as 0 by default.

Define this macro as 1 in *my_basic.c* to treat warnings as error, or they will be ignored silently.

Something like divide by zero, wrong typed arguments passed will trigger warnings.

_HT_ARRAY_SIZE_DEFAULT

Defined as 193 by default. Change this in *my_basic.c* to resize the hash tables. Smaller value will reduce some memory occupation, size of hash table will influence tokenization and parsing time during **loading**, won't influence **running** performance most of the time

(except cross scope identifier lookup).

SINGLE SYMBOL MAX LENGTH

Defined as 128 by default. Max length of a lexical symbol.

8. Memory Occupation

In some memory limited environments, memory occupation is often a sensitive bottleneck. MY-BASIC provides a method to count how much memory has an interpreter context allocated. Write script like below to tell how much memory in bytes does MY-BASIC allocated:

PRINT MEM 'The keyword MEM is right for this

Note that it will take *sizeof(intptr_t)* bytes more of each allocation if this statistics is enabled

Comment the <u>MB_ENABLE_SOURCE_TRACE</u> macro in <u>my_basic.h</u> to disable source trace to reduce some memory occupation, but you will lose the error locating feature as well.

Redefine the _HT_ARRAY_SIZE_DEFAULT macro with a smaller value minimum to 1 in my_basic.c to reduce memory occupied by hash tables in MY-BASIC. Value 1 means a linear lookup.

The memory is limited in embedded systems which can run for years and cause a severe waste of memory due to fragmentation. Besides, it's efficient for MY-BASIC to customizing a memory allocator, even on systems with a plenty of memory. MY-BASIC provides an interface that let you do so.

An allocator need to be in form of:

typedef char* (* mb_memory_allocate_func_t)(unsigned s);

And a freer:

typedef void (* mb_memory_free_func_t)(char* p);

Then you can tell MY-BASIC to use them globally instead of standard *malloc* and *free* by:

MBAPI int mb_set_memory_manager(mb_memory_allocate_func_t a, mb_memory_free_func_t f);

Note the functors only affect things going inside *my_basic.c*, but *main.c* still uses the standard pair.

There is already a simple memory pool implementation in *main.c*. You need to make sure the _*USE_MEM_POOL* macro is defined to enable this pool, and undefine it to disable the mechanism.

There are four functions in this implementation as a tutorial: _open_mem_pool opens the pool when setting up an interpreter; _close_mem_pool closes the pool when terminating; a pair of _pop_mem and _push_mem will be registered to MY-BASIC. Note _pop_mem will call the standard malloc if an expected size is not a common size in MY-BASIC; and it will take sizeof(union _pool_tag_t) extra bytes to store meta data with each common size allocation. A typical workflow may looks like below:

```
_open_mem_pool(); // Open it.

mb_set_memory_manager(_pop_mem, _push_mem); // Register them.

{
    mb_init();
    mb_open(&bas);
    // Other deals with MY-BASIC.
    mb_close(&bas);
    mb_dispose();

}
_close_mem_pool(); // Finished.
```

Strictly speaking, the tutorial pool doesn't guarantee to allocate continuous address memory, it is an object pool other than a memory pool, which pops a free chunk of memory with an expected size to user, and pushes it to the stack back when user frees it instead of freeing it to system. This could be a good start if you would like to implement your own memory pool algorithm optimized for a specific system.

9. Using MY-BASIC as a Standalone Interpreter

You would be familiar with the MY-BASIC interpreter if you have tried the hello world tutorial. There are some useful commands ininteractive interpreter mode:

Command	Summary	Usage
HELP	Shows help information.	
CLS	Clears screen.	
NEW	Clears current program.	
RUN	Runs current program.	
BYE	Quits interpreter.	
LIST	Lists current program.	LIST [I [n]], I is start line
		number, n is line count.
EDIT	Edits	EDIT n, n is line number.
	(modify/insert/remove)	EDIT -i n, insert a line
	a line in current	before a given line, n is
	program.	line number.
		EDIT -r n, remove a line, n
		is line number.
LOAD	Loads a file as current	LOAD *.*.
	program.	
SAVE	Saves current program	SAVE *.*.
	to a file.	
KILL	Deletes a file.	KILL *.*.
DIR	List a directory.	DIR p, p is a directory
		path.

Type a command (maybe also with several arguments) and hint enter to execute it. Command is only an aspect of the interpreter other than keyword, that is to say it is valid to use them as variable identifiers in a program; but to avoid reading confusion and conflict, and anyway, you may consider different identifier naming.

Pass a file path to the binary to load and run that script file in file execution mode.

Pass an argument -e and an expression to evaluate and print it, eg. -e "2 * (3 + 4)", note the double quotation marks are required when an expression contains space characters.

Pass an option -p and a number to set the memory pool threshold size of an interpreter, eg. -e 33554432 to set the threshold to 32MB. MY-BASIC will tidy the memory pool when the free list reached this size.

10. Extra Information

Document version

Version: 1.2.10 Feb. 2016

Author: Wang Renxin License: the MIT license

First edited date: Mar. 8, 2011

Last edited date: Feb. 29, 2016