Hardware Locality (hwloc) 1.7.2

Generated by Doxygen 1.8.4

Tue Sep 3 2013 10:24:22

Contents

1	Hard	ware Locality	1
	1.1	Introduction	1
	1.2	Installation	2
	1.3	CLI Examples	3
	1.4	Programming Interface	7
		1.4.1 Portability	8
		1.4.2 API Example	11
	1.5	Questions and Bugs	13
	1.6	History / Credits	14
	1.7	Further Reading	14
2	Term	ns and Definitions	15
3	Com	mand-Line Tools	19
	3.1	Istopo and Istopo-no-graphics	19
	3.2	hwloc-bind	19
	3.3	hwloc-calc	19
	3.4	hwloc-info	20
	3.5	hwloc-distrib	20
	3.6	hwloc-ps	20
	3.7	hwloc-gather-topology	20
	3.8	hwloc-distances	20
	3.9	hwloc-annotate	20
	3.10	hwloc-assembler	20
	3.11	hwloc-assembler-remote	20
4	Envi	ronment Variables	21
5	CPU	and Memory Binding Overview	23
6	I/O D	Devices Control of the Control of th	25
	6.1	Enabling and requirements	25
	6.2	I/O object hierarchy	25

iv CONTENTS

	6.3	Software devices	25
	6.4	Consulting I/O devices and binding	26
	6.5	Examples	27
7	Multi	i-node Topologies	29
	7.1	Multi-node Objects Specifities	29
	7.2	Assembling topologies with command-line tools	30
	7.3	Assembling topologies with the programming interface	30
	7.4	Example of assembly with the programming interface	30
	٠		
8	_	ct attributes	33
	8.1	Normal attributes	33
	8.2	Custom string infos	33
9	Impo	orting and exporting topologies from/to XML files	35
	9.1	libxml2 and minimalistic XML backends	35
	9.2	XML import error management	36
10	Synt	hetic topologies	37
	-	Synthetic description string	37
		Loading a synthetic topology	37
	10.3	Exporting a topology as a synthetic string	38
11	Intor	onershility With Other Software	30
11	Inter	operability With Other Software	39
		operability With Other Software ad Safety	39 41
12	Thre		
12	Thre Com	ad Safety	41
12	Thre Com 13.1	ad Safety ponents and plugins	41 43
12	Com 13.1 13.2	ad Safety ponents and plugins Components enabled by default	41 43 43
12	Thre Com 13.1 13.2 13.3	ad Safety ponents and plugins Components enabled by default	41 43 43
12	Thre Com 13.1 13.2 13.3	ad Safety ponents and plugins Components enabled by default	41 43 43 43 44
12	Thre Com 13.1 13.2 13.3	ad Safety ponents and plugins Components enabled by default	43 43 43 44 44
12	Thre Com 13.1 13.2 13.3 13.4	ponents and plugins Components enabled by default Selecting which components to use Loading components from plugins Adding new discovery components and plugins 13.4.1 Basics of discovery components	41 43 43 44 44 44
12 13	Thre Com 13.1 13.2 13.3 13.4	ponents and plugins Components enabled by default	41 43 43 44 44 44 44
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb	ponents and plugins Components enabled by default	41 43 43 44 44 44 45
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb 14.1	ponents and plugins Components enabled by default . Selecting which components to use . Loading components from plugins . Adding new discovery components and plugins . 13.4.1 Basics of discovery components . 13.4.2 Registering a new discovery component . Existing components and plugins . edding hwloc in Other Software	41 43 43 44 44 44 45 47
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb 14.1 14.2	ponents and plugins Components enabled by default . Selecting which components to use . Loading components from plugins . Adding new discovery components and plugins . 13.4.1 Basics of discovery components . 13.4.2 Registering a new discovery component . Existing components and plugins . edding hwloc in Other Software Using hwloc's M4 Embedding Capabilities . Example Embedding hwloc .	41 43 43 44 44 44 45 47
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb 14.1 14.2 Freq	ponents and plugins Components enabled by default	41 43 43 44 44 44 45 47 49
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb 14.1 14.2 Freq 15.1	ponents and plugins Components enabled by default Selecting which components to use Loading components from plugins Adding new discovery components and plugins 13.4.1 Basics of discovery components 13.4.2 Registering a new discovery component Existing components and plugins edding hwloc in Other Software Using hwloc's M4 Embedding Capabilities Example Embedding hwloc uently Asked Questions I do not want hwloc to rediscover my enormous machine topology every time I rerun a process	41 43 43 44 44 44 45 47 47 49
12 13	Thre Com 13.1 13.2 13.3 13.4 13.5 Emb 14.1 14.2 Freq 15.1 15.2	ponents and plugins Components enabled by default	41 43 43 44 44 44 45 47 49 51

CONTENTS

	15.4	hwloc o	nly has a	one-dir	nensio	onal v	view o	of the	arch	itectu	ıre, i	t igr	nore	s dis	tance	es .	 	 	 52
	15.5	How ma	ay I ignore	symm	etric n	nultith	ıreadi	ing, h	yper-	threa	adin	g,	?.				 	 	 52
	15.6	What ha	appens if	my topo	ology i	is asy	/mme	tric?									 	 	 53
	15.7	How do	I annotat	e the to	polog	ງy with	n priva	ate no	otes?								 	 	 53
	15.8	Why do	es Valgrin	nd comp	olain a	about	hwloc	c men	nory	leaks	s? .						 	 	 54
	15.9	How do	I handle	API upç	grades	s?											 	 	 54
	15.10	OHow do	I build hw	vloc for	BlueG	Gene/	Q? .										 	 	 54
	15.1	1 How to	get useful	l topolo	gy info	ormat	tion or	n Net	BSD	? .							 	 	 54
16	Mod	ule Inde	x																55
	16.1	Module	S														 	 	 55
17	Data	Structu	re Index																57
	17.1	Data St	ructures							٠.							 	 	 57
18	Mod	ule Docı	umentatio	on															59
	18.1	API ver	sion														 	 	 59
		18.1.1	Detailed	Descrip	otion												 	 	 59
		18.1.2	Macro De	efinition	ı Docu	ument	ation										 	 	 59
			18.1.2.1	HWLC	OC_AF	PI_VE	ERSIC	ON .									 	 	 59
			18.1.2.2	HWLC	CC_CC	ОМРО	ONEN	NT_A	BI.								 	 	 59
		18.1.3	Function	Docum	nentati	ion .											 	 	 59
			18.1.3.1	hwloc	_get_a	api_ve	ersior	n									 	 	 59
	18.2	Topolog	y context														 	 	 60
		18.2.1	Detailed	Descrip	otion												 	 	 60
		18.2.2	Typedef [Docume	entatio	on											 	 	 60
			18.2.2.1	hwloc	_topol	logy_t	ţ										 	 	 60
	18.3		sets (hwlo														 	 	 61
		18.3.1	Detailed	Descrip	otion												 	 	 61
		18.3.2	Typedef [Docume	entatio	on											 	 	 61
			18.3.2.1	hwloc	_cons	st_cpu	uset_t	ι									 	 	 61
			18.3.2.2	hwloc	_cons	st_nod	deset_	_t .									 	 	 61
			18.3.2.3	hwloc	_cpus	set_t											 	 	 61
			18.3.2.4	hwloc	_node	eset_t	t										 	 	 61
	18.4	Topolog	y Object	Types													 	 	 62
		18.4.1	Detailed	Descrip	otion												 	 	 62
		18.4.2	Typedef [Docume	entatio	on											 	 	 62
			18.4.2.1	hwloc	_obj_k	bridge	e_type	e_t									 	 	 62
			18.4.2.2	hwloc	_obj_c	cache	∍_typ∈	e_t .									 	 	 62
			18.4.2.3	hwloc	_obj_c	osdev	/_typ€	∍_t .									 	 	 62
		18.4.3	Enumera	tion Typ	pe Dod	cume	ntatio	n .									 	 	 62

vi CONTENTS

		18.4.3.1	hwloc_compare_types_e	62
		18.4.3.2	hwloc_obj_bridge_type_e	63
		18.4.3.3	hwloc_obj_cache_type_e	63
		18.4.3.4	hwloc_obj_osdev_type_e	63
		18.4.3.5	hwloc_obj_type_t	63
1	18.4.4	Function I	Documentation	64
		18.4.4.1	hwloc_compare_types	64
18.5 T	Topolog	gy Objects		65
1	18.5.1	Detailed [Description	65
1	18.5.2	Typedef D	Documentation	65
		18.5.2.1	$hwloc_obj_t \dots \dots \dots \dots \dots \dots \dots \dots \dots $	65
18.6	Create	and Destro	by Topologies	66
1	18.6.1	Detailed [Description	66
1	18.6.2	Function I	Documentation	66
		18.6.2.1	hwloc_topology_check	66
		18.6.2.2	hwloc_topology_destroy	66
		18.6.2.3	hwloc_topology_init	66
		18.6.2.4	hwloc_topology_load	66
18.7	Configu	re Topolog	gy Detection	68
1	18.7.1	Detailed [Description	68
1	18.7.2	Enumerat	tion Type Documentation	69
		18.7.2.1	hwloc_topology_flags_e	69
1	18.7.3	Function I	Documentation	69
		18.7.3.1	hwloc_topology_get_support	69
		18.7.3.2	hwloc_topology_ignore_all_keep_structure	69
		18.7.3.3	hwloc_topology_ignore_type	69
		18.7.3.4	hwloc_topology_ignore_type_keep_structure	70
		18.7.3.5	hwloc_topology_set_custom	70
		18.7.3.6	hwloc_topology_set_distance_matrix	70
		18.7.3.7	hwloc_topology_set_flags	70
		18.7.3.8	hwloc_topology_set_fsroot	71
		18.7.3.9	hwloc_topology_set_pid	71
		18.7.3.10	hwloc_topology_set_synthetic	71
		18.7.3.11	hwloc_topology_set_xml	72
		18.7.3.12	hwloc_topology_set_xmlbuffer	72
18.8 E	Exporti	ng Topolog	gies to XML	73
1	18.8.1	Detailed [Description	73
1	18.8.2	Function I	Documentation	73
		18.8.2.1	hwloc_export_obj_userdata	73
		18.8.2.2	hwloc_export_obj_userdata_base64	73

CONTENTS vii

	18.8.2.3	hwloc_free_xmlbuffer	74
	18.8.2.4	hwloc_topology_export_xml	74
	18.8.2.5	hwloc_topology_export_xmlbuffer	74
	18.8.2.6	hwloc_topology_set_userdata_export_callback	74
	18.8.2.7	hwloc_topology_set_userdata_import_callback	75
18.9 Tinker	With Topo	logies	76
18.9.1	Detailed	Description	76
18.9.2	Enumera	tion Type Documentation	76
	18.9.2.1	hwloc_restrict_flags_e	76
18.9.3	Function	Documentation	76
	18.9.3.1	hwloc_topology_insert_misc_object_by_cpuset	76
	18.9.3.2	hwloc_topology_insert_misc_object_by_parent	77
	18.9.3.3	hwloc_topology_restrict	77
18.10Get Sc	ome Topolo	ogy Information	78
18.10.	1 Detailed	Description	78
18.10.	2 Enumera	tion Type Documentation	78
	18.10.2.1	hwloc_get_type_depth_e	78
18.10.	3 Function	Documentation	78
	18.10.3.1	hwloc_get_depth_type	78
	18.10.3.2	2 hwloc_get_nbobjs_by_depth	79
	18.10.3.3	B hwloc_get_nbobjs_by_type	79
	18.10.3.4	hwloc_get_type_depth	79
	18.10.3.5	5 hwloc_topology_get_depth	79
	18.10.3.6	6 hwloc_topology_get_flags	79
	18.10.3.7	hwloc_topology_is_thissystem	79
18.11 Retrie	ve Objects		80
18.11.	1 Detailed	Description	80
18.11.	2 Function	Documentation	80
	18.11.2.1	hwloc_get_obj_by_depth	80
	18.11.2.2	2 hwloc_get_obj_by_type	80
18.12Object	/String Cor	nversion	81
18.12.	1 Detailed	Description	81
18.12.	2 Function	Documentation	81
	18.12.2.1	hwloc_obj_add_info	81
	18.12.2.2	2 hwloc_obj_attr_snprintf	81
	18.12.2.3	B hwloc_obj_cpuset_snprintf	81
	18.12.2.4	1 hwloc_obj_get_info_by_name	82
	18.12.2.5	5 hwloc_obj_snprintf	82
	18.12.2.6	6 hwloc_obj_type_of_string	82
	18.12.2.7	hwloc_obj_type_snprintf	82

viii CONTENTS

18.12.2.8 hwloc_obj_type_string	83
18.13CPU binding	84
18.13.1 Detailed Description	84
18.13.2 Enumeration Type Documentation	85
18.13.2.1 hwloc_cpubind_flags_t	85
18.13.3 Function Documentation	85
18.13.3.1 hwloc_get_cpubind	85
18.13.3.2 hwloc_get_last_cpu_location	85
18.13.3.3 hwloc_get_proc_cpubind	86
18.13.3.4 hwloc_get_proc_last_cpu_location	86
18.13.3.5 hwloc_get_thread_cpubind	86
18.13.3.6 hwloc_set_cpubind	86
18.13.3.7 hwloc_set_proc_cpubind	87
18.13.3.8 hwloc_set_thread_cpubind	87
18.14Memory binding	88
18.14.1 Detailed Description	88
18.14.2 Enumeration Type Documentation	89
18.14.2.1 hwloc_membind_flags_t	89
18.14.2.2 hwloc_membind_policy_t	90
18.14.3 Function Documentation	90
18.14.3.1 hwloc_alloc	90
18.14.3.2 hwloc_alloc_membind	91
18.14.3.3 hwloc_alloc_membind_nodeset	91
18.14.3.4 hwloc_free	91
18.14.3.5 hwloc_get_area_membind	91
18.14.3.6 hwloc_get_area_membind_nodeset	91
18.14.3.7 hwloc_get_membind	92
18.14.3.8 hwloc_get_membind_nodeset	92
18.14.3.9 hwloc_get_proc_membind	93
18.14.3.10hwloc_get_proc_membind_nodeset	93
18.14.3.11hwloc_set_area_membind	94
18.14.3.12hwloc_set_area_membind_nodeset	94
18.14.3.13hwloc_set_membind	94
18.14.3.14hwloc_set_membind_nodeset	94
18.14.3.15hwloc_set_proc_membind	95
18.14.3.16hwloc_set_proc_membind_nodeset	95
18.15Building Custom Topologies	96
18.15.1 Detailed Description	96
18.15.2 Function Documentation	96
18.15.2.1 hwloc custom insert group object by parent	96

CONTENTS

18.15.2.2 hwloc_custom_insert_topology	96
18.16Object Type Helpers	97
18.16.1 Detailed Description	97
18.16.2 Function Documentation	97
18.16.2.1 hwloc_get_type_or_above_depth	97
18.16.2.2 hwloc_get_type_or_below_depth	97
18.17Basic Traversal Helpers	98
18.17.1 Detailed Description	98
18.17.2 Function Documentation	98
18.17.2.1 hwloc_get_ancestor_obj_by_depth	98
18.17.2.2 hwloc_get_ancestor_obj_by_type	98
18.17.2.3 hwloc_get_common_ancestor_obj	98
18.17.2.4 hwloc_get_next_child	98
18.17.2.5 hwloc_get_next_obj_by_depth	99
18.17.2.6 hwloc_get_next_obj_by_type	99
18.17.2.7 hwloc_get_pu_obj_by_os_index	99
18.17.2.8 hwloc_get_root_obj	99
18.17.2.9 hwloc_obj_is_in_subtree	99
18.18Finding Objects Inside a CPU set	100
18.18.1 Detailed Description	100
18.18.2 Function Documentation	100
18.18.2.1 hwloc_get_first_largest_obj_inside_cpuset	100
18.18.2.2 hwloc_get_largest_objs_inside_cpuset	100
18.18.2.3 hwloc_get_nbobjs_inside_cpuset_by_depth	101
18.18.2.4 hwloc_get_nbobjs_inside_cpuset_by_type	101
18.18.2.5 hwloc_get_next_obj_inside_cpuset_by_depth	101
18.18.2.6 hwloc_get_next_obj_inside_cpuset_by_type	101
18.18.2.7 hwloc_get_obj_index_inside_cpuset	101
18.18.2.8 hwloc_get_obj_inside_cpuset_by_depth	102
18.18.2.9 hwloc_get_obj_inside_cpuset_by_type	102
18.19Finding a single Object covering at least CPU set	103
18.19.1 Detailed Description	103
18.19.2 Function Documentation	103
18.19.2.1 hwloc_get_child_covering_cpuset	103
18.19.2.2 hwloc_get_obj_covering_cpuset	103
18.20 Finding a set of similar Objects covering at least a CPU set	104
18.20.1 Detailed Description	104
18.20.2 Function Documentation	104
18.20.2.1 hwloc_get_next_obj_covering_cpuset_by_depth	104
18.20.2.2 hwloc_get_next_obj_covering_cpuset_by_type	104

X CONTENTS

18.21 Cache-specific Finding Helpers	105
18.21.1 Detailed Description	105
18.21.2 Function Documentation	105
18.21.2.1 hwloc_get_cache_covering_cpuset	105
18.21.2.2 hwloc_get_cache_type_depth	105
18.21.2.3 hwloc_get_shared_cache_covering_obj	105
18.22 Advanced Traversal Helpers	106
18.22.1 Detailed Description	106
18.22.2 Function Documentation	106
18.22.2.1 hwloc_get_closest_objs	106
18.22.2.2 hwloc_get_obj_below_array_by_type	106
18.22.2.3 hwloc_get_obj_below_by_type	107
18.23Binding Helpers	108
18.23.1 Detailed Description	108
18.23.2 Function Documentation	108
18.23.2.1 hwloc_alloc_membind_policy	108
18.23.2.2 hwloc_alloc_membind_policy_nodeset	108
18.23.2.3 hwloc_distribute	108
18.23.2.4 hwloc_distributev	108
18.24Cpuset Helpers	110
18.24.1 Detailed Description	110
18.24.2 Function Documentation	110
18.24.2.1 hwloc_topology_get_allowed_cpuset	110
18.24.2.2 hwloc_topology_get_complete_cpuset	110
18.24.2.3 hwloc_topology_get_online_cpuset	111
18.24.2.4 hwloc_topology_get_topology_cpuset	111
18.25Nodeset Helpers	112
18.25.1 Detailed Description	112
18.25.2 Function Documentation	112
18.25.2.1 hwloc_topology_get_allowed_nodeset	112
18.25.2.2 hwloc_topology_get_complete_nodeset	112
18.25.2.3 hwloc_topology_get_topology_nodeset	112
18.26Conversion between cpuset and nodeset	114
18.26.1 Detailed Description	114
18.26.2 Function Documentation	114
18.26.2.1 hwloc_cpuset_from_nodeset	114
18.26.2.2 hwloc_cpuset_from_nodeset_strict	
18.26.2.3 hwloc_cpuset_to_nodeset	
18.26.2.4 hwloc_cpuset_to_nodeset_strict	115
18.27 Distances	116

CONTENTS xi

18.27.1 Detailed Description	116
18.27.2 Function Documentation	116
18.27.2.1 hwloc_get_distance_matrix_covering_obj_by_depth	116
18.27.2.2 hwloc_get_latency	116
18.27.2.3 hwloc_get_whole_distance_matrix_by_depth	116
18.27.2.4 hwloc_get_whole_distance_matrix_by_type	117
18.28Advanced I/O object traversal helpers	118
18.28.1 Detailed Description	118
18.28.2 Function Documentation	118
18.28.2.1 hwloc_bridge_covers_pcibus	118
18.28.2.2 hwloc_get_hostbridge_by_pcibus	118
18.28.2.3 hwloc_get_next_bridge	118
18.28.2.4 hwloc_get_next_osdev	118
18.28.2.5 hwloc_get_next_pcidev	118
18.28.2.6 hwloc_get_non_io_ancestor_obj	119
18.28.2.7 hwloc_get_pcidev_by_busid	119
18.28.2.8 hwloc_get_pcidev_by_busidstring	119
18.29The bitmap API	120
18.29.1 Detailed Description	121
18.29.2 Macro Definition Documentation	121
18.29.2.1 hwloc_bitmap_foreach_begin	121
18.29.2.2 hwloc_bitmap_foreach_end	121
18.29.3 Typedef Documentation	122
18.29.3.1 hwloc_bitmap_t	122
18.29.3.2 hwloc_const_bitmap_t	122
18.29.4 Function Documentation	122
18.29.4.1 hwloc_bitmap_allbut	122
18.29.4.2 hwloc_bitmap_alloc	122
18.29.4.3 hwloc_bitmap_alloc_full	122
18.29.4.4 hwloc_bitmap_and	122
18.29.4.5 hwloc_bitmap_andnot	122
18.29.4.6 hwloc_bitmap_asprintf	122
18.29.4.7 hwloc_bitmap_clr	122
18.29.4.8 hwloc_bitmap_clr_range	123
18.29.4.9 hwloc_bitmap_compare	123
18.29.4.10hwloc_bitmap_compare_first	123
18.29.4.11hwloc_bitmap_copy	123
18.29.4.12hwloc_bitmap_dup	123
18.29.4.13hwloc_bitmap_fill	123
18.29.4.14hwloc_bitmap_first	123

xii CONTENTS

CONTENTS xiii

18.31.2.1 hwloc_backend_flag_e	129
18.31.3 Function Documentation	129
18.31.3.1 hwloc_backend_alloc	129
18.31.3.2 hwloc_backend_enable	129
18.31.3.3 hwloc_backends_get_obj_cpuset	129
18.31.3.4 hwloc_backends_notify_new_object	130
18.32Generic components	131
18.32.1 Detailed Description	131
18.32.2 Typedef Documentation	131
18.32.2.1 hwloc_component_type_t	131
18.32.3 Enumeration Type Documentation	131
18.32.3.1 hwloc_component_type_e	131
18.33Core functions to be used by components	132
18.33.1 Detailed Description	132
18.33.2 Typedef Documentation	132
18.33.2.1 hwloc_report_error_t	132
18.33.3 Function Documentation	132
18.33.3.1 hwlocinsert_object_by_cpuset	132
18.33.3.2 hwloc_alloc_setup_object	132
18.33.3.3 hwloc_hide_errors	132
18.33.3.4 hwloc_insert_object_by_cpuset	132
18.33.3.5 hwloc_insert_object_by_parent	133
18.33.3.6 hwloc_report_os_error	133
18.34Helpers for manipulating glibc sched affinity	134
18.34.1 Detailed Description	134
18.34.2 Function Documentation	134
18.34.2.1 hwloc_cpuset_from_glibc_sched_affinity	134
18.34.2.2 hwloc_cpuset_to_glibc_sched_affinity	134
18.35Linux-only helpers	135
18.35.1 Detailed Description	135
18.35.2 Function Documentation	135
18.35.2.1 hwloc_linux_get_tid_cpubind	135
18.35.2.2 hwloc_linux_parse_cpumap_file	135
18.35.2.3 hwloc_linux_set_tid_cpubind	135
18.36Helpers for manipulating Linux libnuma unsigned long masks	136
18.36.1 Detailed Description	136
18.36.2 Function Documentation	136
18.36.2.1 hwloc_cpuset_from_linux_libnuma_ulongs	136
18.36.2.2 hwloc_cpuset_to_linux_libnuma_ulongs	136
18.36.2.3 hwloc_nodeset_from_linux_libnuma_ulongs	136

XIV

18.36.2.4 hwloc_nodeset_to_linux_libnuma_ulongs	136
18.37Helpers for manipulating Linux libnuma bitmask	138
18.37.1 Detailed Description	138
18.37.2 Function Documentation	138
18.37.2.1 hwloc_cpuset_from_linux_libnuma_bitmask	138
18.37.2.2 hwloc_cpuset_to_linux_libnuma_bitmask	138
18.37.2.3 hwloc_nodeset_from_linux_libnuma_bitmask	138
18.37.2.4 hwloc_nodeset_to_linux_libnuma_bitmask	138
18.38OpenCL Specific Functions	139
18.38.1 Detailed Description	139
18.38.2 Function Documentation	139
18.38.2.1 hwloc_opencl_get_device_cpuset	139
18.38.2.2 hwloc_opencl_get_device_osdev	139
18.38.2.3 hwloc_opencl_get_device_osdev_by_index	139
18.39CUDA Driver API Specific Functions	141
18.39.1 Detailed Description	141
18.39.2 Function Documentation	141
18.39.2.1 hwloc_cuda_get_device_cpuset	141
18.39.2.2 hwloc_cuda_get_device_osdev	141
18.39.2.3 hwloc_cuda_get_device_osdev_by_index	141
18.39.2.4 hwloc_cuda_get_device_pci_ids	142
18.39.2.5 hwloc_cuda_get_device_pcidev	142
18.40 CUDA Runtime API Specific Functions	143
18.40.1 Detailed Description	143
18.40.2 Function Documentation	143
18.40.2.1 hwloc_cudart_get_device_cpuset	143
18.40.2.2 hwloc_cudart_get_device_osdev_by_index	143
18.40.2.3 hwloc_cudart_get_device_pci_ids	143
18.40.2.4 hwloc_cudart_get_device_pcidev	144
18.41NVIDIA Management Library Specific Functions	145
18.41.1 Detailed Description	145
18.41.2 Function Documentation	145
18.41.2.1 hwloc_nvml_get_device_cpuset	145
18.41.2.2 hwloc_nvml_get_device_osdev	145
18.41.2.3 hwloc_nvml_get_device_osdev_by_index	145
18.42OpenGL display specific functions	146
18.42.1 Detailed Description	146
18.42.2 Function Documentation	146
18.42.2.1 hwloc_gl_get_display_by_osdev	146
18.42.2.2 hwloc_gl_get_display_osdev_by_name	146

CONTENTS xv

18.42.2.3 hwloc_gl_get_display_osdev_by_port_device	 146
18.43 Intel Xeon Phi (MIC) Specific Functions	 147
18.43.1 Detailed Description	 147
18.43.2 Function Documentation	 147
18.43.2.1 hwloc_intel_mic_get_device_cpuset	 147
18.43.2.2 hwloc_intel_mic_get_device_osdev_by_index	 147
18.44OpenFabrics-Specific Functions	 148
18.44.1 Detailed Description	 148
18.44.2 Function Documentation	 148
18.44.2.1 hwloc_ibv_get_device_cpuset	 148
18.44.2.2 hwloc_ibv_get_device_osdev	 148
18.44.2.3 hwloc_ibv_get_device_osdev_by_name	 148
18.45Myrinet Express-Specific Functions	 149
18.45.1 Detailed Description	 149
18.45.2 Function Documentation	 149
18.45.2.1 hwloc_mx_board_get_device_cpuset	 149
18.45.2.2 hwloc_mx_endpoint_get_device_cpuset	 149
19 Data Structure Documentation	151
19.1 hwloc backend Struct Reference	
19.1.1 Detailed Description	
19.1.2 Field Documentation	
19.1.2.2 discover	
19.1.2.4 get_obj_cpuset	
19.1.2.5 is_custom	
19.1.2.6 is_thissystem	
19.1.2.8 private_data	
19.2 hwloc_obj_attr_u::hwloc_bridge_attr_s Struct Reference	
19.2.2 Field Documentation	
19.2.2.1 depth	
19.2.2.2 domain	
19.2.2.3 downstream	
19.2.2.4 downstream_type	
19.2.2.5 pci	
19.2.2.6 pci	
19.2.2.7 secondary_bus	
	 . 55

xvi CONTENTS

		19.2.2.8	subordinate_bus	. 153
		19.2.2.9	upstream	. 153
		19.2.2.10	O upstream_type	. 153
19.3	hwloc_	obj_attr_u	ı::hwloc_cache_attr_s Struct Reference	. 153
	19.3.1	Detailed	Description	. 153
	19.3.2	Field Doo	cumentation	. 154
		19.3.2.1	associativity	. 154
		19.3.2.2	depth	. 154
		19.3.2.3	linesize	. 154
		19.3.2.4	size	. 154
		19.3.2.5	type	. 154
19.4	hwloc_	componer	nt Struct Reference	. 154
	19.4.1	Detailed	Description	. 154
	19.4.2	Field Doo	cumentation	. 154
		19.4.2.1	abi	. 154
		19.4.2.2	data	. 155
		19.4.2.3	flags	. 155
		19.4.2.4	type	. 155
19.5	hwloc_	disc_comp	ponent Struct Reference	. 155
	19.5.1	Detailed	Description	. 155
	19.5.2	Field Doo	cumentation	. 155
		19.5.2.1	excludes	. 155
		19.5.2.2	instantiate	. 155
		19.5.2.3	name	. 156
		19.5.2.4	priority	. 156
		19.5.2.5	type	. 156
19.6	hwloc_	distances_	_s Struct Reference	. 156
	19.6.1	Detailed	Description	. 156
	19.6.2	Field Doo	cumentation	. 156
		19.6.2.1	latency	. 156
		19.6.2.2	latency_base	. 157
		19.6.2.3	latency_max	. 157
		19.6.2.4	nbobjs	. 157
		19.6.2.5	relative_depth	. 157
19.7	hwloc_	obj_attr_u	:::hwloc_group_attr_s Struct Reference	. 157
	19.7.1	Detailed	Description	. 157
	19.7.2	Field Doo	cumentation	. 157
		19.7.2.1	depth	. 157
19.8	hwloc_	obj Struct	Reference	. 157
	19.8.1	Detailed	Description	. 158

CONTENTS xvii

	19.8.2	Field Doc	cumentation	. 158
		19.8.2.1	allowed_cpuset	. 158
		19.8.2.2	allowed_nodeset	. 159
		19.8.2.3	arity	. 159
		19.8.2.4	attr	. 159
		19.8.2.5	children	. 159
		19.8.2.6	complete_cpuset	. 159
		19.8.2.7	complete_nodeset	. 159
		19.8.2.8	cpuset	. 160
		19.8.2.9	depth	. 160
		19.8.2.10	distances	. 160
		19.8.2.11	distances_count	. 160
		19.8.2.12	? first_child	. 160
		19.8.2.13	3 infos	. 160
		19.8.2.14	infos_count	. 160
		19.8.2.15	is last_child	. 160
		19.8.2.16	S logical_index	. 160
		19.8.2.17	7 memory	. 160
		19.8.2.18	Biname	. 160
		19.8.2.19	next_cousin	. 161
		19.8.2.20	next_sibling	. 161
		19.8.2.21	nodeset	. 161
		19.8.2.22	online_cpuset	. 161
		19.8.2.23	B os_index	. 161
		19.8.2.24	os_level	. 161
		19.8.2.25	parent	. 161
		19.8.2.26	prev_cousin	. 161
		19.8.2.27	prev_sibling	. 162
		19.8.2.28	B sibling_rank	. 162
		19.8.2.29	symmetric_subtree	. 162
		19.8.2.30) type	. 162
		19.8.2.31	userdata	. 162
19.9	hwloc_c	obj_attr_u	Union Reference	. 162
	19.9.1	Detailed [Description	. 163
	19.9.2	Field Doc	cumentation	. 163
		19.9.2.1	bridge	. 163
		19.9.2.2	cache	. 163
		19.9.2.3	group	. 163
		19.9.2.4	osdev	. 163
		19.9.2.5	pcidev	. 163

xviii CONTENTS

19.10hwloc_obj_info_s Struct Reference	63
19.10.1 Detailed Description	63
19.10.2 Field Documentation	63
19.10.2.1 name	63
19.10.2.2 value	63
19.11hwloc_obj_memory_s::hwloc_obj_memory_page_type_s Struct Reference	63
19.11.1 Detailed Description	64
19.11.2 Field Documentation	64
19.11.2.1 count	64
19.11.2.2 size	64
19.12hwloc_obj_memory_s Struct Reference	64
19.12.1 Detailed Description	64
19.12.2 Field Documentation	64
19.12.2.1 local_memory	64
19.12.2.2 page_types	65
19.12.2.3 page_types_len	65
19.12.2.4 total_memory	65
19.13hwloc_obj_attr_u::hwloc_osdev_attr_s Struct Reference	65
19.13.1 Detailed Description	65
19.13.2 Field Documentation	65
19.13.2.1 type	65
19.14hwloc_obj_attr_u::hwloc_pcidev_attr_s Struct Reference	65
19.14.1 Detailed Description	66
19.14.2 Field Documentation	66
19.14.2.1 bus	66
19.14.2.2 class_id	66
19.14.2.3 dev	66
19.14.2.4 device_id	66
19.14.2.5 domain	66
19.14.2.6 func	66
19.14.2.7 linkspeed	66
19.14.2.8 revision	66
19.14.2.9 subdevice_id	66
19.14.2.10subvendor_id	66
19.14.2.11vendor_id	66
19.15hwloc_topology_cpubind_support Struct Reference	66
19.15.1 Detailed Description	66
19.15.2 Field Documentation	67
19.15.2.1 get_proc_cpubind	67
19.15.2.2 get_proc_last_cpu_location	67

CONTENTS xix

19.15.2.3 get_thisproc_cpubind	167
19.15.2.4 get_thisproc_last_cpu_location	167
19.15.2.5 get_thisthread_cpubind	167
19.15.2.6 get_thisthread_last_cpu_location	167
19.15.2.7 get_thread_cpubind	167
19.15.2.8 set_proc_cpubind	167
19.15.2.9 set_thisproc_cpubind	167
19.15.2.10set_thisthread_cpubind	167
19.15.2.11set_thread_cpubind	167
19.16hwloc_topology_discovery_support Struct Reference	168
19.16.1 Detailed Description	168
19.16.2 Field Documentation	168
19.16.2.1 pu	168
19.17hwloc_topology_membind_support Struct Reference	168
19.17.1 Detailed Description	168
19.17.2 Field Documentation	169
19.17.2.1 alloc_membind	169
19.17.2.2 bind_membind	169
19.17.2.3 firsttouch_membind	169
19.17.2.4 get_area_membind	169
19.17.2.5 get_proc_membind	169
19.17.2.6 get_thisproc_membind	169
19.17.2.7 get_thisthread_membind	169
19.17.2.8 interleave_membind	169
19.17.2.9 migrate_membind	169
19.17.2.10nexttouch_membind	169
19.17.2.11replicate_membind	169
19.17.2.12set_area_membind	169
19.17.2.13set_proc_membind	170
19.17.2.14set_thisproc_membind	170
19.17.2.15set_thisthread_membind	170
19.18hwloc_topology_support Struct Reference	170
19.18.1 Detailed Description	170
19.18.2 Field Documentation	170
19.18.2.1 cpubind	170
19.18.2.2 discovery	170
19.18.2.3 membind	170

Chapter 1

Hardware Locality

Portable abstraction of hierarchical architectures for high-performance computing

1.1 Introduction

hwloc provides command line tools and a C API to obtain the hierarchical map of key computing elements, such as: NUMA memory nodes, shared caches, processor sockets, processor cores, processing units (logical processors or "threads") and even I/O devices. hwloc also gathers various attributes such as cache and memory information, and is portable across a variety of different operating systems and platforms. Additionally it may assemble the topologies of multiple machines into a single one so as to let applications consult the topology of an entire fabric or cluster at once.

hwloc primarily aims at helping high-performance computing (HPC) applications, but is also applicable to any project seeking to exploit code and/or data locality on modern computing platforms.

Note that the hwloc project represents the merger of the libtopology project from inria and the Portable Linux Processor Affinity (PLPA) sub-project from Open MPI. Both of these prior projects are now deprecated. The first hwloc release was essentially a "re-branding" of the libtopology code base, but with both a few genuinely new features and a few PLPA-like features added in. Prior releases of hwloc included documentation about switching from PLPA to hwloc; this documentation has been dropped on the assumption that everyone who was using PLPA has already switched to hwloc.

hwloc supports the following operating systems:

- Linux (including old kernels not having sysfs topology information, with knowledge of cpusets, offline CPUs, ScaleMP vSMP, and Kerrighed support)
- · Solaris
- AIX
- · Darwin / OS X
- · FreeBSD and its variants (such as kFreeBSD/GNU)
- NetBSD
- OSF/1 (a.k.a., Tru64)
- HP-UX
- Microsoft Windows
- IBM BlueGene/Q Compute Node Kernel (CNK)

Since it uses standard Operating System information, hwloc's support is mostly independant from the processor type (x86, powerpc, ...) and just relies on the Operating System support. The only exception to this is kFreeBSD, which does not support topology information, and hwloc thus uses an x86-only CPUID-based backend (which can be used for other OSes too, see the Components and plugins section).

To check whether hwloc works on a particular machine, just try to build it and run lstopo or lstopo-no-graphics. If some things do not look right (e.g. bogus or missing cache information), see Questions and Bugs below.

hwloc only reports the number of processors on unsupported operating systems; no topology information is available.

For development and debugging purposes, hwloc also offers the ability to work on "fake" topologies:

- · Symmetrical tree of resources generated from a list of level arities
- · Remote machine simulation through the gathering of Linux sysfs topology files

hwloc can display the topology in a human-readable format, either in graphical mode (X11), or by exporting in one of several different formats, including: plain text, PDF, PNG, and FIG (see CLI Examples below). Note that some of the export formats require additional support libraries.

hwloc offers a programming interface for manipulating topologies and objects. It also brings a powerful CPU bitmap API that is used to describe topology objects location on physical/logical processors. See the Programming Interface below. It may also be used to binding applications onto certain cores or memory nodes. Several utility programs are also provided to ease command-line manipulation of topology objects, binding of processes, and so on.

Perl bindings are available from Bernd Kallies on CPAN.

Python bindings are available from Guy Streeter:

```
Fedora RPM and tarball.git tree (html).
```

1.2 Installation

hwloc (http://www.open-mpi.org/projects/hwloc/) is available under the BSD license. It is hosted as a sub-project of the overall Open MPI project (http://www.open-mpi.org/). Note that hwloc does not require any functionality from Open MPI – it is a wholly separate (and much smaller!) project and code base. It just happens to be hosted as part of the overall Open MPI project.

Nightly development snapshots are available on the web site. Additionally, the code can be directly checked out of Subversion:

```
shell$ svn checkout http://svn.open-mpi.org/svn/hwloc/trunk hwloc-trunk
shell$ cd hwloc-trunk
shell$ ./autogen.sh
```

Note that GNU Autoconf >=2.63, Automake >=1.10 and Libtool >=2.2.6 are required when building from a Subversion checkout.

Installation by itself is the fairly common GNU-based process:

```
shell$ ./configure --prefix=...
shell$ make
shell$ make install
```

The hwloc command-line tool "Istopo" produces human-readable topology maps, as mentioned above. It can also export maps to the "fig" file format. Support for PDF, Postscript, and PNG exporting is provided if the "Cairo" development package (usually cairo-devel or libcairo2-dev) can be found in "Istopo" when hwloc is configured and build.

The hwloc core may also benefit from the following development packages:

1.3 CLI Examples 3

• libnuma for memory binding and migration support on Linux (numactl-devel or libnuma-dev package).

- · hwloc can use one of two different libraries for I/O device discovery:
 - 1. libpciaccess (BSD). The relevant development package is usually libpciaccess-devel or libpciaccess-dev.
 - 2. libpci, from the pciutils package (GPL). The relevant development package is usually pciutils—devel or libpci—dev.
- the AMD OpenCL implementation for OpenCL device discovery.
- · the NVIDIA CUDA Toolkit for CUDA device discovery.
- the NVIDIA Tesla Development Kit for NVML device discovery.
- the NV-CONTROL X extension library (NVCtrl) for NVIDIA display discovery.
- libxml2 for full XML import/export support (otherwise, the internal minimalistic parser will only be able to import XML files that were exported by the same hwloc release). See Importing and exporting topologies from/to XML files for details. The relevant development package is usually libxml2-devel or libxml2-dev.
- libtool's ltdl library for dynamic plugin loading. The relevant development package is usually libtool-ltdl-devel or libltdl-dev.

PCI and XML support may be statically built inside the main hwloc library, or as separate dynamically-loaded plugins (see the Components and plugins section).

Note that because of the possibility of GPL taint (remember that hwloc is BSD-licensed), hwloc's configure script will prefer libpciaccess to the pointils package. Indeed, if libpciaccess is not found, hwloc will not use pointils unless it is specifically requested via the <code>-enable-libpci</code> flag is provided.


Also note that if you install supplemental libraries in non-standard locations, hwloc's configure script may not be able to find them without some help. You may need to specify additional CPPFLAGS, LDFLAGS, or PKG_CONFIG_PATH values on the configure command line.

For example, if libpciaccess was installed into /opt/pciaccess, hwloc's configure script may not find it be default. Try adding PKG_CONFIG_PATH to the ./configure command line, like this:

```
./configure PKG_CONFIG_PATH=/opt/pciaccess/lib/pkgconfig ...
```

1.3 CLI Examples

On a 4-socket 2-core machine with hyperthreading, the lstopo tool may show the following graphical output:



Here's the equivalent output in textual form:

```
Machine (16GB)
  Socket L#0 + L3 L#0 (4096KB)
   L2 L#0 (1024KB) + L1 L#0 (16KB) + Core L#0
     PU L#0 (P#0)
      PU L#1 (P#8)
    L2 L#1 (1024KB) + L1 L#1 (16KB) + Core L#1
     PU L#2 (P#4)
      PU L#3 (P#12)
  Socket L#1 + L3 L#1 (4096KB)
    L2 L#2 (1024KB) + L1 L#2 (16KB) + Core L#2
      PU L#4 (P#1)
     PU L#5 (P#9)
    L2 L#3 (1024KB) + L1 L#3 (16KB) + Core L#3
      PU L#6 (P#5)
     PU L#7 (P#13)
  Socket L#2 + L3 L#2 (4096KB)
    L2 L#4 (1024KB) + L1 L#4 (16KB) + Core L#4
     PU L#8 (P#2)
     PU L#9 (P#10)
    L2 L#5 (1024KB) + L1 L#5 (16KB) + Core L#5
      PU L#10 (P#6)
     PU L#11 (P#14)
  Socket L#3 + L3 L#3 (4096KB)
    L2 L\#6 (1024KB) + L1 L\#6 (16KB) + Core L\#6
     PU L#12 (P#3)
     PU L#13 (P#11)
    L2 L\#7 (1024KB) + L1 L\#7 (16KB) + Core L\#7
     PU L#14 (P#7)
     PU L#15 (P#15)
```


Finally, here's the equivalent output in XML. Long lines were artificially broken for document clarity (in the real output, each XML tag is on a single line), and only socket #0 is shown for brevity:

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topology SYSTEM "hwloc.dtd">
```

1.3 CLI Examples 5

```
<topology>
  <object type="Machine" os_index="0" cpuset="0x0000ffff"</pre>
      complete_cpuset="0x0000fffff" online_cpuset="0x0000fffff"
      allowed_cpuset="0x0000ffff"
      dmi_board_vendor="Dell Computer Corporation" dmi_board_name="0RD318"
      local_memory="16648183808">
    <page_type size="4096" count="4064498"/>
    <page_type size="2097152" count="0"/>
    <object type="Socket" os_index="0" cpuset="0x00001111" ... >
      <object type="Cache" cpuset="0x00001111" ...</pre>
          cache_size="4194304" depth="3" cache_linesize="64">
        <object type="Cache" cpuset="0x00000101" ...</pre>
            cache_size="1048576" depth="2" cache_linesize="64">
          <object type="Cache" cpuset="0x00000101" ...</pre>
              cache_size="16384" depth="1" cache_linesize="64">
             <object type="Core" os_index="0" ... >
               <object type="PU" os_index="0" cpuset="0x00000001"</pre>
                   complete_cpuset="0x00000001" online_cpuset="0x00000001"
                   allowed_cpuset="0x00000001"/>
               <object type="PU" os_index="8" cpuset="0x00000100"</pre>
                   complete_cpuset="0x00000100" online_cpuset="0x00000100"
                   allowed_cpuset="0x00000100"/>
             </object>
          </object>
        </object>
        <object type="Cache" cpuset="0x00001010" ...</pre>
             cache_size="1048576" depth="2" cache_linesize="64">
          <object type="Cache" cpuset="0x00001010"</pre>
               cache_size="16384" depth="1" cache_linesize="64">
             <object type="Core" os_index="1" cpuset="0x00001010" ... >
               <object type="PU" os_index="4" cpuset="0x00000010"</pre>
                   complete_cpuset="0x000000010" online_cpuset="0x00000010"
                   allowed_cpuset="0x00000010"/>
              <object type="PU" os_index="12" cpuset="0x00001000"
    complete_cpuset="0x00001000" online_cpuset="0x00001000"</pre>
                   allowed_cpuset="0x00001000"/>
            </object>
          </object>
        </object>
      </object>
    </object>
    <!-- ...other sockets listed here ... -->
  </object>
</topology>
```

On a 4-socket 2-core Opteron NUMA machine, the 1stopo tool may show the following graphical output:



Here's the equivalent output in textual form:

```
Machine (32GB)

NUMANode L#0 (P#0 8190MB) + Socket L#0

L2 L#0 (1024KB) + L1 L#0 (64KB) + Core L#0 + PU L#0 (P#0)

L2 L#1 (1024KB) + L1 L#1 (64KB) + Core L#1 + PU L#1 (P#1)

NUMANode L#1 (P#1 8192MB) + Socket L#1

L2 L#2 (1024KB) + L1 L#2 (64KB) + Core L#2 + PU L#2 (P#2)

L2 L#3 (1024KB) + L1 L#3 (64KB) + Core L#3 + PU L#3 (P#3)
```

```
NUMANOde L#2 (P#2 8192MB) + Socket L#2

L2 L#4 (1024KB) + L1 L#4 (64KB) + Core L#4 + PU L#4 (P#4)

L2 L#5 (1024KB) + L1 L#5 (64KB) + Core L#5 + PU L#5 (P#5)

NUMANOde L#3 (P#3 8192MB) + Socket L#3


L2 L#6 (1024KB) + L1 L#6 (64KB) + Core L#6 + PU L#6 (P#6)

L2 L#7 (1024KB) + L1 L#7 (64KB) + Core L#7 + PU L#7 (P#7)
```

And here's the equivalent output in XML. Similar to above, line breaks were added and only PU #0 is shown for brevity:

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topology SYSTEM "hwloc.dtd">
<topology>
  <object type="Machine" os_index="0" cpuset="0x000000ff"</pre>
      complete_cpuset="0x000000ff" online_cpuset="0x000000ff"
      allowed_cpuset="0x000000ff" nodeset="0x000000ff"
      \verb|complete_nodeset="0x000000ff"| allowed_nodeset="0x000000ff"|
      dmi_board_vendor="TYAN Computer Corp" dmi_board_name="S4881 ">
    <page_type size="4096" count="0"/>
    <page_type size="2097152" count="0"/>
    <object type="NUMANode" os_index="0" cpuset="0x00000003" ...</pre>
        nodeset="0x00000001" ... local_memory="7514177536">
      <page_type size="4096" count="1834516"/>
      <page_type size="2097152" count="0"/>
      <object type="Socket" os_index="0" cpuset="0x00000003" ... >
        <object type="Cache" cpuset="0x00000001" ...</pre>
            cache_size="1048576" depth="2" cache_linesize="64">
          <object type="Cache" cpuset="0x00000001" ...</pre>
              cache_size="65536" depth="1" cache_linesize="64">
            <object type="Core" os_index="0" ... >
              <object type="PU" os_index="0" cpuset="0x00000001"</pre>
                  complete_cpuset="0x00000001" online_cpuset="0x00000001"
                  allowed_cpuset="0x00000001" nodeset="0x00000001"
                  complete_nodeset="0x00000001" allowed_nodeset="0x00000001"/>
            </object>
          </object>
        </object>
  <!-- ...more objects listed here ... -->
</topology>
```

On a 2-socket quad-core Xeon (pre-Nehalem, with 2 dual-core dies into each socket):



Here's the same output in textual form:

```
Machine (16GB)
Socket L#0
L2 L#0 (4096KB)
L1 L#0 (32KB) + Core L#0 + PU L#0 (P#0)
L1 L#1 (32KB) + Core L#1 + PU L#1 (P#4)
```

```
L2 L#1 (4096KB)

L1 L#2 (32KB) + Core L#2 + PU L#2 (P#2)

L1 L#3 (32KB) + Core L#3 + PU L#3 (P#6)

Socket L#1

L2 L#2 (4096KB)

L1 L#4 (32KB) + Core L#4 + PU L#4 (P#1)

L1 L#5 (32KB) + Core L#5 + PU L#5 (P#5)

L2 L#3 (4096KB)

L1 L#6 (32KB) + Core L#6 + PU L#6 (P#3)

L1 L#7 (32KB) + Core L#7 + PU L#7 (P#7)
```

And the same output in XML (line breaks added, only PU #0 shown):

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE topology SYSTEM "hwloc.dtd">
<t.opoloav>
  <object type="Machine" os_index="0" cpuset="0x000000ff"</pre>
      complete_cpuset="0x000000ff" online_cpuset="0x000000ff"
      allowed_cpuset="0x000000ff" dmi_board_vendor="Dell Inc."
      dmi_board_name="0NR282" local_memory="16865292288">
    <page_type size="4096" count="4117503"/>
    <page_type size="2097152" count="0"/>
    <object type="Socket" os_index="0" cpuset="0x00000055" ... >
      <object type="Cache" cpuset="0x00000011" ...</pre>
          cache_size="4194304" depth="2" cache_linesize="64">
        <object type="Cache" cpuset="0x00000001" ...</pre>
            cache_size="32768" depth="1" cache_linesize="64">
          <object type="Core" os_index="0" ... >
            <object type="PU" os_index="0" cpuset="0x00000001"</pre>
                complete_cpuset="0x00000001" online_cpuset="0x00000001"
                allowed_cpuset="0x00000001"/>
          </object>
        </object>
        <object type="Cache" cpuset="0x00000010" ...</pre>
            cache_size="32768" depth="1" cache_linesize="64">
          <object type="Core" os_index="1" ... >
            <object type="PU" os_index="4" cpuset="0x00000010" ...</pre>
                complete_cpuset="0x00000010" online_cpuset="0x00000010"
                allowed_cpuset="0x00000010"/>
          </object>
        </object>
      </object>
 <!-- ...more objects listed here ... -->
</topology>
```

1.4 Programming Interface

The basic interface is available in **hwloc.h**. It essentially offers low-level routines for advanced programmers that want to manually manipulate objects and follow links between them. Documentation for everything in **hwloc.h** are provided later in this document. Developers should also look at **hwloc/helper.h** (and also in this document, which provides good higher-level topology traversal examples).

To precisely define the vocabulary used by hwloc, a Terms and Definitions section is available and should probably be read first.

Each hwloc object contains a cpuset describing the list of processing units that it contains. These bitmaps may be used for CPU binding and Memory binding. hwloc offers an extensive bitmap manipulation interface in hwloc/bitmap.h.

Moreover, hwloc also comes with additional helpers for interoperability with several commonly used environments. See the Interoperability With Other Software section for details.

The complete API documentation is available in a full set of HTML pages, man pages, and self-contained PDF files (formatted for both both US letter and A4 formats) in the source tarball in doc/doxygen-doc/.


NOTE: If you are building the documentation from a Subversion checkout, you will need to have Doxygen and pdflatex installed – the documentation will be built during the normal "make" process. The documentation is installed during "make install" to \$prefix/share/doc/hwloc/ and your systems default man page tree (under \$prefix, of course).

1.4.1 Portability

As shown in CLI Examples, hwloc can obtain information on a wide variety of hardware topologies. However, some platforms and/or operating system versions will only report a subset of this information. For example, on an PP-C64-based system with 32 cores (each with 2 hardware threads) running a default 2.6.18-based kernel from RHEL 5.4, hwloc is only able to glean information about NUMA nodes and processor units (PUs). No information about caches, sockets, or cores is available.

Similarly, Operating System have varying support for CPU and memory binding, e.g. while some Operating Systems provide interfaces for all kinds of CPU and memory bindings, some others provide only interfaces for a limited number of kinds of CPU and memory binding, and some do not provide any binding interface at all. Hwloc's binding functions would then simply return the ENOSYS error (Function not implemented), meaning that the underlying Operating System does not provide any interface for them. CPU binding and Memory binding provide more information on which hwloc binding functions should be preferred because interfaces for them are usually available on the supported Operating Systems.

Here's the graphical output from Istopo on this platform when Simultaneous Multi-Threading (SMT) is enabled:




And here's the graphical output from Istopo on this platform when SMT is disabled:



Notice that hwloc only sees half the PUs when SMT is disabled. PU #15, for example, seems to change location from NUMA node #0 to #1. In reality, no PUs "moved" – they were simply re-numbered when hwloc only saw half as many. Hence, PU #15 in the SMT-disabled picture probably corresponds to PU #30 in the SMT-enabled picture.

This same "PUs have disappeared" effect can be seen on other platforms – even platforms / OSs that provide much more information than the above PPC64 system. This is an unfortunate side-effect of how operating systems report information to hwloc.

Note that upgrading the Linux kernel on the same PPC64 system mentioned above to 2.6.34, hwloc is able to discover all the topology information. The following picture shows the entire topology layout when SMT is enabled:



Developers using the hwloc API or XML output for portable applications should therefore be extremely careful to not make any assumptions about the structure of data that is returned. For example, per the above reported PPC topology, it is not safe to assume that PUs will always be descendants of cores.

Additionally, future hardware may insert new topology elements that are not available in this version of hwloc. Long-lived applications that are meant to span multiple different hardware platforms should also be careful about making structure assumptions. For example, there may someday be an element "lower" than a PU, or perhaps a new element may exist between a core and a PU.

1.4.2 API Example

The following small C example (named "hwloc-hello.c") prints the topology of the machine and bring the process to the first logical processor of the second core of the machine.

```
/* Example hwloc API program.
 * Copyright © 2009-2010 inria. All rights reserved.
 * Copyright © 2009-2011 Université Bordeaux 1
 * Copyright © 2009-2010 Cisco Systems, Inc. All rights reserved.
 * See COPYING in top-level directory.
* hwloc-hello.c
#include <hwloc.h>
#include <errno.h>
#include <stdio.h>
#include <string.h>
static void print_children(hwloc_topology_t topology,
     hwloc_obj_t obj,
                           int depth)
   char string[128]:
   unsigned i;
    hwloc_obj_snprintf(string, sizeof(string), topology, obj, "#", 0);
   printf("%*s%s\n", 2*depth, "", string);
for (i = 0; i < obj->arity; i++) {
        print_children(topology, obj->children[i], depth + 1);
}
int main(void)
    int depth;
    unsigned i, n;
    unsigned long size;
    int levels;
    char string[128];
    int topodepth;
    hwloc_topology_t topology;
hwloc_cpuset_t cpuset;
    hwloc_obj_t obj;
    /\star Allocate and initialize topology object. \star/
    hwloc_topology_init(&topology);
    /\star ... Optionally, put detection configuration here to ignore
      some objects types, define a synthetic topology, etc....
       The default is to detect all the objects of the machine that
       the caller is allowed to access. See Configure Topology
       Detection. */
    /* Perform the topology detection. */
   hwloc topology load(topology);
    /\star Optionally, get some additional topology information
       in case we need the topology depth later. \star
    topodepth = hwloc_topology_get_depth(topology);
     \star Walk the topology with an array style, from level 0 (always
     \star the system level) to the lowest level (always the proc level).
     for (depth = 0; depth < topodepth; depth++) {</pre>
        printf("*** Objects at level %d\n", depth);
        for (i = 0; i < hwloc_get_nbobjs_by_depth(topology, depth);</pre>
```

```
i++) {
       hwloc_obj_snprintf(string, sizeof(string), topology,
                 hwloc_get_obj_by_depth(topology, depth, i),
"#", 0);
       printf("Index %u: %s\n", i, string);
   }
}
/********************
 * Second example:
 \star Walk the topology with a tree style.
 ********
printf("*** Printing overall tree\n");
print_children(topology, hwloc_get_root_obj(topology), 0);
/+----
* Third example:
* Print the number of sockets.
 ************************
depth = hwloc_get_type_depth(topology, HWLOC_OBJ_SOCKET);
if (depth == HWLOC_TYPE_DEPTH_UNKNOWN) {
   printf("*** The number of sockets is unknown\n");
} else {
   printf("*** %u socket(s)\n",
          hwloc_get_nbobjs_by_depth(topology, depth));
* Fourth example:
 * Compute the amount of cache that the first logical processor
* has above it.
levels = 0;
size = 0;
for (obj = hwloc_get_obj_by_type(topology, HWLOC_OBJ_PU, 0);
    obj;
obj = obj->parent)
 if (obj->type == HWLOC_OBJ_CACHE) {
   levels++;
   size += obj->attr->cache.size;
printf("*** Logical processor 0 has %d caches totaling %luKB\n", levels, size / 1024);
* Fifth example:
 * Bind to only one thread of the last core of the machine.
* First find out where cores are, or else smaller sets of CPUs if
 * the OS doesn't have the notion of a "core".
depth = hwloc_get_type_or_below_depth(topology,
  HWLOC_OBJ_CORE);
/* Get last core. */
obj = hwloc_get_obj_by_depth(topology, depth,
             hwloc_get_nbobjs_by_depth(topology, depth) - 1);
if (obj) {
   /\star Get a copy of its cpuset that we may modify. \star/
   cpuset = hwloc_bitmap_dup(obj->cpuset);
   /\star Get only one logical processor (in case the core is SMT/hyperthreaded). \star/
   hwloc_bitmap_singlify(cpuset);
   /\star And try to bind ourself there. \star/
   if (hwloc_set_cpubind(topology, cpuset, 0)) {
       char *str:
       int error = errno;
       hwloc_bitmap_asprintf(&str, obj->cpuset);
       printf("Couldn't bind to cpuset %s: %s\n", str, strerror(error));
       free(str);
   }
    /* Free our cpuset copy */
   hwloc_bitmap_free(cpuset);
/********************
* Sixth example:
* Allocate some memory on the last NUMA node, bind some existing
 * memory to the last NUMA node.
/* Get last node. */
n = hwloc_get_nbobjs_by_type(topology,
 HWLOC_OBJ_NODE);
if (n) {
```

```
void *m;
   size = 1024*1024;
   obj = hwloc_get_obj_by_type(topology,
  HWLOC\_OBJ\_NODE, n - 1);
   m = hwloc_alloc_membind_nodeset(topology, size, obj->
  nodeset,
           HWLOC_MEMBIND_DEFAULT, 0);
   hwloc_free(topology, m, size);
   m = malloc(size);
   hwloc_set_area_membind_nodeset(topology, m, size, obj->
 nodeset,
           HWLOC_MEMBIND_DEFAULT, 0);
    free(m);
/* Destroy topology object. */
hwloc_topology_destroy(topology);
return 0;
```

hwloc provides a pkg-config executable to obtain relevant compiler and linker flags. For example, it can be used thusly to compile applications that utilize the hwloc library (assuming GNU Make):

```
CFLAGS += $(pkg-config --cflags hwloc)
LDLIBS += $(pkg-config --libs hwloc)
cc hwloc-hello.c $(CFLAGS) -o hwloc-hello $(LDLIBS)
```

On a machine with 4GB of RAM and 2 processor sockets – each socket of which has two processing cores – the output from running hwloc-hello could be something like the following:

```
shell$ ./hwloc-hello
*** Objects at level 0
Index 0: Machine(3938MB)
*** Objects at level 1
Index 0: Socket#0
Index 1: Socket#1
*** Objects at level 2
Index 0: Core#0
Index 1: Core#1
Index 2: Core#3
Index 3: Core#2
*** Objects at level 3
Index 0: PU#0
Index 1: PU#1
Index 2: PU#2
Index 3: PU#3
*** Printing overall tree
Machine (3938MB)
  Socket#0
   Core#0
     PU#0
    Core#1
     PU#1
  Socket#1
    Core#3
     PII#2
    Core#2
      PU#3
*** 2 socket(s)
shell$
```

1.5 Questions and Bugs

Questions should be sent to the devel mailing list (http://www.open-mpi.org/community/lists/hwloc.-php). Bug reports should be reported in the tracker (https://svn.open-mpi.org/trac/hwloc/).

If hwloc discovers an incorrect topology for your machine, the very first thing you should check is to ensure that you have the most recent updates installed for your operating system. Indeed, most of hwloc topology discovery relies

on hardware information retrieved through the operation system (e.g., via the /sys virtual filesystem of the Linux kernel). If upgrading your OS or Linux kernel does not solve your problem, you may also want to ensure that you are running the most recent version of the BIOS for your machine.

If those things fail, contact us on the mailing list for additional help. Please attach the output of Istopo after having given the -enable-debug option to ./configure and rebuilt completely, to get debugging output. Also attach the /proc + /sys tarball generated by the installed script hwloc-gather-topology.sh when submitting problems about Linux, or send the output of kstat $\texttt{cpu_info}$ in the Solaris case, or the output of sysctl hw in the Darwin or BSD cases.

1.6 History / Credits

hwloc is the evolution and merger of the libtopology (http://runtime.bordeaux.inria.fr/libtopology/) project and the Portable Linux Processor Affinity (PLPA) (http://www.open-mpi.org/projects/plpa/) project. Because of functional and ideological overlap, these two code bases and ideas were merged and released under the name "hwloc" as an Open MPI sub-project.

libtopology was initially developed by the inria Runtime Team-Project (http://runtime.bordeaux.-inria.fr/) (headed by Raymond Namyst (http://dept-info.labri.fr/~namyst/). PLPA was initially developed by the Open MPI development team as a sub-project. Both are now deprecated in favor of hwloc, which is distributed as an Open MPI sub-project.

1.7 Further Reading

The documentation chapters include

- · Terms and Definitions
- Command-Line Tools
- · Environment Variables
- · CPU and Memory Binding Overview
- I/O Devices
- · Multi-node Topologies
- · Object Attributes
- Importing and exporting topologies from/to XML files
- · Synthetic Topologies
- · Interoperability With Other Software
- Thread Safety
- · Components and plugins
- · Embedding hwloc in Other Software
- Frequently Asked Questions


Make sure to have had a look at those too!


Chapter 2

Terms and Definitions

- **Object** Interesting kind of part of the system, such as a Core, a Cache, a Memory node, etc. The different types detected by hwloc are detailed in the hwloc obj type t enumeration.
 - They are topologically sorted by CPU set into a tree.
- **CPU set** The set of logical processors (or processing units) logically included in an object (if it makes sense). They are always expressed using physical logical processor numbers (as announced by the OS). They are implemented as the hww.numbers (as announced by the OS). They are implemented as the <a href="https://hww.numbers.com/hww.numbers.c
- **Node set** The set of NUMA memory nodes logically included in an object (if it makes sense). They are always expressed using physical node numbers (as announced by the OS). They are implemented with the <a href="https://hww.numbers.com/hw
- **Bitmap** A possibly-infinite set of bits used for describing sets of objects such as CPUs (CPU sets) or memory nodes (Node sets). They are implemented with the https://hww.nodes.node
- **Parent object** The object logically containing the current object, for example because its CPU set includes the CPU set of the current object.
- Ancestor object The parent object, or its own parent object, and so on.
- **Children object(s)** The object (or objects) contained in the current object because their CPU set is included in the CPU set of the current object.
- Arity The number of children of an object.
- **Sibling objects** Objects which have the same parent. They usually have the same type (and hence are cousins, as well), but they may not if the topology is asymmetric.
- **Sibling rank** Index to uniquely identify objects which have the same parent, and is always in the range [0, parent_arity).
- **Cousin objects** Objects of the same type (and depth) as the current object, even if they do not have the same parent.
- **Level** Set of objects of the same type and depth. All these objects are cousins.
- Depth Nesting level in the object tree, starting from the root object. If the topology is symmetric, the depth of a child is equal to the parent depth plus one, and an object depth is also equal to the number of parent/child links between the root object and the given object. If the topology is asymmetric, the difference between some parent and child depths may be larger than one when some intermediate levels (for instance caches) are missing in only some parts of the machine.
- **OS** or physical index The index that the operating system (OS) uses to identify the object. This may be completely arbitrary, non-unique, non-contiguous, not representative of logical proximity, and may depend on the BIOS configuration. That is why hwloc almost never uses them, only in the default Istopo output (P # x) and cpuset masks.

16 Terms and Definitions





It should be noted that for PU objects, the logical index – as computed linearly by hwloc – is not the same as the OS index.

See also What happens if my topology is asymmetric? for more details.

18 **Terms and Definitions**

Command-Line Tools

hwloc comes with an extensive C programming interface and several command line utilities. Each of them is fully documented in its own manual page; the following is a summary of the available command line tools.

3.1 Istopo and Istopo-no-graphics

Istopo (also known as hwloc-ls) displays the hierarchical topology map of the current system. The output may be graphical or textual, and can also be exported to numerous file formats such as PDF, PNG, XML, and others. Advanced graphical outputs require the "Cairo" development package (usually cairo-devel or libcairo2-dev).

Istopo and Istopo-no-graphics accept the same command-line options. However graphical outputs are only available in Istopo. Textual outputs (those that do not depend on heavy external libraries such as Cairo) are supported in both Istopo and Istopo-no-graphics.

This command can also display the processes currently bound to a part of the machine (via the -ps option).

Note that Istopo can read XML files and/or alternate chroot filesystems and display topological maps representing those systems (e.g., use Istopo to output an XML file on one system, and then use Istopo to read in that XML file and display it on a different system).

3.2 hwloc-bind

hwloc-bind binds processes to specific hardware objects through a flexible syntax. A simple example is binding an executable to specific cores (or sockets or bitmaps or ...). The hwloc-bind(1) man page provides much more detail on what is possible.

hwloc-bind can also be used to retrieve the current process' binding.

3.3 hwloc-calc

hwloc-calc is generally used to create bitmap strings to pass to hwloc-bind. Although hwloc-bind accepts many forms of object specification (i.e., bitmap strings are one of many forms that hwloc-bind understands), they can be useful, compact representations in shell scripts, for example.

hwloc-calc generates bitmap strings from given hardware objects with the ability to aggregate them, intersect them, and more. hwloc-calc generally uses the same syntax than hwloc-bind, but multiple instances may be composed to generate complex combinations.

Note that hwloc-calc can also generate lists of logical processors or NUMA nodes that are convenient to pass to some external tools such as taskset or numactl.

20 Command-Line Tools

3.4 hwloc-info

hwloc-info dumps information about the given objects. It is intended to be used with tools such as grep for filtering certain attribute lines. When no object is specified, hwloc-info prints a summary of the topology.

3.5 hwloc-distrib

hwloc-distrib generates a set of bitmap strings that are uniformly distributed across the machine for the given number of processes. These strings may be used with hwloc-bind to run processes to maximize their memory bandwidth by properly distributing them across the machine.

3.6 hwloc-ps

hwloc-ps is a tool to display the bindings of processes that are currently running on the local machine. By default, hwloc-ps only lists processes that are bound; unbound process (and Linux kernel threads) are not displayed.

3.7 hwloc-gather-topology

hwloc-gather-topology is a Linux-specific tool that saves the relevant topology files of the current machine into a tarball (and the corresponding Istopo output). These files may be used later (possibly offline) for simulating or debugging a machine without actually running on it.

3.8 hwloc-distances

hwloc-distances displays all distance matrices attached to the topology. Note that Istopo may also display distance matrices in its verbose textual output. However Istopo only prints matrices that cover the entire topology while hwloc-distances also displays matrices that ignore part of the topology.

3.9 hwloc-annotate

hwloc-annotate may add object attributes such as string information (see Custom string infos for details). It reads an input topology from a XML file and outputs the annotated topology as another XML file.

3.10 hwloc-assembler

hwloc-assembler combines several XML topology files into a single multi-node XML topology. It may then be used later as input with hwloc_topology_set_xml() or with the HWLOC_XMLFILE environment variable. See Multi-node Topologies for details.

3.11 hwloc-assembler-remote

hwloc-assembler-remote is a frontend to hwloc-assembler. It takes care of contacting the given list of remote hosts (through ssh) and retrieving their topologies as XML before assembling them with hwloc-assembler.

Environment Variables

The behavior of the hwloc library and tools may be tuned thanks to the following environment variables.

HWLOC_XMLFILE=/path/to/file.xml enforces the discovery from the given XML file as if hwloc_topology_set_xml() had been called. This file may have been generated earlier with Istopo file.xml. For convenience, this backend provides empty binding hooks which just return success. To have hwloc still actually call OS-specific hooks, HWLOC_THISSYSTEM should be set 1 in the environment too, to assert that the loaded file is really the underlying system. See also Importing and exporting topologies from/to XML files.

HWLOC XML VERBOSE=1

- HWLOC_SYNTHETIC_VERBOSE=1 enables verbose messages in the XML or synthetic topology backends. hwloc XML backends (see Importing and exporting topologies from/to XML files) can emit some error messages to the error output stream. Enabling these verbose messages within hwloc can be useful for understanding failures to parse input XML topologies. Similarly, enabling verbose messages in the synthetic topology backend can help understand why the description string is invalid. See also Synthetic Topologies.
- HWLOC_FSROOT=/path/to/linux/filesystem-root/ switches to reading the topology from the specified Linux filesystem root instead of the main file-system root, as if hwloc_topology_set_fsroot() had been called. Not using the main file-system root causes hwloc_topology_is_thissystem() to return 0. For convenience, this backend provides empty binding hooks which just return success. To have hwloc still actually call OS-specific hooks, HWLOC_THISSYSTEM should be set 1 in the environment too, to assert that the loaded file is really the underlying system.
- HWLOC_THISSYSTEM=1 enforces the return value of hwloc_topology_is_thissystem(), as if HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM was set with hwloc_topology_set_flags(). It means that it makes hwloc assume that the selected backend provides the topology for the system on which we are running, even if it is not the OS-specific backend but the XML backend for instance. This means making the binding functions actually call the OS-specific system calls and really do binding, while the XML backend would otherwise provide empty hooks just returning success. This can be used for efficiency reasons to first detect the topology once, save it to an XML file, and quickly reload it later through the XML backend, but still having binding functions actually do bind.
- **HWLOC_HIDE_ERRORS=0** enables or disables verbose reporting of errors. The hwloc library may issue warnings to the standard error stream when it detects a problem during topology discovery, for instance if the operating system (or user) gives contradictory topology information. Setting this environment variable to 1 removes the actual displaying of these error messages.
- HWLOC_GROUPING=1 enables or disables objects grouping based on distances. By default, hwloc uses distance matrices between objects (either read from the OS or given by the user) to find groups of close objects. These groups are described by adding intermediate Group objects in the topology. Setting this environment variable to 0 will disable this grouping. This variable supersedes the obsolete HWLOC_IGNORE_DISTANCES variable.

22 Environment Variables

HWLOC_GROUPING_ACCURACY=0.05 relaxes distance comparison during grouping. By default, objects may be grouped if their distances form a minimal distance graph. When setting this variable to 0.02, these distances do not have to be strictly equal anymore, they may just be equal with a 2% error. If set to try instead of a numerical value, hwloc will try to group with perfect accuracy (0, the default), then with 0.01, 0.02, 0.05 and finally 0.1.

- **HWLOC_GROUPING_VERBOSE=0** enables or disables some verbose messages during grouping. If this variable is set to 1, some debug messages will be displayed during distance-based grouping of objects even if debug was not specific at configure time. This is useful when trying to find an interesting distance grouping accuracy.
- $$\label{eq:hwloc_stype} \begin{split} \text{HWLOC}_<&\text{type}>_\text{DISTANCES}=&\text{index}, \dots: X*Y \end{split}$$
- HWLOC_<type>_DISTANCES=begin-end:X*Y*Z
- HWLOC_<type>_DISTANCES=index,...:distance,... sets a distance matrix for objects of the given type and physical indexes. The type should be given as its case-sensitive stringified value (e.g. NUMANode, Socket, Cache, Core, PU). If another distance matrix already exists for the given type, either because the user specified it or because the OS offers it, it will be replaced by the given one.

If the variable value is none, the existing distance matrix for the given type is removed. Otherwise, the variable value first consists in a list of physical indexes that may be specified as a comma-separated list (e.g. 0, 2, 4, 1, 3, 5) or as a range of consecutive indexes (0-5). It is followed by a colon and the corresponding distances:

- If X*Y is given, X groups of Y close objects are specified.
- If X*Y*Z is given, X groups of Y groups of Z close objects are specified.
- Otherwise, the comma-separated list of distances should be given. If N objects are considered, the i*N+j-th value gives the distance from the i-th object to the j-th object. These distance values must use a dot as a decimal separator.

Note that distances are ignored in multi-node topologies.

- HWLOC_PCI_<domain>_<bus>_LOCALCPUS=<cpuset> changes the locality of I/O devices behind the specified PCI hostbridge. If no I/O locality information is available or if the BIOS reports incorrect information, it is possible to move a I/O device tree (the entire set of objects behind a host bridge) near a custom set of processors. domain and bus are the PCI domain and primary bus of the corresponding host bridge.
- **HWLOC_PLUGINS_PATH=/path/to/hwloc/plugins/:...** changes the default search directory for plugins. By default, \$libdir/hwloc is used. The variable may contain several colon-separated directories.
- **HWLOC_PLUGINS_VERBOSE=1** displays verbose information about plugins. List which directories are scanned, which files are loaded, and which components are successfully loaded.
- HWLOC_COMPONENTS=list,of,components forces a list of components to enable or disable. Enable or disable the given comma-separated list of components (if they do not conflict with each other). Component names prefixed with are disabled. Once the end of the list is reached, hwloc falls back to enabling the remaining components (sorted by priority) that do not conflict with the already enabled ones, and unless explicitly disabled in the list. If stop is met, the enabling loop immediately stops, no more component is enabled. If the variable is set to an empty string, no specific component is loaded first, all components are loaded in priority order, this is strictly identical to not specifying any variable. The xml component name may be followed by a XML file to load (xml=file.xml). The synthetic component may be followed by a synthetic topology description (synthetic=node: 2 pu: 3). This variable does not take precedence over the application selecting components with functions such as hwloc_topology_set_xml(). See Components and plugins for details.
- **HWLOC_COMPONENTS_VERBOSE=1** displays verbose information about components. Display messages when components are registered or enabled. This is the recommended way to list the available components with their priority (all of them are *registered* at startup).

CPU and Memory Binding Overview

Some operating systems do not systematically provide separate functions for CPU and memory binding. This means that CPU binding functions may have have effects on the memory binding policy. Likewise, changing the memory binding policy may change the CPU binding of the current thread. This is often not a problem for applications, so by default hwloc will make use of these functions when they provide better binding support.

If the application does not want the CPU binding to change when changing the memory policy, it needs to use the HWLOC_MEMBIND_NOCPUBIND flag to prevent hwloc from using OS functions which would change the CPU binding. Additionally, HWLOC_CPUBIND_NOMEMBIND can be passed to CPU binding function to prevent hwloc from using OS functions would change the memory binding policy. Of course, using these flags will reduce hwloc's overall support for binding, so their use is discouraged.

One can avoid using these flags but still closely control both memory and CPU binding by allocating memory, touching each page in the allocated memory, and then changing the CPU binding. The already-really-allocated memory will then be "locked" to physical memory and will not be migrated. Thus, even if the memory binding policy gets changed by the CPU binding order, the already-allocated memory will not change with it. When binding and allocating further memory, the CPU binding should be performed again in case the memory binding altered the previously-selected CPU binding.

Not all operating systems support the notion of a "current" memory binding policy for the current process, but such operating systems often still provide a way to allocate data on a given node set. Conversely, some operating systems support the notion of a "current" memory binding policy and do not permit allocating data on a specific node set without changing the current policy and allocate the data. To provide the most powerful coverage of these facilities, hwloc provides:

- functions that set/get the current memory binding policies (if supported): hwloc_set/get_membind_*() and hwloc_set/get_proc_membind()
- functions that allocate memory bound to specific node set without changing the current memory binding policy (if supported): hwloc_alloc_membind() and hwloc_alloc_membind_nodeset().
- helpers which, if needed, change the current memory binding policy of the process in order to obtain memory binding: hwloc_alloc_membind_policy() and hwloc_alloc_membind_policy_nodeset()

An application can thus use the two first sets of functions if it wants to manage separately the global process binding policy and directed allocation, or use the third set of functions if it does not care about the process memory binding policy.

See CPU binding and Memory binding for hwloc's API functions regarding CPU and memory binding, respectively.

CPU	and	Memory	/ Bindina	Overview
0.0	ullu	IVICITION Y	Dillaling	O V CI V I C VV

I/O Devices

hwloc usually manipulates processing units and memory but it can also discover I/O devices and report their locality as well. This is useful for placing I/O intensive applications on cores near the I/O devices they use.

6.1 Enabling and requirements

I/O discovery is disabled by default (except in Istopo) so as not to break legacy application by adding unexpected I/O objects to the topology. It can be enabled by passing flags such as HWLOC_TOPOLOGY_FLAG_IO_DEVICES to hwloc_topology_set_flags() before loading the topology.

Note that I/O discovery requires significant help from the operating system. The pciaccess library (the development package is usually libpciaccess-devel or libpciaccess-dev) is needed to detect PCI devices and bridges (libpci/pciutils may be used instead if a GPL dependency is acceptable), and the actual locality of these devices is only currently detected on Linux. Also, some operating systems require privileges for probing PCI devices, see Does hwloc require privileged access? for details.

6.2 I/O object hierarchy

When I/O discovery is enabled and supported, some additional objects (types HWLOC_OBJ_BRIDGE, HWLOC_OBJ_PCI_DEVICE and HWLOC_OBJ_OS_DEVICE) are added to the topology as a child of the object they are close to. For instance, if a I/O Hub is connected to a socket, the corresponding hwloc bridge object (and its PCI bridges and devices children) is inserted as a child of the corresponding hwloc socket object.

These new objects have neither CPU sets nor node sets (NULL pointers) because they are not directly usable by the user applications. Moreover I/O hierarchies may be highly complex (asymmetric trees of bridges). So I/O objects are placed in specific levels with custom depths. Their lists may still be traversed with regular helpers such as hwloc_get_next_obj_by_type(). However, hwloc offers some dedicated helpers such as hwloc_get_next_pcidev() and hwloc_get_next_osdev() for convenience (see Advanced I/O object traversal helpers).

An I/O hierarchy is organized as follows: A hostbridge object (<code>HWLOC_OBJ_BRIDGE</code> object with upstream type <code>Host</code> and downstream type <code>PCI</code>) is attached below a regular object (usually the entire machine or a NUMA node). There may be multiple hostbridges in the machine, attached to different places, but all I/O devices are below one of them. Each hostbridge contains one or several children, either other bridges (usually PCI to PCI) or PCI devices (<code>HWLOC_OBJ_PCI_DEVICE</code>). The number of bridges between the hostbridge and a PCI device depends on the machine and on the topology flags.

6.3 Software devices

Although each PCI device is uniquely identified by its bus ID (e.g. 0000:01:02.3), the application can hardly find out which PCI device is actually used when manipulating software handle (such as the *eth0* network interface, the *sda*

26 I/O Devices

hard drive, or the *mlx4_0* OpenFabrics HCA). Therefore hwloc tries to add software devices (HWLOC_OBJ_OS_-DEVICE, also known as OS devices) below their PCI objects.

hwloc first tries to discover the corresponding names, e.g. *eth0*, *sda* or *mlx4_0*, from the operating system. However, this ability is currently only available on Linux for some classes of devices.

hwloc then tries to discover software devices through additional I/O components using external libraries. For instance proprietary graphics drivers do not offer any OS name, but hwloc may still create one OS object per software handle when supported. For instance the opencl and cuda components may add some opencl0d0 and cuda0 OS device objects.

Here is a list of OS device objects commonly created by hwloc components when I/O discovery is enabled and supported.

- Hard disks (HWLOC_OBJ_OSDEV_BLOCK)
 - sda (Linux component)
- Network interfaces (HWLOC OBJ OSDEV NETWORK)
 - eth0, wlan0, ib0 (Linux component)
- OpenFabrics HCAs (HWLOC_OBJ_OSDEV_OPENFABRICS)
 - mlx4_0, qib0 (Linux component)
- · GPUs (HWLOC OBJ OSDEV GPU)
 - nvml0 for the first NVML device (NVML component, using the NVIDIA Management Library)
 - :0.0 for the first display (GL component, using the NV-CONTROL X extension library, NVCtrl)
- Co-Processors (HWLOC_OBJ_OSDEV_COPROC)
 - opencl0d0 for the first device of the first OpenCL platform, opencl1d3 for the fourth device of the second OpenCL platform (OpenCL component)
 - cuda0 for the first NVIDIA CUDA device (CUDA component, using the NVIDIA CUDA Library)
 - mic0 for the first Intel Xeon Phi (MIC) coprocessor (Linux component)
- DMA engine channel (HWLOC OBJ OSDEV DMA)
 - dma0chan0 (Linux component)

When none of the above strategies is supported and enabled, hwloc cannot place any OS object inside PCI objects. Note that some PCI devices may contain multiple software devices (see the example below).

See also Interoperability With Other Software for managing these devices without considering them as hwloc objects.

6.4 Consulting I/O devices and binding

I/O devices may be consulted by traversing the topology manually (with usual routines such as hwloc_get_obj_by_type()) or by using dedicated helpers (such as hwloc_get_pcidev_by_busid(), see Advanced I/O object traversal helpers).

I/O objects do not actually contain any locality information because their CPU sets and node sets are NULL. Their locality must be retrieved by walking up the object tree (through the parent link) until an non-I/O object is found (see <a href="https://hww.non-null.com/null

Command-line tools are also aware of I/O devices. Istopo displays the interesting ones by default (passing -no-io disables it).

hwloc-calc and hwloc-bind may manipulate I/O devices specified by PCI bus ID or by OS device name.

6.5 Examples 27


• pci=0000:02:03.0 is replaced by the set of CPUs that are close to the PCI device whose bus ID is given.

• os=eth0 is replaced by CPUs that are close to the I/O device whose software handle is called eth0.

This enables easy binding of I/O-intensive applications near the device they use.

6.5 Examples

The following picture shows a dual-socket dual-core host whose PCI bus is connected to the first socket and NUMA node.



Six interesting PCI devices were discovered. However hwloc found some corresponding software devices (*eth0*, *eth1*, *sda*, *mlx4_0*, *ib0*, and *ib1*) for only four of these physical devices. The other ones (*PCI 102b:0532* and *PCI 8086:3a20*) are an unused IDE controller (no disk attached) and a graphic card (no corresponding software device reported to the user by the operating system).

On the contrary, it should be noted three different software devices were found for the last PCI device (*PCI 15b3-:634a*). Indeed this OpenFabrics HCA PCI device object contains one one OpenFabrics software device (*mlx4_0*) and two virtual network interface software devices (*ib0* and *ib1*).

PCI link speed is also reported for some bridges and devices because Istopo was privileged when it discovered the topology.

Here is the corresponding textual output:

Machine (24GB)

28 I/O Devices

```
NUMANode L#0 (P#0 12GB)
  Socket L#0 + L3 L#0 (8192KB)
   L2 L\#0 (256KB) + L1 L\#0 (32KB) + Core L\#0 + PU L\#0 (P\#0)
   L2 L#1 (256KB) + L1 L#1 (32KB) + Core L#1 + PU L#1 (P#2)
  HostBridge
   PCIBridge
     PCI 14e4:163b
       Net "eth0"
     PCI 14e4:163b
       Net "eth1"
   PCIBridge
     PCI 1000:0060
       Block "sda"
   PCIBridge
     PCI 102b:0532
    PCI 8086:3a20
    PCI 15b3:634a
     Net "ib0"
     Net "ib1"
     Net "mlx4_0"
NUMANode L#1 (P#1 12GB) + Socket L#1 + L3 L#1 (8192KB)
  L2 L#2 (256KB) + L1 L#2 (32KB) + Core L#2 + PU L#2 (P#1)
  L2 L#3 (256KB) + L1 L#3 (32KB) + Core L#3 + PU L#3 (P#3)
```

Multi-node Topologies

hwloc is usually used for consulting and manipulating single machine topologies. This includes large systems as long as a single instance of the operating system manages the entire system. However it is sometimes desirable to have multiple independent hosts inside the same topology, for instance when applying algorithms to an entire cluster topology, hwloc therefore offers the ability to agregate multiple host topologies into a single global one.

7.1 Multi-node Objects Specifities

A multi-node topology contains several single-node topologies. Those are assembled by making their own root objects (usually Machine object) children of higher objects. These higher objects include at least the root of the global topology (usually a System object). Some intermediate objects may also exists, for instance to represent switches in a large fabric.

There are actually three possible types of objects that have different properties with respect to cpusets, nodesets and binding. Indeed those cpusets and nodesets were designed for execution and memory binding within a single operating system. Binding on another system or across several different systems would be meaningless.

Local objects Any object that corresponds to the local machine may be manipulated as usual. Obviously, if the multi-node topology does not contain the local machine topology, no such local object exists.

Objects from other nodes Any object that comes from inside another node is represented as usual but its cpusets and nodesets should not be used for binding since binding on another system makes no sense.

Objects above single nodes Any object above single-node topologies does not have any cpuset or nodeset pointer because binding across multiple systems makes no sense. This includes the glocal root object of a multi-node topology and possibly some intermediate objects between this global root and the local root of single-node topologies.

It is important to keep this in mind before binding using multi-node topologies. To make sure binding on an object is possible, one should first check that its cpuset or nodeset pointer is not NULL. Then, one should check whether the object is indeed local.

To find out which machine a given object corresponds to, one may look at the info attributes of the parent Machine object. The HostName info is usually available in Machine objects, it may be retrieved with the following code:

```
hwloc_obj_t machine_obj;
obj = hwloc_get_ancestor_obj_by_type(topology, HWLOC_OBJ_MACHINE, obj);
if (machine_obj)
  return hwloc_obj_get_info_by_name(machine_obj, "HostName");
else
  return NULL;
```

The hwloc assembler scripts (see below) also add AssemblerName and AssemblerIndex info attributes to the Machine objects to identify the corresponding host name and index during assembly.

7.2 Assembling topologies with command-line tools

One way to manipulate multinode topologies is to retrieve other nodes' topologies as XML files and combine them as a global XML topology. It may then be loaded with hwloc_topology_set_xml() or with the HWLOC_XMLFILE environment variable.

The hwloc-assembler and hwloc-assembler-remote utilities offer the ability to combine XML topologies or remote nodes' topologies (see Command-Line Tools).

7.3 Assembling topologies with the programming interface

The hwloc programming interface offers the ability to build multinode topologies using the *custom* interface. A new multinode topology has to be initialized with hwloc_topology_init() and then set to custom with hwloc_topology_set_custom(). Topologies and objects mat then be assembled. Later, the custom topology is finalized as usual with hwloc_topology_load().

A custom topology starts with a single root object of type System. It may be modified by inserting a new child object with hwloc_custom_insert_group_object_by_parent() or by duplicating another topology with hwloc_custom_insert_topology(). Both of these operations require to specify the parent object in the custom topology where the insertion will take place. This parent may be either the root (returned by hwloc_get_root_obj()) or an already-inserted object (returned by hwloc_custom_insert_group_object_by_parent()).

Ideally, any existing object in the custom topology could be the parent. However, special care should be taken when traversing the topology to find such an object because most links between objects (children, siblings, cousins) are not setup until hwloc topology load() is invoked.

7.4 Example of assembly with the programming interface

If the topologies of two hosts have been previously gathered in XML files host1.xml and host2.xml, the global topology may be assembled with the following code.

```
hwloc_topology_t host1, host2, global;
/* initialize global topology */
hwloc_topology_init(&global);
hwloc_topology_set_custom(global);
/\star insert host1 entire topology below the global topology root \star/
hwloc_topology_init(&host1);
hwloc_topology_load(host1);
hwloc_custom_insert_topology(global, hwloc_get_root_obj(global),
                              host1, NULL);
hwloc_topology_destroy(host1);
/\star insert host2 entire topology below the global topology root \star/
hwloc_topology_init(&host2);
hwloc_topology_load(host2);
hwloc_custom_insert_topology(global, hwloc_get_root_obj(global),
                              host2, NULL);
hwloc_topology_destroy(host2);
/* load and play with the global topology */
hwloc_topology_load(global);
```

If a intermediate object such as a switch should be inserted above one of the host topologies:

```
/* insert host2 entire topology below the switch */
hwloc_topology_init(&host2);
hwloc_topology_load(host2);
hwloc_custom_insert_topology(global, switch, host2, NULL);
hwloc_topology_destroy(host2);

/* load and play with the global topology */
hwloc_topology_load(global);
...
```

пли	ltı_n/	\sim	Inn		
wu	111-110	Jue	IUU	ologie	-5

Object attributes

8.1 Normal attributes

hwloc objects have many attributes. The hwloc_obj structure contains a common set of attributes that are available for object types, for instance their type or logical_index.

Each object also contains an attr field that, if non NULL, points to a union hwloc_obj_attr_u of type-specific attribute structures. For instance, a Cache object obj contains cache-specific information in obj->attr->cache, such as its size and associativity. See hwloc_obj_attr_u for details.

8.2 Custom string infos

Aside from the name field of each object, hwloc annotates many objects with string attributes that are made of a key and a value. Each object contains a list of such pairs that may be consulted manually (looking at the object infos array field) or using the hwloc_obj_get_info_by_name(). The user may additionally add new key-value pairs to any object using hwloc_obj_add_info() or the hwloc-annotate program.

Here is a non-exhaustive list of attributes that may be automatically added by hwloc (with the usual corresponding object in parentheses). Note that these attributes heavily depend on the ability of the operating system to report them. Many of them will therefore be missing on some OS.

- **OSName, OSRelease, OSVersion, HostName, Architecture (Machine object)** The operating system name, release, version, the hostname and the architecture name, as reported by the Unix uname command.
- **Backend (Machine object or topology root object)** The name of the hwloc backend/component that filled the topology. If several components were combined, multiple Backend keys may exist, with different values, for instance x86, Linux and pci.
- **LinuxCgroup (Machine object)** The name the Linux control group where the calling process is placed.
- **SyntheticDescription (topology root object)** The description string that was given to hwloc to build this synthetic topology.
- **CPUModel, CPUType (Socket or Machine)** The processor model name, and a more-general processor type name when applicable (Solaris/Sparc). These attributes are usually added to Socket objects. However, when hwloc cannot detect the number of sockets but still knows their (same) model, the attribute may be added to the Machine object instead.
- PCIVendor, PCIDevice (PCI devices and bridges) The vendor and device names of the PCI device.
- CoProcType (Co-Processor OS devices) The type of co-processor, for instance "MIC", "CUDA" or "OpenC-L".
- GPUVendor, GPUModel (GPU or Co-Processor OS devices) The vendor and model names of the GPU device.

34 Object attributes

- OpenCLDeviceType, OpenCLPlatformIndex,
- **OpenCLPlatformName, OpenCLPlatformDeviceIndex (OpenCL GPU OS devices)** The type of OpenCL device, the OpenCL platform index and name, and the index of the device within the platform.
- NVIDIAUUID, NVIDIASerial (NVML GPU OS devices) The UUID and Serial of NVIDIA GPUs.
- **MICFamily, MICSKU, MICSerialNumber, MICActiveCores, MICMemorySize** The family, SKU (model), serial number, number of active cores, and memory size (in kB) of an Intel Xeon Phi (MIC) coprocessor.
- **DMIBoardVendor, DMIBoardName, etc. (Machine object)** DMI hardware information such as the motherboard and chassis models and vendors, the BIOS revision, etc., as reported by Linux under /sys/class/dmi/id/.
- **Address, Port (Network interface OS devices)** The MAC address and the port number of a software network interface, such as eth4 on Linux.
- NodeGUID, SysImageGUID, Port1State, Port2LID, Port2LMC, Port3GID1 (OpenFabrics OS devices) The node GUID and GUID mask, the state of a port #1 (value is 4 when active), the LID and LID mask count of port #2, and GID #1 of port #3.

Importing and exporting topologies from/to XML files

hwloc offers the ability to export topologies to XML files and reload them later. This is for instance useful for loading topologies faster (see I do not want hwloc to rediscover my enormous machine topology every time I rerun a process), manipulating other nodes' topology, or avoiding the need for privileged processes (see Does hwloc require privileged access?).

Topologies may be exported to XML files thanks to hwloc_topology_export_xml (), or to a XML memory buffer with hwloc_topology_export_xmlbuffer (). The Istopo program can also serve as a XML topology export tool.

XML topologies may then be reloaded later with hwloc_topology_set_xml() and hwloc_topology_set_xmlbuffer(). The XMLFILE environment variable also tells hwloc to load the topology from the given XML file.

Note

Loading XML topologies disables binding because the loaded topology may not correspond to the physical machine that loads it. This behavior may be reverted by asserting that loaded file really matches the underlying system with the HWLOC_THISSYSTEM environment variable or the HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM topology flag.

XML topology files are not localized. They use a dot as a decimal separator. Therefore any exported topology can be reloaded on any other machine without requiring to change the locale.

9.1 libxml2 and minimalistic XML backends

hwloc offers two backends for importing/exporting XML.

First, it can use the libxml2 library for importing/exporting XML files. It features full XML support, for instance when those files have to be manipulated by non-hwloc software (e.g. a XSLT parser). The libxml2 backend is enabled by default if libxml2 development headers are available (the relevant development package is usually libxml2-devel or libxml2-dev).

If libxml2 is not available at configure time, or if <code>-disable-libxml2</code> is passed, hwloc falls back to a custom backend. Contrary to the aforementioned full XML backend with libxml2, this minimalistic XML backend cannot be guaranteed to work with external programs. It should only be assumed to be compatible with the same hwloc release (even if using the libxml2 backend). Its advantage is however to always be available without requiring any external dependency.

If libxml2 is available but the core hwloc library should not directly depend on it, the libxml2 support may be built as a dynamicall-loaded plugin. One should pass <code>-enable-plugins</code> to enable plugin support (when supported) and build as plugins all component that support it. Or pass <code>-enable-plugins=xml_libxml</code> to only build this libxml2 support as a plugin.

9.2 XML import error management

Importing XML files can fail at least because of file access errors, invalid XML syntax or non-hwloc-valid XML contents.

Both backend cannot detect all these errors when the input XML file or buffer is selected (when hwloc_topology_set_xml() or hwloc_topology_set_xmlbuffer() is called). Some errors such non-hwloc-valid contents can only be detected later when loading the topology with hwloc_topology_load().

It is therefore strongly recommended to check the return value of both hwloc_topology_set_xml() (or hwloc_topology_set_xmlbuffer()) and hwloc_topology_load() to handle all these errors.

Synthetic topologies

hwloc may load fake or remote topologies so as to consult them without having the underlying hardware available. Aside from loading XML topologies, hwloc also enables the building of *synthetic* topologies that are described by a single string listing the arity of each levels.

For instance, Istopo may create a topology made of 2 NUMA nodes, containing a single socket each, with one cache above two single-threaded cores:

```
$ lstopo -i "node:2 sock:1 cache:1 core:2 pu:1" -
Machine (2048MB)
NUMANode L#0 (P#0 1024MB) + Socket L#0 + L2 L#0 (4096KB)
Core L#0 + PU L#0 (P#0)
Core L#1 + PU L#1 (P#1)
NUMANode L#1 (P#1 1024MB) + Socket L#1 + L2 L#1 (4096KB)
Core L#2 + PU L#2 (P#2)
Core L#3 + PU L#3 (P#3)
```

Replacing - with file.xml in this command line will export this topology to XML as usual.

10.1 Synthetic description string

Each item in the description string gives the type of the level and the number of such children under each object of the previous level. That is why the above topology contains 4 cores (2 cores times 2 nodes).

These type names must be written as machine, node, socket, core, cache, pu, misc, group. They do not need to be written case-sensitively, nor entirely (2 characters such as ma select a Machine level). Note that I/O objects are not available.

The root object does not appear in the string. A Machine object is used by default, and a System object replaces it if a Machine level is specified in the string.

Cache level depths are automatically chosen by hwloc (only a L2 first, then a L1 under it, then L3 above, then L4 etc.). Memory and cache sizes are also automatically chosen. The only way to modifying them is to export to XML and manually modify the file.

10.2 Loading a synthetic topology

Aside from Istopo, the hwloc programming interface offers the same ability by passing the synthetic description string to hwloc_topology_set_synthetic() before hwloc_topology_load().

Synthetic topologies are created by the synthetic component. This component may be enabled by force by setting the HWLOC_COMPONENTS environment variable to something such as synthetic="node:2 core:3 pu:4".

38 Synthetic topologies

Loading a synthetic topology disables binding support since the topology usually does not match the underlying hardware. Binding may be reenabled as usual by setting HWLOC_THISSYSTEM=1 in the environment or by setting the HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM topology flag.

10.3 Exporting a topology as a synthetic string

Istopo may export a topology as a synthetic string by forcing its output format. It offers a convenient way to quickly describe the contents of a machine.

```
$ lstopo --of synthetic --no-io
Socket:1 Cache:1 Cache:2 Cache:1 Cache:1 PU:2
```

The exported string may be passed back to hwloc for recreating another similar topology. The entire tree will be similar, but cache types and memory sizes may be different from the originals.

Such an export is only possible if the topology is totally symmetric, which means the $symmetric_subtree$ field of the root object is set. This usually implies that I/O objects are disabled since attaching I/O busses often cause the topology to become assymetric. Passing -no-io to Istopo is therefore often useful to make synthetic export work (as well as not passing any I/O topology flag when using hwloc_topology_set_synthetic() manually).

Interoperability With Other Software

Although hwloc offers its own portable interface, it still may have to interoperate with specific or non-portable libraries that manipulate similar kinds of objects. hwloc therefore offers several specific "helpers" to assist converting between those specific interfaces and hwloc.

Some external libraries may be specific to a particular OS; others may not always be available. The hwloc core therefore generally does not explicitly depend on these types of libraries. However, when a custom application uses or otherwise depends on such a library, it may optionally include the corresponding hwloc helper to extend the hwloc interface with dedicated helpers.

Most of these helpers use structures that are specific to these external libraries and only meaningful on the local machine. If so, the helper requires the input topology to match the current machine. Some helpers also require I/O device discovery to be supported and enabled for the current topology.

- **Linux specific features** hwloc/linux.h offers Linux-specific helpers that utilize some non-portable features of the Linux system, such as binding threads through their thread ID ("tid") or parsing kernel CPU mask files.
- **Linux libnuma** hwloc/linux-libnuma.h provides conversion helpers between hwloc CPU sets and libnuma-specific types, such as bitmasks. It helps you use libnuma memory-binding functions with hwloc CPU sets.
- **Glibc** hwloc/glibc-sched.h offers conversion routines between Glibc and hwloc CPU sets in order to use hwloc with functions such as sched_getaffinity() or pthread_attr_setaffinity_np().
- **OpenFabrics Verbs** hwloc/openfabrics-verbs.h helps interoperability with the OpenFabrics Verbs interface. For example, it can return a list of processors near an OpenFabrics device. It may also return the corresponding OS device hwloc object for further information (if I/O device discovery is enabled).
- **Myrinet Express** hwloc/myriexpress.h offers interoperability with the Myrinet Express interface. It can return the list of processors near a Myrinet board managed by the MX driver. Note that if I/O device discovery is enabled, such boards may also appear as PCI objects in the topology.
- Intel Xeon Phi (MIC) hwloc/intel-mic.h helps interoperability with Intel Xeon Phi (MIC) coprocessors by returning the list of processors near these devices. It may also return the corresponding OS device hwloc object for further information (if I/O device discovery is enabled).
- AMD OpenCL hwloc/opencl.h enables interoperability with the OpenCL interface. Only the AMD implementation currently offers locality information. It may return the list of processors near an AMD/ATI GPU given as a cl_device_id. It may also return the corresponding OS device hwloc object for further information (if I/O device discovery is enabled).
- **NVIDIA CUDA hwloc/cuda.h** and **hwloc/cudart.h** enable interoperability with NVIDIA CUDA Driver and Runtime interfaces. For instance, it may return the list of processors near NVIDIA GPUs. It may also return the corresponding OS device hwloc object for further information (if I/O device discovery is enabled).
- **NVIDIA Management Library (NVML) hwloc/nvml.h** enables interoperability with the NVIDIA NVML interface. It may return the list of processors near a NVIDIA GPU given as a nvmlDevice_t. It may also return the corresponding OS device hwloc object for further information (if I/O device discovery is enabled).

NVIDIA displays hwloc/gl.h enables interoperability with NVIDIA displays using the NV-CONTROL X extension (NVCtrl library). If I/O device discovery is enabled, it may return the OS device hwloc object that corresponds to a display given as a name such as :0.0 or given as a port/device pair (server/screen).

Taskset command-line tool The taskset command-line tool is widely used for binding processes. It manipulates CPU set strings in a format that is slightly different from hwloc's one (it does not divide the string in fixed-size subsets and separates them with commas). To ease interoperability, hwloc offers routines to convert hwloc CPU sets from/to taskset-specific string format. Most hwloc command-line tools also support the -taskset option to manipulate taskset-specific strings.

Thread Safety

Like most libraries that mainly fill data structures, hwloc is not thread safe but rather reentrant: all state is held in a hwloc_topology_t instance without mutex protection. That means, for example, that two threads can safely operate on and modify two different hwloc_topology_t instances, but they should not simultaneously invoke functions that modify the *same* instance. Similarly, one thread should not modify a hwloc_topology_t instance while another thread is reading or traversing it. However, two threads can safely read or traverse the same hwloc_topology_t instance concurrently.

When running in multiprocessor environments, be aware that proper thread synchronization and/or memory coherency protection is needed to pass hwloc data (such as hwloc_topology_t pointers) from one processor to another (e.g., a mutex, semaphore, or a memory barrier). Note that this is not a hwloc-specific requirement, but it is worth mentioning.

For reference, https://hwloc_topology_t modification operations include (but may not be limited to):

Creation and destruction hwloc_topology_load(), hwloc_topology_load(), <a href="

Also references to objects inside the topology are not valid anymore after these functions return.

Runtime topology modifications hwloc_topology_insert_misc_object_by_* (see Tinker With Topologies.) may modify the topology significantly by adding objects inside the tree, changing the topology depth, etc. hwloc_topology_restrict modifies the topology even more dramatically by removing some objects.

Although references to former objects *may* still be valid after insertion or restriction, it is strongly advised to not rely on any such guarantee and always re-consult the topology to reacquire new instances of objects.

Locating topologies hwloc_topology_ignore*, hwloc_topology_set* (see Configure Topology Detection) do not modify the topology directly, but they do modify internal structures describing the behavior of the upcoming invocation of hwloc_topology_load(). Hence, all of these functions should not be used concurrently.

42 **Thread Safety**

Components and plugins

hwloc is organized in components that are responsible for discovering objects. Depending on the topology configuration, some components will be used, some will be ignored. The usual default is to enable the native operating system component, (e.g. linux or solaris) and the pci miscellaneous component. If available, an architecture-specific component (such as x86) may also improve the topology detection.

If a XML topology is loaded, the xml discovery component will be used instead of all other components. It internally uses a specific class of components for the actual XML import/export routines (xml_libxml and xml_nolibxml) but these will not be discussed here (see libxml2 and minimalistic XML backends).

13.1 Components enabled by default

The hwloc core contains a list of components sorted by priority. Each one is enabled as long as it does not conflict with the previously enabled ones. This includes native operating system components, architecture-specific ones, and if available, I/O components such as pci.

Usually the native operating system component (when it exists, e.g. linux or aix) is enabled first. Then hwloc looks for an architecture specific component (e.g. x86). Finally these also exist a basic component (no_os) that just tries to discover the number of PUs in the system.

Each component discovers as much topology information as possible. Most of them, including most native OS components, do nothing unless the topology is still empty. Some others, such as x86 and pci, can complete and annotate what other backends still earlier.

Default priorities ensure that clever components are invoked first. Native operating system components have higher priorities, and are therefore invoked first, because they likely offer very detailed topology information. If needed, it will be later extended by architecture-specific information (e.g. from the x86 component).

If any configuration function such as hwloc_topology_set_xml() is used before loading the topology, the corresponding component is enabled first. Then, as usual, hwloc enables any other component (based on priorities) that does not conflict.

Certain components that manage a virtual topology, for instance XML topology import, synthetic topology description, or custom building, conflict with all other components. Therefore, one of them may only be loaded (e.g. with <a href="https://doi.org/10.21/by-10.2

The environment variable HWLOC_COMPONENTS_VERBOSE may be set to get verbose messages about component registration (including their priority) and enabling.

13.2 Selecting which components to use

 variable (component names must be separated by commas).

Specifying x86 in this variable will cause the x86 component to take precedence over any other component, including the native operating system component. It is therefore loaded first, before hwloc tries to load all remaining non-conflicting components. In this case, x86 would take care of discovering everything it supports, instead of only completing what the native OS information. This may be useful if the native component is buggy on some platforms.

It is possible to prevent some components from being loaded by prefixing their name with – in the list. For instance x86, -pci will load the x86 component, then let hwloc load all the usual components except pci.

It is possible to prevent all remaining components from being loaded by placing stop in the environment variable. Only the components listed before this keyword will be enabled.

Certain component names (xml and synthetic) accept an argument (e.g. xml=file.xml). These arguments behave exactly as if the corresponding string had been passed to $hwloc_topology_set_xml$ () or $hwloc_topology_set_synthetic$ ().

13.3 Loading components from plugins

Components may optionally be built as plugins so that the hwloc core library does not directly depend on their dependencies (for instance the libpci library). Plugin support may be enabled with the <code>-enable-plugins</code> configure option. All components buildable as plugins will then be built as plugins. The configure option may be given a comma-separated list of component names to specify the exact list of components to build as plugins.

Plugins are built as independent dynamic libraries that are installed in \$libdir/hwloc. All plugins found in this directory are loaded during topology_init(). A specific list of directories (colon-separated) to scan may be specified in the HWLOC_PLUGINS_PATH environment variable.

Note that loading a plugin just means that the corresponding component is registered to the hwloc core. Components are then only enabled if the topology configuration requests it, as explained in the previous sections.

Also note that plugins should carefully be enabled and used when embedding hwloc in another project, see Embedding hwloc in Other Software for details.

13.4 Adding new discovery components and plugins

The types and functions cited below are declared in the hwloc/plugins.h header. Components are supposed to only use hwloc public headers (hwloc.h and anything under the include/hwloc subdirectory) and nothing from the include/private subdirectory in the source tree.

13.4.1 Basics of discovery components

Each discovery component is defined by a $hwloc_disc_component$ structure which contains an instantiate() callback. This function is invoked when this component is actually used by a topology. It fills a new $hwloc_backend$ structure that usually contains discover() and/or $notify_new_object()$ callbacks taking care of the actual topology discovery.

Note

If two discovery components have the same name, only the highest priority one is actually made available. This offers a way for third-party plugins to override existing components.

13.4.2 Registering a new discovery component

Registering components to the hwloc core relies on a hwloc_component structure. Its data field points to the previously defined hwloc_disc_component structure while its type should be HWLOC_COMPONENT_TY-PE_DISC. This structure should be named hwloc_<name>_component.

The configure script should be modified to add <name> to its hwloc_components shell variable so that the component is actually available.

Note

The symbol name of the hwloc_component structure is independent of the name of the discovery component mentioned in the previous section.

When the component is statically built inside the hwloc library, the symbol hwloc_<name>_component is added by configure to the src/static-components.h. The core then registers all components listed in this file.

If the new component may be built as a plugin, the configure script should also define the shell variable hwloc-_<name>_component_maybeplugin=1. When the configure script actually enables the component as a plugin, it will set the variable hwloc_<name>_component to plugin. The build system may then use this variable to change the way the component is built. It should create a hwloc_<name>.so shared object. All these files are loaded in alphabetic order, and the components they contain are registered to the hwloc core.

13.5 Existing components and plugins

All components distributed within hwloc are listed below. The list of actually available components may be listed at running with the HWLOC_COMPONENTS_VERBOSE environment variable (see Environment Variables).

- **aix, darwin, freebsd, hpux, linux, netbsd, osf, solaris, windows** Each officially supported operating system has its own native component, which is statically built when supported, and which is used by default.
- **x86** The x86 architecture (either 32 or 64 bits) has its own component that may complete or replace the previously-found CPU information. It is statically built when supported.
- bgq This component is specific to IBM BlueGene/Q compute node (running CNK). It is built and enabled by default when -host=powerpc64-bgq-linux is passed to configure (see How do I build hwloc for BlueGene/Q?).
- **no_os** A basic component that just tries to detect the number of processing units in the system. It mostly serves on operating systems that are not natively supported. It is always statically built.
- **pci** PCI object discovery uses the external pciaccess library (aka libpciaccess), or optionally the pciutils library (libpci), see I/O Devices. It may be built as a plugin.
- opencl The OpenCL component creates co-processor OS device objects such as opencl0d0 (first device of the first OpenCL platform) or opencl1d3 (fourth device of the second platform). Only the AMD OpenCL implementation currently offers locality information. It may be built as a plugin.
- **cuda** This component creates co-processor OS device objects such as *cuda0* that correspond to NVIDIA GPUs used with CUDA library. **It may be built as a plugin**.
- **nvml** Probing the NVIDIA Management Library creates OS device objects such as *nvml0* that are useful for batch schedulers. It also detects the actual PCIe link bandwidth without depending on power management state and without requiring administrator privileges. **It may be built as a plugin**.
- **gl** Probing the NV-CONTROL X extension (NVCtrl library) creates OS device objects such as :0.0 corresponding to NVIDIA displays. They are useful for graphical applications that need to place computation and/or data near a rendering GPU. **It may be built as a plugin**.
- synthetic Synthetic topology support (see Synthetic Topologies) is always built statically.
- custom Custom topology support (see Multi-node Topologies) is always built statically.
- **xml** XML topology import (see Importing and exporting topologies from/to XML files) is always built statically. It internally uses one of the XML backends (see libxml2 and minimalistic XML backends).
 - xml_nolibxml is a basic and hwloc-specific XML import/export. It is always statically built.

• xml_libxml relies on the external libxml2 library for provinding a feature-complete XML import/export. It may be built as a plugin.

fake A dummy plugin that does nothing but is used for debugging plugin support.

Embedding hwloc in Other Software

It can be desirable to include hwloc in a larger software package (be sure to check out the LICENSE file) so that users don't have to separately download and install it before installing your software. This can be advantageous to ensure that your software uses a known-tested/good version of hwloc, or for use on systems that do not have hwloc pre-installed.

When used in "embedded" mode, hwloc will:

- · not install any header files
- · not build any documentation files
- · not build or install any executables or tests
- not build libhwloc.* instead, it will build libhwloc embedded.*

There are two ways to put hwloc into "embedded" mode. The first is directly from the configure command line:

```
shell$ ./configure --enable-embedded-mode ...
```

The second requires that your software project uses the GNU Autoconf / Automake / Libtool tool chain to build your software. If you do this, you can directly integrate hwloc's m4 configure macro into your configure script. You can then invoke hwloc's configuration tests and build setup by calling an m4 macro (see below).

Although hwloc dynamic shared object plugins may be used in embedded mode, the embedder project will have to manually setup libltdl in its build system so that hwloc can load its plugins at run time. Also, embedders should be aware of complications that can arise due to public and private linker namespaces (e.g., if the embedder project is loaded into a private namespace and then hwloc tries to dynamically load its plugins, such loading may fail since the hwloc plugins can't find the hwloc symbols they need). The embedder project is **strongly** advised not to use hwloc's dynamically loading plugins / libltdl capability.

14.1 Using hwloc's M4 Embedding Capabilities

Every project is different, and there are many different ways of integrating hwloc into yours. What follows is *one* example of how to do it.

If your project uses recent versions Autoconf, Automake, and Libtool to build, you can use hwloc's embedded m4 capabilities. We have tested the embedded m4 with projects that use Autoconf 2.65, Automake 1.11.1, and Libtool 2.2.6b. Slightly earlier versions of may also work but are untested. Autoconf versions prior to 2.65 are almost certain to not work.

You can either copy all the config/hwloc*m4 files from the hwloc source tree to the directory where your project's m4 files reside, or you can tell aclocal to find more m4 files in the embedded hwloc's "config" subdirectory (e.g., add "-lpath/to/embedded/hwloc/config" to your Makefile.am's ACLOCAL_AMFLAGS).

The following macros can then be used from your configure script (only HWLOC_SETUP_CORE *must* be invoked if using the m4 macros):

• HWLOC_SETUP_CORE(config-dir-prefix, action-upon-success, action-upon-failure, print_banner_or_not): Invoke the hwloc configuration tests and setup the hwloc tree to build. The first argument is the prefix to use for AC_OUTPUT files – it's where the hwloc tree is located relative to \$top_srcdir. Hence, if your embedded hwloc is located in the source tree at contrib/hwloc, you should pass [contrib/hwloc] as the first argument. If HWLOC_SETUP_CORE and the rest of configure completes successfully, then "make" traversals of the hwloc tree with standard Automake targets (all, clean, install, etc.) should behave as expected. For example, it is safe to list the hwloc directory in the SUBDIRS of a higher-level Makefile.am. The last argument, if not empty, will cause the macro to display an announcement banner that it is starting the hwloc core configuration tests.

HWLOC_SETUP_CORE will set the following environment variables and AC_SUBST them: HWLOC_EMBEDDED_CFLAGS, HWLOC_EMBEDDED_CPPFLAGS, and HWLOC_EMBEDDED_LIBS. These flags are filled with the values discovered in the hwloc-specific m4 tests, and can be used in your build process as relevant. The _CFLAGS, _CPPFLAGS, and _LIBS variables are necessary to build libhwloc (or libhwloc_embedded) itself.

HWLOC_SETUP_CORE also sets HWLOC_EMBEDDED_LDADD environment variable (and AC_SUBSTs it) to contain the location of the libhwloc_embedded.la convenience Libtool archive. It can be used in your build process to link an application or other library against the embedded hwloc library.

NOTE: If the HWLOC_SET_SYMBOL_PREFIX macro is used, it must be invoked *before* HWLOC_SET-UP_CORE.

- HWLOC_BUILD_STANDALONE: HWLOC_SETUP_CORE defaults to building hwloc in an "embedded" mode (described above). If HWLOC_BUILD_STANDALONE is invoked *before* HWLOC_SETUP_CORE, the embedded definitions will not apply (e.g., libhwloc.la will be built, not libhwloc_embedded.la).
- HWLOC_SET_SYMBOL_PREFIX(foo_): Tells the hwloc to prefix all of hwloc's types and public symbols with "foo_"; meaning that function hwloc_init() becomes foo_hwloc_init(). Enum values are prefixed with an uppercase translation if the prefix supplied; HWLOC_OBJ_SYSTEM becomes FOO_HWLOC_OBJ_SYSTEM. This is recommended behavior if you are including hwloc in middleware it is possible that your software will be combined with other software that links to another copy of hwloc. If both uses of hwloc utilize different symbol prefixes, there will be no type/symbol clashes, and everything will compile, link, and run successfully. If you both embed hwloc without changing the symbol prefix and also link against an external hwloc, you may get multiple symbol definitions when linking your final library or application.
- HWLOC_SETUP_DOCS, HWLOC_SETUP_UTILS, HWLOC_SETUP_TESTS: These three macros only apply when hwloc is built in "standalone" mode (i.e., they should NOT be invoked unless HWLOC_BUILD_ST-ANDALONE has already been invoked).
- HWLOC_DO_AM_CONDITIONALS: If you embed hwloc in a larger project and build it conditionally with Automake (e.g., if HWLOC_SETUP_CORE is invoked conditionally), you must unconditionally invoke HWL-OC_DO_AM_CONDITIONALS to avoid warnings from Automake (for the cases where hwloc is not selected to be built). This macro is necessary because hwloc uses some AM_CONDITIONALs to build itself, and AM_CONDITIONALs cannot be defined conditionally. Note that it is safe (but unnecessary) to call HWLOC_ _DO_AM_CONDITIONALS even if HWLOC_SETUP_CORE is invoked unconditionally. If you are not using Automake to build hwloc, this macro is unnecessary (and will actually cause errors because it invoked AM_* macros that will be undefined).

NOTE: When using the HWLOC_SETUP_CORE m4 macro, it may be necessary to explicitly invoke AC_CANONIC-AL_TARGET (which requires config.sub and config.guess) and/or AC_USE_SYSTEM_EXTENSIONS macros early in the configure script (e.g., after AC_INIT but before AM_INIT_AUTOMAKE). See the Autoconf documentation for further information.

Also note that hwloc's top-level configure.ac script uses exactly the macros described above to build hwloc in a standalone mode (by default). You may want to examine it for one example of how these macros are used.

14.2 Example Embedding hwloc

Here's an example of integrating with a larger project named sandbox that already uses Autoconf, Automake, and Libtool to build itself:

```
# First, cd into the sandbox project source tree
shell$ cd sandbox
shell$ cp -r /somewhere/else/hwloc-<version> my-embedded-hwloc
shell$ edit Makefile.am
 1. Add "-Imy-embedded-hwloc/config" to ACLOCAL_AMFLAGS
 2. Add "my-embedded-hwloc" to SUBDIRS
 3. Add "\$ (HWLOC_EMBEDDED_LDADD)" and "\$ (HWLOC_EMBEDDED_LIBS)" to
    sandbox's executable's LDADD line. The former is the name of the
    Libtool convenience library that hwloc will generate. The latter
    is any dependent support libraries that may be needed by
    $(HWLOC_EMBEDDED_LDADD).
 4. Add "$(HWLOC\_EMBEDDED\_CFLAGS)" to AM_CFLAGS
 5. Add "$(HWLOC_EMBEDDED_CPPFLAGS)" to AM_CPPFLAGS
shell$ edit configure.ac
 1. Add "HWLOC_SET_SYMBOL_PREFIX(sandbox_hwloc_)" line
 2. Add "HWLOC_SETUP_CORE([my-embedded-hwloc], [happy=yes], [happy=no])" line
 3. Add error checking for happy=no case
shell$ edit sandbox.c
 1. Add #include <hwloc.h>
 2. Add calls to sandbox_hwloc_init() and other hwloc API functions
```

Now you can bootstrap, configure, build, and run the sandbox as normal – all calls to "sandbox_hwloc_*" will use the embedded hwloc rather than any system-provided copy of hwloc.

Frequently Asked Questions

15.1 I do not want hwloc to rediscover my enormous machine topology every time I rerun a process

Although the topology discovery is not expensive on common machines, its overhead may become significant when multiple processes repeat the discovery on large machines (for instance when starting one process per core in a parallel application). The machine topology usually does not vary much, except if some cores are stopped/restarted or if the administrator restrictions are modified. Thus rediscovering the whole topology again and again may look useless.

For this purpose, hwloc offers XML import/export features. It lets you save the discovered topology to a file (for instance with the Istopo program) and reload it later by setting the HWLOC_XMLFILE environment variable. The H-WLOC_THISSYSTEM environment variable should also be set to 1 to assert that loaded file is really the underlying system.

Loading a XML topology is usually much faster than querying multiple files or calling multiple functions of the operating system. It is also possible to manipulate such XML files with the C programming interface, and the import/export may also be directed to memory buffer (that may for instance be transmitted between applications through a socket). See also Importing and exporting topologies from/to XML files.

15.2 Why is Istopo slow?

Istopo enables most hwloc discovery flags by default so that the output topology is as precise as possible (while hwloc disables many of them by default). This includes I/O device discovery through PCI libraries as well as external libraries such as NVML. To speed up Istopo, you may disable such features with command-line options such as -no-io.

When NVIDIA GPU probing is enabled with CUDA or NVML, one should make sure that the *Persistent* mode is enabled (with nvidia-smi -pm 1) to avoid significant GPU initialization overhead.

When AMD GPU discovery is enabled with OpenCL and hwloc is used remotely over ssh, some spurious round-trips on the network may significantly increase the discovery time. Forcing the DISPLAY environment variable to the remote X server display (usually:0) instead of only setting the COMPUTE variable may avoid this.

Also remember that these components may be disabled at build-time with configure flags such as -disable-opencl, -disable-cuda or -disable-nvml, and at runtime with the environment variable HWLOC_COMPONENTS=-opencl, cuda, nvml.

If loading topologies is slow because the machine contains tons of processors, one should also consider using XML (see I do not want hwloc to rediscover my enormous machine topology every time I rerun a process).

15.3 Does hwloc require privileged access?

hwloc discovers the topology by querying the operating system. Some minor features may require privileged access to the operation system. For instance PCI link speed discovery on Linux is reserved to root, and the entire PCI discovery on FreeBSD requires access to the /dev/pci special file.

To workaround this limitation, it is recommended to export the topology as a XML file generated by the administrator (with the Istopo program) and make it available to all users (see Importing and exporting topologies from/to XML files). It will offer all discovery information to any application without requiring any privileged access anymore. Only the necessary hardware characteristics will be exported, no sensitive information will be disclosed through this XML export.

This XML-based model also has the advantage of speeding up the discovery because reading a XML topology is usually much faster than querying the operating system again.

15.4 hwloc only has a one-dimensional view of the architecture, it ignores distances

hwloc places all objects in a tree. Each level is a one-dimensional view of a set of similar objects. All children of the same object (siblings) are assumed to be equally interconnected (same distance between any of them), while the distance between children of different objects (cousins) is supposed to be larger.

Modern machines exhibit complex hardware interconnects, so this tree may miss some information about the actual physical distances between objects. The hwloc topology may therefore be annotated with distance information that may be used to build a more realistic representation (multi-dimensional) of each level. For instance, the root object may contain a distance matrix that represents the latencies between any pairs of NUMA nodes if the BIOS and/or operating system reports them.

15.5 How may I ignore symmetric multithreading, hyper-threading, ... ?

hwloc creates one PU (processing unit) object per hardware thread. If your machine supports symmetric multithreading, for instance Hyper-Threading, each Core object may contain multiple PU objects.

```
$ lstopo -
...
Core L#1
PU L#2 (P#1)
PU L#3 (P#3)
```

If you need to ignore symmetric multithreading, you should likely manipulate hwloc Core objects directly:

Whenever you want to bind a process or thread to a core, make sure you singlify its cpuset first, so that the task is actually bound to a single thread within this core (to avoid useless migrations).

```
/* bind on the second core */
hwloc_obj_t core = hwloc_get_obj_by_type(topology, HWLOC_OBJ_CORE, 1);
hwloc_cpuset_t set = hwloc_bitmap_dup(core->cpuset);
hwloc_bitmap_singlify(set);
hwloc_set_cpubind(topology, set, 0);
hwloc_bitmap_free(set);
```

With hwloc-calc or hwloc-bind command-line tools, you may specify that you only want a single-thread within each core by asking for their first PU object:

```
$ hwloc-calc core:4-7
0x0000ff00
$ hwloc-calc core:4-7.pu:0
0x00005500
```

When binding a process on the command-line, you may either specify the exact thread that you want to use, or ask hwloc-bind to singlify the cpuset before binding

```
$ hwloc-bind core:3.pu:0 -- echo "hello from first thread on core #3"
hello from first thread on core #3
...
$ hwloc-bind core:3 --single -- echo "hello from a single thread on core #3"
hello from a single thread on core #3
```

15.6 What happens if my topology is asymmetric?

hwloc supports asymmetric topologies even if most platforms are usually symmetric. For example, there may be different types of processors in a single machine, each with different numbers of cores, symmetric multithreading, or levels of caches.

To understand how hwloc manages such cases, one should first remember the meaning of levels and cousin objects. All objects of the same type are gathered as horizontal levels with a given depth. They are also connected through the cousin pointers of the hwloc_obj structure. Some types, such as Caches or Groups, are annotated with a depth or level attribute (for instance L2 cache or Group1). Moreover caches have a type attribute (for instance L1i or L1d). Such attributes are also taken in account when gathering objects as horizontal levels. To be clear: there will be one level for L1i caches, another level for L1d caches, another one for L2, etc.

If the topology is asymmetric (e.g., if a cache is missing in one of the processors), a given horizontal level will still exist if there exist any objects of that type. However, some branches of the overall tree may not have an object located in that horizontal level. Note that this specific hole within one horizontal level does not imply anything for other levels. All objects of the same type are gathered in horizontal levels even if their parents or children have different depths and types.

Moreover, it is important to understand that a same parent object may have children of different types (and therefore, different depths). These children are therefore siblings (because they have the same parent), but they are not cousins (because they do not belong to the same horizontal levels).

15.7 How do I annotate the topology with private notes?

Each hwloc object contains a userdata field that may be used by applications to store private pointers. This field is only valid during the lifetime of these container object and topology. It becomes invalid as soon the topology is destroyed, or as soon as the object disappears, for instance when restricting the topology. The userdata field is not exported/imported to/from XML by default since hwloc does not know what it contains. This behavior may be changed by specifying application-specific callbacks with hwloc_topology_set_userdata_export_callback() and hwloc_topology_set_userdata_import_callback().

Each object may also contain some *info* attributes (key name and value) that are setup by hwloc during discovery and that may be extended by the user with hwloc_obj_add_info () (see also Object Attributes). Contrary to the userdata field which is unique, multiple info attributes may exist for each object, even with the same name. These attributes are always exported to XML. However only character strings may be used as key names and values.

It is also possible to insert Misc objects with custom names anywhere in the topology (hwloc_topology_-insert_misc_object_by_cpuset()) or as a leaf of the topology (hwloc_topology_insert_misc_object_by_parent()).

15.8 Why does Valgrind complain about hwloc memory leaks?

If you are debugging your application with Valgrind, you want to avoid memory leak reports that are caused by hwloc and not by your program.

hwloc itself is often checked with Valgrind to make sure it does not leak memory. However some global variables in hwloc dependencies are never freed. For instance libz allocates its global state once at startup and never frees it so that it may be reused later. Some libxml2 global state is also never freed because hwloc does not know whether it can safely ask libxml2 to free it (the application may also be using libxml2 outside of hwloc).

These unfreed variables cause leak reports in Valgrind. hwloc installs a Valgrind *suppressions* file to hide them. You should pass the following command-line option to Valgrind to use it:

```
--suppressions=/path/to/hwloc-valgrind.supp
```

15.9 How do I handle API upgrades?

The hwloc interface is extended with every new major release. Any application using the hwloc API should be prepared to check at compile-time whether some features are available in the currently installed hwloc distribution.

To check whether the hwloc version is at least 1.5, you should use:

```
#include <hwloc.h>
#if HWLOC_API_VERSION >= 0x00010500
...
#endif
```

One important change in hwloc 1.5 is the removal of the deprecated cpuset API, which was superseded by the new bitmap API since hwloc 1.1. If your code must work with very old hwloc releases, you should use the latest bitmap API anyway. Then, use something similar to the following code to support old cpuset-only hwloc versions:

```
#include <hwloc.h>
#if HWLOC_API_VERSION < 0x00010100
#define hwloc_bitmap_alloc hwloc_cpuset_alloc
#endif</pre>
```

hwloc 0.9 did not define any $\texttt{HWLOC_API_VERSION}$ but this very old release probably does not deserve support from your application anymore.

15.10 How do I build hwloc for BlueGene/Q?

IBM BlueGene/Q machines run a standard Linux on the I/O node and a custom CNK (*Compute Node Kernel*) on the compute nodes. To run on the compute node, hwloc must be cross-compiled from the I/O node with the following configuration line:

```
./configure --host=powerpc64-bgq-linux --disable-shared --enable-static 
  \label{eq:configure}  \text{CPPFLAGS='-I/bgsys/drivers/ppcfloor-I/bgsys/drivers/ppcfloor/spi/include/kernel/cnk/'}
```

CPPFLAGS may have to be updated if your platform headers are installed in a different directory.

15.11 How to get useful topology information on NetBSD?

The NetBSD (and FreeBSD) backend uses x86-specific topology discovery (through the x86 component). This implementation requires CPU binding so as to query topology information from each individual logical processor. This means that hwloc cannot find any useful topology information unless user-level process binding is allowed by the NetBSD kernel. The security.models.extensions.user_set_cpu_affinity sysctl variable must be set to 1 to do so. Otherwise, only the number of logical processors will be detected.

Chapter 16

Module Index

16.1 Modules

Here	is a	list	ot a	II m	odules

API version
Topology context
Object sets (hwloc_cpuset_t and hwloc_nodeset_t)
Topology Object Types
Topology Objects
Create and Destroy Topologies
Configure Topology Detection
Exporting Topologies to XML
Tinker With Topologies
Get Some Topology Information
Retrieve Objects
Object/String Conversion
CPU binding
Memory binding
Building Custom Topologies
Object Type Helpers
Basic Traversal Helpers
Finding Objects Inside a CPU set
Finding a single Object covering at least CPU set
Finding a set of similar Objects covering at least a CPU set
Finding a set of similar Objects covering at least a CPU set
Cache-specific Finding Helpers
Cache-specific Finding Helpers105Advanced Traversal Helpers106Binding Helpers108
Cache-specific Finding Helpers105Advanced Traversal Helpers106Binding Helpers108
Cache-specific Finding Helpers108Advanced Traversal Helpers108Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114
Cache-specific Finding Helpers108Advanced Traversal Helpers108Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114
Cache-specific Finding Helpers105Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114
Cache-specific Finding Helpers105Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114Distances116Advanced I/O object traversal helpers118
Cache-specific Finding Helpers105Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset112Distances116Advanced I/O object traversal helpers118
Cache-specific Finding Helpers 108 Advanced Traversal Helpers 108 Binding Helpers 108 Cpuset Helpers 110 Nodeset Helpers 112 Conversion between cpuset and nodeset 114 Distances 116 Advanced I/O object traversal helpers 118 The bitmap API 120
Cache-specific Finding Helpers 108 Advanced Traversal Helpers 108 Binding Helpers 108 Cpuset Helpers 110 Nodeset Helpers 112 Conversion between cpuset and nodeset 114 Distances 116 Advanced I/O object traversal helpers 118 The bitmap API 120 Discovery components 128
Cache-specific Finding Helpers 108 Advanced Traversal Helpers 108 Binding Helpers 108 Cpuset Helpers 110 Nodeset Helpers 112 Conversion between cpuset and nodeset 114 Distances 116 Advanced I/O object traversal helpers 118 The bitmap API 120 Discovery components 128 Discovery backends 129 Generic components 131
Cache-specific Finding Helpers106Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset112Distances116Advanced I/O object traversal helpers118The bitmap API120Discovery components126Discovery backends125Generic components131Core functions to be used by components132
Cache-specific Finding Helpers106Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114Distances116Advanced I/O object traversal helpers118The bitmap API120Discovery components126Discovery backends126Generic components131Core functions to be used by components132
Cache-specific Finding Helpers106Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114Distances116Advanced I/O object traversal helpers118The bitmap API120Discovery components126Discovery backends129Generic components131Core functions to be used by components132Helpers for manipulating glibc sched affinity134
Cache-specific Finding Helpers106Advanced Traversal Helpers106Binding Helpers108Cpuset Helpers110Nodeset Helpers112Conversion between cpuset and nodeset114Distances116Advanced I/O object traversal helpers118The bitmap API120Discovery components126Discovery backends125Generic components131Core functions to be used by components132Helpers for manipulating glibc sched affinity134Linux-only helpers135

56 Module Index

CUDA Driver API Specific Functions	141
CUDA Runtime API Specific Functions	
NVIDIA Management Library Specific Functions	145
OpenGL display specific functions	146
Intel Xeon Phi (MIC) Specific Functions	147
OpenFabrics-Specific Functions	148
Myringt Express-Specific Functions	1/0

Chapter 17

Data Structure Index

17.1 Data Structures

Here are the data structures with brief descriptions:

hwloc_backend	
Discovery backend structure	151
hwloc_obj_attr_u::hwloc_bridge_attr_s	
Bridge specific Object Attribues	152
hwloc_obj_attr_u::hwloc_cache_attr_s	
Cache-specific Object Attributes	153
hwloc_component	
Generic component structure	154
hwloc_disc_component	
Discovery component structure	155
hwloc_distances_s	
Distances between objects	156
hwloc_obj_attr_u::hwloc_group_attr_s	
Group-specific Object Attributes	157
hwloc_obj	
Structure of a topology object	157
hwloc_obj_attr_u	
Object type-specific Attributes	162
hwloc_obj_info_s	
Object info	163
hwloc_obj_memory_s::hwloc_obj_memory_page_type_s	
Array of local memory page types, \mathtt{NULL} if no local memory and $\mathtt{page_types}$ is $0 \dots \dots$	163
hwloc_obj_memory_s	
Object memory	164
hwloc_obj_attr_u::hwloc_osdev_attr_s	
OS Device specific Object Attributes	165
hwloc_obj_attr_u::hwloc_pcidev_attr_s	
PCI Device specific Object Attributes	165
hwloc_topology_cpubind_support	
Flags describing actual PU binding support for this topology	166
hwloc_topology_discovery_support	
Flags describing actual discovery support for this topology	168
hwloc_topology_membind_support	
Flags describing actual memory binding support for this topology	168
hwloc_topology_support	
Set of flags describing actual support for this topology	170

58 **Data Structure Index**

Chapter 18

Module Documentation

18.1 API version

Macros

- #define HWLOC_API_VERSION 0x00010700
- #define HWLOC_COMPONENT_ABI 2

Functions

- HWLOC_DECLSPEC unsigned hwloc_get_api_version (void)
- 18.1.1 Detailed Description
- 18.1.2 Macro Definition Documentation
- 18.1.2.1 #define HWLOC_API_VERSION 0x00010700

Indicate at build time which hwloc API version is being used.

18.1.2.2 #define HWLOC_COMPONENT_ABI 2

Current component and plugin ABI version (see hwloc/plugins.h)

- 18.1.3 Function Documentation
- 18.1.3.1 HWLOC_DECLSPEC unsigned hwloc_get_api_version (void)

Indicate at runtime which hwloc API version was used at build time.

18.2 Topology context

Typedefs

• typedef struct hwloc_topology * hwloc_topology_t

18.2.1 Detailed Description

18.2.2 Typedef Documentation

18.2.2.1 typedef struct hwloc_topology* hwloc_topology_t

Topology context.

To be initialized with hwloc_topology_init() and built with hwloc_topology_load().

18.3 Object sets (hwloc_cpuset_t and hwloc_nodeset_t)

Typedefs

- typedef hwloc_bitmap_t hwloc_cpuset_t
- typedef hwloc_const_bitmap_t hwloc_const_cpuset_t
- typedef hwloc bitmap t hwloc nodeset t
- typedef hwloc_const_bitmap_t hwloc_const_nodeset_t

18.3.1 Detailed Description

Hwloc uses bitmaps to represent two distinct kinds of object sets: CPU sets (hwloc_cpuset_t) and NUMA node sets (hwloc_nodeset_t). These types are both typedefs to a common back end type (hwloc_bitmap_t), and therefore all the hwloc bitmap functions are applicable to both hwloc_cpuset_t and hwloc_nodeset_t (see The bitmap API).

The rationale for having two different types is that even though the actions one wants to perform on these types are the same (e.g., enable and disable individual items in the set/mask), they're used in very different contexts: one for specifying which processors to use and one for specifying which NUMA nodes to use. Hence, the name difference is really just to reflect the intent of where the type is used.

18.3.2 Typedef Documentation

18.3.2.1 typedef hwloc_const_bitmap_t hwloc_const_cpuset_t

A non-modifiable hwloc_cpuset_t.

18.3.2.2 typedef hwloc_const_bitmap_t hwloc_const_nodeset_t

A non-modifiable hwloc nodeset t.

18.3.2.3 typedef hwloc bitmap thwloc cpuset t

A CPU set is a bitmap whose bits are set according to CPU physical OS indexes.

It may be consulted and modified with the bitmap API as any hwloc bitmap t (see hwloc/bitmap.h).

18.3.2.4 typedef hwloc bitmap t hwloc nodeset t

A node set is a bitmap whose bits are set according to NUMA memory node physical OS indexes.

It may be consulted and modified with the bitmap API as any hwloc_bitmap_t (see hwloc/bitmap.h).

When binding memory on a system without any NUMA node (when the whole memory is considered as a single memory bank), the nodeset may be either empty (no memory selected) or full (whole system memory selected).

See also Conversion between cpuset and nodeset.

18.4 Topology Object Types

Typedefs

- typedef enum hwloc_obj_cache_type_e hwloc_obj_cache_type_t
- typedef enum
 - hwloc_obj_bridge_type_e hwloc_obj_bridge_type_t
- typedef enum hwloc_obj_osdev_type_e hwloc_obj_osdev_type_t

Enumerations

- enum hwloc_obj_type_t {
 HWLOC_OBJ_SYSTEM, HWLOC_OBJ_MACHINE, HWLOC_OBJ_NODE, HWLOC_OBJ_SOCKET,
 HWLOC_OBJ_CACHE, HWLOC_OBJ_CORE, HWLOC_OBJ_PU, HWLOC_OBJ_GROUP,
 HWLOC_OBJ_MISC, HWLOC_OBJ_BRIDGE, HWLOC_OBJ_PCI_DEVICE, HWLOC_OBJ_OS_DEVICE,
 HWLOC_OBJ_TYPE_MAX }
- enum hwloc_obj_cache_type_e { HWLOC_OBJ_CACHE_UNIFIED, HWLOC_OBJ_CACHE_DATA, HWLOC_OBJ_CACHE_INSTRUCTION }
- enum hwloc_obj_bridge_type_e { HWLOC_OBJ_BRIDGE_HOST, HWLOC_OBJ_BRIDGE_PCI }
- enum hwloc_obj_osdev_type_e {
 HWLOC_OBJ_OSDEV_BLOCK, HWLOC_OBJ_OSDEV_GPU, HWLOC_OBJ_OSDEV_NETWORK, HWLOC_OBJ_OSDEV_OPENFABRICS,
 HWLOC_OBJ_OSDEV_DMA, HWLOC_OBJ_OSDEV_COPROC }
- enum hwloc compare types e { HWLOC TYPE UNORDERED }

Functions

HWLOC_DECLSPEC int hwloc_compare_types (hwloc_obj_type_t type1, hwloc_obj_type_t type2) __hwloc_attribute_const

18.4.1 Detailed Description

18.4.2 Typedef Documentation

18.4.2.1 typedef enum hwloc_obj_bridge_type_e hwloc_obj_bridge_type_t

Type of one side (upstream or downstream) of an I/O bridge.

18.4.2.2 typedef enum hwloc_obj_cache_type_e hwloc_obj_cache_type_t

Cache type.

18.4.2.3 typedef enum hwloc_obj_osdev_type_e hwloc_obj_osdev_type_t

Type of a OS device.

18.4.3 Enumeration Type Documentation

18.4.3.1 enum hwloc_compare_types_e

Enumerator

HWLOC_TYPE_UNORDERED Value returned by hwloc_compare_types when types can not be compared.

18.4.3.2 enum hwloc_obj_bridge_type_e

Type of one side (upstream or downstream) of an I/O bridge.

Enumerator

HWLOC_OBJ_BRIDGE_HOST Host-side of a bridge, only possible upstream. **HWLOC_OBJ_BRIDGE_PCI** PCI-side of a bridge.

18.4.3.3 enum hwloc obj cache type e

Cache type.

Enumerator

HWLOC_OBJ_CACHE_UNIFIED Unified cache.

HWLOC_OBJ_CACHE_DATA Data cache.

HWLOC_OBJ_CACHE_INSTRUCTION Instruction cache. Only used when the HWLOC_TOPOLOGY_FLA-G_ICACHES topology flag is set.

18.4.3.4 enum hwloc_obj_osdev_type_e

Type of a OS device.

Enumerator

HWLOC_OBJ_OSDEV_BLOCK Operating system block device. For instance "sda" on Linux.

HWLOC_OBJ_OSDEV_GPU Operating system GPU device. For instance ":0.0" for a GL display, "card0" for a Linux DRM device.

HWLOC_OBJ_OSDEV_NETWORK Operating system network device. For instance the "eth0" interface on Linux.

HWLOC_OBJ_OSDEV_OPENFABRICS Operating system openfabrics device. For instance the "mlx4_0" InfiniBand HCA device on Linux.

HWLOC_OBJ_OSDEV_DMA Operating system dma engine device. For instance the "dma0chan0" DMA channel on Linux.

HWLOC_OBJ_OSDEV_COPROC Operating system co-processor device. For instance "mic0" for a Xeon Phi (MIC) on Linux, "opencl0d0" for a OpenCL device, "cuda0" for a CUDA device.

18.4.3.5 enum hwloc obj type t

Type of topology object.

Note

Enumerator

HWLOC_OBJ_SYSTEM Whole system (may be a cluster of machines). The whole system that is accessible to hwloc. That may comprise several machines in SSI systems like Kerrighed.

HWLOC_OBJ_MACHINE Machine. The typical root object type. A set of processors and memory with cache coherency.

HWLOC_OBJ_NODE NUMA node. A set of processors around memory which the processors can directly access.

- **HWLOC_OBJ_SOCKET** Socket, physical package, or chip. In the physical meaning, i.e. that you can add or remove physically.
- HWLOC_OBJ_CACHE Cache. Can be L1i, L1d, L2, L3, ...
- HWLOC_OBJ_CORE Core. A computation unit (may be shared by several logical processors).
- HWLOC_OBJ_PU Processing Unit, or (Logical) Processor. An execution unit (may share a core with some other logical processors, e.g. in the case of an SMT core). Objects of this kind are always reported and can thus be used as fallback when others are not.
- HWLOC_OBJ_GROUP Group objects. Objects which do not fit in the above but are detected by hwloc and are useful to take into account for affinity. For instance, some operating systems expose their arbitrary processors aggregation this way. And hwloc may insert such objects to group NUMA nodes according to their distances. These objects are ignored when they do not bring any structure.
- **HWLOC_OBJ_MISC** Miscellaneous objects. Objects without particular meaning, that can e.g. be added by the application for its own use.
- **HWLOC_OBJ_BRIDGE** Bridge. Any bridge that connects the host or an I/O bus, to another I/O bus. Bridge objects have neither CPU sets nor node sets. They are not added to the topology unless I/O discovery is enabled with <a href="https://hww.neither.cpu.org/hww.neith
- **HWLOC_OBJ_PCI_DEVICE** PCI device. These objects have neither CPU sets nor node sets. They are not added to the topology unless I/O discovery is enabled with hwloc_topology_set_flags().
- **HWLOC_OBJ_OS_DEVICE** Operating system device. These objects have neither CPU sets nor node sets. They are not added to the topology unless I/O discovery is enabled with hwloc_topology_set_flags().
- HWLOC_OBJ_TYPE_MAX Sentinel value

18.4.4 Function Documentation

18.4.4.1 HWLOC_DECLSPEC int hwloc_compare_types (hwloc_obj_type_t type1, hwloc_obj_type_t type2) const

Compare the depth of two object types.

Types shouldn't be compared as they are, since newer ones may be added in the future. This function returns less than, equal to, or greater than zero respectively if type1 objects usually include type2 objects, are the same as type2 objects, or are included in type2 objects. If the types can not be compared (because neither is usually contained in the other), HWLOC_TYPE_UNORDERED is returned. Object types containing CPUs can always be compared (usually, a system contains machines which contain nodes which contain sockets which contain caches, which contain cores, which contain processors).

Note

HWLOC_OBJ_PU will always be the deepest.

This does not mean that the actual topology will respect that order: e.g. as of today cores may also contain caches, and sockets may also contain nodes. This is thus just to be seen as a fallback comparison method.

18.5 Topology Objects 65

18.5 Topology Objects

Data Structures

- struct hwloc_obj_memory_s
- struct hwloc_obj
- union hwloc_obj_attr_u
- struct hwloc_distances_s
- struct hwloc_obj_info_s

Typedefs

• typedef struct hwloc_obj * hwloc_obj_t

18.5.1 Detailed Description

18.5.2 Typedef Documentation

18.5.2.1 typedef struct hwloc_obj* hwloc_obj_t

Convenience typedef; a pointer to a struct hwloc_obj.

18.6 Create and Destroy Topologies

Functions

- HWLOC_DECLSPEC int hwloc_topology_init (hwloc_topology_t *topologyp)
- HWLOC_DECLSPEC int hwloc_topology_load (hwloc_topology_t topology)
- HWLOC_DECLSPEC void hwloc_topology_destroy (hwloc_topology_t topology)
- HWLOC_DECLSPEC void hwloc_topology_check (hwloc_topology_t topology)

18.6.1 Detailed Description

18.6.2 Function Documentation

18.6.2.1 HWLOC_DECLSPEC void hwloc_topology_check (hwloc_topology_t topology)

Run internal checks on a topology structure.

The program aborts if an inconsistency is detected in the given topology.

Parameters

topology	is the topology to be checked

Note

This routine is only useful to developers.

The input topology should have been previously loaded with hwloc_topology_load().

18.6.2.2 HWLOC_DECLSPEC void hwloc_topology_destroy (hwloc_topology_t topology)

Terminate and free a topology context.

Parameters

topology	is the topology to be freed

18.6.2.3 HWLOC_DECLSPEC int hwloc_topology_init (hwloc_topology_t * topologyp)

Allocate a topology context.

Parameters

out	topologyp	is assigned a pointer to the new allocated context.
-----	-----------	---

Returns

0 on success, -1 on error.

18.6.2.4 HWLOC_DECLSPEC int hwloc_topology_load (hwloc_topology_t topology)

Build the actual topology.

Build the actual topology once initialized with hwloc_topology_init() and tuned with Configure Topology Detection routines. No other routine may be called earlier using this topology context.

Parameters

topology	is the topology to be loaded with objects.
----------	--

Returns

0 on success, -1 on error.

Note

This function may be called only once per topology.

See Also

Configure Topology Detection

18.7 Configure Topology Detection

Data Structures

- · struct hwloc_topology_discovery_support
- · struct hwloc topology cpubind support
- · struct hwloc topology membind support
- · struct hwloc_topology_support

Enumerations

enum hwloc_topology_flags_e {
 HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM, HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM, HWLOC_TOPOLOGY_FLAG_IO_DEVICES, HWLOC_TOPOLOGY_FLAG_IO_BRIDGES,
 HWLOC_TOPOLOGY_FLAG_WHOLE_IO, HWLOC_TOPOLOGY_FLAG_ICACHES }

Functions

- HWLOC_DECLSPEC int hwloc_topology_ignore_type (hwloc_topology_t topology, hwloc_obj_type_t type)
- HWLOC_DECLSPEC int hwloc_topology_ignore_type_keep_structure (hwloc_topology_t topology, hwloc_-obj_type_t type)
- HWLOC_DECLSPEC int hwloc_topology_ignore_all_keep_structure (hwloc_topology_t topology)
- HWLOC_DECLSPEC int hwloc_topology_set_flags (hwloc_topology_t topology, unsigned long flags)
- HWLOC_DECLSPEC int hwloc_topology_set_pid (hwloc_topology_t __hwloc_restrict topology, hwloc_pid_t pid)
- HWLOC_DECLSPEC int hwloc_topology_set_fsroot (hwloc_topology_t __hwloc_restrict topology, const char
 * hwloc restrict fsroot path)
- HWLOC_DECLSPEC int hwloc_topology_set_synthetic (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict description)
- HWLOC_DECLSPEC int hwloc_topology_set_xml (hwloc_topology_t __hwloc_restrict topology, const char *__hwloc_restrict xmlpath)
- HWLOC_DECLSPEC int hwloc_topology_set_xmlbuffer (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict buffer, int size)
- HWLOC_DECLSPEC int hwloc_topology_set_custom (hwloc_topology_t topology)
- HWLOC_DECLSPEC int hwloc_topology_set_distance_matrix (hwloc_topology_t __hwloc_restrict topology, hwloc_obj_type_t type, unsigned nbobjs, unsigned *os_index, float *distances)
- HWLOC_DECLSPEC struct hwloc_topology_support * hwloc_topology_get_support (hwloc_topology_t __hwloc_restrict topology)

18.7.1 Detailed Description

These functions can optionally be called between hwloc_topology_load()) to configure how the detection should be performed, e.g. to ignore some objects types, define a synthetic topology, etc.

If none of them is called, the default is to detect all the objects of the machine that the caller is allowed to access.

This default behavior may also be modified through environment variables if the application did not modify it already. Setting HWLOC_XMLFILE in the environment enforces the discovery from a XML file as if hwloc_topology_set_xml() had been called. HWLOC_FSROOT switches to reading the topology from the specified Linux filesystem root as if hwloc_topology_set_fsroot() had been called. Finally, HWLOC_THISSYSTEM enforces the return value of hwloc_topology_is_thissystem().

18.7.2 Enumeration Type Documentation

18.7.2.1 enum hwloc_topology_flags_e

Flags to be set onto a topology context before load.

Flags should be given to hwloc_topology_set_flags(). They may also be returned by hwloc_topology_get_flags().

Enumerator

- HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM Detect the whole system, ignore reservations and offline settings. Gather all resources, even if some were disabled by the administrator. For instance, ignore Linux Cpusets and gather all processors and memory nodes, and ignore the fact that some resources may be offline.
- HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM Assume that the selected backend provides the topology for the system on which we are running. This forces hwloc_topology_is_thissystem to return 1, i.e. makes hwloc assume that the selected backend provides the topology for the system on which we are running, even if it is not the OS-specific backend but the XML backend for instance. This means making the binding functions actually call the OS-specific system calls and really do binding, while the XML backend would otherwise provide empty hooks just returning success.

Setting the environment variable HWLOC THISSYSTEM may also result in the same behavior.

This can be used for efficiency reasons to first detect the topology once, save it to an XML file, and quickly reload it later through the XML backend, but still having binding functions actually do bind.

- HWLOC_TOPOLOGY_FLAG_IO_DEVICES Detect PCI devices. By default, I/O devices are ignored. This flag enables I/O device detection using the pci backend. Only the common PCI devices (GPUs, NICs, block devices, ...) and host bridges (objects that connect the host objects to an I/O subsystem) will be added to the topology. Uncommon devices and other bridges (such as PCI-to-PCI bridges) will be ignored.
- HWLOC_TOPOLOGY_FLAG_IO_BRIDGES Detect PCI bridges. This flag should be combined with HWLO-C_TOPOLOGY_FLAG_IO_DEVICES to enable the detection of both common devices and of all useful bridges (bridges that have at least one device behind them).
- HWLOC_TOPOLOGY_FLAG_WHOLE_IO Detect the whole PCI hierarchy. This flag enables detection of all I/O devices (even the uncommon ones) and bridges (even those that have no device behind them) using the pci backend.
- **HWLOC_TOPOLOGY_FLAG_ICACHES** Detect instruction caches. This flag enables detection of Instruction caches, instead of only Data and Unified caches.

18.7.3 Function Documentation

18.7.3.1 HWLOC_DECLSPEC struct hwloc_topology_support* hwloc_topology_get_support(hwloc_topology_t __hwloc_restrict topology)

Retrieve the topology support.

18.7.3.2 HWLOC DECLSPEC int hwloc topology ignore all keep structure (hwloc topology t topology)

Ignore all objects that do not bring any structure.

Ignore all objects that do not bring any structure: Each ignored object should have a single children or be the only child of its parent. I/O objects may not be ignored, topology flags should be used to configure their discovery instead.

18.7.3.3 HWLOC_DECLSPEC int hwloc_topology_ignore_type (hwloc_topology_t topology, hwloc_obj_type_t type)

Ignore an object type.

Ignore all objects from the given type. The bottom-level type HWLOC_OBJ_PU may not be ignored. The top-level object of the hierarchy will never be ignored, even if this function succeeds. I/O objects may not be ignored, topology flags should be used to configure their discovery instead.

18.7.3.4 HWLOC_DECLSPEC int hwloc_topology_ignore_type_keep_structure (hwloc_topology_t topology, hwloc_obj_type_t type_)

Ignore an object type if it does not bring any structure.

Ignore all objects from the given type as long as they do not bring any structure: Each ignored object should have a single children or be the only child of its parent. The bottom-level type HWLOC_OBJ_PU may not be ignored. I/O objects may not be ignored, topology flags should be used to configure their discovery instead.

18.7.3.5 HWLOC DECLSPEC int hwloc topology set custom (hwloc topology t topology)

Prepare the topology for custom assembly.

The topology then contains a single root object. It must then be built by inserting other topologies with hwloc_custom_insert_topology() or single objects with hwloc_custom_insert_group_object_by_parent(). hwloc_topologyload() must be called to finalize the new topology as usual.

Note

If nothing is inserted in the topology, hwloc_topology_load() will fail with errno set to EINVAL. On success, the custom component replaces the previously enabled component (if any), but the topology is not actually modified until hwloc_topology_load().

18.7.3.6 HWLOC_DECLSPEC int hwloc_topology_set_distance_matrix (hwloc_topology_t __hwloc_restrict topology, hwloc_obj_type_t_type, unsigned nbobjs, unsigned * os_index, float * distances)

Provide a distance matrix.

Provide the matrix of distances between a set of objects of the given type. The set may or may not contain all the existing objects of this type. The objects are specified by their OS/physical index in the os_index array. The distances matrix follows the same order. The distance from object i to object j in the i*nbobjs+j.

A single latency matrix may be defined for each type. If another distance matrix already exists for the given type, either because the user specified it or because the OS offers it, it will be replaced by the given one. If nbobjs is 0, os_index is NULL and distances is NULL, the existing distance matrix for the given type is removed.

Note

Distance matrices are ignored in multi-node topologies.

18.7.3.7 HWLOC_DECLSPEC int hwloc_topology_set_flags (hwloc_topology_t topology, unsigned long flags)

Set OR'ed flags to non-yet-loaded topology.

Set a OR'ed set of hwloc topology flags e onto a topology that was not yet loaded.

If this function is called multiple times, the last invokation will erase and replace the set of flags that was previously set.

18.7.3.8 HWLOC_DECLSPEC int hwloc_topology_set_fsroot (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict fsroot_path)

Change the file-system root path when building the topology from sysfs/procfs.

On Linux system, use sysfs and procfs files as if they were mounted on the given fsroot_path instead of the main file-system root. Setting the environment variable HWLOC_FSROOT may also result in this behavior. Not using the main file-system root causes hwloc_topology_is_thissystem() to return 0.

Note that this function does not actually load topology information; it just tells hwloc where to load it from. You'll still need to invoke hwloc topology load() to actually load the topology information.

Returns

- -1 with errno set to ENOSYS on non-Linux and on Linux systems that do not support it.
- -1 with the appropriate errno if fsroot_path cannot be used.

Note

For convenience, this backend provides empty binding hooks which just return success. To have hwloc still actually call OS-specific hooks, the HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM has to be set to assert that the loaded file is really the underlying system.

On success, the Linux component replaces the previously enabled component (if any), but the topology is not actually modified until hwloc_topology_load().

18.7.3.9 HWLOC_DECLSPEC int hwloc_topology_set_pid (hwloc_topology_t __hwloc_restrict topology, hwloc_pid_t pid)

Change which pid the topology is viewed from.

On some systems, processes may have different views of the machine, for instance the set of allowed CPUs. By default, hwloc exposes the view from the current process. Calling hwloc_topology_set_pid() permits to make it expose the topology of the machine from the point of view of another process.

Note

 $\verb|hwloc_pid_t| \textbf{ is } \verb|pid_t| \textbf{ on Unix platforms, and } \verb|HANDLE| \textbf{ on native Windows platforms.} \\$

-1 is returned and errno is set to ENOSYS on platforms that do not support this feature.

18.7.3.10 HWLOC_DECLSPEC int hwloc_topology_set_synthetic (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict description)

Enable synthetic topology.

Gather topology information from the given description, a space-separated string of numbers describing the arity of each level. Each number may be prefixed with a type and a colon to enforce the type of a level. If only some level types are enforced, hwloc will try to choose the other types according to usual topologies, but it may fail and you may have to specify more level types manually. See also the synthetic.

If description was properly parsed and describes a valid topology configuration, this function returns 0. Otherwise -1 is returned and errno is set to EINVAL.

Note that this function does not actually load topology information; it just tells hwloc where to load it from. You'll still need to invoke hwloc_topology_load() to actually load the topology information.

Note

For convenience, this backend provides empty binding hooks which just return success.

On success, the synthetic component replaces the previously enabled component (if any), but the topology is not actually modified until <a href="https://doi.org/10.2016/nc.20

18.7.3.11 HWLOC_DECLSPEC int hwloc_topology_set_xml (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict xmlpath)

Enable XML-file based topology.

Gather topology information from the XML file given at xmlpath. Setting the environment variable HWLOC_XML-FILE may also result in this behavior. This file may have been generated earlier with hwloc_topology_export_xml() or Istopo file.xml.

Note that this function does not actually load topology information; it just tells hwloc where to load it from. You'll still need to invoke hwloc topology load() to actually load the topology information.

Returns

-1 with errno set to EINVAL on failure to read the XML file.

Note

See also hwloc_topology_set_userdata_import_callback() for importing application-specific userdata.

For convenience, this backend provides empty binding hooks which just return success. To have hwloc still actually call OS-specific hooks, the HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM has to be set to assert that the loaded file is really the underlying system.

On success, the XML component replaces the previously enabled component (if any), but the topology is not actually modified until hwloc_topology_load().

18.7.3.12 HWLOC_DECLSPEC int hwloc_topology_set_xmlbuffer (hwloc_topology_t __hwloc_restrict topology, const char *_hwloc_restrict buffer, int size)

Enable XML based topology using a memory buffer (instead of a file, as with hwloc_topology_set_xml()).

Gather topology information from the XML memory buffer given at buffer and of length size. This buffer may have been filled earlier with $hwloc_topology_export_xmlbuffer()$.

Note that this function does not actually load topology information; it just tells hwloc where to load it from. You'll still need to invoke hwloc topology load() to actually load the topology information.

Returns

-1 with errno set to EINVAL on failure to read the XML buffer.

Note

See also hwloc_topology_set_userdata_import_callback() for importing application-specific userdata.

For convenience, this backend provides empty binding hooks which just return success. To have hwloc still actually call OS-specific hooks, the HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM has to be set to assert that the loaded file is really the underlying system.

On success, the XML component replaces the previously enabled component (if any), but the topology is not actually modified until hwloc_topology_load().

18.8 Exporting Topologies to XML.

Functions

- HWLOC DECLSPEC int hwloc topology export xml (hwloc topology t topology, const char *xmlpath)
- HWLOC_DECLSPEC int hwloc_topology_export_xmlbuffer (hwloc_topology_t topology, char **xmlbuffer, int *buflen)
- HWLOC_DECLSPEC void hwloc_free_xmlbuffer (hwloc_topology_t topology, char *xmlbuffer)
- HWLOC_DECLSPEC void hwloc_topology_set_userdata_export_callback (hwloc_topology_t topology, void(*export_cb)(void *reserved, hwloc_topology_t topology, hwloc_obj_t obj))
- HWLOC_DECLSPEC int hwloc_export_obj_userdata (void *reserved, hwloc_topology_t topology, hwloc_obj_t obj, const char *name, const void *buffer, size_t length)
- HWLOC_DECLSPEC int hwloc_export_obj_userdata_base64 (void *reserved, hwloc_topology_t topology, hwloc_obj_t obj, const char *name, const void *buffer, size_t length)
- HWLOC_DECLSPEC void hwloc_topology_set_userdata_import_callback (hwloc_topology_t topology, void(*import_cb)(hwloc_topology_t topology, hwloc_obj_t obj, const char *name, const void *buffer, size_t length))

18.8.1 Detailed Description

18.8.2 Function Documentation

18.8.2.1 HWLOC_DECLSPEC int hwloc_export_obj_userdata (void * reserved, hwloc_topology_t topology, hwloc_obj_t obj, const char * name, const void * buffer, size_t length)

Export some object userdata to XML.

This function may only be called from within the export() callback passed to hwloc_topology_set_userdata_export_callback(). It may be invoked one of multiple times to export some userdata to XML. The buffer content of length length is stored with optional name name.

When importing this XML file, the import() callback (if set) will be called exactly as many times as <a href="https://www.nuorentember.

reserved, topology and obj must be the first three parameters that were given to the export callback.

Only printable characters may be exported to XML string attributes. If a non-printable character is passed in name or buffer, the function returns -1 with errno set to EINVAL.

If exporting binary data, the application should first encode into printable characters only (or use <a href="https://www.ncbe.new.org.ncb.new

18.8.2.2 HWLOC_DECLSPEC int hwloc_export_obj_userdata_base64 (void * reserved, hwloc_topology_t topology, hwloc obj t obj, const char * name, const void * buffer, size t length)

Encode and export some object userdata to XML.

This function is similar to hwloc_export_obj_userdata() but it encodes the input buffer into printable characters before exporting. On import, decoding is automatically performed before the data is given to the import() callback if any.

This function may only be called from within the export() callback passed to hwloc_topology_set_userdata_export_callback().

The function does not take care of portability issues if the export may be reimported on a different architecture.

18.8.2.3 HWLOC_DECLSPEC void hwloc_free_xmlbuffer (hwloc_topology_t topology, char * xmlbuffer)

Free a buffer allocated by hwloc topology export xmlbuffer()

18.8.2.4 HWLOC_DECLSPEC int hwloc_topology_export_xml (hwloc_topology_t topology, const char * xmlpath)

Export the topology into an XML file.

This file may be loaded later through hwloc_topology_set_xml().

Returns

-1 if a failure occured.

Note

See also hwloc_topology_set_userdata_export_callback() for exporting application-specific userdata. Only printable characters may be exported to XML string attributes. Any other character, especially any non-ASCII character, will be silently dropped.

18.8.2.5 HWLOC_DECLSPEC int hwloc_topology_export_xmlbuffer (hwloc_topology_t topology, char ** xmlbuffer, int * buflen)

Export the topology into a newly-allocated XML memory buffer.

xmlbuffer is allocated by the callee and should be freed with hwloc_free_xmlbuffer() later in the caller.

This memory buffer may be loaded later through hwloc_topology_set_xmlbuffer().

Returns

-1 if a failure occured.

Note

See also hwloc_topology_set_userdata_export_callback() for exporting application-specific userdata. Only printable characters may be exported to XML string attributes. Any other character, especially any non-ASCII character, will be silently dropped.

18.8.2.6 HWLOC_DECLSPEC void hwloc_topology_set_userdata_export_callback (hwloc_topology_t topology, void(*)(void *reserved, hwloc_topology_t topology, hwloc_obj_t obj) export_cb)

Set the application-specific callback for exporting userdata.

The object userdata pointer is not exported to XML by default because hwloc does not know what it contains.

This function lets applications set $export_cb$ to a callback function that converts this opaque userdata into an exportable string.

export_cb is invoked during XML export for each object whose userdata pointer is not NULL. The callback should use hwloc_export_obj_userdata() or hwloc_export_obj_userdata_base64() to actually export something to XML (possibly multiple times per object).

 ${\tt export_cb} \ \ \text{may be set to} \ \mathtt{NULL} \ \text{if userdata should not be exported to XML}.$

18.8.2.7 HWLOC_DECLSPEC void hwloc_topology_set_userdata_import_callback (hwloc_topology_t topology, void(*)(hwloc_topology_t topology, hwloc_obj_t obj, const char *name, const void *buffer, size_t length) import_cb)

Set the application-specific callback for importing userdata.

On XML import, userdata is ignored by default because hwloc does not know how to store it in memory.

This function lets applications set import_cb to a callback function that will get the XML-stored userdata and store it in the object as expected by the application.

import_cb is called during hwloc_topology_load() as many times as hwloc_export_obj_userdata() was called during export. The topology is not entirely setup yet. Object attributes are ready to consult, but links between objects are not.

import_cb may be NULL if userdata should be ignored during import.

Note

buffer contains length characters followed by a null byte ('\0'). This function should be called before hwloc_topology_load().

18.9 Tinker With Topologies.

Enumerations

 enum hwloc_restrict_flags_e { HWLOC_RESTRICT_FLAG_ADAPT_DISTANCES, HWLOC_RESTRICT_F-LAG_ADAPT_MISC, HWLOC_RESTRICT_FLAG_ADAPT_IO }

Functions

- HWLOC_DECLSPEC hwloc_obj_t hwloc_topology_insert_misc_object_by_cpuset (hwloc_topology_t topology, hwloc_const_cpuset_t cpuset, const char *name)
- HWLOC_DECLSPEC hwloc_obj_t hwloc_topology_insert_misc_object_by_parent (hwloc_topology_t topology, hwloc_obj_t parent, const char *name)
- HWLOC_DECLSPEC int hwloc_topology_restrict (hwloc_topology_t __hwloc_restrict topology, hwloc_const-_cpuset_t cpuset, unsigned long flags)

18.9.1 Detailed Description

18.9.2 Enumeration Type Documentation

18.9.2.1 enum hwloc_restrict_flags_e

Flags to be given to hwloc_topology_restrict().

Enumerator

- **HWLOC_RESTRICT_FLAG_ADAPT_DISTANCES** Adapt distance matrices according to objects being removed during restriction. If this flag is not set, distance matrices are removed.
- **HWLOC_RESTRICT_FLAG_ADAPT_MISC** Move Misc objects to ancestors if their parents are removed during restriction. If this flag is not set, Misc objects are removed when their parents are removed.
- **HWLOC_RESTRICT_FLAG_ADAPT_IO** Move I/O objects to ancestors if their parents are removed during restriction. If this flag is not set, I/O devices and bridges are removed when their parents are removed.

18.9.3 Function Documentation

18.9.3.1 HWLOC_DECLSPEC hwloc_obj_t hwloc_topology_insert_misc_object_by_cpuset (hwloc_topology_t topology, hwloc_const_cpuset_t cpuset, const char * name)

Add a MISC object to the topology.

A new MISC object will be created and inserted into the topology at the position given by bitmap <code>cpuset</code>. This offers a way to add new intermediate levels to the topology hierarchy.

cpuset and name will be copied to setup the new object attributes.

Returns

the newly-created object.

NULL if the insertion conflicts with the existing topology tree.

Note

If name contains some non-printable characters, they will be dropped when exporting to XML, see hwloc_topology_export_xml().

18.9.3.2 HWLOC_DECLSPEC hwloc_obj_t hwloc_topology_insert_misc_object_by_parent (hwloc_topology_t topology, hwloc_obj_t parent, const char * name)

Add a MISC object as a leaf of the topology.

A new MISC object will be created and inserted into the topology at the position given by parent. It is appended to the list of existing children, without ever adding any intermediate hierarchy level. This is useful for annotating the topology without actually changing the hierarchy.

name will be copied to the setup the new object attributes. However, the new leaf object will not have any cpuset.

Returns

the newly-created object

Note

If name contains some non-printable characters, they will be dropped when exporting to XML, see hwloc_topology_export_xml().

18.9.3.3 HWLOC_DECLSPEC int hwloc_topology_restrict (hwloc_topology_t __hwloc_restrict topology, hwloc_const_cpuset_t cpuset, unsigned long flags)

Restrict the topology to the given CPU set.

Topology topology is modified so as to remove all objects that are not included (or partially included) in the CPU set cpuset. All objects CPU and node sets are restricted accordingly.

flags is a OR'ed set of hwloc_restrict_flags_e.

Note

This call may not be reverted by restricting back to a larger cpuset. Once dropped during restriction, objects may not be brought back, except by loading another topology with hww.cc.topology_load().

Returns

0 on success.

- -1 with errno set to EINVAL if the input cpuset is invalid. The topology is not modified in this case.
- -1 with errno set to ENOMEM on failure to allocate internal data. The topology is reinitialized in this case. It should be either destroyed with hww.nc.topology_destroy() or configured and loaded again.

18.10 Get Some Topology Information

Enumerations

enum hwloc_get_type_depth_e {
 HWLOC_TYPE_DEPTH_UNKNOWN, HWLOC_TYPE_DEPTH_MULTIPLE, HWLOC_TYPE_DEPTH_BRIDGE, HWLOC_TYPE_DEPTH_PCI_DEVICE,
 HWLOC_TYPE_DEPTH_OS_DEVICE }

Functions

- HWLOC_DECLSPEC unsigned hwloc_topology_get_depth (hwloc_topology_t __hwloc_restrict topology) _-_hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_get_type_depth (hwloc_topology_t topology, hwloc_obj_type_t type)
- HWLOC_DECLSPEC hwloc_obj_type_t hwloc_get_depth_type (hwloc_topology_t topology, unsigned depth)
 __hwloc_attribute_pure
- HWLOC_DECLSPEC unsigned hwloc_get_nbobjs_by_depth (hwloc_topology_t topology, unsigned depth)
 _hwloc_attribute_pure
- static __hwloc_inline int hwloc_get_nbobjs_by_type (hwloc_topology_t topology, hwloc_obj_type_t type) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_topology_is_thissystem (hwloc_topology_t __hwloc_restrict topology) __hwloc_attribute_pure
- HWLOC DECLSPEC unsigned long hwloc_topology_get_flags (hwloc_topology_t topology)

18.10.1 Detailed Description

Be sure to see the figure in termsanddefs that shows a complete topology tree, including depths, child/sibling/cousin relationships, and an example of an asymmetric topology where one socket has fewer caches than its peers.

18.10.2 Enumeration Type Documentation

18.10.2.1 enum hwloc get type depth e

Enumerator

HWLOC_TYPE_DEPTH_UNKNOWN No object of given type exists in the topology.

HWLOC_TYPE_DEPTH_MULTIPLE Objects of given type exist at different depth in the topology.

HWLOC_TYPE_DEPTH_BRIDGE Virtual depth for bridge object level.

HWLOC_TYPE_DEPTH_PCI_DEVICE Virtual depth for PCI device object level.

HWLOC_TYPE_DEPTH_OS_DEVICE Virtual depth for software device object level.

18.10.3 Function Documentation

18.10.3.1 HWLOC_DECLSPEC hwloc obj type t hwloc_get_depth_type (hwloc topology t topology, unsigned depth)

Returns the type of objects at depth depth.

Returns

-1 if depth depth does not exist.

18.10.3.2 HWLOC_DECLSPEC unsigned hwloc_get_nbobjs_by_depth (hwloc_topology_t topology, unsigned depth)

Returns the width of level at depth depth.

18.10.3.3 static __hwloc_inline int hwloc_get_nbobjs_by_type (hwloc_topology_t topology, hwloc_obj_type_t type) [static]

Returns the width of level type type.

If no object for that type exists, 0 is returned. If there are several levels with objects of that type, -1 is returned.

18.10.3.4 HWLOC_DECLSPEC int hwloc_get_type_depth (hwloc_topology_t topology, hwloc_obj_type_t type)

Returns the depth of objects of type type.

If no object of this type is present on the underlying architecture, or if the OS doesn't provide this kind of information, the function returns HWLOC_TYPE_DEPTH_UNKNOWN.

If type is absent but a similar type is acceptable, see also hwloc_get_type_or_below_depth() and hwloc_get_type_or_above_depth().

If some objects of the given type exist in different levels, for instance L1 and L2 caches, or L1i and L1d caches, the function returns HWLOC_TYPE_DEPTH_MULTIPLE. See hwloc_get_cache_type_depth() in hwloc/helper.h to better handle this case.

If an I/O object type is given, the function returns a virtual value because I/O objects are stored in special levels that are not CPU-related. This virtual depth may be passed to other hwloc functions such as hwloc_get_obj_by_depth() but it should not be considered as an actual depth by the application. In particular, it should not be compared with any other object depth or with the entire topology depth.

18.10.3.5 HWLOC_DECLSPEC unsigned hwloc_topology_get_depth (hwloc_topology_t __hwloc_restrict topology)

Get the depth of the hierarchical tree of objects.

This is the depth of HWLOC OBJ PU objects plus one.

18.10.3.6 HWLOC_DECLSPEC unsigned long hwloc_topology_get_flags (hwloc_topology_t topology)

Get OR'ed flags of a topology.

Get the OR'ed set of hwloc_topology_flags_e of a topology.

Returns

the flags previously set with hwloc_topology_set_flags().

18.10.3.7 HWLOC_DECLSPEC int hwloc_topology_is_thissystem (hwloc_topology_t _hwloc_restrict topology)

Does the topology context come from this system?

Returns

1 if this topology context was built using the system running this program.

0 instead (for instance if using another file-system root, a XML topology file, or a synthetic topology).

18.11 Retrieve Objects

Functions

HWLOC_DECLSPEC hwloc_obj_t hwloc_get_obj_by_depth (hwloc_topology_t topology, unsigned depth, unsigned idx) __hwloc_attribute_pure

• static __hwloc_inline hwloc_obj_t hwloc_get_obj_by_type (hwloc_topology_t topology, hwloc_obj_type_t type, unsigned idx) __hwloc_attribute_pure

18.11.1 Detailed Description

Be sure to see the figure in termsanddefs that shows a complete topology tree, including depths, child/sibling/cousin relationships, and an example of an asymmetric topology where one socket has fewer caches than its peers.

18.11.2 Function Documentation

18.11.2.1 HWLOC_DECLSPEC hwloc_obj_t hwloc_get_obj_by_depth (hwloc_topology_t topology, unsigned depth, unsigned idx)

Returns the topology object at logical index idx from depth depth.

18.11.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_obj_by_type (hwloc_topology_t topology, hwloc_obj_type_t type, unsigned idx) [static]

Returns the topology object at logical index idx with type type.

If no object for that type exists, NULL is returned. If there are several levels with objects of that type, NULL is returned and ther caller may fallback to hwloc get obj by depth().

18.12 Object/String Conversion

Functions

- HWLOC_DECLSPEC const char * hwloc_obj_type_string (hwloc_obj_type_t type) __hwloc_attribute_const
- HWLOC_DECLSPEC hwloc_obj_type_t hwloc_obj_type_of_string (const char *string) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_obj_type_snprintf (char *__hwloc_restrict string, size_t size, hwloc_obj_t obj, int verbose)
- HWLOC_DECLSPEC int hwloc_obj_attr_snprintf (char *__hwloc_restrict string, size_t size, hwloc_obj_t obj, const char *__hwloc_restrict separator, int verbose)
- HWLOC_DECLSPEC int hwloc_obj_snprintf (char *__hwloc_restrict string, size_t size, hwloc_topology_t topology, hwloc_obj_t obj, const char *__hwloc_restrict indexprefix, int verbose)
- HWLOC_DECLSPEC int hwloc_obj_cpuset_snprintf (char *_hwloc_restrict str, size_t size, size_t nobj, const hwloc_obj_t *_hwloc_restrict objs)
- static __hwloc_inline const char * hwloc_obj_get_info_by_name (hwloc_obj_t obj, const char *name) __- hwloc_attribute_pure
- HWLOC_DECLSPEC void hwloc_obj_add_info (hwloc_obj_t obj, const char *name, const char *value)

18.12.1 Detailed Description

18.12.2 Function Documentation

18.12.2.1 HWLOC_DECLSPEC void hwloc_obj_add_info (hwloc_obj_t obj, const char * name, const char * value)

Add the given info name and value pair to the given object.

The info is appended to the existing info array even if another key with the same name already exists.

The input strings are copied before being added in the object infos.

Note

If value contains some non-printable characters, they will be dropped when exporting to XML, see hwloc_topology_export_xml().

```
18.12.2.2 HWLOC_DECLSPEC int hwloc_obj_attr_snprintf ( char *__hwloc_restrict string, size_t size, hwloc_obj_t obj, const char *__hwloc_restrict separator, int verbose )
```

Stringify the attributes of a given topology object into a human-readable form.

Attribute values are separated by separator.

Only the major attributes are printed in non-verbose mode.

If size is 0, string may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending \0).

18.12.2.3 HWLOC_DECLSPEC int hwloc_obj_cpuset_snprintf (char *_hwloc_restrict str, size_t size, size_t nobj, const hwloc_obj_t *_hwloc_restrict objs)

Stringify the cpuset containing a set of objects.

If size is 0, string may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending \0).

```
18.12.2.4 static __hwloc_inline const char * hwloc_obj_get_info_by_name ( hwloc_obj_t obj, const char * name ) [static]
```

Search the given key name in object infos and return the corresponding value.

If multiple keys match the given name, only the first one is returned.

Returns

NULL if no such key exists.

```
18.12.2.5 HWLOC_DECLSPEC int hwloc_obj_snprintf ( char *__hwloc_restrict string, size_t size, hwloc_topology_t topology, hwloc_obj_t obj, const char *__hwloc_restrict indexprefix, int verbose )
```

Stringify a given topology object into a human-readable form.

Note

This function is deprecated in favor of hwloc_obj_type_snprintf() and hwloc_obj_attr_snprintf() since it is not very flexible and only prints physical/OS indexes.

Fill string string up to size characters with the description of topology object obj in topology topology.

If verbose is set, a longer description is used. Otherwise a short description is used.

indexprefix is used to prefix the os_index attribute number of the object in the description. If NULL, the # character is used.

If size is 0, string may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending 0).

```
18.12.2.6 HWLOC_DECLSPEC hwloc_obj_type_t hwloc_obj_type_of_string ( const char * string )
```

Return an object type from the string.

Returns

-1 if unrecognized.

18.12.2.7 HWLOC_DECLSPEC int hwloc_obj_type_snprintf (char *_hwloc_restrict string, size_t size, hwloc_obj_t obj, int verbose)

Stringify the type of a given topology object into a human-readable form.

It differs from hwloc_obj_type_string() because it prints type attributes such as cache depth and type.

If size is 0, string may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending \0).

 $18.12.2.8 \quad \text{HWLOC_DECLSPEC const char} * \text{hwloc_obj_type_string (} \text{ hwloc_obj_type_t } \textit{type} \text{) const}$

Return a stringified topology object type.

18.13 CPU binding

Enumerations

enum hwloc_cpubind_flags_t { HWLOC_CPUBIND_PROCESS, HWLOC_CPUBIND_THREAD, HWLOC_C-PUBIND_STRICT, HWLOC_CPUBIND_NOMEMBIND }

Functions

- HWLOC_DECLSPEC int hwloc_set_cpubind (hwloc_topology_t topology, hwloc_const_cpuset_t set, int flags)
- · HWLOC DECLSPEC int hwloc get cpubind (hwloc topology t topology, hwloc cpuset t set, int flags)
- HWLOC_DECLSPEC int hwloc_set_proc_cpubind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_-const_cpuset_t set, int flags)
- HWLOC_DECLSPEC int hwloc_get_proc_cpubind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_-cpuset_t set, int flags)
- HWLOC_DECLSPEC int hwloc_set_thread_cpubind (hwloc_topology_t topology, hwloc_thread_t thread, hwloc const cpuset t set, int flags)
- HWLOC_DECLSPEC int hwloc_get_thread_cpubind (hwloc_topology_t topology, hwloc_thread_t thread, hwloc cpuset t set, int flags)
- HWLOC_DECLSPEC int hwloc_get_last_cpu_location (hwloc_topology_t topology, hwloc_cpuset_t set, int flags)
- HWLOC_DECLSPEC int hwloc_get_proc_last_cpu_location (hwloc_topology_t topology, hwloc_pid_t pid, hwloc cpuset t set, int flags)

18.13.1 Detailed Description

It is often useful to call hwloc_bitmap_singlify() first so that a single CPU remains in the set. This way, the process will not even migrate between different CPUs. Some operating systems also only support that kind of binding.

Note

Some operating systems do not provide all hwloc-supported mechanisms to bind processes, threads, etc. and the corresponding binding functions may fail. -1 is returned and errno is set to ENOSYS when it is not possible to bind the requested kind of object processes/threads. errno is set to EXDEV when the requested cpuset can not be enforced (e.g. some systems only allow one CPU, and some other systems only allow one NUMA node).

The most portable version that should be preferred over the others, whenever possible, is

```
hwloc_set_cpubind(topology, set, 0),
```

as it just binds the current program, assuming it is single-threaded, or

```
hwloc_set_cpubind(topology, set, HWLOC_CPUBIND_THREAD),
```

which binds the current thread of the current program (which may be multithreaded).

Note

To unbind, just call the binding function with either a full cpuset or a cpuset equal to the system cpuset. On some operating systems, CPU binding may have effects on memory binding, see HWLOC_CPUBIND_N-OMEMBIND

Running Istopo –top can be a very convenient tool to check how binding actually happened.

18.13 CPU binding 85

18.13.2 Enumeration Type Documentation

18.13.2.1 enum hwloc_cpubind_flags_t

Process/Thread binding flags.

These bit flags can be used to refine the binding policy.

The default (0) is to bind the current process, assumed to be single-threaded, in a non-strict way. This is the most portable way to bind as all operating systems usually provide it.

Note

Not all systems support all kinds of binding. See the "Detailed Description" section of CPU binding for a description of errors that can occur.

Enumerator

HWLOC_CPUBIND_PROCESS Bind all threads of the current (possibly) multithreaded process.

HWLOC_CPUBIND_THREAD Bind current thread of current process.

HWLOC_CPUBIND_STRICT Request for strict binding from the OS. By default, when the designated CP-Us are all busy while other CPUs are idle, operating systems may execute the thread/process on those other CPUs instead of the designated CPUs, to let them progress anyway. Strict binding means that the thread/process will _never_ execute on other cpus than the designated CPUs, even when those are busy with other tasks and other CPUs are idle.

Note

Depending on the operating system, strict binding may not be possible (e.g., the OS does not implement it) or not allowed (e.g., for an administrative reasons), and the function will fail in that case.

When retrieving the binding of a process, this flag checks whether all its threads actually have the same binding. If the flag is not given, the binding of each thread will be accumulated.

Note

This flag is meaningless when retrieving the binding of a thread.

HWLOC_CPUBIND_NOMEMBIND Avoid any effect on memory binding. On some operating systems, some CPU binding function would also bind the memory on the corresponding NUMA node. It is often not a problem for the application, but if it is, setting this flag will make hwloc avoid using OS functions that would also bind memory. This will however reduce the support of CPU bindings, i.e. potentially return -1 with errno set to ENOSYS in some cases.

This flag is only meaningful when used with functions that set the CPU binding. It is ignored when used with functions that get CPU binding information.

18.13.3 Function Documentation

18.13.3.1 HWLOC_DECLSPEC int hwloc_get_cpubind (hwloc_topology_t topology, hwloc_cpuset_t set, int flags)

Get current process or thread binding.

Writes into set the physical cpuset which the process or thread (according to flags) was last bound to.

18.13.3.2 HWLOC_DECLSPEC int hwloc_get_last_cpu_location (hwloc_topology_t topology, hwloc_cpuset_t set, int flags)

Get the last physical CPU where the current process or thread ran.

The operating system may move some tasks from one processor to another at any time according to their binding, so this function may return something that is already outdated.

flags can include either HWLOC_CPUBIND_PROCESS or HWLOC_CPUBIND_THREAD to specify whether the query should be for the whole process (union of all CPUs on which all threads are running), or only the current thread. If the process is single-threaded, flags can be set to zero to let hwloc use whichever method is available on the underlying OS.

18.13.3.3 HWLOC_DECLSPEC int hwloc_get_proc_cpubind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_cpuset t set, int flags)

Get the current physical binding of process pid.

Note

hwloc_pid_t is pid_t on Unix platforms, and HANDLE on native Windows platforms. HWLOC CPUBIND THREAD can not be used in flags.

As a special case on Linux, if a tid (thread ID) is supplied instead of a pid (process ID), the binding for that specific thread is returned.

18.13.3.4 HWLOC_DECLSPEC int hwloc_get_proc_last_cpu_location (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_cpuset_t set, int flags)

Get the last physical CPU where a process ran.

The operating system may move some tasks from one processor to another at any time according to their binding, so this function may return something that is already outdated.

Note

hwloc_pid_t is pid_t on Unix platforms, and HANDLE on native Windows platforms. As a special case on Linux, if a tid (thread ID) is supplied instead of a pid (process ID) and HWLOC_CPUBIND_THREAD is passed in flags, the binding for that specific thread is returned.

18.13.3.5 HWLOC_DECLSPEC int hwloc_get_thread_cpubind (hwloc_topology_t topology, hwloc_thread_t thread, hwloc_cpuset_t set, int flags)

Get the current physical binding of thread tid.

Note

18.13.3.6 HWLOC_DECLSPEC int hwloc_set_cpubind (hwloc_topology_t topology, hwloc_const_cpuset_t set, int flags)

Bind current process or thread on cpus given in physical bitmap set.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced

18.13 CPU binding 87

18.13.3.7 HWLOC_DECLSPEC int hwloc_set_proc_cpubind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_const_cpuset_t set, int flags)

Bind a process pid on cpus given in physical bitmap set.

Note

 $\label{loc_pid_t} \mbox{hwloc_pid_t is pid_t on Unix platforms, and $\tt HANDLE$ on native Windows platforms.} \\ \mbox{HWLOC_CPUBIND_THREAD can not be used in flags.}$

18.13.3.8 HWLOC_DECLSPEC int hwloc_set_thread_cpubind (hwloc_topology_t topology, hwloc_thread_t thread, hwloc_const_cpuset_t set, int flags)

Bind a thread thread on cpus given in physical bitmap set.

Note

 $\label{loc_thread_tispthread_ton Unix platforms, and HANDLE on native Windows platforms. \\ HWLOC_CPUBIND_PROCESS can not be used in flags. \\$

18.14 Memory binding

Enumerations

enum hwloc_membind_policy_t {
 HWLOC_MEMBIND_DEFAULT, HWLOC_MEMBIND_FIRSTTOUCH, HWLOC_MEMBIND_BIND, HWLOC-MEMBIND_INTERLEAVE,
 HWLOC_MEMBIND_REPLICATE, HWLOC_MEMBIND_NEXTTOUCH, HWLOC_MEMBIND_MIXED }

 enum hwloc_membind_flags_t {
 HWLOC_MEMBIND_PROCESS, HWLOC_MEMBIND_THREAD, HWLOC_MEMBIND_STRICT, HWLOC_MEMBIND_MIGRATE,
 HWLOC_MEMBIND_NOCPUBIND }

Functions

- HWLOC_DECLSPEC int hwloc_set_membind_nodeset (hwloc_topology_t topology, hwloc_const_nodeset_t nodeset, hwloc membind policy t policy, int flags)
- HWLOC_DECLSPEC int hwloc_set_membind (hwloc_topology_t topology, hwloc_const_cpuset_t cpuset, hwloc membind policy t policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_membind_nodeset (hwloc_topology_t topology, hwloc_nodeset_t node-set, hwloc_membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_membind (hwloc_topology_t topology, hwloc_cpuset_t cpuset, hwloc_-membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC int hwloc_set_proc_membind_nodeset (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)
- HWLOC_DECLSPEC int hwloc_set_proc_membind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_const_cpuset_t cpuset, hwloc_membind_policy_t policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_proc_membind_nodeset (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_nodeset_t nodeset, hwloc_membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_proc_membind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_cpuset_t cpuset, hwloc_membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC int hwloc_set_area_membind_nodeset (hwloc_topology_t topology, const void *addr, size_t len, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)
- HWLOC_DECLSPEC int hwloc_set_area_membind (hwloc_topology_t topology, const void *addr, size_t len, hwloc_const_cpuset_t cpuset, hwloc_membind_policy_t policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_area_membind_nodeset (hwloc_topology_t topology, const void *addr, size_t len, hwloc_nodeset_t nodeset, hwloc_membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC int hwloc_get_area_membind (hwloc_topology_t topology, const void *addr, size_t len, hwloc_cpuset_t cpuset, hwloc_membind_policy_t *policy, int flags)
- HWLOC_DECLSPEC void * hwloc_alloc (hwloc_topology_t topology, size_t len)
- HWLOC_DECLSPEC void * hwloc_alloc_membind_nodeset (hwloc_topology_t topology, size_t len, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags) __hwloc_attribute_malloc
- HWLOC_DECLSPEC void * hwloc_alloc_membind (hwloc_topology_t topology, size_t len, hwloc_const_-cpuset_t cpuset, hwloc_membind_policy_t policy, int flags) __hwloc_attribute_malloc
- HWLOC_DECLSPEC int hwloc_free (hwloc_topology_t topology, void *addr, size_t len)

18.14.1 Detailed Description

Memory binding can be done three ways:

- explicit memory allocation thanks to hwloc_alloc_membind and friends: the binding will have effect on the memory allocated by these functions.
- implicit memory binding through binding policy: hwloc_set_membind and friends only define the current policy of the process, which will be applied to the subsequent calls to malloc() and friends.

18.14 Memory binding 89

 migration of existing memory ranges, thanks to hwloc_set_area_membind() and friends, which move alreadyallocated data.

Note

Not all operating systems support all three ways Using a binding flag or policy that is not supported by the underlying OS will cause hwloc's binding functions to fail and return -1. errno will be set to ENOSYS when the system does support the specified action or policy (e.g., some systems only allow binding memory on a per-thread basis, whereas other systems only allow binding memory for all threads in a process). errno will be set to EXDEV when the requested cpuset can not be enforced (e.g., some systems only allow binding memory to a single NUMA node).

The most portable form that should be preferred over the others whenever possible is as follows:

This will allocate some memory hopefully bound to the specified set. To do so, hwloc will possibly have to change the current memory binding policy in order to actually get the memory bound, if the OS does not provide any other way to simply allocate bound memory without changing the policy for all allocations. That is the difference with hwloc_alloc_membind(), which will never change the current memory binding policy. Note that since HWLOC_ME-MBIND_STRICT was not specified, failures to bind will not be reported – generally, only memory allocation failures will be reported (e.g., even a plain malloc() would have failed with ENOMEM).

Each hwloc memory binding function is available in two forms: one that takes a CPU set argument and another that takes a NUMA memory node set argument (see Object sets (hwloc_cpuset_t and hwloc_nodeset_t) and The bitmap API for a discussion of CPU sets and NUMA memory node sets). The names of the latter form end with _nodeset. It is also possible to convert between CPU set and node set using hwloc_cpuset_to_nodeset() or hwloc-cpuset from nodeset().

Note

On some operating systems, memory binding affects the CPU binding; see HWLOC_MEMBIND_NOCPUBIND

18.14.2 Enumeration Type Documentation

18.14.2.1 enum hwloc membind flags t

Memory binding flags.

These flags can be used to refine the binding policy. All flags can be logically OR'ed together with the exception of HWLOC_MEMBIND_PROCESS and HWLOC_MEMBIND_THREAD; these two flags are mutually exclusive.

Note

Not all systems support all kinds of binding. See the "Detailed Description" section of Memory binding for a description of errors that can occur.

Enumerator

- **HWLOC_MEMBIND_PROCESS** Set policy for all threads of the specified (possibly multithreaded) process. This flag is mutually exclusive with HWLOC_MEMBIND_THREAD.
- **HWLOC_MEMBIND_THREAD** Set policy for a specific thread of the current process. This flag is mutually exclusive with HWLOC_MEMBIND_PROCESS.
- **HWLOC_MEMBIND_STRICT** Request strict binding from the OS. The function will fail if the binding can not be guaranteed / completely enforced.

This flag has slightly different meanings depending on which function it is used with.

HWLOC_MEMBIND_MIGRATE Migrate existing allocated memory. If the memory cannot be migrated and the HWLOC_MEMBIND_STRICT flag is passed, an error will be returned.

HWLOC_MEMBIND_NOCPUBIND Avoid any effect on CPU binding. On some operating systems, some underlying memory binding functions also bind the application to the corresponding CPU(s). Using this flag will cause hwloc to avoid using OS functions that could potentially affect CPU bindings. Note, however, that using NOCPUBIND may reduce hwloc's overall memory binding support. Specifically: some of hwloc's memory binding functions may fail with errno set to ENOSYS when used with NOCPUBIND.

18.14.2.2 enum hwloc membind policy t

Memory binding policy.

These constants can be used to choose the binding policy. Only one policy can be used at a time (i.e., the values cannot be OR'ed together).

Note

Not all systems support all kinds of binding. See the "Detailed Description" section of Memory binding for a description of errors that can occur.

Enumerator

HWLOC_MEMBIND_DEFAULT Reset the memory allocation policy to the system default.

HWLOC_MEMBIND_FIRSTTOUCH Allocate memory but do not immediately bind it to a specific locality. Instead, each page in the allocation is bound only when it is first touched. Pages are individually bound to the local NUMA node of the first thread that touches it. If there is not enough memory on the node, allocation may be done in the specified cpuset before allocating on other nodes.

HWLOC_MEMBIND_BIND Allocate memory on the specified nodes.

HWLOC_MEMBIND_INTERLEAVE Allocate memory on the given nodes in an interleaved / round-robin manner. The precise layout of the memory across multiple NUMA nodes is OS/system specific. Interleaving can be useful when threads distributed across the specified NUMA nodes will all be accessing the whole memory range concurrently, since the interleave will then balance the memory references.

HWLOC_MEMBIND_REPLICATE Replicate memory on the given nodes; reads from this memory will attempt to be serviced from the NUMA node local to the reading thread. Replicating can be useful when multiple threads from the specified NUMA nodes will be sharing the same read-only data. This policy can only be used with existing memory allocations (i.e., the hwloc_set_*membind*() functions); it cannot be used with functions that allocate new memory (i.e., the hwloc_alloc*() functions).

HWLOC_MEMBIND_NEXTTOUCH For each page bound with this policy, by next time it is touched (and next time only), it is moved from its current location to the local NUMA node of the thread where the memory reference occurred (if it needs to be moved at all).

HWLOC_MEMBIND_MIXED Returned by hwloc_get_membind*() functions when multiple threads or parts of a memory area have differing memory binding policies.

18.14.3 Function Documentation

18.14.3.1 HWLOC_DECLSPEC void* hwloc_alloc (hwloc_topology_t topology, size_t len)

Allocate some memory.

This is equivalent to malloc(), except that it tries to allocate page-aligned memory from the OS.

Note

The allocated memory should be freed with hwloc free().

18.14 Memory binding 91

18.14.3.2 HWLOC_DECLSPEC void* hwloc_alloc_membind (hwloc_topology_t topology, size_t len, hwloc_const_cpuset_t cpuset, hwloc_membind_policy_t policy, int flags)

Allocate some memory on memory nodes near the given physical cpuset cpuset.

Returns

NULL with errno set to ENOSYS if the action is not supported and HWLOC_MEMBIND_STRICT is given NULL with errno set to EXDEV if the binding cannot be enforced and HWLOC_MEMBIND_STRICT is given

Note

The allocated memory should be freed with hwloc free().

18.14.3.3 HWLOC_DECLSPEC void* hwloc_alloc_membind_nodeset (hwloc_topology_t topology, size_t len, hwloc const nodeset t nodeset, hwloc membind policy t policy, int flags)

Allocate some memory on the given physical nodeset nodeset.

Returns

NULL with errno set to ENOSYS if the action is not supported and HWLOC_MEMBIND_STRICT is given NULL with errno set to EXDEV if the binding cannot be enforced and HWLOC_MEMBIND_STRICT is given

Note

The allocated memory should be freed with hwloc free().

18.14.3.4 HWLOC_DECLSPEC int hwloc_free (hwloc_topology_t topology, void * addr, size_t len)

Free memory that was previously allocated by hwloc_alloc() or hwloc_alloc_membind().

18.14.3.5 HWLOC_DECLSPEC int hwloc_get_area_membind (hwloc_topology_t topology, const void * addr, size_t len, hwloc_cpuset_t cpuset, hwloc_membind_policy_t * policy, int flags)

Query the CPUs near the physical NUMA node(s) and binding policy of the memory identified by (addr, len).

This function has two output parameters: <code>cpuset</code> and <code>policy</code>. The values returned in these parameters depend on both the <code>flags</code> passed in and the memory binding policies and nodesets of the pages in the address range.

If HWLOC_MEMBIND_STRICT is specified, the target pages are first checked to see if they all have the same memory binding policy and nodeset. If they do not, -1 is returned and errno is set to EXDEV. If they are identical across all pages, the policy is returned in policy. cpuset is set to the union of CPUs near the NUMA node(s) in the nodeset.

If HWLOC_MEMBIND_STRICT is not specified, the union of all NUMA node(s) containing pages in the address range is calculated. cpuset is then set to the CPUs near the NUMA node(s) in this union. If all pages in the target have the same policy, it is returned in policy. Otherwise, policy is set to HWLOC_MEMBIND_MIXED.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

18.14.3.6 HWLOC_DECLSPEC int hwloc_get_area_membind_nodeset (hwloc_topology_t topology, const void * addr, size_t len, hwloc_nodeset_t nodeset, hwloc_membind_policy_t * policy, int flags_)

Query the physical NUMA node(s) and binding policy of the memory identified by (addr, len).

This function has two output parameters: nodeset and policy. The values returned in these parameters depend on both the flags passed in and the memory binding policies and nodesets of the pages in the address range.

If HWLOC_MEMBIND_STRICT is specified, the target pages are first checked to see if they all have the same memory binding policy and nodeset. If they do not, -1 is returned and errno is set to EXDEV. If they are identical across all pages, the nodeset and policy are returned in nodeset and policy, respectively.

If HWLOC_MEMBIND_STRICT is not specified, nodeset is set to the union of all NUMA node(s) containing pages in the address range. If all pages in the target have the same policy, it is returned in policy. Otherwise, policy is set to HWLOC MEMBIND MIXED.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

18.14.3.7 HWLOC_DECLSPEC int hwloc_get_membind (hwloc_topology_t topology, hwloc_cpuset_t cpuset, hwloc_membind_policy_t * policy, int flags)

Query the default memory binding policy and physical locality of the current process or thread (the locality is returned in cpuset as CPUs near the locality's actual NUMA node(s)).

This function has two output parameters: <code>cpuset</code> and <code>policy</code>. The values returned in these parameters depend on both the <code>flags</code> passed in and the current memory binding policies and nodesets in the queried target.

Passing the HWLOC_MEMBIND_PROCESS flag specifies that the query target is the current policies and nodesets for all the threads in the current process. Passing HWLOC_MEMBIND_THREAD specifies that the query target is the current policy and nodeset for only the thread invoking this function.

If neither of these flags are passed (which is the most portable method), the process is assumed to be single threaded. This allows hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

HWLOC_MEMBIND_STRICT is only meaningful when HWLOC_MEMBIND_PROCESS is also specified. In this case, hwloc will check the default memory policies and nodesets for all threads in the process. If they are not identical, -1 is returned and errno is set to EXDEV. If they are identical, the policy is returned in policy. cpuset is set to the union of CPUs near the NUMA node(s) in the nodeset.

Otherwise, if HWLOC_MEMBIND_PROCESS is specified (and HWLOC_MEMBIND_STRICT is *not* specified), the default nodeset from each thread is logically OR'ed together. cpuset is set to the union of CPUs near the NUMA node(s) in the resulting nodeset. If all threads' default policies are the same, policy is set to that policy. If they are different, policy is set to HWLOC_MEMBIND_MIXED.

In the HWLOC_MEMBIND_THREAD case (or when neither HWLOC_MEMBIND_PROCESS or HWLOC_MEMBIND_THREAD is specified), there is only one nodeset and policy. The policy is returned in policy; cpuset is set to the union of CPUs near the NUMA node(s) in the nodeset.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

18.14.3.8 HWLOC_DECLSPEC int hwloc_get_membind_nodeset (hwloc_topology_t topology, hwloc_nodeset_t nodeset, hwloc_membind_policy_t * policy, int flags)

Query the default memory binding policy and physical locality of the current process or thread.

This function has two output parameters: nodeset and policy. The values returned in these parameters depend on both the flags passed in and the current memory binding policies and nodesets in the queried target.

Passing the HWLOC_MEMBIND_PROCESS flag specifies that the query target is the current policies and nodesets for all the threads in the current process. Passing HWLOC_MEMBIND_THREAD specifies that the query target is the current policy and nodeset for only the thread invoking this function.

If neither of these flags are passed (which is the most portable method), the process is assumed to be single threaded. This allows hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

HWLOC_MEMBIND_STRICT is only meaningful when HWLOC_MEMBIND_PROCESS is also specified. In this

18.14 Memory binding 93

case, hwloc will check the default memory policies and nodesets for all threads in the process. If they are not identical, -1 is returned and errno is set to EXDEV. If they are identical, the values are returned in nodeset and policy.

Otherwise, if HWLOC_MEMBIND_PROCESS is specified (and HWLOC_MEMBIND_STRICT is *not* specified), nodeset is set to the logical OR of all threads' default nodeset. If all threads' default policies are the same, policy is set to that policy. If they are different, policy is set to HWLOC_MEMBIND_MIXED.

In the HWLOC_MEMBIND_THREAD case (or when neither HWLOC_MEMBIND_PROCESS or HWLOC_MEMBIND_THREAD is specified), there is only one nodeset and policy; they are returned in nodeset and policy, respectively.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

18.14.3.9 HWLOC_DECLSPEC int hwloc_get_proc_membind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_cpuset_t cpuset, hwloc_membind_policy_t * policy, int flags)

Query the default memory binding policy and physical locality of the specified process (the locality is returned in cpuset as CPUs near the locality's actual NUMA node(s)).

This function has two output parameters: <code>cpuset</code> and <code>policy</code>. The values returned in these parameters depend on both the <code>flags</code> passed in and the current memory binding policies and nodesets in the queried target.

Passing the HWLOC_MEMBIND_PROCESS flag specifies that the query target is the current policies and nodesets for all the threads in the specified process. If HWLOC_MEMBIND_PROCESS is not specified (which is the most portable method), the process is assumed to be single threaded. This allows hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

Note that it does not make sense to pass HWLOC_MEMBIND_THREAD to this function.

If HWLOC_MEMBIND_STRICT is specified, hwloc will check the default memory policies and nodesets for all threads in the specified process. If they are not identical, -1 is returned and errno is set to EXDEV. If they are identical, the policy is returned in policy. cpuset is set to the union of CPUs near the NUMA node(s) in the nodeset.

Otherwise, the default nodeset from each thread is logically OR'ed together. <code>cpuset</code> is set to the union of CPUs near the NUMA node(s) in the resulting nodeset. If all threads' default policies are the same, <code>policy</code> is set to that policy. If they are different, <code>policy</code> is set to HWLOC_MEMBIND_MIXED.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

Note

hwloc_pid_t is pid_t on Unix platforms, and HANDLE on native Windows platforms.

18.14.3.10 HWLOC_DECLSPEC int hwloc_get_proc_membind_nodeset (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_nodeset_t nodeset, hwloc_membind_policy_t * policy, int flags)

Query the default memory binding policy and physical locality of the specified process.

This function has two output parameters: nodeset and policy. The values returned in these parameters depend on both the flags passed in and the current memory binding policies and nodesets in the queried target.

Passing the HWLOC_MEMBIND_PROCESS flag specifies that the query target is the current policies and nodesets for all the threads in the specified process. If HWLOC_MEMBIND_PROCESS is not specified (which is the most portable method), the process is assumed to be single threaded. This allows hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

Note that it does not make sense to pass HWLOC_MEMBIND_THREAD to this function.

If HWLOC_MEMBIND_STRICT is specified, hwloc will check the default memory policies and nodesets for all threads in the specified process. If they are not identical, -1 is returned and errno is set to EXDEV. If they are identical, the values are returned in nodeset and policy.

Otherwise, nodeset is set to the logical OR of all threads' default nodeset. If all threads' default policies are the same, policy is set to that policy. If they are different, policy is set to HWLOC MEMBIND MIXED.

If any other flags are specified, -1 is returned and errno is set to EINVAL.

Note

hwloc_pid_t is pid_t on Unix platforms, and HANDLE on native Windows platforms.

18.14.3.11 HWLOC_DECLSPEC int hwloc_set_area_membind (hwloc_topology_t topology, const void * addr, size_t len, hwloc const cpuset t cpuset, hwloc membind policy t policy, int flags)

Bind the already-allocated memory identified by (addr, len) to the NUMA node(s) near physical cpuset.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced
- 18.14.3.12 HWLOC_DECLSPEC int hwloc_set_area_membind_nodeset (hwloc_topology_t topology, const void * addr, size_t len, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)

Bind the already-allocated memory identified by (addr, len) to the NUMA node(s) in physical nodeset.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced
- 18.14.3.13 HWLOC_DECLSPEC int hwloc_set_membind (hwloc_topology_t topology, hwloc_const_cpuset_t cpuset, hwloc_membind_policy_t policy, int flags)

Set the default memory binding policy of the current process or thread to prefer the NUMA node(s) near the specified physical cpuset.

If neither HWLOC_MEMBIND_PROCESS nor HWLOC_MEMBIND_THREAD is specified, the current process is assumed to be single-threaded. This is the most portable form as it permits hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced
- 18.14.3.14 HWLOC_DECLSPEC int hwloc_set_membind_nodeset (hwloc_topology_t topology, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)

Set the default memory binding policy of the current process or thread to prefer the NUMA node(s) specified by physical nodeset.

If neither HWLOC_MEMBIND_PROCESS nor HWLOC_MEMBIND_THREAD is specified, the current process is assumed to be single-threaded. This is the most portable form as it permits hwloc to use either process-based OS functions or thread-based OS functions, depending on which are available.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced

18.14 Memory binding 95

18.14.3.15 HWLOC_DECLSPEC int hwloc_set_proc_membind (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_const_cpuset_t cpuset, hwloc_membind_policy_t policy, int flags)

Set the default memory binding policy of the specified process to prefer the NUMA node(s) near the specified physical cpuset.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced

Note

 $\verb|hwloc_pid_t| \textbf{ is } \verb|pid_t| \textbf{ on Unix platforms, and } \verb|HANDLE| \textbf{ on native Windows platforms.} \\$

18.14.3.16 HWLOC_DECLSPEC int hwloc_set_proc_membind_nodeset (hwloc_topology_t topology, hwloc_pid_t pid, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)

Set the default memory binding policy of the specified process to prefer the NUMA node(s) specified by physical nodeset.

Returns

- -1 with errno set to ENOSYS if the action is not supported
- -1 with errno set to EXDEV if the binding cannot be enforced

Note

hwloc_pid_t is pid_t on Unix platforms, and HANDLE on native Windows platforms.

18.15 Building Custom Topologies

Functions

HWLOC_DECLSPEC int hwloc_custom_insert_topology (hwloc_topology_t newtopology, hwloc_obj_t new-parent, hwloc_topology_t oldtopology, hwloc_obj_t oldroot)

HWLOC_DECLSPEC hwloc_obj_t hwloc_custom_insert_group_object_by_parent (hwloc_topology_t topology, hwloc_obj_t parent, int groupdepth)

18.15.1 Detailed Description

A custom topology may be initialized by calling hwloc_topology_set_custom() after hwloc_topology_init(). It may then be modified by inserting objects or entire topologies. Once done assembling, hwloc_topology_load() should be invoked as usual to finalize the topology.

18.15.2 Function Documentation

18.15.2.1 HWLOC_DECLSPEC hwloc_obj_t hwloc_custom_insert_group_object_by_parent (hwloc_topology_t topology, hwloc_obj_t parent, int groupdepth)

Insert a new group object inside a custom topology.

An object with type HWLOC OBJ GROUP is inserted as a new child of object parent.

groupdepth is the depth attribute to be given to the new object. It may for instance be 0 for top-level groups, 1 for their children, and so on.

The custom topology <code>newtopology</code> must have been prepared with <code>hwloc_topology_set_custom()</code> and not loaded with <code>hwloc_topology_load()</code> yet.

parent may be either the root of topology or an object that was added earlier through hwloc_custom_insert_group_object_by_parent().

18.15.2.2 HWLOC_DECLSPEC int hwloc_custom_insert_topology (hwloc_topology_t newtopology, hwloc_obj_t newparent, hwloc_topology_t oldtopology, hwloc_obj_t oldroot)

Insert an existing topology inside a custom topology.

Duplicate the existing topology oldtopology inside a new custom topology newtopology as a leaf of object newparent.

If oldroot is not NULL, duplicate oldroot and all its children instead of the entire oldtopology. Passing the root object of oldtopology in oldroot is equivalent to passing NULL.

The custom topology newtopology must have been prepared with hwloc_topology_set_custom() and not loaded with hwloc_topology_load() yet.

newparent may be either the root of newtopology or an object that was added through hwloc_custom_insert_group_object_by_parent().

18.16 Object Type Helpers

Functions

- static __hwloc_inline int hwloc_get_type_or_below_depth (hwloc_topology_t topology, hwloc_obj_type_t type) hwloc attribute pure
- static __hwloc_inline int hwloc_get_type_or_above_depth (hwloc_topology_t topology, hwloc_obj_type_- t type) __hwloc_attribute_pure

18.16.1 Detailed Description

Be sure to see the figure in termsanddefs that shows a complete topology tree, including depths, child/sibling/cousin relationships, and an example of an asymmetric topology where one socket has fewer caches than its peers.

18.16.2 Function Documentation

Returns the depth of objects of type type or above.

If no object of this type is present on the underlying architecture, the function returns the depth of the first "present" object typically containing type.

If some objects of the given type exist in different levels, for instance L1 and L2 caches, the function returns HWL-OC TYPE DEPTH MULTIPLE.

Returns the depth of objects of type type or below.

If no object of this type is present on the underlying architecture, the function returns the depth of the first "present" object typically found inside type.

If some objects of the given type exist in different levels, for instance L1 and L2 caches, the function returns HWL-OC TYPE DEPTH MULTIPLE.

18.17 Basic Traversal Helpers

Functions

- static __hwloc_inline hwloc_obj_t hwloc_get_root_obj (hwloc_topology_t topology) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_ancestor_obj_by_depth (hwloc_topology_t topology __hwloc_attribute_unused, unsigned depth, hwloc_obj_t obj) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_ancestor_obj_by_type (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_type_t type, hwloc_obj_t obj) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_by_depth (hwloc_topology_t topology, unsigned depth, hwloc obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_by_type (hwloc_topology_t topology, hwloc_obj_type-_t type, hwloc_obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_pu_obj_by_os_index (hwloc_topology_t topology, unsigned os_index) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_next_child (hwloc_topology_t topology __hwloc_attribute_-unused, hwloc obj_t parent, hwloc obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_common_ancestor_obj (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t obj1, hwloc_obj_t obj2) __hwloc_attribute_pure
- static __hwloc_inline int hwloc_obj_is_in_subtree (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t obj, hwloc_obj_t subtree_root) __hwloc_attribute_pure

18.17.1 Detailed Description

Be sure to see the figure in termsanddefs that shows a complete topology tree, including depths, child/sibling/cousin relationships, and an example of an asymmetric topology where one socket has fewer caches than its peers.

18.17.2 Function Documentation

```
18.17.2.1 static __hwloc_inline hwloc_obj_t hwloc_get_ancestor_obj_by_depth ( hwloc_topology_t topology __hwloc_attribute_unused, unsigned depth, hwloc_obj_t obj_) [static]
```

Returns the ancestor object of obj at depth depth.

```
18.17.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_ancestor_obj_by_type ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_type_type, hwloc_obj_tobj_) [static]
```

Returns the ancestor object of obj with type type.

```
18.17.2.3 static __hwloc_inline hwloc_obj_t hwloc_get_common_ancestor_obj( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t obj1, hwloc_obj_t obj2) [static]
```

Returns the common parent object to objects IvI1 and IvI2.

```
18.17.2.4 static __hwloc_inline hwloc_obj_t hwloc_get_next_child ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t parent, hwloc_obj_t prev ) [static]
```

Return the next child.

If prev is NULL, return the first child.

18.17.2.5 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_by_depth (hwloc_topology_t topology, unsigned depth, hwloc_obj_t prev) [static]

Returns the next object at depth depth.

If prev is NULL, return the first object at depth depth.

```
18.17.2.6 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_by_type ( hwloc_topology_t topology, hwloc_obj_type_t type, hwloc_obj_t prev ) [static]
```

Returns the next object of type type.

If prev is NULL, return the first object at type type. If there are multiple or no depth for given type, return NULL and let the caller fallback to hwloc_get_next_obj_by_depth().

```
18.17.2.7 static __hwloc_inline hwloc_obj_t hwloc_get_pu_obj_by_os_index ( hwloc_topology_t topology, unsigned os_index ) [static]
```

Returns the object of type HWLOC_OBJ_PU with os_index.

Note

The os_index field of object should most of the times only be used for pretty-printing purpose. Type HWLO-C_OBJ_PU is the only case where os_index could actually be useful, when manually binding to processors. However, using CPU sets to hide this complexity should often be preferred.

```
18.17.2.8 static __hwloc_inline hwloc_obj_t hwloc_get_root_obj( hwloc_topology_t topology ) [static]
```

Returns the top-object of the topology-tree.

Its type is typically HWLOC_OBJ_MACHINE but it could be different for complex topologies. This function replaces the old deprecated hwloc_get_system_obj().

```
18.17.2.9 static __hwloc_inline int hwloc_obj_is_in_subtree ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t obj, hwloc_obj_t subtree_root ) [static]
```

Returns true if obj is inside the subtree beginning with subtree_root.

Note

This function assumes that both obj and subtree_root have a cpuset.

18.18 Finding Objects Inside a CPU set

Functions

- static __hwloc_inline hwloc_obj_t hwloc_get_first_largest_obj_inside_cpuset (hwloc_topology_t topology, hwloc const cpuset t set)
- HWLOC_DECLSPEC int hwloc_get_largest_objs_inside_cpuset (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_t *__hwloc_restrict objs, int max)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, hwloc_obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_inside_cpuset_by_type (hwloc_topology_t topology, hwloc const cpuset t set, hwloc obj_type_t type, hwloc obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_obj_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, unsigned idx) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_obj_inside_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type, unsigned idx) __hwloc_attribute_pure
- static __hwloc_inline unsigned hwloc_get_nbobjs_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth) __hwloc_attribute_pure
- static __hwloc_inline int hwloc_get_nbobjs_inside_cpuset_by_type (hwloc_topology_t topology, hwloc_constcpuset_t set, hwloc_obj_type_t type) __hwloc_attribute_pure
- static __hwloc_inline int hwloc_get_obj_index_inside_cpuset (hwloc_topology_t topology __hwloc_attributeunused, hwloc_const_cpuset_t set, hwloc_obj_t obj) __hwloc_attribute_pure

18.18.1 Detailed Description

18.18.2 Function Documentation

18.18.2.1 static __hwloc_inline hwloc_obj_t hwloc_get_first_largest_obj_inside_cpuset (hwloc_topology_t topology, hwloc_const_cpuset_t set) [static]

Get the first largest object included in the given cpuset set.

Returns

the first object that is included in set and whose parent is not.

This is convenient for iterating over all largest objects within a CPU set by doing a loop getting the first largest object and clearing its CPU set from the remaining CPU set.

Note

This function cannot work if the root object does not have a CPU set, e.g. if the topology is made of different machines.

```
18.18.2.2 HWLOC_DECLSPEC int hwloc_get_largest_objs_inside_cpuset ( hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_t *_hwloc_restrict objs, int max )
```

Get the set of largest objects covering exactly a given cpuset $\mathtt{set}.$

Returns

the number of objects returned in objs.

Note

This function cannot work if the root object does not have a CPU set, e.g. if the topology is made of different machines.

18.18.2.3 static __hwloc_inline unsigned hwloc_get_nbobjs_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth) [static]

Return the number of objects at depth depth included in CPU set set.

Note

This function cannot work if objects at the given depth do not have CPU sets or if the topology is made of different machines.

18.18.2.4 static __hwloc_inline int hwloc_get_nbobjs_inside_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type) [static]

Return the number of objects of type type included in CPU set set.

If no object for that type exists inside CPU set set, 0 is returned. If there are several levels with objects of that type inside CPU set set, -1 is returned.

Note

This function cannot work if objects of the given type do not have CPU sets or if the topology is made of different machines.

18.18.2.5 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, hwloc_obj_t prev) [static]

Return the next object at depth depth included in CPU set set.

If prev is NULL, return the first object at depth depth included in set. The next invokation should pass the previous return value in prev so as to obtain the next object in set.

Note

This function cannot work if objects at the given depth do not have CPU sets or if the topology is made of different machines.

18.18.2.6 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_inside_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type, hwloc_obj_t prev) [static]

Return the next object of type type included in CPU set set.

If there are multiple or no depth for given type, return \mathtt{NULL} and let the caller fallback to $\mathsf{hwloc_get_next_obj_inside_cpuset_by_depth}()$.

Note

This function cannot work if objects of the given type do not have CPU sets or if the topology is made of different machines.

18.18.2.7 static __hwloc_inline int hwloc_get_obj_index_inside_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_const_cpuset_t set, hwloc_obj_t obj) [static]

Return the logical index among the objects included in CPU set set.

Consult all objects in the same level as obj and inside CPU set set in the logical order, and return the index of obj within them. If set covers the entire topology, this is the logical index of obj. Otherwise, this is similar to a logical index within the part of the topology defined by CPU set set.

18.18.2.8 static __hwloc_inline hwloc_obj_t hwloc_get_obj_inside_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, unsigned idx) [static]

Return the (logically) idx -th object at depth depth included in CPU set set.

Note

This function cannot work if objects at the given depth do not have CPU sets or if the topology is made of different machines.

18.18.2.9 static __hwloc_inline hwloc_obj_t hwloc_get_obj_inside_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type, unsigned idx) [static]

Return the idx -th object of type type included in CPU set set.

If there are multiple or no depth for given type, return NULL and let the caller fallback to $\texttt{hwloc_get_obj_inside_cpuset_by_depth}()$.

Note

This function cannot work if objects of the given type do not have CPU sets or if the topology is made of different machines.

18.19 Finding a single Object covering at least CPU set

Functions

- static __hwloc_inline hwloc_obj_t hwloc_get_child_covering_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_const_cpuset_t set, hwloc_obj_t parent) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_obj_covering_cpuset (hwloc_topology_t topology, hwloc_const-_cpuset_t set) __hwloc_attribute_pure

18.19.1 Detailed Description

18.19.2 Function Documentation

```
18.19.2.1 static __hwloc_inline hwloc_obj_t hwloc_get_child_covering_cpuset ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_const_cpuset_t set, hwloc_obj_t parent ) [static]
```

Get the child covering at least CPU set set.

Returns

NULL if no child matches or if set is empty.

Note

This function cannot work if parent does not have a CPU set.

```
18.19.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_obj_covering_cpuset ( hwloc_topology_t topology, hwloc_const_cpuset_t set ) [static]
```

Get the lowest object covering at least CPU set set.

Returns

NULL if no object matches or if set is empty.

Note

This function cannot work if the root object does not have a CPU set, e.g. if the topology is made of different machines.

18.20 Finding a set of similar Objects covering at least a CPU set

Functions

- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_covering_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, hwloc_obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_covering_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type, hwloc_obj_t prev)

18.20.1 Detailed Description

18.20.2 Function Documentation

18.20.2.1 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_covering_cpuset_by_depth (hwloc_topology_t topology, hwloc_const_cpuset_t set, unsigned depth, hwloc_obj_t prev) [static]

Iterate through same-depth objects covering at least CPU set set.

If object prev is NULL, return the first object at depth depth covering at least part of CPU set set. The next invokation should pass the previous return value in prev so as to obtain the next object covering at least another part of set.

Note

This function cannot work if objects at the given depth do not have CPU sets or if the topology is made of different machines.

18.20.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_next_obj_covering_cpuset_by_type (hwloc_topology_t topology, hwloc_const_cpuset_t set, hwloc_obj_type_t type, hwloc_obj_t prev) [static]

Iterate through same-type objects covering at least CPU set set.

If object prev is NULL, return the first object of type type covering at least part of CPU set set. The next invokation should pass the previous return value in prev so as to obtain the next object of type type covering at least another part of set.

If there are no or multiple depths for type type, NULL is returned. The caller may fallback to $hwloc_get_next_obj_covering_cpuset_by_depth()$ for each depth.

Note

This function cannot work if objects of the given type do not have CPU sets or if the topology is made of different machines.

18.21 Cache-specific Finding Helpers

Functions

- static __hwloc_inline int hwloc_get_cache_type_depth (hwloc_topology_t topology, unsigned cachelevel, hwloc_obj_cache_type_t cachetype)
- static __hwloc_inline hwloc_obj_t hwloc_get_cache_covering_cpuset (hwloc_topology_t topology, hwloc_const_cpuset_t set) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_shared_cache_covering_obj (hwloc_topology_t topology __- hwloc_attribute_unused, hwloc_obj_t obj) __hwloc_attribute_pure

18.21.1 Detailed Description

18.21.2 Function Documentation

```
18.21.2.1 static __hwloc_inline hwloc_obj_t hwloc_get_cache_covering_cpuset ( hwloc_topology_t topology, hwloc_const_cpuset_t set ) [static]
```

Get the first cache covering a cpuset set.

Returns

NULL if no cache matches.

Note

This function cannot work if the root object does not have a CPU set, e.g. if the topology is made of different machines.

```
18.21.2.2 static __hwloc_inline int hwloc_get_cache_type_depth ( hwloc_topology_t topology, unsigned cachelevel, hwloc_obj_cache_type_t cachetype ) [static]
```

Find the depth of cache objects matching cache depth and type.

Return the depth of the topology level that contains cache objects whose attributes match cachedepth and cachetype. This function intends to disambiguate the case where hwloc_get_type_depth() returns HWLOC_T-YPE DEPTH MULTIPLE.

If no cache level matches, HWLOC_TYPE_DEPTH_UNKNOWN is returned.

If cachetype is HWLOC_OBJ_CACHE_UNIFIED, the depth of the unique matching unified cache level is returned.

If cachetype is HWLOC_OBJ_CACHE_DATA or HWLOC_OBJ_CACHE_INSTRUCTION, either a matching cache, or a unified cache is returned.

If cachetype is -1, it is ignored and multiple levels may match. The function returns either the depth of a uniquely matching level or HWLOC_TYPE_DEPTH_MULTIPLE.

```
18.21.2.3 static __hwloc_inline hwloc_obj_t hwloc_get_shared_cache_covering_obj ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t obj ) [static]
```

Get the first cache shared between an object and somebody else.

Returns

NULL if no cache matches or if an invalid object is given.

18.22 Advanced Traversal Helpers

Functions

- HWLOC_DECLSPEC unsigned hwloc_get_closest_objs (hwloc_topology_t topology, hwloc_obj_t src, hwloc_obj_t * __hwloc_restrict objs, unsigned max)
- static __hwloc_inline hwloc_obj_t hwloc_get_obj_below_by_type (hwloc_topology_t topology, hwloc_obj_type_t type1, unsigned idx1, hwloc_obj_type_t type2, unsigned idx2) __hwloc_attribute_pure
- static __hwloc_inline hwloc_obj_t hwloc_get_obj_below_array_by_type (hwloc_topology_t topology, int nr, hwloc_obj_type_t *typev, unsigned *idxv) __hwloc_attribute_pure

18.22.1 Detailed Description

Be sure to see the figure in termsanddefs that shows a complete topology tree, including depths, child/sibling/cousin relationships, and an example of an asymmetric topology where one socket has fewer caches than its peers.

18.22.2 Function Documentation

```
18.22.2.1 HWLOC_DECLSPEC unsigned hwloc_get_closest_objs ( hwloc_topology_t topology, hwloc_obj_t src, hwloc_obj_t *_hwloc_restrict objs, unsigned max )
```

Do a depth-first traversal of the topology to find and sort.

all objects that are at the same depth than src. Report in objs up to max physically closest ones to src.

Returns

```
the number of objects returned in objs. 0 if src is an I/O object.
```

Note

This function requires the src object to have a CPU set.

```
18.22.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_obj_below_array_by_type ( hwloc_topology_t topology, int nr, hwloc obj type t * typev, unsigned * idxv ) [static]
```

Find an object below a chain of objects specified by types and indexes.

This is a generalized version of hwloc get obj below by type().

Arrays typev and idxv must contain nr types and indexes.

Start from the top system object and walk the arrays typev and idxv. For each type and logical index couple in the arrays, look under the previously found object to find the index-th object of the given type. Indexes are specified within the parent, not withing the entire system.

For instance, if nr is 3, typev contains NODE, SOCKET and CORE, and idxv contains 0, 1 and 2, return the third core object below the second socket below the first NUMA node.

Note

This function requires all these objects and the root object to have a CPU set.

18.22.2.3 static __hwloc_inline hwloc_obj_t hwloc_get_obj_below_by_type (hwloc_topology_t topology, hwloc_obj_type_t type1, unsigned idx1, hwloc_obj_type_t type2, unsigned idx2) [static]

Find an object below another object, both specified by types and indexes.

Start from the top system object and find object of type type1 and logical index idx1. Then look below this object and find another object of type type2 and logical index idx2. Indexes are specified within the parent, not withing the entire system.

For instance, if type1 is SOCKET, idx1 is 2, type2 is CORE and idx2 is 3, return the fourth core object below the third socket.

Note

This function requires these objects to have a CPU set.

18.23 Binding Helpers

Functions

- static __hwloc_inline void hwloc_distributev (hwloc_topology_t topology, hwloc_obj_t *root, unsigned n_roots, hwloc_cpuset_t *cpuset, unsigned n, unsigned until)
- static __hwloc_inline void hwloc_distribute (hwloc_topology_t topology, hwloc_obj_t root, hwloc_cpuset_t *set, unsigned n, unsigned until)
- static __hwloc_inline void * hwloc_alloc_membind_policy_nodeset (hwloc_topology_t topology, size_t len, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags)
- static __hwloc_inline void * hwloc_alloc_membind_policy (hwloc_topology_t topology, size_t len, hwloc_const_cpuset_t set, hwloc_membind_policy_t policy, int flags)

18.23.1 Detailed Description

18.23.2 Function Documentation

```
18.23.2.1 static __hwloc_inline void* hwloc_alloc_membind_policy ( hwloc_topology_t topology, size_t len, hwloc_const_cpuset_t set, hwloc_membind_policy_t policy, int flags ) [static]
```

Allocate some memory on the memory nodes near given cpuset cpuset.

This is similar to hwloc_alloc_membind_policy_nodeset, but for a given cpuset.

```
18.23.2.2 static __hwloc_inline void* hwloc_alloc_membind_policy_nodeset ( hwloc_topology_t topology, size_t len, hwloc_const_nodeset_t nodeset, hwloc_membind_policy_t policy, int flags ) [static]
```

Allocate some memory on the given nodeset nodeset.

This is similar to hwloc_alloc_membind except that it is allowed to change the current memory binding policy, thus providing more binding support, at the expense of changing the current state.

```
18.23.2.3 static __hwloc_inline void hwloc_distribute ( hwloc_topology_t topology, hwloc_obj_t root, hwloc_cpuset_t * set, unsigned n, unsigned until ) [static]
```

```
18.23.2.4 static __hwloc_inline void hwloc_distributev ( hwloc_topology_t topology, hwloc_obj_t * roots, unsigned n_roots, hwloc_cpuset_t * set, unsigned n_roots, hwloc_cpuset_t * set, unsigned n_roots, unsigned n_roots
```

Distribute n items over the topology under root.

Distribute n items over the topology under roots.

Array cpuset will be filled with n cpusets recursively distributed linearly over the topology under root, down to depth until (which can be INT_MAX to distribute down to the finest level).

This is typically useful when an application wants to distribute n threads over a machine, giving each of them as much private cache as possible and keeping them locally in number order.

The caller may typically want to also call hwloc_bitmap_singlify() before binding a thread so that it does not move at all.

Note

This function requires the root object to have a CPU set.

This is the same as hwloc distribute, but takes an array of roots instead of just one root.

18.23 Binding Helpers 109

This function requires the ${\tt roots}$ objects to have a CPU set.

18.24 Cpuset Helpers

Functions

```
    static __hwloc_inline
    hwloc_const_cpuset_t
    hwloc_topology_get_complete_cpuset
    (hwloc_topology_t topology) __hwloc_-attribute pure
```

- static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_topology_cpuset (hwloc_topology_t topology) __hwloc_attribute-_pure
- static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_online_cpuset (hwloc_topology_t topology) __hwloc_attribute_pure
- static __hwloc_inline
 hwloc_const_cpuset_t hwloc_topology_get_allowed_cpuset (hwloc_topology_t topology) __hwloc_attribute__pure

18.24.1 Detailed Description

18.24.2 Function Documentation

```
18.24.2.1 static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_allowed_cpuset( hwloc_topology_t topology ) [static]
```

Get allowed CPU set.

Returns

the CPU set of allowed logical processors of the system. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned cpuset is not newly allocated and should thus not be changed or freed, hwloc_cpuset_dup must be used to obtain a local copy.

```
18.24.2.2 static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_complete_cpuset( hwloc_topology_t topology ) [static]
```

Get complete CPU set.

Returns

the complete CPU set of logical processors of the system. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned cpuset is not newly allocated and should thus not be changed or freed; hwloc_cpuset_dup must be used to obtain a local copy.

18.24 Cpuset Helpers 111

18.24.2.3 static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_online_cpuset(hwloc_topology_t topology) [static]

Get online CPU set.

Returns

the CPU set of online logical processors of the system. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned cpuset is not newly allocated and should thus not be changed or freed; hwloc_cpuset_dup must be used to obtain a local copy.

18.24.2.4 static __hwloc_inline hwloc_const_cpuset_t hwloc_topology_get_topology_cpuset (hwloc_topology_t topology) [static]

Get topology CPU set.

Returns

the CPU set of logical processors of the system for which hwloc provides topology information. This is equivalent to the cpuset of the system object. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned cpuset is not newly allocated and should thus not be changed or freed; hwloc_cpuset_dup must be used to obtain a local copy.

18.25 Nodeset Helpers

Functions

```
    static __hwloc_inline
hwloc_const_nodeset_t hwloc_topology_get_complete_nodeset (hwloc_topology_t topology) __hwloc_-
attribute_pure
```

```
    static __hwloc_inline
    hwloc_const_nodeset_t hwloc_topology_get_topology_nodeset (hwloc_topology_t topology) __hwloc_-attribute_pure
```

```
    static __hwloc_inline
    hwloc_const_nodeset_t hwloc_topology_get_allowed_nodeset (hwloc_topology_t topology) __hwloc_-attribute pure
```

18.25.1 Detailed Description

18.25.2 Function Documentation

```
18.25.2.1 static __hwloc_inline hwloc_const_nodeset_t hwloc_topology_get_allowed_nodeset( hwloc_topology_t topology ) [static]
```

Get allowed node set.

Returns

the node set of allowed memory of the system. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned nodeset is not newly allocated and should thus not be changed or freed, hwloc_nodeset_dup must be used to obtain a local copy.

```
18.25.2.2 static __hwloc_inline hwloc_const_nodeset_t hwloc_topology_get_complete_nodeset( hwloc_topology_t topology ) [static]
```

Get complete node set.

Returns

the complete node set of memory of the system. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned nodeset is not newly allocated and should thus not be changed or freed; hwloc_nodeset_dup must be used to obtain a local copy.

```
18.25.2.3 static __hwloc_inline hwloc_const_nodeset_t hwloc_topology_get_topology_nodeset( hwloc_topology_t topology ) [static]
```

Get topology node set.

18.25 Nodeset Helpers 113

Returns

the node set of memory of the system for which hwloc provides topology information. This is equivalent to the nodeset of the system object. If the topology is the result of a combination of several systems, NULL is returned.

Note

The returned nodeset is not newly allocated and should thus not be changed or freed; hwloc_nodeset_dup must be used to obtain a local copy.

18.26 Conversion between cpuset and nodeset

Functions

- static __hwloc_inline void hwloc_cpuset_to_nodeset (hwloc_topology_t topology, hwloc_const_cpuset_t _-cpuset, hwloc_nodeset_t nodeset)
- static __hwloc_inline void hwloc_cpuset_to_nodeset_strict (struct hwloc_topology *topology, hwloc_const_cpuset_t_cpuset, hwloc_nodeset_t nodeset)
- static __hwloc_inline void hwloc_cpuset_from_nodeset (hwloc_topology_t topology, hwloc_cpuset_t_cpuset, hwloc_const_nodeset_t nodeset)
- static __hwloc_inline void hwloc_cpuset_from_nodeset_strict (struct hwloc_topology *topology, hwloc_cpuset t cpuset, hwloc const nodeset t nodeset)

18.26.1 Detailed Description

There are two semantics for converting cpusets to nodesets depending on how non-NUMA machines are handled.

When manipulating nodesets for memory binding, non-NUMA machines should be considered as having a single NUMA node. The standard conversion routines below should be used so that marking the first bit of the nodeset means that memory should be bound to a non-NUMA whole machine.

When manipulating nodesets as an actual list of NUMA nodes without any need to handle memory binding on non-NUMA machines, the strict conversion routines may be used instead.

18.26.2 Function Documentation

```
18.26.2.1 static __hwloc_inline void hwloc_cpuset_from_nodeset ( hwloc_topology_t topology, hwloc_cpuset_t __cpuset, hwloc_const_nodeset_t nodeset ) [static]
```

Convert a NUMA node set into a CPU set and handle non-NUMA cases.

If the topology contains no NUMA nodes, the machine is considered as a single memory node, and the following behavior is used: If nodeset is empty, cpuset will be emptied as well. Otherwise cpuset will be entirely filled. This is useful for manipulating memory binding sets.

```
18.26.2.2 static __hwloc_inline void hwloc_cpuset_from_nodeset_strict( struct hwloc_topology * topology, hwloc_cpuset_t __cpuset, hwloc_const_nodeset_t nodeset ) [static]
```

Convert a NUMA node set into a CPU set without handling non-NUMA cases.

This is the strict variant of hwloc_cpuset_from_nodeset. It does not fix non-NUMA cases. If the topology contains some NUMA nodes, behave exactly the same. However, if the topology contains no NUMA nodes, return an empty cpuset.

```
18.26.2.3 static __hwloc_inline void hwloc_cpuset_to_nodeset ( hwloc_topology_t topology, hwloc_const_cpuset_t __cpuset, hwloc_nodeset_t nodeset ) [static]
```

Convert a CPU set into a NUMA node set and handle non-NUMA cases.

If some NUMA nodes have no CPUs at all, this function never sets their indexes in the output node set, even if a full CPU set is given in input.

If the topology contains no NUMA nodes, the machine is considered as a single memory node, and the following behavior is used: If cpuset is empty, nodeset will be emptied as well. Otherwise nodeset will be entirely filled.

18.26.2.4 static __hwloc_inline void hwloc_cpuset_to_nodeset_strict (struct hwloc_topology * topology, hwloc_const_cpuset_t_cpuset, hwloc_nodeset_t nodeset) [static]

Convert a CPU set into a NUMA node set without handling non-NUMA cases.

This is the strict variant of hwloc_cpuset_to_nodeset. It does not fix non-NUMA cases. If the topology contains some NUMA nodes, behave exactly the same. However, if the topology contains no NUMA nodes, return an empty nodeset.

18.27 Distances

Functions

- static __hwloc_inline struct hwloc_distances_s * hwloc_get_whole_distance_matrix_by_depth (hwloc_topology_t topology, unsigned depth)
- static __hwloc_inline struct
 hwloc_distances_s * hwloc_get_whole_distance_matrix_by_type (hwloc_topology_t topology, hwloc_obj_type_t type)
- static __hwloc_inline struct
 hwloc_distances_s * hwloc_get_distance_matrix_covering_obj_by_depth (hwloc_topology_t topology, hwloc_obj_t obj, unsigned depth, unsigned *firstp)
- static __hwloc_inline int hwloc_get_latency (hwloc_topology_t topology, hwloc_obj_t obj1, hwloc_obj_t obj2, float *latency, float *reverse_latency)

18.27.1 Detailed Description

18.27.2 Function Documentation

```
18.27.2.1 static __hwloc_inline struct hwloc_distances_s* hwloc_get_distance_matrix_covering_obj_by_depth (
    hwloc_topology_t topology, hwloc_obj_t obj, unsigned depth, unsigned * firstp ) [static]
```

Get distances for the given depth and covering some objects.

Return a distance matrix that describes depth depth and covers at least object obj and all its children.

When looking for the distance between some objects, a common ancestor should be passed in obj.

firstp is set to logical index of the first object described by the matrix.

The returned structure belongs to the hwloc library. The caller should not modify or free it.

```
18.27.2.2 static __hwloc_inline int hwloc_get_latency ( hwloc_topology_t topology, hwloc_obj_t obj1, hwloc_obj_t obj2, float * latency, float * reverse_latency ) [static]
```

Get the latency in both directions between two objects.

Look at ancestor objects from the bottom to the top until one of them contains a distance matrix that matches the objects exactly.

latency gets the value from object obj1 to obj2, while reverse_latency gets the reverse-direction value, which may be different on some architectures.

Returns

-1 if no ancestor contains a matching latency matrix.

```
18.27.2.3 static __hwloc_inline struct hwloc_distances_s* hwloc_get_whole_distance_matrix_by_depth ( hwloc_topology_t topology, unsigned depth ) [static]
```

Get the distances between all objects at the given depth.

Returns

a distances structure containing a matrix with all distances between all objects at the given depth.

Slot i+nbobjs*j contains the distance from the object of logical index i the object of logical index j.

18.27 Distances

Note

This function only returns matrices covering the whole topology, without any unknown distance value. Those matrices are available in top-level object of the hierarchy. Matrices of lower objects are not reported here since they cover only part of the machine.

The returned structure belongs to the hwloc library. The caller should not modify or free it.

Returns

NULL if no such distance matrix exists.

Get the distances between all objects of a given type.

Returns

a distances structure containing a matrix with all distances between all objects of the given type.

Slot i+nbobjs*j contains the distance from the object of logical index i the object of logical index j.

Note

This function only returns matrices covering the whole topology, without any unknown distance value. Those matrices are available in top-level object of the hierarchy. Matrices of lower objects are not reported here since they cover only part of the machine.

The returned structure belongs to the hwloc library. The caller should not modify or free it.

Returns

NULL if no such distance matrix exists.

18.28 Advanced I/O object traversal helpers

Functions

- static __hwloc_inline hwloc_obj_t hwloc_get_non_io_ancestor_obj (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t ioobj)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_pcidev (hwloc_topology_t topology, hwloc_obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_pcidev_by_busid (hwloc_topology_t topology, unsigned domain, unsigned bus, unsigned dev, unsigned func)
- static __hwloc_inline hwloc_obj_t hwloc_get_pcidev_by_busidstring (hwloc_topology_t topology, const char *busid)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_osdev (hwloc_topology_t topology, hwloc_obj_t prev)
- static __hwloc_inline hwloc_obj_t hwloc_get_next_bridge (hwloc_topology_t topology, hwloc_obj_t prev)
- static __hwloc_inline int hwloc_bridge_covers_pcibus (hwloc_obj_t bridge, unsigned domain, unsigned bus)
- static __hwloc_inline hwloc_obj_t hwloc_get_hostbridge_by_pcibus (hwloc_topology_t topology, unsigned domain, unsigned bus)

18.28.1 Detailed Description

18.28.2 Function Documentation

- 18.28.2.1 static __hwloc_inline int hwloc_bridge_covers_pcibus (hwloc_obj_t bridge, unsigned domain, unsigned bus) [static]
- 18.28.2.2 static __hwloc_inline hwloc_obj_t hwloc_get_hostbridge_by_pcibus (hwloc_topology_t topology, unsigned domain, unsigned bus) [static]

Find the hostbridge that covers the given PCI bus.

This is useful for finding the locality of a bus because it is the hostbridge parent cpuset.

```
18.28.2.3 static __hwloc_inline hwloc_obj_t hwloc_get_next_bridge ( hwloc_topology_t topology, hwloc_obj_t prev )
[static]
```

Get the next bridge in the system.

Returns

the first bridge if prev is NULL.

18.28.2.4 static __hwloc_inline hwloc_obj_t hwloc_get_next_osdev (hwloc_topology_t topology, hwloc_obj_t prev) [static]

Get the next OS device in the system.

Returns

the first OS device if prev is NULL.

18.28.2.5 static __hwloc_inline hwloc_obj_t hwloc_get_next_pcidev (hwloc_topology_t topology, hwloc_obj_t prev) [static]

Get the next PCI device in the system.

Returns

the first PCI device if prev is NULL.

```
18.28.2.6 static __hwloc_inline hwloc_obj_t hwloc_get_non_io_ancestor_obj ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t ioobj ) [static]
```

Get the first non-I/O ancestor object.

Given the I/O object ioobj, find the smallest non-I/O ancestor object. This regular object may then be used for binding because its locality is the same as ioobj.

```
18.28.2.7 static __hwloc_inline hwloc_obj_t hwloc_get_pcidev_by_busid ( hwloc_topology_t topology, unsigned domain, unsigned bus, unsigned dev, unsigned func ) [static]
```

Find the PCI device object matching the PCI bus id given domain, bus device and function PCI bus id.

```
18.28.2.8 static __hwloc_inline hwloc_obj_t hwloc_get_pcidev_by_busidstring ( hwloc_topology_t topology, const char * busid ) [static]
```

Find the PCI device object matching the PCI bus id given as a string xxxx:yy:zz.t or yy:zz.t.

18.29 The bitmap API

Macros

- #define hwloc_bitmap_foreach_begin(id, bitmap)
- #define hwloc_bitmap_foreach_end()

Typedefs

- typedef struct hwloc bitmap s * hwloc bitmap t
- typedef struct hwloc_bitmap_s * hwloc_const_bitmap_t

Functions

- HWLOC DECLSPEC hwloc bitmap t hwloc bitmap alloc (void) hwloc attribute malloc
- HWLOC_DECLSPEC hwloc_bitmap_t hwloc_bitmap_alloc_full (void) __hwloc_attribute_malloc
- HWLOC_DECLSPEC void hwloc_bitmap_free (hwloc_bitmap_t bitmap)
- HWLOC_DECLSPEC hwloc_bitmap_t hwloc_bitmap_dup (hwloc_const_bitmap_t bitmap) __hwloc_attribute-_malloc
- HWLOC_DECLSPEC void hwloc_bitmap_copy (hwloc_bitmap_t dst, hwloc_const_bitmap_t src)
- HWLOC_DECLSPEC int hwloc_bitmap_snprintf (char *__hwloc_restrict buf, size_t buflen, hwloc_const_-bitmap t bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_asprintf (char **strp, hwloc_const_bitmap_t bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_sscanf (hwloc_bitmap_t bitmap, const char *__hwloc_restrict string)
- HWLOC_DECLSPEC int hwloc_bitmap_list_snprintf (char *__hwloc_restrict buf, size_t buflen, hwloc_const_bitmap_t bitmap)
- HWLOC DECLSPEC int hwloc bitmap list asprintf (char **strp, hwloc const bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_list_sscanf (hwloc_bitmap_t bitmap, const char *_hwloc_restrict string)
- HWLOC_DECLSPEC int hwloc_bitmap_taskset_snprintf (char *__hwloc_restrict buf, size_t buflen, hwloc_-const_bitmap_t bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_taskset_asprintf (char **strp, hwloc_const_bitmap_t bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_taskset_sscanf (hwloc_bitmap_t bitmap, const char *__hwloc_restrict string)
- HWLOC DECLSPEC void hwloc bitmap zero (hwloc bitmap t bitmap)
- HWLOC_DECLSPEC void hwloc_bitmap_fill (hwloc_bitmap_t bitmap)
- HWLOC_DECLSPEC void hwloc_bitmap_only (hwloc_bitmap_t bitmap, unsigned id)
- HWLOC_DECLSPEC void hwloc_bitmap_allbut (hwloc_bitmap_t bitmap, unsigned id)
- HWLOC_DECLSPEC void hwloc_bitmap_from_ulong (hwloc_bitmap_t bitmap, unsigned long mask)
- HWLOC_DECLSPEC void hwloc_bitmap_from_ith_ulong (hwloc_bitmap_t bitmap, unsigned i, unsigned long mask)
- HWLOC_DECLSPEC void hwloc_bitmap_set (hwloc_bitmap_t bitmap, unsigned id)
- · HWLOC DECLSPEC void hwloc bitmap set range (hwloc bitmap t bitmap, unsigned begin, int end)
- HWLOC_DECLSPEC void hwloc_bitmap_set_ith_ulong (hwloc_bitmap_t bitmap, unsigned i, unsigned long mask)
- HWLOC_DECLSPEC void hwloc_bitmap_clr (hwloc_bitmap_t bitmap, unsigned id)
- HWLOC_DECLSPEC void hwloc_bitmap_clr_range (hwloc_bitmap_t bitmap, unsigned begin, int end)
- HWLOC DECLSPEC void hwloc bitmap singlify (hwloc bitmap t bitmap)
- HWLOC_DECLSPEC unsigned long hwloc_bitmap_to_ulong (hwloc_const_bitmap_t bitmap) __hwloc_attribute pure
- HWLOC_DECLSPEC unsigned long hwloc_bitmap_to_ith_ulong (hwloc_const_bitmap_t bitmap, unsigned i)
 _hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_isset (hwloc_const_bitmap_t bitmap, unsigned id) __hwloc_attribute-pure

18.29 The bitmap API 121

- HWLOC_DECLSPEC int hwloc_bitmap_iszero (hwloc_const_bitmap_t bitmap) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_isfull (hwloc_const_bitmap_t bitmap) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_first (hwloc_const_bitmap_t bitmap) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_next (hwloc_const_bitmap_t bitmap, int prev) __hwloc_attribute_pure
- HWLOC DECLSPEC int hwloc bitmap last (hwloc const bitmap t bitmap) hwloc attribute pure
- HWLOC DECLSPEC int hwloc bitmap weight (hwloc const bitmap t bitmap) hwloc attribute pure
- HWLOC_DECLSPEC void hwloc_bitmap_or (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap t bitmap2)
- HWLOC_DECLSPEC void hwloc_bitmap_and (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2)
- HWLOC_DECLSPEC void hwloc_bitmap_andnot (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc const bitmap t bitmap2)
- HWLOC_DECLSPEC void hwloc_bitmap_xor (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap2)
- HWLOC DECLSPEC void hwloc_bitmap_not (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap)
- HWLOC_DECLSPEC int hwloc_bitmap_intersects (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_isincluded (hwloc_const_bitmap_t sub_bitmap, hwloc_const_-bitmap_t super_bitmap) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_isequal (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_compare_first (hwloc_const_bitmap_t bitmap_t bitmap_t bitmap_t bitmap_t) __hwloc_attribute_pure
- HWLOC_DECLSPEC int hwloc_bitmap_compare (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2) __hwloc_attribute_pure

18.29.1 Detailed Description

The hwloc_bitmap_t type represents a set of objects, typically OS processors – which may actually be hardware threads (represented by hwloc_cpuset_t, which is a typedef for hwloc_bitmap_t) – or memory nodes (represented by hwloc_nodeset_t, which is also a typedef for hwloc_bitmap_t).

Both CPU and node sets are always indexed by OS physical number.

Note

CPU sets and nodesets are described in Object sets (hwloc_cpuset_t and hwloc_nodeset_t).

A bitmap may be of infinite size.

18.29.2 Macro Definition Documentation

18.29.2.1 #define hwloc_bitmap_foreach_begin(id, bitmap)

Loop macro iterating on bitmap bitmap.

index is the loop variable; it should be an unsigned int. The first iteration will set index to the lowest index in the bitmap. Successive iterations will iterate through, in order, all remaining indexes that in the bitmap. To be specific: each iteration will return a value for index such that hwloc_bitmap_isset(bitmap, index) is true.

The assert prevents the loop from being infinite if the bitmap is infinite.

18.29.2.2 #define hwloc_bitmap_foreach_end()

Value:

} \
} while (0)

```
18.29.3 Typedef Documentation
18.29.3.1 typedef struct hwloc_bitmap_s* hwloc_bitmap_t
Set of bits represented as an opaque pointer to an internal bitmap.
18.29.3.2 typedef struct hwloc_bitmap_s* hwloc_const_bitmap_t
a non-modifiable hwloc_bitmap_t
18.29.4 Function Documentation
18.29.4.1 HWLOC_DECLSPEC void hwloc_bitmap_allbut ( hwloc_bitmap_t bitmap, unsigned id )
Fill the bitmap and clear the index id.
18.29.4.2 HWLOC_DECLSPEC hwloc_bitmap_t hwloc_bitmap_alloc ( void )
Allocate a new empty bitmap.
Returns
     A valid bitmap or NULL.
The bitmap should be freed by a corresponding call to <a href="https://hww.bitmap_free">hwloc_bitmap_free</a>().
18.29.4.3 HWLOC_DECLSPEC hwloc_bitmap_t hwloc_bitmap_alloc_full ( void )
Allocate a new full bitmap.
18.29.4.4 HWLOC_DECLSPEC void hwloc_bitmap_and ( hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1,
         hwloc_const_bitmap_t bitmap2)
And bitmaps bitmap1 and bitmap2 and store the result in bitmap res.
res can be the same as bitmap1 or bitmap2
18.29.4.5 HWLOC_DECLSPEC void hwloc_bitmap_andnot ( hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1,
         hwloc_const_bitmap_t bitmap2)
And bitmap bitmap1 and the negation of bitmap2 and store the result in bitmap res.
res can be the same as bitmap1 or bitmap2
18.29.4.6 HWLOC_DECLSPEC int hwloc_bitmap_asprintf ( char ** strp, hwloc_const_bitmap_t bitmap )
Stringify a bitmap into a newly allocated string.
18.29.4.7 HWLOC_DECLSPEC void hwloc_bitmap_clr ( hwloc_bitmap_t bitmap, unsigned id )
Remove index id from bitmap bitmap.
```

18.29 The bitmap API 123

18.29.4.8 HWLOC_DECLSPEC void hwloc_bitmap_clr_range (hwloc_bitmap_t bitmap, unsigned begin, int end)

Remove indexes from begin to end in bitmap bitmap.

If end is -1, the range is infinite.

18.29.4.9 HWLOC_DECLSPEC int hwloc_bitmap_compare (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2)

Compare bitmaps bitmap1 and bitmap2 using their highest index.

Higher most significant bit is higher. The empty bitmap is considered lower than anything.

18.29.4.10 HWLOC_DECLSPEC int hwloc_bitmap_compare_first (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap t bitmap2)

Compare bitmaps bitmap1 and bitmap2 using their lowest index.

Smaller least significant bit is smaller. The empty bitmap is considered higher than anything.

18.29.4.11 HWLOC_DECLSPEC void hwloc_bitmap_copy (hwloc_bitmap_t dst, hwloc_const_bitmap_t src)

Copy the contents of bitmap src into the already allocated bitmap dst.

18.29.4.12 HWLOC_DECLSPEC hwloc_bitmap_t hwloc_bitmap_dup (hwloc_const_bitmap_t bitmap)

Duplicate bitmap bitmap by allocating a new bitmap and copying bitmap contents.

If bitmap is NULL, NULL is returned.

18.29.4.13 HWLOC_DECLSPEC void hwloc_bitmap_fill (hwloc_bitmap_t bitmap)

Fill bitmap bitmap with all possible indexes (even if those objects don't exist or are otherwise unavailable)

18.29.4.14 HWLOC_DECLSPEC int hwloc_bitmap_first (hwloc_const_bitmap_t bitmap)

Compute the first index (least significant bit) in bitmap bitmap.

Returns

-1 if no index is set.

18.29.4.15 HWLOC_DECLSPEC void hwloc_bitmap_free (hwloc_bitmap_t bitmap)

Free bitmap bitmap.

If bitmap is NULL, no operation is performed.

18.29.4.16 HWLOC_DECLSPEC void hwloc_bitmap_from_ith_ulong (hwloc_bitmap_t bitmap, unsigned i, unsigned long mask)

Setup bitmap bitmap from unsigned long mask used as i -th subset.

18.29.4.17 HWLOC_DECLSPEC void hwloc_bitmap_from_ulong (hwloc_bitmap_t bitmap, unsigned long mask)

Setup bitmap bitmap from unsigned long mask.

18.29.4.18 HWLOC_DECLSPEC int hwloc_bitmap_intersects (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2)

Test whether bitmaps bitmap1 and bitmap2 intersects.

18.29.4.19 HWLOC_DECLSPEC int hwloc_bitmap_isequal (hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap_t bitmap2)

Test whether bitmap bitmap1 is equal to bitmap bitmap2.

18.29.4.20 HWLOC_DECLSPEC int hwloc_bitmap_isfull (hwloc_const_bitmap_t bitmap)

Test whether bitmap bitmap is completely full.

18.29.4.21 HWLOC_DECLSPEC int hwloc_bitmap_isincluded (hwloc_const_bitmap_t sub_bitmap, hwloc_const_bitmap_t super_bitmap)

Test whether bitmap sub_bitmap is part of bitmap super_bitmap.

18.29.4.22 HWLOC_DECLSPEC int hwloc_bitmap_isset (hwloc_const_bitmap_t bitmap, unsigned id)

Test whether index id is part of bitmap bitmap.

18.29.4.23 HWLOC_DECLSPEC int hwloc_bitmap_iszero (hwloc_const_bitmap_t bitmap)

Test whether bitmap bitmap is empty.

18.29.4.24 HWLOC_DECLSPEC int hwloc_bitmap_last (hwloc_const_bitmap_t bitmap)

Compute the last index (most significant bit) in bitmap bitmap.

Returns

-1 if no index is bitmap, or if the index bitmap is infinite.

18.29.4.25 HWLOC_DECLSPEC int hwloc_bitmap_list_asprintf (char ** strp, hwloc_const_bitmap_t bitmap)

Stringify a bitmap into a newly allocated list string.

18.29.4.26 HWLOC_DECLSPEC int hwloc_bitmap_list_snprintf (char *_hwloc_restrict buf, size_t buflen, hwloc_const_bitmap_t bitmap)

Stringify a bitmap in the list format.

Lists are comma-separated indexes or ranges. Ranges are dash separated indexes. The last range may not have a ending indexes if the bitmap is infinite.

Up to buflen characters may be written in buffer buf.

18.29 The bitmap API 125

If buflen is 0, buf may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending 0).

18.29.4.27 HWLOC_DECLSPEC int hwloc_bitmap_list_sscanf (hwloc_bitmap_t bitmap, const char *_hwloc_restrict string)

Parse a list string and stores it in bitmap bitmap.

18.29.4.28 HWLOC_DECLSPEC int hwloc_bitmap_next (hwloc_const_bitmap_t bitmap, int prev)

Compute the next index in bitmap bitmap which is after index prev.

If prev is -1, the first index is returned.

Returns

-1 if no index with higher index is bitmap.

18.29.4.29 HWLOC_DECLSPEC void hwloc_bitmap_not (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap)

Negate bitmap bitmap and store the result in bitmap res.

res can be the same as bitmap

18.29.4.30 HWLOC_DECLSPEC void hwloc_bitmap_only (hwloc_bitmap_t bitmap, unsigned id)

Empty the bitmap bitmap and add bit id.

18.29.4.31 HWLOC_DECLSPEC void hwloc_bitmap_or (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap2)

Or bitmaps bitmap1 and bitmap2 and store the result in bitmap res.

 $\verb"res" \textbf{ can be the same as} \verb"bitmap" 1 \textbf{ or} \verb"bitmap" 2$

18.29.4.32 HWLOC_DECLSPEC void hwloc_bitmap_set (hwloc_bitmap_t bitmap, unsigned id)

Add index id in bitmap bitmap.

18.29.4.33 HWLOC_DECLSPEC void hwloc_bitmap_set_ith_ulong (hwloc_bitmap_t bitmap, unsigned i, unsigned long mask)

Replace i -th subset of bitmap bitmap with unsigned long mask.

18.29.4.34 HWLOC_DECLSPEC void hwloc_bitmap_set_range (hwloc_bitmap_t bitmap, unsigned begin, int end)

Add indexes from begin to end in bitmap bitmap.

If end is -1, the range is infinite.

18.29.4.35 HWLOC_DECLSPEC void hwloc_bitmap_singlify (hwloc_bitmap_t bitmap)

Keep a single index among those set in bitmap bitmap.

May be useful before binding so that the process does not have a chance of migrating between multiple logical CPUs in the original mask.

```
18.29.4.36 HWLOC_DECLSPEC int hwloc_bitmap_snprintf ( char *_hwloc_restrict buf, size_t buflen, hwloc_const_bitmap_t bitmap )
```

Stringify a bitmap.

Up to buflen characters may be written in buffer buf.

If buflen is 0, buf may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending \0).

```
18.29.4.37 HWLOC_DECLSPEC int hwloc_bitmap_sscanf ( hwloc_bitmap_t bitmap, const char *_hwloc_restrict string )
```

Parse a bitmap string and stores it in bitmap bitmap.

```
18.29.4.38 HWLOC_DECLSPEC int hwloc_bitmap_taskset_asprintf ( char ** strp, hwloc_const_bitmap_t bitmap_t
```

Stringify a bitmap into a newly allocated taskset-specific string.

```
18.29.4.39 HWLOC_DECLSPEC int hwloc_bitmap_taskset_snprintf ( char *_hwloc_restrict buf, size_t buflen, hwloc_const_bitmap_t bitmap_)
```

Stringify a bitmap in the taskset-specific format.

The taskset command manipulates bitmap strings that contain a single (possible very long) hexadecimal number starting with 0x.

Up to buflen characters may be written in buffer buf.

If buflen is 0, buf may safely be NULL.

Returns

the number of character that were actually written if not truncating, or that would have been written (not including the ending 0).

18.29.4.40 HWLOC_DECLSPEC int hwloc_bitmap_taskset_sscanf (hwloc_bitmap_t bitmap, const char *_hwloc_restrict string)

Parse a taskset-specific bitmap string and stores it in bitmap bitmap.

18.29.4.41 HWLOC_DECLSPEC unsigned long hwloc_bitmap_to_ith_ulong (hwloc_const_bitmap_t bitmap, unsigned i)

Convert the i -th subset of bitmap bitmap into unsigned long mask.

18.29 The bitmap API 127

18.29.4.42 HWLOC_DECLSPEC unsigned long hwloc_bitmap_to_ulong (hwloc_const_bitmap_t bitmap)

Convert the beginning part of bitmap bitmap into unsigned long mask.

18.29.4.43 HWLOC_DECLSPEC int hwloc_bitmap_weight (hwloc_const_bitmap_t bitmap)

Compute the "weight" of bitmap bitmap (i.e., number of indexes that are in the bitmap).

Returns

the number of indexes that are in the bitmap.

18.29.4.44 HWLOC_DECLSPEC void hwloc_bitmap_xor (hwloc_bitmap_t res, hwloc_const_bitmap_t bitmap1, hwloc_const_bitmap2)

Xor bitmaps bitmap1 and bitmap2 and store the result in bitmap res.

res can be the same as bitmap1 or bitmap2

18.29.4.45 HWLOC_DECLSPEC void hwloc_bitmap_zero (hwloc_bitmap_t bitmap)

Empty the bitmap bitmap.

18.30 Discovery components

Data Structures

· struct hwloc_disc_component

Typedefs

 typedef enum hwloc_disc_component_type_e hwloc_disc_component_type_t

Enumerations

enum hwloc_disc_component_type_e { HWLOC_DISC_COMPONENT_TYPE_CPU, HWLOC_DISC_COMPONENT_TYPE_MISC }

18.30.1 Detailed Description

18.30.2 Typedef Documentation

18.30.2.1 typedef enum hwloc disc component type e hwloc disc component type t

Discovery component type.

18.30.3 Enumeration Type Documentation

18.30.3.1 enum hwloc_disc_component_type_e

Discovery component type.

Enumerator

HWLOC_DISC_COMPONENT_TYPE_CPU CPU-only discovery through the OS, or generic no-OS support.

HWLOC_DISC_COMPONENT_TYPE_GLOBAL xml, synthetic or custom, platform-specific components such as bgq. Anything the discovers CPU and everything else. No misc backend is expected to complement a global component.

HWLOC_DISC_COMPONENT_TYPE_MISC PCI, etc.

18.31 Discovery backends

Data Structures

· struct hwloc backend

Enumerations

enum hwloc_backend_flag_e { HWLOC_BACKEND_FLAG_NEED_LEVELS }

Functions

- HWLOC_DECLSPEC struct hwloc_backend * hwloc_backend_alloc (struct hwloc_disc_component *component)
- HWLOC_DECLSPEC int hwloc_backend_enable (struct hwloc_topology *topology, struct hwloc_backend *backend)
- HWLOC_DECLSPEC int hwloc_backends_get_obj_cpuset (struct hwloc_backend *caller, struct hwloc_obj *obj, hwloc_bitmap_t cpuset)
- HWLOC_DECLSPEC int hwloc_backends_notify_new_object (struct hwloc_backend *caller, struct hwloc_obj *obj)

18.31.1 Detailed Description

18.31.2 Enumeration Type Documentation

18.31.2.1 enum hwloc backend flag e

Backend flags.

Enumerator

HWLOC_BACKEND_FLAG_NEED_LEVELS Levels should be reconnected before this backend discover() is used.

18.31.3 Function Documentation

18.31.3.1 HWLOC_DECLSPEC struct hwloc_backend* hwloc_backend_alloc (struct hwloc_disc_component * component)

Allocate a backend structure, set good default values, initialize backend->component and topology, etc. The caller will then modify whatever needed, and call hwloc_backend_enable().

18.31.3.2 HWLOC_DECLSPEC int hwloc_backend_enable (struct hwloc_topology * topology, struct hwloc_backend * backend)

Enable a previously allocated and setup backend.

18.31.3.3 HWLOC_DECLSPEC int hwloc_backends_get_obj_cpuset (struct hwloc_backend * caller, struct hwloc_obj * obj, hwloc_bitmap_t cpuset)

Used by backends discovery callbacks to request locality information from others.

Traverse the list of enabled backends until one has a get_obj_cpuset() method, and call it.

18.31.3.4 HWLOC_DECLSPEC int hwloc_backends_notify_new_object (struct hwloc_backend * caller, struct hwloc_obj * obj)

Used by backends discovery callbacks to notify other backends of new objects.

Traverse the list of enabled backends (all but caller) and invoke their notify_new_object() method to notify them that a new object just got added to the topology.

Currently only used for notifying of new PCI device objects.

18.32 Generic components

Data Structures

· struct hwloc_component

Typedefs

typedef enum hwloc_component_type_e hwloc_component_type_t

Enumerations

 enum hwloc_component_type_e { HWLOC_COMPONENT_TYPE_DISC, HWLOC_COMPONENT_TYPE_-XML }

18.32.1 Detailed Description

18.32.2 Typedef Documentation

18.32.2.1 typedef enum hwloc_component_type_e hwloc_component_type_t

Generic component type.

18.32.3 Enumeration Type Documentation

18.32.3.1 enum hwloc_component_type_e

Generic component type.

Enumerator

HWLOC_COMPONENT_TYPE_DISC The data field must point to a struct hwloc_disc_component. **HWLOC_COMPONENT_TYPE_XML** The data field must point to a struct hwloc_xml_component.

18.33 Core functions to be used by components

Typedefs

typedef void(* hwloc_report_error_t)(const char *msg, int line)

Functions

- HWLOC_DECLSPEC struct hwloc_obj * hwloc_insert_object_by_cpuset (struct hwloc_topology *topology, hwloc obj t obj)
- HWLOC_DECLSPEC void hwloc_report_os_error (const char *msg, int line)
- HWLOC_DECLSPEC int hwloc_hide_errors (void)
- HWLOC_DECLSPEC struct hwloc_obj * hwloc_insert_object_by_cpuset (struct hwloc_topology *topology, hwloc_obj_t obj, hwloc_report_error_t report_error)
- HWLOC_DECLSPEC void hwloc_insert_object_by_parent (struct hwloc_topology *topology, hwloc_obj_t parent, hwloc_obj_t obj)
- static __hwloc_inline struct
 hwloc_obj * hwloc_alloc_setup_object (hwloc_obj_type_t type, signed os_index)

18.33.1 Detailed Description

18.33.2 Typedef Documentation

18.33.2.1 typedef void(* hwloc_report_error_t)(const char *msg, int line)

Type of error callbacks during object insertion.

18.33.3 Function Documentation

18.33.3.1 HWLOC_DECLSPEC struct hwloc_obj* hwloc_insert_object_by_cpuset (struct hwloc_topology * topology, hwloc_obj_t obj, hwloc_report_error t report_error)

Add an object to the topology and specify which error callback to use.

Aside from the error callback selection, this function is identical to https://www.nusertobject_by_cpuset()

18.33.3.2 static __hwloc_inline struct hwloc_obj* hwloc_alloc_setup_object (hwloc_obj_type_t type, signed os_index) [static]

Allocate and initialize an object of the given type and physical index.

```
18.33.3.3 HWLOC_DECLSPEC int hwloc_hide_errors ( void )
```

Check whether insertion errors are hidden.

18.33.3.4 HWLOC_DECLSPEC struct hwloc_obj* hwloc_insert_object_by_cpuset (struct hwloc_topology * topology, hwloc_obj_t obj)

Add an object to the topology.

It is sorted along the tree of other objects according to the inclusion of cpusets, to eventually be added as a child of the smallest object including this object.

If the cpuset is empty, the type of the object (and maybe some attributes) must be enough to find where to insert the object. This is especially true for NUMA nodes with memory and no CPUs.

The given object should not have children.

This shall only be called before levels are built.

In case of error, hwloc report os error() is called.

Returns the object on success. Returns NULL and frees obj on error. Returns another object and frees obj if it was merged with an identical pre-existing object.

18.33.3.5 HWLOC_DECLSPEC void hwloc_insert_object_by_parent (struct hwloc_topology * topology, hwloc_obj_t parent, hwloc_obj_t obj)

Insert an object somewhere in the topology.

It is added as the last child of the given parent. The cpuset is completely ignored, so strange objects such as I/O devices should preferably be inserted with this.

The given object may have children.

Remember to call topology_connect() afterwards to fix handy pointers.

18.33.3.6 HWLOC_DECLSPEC void hwloc_report_os_error (const char * msg, int line)

Report an insertion error from a backend.

18.34 Helpers for manipulating glibc sched affinity

Functions

- static __hwloc_inline int hwloc_cpuset_to_glibc_sched_affinity (hwloc_topology_t topology __hwloc_-attribute_unused, hwloc_const_cpuset_t hwlocset, cpu_set_t *schedset, size_t schedsetsize)
- static __hwloc_inline int hwloc_cpuset_from_glibc_sched_affinity (hwloc_topology_t topology __hwloc_-attribute_unused, hwloc_cpuset_t hwlocset, const cpu_set_t *schedset, size_t schedsetsize)

18.34.1 Detailed Description

18.34.2 Function Documentation

```
18.34.2.1 static __hwloc_inline int hwloc_cpuset_from_glibc_sched_affinity ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_cpuset_t hwlocset, const cpu_set_t * schedset, size_t schedsetsize ) [static]
```

Convert glibc sched affinity CPU set schedset into hwloc CPU set.

This function may be used before calling sched_setaffinity or any other function that takes a cpu_set_t as input parameter.

schedsetsize should be sizeof(cpu_set_t) unless schedset was dynamically allocated with CPU_ALLOC

```
18.34.2.2 static __hwloc_inline int hwloc_cpuset_to_glibc_sched_affinity ( hwloc_topology_t topology __hwloc_attribute_unused, hwloc_const_cpuset_t hwlocset, cpu_set_t * schedset, size_t schedsetsize ) [static]
```

Convert hwloc CPU set toposet into glibc sched affinity CPU set schedset.

This function may be used before calling sched_setaffinity or any other function that takes a cpu_set_t as input parameter.

schedsetsize should be sizeof(cpu_set_t) unless schedset was dynamically allocated with CPU_ALLOC

18.35 Linux-only helpers

Functions

- HWLOC_DECLSPEC int hwloc_linux_parse_cpumap_file (FILE *file, hwloc_cpuset_t set)
- HWLOC_DECLSPEC int hwloc_linux_set_tid_cpubind (hwloc_topology_t topology, pid_t tid, hwloc_const_cpuset_t set)
- HWLOC_DECLSPEC int hwloc_linux_get_tid_cpubind (hwloc_topology_t topology, pid_t tid, hwloc_cpuset_t set)

18.35.1 Detailed Description

This includes helpers for manipulating linux kernel cpumap files, and hwloc equivalents of the Linux sched_setaffinity and sched_getaffinity system calls.

18.35.2 Function Documentation

18.35.2.1 HWLOC_DECLSPEC int hwloc_linux_get_tid_cpubind (hwloc_topology_t topology, pid_t tid, hwloc_cpuset_t set)

Get the current binding of thread tid.

The behavior is exactly the same as the Linux sched_getaffinity system call, but uses a hwloc cpuset.

18.35.2.2 HWLOC_DECLSPEC int hwloc_linux_parse_cpumap_file (FILE * file, hwloc_cpuset_t set)

Convert a linux kernel cpumap file file into hwloc CPU set.

Might be used when reading CPU set from sysfs attributes such as topology and caches for processors, or local_cpus for devices.

18.35.2.3 HWLOC_DECLSPEC int hwloc_linux_set_tid_cpubind (hwloc_topology_t topology, pid_t tid, hwloc_const_cpuset_t set)

Bind a thread tid on cpus given in cpuset set.

The behavior is exactly the same as the Linux sched_setaffinity system call, but uses a hwloc cpuset.

18.36 Helpers for manipulating Linux libnuma unsigned long masks

Functions

- static __hwloc_inline int hwloc_cpuset_to_linux_libnuma_ulongs (hwloc_topology_t topology, hwloc_const_-cpuset_t cpuset, unsigned long *mask, unsigned long *maxnode)
- static __hwloc_inline int hwloc_nodeset_to_linux_libnuma_ulongs (hwloc_topology_t topology, hwloc_const_nodeset_t nodeset, unsigned long *mask, unsigned long *maxnode)
- static __hwloc_inline int hwloc_cpuset_from_linux_libnuma_ulongs (hwloc_topology_t topology, hwloc_cpuset_t cpuset, const unsigned long *mask, unsigned long maxnode)
- static __hwloc_inline int hwloc_nodeset_from_linux_libnuma_ulongs (hwloc_topology_t topology, hwloc_nodeset_t nodeset, const unsigned long *mask, unsigned long maxnode)

18.36.1 Detailed Description

18.36.2 Function Documentation

18.36.2.1 static __hwloc_inline int hwloc_cpuset_from_linux_libnuma_ulongs (hwloc_topology_t topology, hwloc_cpuset_t cpuset, const unsigned long * mask, unsigned long maxnode) [static]

Convert the array of unsigned long mask into hwloc CPU set.

mask is a array of unsigned long that will be read. maxnode contains the maximal node number that may be read in mask.

This function may be used after calling get_mempolicy or any other function that takes an array of unsigned long as output parameter (and possibly a maximal node number as input parameter).

```
18.36.2.2 static __hwloc_inline int hwloc_cpuset_to_linux_libnuma_ulongs ( hwloc_topology_t topology, hwloc_const_cpuset_t cpuset, unsigned long * mask, unsigned long * maxnode ) [static]
```

Convert hwloc CPU set cpuset into the array of unsigned long mask.

mask is the array of unsigned long that will be filled. maxnode contains the maximal node number that may be stored in mask. maxnode will be set to the maximal node number that was found, plus one.

This function may be used before calling set_mempolicy, mbind, migrate_pages or any other function that takes an array of unsigned long and a maximal node number as input parameter.

```
18.36.2.3 static __hwloc_inline int hwloc_nodeset_from_linux_libnuma_ulongs ( hwloc_topology_t topology, hwloc_nodeset_t nodeset, const unsigned long * mask, unsigned long maxnode ) [static]
```

Convert the array of unsigned long mask into hwloc NUMA node set.

mask is a array of unsigned long that will be read. maxnode contains the maximal node number that may be read in mask.

This function may be used after calling get_mempolicy or any other function that takes an array of unsigned long as output parameter (and possibly a maximal node number as input parameter).

```
18.36.2.4 static __hwloc_inline int hwloc_nodeset_to_linux_libnuma_ulongs ( hwloc_topology_t topology, hwloc_const_nodeset_t nodeset, unsigned long * mask, unsigned long * maxnode ) [static]
```

Convert hwloc NUMA node set nodeset into the array of unsigned long mask.

mask is the array of unsigned long that will be filled. maxnode contains the maximal node number that may be stored in mask. maxnode will be set to the maximal node number that was found, plus one.

This function may be used before calling set_mempolicy, mbind, migrate_pages or any other function that takes an array of unsigned long and a maximal node number as input parameter.

18.37 Helpers for manipulating Linux libnuma bitmask

Functions

- static __hwloc_inline struct
 bitmask * hwloc_cpuset_to_linux_libnuma_bitmask (hwloc_topology_t topology, hwloc_const_cpuset_t cpuset) __hwloc_attribute_malloc
- static __hwloc_inline struct
 bitmask * hwloc_nodeset_to_linux_libnuma_bitmask (hwloc_topology_t topology, hwloc_const_nodeset_t nodeset)
 hwloc attribute malloc
- static __hwloc_inline int hwloc_cpuset_from_linux_libnuma_bitmask (hwloc_topology_t topology, hwloc_cpuset_t cpuset, const struct bitmask *bitmask)
- static __hwloc_inline int hwloc_nodeset_from_linux_libnuma_bitmask (hwloc_topology_t topology, hwloc_nodeset_t nodeset, const struct bitmask *bitmask)

18.37.1 Detailed Description

18.37.2 Function Documentation

18.37.2.1 static __hwloc_inline int hwloc_cpuset_from_linux_libnuma_bitmask (hwloc_topology_t topology, hwloc_cpuset_t cpuset, const struct bitmask * bitmask *) [static]

Convert libnuma bitmask bitmask into hwloc CPU set cpuset.

This function may be used after calling many numa functions that use a struct bitmask as an output parameter.

```
18.37.2.2 static __hwloc_inline struct bitmask * hwloc_cpuset_to_linux_libnuma_bitmask ( hwloc_topology_t topology, hwloc_const_cpuset_t cpuset ) [static]
```

Convert hwloc CPU set cpuset into the returned libnuma bitmask.

The returned bitmask should later be freed with numa_bitmask_free.

This function may be used before calling many numa_functions that use a struct bitmask as an input parameter.

Returns

newly allocated struct bitmask.

```
18.37.2.3 static __hwloc_inline int hwloc_nodeset_from_linux_libnuma_bitmask ( hwloc_topology_t topology, hwloc_nodeset_t nodeset, const struct bitmask * bitmask ) [static]
```

Convert libnuma bitmask bitmask into hwloc NUMA node set nodeset.

This function may be used after calling many numa_functions that use a struct bitmask as an output parameter.

```
18.37.2.4 static __hwloc_inline struct bitmask * hwloc_nodeset_to_linux_libnuma_bitmask ( hwloc_topology_t topology, hwloc_const_nodeset_t nodeset ) [static]
```

Convert hwloc NUMA node set nodeset into the returned libnuma bitmask.

The returned bitmask should later be freed with numa bitmask free.

This function may be used before calling many numa_functions that use a struct bitmask as an input parameter.

Returns

newly allocated struct bitmask.

18.38 OpenCL Specific Functions

Functions

- static __hwloc_inline int hwloc_opencl_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, cl_device_id device __hwloc_attribute_unused, hwloc_cpuset_t set)
- static __hwloc_inline hwloc_obj_t hwloc_opencl_get_device_osdev_by_index (hwloc_topology_t topology, unsigned platform_index, unsigned device_index)
- static __hwloc_inline hwloc_obj_t hwloc_opencl_get_device_osdev (hwloc_topology_t topology __hwloc_-attribute_unused, cl_device_id device __hwloc_attribute_unused)

18.38.1 Detailed Description

18.38.2 Function Documentation

```
18.38.2.1 static __hwloc_inline int hwloc_opencl_get_device_cpuset ( hwloc_topology_t topology hwloc attribute unused, cl device id device hwloc attribute unused, hwloc cpuset t set ) [static]
```

Get the CPU set of logical processors that are physically close to OpenCL device device.

Return the CPU set describing the locality of the OpenCL device device.

Topology topology and device device must match the local machine. I/O devices detection and the OpenCL component are not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see hwloc_opencl_get_device_osdev, and hwloc_opencl_get_device_osdev. If more information about the device is needed, OS objects should be used instead, see hwloc_opencl_get_device_osdev. If more information about the device is needed, OS objects should be used instead, see hwloc_opencl_get_device_osdev. If more information about the device is needed, OS objects should be used instead, see hwloc_opencl_get_device_osdev. If more information about the device is needed, OS objects should be used instead, see hwloc_opencl_get_device_osdev. If more information about the device is needed, or see hwloc_opencl_get_device_osdev. If more information about the device is needed, or see hwloc_opencl_get_device_osdev. If more information about the device is needed.

This function is currently only implemented in a meaningful way for Linux with the AMD OpenCL implementation; other systems will simply get a full cpuset.

```
18.38.2.2 static __hwloc_inline hwloc_obj_t hwloc_opencl_get_device_osdev ( hwloc_topology_t topology __hwloc_attribute_unused, cl_device_id device __hwloc_attribute_unused ) [static]
```

Get the hwloc OS device object corresponding to OpenCL device device.

Return the hwloc OS device object that describes the given OpenCL device device. Return NULL if there is none.

Topology topology and device device must match the local machine. I/O devices detection and the OpenCL component must be enabled in the topology. If not, the locality of the object may still be found using hwloc_opencl_get_device_cpuset().

Note

The corresponding hwloc PCI device may be found by looking at the result parent pointer.

```
18.38.2.3 static __hwloc_inline hwloc_obj_t hwloc_opencl_get_device_osdev_by_index ( hwloc_topology_t topology, unsigned platform_index, unsigned device_index ) [static]
```

Get the hwloc OS device object corresponding to the OpenCL device for the given indexes.

Return the OS device object describing the OpenCL device whose platform index is $platform_index$, and whose device index within this platform if $device_index$. Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the OpenCL component must be enabled in the topology.

Note

18.39 CUDA Driver API Specific Functions

Functions

- static __hwloc_inline int hwloc_cuda_get_device_pci_ids (hwloc_topology_t topology __hwloc_attribute_unused, CUdevice cudevice, int *domain, int *bus, int *dev)
- static __hwloc_inline int hwloc_cuda_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, CUdevice cudevice, hwloc_cpuset_t set)
- static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_pcidev (hwloc_topology_t topology, CUdevice cudevice)
- static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_osdev (hwloc_topology_t topology, CUdevice cudevice)
- static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_osdev_by_index (hwloc_topology_t topology, unsigned idx)

18.39.1 Detailed Description

18.39.2 Function Documentation

Get the CPU set of logical processors that are physically close to device cudevice.

Return the CPU set describing the locality of the CUDA device cudevice.

Topology topology and device cudevice must match the local machine. I/O devices detection and the CUDA component are not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see hwloc_cuda_get_device_osdev () and hwloc_cuda_get_device_osdev ().

This function is currently only implemented in a meaningful way for Linux; other systems will simply get a full cpuset.

```
18.39.2.2 static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_osdev ( hwloc_topology_t topology, CUdevice cudevice ) [static]
```

Get the hwloc OS device object corresponding to CUDA device cudevice.

Return the hwloc OS device object that describes the given CUDA device cudevice. Return NULL if there is none.

Topology topology and device cudevice must match the local machine. I/O devices detection and the NVML component must be enabled in the topology. If not, the locality of the object may still be found using hwloc_cuda_get_device_cpuset().

Note

The corresponding hwloc PCI device may be found by looking at the result parent pointer.

```
18.39.2.3 static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_osdev_by_index ( hwloc_topology_t topology, unsigned idx ) [static]
```

Get the hwloc OS device object corresponding to the CUDA device whose index is idx.

Return the OS device object describing the CUDA device whose index is idx. Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the CUDA component must be enabled in the topology.

Note

The corresponding PCI device object can be obtained by looking at the OS device parent object. This function is identical to hwloc_cudart_get_device_osdev_by_index().

Return the domain, bus and device IDs of the CUDA device cudevice.

Device cudevice must match the local machine.

18.39.2.5 static __hwloc_inline hwloc_obj_t hwloc_cuda_get_device_pcidev (hwloc_topology_t topology, CUdevice cudevice) [static]

Get the hwloc PCI device object corresponding to the CUDA device cudevice.

Return the PCI device object describing the CUDA device cudevice. Return NULL if there is none.

Topology topology and device cudevice must match the local machine. I/O devices detection must be enabled in topology topology. The CUDA component is not needed in the topology.

18.40 CUDA Runtime API Specific Functions

Functions

- static __hwloc_inline int hwloc_cudart_get_device_pci_ids (hwloc_topology_t topology __hwloc_attribute_-unused, int idx, int *domain, int *bus, int *dev)
- static __hwloc_inline int hwloc_cudart_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_-unused, int idx, hwloc_cpuset_t set)
- static hwloc inline hwloc obj t hwloc cudart get device pcidev (hwloc topology t topology, int idx)
- static __hwloc_inline hwloc_obj_t hwloc_cudart_get_device_osdev_by_index (hwloc_topology_t topology, unsigned idx)

18.40.1 Detailed Description

18.40.2 Function Documentation

```
18.40.2.1 static __hwloc_inline int hwloc_cudart_get_device_cpuset ( hwloc_topology_t topology __hwloc_attribute_unused, int idx, hwloc_cpuset_t set ) [static]
```

Get the CPU set of logical processors that are physically close to device idx.

Return the CPU set describing the locality of the CUDA device whose index is idx.

Topology topology and device idx must match the local machine. I/O devices detection and the CUDA component are not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see <a href="https://hww.needed.com/hww.needed.co

This function is currently only implemented in a meaningful way for Linux; other systems will simply get a full cpuset.

```
18.40.2.2 static __hwloc_inline hwloc_obj_t hwloc_cudart_get_device_osdev_by_index ( hwloc_topology_t topology, unsigned idx ) [static]
```

Get the hwloc OS device object corresponding to the CUDA device whose index is idx.

Return the OS device object describing the CUDA device whose index is idx. Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the CUDA component must be enabled in the topology. If not, the locality of the object may still be found using $hwloc_cudart_get_device_cpuset()$.

Note

The corresponding PCI device object can be obtained by looking at the OS device parent object. This function is identical to hwloc_cuda_get_device_osdev_by_index().

```
18.40.2.3 static __hwloc_inline int hwloc_cudart_get_device_pci_ids ( hwloc_topology_t topology __hwloc_attribute_unused, int idx, int * domain, int * bus, int * dev ) [static]
```

Return the domain, bus and device IDs of the CUDA device whose index is idx.

Device index idx must match the local machine.

18.40.2.4 static __hwloc_inline hwloc_obj_t hwloc_cudart_get_device_pcidev (hwloc_topology_t topology, int idx) [static]

Get the hwloc PCI device object corresponding to the CUDA device whose index is idx.

Return the PCI device object describing the CUDA device whose index is idx. Return NULL if there is none.

Topology topology and device idx must match the local machine. I/O devices detection must be enabled in topology topology. The CUDA component is not needed in the topology.

18.41 NVIDIA Management Library Specific Functions

Functions

- static __hwloc_inline int hwloc_nvml_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_-unused, nvmlDevice_t device, hwloc_cpuset_t set)
- static __hwloc_inline hwloc_obj_t hwloc_nvml_get_device_osdev_by_index (hwloc_topology_t topology, unsigned idx)
- static __hwloc_inline hwloc_obj_t hwloc_nvml_get_device_osdev (hwloc_topology_t topology, nvmlDevice_t device)

18.41.1 Detailed Description

18.41.2 Function Documentation

18.41.2.1 static __hwloc_inline int hwloc_nvml_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, nvmlDevice_t device, hwloc_cpuset_t set) [static]

Get the CPU set of logical processors that are physically close to NVML device device.

Return the CPU set describing the locality of the NVML device device.

Topology topology and device device must match the local machine. I/O devices detection and the NVML component are not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see hwloc nvml get device osdev() and hwloc nvml get device osdev by index().

This function is currently only implemented in a meaningful way for Linux; other systems will simply get a full cpuset.

```
18.41.2.2 static __hwloc_inline hwloc_obj_t hwloc_nvml_get_device_osdev ( hwloc_topology_t topology, nvmlDevice_t device ) [static]
```

Get the hwloc OS device object corresponding to NVML device device.

Return the hwloc OS device object that describes the given NVML device device. Return NULL if there is none.

Topology topology and device device must match the local machine. I/O devices detection and the NVML component must be enabled in the topology. If not, the locality of the object may still be found using hwloc_nvml_get_device_cpuset().

Note

The corresponding hwloc PCI device may be found by looking at the result parent pointer.

```
18.41.2.3 static __hwloc_inline hwloc_obj_t hwloc_nvml_get_device_osdev_by_index ( hwloc_topology_t topology, unsigned idx ) [static]
```

Get the hwloc OS device object corresponding to the NVML device whose index is idx.

Return the OS device object describing the NVML device whose index is idx. Returns NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the NVML component must be enabled in the topology.

Note

18.42 OpenGL display specific functions

Functions

- static __hwloc_inline hwloc_obj_t hwloc_gl_get_display_osdev_by_port_device (hwloc_topology_t topology, unsigned port, unsigned device)
- static __hwloc_inline hwloc_obj_t hwloc_gl_get_display_osdev_by_name (hwloc_topology_t topology, const char *name)
- static __hwloc_inline int hwloc_gl_get_display_by_osdev (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj_t osdev, unsigned *port, unsigned *device)

18.42.1 Detailed Description

18.42.2 Function Documentation

18.42.2.1 static __hwloc_inline int hwloc_gl_get_display_by_osdev (hwloc_topology_t topology __hwloc_attribute_unused, hwloc_obj t osdev, unsigned * port, unsigned * device) [static]

Get the OpenGL display port and device corresponding to the given hwloc OS object.

Return the OpenGL display port (server) in port and device (screen) in screen that correspond to the given hwloc OS device object. Return -1 if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the GL component must be enabled in the topology.

18.42.2.2 static __hwloc_inline hwloc_obj_t hwloc_gl_get_display_osdev_by_name (hwloc_topology_t topology, const char * name) [static]

Get the hwloc OS device object corresponding to the OpenGL display given by name.

Return the OS device object describing the OpenGL display whose name is name, built as ":port.device" such as ":0.0". Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the GL component must be enabled in the topology.

Note

The corresponding PCI device object can be obtained by looking at the OS device parent object.

18.42.2.3 static __hwloc_inline hwloc_obj_t hwloc_gl_get_display_osdev_by_port_device (hwloc_topology_t topology, unsigned port, unsigned device) [static]

Get the hwloc OS device object corresponding to the OpenGL display given by port and device index.

Return the OS device object describing the OpenGL display whose port (server) is port and device (screen) is device. Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection and the GL component must be enabled in the topology.

Note

18.43 Intel Xeon Phi (MIC) Specific Functions

Functions

- static __hwloc_inline int hwloc_intel_mic_get_device_cpuset (hwloc_topology_t topology __hwloc_attributeunused, int idx __hwloc_attribute_unused, hwloc_cpuset_t set)
- static __hwloc_inline hwloc_obj_t hwloc_intel_mic_get_device_osdev_by_index (hwloc_topology_t topology, unsigned idx)

18.43.1 Detailed Description

18.43.2 Function Documentation

```
18.43.2.1 static __hwloc_inline int hwloc_intel_mic_get_device_cpuset ( hwloc_topology_t topology __hwloc_attribute_unused, int idx __hwloc_attribute_unused, hwloc_cpuset_t set ) [static]
```

Get the CPU set of logical processors that are physically close to MIC device whose index is idx.

Return the CPU set describing the locality of the MIC device whose index is idx.

Topology topology and device index idx must match the local machine. I/O devices detection is not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see <a href="https://hww.needed.com/hww.needed.co

This function is currently only implemented in a meaningful way for Linux; other systems will simply get a full cpuset.

```
18.43.2.2 static __hwloc_inline hwloc_obj_t hwloc_intel_mic_get_device_osdev_by_index ( hwloc_topology_t topology, unsigned idx ) [static]
```

Get the hwloc OS device object corresponding to the MIC device for the given index.

Return the OS device object describing the MIC device whose index is idx. Return NULL if there is none.

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection must be enabled in the topology.

Note

18.44 OpenFabrics-Specific Functions

Functions

- static __hwloc_inline int hwloc_ibv_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_-unused, struct ibv device *ibdev, hwloc cpuset t set)
- static __hwloc_inline hwloc_obj_t hwloc_ibv_get_device_osdev_by_name (hwloc_topology_t topology, const char *ibname)
- static __hwloc_inline hwloc_obj_t hwloc_ibv_get_device_osdev (hwloc_topology_t topology, struct ibv_device *ibdev)

18.44.1 Detailed Description

18.44.2 Function Documentation

18.44.2.1 static __hwloc_inline int hwloc_ibv_get_device_cpuset (hwloc_topology_t topology __hwloc_attribute_unused, struct ibv_device * ibdev, hwloc_cpuset_t set) [static]

Get the CPU set of logical processors that are physically close to device ibdev.

Return the CPU set describing the locality of the OpenFabrics device ibdev.

Topology topology and device ibdev must match the local machine. I/O devices detection is not needed in the topology.

The function only returns the locality of the device. If more information about the device is needed, OS objects should be used instead, see hwloc_ibv_get_device_osdev, and hwloc_ibv_get_device_osdev, by _name().

This function is currently only implemented in a meaningful way for Linux; other systems will simply get a full cpuset.

```
18.44.2.2 static __hwloc_inline hwloc_obj_t hwloc_ibv_get_device_osdev ( hwloc_topology_t topology, struct ibv_device * ibdev ) [static]
```

Get the hwloc OS device object corresponding to the OpenFabrics device ibdev.

Return the OS device object describing the OpenFabrics device ibdev. Returns NULL if there is none.

Topology topology and device ibdev must match the local machine. I/O devices detection must be enabled in the topology. If not, the locality of the object may still be found using hwloc_ibv_get_device_cpuset().

Note

The corresponding PCI device object can be obtained by looking at the OS device parent object.

```
18.44.2.3 static __hwloc_inline hwloc_obj_t hwloc_ibv_get_device_osdev_by_name ( hwloc_topology_t topology, const char * ibname ) [static]
```

Get the hwloc OS device object corresponding to the OpenFabrics device named ibname.

Return the OS device object describing the OpenFabrics device whose name is ibname. Returns NULL if there is none. The name ibname is usually obtained from ibv_get_device_name().

The topology topology does not necessarily have to match the current machine. For instance the topology may be an XML import of a remote host. I/O devices detection must be enabled in the topology.

Note

18.45 Myrinet Express-Specific Functions

Functions

- static __hwloc_inline int hwloc_mx_board_get_device_cpuset (hwloc_topology_t topology, unsigned id, hwloc cpuset t set)
- static __hwloc_inline int hwloc_mx_endpoint_get_device_cpuset (hwloc_topology_t topology, mx_endpoint_t endpoint, hwloc_cpuset_t set)

18.45.1 Detailed Description

18.45.2 Function Documentation

18.45.2.1 static __hwloc_inline int hwloc_mx_board_get_device_cpuset (hwloc_topology_t topology, unsigned id, hwloc_cpuset_t set) [static]

Get the CPU set of logical processors that are physically close the MX board id.

Return the CPU set describing the locality of the Myrinet Express board whose index is id.

Topology topology and device id must match the local machine. I/O devices detection is not needed in the topology.

The function only returns the locality of the device. No additional information about the device is available.

18.45.2.2 static __hwloc_inline int hwloc_mx_endpoint_get_device_cpuset (hwloc_topology_t topology, mx_endpoint_t endpoint, hwloc_cpuset_t set) [static]

Get the CPU set of logical processors that are physically close the MX endpoint endpoint.

Return the CPU set describing the locality of the Myrinet Express board that runs the MX endpoint endpoint.

Topology topology and device id must match the local machine. I/O devices detection is not needed in the topology.

The function only returns the locality of the endpoint. No additional information about the endpoint or device is available.

Chapter 19

Data Structure Documentation

19.1 hwloc_backend Struct Reference

#include <plugins.h>

Data Fields

- · unsigned long flags
- int is_custom
- int is_thissystem
- void * private_data
- void(* disable)(struct hwloc backend *backend)
- int(* discover)(struct hwloc_backend *backend)
- int(* get_obj_cpuset)(struct hwloc_backend *backend, struct hwloc_backend *caller, struct hwloc_obj *obj, hwloc_bitmap_t cpuset)
- int(* notify_new_object)(struct hwloc_backend *backend, struct hwloc_backend *caller, struct hwloc_obj *obj)

19.1.1 Detailed Description

Discovery backend structure.

A backend is the instantiation of a discovery component. When a component gets enabled for a topology, its instantiate() callback creates a backend.

hwloc_backend_alloc() initializes all fields to default values that the component may change (except "component" and "next") before enabling the backend with hwloc backend enable().

19.1.2 Field Documentation

19.1.2.1 void(* hwloc_backend::disable)(struct hwloc_backend *backend)

Callback for freeing the private data. May be NULL.

19.1.2.2 int(* hwloc_backend::discover)(struct hwloc_backend *backend)

Main discovery callback. returns > 0 if it modified the topology tree, -1 on error, 0 otherwise. May be NULL if type is HWLOC_DISC_COMPONENT_TYPE_MISC.

19.1.2.3 unsigned long hwloc_backend::flags

Backend flags, as an OR'ed set of HWLOC_BACKEND_FLAG_*.

19.1.2.4 int(* hwloc_backend::get_obj_cpuset)(struct hwloc_backend *backend, struct hwloc_backend *caller, struct hwloc_obj *obj, hwloc_bitmap_t cpuset)

Callback used by the PCI backend to retrieve the locality of a PCI object from the OS/cpu backend. May be NULL.

19.1.2.5 int hwloc backend::is custom

Backend-specific 'is_custom' property. Shortcut on !strcmp(..->component->name, "custom"). Only the custom component should touch this.

19.1.2.6 int hwloc_backend::is_thissystem

Backend-specific 'is_thissystem' property. Set to 0 or 1 if the backend should enforce the thissystem flag when it gets enabled. Set to -1 if the backend doesn't care (default).

19.1.2.7 int(* hwloc_backend::notify_new_object)(struct hwloc_backend *backend, struct hwloc_backend *caller, struct hwloc_obj *obj)

Callback called by backends to notify this backend that a new object was added. returns > 0 if it modified the topology tree, 0 otherwise. May be NULL.

19.1.2.8 void* hwloc_backend::private_data

Backend private data, or NULL if none.

The documentation for this struct was generated from the following file:

• plugins.h

19.2 hwloc_obj_attr_u::hwloc_bridge_attr_s Struct Reference

```
#include <hwloc.h>
```

} downstream

Data Fields

```
    union {
        struct hwloc_pcidev_attr_s pci
    } upstream
    hwloc_obj_bridge_type_t upstream_type
    union {
        struct {
            unsigned short domain
            unsigned char secondary_bus
            unsigned char subordinate_bus
        } pci
```

- hwloc_obj_bridge_type_t downstream_type
- · unsigned depth

19.2.1 Detailed Description

Bridge specific Object Attribues.

19.2.2 Field Documentation

- 19.2.2.1 unsigned hwloc_obj_attr_u::hwloc_bridge_attr_s::depth
- 19.2.2.2 unsigned short hwloc_obj_attr_u::hwloc_bridge_attr_s::domain
- 19.2.2.3 union { ... } hwloc_obj_attr_u::hwloc_bridge_attr_s::downstream
- 19.2.2.4 hwloc_obj_bridge_type_t hwloc_obj_attr_u::hwloc_bridge_attr_s::downstream_type
- 19.2.2.5 struct { ... } hwloc_obj_attr_u::hwloc_bridge_attr_s::pci
- 19.2.2.6 struct hwloc_pcidev_attr_s hwloc_obj_attr_u::hwloc_bridge_attr_s::pci
- 19.2.2.7 unsigned char hwloc_obj_attr_u::hwloc_bridge_attr_s::secondary_bus
- 19.2.2.8 unsigned char hwloc_obj_attr_u::hwloc_bridge_attr_s::subordinate_bus
- 19.2.2.9 union { ... } hwloc_obj_attr_u::hwloc_bridge_attr_s::upstream
- 19.2.2.10 hwloc_obj_bridge_type_t hwloc_obj_attr_u::hwloc_bridge_attr_s::upstream_type

The documentation for this struct was generated from the following file:

hwloc.h

19.3 hwloc_obj_attr_u::hwloc_cache_attr_s Struct Reference

#include <hwloc.h>

Data Fields

- hwloc_uint64_t size
- · unsigned depth
- · unsigned linesize
- · int associativity
- hwloc_obj_cache_type_t type

19.3.1 Detailed Description

Cache-specific Object Attributes.

19.3.2 Field Documentation

19.3.2.1 int hwloc_obj_attr_u::hwloc_cache_attr_s::associativity

Ways of associativity, -1 if fully associative, 0 if unknown.

19.3.2.2 unsigned hwloc_obj_attr_u::hwloc_cache_attr_s::depth

Depth of cache (e.g., L1, L2, ...etc.)

19.3.2.3 unsigned hwloc_obj_attr_u::hwloc_cache_attr_s::linesize

Cache-line size in bytes. 0 if unknown.

19.3.2.4 hwloc_uint64_t hwloc_obj_attr_u::hwloc_cache_attr_s::size

Size of cache in bytes.

19.3.2.5 hwloc_obj_cache_type_t hwloc_obj_attr_u::hwloc_cache_attr_s::type

Cache type.

The documentation for this struct was generated from the following file:

· hwloc.h

19.4 hwloc_component Struct Reference

```
#include <plugins.h>
```

Data Fields

- · unsigned abi
- hwloc_component_type_t type
- unsigned long flags
- void * data

19.4.1 Detailed Description

Generic component structure.

Generic components structure, either statically listed by configure in static-components.h or dynamically loaded as a plugin.

19.4.2 Field Documentation

19.4.2.1 unsigned hwloc_component::abi

Component ABI version, set to HWLOC_COMPONENT_ABI.

19.4.2.2 void* hwloc_component::data

Component data, pointing to a struct hwloc_disc_component or struct hwloc_xml_component.

19.4.2.3 unsigned long hwloc_component::flags

Component flags, unused for now.

19.4.2.4 hwloc component type t hwloc_component::type

Component type.

The documentation for this struct was generated from the following file:

plugins.h

19.5 hwloc_disc_component Struct Reference

```
#include <plugins.h>
```

Data Fields

- hwloc_disc_component_type_t type
- · const char * name
- unsigned excludes
- struct hwloc_backend *(* instantiate)(struct hwloc_disc_component *component, const void *data1, const void *data2, const void *data3)
- · unsigned priority

19.5.1 Detailed Description

Discovery component structure.

This is the major kind of components, taking care of the discovery. They are registered by generic components, either statically-built or as plugins.

19.5.2 Field Documentation

19.5.2.1 unsigned hwloc_disc_component::excludes

Component types to exclude, as an OR'ed set of HWLOC_DISC_COMPONENT_TYPE_*.

For a GLOBAL component, this usually includes all other types (\sim 0).

Other components only exclude types that may bring conflicting topology information. MISC components should likely not be excluded since they usually bring non-primary additional information.

19.5.2.2 struct hwloc_backend*(* hwloc_disc_component::instantiate)(struct hwloc_disc_component *component, const void *data1, const void *data2, const void *data3)

19.5.2.3 const char* hwloc_disc_component::name

Name. If this component is built as a plugin, this name does not have to match the plugin filename.

19.5.2.4 unsigned hwloc_disc_component::priority

Component priority. Used to sort topology->components, higher priority first. Also used to decide between two components with the same name.

Usual values are 50 for native OS (or platform) components, 45 for x86, 40 for no-OS fallback, 30 for global components (xml/synthetic/custom), 20 for pci, 10 for other misc components (opencl etc.).

19.5.2.5 hwloc_disc_component_type_t hwloc_disc_component::type

Discovery component type.

The documentation for this struct was generated from the following file:

• plugins.h

19.6 hwloc distances s Struct Reference

#include <hwloc.h>

Data Fields

- · unsigned relative depth
- unsigned nbobjs
- float * latency
- · float latency_max
- · float latency_base

19.6.1 Detailed Description

Distances between objects.

One object may contain a distance structure describing distances between all its descendants at a given relative depth. If the containing object is the root object of the topology, then the distances are available for all objects in the machine.

If the latency pointer is not NULL, the pointed array contains memory latencies (non-zero values), as defined by the ACPI SLIT specification.

In the future, some other types of distances may be considered. In these cases, latency may be NULL.

19.6.2 Field Documentation

19.6.2.1 float* hwloc_distances_s::latency

Matrix of latencies between objects, stored as a one-dimension array. May be NULL if the distances considered here are not latencies. Values are normalized to get 1.0 as the minimal value in the matrix. Latency from i-th to j-th object is stored in slot i*nbobjs+j.

19.6.2.2 float hwloc_distances_s::latency_base

The multiplier that should be applied to latency matrix to retrieve the original OS-provided latencies. Usually 10 on Linux since ACPI SLIT uses 10 for local latency.

19.6.2.3 float hwloc_distances_s::latency_max

The maximal value in the latency matrix.

19.6.2.4 unsigned hwloc_distances_s::nbobjs

Number of objects considered in the matrix. It is the number of descendant objects at relative_depth below the containing object. It corresponds to the result of hwloc_get_nbobjs_inside_cpuset_by_depth.

19.6.2.5 unsigned hwloc_distances_s::relative_depth

Relative depth of the considered objects below the object containing this distance information.

The documentation for this struct was generated from the following file:

· hwloc.h

19.7 hwloc_obj_attr_u::hwloc_group_attr_s Struct Reference

#include <hwloc.h>

Data Fields

· unsigned depth

19.7.1 Detailed Description

Group-specific Object Attributes.

19.7.2 Field Documentation

19.7.2.1 unsigned hwloc_obj_attr_u::hwloc_group_attr_s::depth

Depth of group object.

The documentation for this struct was generated from the following file:

· hwloc.h

19.8 hwloc_obj Struct Reference

#include <hwloc.h>

Data Fields

- hwloc_obj_type_t type
- · unsigned os_index
- char * name
- struct hwloc_obj_memory_s memory
- union hwloc_obj_attr_u * attr
- unsigned depth
- unsigned logical index
- · signed os_level
- struct hwloc_obj * next_cousin
- struct hwloc_obj * prev_cousin
- struct hwloc_obj * parent
- · unsigned sibling rank
- struct hwloc_obj * next_sibling
- struct hwloc_obj * prev_sibling
- · unsigned arity
- struct hwloc obj ** children
- struct hwloc obj * first child
- struct hwloc_obj * last_child
- void * userdata
- hwloc_cpuset_t cpuset
- hwloc_cpuset_t complete_cpuset
- hwloc_cpuset_t online_cpuset
- hwloc_cpuset_t allowed_cpuset
- · hwloc nodeset t nodeset
- hwloc_nodeset_t complete_nodeset
- · hwloc nodeset tallowed nodeset
- struct hwloc distances s ** distances
- unsigned distances_count
- struct hwloc_obj_info_s * infos
- unsigned infos_count
- int symmetric_subtree

19.8.1 Detailed Description

Structure of a topology object.

Applications must not modify any field except hwloc_obj.userdata.

19.8.2 Field Documentation

19.8.2.1 hwloc_cpuset_t hwloc_obj::allowed_cpuset

The CPU set of allowed logical processors.

This includes the CPUs contained in this object which are allowed for binding, i.e. passing them to the hwloc binding functions should not return permission errors. This is usually restricted by administration rules. Some of them may however be offline so binding to them may still not be possible, see online_cpuset.

Note

Its value must not be changed, hwloc bitmap dup must be used instead.

19.8.2.2 hwloc_nodeset_t hwloc_obj::allowed_nodeset

The set of allowed NUMA memory nodes.

This includes the NUMA memory nodes contained in this object which are allowed for memory allocation, i.e. passing them to NUMA node-directed memory allocation should not return permission errors. This is usually restricted by administration rules.

If there are no NUMA nodes in the machine, all the memory is close to this object, so allowed_nodeset is full.

Note

Its value must not be changed, hwloc bitmap dup must be used instead.

19.8.2.3 unsigned hwloc_obj::arity

Number of children.

19.8.2.4 union hwloc_obj_attr_u* hwloc_obj::attr

Object type-specific Attributes, may be NULL if no attribute value was found.

19.8.2.5 struct hwloc_obj** hwloc_obj::children

Children, children[0 .. arity -1].

19.8.2.6 hwloc_cpuset_t hwloc_obj::complete_cpuset

The complete CPU set of logical processors of this object,.

This includes not only the same as the cpuset field, but also the CPUs for which topology information is unknown or incomplete, and the CPUs that are ignored when the HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM flag is not set. Thus no corresponding PU object may be found in the topology, because the precise position is undefined. It is however known that it would be somewhere under this object.

Note

Its value must not be changed, hwloc_bitmap_dup must be used instead.

19.8.2.7 hwloc nodeset t hwloc_obj::complete_nodeset

The complete NUMA node set of this object,.

This includes not only the same as the nodeset field, but also the NUMA nodes for which topology information is unknown or incomplete, and the nodes that are ignored when the HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM flag is not set. Thus no corresponding NODE object may be found in the topology, because the precise position is undefined. It is however known that it would be somewhere under this object.

If there are no NUMA nodes in the machine, all the memory is close to this object, so <code>complete_nodeset</code> is full.

Note

Its value must not be changed, hwloc bitmap dup must be used instead.

19.8.2.8 hwloc_cpuset_t hwloc_obj::cpuset

CPUs covered by this object.

This is the set of CPUs for which there are PU objects in the topology under this object, i.e. which are known to be physically contained in this object and known how (the children path between this object and the PU objects).

If the HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM configuration flag is set, some of these CPUs may be offline, or not allowed for binding, see online cpuset and allowed cpuset.

Note

Its value must not be changed, hwloc_bitmap_dup must be used instead.

19.8.2.9 unsigned hwloc_obj::depth

Vertical index in the hierarchy. If the topology is symmetric, this is equal to the parent depth plus one, and also equal to the number of parent/child links from the root object to here.

19.8.2.10 struct hwloc_distances_s** hwloc_obj::distances

Distances between all objects at same depth below this object.

19.8.2.11 unsigned hwloc_obj::distances_count

19.8.2.12 struct hwloc_obj* hwloc_obj::first_child

First child.

19.8.2.13 struct hwloc_obj_info_s* hwloc_obj::infos

Array of stringified info type=name.

19.8.2.14 unsigned hwloc_obj::infos_count

Size of infos array.

19.8.2.15 struct hwloc_obj* hwloc_obj::last_child

Last child.

19.8.2.16 unsigned hwloc_obj::logical_index

Horizontal index in the whole list of similar objects, could be a "cousin_rank" since it's the rank within the "cousin" list below.

19.8.2.17 struct hwloc_obj_memory_s hwloc_obj::memory

Memory attributes.

19.8.2.18 char* hwloc_obj::name

Object description if any.

19.8.2.19 struct hwloc_obj* hwloc_obj::next_cousin

Next object of same type and depth.

19.8.2.20 struct hwloc_obj* hwloc_obj::next_sibling

Next object below the same parent.

19.8.2.21 hwloc_nodeset_t hwloc_obj::nodeset

NUMA nodes covered by this object or containing this object.

This is the set of NUMA nodes for which there are NODE objects in the topology under or above this object, i.e. which are known to be physically contained in this object or containing it and known how (the children path between this object and the NODE objects).

In the end, these nodes are those that are close to the current object.

If the HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM configuration flag is set, some of these nodes may not be allowed for allocation, see allowed_nodeset.

If there are no NUMA nodes in the machine, all the memory is close to this object, so nodeset is full.

Note

Its value must not be changed, hwloc_bitmap_dup must be used instead.

19.8.2.22 hwloc_cpuset_t hwloc_obj::online_cpuset

The CPU set of online logical processors.

This includes the CPUs contained in this object that are online, i.e. draw power and can execute threads. It may however not be allowed to bind to them due to administration rules, see allowed cpuset.

Note

Its value must not be changed, hwloc_bitmap_dup must be used instead.

19.8.2.23 unsigned hwloc_obj::os_index

OS-provided physical index number.

19.8.2.24 signed hwloc_obj::os_level

OS-provided physical level, -1 if unknown or meaningless.

19.8.2.25 struct hwloc_obj* hwloc_obj::parent

Parent, NULL if root (system object)

19.8.2.26 struct hwloc_obj* hwloc_obj::prev_cousin

Previous object of same type and depth.

```
19.8.2.27 struct hwloc_obj* hwloc_obj::prev_sibling
```

Previous object below the same parent.

19.8.2.28 unsigned hwloc_obj::sibling_rank

Index in parent's children[] array.

19.8.2.29 int hwloc_obj::symmetric_subtree

Set if the subtree of objects below this object is symmetric, which means all children and their children have identical subtrees. If set in the topology root object, Istopo may export the topology as a synthetic string.

```
19.8.2.30 hwloc_obj_type_t hwloc_obj::type
```

Type of object.

```
19.8.2.31 void* hwloc_obj::userdata
```

Application-given private data pointer, initialized to NULL, use it as you wish. See <a href="https://hww.nuse.com/hw/hw/com/hw/

The documentation for this struct was generated from the following file:

· hwloc.h

19.9 hwloc_obj_attr_u Union Reference

```
#include <hwloc.h>
```

Data Structures

- struct hwloc_bridge_attr_s
- struct hwloc_cache_attr_s
- struct hwloc_group_attr_s
- struct hwloc_osdev_attr_s
- struct hwloc_pcidev_attr_s

Data Fields

- struct
 - hwloc_obj_attr_u::hwloc_cache_attr_s cache
- · struct
- hwloc_obj_attr_u::hwloc_group_attr_s group
- struct
 - hwloc_obj_attr_u::hwloc_pcidev_attr_s pcidev
- struct
 - hwloc_obj_attr_u::hwloc_bridge_attr_s bridge
- struct
 - hwloc_obj_attr_u::hwloc_osdev_attr_s osdev

19.9.1 Detailed Description

Object type-specific Attributes.

19.9.2 Field Documentation

19.9.2.1 struct hwloc_obj_attr_u::hwloc_bridge_attr_s hwloc_obj_attr_u::bridge

19.9.2.2 struct hwloc_obj_attr_u::hwloc_cache_attr_s hwloc_obj_attr_u::cache

19.9.2.3 struct hwloc_obj_attr_u::hwloc_group_attr_s hwloc_obj_attr_u::group

19.9.2.4 struct hwloc_obj_attr_u::hwloc_osdev_attr_s hwloc_obj_attr_u::osdev

19.9.2.5 struct hwloc_obj_attr_u::hwloc_pcidev_attr_s hwloc_obj_attr_u::pcidev

The documentation for this union was generated from the following file:

· hwloc.h

19.10 hwloc_obj_info_s Struct Reference

#include <hwloc.h>

Data Fields

- char * name
- char * value

19.10.1 Detailed Description

Object info.

19.10.2 Field Documentation

19.10.2.1 char* hwloc_obj_info_s::name

Info name.

19.10.2.2 char* hwloc_obj_info_s::value

Info value.

The documentation for this struct was generated from the following file:

• hwloc.h

19.11 hwloc_obj_memory_s::hwloc_obj_memory_page_type_s Struct Reference

#include <hwloc.h>

Data Fields

- hwloc_uint64_t size
- hwloc_uint64_t count

19.11.1 Detailed Description

Array of local memory page types, NULL if no local memory and page_types is 0.

The array is sorted by increasing size fields. It contains page_types_len slots.

19.11.2 Field Documentation

19.11.2.1 hwloc_uint64_t hwloc_obj_memory_s::hwloc_obj_memory_page_type_s::count

Number of pages of this size.

19.11.2.2 hwloc_uint64_t hwloc_obj_memory_s::hwloc_obj_memory_page_type_s::size

Size of pages.

The documentation for this struct was generated from the following file:

· hwloc.h

19.12 hwloc_obj_memory_s Struct Reference

```
#include <hwloc.h>
```

Data Structures

· struct hwloc obj memory page type s

Data Fields

- hwloc_uint64_t total_memory
- hwloc_uint64_t local_memory
- unsigned page_types_len
- struct hwloc_obj_memory_s::hwloc_obj_memory_page_type_s * page_types

19.12.1 Detailed Description

Object memory.

19.12.2 Field Documentation

19.12.2.1 hwloc_uint64_t hwloc_obj_memory_s::local_memory

Local memory (in bytes)

19.12.2.2 struct hwloc_obj_memory_s::hwloc_obj_memory_page_type_s * hwloc_obj_memory_s::page_types

19.12.2.3 unsigned hwloc_obj_memory_s::page_types_len

Size of array page_types.

19.12.2.4 hwloc uint64 t hwloc obj memory s::total memory

Total memory (in bytes) in this object and its children.

The documentation for this struct was generated from the following file:

· hwloc.h

19.13 hwloc_obj_attr_u::hwloc_osdev_attr_s Struct Reference

```
#include <hwloc.h>
```

Data Fields

hwloc_obj_osdev_type_t type

19.13.1 Detailed Description

OS Device specific Object Attributes.

19.13.2 Field Documentation

19.13.2.1 hwloc_obj_osdev_type_t hwloc_obj_attr_u::hwloc_osdev_attr_s::type

The documentation for this struct was generated from the following file:

· hwloc.h

19.14 hwloc_obj_attr_u::hwloc_pcidev_attr_s Struct Reference

```
#include <hwloc.h>
```

Data Fields

- · unsigned short domain
- · unsigned char bus
- unsigned char dev
- · unsigned char func
- unsigned short class_id
- · unsigned short vendor_id
- unsigned short device_id
- unsigned short subvendor_id
- unsigned short subdevice_id
- unsigned char revision
- · float linkspeed

19.14.1 Detailed Description

PCI Device specific Object Attributes.

19.14.2.1 unsigned char hwloc_obj_attr_u::hwloc_pcidev_attr_s::bus 19.14.2.2 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::class_id 19.14.2.3 unsigned char hwloc_obj_attr_u::hwloc_pcidev_attr_s::dev 19.14.2.4 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::device_id 19.14.2.5 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::domain 19.14.2.6 unsigned char hwloc_obj_attr_u::hwloc_pcidev_attr_s::func 19.14.2.7 float hwloc_obj_attr_u::hwloc_pcidev_attr_s::linkspeed 19.14.2.8 unsigned char hwloc_obj_attr_u::hwloc_pcidev_attr_s::revision 19.14.2.9 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::subdevice_id 19.14.2.10 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::subvendor_id

The documentation for this struct was generated from the following file:

19.14.2.11 unsigned short hwloc_obj_attr_u::hwloc_pcidev_attr_s::vendor_id

hwloc.h

19.15 hwloc_topology_cpubind_support Struct Reference

#include <hwloc.h>

Data Fields

- unsigned char set_thisproc_cpubind
- · unsigned char get_thisproc_cpubind
- unsigned char set_proc_cpubind
- unsigned char get_proc_cpubind
- unsigned char set_thisthread_cpubind
- unsigned char get_thisthread_cpubind
- · unsigned char set_thread_cpubind
- · unsigned char get_thread_cpubind
- unsigned char get_thisproc_last_cpu_location
- unsigned char get_proc_last_cpu_location
- unsigned char get_thisthread_last_cpu_location

19.15.1 Detailed Description

Flags describing actual PU binding support for this topology.

19.15.2 Field Documentation

19.15.2.1 unsigned char hwloc_topology_cpubind_support::get_proc_cpubind

Getting the binding of a whole given process is supported.

19.15.2.2 unsigned char hwloc_topology_cpubind_support::get_proc_last_cpu_location

Getting the last processors where a whole process ran is supported

19.15.2.3 unsigned char hwloc_topology_cpubind_support::get_thisproc_cpubind

Getting the binding of the whole current process is supported.

19.15.2.4 unsigned char hwloc_topology_cpubind_support::get_thisproc_last_cpu_location

Getting the last processors where the whole current process ran is supported

19.15.2.5 unsigned char hwloc_topology_cpubind_support::get_thisthread_cpubind

Getting the binding of the current thread only is supported.

19.15.2.6 unsigned char hwloc_topology_cpubind_support::get_thisthread_last_cpu_location

Getting the last processors where the current thread ran is supported

19.15.2.7 unsigned char hwloc_topology_cpubind_support::get_thread_cpubind

Getting the binding of a given thread only is supported.

19.15.2.8 unsigned char hwloc_topology_cpubind_support::set_proc_cpubind

Binding a whole given process is supported.

19.15.2.9 unsigned char hwloc_topology_cpubind_support::set_thisproc_cpubind

Binding the whole current process is supported.

19.15.2.10 unsigned char hwloc_topology_cpubind_support::set_thisthread_cpubind

Binding the current thread only is supported.

19.15.2.11 unsigned char hwloc_topology_cpubind_support::set_thread_cpubind

Binding a given thread only is supported.

The documentation for this struct was generated from the following file:

· hwloc.h

19.16 hwloc_topology_discovery_support Struct Reference

#include <hwloc.h>

Data Fields

· unsigned char pu

19.16.1 Detailed Description

Flags describing actual discovery support for this topology.

19.16.2 Field Documentation

19.16.2.1 unsigned char hwloc_topology_discovery_support::pu

Detecting the number of PU objects is supported.

The documentation for this struct was generated from the following file:

· hwloc.h

19.17 hwloc_topology_membind_support Struct Reference

#include <hwloc.h>

Data Fields

- · unsigned char set_thisproc_membind
- unsigned char get_thisproc_membind
- unsigned char set_proc_membind
- unsigned char get_proc_membind
- unsigned char set_thisthread_membind
- unsigned char get_thisthread_membind
- · unsigned char set_area_membind
- unsigned char get_area_membind
- unsigned char alloc_membind
- unsigned char firsttouch_membind
- unsigned char bind_membind
- unsigned char interleave_membind
- unsigned char replicate_membind
- unsigned char nexttouch_membind
- · unsigned char migrate_membind

19.17.1 Detailed Description

Flags describing actual memory binding support for this topology.

- 19.17.2 Field Documentation
- 19.17.2.1 unsigned char hwloc_topology_membind_support::alloc_membind

 Allocating a bound memory area is supported.
- 19.17.2.2 unsigned char hwloc_topology_membind_support::bind_membind Bind policy is supported.
- 19.17.2.3 unsigned char hwloc_topology_membind_support::firsttouch_membind First-touch policy is supported.
- 19.17.2.4 unsigned char hwloc_topology_membind_support::get_area_membind

 Getting the binding of a given memory area is supported.
- 19.17.2.5 unsigned char hwloc_topology_membind_support::get_proc_membind

 Getting the binding of a whole given process is supported.
- 19.17.2.6 unsigned char hwloc_topology_membind_support::get_thisproc_membind
 Getting the binding of the whole current process is supported.
- 19.17.2.7 unsigned char hwloc_topology_membind_support::get_thisthread_membind
 Getting the binding of the current thread only is supported.
- 19.17.2.8 unsigned char hwloc_topology_membind_support::interleave_membind
 Interleave policy is supported.
- 19.17.2.9 unsigned char hwloc_topology_membind_support::migrate_membind Migration flags is supported.
- 19.17.2.10 unsigned char hwloc_topology_membind_support::nexttouch_membind

 Next-touch migration policy is supported.
- 19.17.2.11 unsigned char hwloc_topology_membind_support::replicate_membind Replication policy is supported.
- 19.17.2.12 unsigned char hwloc_topology_membind_support::set_area_membind Binding a given memory area is supported.

19.17.2.13 unsigned char hwloc_topology_membind_support::set_proc_membind

Binding a whole given process is supported.

19.17.2.14 unsigned char hwloc_topology_membind_support::set_thisproc_membind

Binding the whole current process is supported.

19.17.2.15 unsigned char hwloc_topology_membind_support::set_thisthread_membind

Binding the current thread only is supported.

The documentation for this struct was generated from the following file:

· hwloc.h

19.18 hwloc_topology_support Struct Reference

```
#include <hwloc.h>
```

Data Fields

- struct hwloc_topology_discovery_support * discovery
- struct
 hwloc topology cpubind support * cpubind
- struct hwloc topology membind support * membind

19.18.1 Detailed Description

Set of flags describing actual support for this topology.

This is retrieved with https://hww.nct.noi.org/nct.noi.org/nct/ and will be valid until the topology object is destroyed. Note: the values are correct only after discovery.

19.18.2 Field Documentation

- 19.18.2.1 struct hwloc topology cpubind support* hwloc_topology_support::cpubind
- 19.18.2.2 struct hwloc_topology_discovery_support* hwloc_topology_support::discovery
- 19.18.2.3 struct hwloc_topology_membind_support* hwloc_topology_support::membind

The documentation for this struct was generated from the following file:

hwloc.h

Index

API version, 59	Building Custom Topologies, 96
HWLOC_API_VERSION, 59	hwloc_custom_insert_group_object_by_parent, 96
hwloc_get_api_version, 59	hwloc_custom_insert_topology, 96
abi	bus
hwloc_component, 154	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
Advanced I/O object traversal helpers, 118	_ <i>_</i>
hwloc_bridge_covers_pcibus, 118	CPU binding
hwloc_get_hostbridge_by_pcibus, 118	HWLOC_CPUBIND_NOMEMBIND, 85
hwloc_get_next_bridge, 118	HWLOC CPUBIND PROCESS, 85
hwloc_get_next_osdev, 118	HWLOC_CPUBIND_STRICT, 85
hwloc get next pcidev, 118	HWLOC_CPUBIND_THREAD, 85
hwloc_get_non_io_ancestor_obj, 119	CPU binding, 84
hwloc_get_pcidev_by_busid, 119	hwloc_cpubind_flags_t, 85
	hwloc_get_cpubind, 85
hwloc_get_pcidev_by_busidstring, 119	hwloc_get_last_cpu_location, 85
Advanced Traversal Helpers, 106	hwloc_get_proc_cpubind, 86
hwloc_get_closest_objs, 106	hwloc_get_proc_last_cpu_location, 86
hwloc_get_obj_below_array_by_type, 106	
hwloc_get_obj_below_by_type, 106	hwloc_get_thread_cpubind, 86 hwloc_set_cpubind, 86
alloc_membind	·
hwloc_topology_membind_support, 169	hwloc_set_proc_cpubind, 86
allowed_cpuset	hwloc_set_thread_cpubind, 87
hwloc_obj, 158	CUDA Driver API Specific Functions, 141
allowed_nodeset	hwloc_cuda_get_device_cpuset, 141
hwloc_obj, 158	hwloc_cuda_get_device_osdev, 141
arity	hwloc_cuda_get_device_osdev_by_index, 141
hwloc_obj, 159	hwloc_cuda_get_device_pci_ids, 142
associativity	hwloc_cuda_get_device_pcidev, 142
hwloc_obj_attr_u::hwloc_cache_attr_s, 154	CUDA Runtime API Specific Functions, 143
attr	hwloc_cudart_get_device_cpuset, 143
hwloc_obj, 159	hwloc_cudart_get_device_osdev_by_index, 143
	hwloc_cudart_get_device_pci_ids, 143
Basic Traversal Helpers, 98	hwloc_cudart_get_device_pcidev, 143
hwloc_get_ancestor_obj_by_depth, 98	cache
hwloc_get_ancestor_obj_by_type, 98	hwloc_obj_attr_u, 163
hwloc_get_common_ancestor_obj, 98	Cache-specific Finding Helpers, 105
hwloc_get_next_child, 98	hwloc_get_cache_covering_cpuset, 105
hwloc_get_next_obj_by_depth, 98	hwloc_get_cache_type_depth, 105
hwloc_get_next_obj_by_type, 99	hwloc_get_shared_cache_covering_obj, 105
hwloc_get_pu_obj_by_os_index, 99	children
hwloc_get_root_obj, 99	hwloc_obj, 159
hwloc_obj_is_in_subtree, 99	class_id
bind_membind	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
hwloc_topology_membind_support, 169	complete_cpuset
Binding Helpers, 108	hwloc_obj, 159
hwloc_alloc_membind_policy, 108	complete_nodeset
hwloc_alloc_membind_policy_nodeset, 108	hwloc_obj, 159
hwloc_distribute, 108	Configure Topology Detection, 68
hwloc distributev, 108	HWLOC TOPOLOGY FLAG ICACHES, 69
bridge	HWLOC_TOPOLOGY_FLAG_IO_BRIDGES, 69
hwloc_obj_attr_u, 163	HWLOC_TOPOLOGY_FLAG_IO_DEVICES, 69

HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM,	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
69	disable
HWLOC_TOPOLOGY_FLAG_WHOLE_IO, 69	hwloc_backend, 151
HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM,	discover
69	hwloc_backend, 151
hwloc_topology_flags_e, 69	discovery
hwloc_topology_get_support, 69	hwloc_topology_support, 170
hwloc_topology_ignore_all_keep_structure, 69	Discovery backends, 129
hwloc_topology_ignore_type, 69	HWLOC_BACKEND_FLAG_NEED_LEVELS, 129
hwloc_topology_ignore_type_keep_structure, 70	hwloc backend alloc, 129
hwloc_topology_set_custom, 70	hwloc backend enable, 129
hwloc_topology_set_distance_matrix, 70	hwloc_backend_flag_e, 129
hwloc_topology_set_flags, 70	hwloc_backends_get_obj_cpuset, 129
hwloc_topology_set_fsroot, 70	hwloc_backends_notify_new_object, 129
hwloc_topology_set_pid, 71	Discovery components, 128
hwloc_topology_set_synthetic, 71	HWLOC_DISC_COMPONENT_TYPE_CPU, 128
hwloc_topology_set_xml, 71	HWLOC_DISC_COMPONENT_TYPE_GLOBAL,
hwloc_topology_set_xmlbuffer, 72	128
	HWLOC DISC COMPONENT TYPE MISC, 128
Conversion between cpuset and nodeset, 114	
hwloc_cpuset_from_nodeset, 114	hwloc_disc_component_type_e, 128
hwloc_cpuset_from_nodeset_strict, 114	hwloc_disc_component_type_t, 128
hwloc_cpuset_to_nodeset, 114	Distances, 116
hwloc_cpuset_to_nodeset_strict, 114	hwloc_get_distance_matrix_covering_obj_by
Core functions to be used by components, 132	depth, 116
hwlocinsert_object_by_cpuset, 132	hwloc_get_latency, 116
hwloc_alloc_setup_object, 132	hwloc_get_whole_distance_matrix_by_depth, 116
hwloc_hide_errors, 132	hwloc_get_whole_distance_matrix_by_type, 117
hwloc_insert_object_by_cpuset, 132	distances
hwloc_insert_object_by_parent, 133	hwloc_obj, 160
hwloc_report_error_t, 132	distances_count
hwloc_report_os_error, 133	hwloc_obj, 160
count	domain
hwloc_obj_memory_s::hwloc_obj_memory_page-	hwloc_obj_attr_u::hwloc_bridge_attr_s, 153
_type_s, 164	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
cpubind	downstream
hwloc_topology_support, 170	hwloc obj attr u::hwloc bridge attr s, 153
cpuset	downstream_type
hwloc_obj, 159	hwloc_obj_attr_u::hwloc_bridge_attr_s, 153
Cpuset Helpers, 110	_ , 0 <i>,</i>
hwloc_topology_get_allowed_cpuset, 110	excludes
hwloc_topology_get_complete_cpuset, 110	hwloc_disc_component, 155
hwloc_topology_get_online_cpuset, 110	Exporting Topologies to XML., 73
hwloc_topology_get_topology_cpuset, 111	hwloc_export_obj_userdata, 73
Create and Destroy Topologies, 66	hwloc_export_obj_userdata_base64, 73
hwloc_topology_check, 66	hwloc_free_xmlbuffer, 73
hwloc topology destroy, 66	hwloc topology export xml, 74
hwloc_topology_init, 66	hwloc_topology_export_xmlbuffer, 74
hwloc_topology_load, 66	hwloc_topology_set_userdata_export_callback, 74
nwioc_topology_load, oo	hwloc_topology_set_userdata_import_callback, 74
data	po.t_company
hwloc_component, 154	Finding a set of similar Objects covering at least a CPU
depth	set, 104
hwloc_obj, 160	hwloc_get_next_obj_covering_cpuset_by_depth,
hwloc_obj_attr_u::hwloc_bridge_attr_s, 153	104
hwloc_obj_attr_u::hwloc_cache_attr_s, 154	hwloc_get_next_obj_covering_cpuset_by_type,
hwloc_obj_attr_u::hwloc_group_attr_s, 157	104
dev	Finding a single Object covering at least CPU set, 103
hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166	hwloc_get_child_covering_cpuset, 103
device_id	hwloc_get_obj_covering_cpuset, 103
·· <u>-</u>	95_95(_55)_557511119_5pa6661, 100

Finding Objects Inside a CPU set, 100	get_thisthread_membind
hwloc_get_first_largest_obj_inside_cpuset, 100	hwloc_topology_membind_support, 169
hwloc_get_largest_objs_inside_cpuset, 100	get_thread_cpubind
hwloc_get_nbobjs_inside_cpuset_by_depth, 100	hwloc_topology_cpubind_support, 167
hwloc_get_nbobjs_inside_cpuset_by_type, 101	group
hwloc_get_next_obj_inside_cpuset_by_depth, 101	hwloc_obj_attr_u, 163
hwloc_get_next_obj_inside_cpuset_by_type, 101	
hwloc_get_obj_index_inside_cpuset, 101	HWLOC_BACKEND_FLAG_NEED_LEVELS
hwloc_get_obj_inside_cpuset_by_depth, 101	Discovery backends, 129
hwloc get obj inside cpuset by type, 102	HWLOC_COMPONENT_TYPE_DISC
first_child	Generic components, 131
hwloc obj, 160	HWLOC_COMPONENT_TYPE_XML
firsttouch_membind	Generic components, 131
hwloc_topology_membind_support, 169	HWLOC_CPUBIND_NOMEMBIND
flags	CPU binding, 85
hwloc_backend, 151	HWLOC_CPUBIND_PROCESS
hwloc_component, 155	CPU binding, 85
func	HWLOC_CPUBIND_STRICT
hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166	CPU binding, 85
nwioc_obj_atti_unwioc_poldev_atti_s, roo	HWLOC_CPUBIND_THREAD
Generic components, 131	CPU binding, 85
HWLOC_COMPONENT_TYPE_DISC, 131	HWLOC_DISC_COMPONENT_TYPE_CPU
HWLOC_COMPONENT_TYPE_XML, 131	Discovery components, 128
hwloc_component_type_e, 131	HWLOC_DISC_COMPONENT_TYPE_GLOBAL
hwloc_component_type_t, 131	Discovery components, 128
Get Some Topology Information, 78	HWLOC_DISC_COMPONENT_TYPE_MISC
HWLOC_TYPE_DEPTH_BRIDGE, 78	Discovery components, 128
HWLOC_TYPE_DEPTH_MULTIPLE, 78	HWLOC_MEMBIND_BIND
HWLOC_TYPE_DEPTH_OS_DEVICE, 78	Memory binding, 90
HWLOC_TYPE_DEPTH_PCI_DEVICE, 78	HWLOC_MEMBIND_DEFAULT
HWLOC_TYPE_DEPTH_UNKNOWN, 78	Memory binding, 90
hwloc_get_depth_type, 78	HWLOC_MEMBIND_FIRSTTOUCH
hwloc_get_nbobjs_by_depth, 78	Memory binding, 90
hwloc_get_nbobjs_by_type, 79	HWLOC_MEMBIND_INTERLEAVE
hwloc_get_type_depth, 79	Memory binding, 90
hwloc_get_type_depth_e, 78	HWLOC_MEMBIND_MIGRATE
hwloc_topology_get_depth, 79	Memory binding, 89
hwloc_topology_get_flags, 79	HWLOC_MEMBIND_MIXED
hwloc_topology_is_thissystem, 79	Memory binding, 90
get_area_membind	HWLOC_MEMBIND_NEXTTOUCH
hwloc_topology_membind_support, 169	Memory binding, 90
get_obj_cpuset	HWLOC_MEMBIND_NOCPUBIND
hwloc_backend, 152	Memory binding, 90
get_proc_cpubind	HWLOC_MEMBIND_PROCESS
hwloc_topology_cpubind_support, 167	Memory binding, 89
get_proc_last_cpu_location	HWLOC_MEMBIND_REPLICATE
hwloc_topology_cpubind_support, 167	Memory binding, 90
get proc membind	HWLOC_MEMBIND_STRICT
hwloc_topology_membind_support, 169	Memory binding, 89
get_thisproc_cpubind	HWLOC_MEMBIND_THREAD
hwloc_topology_cpubind_support, 167	Memory binding, 89
get_thisproc_last_cpu_location	HWLOC_OBJ_BRIDGE
hwloc_topology_cpubind_support, 167	Topology Object Types, 64
get_thisproc_membind	HWLOC_OBJ_BRIDGE_HOST
hwloc_topology_membind_support, 169	Topology Object Types, 63
get_thisthread_cpubind	HWLOC_OBJ_BRIDGE_PCI
hwloc_topology_cpubind_support, 167	Topology Object Types, 63
get_thisthread_last_cpu_location	HWLOC_OBJ_CACHE
hwloc topology coubind support, 167	Topology Object Types, 64

HWLOC_OBJ_CACHE_DATA	HWLOC_TYPE_DEPTH_BRIDGE
Topology Object Types, 63	Get Some Topology Information, 78
HWLOC_OBJ_CACHE_INSTRUCTION	HWLOC_TYPE_DEPTH_MULTIPLE
Topology Object Types, 63	Get Some Topology Information, 78
HWLOC OBJ CACHE UNIFIED	HWLOC TYPE DEPTH OS DEVICE
Topology Object Types, 63	Get Some Topology Information, 78
HWLOC_OBJ_CORE	HWLOC TYPE DEPTH PCI DEVICE
Topology Object Types, 64	Get Some Topology Information, 78
HWLOC_OBJ_GROUP	HWLOC_TYPE_DEPTH_UNKNOWN
Topology Object Types, 64	Get Some Topology Information, 78
HWLOC OBJ MACHINE	HWLOC_TYPE_UNORDERED
Topology Object Types, 63	Topology Object Types, 62
HWLOC_OBJ_MISC	HWLOC_API_VERSION
Topology Object Types, 64	API version, 59
HWLOC_OBJ_NODE	HWLOC_COMPONENT_ABI
Topology Object Types, 63	API version, 59
HWLOC_OBJ_OS_DEVICE	Helpers for manipulating glibc sched affinity, 134
Topology Object Types, 64	hwloc_cpuset_from_glibc_sched_affinity, 134
HWLOC_OBJ_OSDEV_BLOCK	hwloc_cpuset_to_glibc_sched_affinity, 134
Topology Object Types, 63	Helpers for manipulating Linux libnuma bitmask, 138
HWLOC_OBJ_OSDEV_COPROC	hwloc cpuset from linux libnuma bitmask, 138
Topology Object Types, 63	hwloc_cpuset_to_linux_libnuma_bitmask, 138
HWLOC_OBJ_OSDEV_DMA	hwloc_nodeset_from_linux_libnuma_bitmask, 138
Topology Object Types, 63	hwloc_nodeset_to_linux_libnuma_bitmask, 138
HWLOC_OBJ_OSDEV_GPU	Helpers for manipulating Linux libnuma unsigned long
Topology Object Types, 63	masks, 136
HWLOC OBJ OSDEV NETWORK	hwloc_cpuset_from_linux_libnuma_ulongs, 136
Topology Object Types, 63	hwloc_cpuset_to_linux_libnuma_ulongs, 136
HWLOC_OBJ_OSDEV_OPENFABRICS	hwloc_nodeset_from_linux_libnuma_ulongs, 136
Topology Object Types, 63	hwloc_nodeset_to_linux_libnuma_ulongs, 136
HWLOC OBJ PCI DEVICE	hwloc insert_object_by_cpuset
Topology Object Types, 64	Core functions to be used by components, 132
HWLOC_OBJ_PU	hwloc_alloc
Topology Object Types, 64	Memory binding, 90
HWLOC_OBJ_SOCKET	hwloc_alloc_membind
Topology Object Types, 64	Memory binding, 90
HWLOC_OBJ_SYSTEM	hwloc_alloc_membind_nodeset
Topology Object Types, 63	Memory binding, 91
HWLOC_OBJ_TYPE_MAX	hwloc_alloc_membind_policy
Topology Object Types, 64	Binding Helpers, 108
HWLOC_RESTRICT_FLAG_ADAPT_DISTANCES	hwloc_alloc_membind_policy_nodeset
Tinker With Topologies., 76	Binding Helpers, 108
HWLOC_RESTRICT_FLAG_ADAPT_IO	hwloc_alloc_setup_object
Tinker With Topologies., 76	Core functions to be used by components, 132
HWLOC_RESTRICT_FLAG_ADAPT_MISC	hwloc backend, 151
Tinker With Topologies., 76	disable, 151
HWLOC_TOPOLOGY_FLAG_ICACHES	discover, 151
Configure Topology Detection, 69	flags, 151
HWLOC_TOPOLOGY_FLAG_IO_BRIDGES	get_obj_cpuset, 152
Configure Topology Detection, 69	is_custom, 152
HWLOC_TOPOLOGY_FLAG_IO_DEVICES	is_thissystem, 152
Configure Topology Detection, 69	notify_new_object, 152
HWLOC_TOPOLOGY_FLAG_IS_THISSYSTEM	private_data, 152
Configure Topology Detection, 69	hwloc_backend_alloc
HWLOC_TOPOLOGY_FLAG_WHOLE_IO	Discovery backends, 129
Configure Topology Detection, 69	hwloc_backend_enable
HWLOC_TOPOLOGY_FLAG_WHOLE_SYSTEM	Discovery backends, 129
Configure Topology Detection, 69	hwloc_backend_flag_e
Comigate Topology Detection, 03	HITTIOU DUONOHU HUY E

Discovery backends, 129	The bitmap API, 124
hwloc_backends_get_obj_cpuset	hwloc_bitmap_list_snprintf
Discovery backends, 129	The bitmap API, 124
hwloc_backends_notify_new_object	hwloc_bitmap_list_sscanf
Discovery backends, 129	The bitmap API, 125
hwloc_bitmap_allbut	hwloc_bitmap_next
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_alloc	hwloc_bitmap_not
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_alloc_full	hwloc_bitmap_only
The bitmap API, 122	The bitmap API, 125
hwloc bitmap and	hwloc_bitmap_or
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_andnot	hwloc_bitmap_set
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_asprintf	hwloc_bitmap_set_ith_ulong
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_clr	hwloc bitmap set range
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_clr_range	hwloc_bitmap_singlify
The bitmap API, 122	The bitmap API, 125
hwloc_bitmap_compare	hwloc bitmap snprintf
The bitmap API, 123	The bitmap API, 126
hwloc_bitmap_compare_first	hwloc_bitmap_sscanf
The bitmap API, 123	The bitmap API, 126
•	•
hwloc_bitmap_copy The bitmap_API_100	hwloc_bitmap_t
The bitmap API, 123	The bitmap API, 122
hwloc_bitmap_dup	hwloc_bitmap_taskset_asprintf
The bitmap API, 123	The bitmap API, 126
hwloc_bitmap_fill	hwloc_bitmap_taskset_snprintf
The bitmap API, 123	The bitmap API, 126
hwloc_bitmap_first	hwloc_bitmap_taskset_sscanf
The bitmap API, 123	The bitmap API, 126
hwloc_bitmap_foreach_begin	hwloc_bitmap_to_ith_ulong
The bitmap API, 121	The bitmap API, 126
hwloc_bitmap_foreach_end	hwloc_bitmap_to_ulong
The bitmap API, 121	The bitmap API, 126
hwloc_bitmap_free	hwloc_bitmap_weight
The bitmap API, 123	The bitmap API, 127
hwloc_bitmap_from_ith_ulong	hwloc_bitmap_xor
The bitmap API, 123	The bitmap API, 127
hwloc_bitmap_from_ulong	hwloc_bitmap_zero
The bitmap API, 123	The bitmap API, 127
hwloc_bitmap_intersects	hwloc_bridge_covers_pcibus
The bitmap API, 124	Advanced I/O object traversal helpers, 118
hwloc_bitmap_isequal	hwloc_compare_types
The bitmap API, 124	Topology Object Types, 64
hwloc_bitmap_isfull	hwloc_compare_types_e
The bitmap API, 124	Topology Object Types, 62
hwloc_bitmap_isincluded	hwloc_component, 154
The bitmap API, 124	abi, 154
hwloc_bitmap_isset	data, 154
The bitmap API, 124	flags, 155
hwloc_bitmap_iszero	type, 155
The bitmap API, 124	hwloc_component_type_e
hwloc_bitmap_last	Generic components, 131
The bitmap API, 124	hwloc_component_type_t
hwloc_bitmap_list_asprintf	Generic components, 131
_ ·- ·	• '

hwloc_const_bitmap_t	Building Custom Topologies, 96
The bitmap API, 122	hwloc_disc_component, 155
hwloc_const_cpuset_t	excludes, 155
Object sets (hwloc_cpuset_t and hwloc_nodeset	instantiate, 155
t), 61	name, 155
hwloc_const_nodeset_t	priority, 156
Object sets (hwloc_cpuset_t and hwloc_nodeset	type, 156
t), 61	hwloc_disc_component_type_e
hwloc_cpubind_flags_t	Discovery components, 128
CPU binding, 85	hwloc_disc_component_type_t
hwloc_cpuset_from_glibc_sched_affinity	Discovery components, 128
Helpers for manipulating glibc sched affinity, 134	hwloc_distances_s, 156
hwloc_cpuset_from_linux_libnuma_bitmask	latency, 156
Helpers for manipulating Linux libnuma bitmask,	latency_base, 156
138	latency_max, 157
hwloc_cpuset_from_linux_libnuma_ulongs	nbobjs, 157
Helpers for manipulating Linux libnuma unsigned	relative_depth, 157
long masks, 136	hwloc_distribute
hwloc_cpuset_from_nodeset	Binding Helpers, 108
Conversion between cpuset and nodeset, 114	hwloc_distributev
hwloc_cpuset_from_nodeset_strict	Binding Helpers, 108
Conversion between cpuset and nodeset, 114	hwloc_export_obj_userdata
hwloc_cpuset_t	Exporting Topologies to XML., 73
Object sets (hwloc cpuset t and hwloc nodeset -	
	hwloc_export_obj_userdata_base64
t), 61	Exporting Topologies to XML., 73
hwloc_cpuset_to_glibc_sched_affinity	hwloc_free
Helpers for manipulating glibc sched affinity, 134	Memory binding, 91
hwloc_cpuset_to_linux_libnuma_bitmask	hwloc_free_xmlbuffer
Helpers for manipulating Linux libnuma bitmask,	Exporting Topologies to XML., 73
138	hwloc_get_ancestor_obj_by_depth
hwloc_cpuset_to_linux_libnuma_ulongs	Basic Traversal Helpers, 98
Helpers for manipulating Linux libnuma unsigned	hwloc_get_ancestor_obj_by_type
long masks, 136	Basic Traversal Helpers, 98
hwloc_cpuset_to_nodeset	hwloc_get_api_version
Conversion between cpuset and nodeset, 114	API version, 59
hwloc_cpuset_to_nodeset_strict	hwloc_get_area_membind
Conversion between cpuset and nodeset, 114	Memory binding, 91
hwloc_cuda_get_device_cpuset	hwloc_get_area_membind_nodeset
CUDA Driver API Specific Functions, 141	Memory binding, 91
hwloc_cuda_get_device_osdev	hwloc_get_cache_covering_cpuset
CUDA Driver API Specific Functions, 141	Cache-specific Finding Helpers, 105
hwloc_cuda_get_device_osdev_by_index	hwloc_get_cache_type_depth
CUDA Driver API Specific Functions, 141	Cache-specific Finding Helpers, 105
hwloc_cuda_get_device_pci_ids	hwloc_get_child_covering_cpuset
CUDA Driver API Specific Functions, 142	Finding a single Object covering at least CPU set,
hwloc_cuda_get_device_pcidev	103
CUDA Driver API Specific Functions, 142	hwloc_get_closest_objs
hwloc_cudart_get_device_cpuset	Advanced Traversal Helpers, 106
CUDA Runtime API Specific Functions, 143	hwloc_get_common_ancestor_obj
hwloc_cudart_get_device_osdev_by_index	Basic Traversal Helpers, 98
CUDA Runtime API Specific Functions, 143	hwloc_get_cpubind
hwloc_cudart_get_device_pci_ids	CPU binding, 85
CUDA Runtime API Specific Functions, 143	hwloc_get_depth_type
hwloc_cudart_get_device_pcidev	Get Some Topology Information, 78
CUDA Runtime API Specific Functions, 143	hwloc_get_distance_matrix_covering_obj_by_depth
hwloc_custom_insert_group_object_by_parent	Distances, 116
Building Custom Topologies, 96	hwloc_get_first_largest_obj_inside_cpuset
hwloc_custom_insert_topology	Finding Objects Inside a CPU set, 100
<u>-</u>	

hwloc_get_hostbridge_by_pcibus	Finding Objects Inside a CPU set, 101
Advanced I/O object traversal helpers, 118	hwloc_get_obj_inside_cpuset_by_type
hwloc_get_largest_objs_inside_cpuset	Finding Objects Inside a CPU set, 102
Finding Objects Inside a CPU set, 100	hwloc_get_pcidev_by_busid
hwloc_get_last_cpu_location	Advanced I/O object traversal helpers, 119
CPU binding, 85	hwloc_get_pcidev_by_busidstring
hwloc_get_latency	Advanced I/O object traversal helpers, 119
Distances, 116	hwloc_get_proc_cpubind
hwloc_get_membind	CPU binding, 86
Memory binding, 92	hwloc_get_proc_last_cpu_location
hwloc_get_membind_nodeset	CPU binding, 86
Memory binding, 92	hwloc_get_proc_membind
hwloc_get_nbobjs_by_depth	Memory binding, 93
Get Some Topology Information, 78	hwloc_get_proc_membind_nodeset
hwloc_get_nbobjs_by_type	Memory binding, 93
Get Some Topology Information, 79	hwloc_get_pu_obj_by_os_index
hwloc_get_nbobjs_inside_cpuset_by_depth	Basic Traversal Helpers, 99
Finding Objects Inside a CPU set, 100	hwloc_get_root_obj
hwloc_get_nbobjs_inside_cpuset_by_type	Basic Traversal Helpers, 99
Finding Objects Inside a CPU set, 101	hwloc_get_shared_cache_covering_obj
hwloc get next bridge	Cache-specific Finding Helpers, 105
Advanced I/O object traversal helpers, 118	hwloc_get_thread_cpubind
· · · · · · · · · · · · · · · · · · ·	CPU binding, 86
hwloc_get_next_child	
Basic Traversal Helpers, 98	hwloc_get_type_depth
hwloc_get_next_obj_by_depth	Get Some Topology Information, 79
Basic Traversal Helpers, 98	hwloc_get_type_depth_e
hwloc_get_next_obj_by_type	Get Some Topology Information, 78
Basic Traversal Helpers, 99	hwloc_get_type_or_above_depth
hwloc_get_next_obj_covering_cpuset_by_depth	Object Type Helpers, 97
Finding a set of similar Objects covering at least a	hwloc_get_type_or_below_depth
CPU set, 104	Object Type Helpers, 97
hwloc_get_next_obj_covering_cpuset_by_type	hwloc_get_whole_distance_matrix_by_depth
Finding a set of similar Objects covering at least a	Distances, 116
CPU set, 104	hwloc_get_whole_distance_matrix_by_type
hwloc_get_next_obj_inside_cpuset_by_depth	Distances, 117
Finding Objects Inside a CPU set, 101	hwloc_gl_get_display_by_osdev
hwloc_get_next_obj_inside_cpuset_by_type	OpenGL display specific functions, 146
Finding Objects Inside a CPU set, 101	hwloc_gl_get_display_osdev_by_name
hwloc_get_next_osdev	OpenGL display specific functions, 146
Advanced I/O object traversal helpers, 118	hwloc_gl_get_display_osdev_by_port_device
hwloc_get_next_pcidev	OpenGL display specific functions, 146
Advanced I/O object traversal helpers, 118	hwloc_hide_errors
hwloc_get_non_io_ancestor_obj	Core functions to be used by components, 132
Advanced I/O object traversal helpers, 119	hwloc_ibv_get_device_cpuset
hwloc_get_obj_below_array_by_type	OpenFabrics-Specific Functions, 148
Advanced Traversal Helpers, 106	hwloc_ibv_get_device_osdev
hwloc_get_obj_below_by_type	OpenFabrics-Specific Functions, 148
Advanced Traversal Helpers, 106	hwloc_ibv_get_device_osdev_by_name
hwloc_get_obj_by_depth	OpenFabrics-Specific Functions, 148
Retrieve Objects, 80	hwloc_insert_object_by_cpuset
hwloc_get_obj_by_type	Core functions to be used by components, 132
Retrieve Objects, 80	hwloc_insert_object_by_parent
hwloc_get_obj_covering_cpuset	Core functions to be used by components, 133
Finding a single Object covering at least CPU set,	hwloc_intel_mic_get_device_cpuset
103	Intel Xeon Phi (MIC) Specific Functions, 147
	• • •
hwloc_get_obj_index_inside_cpuset	hwloc_intel_mic_get_device_osdev_by_index
Finding Objects Inside a CPU set, 101	Intel Xeon Phi (MIC) Specific Functions, 147
hwloc_get_obj_inside_cpuset_by_depth	hwloc_linux_get_tid_cpubind

Linux-only helpers, 135	nodeset, 161
hwloc linux parse cpumap file	online_cpuset, 161
Linux-only helpers, 135	os_index, 161
hwloc_linux_set_tid_cpubind	os_level, 161
Linux-only helpers, 135	parent, 161
hwloc membind flags t	prev_cousin, 161
Memory binding, 89	prev_sibling, 161
hwloc_membind_policy_t	sibling_rank, 162
Memory binding, 90	symmetric subtree, 162
hwloc_mx_board_get_device_cpuset	type, 162
Myrinet Express-Specific Functions, 149	userdata, 162
hwloc mx endpoint get device cpuset	hwloc obj add info
Myrinet Express-Specific Functions, 149	Object/String Conversion, 81
hwloc_nodeset_from_linux_libnuma_bitmask	hwloc_obj_attr_snprintf
Helpers for manipulating Linux libnuma bitmask,	Object/String Conversion, 81
138	hwloc_obj_attr_u, 162
hwloc_nodeset_from_linux_libnuma_ulongs	bridge, 163
Helpers for manipulating Linux libnuma unsigned	cache, 163
long masks, 136	group, 163
hwloc_nodeset_t	osdev, 163
Object sets (hwloc_cpuset_t and hwloc_nodeset	pcidev, 163
t), 61	hwloc_obj_attr_u::hwloc_bridge_attr_s, 152
hwloc_nodeset_to_linux_libnuma_bitmask	depth, 153
Helpers for manipulating Linux libnuma bitmask,	domain, 153
138	downstream, 153
hwloc_nodeset_to_linux_libnuma_ulongs	downstream_type, 153
Helpers for manipulating Linux libnuma unsigned	pci, 153
long masks, 136	secondary_bus, 153
hwloc_nvml_get_device_cpuset	subordinate_bus, 153
NVIDIA Management Library Specific Functions,	upstream, 153
145	upstream_type, 153
hwloc_nvml_get_device_osdev	hwloc_obj_attr_u::hwloc_cache_attr_s, 153
NVIDIA Management Library Specific Functions,	associativity, 154
145	depth, 154
hwloc_nvml_get_device_osdev_by_index	linesize, 154
NVIDIA Management Library Specific Functions,	size, 154
145	type, 154
hwloc_obj, 157	hwloc_obj_attr_u::hwloc_group_attr_s, 157
allowed_cpuset, 158	depth, 157
allowed_nodeset, 158	hwloc_obj_attr_u::hwloc_osdev_attr_s, 165
arity, 159	type, 165
attr, 159	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 165
children, 159	bus, 166
complete_cpuset, 159	class_id, 166
complete_nodeset, 159	dev, 166
cpuset, 159	device_id, 166
depth, 160	domain, 166
distances, 160	func, 166
distances_count, 160	linkspeed, 166
first_child, 160	revision, 166
infos, 160	subdevice_id, 166
infos_count, 160	subvendor_id, 166
last_child, 160	vendor_id, 166
logical_index, 160	hwloc_obj_bridge_type_e
memory, 160	Topology Object Types, 62
name, 160	hwloc_obj_bridge_type_t
next_cousin, 160	Topology Object Types, 62
next_sibling, 161	hwloc_obj_cache_type_e

Topology Object Types, 63	Memory binding, 94
hwloc_obj_cache_type_t	hwloc_set_proc_cpubind
Topology Object Types, 62	CPU binding, 86
hwloc_obj_cpuset_snprintf	hwloc_set_proc_membind
Object/String Conversion, 81	Memory binding, 94
hwloc_obj_get_info_by_name	hwloc_set_proc_membind_nodeset
Object/String Conversion, 82	Memory binding, 95
hwloc_obj_info_s, 163	hwloc_set_thread_cpubind
name, 163	CPU binding, 87
value, 163	hwloc_topology_check
hwloc_obj_is_in_subtree	Create and Destroy Topologies, 66
Basic Traversal Helpers, 99	hwloc_topology_cpubind_support, 166
hwloc_obj_memory_s, 164	get_proc_cpubind, 167
local_memory, 164	get_proc_last_cpu_location, 167
page_types, 164	get_thisproc_cpubind, 167
page_types_len, 165	get_thisproc_last_cpu_location, 167
total_memory, 165	get_thisthread_cpubind, 167
hwloc_obj_memory_s::hwloc_obj_memory_page_type-	get_thisthread_last_cpu_location, 167
_s, 163	get_thread_cpubind, 167
count, 164	set_proc_cpubind, 167
size, 164	set thisproc cpubind, 167
hwloc obj osdev type e	set_thisthread_cpubind, 167
Topology Object Types, 63	set_thread_cpubind, 167
hwloc obj osdev type t	hwloc topology destroy
Topology Object Types, 62	Create and Destroy Topologies, 66
hwloc_obj_snprintf	hwloc_topology_discovery_support, 168
Object/String Conversion, 82	pu, 168
hwloc_obj_t	hwloc_topology_export_xml
Topology Objects, 65	Exporting Topologies to XML., 74
hwloc_obj_type_of_string	hwloc_topology_export_xmlbuffer
Object/String Conversion, 82	Exporting Topologies to XML., 74
hwloc_obj_type_snprintf	hwloc_topology_flags_e
Object/String Conversion, 82	Configure Topology Detection, 69
hwloc_obj_type_string	hwloc_topology_get_allowed_cpuset
Object/String Conversion, 82	Cpuset Helpers, 110
hwloc_obj_type_t	hwloc_topology_get_allowed_nodeset
Topology Object Types, 63	Nodeset Helpers, 112
hwloc_opencl_get_device_cpuset	hwloc_topology_get_complete_cpuset
OpenCL Specific Functions, 139	Cpuset Helpers, 110
hwloc_opencl_get_device_osdev	hwloc_topology_get_complete_nodeset
OpenCL Specific Functions, 139	Nodeset Helpers, 112
hwloc_opencl_get_device_osdev_by_index	hwloc_topology_get_depth
OpenCL Specific Functions, 139	Get Some Topology Information, 79
hwloc_report_error_t	hwloc_topology_get_flags
Core functions to be used by components, 132	Get Some Topology Information, 79
hwloc_report_os_error	hwloc_topology_get_online_cpuset
Core functions to be used by components, 133	Cpuset Helpers, 110
hwloc_restrict_flags_e	hwloc_topology_get_support
Tinker With Topologies., 76	Configure Topology Detection, 69
hwloc_set_area_membind	hwloc_topology_get_topology_cpuset
Memory binding, 94	Cpuset Helpers, 111
hwloc_set_area_membind_nodeset	hwloc_topology_get_topology_nodeset
Memory binding, 94	Nodeset Helpers, 112
hwloc_set_cpubind	hwloc_topology_ignore_all_keep_structure
CPU binding, 86	Configure Topology Detection, 69
hwloc_set_membind	hwloc_topology_ignore_type
Memory binding, 94	Configure Topology Detection, 69
hwloc_set_membind_nodeset	hwloc_topology_ignore_type_keep_structure

Configure Topology Detection, 70	hwloc_obj, 160
hwloc topology init	instantiate
Create and Destroy Topologies, 66	hwloc disc component, 155
hwloc_topology_insert_misc_object_by_cpuset	Intel Xeon Phi (MIC) Specific Functions, 147
Tinker With Topologies., 76	hwloc_intel_mic_get_device_cpuset, 147
hwloc_topology_insert_misc_object_by_parent	hwloc_intel_mic_get_device_osdev_by_index, 147
Tinker With Topologies., 76	interleave_membind
hwloc_topology_is_thissystem	hwloc_topology_membind_support, 169
Get Some Topology Information, 79	is_custom
hwloc_topology_load	hwloc backend, 152
Create and Destroy Topologies, 66	is_thissystem
hwloc_topology_membind_support, 168	hwloc backend, 152
alloc_membind, 169	TIWIOC_DUCKCTIA, TOE
bind_membind, 169	last_child
firsttouch_membind, 169	hwloc_obj, 160
get_area_membind, 169	latency
·	hwloc_distances_s, 156
get_proc_membind, 169	latency_base
get_thisproc_membind, 169	hwloc_distances_s, 156
get_thisthread_membind, 169	latency max
interleave_membind, 169	hwloc_distances_s, 157
migrate_membind, 169	linesize
nexttouch_membind, 169	
replicate_membind, 169	hwloc_obj_attr_u::hwloc_cache_attr_s, 154
set_area_membind, 169	linkspeed
set_proc_membind, 169	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
set_thisproc_membind, 170	Linux-only helpers, 135
set_thisthread_membind, 170	hwloc_linux_get_tid_cpubind, 135
hwloc_topology_restrict	hwloc_linux_parse_cpumap_file, 135
Tinker With Topologies., 77	hwloc_linux_set_tid_cpubind, 135
hwloc_topology_set_custom	local_memory
Configure Topology Detection, 70	hwloc_obj_memory_s, 164
hwloc_topology_set_distance_matrix	logical_index
Configure Topology Detection, 70	hwloc_obj, 160
hwloc_topology_set_flags	membind
Configure Topology Detection, 70	
hwloc_topology_set_fsroot	hwloc_topology_support, 170
Configure Topology Detection, 70	memory
hwloc_topology_set_pid	hwloc_obj, 160
Configure Topology Detection, 71	Memory binding, 88
hwloc_topology_set_synthetic	HWLOC_MEMBIND_BIND, 90
Configure Topology Detection, 71	HWLOC_MEMBIND_DEFAULT, 90
hwloc_topology_set_userdata_export_callback	HWLOC_MEMBIND_FIRSTTOUCH, 90
Exporting Topologies to XML., 74	HWLOC_MEMBIND_INTERLEAVE, 90
hwloc_topology_set_userdata_import_callback	HWLOC_MEMBIND_MIGRATE, 89
Exporting Topologies to XML., 74	HWLOC_MEMBIND_MIXED, 90
hwloc_topology_set_xml	HWLOC_MEMBIND_NEXTTOUCH, 90
Configure Topology Detection, 71	HWLOC_MEMBIND_NOCPUBIND, 90
hwloc_topology_set_xmlbuffer	HWLOC_MEMBIND_PROCESS, 89
Configure Topology Detection, 72	HWLOC_MEMBIND_REPLICATE, 90
hwloc_topology_support, 170	HWLOC_MEMBIND_STRICT, 89
cpubind, 170	HWLOC_MEMBIND_THREAD, 89
discovery, 170	hwloc_alloc, 90
membind, 170	hwloc_alloc_membind, 90
hwloc_topology_t	hwloc_alloc_membind_nodeset, 91
Topology context, 60	hwloc_free, 91
	hwloc_get_area_membind, 91
infos	hwloc_get_area_membind_nodeset, 91
hwloc_obj, 160	hwloc_get_membind, 92
infos_count	hwloc_get_membind_nodeset, 92

hwloc_get_proc_membind, 93	hwloc_obj, 161
hwloc_get_proc_membind_nodeset, 93	OpenCL Specific Functions, 139
hwloc_membind_flags_t, 89	hwloc_opencl_get_device_cpuset, 139
hwloc_membind_policy_t, 90	hwloc_opencl_get_device_osdev, 139
hwloc_set_area_membind, 94	hwloc_opencl_get_device_osdev_by_index, 139
hwloc_set_area_membind_nodeset, 94	OpenFabrics-Specific Functions, 148
hwloc_set_membind, 94	hwloc_ibv_get_device_cpuset, 148
hwloc_set_membind_nodeset, 94	hwloc_ibv_get_device_osdev, 148
hwloc_set_proc_membind, 94	hwloc_ibv_get_device_osdev_by_name, 148
hwloc_set_proc_membind_nodeset, 95	OpenGL display specific functions, 146
migrate_membind	hwloc_gl_get_display_by_osdev, 146
hwloc_topology_membind_support, 169	hwloc_gl_get_display_osdev_by_name, 146
Myrinet Express-Specific Functions, 149	hwloc_gl_get_display_osdev_by_port_device, 146
hwloc_mx_board_get_device_cpuset, 149	os_index
hwloc_mx_endpoint_get_device_cpuset, 149	hwloc_obj, 161
NIVIDIA Managament Library Considia Franctions 145	os_level
NVIDIA Management Library Specific Functions, 145	hwloc_obj, 161
hwloc_nvml_get_device_cpuset, 145	osdev
hwloc_nvml_get_device_osdev, 145	hwloc_obj_attr_u, 163
hwloc_nvml_get_device_osdev_by_index, 145	nana kunan
name	page_types
hwloc_disc_component, 155 hwloc_obj, 160	hwloc_obj_memory_s, 164
hwloc_obj_info_s, 163	page_types_len
_ ·	hwloc_obj_memory_s, 165
nbobjs	parent
hwloc_distances_s, 157 next_cousin	hwloc_obj, 161
hwloc_obj, 160	bwlee chi attr unbwlee bridge attr e 152
next_sibling	hwloc_obj_attr_u::hwloc_bridge_attr_s, 153 pcidev
hwloc_obj, 161	hwloc_obj_attr_u, 163
nexttouch_membind	prev_cousin
hwloc_topology_membind_support, 169	hwloc_obj, 161
nodeset	prev_sibling
hwloc_obj, 161	hwloc obj, 161
Nodeset Helpers, 112	priority
hwloc_topology_get_allowed_nodeset, 112	hwloc_disc_component, 156
hwloc_topology_get_complete_nodeset, 112	private_data
hwloc_topology_get_topology_nodeset, 112	hwloc_backend, 152
notify_new_object	pu
hwloc_backend, 152	hwloc topology discovery support, 168
	_ 1
Object sets (hwloc_cpuset_t and hwloc_nodeset_t), 61	relative_depth
hwloc_const_cpuset_t, 61	hwloc_distances_s, 157
hwloc_const_nodeset_t, 61	replicate_membind
hwloc_cpuset_t, 61	hwloc_topology_membind_support, 169
hwloc_nodeset_t, 61	Retrieve Objects, 80
Object Type Helpers, 97	hwloc_get_obj_by_depth, 80
hwloc_get_type_or_above_depth, 97	hwloc_get_obj_by_type, 80
hwloc_get_type_or_below_depth, 97	revision
Object/String Conversion, 81	hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
hwloc_obj_add_info, 81	
hwloc_obj_attr_snprintf, 81	secondary_bus
hwloc_obj_cpuset_snprintf, 81	hwloc_obj_attr_u::hwloc_bridge_attr_s, 153
hwloc_obj_get_info_by_name, 82	set_area_membind
hwloc_obj_snprintf, 82	hwloc_topology_membind_support, 169
hwloc_obj_type_of_string, 82	set_proc_cpubind
hwloc_obj_type_snprintf, 82	hwloc_topology_cpubind_support, 167
hwloc_obj_type_string, 82	set_proc_membind
online_cpuset	hwloc_topology_membind_support, 169

set_thisproc_cpubind	hwloc_bitmap_set, 125
hwloc_topology_cpubind_support, 167	hwloc_bitmap_set_ith_ulong, 125
set_thisproc_membind	hwloc_bitmap_set_range, 125
hwloc_topology_membind_support, 170	hwloc_bitmap_singlify, 125
set_thisthread_cpubind	hwloc_bitmap_snprintf, 126
hwloc_topology_cpubind_support, 167	hwloc_bitmap_sscanf, 126
set_thisthread_membind	hwloc_bitmap_t, 122
hwloc_topology_membind_support, 170	hwloc_bitmap_taskset_asprintf, 126
set_thread_cpubind	hwloc_bitmap_taskset_snprintf, 126
hwloc topology cpubind support, 167	hwloc_bitmap_taskset_sscanf, 126
sibling rank	hwloc_bitmap_to_ith_ulong, 126
hwloc_obj, 162	hwloc_bitmap_to_ulong, 126
size	hwloc_bitmap_weight, 127
hwloc_obj_attr_u::hwloc_cache_attr_s, 154	hwloc_bitmap_xor, 127
hwloc_obj_memory_s::hwloc_obj_memory_page-	hwloc_bitmap_zero, 127
_type_s, 164	hwloc_const_bitmap_t, 122
subdevice id	Tinker With Topologies., 76
hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166	· -
subordinate_bus	HWLOC_RESTRICT_FLAG_ADAPT_DISTANCE-
hwloc_obj_attr_u::hwloc_bridge_attr_s, 153	S, 76
subvendor id	HWLOC_RESTRICT_FLAG_ADAPT_IO, 76
hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166	HWLOC_RESTRICT_FLAG_ADAPT_MISC, 76
symmetric subtree	hwloc_restrict_flags_e, 76
hwloc obj, 162	hwloc_topology_insert_misc_object_by_cpuset, 76
11WIOC_ODJ, 102	hwloc_topology_insert_misc_object_by_parent, 76
The bitmap API, 120	hwloc_topology_restrict, 77
hwloc_bitmap_allbut, 122	Topology context, 60
hwloc_bitmap_alloc, 122	hwloc_topology_t, 60
hwloc_bitmap_alloc_full, 122	Topology Object Types, 62
hwloc_bitmap_and, 122	HWLOC_OBJ_BRIDGE, 64
	HWLOC_OBJ_BRIDGE_HOST, 63
hwloc_bitmap_andnot, 122	HWLOC_OBJ_BRIDGE_PCI, 63
hwloc_bitmap_asprintf, 122	HWLOC_OBJ_CACHE, 64
hwloc_bitmap_clr, 122	HWLOC_OBJ_CACHE_DATA, 63
hwloc_bitmap_clr_range, 122	HWLOC_OBJ_CACHE_INSTRUCTION, 63
hwloc_bitmap_compare, 123	HWLOC_OBJ_CACHE_UNIFIED, 63
hwloc_bitmap_compare_first, 123	HWLOC OBJ CORE, 64
hwloc_bitmap_copy, 123	HWLOC_OBJ_GROUP, 64
hwloc_bitmap_dup, 123	HWLOC OBJ MACHINE, 63
hwloc_bitmap_fill, 123	·
hwloc_bitmap_first, 123	HWLOC_OBJ_MISC, 64
hwloc_bitmap_foreach_begin, 121	HWLOC_OBJ_NODE, 63
hwloc_bitmap_foreach_end, 121	HWLOC_OBJ_OS_DEVICE, 64
hwloc_bitmap_free, 123	HWLOC_OBJ_OSDEV_BLOCK, 63
hwloc_bitmap_from_ith_ulong, 123	HWLOC_OBJ_OSDEV_COPROC, 63
hwloc_bitmap_from_ulong, 123	HWLOC_OBJ_OSDEV_DMA, 63
hwloc_bitmap_intersects, 124	HWLOC_OBJ_OSDEV_GPU, 63
hwloc_bitmap_isequal, 124	HWLOC_OBJ_OSDEV_NETWORK, 63
hwloc_bitmap_isfull, 124	HWLOC_OBJ_OSDEV_OPENFABRICS, 63
hwloc_bitmap_isincluded, 124	HWLOC_OBJ_PCI_DEVICE, 64
hwloc_bitmap_isset, 124	HWLOC_OBJ_PU, 64
hwloc_bitmap_iszero, 124	HWLOC_OBJ_SOCKET, 64
hwloc_bitmap_last, 124	HWLOC_OBJ_SYSTEM, 63
hwloc_bitmap_list_asprintf, 124	HWLOC_OBJ_TYPE_MAX, 64
hwloc_bitmap_list_snprintf, 124	HWLOC_TYPE_UNORDERED, 62
hwloc_bitmap_list_sscanf, 125	hwloc_compare_types, 64
hwloc_bitmap_next, 125	hwloc_compare_types_e, 62
hwloc_bitmap_not, 125	hwloc_obj_bridge_type_e, 62
hwloc_bitmap_only, 125	hwloc_obj_bridge_type_t, 62
hwloc_bitmap_or, 125	hwloc_obj_cache_type_e, 63

```
hwloc_obj_cache_type_t, 62
    hwloc_obj_osdev_type_e, 63
    hwloc_obj_osdev_type_t, 62
    hwloc_obj_type_t, 63
Topology Objects, 65
    hwloc_obj_t, 65
total_memory
    hwloc_obj_memory_s, 165
type
    hwloc_component, 155
    hwloc_disc_component, 156
    hwloc_obj, 162
    hwloc_obj_attr_u::hwloc_cache_attr_s, 154
    hwloc_obj_attr_u::hwloc_osdev_attr_s, 165
upstream
    hwloc_obj_attr_u::hwloc_bridge_attr_s, 153
upstream_type
    hwloc_obj_attr_u::hwloc_bridge_attr_s, 153
userdata
    hwloc_obj, 162
value
    hwloc_obj_info_s, 163
vendor_id
    hwloc_obj_attr_u::hwloc_pcidev_attr_s, 166
```