# Notes for Using "Imfit"

# Peter Erwin MPE and USM erwin@sigmaxi.net

# October 9, 2012

# **Contents**

| 1      | What Is It?   | 2                          |
|--------|---|----------------------------|
| 2      | Getting and Installing Imfit  2.1 Pre-Compiled Binaries  2.2 Building Imfit from Source: Outline  2.3 Building Imfit from Source: Details  2.3.1 Telling SCons Where to Find Header Files and Libraries  2.3.2 Option: Compiling with OpenMP Support  2.3.3 Options: Compiling without FFT Multithreading | 3<br>4<br>4<br>5<br>5<br>5 |
| 3      | Trying It Out   | 6                          |
| 4      | Using Imfit   | 6                          |
| 5<br>6 | 5.2 Parameter Limits  | 8<br>10<br>11              |
| 7      | Images  | <b>13</b> 13               |
| 8      | 8.1 Masks   | 14<br>14<br>14<br>15       |
| 9      | Minimization Options: Levenberg-Marquardt vs. Differential Evolution  | 15                         |
| 10     | Output  | 16                         |

| 11 | Makeimage  | 16 |
|----|--|----|
|    | 11.1 Using Makeimage                                   | 17 |
|    | 11.2 Configuration Files for Makeimage                 | 17 |
|    | 11.3 Generating Single-Function Output Images          | 18 |
|    | 11.4 Using Makeimage to Estimate Fluxes and Magnitudes | 18 |
| 12 | Rolling Your Own Functions                             | 19 |
|    | 12.1 Basic Requirements                                | 19 |
|    | 12.2 A Simple Example                                  | 19 |
|    | 12.2.1 Create and Edit the Header File                 | 20 |
|    | 12.2.2 Create and Edit the Class File                  | 20 |
|    | 12.2.3 Edit add_functions.cpp                          | 22 |
|    | 12.2.4 Edit the SConstruct File                        | 22 |
| A  | Standard Functions in Detail                           | 22 |
|    | A.1 FlatSky  | 23 |
|    | A.2 Gaussian   | 23 |
|    | A.3 Moffat   | 23 |
|    | A.4 Exponential  | 24 |
|    | A.5 Exponential_GenEllipse                             | 24 |
|    | A.6 Sersic   | 24 |
|    | A.7 Sersic_GenEllipse                                  | 25 |
|    | A.8 Core-Sersic  | 25 |
|    | A.9 BrokenExponential                                  | 26 |
|    | A.10 Gaussian Ring                                     | 26 |
|    | A.11 GaussianRing2Side                                 | 26 |
|    | A.12 EdgeOnDisk  | 27 |
|    | A.13 EdgeOnRing  | 27 |
|    | A.14 EdgeOnRing2Side                                   | 28 |
|    | A.15 ExponentialDisk3D                                 | 28 |
| В  | Acknowledgments  | 29 |
|    | B.1 Data Sources                                       | 29 |
|    | B.2 Specific Software Acknowledgments                  |    |
|    | B.2.1 Minpack  |    |

# 1 What Is It?

Imfit is a program for fitting astronomical images — more specifically, for fitting images of galaxies, though it could certainly be used for fitting other sources. The user specifies a set of one or more 2D functions (e.g., elliptical exponential, elliptical Sérsic, circular Gaussian) which will be added together in order to generate a model image; this model image will then be matched to the input image by adjusting the 2D function parameters via nonlinear minimization of the total  $\chi^2$ .

The 2D functions can be grouped into arbitrary sets sharing a common (x, y) position on the image plane; this allows galaxies with off-center components or multiple galaxies to be fit simultaneously. Parameters for the individual functions can be held fixed or restricted to user-specified ranges. The model image can (optionally) be convolved with a Point Spread Function (PSF) image to better match the input image; the PSF image can be any square, centered image the user supplies (e.g., an analytic 2D Gaussian or Moffat, a *Hubble Space Telescope* PSF generated by the TinyTim program Krist [1995]<sup>1</sup>, or an actual stellar image).

A key part of imfit is a modular, object-oriented design that allows easy addition of new, user-specified 2D image functions. This is accomplished by writing C++ code for a new image-function class (this can be done by copying and modifying an existing pair of .h/.cpp files for one of the pre-supplied image functions), making small modifications to two additional files to include references to the new function, and re-compiling the program.

An additional auxiliary program called makeimage, built from the same codebase, exists for generating artificial galaxy images (using the same input/output parameter-file format as imfit).

Imfit is an open-source project; the source code is freely available under the GNU Public License (GPL).

**System Requirements:** Imfit has been built and tested on Intel-based MacOS X (Snow Leopard and Lion) and Linux (Ubuntu) systems. It uses standard C++ and should work on any Unix-style system with a modern C++ compiler and the Standard Template Library (e.g., GCC v4 or higher<sup>2</sup>). It relies on two external, open-source libraries: version 3 of the CFITSIO library<sup>3</sup> for FITS image I/O and version 3 of the FFTW (Fastest Fourier Transform in the West) library<sup>4</sup> for PSF convolution.

Imfit also makes use of Craig Markwardt's mpfit code (an enhanced version of the MINPACK-1 Levernberg-Marquardt least-squares fitting code) and the Differential Evolution fitting code of Rainer Storn and Kenneth Price (more specifically, a C++ wrapper written by Lester E. Godwin).

# 2 Getting and Installing Imfit

## 2.1 Pre-Compiled Binaries

Pre-built binaries for Intel-based MacOS X and Linux systems, along with the source code, are available at http://www.mpe.mpg.de/~erwin/code/imfit/. The pre-compiled binaries included statically linked versions of the CFITSIO, FFTW, and GSL libraries, so you do not need to have those installed.

 $<sup>^{1}</sup>$ http://www.stsci.edu/hst/observatory/focus/TinyTim

<sup>&</sup>lt;sup>2</sup>GCC v4.2 or higher is necessary to take advantage of OpenMP-related speedups.

<sup>3</sup>http://heasarc.nasa.gov/fitsio/

<sup>4</sup>http://www.fftw.org/

## 2.2 Building Imfit from Source: Outline

- 1. Install the CFITSIO library.
- 2. Install the FFTW library note that if you have a multi-core CPU (or multiple CPUs sharing main memory), you should install the threaded version of FFTW as well, since this speeds up PSF convolution.
- 3. (Optional) Install the GNU Scientific Library (GSL) this is only necessary if you wish to use 2D image functions that rely on GSL. Currently, the only such functions are the EdgeOnDisk (func\_edge-on-disk.cpp) component, which uses a modified Bessell function, and the sample 3D line-of-sight integration functions (e.g., ExponentialDisk3D, func\_expdisk3d.cpp). Imfit can easily be built without these components, if for some reason you don't have access to the GSL.
- 4. Install SCons.
- 5. Build imfit and makeimage.
- 6. (optional) Run test scripts do\_imfit\_tests and do\_makeimage\_tests.

### 2.3 Building Imfit from Source: Details

Assuming that CFITSIO and FFTW (and optionally GSL) have already been installed on your system, unpack the source-code tarball (imfit-x.x-source.tar.gz) in some convenient location.

Imfit uses SCons for the build process. SCons is a Python-based build system that is somewhat easier to use and more flexible than the traditional make system; it can be downloaded from http://www.scons.org/.

If things are simple, you should be able to build imfit and the companion program makeimage with the following commands:

```
$ scons imfit
$ scons makeimage
```

This will produce two binary executable files: imfit and makeimage. Copy these to some convenient place on your path.

If you do not have GSL installed, you will get compilation errors; use the following commands instead:

```
$ scons --no-gsl imfit
$ scons --no-gsl makeimage
```

Various other compilation options may be useful; these are explained in the next subsections (note that all the SCons options can be combined on the command line).

Finally, there are two shell scripts - do\_imfit\_tests and do\_makeimage\_tests - which can be run to do some very simple sanity checks (e.g., do the programs fit some simple images correctly, are common config-file errors caught, etc.). They make use of files and data in the tests/ subdirectory. (For the full set of tests to run, you should have

Python version 2.6 or 2.7 installed, along with the numpy<sup>5</sup> and pyfits<sup>6</sup> Python libraries. If these are not available, then the parts of the tests which compare output images with reference versions will simply be skipped.)

#### 2.3.1 Telling SCons Where to Find Header Files and Libraries

By default, the SConstruct file (the equivalent of a Makefile for SCons) tells SCons to look for header files in /usr/local/include and library files in /usr/local/lib. If you have the FFTW, CFITSIO, and (optionally) GSL headers and libraries installed somewhere else, you can tell SCons about this by using the --header-path and --lib-path options:

```
$ scons --header-path=/some/path ...
$ scons --lib-path=/some/other/path ...
```

(note that "..." is meant to stand for the rest of the compilation command, whatever that may be).

Multiple paths can be specified if they are separated by colons, e.g.

```
$ scons --lib-path=/some/path:/some/other/path ...
```

#### 2.3.2 Option: Compiling with OpenMP Support

Imfit and makeimage can be compiled to take advantage of OpenMP compiler support, which speeds up image computation by splitting it up across multiple CPUs (and multiple cores within multi-core CPUs). Currently, the code uses OpenMP 2.5 options, which means that if you are using the GCC compiler, you need version 4.2 or higher.

To include OpenMP support, compile using the following options:

```
$ scons --openmp imfit
$ scons --openmp makeimage
```

#### 2.3.3 Options: Compiling without FFT Multithreading

By default, imfit and makeimage are compiled to take advantage of multi-core CPUs (and other shared-memory multiple-processor systems) when performing PSF convolutions by using the multithreaded version of the FFTW library. If you do not have (or cannot build) the multithreaded FFTW library, you can remove multithreaded FFT computation by compiling with the following commands:

```
$ scons --no-threading imfit
$ scons --no-threading makeimage
```

<sup>5</sup>http://numpy.scipy.org/

<sup>&</sup>lt;sup>6</sup>http://www.stsci.edu/institute/software\_hardware/pyfits

# 3 Trying It Out

In the examples/ directory are some sample galaxy images, masks, PSF images, and configuration files.

To give imfit a quick spin (and check that it's working on your system), change to the examples/ directory and execute the following on the command line (assuming that imfit is now in your path):

```
$ imfit ic3478rss_256.fits -c config_sersic_ic3478_256.dat --sky=130.14
```

This converges to a fit in a few seconds or less (e.g., about 0.5 seconds on a 2011 MacBook Pro with a 2.3 GHz Core i7 processor). In addition to being printed to the screen, the final fit is saved in a file called bestfit\_parameters\_imfit.dat.

The preceding command told imfit to fit using every pixel in the image and to estimate the noise assuming an original (previously subtracted) sky level of 130.14, an A/D gain of 1.0, and zero read noise (the latter two are default values). A better approach would be to include a mask (telling imfit to ignore, e.g., pixels occupied by bright stars) and to specify more accurate values of the gain and read noise:

```
$ imfit ic3478rss_256.fits -c config_sersic_ic3478_256.dat --mask ic3478rss_256_mask.fits --gain=4.725 --readnoise=4.3 --sky=130.14
```

If you want to see what the best-fitting model looks like, you can use the companion program makeimage on the output file:

```
$ makeimage bestfit_parameters_imfit.dat --refimage ic3478rss_256.fits
```

This will generate and save the model image in a file called modelimage.fits.

You can also fit the image using PSF convolution, by adding the "--psf" option and a valid FITS image for the PSF; the examples/ directory contains a Moffat PSF image which matches stars in the original image fairly well:

```
imfit ic3478rss_256.fits -c config_sersic_ic3478_256.dat --mask ic3478rss_256_mask.fits --gain=4.725 --readnoise=4.3 --sky=130.14 --psf psf_moffat_51.fits
```

The PSF image was generated using makeimage and the configuration file makeimage\_config\_moffat\_psf\_51\_for\_ic3478rss.dat:

```
\label{lem:makeimage} $$--ncols=51 --nrows=51 -o psf_moffat_51.fits makeimage\_config_moffat_psf_51_for_ic3478rss.dat
```

# 4 Using Imfit

Basic use of imfit from the command line looks like this:

```
$ imfit -c config-file input-image [options]
```

where *config-file* is the name of the configuration file which describes the model (the combination of 2D functions, initial values for parameters, and possible limits on parameter values) and *input-image* is the FITS image we want to fit with the model.

The "options" are a set of command-line flags and options (use "imfit -h" or "imfit --help" to see the complete list). Options must be followed by an appropriate value (e.g., a filename, an integer, a floating-point number); this can be separated from the option by a space, or they can be connected with an equals sign. In other words, both of the following are valid:

```
imfit --gain 2.5
imfit --gain=2.5
```

Note that imfit does not follow the full GNU standard for command-line options and flags (as implemented by, e.g., the GNU getopt library): you cannot merge multiple one-character flags into a single item (if "-a" and "-b" are flags, "-a -b" will work, but "-ab" will not), and you cannot merge a one-character option and its target ("-cfoo.dat" is not a valid substitute for "-c foo.dat").

Some notable and useful command-line flags and options include:

- --psf *psf-image* specifies a FITS image to be convolved with the model image.
- --mask *mask-image* specifies a FITS image which marks bad pixels to be ignored in the fitting process (by default, zero values in the mask indicate *good* pixels, and positive values indicate bad pixels).
- --mask-zero-is-bad indicates that zero values (actually, any value < 1.0) in the mask correspond to *bad* pixels, with values ≥ 1.0 being good pixels.
- --noise *noisemap-image* specifies a pre-existing noise or error FITS image to use in the fitting process (by default, pixel values in the noise map are assumed to be sigma values).
- --errors-are-variances indicates that pixel values in the noise map are variances (sigma<sup>2</sup>) instead of sigmas.
- --errors-are-weights indicates that pixel values in the noise map should be interpreted as weights, not as sigmas or variances.
- --sky *sky-level* specifies an original sky background level (in counts/pixel) that was subtracted from the image; used for internal computation of the noise map.
- --gain *value* specifies the A/D gain (in electrons/ADU) of the input image; used for internal computation of the noise map.
- --readnoise *value* specifies the read noise (in electrons) of the input image; used for internal computation of the noise map.

- --ncombined value if values in the input image are the result of averaging (or computing the median of) two or more original images, then this option should be used to specify the number of original images; used for internal computation of the noise map. If multiple images were added together with no rescaling, then do not use this option.
- --save-params output-filename specifies that parameters for best-fitting model should be saved using the specified filename (default is for these to be saved in a file named bestfit\_parameters\_imfit.dat).
- --save-model output-filename the best-fitting model image will be saved using the specified filename.
- --save-residual *output-filename* the residual image (input image best-fitting model image) will be saved using the specified filename.
- --de use Differential Evolution instead of Levenberg-Marquardt as the  $\chi^2$  minimization technique (WARNING: much slower!)
- --chisquare-only Evaluate the  $\chi^2$  value for the initial input model as a fit to the input image, *without* doing any minimization to find a better solution. bigskip
- --max-threads specifies the maximum number of CPU cores to use during computation (the default is to use *all* available CPU cores); has no effect if imfit was compiled without OpenMP or FFTW multithreading support.
- --list-functions list all the functions imfit can use.
- --list-parameters list all the individual parameters (in correct order) for each
  of the functions that imfit can use.

# 5 The Configuration File

Imfit always requires a configuration file, which specifies the model which will be fit to the input image, initial values for model parameters, any limits on parameter values (optional for fitting with the Levenberg-Marquardt solver, but required for fitting with the Differential Evolution solver), and possibly additional information (e.g, gain and read noise for the input image).

The configuration file should be a plain text file. Blank lines and lines beginning with "#" are ignored; in fact, anything on the same line after a "#" is ignored, which allows for comments at the end of lines.

A model for an image is specified by one or more **function blocks**, each of which is a group of one or more 2D image functions sharing a common (x, y) spatial position. Each

function-specification consists of a line beginning with "FUNCTION" and containing the function name, followed by one or more lines with specifications for that function's parameters.

More formally, the format for a configuration file is:

- 1. Optional specifications of general parameters and settings (e.g., the input image's A/D gain and read noise)
- 2. One or more function blocks, each of which contains:
  - (a) X-position parameter-specification line
  - (b) Y-position parameter-specification line
  - (c) One or more function + parameters specifications, each of which contains:
    - i. FUNCTION + function-name line
    - ii. one or more parameter-specification lines

This probably sounds more complicated than it is in practice. Here is a very barebones example of a configuration file:

```
X0 150.1

Y0 149.5

FUNCTION Exponential

PA 95.0

ell 0.45

I_0 90.0

h 15.0
```

This describes a model consisting of a single elliptical exponential function, with initial values for the x and y position on the image, the position angle (PA), the ellipticity (ell), the central intensity (I\_0) in counts/pixel, and the exponential scale length in pixels (h). None of the parameters have limits on their possible values.

Here is the same file, with some additional annotations and with limits on some of the parameters (comments are colored red for clarity):

#### # This line is a comment

```
X0 150.1 148,152

Y0 149.5 148,152 # a note

FUNCTION Exponential # here is a comment

PA 95.0 0,180 # limits on the position angle

ell 0.45 0,1 # ellipticity should always be 0--1

I_{-0} 90.0 fixed # keep central intensity fixed

h 15.0
```

Here we can see the use of comments (lines or parts of lines beginning with "#") and the use of parameter limits in the form of "lower,upper": the X0 and Y0 parameters are required to remain  $\geq 148$  and  $\leq 152$ , the position angle is limited to 0–180, the ellipticity must stay  $\geq 0$  and  $\leq 1$ , and the central intensity I\_0 is held fixed at its initial value.

Finally, here is a more elaborate example, specifying a model that has two function blocks, with the first block having two individual functions (so this could be a model for, e.g., simultaneously fitting two galaxies in the same image, one as Sérsic + exponential, the other with just an exponential):

```
# This line is a comment
GAIN 2.7 # A/D gain for image in e/ADU
READNOISE 4.5 # image read-noise in electrons
# This is the first function block: Sersic + exponential
     150.1
            148,152
     149.5
YΟ
              148,152
FUNCTION Sersic # A Sersic function
PA
    95.0
            0,180
ell
    0.05
            0,1
    2.5
n
            0.5, 4.0
                       # Sersic index
I_{-}e
    20.0
             # intensity at the half-light radius
     5.0
            # half-light radius in pixels
FUNCTION Exponential
PA
   95.0
            0,180
     0.45
            0,1
ell
I_0
     90.0 fixed
    15.0
# This is the second function block: just a single exponential
     225.0
              224,226
XΟ
YΟ
     181.7
              180,183
FUNCTION Exponential
    22.0
            0,180
    0.25
ell
            0,1
I_0
     10.0
     20.0
h
```

### 5.1 Parameter Names, Specifications, and Values

The X0/Y0 position lines at the start of each function block and the individual parameter lines for each function all share a common format:

parameter-name initial-parameter-value optional-limits

The separation between the individual pieces must consist of one or more spaces and/or tabs. The final piece specifying the limits is optional (except that fitting in Differential Evolution mode *requires* that there be limits for each parameter).

**Parameter Names:** The X0/Y0 positional parameters for each function block must be labeled "X0" and "Y0". Names for the parameters of individual functions can be anything the user desires; only the order matters. Thus, the position-angle parameter could be labeled "PA", "PosAngle", "angle", or any non-space-containing string — though it's a good idea to have it be something relevant and understandable.

**Important Note:** *Do not change the order of the parameters for a particular function!* Because the strings giving the parameter names can be anything at all, imfit actually ignores them and simply assumes that all parameters are in the correct order for each function.

Note that any output which imfit generates will use the default parameter names defined in the individual function code (use "--list-parameters" to see what these are for each function).

Values for Positional Parameter (X0, Y0): The positional parameters for each function block are pixel values – X0 for the column number and Y0 for the row number. Imfit uses the IRAF pixel-numbering convention: the center of first pixel in the image (the lower left pixel in a standard display) is at (1.0, 1.0), with the lower-left corner of that pixel having the coordinates (0.5, 0.5).

**General Parameter Values for Functions**: The meaning of the individual parameter values for the various 2D image functions is set by the functions themselves, but in general:

- position angles are measured in degrees counter-clockwise from the image's vertical (+y) axis (i.e., degrees E of N if the image has standard astronomical orientation);
- ellipticity = 1 b/a, where a and b are the semi-major and semi-minor axes of an ellipse;
- intensities are in counts/pixel;
- lengths are in pixels.

If you write your own functions, you are encouraged to stick to these conventions.

#### 5.2 Parameter Limits

Individual parameters can be limited in two ways:

- 1. Held fixed;
- 2. Restricted to lie between lower and upper limits.

To hold a parameter fixed, use the string "fixed" after the initial-value specification, e.g.:

X0 442.85 fixed

To specify lower and upper limits for a parameter, include them as a comma-separated pair following the initial-value specification, e.g.:

xo 442.85 441.0,443.5

# 6 Standard Image Functions

Imfit comes with the following 2D image functions, each of which can be used as many times as desired. (As mentioned above, imfit is designed so that constructing and using new functions is a relatively simple process.) Note that elliptical functions can always be made circular by setting the "ellipticity" parameter to 0.0 and specifying that it be held fixed. See Appendix A for more complete discussions of each function, including their parameters.

- FlatSky a uniform sky background.
- Gaussian an elliptical 2D Gaussian function.
- Moffat an elliptical 2D Moffat function.
- Exponential an elliptical 2D exponential function.
- Exponential\_GenEllipse an elliptical 2D exponential function using generalized ellipses ("boxy" to "disky" shapes) for the isophote shapes.
- Sersic an elliptical 2D Sérsic function.
- Sersic\_GenEllipse an elliptical 2D Sérsic function using generalized ellipses ("boxy" to "disky" shapes) for the isophotes.
- Core-Sersic an elliptical 2D Core-Sérsic function.
- BrokenExponential similar to Exponential, but with two exponential radial zones (with different scalelengths) joined by a transition region at R<sub>break</sub> of variable sharpness.
- GaussianRing an elliptical ring with a radial profile consisting of a Gaussian centered at  $r = R_{ring}$ .
- GaussianRing2Side like GaussianRing, but with a radial profile consisting of an asymmetric Gaussian (different values of  $\sigma$  for  $r < R_{\text{ring}}$  and  $r > R_{\text{ring}}$ ).
- EdgeOnDisk the analytical form for a perfectly edge-on exponential disk, using
  the Bessel-function solution of van der Kruit & Searle [1981] for the radial profile
  and the generalized sech function of van der Kruit [1988] for the vertical profile.
  Note that this function requires that the GNU Scientific Library (GSL) be installed;
  if the GSL is not installed, imfit should be compiled without this function (see
  Section 2.3).

- EdgeOnRing a simplistic model for an edge-on ring, using a Gaussian for the radial profile and another Gaussian (with different  $\sigma$ ) for the vertical profile.
- EdgeOnRing2Side like EdgeOnRing, but using an asymmetric Gaussian for the radial profile (see description of GaussianRing2Side).
- ExponentialDisk3D an experimental component which uses line-of-sight integration through a 3D luminosity-density model of an exponential disk, observed at an arbitrary inclination, to generate a projected surface-brightness image. As in the case of the EdgeOnDisk component, the GSL is required for this component.

A list of the currently available functions can always be obtained by running imfit with the "--list-functions" option:

```
$ imfit --list-functions
```

The complete list of function parameters for each function (suitable for copying and pasting into a configuration file) can always be obtained by running imfit with the "--list-parameters" option:

```
$ imfit --list-paremeters
```

# 7 Images

Imfit is designed to fit 2D astronomical images in FITS format, where pixel values are some form of linear surface-brightness (or surface density) measurement. The default internal error calculations (see Section 8.2, below) assume that pixel values are integrated counts (e.g., ADUs), which can be converted to detected photons using the A/D gain. However, since imfit can also accept a user-supplied noise/error image in FITS format, you can use any linear pixel values as long as the corresponding noise image is appropriately scaled to match.

If your image is in counts/second, you should multiply it by the exposure time to recover the integrated counts (or incorporate the exposure time into the gain value), otherwise imfit will overestimate the errors. (Future versions of imfit may include a means of directly specifying the exposure time.)

If the image is an *average* of N input images of the same exposure time, you can either multipy the image by N or use the "--ncombined" option to tell imfit how to adjust the error estimations.

Imfit does *not* assume the presence of any particular header keywords in the FITS file.

### 7.1 Specifying Image Subsections, Compressed Images, etc.

In many cases, you may want to fit an object which is much smaller than the whole image. You can always make a smaller cutout image and fit that, but it may be convenient to specify the image subsection directly. You can do this using a subset of the image-section syntax of CFITSIO (which will be familiar to you if you've ever worked with image sections in IRAF). An example:

ic3478rss\_256.fits[45:150,200:310]

This will fit columns 45–150 and rows 200–310 of the image (column and row numbering starts at 1). Pixel coordinates in the configuration (and output) files refer to locations within the *full* image.

The only kind of image section specification that's allowed is a simple [x1:x2,y1:y2] format, though you can specify all of a particular dimension using an asterisk (e.g., [\*,y1:y2] to specify the full range of x values). More complicated expressions which might extract part of a 3D datacube are not (currently) possible. However, you *can* specify a particular extension (header-data unit) in a multi-extension FITS file, e.g.:

ic3478rss.fits[2] ic3478rss.fits[2][45:150,200:310]

Obviously, if you are also using a mask image (and/or a noise image), you should specify the same subsection in those images!

You can also use fit (or generate) images which have been compressed with gzip or Unix compress — e.g., ic3478rss\_256.fits.gz, and images, masks, etc., can even be read via http:// or ftp:// URLs which point directly to accessible FITS files — e.g., http://someplace.net/images/somefile.fits (you cannot *save* files to URLs, however).

# 8 Extras for Fitting Images

### 8.1 Masks

A mask image can be supplied to imfit by using the command-line options --mask. The mask image should be an *integer*-valued FITS file with the same dimensions as the image being fitted (IRAF .pl mask files are not recognized, but these can be converted to FITS format within IRAF). The default is to treat zero-valued pixels in the mask image as *good* and pixels with values > 0 as *bad* (i.e., to be excluded from the fit); however, you can specify that zero-valued pixels are *bad* with the command-line flag --mask-zero-is-bad.

# 8.2 Noise, Variance, or Weight Maps

By default, imfit calculates a weight map internally, using the input pixel intensities, the A/D gain, any previously subtracted background level, and the read noise to estimate Gaussian errors  $\sigma_i$  for each pixel i. The final weight map is  $w_i = 1/\sigma_i^2$ . These weights are then used in the  $\chi^2$  calculation, summing over all N pixels:

$$\chi^2 = \sum_{i=0}^{N} w_i (I_{\text{mod},i} - I_{\text{im},i})^2, \tag{1}$$

where  $I_{\text{mod},i}$  and  $I_{\text{im},i}$  are the model and data intensities in counts/pixel, respectively. (Masking is handled by setting  $w_i = 0$  for masked pixels.)

If you have a pre-existing error map as a FITS image, you can tell imfit to use that instead, via the --noise command-line option. By default, the pixel values in this image are assumed to be errors  $\sigma_i$  in units of ADU/pixel. If the values are *variances*  $(\sigma_i^2)$ , you can specify this with the --errors-are-variances flag. You can also tell imfit that the pixel values in the noise map are actual *weights*  $w_i$  via the --errors-are-weights flag, if that happens to be the case. (If a mask image is supplied, the weights of all masked pixels will still be set to 0, regardless of their individual values in the weight image.)

Note that imfit does *not* try to obtain information (such as the A/D gain or read noise) from the FITS header of an image. This is primarily because there is little consistency in header names across the wide range of astronomical images, so it is difficult pick one name, or even a small set, and assume that it will be present in a given image's header; this is even more true if an image is the result of a simulation. (And some image headers use "gain" to mean *inverse* gain (electrons/ADU) . . . .)

#### 8.3 PSF Convolution

TBD.

PSF images should be square, ideally with width = an odd number of pixels, and the PSF should be centered in the central pixel. (An off-center PSF can certainly be used, but the resulting convolved model images will be shifted.)

# 9 Minimization Options: Levenberg-Marquardt vs. Differential Evolution

The default  $\chi^2$  minimization used by imfit is a Levenberg-Marquardt algorithm, based on the classic MINPACK-1 implementation with enhancements by Craig Markwardt.<sup>7</sup> This is very fast and robust, but requires an initial guess for the parameter values and can sometimes become trapped in local minima in the  $\chi^2$  landscape.

A semi-experimental alternate minimization algorithm is available via the --de flag. This performs the  $\chi^2$  minimization using Differential Evolution (DE) [Storn & Price, 1997], a genetic-algorithms approach which is, at least in principle, more likely to find the global  $\chi^2$  minimum. It has the drawback of being *much* slower than Levenberg-Marquardt minimization. For example, fitting a single Sérsic function to the  $256 \times 256$  image in the examples/ subdirectory takes  $\sim 60$  times as long when using Differential Evolution as it does when using L-M minimization (though this might be improved by specifying narrower parameter ranges in the configuration file).

The Differential Evolution approach *requires* lower and upper limits for *all* parameters in the configuration file (see Section 5.2); this is because DE generates parameter-value "genomes" by random uniform sampling from the ranges specified by the parameter limits. The format of the configuration file still requires that initial-guess values be present for all parameters as well, though these are actually ignored by the DE al-

<sup>&</sup>lt;sup>7</sup>Original C version available at http://www.physics.wisc.edu/~craigm/idl/cmpfit.html

<sup>8</sup>http://www.icsi.berkeley.edu/~storn/code.html

gorithm. (This is to ensure that the same configuration file can be used with either minimization routine.)

TBD. [more details of DE implementation]

Note that the DE algorithm does *not* produce error estimates for the best-fitting parameter values, in contrast to the Levenberg-Marquardt approach. However, the L-M error estimates are themselves only reliable if the minimum in the  $\chi^2$  landscape is symmetric and parabolic, and if the errors for the input image are truly Gaussian and well-determined.

The fact that the minimization algorithms are relatively decoupled from the rest of the code means that future versions of imfit could potentially include other minimization techniques.

# 10 Output

TBD.

Assuming that the fitting process converges, imfit will print a summary of the results, including the final, best-fitting parameter values. The output parameter list is in the same format as the configuration file, except that error estimates are listed after each parameter value. The error estimates are separated from the parameter values by "#"; this means that you can copy and paste the parameter list into a text file and use that file as an input configuration file for imfit or makeimage.

The best-fitting parameters will also be written to an output text file (default name = bestfit\_parameters\_imfit.dat; use --save-params to specify a different name), without the error estimates. The output file will also include a copy of the original command used to start imfit and the date and time it was generated; these are commented out so that the file can be used as an imfit or makeimage configuration file.

Also printed are the total  $\chi^2$ , the reduced  $\chi^2$  (which accounts for the total number of unmasked pixels and non-fixed parameter values), and two alternate measures of the fit: the Akaike Information Criterion (AIC) and the Bayesian Information Criterion (BIC). The latter two are included on a provisional basis; they are, in principle, useful for comparing different models fit to the same data.

TBD.

# 11 Makeimage

Imfit has a companion program called makeimage, which will generate model images using the same functions (and parameter files) as imfit. In fact (as noted above), the output "best-fitting parameters" file generated by imfit can be used as input to makeimage, as can an imfit configuration file.

Makeimage *does* require an output image size. This can be specified via command-line flags ("--ncols" and "--nrows"), via specifications in the configuration file (see

<sup>&</sup>lt;sup>9</sup>If Differential Evolution is used as the minimization technique, no errors are estimated.

below), or by supplying a reference FITS image ("--refimage *image-filename*"); in the latter case, the output image will have the same dimensions as the reference image.

Makeimage can also be run in a special mode to estimate the magnitudes and fractional luminosities of different components in a model.

### 11.1 Using Makeimage

Basic use of makeimage from the command line looks like this:

```
$ makeimage [options] config-file
```

where *config-file* is the name of the imfit-style configuration file which describes the model.

As for imfit, the "options" are a set of command-line flags and options (use "makeimage -h" or "makeimage --help" to see the complete list). Options must be followed by an appropriate value (e.g., a filename, an integer, a floating-point number); this can be separated from the option by a space, or they can be connected with an equals sign.

Some notable and useful command-line flags and options include:

- --output *filename* filename for the output model image (default = "modelimage.fits").
- --refimage *filename* existing reference image to use for determining output image dimensions.
- --ncols *N\_columns* number of columns in output image
- --nrows *N\_rows* number of rows in output image
- --psf *psf-image* specifies a FITS image to be convolved with the model image.
- --list-functions list all the functions makeimage can use
- --list-parameters list all the individual parameters (in correct order) for each functions that makeimage can use

#### 11.2 Configuration Files for Makeimage

The configuration file for makeimage has essentially the same format as that for imfit; any parameter limits that might be present are ignored.

Optional general parameters like GAIN and READNOISE are ignored, but the following optional general parameters are available:

- NCOLS number of columns for the output image (x-size)
- NROWS number of rows for the output image (y-size)

## 11.3 Generating Single-Function Output Images

Makeimage can also output individual images for each function in the configuration file. For example, if the configuration file specifies a model with one Sérsic function and two exponential functions, makeimage can generate three separate FITS files, in addition to the (standard) sum of all three functions. This is done with the --output-functions option:

```
--output-functions root-name
```

where *root-name* is a string that all output single-function filenames will start with. The single-function filenames will be sequentially numbered (starting with 1) according to the order of functions in the configuration file, and the name of each function will added to the end; the resulting filenames will have this format:

```
root-nameN_function-name.fits
```

Using the example specified above (a model with one Sérsic and two exponential functions), one could execute the following command

```
$ makeimage config-file --output-functions mod
```

and the result would be three FITS files, named mod1\_Sersic.fits, mod2\_Exponential.fits, and mod3\_Exponential.fits.

### 11.4 Using Makeimage to Estimate Fluxes and Magnitudes

Given a configuration file, you can use makeimage to estimate the total fluxes and magnitudes of different model components. For some components – e.g., the purely elliptical versions of the Gaussian, Exponential, and Sersic functions – there are analytical expressions which could be used. But since imfit and makeimage are designed to use arbitrary functions, including ones which do not have analytical expressions for total flux, makeimage estimates the flux for each component by internally constructing a large model image for each component function in the configuration file, with the component centered within this image, and then summing the pixel values of that image. The output includes a list of total and relative fluxes for each component in the model image (and their magnitudes, if a zero point is supplied).

\$ makeimage -print-fluxes config-file

Useful command-line flags and options:

- --estimation-size *N\_columns\_and\_rows* size of the (square) image to construct (the default size is 5000 pixels on a side)
- --zero-point *value* zero point for converting total counts to magnitudes:

$$m = Z - 2.5 \log_{10}(\text{counts}) \tag{2}$$

This enables you to compute things like bulge/total ratios – but it's up to you to determine which component(s) should be considered "bulge", "disk", etc.

When run in this mode, makeimage will still produce an output image file – unless you also specify the –-nosave option.

# 12 Rolling Your Own Functions

### 12.1 Basic Requirements

A new image function should be implemented in C++ as a subclass of the FunctionObject base class (function\_object.h, function\_object.cpp). At a minimum, it should provide its own implementation of the following public methods, which are defined as virtual methods in the base class:

- Setup() this is used by the calling program to supply the current set of function parameters (including the  $(x_0, y_0)$  pixel values for the center) prior to determining intensity values for individual pixels. This is a convenient place to do any general calculations which don't depend on the exact pixel (x, y) values.
- GetValue() this is used by the calling program to obtain the surface brightness for a given pixel location (x, y). In existing FunctionObject classes, this method often calls other (private) methods to handle details of the calculation.
- GetClassShortName() this is a class function which is used to obtain the short version of the class name as a string.

The new class should also redefine the following internal class constants:

- N\_PARAMS;
- PARAM\_LABELS;
- FUNCTION\_NAME.

The add\_functions.cpp file should then be updated by:

- 1. including the header file for the new class;
- 2. adding 2 lines to the PopulateFactoryMap() function to add the ability to create an instance of the new class.

Finally, the name of the C++ implementation file for the new class should be added to the Sconstruct file to ensure it gets included in the compilation.

Existing examples of FunctionObject subclasses can be found in the "function\_objects" subdirectory of the source-code distribution, and are the best place to look in order to get a better sense of how to implement new FunctionObject subclasses.

### 12.2 A Simple Example

To illustrate, we'll make a new version of the Moffat function (which already exists, so this is purely for pedagogical purposes) by copying and modifying the code for the Gaussian function.

We need to make three sets of changes:

• Change the class name from "Gaussian" to our new name ("NewMoffat");

- Change the relevant code which computes the function;
- Rename, add, or delete variables to accomodate the new algorithm.

#### 12.2.1 Create and Edit the Header File

Change directory to the directory with the imfit source code, and then cd to the "function\_objects" subdirectory. Copy the file func\_gaussian.h and rename it to func\_new-moffat.h. Edit this file and change the following lines:

```
#define CLASS_SHORT_NAME "Gaussian"
(replace "Gaussian" with "NewMoffat")
class Gaussian : public FunctionObject
(replace Gaussian with NewMoffat)
    Gaussian();
(replace Gaussian with NewMoffat)
    And finally edit the list of class data members, changing this:
    private:
        double x0, y0, PA, ell, I_0, sigma; // parameters
        double q, PA_rad, cosPA, sinPA; // other useful (shape-related) quantities
to this:
    private:
        double x0, y0, PA, ell, I_0, fwhm, beta; // parameters
        double x0, y0, PA, ell, I_0, fwhm, beta; // parameters
        double x0, y0, PA, ell, I_0, fwhm, beta; // parameters
        double q, PA_rad, cosPA, sinPA; // other useful (shape-related) quantities
```

#### 12.2.2 Create and Edit the Class File

Copy the file func\_gaussian.cpp and rename it to func\_new-moffat.cpp.

Initial changes, including parameter number and names:

Edit this file and change the following lines (changed text indicated in red):

```
#include "func_new-moffat.h"

const int N_PARAMS = 5;

const char PARAM_LABELS[][20] = {"PA", "ell", "I_0", "fwhm", "beta"};

const char FUNCTION_NAME[] = "Moffat function";
```

Change references to class name:

Change all class references from "Gaussian" to "NewMoffat" (e.g., Gaussian::Setup becomes NewMoffat::Setup).

Changes to Setup method:

In the Setup method, you need to change how the input is converted into parameters, and do any useful pre-computations. So the initial processing of the "params" input changes from this:

```
PA = params[0 + offsetIndex];
  ell = params[1 + offsetIndex];
  I_0 = params[2 + offsetIndex];
  sigma = params[3 + offsetIndex];
  to this:
  PA = params[0 + offsetIndex];
  ell = params[1 + offsetIndex];
  I_0 = params[2 + offsetIndex];
  fwhm = params[3 + offsetIndex];
  beta = params[4 + offsetIndex];
and at the end we replace this:
  twosigma_squared = 2.0 * sigma*sigma;
with this:
  // compute alpha:
  double exponent = pow(2.0, 1.0/beta);
  alpha = 0.5*fwhm/sqrt(exponent - 1.0);
```

Changes to CalculateIntensity method:

Although it is the public method GetValue() which is called by other parts of the program, we don't actually need to change the current version of that method in this simple example. The code in the original Gaussian version of GetValue() just converts pixel positions to a scaled radius value, given input values for the center, ellipticity, and position angle, and then calls the private method CalculateIntensity() to determine the intensity as a function of the radius. Since we're still assuming a perfectly elliptical shape, we can keep the existing code. It probably doesn't make sense to change the CalculateSubsamples method, either, so we can leave that alone.

Instead, we actually implement the details of the new function's algorithm in CalculateIntensity(). Replace the original version of this method with the following:

```
double NewMoffat::CalculateIntensity( double r )
{
   double scaledR, denominator;
```

```
scaledR = r / alpha;
denominator = pow((1.0 + scaledR*scaledR), beta);
return (I_0 / denominator);
}
```

At this point, most of the work is done. We only need to update add\_functions.cpp so it knows about the new function and update the SConstruct file so that the new function is included in the compilation.

### 12.2.3 Edit add\_functions.cpp

We need to do two simple things here:

- Include the header file for our new function. Add the following line near the top
  of the file, where the other header files are included:
  #include "func\_new-moffat.h"
- 2. Add code to generate an instance of our new class as part of the function-factory map. Inside the function PopulateFactoryMap, add the following lines:

```
NewMoffat::GetClassShortName(classFuncName);
input_factory_map[classFuncName] = new funcobj_factory<NewMoffat>();
```

#### 12.2.4 Edit the SConstruct File

In the SConstruct file, locate the place where the variable "functionobject\_obj\_string" is defined (currently somewhere near line 269, though this might change in the future). This is a string containing a compact list of all the filenames containing function-object code. Insert our new function's name ("func\_new-moffat") into the list.

That's it! You should now be able to recompile imfit and makeimage (see Section 2.3) to use the new function. (Assuming there aren't any bugs in your new code....)

#### A Standard Functions in Detail

Unless otherwise noted, all "intensity" parameters (I\_sky, I\_0, I\_e, etc.) are in units of counts per pixel, and all lengths are in pixels.

A sample function specification (giving the parameters in their proper order) is listed for each function description.

"Elliptical" functions are defined to have an intensity which is constant on concentric, similar ellipses (with specified ellipticity and major-axis position angle); the intensity profile is defined as a function of the major axis *a*.

#### Common parameters:

- PA = position angle (e.g., of the major axis), measured in degrees CCW from the image +y axis. This is equivalent to standard astronomical position angles *if* your image has standard astronomical orientation (N up, E to the left).
- ell = ellipticity (1 b/a), where a and b are semi-major and semi-minor axes of the ellipse, respectively).

## A.1 FlatSky

A uniform background:  $I(x,y) = I_{\text{skv}}$  everywhere.

FUNCTION FlatSky I\_sky

#### A.2 Gaussian

This is an elliptical 2D Gaussian function, with the major-axis intensity profile given by

$$I(a) = I_0 \exp(-a^2/\sigma^2).$$
 (3)

FUNCTION Gaussian

PA

ell

I\_0

sigma

#### A.3 Moffat

This is an elliptical 2D Moffat function, with the major-axis intensity profile given by

$$I(a) = \frac{I_0}{(1 + (a/\alpha)^2)^{\beta}},\tag{4}$$

where  $\alpha$  is defined as

$$\alpha = \frac{\text{FWHM}}{2\sqrt{2^{1/\beta} - 1}}.$$
 (5)

In practice, FWHM describes the overall width of the profile, while  $\beta$  describes that strength of the wings: lower values of  $\beta$  mean more intensity in the wings than is the case for a Gaussian (as  $\beta \to \infty$ , the Moffat profile approaches a Gaussian).

The Moffat function is often a good approximation to typical telescope PSFs (see, e.g., Trujillo et al. 2001), and makeimage can easily be used to generate Moffat PSF images.

FUNCTION Moffat

PA

ell

I\_0

fwhm

beta

# A.4 Exponential

This is an elliptical 2D exponential function, with the major-axis intensity profile given by

$$I(a) = I_0 \exp(-a/h), \tag{6}$$

where  $I_0$  is the central surface brightness and h is the scale length.

FUNCTION Exponential

PA

ell

I\_0

h

## A.5 Exponential\_GenEllipse

Similar to the Exponential function, but using generalized ellipses ("boxy" to "disky" shapes) instead of pure ellipses for the isophote shapes. Following Athanassoula et al. [1990], the shape of the elliptical isophotes is controlled by the c0 parameter, such that a generalized ellipse with ellipticity = 1 - b/a is described by

$$\left(\frac{|x|}{a}\right)^{c_0+2} + \left(\frac{|y|}{b}\right)^{c_0+2} = 1,\tag{7}$$

where |x| and |y| are distances from the ellipse center in the coordinate system aligned with the ellipse major axis ( $c_0$  corresponds to c-2 in the original formulation of Athanassoula et al). Thus, values of  $c_0 < 0$  correspond to disky isophotes, while values > 0 describe boxy isophotes;  $c_0 = 0$  corresponds to a perfect ellipse.

FUNCTION Exponential\_GenEllipse

PΑ

ell

c0

I\_0

h

#### A.6 Sersic

This is an elliptical 2D Sérsic function with the major-axis intensity profile given by

$$I(a) = I_e \exp\left\{-b_n \left[ \left(\frac{a}{r_e}\right)^{1/n} - 1 \right] \right\}, \tag{8}$$

where  $I_e$  is the surface brightness at the effective (half-light) radius  $r_e$  and n is the Sérsic index controlling the shape of the intensity profile. The value of  $b_n$  is formally given by the solution to the transcendental equation

$$\Gamma(2n) = 2\gamma(2n, b_n), \tag{9}$$

where  $\Gamma(a)$  is the gamma function and  $\gamma(a,x)$  is the incomplete gamma function. However, in the current implementation  $b_n$  is calculated via the polynomial approximation of Ciotti & Bertin [1999] when n > 0.36 and the approximation of MacArthur, Courteau, & Holtzman [2003] when  $n \leq 0.36$ .

Note that the Sérsic function is equivalent to the de Vaucouleurs " $r^{1/4}$ " profile when n=4, to an exponential when n=1, and to a Gaussian when n=0.5.

```
FUNCTION Sersic PA ell n I_e r_e
```

### A.7 Sersic\_GenEllipse

Similar to the Sersic function, but using generalized ellipses ("boxy" to "disky" shapes) instead of pure ellipses for the isophote shapes. See the discussion of the Exponential\_GenEllipse function above for details of the isophote shapes.

```
FUNCTION Sersic_GenEllipse
PA
ell
c0
n
I_e
r_e
```

#### A.8 Core-Sersic

This generates an elliptical 2D function with the major-axis intensity profile given by the Core-Sérsic model [Graham et al., 2003, Trujillo et al., 2004]. This has a Sérsic profile (parameterized by n and  $r_e$ ) for radii > the break radius  $r_b$  and a single power law with index  $\gamma$  for radii <  $r_b$ . The transition between the two regimes is mediated by the parameter  $\alpha$ : for low values of  $\alpha$ , the transition is very gradual and smooth, while for high values of  $\alpha$  the transition becomes very abrupt (a perfectly sharp transition can be approximated by setting  $\alpha$  = some large number such as 100). The overall intensity scaling is set by  $I_b$ , the intensity at the break radius  $r_b$ .

```
FUNCTION Core-Sersic PA ell n I_b r_e r_b
```

alpha gamma

## A.9 BrokenExponential

Similar to Exponential, but with two exponential radial zones (with different scale-lengths) joined by a transition region at  $R_b$  of variable sharpness:

$$I(a) = S I_0 e^{-\frac{a}{h_1}} [1 + e^{\alpha(a - R_b)}]^{\frac{1}{\alpha}(\frac{1}{h_1} - \frac{1}{h_2})},$$
 (10)

where  $I_0$  is the central intensity of the inner exponential,  $h_1$  and  $h_2$  are the inner and outer exponential scale lengths,  $R_b$  is the break radius, and  $\alpha$  parameterizes the sharpness of the break. (See Erwin, Pohlen, & Beckman [2008].) Low values of  $\alpha$  mean very smooth, gradual breaks, while high values correspond to abrupt transitions. S is a scaling factor, given by

$$S = (1 + e^{-\alpha R_b})^{\frac{1}{\alpha}(\frac{1}{h_1} - \frac{1}{h_2})}. \tag{11}$$

Note that the parameter  $\alpha$  has units of length<sup>-1</sup> (i.e., pixels<sup>-1</sup>).

FUNCTION BrokenExponential

PA

ell

I\_0

h1

h2 r\_break

alpha

# A.10 GaussianRing

An elliptical ring with a radial profile consisting of a Gaussian centered at  $r = R_{ring}$ .

FUNCTION GaussianRing

PA

ell

Α

R\_ring

sigma\_r

### A.11 GaussianRing2Side

Similar to GaussianRing, but now using an asymmetric Gaussian (different values of  $\sigma$  for  $r < R_{\text{ring}}$  and  $r > R_{\text{ring}}$ ).

FUNCTION GaussianRing2Side

PA

```
ell
A
R_ring
sigma_r_in
sigma_r_out
```

# A.12 EdgeOnDisk

This function provides the analytical form for a perfectly edge-on disk with a radial exponential profile, using the Bessel-function solution of van der Kruit & Searle [1981] for the radial profile and the generalized sech function of van der Kruit [1988] for the vertical profile. The position angle parameter (PA) describes the angle of the disk plane; there is no ellipticity parameter.

In a coordinate system aligned with the edge-on disk, the intensity at radius r from the central axis (in the direction parallel to the galaxy plane) and at height z from the midplane is given by

$$I(r,z) = \mu(0,0) (r/h) K_1(r/h) \operatorname{sech}^{\alpha}(r/(\alpha z_0))$$
 (12)

where h is the exponential scale length in the disk plane,  $z_0$  is the vertical scale height, and  $K_1$  is the modified Bessel function. The central surface brightness  $\mu(0,0)$  is given by

$$\mu(0,0) = 2h L_0, \tag{13}$$

where  $L_0$  is the central luminosity *density* (see van der Kruit & Searle 1981). Note that  $L_0$  is the actual parameter required by the function;  $\mu(0,0)$  is calculated internally.

When  $\alpha = 2$ , this reduces to the familiar sech<sup>2</sup> model for the vertical distribution of a disk (with  $z_0$  corresponding to 1/2 of the  $z_0$  in the original definition of van der Kruit & Searle [1981]). When  $\alpha = \infty$ , the vertical distribution becomes exponential; in practice, you can approximate this by setting  $\alpha$  equal to some fixed, large number.

Note that this particular function requires that the GNU Scientific Library (GSL) be installed; if the GSL is not installed, imfit should be compiled without this function. (The pre-compiled binary versions include the necessary code from the GSL.)

```
FUNCTION EdgeOnDisk
PA
L_0
h
alpha
z_0
```

### A.13 EdgeOnRing

A simplistic model for an edge-on ring, using two offset components located at distance  $\pm r$  from the center of the function block. Each component (i.e., each side of the ring) is a symmetric Gaussian with size  $sigma_r$  for the radial profile and a symmetric Gaussian with size  $sigma_z$  for the vertical profile.

```
FUNCTION EdgeOnRing
PA
I_O
r
sigma_r
sigma_z
```

# A.14 EdgeOnRing2Side

Similar to EdgeOnRing, but now the radial profile for the two components is asymmetric: the inner ( $|R| < R_{\rm ring}$ ) side of each component is a Gaussian with radial size sigma\_r\_in, while the outer side has radial size sigma\_r\_out.

```
FUNCTION EdgeOnRing2Side
PA
I_O
r
sigma_r_in
sigma_r_out
sigma_z
```

# A.15 ExponentialDisk3D

In contrast to the EdgeOnDisk function (above), which is the analytic solution to a perfectly edge-on exponential disk, this function implements a 3D luminosity density model of an exponential disk, and uses line-of-sight integration to create the projected surface-brightness profile for any inclination.

In a cylindrical coordinate system (r, z) aligned with the disk (where the disk midplane has z = 0), the luminosity density at radius r from the central axis and at height z from the midplane is given by

$$j(r,z) = J_0 \exp(-r/h) \exp(-z/h_z)$$
(14)

where h is the exponential scale length in the disk plane,  $h_z$  is the vertical exponential scale height, and  $J_0$  is the central luminosity density.

```
FUNCTION ExponentialDisk3D PA inc J_0 h h_z
```

Because this function performs numerical integration for each pixel value, it can be slower than the analytic EdgeOnDisk function (though the latter is correct only in the  $i = 90^{\circ}$  case), and even slower than the standard Exponential function.

Note that this particular function requires that the GNU Scientific Library (GSL) be installed; if the GSL is not installed, imfit should be compiled without this function. (The pre-compiled binary versions include the necessary code from the GSL.)

# **B** Acknowledgments

Major inspirations for Imfit include both GALFIT [Peng et al., 2002, 2010] and BUDDA [de Souza, Gadotti, & dos Anjos, 2004, Gadotti, 2008].

Thanks also to Michael Opitsch and Michael Williams for being (partly unwitting) beta testers, and for their feedback, to Martin Kuemmel for suggestion an improvement (and finding a related bug), to Roberto Saglia for urging me to implement the Core-Sérsic function, and to Maximilian Fabricius for suggesting improvements to the documentation.

#### **B.1** Data Sources

Sample FITS images for demonstration and testing use are taken from Data Release 7 [Abazajian et al., 2009] of the Sloan Digital Sky Survey [York et al., 2000]. Funding for the creation and distribution of the SDSS Archive has been provided by the Alfred P. Sloan Foundation, the Participating Institutions, the National Aeronautics and Space Administration, the National Science Foundation, the U.S. Department of Energy, the Japanese Monbukagakusho, and the Max Planck Society. The SDSS Web site is http://www.sdss.org/.

The SDSS is managed by the Astrophysical Research Consortium (ARC) for the Participating Institutions. The Participating Institutions are The University of Chicago, Fermilab, the Institute for Advanced Study, the Japan Participation Group, The Johns Hopkins University, the Korean Scientist Group, Los Alamos National Laboratory, the Max-Planck-Institute for Astronomy (MPIA), the Max-Planck-Institute for Astrophysics (MPA), New Mexico State University, University of Pittsburgh, University of Portsmouth, Princeton University, the United States Naval Observatory, and the University of Washington.

#### **B.2** Specific Software Acknowledgments

#### **B.2.1** Minpack

This product includes software developed by the University of Chicago, as Operator of the Argonne National Laboratory.

#### References

Abazajian, K. N.., et al. 2009, "The Seventh Data Release of the Sloan Digital Sky Survey", *Astrophys.J. Supplement* **182**: 182

Athanassoula, E., Morin, S., Wozniak, H., Puy, D., Pierce, M. J., Lombard, J., & Bosma, A. 1990, *Monthly Notices of the Royal Astronomical Society* **245**: 130.

Ciotti, L., & Bertin, G. 1999, "Analytical properties of the  $R^{1/m}$  law", *Astron. Astrophys.* **352**: 447.

- de Souza, R. E., Gadotti, D. A., & dos Anjos, S. 2004, "BUDDA: A New Two-dimensional Bulge/Disk Decomposition Code for Detailed Structural Analysis of Galaxies", *Astrophys.J. Supplement* **153**: 411.
- Erwin, P., Pohlen, B., & Beckman, J. E. 2008, "The Outer Disks of Early-Type Galaxies. I. Surface-Brightness Profiles of Barred Galaxies", *Astron.J.* **135**: 20.
- Gadotti, D. A. 2008, "Image decomposition of barred galaxies and AGN hosts", Monthly Notices of the Royal Astronomical Society **384**: 420.
- Graham, A., Erwin, P., Trujillo, I., & Asensio Ramos, A. 2003 "A New Empirical Model for the Structural Analysis of Early-Type Galaxies, and A Critical Review of the Nuker Model", *Astron.J.* **125**: 2951
- Krist, J. 1995, "Simulation of HST PSFs using Tiny Tim", in *Astronomical Data Analysis Software and Systems IV*, R.A. Shaw, H.E. Payne, and J.J.E. Hayes, eds., *ASP Conference Series* 77: 349.
- MacArthur, L. A., Courteau, S., & Holtzman, J. A. 2003, "Structure of Disk-dominated Galaxies. I. Bulge/Disk Parameters, Simulations, and Secular Evolution", *Astrophys. J.* 582: 689
- Peng, C. Y., Ho, L. C., Impey, C. D., & Rix, H. W. 2002, "Detailed Structural Decomposition of Galaxy Images", *Astron.J.* **124**: 266
- Peng, C. Y., Ho, L. C., Impey, C. D., & Rix, H. W. 2010, "Detailed Decomposition of Galaxy Images. II. Beyond Axisymmetric Models", *Astron. J.* 139: 2097
- Sérsic, J.-L. 1968, Atlas de Galaxias Australes (Cordoba: Obs. Astron.)
- Storn, R. and Price, K. 1997, "Differential Evolution A Simple and Efficient Heuristic for Global Optimization Over Continuous Spaces", *Journal of Global Optimization* 11: 314
- Trujillo, I., Aguerri, J. A. L., Cepa, J., & Gutiérrez, C. M. 2001, "The effects of seeing on Sérsic profiles II. The Moffat PSF", Monthly Notices of the Royal Astronomical Society 328: 977.
- Trujillo, I., Erwin, P., Asensio Ramos, A., & Graham, A. 2004, "Evidence for a New Elliptical-Galaxy Paradigm: Sérsic and Core Galaxies", *Astron.J.* **127**: 1917
- van der Kruit, P. C., & Searle, L. 1981, "Surface Photometry of Edge-on Spiral Galaxies: I. A Model for the Three-dimensional Distribution of Light in Galactic Disks", *Astron. Astrophys.* **95**: 105
- van der Kruit, P. 1988, "The Three-dimensional Distribution of Light and Mass in Disks of Spiral Galaxies", *Astron. Astrophys.* **192**: 117
- York, D. G., et al. 2000, "The Sloan Digital Sky Survey: Technical Summary", *Astron.J.* **120**: 1579