

Transport Layer



OSI Layer 4: Transport Layer

- An overview of layer 4
- ■TCP (Transmission Control Protocol)
- □UDP(User Datagram Protocol)
- □An application: NAT and PAT

OSI Layer 4: Transport Layer

- □ Layer 4 performs multiple functions:
 - segmenting upper-layer application data
 - establishing end-to-end operations
 - sending segments from one end host to another
 - •Flow control and reliability
 - can be compared to talking to a foreigner.
 - Often you would ask the foreigner to <u>repeat his/her</u> words (<u>reliability</u>) and <u>to speak slowly (flow control</u>)

Layer 4: The Transport Layer


- Two particularly important Layer 4 protocols:
 - Transmission Control Protocol (TCP)
 - User Datagram Protocol (UDP)

Layer 4: The Transport Layer

- ■Divide outgoing messages into segments
- Reassemble messages at the destination station
- ■TCP: reliable
 - Connection -oriented
 - Software checking for segment
 - Re-send anything lost or error
 - Uses acknowledgments
 - Provides flow control
- ■UDP: unreliable
 - connectionless
 - provides no software checking for segment
 - uses no acknowledgments
 - provides no flow control

Service Model

Port Numbers



- Both TCP and UDP use port to keep track of different conversations that cross the network at the same time
- □ Application software developers have agreed to use the well-known port numbers that are defined in RFC1700
- ☐ Port numbers below 255 are reserved for TCP and UDP public applications.

Socket


- ■Socket is presented as (IP_address, port)
- □Every connection is expressed as (socket_{source}, socket_{destination}), which is a point-to-point full-duplex channel
- TCP does not support multicast and broadcast

Layer 4: The Transport Layer

- □An overview of layer 4
- ■TCP (Transmission Control Protocol)
- UDP(User Datagram Protocol)
- □An application: NAT and PAT

TCP Service Model

- ☐ Problems must be solved in TCP:
 - Reliable transfer
 - Flow control
 - Sliding window
 - congestion avoidance...
 - Connection management
 - Establish connection: three handshakes
 - Release connection: four handshakes




- □ 源端口和目的端口字段——各占 2 字节
- □ 端口是运输层与应用层的服务接口
- □运输层的复用和分用功能都要通过端口才能实现



- □序号字段——占 4 字节
- □TCP 传送的数据流中的每一个字节都编上一个序号
- □序号字段的值指本报文段所发送的数据的第一个字节的序号



□ 确认号字段——占 4 字节,是期望收到对方的下一个报文段的数据的第一个字节的序号




- □数据偏移(即首部长度)——占4位
- □指出 TCP 报文段的数据起始处距TCP 报文段的起始处的长度
- □单位是 32 位字(以 4 字节为计算单位)



□保留字段——占6位,保留为今后使用,目前置0



- □紧急 URG =1 时,表明紧急指针字段有效
- □告诉系统此报文段中有紧急数据,应尽快传送(相当于高优先级的数据)



□ACK = 1 时确认号字段有效

□ACK = 0 时确认号字段无效



□推送 PSH (PuSH) —— 接收 TCP 收到 PSH = 1 的报文段,就尽快地交付接收应用进程,而不再等到整个缓存都填满了后再向上交付



□复位 RST (ReSeT= 1 时,表明 TCP 连接中出现严重差错(如由于主机崩溃或其他原因),必须释放连接,然后再重新建立运输连接



□同步 SYN=1 表示这是一个连接请求或连接接受报文



□终止 FIN (FINish) —— 用来释放一个连接。FIN =1 表明此报文段的发送端的数据已发送完毕,并要求释放运输连接。



□窗口字段——占2字节,用来让对方设置发送窗口的依据,单位为字节。



□检验和 —— 占 2 字节。检验和字段检验的范围包括首部和数据这两部分



□紧急指针字段 —— 占 16 位,指出在本报文段中紧急数据共有多少个字节(紧急数据放在本报文段数据的最前面)



- □TCP 最初只有一种选项,即最大报文段长度 MSS(Maximum Segment Size)
- ■MSS 告诉对方缓存所能接收的报文段的数据字段的最大长度是 MSS 个字节
- □数据字段加上 TCP 首部才等于整个的 TCP 报文段





□填充字段 —— 这是为了使整个首部长度是 4 字节的整数倍。

TCP Protocol

- Hosts exchange data by using segment(TPDU)
- □ Each segment has:
 - a header of 20 bytes(except optional parts)
 - O or more data bytes
- The size of the segment must be matched with IP packets, and also must satisfy the demand of bottom layers
 - For example, the MTU(Maximal Transfer Unit) of Ethernet is 1500 bytes
- Each byte has a 32 bits sequence number


Reliable Connection?






□**The First Handshake**

- Server: executes LISTEN and ACCEPT primitive, and monitors passively
- ■Client: executes CONNECT primitive, generate a TCP segment with <u>SYN=1 and ACK=0</u>, which stands for connection request




- □ The Second Handshake
 - Server checks if exists service process monitoring the port
 - If none process, answer a TCP segment with RST=1
 - If exists process, decides to reject or to accept the request
 - If accept the connection request, send a segment with SYN=1 and ACK=1




□ The Third Handshake

The client sends a segment with SYN=0 and ACK=1 to acknowledge the connection



□When the server receives the acknowledgement, it informs the upper layer applications



Example: Establish Connection

TCP A TCP B

1. CLOSED LISTEN

2. SYN-SENT --> <SEQ=100> <CTL=SYN> --> SYN-RECEIVED


3. ESTABLISHED <-- <SEQ=300><ACK=101><CTL=SYN,ACK> <-- SYN-RECEIVED

4. ESTABLISHED --> <SEQ=101> <ACK=301> <CTL=ACK> --> ESTABLISHED

5. ESTABLISHED --> <SEQ=101> <ACK=301> <CTL=ACK> <DATA> --> ESTABLISHED

- Basic 3-Way Handshake for Connection Synchronization
- Note that the ACK does not occupy sequence number space (if it did, we would wind up ACKing ACK's!)


Data transfer —stop-and-wait protocol



Data transfer

- ——stop-and-wait protocol
 - After sending a segment, preserve a backup temporarily
 - □ Each segment and ACK must have ID
 - The resend-time must be more than average-travel-time *2
 - stop-and-wait protocol is a simple protocol, but has poor efficiency

Data transfer —Lost ACK and Late ACK




Reliable Communication

segment


- ARQ (Automatic Repeat reQuest).
 - It means the 'resend request' is automatically sent and the receiver need not request the sender to resend the error

Contiguous ARQ Protocol






- □ 发送端要发送 900 字节长的数据,划分为 9 个 100 字节长的报文段,而发送窗口确定为 500 字节。
- □ 发送端只要收到了对方的确认,发送窗口就可 前移。
- □ 发送 TCP 要维护一个指针。每发送一个报文 段,指针就向前移动一个报文段的距离。



- □ 发送端已发送了 400 字节的数据,但只收到对前 200 字节数据的确认,同时窗口大小不变。
- □ 现在发送端还可发送 300 字节。

- 发送端收到了对方对前 400 字节数据的确认,但对方通知发送端必须把窗口减小到 400 字节。
- 现在发送端最多还可发送 400 字节的数据。



利用可变窗口大小进行流量控制 双方确定的窗口值是 400

主	机 A 主 SEQ = 1	机 B A i
	SEQ = 101	Ai
	SEQ = 201	
	ACK = 201, WIN = 300	允i
	SEQ = 301	Αį
	SEQ = 401	Αį
	SEQ = 201	↓ ハ~ ↓ A 走
	ACK = 501, WIN = 100	允许
	SEQ = 501	AE
	ACK = 601, WIN = 0	不多
		; 'I')

A 还能发送 300 字节

A还能发送 200 字节

允许 A 再发送 300 字节(序号 201 至 500)

A 还能发送 200 字节(序号 301 至 500)


A 还能发送 100 字节(序号 401 至 500)


A 超时重发,但不能发送序号 500 以后的数据


允许 A 再发送 100 字节(序号 501 至 600)


A已把发送窗口用完(序号 501 至 600)


不允许 A 再发送(到序号 600 的数据都已收到)











Why must wait for 2MSL?

- □To ensure the last ACK sent by A can reach B
- To prevent any invalid connection request segment from emerging
 - After waiting for 2MSL, we can make sure that all segments on the connection have disappeared


TCP的计时器

□重传计时器

□坚持计时器□

□ 保持计时器 □

□时间等待计时器□



限 态

Layer 4: The Transport Layer

- An Overview of Layer 4
- TCP (Transmission Control Protocol)
- UDP(User Datagram Protocol)
- An application: NAT and PAT

UDP ☐(User Datagram Protocol)


- □Why do we need UDP?
 - No connection establishment (which can add delay)
 - Simple: no connection state at sender, receiver
 - Small segment header
 - No congestion control: UDP can blast away as fast as desired

UDP (User Datagram Protocol)

- Connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others
- ☐ Often used for streaming multimedia application ☐
 - loss tolerant
 - rate sensitive □
- ☐ UDP are used in:
 - RIP: To send the route information periodically
 - ■DNS: Avoid the delay to setup the TCP connection
 - SNMP: When congestion, SNMP must still runable. Without the congestion and reliability control mechanism, UDP has better performance than TCP under the circumstances.
 - Other protocols include TFTP, DHCP
- ☐ Add reliability at application layer if necessary

UDP (User Datagram Protocol)

UDP Segment Format



No sequence or acknowledgement fields


Layer 4: The Transport Layer

- An Overview of Layer 4
- TCP (Transmission Control Protocol)
- UDP(User Datagram Protocol)
- An application: NAT and PAT

What is NAT?

- ■NAT, is the process of swapping one address for another in the IP packet header
- □In practice, NAT is used to allow hosts that are privately addressed to access the Internet
- ☐One of solutions to IP address depletion
 - Conserves registered (legal) addresses
 - Increases Flexibility when connecting to Internet
- RFC 1631 Network Address Translator (NAT)

NAT a simple concept



NAT types

□Static NAT:

Fixed mapping of an internal address to an registered address

□Dynamic NAT:

Mapping is done dynamically on a first come first served basis

□PAT (Overload):

Port address translation is used to allow many internal users to share a single 'inside global' address


NAT address types

□Inside Local address (内部本地地址):内网IP地址


□Inside Global address (内部全局地址): 注册IP地址, 对外部展示的内部地址

□Outside Global address (外部全局地址):由主机所有者分配的IP地址。通常是注册地址。


NAT address types



Static: How does it work?



Dynamic: How does it work?




10.1.1.4

Advantages and Disadvantages of NAT

- Advantage: since not every inside host needs outside access at the same time, you can get away with using a small pool of globally unique addresses to serve a relatively large number of privately addressed hosts.
- □ Disadvantage: one-to-one mapping.
- That is, if the private address space is a /8, but the public address is a /24, only 254 hosts can access the Internet at a time.

PAT: How does it work?



10.1.1.4

PAT Operation

