CE394M: Isoparametric elements and Gauss integration

Krishna Kumar

University of Texas at Austin


krishnak@utexas.edu

February 9, 2019

Overview

Rectangular elements

2 Isoparametric elements



Four-node rectangular element. The nodes are by definition numbered counter-clockwise.


As the element has four nodes, it is necessary to start with a polynomial that has four parameters.

$$Te = \alpha_0^e + \alpha_1^e x + \alpha_2^e y + \alpha_3^e xy$$

It is possible to express $(\alpha_0^e, \alpha_1^e, \alpha_2^e, \alpha_3^e)$ in terms of the nodal values $(T_1^e, T_2^e, T_3^e, T_4^e)$. A derivation shape functions is tedious as it is necessary to invert a 4 x 4 matrix.

The Shape Functions should be 1 at each node, and 0 otherwise can be used to determine the 4 coefficients.

An alternative and more elegant approach is to construct the shape functions by the **tensor product method**. This is based on taking products of one-dimensional shape functions.



Construction of two dimensional shape functions.

For example, N_2^e , which has to have the value one at node 2 and zero at the other nodes, is obtained by taking the product of the one-dimensional shape functions $N_2^{e,1d}(x)$ and $N_1^{e,1d}(y)$.

$$N_2^e = N_2^{e,1d}(x) \times N_1^{e,1d}(y)$$

As visible in the figure above the product $N_2^{e,1d}(x) \times N_1^{e,1d}(y)$ has the value one at node 2 and is zero at nodes 1, 3 and 4.


$$N_2^e(x,y) = \frac{x - x_1^e}{x_2^e - x_1^e} \frac{y - y_4^e}{y_1^e - y_4^e} = -\frac{1}{A^e} (x - x_1^e) (y - y_4^e)$$

The four shape functions, also called **bilinear shape functions**, for the quadrilateral element are:

$$\begin{split} N_1^e(x,y) &= \frac{x - x_2^e}{x_1^e - x_2^e} \frac{y - y_4^e}{y_1^e - y_4^e} = -\frac{1}{A^e} (x - x_2^e) (y - y_4^e) \\ N_2^e(x,y) &= \frac{x - x_1^e}{x_2^e - x_1^e} \frac{y - y_4^e}{y_1^e - y_4^e} = -\frac{1}{A^e} (x - x_1^e) (y - y_4^e) \\ N_3^e(x,y) &= \frac{x - x_1^e}{x_2^e - x_1^e} \frac{y - y_1^e}{y_4^e - y_1^e} = -\frac{1}{A^e} (x - x_1^e) (y - y_1^e) \\ N_4^e(x,y) &= \frac{x - x_2^e}{x_1^e - x_2^e} \frac{y - y_1^e}{y_4^e - y_1^e} = -\frac{1}{A^e} (x - x_2^e) (y - y_1^e) \end{split}$$


where A^e is the area of the element.

The four shape functions are plotted in the following figure:




Four shape functions of the rectangular element (on $[0,2] \times [0,2]$).

If the sf equations are used for interpolating the temperature field over arbitrary quadrilaterals, the scalar field (e.g., temperature) across the element boundaries will be not continuous.




Two element mesh with rectangle shape functions. Although the two nodal values on the edge agree, the temperature distribution is still discontinuous.



The computed shape functions are suitable for rectangles and could be used with meshes consisting only of rectangles, but they are not suitable for arbitrary quadrilaterals.

Therefore, these shape functions are of limited use for practical applications. To obtain the shape functions for arbitrary quadrilaterals we need to visit the idea of isoparametric mapping.



Shape functions for a two-noded element.

Global coordinate x and local coordinate ξ



Although isoparametric mapping is not particularly useful in one dimension, it is very helpful for understanding the general approach.

consider a coordinate transformation which transforms (maps) the coordinate x into a local (element specific) coordinate ξ :



Mapping of the parent element onto the physical element.

The coordinate ξ fulfills the relationships:

$$x = x_1^e$$
 at $\xi = -1$ and $x = x_2^e$ at $\xi = 1$

"stretch transformation" of $x(\xi)$:

$$x(\xi) = x_1^e + \frac{1}{2}(x_2^e - x_1^e)(1 + \xi)$$
$$= \frac{x_1^e + x_2^e}{2} + \frac{x_2^e - x_1^e}{2}\xi$$

The shape functions $N_1^e = (1 - x/I)$ and $N_2^e = (x/I)$ can also be expressed using ξ :

$$N_1^e(\xi) = \frac{1}{2}(1-\xi)$$
 $N_2^e(\xi) = \frac{1}{2}(1+\xi)$

The key idea of the isoparametric concept is to use these shape functions for writing the coordinate transformation between x and ξ

$$x(\xi) = N_1^e(\xi)x_1^e + N_2^e(\xi)x_2^e$$

$$= \frac{1}{2}(1-\xi)x_1^e + \frac{1}{2}(1+\xi)x_2^e$$

$$= \frac{x_1^e + x_2^e}{2} + \frac{x_2^e - x_1^e}{2}\xi$$



Mapping of the parent element onto the physical element.

- The coordinate ξ is usually called the **natural coordinate** and always lies by definition between -1 and +1.
- The parent element is solely for numerical purposes.
- The finite element analysis is still performed over the physical domain.

In an isoparametric element the field variable, like displacement, is approximated with the same set of shape functions as those used for the coordinate transformation:

$$u(\xi) = N_1^e(\xi)a_1^e + N_2^e(\xi)a_2^e$$

To compute the derivatives which appear in the weak form the chain rule is used:

$$\frac{du}{dx} = \frac{du}{d\xi} \frac{d\xi}{dx}$$

The derivative $d\xi/dx$ is determined from the mapping between ξ and x