Quantum++ v1.3

Generated by Doxygen 1.8.15

1 Quantum++	1
2 Namespace Index	3
2.1 Namespace List	3
3 Hierarchical Index	5
3.1 Class Hierarchy	5
4 Class Index	7
4.1 Class List	7
5 File Index	11
5.1 File List	11
6 Namespace Documentation	13
6.1 qpp Namespace Reference	13
6.1.1 Detailed Description	26
6.1.2 Typedef Documentation	26
6.1.2.1 bigint	26
6.1.2.2 bra	27
6.1.2.3 cmat	27
6.1.2.4 cplx	27
6.1.2.5 dmat	27
6.1.2.6 dyn_col_vect	27
6.1.2.7 dyn_mat	28
6.1.2.8 dyn_row_vect	28
6.1.2.9 idx	28
6.1.2.10 ket	28
6.1.2.11 to void	28
6.1.3 Enumeration Type Documentation	28
6.1.3.1 anonymous enum	28
	29
6.1.4 Function Documentation	
6.1.4.1 absm()	29
6.1.4.2 abssq() [1/3]	29
6.1.4.3 abssq() [2/3]	30
<b>6.1.4.4 abssq()</b> [3/3]	30
6.1.4.5 adjoint()	30
6.1.4.6 anticomm()	31
<b>6.1.4.7 apply()</b> [1/5]	31
<b>6.1.4.8 apply()</b> [2/5]	32
<b>6.1.4.9 apply()</b> [3/5]	32
<b>6.1.4.10 apply()</b> [4/5]	33
<b>6.1.4.11 apply()</b> [5/5]	33
6.1.4.12 applyCTRL() [1/2]	34

6.1.4.13 applyCTRL() [2/2]	34
6.1.4.14 applyQFT()	35
6.1.4.15 applyTFQ()	35
6.1.4.16 avg()	36
6.1.4.17 bloch2rho()	36
6.1.4.18 choi2kraus()	37
6.1.4.19 choi2super()	37
6.1.4.20 comm()	38
6.1.4.21 complement()	38
6.1.4.22 compperm()	39
6.1.4.23 concurrence()	39
6.1.4.24 conjugate()	39
6.1.4.25 contfrac2x()	40
<b>6.1.4.26 convergents()</b> [1/2]	40
<b>6.1.4.27 convergents()</b> [2/2]	41
6.1.4.28 cor()	41
6.1.4.29 cosm()	42
6.1.4.30 cov()	42
6.1.4.31 cwise()	43
6.1.4.32 det()	43
· ·	43
<b>6.1.4.34 dirsum()</b> [2/4]	44
<b>6.1.4.35 dirsum()</b> [3/4]	44
V	45
6.1.4.37 dirsumpow()	45
	46
<b>6.1.4.39 disp()</b> [2/5]	46
<b>6.1.4.40 disp()</b> [3/5]	47
<b>6.1.4.41 disp()</b> [4/5]	47
<b>6.1.4.42 disp()</b> [5/5]	48
	48
	49
<b>6.1.4.45</b> entanglement() [1/2]	49
<b>6.1.4.46 entanglement()</b> [2/2]	50
<b>6.1.4.47 entropy()</b> [1/2]	50
	50
6.1.4.49 evals()	51
6.1.4.50 evects()	51
	52
•	52
6.1.4.53 funm()	52
<b>6.1.4.54 gcd()</b> [1/2]	53

6.1.4.55 gcd() [2/2] 53
6.1.4.56 gconcurrence()
6.1.4.57 grams() [1/3]
<b>6.1.4.58 grams()</b> [2/3]
<b>6.1.4.59 grams()</b> [3/3]
6.1.4.60 hash_eigen()
6.1.4.61 heig()
6.1.4.62 hevals()
6.1.4.63 hevects()
6.1.4.64 inverse()
6.1.4.65 invperm()
6.1.4.66 ip() [1/2] 58
6.1.4.67 ip() [2/2] 59
6.1.4.68 isprime()
6.1.4.69 kraus2choi()
6.1.4.70 kraus2super()
6.1.4.71 kron() [1/4]
6.1.4.72 kron() [2/4]
6.1.4.73 kron() [3/4]
6.1.4.74 kron() [4/4]
6.1.4.75 kronpow()
6.1.4.76 lcm() [1/2]
6.1.4.77 lcm() [2/2]
6.1.4.78 load()
6.1.4.79 loadMATLAB() [1/2]
6.1.4.80 loadMATLAB() [2/2]
6.1.4.81 logdet()
6.1.4.82 logm()
6.1.4.83 lognegativity() [1/2]
6.1.4.84 lognegativity() [2/2]
6.1.4.85 marginalX()
6.1.4.86 marginalY()
6.1.4.87 measure() [1/9]
6.1.4.88 measure() [2/9]
6.1.4.89 measure() [3/9]
6.1.4.90 measure() [4/9]
6.1.4.91 measure() [5/9]
6.1.4.92 measure() [6/9]
6.1.4.93 measure() [7/9]
6.1.4.94 measure() [8/9]
6.1.4.95 measure() [9/9]
6.1.4.96 measure_seq() [1/2]

6.1.4.97 measure_seq() [2/2]
6.1.4.98 mket() [1/2]
6.1.4.99 mket() [2/2]
6.1.4.100 modinv()
6.1.4.101 modmul()
6.1.4.102 modpow()
6.1.4.103 mprj() [1/2]
6.1.4.104 mprj() [2/2]
6.1.4.105 multiidx2n()
6.1.4.106 n2multiidx()
6.1.4.107 negativity() [1/2]
6.1.4.108 negativity() [2/2]
6.1.4.109 norm()
6.1.4.110 normalize()
6.1.4.111 omega()
6.1.4.112 powm()
6.1.4.113 prj()
6.1.4.114 prod() [1/3]
6.1.4.115 prod() [2/3]
6.1.4.116 prod() [3/3]
6.1.4.117 ptrace() [1/2]
6.1.4.118 ptrace() [2/2]
6.1.4.119 ptrace1() [1/2]
6.1.4.120 ptrace1() [2/2]
6.1.4.121 ptrace2() [1/2]
6.1.4.122 ptrace2() [2/2]
6.1.4.123 ptranspose() [1/2]
6.1.4.124 ptranspose() [2/2]
6.1.4.125 QFT()
6.1.4.126 qmutualinfo() [1/2]
6.1.4.127 qmutualinfo() [2/2]
6.1.4.128 rand() [1/5]
6.1.4.129 rand() [2/5] 90
6.1.4.130 rand() [3/5]
6.1.4.131 rand() [4/5] 91
6.1.4.132 rand() [5/5]
6.1.4.133 randH()
6.1.4.134 randidx()
6.1.4.135 randket()
6.1.4.136 randkraus()
6.1.4.137 randn() [1/4]
6.1.4.138 randn() [2/4] 94

6.1.4.139 randn() [3/4] 94
6.1.4.140 randn() [4/4]
6.1.4.141 randperm()
6.1.4.142 randprime()
6.1.4.143 randprob()
6.1.4.144 randrho()
6.1.4.145 randU()
6.1.4.146 randV()
6.1.4.147 renyi() [1/2]
6.1.4.148 renyi() [2/2]
6.1.4.149 reshape()
6.1.4.150 rho2bloch()
6.1.4.151 rho2pure()
6.1.4.152 save()
6.1.4.153 saveMATLAB() [1/2]
6.1.4.154 saveMATLAB() [2/2]
6.1.4.155 schatten()
6.1.4.156 schmidtA() [1/2]
6.1.4.157 schmidtA() [2/2]
6.1.4.158 schmidtB() [1/2]
6.1.4.159 schmidtB() [2/2]
6.1.4.160 schmidtcoeffs() [1/2]
6.1.4.161 schmidtcoeffs() [2/2]
6.1.4.162 schmidtprobs() [1/2]
6.1.4.163 schmidtprobs() [2/2]
6.1.4.164 sigma()
6.1.4.165 sinm()
6.1.4.166 spectralpowm()
6.1.4.167 sqrtm()
6.1.4.168 sum() [1/3]
6.1.4.169 sum() [2/3]
6.1.4.170 sum() [3/3]
6.1.4.171 super2choi()
6.1.4.172 svals()
6.1.4.173 svd()
6.1.4.174 svdU()
6.1.4.175 svdV()
6.1.4.176 syspermute() [1/2]
6.1.4.177 syspermute() [2/2]
6.1.4.178 TFQ()
6.1.4.179 trace()
6.1.4.180 transpose()

6.1.4.181 tsallis() [1/2]	 113
6.1.4.182 tsallis() [2/2]	 114
6.1.4.183 uniform()	 114
6.1.4.184 var()	 115
6.1.4.185 x2contfrac()	 115
6.1.5 Variable Documentation	 116
6.1.5.1 chop	 116
6.1.5.2 ee	 116
6.1.5.3 infty	 116
6.1.5.4 maxn	 116
6.1.5.5 pi	 116
6.2 qpp::exception Namespace Reference	 116
6.2.1 Detailed Description	 118
6.3 qpp::experimental Namespace Reference	 118
6.3.1 Detailed Description	 118
6.4 qpp::internal Namespace Reference	 118
6.4.1 Detailed Description	 120
6.4.2 Function Documentation	 120
6.4.2.1 abs_chop() [1/2]	 120
<b>6.4.2.2 abs_chop()</b> [2/2]	 120
6.4.2.3 check_cvector()	 120
6.4.2.4 check_dims()	 121
6.4.2.5 check_dims_match_cvect()	 121
6.4.2.6 check_dims_match_mat()	 121
6.4.2.7 check_dims_match_rvect()	 121
6.4.2.8 check_eq_dims()	 121
6.4.2.9 check_matching_sizes()	 121
6.4.2.10 check_no_duplicates()	 122
6.4.2.11 check_nonzero_size()	 122
6.4.2.12 check_perm()	 122
6.4.2.13 check_qubit_cvector()	 122
6.4.2.14 check_qubit_matrix()	 122
6.4.2.15 check_qubit_rvector()	 122
6.4.2.16 check_qubit_vector()	 123
6.4.2.17 check_rvector()	 123
6.4.2.18 check_square_mat()	 123
6.4.2.19 check_subsys_match_dims()	 123
6.4.2.20 check_vector()	 123
6.4.2.21 dirsum2()	
6.4.2.22 get_dim_subsys()	
6.4.2.23 get_num_subsys()	 124
6.4.2.24 hash_combine()	 124

6.4.2.25 kron2()	 124
6.4.2.26 multiidx2n()	 125
6.4.2.27 n2multiidx()	 125
6.4.2.28 variadic_vector_emplace() [1/2]	 125
6.4.2.29 variadic_vector_emplace() [2/2]	 125
6.5 qpp::literals Namespace Reference	 125
6.5.1 Function Documentation	 126
6.5.1.1 operator""""_bra()	 126
6.5.1.2 operator"""i() [1/2]	 126
<b>6.5.1.3</b> operator"""i() [2/2]	 126
6.5.1.4 operator"""if() [1/2]	 127
6.5.1.5 operator"""if() [2/2]	 127
6.5.1.6 operator""""_ket()	 127
6.5.1.7 operator""""_prj()	 127
	400
7 Class Documentation	129
7.1 qpp::Bit_circuit Class Reference	
7.1.1 Detailed Description	
7.1.2 Constructor & Destructor Documentation	
7.1.2.1 Bit_circuit() [1/2]	
7.1.2.2 Bit_circuit() [2/2]	
7.1.2.3 ~Bit_circuit()	
7.1.3 Member Function Documentation	
7.1.3.1 CNOT()	
7.1.3.2 FRED()	
7.1.3.3 get_gate_count()	
7.1.3.4 get_gate_depth()	
7.1.3.5 NOT()	
7.1.3.6 reset()	
7.1.3.7 SWAP()	
7.1.3.8 TOF()	
7.1.3.9 X()	
7.1.4 Member Data Documentation	
7.1.4.1 bCNOT	
7.1.4.2 bFRED	 136
7.1.4.3 bNOT	 136
7.1.4.4 bSWAP	 136
7.1.4.5 bTOF	 136
7.1.4.6 btotal	 136
7.1.4.7 count	 137
7.1.4.8 depth	 137
7.2 app: Codes Class Reference	137

7.2.1 Detailed Description
7.2.2 Member Enumeration Documentation
7.2.2.1 Type
7.2.3 Constructor & Destructor Documentation
7.2.3.1 Codes()
7.2.3.2 ~Codes()
7.2.4 Member Function Documentation
7.2.4.1 codeword()
7.2.5 Friends And Related Function Documentation
7.2.5.1 internal::Singleton < const Codes >
7.3 qpp::exception::CustomException Class Reference
7.3.1 Detailed Description
7.3.2 Constructor & Destructor Documentation
7.3.2.1 CustomException()
7.3.3 Member Function Documentation
7.3.3.1 description()
7.3.4 Member Data Documentation
7.3.4.1 what
7.4 qpp::exception::DimsInvalid Class Reference
7.4.1 Detailed Description
7.4.2 Member Function Documentation
7.4.2.1 description()
7.4.2.2 Exception()
7.5 qpp::exception::DimsMismatchCvector Class Reference
7.5.1 Detailed Description
7.5.2 Member Function Documentation
7.5.2.1 description()
7.5.2.2 Exception()
7.6 qpp::exception::DimsMismatchMatrix Class Reference
7.6.1 Detailed Description
7.6.2 Member Function Documentation
7.6.2.1 description()
7.6.2.2 Exception()
7.7 qpp::exception::DimsMismatchRvector Class Reference
7.7.1 Detailed Description
7.7.2 Member Function Documentation
7.7.2.1 description()
7.7.2.2 Exception()
7.8 qpp::exception::DimsMismatchVector Class Reference
7.8.1 Detailed Description
7.8.2 Member Function Documentation
7.8.2.1 description()

7.8.2.2 Exception()	52
7.9 qpp::exception::DimsNotEqual Class Reference	53
7.9.1 Detailed Description	54
7.9.2 Member Function Documentation	54
7.9.2.1 description()	54
7.9.2.2 Exception()	54
7.10 qpp::internal::Display_Impl_ Struct Reference	55
7.10.1 Member Function Documentation	55
7.10.1.1 display_impl_()	55
7.11 qpp::exception::Duplicates Class Reference	56
7.11.1 Detailed Description	57
7.11.2 Member Function Documentation	57
7.11.2.1 description()	57
7.11.2.2 Exception()	57
7.12 qpp::Dynamic_bitset Class Reference	57
7.12.1 Detailed Description	60
7.12.2 Member Typedef Documentation	60
7.12.2.1 storage_type	60
7.12.2.2 value_type	60
7.12.3 Constructor & Destructor Documentation	60
7.12.3.1 Dynamic_bitset()	60
7.12.3.2 ~Dynamic_bitset()	61
7.12.4 Member Function Documentation	61
7.12.4.1 all()	61
7.12.4.2 any()	61
7.12.4.3 count()	61
7.12.4.4 data()	62
7.12.4.5 display()	62
7.12.4.6 flip() [1/2]	62
7.12.4.7 flip() [2/2]	63
7.12.4.8 get()	63
7.12.4.9 index_()	63
7.12.4.10 none()	64
7.12.4.11 offset_()	64
7.12.4.12 operator"!=()	64
7.12.4.13 operator-()	65
7.12.4.14 operator==()	65
7.12.4.15 rand() [1/2] 1	65
7.12.4.16 rand() [2/2] 1	66
7.12.4.17 reset() [1/2]	66
7.12.4.18 reset() [2/2]	66
7.12.4.19 set() [1/2]	67

7.12.4.20 set() [2/2]	167
7.12.4.21 size()	167
7.12.4.22 storage_size()	167
7.12.4.23 to_string()	168
7.12.5 Member Data Documentation	168
7.12.5.1 n	168
7.12.5.2 storage_size	168
7.12.5.3 v	169
7.13 qpp::internal::EqualEigen Class Reference	169
7.13.1 Detailed Description	169
7.13.2 Member Function Documentation	169
7.13.2.1 operator()()	169
7.14 qpp::exception::Exception Class Reference	170
7.14.1 Detailed Description	171
7.14.2 Constructor & Destructor Documentation	172
7.14.2.1 Exception()	172
7.14.3 Member Function Documentation	172
7.14.3.1 description()	172
7.14.3.2 what()	172
7.14.4 Member Data Documentation	173
7.14.4.1 msg	173
7.14.4.2 where	173
7.15 qpp::Gates Class Reference	173
7.15.1 Detailed Description	175
7.15.2 Constructor & Destructor Documentation	175
7.15.2.1 Gates()	175
7.15.2.2 ~Gates()	176
7.15.3 Member Function Documentation	176
7.15.3.1 CTRL()	176
7.15.3.2 expandout() [1/3]	176
<b>7.15.3.3 expandout()</b> [2/3]	177
<b>7.15.3.4 expandout()</b> [3/3]	178
7.15.3.5 Fd()	178
7.15.3.6 get_name()	179
7.15.3.7 ld()	179
7.15.3.8 MODMUL()	180
7.15.3.9 Rn()	180
7.15.3.10 RX()	181
7.15.3.11 RY()	181
7.15.3.12 RZ()	181
7.15.3.13 SWAPd()	182
7.15.3.14 Xd()	182

7.15.3.15 Zd()	32
7.15.4 Friends And Related Function Documentation	33
7.15.4.1 internal::Singleton < const Gates >	33
7.15.5 Member Data Documentation	33
7.15.5.1 CNOT	33
7.15.5.2 CNOTba	33
7.15.5.3 CZ	33
7.15.5.4 FRED	34
7.15.5.5 H	34
7.15.5.6 ld2	34
7.15.5.7 S	34
7.15.5.8 SWAP	34
7.15.5.9 T	34
7.15.5.10 TOF	35
7.15.5.11 X	35
7.15.5.12 Y	35
7.15.5.13 Z	35
7.16 qpp::QCircuit::GateStep Struct Reference	36
7.16.1 Detailed Description	37
7.16.2 Constructor & Destructor Documentation	37
7.16.2.1 GateStep() [1/2]	37
7.16.2.2 GateStep() [2/2]	37
7.16.3 Member Data Documentation	37
7.16.3.1 ctrl	37
7.16.3.2 gate_hash	38
7.16.3.3 gate_type	38
7.16.3.4 name	38
7.16.3.5 target	38
7.17 qpp::internal::HashEigen Class Reference	38
7.17.1 Detailed Description	39
7.17.2 Member Function Documentation	39
7.17.2.1 operator()()	39
7.18 qpp::IDisplay Class Reference	39
7.18.1 Detailed Description	90
7.18.2 Constructor & Destructor Documentation	90
7.18.2.1 ∼IDisplay()	90
7.18.3 Member Function Documentation	90
7.18.3.1 display()	90
7.18.4 Friends And Related Function Documentation	91
7.18.4.1 operator<<	91
7.19 qpp::IJSON Class Reference	91
7.19.1 Detailed Description	92

7.19.2 Constructor & Destructor Documentation
7.19.2.1 ~IJSON()
7.19.3 Member Function Documentation
7.19.3.1 to_JSON()
7.20 qpp::Init Class Reference
7.20.1 Detailed Description
7.20.2 Constructor & Destructor Documentation
7.20.2.1 Init()
7.20.2.2 ~Init()
7.20.3 Friends And Related Function Documentation
7.20.3.1 internal::Singleton < const Init >
7.21 qpp::exception::InvalidIterator Class Reference
7.21.1 Detailed Description
7.21.2 Member Function Documentation
7.21.2.1 description()
7.21.2.2 Exception()
7.22 qpp::internal::IOManipEigen Class Reference
7.22.1 Constructor & Destructor Documentation
7.22.1.1 IOManipEigen() [1/2]
7.22.1.2 IOManipEigen() [2/2]
7.22.2 Member Function Documentation
7.22.2.1 display()
7.22.3 Member Data Documentation
7.22.3.1 A
7.22.3.2 chop
7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference
7.23.1 Constructor & Destructor Documentation
7.23.1.1 IOManipPointer() [1/2]
7.23.1.2 IOManipPointer() [2/2]
7.23.2 Member Function Documentation
7.23.2.1 display()
7.23.2.2 operator=()
7.23.3 Member Data Documentation
7.23.3.1 chop
7.23.3.2 end
7.23.3.3 N
7.23.3.4 p
7.23.3.5 separator
7.23.3.6 start
7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference
7.24.1 Constructor & Destructor Documentation
7.24.1.1 IOManipRange() [1/2]

7.24.1.2 IOManipRange() [2/2]	)4
7.24.2 Member Function Documentation	)4
7.24.2.1 display()	)4
7.24.2.2 operator=()	)4
7.24.3 Member Data Documentation	)4
7.24.3.1 chop	)5
7.24.3.2 end	)5
7.24.3.3 first	)5
7.24.3.4 last	)5
7.24.3.5 separator	)5
7.24.3.6 start	)5
$7.25 \; qpp::is\_complex < T > Struct \; Template \; Reference  \dots \qquad \qquad$	ე6
7.25.1 Detailed Description	ე6
7.26 qpp::is_complex< std::complex< T > > Struct Template Reference	)7
7.26.1 Detailed Description	)7
7.27 qpp::is_iterable < T, typename > Struct Template Reference	)8
7.27.1 Detailed Description	38
7.28 qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 20	ງ9
7.28.1 Detailed Description	10
7.29 qpp::is_matrix_expression< Derived > Struct Template Reference	10
7.29.1 Detailed Description	10
7.30 qpp::QCircuit::iterator Class Reference	11
7.30.1 Detailed Description	12
7.30.2 Member Typedef Documentation	12
7.30.2.1 difference_type	12
7.30.2.2 iterator_category	12
7.30.2.3 pointer	13
7.30.2.4 reference	13
7.30.2.5 value_type	13
7.30.3 Constructor & Destructor Documentation	13
7.30.3.1 iterator() [1/2]	13
7.30.3.2 iterator() [2/2]	13
7.30.4 Member Function Documentation	13
7.30.4.1 operator *()	14
7.30.4.2 operator"!=()	14
7.30.4.3 operator++() [1/2]	14
7.30.4.4 operator++() [2/2]	14
7.30.4.5 operator=()	15
7.30.4.6 operator==()	15
7.30.4.7 set_begin_()	15
7.30.4.8 set_end_()	1 =

7.30.5 Member Data Documentation	16
7.30.5.1 elem	16
7.30.5.2 qc	16
7.31 qpp::make_void < Ts > Struct Template Reference	16
7.31.1 Detailed Description	16
7.31.2 Member Typedef Documentation	17
7.31.2.1 type	17
7.32 qpp::exception::MatrixMismatchSubsys Class Reference	17
7.32.1 Detailed Description	18
7.32.2 Member Function Documentation	18
7.32.2.1 description()	19
7.32.2.2 Exception()	19
7.33 qpp::exception::MatrixNotCvector Class Reference	19
7.33.1 Detailed Description	21
7.33.2 Member Function Documentation	21
7.33.2.1 description()	21
7.33.2.2 Exception()	21
7.34 qpp::exception::MatrixNotRvector Class Reference	21
7.34.1 Detailed Description	23
7.34.2 Member Function Documentation	23
7.34.2.1 description()	23
7.34.2.2 Exception()	23
7.35 qpp::exception::MatrixNotSquare Class Reference	23
7.35.1 Detailed Description	25
7.35.2 Member Function Documentation	25
7.35.2.1 description()	25
7.35.2.2 Exception()	25
7.36 qpp::exception::MatrixNotSquareNorCvector Class Reference	25
7.36.1 Detailed Description	27
7.36.2 Member Function Documentation	27
7.36.2.1 description()	27
7.36.2.2 Exception()	27
7.37 qpp::exception::MatrixNotSquareNorRvector Class Reference	27
7.37.1 Detailed Description	29
7.37.2 Member Function Documentation	29
7.37.2.1 description()	29
7.37.2.2 Exception()	29
7.38 qpp::exception::MatrixNotSquareNorVector Class Reference	29
7.38.1 Detailed Description	31
7.38.2 Member Function Documentation	31
7.38.2.1 description()	31
7.38.2.2 Exception()	31

7.39 qpp::exception::MatrixNotVector Class Reference
7.39.1 Detailed Description
7.39.2 Member Function Documentation
7.39.2.1 description()
7.39.2.2 Exception()
7.40 qpp::QCircuit::MeasureStep Struct Reference
7.40.1 Detailed Description
7.40.2 Constructor & Destructor Documentation
7.40.2.1 MeasureStep() [1/2]
7.40.2.2 MeasureStep() [2/2]
7.40.3 Member Data Documentation
7.40.3.1 c_reg
7.40.3.2 mats_hash
7.40.3.3 measurement_type
7.40.3.4 name
7.40.3.5 target
7.41 qpp::exception::NoCodeword Class Reference
7.41.1 Detailed Description
7.41.2 Member Function Documentation
7.41.2.1 description()
7.41.2.2 Exception()
7.42 qpp::NoiseBase < T > Class Template Reference
7.42.1 Detailed Description
7.42.2 Member Typedef Documentation
7.42.2.1 noise_type
7.42.2.1 noise_type
7.42.2.1 noise_type  <
7.42.2.1 noise_type  <
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ∼NoiseBase()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.4 get_Ks()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.4 get_Ks()       24         7.42.4.5 get_last_idx()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.5 get_last_idx()       24         7.42.4.5 get_last_idx()       24         7.42.4.6 get_last_K()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.4 get_Ks()       24         7.42.4.5 get_last_idx()       24         7.42.4.6 get_last_idx()       24         7.42.4.7 get_last_p()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.4 get_Ks()       24         7.42.4.5 get_last_idx()       24         7.42.4.6 get_last_jdx()       24         7.42.4.7 get_last_p()       24         7.42.4.8 get_probs()       24
7.42.2.1 noise_type       24         7.42.3 Constructor & Destructor Documentation       24         7.42.3.1 NoiseBase() [1/2]       24         7.42.3.2 NoiseBase() [2/2]       24         7.42.3.3 ~NoiseBase()       24         7.42.4 Member Function Documentation       24         7.42.4.1 compute_probs_()       24         7.42.4.2 compute_state_()       24         7.42.4.3 get_d()       24         7.42.4.4 get_Ks()       24         7.42.4.5 get_last_idx()       24         7.42.4.6 get_last_K()       24         7.42.4.7 get_last_p()       24         7.42.4.8 get_probs()       24         7.42.4.9 operator()() [1/3]       24

7.42.5.1 d	245
7.42.5.2 generated	245
7.42.5.3 i	245
7.42.5.4 Ks	245
7.42.5.5 probs	246
7.43 qpp::NoiseType Class Reference	246
7.43.1 Detailed Description	246
7.44 qpp::exception::NotBipartite Class Reference	246
7.44.1 Detailed Description	248
7.44.2 Member Function Documentation	248
7.44.2.1 description()	248
7.44.2.2 Exception()	248
7.45 qpp::exception::NotImplemented Class Reference	248
7.45.1 Detailed Description	250
7.45.2 Member Function Documentation	250
7.45.2.1 description()	250
7.45.2.2 Exception()	250
7.46 qpp::exception::NotQubitCvector Class Reference	250
7.46.1 Detailed Description	252
7.46.2 Member Function Documentation	252
7.46.2.1 description()	252
7.46.2.2 Exception()	252
7.47 qpp::exception::NotQubitMatrix Class Reference	252
7.47.1 Detailed Description	254
7.47.2 Member Function Documentation	254
7.47.2.1 description()	254
7.47.2.2 Exception()	254
7.48 qpp::exception::NotQubitRvector Class Reference	254
7.48.1 Detailed Description	256
7.48.2 Member Function Documentation	256
7.48.2.1 description()	256
7.48.2.2 Exception()	256
7.49 qpp::exception::NotQubitSubsys Class Reference	256
7.49.1 Detailed Description	258
7.49.2 Member Function Documentation	258
7.49.2.1 description()	258
7.49.2.2 Exception()	258
7.50 qpp::exception::NotQubitVector Class Reference	258
7.50.1 Detailed Description	260
7.50.2 Member Function Documentation	260
7.50.2.1 description()	260
7.50.2.2 Exception()	260

7.51 qpp::exception::OutOfRange Class Reference	
7.51.1 Detailed Description	
7.51.2 Member Function Documentation	
7.51.2.1 description()	
7.51.2.2 Exception()	
7.52 qpp::exception::PermInvalid Class Reference	
7.52.1 Detailed Description	
7.52.2 Member Function Documentation	
7.52.2.1 description()	
7.52.2.2 Exception()	
7.53 qpp::exception::PermMismatchDims Class Reference	34
7.53.1 Detailed Description	36
7.53.2 Member Function Documentation	36
7.53.2.1 description()	36
7.53.2.2 Exception()	36
7.54 qpp::QCircuit Class Reference	37
7.54.1 Detailed Description	71
7.54.2 Member Typedef Documentation	71
7.54.2.1 const_iterator	72
7.54.3 Member Enumeration Documentation	72
7.54.3.1 GateType	72
7.54.3.2 MeasureType	72
7.54.3.3 StepType	74
7.54.4 Constructor & Destructor Documentation	74
7.54.4.1 QCircuit()	74
7.54.4.2 ~QCircuit()	75
7.54.5 Member Function Documentation	75
7.54.5.1 add_circuit()	75
7.54.5.2 add_dit()	75
7.54.5.3 add_hash_()	76
7.54.5.4 add_qudit()	76
7.54.5.5 begin() [1/2]	77
7.54.5.6 begin() [2/2]	77
7.54.5.7 cbegin()	77
7.54.5.8 cCTRL() [1/4]	77
7.54.5.9 cCTRL() [2/4]	78
7.54.5.10 cCTRL() [3/4]	78
7.54.5.11 cCTRL() [4/4]	79
7.54.5.12 cCTRL_custom()	79
7.54.5.13 cend()	30
7.54.5.14 CTRL() [1/4]	30
7.54.5.15 CTRL() [2/4]	31

281
281
282
282
283
283
283
284
284
285
285
286
286
286
287
287
287
288
288
288
289
289
289
289
290
290
290
290
291
291
291
292
292
292
293
293
294
294
294
295
295
296

7.54.6.1 operator << [1/4]	96
7.54.6.2 operator << [2/4]	96
7.54.6.3 operator << [3/4]	96
7.54.6.4 operator << [4/4]	97
7.54.6.5 QEngine	97
7.54.7 Member Data Documentation	97
7.54.7.1 cmat_hash_tbl	97
7.54.7.2 count	98
7.54.7.3 d	98
7.54.7.4 gates	98
7.54.7.5 measured	98
7.54.7.6 measurement_count	98
7.54.7.7 measurements	98
7.54.7.8 name	99
7.54.7.9 nc	99
7.54.7.10 nq	99
7.54.7.11 step_types	99
7.55 qpp::QEngine Class Reference	00
7.55.1 Detailed Description	02
7.55.2 Constructor & Destructor Documentation	02
7.55.2.1 QEngine() [1/3]	02
7.55.2.2 QEngine() [2/3]	03
7.55.2.3 QEngine() [3/3]	03
7.55.2.4 ~QEngine()	03
7.55.3 Member Function Documentation	03
7.55.3.1 display()	03
7.55.3.2 execute() [1/3]	04
7.55.3.3 execute() [2/3]	04
7.55.3.4 execute() [3/3]	04
7.55.3.5 get_circuit()	05
7.55.3.6 get_dit()	05
7.55.3.7 get_dits()	
7.55.3.8 get_measured() [1/2]	05
7.55.3.9 get_measured() [2/2]	06
7.55.3.10 get_non_measured()	06
7.55.3.11 get_probs()	06
7.55.3.12 get_psi()	07
7.55.3.13 get_relative_pos_()	07
7.55.3.14 get_stats()	07
7.55.3.15 operator=()	07
7.55.3.16 reset()	80
7.55.3.17 reset_stats()	08

7.55.3.18 set_dit()	308
7.55.3.19 set_measured_()	308
7.55.3.20 set_psi()	309
7.55.3.21 to_JSON()	309
7.55.4 Member Data Documentation	309
7.55.4.1 dits	310
7.55.4.2 probs	310
7.55.4.3 psi	310
7.55.4.4 qc	310
7.55.4.5 stats	310
7.55.4.6 subsys	310
7.56 qpp::QNoisyEngine < NoiseModel > Class Template Reference	311
7.56.1 Detailed Description	312
7.56.2 Constructor & Destructor Documentation	312
7.56.2.1 QNoisyEngine()	312
7.56.3 Member Function Documentation	313
7.56.3.1 execute() [1/4]	313
7.56.3.2 execute() [2/4]	313
7.56.3.3 execute() [3/4]	313
7.56.3.4 execute() [4/4]	314
7.56.3.5 get_noise_results()	314
7.56.4 Member Data Documentation	314
7.56.4.1 noise	314
7.56.4.2 noise_results	315
7.57 qpp::QubitAmplitudeDampingNoise Class Reference	315
7.57.1 Detailed Description	316
7.57.2 Constructor & Destructor Documentation	316
7.57.2.1 QubitAmplitudeDampingNoise()	316
7.58 qpp::QubitBitFlipNoise Class Reference	316
7.58.1 Detailed Description	317
7.58.2 Constructor & Destructor Documentation	318
7.58.2.1 QubitBitFlipNoise()	318
7.59 qpp::QubitBitPhaseFlipNoise Class Reference	318
7.59.1 Detailed Description	319
7.59.2 Constructor & Destructor Documentation	319
7.59.2.1 QubitBitPhaseFlipNoise()	319
7.60 qpp::QubitDepolarizingNoise Class Reference	320
7.60.1 Detailed Description	321
7.60.2 Constructor & Destructor Documentation	321
7.60.2.1 QubitDepolarizingNoise()	321
7.61 qpp::QubitPhaseDampingNoise Class Reference	321
7.61.1 Detailed Description	322

7.61.2 Constructor & Destructor Documentation	22
7.61.2.1 QubitPhaseDampingNoise()	22
7.62 qpp::QubitPhaseFlipNoise Class Reference	23
7.62.1 Detailed Description	24
7.62.2 Constructor & Destructor Documentation	24
7.62.2.1 QubitPhaseFlipNoise()	24
7.63 qpp::exception::QuditAlreadyMeasured Class Reference	24
7.63.1 Detailed Description	25
7.63.2 Member Function Documentation	25
7.63.2.1 description()	26
7.63.2.2 Exception()	26
7.64 qpp::QuditDepolarizingNoise Class Reference	26
7.64.1 Detailed Description	27
7.64.2 Constructor & Destructor Documentation	27
7.64.2.1 QuditDepolarizingNoise()	27
7.64.3 Member Function Documentation	28
7.64.3.1 fill_Ks_()	28
7.64.3.2 fill_probs_()	28
7.65 qpp::RandomDevices Class Reference	29
7.65.1 Detailed Description	30
7.65.2 Constructor & Destructor Documentation	30
7.65.2.1 RandomDevices()	30
7.65.2.2 ~RandomDevices()	31
7.65.3 Member Function Documentation	31
7.65.3.1 get_prng()	31
7.65.3.2 load()	31
7.65.3.3 save()	31
7.65.4 Friends And Related Function Documentation	32
7.65.4.1 internal::Singleton < RandomDevices >	32
7.65.5 Member Data Documentation	32
7.65.5.1 prng	32
7.65.5.2 rd	32
7.66 qpp::internal::Singleton < T > Class Template Reference	32
7.66.1 Detailed Description	33
7.66.2 Constructor & Destructor Documentation	33
7.66.2.1 Singleton() [1/2]	33
7.66.2.2 Singleton() [2/2]	34
7.66.2.3 ~Singleton()	34
7.66.3 Member Function Documentation	34
7.66.3.1 get_instance()	34
7.66.3.2 get_thread_local_instance()	34
7.66.3.3 operator=()	34

7.67 qpp::exception::SizeMismatch Class Reference	335
7.67.1 Detailed Description	336
7.67.2 Member Function Documentation	336
7.67.2.1 description()	336
7.67.2.2 Exception()	336
7.68 qpp::NoiseType::StateDependent Class Reference	337
7.68.1 Detailed Description	337
7.69 qpp::NoiseType::StateIndependent Class Reference	337
7.69.1 Detailed Description	337
7.70 qpp::States Class Reference	337
7.70.1 Detailed Description	339
7.70.2 Constructor & Destructor Documentation	340
7.70.2.1 States()	340
7.70.2.2 ~States()	340
7.70.3 Member Function Documentation	340
7.70.3.1 jn()	340
7.70.3.2 mes()	340
7.70.3.3 minus()	341
7.70.3.4 one()	341
7.70.3.5 plus()	342
7.70.3.6 zero()	342
7.70.3.6 Zeio()	
7.70.3 Priends And Related Function Documentation	
	342
7.70.4 Friends And Related Function Documentation	342 342
7.70.4 Friends And Related Function Documentation	342 342 342
7.70.4 Friends And Related Function Documentation	342 342 342 343
7.70.4 Friends And Related Function Documentation	342 342 342 343 343
7.70.4 Friends And Related Function Documentation	342 342 343 343 343
7.70.4 Friends And Related Function Documentation	342 342 343 343 343 343
7.70.4 Friends And Related Function Documentation	342 342 343 343 343 343 343
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States > 7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ	342 342 343 343 343 343 343 343
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00	342 342 343 343 343 343 343 343 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01	342 342 343 343 343 343 343 343 344 344
7.70.4 Friends And Related Function Documentation .  7.70.4.1 internal::Singleton < const States > .  7.70.5 Member Data Documentation .  7.70.5.1 b00 .  7.70.5.2 b01 .  7.70.5.3 b10 .  7.70.5.4 b11 .  7.70.5.5 GHZ .  7.70.5.6 pb00 .  7.70.5.7 pb01 .  7.70.5.8 pb10	342 342 343 343 343 343 343 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton< const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11	342 342 343 343 343 343 343 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton< const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ	342 342 343 343 343 343 343 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ 7.70.5.11 pW	342 342 343 343 343 343 344 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ 7.70.5.11 pW 7.70.5.12 px0	342 342 343 343 343 343 344 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ 7.70.5.11 pW 7.70.5.12 px0 7.70.5.13 px1	342 342 343 343 343 343 344 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ 7.70.5.11 pW 7.70.5.12 px0 7.70.5.13 px1 7.70.5.14 py0	342 342 343 343 343 343 344 344 344 344
7.70.4 Friends And Related Function Documentation 7.70.4.1 internal::Singleton < const States >  7.70.5 Member Data Documentation 7.70.5.1 b00 7.70.5.2 b01 7.70.5.3 b10 7.70.5.4 b11 7.70.5.5 GHZ 7.70.5.6 pb00 7.70.5.7 pb01 7.70.5.8 pb10 7.70.5.9 pb11 7.70.5.10 pGHZ 7.70.5.11 pW 7.70.5.12 px0 7.70.5.13 px1 7.70.5.14 py0 7.70.5.15 py1	342 342 343 343 343 343 344 344 344 345 345 345

7.70.5.19 x0
7.70.5.20 x1
7.70.5.21 y0
7.70.5.22 y1
7.70.5.23 z0
7.70.5.24 z1
7.71 qpp::exception::SubsysMismatchDims Class Reference
7.71.1 Detailed Description
7.71.2 Member Function Documentation
7.71.2.1 description()
7.71.2.2 Exception()
7.72 qpp::Timer < T, CLOCK_T > Class Template Reference
7.72.1 Detailed Description
7.72.2 Constructor & Destructor Documentation
7.72.2.1 Timer()
7.72.2.2 ~Timer()
7.72.3 Member Function Documentation
7.72.3.1 display()
7.72.3.2 get_duration()
7.72.3.3 tic()
7.72.3.4 tics()
7.72.3.5 toc()
7.72.4 Member Data Documentation
7.72.4.1 end
7.72.4.2 start
7.73 qpp::exception::TypeMismatch Class Reference
7.73.1 Detailed Description
7.73.2 Member Function Documentation
7.73.2.1 description()
7.73.2.2 Exception()
7.74 qpp::exception::UndefinedType Class Reference
7.74.1 Detailed Description
7.74.2 Member Function Documentation
7.74.2.1 description()
7.74.2.2 Exception()
7.75 qpp::exception::Unknown Class Reference
7.75.1 Detailed Description
7.75.2 Member Function Documentation
7.75.2.1 description()
7.75.2.2 Exception()
7.76 qpp::QCircuit::iterator::value_type_ Class Reference
7.76.1 Detailed Description

	7.76.2 Constructor & Destructor Documentation	360
	7.76.2.1 value_type_() [1/2]	360
	7.76.2.2 value_type_() [2/2]	361
	7.76.3 Member Function Documentation	361
	7.76.3.1 display()	361
	7.76.3.2 operator=()	361
	7.76.4 Member Data Documentation	361
	7.76.4.1 gates_ip	362
	7.76.4.2 ip	362
	7.76.4.3 measurements_ip	362
	7.76.4.4 type	362
	7.76.4.5 value_type_qc	362
	7.77 qpp::exception::ZeroSize Class Reference	363
	7.77.1 Detailed Description	364
	7.77.2 Member Function Documentation	364
	7.77.2.1 description()	364
	7.77.2.2 Exception()	364
0	File Documentation	365
0	8.1 classes/circuits/circuits.h File Reference	
	8.1.1 Detailed Description	
	8.2 classes/circuits/engines.h File Reference	
	8.2.1 Detailed Description	
	8.3.1 Detailed Description	
	8.4 classes/exception.h File Reference	
	8.4.1 Detailed Description	
	8.5 classes/gates.h File Reference	
	·	
	8.6 classes/idisplay.h File Reference	
	8.7 classes/init.h File Reference	
	8.7.1 Detailed Description	
	8.8 classes/noise.h File Reference	
	8.8.1 Detailed Description	
	8.9 classes/random_devices.h File Reference	
	8.9.1 Detailed Description	
	8.10 classes/reversible.h File Reference	
	8.10.1 Detailed Description	
	8.11 classes/states.h File Reference	
	8.11.1 Detailed Description	
	8.12 classes/timer.h File Reference	375

405

8.12.1 Detailed Description
8.13 constants.h File Reference
8.13.1 Detailed Description
8.14 entanglement.h File Reference
8.14.1 Detailed Description
8.15 entropies.h File Reference
8.15.1 Detailed Description
8.16 experimental/experimental.h File Reference
8.16.1 Detailed Description
8.17 functions.h File Reference
8.17.1 Detailed Description
8.18 input_output.h File Reference
8.18.1 Detailed Description
8.19 instruments.h File Reference
8.19.1 Detailed Description
8.20 internal/classes/iomanip.h File Reference
8.20.1 Detailed Description
8.21 internal/classes/singleton.h File Reference
8.21.1 Detailed Description
8.22 internal/util.h File Reference
8.22.1 Detailed Description
8.23 MATLAB/matlab.h File Reference
8.23.1 Detailed Description
8.24 number_theory.h File Reference
8.24.1 Detailed Description
8.25 operations.h File Reference
8.25.1 Detailed Description
8.26 qpp.h File Reference
8.26.1 Detailed Description
8.26.2 Macro Definition Documentation
8.26.2.1 QPP_UNUSED
8.27 random.h File Reference
8.27.1 Detailed Description
8.28 statistics.h File Reference
8.28.1 Detailed Description
8.29 traits.h File Reference
8.29.1 Detailed Description
8.30 types.h File Reference
8.30.1 Detailed Description
8.31 /Users/vlad/qpp/README.md File Reference

Index

### Quantum++

Version 1.3 - 25 July 2019

Build status:

Chat (questions/issues)

#### **About**

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see <a href="http://eigen.tuxfamily.org/dox/">http://eigen.tuxfamily.org/dox/</a>. For a simple Eigen 3 quick ASCII reference see <a href="http://eigen.tuxfamily.org/dox/AsciiQuick←">http://eigen.tuxfamily.org/dox/AsciiQuick←</a> Reference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

2 Quantum++

#### License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

#### Installation instructions and further documentation

Please see the installation guide `INSTALL.md` and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

# Namespace Index

### 2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

p	
Quantum++ main namespace	13
p::exception	
Quantum++ exception hierarchy namespace	116
p::experimental	
Experimental/test functions/classes, do not use or modify	118
p::internal	
Internal utility functions, do not use them directly or modify them	118
p::literals	125

4 Namespace Index

## **Hierarchical Index**

### 3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
app::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	
qpp::exception::TypeMismatch	353
qpp::exception::UndefinedType	355
qpp::exception::Unknown	357
qpp::exception::ZeroSize	363
false_type	
qpp::is_complex < T >	206
qpp::is_iterable < T, typename >	208
qpp::QCircuit::GateStep	. 186
qpp::internal::HashEigen	. 188
qpp::IDisplay	. 189
qpp::Dynamic bitset	
qpp::Bit circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	267
qpp::QEngine	300
is base of	
qpp::is_matrix_expression< Derived >	210
qpp::QCircuit::iterator	
qpp::make void< Ts >	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
***	
qpp::QubitPhaseDampingNoise	
qpp::NoiseBase < NoiseType::StateIndependent >	
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	326
qpp::NoiseType	. 246
$qpp::internal::Singleton < T > \dots \dots$	. 332
qpp::internal::Singleton < const Codes >	. 332
qpp::Codes	137
app::internal::Singleton < const Gates >	
qpp::Gates	
qpp::internal::Singleton < const Init >	
qpp::Init	
$qpp :: internal :: Singleton < const \ States > \dots $	. 332
qpp::States	337
qpp::internal::Singleton< RandomDevices >	. 332
qpp::RandomDevices	
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	
true_type	. 557
qpp::is_complex< std::complex< T >>	30°
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval<	
<pre>characteristic = continuous</pre>	
$\sim$ ().enu()), ueonype(*(siuueonyai $<$ 1 $>$ ().beyin())) $>$ $>$	208

## **Class Index**

#### 4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	
qpp::exception::CustomException	
Custom exception	
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	
qpp::exception::DimsNotEqual	
Dimensions not equal exception	
qpp::internal::Display_Impl	
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime	
qpp::internal::EqualEigen	
Functor for comparing Eigen expressions for equality	
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	
qpp::Gates	
Const Singleton class that implements most commonly used gates	
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	
qpp::internal::HashEigen	
Functor for hashing Eigen expressions	
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) of	0

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const 189

8 Class Index

qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support app::Init	191
Const Singleton class that performs additional initializations/cleanups	192
pp::exception::InvalidIterator	.02
Invalid iterator	194
qpp::internal::IOManipEigen	196
qpp::internal::IOManipPointer< PointerType >	199
qpp::internal::IOManipRange< InputIterator >	
qpp::is_complex< T >	
Checks whether the type is a complex type	206
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	207
qpp::is_iterable< T, typename >	
Checks whether $T$ is compatible with an STL-like iterable container $\dots$	208
qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(std::decltype(std::declval < T >().end()), decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::decltype(std::declt	ecltype(*(std::declval<
iterable containers	209
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	210
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	211
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	216
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	217
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	219
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	221
qpp::exception::MatrixNotSquare	
Matrix is not square exception	223
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	225
qpp::exception::MatrixNotSquareNorRvector	007
Matrix is not square nor row vector exception	227
qpp::exception::MatrixNotSquareNorVector	000
Matrix is not square nor vector exception	229
qpp::exception::MatrixNotVector	004
Matrix is not a vector exception	231
qpp::QCircuit::MeasureStep One step consisting only of measurements in the circuit	222
pp::exception::NoCodeword	200
Codeword does not exist exception	236
qpp::NoiseBase< T >	200
Base class for all noise models, derive your particular noise model	238
qpp::NoiseType	200
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	210
Not bi-partite exception	246
qpp::exception::NotImplemented	
Code not yet implemented	248
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	250
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	252
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	254

4.1 Class List

qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	256
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	258
qpp::exception::OutOfRange	
Argument out of range exception	260
qpp::exception::PermInvalid	
Invalid permutation exception	262
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	264
qpp::QCircuit	
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	300
qpp::QNoisyEngine < NoiseModel >	
Noisy quantum circuit engine, executes qpp::QCircuit	311
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	315
qpp::QubitBitFlipNoise	
Qubit bit flip noise	316
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	318
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	320
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	321
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	323
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	324
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	326
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	329
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	332
qpp::exception::SizeMismatch	
Size mismatch exception	335
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	337
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	337
qpp::States	
Const Singleton class that implements most commonly used states	337
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	347
qpp::Timer< T, CLOCK_T >	
Chronometer	349
qpp::exception::TypeMismatch	٠
Type mismatch exception	353
qpp::exception::UndefinedType	
Not defined for this type exception	355
qpp::exception::Unknown	
Unknown exception	357
qpp::QCircuit::iterator::value_type_	
Value type class for qpp::QCircuit::iterator	359

10		Class Index

qpp::exception::ZeroSize													
Object has zero size exception	 	 			 						 	. :	363

# **Chapter 5**

# File Index

## 5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	376
entanglement.h	
Entanglement functions	377
entropies.h	
Entropy functions	379
functions.h	
Generic quantum computing functions	380
input_output.h	
Input/output functions	385
instruments.h	
	386
number_theory.h	
	392
operations.h	
Quantum operation functions	394
qpp.h	
Quantum++ main header file, includes all other necessary headers	396
random.h	
Randomness-related functions	398
statistics.h	
Statistics functions	399
traits.h	
Type traits	400
types.h	
7,6	402
classes/codes.h	
Quantum error correcting codes	367
classes/exception.h	
Exceptions	367
classes/gates.h	
Quantum gates	369
classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	370

12 File Index

classes/init.h	
Initialization	371
classes/noise.h	
Noise models	372
classes/random_devices.h	
Random devices	373
classes/reversible.h	
Support for classical reversible circuits	373
classes/states.h	
Quantum states	374
classes/timer.h	
Timing	375
classes/circuits/circuits.h	
Qudit quantum circuits	365
classes/circuits/engines.h	
Qudit quantum engines	366
experimental/experimental.h	
Experimental/test functions/classes	380
internal/util.h	
Internal utility functions	389
internal/classes/iomanip.h	
Input/output manipulators	388
internal/classes/singleton.h	
Singleton pattern via CRTP	389
MATLAB/matlab.h	
Input/output interfacing with MATLAR	391

## **Chapter 6**

# **Namespace Documentation**

## 6.1 qpp Namespace Reference

Quantum++ main namespace.

## **Namespaces**

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

## Classes

• class Bit\_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

- struct is\_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is\_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is\_iterable < T,\ to\_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$ 

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is\_matrix\_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to\_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

#### **Typedefs**

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void\_t.

using idx = std::size\_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

#### **Enumerations**

• enum { RES, PROB, ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

## **Functions**

cplx omega (idx D)

D-th root of unity.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

dyn\_col\_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
&dims)

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt coefficients of the bi-partite pure state A.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Bob side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Bob side.

• template<typename Derived >

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Schmidt probabilities of the bi-partite pure state A.

```
• template<typename Derived >
  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

      Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

      Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  \mbox{double } \mbox{qmutualinfo (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std::vector} < \mbox{idx} > \&\mbox{subsysA, const}
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
     Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.
• template<typename Derived >
  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple < cmat, dyn col vect < double >, cmat > svd (const Eigen::MatrixBase < Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
```

Kronecker product.

```
Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.

    template<typename T, typename... Args>

  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As)
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn mat< typename T::Scalar > dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::↔
  MatrixBase< Derived2 > &B)
     Commutator.
- template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector < idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector< idx > &mask, idx d=2)
```

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

```
std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

```
std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

• template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

Container::value\_type prod (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn col vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

• template<typename Derived >

```
internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
```

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename InputIterator} >$ 

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const\_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std ::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

• template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer\_list < cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const cmat &V, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure\_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template < typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< cplx > >::type loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector < std::pair < int, int > > convergents (const std::vector < int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$ 

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std← ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &dims)

Partial trace.

template<typename Derived >

dyn mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

• template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric\_limits< idx >::min(), idx b=std::numeric\_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double a QPP\_UNUSED\_=0, double b QPP\_UNUSED =1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

```
dmat rand (idx rows, idx cols, double a, double b)
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

```
cmat rand (idx rows, idx cols, double a, double b)
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

• template<typename Derived >

Derived randn (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double mean QPP\_UNUSED\_=0, double sigma QPP\_UNUSED\_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

```
dmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

```
cmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >
 double avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable<
 Container >::value >::type \*=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Correlation.

#### **Variables**

constexpr double chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 $\pi$ 

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.

## 6.1.1 Detailed Description

Quantum++ main namespace.

#### 6.1.2 Typedef Documentation

#### 6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

### Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

#### 6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

## 6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

## 6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

## 6.1.2.6 dyn\_col\_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

#### Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

```
6.1.2.7 dyn_mat
```

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

#### Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

#### 6.1.2.8 dyn\_row\_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

#### Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

#### 6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

#### 6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

### 6.1.2.11 to\_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

## 6.1.3 Enumeration Type Documentation

## 6.1.3.1 anonymous enum

```
anonymous enum
```

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

#### Enumerator

RES	Measurement result(s)
PROB	Probabilit(y)/(ies)
ST	Output state(s)

## 6.1.4 Function Documentation

#### 6.1.4.1 absm()

Matrix absolute value.

#### **Parameters**

```
A Eigen expression
```

## Returns

Matrix absolute value of A

## 6.1.4.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

#### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

#### **Parameters**

```
c STL-like container
```

#### Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

#### **Parameters**

```
A Eigen expression
```

## Returns

Real vector consisting of the absolute values squared

## 6.1.4.5 adjoint()

## Adjoint.

```
A Eigen expression
```

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

#### 6.1.4.6 anticomm()

Anti-commutator.

#### See also

qpp::comm()

Anti-commutator  $\{A,B\}=AB+BA$ . Both A and B must be Eigen expressions over the same scalar field.

#### **Parameters**

Α	Eigen expression
В	Eigen expression

## Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

## **6.1.4.7** apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

## Note

The dimension of the gate A must match the dimension of target

state	Eigen expression				
Α	Eigen expression				
catarget by Subsystem indexes where the gate A is applie					
dims	Dimensions of the multi-partite system				

Gate A applied to the part target of state

```
6.1.4.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

#### Note

The dimension of the gate A must match the dimension of target

## **Parameters**

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

## Returns

Gate A applied to the part target of state

```
6.1.4.9 apply() [3/5]
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

## Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
d	Subsystem dimensions	

Output density matrix after the action of the channel

## 6.1.4.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

#### See also

```
qpp::Gates::CTRL()
```

#### Note

The dimension of the gate A must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

#### **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

### Returns

CTRL-A gate applied to the part target of state

#### 6.1.4.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

#### See also

```
qpp::Gates::CTRL()
```

#### Note

The dimension of the gate A must match the dimension of target

#### **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

#### Returns

CTRL-A gate applied to the part target of state

## 6.1.4.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

#### **Parameters**

Α	Eigen expression	
target	Subsystem indexes where the QFT is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

### Returns

Qudit Quantum Fourier transform applied to the part target of A

## 6.1.4.15 applyTFQ()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::applyTFQ (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
idx d = 2,
bool swap = true )
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

#### Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

#### 6.1.4.16 avg()

## Average.

## **Parameters**

prob	Real probability vector representing the probability distribution of $X$
X	Real random variable values represented by an STL-like container

## Returns

Average of X

## 6.1.4.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

## See also

qpp::rho2bloch()

r 3-dimensional real vector

#### Returns

Qubit density matrix

## 6.1.4.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

#### See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy  $Tr(K_i^\dagger K_j) = \delta_{ij}$  for all  $i \neq j$ 

#### **Parameters**

A Choi matrix

#### Returns

Set of orthogonal Kraus operators

## 6.1.4.19 choi2super()

Converts Choi matrix to superoperator matrix.

## See also

qpp::super2choi()

```
A Choi matrix
```

## Returns

Superoperator matrix

## 6.1.4.20 comm()

Commutator.

#### See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

## **Parameters**

Α	Eigen expression
В	Eigen expression

## Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as  ${\it A}$ 

## 6.1.4.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

subsys	Subsystem vector
n	Total number of systems

Complement of *subsys* with respect to the set  $\{0, 1, \dots, n-1\}$ 

## 6.1.4.22 compperm()

Compose permutations.

#### **Parameters**

perm	Permutation
sigma	Permutation

#### Returns

Composition of the permutations  $perm \circ sigma = perm(sigma)$ 

## 6.1.4.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

#### **Parameters**

```
A Eigen expression
```

## Returns

Wootters concurrence

## 6.1.4.24 conjugate()

Complex conjugate.

```
A Eigen expression
```

## Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

## 6.1.4.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

#### See also

```
qpp::x2contfrac()
```

#### Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

## **Parameters**

cf	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

#### Returns

Real representation of the simple continued fraction

## **6.1.4.26** convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

## Convergents.

## See also

qpp::contfrac2x() and qpp::x2contfrac()

```
cf Continued fraction
```

## Returns

Vector of convergents pairs  $(a_k, b_k)$  that approximate the number represented by the continued fraction

## **6.1.4.27 convergents()** [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

## Convergents.

#### See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

#### Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

#### **Parameters**

Χ	Real number
Ν	Number of convergents.

#### Returns

Vector of convergents pairs  $(a_k, b_k)$  that approximate the number x

## 6.1.4.28 cor()

#### Correlation.

probXY	Real matrix representing the joint probability distribution of <i>X</i> and <i>Y</i> in lexicographical order ( <i>X</i> label the rows, <i>Y</i> labels the columns)	
X	Real random variable values represented by an STL-like container	
Y	Real random variable values represented by an STL-like container	

## Returns

Correlation of X and Y

## 6.1.4.29 cosm()

Matrix cos.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Matrix cosine of A

## 6.1.4.30 cov()

#### Covariance.

probXY	Real matrix representing the joint probability distribution of $X$ and $Y$ in lexicographical order ( $X$ labels the rows, $Y$ labels the columns)
Χ	Real random variable values represented by an STL-like container
Υ	Real random variable values represented by an STL-like container

Covariance of X and Y

## 6.1.4.31 cwise()

## Functor.

#### **Parameters**

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

## Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

## 6.1.4.32 det()

#### Determinant.

## **Parameters**

```
A Eigen expression
```

## Returns

Determinant of A, as a scalar over the same scalar field as A. Returns  $\pm \infty$  when the determinant overflows/underflows.

Direct sum.

#### See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

#### **Parameters**

```
head Eigen expression
```

#### Returns

Its argument head

#### **6.1.4.34** dirsum() [2/4]

Direct sum.

#### See also

qpp::dirsumpow()

#### **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

## Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

## **6.1.4.35** dirsum() [3/4]

Direct sum.

## See also

qpp::dirsumpow()

As std::vector of Eigen expressions

# Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

#### See also

qpp::dirsumpow()

#### **Parameters**

As std::initializer\_list of Eigen expressions, such as {A1, A2, ..., Ak}

# Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

#### 6.1.4.37 dirsumpow()

Direct sum power.

# See also

qpp::dirsum()

Α	Eigen expression	
n	Non-negative integer	

#### **Returns**

Direct sum of A with itself n times  $A^{\oplus n}$ , as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

#### **Parameters**

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

# Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

# **Parameters**

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

# Returns

Instance of qpp::internal::IOManipEigen

```
6.1.4.40 disp() [3/5]
```

Range ostream manipulator.

#### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

#### Returns

Instance of qpp::internal::IOManipRange

```
6.1.4.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

# **Parameters**

С	Container
separator	Separator
start	Left marking
end	Right marking

# Returns

Instance of qpp::internal::IOManipRange

#### **6.1.4.42** disp() [5/5]

C-style pointer ostream manipulator.

#### **Parameters**

p	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

#### Returns

Instance of qpp::internal::IOManipPointer

# 6.1.4.43 egcd()

Extended greatest common divisor of two integers.

# See also

```
qpp::gcd()
```

# **Parameters**

а	Integer
b	Integer

# Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

#### 6.1.4.44 eig()

Full eigen decomposition.

See also

qpp::heig()

#### **Parameters**

```
A Eigen expression
```

#### Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

#### **6.1.4.45** entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

#### See also

```
qpp::entropy()
```

# **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

# Returns

Entanglement, with the logarithm in base 2

#### 6.1.4.46 entanglement() [2/2]

```
template<typename Derived > double qpp::entanglement ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

#### See also

```
qpp::entropy()
```

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Entanglement, with the logarithm in base 2

# 6.1.4.47 entropy() [1/2] template<typename Derived > double qpp::entropy (

const Eigen::MatrixBase< Derived > & A )

von-Neumann entropy of the density matrix A

#### **Parameters**

```
A Eigen expression
```

#### Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

prob Real probability vector

# Returns

Shannon entropy, with the logarithm in base 2

#### 6.1.4.49 evals()

Eigenvalues.

See also

qpp::hevals()

#### **Parameters**

A Eigen expression

# Returns

Eigenvalues of A, as a complex dynamic column vector

#### 6.1.4.50 evects()

Eigenvectors.

See also

qpp::hevects()

# **Parameters**

A Eigen expression

#### Returns

Eigenvectors of A, as columns of a complex dynamic matrix

# 6.1.4.51 expm()

Matrix exponential.

#### **Parameters**

```
A Eigen expression
```

# Returns

Matrix exponential of A

# 6.1.4.52 factors()

Prime factor decomposition.

Note

Runs in  $\mathcal{O}(\sqrt{n})$  time complexity

#### **Parameters**

```
a Integer different from 0, 1 or -1
```

#### Returns

Integer vector containing the factors

# 6.1.4.53 funm()

```
template<typename Derived >
cmat qpp::funm (
```

```
const Eigen::MatrixBase< Derived > & A,
cplx(*)(const cplx &) f )
```

Functional calculus f(A)

#### **Parameters**

Α	Eigen expression
f	Pointer-to-function from complex to complex

# Returns

f(A)

Greatest common divisor of two integers.

# See also

qpp::lcm()

## **Parameters**

а	Integer
b	Integer

# Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

# See also

qpp::lcm()

```
as List of integers
```

# Returns

Greatest common divisor of all numbers in as

# 6.1.4.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

# **Parameters**

```
A Eigen expression
```

# Returns

G-concurrence

# **6.1.4.57** grams() [1/3]

Gram-Schmidt orthogonalization.

As std::vector of Eigen expressions as column vectors

#### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

#### **Parameters**

As std::initializer\_list of Eigen expressions as column vectors

#### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

#### **Parameters**

A Eigen expression, the input vectors are the columns of A

# Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

#### 6.1.4.60 hash\_eigen()

Computes the hash of en Eigen matrix/vector/expression.

#### Note

```
Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine
```

#### **Parameters**

Α	Eigen expression
seed	Seed, 0 by default

#### Returns

Hash of its argument

# 6.1.4.61 heig()

Full eigen decomposition of Hermitian expression.

## See also

qpp::eig()

# **Parameters**

A Eigen expression

# Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

## 6.1.4.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

#### **Parameters**

```
A Eigen expression
```

# Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

# 6.1.4.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

#### **Parameters**

```
A Eigen expression
```

# Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

## 6.1.4.64 inverse()

Inverse.

```
A Eigen expression
```

# Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

# 6.1.4.65 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > qpp::invperm ( $$ const std::vector < idx > & perm ) [inline] $$
```

Inverse permutation.

# **Parameters**

perm	Permutation
------	-------------

#### Returns

Inverse of the permutation perm

# **6.1.4.66** ip() [1/2]

Generalized inner product.

# **Parameters**

phi	Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which <i>phi</i> is defined	
dims	Dimensions of the multi-partite system	

# Returns

Inner product  $\langle \phi_{subsys} | \psi \rangle$ , as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

#### **Parameters**

phi	Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
d	Subsystem dimensions	

#### Returns

Inner product  $\langle \phi_{subsys} | \psi \rangle$ , as a scalar or column vector over the remaining Hilbert space

# 6.1.4.68 isprime()

```
bool qpp::isprime ( bigint p, idx k = 80 ) [inline]
```

Primality test based on the Miller-Rabin's algorithm.

#### **Parameters**

р	Integer different from 0, 1 or -1	
k	Number of iterations. The probability of a false positive is $2^{-k}$ .	

# Returns

True if the number is (most-likely) prime, false otherwise

# 6.1.4.69 kraus2choi()

Choi matrix.

#### See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|$ ,  $|0\rangle\langle 1|$  etc.

Note

The superoperator matrix S and the Choi matrix C are related by  $S_{ab,mn}=C_{ma,nb}$ 

#### **Parameters**

```
Ks Set of Kraus operators
```

#### Returns

Choi matrix

# 6.1.4.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|$ ,  $|0\rangle\langle 1|$  etc.

#### **Parameters**

```
Ks Set of Kraus operators
```

#### Returns

Superoperator matrix

Kronecker product.

•		
See	а	เรด

qpp::kronpow()

Used to stop the recursion for the variadic template version of <a href="app::kron()">app::kron()</a>

head   Eigen expressio	n
------------------------	---

# Returns

Its argument head

Kronecker product.

#### See also

qpp::kronpow()

#### **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

# Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# Kronecker product.

# See also

qpp::kronpow()

```
As std::vector of Eigen expressions
```

# Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# See also

qpp::kronpow()

#### **Parameters**

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

#### Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# 6.1.4.75 kronpow()

Kronecker power.

#### See also

qpp::kron()

Α	Eigen expression
n	Non-negative integer

#### **Returns**

Kronecker product of A with itself n times  $A^{\otimes n}$ , as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

#### See also

qpp::gcd()

# **Parameters**

а	Integer	
b	Integer	

# Returns

Least common multiple of a and b

Least common multiple of a list of integers.

# See also

qpp::gcd()

# **Parameters**

as List of integers

#### Returns

Least common multiple of all numbers in as

#### 6.1.4.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

#### See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

#### Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

#### **Parameters**

```
fname Output file name
```

#### 6.1.4.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

# See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

# Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

# **Template Parameters**

#### **Parameters**

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

# Returns

Eigen dynamic matrix

# 6.1.4.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

#### See also

#### qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

# **Template Parameters**

Derived	Non-complex Eigen type
---------	------------------------

#### **Parameters**

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded	

#### Returns

Eigen dynamic matrix

#### 6.1.4.81 logdet()

```
{\tt template}{<}{\tt typename \ Derived} >
Derived::Scalar qpp::logdet (
              const Eigen::MatrixBase< Derived > & A )
```

Logarithm of the determinant.

Useful when the determinant overflows/underflows

#### **Parameters**

```
Eigen expression
```

#### Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

# 6.1.4.82 logm()

```
template<typename Derived >
cmat qpp::logm (
            const Eigen::MatrixBase< Derived > & A )
```

Matrix logarithm.

# **Parameters**

```
A | Eigen expression
```

# Returns

Matrix logarithm of A

# 6.1.4.83 lognegativity() [1/2]

```
{\tt template}{<}{\tt typename~Derived}>
double qpp::lognegativity (
              const Eigen::MatrixBase< Derived > & A,
              const std::vector< idx > & dims )
```

Logarithmic negativity of the bi-partite mixed state A.

# **Parameters**

Α	Eigen expression
alian a	Disconsions of the bij soutite avetous
aims	Dimensions of the bi-partite system
Congrated	by Doyygon

Generated by Doxygen

#### Returns

Logarithmic negativity, with the logarithm in base 2

```
6.1.4.84 lognegativity() [2/2] template<typename Derived > double qpp::lognegativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Logarithmic negativity of the bi-partite mixed state A.

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Logarithmic negativity, with the logarithm in base 2

# 6.1.4.85 marginalX()

Marginal distribution.

#### **Parameters**

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

# Returns

Real vector consisting of the marginal distribution of X

# 6.1.4.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

#### Returns

Real vector consisting of the marginal distribution of Y

# 

Measures the state vector or density operator A using the set of Kraus operators Ks.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

# **6.1.4.88** measure() [2/9]

Measures the state vector or density matrix  $\boldsymbol{A}$  using the set of Kraus operators  $\boldsymbol{Ks}$ .

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

#### **Parameters**

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

# See also

```
qpp::measure_seq()
```

# Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.4.91** measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

# See also

```
qpp::measure_seq()
```

# Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

# Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.4.92** measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.4.93** measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

# Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.4.94** measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target Subsystem indexes that are measured		
dims	Dimensions of the multi-partite system	

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.4.95** measure() [9/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target Subsystem indexes that are measured	
d	Subsystem dimensions

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

std::vector< idx > target,
std::vector< idx > dims )

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

#### See also

qpp::measure()

6.1.4.96 measure\_seq() [1/2]

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

#### Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

# See also

qpp::measure()

# **Parameters**

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

# Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

#### See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|\text{mask}\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

#### **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

#### Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.4.99 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

## See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

# Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

# Returns

Multi-partite qudit state vector, as a complex dynamic column vector

# 6.1.4.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

#### **Parameters**

а	Non-negative integer
р	Non-negative integer

# Returns

```
Modular inverse a^{-1} \mod p
```

# 6.1.4.101 modmul()

Modular multiplication without overflow.

Computes  $ab \bmod p$  without overflow

# **Parameters**

а	Integer
b	Integer
р	Positive integer

# Returns

 $ab \bmod p \text{ avoiding overflow}$ 

# 6.1.4.102 modpow()

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes  $a^n \mod p$ 

#### **Parameters**

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

#### Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

#### **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

# Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

```
6.1.4.104 mprj() [2/2] cmat qpp::mprj ( const std::vector< idx > \& mask, idx d = 2) [inline]
```

Projector onto multi-partite qudit ket.

#### See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

#### **Parameters**

mask	std::vector of non-negative integers
d	Subsystem dimensions

#### Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

# 6.1.4.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

## See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

#### **Parameters**

midx	Multi-index
dims	Dimensions of the multi-partite system

# Returns

Non-negative integer index

# 6.1.4.106 n2multiidx()

Non-negative integer index to multi-index.

#### See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

# **Parameters**

n	Non-negative integer index
dims	Dimensions of the multi-partite system

#### Returns

Multi-index of the same size as dims

```
6.1.4.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

# **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Negativity

# 6.1.4.108 negativity() [2/2]

Negativity of the bi-partite mixed state A.

## **Parameters**

Α	Eigen expression
d	Subsystem dimensions

Negativity

```
6.1.4.109 norm()
```

Frobenius norm.

**Parameters** 

```
A Eigen expression
```

Returns

Frobenius norm of A

# 6.1.4.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

# Parameters

```
A Eigen expression
```

Returns

Normalized state vector or density matrix

# 6.1.4.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

```
D Non-negative integer
```

### Returns

D-th root of unity  $\exp(2\pi i/D)$ 

#### 6.1.4.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

#### See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention  $A^0 = I$ .

#### **Parameters**

Α	Eigen expression
n	Non-negative integer

#### Returns

Matrix power  $A^n$ , as a dynamic matrix over the same scalar field as  ${\it A}$ 

# 6.1.4.113 prj()

### Projector.

Normalized projector onto state vector

# **Parameters**

A Eigen expression

Projector onto the state vector *A*, or the matrix *Zero* if *A* has norm zero, as a dynamic matrix over the same scalar field as *A* 

Element-wise product of A.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

# **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

```
6.1.4.116 prod() [3/3]

template<typename Container >
Container::value_type qpp::prod (
```

```
const Container & c,
typename std::enable_if< is_iterable< Container >::value >::type * = nullptr )
```

Element-wise product of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

#### Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

#### See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

#### See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

### 6.1.4.119 ptrace1() [1/2]

Partial trace.

#### See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsystem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

### 6.1.4.120 ptrace1() [2/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptrace1 (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsystem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

### 6.1.4.121 ptrace2() [1/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

# Returns

Partial trace  $Tr_B(\cdot)$  over the second subsytem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

#### **6.1.4.122** ptrace2() [2/2]

Partial trace.

#### See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_B(\cdot)$  over the second subsystem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

### 6.1.4.123 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

#### 6.1.4.124 ptranspose() [2/2]

### Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

#### Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

#### 6.1.4.125 QFT()

Qudit quantum Fourier transform.

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

### Returns

Qudit quantum Fourier transform applied on A

#### **6.1.4.126** qmutualinfo() [1/2]

```
template<typename Derived >
double qpp::qmutualinfo (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & subsysA,
const std::vector< idx > & subsysB,
const std::vector< idx > & dims )
```

Quantum mutual information between 2 subsystems of a composite system.

#### **Parameters**

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

### Returns

Mutual information between the 2 subsystems

### 6.1.4.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

#### **Parameters**

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

# Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

#### Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

#### Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

#### **Parameters**

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

#### Returns

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

#### Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
Generated	bਾਈਅਰਾਜ਼ੀhe interval, does not belong to it

Random complex matrix

# 6.1.4.133 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

# **Parameters**

D Dimension of the Hilbert space

#### Returns

Random Hermitian matrix

### 6.1.4.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

#### **Parameters**

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

#### Returns

Random index (idx) uniformly distributed in the interval [a, b]

# 6.1.4.135 randket()

```
ket qpp::randket (
        idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

D Dimension of the Hilbert space

#### Returns

Random normalized ket

#### 6.1.4.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

#### Note

The set of Kraus operators satisfy the closure condition  $\sum_i K_i^{\dagger} K_i = I$ 

#### **Parameters**

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

# Returns

Set of N Kraus operators satisfying the closure condition

# **6.1.4.137** randn() [1/4]

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

#### Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) normally distributed in N(0,2)
cmat mat = randn<cmat>(3, 3, 0, 2);
```

# **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

#### **Parameters**

mean	Mean
sigma	Standard deviation

# Returns

Random real number normally distributed in N(mean, sigma)

### 6.1.4.141 randperm()

```
\label{eq:std:vector} $$ std::vector < idx> qpp::randperm ( idx N) [inline] $$
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

#### **Parameters**

```
N Size of the permutation
```

#### Returns

Random permutation of size N

# 6.1.4.142 randprime()

```
bigint b,
idx N = 1000) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
Ν	Maximum number of candidates

#### Returns

Random big integer uniformly distributed in the interval [a, b]

### 6.1.4.143 randprob()

```
std::vector<double> qpp::randprob (
    idx N ) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

#### **Parameters**

N Size of the probability vector

#### Returns

Random probability vector

# 6.1.4.144 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

# **Parameters**

D Dimension of the Hilbert space

### Returns

Random density matrix

### 6.1.4.145 randU()

```
cmat qpp::randU (
          idx D = 2 ) [inline]
```

Generates a random unitary matrix.

### **Parameters**

```
D Dimension of the Hilbert space
```

### Returns

Random unitary

### 6.1.4.146 randV()

Generates a random isometry matrix.

#### **Parameters**

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

# Returns

Random isometry matrix

Renyi-  $\alpha$  entropy of the density matrix  ${\it A}$ , for  $\alpha \geq 0$ .

### Note

When lpha o 1 the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

#### Returns

Renyi-  $\alpha$  entropy, with the logarithm in base 2

Renyi-  $\alpha$  entropy of the probability distribution *prob*, for  $\alpha \geq 0$ .

#### Note

When  $\alpha \to 1$  the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

#### **Parameters**

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha = \infty$

#### Returns

Renyi-  $\alpha$  entropy, with the logarithm in base 2

# 6.1.4.149 reshape()

# Reshape.

Uses column-major order when reshaping (same as MATLAB)

#### **Parameters**

Α	Eigen expression
	Number of rows of the reshaped matrix
Generated COIS	by Noxyber of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

#### 6.1.4.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

#### See also

qpp::bloch2rho()

#### Note

It is implicitly assumed that the density matrix is Hermitian

#### **Parameters**

```
A Eigen expression
```

#### Returns

3-dimensional Bloch vector

# 6.1.4.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

#### Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

#### **Parameters**

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

#### 6.1.4.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

#### See also

qpp::load()

#### **Parameters**

Α	Eigen expression
fname	Output file name

# **6.1.4.153** saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

#### See also

qpp::loadMATLAB()

### **Template Parameters**

Complex Eigen type

#### **Parameters**

Α	Eigen expression over the complex field
---	---

mat_file MATALB .mat file		MATALB .mat file
	var_name	Variable name in the .mat file representing the matrix to be saved
	mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

# **6.1.4.154** saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

#### See also

qpp::loadMATLAB()

# **Template Parameters**

igen type

#### **Parameters**

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

# 6.1.4.155 schatten()

# Schatten matrix norm.

### **Parameters**

Α	Eigen expression
р	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

# Returns

Unitary matrix  ${\cal U}$  whose columns represent the Schmidt basis vectors on Alice side.

# 

Schmidt basis on Alice side.

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

# 6.1.4.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

# 

Schmidt basis on Bob side.

idx d = 2)

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

# 

Schmidt coefficients of the bi-partite pure state A.

# Note

The sum of the squares of the Schmidt coefficients equals 1

# See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

### **6.1.4.161** schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

#### Note

The sum of the squares of the Schmidt coefficients equals 1

#### See also

qpp::schmidtprobs()

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

# **6.1.4.162** schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

#### See also

qpp::schmidtcoeffs()

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

### 6.1.4.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

# See also

qpp::schmidtcoeffs()

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

#### 6.1.4.164 sigma()

#### Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

#### Returns

Standard deviation of X

# 6.1.4.165 sinm()

Matrix sin.

#### **Parameters**

A Eigen expression

#### Returns

Matrix sine of A

# 6.1.4.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of  $\emph{A}$  to compute the matrix power. By convention  $\emph{A}^0 = \emph{I}$  .

# **Parameters**

Α	Eigen expression
Z	Complex number

Matrix power  $A^z$ 

# 6.1.4.167 sqrtm()

Matrix square root.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Matrix square root of A

```
6.1.4.168 sum() [1/3]
```

Element-wise sum of A.

#### **Parameters**

```
A Eigen expression
```

# Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.4.169 sum() [2/3]
```

Element-wise sum of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

# Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

### 6.1.4.171 super2choi()

Converts superoperator matrix to Choi matrix.

# See also

qpp::choi2super()

#### **Parameters**

A Superoperator matrix

Choi matrix

### 6.1.4.172 svals()

Singular values.

#### **Parameters**

A Eigen expression

#### Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

#### 6.1.4.173 svd()

Full singular value decomposition.

#### **Parameters**

A Eigen expression

# Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

### 6.1.4.174 svdU()

Left singular vectors.

```
A Eigen expression
```

### Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

#### 6.1.4.175 svdV()

Right singular vectors.

# **Parameters**

```
A Eigen expression
```

#### Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

# 6.1.4.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

#### **Parameters**

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit *perm[i]* is permuted to the location *i*.

#### **Parameters**

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

#### Returns

Permuted system, as a dynamic matrix over the same scalar field as A

# 6.1.4.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

### **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

# Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

#### 6.1.4.179 trace()

Trace.

**Parameters** 

```
A Eigen expression
```

#### Returns

Trace of A, as a scalar over the same scalar field as A

### 6.1.4.180 transpose()

Transpose.

**Parameters** 

```
A Eigen expression
```

#### Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.4.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \ge 0$ .

Note

When  $q \to 1$  the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Α	Eigen expression
q	Non-negative real number

#### Returns

Tsallis- q entropy

```
6.1.4.182 tsallis() [2/2] double qpp::tsallis ( const std::vector< double > & prob, double q ) [inline]
```

Tsallis- q entropy of the probability distribution prob, for  $q \ge 0$ .

#### Note

When  $q \to 1$  the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

# **Parameters**

prob	Real probability vector	
q	Non-negative real number	

#### Returns

Tsallis- q entropy

# 6.1.4.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

# **Parameters**

N Size of the alphabet

Real vector consisting of a uniform distribution of size N

### 6.1.4.184 var()

Variance.

#### **Parameters**

prob	Real probability vector representing the probability distribution of $X$
Χ	Real random variable values represented by an STL-like container

#### Returns

Variance of X

#### 6.1.4.185 x2contfrac()

Simple continued fraction expansion.

### See also

```
qpp::contfrac2x()
```

#### **Parameters**

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

#### Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

# 6.1.5 Variable Documentation

# 6.1.5.1 chop

```
constexpr double qpp::chop = 1e-16
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

#### 6.1.5.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

#### 6.1.5.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

# 6.1.5.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

# 6.1.5.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

# 6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

#### Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

## 6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

## 6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

#### 6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

## 6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

#### **Classes**

- struct Display Impl
- class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- · class IOManipEigen
- class IOManipPointer
- class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

#### **Functions**

template < class T >
 void hash\_combine (std::size\_t &seed, const T &v)

Hash combine.

- void n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- template<typename Derived >

bool check\_square\_mat (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check\_vector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool <a href="mailto:check\_rvector">bool check\_rvector</a> (const Eigen::MatrixBase</a> Derived > &A)

template<typename Derived >

bool check cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool check\_dims\_match\_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

 $bool\ check\_dims\_match\_cvect\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$ 

template<typename Derived >

bool check\_dims\_match\_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check\_eq\_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check\_no\_duplicates (std::vector< idx > v)
- bool check subsys match dims (const std::vector < idx > &subsys, const std::vector < idx > &dims)
- template<typename Derived >

bool check\_qubit\_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check\_qubit\_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check\_qubit\_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >

 $bool\ check\_qubit\_vector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$ 

- bool check\_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

 $dyn_mat$ < typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen:: $\leftrightarrow$  MatrixBase< Derived2 > &B)

- template<typename Derived1 , typename Derived2 >
   dyn\_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
   ::MatrixBase< Derived2 > &B)
- template<typename T >
   void variadic\_vector\_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
   void variadic vector emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx get\_num\_subsys (idx D, idx d)
- idx get\_dim\_subsys (idx sz, idx N)
- template<typename T, typename std::enable\_if< std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value >::type \* = nullptr>
   T abs\_chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable\_if<!(std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value)>::type \* = nullptr>
   T abs\_chop (const T &x, double QPP\_UNUSED\_chop=qpp::chop)

#### 6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

#### 6.4.2 Function Documentation

6.4.2.3 check\_cvector()

template<typename Derived >

bool gpp::internal::check\_cvector (

const Eigen::MatrixBase< Derived > & A )

```
6.4.2.4 check_dims()
```

```
bool qpp::internal::check_dims ( \mbox{const std::vector} < \mbox{idx} > \mbox{\& dims} \mbox{)} \quad \mbox{[inline]}
```

#### 6.4.2.5 check\_dims\_match\_cvect()

#### 6.4.2.6 check\_dims\_match\_mat()

## 6.4.2.7 check\_dims\_match\_rvect()

#### 6.4.2.8 check\_eq\_dims()

#### 6.4.2.9 check\_matching\_sizes()

#### 6.4.2.10 check\_no\_duplicates()

```
bool qpp::internal::check_no_duplicates (
            std::vector < idx > v) [inline]
6.4.2.11 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.12 check_perm()
bool qpp::internal::check_perm (
             const std::vector< idx > & perm) [inline]
6.4.2.13 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check\_qubit\_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.16 check_qubit_vector()
```

```
template<typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.17 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.18 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.19 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
             const std::vector< idx > & subsys,
             const std::vector< idx > & dims) [inline]
6.4.2.20 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.21 dirsum2()
template<typename Derived1 , typename Derived2 >
\label{lem:dyn_mat} $$\operatorname{dyn\_mat}<\operatorname{typename}$$ Derived1::Scalar> qpp::internal::dirsum2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
```

#### 6.4.2.22 get\_dim\_subsys()

## 6.4.2.23 get\_num\_subsys()

#### 6.4.2.24 hash\_combine()

Hash combine.

## **Template Parameters**

1 Type
--------

## **Parameters**

seed	Initial seed, will be updated by the function
V	Value with which the hash is combined

## 6.4.2.25 kron2()

#### 6.4.2.26 multiidx2n()

```
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.27 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.28 variadic_vector_emplace() [1/2]
template < typename T >
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & )
6.4.2.29 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > \& v,
             First && first,
             Args &&... args )
```

#### 6.5 qpp::literals Namespace Reference

#### **Functions**

```
    constexpr cplx operator""_i (unsigned long long int x) noexcept

      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr cplx operator""_i (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)

    constexpr std::complex< float > operator""_if (unsigned long long int x) noexcept

      User-defined literal for complex i = \sqrt{-1} (integer overload)

    constexpr std::complex< float > operator""_if (long double x) noexcept

      User-defined literal for complex i = \sqrt{-1} (real overload)
• template<char... Bits>
  ket operator""_ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra operator""_bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat operator""_prj ()
      Multi-partite qubit projector user-defined literal.
```

## 6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator""_bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
gpp::mket() and gpp::adjoint()
```

Constructs the multi-partite qubit bra  $\langle Bits |$ 

**Template Parameters** 

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

cplx z = 4.5\_i; // type of z is std::complex<double>

```
6.5.1.4 operator"""_if() [1/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
auto z = 4_if; // type of z is std::complex<double>
6.5.1.5 operator"""_if() [2/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
auto z = 4.5_if; // type of z is std::complex<float>
6.5.1.6 operator"""_ket()
template<char... Bits>
ket qpp::literals::operator""_ket ( )
Multi-partite qubit ket user-defined literal.
See also
     qpp::mket()
Constructs the multi-partite qubit ket |Bits>
Template Parameters
 Bits
        String of binary numbers representing the qubit ket
Returns
     Multi-partite qubit ket, as a complex dynamic column vector
6.5.1.7 operator"""_prj()
```

Generated by Doxygen

template<char... Bits>

cmat qpp::literals::operator""\_prj ( )
Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector  $|Bits\rangle\langle Bits|$  (in the computational basis)

**Template Parameters** 

Bits String of binary numbers representing the qubit state to project on

Returns

Multi-partite qubit projector, as a complex dynamic matrix

# **Chapter 7**

# **Class Documentation**

# 7.1 qpp::Bit\_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit\_circuit:



Collaboration diagram for qpp::Bit\_circuit:



#### **Public Member Functions**

• Bit\_circuit (idx n)

Constructs a bit circuit instance.

• Bit\_circuit (const Dynamic\_bitset &dynamic\_bitset)

Conversion constructor, used to initialize a qpp::Bit\_circuit with a qpp::Dynamic\_bitset.

Bit\_circuit & X (idx i)

Bit flip.

virtual ∼Bit\_circuit ()=default

Default virtual destructor.

• Bit\_circuit & NOT (idx i)

Bit flip.

Bit\_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit\_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit\_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit\_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

Bit\_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get\_gate\_count (const std::string &name={}) const Bit circuit gate count.
- idx get\_gate\_depth (const std::string &name={}) const

Bit circuit gate depth.

#### **Private Attributes**

- std::unordered\_map< std::string, idx > depth\_ {}
   gate depths
- Dynamic\_bitset bNOT\_
- Dynamic\_bitset bCNOT\_
- Dynamic\_bitset bSWAP\_
- Dynamic\_bitset bTOF\_
- Dynamic\_bitset bFRED\_
- Dynamic\_bitset btotal\_

used for depth calculations

## **Additional Inherited Members**

## 7.1.1 Detailed Description

Classical reversible circuit simulator.

#### 7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

#### **Parameters**

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit\_circuit with a qpp::Dynamic\_bitset.

#### **Parameters**

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

## 7.1.3 Member Function Documentation

## 7.1.3.1 CNOT()

Controlled-NOT.

## **Parameters**

ctrl	Control bit index
target	Target bit index

#### Returns

Reference to the current instance

## 7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

#### **Parameters**

i	Control bit index
j	Target first bit index
k	Target second bit index

#### Returns

Reference to the current instance

#### 7.1.3.3 get\_gate\_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

#### **Parameters**

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.
------	--

#### Returns

Gate count

#### 7.1.3.4 get\_gate\_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

#### **Parameters**

name	Gate name (optional	). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

#### **Parameters**

```
i Bit position in the circuit
```

#### Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

#### Returns

Reference to the current instance

## 7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
         idx i,
         idx j) [inline]
```

Swap bits.

## **Parameters**

i	Bit index
j	Bit index

#### Returns

Reference to the current instance

## 7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

#### **Parameters**

i	Control first bit index
j	Control second bit index
k	Target bit index

#### Returns

Reference to the current instance

## 7.1.3.9 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx i) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

#### **Parameters**

i Bit position in the circuit

#### Returns

Reference to the current instance

## 7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

#### 7.1.4.8 depth\_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

# 7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



## **Public Types**

enum Type { Type::FIVE\_QUBIT, Type::SEVEN\_QUBIT\_STEANE, Type::NINE\_QUBIT\_SHOR }
 Code types, add more codes here if needed.

## **Public Member Functions**

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

## **Private Member Functions**

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

#### **Friends**

class internal::Singleton < const Codes >

## **Additional Inherited Members**

#### 7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

## 7.2.2 Member Enumeration Documentation

#### 7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

## See also

qpp::Codes::codeword()

#### **Enumerator**

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

## 7.2.3 Constructor & Destructor Documentation

## 7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

#### 7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

## 7.2.4 Member Function Documentation

#### 7.2.4.1 codeword()

Returns the codeword of the specified code type.

#### See also

```
qpp::Codes::Type
```

#### **Parameters**

type	Code type
i	Codeword index

## Returns

i-th codeword of the code type

## 7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

# 7.3 qpp::exception::CustomException Class Reference

Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



## **Public Member Functions**

• CustomException (const std::string &where, const std::string &what)

## **Private Member Functions**

• std::string description () const override Exception description.

#### **Private Attributes**

std::string what\_{{}}

#### 7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

#### 7.3.2 Constructor & Destructor Documentation

#### 7.3.2.1 CustomException()

#### 7.3.3 Member Function Documentation

#### 7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.3.4 Member Data Documentation

#### 7.3.4.1 what\_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

#### 7.4.2 Member Function Documentation

#### 7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.4.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

#### 7.5.2 Member Function Documentation

#### 7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.5.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
WITCIC	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



#### **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

#### 7.6.2 Member Function Documentation

#### 7.6.2.1 description()

```
std::string qpp::exception::DimsMismatchMatrix::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.6.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

#### 7.7.2 Member Function Documentation

#### 7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.7.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



#### **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

#### 7.8.2 Member Function Documentation

#### 7.8.2.1 description()

```
std::string qpp::exception::DimsMismatchVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.8.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

# 7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

## 7.9.2 Member Function Documentation

## 7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description ( ) const [inline], [override], [virtual]

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.9.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

# Parameters

where Text representing where the exception occurred


The documentation for this class was generated from the following file:

· classes/exception.h

# 7.10 qpp::internal::Display\_Impl\_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display\_Impl\_:



## **Public Member Functions**

template<typename T >
 std::ostream & display\_impl\_ (const T &A, std::ostream &os, double chop=qpp::chop) const

# 7.10.1 Member Function Documentation

# 7.10.1.1 display\_impl\_()

The documentation for this struct was generated from the following file:


• internal/util.h

# 7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

## 7.11.2 Member Function Documentation

## 7.11.2.1 description()

```
std::string qpp::exception::Duplicates::description ( ) const [inline], [override], [virtual]
```

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.11.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.12 qpp::Dynamic\_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic\_bitset:



Collaboration diagram for qpp::Dynamic\_bitset:



# **Public Types**

- using value\_type = unsigned int type of the storage elements
- using storage\_type = std::vector< value\_type > type of the storage

## **Public Member Functions**

• Dynamic\_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic\_bitset ()=default

Default virtual destructor.

const storage\_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage\_size () const noexcept

Size of the underlying storage space (in units of value\_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

• bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic\_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic\_bitset & set () noexcept

Set all bits to true.

Dynamic\_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

Dynamic\_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic\_bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic\_bitset & reset () noexcept

Sets all bits to false.

• Dynamic\_bitset & flip (idx pos)

Flips the bit at position pos.

Dynamic\_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic\_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic\_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic\_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char\_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic\_string < CharT, Traits, Allocator > to\_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

# **Protected Member Functions**

• idx index\_ (idx pos) const

Index of the pos bit in the storage space.

idx offset\_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

## **Protected Attributes**

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

## **Private Member Functions**

## 7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

# 7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

# 7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

## **Parameters**

*n* Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

## 7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

## Returns

True if all of the bits are set

## 7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

## Returns

True if any of the bits is set

# 7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

## Returns

Hamming weight

## 7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

# 7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

#### **Parameters**

os Output stream passed by reference

## Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

## **Parameters**

pos Position in the bitset

# Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

## Returns

Reference to the current instance

# 7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

#### **Parameters**

pos Position in the bitset

## Returns

The value of the bit at position pos

# 7.12.4.9 index\_()

Index of the pos bit in the storage space.

## **Parameters**

```
pos Bit location
```

## Returns

Index of the pos bit in the storage space

## 7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

## Returns

True if none of the bits are set

## 7.12.4.11 offset\_()

Offset of the pos bit in the storage space relative to its index.

## **Parameters**

```
pos Bit location
```

## Returns

Offset of the pos bit in the storage space relative to its index

## 7.12.4.12 operator"!=()

Inequality operator.

#### **Parameters**

```
rhs Dynamic_bitset against which the inequality is being tested
```

## Returns

True if the bitsets are not equal (bit by bit), false otherwise

## 7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

## **Parameters**

rhs Dynamic\_bitset against which the Hamming distance is computed

## Returns

Hamming distance

## 7.12.4.14 operator==()

Equality operator.

## **Parameters**

```
rhs Dynamic_bitset against which the equality is being tested
```

## Returns

True if the bitsets are equal (bit by bit), false otherwise

## **7.12.4.15** rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

# **Parameters**

pos	Position in the bitset
р	Probability

## Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

## **Parameters**

```
p Probability
```

## Returns

Reference to the current instance

Sets the bit at position pos to false.

## **Parameters**

pos Position in the bitset	
----------------------------	--

# Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

## **Parameters**

pos	Position in the bitset
value	Bit value

# Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

## Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

# Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value\_type, unsigned int by default)

#### Returns

Size of the underlying storage space

# 7.12.4.23 to\_string()

## String representation.

## **Template Parameters**

CharT	String character type
Traits	String traits
Allocator	String Allocator

## **Parameters**

	Character representing the zero
one	Character representing the one

#### Returns

The bitset as a string

## 7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

# 7.12.5.2 storage\_size\_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

# storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

· classes/reversible.h

# 7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

## **Public Member Functions**

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

# 7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case it simply returns false)

## 7.13.2 Member Function Documentation

# 7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

# 7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



## **Public Member Functions**

- Exception (const std::string &where)
  - Constructs an exception.
- const char \* what () const noexcept override
  - Overrides std::exception::what()
- virtual std::string description () const =0

Exception description.

# **Private Attributes**

- std::string where
- std::string msg\_

# 7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception::description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

## Example:

```
namespace qpp
{
namespace exception
{
    class ZeroSize : public Exception
    {
        public:
            std::string description() const override
            {
                  return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

## 7.14.2 Constructor & Destructor Documentation

## 7.14.2.1 Exception()

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

## 7.14.3 Member Function Documentation

#### 7.14.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
```

Exception description.

#### Returns

## **Exception** description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

```
7.14.3.2 what()
```

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

## Returns

**Exception** description

## 7.14.4 Member Data Documentation

# 7.14.4.1 msg\_

std::string qpp::exception::Exception::msg\_ [mutable], [private]

## 7.14.4.2 where\_

std::string qpp::exception::Exception::where\_ [private]

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



## **Public Member Functions**

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n.

cmat RX (double theta) const

Qubit rotation of theta about the X axis.

cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

• cmat SWAPd (idx D=2) const

SWAP gate for qudits.

• cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

• cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements  $|x\rangle \longrightarrow |ax \bmod N\rangle$ .

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &ctrl, const std::vector< idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::initializer\_list< idx > &dims) const

Expands out.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
idx d=2) const

Expands out.

std::string get\_name (const cmat &U) const

Get the name of the most common qubit gates.

## **Public Attributes**

• cmat Id2 {cmat::Identity(2, 2)}

Identity gate.

cmat H {cmat::Zero(2, 2)}

Hadamard gate.

cmat X {cmat::Zero(2, 2)}

Pauli Sigma-X gate.

cmat Y {cmat::Zero(2, 2)}

```
Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

     Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

     S gate.

    cmat T {cmat::Zero(2, 2)}

      T gate.
cmat CNOT {cmat::ldentity(4, 4)}
     Controlled-NOT control target gate.
cmat CZ {cmat::Identity(4, 4)}
     Controlled-Phase gate.
cmat CNOTba {cmat::Zero(4, 4)}
     Controlled-NOT target->control gate.
cmat SWAP {cmat::Identity(4, 4)}
     SWAP gate.
• cmat TOF {cmat::ldentity(8, 8)}
      Toffoli gate.
cmat FRED {cmat::Identity(8, 8)}
     Fredkin gate.
```

## **Private Member Functions**

• Gates ()

Initializes the gates.

• ∼Gates ()=default

Default destructor.

## **Friends**

class internal::Singleton < const Gates >

## **Additional Inherited Members**

# 7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

# 7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]
Initializes the gates.
```

## 7.15.2.2 $\sim$ Gates()

```
qpp::Gates::~Gates ( ) [private], [default]
```

Default destructor.

# 7.15.3 Member Function Documentation

## 7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

## See also

```
qpp::applyCTRL()
```

## Note

The dimension of the gate A must match the dimension of target

## **Parameters**

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

#### Returns

CTRL-A gate, as a matrix over the same scalar field as A

## **7.15.3.2 expandout()** [1/3]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::Gates::expandout (
```

```
const Eigen::MatrixBase< Derived > & A,
idx pos,
const std::vector< idx > & dims ) const [inline]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

## **Parameters**

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

## Returns

Tensor product  $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

## 7.15.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer\_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. <a href="qpp::idx">qpp::idx</a>, which has the net effect of picking the wrong (non-vector) <a href="qpp::expandout">qpp::expandout</a>() overload

#### **Parameters**

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Generated by Doxygen

#### Returns

Tensor product  $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

idx d = 2) const [inline]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

## **Parameters**

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

# Returns

Tensor product  $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

## 7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

#### **Parameters**

D Dimension of the Hilbert space

## Returns

Fourier transform gate for qudits

## 7.15.3.6 get\_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

#### **Parameters**

U Complex matrix representing the quantum gate

# Returns

The name of the gate (if any), otherwise the empty string

# 7.15.3.7 Id()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

#### **Parameters**

D | Dimension of the Hilbert space

## Returns

Identity gate on a Hilbert space of dimension D

# 7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements  $|x\rangle \longrightarrow |ax \bmod N\rangle$ .

#### Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy  $n \geq \lceil \log_2(N) \rceil$ 

#### **Parameters**

а	Positive integer less than N
N	Positive integer
n	Number of qubits required for implementing the gate

## Returns

Modular multiplication gate

## 7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

## **Parameters**

theta	Rotation angle
n	3-dimensional real (unit) vector

## Returns

Rotation gate

## 7.15.3.10 RX()

Qubit rotation of theta about the X axis.

## **Parameters**

theta	Rotation angle
-------	----------------

# Returns

Rotation gate

## 7.15.3.11 RY()

Qubit rotation of theta about the Y axis.

# **Parameters**

theta Rotat	tion angle
-------------	------------

## Returns

Rotation gate

# 7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

# **Parameters**

theta	Rotation angle

## Returns

Rotation gate

# 7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

## **Parameters**

D Dimension of the Hilbert space

## Returns

SWAP gate for qudits

# 7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

## **Parameters**

D Dimension of the Hilbert space

## Returns

Generalized X gate for qudits

# 7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

```
Defined as Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|
```

## **Parameters**

D Dimension of the Hilbert space

## Returns

Generalized Z gate for qudits

## 7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
```

```
friend class internal::Singleton< const Gates > [friend]
```

## 7.15.5 Member Data Documentation

## 7.15.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

## 7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

## 7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

```
7.15.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
```

```
7.15.5.10 TOF
```

```
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
```

Toffoli gate.

## 7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

# 7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

## 7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


classes/gates.h

# 7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::GateStep:



## **Public Member Functions**

• GateStep ()=default

Default constructor.

GateStep (GateType gate\_type, std::size\_t gate\_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name={})

Constructs a gate step instance.

# **Public Attributes**

```
GateType gate_type_ = GateType::NONE
```

gate type

std::size\_t gate\_hash\_ {}

gate hash

• std::vector<  $idx > ctrl_{\{\}}$ 

control

std::vector< idx > target\_ {}

target where the gate is applied

std::string name\_{}{}

custom name of the step

# 7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

## 7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 GateStep() [1/2]

qpp::QCircuit::GateStep::GateStep ( ) [default]
```

Default constructor.

## 7.16.2.2 GateStep() [2/2]

```
qpp::QCircuit::GateStep::GateStep (
    GateType gate_type,
    std::size_t gate_hash,
    const std::vector< idx > & ctrl,
    const std::vector< idx > & target,
    std::string name = {} ) [inline], [explicit]
```

Constructs a gate step instance.

## **Parameters**

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

## 7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_ {}
control
```

```
7.16.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_ {}
gate hash
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_ {}
custom name of the step
7.16.3.5 target_
std::vector<idx> qpp::QCircuit::GateStep::target_ {}
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits/circuits.h

# 7.17 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

# **Public Member Functions**

template < typename Derived >
 std::size\_t operator() (const Eigen::MatrixBase < Derived > &A) const

## 7.17.1 Detailed Description

Functor for hashing Eigen expressions.

## 7.17.2 Member Function Documentation

#### 7.17.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

# 7.18 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



#### **Public Member Functions**

virtual ~IDisplay ()=default
 Default virtual destructor.

#### **Private Member Functions**

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

#### **Friends**

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)</li>
 Overloads the extraction operator.

#### 7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

#### 7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

#### 7.18.3 Member Function Documentation

```
7.18.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value\_type\_, qpp::Dynamic\_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK\_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

#### 7.18.4 Friends And Related Function Documentation

#### 7.18.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function <a href="mailto:qpp::IDisplay::display">qpp::IDisplay::display()</a>

The documentation for this class was generated from the following file:


· classes/idisplay.h

# 7.19 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



## **Public Member Functions**

virtual ∼IJSON ()=default

Default virtual destructor.

• virtual std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

## 7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#### 7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

#### 7.19.3 Member Function Documentation

JSON representation of the derived instance, must be overridden by all derived classes.

**Parameters** 

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

## 7.20 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



## **Private Member Functions**

- Init ()
  - Additional initializations.
- ∼Init ()

Cleanups.

## **Friends**

class internal::Singleton < const Init >

#### **Additional Inherited Members**

## 7.20.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7 20 2	Constructor	& Destructor	Documentation
1.ZU.Z	CONSTRUCTOR	a nesilucioi	Documentation

```
7.20.2.1 Init()

qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.20.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

#### 7.20.3 Friends And Related Function Documentation

```
7.20.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

# 7.21 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



## **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.21.1 Detailed Description

Invalid iterator.

#### 7.21.2 Member Function Documentation

## 7.21.2.1 description()

```
std::string qpp::exception::InvalidIterator::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.21.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

• classes/exception.h


# 7.22 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



#### **Public Member Functions**

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

## **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

## **Private Attributes**

- cmat A
- double chop\_

#### 7.22.1 Constructor & Destructor Documentation

#### 7.22.2 Member Function Documentation

```
7.22.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

#### 7.22.3 Member Data Documentation

#### 7.22.3.1 A\_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.22.3.2 chop\_

double qpp::internal::IOManipEigen::chop\_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


## 7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



#### **Public Member Functions**

- IOManipPointer (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

#### **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

#### **Private Attributes**

- const PointerType \* p\_
- idx N
- std::string separator\_
- std::string start
- std::string end
- · double chop\_

#### 7.23.1 Constructor & Destructor Documentation

```
7.23.1.1 IOManipPointer() [1/2]
```

## 7.23.1.2 **IOManipPointer()** [2/2]

### 7.23.2 Member Function Documentation

#### 7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

#### 7.23.2.2 operator=()

#### 7.23.3 Member Data Documentation

```
7.23.3.1 chop_
```

```
template<typename PointerType >
double qpp::internal::IOManipPointer< PointerType >::chop_ [private]
```

#### 7.23.3.2 end\_

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

## 7.23.3.3 N\_

```
template<typename PointerType >
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

#### 7.23.3.4 p\_

```
template<typename PointerType >
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

#### 7.23.3.5 separator

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

#### 7.23.3.6 start\_

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


# 7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



#### **Public Member Functions**

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

### **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

### **Private Attributes**

- InputIterator first\_
- InputIterator last\_
- std::string separator\_
- std::string start\_
- std::string end\_
- double chop\_

#### 7.24.1 Constructor & Destructor Documentation

#### 7.24.1.1 | IOManipRange() [1/2]

#### 7.24.1.2 | IOManipRange() [2/2]

#### 7.24.2 Member Function Documentation

### 7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

#### 7.24.2.2 operator=()

#### 7.24.3 Member Data Documentation

```
7.24.3.1 chop_
template<typename InputIterator >
double qpp::internal::IOManipRange< InputIterator >::chop_ [private]
7.24.3.2 end
{\tt template}{<}{\tt typename~InputIterator~>}
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.24.3.3 first_
template<typename InputIterator >
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.24.3.4 last
{\tt template}{<}{\tt typename \ InputIterator} >
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.24.3.5 separator_
template<typename InputIterator >
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.24.3.6 start
{\tt template}{<}{\tt typename~InputIterator~>}
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


• internal/classes/iomanip.h

# 7.25 qpp::is\_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_complex< T >:



Collaboration diagram for qpp::is\_complex< T >:



#### 7.25.1 Detailed Description

template < typename T > struct qpp::is\_complex < T >

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>* 

The documentation for this struct was generated from the following file:


traits.h

# 7.26 qpp::is\_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is\_complex < std::complex < T > :



Collaboration diagram for qpp::is\_complex< std::complex< T >>:



## 7.26.1 Detailed Description

 $\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}$ 

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

# 7.27 qpp::is\_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_iterable < T, typename >:



Collaboration diagram for qpp::is\_iterable < T, typename >:



## 7.27.1 Detailed Description

template<typename T, typename = void> struct qpp::is\_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

7.28 qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is\_iterable< T, to\_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().begin())) > :



#### 7.28.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is\_iterable < T, \ to\_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std \leftarrow ::declval < T > ().begin())) > \\ \end{cases}$ 

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

## 7.29 qpp::is\_matrix\_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_matrix\_expression< Derived >:



Collaboration diagram for qpp::is\_matrix\_expression< Derived >:



## 7.29.1 Detailed Description

template<typename Derived>
struct qpp::is\_matrix\_expression< Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived >*. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

# 7.30 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



#### Classes

· class value\_type\_

Value type class for qpp::QCircuit::iterator.

## **Public Types**

• using difference\_type = long long

iterator trait

• using value\_type = value\_type\_

iterator trait

using pointer = const value\_type \*

iterator trait

• using reference = const value\_type &

iterator trait

using iterator\_category = std::forward\_iterator\_tag

iterator trait

#### **Public Member Functions**

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

const value\_type\_ & operator \* () const

Safe de-referencing operator.

void set\_begin\_ (const QCircuit \*qc)

Sets the iterator to std::begin(this)

void set\_end\_ (const QCircuit \*qc)

Sets the iterator to std::begin(this)

#### **Private Attributes**

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value\_type\_ elem\_ {nullptr}

## 7.30.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const\_iterator by default

## 7.30.2 Member Typedef Documentation

```
7.30.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

## 7.30.2.2 iterator\_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.30.2.3 pointer
using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait
7.30.2.4 reference
using qpp::QCircuit::iterator::reference = const value_type&
iterator trait
7.30.2.5 value_type
using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
7.30.3 Constructor & Destructor Documentation
7.30.3.1 iterator() [1/2]
qpp::QCircuit::iterator::iterator ( ) [default]
Default constructor.
7.30.3.2 iterator() [2/2]
qpp::QCircuit::iterator::iterator (
```

# 7.30.4 Member Function Documentation

const iterator & ) [default]

Default copy constructor.

```
7.30.4.1 operator *()
```

```
const value_type_& qpp::QCircuit::iterator::operator * ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

## 7.30.4.2 operator"!=()

Inequality operator.

**Parameters** 

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.30.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.30.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.30.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.30.4.6 operator==()
```

Equality operator.

**Parameters** 

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.30.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

**Parameters** 

qc | Pointer to constant quantum circuit

```
7.30.4.8 set_end_()
```

Sets the iterator to std::begin(this)

#### **Parameters**

qc Pointer to constant quantum circuit

#### 7.30.5 Member Data Documentation

```
7.30.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.30.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
< non-owning pointer to the parent const quantum circuit</pre>
```

The documentation for this class was generated from the following file:

• classes/circuits/circuits.h

# 7.31 qpp::make\_void < Ts > Struct Template Reference

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

```
#include <traits.h>
```

## **Public Types**

• typedef void type

## 7.31.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

See also

qpp::to\_void<>

## 7.31.2 Member Typedef Documentation

## 7.31.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

# 7.32 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



## **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.32.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

## 7.32.2 Member Function Documentation

#### 7.32.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.32.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.33 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



## **Public Member Functions**

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

## 7.33.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

## 7.33.2 Member Function Documentation

#### 7.33.2.1 description()

```
std::string qpp::exception::MatrixNotCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.33.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.34 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



## **Public Member Functions**

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

## 7.34.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

## 7.34.2 Member Function Documentation

#### 7.34.2.1 description()

```
std::string qpp::exception::MatrixNotRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.34.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.35 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



## **Public Member Functions**

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.35.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

# 7.35.2 Member Function Documentation

#### 7.35.2.1 description()

```
std::string qpp::exception::MatrixNotSquare::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.35.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.36 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.36.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

# 7.36.2 Member Function Documentation

#### 7.36.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.36.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.37 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.37.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

# 7.37.2 Member Function Documentation

#### 7.37.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.37.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

# **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.38 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.38.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

# 7.38.2 Member Function Documentation

#### 7.38.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.38.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.39 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.39.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

# 7.39.2 Member Function Documentation

#### 7.39.2.1 description()

```
std::string qpp::exception::MatrixNotVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.39.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.40 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



#### **Public Member Functions**

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement\_type, const std::vector< std::size\_t > &mats\_hash, const std
 ::vector< idx > &target, idx c\_reg, std::string name={})

Constructs a measurement step instance.

#### **Public Attributes**

MeasureType measurement\_type\_ = MeasureType::NONE

measurement type

- std::vector< std::size\_t >  $mats\_hash\_$  {}
- std::vector< idx > target\_{}{}

target where the measurement is applied

- idx c\_reg\_ {}

custom name of the step

#### 7.40.1 Detailed Description

One step consisting only of measurements in the circuit.

#### 7.40.2 Constructor & Destructor Documentation

```
7.40.2.1 MeasureStep() [1/2]
```

```
qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

#### 7.40.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

#### **Parameters**

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

#### 7.40.3 Member Data Documentation

```
7.40.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.40.3.2 mats_hash_
```

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_ {}
```

hashes of measurement matrix/matrices

#### 7.40.3.3 measurement\_type\_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

```
7.40.3.4 name_
```

```
std::string qpp::QCircuit::MeasureStep::name_ {}
```

custom name of the step

# 7.40.3.5 target\_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_ {}
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits/circuits.h

# 7.41 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.41.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

#### 7.41.2 Member Function Documentation

#### 7.41.2.1 description()

std::string qpp::exception::NoCodeword::description ( ) const [inline], [override], [virtual]
Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.41.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.42 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



#### **Public Types**

• using noise\_type = T

# **Public Member Functions**

template<typename U = noise\_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable\_if< std::is\_same< NoiseType::StateDependent,
 U >::value >::type \*=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise\_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable\_if< std::is\_same< NoiseType::StateIndependent, U >::value >::type \*=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get\_Ks () const

Vector of noise operators.

• std::vector< double > get\_probs () const

Vector of probabilities corresponding to each noise operator.

idx get\_last\_idx () const

Index of the last occurring noise element.

double get\_last\_p () const

Probability of the last occurring noise element.

cmat get\_last\_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

#### **Protected Member Functions**

void compute\_probs\_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

cmat compute\_state\_ (const cmat &state, const std::vector< idx > &target) const

Compute the resulting state after the noise was applied.

# **Protected Attributes**

const std::vector< cmat > Ks\_

Kraus operators.

std::vector< double > probs

probabilities

idx d\_ {}

qudit dimension

idx i\_ {}

index of the last occurring noise element

bool generated\_ {false}

invoked, or if the noise is state-independent

# 7.42.1 Detailed Description

```
\label{eq:class} \begin{array}{l} \text{template}{<} \text{class T}{>} \\ \text{class qpp::NoiseBase}{<} \text{T}{>} \end{array}
```

Base class for all noise models, derive your particular noise model.

# 7.42.2 Member Typedef Documentation

# 7.42.2.1 noise\_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

#### 7.42.3 Constructor & Destructor Documentation

#### 7.42.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

#### **Parameters**

Ks | Vector of noise (Kraus) operators that specify the noise

#### 7.42.3.2 NoiseBase() [2/2]

```
template<class T>
template<typename U = noise_type>
```

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

#### **Parameters**

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

#### 7.42.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

#### 7.42.4 Member Function Documentation

#### 7.42.4.1 compute\_probs\_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

# **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

#### 7.42.4.2 compute\_state\_()

Compute the resulting state after the noise was applied.

#### **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

# Returns

Resulting state after the noise was applied

#### 7.42.4.3 get\_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

#### Returns

Qudit dimension

# 7.42.4.4 get\_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

#### Returns

Vector of noise operators

```
7.42.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

#### Returns

Index of the last occurring noise element

#### 7.42.4.6 get\_last\_K()

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

#### Returns

Last occurring noise element

#### 7.42.4.7 get\_last\_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

#### Returns

Probability of the last occurring noise element

#### 7.42.4.8 get\_probs()

```
template < class T >
std::vector < double > qpp::NoiseBase < T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

#### Returns

Probability vector

#### **7.42.4.9** operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

#### **Parameters**

State vector or density matrix	state
--------------------------------	-------

#### Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

#### Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

const std::vector< idx > & target) const [inline], [virtual]

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

#### 7.42.5 Member Data Documentation

```
7.42.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.42.5.2 generated
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.42.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
```

```
7.42.5.4 Ks_
```

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

#### 7.42.5.5 probs\_

```
template < class T>
std::vector < double > qpp::NoiseBase < T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

# 7.43 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

#### Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

# 7.43.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.44 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



# **Public Member Functions**

- std::string description () const override Exception description.
- Exception (const std::string &where)

  Constructs an exception.

# 7.44.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

# 7.44.2 Member Function Documentation

#### 7.44.2.1 description()

```
std::string qpp::exception::NotBipartite::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.44.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.45 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotImplemented:$ 



Collaboration diagram for qpp::exception::NotImplemented:



# **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.45.1 Detailed Description

Code not yet implemented.

#### 7.45.2 Member Function Documentation

#### 7.45.2.1 description()

```
std::string qpp::exception::NotImplemented::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.45.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred
wilele	I TEXT TEDITESELLING WHELE THE EXCEPTION OCCURRED

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.46 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.46.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

# 7.46.2 Member Function Documentation

#### 7.46.2.1 description()

```
std::string qpp::exception::NotQubitCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.46.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.47 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.47.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

# 7.47.2 Member Function Documentation

#### 7.47.2.1 description()

std::string qpp::exception::NotQubitMatrix::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.47.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the	exception occurred
-----------------------------------	--------------------

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.48 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.48.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

# 7.48.2 Member Function Documentation

#### 7.48.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.48.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.49 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.49.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

# 7.49.2 Member Function Documentation

#### 7.49.2.1 description()

std::string qpp::exception::NotQubitSubsys::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.49.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.50 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.50.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

# 7.50.2 Member Function Documentation

#### 7.50.2.1 description()

std::string qpp::exception::NotQubitVector::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.50.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

	where	Text representing where the exception occurred	1
--	-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.51 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.51.1 Detailed Description

Argument out of range exception.

Argument out of range

## 7.51.2 Member Function Documentation

## 7.51.2.1 description()

```
std::string qpp::exception::OutOfRange::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.51.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.52 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.52.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

## 7.52.2 Member Function Documentation

## 7.52.2.1 description()

```
std::string qpp::exception::PermInvalid::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.52.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.53 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.53.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

## 7.53.2 Member Function Documentation

## 7.53.2.1 description()

```
std::string qpp::exception::PermMismatchDims::description ( ) const [inline], [override],
[virtual]
```

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.53.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.54 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



## **Classes**

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

## **Public Types**

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

GateType::CUSTOM, GateType::FAN, GateType::SINGLE\_CTRL\_SINGLE\_TARGET, GateType::SINGLE\_CTRL\_MULTIPLE\_

GateType::MULTIPLE CTRL SINGLE TARGET, GateType::MULTIPLE CTRL MULTIPLE TARGET,

GateType::CUSTOM CTRL, GateType::SINGLE cCTRL SINGLE TARGET,

GateType::SINGLE cCTRL MULTIPLE TARGET, GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE\_cCTRL\_MULTIPLE\_TARGET, GateType::CUSTOM\_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE\_Z, MeasureType::MEASURE\_V, MeasureType::MEASURE V MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

· using const iterator = iterator

both iterators are const\_iterators

#### **Public Member Functions**

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

const\_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

· const\_iterator end () const noexcept

Constant iterator to the next to the last element.

· const\_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

idx get\_nq () const noexcept

Total number of qudits in the circuit.

• idx get\_nc () const noexcept

Total number of classical dits in the circuit.

• idx get\_d () const noexcept

Dimension of the comprising qudits.

• std::string get\_name () const

Quantum circuit name.

• idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get\_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get non measured () const

Vector of non-measured qudit indexes.

idx get\_gate\_count (const std::string &name={}) const

Quantum circuit gate count.

idx get\_gate\_depth (const std::string &name={}) const

Quantum circuit gate depth.

idx get\_measurement\_count () const noexcept

Quantum circuit total measurement count.

idx get\_measurement\_count (const std::string &name) const

Quantum circuit measurement count.

idx get\_step\_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

idx get nop count () const

No-op count.

QCircuit & add\_qudit (idx n=1, idx i=-1)

Adds n additional qudits before qudit i (by default adds them at the end)

QCircuit & add\_dit (idx n=1, idx i=-1)

Adds n additional classical dits before dit i (by default adds them at the end)

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, const std::initializer list< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate\_fan (const cmat &U, std::string name={})

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate custom (const cmat &U, const std::vector < idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer\_list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

• QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP UNUSED =true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer\_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL\_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuit & cCTRL (const cmat &U, idx ctrl\_dit, idx target, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl\_dit, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl\_dits, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL\_custom (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

• QCircuit & measureZ (idx target, idx c\_reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c\_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c\_reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V

• QCircuit & nop ()

No operation (no-op)

· QCircuit & replicate (idx n)

Replicates the circuit.

• QCircuit & add\_circuit (QCircuit other, bigint pos\_qudit, idx pos\_dit=-1)

Appends a quantum circuit description to the current one.

• std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const override

qpp::IJOSN::to\_JSON() override

#### **Private Member Functions**

void add\_hash\_ (const cmat &U, std::size\_t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get\_measurements\_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get\_gates\_ () const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered\_map< std::size\_t, cmat > & get\_cmat\_hash\_tbl\_ () const noexcept

Hash table with the matrices used in the circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

#### **Private Attributes**

```
• idx nq_
     number of qudits

    idx nc

     number of classical "dits"

    const idx d

     qudit dimension

    std::string name

     optional circuit name

    std::vector< bool > measured

     keeps track of the measured qudits
std::unordered_map< std::size_t, cmat > cmat_hash_tbl_ {}
std::unordered_map< std::string, idx > count_{{}}
     gate counts

    std::unordered_map< std::string, idx > measurement_count_{}{}

     measurement counts
std::vector< GateStep > gates_{}{}
std::vector< MeasureStep > measurements_{}{}
     measurements
std::vector < StepType > step_types_{}
     type of each step
```

### **Friends**

- · class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate\_type)</li>

Extraction operator overload for qpp::QCircuit::GateType enum class.

std::ostream & operator<< (std::ostream &os, const GateStep &gate\_step)</li>

Extraction operator overload for <a href="mailto:qpp::QCircuit::GateStep">qpp::QCircuit::GateStep</a> class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure\_type)</li>

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure\_step)</li>

Extraction operator overload for qpp::QCircuit::MeasureStep class.

#### 7.54.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

## 7.54.2 Member Typedef Documentation

## 7.54.2.1 const\_iterator

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const\_iterators

## 7.54.3 Member Enumeration Documentation

## 7.54.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

#### Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	controls and multiple targets custom controlled gate with multiple classical

## 7.54.3.2 MeasureType

enum qpp::QCircuit::MeasureType [strong]

Type of measurement being executed in a measurement step.		

#### Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$

## 7.54.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

## Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT measurement	
NOP	no-op

## 7.54.4 Constructor & Destructor Documentation

## 7.54.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

### Note

The measurement results can only be stored in the classical dits of which number is specified by *nc* 

## **Parameters**

nq	Number of qbits
nc	Number of classical dits (optional)
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$ )
name	Circuit name (optional)

#### 7.54.4.2 $\sim$ QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

#### 7.54.5 Member Function Documentation

#### 7.54.5.1 add\_circuit()

Appends a quantum circuit description to the current one.

#### Note

If qudit indexes of the added quantum circuit description do not totally overlap with the indexes of the current quantum circuit description, then the required number of additional qudits are automatically added to the current quantum circuit description

#### **Parameters**

other	Quantum circuit description
pos_qudit	The index of the first qudit of <i>other</i> relative to the index of the first qudit of the current quantum circuit description, with the rest following in order. If negative or greater than the total number of qudits of the current quantum circuit description, the required number of additional qudits are automatically added to the current quantum circuit description.
pos_dit	The first classical dit of <i>other</i> is inserted before the <i>pos_dit</i> classical dit index of the current quantum circuit description (in the classical dits array), the rest following in order. By default, insertion is performed at the end.

## Returns

Reference to the current instance

## 7.54.5.2 add\_dit()

```
QCircuit& qpp::QCircuit::add_dit (  \mbox{idx } n = 1, \\ \mbox{idx } i = -1 \mbox{) [inline]}
```

Adds *n* additional classical dits before dit *i* (by default adds them at the end)

#### Note

Classical dits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

#### **Parameters**

n	Number of classical dits
i	Classical dit index

#### **Returns**

Reference to the current instance

## 7.54.5.3 add\_hash\_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

## Parameters

U	Complex matrix
hashL	Hash value of U

## 7.54.5.4 add\_qudit()

Adds n additional qudits before qudit i (by default adds them at the end)

Note

Qudits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

#### **Parameters**

n	Number of qudits
i	Qudit index

## Returns

Reference to the current instance

```
7.54.5.5 begin() [1/2]
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.6 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.7 cbegin()
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate	
ctrl_dit	Classical control dit index	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

## **Parameters**

U	Single qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

#### Returns

Reference to the current instance

## 7.54.5.12 cCTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

#### **Parameters**

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate $U$ is applied depending on the values of the classical control dits
name	Optional gate name

## Returns

Reference to the current instance

## 7.54.5.13 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

### Returns

Constant iterator to the next to the last element

idx target,

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

std::string name = {} ) [inline]

## Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

### Returns

Reference to the current instance

```
7.54.5.15 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the control qudits
name	Optional gate name

#### Returns

Reference to the current instance

```
7.54.5.16 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

## Returns

Reference to the current instance

```
7.54.5.17 CTRL() [4/4]
```

```
QCircuit& qpp::QCircuit::CTRL (

const cmat & U,
```

```
const std::vector< idx > & ctrl,
const std::vector< idx > & target,
std::string name = {} ) [inline]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the control qudits
name	Optional gate name

### Returns

Reference to the current instance

## 7.54.5.18 CTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

## Parameters

U	Multiple-qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes where the gate $U$ is applied depending on the values of the control qudits	
name	Optional gate name	

#### Returns

Reference to the current instance

### 7.54.5.19 display()

## qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

#### **Parameters**

os Output stream passed by reference

## Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.20 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

## Returns

Iterator to the next to the last element

```
7.54.5.21 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

## Returns

Constant iterator to the next to the last element

std::string name = {} ) [inline]

Applies the single qudit gate *U* on single qudit *i*.

#### **Parameters**

U	Single qudit quantum gate
i	Qudit index
name Generated b	Optional gate name

#### Returns

Reference to the current instance

Applies the two qudit gate *U* on qudits *i* and *j*.

#### **Parameters**

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

## Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

## Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

#### Returns

Reference to the current instance

## 7.54.5.25 gate\_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

### **Parameters**

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

### Returns

Reference to the current instance

```
7.54.5.26 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

## Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

## Returns

Reference to the current instance

### **7.54.5.27** gate\_fan() [2/3]

Applies the single qudit gate *U* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

#### Returns

Reference to the current instance

```
7.54.5.28 gate_fan() [3/3]
```

Applies the single qudit gate *U* on every remaining non-measured qudit.

#### **Parameters**

U	Single qudit quantum gate
name	Optional gate name

## Returns

Reference to the current instance

## 7.54.5.29 get\_cmat\_hash\_tbl\_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

#### Returns

Hash table with the matrices used in the circuit

```
7.54.5.30 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

#### Returns

**Qudit dimension** 

## 7.54.5.31 get\_gate\_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

### **Parameters**

name	Gate name (optional)
------	----------------------

## Returns

Gate count

## 7.54.5.32 get\_gate\_depth()

Quantum circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

## **Parameters**

name	Gate name (optional)	

```
Returns
```

Gate depth

```
7.54.5.33 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

#### Returns

Vector of qpp::QCircuit::GateStep

Check whether qudit *i* was already measured.

### **Parameters**

i Qudit index

### Returns

True if qudit i was already measured, false othwewise

```
7.54.5.35 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

## Returns

Vector of already measured qudit indexes

```
7.54.5.36 get_measurement_count() [1/2]
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

Quantum circuit measurement count.

#### **Parameters**

name	Measurement name
Hairie	Measurement name

**Returns** 

Measurement count

```
7.54.5.38 get_measurements_()
```

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.54.5.39 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.54.5.40 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

#### Returns

Total number of classical dits

```
7.54.5.41 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

#### Returns

Vector of non-measured qudit indexes

```
7.54.5.42 get_nop_count()
```

```
idx qpp::QCircuit::get_nop_count ( ) const [inline]
```

No-op count.

## Returns

No-op count

#### 7.54.5.43 get\_nq()

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

### Returns

Total number of qudits

#### 7.54.5.44 get\_step\_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

#### Returns

Total (gates + measurements) count

## **7.54.5.45** measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

### **Parameters**

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

## Returns

Reference to the current instance

## **7.54.5.46** measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

## **Parameters**

Gen <i>enahe</i> nib	y <b>ுதர்ஞா</b> al measurement name
c_reg	Classical register where the value of the measurement is stored
target	Target qudit indexes that are jointly measured
V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V

#### Returns

Reference to the current instance

## 7.54.5.47 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

## **Parameters**

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Z"

## Returns

Reference to the current instance

```
7.54.5.48 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

## Returns

Reference to the current instance

```
7.54.5.49 QFT() [1/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

#### **Parameters**

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

#### Returns

Reference to the current instance

```
7.54.5.50 QFT() [2/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

#### **Parameters**

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

## Returns

Reference to the current instance

```
7.54.5.51 QFT() [3/3]
```

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

## **Parameters**

swap	Swaps the qubits at the end (true by default)
------	---

## Returns

Reference to the current instance

### 7.54.5.52 replicate()

Replicates the circuit.

Note

The circuit should not contain any measurements when invoking this member function

#### **Parameters**

```
n Number of repetitions. If n == 1, returns the original circuit.
```

## Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

### **Parameters**

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

#### Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

#### **Parameters**

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

#### Returns

Reference to the current instance

```
7.54.5.55 TFQ() [3/3]
```

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

#### **Parameters**

swap	Swaps the qubits at the end (true by default)
------	---

### Returns

Reference to the current instance

```
7.54.5.56 to_JSON()
```

qpp::IJOSN::to\_JSON() override

Displays the quantum circuit in JSON format

## **Parameters**

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

## Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

## 7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

#### **Parameters**

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

### Returns

Output stream

```
7.54.6.2 operator << [2/4]
```

Extraction operator overload for qpp::QCircuit::GateStep class.

### **Parameters**

os	Output stream
gate_step	qpp::QCircuit::GateStep class

#### Returns

Output stream

```
7.54.6.3 operator << [3/4]
```

Extraction operator overload for <a href="mailto:qpp::QCircuit::MeasureType">qpp::QCircuit::MeasureType</a> enum class.

#### **Parameters**

os	Output stream
measure_type	qpp::QCircuit::MeasureType enum class

### Returns

Output stream

```
7.54.6.4 operator << [4/4]
```

```
std::ostream& operator<< (
          std::ostream & os,
          const MeasureStep & measure_step ) [friend]</pre>
```

Extraction operator overload for qpp::QCircuit::MeasureStep class.

#### **Parameters**

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

### Returns

Output stream

### 7.54.6.5 QEngine

```
friend class QEngine [friend]
```

### 7.54.7 Member Data Documentation

### 7.54.7.1 cmat\_hash\_tbl\_

```
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
```

hash table with the matrices used in the circuit, with [Key = std::size\_t, Value = cmat]

```
7.54.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.54.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.54.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.54.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.54.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
7.54.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
```

```
7.54.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.54.7.9 nc_
idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.54.7.10 nq_
idx qpp::QCircuit::nq_ [private]
number of qudits
7.54.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits/circuits.h

# 7.55 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



## **Public Member Functions**

• QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

ket get\_psi () const

Underlying quantum state.

std::vector< idx > get\_dits () const

Vector with the values of the underlying classical dits.

• idx get dit (idx i) const

Value of the classical dit at position i.

• std::vector< double > get\_probs () const

Vector of underlying measurement outcome probabilities.

• bool get\_measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get\_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get\_non\_measured () const

Vector of non-measured gudit indexes.

const QCircuit & get\_circuit () const noexcept

Quantum circuit.

• const std::map < idx, idx > & get\_stats () const

Measurement statistics for multiple runs.

• QEngine & set\_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set\_psi (const ket &psi)

Sets the underlying quantum state to psi.

• QEngine & reset\_stats ()

Resets the collected measurement statistics hash table.

void reset (bool clear\_stats=true)

Resets the engine.

virtual void execute (const QCircuit::iterator::value\_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

void execute (idx reps=1, bool clear stats=true)

Executes the entire quantum circuit.

• std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const override

qpp::IJOSN::to\_JSON() override

#### **Protected Member Functions**

void set\_measured\_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

• std::vector< idx > get relative pos (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

### **Protected Attributes**

### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

### 7.55.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

### 7.55.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

qpp::QEngine(QCircuit&&)

Note

The initial underlying quantum state is set to  $|0\rangle^{\otimes n}$ 

#### **Parameters**

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

### 7.55.2.4 ~QEngine()

```
\label{eq:condition} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

#### 7.55.3 Member Function Documentation

```
7.55.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

#### **Parameters**

```
os Output stream passed by reference
```

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

#### **Parameters**

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

### **Parameters**

```
it Iterator to the step to be executed
```

```
7.55.3.4 execute() [3/3]

void qpp::QEngine::execute (
        idx reps = 1,
        bool clear_stats = true ) [inline]
```

Executes the entire quantum circuit.

### **Parameters**

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

```
7.55.3.5 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.55.3.6 get_dit()
```

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

#### **Parameters**

```
i Classical dit index
```

### Returns

Value of the classical dit at position i

```
7.55.3.7 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.55.3.8 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit  $\emph{i}$  was already measured.

#### **Parameters**

i Qudit index

#### Returns

True if qudit i was already measured, false othwewise

```
7.55.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

#### Returns

Vector of already measured qudit indexes

#### 7.55.3.10 get\_non\_measured()

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

#### Returns

Vector of non-measured qudit indexes

```
7.55.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state  $(|00\rangle+|11\rangle)/\sqrt{2}$ , then the vector of outcome probabilities will be [0.5, 1].

#### Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index  $c\_reg$ , then the outcome probability is automatically stored at the same index  $c\_reg$  in the probability vector.

#### Returns

Vector of underlying measurement outcome probabilities

```
7.55.3.12 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

#### Returns

Underlying quantum state

#### 7.55.3.13 get\_relative\_pos\_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

#### **Parameters**



#### Returns

Vector of qudit indexes

### 7.55.3.14 get\_stats()

```
const std::map<idx, idx>& qpp::QEngine::get_stats ( ) const [inline]
```

Measurement statistics for multiple runs.

### Returns

Hash table with collected measurement statistics for multiple runs, with hash key being the decimal value of the vector of measurement results and value being the number of occurrences (of the vector of measurement results), with the most significant bit located at index 0 (i.e. top/left) of the classical dits array.

#### 7.55.3.15 operator=()

Default copy assignment operator.

#### Returns

Reference to the current instance

#### 7.55.3.16 reset()

```
void qpp::QEngine::reset (
          bool clear_stats = true ) [inline]
```

Resets the engine.

### **Parameters**

clear_stats	Resets the collected measurement statistics hash table (true by default)
-------------	--

Re-initializes everything to zero and sets the initial state to  $|0\rangle^{\otimes n}$ 

### 7.55.3.17 reset\_stats()

```
QEngine& qpp::QEngine::reset_stats ( ) [inline]
```

Resets the collected measurement statistics hash table.

#### Returns

Reference to the current instance

### 7.55.3.18 set\_dit()

Sets the classical dit at position i.

### Parameters

i	Classical dit index
value	Classical dit value

#### Returns

Reference to the current instance

## 7.55.3.19 set\_measured\_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

#### **Parameters**

i Qudit index

#### 7.55.3.20 set\_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

#### **Parameters**

```
psi State vector
```

#### Returns

Reference to the current instance

# 7.55.3.21 to\_JSON()

qpp::IJOSN::to\_JSON() override

Displays the state of the engine in JSON format

#### **Parameters**

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

### Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

#### 7.55.4 Member Data Documentation

```
7.55.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.55.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.55.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector
7.55.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit
7.55.4.5 stats_
std::map<idx, idx> qpp::QEngine::stats_ [protected]
measurement statistics for multiple runs
7.55.4.6 subsys_
std::vector<idx> qpp::QEngine::subsys_ [protected]
keeps track of the measured subsystems, re-label them after measurements
```

• classes/circuits/engines.h


The documentation for this class was generated from the following file:

# 7.56 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



### **Public Member Functions**

- QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)
  - Constructs a noisy quantum engine out of a quantum circuit.
- void execute (const QCircuit::iterator::value\_type &elem) override
   Executes one step in the quantum circuit.
- std::vector < std::vector < idx > > get\_noise\_results () const
   Vector of noise results obtained before every step in the circuit.
- virtual void execute (const QCircuit::iterator::value\_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute (idx reps=1, bool clear\_stats=true)

Executes the entire quantum circuit.

### **Private Attributes**

```
• const NoiseModel noise_
```

quantum noise model

 std::vector< std::vector< idx >> noise\_results\_ noise results

### **Additional Inherited Members**

### 7.56.1 Detailed Description

```
template<typename NoiseModel> class qpp::QNoisyEngine< NoiseModel>
```

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

```
qpp::QCircuit, qpp::NoiseBase
```

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every step in the logical circuit

**Template Parameters** 

```
NoiseModel | Quantum noise model, should be derived from qpp::NoiseBase
```

### 7.56.2 Constructor & Destructor Documentation

#### 7.56.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

### **Parameters**

qc	Quantum circuit
noise	Quantum noise model

### 7.56.3 Member Function Documentation

```
7.56.3.1 execute() [1/4]
```

```
template<typename NoiseModel >
virtual void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

#### **Parameters**

elem	Step to be executed
------	---------------------

### **7.56.3.2** execute() [2/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes the entire quantum circuit.

### **Parameters**

reps		Number of repetitions
clear_st	ats	Resets the collected measurement statistics hash table before the run

### **7.56.3.3 execute()** [3/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

#### **Parameters**

Executes one step in the quantum circuit.

#### **Parameters**

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

#### 7.56.3.5 get\_noise\_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

#### Returns

Vector of noise results

#### 7.56.4 Member Data Documentation

```
7.56.4.1 noise_
```

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

#### 7.56.4.2 noise\_results\_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
noise results
```

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

# 7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



### **Public Member Functions**

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

### **Additional Inherited Members**

## 7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

#### 7.57.2 Constructor & Destructor Documentation

#### 7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

#### **Parameters**

gamma	Amplitude damping coefficient
-------	-------------------------------

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



### **Public Member Functions**

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

### **Additional Inherited Members**

## 7.58.1 Detailed Description

Qubit bit flip noise.

### 7.58.2 Constructor & Destructor Documentation

### 7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

**Parameters** 

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Bit Phase Flip Noise:$ 



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



### **Public Member Functions**

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

### **Additional Inherited Members**

### 7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

### 7.59.2 Constructor & Destructor Documentation

### 7.59.2.1 QubitBitPhaseFlipNoise()

Qubit bit-phase flip noise constructor.

### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



### **Public Member Functions**

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

**Additional Inherited Members** 

### 7.60.1 Detailed Description

Qubit depolarizing noise.

### 7.60.2 Constructor & Destructor Documentation

### 7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

#### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Phase Damping Noise:$ 



Collaboration diagram for qpp::QubitPhaseDampingNoise:



### **Public Member Functions**

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

### **Additional Inherited Members**

### 7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

### 7.61.2 Constructor & Destructor Documentation

### 7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

### **Parameters**

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



## **Public Member Functions**

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

### **Additional Inherited Members**

### 7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

### 7.62.2 Constructor & Destructor Documentation

### 7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

#### **Parameters**

```
p Noise probability
```

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

### 7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

### 7.63.2 Member Function Documentation

#### 7.63.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description ( ) const [inline], [override],
[virtual]

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.63.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



#### **Public Member Functions**

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

#### **Private Member Functions**

• std::vector< cmat > fill\_Ks\_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill\_probs\_ (double p, idx d) const
 Fills the probability vector.

### **Additional Inherited Members**

### 7.64.1 Detailed Description

Qudit depolarizing noise.

#### 7.64.2 Constructor & Destructor Documentation

#### 7.64.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

#### **Parameters**

р	Noise probability
d	Qudit dimension

# 7.64.3 Member Function Documentation

```
7.64.3.1 fill_Ks_()
```

```
std::vector<cmat> qpp::QuditDepolarizingNoise::fill_Ks_ (
          idx d) const [inline], [private]
```

Fills the Kraus operator vector.

#### **Parameters**

```
d Qudit dimension
```

#### Returns

Vector of Kraus operators representing the depolarizing noise

```
7.64.3.2 fill_probs_()
```

```
\label{eq:continuous} $$ std::vector<double> qpp::QuditDepolarizingNoise::fill_probs_ ($ double p, $ idx d ) const [inline], [private] $$
```

Fills the probability vector.

#### **Parameters**

р	Probability
d	Qudit dimension

### Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random\_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



### **Public Member Functions**

• std::mt19937 & get\_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

### **Private Member Functions**

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

### **Private Attributes**

 std::random\_device rd\_ used to seed std::mt19937 prng\_

std::mt19937 prng\_

Mersenne twister random number generator.

#### **Friends**

class internal::Singleton < RandomDevices >

#### **Additional Inherited Members**

### 7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random\_device engine. The latter is used to seed the Mersenne twister.

### Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use <a href="https://example.com/qpp::rand">qpp::rand()</a> instead!

#### 7.65.2 Constructor & Destructor Documentation

### 7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

```
7.65.2.2 ∼RandomDevices()
```

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

### 7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

#### Returns

Reference to the internal PRNG object

### 7.65.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

### **Parameters**

```
is Input stream
```

#### Returns

The input stream

### 7.65.3.3 save()

Saves the state of the PRNG to an output stream.

#### **Parameters**

os Output stream

#### Returns

The output stream

#### 7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

### 7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng\_

The documentation for this class was generated from the following file:

• classes/random\_devices.h

# 7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

#### **Static Public Member Functions**

- static T & get\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)
- static T & get\_thread\_local\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)

#### **Protected Member Functions**

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

## 7.66.1 Detailed Description

```
template<typename T>
class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get\_instance() (qpp::internal::Singleton::get\_thread\_local\_instance()), which returns a reference (thread\_local\_reference) to your newly created singleton (thread-safe in C++11).

#### Example:

#### See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

#### 7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]

template<typename T>

qpp::internal::Singleton< T >::Singleton ( ) [protected], [default], [noexcept]
```

# 7.66.2.2 Singleton() [2/2] template<typename T> qpp::internal::Singleton< T >::Singleton ( const Singleton< T > & ) [protected], [delete] 7.66.2.3 $\sim$ Singleton() template<typename T> $\label{thm:prop} \mbox{virtual qpp::internal::Singleton< $T>::\sim Singleton () [protected], [virtual], [default]$ 7.66.3 Member Function Documentation 7.66.3.1 get\_instance() template<typename T> static T& qpp::internal::Singleton< T >::get\_instance ( ) [inline], [static], [noexcept] 7.66.3.2 get\_thread\_local\_instance() template<typename T> static T& qpp::internal::Singleton< T >::get\_thread\_local\_instance ( ) [inline], [static], [noexcept] 7.66.3.3 operator=() template<typename T> Singleton& qpp::internal::Singleton< T >::operator= ( const Singleton< T > & ) [protected], [delete]

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

## 7.67 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

## 7.67.2 Member Function Documentation

## 7.67.2.1 description()

std::string qpp::exception::SizeMismatch::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.67.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

## 7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

## 7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

## 7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

## 7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

## 7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



## **Public Member Functions**

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$  state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

## **Public Attributes**

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

#### **Private Member Functions**

- States ()
- ∼States ()=default

Default destructor.

## **Friends**

class internal::Singleton < const States >

#### **Additional Inherited Members**

## 7.70.1 Detailed Description

const Singleton class that implements most commonly used states

## 7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

## 7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$  state of *n* qudits

## Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

## Returns

 $|j\rangle^{\otimes n}$  state of *n* qudits

## 7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

#### **Parameters**

d Subsystem dimensions

## Returns

Maximally entangled state  $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$  of 2 qudits

## 7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

## **Parameters**

n Non-negative integer

#### Returns

Minus state  $|-\rangle^{\otimes n}$  of n qubits

## 7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

#### **Parameters**

n	Non-negative integer
d	Subsystem dimensions

## Returns

One state  $|1\rangle^{\otimes n}$  of n qudits

## 7.70.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

## **Parameters**

```
n Non-negative integer
```

## Returns

Plus state  $|+\rangle^{\otimes n}$  of n qubits

## 7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

## **Parameters**

n	Non-negative integer
d	Subsystem dimensions

## Returns

Zero state  $|0\rangle^{\otimes n}$  of n qudits

## 7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

friend class internal::Singleton< const States > [friend]

## 7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

#### 7.70.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

## 7.70.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

## 7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

## 7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

## 7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

## 7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

#### 7.71.2 Member Function Documentation

#### 7.71.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description ( ) const [inline], [override],
[virtual]

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.71.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

## 7.72 qpp::Timer < T, CLOCK\_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK\_T >:



Collaboration diagram for qpp::Timer < T, CLOCK\_T >:



#### **Public Member Functions**

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual  $\sim$ Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

· const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get\_duration () const noexcept

Duration specified by U.

## **Protected Attributes**

- CLOCK\_T::time\_point start\_
- CLOCK\_T::time\_point end\_

#### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

## 7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

#### **Template Parameters**

T	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_ <i>T</i>	

## 7.72.2 Constructor & Destructor Documentation

## 7.72.2.1 Timer()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double>, typename CLOCK_T = std::chrono::steady &clock> \\ qpp::Timer < T, CLOCK_T >::Timer ( ) [inline], [noexcept] \\ \end{tabular}
```

Constructs an instance with the current time as the starting point.

## 7.72.2.2 $\sim$ Timer()

```
\label{top:clock} $$ $ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ $ \end{tikzpename} $$ CLOCK_T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tiz
```

Default virtual destructor.

#### 7.72.3 Member Function Documentation

## 7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of <a href="mailto:qpp::Timer::toc">qpp::Timer::toc</a>()

#### **Parameters**

os Output stream passed by reference

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

#### 7.72.3.2 get\_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

## **Template Parameters**

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

## Returns

Duration that passed between the instantiation/reset and invocation of <a href="mailto:qpp::Timer::toc">qpp::Timer::toc</a>()

#### 7.72.3.3 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

#### 7.72.3.4 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

#### Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

## 7.72.3.5 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

## 7.72.4 Member Data Documentation

#### 7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start\_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

## 7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

## 7.73.2 Member Function Documentation

## 7.73.2.1 description()

std::string qpp::exception::TypeMismatch::description ( ) const [inline], [override], [virtual]
Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.73.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

## 7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Undefined Type:$ 



Collaboration diagram for qpp::exception::UndefinedType:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

## 7.74.2 Member Function Documentation

## 7.74.2.1 description()

std::string qpp::exception::UndefinedType::description ( ) const [inline], [override], [virtual]
Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.74.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

## 7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

## 7.75.2 Member Function Documentation

## 7.75.2.1 description()

std::string qpp::exception::Unknown::description ( ) const [inline], [override], [virtual]
Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.75.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

· classes/exception.h


## 7.76 qpp::QCircuit::iterator::value\_type\_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value\_type\_:



Collaboration diagram for qpp::QCircuit::iterator::value\_type\_:



## **Public Member Functions**

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

## **Public Attributes**

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

## **Private Member Functions**

## 7.76.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

## 7.76.2 Constructor & Destructor Documentation

#### **Parameters**

	value_type_qc	Pointer to constant quantum circuit
--	---------------	-------------------------------------

Default copy constructor.

#### 7.76.3 Member Function Documentation

## 7.76.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

#### **Parameters**

```
os Output stream passed by reference
```

## Returns

Reference to the output stream

Implements qpp::IDisplay.

## 7.76.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

## 7.76.4 Member Data Documentation

```
7.76.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.76.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.4.3 measurements_ip_
\verb|std::vector<| \texttt{MeasureStep}>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| to the const_iterator | to the const_itera
measurements instruction pointer
7.76.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```


• classes/circuits/circuits.h

## 7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

## 7.77.2 Member Function Documentation

## 7.77.2.1 description()

std::string qpp::exception::ZeroSize::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.77.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where	Text representing where the exception occurred
WITCIC	Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h


## **Chapter 8**

## **File Documentation**

## 8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



## Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value\_type\_

Value type class for qpp::QCircuit::iterator.

366 File Documentation

## **Namespaces**

• qpp

Quantum++ main namespace.


## 8.1.1 Detailed Description

Qudit quantum circuits.

## 8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



#### Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

## **Namespaces**

• qpp

Quantum++ main namespace.


## 8.2.1 Detailed Description

Qudit quantum engines.

## 8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



## Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

## **Namespaces**

qpp

Quantum++ main namespace.

## 8.3.1 Detailed Description

Quantum error correcting codes.

## 8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



368 File Documentation

#### **Classes**

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

• class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

· class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

### **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


## 8.4.1 Detailed Description

Exceptions.

# 8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



### Classes

· class qpp::Gates

const Singleton class that implements most commonly used gates

# **Namespaces**

• qpp

Quantum++ main namespace.

# 8.5.1 Detailed Description

Quantum gates.

# 8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



## Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

## **Namespaces**

• qpp

Quantum++ main namespace.


# 8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

# 8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



## **Classes**

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.7.1 Detailed Description

Initialization.

## 8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



#### **Classes**

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

## **Namespaces**

• qpp

Quantum++ main namespace.


## 8.8.1 Detailed Description

Noise models.

# 8.9 classes/random\_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



### Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

## **Namespaces**

qpp

Quantum++ main namespace.


# 8.9.1 Detailed Description

Random devices.

## 8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



## Classes

• class qpp::Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit\_circuit

Classical reversible circuit simulator.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.10.1 Detailed Description

Support for classical reversible circuits.

# 8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



### Classes

· class qpp::States

const Singleton class that implements most commonly used states

# **Namespaces**

qpp

Quantum++ main namespace.

# 8.11.1 Detailed Description

Quantum states.

# 8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



# **Classes**

class qpp::Timer < T, CLOCK\_T >
 Chronometer.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.12.1 Detailed Description

Timing.

### 8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

· qpp::literals

### **Enumerations**

enum { qpp::RES, qpp::PROB, qpp::ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

## **Functions**

- constexpr cplx qpp::literals::operator""\_i (unsigned long long int x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (integer overload)
- constexpr cplx qpp::literals::operator""\_i (long double x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (real overload)
- constexpr std::complex< float > qpp::literals::operator""\_if (unsigned long long int x) noexcept
  - User-defined literal for complex  $i=\sqrt{-1}$  (integer overload)
- constexpr std::complex< float > qpp::literals::operator""\_if (long double x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (real overload)
- cplx qpp::omega (idx D)

D-th root of unity.

### Variables

• constexpr double qpp::chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 $\pi$ 

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double <a href="mailto:qpp::infty">qpp::infty</a> = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.


## 8.13.1 Detailed Description

Constants.

# 8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


### 8.14.1 Detailed Description

Entanglement functions.

# 8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$ 

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi-  $\alpha$  entropy of the density matrix A, for  $\alpha \geq 0$ .

double <a href="mailto:qpp::renyi">qpp::renyi</a> (const std::vector< double > &prob, double alpha)

Renyi-  $\alpha$  entropy of the probability distribution prob, for  $\alpha \geq 0.$ 

• template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \geq 0$ .

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for  $q \geq 0$ .

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$ 

Quantum mutual information between 2 subsystems of a composite system.

## 8.15.1 Detailed Description

Entropy functions.

# 8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

## **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


## 8.16.1 Detailed Description

Experimental/test functions/classes.

# 8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



# Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

### **Namespaces**

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Internal utility functions, do not use them directly or modify them.

#### **Functions**

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.
template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
ullet template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

Eigenvectors.

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
template<typename Derived >
  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
ullet template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
ullet template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.
\bullet \ \ {\it template}{<} {\it typename Derived}>
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >
```

dyn\_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

Anti-commutator.

• template<typename Derived >

 $\label{localized} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{qpp::prj (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A})$ 

Projector.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)

Gram-Schmidt orthogonalization.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::grams (const std::initializer\_list< Derived > &As)

Gram-Schmidt orthogonalization.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > dpp::grams (const Eigen::MatrixBase < Derived > &A)$ 

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator\_traits< InputIterator >::value\_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value\_type qpp::sum (const Container &c, typename std::enable\_if< is\_iterable< Container >
::value >::type \*=nullptr)

Element-wise sum of the elements of an STL-like container.

• template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value\_type qpp::prod (const Container &c, typename std::enable\_if< is\_iterable< Container >
::value >::type \*=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator""_ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

bra qpp::literals::operator""\_bra ()

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

cmat qpp::literals::operator""\_prj ()

Multi-partite qubit projector user-defined literal.

• template<class T >

void qpp::internal::hash\_combine (std::size\_t &seed, const T &v)

Hash combine.

template<typename Derived >

 $std::size\_t \; qpp::hash\_eigen \; (const \; Eigen::MatrixBase < \; Derived > \&A, \; std::size\_t \; seed=0)$ 

Computes the hash of en Eigen matrix/vector/expression.


## 8.17.1 Detailed Description

Generic quantum computing functions.

# 8.18 input\_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

qpp

Quantum++ main namespace.

### **Functions**

- template<typename Derived >
   internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
   Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const\_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename
 std::enable if< is iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

template<typename Derived >
 void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >
 dyn\_mat< typename Derived::Scalar > qpp::load (const std::string &fname)
 Loads Eigen matrix from a binary file (internal format) in double precision.


### 8.18.1 Detailed Description

Input/output functions.

#### 8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

ullet template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$ 

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


### 8.19.1 Detailed Description

Measurement functions.

# 8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



### Classes

- class qpp::internal::IOManipRange
   InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

## **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


## 8.20.1 Detailed Description

Input/output manipulators.

# 8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



## Classes

• class qpp::internal::Singleton < T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

## **Namespaces**

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


## 8.21.1 Detailed Description

Singleton pattern via CRTP.

# 8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



#### Classes

• struct qpp::internal::Display\_Impl\_

### **Namespaces**

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

#### **Functions**

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx qpp::internal::multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- template<typename Derived >
   bool qpp::internal::check\_square\_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
   bool qpp::internal::check\_nonzero\_size (const T &x) noexcept
- template<typename T1, typename T2 >
   bool qpp::internal::check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check\_dims (const std::vector< idx > &dims)
- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check\_eq\_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool gpp::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check\_subsys\_match\_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
   bool qpp::internal::check\_qubit\_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check\_perm (const std::vector< idx > &perm)
   template<typename Derived1, typename Derived2 >
   dvp\_mat< typename Derived1::Seplar > constitutorsal::krap2 (const\_Eigen::MatrixPage < Derived1</li>
- dyn\_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1 , typename Derived2 >
   dyn\_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
   const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
   void qpp::internal::variadic\_vector\_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
   void qpp::internal::variadic\_vector\_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get\_num\_subsys (idx D, idx d)
- idx qpp::internal::get\_dim\_subsys (idx sz, idx N)
- template < typename T, typename std::enable\_if < std::numeric\_limits < T >::is\_iec559||is\_complex < T >::value >::type \* = nullptr > T qpp::internal::abs chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable\_if<!(std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value)>::type \* = nullptr> T qpp::internal::abs\_chop (const T &x, double QPP\_UNUSED\_chop=qpp::chop)

### 8.22.1 Detailed Description

Internal utility functions.

### 8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >
 std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::← Scalar > >::type qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


### 8.23.1 Detailed Description

Input/output interfacing with MATLAB.

# 8.24 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int >> qpp::convergents (double x, idx N)

Convergents.


### 8.24.1 Detailed Description

Number theory functions.

# 8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

### **Functions**

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

 $\textit{Applies the gate A to the part target of the multi-partite state vector or density \textit{matrix state}.}$ 

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
 ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >
 dyn\_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template < typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

### 8.25.1 Detailed Description

Quantum operation functions.

# 8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <map>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
```

```
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Macros**

• #define QPP\_UNUSED\_

### 8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

#### 8.26.2 Macro Definition Documentation


### 8.26.2.1 QPP\_UNUSED\_

#define QPP\_UNUSED\_

### 8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric\_limits < idx >::min(), idx b=std::numeric\_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived qpp::rand (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double a QPP\_UNUSED\_=0, double b QPP\_UNUSED\_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double mean QPP\_UNUSED\_=0, double sigma QPP\_UNUSED =1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


#### 8.27.1 Detailed Description

Randomness-related functions.

## 8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

qpp

Quantum++ main namespace.

### **Functions**

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Average.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$ 

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_← iterable< Container >::value >::type \*=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

double <a href="mailto:double-qpp::cor">double qpp::cor</a> (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if</a> is\_iterable</a> Container >::value >::type \*=nullptr)

Correlation.

## 8.28.1 Detailed Description


Statistics functions.

### 8.29 traits.h File Reference

Type traits.

8.29 traits.h File Reference 401

This graph shows which files directly or indirectly include this file:



### Classes

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is\_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().end()), decltyp

struct qpp::is\_matrix\_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is\_complex< T >

Checks whether the type is a complex type.

struct qpp::is\_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

### **Namespaces**

• qpp

Quantum++ main namespace.

# **Typedefs**

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


# 8.29.1 Detailed Description

Type traits.

# 8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



## **Namespaces**

qpp

Quantum++ main namespace.

## **Typedefs**

• using qpp::idx = std::size\_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex< double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$ 

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.30.1	Detaile	d De	scription
0.50.1	Detaile	u DC	SCHULIOH

Type aliases.

8.31 /Users/vlad/qpp/README.md File Reference

## Index

/Users/vlad/qpp/README.md, 403	anticomm
~Bit circuit	qpp, 31
qpp::Bit_circuit, 132	any
~Codes	qpp::Dynamic bitset, 161
qpp::Codes, 139	apply
~Dynamic_bitset	qpp, 31–33
qpp::Dynamic_bitset, 161	applyCTRL
~Gates	qpp, 34
qpp::Gates, 175	applyQFT
~IDisplay	qpp, 35
qpp::IDisplay, 190	applyTFQ
~IJSON	qpp, 35
qpp::IJSON, 192	avg
~Init	qpp, 36
qpp::Init, 194	۹۲۲, ۵۵
~NoiseBase	b00
qpp::NoiseBase< T >, 241	qpp::States, 342
~QCircuit	b01
qpp::QCircuit, 275	qpp::States, 343
~QEngine	b10
app::QEngine, 303	qpp::States, 343
~RandomDevices	b11
qpp::RandomDevices, 330	qpp::States, 343
~Singleton	bCNOT
qpp::internal::Singleton< T >, 334	qpp::Bit_circuit, 136
~States	begin
_	qpp::QCircuit, 277
qpp::States, 340 ∼Timer	bFRED_
qpp::Timer< T, CLOCK_T >, 350	qpp::Bit_circuit, 136
qpp ⊓mer < 1, 0L00K_1 >, 330	bigint
Α	qpp, 26
qpp::internal::IOManipEigen, 198	Bit_circuit
abs_chop	qpp::Bit_circuit, 131
qpp::internal, 120	bloch2rho
absm	
qpp, 29	qpp, 36 bNOT
abssq	— <u> </u>
qpp, 29, 30	qpp::Bit_circuit, 136 bra
add_circuit	
qpp::QCircuit, 275	qpp, 26 bSWAP
add_dit	_
	qpp::Bit_circuit, 136
qpp::QCircuit, 275 add_hash_	bTOF_
	qpp::Bit_circuit, 136
qpp::QCircuit, 276	btotal_
add_qudit	qpp::Bit_circuit, 136
qpp::QCircuit, 276	o rog
adjoint	C_reg_
qpp, 30	qpp::QCircuit::MeasureStep, 235
all	cbegin
qpp::Dynamic_bitset, 161	qpp::QCircuit, 277

cCTRL		classes/gates.h, 369
qpp::QCircuit, 277-279		classes/idisplay.h, 370
cCTRL_custom		classes/init.h, 371
qpp::QCircuit, 279		classes/noise.h, 372
cend		classes/random_devices.h, 373
qpp::QCircuit, 280		classes/reversible.h, 373
check_cvector		classes/states.h, 374
qpp::internal, 120		classes/timer.h, 375
check dims		cmat
qpp::internal, 120		qpp, <mark>27</mark>
check_dims_match_cvect		cmat_hash_tbl_
qpp::internal, 121		qpp::QCircuit, 297
check_dims_match_mat		CNOT
qpp::internal, 121		qpp::Bit_circuit, 132
check_dims_match_rvect		qpp::Gates, 183
qpp::internal, 121		CNOTba
check_eq_dims		qpp::Gates, 183
qpp::internal, 121		Codes
check_matching_sizes		qpp::Codes, 139
qpp::internal, 121		codeword
check_no_duplicates		
		qpp::Codes, 139
qpp::internal, 121		comm
check_nonzero_size		qpp, 38
qpp::internal, 122		complement
check_perm		qpp, 38
qpp::internal, 122		compperm
check_qubit_cvector		qpp, 39
qpp::internal, 122		compute_probs_
check_qubit_matrix		qpp::NoiseBase< T >, 241
qpp::internal, 122		compute_state_
check_qubit_rvector		qpp::NoiseBase< T >, 241
qpp::internal, 122		concurrence
check_qubit_vector		qpp, <mark>39</mark>
qpp::internal, 122		conjugate
check_rvector		qpp, <mark>39</mark>
qpp::internal, 123		const_iterator
check_square_mat		qpp::QCircuit, 271
qpp::internal, 123		constants.h, 376
check_subsys_match_dims		contfrac2x
qpp::internal, 123		qpp, 40
check_vector		convergents
qpp::internal, 123		qpp, 40, 41
choi2kraus		cor
qpp, 37		qpp, 41
choi2super		cosm
qpp, 37		qpp, 42
chop		count
qpp, 116		qpp::Dynamic_bitset, 161
chop_		count
qpp::internal::IOManipEigen, 198		qpp::Bit_circuit, 136
qpp::internal::IOManipPointer< PointerType		qpp::QCircuit, 297
201	>,	
-	_	COV
qpp::internal::IOManipRange< InputIterator	>,	qpp, 42
204		cplx
classes/circuits/circuits.h, 365		qpp, 27
classes/circuits/engines.h, 366		CTRL
classes/codes.h, 367		qpp::Gates, 176
classes/exception.h, 367		qpp::QCircuit, 280, 281

ctrl_	qpp::exception::Unknown, 358
qpp::QCircuit::GateStep, 187	qpp::exception::ZeroSize, 364
CTRL_custom	det
qpp::QCircuit, 282	qpp, 43
CUSTOM	difference_type
qpp::QCircuit, 272	qpp::QCircuit::iterator, 212
CUSTOM_cCTRL	dirsum
qpp::QCircuit, 272	qpp, 43–45
CUSTOM_CTRL	dirsum2
qpp::QCircuit, 272	qpp::internal, 123
CustomException	dirsumpow
qpp::exception::CustomException, 141	qpp, 45
cwise	disp
qpp, 43	qpp, 46, 47
CZ	display
qpp::Gates, 183	qpp::Dynamic_bitset, 162
	qpp::IDisplay, 190
d_	qpp::internal::IOManipEigen, 198
qpp::NoiseBase< T >, 245	<pre>qpp::internal::IOManipPointer&lt; PointerType &gt;,</pre>
qpp::QCircuit, 298	200
data	qpp::internal::IOManipRange< InputIterator >,
qpp::Dynamic_bitset, 161	204
depth_	qpp::QCircuit, 282
qpp::Bit_circuit, 137	qpp::QCircuit::iterator::value_type_, 361
description	qpp::QEngine, 303
qpp::exception::CustomException, 142	qpp::Timer< T, CLOCK_T >, 351
qpp::exception::DimsInvalid, 144	display_impl_
qpp::exception::DimsMismatchCvector, 146	qpp::internal::Display_Impl_, 155
qpp::exception::DimsMismatchMatrix, 148	dits_
qpp::exception::DimsMismatchRvector, 150	qpp::QEngine, 309
qpp::exception::DimsMismatchVector, 152	dmat
qpp::exception::DimsNotEqual, 154	qpp, 27
qpp::exception::Duplicates, 157	dyn_col_vect
qpp::exception::Exception, 172	qpp, 27
qpp::exception::InvalidIterator, 196	dyn mat
qpp::exception::MatrixMismatchSubsys, 218	qpp, 27
qpp::exception::MatrixNotCvector, 221	dyn_row_vect
qpp::exception::MatrixNotRvector, 223	qpp, 28
qpp::exception::MatrixNotSquare, 225	Dynamic_bitset
qpp::exception::MatrixNotSquareNorCvector, 227	qpp::Dynamic_bitset, 160
qpp::exception::MatrixNotSquareNorRvector, 229	4pp.12 / 1.6.1.1.5_51.651, 1.65
qpp::exception::MatrixNotSquareNorVector, 231	ee
qpp::exception::MatrixNotVector, 233	qpp, 116
qpp::exception::NoCodeword, 237	egcd
qpp::exception::NotBipartite, 248	qpp, 48
qpp::exception::NotImplemented, 250	eig
qpp::exception::NotQubitCvector, 252	qpp, 48
qpp::exception::NotQubitMatrix, 254	elem_
qpp::exception::NotQubitRvector, 256	qpp::QCircuit::iterator, 216
qpp::exception::NotQubitSubsys, 258	end
qpp::exception::NotQubitVector, 260	qpp::QCircuit, 283
qpp::exception::OutOfRange, 262	end_
qpp::exception::PermInvalid, 264	qpp::internal::IOManipPointer< PointerType >,
qpp::exception::PermMismatchDims, 266	201
qpp::exception::QuditAlreadyMeasured, 325	qpp::internal::IOManipRange< InputIterator >,
qpp::exception::SizeMismatch, 336	205
qpp::exception::SubsysMismatchDims, 348	qpp::Timer< T, CLOCK_T >, 352
qpp::exception::TypeMismatch, 354	entanglement
qpp::exception::UndefinedType, 356	qpp, 49

entanglement.h, 377	fill_Ks_
entropies.h, 379	qpp::QuditDepolarizingNoise, 328
entropy	fill_probs_
qpp, 50	qpp::QuditDepolarizingNoise, 328
evals	first_
qpp, <del>5</del> 1	qpp::internal::IOManipRange< InputIterator >,
evects	205
qpp, <del>5</del> 1	FIVE_QUBIT
Exception	qpp::Codes, 138
qpp::exception::DimsInvalid, 144	flip
qpp::exception::DimsMismatchCvector, 146	qpp::Dynamic_bitset, 162
qpp::exception::DimsMismatchMatrix, 148	FRED
qpp::exception::DimsMismatchRvector, 150	qpp::Bit_circuit, 132
qpp::exception::DimsMismatchVector, 152	qpp::Gates, 183
qpp::exception::DimsNotEqual, 154	functions.h, 380
qpp::exception::Duplicates, 157	funm
qpp::exception::Exception, 172	qpp, <del>5</del> 2
qpp::exception::InvalidIterator, 196	GATE
qpp::exception::MatrixMismatchSubsys, 219	
qpp::exception::MatrixNotCvector, 221	qpp::QCircuit, 274
qpp::exception::MatrixNotRvector, 223	gate
qpp::exception::MatrixNotSquare, 225	qpp::QCircuit, 283, 284
qpp::exception::MatrixNotSquareNorCvector, 227	gate_custom
qpp::exception::MatrixNotSquareNorRvector, 229	qpp::QCircuit, 285
qpp::exception::MatrixNotSquareNorVector, 231	gate_fan
qpp::exception::MatrixNotVector, 233	qpp::QCircuit, 285, 286
qpp::exception::NoCodeword, 237	gate_hash_
qpp::exception::NotBipartite, 248	qpp::QCircuit::GateStep, 187
qpp::exception::NotImplemented, 250	gate_type_
qpp::exception::NotQubitCvector, 252	qpp::QCircuit::GateStep, 188
qpp::exception::NotQubitMatrix, 254	Gates
qpp::exception::NotQubitRvector, 256	qpp::Gates, 175
qpp::exception::NotQubitSubsys, 258	gates_
qpp::exception::NotQubitVector, 260	qpp::QCircuit, 298
qpp::exception::OutOfRange, 262	gates_ip_ qpp::QCircuit::iterator::value_type_, 361
qpp::exception::PermInvalid, 264	
qpp::exception::PermMismatchDims, 266	GateStep qpp::QCircuit::GateStep, 187
qpp::exception::QuditAlreadyMeasured, 326	GateType
qpp::exception::SizeMismatch, 336	qpp::QCircuit, 272
qpp::exception::SubsysMismatchDims, 348	
qpp::exception::TypeMismatch, 354	gcd
qpp::exception::UndefinedType, 356	qpp, 53 gconcurrence
qpp::exception::Unknown, 358	qpp, 54
qpp::exception::ZeroSize, 364	generated_
execute	qpp::NoiseBase< T >, 245
qpp::QEngine, 304	
qpp::QNoisyEngine < NoiseModel >, 313, 314	get qpp::Dynamic_bitset, 163
expandout	get_circuit
qpp::Gates, 176–178	qpp::QEngine, 305
experimental/experimental.h, 380	get_cmat_hash_tbl_
expm	qpp::QCircuit, 286
qpp, 52	
factors	get_d qpp::NoiseBase< T >, 242
qpp, 52	qpp::QCircuit, 286
qpp, 32 FAN	get_dim_subsys
qpp::QCircuit, 272	qpp::internal, 123
Fd	get_dit
qpp::Gates, 178	qpp::QEngine, 305
4ppaa.oo,	4pp

get_dits	get_thread_local_instance
qpp::QEngine, 305	qpp::internal::Singleton< T >, 334
get_duration	GHZ
qpp::Timer $<$ T, CLOCK_T $>$ , 351	qpp::States, 343
get_gate_count	grams
qpp::Bit_circuit, 133	qpp, 54, 55
qpp::QCircuit, 287	
get_gate_depth	H
qpp::Bit_circuit, 133	qpp::Gates, 184
qpp::QCircuit, 287	hash_combine
get_gates_	qpp::internal, 124
qpp::QCircuit, 288	hash_eigen
get_instance	qpp, 55
qpp::internal::Singleton< T >, 334	heig
get_Ks	qpp, 56
qpp::NoiseBase< T >, 242	hevals
get_last_idx	qpp, 56
qpp::NoiseBase< T >, 242	hevects
get_last_K	qpp, 57
qpp::NoiseBase< T >, 243	;
get_last_p	i
qpp::NoiseBase< T >, 243	qpp::NoiseBase< T >, 245
get_measured	ld
qpp::QCircuit, 288	qpp::Gates, 179
qpp::QEngine, 305, 306	ld2
get_measurement_count	qpp::Gates, 184
qpp::QCircuit, 288, 289	idx
get measurements	qpp, 28
qpp::QCircuit, 289	index_
get_name	qpp::Dynamic_bitset, 163
qpp::Gates, 179	infty
qpp::QCircuit, 289	qpp, 116
get nc	Init
qpp::QCircuit, 289	qpp::Init, 194
get_noise_results	input_output.h, 385
qpp::QNoisyEngine < NoiseModel >, 314	instruments.h, 386
get_non_measured	internal/classes/iomanip.h, 388
qpp::QCircuit, 290	internal/classes/singleton.h, 389
qpp::QEngine, 306	internal/util.h, 389
get_nop_count	internal::Singleton< const Codes >
qpp::QCircuit, 290	qpp::Codes, 139
get_nq	internal::Singleton < const Gates >
qpp::QCircuit, 290	qpp::Gates, 183
get_num_subsys	internal::Singleton< const Init >
qpp::internal, 124	qpp::Init, 194
	internal::Singleton < const States >
get_prng	qpp::States, 342
qpp::RandomDevices, 331	internal::Singleton< RandomDevices >
get_probs	qpp::RandomDevices, 332
qpp::NoiseBase< T >, 243	inverse
qpp::QEngine, 306	qpp, 57
get_psi	invperm
qpp::QEngine, 306	qpp, 58
get_relative_pos_	IOManipEigen
qpp::QEngine, 307	qpp::internal::IOManipEigen, 198
get_stats	IOManipPointer
qpp::QEngine, 307	qpp::internal::IOManipPointer< PointerType >
get_step_count	200
qpp::QCircuit, 290	IOManipRange

	qpp::internal::IOManipRange< InputIterator >	
	203, 204	qpp, 74, 75
ip	qpp, 58, 59	MEASURE_V qpp::QCircuit, 274
ip_	<b>ч</b> рр, 50, 55	MEASURE V MANY
·P_	qpp::QCircuit::iterator::value_type_, 362	qpp::QCircuit, 274
ispri		MEASURE_Z
	qpp, 59	qpp::QCircuit, 274
itera	tor	measured_
	qpp::QCircuit::iterator, 213	qpp::QCircuit, 298
itera	tor_category	MEASUREMENT
	qpp::QCircuit::iterator, 212	qpp::QCircuit, 274
jn		measurement_count_ qpp::QCircuit, 298
J''	qpp::States, 340	measurement_type_
	4pp.::e.a.co, 0 :0	qpp::QCircuit::MeasureStep, 235
ket		measurements
	qpp, 28	qpp::QCircuit, 298
krau	s2choi	measurements_ip_
	qpp, 59	<pre>qpp::QCircuit::iterator::value_type_, 362</pre>
krau	s2super	MeasureStep
	qpp, 60	qpp::QCircuit::MeasureStep, 234, 235
kron		MeasureType
leron	qpp, 60, 62, 63	qpp::QCircuit, 272
kron	qpp::internal, 124	measureV
kron		qpp::QCircuit, 291 measureZ
141011	qpp, 63	qpp::QCircuit, 292
Ks_	albe, and	mes
_		11100
	qpp::NoiseBase< T >, 245	gpp::States, 340
	qpp::NoiseBase< T >, 245	qpp::States, 340 minus
last_	-	
last_	- qpp::internal::IOManipRange< InputIterator >	minus
	-	minus qpp::States, 341 >, mket qpp, 75, 76
last_	qpp::internal::IOManipRange< InputIterator > 205	minus qpp::States, 341 >, mket qpp, 75, 76 modinv
lcm	qpp::internal::IOManipRange< InputIterator > 205 qpp, 64	minus qpp::States, 341 >, mket qpp, 75, 76 modinv qpp, 76
	qpp::internal::IOManipRange< InputIterator > 205 qpp, 64	minus qpp::States, 341 >, mket qpp, 75, 76 modinv qpp, 76 MODMUL
lcm	qpp::internal::IOManipRange< InputIterator > 205  qpp, 64  qpp, 65	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180
lcm load	qpp::internal::IOManipRange< InputIterator > 205 qpp, 64	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180 modmul
lcm load	qpp::internal::IOManipRange< InputIterator > 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180 modmul qpp, 77
lcm load	qpp::internal::IOManipRange< InputIterator > 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66	minus
lcm load	qpp::internal::IOManipRange< InputIterator > 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180 modmul qpp, 77
lcm load	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180 modmul qpp, 77 modpow qpp, 77
lcm load load logd	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67	minus qpp::States, 341  >, mket qpp, 75, 76 modinv qpp, 76 MODMUL qpp::Gates, 180 modmul qpp, 77 modpow qpp, 77 mprj
lcm load load logd	qpp::internal::IOManipRange< InputIterator > 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 1 qpp, 67 egativity	minus
lcm load load logd	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67	minus
load load logd logn	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67 egativity qpp, 67, 68	minus
load load logd logn	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 qpp, 67 egativity qpp, 67, 68  ginalX	minus
load load logd logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68	minus
load load logd logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68 ginalY	minus
load load logd logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68	minus
load load logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 n qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68 ginalY qpp, 68	minus
load load logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 in qpp, 67 egativity qpp, 67, 68 ginalX qpp, 68 ginalY qpp, 68 ILAB/matlab.h, 391	minus
load load logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68 ginalY qpp, 68 ;LAB/matlab.h, 391 s_hash_ qpp::QCircuit::MeasureStep, 235 n	minus
load load logn logn mare	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68 ginalY qpp, 68 rLAB/matlab.h, 391 s_hash_ qpp::QCircuit::MeasureStep, 235	minus
load load logd logn mare MAT mats	qpp::internal::IOManipRange< InputIterator 205  qpp, 64  qpp, 65 qpp::RandomDevices, 331  MATLAB qpp, 65, 66 et qpp, 66 qpp, 67 egativity qpp, 67, 68  ginalX qpp, 68 ginalY qpp, 68 ;LAB/matlab.h, 391 s_hash_ qpp::QCircuit::MeasureStep, 235 n	minus

app:internal::IOManipPointer         > operator-+ app::Qirouti::iterator, 214 operator-+ app::Qirouti::iterator, 214 operator app::Qirouti::GateStep, 168 app::QCirouti::GateStep, 188 app::QCirouti::MeasureStep, 235 nc_ app::QCirouti::MeasureStep, 236 npp::QCirouti::MeasureStep, 235 npp::QCirouti::MeasureStep, 236 npp::QCirouti::MeasureStep, 236 npp::QCirouti::MeasureStep, 236 npp::QCirouti::MeasureStep, 236 npp::QCirouti::MeasureStep, 2	N_	qpp, 79 qpp::internal, 125		qpp::internal::EqualEigen, 169 qpp::internal::HashEigen, 189 qpp::NoiseBase< T >, 243, 244	
n_	IN_		>,	operator++	
app::Dynamic_bitset, 164  app::Qcircuit, 298     app::Qcircuit, 298     app::Qcircuit, 299     app::Qcircuit, 290     app::Qcircuit, 290     app::Qcircuit, 290     app::Qcircuit, 272, 274     app::Qcircuit, 272, 274     app::Qcircuit, 272, 274     app::Qcircuit, 272     app::Qcircuit, 272     app::Qcircuit, 274     app::Qcircuit, 292     app::Qcircuit, 292     app::Qcircuit, 292     app::Qcircuit, 292     app::Qcircuit, 299     app::Qcircuit:iterator, 214     app::Qcircuit:iterator, 213     app::Qcircuit:iterator, 213     app::Qcircuit:iterator, 214     app::Qcircuit:iterator, 215     app::Qcircuit:iterator, 216     app::Qcircuit:iterator, 210     app::Qcircuit:iterator, 212     app::Qcircuit:itera	n	201			
app::Ocircuit; 298   app::Ocircuit: MeasureStep, 188   app::Ocircuit: MeasureStep, 235   201   app::internal::IOManipPointer<   PointerType   >, 201   app::Internal::IOManipPointer<   PointerType   >, 201   app::Internal::IOManipPointer<   PointerType   >, 201   app::Internal::IOManipPointer<   PointerType   >, 204   app::Internal::IOManipPointer   >, 394   app::Ocircuit::Iterator, 214   app::Ocircuit::Iterator, 214   app::Ocircuit::Iterator, 215   app::Ocircuit::Iterator, 216   app::Ocircuit::Iterator, 216   app::Ocircuit::Iterator, 217   app::Ocircuit::Iterator, 218   app::Ocircuit::Iterator, 219   app::Ocircuit::Iterator, 210   app::Ocircuit::Iterator, 210   app::Ocircuit::Iterator, 211   app::Ocircuit::Iterator, 212   app::Ocircuit::Iterator, 214   app::Ocir		qpp::Dynamic_bitset, 168		•	
qpp::OCircuit::MeasureStep, 188         201           qpp::OCircuit:MeasureStep, 235         qpp:internal::IOManipRange < InputIterator >, 204           nc qpp::OCircuit, 299         qpp:internal::Singleton < T >, 334           qpp::OCircuit; 299         qpp:internal::Singleton < T >, 334           qpp::OCoicoit; 214         qpp::OCircuit:iterator; 214           qpp::ONoisyEngine < NoiseModel >, 314         qpp::Ocircuit:iterator; 215           noise qpp::NoiseBase < T >, 240         qpp::Dynamic_bitset, 165           NONE         qpp::MoliseBase < T >, 240           NONE         qpp::MoliseBase < T >, 240           NONE         qpp::Iterals, 126           qpp::Dynamic_bitset, 163         qpp::Iterals, 126           NOP         qpp::OCircuit, 272, 274           none         qpp::Iterals, 127           qpp::QCircuit, 292         qpp::Iterals, 127           norm         qpp::GLicricuit, 134           normalize         qpp::States, 343           qpp::Dynamic_bitset, 164         ppi:           qpp::Dynamic_bitset, 164         qpp::States, 344           pi         qpp::States, 341           popr:states, 341         pointernal::Singleton < T >, 334           qpp::Dynamic_bitset, 164         qpp::States, 344           qpp::Dynamic_bitset, 164         qpp::Dy	nam	e_		operator=	
qpp::QCircuit; MeasureStep, 235 nc_ qpp::QCircuit, 299 negativity qpp, 80 NINE_QUBIT_SHOR qpp::Codes, 138 noise qpp::ONoisyEngine < NoiseModel >, 314 noise_Type qpp::NoiseBase < T >, 240 NoiseBase qpp::NoiseBase < T >, 240 NoiseBase qpp::Corcuit; 272, 274 none qpp::Dynamic_bitset, 163 NOP qpp::Circuit, 274 nop qpp::Ocircuit, 274 nop qpp::Circuit, 274 nop qpp::Circuit, 274 nop qpp::Circuit, 292 norm qpp, 81 NOT qpp::States, 343 pb10 qpp::States, 344 pg::States, 344 pg::States, 344 pg::States, 344 pp::Circuit, 299 number_theory.h, 392 offset qpp::Circuit, 299 number_theory.h, 392 offset qpp::Circuit, 299 number_theory.h, 394 operator * qpp::Circuit:tierator, 214 operatorlae qpp::Colrcuit:tierator, 213 operatorlae qpp::Colrcuit:tierator, 214 qpp::Colrcuitititerator, 214 qpp::Colrcuitititerator, 214 qpp::Colrcuitititerator, 214 qpp::Colrcuitititititititititierator, 214 qpp::Colrcuitititierator, 214 qpp::Colrcuitititierator, 214 qpp::Colrcuititititerator, 214 qpp::Colrcuititititierator, 214 qpp::Colrcuitititierator, 215 qpp::Colrcuitititierator, 214 qpp::Colrcuititierator, 214 qpp::Colrcuititierator, 214 qpp::Colrcuititierator, 214 qpp::Colrcuititierator, 214 qpp::Colrcuititierator, 214 qpp::Colrcuititierator, 214 qpp::Co					>,
nc_ qpp::OCircuit, 299 negativity					
negativity qpp. 80 NINE_OUBIT_SHOR qpp::Cordes, 138 noise qpp::ONoisyEngine < NoiseModel >, 314 noise_results qpp::ONoisyEngine < NoiseModel >, 314 noise_results qpp::NoiseBase < T >, 240 NOiseBase qpp::NoiseBase < T >, 240 NONE qpp::OCircuit, 272, 274 none qpp::Oricuit, 272, 274 nop qpp::Ocircuit, 274 nop qpp::Ocircuit, 274 nop qpp::Ocircuit, 292 norm qpp. 81 normalize qpp::Dynamic_bitset, 164 norega qpp::Ocircuit, 134 nq qpp::Ocircuit, 134 nq qpp::Ocircuit, 299 number_theory.h, 392 offset_ qpp::States, 341 operations.h, 394 operatort = qpp::Ocircuit:iterator, 214 qpp::Ocircuit;iterator, 215 operator = qpp::Ocircuit, 214 qpp::Ocircuit, 214 qpp::Ocircuit, 225 operator = qpp::Ocircuit, 226 operator = qpp::Ocircuit, 226 operator = qpp::Ocircuit, 227 qpp::Iterats, 126 operator = qpp::Ocircuit, 227 qpp::Iterats, 126 operator = qpp::States, 344 pb11 qpp::States, 344 pb11 qpp::States, 344 ppi:Ocircuit, 229 qpp::States, 344 ppi:Ocircuit; 229 qpp::States, 344 ppi:Ocircuit:iterator, 212 powm qpp:States, 341 operators qpp::Ocircuit:iterator, 213 operator = qpp::Ocircuit:iterator, 214 qpp::Ocircuit:iterator, 212 qpp::Ocircuit:iterator, 212 qpp::Ocircuit:iterator, 213 qpp::Ocircuit:iterator, 214 qpp::Ocircuit:iterator, 214 qpp::Ocircuit:iterator, 214	nc_			204	>,
qpp; 80 NINE_QUBIT_SHOR qpp::Codes, 138 noise_ qpp::Colories; 138 noise_ qpp::Colories; 218 qpp::Co	noar				
NINE_QUBIT_SHOR         qpp::QEngine, 307           qpp::Codes, 138         operator==           noise_         qpp::Dynamic_bitset, 165           qpp::DNoisyEngine         qpp::Dynamic_bitset, 165           qpp::DNoisyEngine         qpp::Direcult::iterator, 215           operator**_bra         qpp::Iterals, 126           operator**_bra         qpp::Iterals, 126           operator**_if         qpp::Iterals, 127           operator**_if         qpp::Iterals, 127           operator**_operator**_if         qpp::Iterals, 126           operator**_operator**_if         qpp::Iterals, 126 <td>nege</td> <td></td> <td></td> <td></td> <td></td>	nege				
operator==  opp::CNoisyEngine< NoiseModel >, 314  noise_results_	NINI				
noise_         qpp::Dynamic_bitset, 165           qpp::QNoisyEngine < NoiseModel >, 314         qpp::Dnamic_bitset, 165           noise_results_         qpp::NoiseBase < T >, 240           NoiseBase         T >, 240           NoiseBase         T >, 240           NoiseBase         T >, 240           NONE         qpp::Iterals, 126           qpp::QCircuit, 272, 274         qpp::Iterals, 126, 127           none         qpp::Iterals, 127           qpp::QCircuit, 274         ppc::Iterals, 127           nop         qpp::Iterals, 127           ppp::QCircuit, 292         pp::Iterals, 127           norm         qpp::Iterals, 127           ppp::QCircuit, 292         pp::Iterals, 127           norm         qpp::Iterals, 127           ppp::QCircuit, 292         ppp::Iterals, 127           norm         qpp::Iterals, 127           ppp::QCircuit, 292         ppp::Iterals, 127           norm         qpp::Iterals, 126           qpp::States, 341         qpp::States, 343           ppi:QCircuit, 292         pp::States, 344           ppi:Qpp::States, 344         ppi:Qpp::States, 344           ppi:Qpp::Qpp::Qpp::Qpp::Qpp::Qpp::Qpp::					
opp::QNoisyEngine         NoiseModel >, 314         opp::QCircuit::iterator, 215           noise_results         operator***_bra         operator***_bra           opp::NoiseBase         T >, 240         opp::Iterals, 126           NoiseBase         opp::NoiseBase         T >, 240           NoiseBase         operator***_if         opp::Iterals, 126           opp::NoiseBase         T >, 240         operator***_let           opp::QCircuit, 272, 274         operator***_let           opp::QCircuit, 272, 274         operator***_let           opp::QCircuit, 274         operator***_let           opp::QCircuit, 274         operator***_let           opp::QCircuit, 274         pp::Qp::Iterals, 127           nop         opp::QCircuit, 292         pp::Iterals, 127           nor         opp::QCircuit, 292         pp::Iterals, 127           nor         opp::QCircuit, 292         pp::Donamic_IoManipPointer         PointerType >,           opp::States, 343         pb01         opp::States, 343           normalize         opp::States, 344         opp::States, 344           opp::States, 344         ppi:         opp::States, 344           offset_         pi         opp::States, 344           one         opp::States, 344         opp::States, 344	nois			•	
app::QNoisyEngine < NoiseModel >, 314         app::Iterals, 126           noise_type         operator""_i           app::NoiseBase < T >, 240         app::Iterals, 126           NoiseBase         operator""if           app::NoiseBase < T >, 240         app::Iterals, 126, 127           NONE         operator""-ket           app::QCircuit, 272, 274         app::Iterals, 127           none         operator""-prj           app::QCircuit, 274         pcp::Iterals, 127           nop         app::Iterals, 127           nop         app::Iterals, 127           norm         app::Qcircuit, 292           norm         app::Gircuit, 292           norm         app::States, 343           app::Blt_circuit, 134         app::States, 343           norm         app::States, 344           app::Blt_circuit, 134         app::States, 344           nq         pfi:Iterals, 126, 127           norm         app::States, 344           pb::Dynamic_bitset, 164         app::States, 344           pp::Dynamic_bitset, 164         app::States, 344           pp::Dynamic_bitset, 164         app::States, 341           one         app::States, 341           operator**         app::States, 341           oper		qpp::QNoisyEngine < NoiseModel >, 314			
noise_type         operator""_i           qpp::NoiseBase < T >, 240         operator"": if           qpp::NoiseBase < T >, 240         operator"": ket           qpp::QCircuit, 272, 274         operator""-yet           qpp::Dynamic_bitset, 163         operator""-prj           nop         qpp::Iterals, 127           NOP         pp::Iterals, 127           qpp::QCircuit, 274         P_           nop         qpp::Internal::IOManipPointer         PointerType >,           qpp::QCircuit, 292         201           norm         pb01         qpp::States, 343           normalize         pb01         qpp::States, 343           normalize         pb10         qpp::States, 344           normalize         pb11         qpp::States, 344           normalize         pb11         qpp::States, 344           normalize         pp::Dynamic_bitset, 164         pp::States, 344           normalize         pi         qpp::States, 344           normalize         p	nois	e_results_		operator""_bra	
qpp::NoiseBase         T >, 240         qpp::literals, 126           NoiseBase         operator" if         qpp::literals, 126, 127           NONE         operator" ket         qpp::literals, 127           none         operator" prj         qpp::literals, 127           NOP         qpp::Dynamic_bitset, 163         qpp::literals, 127           NOP         qpp::Qcircuit, 274         P_           nop         qpp::Internal::IOManipPointer         PointerType >,           qpp::Qcircuit, 292         201           norm         qpp::States, 343           normalize         pb01         qpp::States, 343           qpp. 81         qpp::States, 343           NOT         pb10         qpp::States, 344           qpp::Bit_circuit, 134         qpp::States, 344           nq         qpp::States, 344           pGHZ         qpp::States, 344           qpp::Dynamic_bitset, 164         ppp::States, 341           omega         plus           qpp::States, 341         pointer           operator*         qpp::Qcircuit::iterator, 212           operator*         qpp. 82           pp::Dynamic_bitset, 164         pp;           operator*         qpp. 82           pp::Dynamic_bitset, 164 </td <td></td> <td>qpp::QNoisyEngine &lt; NoiseModel &gt;, 314</td> <td></td> <td>qpp::literals, 126</td> <td></td>		qpp::QNoisyEngine < NoiseModel >, 314		qpp::literals, 126	
NoiseBase         operator""_if         qpp::NoiseBase < T >, 240         operator""_if         qpp::Ilterals, 126, 127           NONE         operator""_ket         qpp::Ilterals, 127           none         operator""_prj         qpp::Ilterals, 127           NOP         qpp::Ilterals, 127           NOP         qpp::Internal::IOManipPointer         PointerType         >,           qpp::OCircuit, 274         p-         qpp::Internal::IOManipPointer         PointerType         >,           norm         qpp. 81         qpp::States, 343           normalize         qpp.         pb00         qpp::States, 344           qpp::Bit_circuit, 134         qpp::States, 344         pb10         qpp::States, 344           nd         qpp::States, 344         pp::States, 344         pp::States, 344           nd         qpp::Dynamic_bitset, 164         qpp. 116         pp::States, 341           one         qpp::States, 341         qpp::States, 341         qpp::Cyramic_bitset, 394           operator*         qpp::Qcircuit::iterator, 213         powm           operatorship; Dynamic_bitset, 164         pp;         pp::Qpp::Qnamic_bitset, 164         pp;           operatorship; Dynamic_bitset, 164         pp::Qnamic_bitset, 164         pp::Qnamic_bitset, 164         pp::Qnamic_bitset, 164	nois	e_type		operator""_i	
qpp::NoiseBase       T >, 240       qpp::literals, 126, 127         NONE       operator""_ket       qpp::literals, 127         none       operator""_prj       qpp::literals, 127         NOP       qpp::Dynamio_bitset, 163       qpp::literals, 127         NOP       qpp::Internal::IOManipPointer       PointerType       >,         qpp::QCircuit, 274       P_       qpp::Internal::IOManipPointer       PointerType       >,         qpp::QCircuit, 292       pb00       qpp::States, 343         norm       qpp::States, 343       pb01       qpp::States, 344         NOT       pb10       qpp::States, 344         qpp::QCircuit, 134       pb11       qpp::States, 344         nqp::QCircuit, 299       qpp::States, 344         number_theory.h, 392       pGHZ       qpp::States, 344         offset_qpp::Dynamic_bitset, 164       pi       qpp::States, 341         one       qpp::States, 341       qpp::QCircuit::iterator, 212         operator *       qpp::QCircuit::iterator, 213       prj         operator !=       qpp::Dynamic_bitset, 164       prng_qpp::Dynamic_bitset, 164         qpp::Dynamic_bitset, 164       prng_qpp::Dynamic_bitset, 164       prng_qpp::Dynamic_bitset, 164          qpp::Dynamic_bitset, 164       prng_qpp::Dyna		qpp::NoiseBase< T >, 240			
NONE         operator****_ket         qpp::lterals, 127           none         operator****_prj         qpp::lterals, 127           NOP         qpp::QCircuit, 274         p_           nop         qpp::Internal::IOManipPointer         PointerType         >,           qpp::QCircuit, 292         201           norm         pb00         qpp::States, 343           normalize         qpp::States, 343           qpp, 81         qpp::States, 343           NOT         qpp::States, 344           qpp::Blt_circuit, 134         qpp::States, 344           nqp         qpp::States, 344           pt1         qpp::States, 344           pGHZ         qpp::States, 344           qpp::Dynamic_bitset, 164         qpp, 116           one         qpp::States, 341           one         qpp::States, 341           operator *         qpp::QCircuit::iterator, 212           operator s         qpp, 82           qpp::Dynamic_bitset, 164         prg           opp::Dynamic_bitset, 164 <td< td=""><td>Nois</td><td></td><td></td><td>•</td><td></td></td<>	Nois			•	
qpp::QCircuit, 272, 274         qpp:ilterals, 127           none         operator""_prj           qpp::Dynamic_bitset, 163         qpp:ilterals, 127           NOP         qpp:ilterals, 127           app::QCircuit, 274         P_           nop         qpp:internal::IOManipPointer         PointerType         >,           app::QCircuit, 292         201         pointerType         >,           norm         qpp::States, 343         pointer         pointerType         >,           app::Bit_circuit, 134         qpp::States, 343         pointer         qpp::States, 341         powm         qpp::Qcircuit::iterator, 212         powm         qpp::Qcircuit::iterator, 212         powm         qpp, 82         prj         qpp, 82         prj         qpp, 82         prig         qpp;:Qalicuit::iterator, 214         qpp::RandomDevices, 332         qpp::RandomDevices, 332         qpp::RandomDevices, 332					
none         operator***_orj           qpp::Dynamic_bitset, 163         qpp::lterals, 127           NOP         qpp::QCircuit, 274           nop         qpp::Internal::IOManipPointer         PointerType         >,           qpp::QCircuit, 292         201         pb00         qpp::States, 343         pb01         qpp::States, 343         pb01         qpp::States, 343         pb01         qpp::States, 344         pb10         qpp::States, 344         pb11         qpp::States, 344         pb11         qpp::States, 344         pb11         qpp::States, 344         pb11         qpp::States, 344         pb12         qpp::States, 344         pb11         qpp::States, 344         pb12         qpp::States, 344         pp1         qpp::States, 344         pp2         qpp::States, 344         pp2         qpp::States, 341         qpp::States, 341         qpp::States, 341         qpp::States, 341         pp2         qpp::Qcircuit::iterator, 212         ppowm         qpp::Qcircuit::iterator, 212         ppwm         qpp. 82         pp3         qpp. 82         pp3         qpp::Qcircuit::iterator, 214         qpp::Qcircuit::iterator, 214         qpp::RandomDevices, 332	NON				
qpp::Dynamic_bitset, 163       qpp::Iterals, 127         NOP       qpp::QCircuit, 274         nop       qpp::Internal::IOManipPointer       PointerType >,         qpp::QCircuit, 292       201         norm       pb00       qpp::States, 343         qpp, 81       qpp::States, 343         NOT       pb10       qpp::States, 344         qpp::Bit_circuit, 134       qpp::States, 344         nq_       qpp::States, 344         number_theory.h, 392       pGHZ         qpp::Dynamic_bitset, 164       qpp         omega       plus         qpp, 81       qpp::States, 341         one       qpp::States, 341         operations.h, 394       powm         operator *       qpp, 82         qpp::QCircuit::iterator, 213       prj         opperator!=       qpp, 82         qpp::Dynamic_bitset, 164       prng_         qpp::QCircuit::iterator, 214       qpp::RandomDevices, 332					
NOP       qpp::QCircuit, 274       p_ qpp::internal::IOManipPointer       PointerType >, 201         norm       pb00       qpp::States, 343         qpp, 81       qpp::States, 343         normalize       qpp::States, 343         qpp, 81       qpp::States, 343         NOT       qpp::States, 344         qpp::Bit_circuit, 134       qpp::States, 344         nq_       qpp::States, 344         number_theory.h, 392       pGHZ         qpp::States, 344       pi         qpp::Dynamic_bitset, 164       qpp, 116         omega       qpp;:States, 341         one       qpp::States, 341         one       qpp::Qcircuit::iterator, 212         operator *       qpp, 82         qpp::Qcircuit::iterator, 213       pri         operator!=       qpp, 82         qpp::Qcircuit::iterator, 214       qpp::RandomDevices, 332	none				
app::QCircuit, 274	NOE			qppiiterais, 127	
nop         qpp::internal::IOManipPointer         PointerType         >,           qpp::QCircuit, 292         201         pb00         qpp::States, 343         pb01         qpp::States, 343         pb01         qpp::States, 343         pb01         qpp::States, 343         pb01         qpp::States, 344         pb10         qpp::States, 344         pb11         qpp::States, 344         pb11         qpp::States, 344         pb11         qpp::States, 344         pp::States, 344         pp::Dp::States, 344         pp::States, 341         qpp::States, 341         pp::CCircuit::iterator, 212         pp::CCircuit::iterator, 212         pp::CCircuit::iterator, 212         pp::CCircuit::iterator, 213         pp::CCircuit::iterator, 213         pp::CCircuit::iterator, 213         pp::CCircuit::iterator, 214         pp::CCircuit::iterator, 214         qpp::RandomDevices, 332					
app::QCircuit, 292       201         norm       pb00         app, 81       app::States, 343         normalize       pb01         app, 81       app::States, 343         NOT       app::States, 344         nq       app::States, 344         nq       app::States, 344         number_theory.h, 392       pGHZ         app::Dynamic_bitset, 164       app::States, 344         omega       plus         app, 81       app::States, 341         one       app::States, 341         operations.h, 394       powm         operations.h, 394       powm         operator!=       app, 82         app::Dynamic_bitset, 164       prig         app::Dynamic_bitset, 164       prig         app::Dynamic_bitset, 164       app::RandomDevices, 332	INOI			p_	
norm       pb000         qpp, 81       qpp::States, 343         normalize       pb01         qpp, 81       qpp::States, 343         NOT       pb10         qpp::Bit_circuit, 134       qpp::States, 344         nq_       qpp::States, 344         number_theory.h, 392       pGHZ         qpp::States, 344       pi         qpp::Dynamic_bitset, 164       qpp::States, 344         omega       plus         qpp, 81       qpp::States, 341         one       qpp::States, 341         operations.h, 394       powm         operations.h, 394       powm         operator!=       qpp, 82         qpp::QCircuit::iterator, 213       prj         operator!=       qpp, 82         qpp::QCircuit::iterator, 214       qpp::RandomDevices, 332					>,
normalize		qpp::QCircuit, 274		qpp::internal::IOManipPointer< PointerType	>,
app, 81       app::States, 343         NOT       pb10         app::Bit_circuit, 134       app::States, 344         nq_       pb11         app::QCircuit, 299       app::States, 344         number_theory.h, 392       pGHZ         app::States, 344       pi         app::Dynamic_bitset, 164       app::States, 344         omega       plus         app, 81       app::States, 341         one       pointer         app::States, 341       app::QCircuit::iterator, 212         operations.h, 394       powm         operator *       app, 82         app::QCircuit::iterator, 213       prj         operator!=       app, 82         app::Dynamic_bitset, 164       prng_         app::RandomDevices, 332	nop	qpp::QCircuit, 274 qpp::QCircuit, 292		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
NOT	nop	qpp::QCircuit, 274 qpp::QCircuit, 292		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
qpp::Bit_circuit, 134       qpp::States, 344         nq	nop	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
pb11	nop norn norn	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  alize qpp, 81		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
qpp::QCircuit, 299 number_theory.h, 392  offset	nop norn norn	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
number_theory.h, 392  offset	nop norn norn NOT	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81		<pre>qpp::internal::IOManipPointer&lt; PointerType</pre>	>,
offset pi	nop norn norn NOT	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11	>,
qpp::Dynamic_bitset, 164qpp, 116omegaplusqpp, 81qpp::States, 341onepointerqpp::States, 341qpp::QCircuit::iterator, 212operations.h, 394powmoperator *qpp, 82qpp::QCircuit::iterator, 213prjoperator!=qpp, 82qpp::Dynamic_bitset, 164prng_qpp::QCircuit::iterator, 214qpp::RandomDevices, 332	nop norn norn NOT nq_	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344	>,
omega       plus         qpp, 81       qpp::States, 341         one       pointer         qpp::QCircuit::iterator, 212         operations.h, 394       powm         operator *       qpp, 82         qpp::QCircuit::iterator, 213       prj         operator!=       qpp, 82         qpp::Dynamic_bitset, 164       prng_         qpp::QCircuit::iterator, 214       qpp::RandomDevices, 332	nop norn norn NOT nq_	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ	>,
qpp, 81       qpp::States, 341         one       pointer         qpp::States, 341       qpp::QCircuit::iterator, 212         operations.h, 394       powm         operator *       qpp, 82         qpp::QCircuit::iterator, 213       prj         operator!=       qpp, 82         qpp::Dynamic_bitset, 164       prng_         qpp::QCircuit::iterator, 214       qpp::RandomDevices, 332	nop norn norn NOT nq_ num	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344	>,
one pointer qpp::States, 341 qpp::QCircuit::iterator, 212 operations.h, 394 powm operator * qpp, 82 qpp::QCircuit::iterator, 213 prj operator!= qpp, 82 qpp::Dynamic_bitset, 164 qpp::QCircuit::iterator, 214 qpp::RandomDevices, 332	nop norn norn NOT nq_ num	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi	>,
<pre>qpp::States, 341</pre>	nop norn norn NOT nq_ num offse	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116	>,
operations.h, 394 powm operator * qpp, 82 qpp::QCircuit::iterator, 213 prj operator!= qpp, 82 qpp::Dynamic_bitset, 164 prng_ qpp::QCircuit::iterator, 214 qpp::RandomDevices, 332	nop norn norn NOT nq_ num offse	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus	>,
operator * qpp, 82 qpp::QCircuit::iterator, 213 prj operator!= qpp, 82 qpp::Dynamic_bitset, 164 prng_ qpp::QCircuit::iterator, 214 qpp::RandomDevices, 332	nop norn norn NOT nq_ num offse ome	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pbHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer	>,
<pre>qpp::QCircuit::iterator, 213</pre>	nop norn norn NOT nq_ num offse ome	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341		qpp::internal::IOManipPointer< PointerType 201  pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pbHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212	>,
operator!= qpp, 82 qpp::Dynamic_bitset, 164 prng_ qpp::QCircuit::iterator, 214 qpp::RandomDevices, 332	nop norn norn NOT nq_ num offse ome oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394		qpp::internal::IOManipPointer< PointerType 201  pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm	>,
qpp::Dynamic_bitset, 164prng_qpp::QCircuit::iterator, 214qpp::RandomDevices, 332	nop norn norn NOT nq_ num offse ome oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299  ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164  ga qpp, 81  qpp::States, 341  ations.h, 394  ator *		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pbHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82	>,
qpp::QCircuit::iterator, 214 qpp::RandomDevices, 332	nop norn norn norn norn norn norn norn offse ome oper oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pbHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prj	>,
" '	nop norn norn norn norn norn norn norn offse ome oper oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213 ator!=		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 343 pb10 qpp::States, 344 pb11 qpp::States, 344 pbHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prj qpp, 82	>,
	nop norn norn norn norn norn norn norn offse ome oper oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213 ator!= qpp::Dynamic_bitset, 164		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 344 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prij qpp, 82 prng_	>,
·	nop norn norn NOT nq_ num offse ome oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213 ator!= qpp::Dynamic_bitset, 164 qpp::QCircuit::iterator, 214		qpp::internal::IOManipPointer< PointerType 201  pb00 qpp::States, 343 pb01 qpp::States, 344 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prig qpp, 82 prig qpp::RandomDevices, 332	>,
qpp::QCircuit, 296, 297 probs_	nop norn norn NOT nq_ num offse ome oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213 ator!= qpp::Dynamic_bitset, 164 qpp::QCircuit::iterator, 214 ator<<<		qpp::internal::IOManipPointer< PointerType 201  pb00 qpp::States, 343 pb01 qpp::States, 344 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prig qpp, 82 prig qpp::RandomDevices, 332 PROB	>,
	nop norn norn NOT nq_ num offse ome oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299  ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164  ga qpp, 81  qpp::States, 341  ations.h, 394  ator * qpp::QCircuit::iterator, 213  ator!= qpp::Dynamic_bitset, 164  qpp::QCircuit::iterator, 214  ator<<< qpp::QCircuit::iterator, 214  ator<<< qpp::IDisplay, 191		qpp::internal::IOManipPointer< PointerType 201 pb00 qpp::States, 343 pb01 qpp::States, 344 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prj qpp, 82 pri qpp, 82 prng_ qpp::RandomDevices, 332 PROB qpp, 29	>,
operator() qpp::NoiseBase < T >, 245	nop norn norn norn norn norn norn norn offse ome oper oper	qpp::QCircuit, 274  qpp::QCircuit, 292  qpp, 81  nalize qpp, 81  qpp::Bit_circuit, 134  qpp::QCircuit, 299 ber_theory.h, 392  et_ qpp::Dynamic_bitset, 164 ga qpp, 81  qpp::States, 341 ations.h, 394 ator * qpp::QCircuit::iterator, 213 ator!= qpp::Dynamic_bitset, 164 qpp::QCircuit::iterator, 214 ator<<< qpp::Dynamic_bitset, 164 qpp::QCircuit::iterator, 214 ator<<< qpp::IDisplay, 191 qpp::QCircuit, 296, 297		qpp::internal::IOManipPointer< PointerType 201  pb00 qpp::States, 343 pb01 qpp::States, 344 pb10 qpp::States, 344 pb11 qpp::States, 344 pGHZ qpp::States, 344 pi qpp, 116 plus qpp::States, 341 pointer qpp::QCircuit::iterator, 212 powm qpp, 82 prj qpp, 82 prng_ qpp::RandomDevices, 332 PROB qpp, 29 probs_	>,

qpp::QEngine, 310	cmat, 27
prod	comm, 38
qpp, 83	complement, 38
psi_	compperm, 39
qpp::QEngine, 310	concurrence, 39
ptrace	conjugate, 39
qpp, 84	contfrac2x, 40
ptrace1	convergents, 40, 41
qpp, 85	cor, 41
ptrace2	cosm, 42
qpp, 86	cov, 42
ptranspose	cplx, 27
qpp, 87 pW	cwise, 43
qpp::States, 344	det, 43 dirsum, 43–45
px0	dirsumpow, 45
qpp::States, 344	disp, 46, 47
px1	dmat, 27
qpp::States, 344	dyn col vect, 27
py0	dyn_mat, 27
qpp::States, 345	dyn_row_vect, 28
py1	ee, 116
qpp::States, 345	egcd, 48
pz0	eig, 48
qpp::States, 345	entanglement, 49
pz1	entropy, 50
qpp::States, 345	evals, 51
qc_	evects, 51
qpp::QCircuit::iterator, 216	expm, 52
qpp::QEngine, 310	factors, 52
QCircuit	funm, 52
qpp::QCircuit, 274	gcd, 53
QEngine	gconcurrence, 54
qpp::QCircuit, 297	grams, 54, 55
qpp::QEngine, 302, 303	hash_eigen, 55
QFT	heig, 56 hevals, 56
qpp, 88	hevects, 57
qpp::QCircuit, 292, 293	idx, 28
qmutualinfo	infty, 116
qpp, 88, 89 QNoisyEngine	inverse, 57
qpp::QNoisyEngine < NoiseModel >, 312	invperm, 58
qpp, 13	ip, 58, 59
absm, 29	isprime, 59
abssq, 29, 30	ket, 28
adjoint, 30	kraus2choi, 59
anticomm, 31	kraus2super, 60
apply, 31–33	kron, 60, 62, 63
applyCTRL, 34	kronpow, 63
applyQFT, 35	lcm, 64
applyTFQ, 35	load, 65
avg, 36	loadMATLAB, 65, 66
bigint, 26	logdet, 66
bloch2rho, 36	logm, 67
bra, 26 choi2kraus, 37	lognegativity, 67, 68 marginalX, 68
choi2super, 37	marginalY, 68
chop, 116	maxn, 116
5110p, 110	maxii, TTO

measure, 69–73		svdV, 111
measure_seq, 74, 75		syspermute, 111, 112
mket, 75, 76		TFQ, 112
modiny, 76		to_void, 28
modmul, 77		trace, 112
modpow, 77		transpose, 113
mprj, 78		tsallis, 113, 114
multiidx2n, 79		uniform, 114
n2multiidx, 79		var, 115
negativity, 80		x2contfrac, 115
norm, 81	app.	h, 396
normalize, 81		QPP_UNUSED_, 397
omega, 81	app:	:Bit_circuit, 129
pi, 116		~Bit_circuit, 132
powm, 82		bCNOT_, 136
pri, 82		bFRED_, 136
PROB, 29		Bit_circuit, 131
prod, 83		bNOT , 136
ptrace, 84		bSWAP_, 136
ptrace1, 85		bTOF_, 136
ptrace2, 86		btotal , 136
•		CNOT, 132
ptranspose, 87		
QFT, 88		count_, 136
qmutualinfo, 88, 89		depth_, 137
rand, 89–91		FRED, 132
randH, 92		get_gate_count, 133
randidx, 92		get_gate_depth, 133
randket, 92		NOT, 134
randkraus, 93		reset, 134
randn, 93–95		SWAP, 134
randperm, 95		TOF, 135
randprime, 95		X, 135
randprob, 97	dbb:	:Codes, 137
randrho, 97		$\sim$ Codes, 139
randU, 97		Codes, 139
randV, 98		codeword, 139
renyi, 98, 99		FIVE_QUBIT, 138
RES, 29		internal::Singleton < const Codes >, 139
reshape, 99		NINE_QUBIT_SHOR, 138
rho2bloch, 100		SEVEN_QUBIT_STEANE, 138
rho2pure, 100		Type, 138
save, 101	qpp:	:Dynamic_bitset, 157
saveMATLAB, 101, 102		~Dynamic_bitset, 161
schatten, 102		all, 161
schmidtA, 103		any, 161
schmidtB, 103, 104		count, 161
schmidtcoeffs, 104, 105		data, 161
schmidtprobs, 105, 106		display, 162
sigma, 106		Dynamic_bitset, 160
sinm, 107		flip, 162
spectralpowm, 107		get, 163
sqrtm, 108		index_, 163
ST, 29		n_, 168
sum, 108, 109		none, 163
super2choi, 109		offset_, 164
svals, 110		operator!=, 164
svd, 110		operator-, 164
svd, 110 svdU, 110		operator==, 165
0740, 110		oporator—, 100

rand, 165, 166	description, 227
reset, 166	Exception, 227
set, 166, 167	qpp::exception::MatrixNotSquareNorRvector, 227
size, 167	description, 229
storage_size, 167	Exception, 229
storage_size_, 168	qpp::exception::MatrixNotSquareNorVector, 229
storage_type, 160	description, 231
to_string, 167	Exception, 231
v_, 168	qpp::exception::MatrixNotVector, 231
value_type, 160	description, 233
qpp::exception, 116	Exception, 233
qpp::exception::CustomException, 140	qpp::exception::NoCodeword, 236
CustomException, 141	description, 237
description, 142	Exception, 237
what_, 142	qpp::exception::NotBipartite, 246
qpp::exception::DimsInvalid, 143	description, 248
description, 144	Exception, 248
Exception, 144	qpp::exception::NotImplemented, 248
qpp::exception::DimsMismatchCvector, 145	description, 250
description, 146	Exception, 250
Exception, 146	qpp::exception::NotQubitCvector, 250
qpp::exception::DimsMismatchMatrix, 147	description, 252
description, 148	Exception, 252
Exception, 148	qpp::exception::NotQubitMatrix, 252
qpp::exception::DimsMismatchRvector, 149	description, 254
description, 150	Exception, 254
Exception, 150	qpp::exception::NotQubitRvector, 254
qpp::exception::DimsMismatchVector, 151	description, 256
	·
description, 152	Exception, 256
Exception, 152	qpp::exception::NotQubitSubsys, 256
qpp::exception::DimsNotEqual, 153	description, 258
description, 154	Exception, 258
Exception, 154	qpp::exception::NotQubitVector, 258
qpp::exception::Duplicates, 156	description, 260
description, 157	Exception, 260
Exception, 157	qpp::exception::OutOfRange, 260
qpp::exception::Exception, 170	description, 262
description, 172	Exception, 262
Exception, 172	qpp::exception::PermInvalid, 262
msg_, 173	description, 264
what, 172	Exception, 264
where_, 173	qpp::exception::PermMismatchDims, 264
qpp::exception::InvalidIterator, 194	description, 266
description, 196	Exception, 266
Exception, 196	qpp::exception::QuditAlreadyMeasured, 324
qpp::exception::MatrixMismatchSubsys, 217	description, 325
description, 218	Exception, 326
Exception, 219	qpp::exception::SizeMismatch, 335
qpp::exception::MatrixNotCvector, 219	description, 336
description, 221	Exception, 336
Exception, 221	qpp::exception::SubsysMismatchDims, 347
qpp::exception::MatrixNotRvector, 221	description, 348
description, 223	Exception, 348
Exception, 223	qpp::exception::TypeMismatch, 353
qpp::exception::MatrixNotSquare, 223	description, 354
description, 225	Exception, 354
Exception, 225	qpp::exception::UndefinedType, 355
•	
qpp::exception::MatrixNotSquareNorCvector, 225	description, 356

o-o	
Exception, 356	check_no_duplicates, 121
qpp::exception::Unknown, 357	check_nonzero_size, 122
description, 358	check_perm, 122
Exception, 358	check_qubit_cvector, 122
qpp::exception::ZeroSize, 363	check_qubit_matrix, 122
description, 364	check_qubit_rvector, 122
Exception, 364	check_qubit_vector, 122
qpp::experimental, 118	check_rvector, 123
qpp::Gates, 173	check_square_mat, 123
~Gates, 175	check_subsys_match_dims, 123
CNOT, 183	check_vector, 123
CNOTba, 183	dirsum2, 123
CTRL, 176	get_dim_subsys, 123
CZ, 183	get_num_subsys, 124
expandout, 176–178	hash_combine, 124
Fd, 178	kron2, 124
FRED, 183	multiidx2n, 124
Gates, 175	n2multiidx, 125
get_name, 179	variadic_vector_emplace, 125
H, 184	qpp::internal::Display_Impl_, 155
ld, 179	display_impl_, 155
ld2, 184	qpp::internal::EqualEigen, 169
internal::Singleton < const Gates >, 183	operator(), 169
MODMUL, 180	qpp::internal::HashEigen, 188
Rn, 180	operator(), 189
RX, 181	qpp::internal::IOManipEigen, 196
RY, 181	A_, 198
RZ, 181	chop_, 198
S, 184	display, 198
SWAP, 184	IOManipEigen, 198
SWAPd, 182	qpp::internal::IOManipPointer< PointerType >, 199
T, 184	chop_, 201
TOF, 184	display, 200
X, 185	end_, 201
Xd, 182	IOManipPointer, 200
Y, 185	N_, 201
Z, 185	operator=, 201
Zd, 182	p_, 201
qpp::IDisplay, 189	separator_, 202
~IDisplay, 190	start_, 202 qpp::internal::IOManipRange< InputIterator >, 202
display, 190	
operator<<, 191 qpp::IJSON, 191	chop_, 204 display, 204
	end_, 205
~IJSON, 192 to_JSON, 192	first , 205
qpp::Init, 192	<del></del>
~Init, 192 ∼Init, 194	IOManipRange, 203, 204
Init, 194	last_, 205
internal::Singleton< const Init >, 194	operator=, 204 separator_, 205
app::internal, 118	start , 205
abs_chop, 120	qpp::internal::Singleton< T >, 332
check_cvector, 120	~Singleton, 334
check_dims, 120	get_instance, 334
check_dims_match_cvect, 121	get_thread_local_instance, 334
check_dims_match_evect, 121 check_dims_match_mat, 121	operator=, 334
check_dims_match_rvect, 121	Singleton, 333
check_eq_dims, 121	qpp::is_complex< std::complex< T > >, 207
check_matching_sizes, 121	qpp::is_complex $<$ T >, 206
	all home—considered ( ) ( )

qpp::is_iterable< T, to_void< decltype(std::declval<	
T >().begin()), decltype(std::declval< T	9 , ,
>().end()), decltype(*(std::declval< T	g
>().begin()))> >, 209	gate_fan, 285, 286
qpp::is_iterable < T, typename >, 208	gates_, 298
qpp::is_matrix_expression< Derived >, 210	GateType, 272
qpp::literals, 125	get_cmat_hash_tbl_, 286
operator""_bra, 126	get_d, 286
operator""_i, 126	get_gate_count, 287
operator""_if, 126, 127	get_gate_depth, 287
operator""_ket, 127	get_gates_, 288
operator""_prj, 127	get_measured, 288
qpp::make_void< Ts >, 216	get_measurement_count, 288, 289
type, 217	get_measurements_, 289
qpp::NoiseBase< T >, 238	get_name, 289
∼NoiseBase, 241	get_nc, 289
compute_probs_, 241	get_non_measured, 290
compute_state_, 241	get_nop_count, 290
d_, 245	get_nq, 290
generated_, 245	get_step_count, 290
get_d, 242	MEASURE_V, 274
get_Ks, 242	MEASURE_V_MANY, 274
get_last_idx, 242	MEASURE_Z, 274
get_last_K, 243	measured_, 298
get_last_p, 243	MEASUREMENT, 274
get_probs, 243	measurement_count_, 298
i_, 245	measurements_, 298
Ks_, 245	MeasureType, 272
noise_type, 240	measureV, 291
NoiseBase, 240	measureZ, 292
operator(), 243, 244	MULTIPLE_cCTRL_MULTIPLE_TARGET, 272
probs_, 245	MULTIPLE_cCTRL_SINGLE_TARGET, 272
qpp::NoiseType, 246	MULTIPLE_CTRL_MULTIPLE_TARGET, 272
qpp::NoiseType::StateDependent, 337	MULTIPLE_CTRL_SINGLE_TARGET, 272
qpp::NoiseType::StateIndependent, 337	name_, 298
qpp::QCircuit, 267	nc_, 299
~QCircuit, 275	NONE, 272, 274
add_circuit, 275	NOP, 274
add_dit, 275	nop, 292
add_hash_, 276	nq_, 299
add_qudit, 276	operator<<, 296, 297
begin, 277	QCircuit, 274
cbegin, 277	QEngine, 297
cCTRL, 277–279	QFT, 292, 293
cCTRL_custom, 279	replicate, 293
cend, 280	SINGLE, 272
cmat_hash_tbl_, 297	SINGLE_cCTRL_MULTIPLE_TARGET, 272
const_iterator, 271	SINGLE_cCTRL_SINGLE_TARGET, 272
count_, 297	SINGLE_CTRL_MULTIPLE_TARGET, 272
CTRL, 280, 281	SINGLE_CTRL_SINGLE_TARGET, 272
CTRL_custom, 282	step_types_, 299
CUSTOM, 272	StepType, 274
CUSTOM_cCTRL, 272	TFQ, 294, 295
CUSTOM_CTRL, 272	THREE, 272
d_, 298	to_JSON, 295
display, 282	TWO, 272
end, 283	qpp::QCircuit::GateStep, 186
FAN, 272	ctrl_, 187

gate_hash 187 gate_hype 188 GateStep. 187 name 188 target 188 target 188 starget 189 start 310 subsys 310 special start 212 special start 213 special start 214 special start 214 special start 214 special start 214 special start 215 spointer 212 spointer 215 spointer 212 spointer 212 spointer 215 spointer 212 spointer		
GateSiep, 187         set_psi, 309           name , 188         stats , 310           target_, 188         stats , 310           difference_type, 212         subsys_, 310           elem , 216         set_psi, 213           ilerator_c131         set_evelte, 313, 314           operator *, 213         set_psi, 312           operator *, 214         operator *, 214           operator *, 214         coperator *, 215           operator *, 212         qp::QublitAmplitudeDampingNoise, 315           operator *, 212         qp::QublitMpolitudeDampingNoise, 316           operator *, 213         qp::QublitMpolity ober, 318           operator *, 214         qp::QublitMpolity ober, 318           operator *, 215         qp::QublitMpolity ober, 319           operator *, 361         qp::QublitMpolity ober, 320           ip., 362         qp::QublitMpolity ober, 361           operator *, 361         qp::QublitMpolity ober, 362 <td>gate_hash_, 187</td> <td>set_dit, 308</td>	gate_hash_, 187	set_dit, 308
name188 target188 dpp::OCircutt:iterator, 211 difference_type, 212 elem216 iterator, 213		
target188  qpp::QCircuit:terator, 211  difference_type, 212 elem216 iterator, 213 iterator_category, 212 operator *, 213 operator!*, 214 operator=, 214 operator=, 214 operator=, 215 pointer, 212 qp_::Qbircuit:terator; 215 pointer, 212 qp_::Qbircuit:terator; 216 reference, 213 set_end215 set_end215 set_end215 set_end215 set_end215 set_end215 set_end215 set_end215 set_end215 set_end216 qpp::QubitPasePinyNoise, 316 QubitBirlipNoise, 318 QubitPhasePinyNoise, 320 QubitPhasePinyNoise, 321 qpp::QubitPhasePinyNoise, 321 qpp::QubitPhasePinyNoise, 321 qpp::QubitPhasePinyNoise, 322 qpp::QubitPhasePinyNoise, 324 qpp::QubitPhasePinyNoise, 324 qpp::QubitPhasePinyNoise, 324 qpp::QubitPhasePinyNoise, 325 massurements_ip382 operator=, 361 type382 qpp::QubitPhasePinyNoise, 324 qpp::QubitPhasePinyNoise, 324 qpp::QubitPhasePinyNoise, 325 massurement_type360, 361 value_typeqc362 qpp::QubitPhasePinyNoise, 327 qpp::RandomDevices, 329 value_typegc382 ppr::QubitPhasePinyNoise, 327 qpp::RandomDevices, 330 get_prote, 330 dist303 dist303 dist303 dist303 dist304 get_circuit, 305 get_dist, 305 get_dist, 305 get_dist, 305 get_measured, 305, 306 get_proth, 307 portor, 212 qpp::QubitPhasePinyNoise, 316 qpp::QubitPhasePinyNoise, 327 qpp::RandomDevices, 330 qpt_prother, 215 qpp::States, 337 qpp::States, 337 qpp::States, 337 qpp::States, 340 hoin, 343 hoin, 344 hoise_prother, 216 qpp::QubitPhasePinyNoise, 316 qpp::QubitPhasePinyNoise, 327 qpp::RandomDevices, 329 value_typeqc362 qpp::QubitPhasePin	•	<del>-</del>
app::Oclicuit:iterator, 211         to_JSON, 309           difference_type, 212         app::ONoisyEngine < NoiseModel >, 311           elem 216         execute, 313, 314           iterator, 213         get_noise_results, 314           operator *, 214         operator*, 214           operator*, 214         operator*, 216           operator*, 216         qp::OubliAimplitudeDampingNoise, 315           operator*, 217         qp::OubliAimplitudeDampingNoise, 316           operator*, 218         qp::OubliBiliPhose, 318           operator*, 219         qp::OubliBiliPhose, 318           operator*, 216         qp::OubliBiliPhose, 318           operator*, 217         qp::OubliBiliPhose, 318           operator*, 218         qp::OubliBiliPhose, 318           operator*, 219         qp::OubliBiliPhose, 318           operator*, 216         qp::OubliBiliPhose, 318           operator*, 217         qp::OubliBiliPhose, 318           operator*, 218         qp::OubliBiliPhose, 318           operator*, 219         qp::OubliBiliPhose, 318           operator*, 216         qp::OubliBiliPhose, 318           operator*, 217         qp::OubliPhasePlipNoise, 321           operator*, 218         qp::OubliPhasePlipNoise, 321           operator*, 361         qp::OubliPhasePlipNoise, 322<		
difference_type, 212 elem218 iterator_213 iterator_213 iterator_213 operator**, 213 operator**, 214 operator**, 214 operator**, 214 operator**, 214 operator**, 215 pointer, 212 qc216 reference, 213 set_begin215 set_end215 set_end215 value_type1215 gates_ip361 ip362 operator**, 381 ip362 operator**,	· —	• —
elem216 iterator_category, 212 operator +, 213 operatorf=_214 operator=_215 operatorf=_214 operator==_215 operator=_215 operator=_215 operator=_215 operator=_216 operator==_215 operator=_215 operator=_216 operator==_215 operator=_216 operator==_215 operator=_216 operator==_215 operator=_216 operator==_217 operator=_217 operator==_218 operator=_218 operator=_219		
iterator, 213 iterator_category, 212 operator *, 213 operator *, 213 operator *, 214 operator *, 214 operator *, 215 operator *, 214 operator *, 215 operator *, 216 operator *, 216 operator *, 217 operator *, 217 operator *, 218 operator *, 218 operator *, 219 operator *, 219 operator *, 219 operator *, 210 operator *, 211 operator *, 215 set_end_, 216 cubititifierionse, 318 spp::QubitifieripNoise, 318 spp::QubitifieripNoise, 318 spp::QubitifieripNoise, 319 spp::QubitifieripNoise, 319 spp::QubitifieripNoise, 319 spp::QubitifieripNoise, 321 spp::QubitifieripNoise, 321 spp::QubitifieripNoise, 321 spp::QubitifieripNoise, 321 spp::QubitifieripNoise, 322 spp:	— · ·	
iterator_category, 212     operator *, 213     operator *, 214     operator =, 214     operator =, 215     operator =, 215     pointer, 212     qc, 216     reference, 213     set_begin_, 215     set_end_, 215     set_end_, 215     set_end_, 215     qpp::OubitBifFipNoise, 316     QubitBifFipNoise, 318     QubitBifFhaseFilpNoise, 318     QubitBifPhaseFilpNoise, 319     qpp::OubitBifFipNoise, 318     QubitBifPhaseFilpNoise, 319     qpp::OubitBifFhaseFilpNoise, 319     qpp::OubitBifFhaseFilpNoise, 319     qpp::OubitBifFhaseFilpNoise, 319     qpp::OubitBifFhaseFilpNoise, 319     qpp::OubitPhaseFilpNoise, 319     qpp::OubitPhaseFilpNoise, 320     QubitDepolarizingNoise, 321     qubitPhaseFilpNoise, 322     qpp::OubitPhaseFilpNoise, 323     qpp::OubitPhaseFilpNoise, 322     qpp::OubitPhaseFilpNoise, 323     qpp::OubitPhaseFilpNoise, 322     qpp::OubitPhaseFilpNoise, 322     qpp::OubitPhaseFilpNoise, 322     qpp::OubitPhaseFilpNoise, 323     qpp::OubitPhaseFilpNoise, 323     qpp::OubitPhaseFilpNoise, 328     qpp::OubitPhaseFilpNoise, 328     qpp::OubitPhaseFilpNoise, 328     qpp::OubitPhaseFilpNoise, 328     qpp::OubitPhaseFilpNoise, 328     qpp::Oubit		
operator+, 213 operator+, 214 operator+, 214 operator+, 214 operator-, 215 operator-, 215 pointer, 212 q 216 reference, 213 set_begin_, 215 set_end_, 215 set_end_, 215 value_type_, 213 display, 361 gates_ip 361 type 382 value_type 380, 361 value_type 380, 361 value_type 380, 361 value_type 382 measurements_ip 382 value_type 382 measurestep, 234, 235 mats_hash 235 mats_hash 235 measurement_type 235 mats_ash 235 measurement_type 330 dist 309 execute_, 304 ggt_circuit, 305 ggt_dits_ 305 ggt_dits_ 305 ggt_measured, 305, 306 ggt_probs_, 306 ggt_probs_, 306 ggt_probs_, 307 ggt_states_, 307 operator=, 214 ONoisyEngine, 312 qpp::QubitMmplitudeDampingNoise, 316 qpp::QubitBilFilpNoise, 318 qpp::QubitBilFilpNoise, 318 qpp::QubitBilFilpNoise, 318 qpp::QubitBhaseFilpNoise, 319 qpp::QubitPhaseFilpNoise, 320 QubitPhaseFilpNoise, 321 qpp::QubitPhaseFilpNoise, 322 qpp::QubitPhaseFilpNoise, 321 QubitPhaseFilpNoise, 321 qpp::QubitPhaseFilpNoise, 321 qpp::QubitPhaseFilpNoise, 322 qpp::QubitPhaseFilpNo		· · · · · · · · · · · · · · · · · · ·
operatorI=, 214 operatorI=, 214 operatorI=, 214 operatorI=, 215 pointer, 215 pointer, 212 qe 216 reference, 213 set_begin_, 215 set_end 215 value_type, 213 qpp::CubitMile polarizingNoise, 316 QubitBitPhaseFilpNoise, 318 QubitBitPhaseFilpNoise, 318 QubitBitPhaseFilpNoise, 319 qpp::QubitDepolarizingNoise, 320 QubitPhaseDampingNoise, 320 QubitDepolarizingNoise, 320 QubitPhaseDampingNoise, 320 QubitDepolarizingNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhaseFilpNoise, 319 qpp::QubitPhaseDampingNoise, 320 QubitPhaseFilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhaseFilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 321 qpp::QubitPhaseDampingNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhaseDampingNoise, 320 QubitPhasePilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhasePilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhasePilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhasePilpNoise, 321 qpp::QubitPhaseDampingNoise, 320 QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 322 qpp::QubitDepolarizingNoise, 322 qpp::QubitDepolarizingNoise, 322 qpp::QubitPhasePilpNoise, 324 qpp::QubitPhasePilpNoise, 324 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 322 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 320 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 320 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 322 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilpNoise, 321 qpp::QubitPhasePilp		
operator++, 214	•	
operator=, 214	•	· ·
operator==, 215     pointer, 212     qc_ 216     reference, 213     set_begin_, 215     set_end_, 215     value_type, 213     qpp::QubitBitPhaseFilpNoise, 319     qpp::QubitDepolarizingNoise, 321     qubitPhaseDampingNoise, 321     qubitPhaseDampingNoise, 321     qubitPhaseDampingNoise, 322     qpp::QubitPhaseDampingNoise, 322     qpp::QubitPhaseDampingNoise, 322     qpp::QubitPhasePilpNoise, 322     qpp::QubitPhasePilpNoise, 323     QubitPhasePilpNoise, 324     qpp::QubitPhasePilpNoise, 324     qpp::QubitPhasePilpNoise, 322     qpp::QubitPhasePilpNoise, 326     qpp::QubitPhasePilpNoise, 327     qpp::RandomDevices, 328     set_end_, 236     value_type_, 360, 361     value_type_, 362     value_type_, 366, 361     value_type_, 235     mats_hash_, 235     mats_hash_, 235     measurement_type_, 235     measurement_type_, 235     measurement_type_, 235     measurement_type_, 235     mats_hash_, 235     measurement_type_, 235     mats_hash_, 235     reg_, 234     app::QubitPhasePilpNoise, 321     qpp::QubitPhasePilpNoise, 322     qpp::QubitPhasePilpNoise, 321     qpp::QubitPhasePilpNoise, 322     qpp::QubitPhasePilpNoise, 328     fill prois_, 328     fill prois_, 328     fill prois_, 328		
pointer, 212 qc_, 216 qc_, 216 reference, 213 set_begin_, 215 set_end_, 215 set_end_, 215 set_end_, 215 set_end_, 216 value_type, 213 qpp::QubitIlepolarizingNoise, 320 QubitIlepolarizingNoise, 321 qpp::QubitIlepolarizingNoise, 322 qpp::QubitIlepolarizingNoise, 322 qpp::QubitIlepolarizingNoise, 323 QubitIlepolarizingNoise, 323 QubitIlepolarizingNoise, 324 qpp::QubitIlepolarizingNoise, 326 fill_ks_, 328 fill_probs_, 328 QubitIlepolarizingNoise, 326 fill_ks_, 328 fill_probs_, 328 QubitIlepolarizingNoise, 326 fill_ks_, 328 fill_probs_, 328 QubitIlepolarizingNoise, 327 qpp::RandomDevices, 330 get_prandomDevices, 330 get	•	· · · · ·
qc_, 216 reference, 213	•	
reference, 213 set_begin_, 215 set_end_, 215 value_type, 213 qpp::CubilDepolarizingNoise, 321 qpp:CCircut::tlerator::value_type_, 359 display, 361 gates_ip, 361 ip 362 measurements_ip, 362 operator=, 361 type, 362 qpp:CCircut::MeasureStep, 233 c_reg 235 measurement_type_, 236 qpp:CCircut::MeasureStep, 233 c_reg 235 measurement_type_, 235 measurement_type_, 235 measurement_type_, 235 measurement_type_, 235 measurement_type_, 235 measurement_type_, 360 qpp:CEngine, 300 ~CEngine, 300 dislay, 303 dislay, 303 dislay, 303 dislay, 309 execute, 304 get_circut, 305 get_dit, 305 get_dit, 305 get_dits, 305 get_measured, 306 get_probs, 307 operator=, 307 probs_, 310 qc 310 qc 310 QEngine, 302, 303 reset, 307 pw, 344 plus, 341 plus, 344 plus, 345 plus, 346 ppp:QubitPhasedDampingNoise, 326 pp	·	•
set_begin 215         qpp::QubitDepolarizingNoise, 320           set_end 215         QubitDepolarizingNoise, 321           value_type, 213         qpp::QubitPhaseDampingNoise, 321           qpp::QubitPhasePilpNoise, 321         qpp::QubitPhaseFilpNoise, 322           display, 361         qpp::QubitPhaseFilpNoise, 323           gates_ip 362         qpp::QubitPhaseFilpNoise, 324           ip 362         qpp::QubitPhaseFilpNoise, 326           measurements_ip 362         qpp::QuditDepolarizingNoise, 326           operator=, 361         fill_ks 328           type 362         qpp::QuditDepolarizingNoise, 326           value_type 360, 361         qpp::RandomDevices, 328           value_type 360, 361         qpp::RandomDevices, 329           value_type 360, 361         qpp::RandomDevices, 320           qpp::Clircuit::MeasureStep, 233         get_prng, 331           c_reg 235         internal::Singleton<		
set_end215 value_type, 213 qpp::QubitPhaseDampingNoise, 321 qpp::QubitUbensaeDampingNoise, 321 qpp::QubitPhaseDampingNoise, 322 display, 361 gates_ip361 gates_ip361 ip362 measurements_ip, 362 operator=, 361 type360, 361 value_type_qc362 qpp::QubitPhaseFlipNoise, 326 fill_ks328 fill_probs, 328 fill_probs, 328 get_pring, 361 type360, 361 value_type_qc362 qpp::QubitPhaseFlipNoise, 326 fill_ks328 fill_probs, 328 fill_probs, 328 get_pring, 331 c_reg235 mats_hash 235 mats_hash 235 measurement_type, 235 MeasureStep, 234, 235 name, 235 target236 qpp::Qcircuit::MeasureStep, 233 display, 303 display, 305 get_circuit, 305 get_dit, 305 get_dit, 305 get_dit, 305 get_dit, 305 get_measured, 306, 306 get_probs, 306 get_probs, 306 get_probs, 306 get_probs, 307 qpet_states, 307 operator=, 307 ppb10, 344 pps, 341 pps, 310 ppi, 310 ppi, 310 QCEngine, 302, 303 reset, 307 ppX, 344 ppx, 344 plus, 341 plus, 341 plus, 341 plus, 341 plus, 341 plus, 344		•
value_type, 213         qpp::QubitPhaseDampingNoise, 321           qpp::QubitIntaseEnampingNoise, 322         QubitPhaseEnampingNoise, 322           display, 361         qpp::QubitPhaseFlipNoise, 323           gates_ip_, 361         QubitPhaseFlipNoise, 324           ip_, 362         qpp::QuditDepolarizingNoise, 326           measurements_ip_, 362         fill_probs_, 328           operator=, 361         fill_probs_, 328           type_, 362         QuditDepolarizingNoise, 327           value_type_, 360, 361         qpp::RandomDevices, 329           value_type_, 362         qpp::RandomDevices, 320           qpp::QCircuit:.MeasureStep, 233         get_prng, 331           _ reg_, 235         linternal::Singleton           mats_hash_, 235         gad, 331           measurement_type_, 235         prng_, 332           MeasureStep, 234, 235         rd_, 332           target_, 236         save, 331           qpp::QEngine, 300         qpp::States, 337           ~CEngine, 303         b00, 342           disjay, 303         b01, 343           get_circuit, 305         b11, 343           get_dits, 305         get_measured, 304           get_measured, 306         mes, 340           get_pris, 306         mes, 340		
qpp::QCircuit::iterator::value_type 359         QubitPhaseDampingNoise, 322           display, 361         qpp::QubitPhaseFlipNoise, 323           gates_ip_, 361         QubitPhaseFlipNoise, 324           ip 362         qpp::QubitPhaseFlipNoise, 326           measurements_ip_, 362         fill_Ks, 328           operator=, 361         type 360, 361           type 360, 361         qpp::RandomDevices, 329           value_type 360, 361         qpp::RandomDevices, 330           value_type 360, 361         qpp::RandomDevices, 330           value_type 360, 361         qpp::RandomDevices, 329           value_type 360, 361         qpp::RandomDevices, 330           value_type 352         qpp::RandomDevices, 330           qpp::QubitPhaseFlipNoise, 322         qpp::RandomDevices, 329           value_type 360, 361         qpp::RandomDevices, 329           value_type 362         qpp::RandomDevices, 330           qpp::RandomDevices, 329         qpp::RandomDevices, 330           qpp::RandomDevices, 329         qpp::RandomDevices, 330           qpp::RandomDevices, 329         qpp::RandomDevices, 332           qpp::RandomDevices, 329         qpp::RandomDevices, 332           ppp::RandomDevices, 329         qpp::RandomDevices, 329           ppp::RandomDevices, 329         qpp::RandomDevic		
display, 361     gates_ip361     gates_ip362     ip362     measurements_ip362     operator=, 361     type362     operator=, 361     type362     value_type360, 361     value_type360, 361     value_type362     qpp::Qcircuit::MeasureStep, 233     c_reg235     measurement_type235     measurement_type325     measurestep, 234, 235     name235     raget236     qpp::QEngine, 300     qpp::QEngine, 303     display, 303     display, 303     display, 305     get_dit, 305     get_dit, 305     get_dit, 305     get_measured, 306, 306     get_non_measured, 306     get_non_measured, 306     get_non_measured, 306     get_non_measured, 306     get_non_measured, 306     get_non_measured, 307     poperator=, 307     operator=, 307     operator=, 307     popsi, 310     QEngine, 300     qpt. 344     petdit, 305     get_relative_pos307     poptator=, 307     popsi310     QEngine, 302     qpt. 344     pet344     pet341     qpp::Qbit in, 344     petsi306     getrelative_pos307     poptator=, 307     popt		
gates_ip_, 361         QubitPhaseFlipNoise, 324           ip_, 362         qpp::QuditIbepolarizingNoise, 326           measurements_ip_, 362         fill_Ks_, 328           operator=, 361         fill_probs_, 328           type_, 362         QuditDepolarizingNoise, 327           value_type_, 360, 361         qpp::RandomDevices, 329           value_type_, 26_, 362         ~RandomDevices, 330           qpp::QCircuit::MeasureStep, 233         get_prng, 331           c_reg_, 235         load, 331           mats_hash_, 235         prng_, 332           measurement_type_, 235         RandomDevices, 330           name_, 235         rd_, 332           target_, 236         save, 331           qpp::QEngine, 300         qpp::States, 337           ~QEngine, 303         dpp::States, 340           display, 303         b00, 342           dis_, 309         b01, 343           get_circuit, 305         ght_, 343           get_dit, 305         ght_, 343           get_dit, 305         ght_, 343           get_measured, 305, 306         get_measured, 306           get_pois, 306         mes, 340           get_pois, 306         mes, 340           get_pois, 306         none, 341           qe		. •
ip 362 measurements_ip 362 operator=, 361 type 362 value_type 360, 361 value_type_ oc 362 qpp::QCircuit::MeasureStep, 233 c_reg 235 measurement_type 235 measurement_type 235 measurement_type 235 MeasureStep, 234, 235 name 236 qpp::QEngine, 300 ~QEngine, 300 execute, 304 get_circuit, 305 get_dit, 305 get_dit, 305 get_dit, 305 get_measured, 305, 306 get_probs, 306 get_probs, 306 get_props, 307 poperator=, 307 poperator=, 307 poperator=, 307 pow, 344 plus, 344 plus, 344 plus, 344 plus, 341 plus, 344 ppo,		
measurements_ip 362     operator=_ 361     type 362     operator=_ 361     type 362     value_type 360, 361     value_type_ qc 362     qpp::Circuit::MeasureStep, 233         c_reg 235     mats_hash 235     measurement_type 235     MeasureStep, 234, 235     mats_hash 235     measurement_type 235     MeasureStep, 234, 235     name 235     reg 236     qpp::Clargine, 300     qpp::States, 337     ~QEngine, 303     display, 303     dis 309     execute, 304     get_circuit, 305     get_dit, 305     get_dit, 305     get_dits, 305     get_measured, 305, 306     get_non_measured, 306     get_probs, 306     get_probs 307     get_stats, 307     probs, 310     perior 301     perior 302     perior 303     perior 304     perior 306     get_ron 307     perior 307     porba, 310     perior 302     perior 302     perior 307     probs, 310     perior 302     perior 302     perior 303     perior 304     perior 307     probs, 310     perior 302     perior 302     perior 303     perior 304     perior 307     probs, 310     perior 307     probs, 310     perior 307     profine, 302     perior 302     perior 303     perior 304     perior 307     profine, 302     profine, 302     profine, 303     profine, 303		·
operator=, 361 type		
type_, 362     value_type_, 360, 361     value_type_qc_, 362     value_type_qc_, 362     qpp::QCircuit::MeasureStep, 233     c_req_, 235     mats_hash_, 235     measurement_type_, 235     MeasureStep, 234, 235     name_, 235     target_, 236     qpp::QEngine, 300     value_nype_qc_, 332     save, 331     qpp::QEngine, 300     value_nype_qc_, 335     measurement_type_, 235     MeasureStep, 234, 235     name_, 235     target_, 236     save, 331     qpp::QEngine, 300     value_type_, 303     display, 303     display, 303     dits_, 309     execute, 304     get_circuit, 305     get_dit, 305     get_dit, 305     get_dit, 305     get_dit, 305     get_dits, 305     get_measured, 305, 306     get_non_measured, 306     get_probs, 306     get_probs, 306     get_probs_, 306     get_probs_, 307     get_stats_, 307     operator=, 307     probs_, 310     per_, 310     QEngine, 302, 303     reset, 307     puls, 341     puls, 341     pc_, 310     QEngine, 302, 303     reset, 307     py, 344     reset, 307     py, 344     reset, 307     py, 344     reset, 307     py, 344		
value_type 360, 361     value_type_qc 362  qpp::Qcircuit::MeasureStep, 233     c_reg 235     mats_hash 235     measurement_type, 235     MeasureStep, 234, 235     name 235     target 236  qpp::QEngine, 300     qel_pri, 303     display, 303     display, 303     dist 309     execute, 304     get_circuit, 305     get_dit, 305     get_dits, 305     get_measured, 306     get_non_measured, 306     get_non_measured, 306     get_relative_pos, 307     get_stats, 307     operator=, 307     pot, 310     person, 302     qep::QEngine, 303     cybet_dits, 305     get_dits, 305     get_dits, 305     get_loid, 305     get_non_measured, 306     get_pois, 306     get_relative_pos, 307     get_stats, 307     operator=, 307     pb00, 343     pet_i_, 310     qc, 310     QEngine, 302, 303     reset, 307     pw, 344     puls, 341     QEngine, 302, 303     reset, 307     pw, 344     pw, 344     reset, 307     pw, 344     pw, 344		_ <del>,</del>
value_type_qc_, 362  qpp::QCircuit::MeasureStep, 233		,
qpp::QCircuit::MeasureStep, 233         get_prng, 331           c_reg, 235         internal::Singleton<		
c_reg_, 235       internal::Singleton < RandomDevices >, 332         mats_hash_, 235       load, 331         measurement_type_, 235       prng_, 332         MeasureStep, 234, 235       RandomDevices, 330         name_, 235       rd_, 332         target_, 236       save, 331         qpp::QEngine, 300       qpp::States, 337         ~QEngine, 303       ~States, 340         display, 303       b00, 342         dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       g1, 343         get_dit, 305       get_dit, 343         get_dits, 305       internal::Singleton < const States >, 342         get_measured, 305, 306       jn, 340         get_probs, 306       mes, 340         get_posi, 306       mes, 341         get_psi, 306       one, 341         get_relative_pos_, 307       pb00, 343         get_stats, 307       pb00, 343         operator=, 307       pb10, 344         pri, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344		
measurement_type, 235         prng, 332           MeasureStep, 234, 235         RandomDevices, 330           name, 235         rd, 332           target_, 236         save, 331           qpp::States, 337         QEngine, 303           ~QEngine, 303         ~States, 340           display, 303         b00, 342           display, 309         b01, 343           execute, 304         b10, 343           get_circuit, 305         b11, 343           get_dit, 305         GHZ, 343           get_dits, 305         internal::Singleton < const States >, 342           get_measured, 305, 306         jn, 340           get_probs, 306         mes, 340           get_probs, 306         minus, 341           get_pris, 306         one, 341           get_stats, 307         pb00, 343           get_stats, 307         pb01, 344           porbs, 310         pb11, 344           psi, 310         pGHZ, 344           qc, 310         plus, 341           QEngine, 302, 303         pW, 344           reset, 307         px0, 344		internal::Singleton< RandomDevices >, 332
MeasureStep, 234, 235       RandomDevices, 330         name_, 235       rd_, 332         target_, 236       save, 331         qpp::QEngine, 300       qpp::States, 337         ~QEngine, 303       ~States, 340         display, 303       b00, 342         dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       b11, 343         get_dit, 305       GHZ, 343         get_dits, 305       internal::Singleton < const States >, 342         get_measured, 305, 306       jn, 340         get_non_measured, 306       mes, 340         get_probs, 306       minus, 341         get_psi, 306       one, 341         get_stats, 307       pb00, 343         get_stats, 307       pb10, 343         operator=, 307       pb10, 344         psi_, 310       pb11, 344         psi_, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344	mats_hash_, 235	load, 331
name_, 235 target_, 236 save, 331 qpp::QEngine, 300 qpp::States, 337  ~QEngine, 303 display, 303 display, 303 dits_, 309 execute, 304 get_circuit, 305 get_dit, 305 get_dits, 305 get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_relative_pos_, 307 get_states, 307 pb00, 343 get_states, 307 pcHz, 344 pc_, 310 QEngine, 302, 303 reset, 307  qpt, 344 ppw, 344	measurement_type_, 235	prng_, 332
target_, 236 qpp::QEngine, 300 qpp::States, 337 ~QEngine, 303 display, 303 display, 303 dits_, 309 execute, 304 get_circuit, 305 get_dit, 305 get_dits, 305 get_dits, 305 get_measured, 305, 306 get_probs, 306 get_probs, 306 get_probs, 306 get_relative_pos_, 307 get_stats, 307 pobal, 310 QEngine, 302, 303 reset, 307  px 344  qpp::States, 337  pb00, 342 b00, 342 b01, 343 b00, 343 b10, 343 b11, 343 b11, 343 get_dit, 305 get_state, 307 pb00, 341 pb10, 343 pb11, 344 psi_, 310 pGHZ, 344 pc_, 310 QEngine, 302, 303 pW, 344 px0, 344	MeasureStep, 234, 235	RandomDevices, 330
qpp::QEngine, 300       qpp::States, 337         ~QEngine, 303       ~States, 340         display, 303       b00, 342         dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       b11, 343         get_dit, 305       GHZ, 343         get_dits, 305       internal::Singleton < const States >, 342         get_measured, 305, 306       jn, 340         get_probs, 306       mes, 340         get_probs, 306       minus, 341         get_relative_pos_, 307       pb00, 343         get_stats, 307       pb01, 343         operator=, 307       pb10, 344         probs_, 310       pb11, 344         ps_, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344	name_, 235	rd_, 332
~QEngine, 303       ~States, 340         display, 303       b00, 342         dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       b11, 343         get_dit, 305       GHZ, 343         get_dits, 305       internal::Singleton < const States >, 342         get_measured, 305, 306       jn, 340         get_probs, 306       mes, 340         get_probs, 306       minus, 341         get_psi, 306       one, 341         get_relative_pos_, 307       pb00, 343         get_stats, 307       pb01, 343         operator=, 307       pb10, 344         probs_, 310       pb11, 344         psi_, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344	target_, 236	save, 331
display, 303       b00, 342         dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       b11, 343         get_dit, 305       GHZ, 343         get_dits, 305       internal::Singleton< const States >, 342         get_measured, 305, 306       jn, 340         get_probs, 306       mes, 340         get_psi, 306       minus, 341         get_relative_pos_, 307       pb00, 343         get_stats, 307       pb00, 343         operator=, 307       pb10, 344         probs_, 310       pb11, 344         psi_, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344	qpp::QEngine, 300	qpp::States, 337
dits_, 309       b01, 343         execute, 304       b10, 343         get_circuit, 305       b11, 343         get_dit, 305       GHZ, 343         get_dits, 305       internal::Singleton < const States >, 342         get_measured, 305, 306       jn, 340         get_probs, 306       mes, 340         get_probs, 306       minus, 341         get_psi, 306       one, 341         get_relative_pos_, 307       pb00, 343         get_stats, 307       pb01, 343         operator=, 307       pb10, 344         probs_, 310       pb11, 344         psi_, 310       pGHZ, 344         qc_, 310       plus, 341         QEngine, 302, 303       pW, 344         reset, 307       px0, 344	$\sim$ QEngine, 303	$\sim$ States, 340
execute, 304 get_circuit, 305 get_dit, 305 get_dit, 305 get_dits, 305 get_dits, 305 get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_probs, 306 get_probs, 306 get_relative_pos_, 307 get_stats, 307 operator=, 307 probs_, 310 psi_, 310 QEngine, 302, 303 pet_get_idt, 305 pet_probs, 306 pet_probs, 306 pet_probs_, 310 pch_Z, 344 pcs_, 310 QEngine, 302, 303 px, 344 px0, 344 px0, 344 px0, 344 px0, 344	·	b00, 342
get_circuit, 305 get_dit, 305 get_dit, 305 get_dits, 305 get_dits, 305 get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_probs, 306 get_psi, 306 get_relative_pos_, 307 get_stats, 307 operator=, 307 probs_, 310 psi_, 310 QEngine, 302, 303 rest, 307 pb11, 344 psi_, 310 QEngine, 302, 303 pkd, 343 pkd, 344		
get_dit, 305 get_dits, 305 get_dits, 305 get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_probs, 306 get_relative_pos_, 307 get_stats, 307 operator=, 307 probs_, 310 psi_, 310 QEngine, 302, 303 reset, 307 get_dits, 307 pk, 344 probs_, 310 plus, 341 pGHZ, 344 probs_, 310 plus, 341 pGHZ, 344 probs_, 310 pGHZ, 344 probs_, 310 pW, 344 px0, 344		
get_dits, 305 get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_probs, 306 get_relative_pos_, 307 get_stats, 307 operator=, 307 probs_, 310 psi_, 310 QEngine, 302, 303 ret_measured, 305, 306 jn, 340 mes, 340 mes, 340 mes, 341 one, 341 one, 341 pb00, 343 pb01, 343 opb01, 344 pb11, 344 psi_, 310 pGHZ, 344 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 internal::Singleton< const States >, 342 in, 340 mes, 340 mes, 340 one, 341 pb00, 343 pb01, 343 pb11, 344 psi_, 310 pGHZ, 344 plus, 341 pW, 344 reset, 307		
get_measured, 305, 306 get_non_measured, 306 get_probs, 306 get_probs, 306 get_pros, 306 get_pros, 307 get_relative_pos_, 307 get_stats, 307 pb00, 343 get_stats, 307 pb01, 343 operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 QEngine, 302, 303 pW, 344 reset, 307 pin, 340 mes, 340 mes, 340 mes, 340 pb00, 341 pb00, 343 pb01, 343 pb11, 344 psi_, 310 pGHZ, 344 plus, 341 pW, 344 reset, 307	<del>-</del> —	
get_non_measured, 306 get_probs, 306 get_psi, 306 get_psi, 306 get_relative_pos_, 307 get_stats, 307 get_stats, 307 pb00, 343 operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 QEngine, 302, 303 pW, 344 reset, 307 mes, 340 mes, 340 pb00, 341 pb00, 343 pb11, 344 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 pW, 344 reset, 307	<del>-</del> —	
get_probs, 306 minus, 341 get_psi, 306 one, 341 get_relative_pos_, 307 pb00, 343 get_stats, 307 pb01, 343 operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	<del>-</del> —	
get_psi, 306 one, 341 get_relative_pos_, 307 pb00, 343 get_stats, 307 pb01, 343 operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	· · · · · · · · · · · · · · · · · · ·	
get_relative_pos_, 307		•
get_stats, 307 pb01, 343 operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344		
operator=, 307 pb10, 344 probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	<del>-</del>	•
probs_, 310 pb11, 344 psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	<del>-</del> —	•
psi_, 310 pGHZ, 344 qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	•	•
qc_, 310 plus, 341 QEngine, 302, 303 pW, 344 reset, 307 px0, 344	. —	•
QEngine, 302, 303 pW, 344 reset, 307 px0, 344	• —	•
reset, 307 px0, 344	• —	•
• •		·
		•
		Pv. 13 0 1 1

py0, 345	qpp, 95
py1, 345	randprob
pz0, 345	qpp, 97
pz1, 345	randrho
States, 340	qpp, 97
W, 345	randU
x0, 345	qpp, 97
x1, 346	randV
y0, 346	qpp, 98
y1, 346	rd
z0, 346	qpp::RandomDevices, 332
z1, 346	reference
zero, 342	qpp::QCircuit::iterator, 213
qpp::Timer< T, CLOCK_T >, 349	
~Timer, 350	renyi
display, 351	qpp, 98, 99
end , 352	replicate
get_duration, 351	qpp::QCircuit, 293
start_, 352	RES
	qpp, 29
tic, 351	reset
tics, 352	qpp::Bit_circuit, 134
Timer, 350	qpp::Dynamic_bitset, 166
toc, 352	qpp::QEngine, 307
QPP_UNUSED_	reset_stats
qpp.h, 397	qpp::QEngine, 308
QubitAmplitudeDampingNoise	reshape
qpp::QubitAmplitudeDampingNoise, 316	qpp, 99
QubitBitFlipNoise	rho2bloch
qpp::QubitBitFlipNoise, 318	qpp, 100
QubitBitPhaseFlipNoise	rho2pure
qpp::QubitBitPhaseFlipNoise, 319	qpp, 100
QubitDepolarizingNoise	Rn
qpp::QubitDepolarizingNoise, 321	qpp::Gates, 180
QubitPhaseDampingNoise	RX
qpp::QubitPhaseDampingNoise, 322	qpp::Gates, 181
QubitPhaseFlipNoise	RY
qpp::QubitPhaseFlipNoise, 324	qpp::Gates, 181
QuditDepolarizingNoise	RZ
qpp::QuditDepolarizingNoise, 327	qpp::Gates, 181
	qppdates, 101
rand	S
qpp, 89–91	
qpp::Dynamic_bitset, 165, 166	qpp::Gates, 184
randH	save
qpp, 92	qpp, 101
randidx	qpp::RandomDevices, 331
qpp, 92	saveMATLAB
randket	qpp, 101, 102
qpp, 92	schatten
randkraus	qpp, 102
qpp, 93	schmidtA
randn	qpp, 103
qpp, 93–95	schmidtB
random.h, 398	qpp, 103, 104
RandomDevices	schmidtcoeffs
qpp::RandomDevices, 330	qpp, 104, 105
randperm	schmidtprobs
qpp, 95	qpp, 105, 106
randprime	separator_

anr	o::internal::IOManipPointer<	PointerTyne	>,	qpp::Dynamic_bitset, 167
ЧР	202	1 officer type	/,	storage_size_
apr	o::internal::IOManipRange<	InputIterator	>,	qpp::Dynamic_bitset, 168
41414	205		,	storage_type
set				qpp::Dynamic_bitset, 160
qpr	o::Dynamic bitset, 166, 167			subsys_
set_beg				qpp::QEngine, 310
	o::QCircuit::iterator, 215			sum
set_dit				qpp, 108, 109
qpp	o::QEngine, 308			super2choi
set_end	_			qpp, 109
qpp	o::QCircuit::iterator, 215			svals
set_mea	asured_			qpp, 110
qpp	o::QEngine, 308			svd
set_psi				qpp, 110
qpp	o::QEngine, 309			svdU
	_QUBIT_STEANE			qpp, 110
qpp	o::Codes, 138			svdV
sigma				qpp, 111
	o, 106			SWAP
SINGLE				qpp::Bit_circuit, 134
	o::QCircuit, 272			qpp::Gates, 184
	_cCTRL_MULTIPLE_TARGE	Γ		SWAPd
	o::QCircuit, 272			qpp::Gates, 182
	_cCTRL_SINGLE_TARGET			syspermute
	o::QCircuit, 272			qpp, 111, 112
	_CTRL_MULTIPLE_TARGET			Т
	o::QCircuit, 272			qpp::Gates, 184
	_CTRL_SINGLE_TARGET			target_
	o::QCircuit, 272			qpp::QCircuit::GateStep, 188
Singleto				qpp::QCircuit::MeasureStep, 236
qpp	o::internal::Singleton $<$ T $>$ , 33	33		TFQ
sinm				qpp, 112
qpp	, 107			qpp::QCircuit, 294, 295
size				THREE
	o::Dynamic_bitset, 167			qpp::QCircuit, 272
spectral				tic
	, 107			qpp::Timer< T, CLOCK_T >, 351
sqrtm				tics
	, 108			qpp::Timer $<$ T, CLOCK_T $>$ , 352
ST				Timer
	o, <del>29</del>			qpp::Timer< T, CLOCK_T >, 350
start_	· · · · · · · · · · · · · · · · · · ·	D		to_JSON
dbb	o::internal::IOManipPointer<	PointerType	>,	qpp::IJSON, 192
	202			qpp::QCircuit, 295
dbb	o::internal::IOManipRange<	InputIterator	>,	qpp::QEngine, 309
	205	0		to_string
	o::Timer $<$ T, CLOCK_T $>$ , 35	2		qpp::Dynamic_bitset, 167
States	ouCtatae 240			to_void
	o::States, 340			qpp, 28
statistics	s.n, 399			toc
stats_	ouOFarina 010			qpp::Timer< T, CLOCK_T >, 352
	o::QEngine, 310			TOF
step_typ				qpp::Bit_circuit, 135
	o::QCircuit, 299			qpp::Gates, 184
StepTyp				trace
	o::QCircuit, 274			qpp, 112
storage_	_size			traits.h, 400

```
transpose
                                                             qpp::Gates, 185
     qpp, 113
                                                        z0
tsallis
                                                             qpp::States, 346
     qpp, 113, 114
                                                        z1
TWO
                                                             qpp::States, 346
     qpp::QCircuit, 272
                                                        Zd
Type
                                                             qpp::Gates, 182
     qpp::Codes, 138
                                                        zero
                                                             qpp::States, 342
type
     qpp::make_void< Ts >, 217
type_
     qpp::QCircuit::iterator::value_type_, 362
types.h, 402
uniform
     qpp, 114
     qpp::Dynamic_bitset, 168
value_type
     qpp::Dynamic_bitset, 160
     qpp::QCircuit::iterator, 213
value_type_
     qpp::QCircuit::iterator::value_type_, 360, 361
value_type_qc_
     qpp::QCircuit::iterator::value_type_, 362
var
     qpp, 115
variadic_vector_emplace
     qpp::internal, 125
W
     qpp::States, 345
what
     qpp::exception::Exception, 172
what
     qpp::exception::CustomException, 142
where
     qpp::exception::Exception, 173
Χ
     qpp::Bit_circuit, 135
     qpp::Gates, 185
x0
     qpp::States, 345
х1
     qpp::States, 346
x2contfrac
     qpp, 115
Xd
     qpp::Gates, 182
Υ
     qpp::Gates, 185
y0
     qpp::States, 346
у1
     qpp::States, 346
```

Ζ