Quantum++ for the impatient

Author: Vlad Gheorghiu vgheorgh@gmail.com

Dated: December 3, 2014

Contents

1	Introduction						
2 Installation							
3	Data types, constants and global objects						
	3.1 Data types	. 4					
	3.2 Constants	. 4					
	3.3 Global singleton classes and instances	. 5					
4	Simple examples	5					
	4.1 Gates and states	. 5					
	4.2 Measurements	. 7					
	4.3 Quantum operations	. 8					
	4.4 Input/output	. 9					
5	Brief description of Quantum++ file structure	10					
6	Advanced topics						
	6.1 Exceptions	. 11					
	6.2 Aliasing	. 11					
	6.3 Optimizations	. 11					
	6.4 Extending Quantum++	. 11					
\mathbf{L}	ist of source codes						
	1 Minimal example	. 3					
	2 Gates and states	. 6					
	3 Measurements	. 7					
	4 Quantum operations	. 12					
	5 Input/output	. 13					

1 Introduction

Quantum++ is a C++11 general purpose quantum computing simulator, composed solely of of header files, and uses the Eigen linear algebra library. The simulator defines a large collection of (template) quantum computing related functions and few useful classes. The main data types are complex vectors and complex matrices, as I will describe below. Most functions operate on such vectors/matrices, and always return the result by value. Collection of objects are implemented via the standard library container std::vector<>, specialized accordingly. Ease of use and performance were among the most important design factors.

2 Installation

To get started with Quantum++, first download the Eigen library from http://eigen.tuxfamily.org and unzip it into the home directory¹, as \$HOME/eigen. You can change the name of the directory, but in the current document I will use \$HOME/eigen as the location of Eigen library. Next, download the Quantum++ library from http://vsoftco.github.io/qpp/ and unzip it into the home directory as \$HOME/qpp. Finally, make sure that your compiler supports C++11 and preferably OpenMP. I recommend g++, version 4.8 or later. You are now ready to go!

We next build a simple minimal example to test that the installation was successful. Create a directory called \$HOME/qpp_examples, and inside it create the file ex1.cpp, with the content listed in the Listing 1. A verbatim copy of Listing 1 is also available at \$HOME/qpp/examples/ex1.cpp.

```
// Minimal example
// Source: ./examples/ex1.cpp
#include <qpp.h>

int main()
{
    std::cout << "Hello Quantum++!" << std::endl;
}</pre>
```

Listing 1: Minimal example

Next compile the file using a C++11 compliant compiler such as g++ version 4.8 or later. From inside the directory \$HOME/qpp_examples, type

```
g++ -std=c++11 -isystem $HOME/eigen -I $HOME/qpp/include ex1.cpp -o ex1
```

Your compile command may differ from the above, depending on the name of your C++ compiler and operating system. If everything went fine, then the above command builds the executable ex1 in the directory \$HOME/qpp_examples. To run it, type ./ex1 from inside the directory \$HOME/qpp_examples. The output should look like

Congratulations, everything seems to be working!

 $^{^{1}}$ I implicitly assume from now on that you use a UNIX-based system, although everything should translate into Windows as well, with slight modifications

3 Data types, constants and global objects

All functions, classes and global objects defined by the library lie inside the namespace qpp. To avoid additional typing, I will omit the prefix qpp:: in the rest of this document. I recommend the using directive

using namespace qpp;

in your main .cpp file.

3.1 Data types

The most important data types are defined via typedefs in the header file types.h² (inside the include directory of the Quantum++ source distribution). We list them in Table 1.

cplx	Complex number, alias for std::complex <double></double>
idx	Index (non-negative integer), alias for std::size_t
cmat	Complex dynamic matrices, alias for Eigen::MatrixXcd
dmat	Double dynamic matrices, alias for Eigen::MatrixXd
ket	Complex dynamic column vector, alias for Eigen::VectorXcd
bra	Complex dynamic row vector, alias for Eigen::RowVectorXcd
dyn_mat <scalar></scalar>	Dynamic matrix template alias over the field Scalar, alias for
	Eigen::Matrix <scalar, eigen::dynamic="" eigen::dynamic,=""></scalar,>
dyn_col_vect <scalar></scalar>	Dynamic column vector template alias over the field Scalar, alias for
	Eigen::Matrix <scalar, 1="" eigen::dynamic,=""></scalar,>
dyn_row_vect <scalar></scalar>	Dynamic row vector template alias over the field Scalar, alias for
	Eigen::Matrix <scalar, 1,="" eigen::dynamic=""></scalar,>

Table 1: User-defined data types

3.2 Constants

The important constants are defined in the header file constants.h and are listed in Table 2.

constexpr double pi = 3.1415;	π
constexpr double ee = 2.7182;	e, base of natural logarithms
constexpr idx infty = -1;	Infinity
<pre>constexpr idx maxn = 64;</pre>	Maximum number of allowed qu(d)its (subsystems)
<pre>constexpr double eps = 1e-12;</pre>	Used in comparing floating point values to zero
<pre>constexpr double chop = 1e-10;</pre>	Used in display manipulators to set numbers to zero
constexpr cplx operator""_i	User-defined literal for the imaginary number $i := \sqrt{-1}$
(unsigned long long int x)	
constexpr cplx operator""_i	User-defined literal for the imaginary number $i := \sqrt{-1}$
(unsigned long double int x)	
cplx omega(idx D)	D-th root of unity $e^{2\pi i/D}$

Table 2: User-defined constants

²All necessary Quantum++ header files, together with other important system headers, such as <iostream>, <cmath> etc., are automatically included in qpp.h, hence most of the time you should only include qpp.h in the main .cpp file.

3.3 Global singleton classes and instances

Some useful classes are defined as singletons, are globally available, and are initialized at runtime in the header file qpp.h, before the starting of int main(), as listed in Table 3.

<pre>const Init& init = Init::get_instance();</pre>	Library initialization (welcome messages etc.)
<pre>const Codes& codes = Codes::get_instance();</pre>	Quantum error correcting codes
<pre>const Gates& gt = Gates::get_instance();</pre>	Quantum gates
<pre>const States& st = States::get_instance();</pre>	Quantum states
RandomDevices& rdevs =	Random number generator engines
RandomDevices::get_instance()	

Table 3: Global singleton classes and instances

4 Simple examples

All examples of this section are copied verbatim from the directory ./examples and compiled successfully. Each listing corresponds to a unique example, e.g. Listing 2 corresponds to ./examples/ex2.cpp. For convenience, the location of the source file is also displayed in the first line of each example, as a C++ comment.

The examples are simple and demonstrate the main feature of Quantum++. They cover only a small part of library functions, but enough to get the interested user started. For extensive about all library functions, including various overloads, the user should consult the complete reference located at ./doc/refman.pdf. A more comprehensive (but also more complicated) example, that consists of a collection of quantum information processing routines, is located at ./examples/example.cpp.

4.1 Gates and states

We introduce the main objects used by Quantum++: gates, states and basic operations. Consider the code in Listing 2, which may output

```
>>> Starting Quantum++...
   >>> Wed Dec 3 18:01:56 2014
   The result of applying the bit-flip gate X on |0> is:
5
   1.0000
   The result of applying the gate CNOTab on |10> is:
        0
        0
9
        0
11
   Generating the random one-qubit gate U:
12
   -0.4205 - 0.4362i -0.5660 - 0.5591i
13
   -0.3837 - 0.6969i
                        0.3051 + 0.5234i
14
   The result of applying the Controlled-U gate on |10> is:
15
                   0
16
                   0
   -0.4205 - 0.4362i
18
   -0.3837 - 0.6969i
```

```
// Gates and states
   // Source: ./examples/ex2.cpp
   #include <qpp.h>
   using namespace qpp;
   int main()
   {
        ket psi = st.z0; // |0> state
        cmat U = gt.X;
        ket result = U * psi;
10
11
        std::cout << "The result of applying the bit-flip gate X on |0> is:\n";
12
        std::cout << disp(result) << std::endl;</pre>
13
14
        psi = mket({1, 0}); // |10> state
15
        U = gt.CNOTab; // Controlled-NOT
16
        result = U * psi;
17
18
        std::cout << "The result of applying the gate CNOTab on |10> is:\n";
        std::cout << disp(result) << std::endl;</pre>
20
21
        U = randU(2);
22
        std::cout << "Generating a random one-qubit gate U:\n";
        std::cout << disp(U) << std::endl;</pre>
24
        result = applyCTRL(psi, U, {0}, {1});
26
        std::cout << "The result of applying the Controlled-U gate on |10> is:\n";
27
        std::cout << disp(result) << std::endl;</pre>
28
   }
29
```

Listing 2: Gates and states

```
20
21 >>> Exiting Quantum++...
22 >>> Wed Dec 3 18:01:56 2014
```

In line 4, we bring the namespace qpp into the global namespace.

In line 8 we use the singleton st to declare psi as the zero eigenvector $|0\rangle$ of the Z Pauli operator. In line 9 we assign to the gate U the bit flip gate gt.X, compute the result of the operation $X|0\rangle$ in line 10, and display the result $|1\rangle$ in lines 12 and 13. In line 13 we use the format manipulator disp(), which is especially useful when displaying complex matrices, as it displays the entries of the latter in the form a+bi, in contrast to the form (a,b) used by the C++ standard library. The manipulator also accepts additional parameters that allows e.g. setting to zero numbers smaller than some given value (useful to chop small values), and it is in addition overloaded for standard containers, iterators and C-style arrays.

In line 15 we reassign to psi the state $|10\rangle$ via the function mket(). We could have also used the Eigen insertion operator

```
ket psi(4); // must specify the dimension before insertion of elements via <<
psi << 0, 0, 1, 0;</pre>
```

however the mket() function is more concise. In line 16 we declare a gate U as the Controlled-NOT with control as the first subsystem, and target as the last, using the global singleton gt. In line 17 we declare the

ket result as the result of applying the Controlled-NOT gate to the state $|10\rangle$, i.e. $|11\rangle$. We then display the result of the computation in lines 19 and 20.

Next, in line 22 we generate a random unitary gate via the function randU(), then in line 26 apply the Controlled-U, with control as the first qubit and target as the second qubit, to the state psi. Finally, we display the result in lines 27 and 28.

4.2 Measurements

Let us now complicate things a bit and introduce measurements. Consider the example in Listing 3, which outputs

```
// Measurements
   // Source: ./examples/ex3.cpp
   #include <qpp.h>
   using namespace qpp;
   int main()
6
    {
        ket psi = mket({0, 0});
        cmat U = gt.CNOTab * kron(gt.H, gt.Id2);
        ket result = U * psi; // we have the Bell state (|00>+|11>)/sqrt(2)
10
11
        std::cout << "We just produced the Bell state:\n";</pre>
12
        std::cout << disp(result) << std::endl;</pre>
13
        // apply a bit flip on the second qubit
15
        result = apply(result, gt.X, {1}); // we produced (|01>+|10>)/sqrt(2)
16
        std::cout << "We produced the Bell state:\n";</pre>
17
        std::cout << disp(result) << std::endl;</pre>
18
19
        // measure the first qubit in the X basis
20
        auto m = measure(result, gt.H, {0});
21
        std::cout << "Measurement result: " << std::get<0>(m);
22
        std::cout << std::endl << "Probabilities: ";</pre>
23
        std::cout << disp(std::get<1>(m), ", ") << std::endl;
24
        std::cout << "Resulting states: " << std::endl;</pre>
25
        for (auto && elem : std::get<2>(m))
26
            std::cout << disp(elem) << std::endl << std::endl;</pre>
27
28
```

Listing 3: Measurements

```
10
   0.7071
11
   0.7071
12
         0
   Measurement result: 1
14
   Probabilities: [0.5000, 0.5000]
   Resulting states:
16
   0.5000
              0.5000
   0.5000
              0.5000
18
19
    0.5000
               -0.5000
20
    -0.5000
                0.5000
21
22
23
   >>> Exiting Quantum++...
24
   >>> Wed Dec
                  3 18:01:56 2014
25
```

In line 9, we use the function kron() to create the tensor product (Kronecker product) of the Hadamard gate on the first qubit and identity on the second qubit, then we left-multiply it by the Controlled-NOT gate. In line 10 we compute the result of the operation $CNOT_{ab}(H\otimes I)|00\rangle$, which is the Bell state $(|00\rangle+|11\rangle)/\sqrt{2}$. We display it in lines 12 and 13.

In line 16 we use the function apply() to apply the gate X on the second qubit³ of the previously produced Bell state. The function apply() takes as its third parameter a list of subsystems, and in our case {1} denotes the second subsystem, not the first. The function apply(), as well as many other functions that we will encounter, have a variety of useful overloads, see doc/refman.pdf for a detailed library reference. In lines 17 and 18 we display the newly created Bell state.

In line 21 we use the function measure() to perform a measurement of the first qubit (subsystem {0}) in the X basis. You may be confused by the apparition of gt.H, however this overload of the function measure() takes as its second parameter the measurement basis, specified as the columns of a complex matrix. In our case, the eigenvectors of the X operator are just the columns of the Hadamard matrix. As mentioned before, as all other library functions, measure() returns by value, hence it does not modify its argument. The return of measure is a tuple consisting of the measurement result, the outcome probabilities, and the possible output states. Technically measure() returns a

```
std::tuple<std::size_t, std::vector<double>, std::vector<cmat>>
```

Instead of using this long type definition, we use the new C++11 auto keyword to define the type of the result m of measure(). In lines 22-27 we use the standard std::get<>() function to retrieve each element of the tuple, then display the measurement result, the probabilities and the resulting output states.

4.3 Quantum operations

In Listing 4 we introduce quantum operations: quantum channels, as well as the partial trace and partial transpose operations. The output of this program is

```
>>> Starting Quantum++...
>>> Wed Dec 3 18:01:56 2014

Initial state:
5 0.5000 0 0 0.5000
```

³Quantum++ uses the C/C++ numbering convention, with indexes starting from zero.

```
0
              0
                  0
                             0
6
         0
                  0
                             0
              0
                  0
                       0.5000
   Eigenvalues of the partial transpose of Bell-O state are:
               0.5000
                         0.5000
                                    0.5000
10
   Measurement channel with 2 Kraus operators:
   1.0000
12
         0
              0
        and
14
   0
              0
15
   0
        1.0000
16
   Superoperator matrix of the channel:
17
   1.0000
                             0
              0
                  0
18
                             0
                  0
19
         0
              0
                  0
                             0
20
         0
              0
                  0
                       1.0000
21
                 of the channel:
   Choi matrix
    1.0000
                  0
              0
23
                             0
         0
              0
                  0
         0
              0
                  0
                             0
25
                       1.0000
              0
                  0
                     the measurement channel on the first qubit:
   After applying
27
                             0
   0.5000
              0
                  0
                             0
         0
              0
                  0
29
                             0
         0
              0
                  0
30
              0
                  0
                       0.5000
31
                      tracing down the second subsystem:
   After partially
32
   0.5000
33
              0.5000
34
   Entropy: 1.0000
35
36
   >>> Exiting Quantum++...
37
   >>> Wed Dec
                  3 18:01:56 2014
38
```

The example should by now be self-explanatory.

In line 8 we define the input state **rho** as the projector onto the Bell state $(|00\rangle + |11\rangle)/\sqrt{2}$, then display it in lines 9 and 10.

In lines 13–15 we partially transpose the first qubit, then display the eigenvalues of the resulting matrix rhoTA.

In lines 17–19 we define a quantum channel Ks consisting of two Kraus operators: $|0\rangle\langle 0|$ and $|1\rangle\langle 1|$, then display the latter. Note that Quantum++ uses the std::vector<cmat> container to store the Kraus operators and define a quantum channel.

In lines 21–25 we display the superoperator matrix as well as the Choi matrix of the channel Ks.

Next, in lines 28–30 we apply the channel Ks to the first qubit of the input state rho, then display the output state rhoOut.

In lines 33–35 we take the partial trace of the output state rhoOut, then display the resulting state rhoA. Finally, in lines 38 and 39 we compute the von-Neumann entropy of the resulting state and display it.

4.4 Input/output

In Listing 5 we introduce the input/output functions of Quantum++, as well as the input/output interfacing with MATLAB. The program saves a matrix in both Quantum++ internal format as well as in

MATLAB format, then loads it back and tests that the norm difference between the saved/loaded matrix is zero.

```
>>> Starting Quantum++...
>>> Wed Dec 3 18:01:56 2014

Norm difference load/save: 0.0000
Norm difference MATLAB load/save: 0.0000

>>> Exiting Quantum++...
>>> Wed Dec 3 18:01:56 2014
```

5 Brief description of Quantum++ file structure

A brief description of the Quantum++ file structure is presented below. The directories and their brief descriptions are emphasized using **bold fonts**. The main header file qpp.h is emphasized in red fonts.

./	
doc/ Documentation	1
html/ HTML documentation	1
index.html	е
quick.pdf	е
refman.pdf	
examples/ Usage examples	5
ex*.cppExample source files	\mathbf{s}
include/ Header files	5
MATLAB/MATLAB support	
matlab.h	3
classes/ Class definitions	
codes.hQuantum error correcting codes	s
exception.hExceptions	\mathbf{s}
gates.h Quantum gates	\mathbf{s}
init.hInitialization	1
random_devices.h	\mathbf{s}
states.hQuantum states	\mathbf{s}
timer.h	
experimental/ Experimental/test functions/classes, do not use or modify	
test.h Experimental/test functions/classes	
internal implementation details, do not use/modify	
classes/Internal class definitions	3
iomanip.h	
singleton.h	
util.hInternal utility functions	\mathbf{s}
constants.h	
entanglement.h	
entropies.h Entropy functions	
functions.h	
input_output.h Input/output functions	\mathbf{s}
instruments.h	
number_theory.h	
operations.h	\mathbf{s}

	The second secon	
l	1 11 1	
		Type aliases
_	CMakeLists.txt .	cmake configuration file, builds ./examples/example.cpp
	COPYING	
	README.md	Building instructions
	RELEASE.md	
	VERSION	
	run_OSX_MATLAB .	Script for running with MATLAB support under OS X

6 Advanced topics

- 6.1 Exceptions
- 6.2 Aliasing
- 6.3 Optimizations
- 6.4 Extending Quantum++

```
// Quantum operations
   // Source: ./examples/ex4.cpp
   #include <qpp.h>
   using namespace qpp;
   int main()
        cmat rho = st.pb00; // projector onto the Bell state (|00>+|11>)/sqrt(2)
        std::cout << "Initial state:\n";</pre>
        std::cout << disp(rho) << std::endl;
10
11
        // partial transpose of first subsystem
12
        cmat rhoTA = ptranspose(rho, {0});
13
        std::cout << "Eigenvalues of the partial transpose of Bell-0 state are:\n";
14
        std::cout << disp(transpose(hevals(rhoTA))) << std::endl;</pre>
15
16
        std::cout << "Measurement channel with 2 Kraus operators:\n";</pre>
17
        std::vector<cmat> Ks {st.pz0, st.pz1}; // 2 Kraus operators
18
                                              and \n" << disp(Ks[1]) << std::endl;</pre>
        std::cout << disp(Ks[0]) << "\n
19
20
        std::cout << "Superoperator matrix of the channel:\n";
21
        std::cout << disp(super(Ks)) << std::endl;</pre>
22
23
        std::cout << "Choi matrix of the channel:\n";</pre>
24
        std::cout << disp(choi(Ks)) << std::endl;</pre>
25
        // apply the channel onto the first subsystem
27
        cmat rhoOut = apply(rho, Ks, {0});
28
        std::cout << "After applying the measurement channel on the first qubit:\n";</pre>
29
        std::cout << disp(rhoOut) << std::endl;</pre>
30
31
        // take the partial trace over the second subsystem
32
        cmat rhoA = ptrace(rhoOut, {1});
33
        std::cout << "After partially tracing down the second subsystem:\n";
34
        std::cout << disp(rhoA) << std::endl;</pre>
35
36
        // compute the von-Neumann entropy
37
        double ent = entropy(rhoA);
38
        std::cout << "Entropy: " << ent << std::endl;</pre>
39
   }
40
```

Listing 4: Quantum operations

```
// Input/output
   // Source: ./examples/ex5.cpp
   #include <qpp.h>
   #include <MATLAB/matlab.h>
   using namespace qpp;
   int main()
   {
        // Quantum++ native input/output
        cmat rho = randrho(256); // an 8 qubit density operator
10
        save(rho, "rho.dat"); // save it
11
        cmat loaded_rho = load<cmat>("rho.dat"); // load it back
12
        // display the difference in norm, should be 0
13
        std::cout << "Norm difference load/save: ";</pre>
        std::cout << norm(loaded_rho - rho) << std::endl;</pre>
15
        // Interfacing with MATLAB
17
        saveMATLABmatrix(rho, "rho.mat", "rho", "w");
18
        loaded_rho = loadMATLABmatrix<cmat>("rho.mat",
19
        // display the difference in norm, should be 0
20
        std::cout << "Norm difference MATLAB load/save: ";</pre>
21
        std::cout << norm(loaded_rho - rho) << std::endl;</pre>
22
23
```

Listing 5: Input/output