Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 			 	 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 			 	 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 			 	 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 			 	 11
6	Nam	nespace	Docume	ntat	tion												13
	6.1	qpp Na	amespace	Ref	feren	ice .		 	 	 	 		 			 	 13
		6.1.1	Detailed	Des	script	tion		 	 	 	 		 			 	 26
		6.1.2	Typedef	Doc	ume	ntatio	on .	 	 	 	 		 			 	 26
			6.1.2.1	bi	gint			 	 	 	 		 			 	 26
			6.1.2.2	br	a.			 	 	 	 		 			 	 26
			6.1.2.3	cr	nat			 	 	 	 		 			 	 26
			6.1.2.4	cp	olx .			 	 	 	 		 			 	 26
			6.1.2.5	dr	mat			 	 	 	 		 			 	 27
			6.1.2.6	dy	yn_co	ol_ve	ct .	 	 	 	 		 			 	 27
			6.1.2.7	dy	yn_m	at .		 	 	 	 		 			 	 27
			6.1.2.8	d١	vn ro	W V	ect	 	 	 	 		 			 	 27

ii CONTENTS

	6.1.2.9	idx	. 28
	6.1.2.10	ket	. 28
	6.1.2.11	to_void	. 28
6.1.3	Function	Documentation	. 28
	6.1.3.1	absm()	. 28
	6.1.3.2	abssq() [1/3]	. 29
	6.1.3.3	abssq() [2/3]	. 29
	6.1.3.4	abssq() [3/3]	. 29
	6.1.3.5	adjoint()	. 30
	6.1.3.6	anticomm()	. 30
	6.1.3.7	apply() [1/5]	. 31
	6.1.3.8	apply() [2/5]	. 31
	6.1.3.9	apply() [3/5]	. 32
	6.1.3.10	apply() [4/5]	. 32
	6.1.3.11	apply() [5/5]	. 33
	6.1.3.12	applyCTRL() [1/2]	. 33
	6.1.3.13	applyCTRL() [2/2]	. 34
	6.1.3.14	applyQFT()	. 34
	6.1.3.15	applyTFQ()	. 35
	6.1.3.16	avg()	. 35
	6.1.3.17	bloch2rho()	. 36
	6.1.3.18	choi2kraus()	. 36
	6.1.3.19	choi2super()	. 37
	6.1.3.20	comm()	. 37
	6.1.3.21	complement()	. 38
	6.1.3.22	compperm()	. 38
	6.1.3.23	concurrence()	. 38
	6.1.3.24	conjugate()	. 40
	6.1.3.25	contfrac2x()	. 40
	6.1.3.26	convergents() [1/2]	. 41

CONTENTS

6.1.3.27	convergents() [2/2]	41
6.1.3.28	cor()	42
6.1.3.29	cosm()	42
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	43
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	44
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	45
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	46
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	49
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	51
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	53
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	54

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	56
6.1.3.62	hevects()	57
6.1.3.63	inverse()	57
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	58
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	59
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	60
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	61
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	66
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	67
6.1.3.86	measure() [1/9]	68

CONTENTS

6.1.3.87 measure() [2/9]	8
6.1.3.88 measure() [3/9]	59
6.1.3.89 measure() [4/9]	69
6.1.3.90 measure() [5/9]	70
6.1.3.91 measure() [6/9]	71
6.1.3.92 measure() [7/9]	71
6.1.3.93 measure() [8/9]	72
6.1.3.94 measure() [9/9]	73
6.1.3.95 measure_seq() [1/2]	73
6.1.3.96 measure_seq() [2/2]	74
6.1.3.97 mket() [1/2]	74
6.1.3.98 mket() [2/2]	75
6.1.3.99 modinv()	75
6.1.3.100 modmul()	76
6.1.3.101 modpow()	76
6.1.3.102 mprj() [1/2]	77
6.1.3.103 mprj() [2/2]	77
6.1.3.104 multiidx2n()	78
6.1.3.105 n2multiidx()	78
6.1.3.106 negativity() [1/2]	79
6.1.3.107 negativity() [2/2]	79
6.1.3.108 norm()	30
6.1.3.109 omega()	30
6.1.3.110 operator""" _i()	30
6.1.3.111 powm()	31
6.1.3.112 prj()	31
6.1.3.113 prod() [1/3]	32
6.1.3.114 prod() [2/3]	32
6.1.3.115 prod() [3/3]	32
6.1.3.116 ptrace() [1/2] 8	33

vi

6.1.3.117 ptrace() [2/2]	33
6.1.3.118 ptrace1() [1/2] 8	34
6.1.3.119 ptrace1() [2/2] 8	34
6.1.3.120 ptrace2() [1/2] 8	36
6.1.3.121 ptrace2() [2/2] 8	36
6.1.3.122 ptranspose() [1/2]	37
6.1.3.123 ptranspose() [2/2]	37
6.1.3.124 QFT()	38
6.1.3.125 qmutualinfo() [1/2]	38
6.1.3.126 qmutualinfo() [2/2]	39
6.1.3.127 rand() [1/5]	39
6.1.3.128 rand() [2/5] 9	90
6.1.3.129 rand() [3/5]	90
6.1.3.130 rand() [4/5]	90
6.1.3.131 rand() [5/5] 9	91
6.1.3.132 randH()	91
6.1.3.133 randidx()	93
6.1.3.134 randket()	93
6.1.3.135 randkraus()	94
6.1.3.136 randn() [1/4] 9	94
6.1.3.137 randn() [2/4] 9	94
6.1.3.138 randn() [3/4] 9	95
6.1.3.139 randn() [4/4] 9	95
6.1.3.140 randperm()	96
6.1.3.141 randprime()	96
6.1.3.142 randprob()	97
6.1.3.143 randrho()	97
6.1.3.144 randU()	97
6.1.3.145 randV()	98
6.1.3.146 renyi() [1/2]	98

CONTENTS vii

6.1.3.147 renyi() [2/2]
6.1.3.148 reshape()
6.1.3.149 rho2bloch()
6.1.3.150 rho2pure()
6.1.3.151 save()
6.1.3.152 saveMATLAB() [1/2]
6.1.3.153 saveMATLAB() [2/2] 102
6.1.3.154 schatten()
6.1.3.155 schmidtA() [1/2]
6.1.3.156 schmidtA() [2/2]
6.1.3.157 schmidtB() [1/2]
6.1.3.158 schmidtB() [2/2]
6.1.3.159 schmidtcoeffs() [1/2] 104
6.1.3.160 schmidtcoeffs() [2/2] 105
6.1.3.161 schmidtprobs() [1/2]
6.1.3.162 schmidtprobs() [2/2] 106
6.1.3.163 sigma()
6.1.3.164 sinm()
6.1.3.165 spectralpowm()
6.1.3.166 sqrtm()
6.1.3.167 sum() [1/3]
6.1.3.168 sum() [2/3]
6.1.3.169 sum() [3/3]
6.1.3.170 super2choi()
6.1.3.171 svals()
6.1.3.172 svd()
6.1.3.173 svdU()
6.1.3.174 svdV()
6.1.3.175 syspermute() [1/2]
6.1.3.176 syspermute() [2/2]

viii CONTENTS

		6.1.3.177	7 TFQ()	 112
		6.1.3.178	3 trace()	 113
		6.1.3.179	9 transpose()	 113
		6.1.3.180	O tsallis() [1/2]	 113
		6.1.3.181	1 tsallis() [2/2]	 114
		6.1.3.182	2 uniform()	 114
		6.1.3.183	3 var()	 115
		6.1.3.184	4 x2contfrac()	 115
	6.1.4	Variable	Documentation	 116
		6.1.4.1	chop	 116
		6.1.4.2	ee	 116
		6.1.4.3	eps	 116
		6.1.4.4	idx_infty	 116
		6.1.4.5	infty	 116
		6.1.4.6	maxn	 117
		6.1.4.7	pi	 117
6.2	qpp::ex	ception N	amespace Reference	 117
	6.2.1	Detailed	Description	 118
6.3	qpp::ex	perimenta	al Namespace Reference	 119
	6.3.1	Detailed	Description	 119
6.4	qpp::in	ternal Nan	nespace Reference	 119
	6.4.1	Detailed	Description	 120
	6.4.2	Function	Documentation	 120
		6.4.2.1	check_cvector()	 120
		6.4.2.2	check_dims()	 120
		6.4.2.3	check_dims_match_cvect()	 121
		6.4.2.4	check_dims_match_mat()	 121
		6.4.2.5	check_dims_match_rvect()	 121
		6.4.2.6	check_eq_dims()	 121
		6.4.2.7	check_matching_sizes()	 121

CONTENTS

		6.4.2.8	check_no_duplicates()	 121
		6.4.2.9	check_nonzero_size()	 122
		6.4.2.10	check_perm()	 122
		6.4.2.11	check_qubit_cvector()	 122
		6.4.2.12	check_qubit_matrix()	 122
		6.4.2.13	check_qubit_rvector()	 122
		6.4.2.14	check_qubit_vector()	 122
		6.4.2.15	check_rvector()	 123
		6.4.2.16	check_square_mat()	 123
		6.4.2.17	check_subsys_match_dims()	 123
		6.4.2.18	check_vector()	 123
		6.4.2.19	dirsum2()	 123
		6.4.2.20	get_dim_subsys()	 123
		6.4.2.21	get_num_subsys()	 124
		6.4.2.22	kron2()	 124
		6.4.2.23	multiidx2n()	 124
		6.4.2.24	n2multiidx()	 124
		6.4.2.25	variadic_vector_emplace() [1/2]	 124
		6.4.2.26	variadic_vector_emplace() [2/2]	 124
6.5	qpp::lit	erals Nam	nespace Reference	 125
	6.5.1	Function	Documentation	 125
		6.5.1.1	operator""""_bra()	 125
		6.5.1.2	operator""""_i()	 125
		6.5.1.3	operator""""_ket()	 126
		6.5.1.4	operator"""" _prj()	 126

CONTENTS

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	xception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	xception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()
		7.12.4.9 index_()

CONTENTS xiii

		7.12.4.10 none()	161
		7.12.4.11 offset_()	161
		7.12.4.12 operator"!=()	162
		7.12.4.13 operator-()	162
		7.12.4.14 operator==()	162
		7.12.4.15 rand() [1/2]	164
		7.12.4.16 rand() [2/2] 1	164
		7.12.4.17 reset() [1/2]	165
		7.12.4.18 reset() [2/2]	165
		7.12.4.19 set() [1/2]	165
		7.12.4.20 set() [2/2]	166
		7.12.4.21 size()	166
		7.12.4.22 storage_size()	166
		7.12.4.23 to_string()	166
	7.12.5	Member Data Documentation	167
		7.12.5.1 N	167
		7.12.5.2 storage_size	167
		7.12.5.3 v	167
7.13	qpp::ex	cception::Exception Class Reference	168
	7.13.1	Detailed Description	169
	7.13.2	Constructor & Destructor Documentation	170
		7.13.2.1 Exception()	170
	7.13.3	Member Function Documentation	170
		7.13.3.1 type_description()	170
		7.13.3.2 what()	171
	7.13.4	Member Data Documentation	171
		7.13.4.1 msg	171
		7.13.4.2 where	171
7.14	qpp::Bi	t_circuit::Gate_count Struct Reference	171
	7.14.1	Member Data Documentation	171

xiv CONTENTS

	7.14.1.1 CNOT	172
	7.14.1.2 FRED	172
	7.14.1.3 NOT	172
	7.14.1.4 SWAP	172
	7.14.1.5 TOF	172
	7.14.1.6 X	172
7.15 qpp::Ga	ates Class Reference	173
7.15.1	Detailed Description	175
7.15.2	Constructor & Destructor Documentation	175
	7.15.2.1 Gates()	175
	7.15.2.2 ~Gates()	175
7.15.3	Member Function Documentation	176
	7.15.3.1 CTRL()	176
	7.15.3.2 expandout() [1/3]	176
	7.15.3.3 expandout() [2/3]	177
	7.15.3.4 expandout() [3/3]	178
	7.15.3.5 Fd()	178
	7.15.3.6 get_name()	179
	7.15.3.7 ld()	179
	7.15.3.8 MODMUL()	179
	7.15.3.9 Rn()	180
	7.15.3.10 RX()	180
	7.15.3.11 RY()	181
	7.15.3.12 RZ()	181
	7.15.3.13 SWAPd()	181
	7.15.3.14 Xd()	183
	7.15.3.15 Zd()	183
7.15.4	Friends And Related Function Documentation	184
	7.15.4.1 internal::Singleton < const Gates >	184
7.15.5	Member Data Documentation	184

CONTENTS xv

		7.15.5.1 CNOT
		7.15.5.2 CNOTba
		7.15.5.3 CZ
		7.15.5.4 FRED
		7.15.5.5 H
		7.15.5.6 ld2
		7.15.5.7 S
		7.15.5.8 SWAP
		7.15.5.9 T
		7.15.5.10 TOF
		7.15.5.11 X
		7.15.5.12 Y
		7.15.5.13 Z
7.16	qpp::ex	perimental::QCircuitDescription::GateStep Struct Reference
	7.16.1	Detailed Description
	7.16.2	Constructor & Destructor Documentation
		7.16.2.1 GateStep() [1/2]
		7.16.2.2 GateStep() [2/2]
	7.16.3	Member Data Documentation
		7.16.3.1 ctrl
		7.16.3.2 gate
		7.16.3.3 gate_type
		7.16.3.4 name
		7.16.3.5 step_no
		7.16.3.6 target
7.17	qpp::ID	isplay Class Reference
	7.17.1	Detailed Description
	7.17.2	Constructor & Destructor Documentation
		7.17.2.1 IDisplay() [1/3]
		7.17.2.2 IDisplay() [2/3]

xvi CONTENTS

		7.17.2.3 IDisplay() [3/3]	191
		7.17.2.4 ~IDisplay()	191
	7.17.3	Member Function Documentation	191
		7.17.3.1 display()	191
		7.17.3.2 operator=() [1/2]	191
		7.17.3.3 operator=() [2/2]	192
	7.17.4	Friends And Related Function Documentation	192
		7.17.4.1 operator<<	192
7.18	qpp::Ini	it Class Reference	192
	7.18.1	Detailed Description	193
	7.18.2	Constructor & Destructor Documentation	193
		7.18.2.1 Init()	193
		7.18.2.2 ~Init()	194
	7.18.3	Friends And Related Function Documentation	194
		7.18.3.1 internal::Singleton < const Init >	194
7.19	qpp::int	ternal::IOManipEigen Class Reference	194
	7.19.1	Constructor & Destructor Documentation	195
		7.19.1.1 IOManipEigen() [1/2]	195
		7.19.1.2 IOManipEigen() [2/2]	195
	7.19.2	Member Function Documentation	195
		7.19.2.1 display()	195
	7.19.3	Member Data Documentation	196
		7.19.3.1 A	196
		7.19.3.2 chop	196
7.20	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	196
	7.20.1	Constructor & Destructor Documentation	197
		7.20.1.1 IOManipPointer() [1/2]	198
		7.20.1.2 IOManipPointer() [2/2]	198
	7.20.2	Member Function Documentation	198
		7.20.2.1 display()	198

CONTENTS xvii

		7.20.2.2 operator=()	198
	7.20.3	Member Data Documentation	198
		7.20.3.1 end	199
		7.20.3.2 N	199
		7.20.3.3 p	199
		7.20.3.4 separator	199
		7.20.3.5 start	199
7.21	qpp::int	ternal::IOManipRange < InputIterator > Class Template Reference	200
	7.21.1	Constructor & Destructor Documentation	201
		7.21.1.1 IOManipRange() [1/2]	201
		7.21.1.2 IOManipRange() [2/2]	201
	7.21.2	Member Function Documentation	201
		7.21.2.1 display()	201
		7.21.2.2 operator=()	202
	7.21.3	Member Data Documentation	202
		7.21.3.1 end	202
		7.21.3.2 first	202
		7.21.3.3 last	202
		7.21.3.4 separator	202
		7.21.3.5 start	202
7.22	qpp::is_	_complex< T > Struct Template Reference	203
	7.22.1	Detailed Description	203
7.23	qpp::is_	_complex< std::complex< T > > Struct Template Reference	204
	7.23.1	Detailed Description	204
7.24	qpp::is_	_iterable < T, typename > Struct Template Reference	205
	7.24.1	Detailed Description	205
7.25		_iterable $<$ T, to_void $<$ decltype(std::declval $<$ T $>$ ().begin()), decltype(std::declval $<$ T d()), typename T::value_type $>$ $>$ Struct Template Reference	206
	7.25.1	Detailed Description	207
7.26	qpp::is_	_matrix_expression< Derived > Struct Template Reference	207
	7.26.1	Detailed Description	208

xviii CONTENTS

7.27	qpp::ma	ake_void< Ts > Struct Template Reference	:08
	7.27.1	Detailed Description	208
	7.27.2	Member Typedef Documentation	208
		7.27.2.1 type	:08
7.28	qpp::ex	cception::MatrixMismatchSubsys Class Reference	:09
	7.28.1	Detailed Description	10
	7.28.2	Member Function Documentation	10
		7.28.2.1 Exception()	10
		7.28.2.2 type_description()	10
7.29	qpp::ex	cception::MatrixNotCvector Class Reference	!11
	7.29.1	Detailed Description	12
	7.29.2	Member Function Documentation	12
		7.29.2.1 Exception()	12
		7.29.2.2 type_description()	12
7.30	qpp::ex	cception::MatrixNotRvector Class Reference	13
	7.30.1	Detailed Description	14
	7.30.2	Member Function Documentation	14
		7.30.2.1 Exception()	14
		7.30.2.2 type_description()	14
7.31	qpp::ex	cception::MatrixNotSquare Class Reference	15
	7.31.1	Detailed Description	16
	7.31.2	Member Function Documentation	16
		7.31.2.1 Exception()	16
		7.31.2.2 type_description()	16
7.32	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	17
	7.32.1	Detailed Description	18
	7.32.2	Member Function Documentation	18
		7.32.2.1 Exception()	18
		7.32.2.2 type_description()	18
7.33	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	19

CONTENTS xix

	7.33.1	Detailed Description	220
	7.33.2	Member Function Documentation	220
		7.33.2.1 Exception()	220
		7.33.2.2 type_description()	220
7.34	qpp::ex	ception::MatrixNotSquareNorVector Class Reference	221
	7.34.1	Detailed Description	222
	7.34.2	Member Function Documentation	222
		7.34.2.1 Exception()	222
		7.34.2.2 type_description()	222
7.35	qpp::ex	ception::MatrixNotVector Class Reference	223
	7.35.1	Detailed Description	224
	7.35.2	Member Function Documentation	224
		7.35.2.1 Exception()	224
		7.35.2.2 type_description()	224
7.36	qpp::ex	perimental::QCircuitDescription::MeasureStep Struct Reference	225
	7.36.1	Detailed Description	225
	7.36.2	Constructor & Destructor Documentation	226
		7.36.2.1 MeasureStep() [1/2]	226
		7.36.2.2 MeasureStep() [2/2]	226
	7.36.3	Member Data Documentation	226
		7.36.3.1 c_reg	226
		7.36.3.2 mats	227
		7.36.3.3 measurement_type	227
		7.36.3.4 name	227
		7.36.3.5 step_no	227
		7.36.3.6 target	227
7.37	qpp::ex	ception::NoCodeword Class Reference	228
	7.37.1	Detailed Description	229
	7.37.2	Member Function Documentation	229
		7.37.2.1 Exception()	229

CONTENTS

		7.37.2.2	typ	e_des	cripti	ion()				 	 		 	 		 	229
7.38	qpp::ex	ception::N	NotB	ipartite	Cla	ss R	efere	nce		 	 		 	 		 	230
	7.38.1	Detailed I	Des	cription	ı .					 	 		 	 		 	231
	7.38.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	231
		7.38.2.1	Ex	ception	า() .					 	 		 	 		 	231
		7.38.2.2	typ	e_des	cripti	i <mark>ion(</mark>)				 	 		 	 		 	231
7.39	qpp::ex	ception::N	NotIr	npleme	entec	d Cla	iss Ro	efere	ence	 	 		 	 		 	232
	7.39.1	Detailed I	Des	cription	ı .					 	 		 	 		 	233
	7.39.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	233
		7.39.2.1	Ex	ception	า() .					 	 		 	 		 	233
		7.39.2.2	typ	e_des	cripti	iion()				 	 		 	 		 	233
7.40	qpp::ex	ception::N	NotC	ubitCv	ecto	r Cla	iss R	efere	ence	 	 		 	 		 	234
	7.40.1	Detailed I	Des	cription	ı .					 	 		 	 		 	235
	7.40.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	235
		7.40.2.1	Ex	ceptior	า() .					 	 		 	 		 	235
		7.40.2.2	typ	e_des	cripti	i <mark>ion(</mark>)				 	 		 	 		 	235
7.41	qpp::ex	ception::N	NotC	ubitMa	ıtrix (Class	s Ref	feren	ce .	 	 		 	 		 	236
	7.41.1	Detailed I	Des	cription	ı .					 	 		 	 		 	237
	7.41.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	237
		7.41.2.1	Ex	ception	า() .					 	 		 	 		 	237
		7.41.2.2	typ	e_des	cripti	ion()				 	 		 	 		 	237
7.42	qpp::ex	ception::N	NotC	ubitRv	ecto	r Cla	iss R	efere	ence	 	 		 	 		 	238
	7.42.1	Detailed I	Des	criptior	ı .					 	 		 	 		 	239
	7.42.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	239
		7.42.2.1	Ex	ceptior	า() .					 	 		 	 		 	239
		7.42.2.2	typ	e_des	cripti	tion()				 	 		 	 		 	239
7.43	qpp::ex	ception::N	VotC	ubitSu	bsys	s Cla	ss Re	efere	nce	 	 		 	 		 	240
	7.43.1	Detailed I	Des	criptior	ı .					 	 		 	 		 	241
	7.43.2	Member F	Fun	ction D	ocur	ment	tation	١.		 	 		 	 		 	241
		7.43.2.1	Ex	ceptior	า() .					 	 		 	 		 	241

CONTENTS xxi

		7.43.2.2	type_descrip	tion()			 	٠.	 	 	 	241
7.44	qpp::ex	ception::N	lotQubitVector	Class Refe	erence .		 		 	 	 	242
	7.44.1	Detailed	Description .				 		 	 	 	243
	7.44.2	Member	Function Docu	mentation			 		 	 	 	243
		7.44.2.1	Exception() .				 		 	 	 	243
		7.44.2.2	type_descrip	tion()			 		 	 	 	243
7.45	qpp::ex	ception::C	outOfRange Cl	ass Referer	nce		 		 	 	 	244
	7.45.1	Detailed	Description .				 		 	 	 	245
	7.45.2	Member	Function Docu	mentation			 		 	 	 	245
		7.45.2.1	Exception() .				 		 	 	 	245
		7.45.2.2	type_descrip	tion()			 		 	 	 	245
7.46	qpp::ex	ception::P	ermInvalid Cla	ss Referen	ce		 		 	 	 	246
	7.46.1	Detailed	Description .				 		 	 	 	247
	7.46.2	Member	Function Docu	mentation			 		 	 	 	247
		7.46.2.1	Exception() .				 		 	 	 	247
		7.46.2.2	type_descrip	tion()			 		 	 	 	247
7.47	qpp::ex	ception::P	ermMismatchI	Dims Class	Referen	ce	 		 	 	 	248
	7.47.1	Detailed	Description .				 		 	 	 	249
	7.47.2	Member	Function Docu	mentation			 		 	 	 	249
		7.47.2.1	Exception() .				 		 	 	 	249
		7.47.2.2	type_descrip	tion()			 		 	 	 	249
7.48	qpp::ex	perimenta	l::QCircuit Cla	ss Referenc	ce		 		 	 	 	250
	7.48.1	Construc	tor & Destructo	or Documer	ntation .		 		 	 	 	251
		7.48.1.1	QCircuit()				 		 	 	 	252
	7.48.2	Member	Function Docu	mentation			 		 	 	 	252
		7.48.2.1	display()				 		 	 	 	252
		7.48.2.2	get_circuit_d	escription()			 		 	 	 	252
		7.48.2.3	get_dit()				 		 	 	 	253
		7.48.2.4	get_dits()				 		 	 	 	253
		7.48.2.5	get_ip()				 		 	 	 	253

xxii CONTENTS

		7.48.2.6 get_m_ip()	53
		7.48.2.7 get_measured() [1/2]	53
		7.48.2.8 get_measured() [2/2]	54
		7.48.2.9 get_not_measured()	54
		7.48.2.10 get_probs()	54
		7.48.2.11 get_psi()	55
		7.48.2.12 get_q_ip()	55
		7.48.2.13 get_relative_pos_()	55
		7.48.2.14 reset()	55
		7.48.2.15 run()	56
		7.48.2.16 set_dit()	56
		7.48.2.17 set_measured_()	56
	7.48.3	Member Data Documentation	56
		7.48.3.1 dits	57
		7.48.3.2 ip	57
		7.48.3.3 m_ip	57
		7.48.3.4 probs	57
		7.48.3.5 psi	57
		7.48.3.6 q_ip	57
		7.48.3.7 qcd	58
		7.48.3.8 subsys	58
7.49	qpp::Q0	Circuit Class Reference	58
	7.49.1	Detailed Description	58
7.50	qpp::ex	perimental::QCircuitDescription Class Reference	59
	7.50.1	Member Enumeration Documentation	32
		7.50.1.1 GateType	32
		7.50.1.2 MeasureType	33
	7.50.2	Constructor & Destructor Documentation	33
		7.50.2.1 QCircuitDescription()	33
	7.50.3	Member Function Documentation	33

CONTENTS xxiii

7.50.3.1 cCTRL() [1/4]
7.50.3.3 cCTRL() [3/4]
7.50.3.4 cCTRL() [4/4]
7.50.3.5 cCTRL_custom()
7.50.3.6 CTRL() [1/4]
7.50.3.7 CTRL() [2/4]
7.50.3.8 CTRL() [3/4]
7.50.3.9 CTRL() [4/4]
7.50.3.10 CTRL_custom()
7.50.3.11 display()
7.50.3.12 gate() [1/3]
7.50.3.13 gate() [2/3]
7.50.3.14 gate() [3/3]
7.50.3.15 gate_custom()
7.50.3.16 gate_fan() [1/2]
7.50.3.17 gate_fan() [2/2]
7.50.3.18 get_d()
7.50.3.19 get_gate_count()
7.50.3.20 get_gates()
7.50.3.21 get_measured() [1/2]
7.50.3.22 get_measured() [2/2]
7.50.3.23 get_measurement_count()
7.50.3.24 get_measurement_steps()
7.50.3.25 get_measurements()
7.50.3.26 get_name()
7.50.3.27 get_nc()
7.50.3.28 get_non_measured()
7.50.3.29 get_nq()
7.50.3.30 get_total_count()

xxiv CONTENTS

		7.50.3.31 measureV() [1/2]	<u>?</u> 74
		7.50.3.32 measureV() [2/2]	275
		7.50.3.33 measureZ()	275
		7.50.3.34 QFT()	276
		7.50.3.35 TFQ()	276
	7.50.4	Friends And Related Function Documentation	276
		7.50.4.1 operator << [1/4]	277
		7.50.4.2 operator << [2/4]	277
		7.50.4.3 operator << [3/4]	277
		7.50.4.4 operator<< [4/4]	278
	7.50.5	Member Data Documentation	278
		7.50.5.1 d	278
		7.50.5.2 gates	278
		7.50.5.3 measured	278
		7.50.5.4 measurement_steps	279
		7.50.5.5 measurements	279
		7.50.5.6 name	279
		7.50.5.7 nc	279
		7.50.5.8 nq	279
		7.50.5.9 step_cnt	279
7.51	qpp::Q0	CircuitDescription Class Reference	280
	7.51.1	Detailed Description	280
7.52	qpp::ex	ception::QuditAlreadyMeasured Class Reference	280
	7.52.1	Detailed Description	281
	7.52.2	Member Function Documentation	281
		7.52.2.1 Exception()	281
		7.52.2.2 type_description()	282
7.53	qpp::Ra	andomDevices Class Reference	282
	7.53.1	Detailed Description	284
	7.53.2	Constructor & Destructor Documentation	284

CONTENTS xxv

		7.53.2.1 F	andomDevices()			 	 	 	284
		7.53.2.2	RandomDevices() .			 	 	 	284
	7.53.3	Member Fu	nction Documentation			 	 	 	284
		7.53.3.1	et_prng()			 	 	 	284
		7.53.3.2 le	oad()			 	 	 	284
		7.53.3.3 s	ave()			 	 	 	285
	7.53.4	Friends And	d Related Function Doo	cumentation		 	 	 	285
		7.53.4.1 i	nternal::Singleton< Ra	ndomDevices	s >	 	 	 	285
	7.53.5	Member Da	ta Documentation			 	 	 	285
		7.53.5.1 p	rng			 	 	 	285
		7.53.5.2 r	<u>d_</u>			 	 	 	286
7.54	qpp::int	ernal::Single	eton< T > Class Temp	late Referenc	e	 	 	 	286
	7.54.1	Detailed De	escription			 	 	 	286
	7.54.2	Constructo	& Destructor Docume	ntation		 	 	 	287
		7.54.2.1	ingleton() [1/2]			 	 	 	287
		7.54.2.2	ingleton() [2/2]			 	 	 	287
		7.54.2.3	Singleton()			 	 	 	287
	7.54.3	Member Fu	nction Documentation			 	 	 	287
		7.54.3.1	et_instance()			 	 	 	287
		7.54.3.2	et_thread_local_instan	nce()		 	 	 	287
		7.54.3.3	perator=()			 	 	 	288
7.55	qpp::ex	ception::Siz	eMismatch Class Refer	rence		 	 	 	288
	7.55.1	Detailed De	escription			 	 	 	289
	7.55.2	Member Fu	nction Documentation			 	 	 	289
		7.55.2.1 E	exception()			 	 	 	289
		7.55.2.2 t	vpe_description()			 	 	 	290
7.56	qpp::St	ates Class F	Reference			 	 	 	290
	7.56.1	Detailed De	escription			 	 	 	292
	7.56.2	Constructo	& Destructor Docume	ntation		 	 	 	293
		7.56.2.1	tates()			 	 	 	293

xxvi CONTENTS

	7.56.2.2	\sim State	es()							 		 		 			293
7.56.3	Member Fi	unctio	n Doc	umei	ntatio	on				 		 		 			293
	7.56.3.1 j	jn() .								 		 		 			293
	7.56.3.2	mes()								 		 		 			293
	7.56.3.3	minus	()							 		 		 			294
	7.56.3.4	one()								 		 		 			294
	7.56.3.5	plus()								 		 		 			295
	7.56.3.6	zero()								 		 		 			295
7.56.4	Friends An	nd Rela	ated F	unct	ion [Docu	ıme	ntati	on	 		 		 			295
	7.56.4.1 i	interna	al::Sin	gleto	n<	cons	st St	ates	s >	 		 		 			295
7.56.5	Member D	ata Do	ocume	entati	on .					 		 		 			295
	7.56.5.1 I	b00 .								 		 		 			296
	7.56.5.2	b01 .								 		 		 			296
	7.56.5.3	b10 .								 		 		 			296
	7.56.5.4	b11 .								 		 		 			296
	7.56.5.5	GHZ								 		 		 			296
	7.56.5.6	pb00								 		 		 			296
	7.56.5.7	pb01								 		 		 			297
	7.56.5.8	pb10								 		 		 			297
	7.56.5.9	pb11								 		 		 			297
	7.56.5.10	pGHZ								 		 		 			297
	7.56.5.11	pW .								 		 		 			297
	7.56.5.12	px0 .								 		 		 			297
	7.56.5.13	px1 .								 		 		 			298
	7.56.5.14	py0 .								 		 		 			298
	7.56.5.15	py1 .								 		 		 			298
	7.56.5.16	pz0 .								 		 		 			298
	7.56.5.17	pz1 .								 		 		 			298
	7.56.5.18	w								 		 		 			298
	7.56.5.19	х 0 .								 		 		 			299

CONTENTS xxvii

		7.56.5.20 x1	299
		7.56.5.21 y0	299
		7.56.5.22 y1	299
		7.56.5.23 z0	299
		7.56.5.24 z1	299
7.57	qpp::ex	ception::SubsysMismatchDims Class Reference	300
	7.57.1	Detailed Description	301
	7.57.2	Member Function Documentation	301
		7.57.2.1 Exception()	301
		7.57.2.2 type_description()	301
7.58	qpp::Ti	mer< T, CLOCK_T > Class Template Reference	302
	7.58.1	Detailed Description	303
	7.58.2	Constructor & Destructor Documentation	303
		7.58.2.1 Timer() [1/3]	303
		7.58.2.2 Timer() [2/3]	304
		7.58.2.3 Timer() [3/3]	304
		7.58.2.4 ~Timer()	304
	7.58.3	Member Function Documentation	304
		7.58.3.1 display()	304
		7.58.3.2 get_duration()	305
		7.58.3.3 operator=() [1/2]	305
		7.58.3.4 operator=() [2/2]	305
		7.58.3.5 tic()	306
		7.58.3.6 tics()	306
		7.58.3.7 toc()	306
	7.58.4	Member Data Documentation	306
		7.58.4.1 end	306
		7.58.4.2 start	307
7.59	qpp::ex	ception::TypeMismatch Class Reference	307
	7.59.1	Detailed Description	308

xxviii CONTENTS

		7.59.2	Member Function Documentation	80
			7.59.2.1 Exception()	80
			7.59.2.2 type_description()	09
	7.60	qpp::ex	ception::UndefinedType Class Reference	09
		7.60.1	Detailed Description	10
		7.60.2	Member Function Documentation	10
			7.60.2.1 Exception()	10
			7.60.2.2 type_description()	11
	7.61	qpp::ex	ception::Unknown Class Reference	11
		7.61.1	Detailed Description	12
		7.61.2	Member Function Documentation	12
			7.61.2.1 Exception()	12
			7.61.2.2 type_description()	13
	7.62	qpp::ex	ception::ZeroSize Class Reference	13
		7.62.1	Detailed Description	14
		7.62.2	Member Function Documentation	14
			7.62.2.1 Exception()	14
			7.62.2.2 type_description()	15
8	File I	Docume	entation 3	17
	8.1	classes	/codes.h File Reference	17
		8.1.1	Detailed Description	17
	8.2	classes	•	18
		8.2.1	Detailed Description	20
	8.3	classes	/gates.h File Reference	20
		8.3.1	Detailed Description	20
	8.4	classes	/idisplay.h File Reference	21
		8.4.1		21
	8.5	classes	•	21
		8.5.1		22
	8.6	classes	/random_devices.h	22

CONTENTS xxix

	8.6.1	Detailed Description		 	322
8.7	classes	s/reversible.h File Reference		 	323
	8.7.1	Detailed Description		 	323
8.8	classes	s/states.h File Reference		 	323
	8.8.1	Detailed Description		 	324
8.9	classes	s/timer.h File Reference		 	324
	8.9.1	Detailed Description		 	325
8.10	constan	nts.h File Reference		 	325
	8.10.1	Detailed Description		 	326
8.11	entangl	lement.h File Reference		 	326
	8.11.1	Detailed Description		 	328
8.12	entropie	ies.h File Reference		 	328
	8.12.1	Detailed Description		 	329
8.13	experim	mental/experimental.h File Reference		 	329
	8.13.1	Detailed Description		 	329
8.14	function	ns.h File Reference		 	329
	8.14.1	Detailed Description		 	334
8.15	input_o	output.h File Reference		 	334
	8.15.1	Detailed Description		 	335
8.16	instrum	nents.h File Reference		 	335
	8.16.1	Detailed Description		 	336
8.17	internal	I/classes/iomanip.h File Reference		 	336
	8.17.1	Detailed Description		 	337
8.18	internal	Il/classes/singleton.h File Reference		 	337
	8.18.1	Detailed Description		 	338
8.19	internal	ıl/util.h File Reference		 	338
	8.19.1	Detailed Description		 	339
8.20	MATLA	AB/matlab.h File Reference		 	340
	8.20.1	Detailed Description		 	340
8.21	number	er_theory.h File Reference		 	340

CONTENTS

	8.21.1 Detailed Description	342
8.22	operations.h File Reference	342
	8.22.1 Detailed Description	344
8.23	qpp.h File Reference	344
	8.23.1 Detailed Description	345
	8.23.2 Macro Definition Documentation	346
	8.23.2.1 QPP_UNUSED	346
8.24	random.h File Reference	346
	8.24.1 Detailed Description	347
8.25	statistics.h File Reference	347
	8.25.1 Detailed Description	349
8.26	traits.h File Reference	349
	8.26.1 Detailed Description	350
8.27	types.h File Reference	350
	8.27.1 Detailed Description	351
8.28	/Users/vlad/qpp/README.md File Reference	351
Index		353

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
qpp::exception::SubsysMismatchDims
gpp::exception::TypeMismatch

6 Hierarchical Index

qpp::exception::UndefinedType
qpp::exception::Unknown
qpp::exception::ZeroSize
false_type
qpp::is_complex < T >
qpp::is_iterable < T, typename >
qpp::Bit_circuit::Gate_count
qpp::experimental::QCircuitDescription::GateStep
qpp::IDisplay
qpp::Dynamic_bitset
qpp::Bit_circuit
app::experimental::QCircuit
app::experimental::QCircuitDescription
qpp::internal::IOManipEigen
qpp::internal::IOManipPointer< PointerType >
qpp::internal::IOManipRange < InputIterator >
qpp::Timer< T, CLOCK_T >
is_base_of
qpp::is_matrix_expression< Derived >
qpp::make_void < Ts >
qpp::experimental::QCircuitDescription::MeasureStep
qpp::QCircuit
qpp::QCircuitDescription
$qpp::internal::Singleton < T > \dots \dots$
qpp::internal::Singleton < const Codes >
qpp::Codes
qpp::internal::Singleton < const Gates >
qpp::Gates
qpp::internal::Singleton< const Init >
qpp::Init
qpp::internal::Singleton < const States >
qpp::States
qpp::internal::Singleton< RandomDevices >
qpp::RandomDevices
true_type
qpp::is_complex < std::complex < T >>
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T
>().end()), typename T::value type >>

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
::bitset <n>)</n>	155
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	168
qpp::Bit_circuit::Gate_count	171
qpp::Gates	
Const Singleton class that implements most commonly used gates	173
qpp::experimental::QCircuitDescription::GateStep	
One step consisting only of gates/operators in the circuit	186
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
189	
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	192

8 Class Index

qpp::internal::IOManipEigen	194
qpp::internal::IOManipPointer< PointerType >	196
qpp::internal::IOManipRange < InputIterator >	200
qpp::is complex< T >	
Checks whether the type is a complex type	203
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	204
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container	205
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), ty	
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	rpename 1value_type
iterable containers	206
qpp::is_matrix_expression< Derived >	200
Checks whether the type is an Eigen matrix expression	207
	207
<pre>qpp::make_void < Ts > Helper for qpp::to_void <> alias template</pre>	000
	200
qpp::exception::MatrixMismatchSubsys	000
Matrix mismatch subsystems exception	209
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	211
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	213
qpp::exception::MatrixNotSquare	
Matrix is not square exception	215
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	217
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	219
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	221
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	223
qpp::experimental::QCircuitDescription::MeasureStep	
One step consisting only of measurements in the circuit	225
qpp::exception::NoCodeword	
Codeword does not exist exception	228
qpp::exception::NotBipartite	220
Not bi-partite exception	220
	230
qpp::exception::NotImplemented	000
Code not yet implemented	232
qpp::exception::NotQubitCvector	004
Column vector is not 2 x 1 exception	234
qpp::exception::NotQubitMatrix	000
Matrix is not 2 x 2 exception	236
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	238
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	240
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	242
qpp::exception::OutOfRange	
Argument out of range exception	244
qpp::exception::PermInvalid	
Invalid permutation exception	246
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	248
qpp::experimental::QCircuit	

4.1 Class List

qpp::QCircuit	
Quantum circuit simulator	258
qpp::experimental::QCircuitDescription	259
qpp::QCircuitDescription	
Quantum circuit description class	280
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	280
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	282
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)	
qpp::exception::SizeMismatch	
Size mismatch exception	288
qpp::States	
Const Singleton class that implements most commonly used states	290
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	300
qpp::Timer< T, CLOCK_T >	
Chronometer	302
qpp::exception::TypeMismatch	
Type mismatch exception	307
qpp::exception::UndefinedType	
Not defined for this type exception	309
qpp::exception::Unknown	
Unknown exception	311
qpp::exception::ZeroSize	
Object has zero size exception	313

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	325
entanglement.h	
Entanglement functions	326
entropies.h	
Entropy functions	328
functions.h	
Generic quantum computing functions	329
input_output.h	
	334
instruments.h	
	335
number_theory.h	
,,	340
operations.h	
	342
qpp.h	
•	344
random.h	
	346
statistics.h	247
	347
traits.h	240
71	349
types.h	350
Type aliases	300
	317
classes/exception.h	317
•	318
classes/gates.h	010
	320
classes/idisplay.h) <u>_</u> U
	321
classes/init.h	ا عر
	321

12 File Index

classes/random_devices.h	
Random devices	 322
classes/reversible.h	
Support for classical reversible circuits	 323
classes/states.h	
Quantum states	 323
classes/timer.h	
Timing	 324
experimental/experimental.h	
Experimental/test functions/classes	 329
internal/util.h	
Internal utility functions	 338
internal/classes/iomanip.h	
Input/output manipulators	 336
internal/classes/singleton.h	
Singleton pattern via CRTP	 337
MATLAB/matlab.h	
Input/output interfacing with MATLAB	 340

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

 $\textit{Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset < N >) \\$

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class Init

const Singleton class that performs additional initializations/cleanups

struct is_complex

Checks whether the type is a complex type.

struct is complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct \ is_iterable < T, \ to_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ typename \ T::value_type(std::declval < T > ().end()), \ typename \ T::value_typename \ T::value_t$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

· struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make_void

Helper for qpp::to_void<> alias template.

class QCircuit

Quantum circuit simulator.

· class QCircuitDescription

Quantum circuit description class.

class RandomDevices

Singleton class that manages the source of randomness in the library.

class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

• template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Functions

```
    constexpr cplx operator"" _i (long double x) noexcept

      User-defined literal for complex i = \sqrt{-1} (real overload)

    cplx omega (idx D)

      D-th root of unity.
• template<typename Derived >
  dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
  &dims)
     Schmidt coefficients of the bi-partite pure state A.
• template<typename Derived >
  dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.

    template<typename Derived >

  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
  &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
template<typename Derived >
  \label{lem:double entanglement} \mbox{double entanglement (const Eigen::MatrixBase< Derived > \&A, const std::vector< idx > \&dims)}
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
ullet template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.
```

```
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
     Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adioint.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase < Derived > &A)
      Determinant.
• template<typename Derived >
  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.
template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase < Derived > &A)
```

Element-wise product of A.

```
• template<typename Derived >
  double norm (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
template<typename Derived >
  \label{eq:const_equal} \mbox{dyn\_col\_vect} < \mbox{cplx} > \mbox{evals} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A})
      Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
      Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
      Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
      Right singular vectors.

    template<typename Derived >

  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
      Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
      Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
```

Matrix cos. • template<typename Derived > cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z) Matrix power. • template<typename Derived > dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n) Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm. template<typename Derived > double schatten (const Eigen::MatrixBase< Derived > &A, double p) Schatten matrix norm. • template<typename OutputScalar , typename Derived > dyn mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const typename Derived::Scalar &)) Functor. template<typename T > dyn_mat< typename T::Scalar > kron (const T &head) Kronecker product. template<typename T, typename... Args> dyn mat< typename T::Scalar > kron (const T &head, const Args &... tail) Kronecker product. template<typename Derived > dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As) Kronecker product. template<typename Derived > dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As) Kronecker product. • template<typename Derived > dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n) Kronecker power. template<typename T > dyn_mat< typename T::Scalar > dirsum (const T &head) Direct sum. • template<typename T , typename... Args> dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail) Direct sum. template<typename Derived > dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As) Direct sum. • template<typename Derived > dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)

Direct sum.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)

Direct sum power.

• template<typename Derived >

dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx cols)

Reshape.

template<typename Derived1 , typename Derived2 >

dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::← MatrixBase < Derived2 > &B)

Commutator.

19 template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B) Anti-commutator. template<typename Derived > dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A) Projector. template<typename Derived > dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As) Gram-Schmidt orthogonalization. template<typename Derived > dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As) Gram-Schmidt orthogonalization. • template<typename Derived > dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A) Gram-Schmidt orthogonalization. std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims) Non-negative integer index to multi-index. idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims) Multi-index to non-negative integer index. ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims) Multi-partite qudit ket. ket mket (const std::vector < idx > &mask, idx d=2) Multi-partite qudit ket. cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims) Projector onto multi-partite qudit ket. cmat mprj (const std::vector < idx > &mask, idx d=2) Projector onto multi-partite qudit ket. • template<typename InputIterator > std::vector< double > abssq (InputIterator first, InputIterator last) Computes the absolute values squared of an STL-like range of complex numbers. template<typename Container > std::vector< double > abssq (const Container &c, typename std::enable if< is iterable< Container >::value >::type *=nullptr) Computes the absolute values squared of an STL-like container. template<typename Derived > std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A) Computes the absolute values squared of an Eigen expression. template<typename InputIterator > std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last) Element-wise sum of an STL-like range. • template<typename Container > Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value

>::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

template<typename T >

std::vector< T > complement (std::vector< T > subsys, idx N)

Constructs the complement of a subsystem vector.

• template<typename Derived >

std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

• internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

• std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived >
 cmat apply (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

 $\begin{array}{l} \textbf{cmat apply} \ (\textbf{const Eigen::} \textbf{MatrixBase} < \textbf{Derived} > \& \textbf{A}, \ \textbf{const std::} \textbf{vector} < \textbf{cmat} > \& \textbf{Ks}, \ \textbf{const std::} \textbf{vector} < \textbf{idx} \\ > \& \textbf{target}, \ \textbf{const std::} \textbf{vector} < \textbf{idx} > \& \textbf{dims}) \end{array}$

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &dims)

Partial trace.

• template<typename Derived >

 $\label{localization} \mbox{dyn_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx d=2)}$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std
::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector < idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

 $\label{lem:const} \begin{tabular}{ll} double & var (const std::vector < double > & prob, const Container & X, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Variance.

template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double eps = 1e-12

Used to decide whether a number or expression in double precision is zero or not.

constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

- constexpr double ee = 2.718281828459045235360287471352662497
 Base of natural logarithm, e.
- constexpr double infty = std::numeric_limits<double>::max()
 Used to denote infinity in double precision.
- const idx idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

```
6.1.2.5 dmat
```

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void t.

See also


```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters



Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

6.1.3.3 abssq() [2/3]

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

6.1.3.4 abssq() [3/3]

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB+BA, as a dynamic matrix over the same scalar field as \emph{A}

```
6.1.3.7 apply() [1/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

```
6.1.3.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
dims	Dimensions of the multi-partite system	

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
d	Subsystem dimensions	

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	get Subsystem indexes where the gate A is applied	
எனிச்சுக்க by Diagensions of the multi-partite system		

Returns

CTRL-A gate applied to the part target of state

```
6.1.3.13 applyCTRL() [2/2]
```

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	Subsystem indexes where the gate A is applied	
d	Subsystem dimensions	

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Α	Eigen expression	
target	Subsystem indexes where the QFT is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the TFQ is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^\dagger K_j) = \delta_{ij}$ for all $i \neq j$

```
A Choi matrix
```

Returns

Set of orthogonal Kraus operators

6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
B	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
N	Total number of systems

Returns

Complement of subsys with respect to the set $\{0,1,\dots,N-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

6.1 qpp Namespace Reference 39 Wootters concurrence of the bi-partite qubit mixed state A.

A Eigen expression

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

A Eigen expression

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

qpp::x2contfrac()

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Real representation of the simple continued fraction

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Χ	Real number
N	Number of convergents.

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)	
Χ	Real random variable values represented by an STL-like container	
Y	Real random variable values represented by an STL-like container	

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the $\operatorname{\it OutputScalar}$ scalar field

6.1.3.32 det()

Determinant.

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

```
head Eigen expression
```

Returns

Its argument head

```
6.1.3.34 dirsum() [2/4]
```

Direct sum.

See also

qpp::dirsumpow()

head	Eigen expression
tail Variadic Eigen expression (zero or more paramete	

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

```
As std::vector of Eigen expressions
```

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression	
chop	Set to zero the elements smaller in absolute value than chop	

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double></double>	
chop	hop Set to zero the elements smaller in absolute value than chop	

Returns

Instance of qpp::internal::IOManipEigen

const std::string & end = "]")

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

```
template<typename Derived >
double qpp::entanglement (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.3.49 evals()

Eigenvalues.

See also

qpp::hevals()

A Eigen expression

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

A Eigen expression

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

```
6.1.3.52 factors()
```

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

qpp::lcm()

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

qpp::lcm()

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

A Eigen expression

Returns

G-concurrence

Gram-Schmidt orthogonalization.

Parameters

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

```
A Eigen expression
```

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

Inverse permutation.

Parameters

Returns

Inverse of the permutation perm

```
6.1.3.65 ip() [1/2]
```

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

```
6.1.3.66 ip() [2/2]
```

Generalized inner product.

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

```
6.1.3.70 kron() [1/4]
```

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of qpp::kron()

Parameters

head Eigen expression

Its argument head

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

```
qpp::gcd()
```

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

fname Output file name

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLAB<ket>("input.mat");
```

Template Parameters

Derived Complex Eigen type

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.3.82 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dima	Dimensions of the bi partite system
aims	Dimensions of the bi-partite system

Logarithmic negativity, with the logarithm in base 2

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Ylabels the columns)

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.3.87 measure() [2/9]
```

Measures the state vector or density matrix \boldsymbol{A} using the set of Kraus operators \boldsymbol{Ks} .

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

```
    Eigen expression
    Unitary matrix whose columns represent the measurement basis vectors
```

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

qpp::measure_seq()

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

const std::vector< idx > & target,

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

idx d = 2)

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.3.98 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
          bigint a,
          bigint b,
          bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

Non-negative integer index to multi-index.

See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

Negativity of the bi-partite mixed state A.

Α	Eigen expression
d	Subsystem dimensions

Negativity

```
6.1.3.108 norm()
```

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

```
6.1.3.109 omega()
```

```
cplx qpp::omega (
    idx D ) [inline]
```

D-th root of unity.

Parameters

```
D Non-negative integer
```

Returns

D-th root of unity $\exp(2\pi i/D)$

```
6.1.3.110 operator""" _i()
```

User-defined literal for complex $i=\sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.111 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.112 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

```
c STL-like container
```

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.117 ptrace() [2/2]
```

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.118 ptrace1() [1/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

,	Α	Eigen expression
-	dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.119 ptrace1() [2/2]

Partial trace.

Sa	_	2	len
26	е	ы	180

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsystem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 QFT()

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.125 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Mutual information between the 2 subsystems

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

Parameters

	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random big integer uniformly distributed in the interval [a, b]

```
6.1.3.129 rand() [3/5]

template<typename Derived >
Derived qpp::rand (
    idx rows,
    idx cols,
    double a = 0,
    double b = 1)
```

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.130 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows,
        idx cols,
        double a,
        double b) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) uniformly distributed in [-1,1) cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix	
cols	Number of columns of the random generated matrix	
а	Beginning of the interval, belongs to it	
b	End of the interval, does not belong to it	

Returns

Random complex matrix

6.1.3.132 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

D Dimension of the Hilbert space

Returns

Random Hermitian matrix

6.1.3.133 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

a Beginning of the interval, belongs to itb End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.134 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.135 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

```
6.1.3.136 randn() [1/4]

template<typename Derived >
Derived qpp::randn (
    idx rows,
    idx cols,
    double mean = 0,
    double sigma = 1)
```

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.137 randn() [2/4]

template<>>
dmat qpp::randn (
        idx rows,
        idx cols,
        double mean,
        double sigma ) [inline]
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix	
cols	Number of columns of the random generated matrix	
mean	Mean	
sigma	Standard deviation	

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.140 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.141 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b End of the interval, belongs to it	
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.142 randprob()

```
\begin{tabular}{ll} \tt std::vector<double> qpp::randprob ( & idx N) & [inline] \end{tabular}
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.143 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D | Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.144 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.145 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.146 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression	
alpha	A Non-negative real number, use app::infty for $lpha=\infty$	

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector	
alpha	Non-negative real number, use qpp::infty for $\alpha = \infty$	

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.148 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.149 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.150 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.151 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.152 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex	Eigen type
1	3 - 71 -

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB <i>matOpen()</i> documentation for details	

6.1.3.153 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 schatten()

Schatten matrix norm.

	Α	Eigen expression
ĺ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal U}$ whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.157 schmidtB() [1/2] template<typename Derived >

cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.160 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.162 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.164 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.165 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.166 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.167 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.168 sum() [2/3]
```

Element-wise sum of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.170 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Choi matrix

6.1.3.171 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.172 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.173 svdU()

Left singular vectors.

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.174 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.175 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.177 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.178 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.179 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.180 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution prob, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.182 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.183 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.184 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

X	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = 1e-12
```

Used to decide whether a number or expression in double precision is zero or not.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class MatrixNotCvector

Matrix is not a column vector exception.

• class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

· class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

· class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

• class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

• class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

Classes

- · class QCircuit
- · class QCircuitDescription

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_vector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check rvector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

 $bool\ check_dims_match_cvect\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

- template<typename Derived >
 bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
 bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check no duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool check_perm (const std::vector < idx > &perm)
- template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)
- template<typename T > void variadic_vector_emplace (std::vector< T > &)
- $\label{eq:continuous} \begin{array}{ll} \bullet & \mathsf{template} < \mathsf{typename} \ \mathsf{T} \ , \ \mathsf{typename} ... \ \mathsf{Args} > \\ & \mathsf{void} \ \mathsf{variadic_vector_emplace} \ (\mathsf{std} :: \mathsf{vector} < \mathsf{T} > \& \mathsf{v}, \ \mathsf{First} \ \& \& \mathsf{first}, \ \mathsf{Args} \ \& \& ... \ \mathsf{args}) \end{array}$
- idx get_num_subsys (idx sz, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims ( const std::vector< idx > & dims) [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx sz,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
```

Args &&... args)

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7


Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector < idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset Dynamic bitset
```

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

Default destructor.

• \sim Codes ()=default

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference


Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.6.2.2 type_description()

std::string qpp::exception::DimsMismatchMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.8.2.2 type_description()

std::string qpp::exception::DimsMismatchVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where Text re	epresenting where	e the exception occurr	ed
---------------	-------------------	------------------------	----

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

Dynamic_bitset (idx N)

Constructor, initializes all bits to false (zero)

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

· bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

· bool all () const noexcept

Checks whether all bits are set.

bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic bitset & set () noexcept

Set all bits to true.

Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

• Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
    idx storage_size_
        Storage size.
    idx N_
        Number of bits.
    std::vector < value_type > v_
        Storage space.
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
Type of the storage.
7.12.2.2 value_type
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

using qpp::Dynamic_bitset::value_type = unsigned int

7.12.3.1 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset (
    idx N ) [inline]
```

Constructor, initializes all bits to false (zero)

_					
D۵	ra	m	^	'n	PC

N Number of bits in the bitset

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

```
7.12.4.8 get()
```

The value of the bit at position pos.

Parameters

```
pos Position in the bitset
```

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

rhs Dynamic_bitset against which the inequality is being tested

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

7.12 gpp::Dynamic	bitset Class	Reference
-------------------	--------------	-----------

Equality operator.

Parameters

rhs Dynamic_bitset against which the equality is being tested

Returns

True if the bitsets are equal (bit by bit), false otherwise

```
7.12.4.15 rand() [1/2]
Dynamic_bitset& qpp::Dynamic_bitset::rand (
```

idx pos,

Sets the bit at position pos according to a Bernoulli(p) distribution.

double p = 0.5) [inline]

Parameters


pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters



Returns

Reference to the current instance

```
7.12.4.17 reset() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::reset (
        idx pos ) [inline]
```

Sets the bit at position pos to false.

Parameters

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset@ qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
```

Sets all bits to false.

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset@ qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

7.12.4.21 size()

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

7.12.4.22 storage_size()

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

zero	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.

7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

7.12.5.3 v_

```
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
```

Storage space.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.13 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- virtual const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string type_description () const =0
 - Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector, qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchDims, qpp::exception::DimsMismatchRvector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSubsys, qpp::exception::MatrixNotSquare qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquare, qpp::exception::ZeroSize, and qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

#include <classes/reversible.h>

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:


• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.
    • template<typename Derived >
      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    • cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.
    cmat CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::~Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression	
pos	Position	
dims	Dimensions of the multi-partite system	

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression	
pos	Position	
dims	Dimensions of the multi-partite system	

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N	
Ν	Positive integer	
n	Number of qubits required for implementing the gate	

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

theta F	otation angle
---------	---------------

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
          idx D = 2) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.


The documentation for this class was generated from the following file:

· classes/gates.h

7.16 qpp::experimental::QCircuitDescription::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

Collaboration diagram for qpp::experimental::QCircuitDescription::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx step_no, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is being applied
    idx step_no_
        step number
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
-4-4	0
ctrl	Control qudit indexes
target	Target qudit indexes
targot	ranger quair interior
step no	Circuit step number
στορ_πο	Circuit stop Hamber
name	Optional gate name
_	

7.16.3 Member Data Documentation

custom name of the step

```
7.16.3.1 ctrl_
std::vector<idx> qpp::experimental::QCircuitDescription::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::experimental::QCircuitDescription::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::experimental::QCircuitDescription::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::experimental::QCircuitDescription::GateStep::name_
```

7.16.3.5 step_no_

idx qpp::experimental::QCircuitDescription::GateStep::step_no_

step number

7.16.3.6 target_

std::vector<idx> qpp::experimental::QCircuitDescription::GateStep::target_

target where the gate is being applied

The documentation for this struct was generated from the following file:


· experimental/experimental.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

• IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

• IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 IDisplay() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

```
7.17.2.4 ~|Display()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

```
7.17.3.1 display()
virtual std::ostream& qpp::IDisplay::display (
```

std::ostream & os) const [private], [pure virtual]

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Default copy assignment operator.

```
7.17.3.3 operator=() [2/2]
```

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

7.17.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.18 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()

Cleanups.

Friends

- class internal::Singleton < const Init >

Additional Inherited Members

7.18.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.18.2 Constructor & Destructor Documentation

7.18.2.1 Init()

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

7.18.2.2 ∼Init()

qpp::Init::~Init () [inline], [private]

Cleanups.

7.18.3 Friends And Related Function Documentation

7.18.3.1 internal::Singleton < const Init >

friend class internal::Singleton< const Init > [friend]


The documentation for this class was generated from the following file:

· classes/init.h


7.19 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- double chop_

7.19.1 Constructor & Destructor Documentation

7.19.2 Member Function Documentation

```
7.19.2.1 display()
std::ostream& qpp::internal::IOManipEigen::display (
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.19.3 Member Data Documentation

7.19.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.19.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.20 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_

7.20.1 Constructor & Destructor Documentation

7.20.1.1 IOManipPointer() [1/2]

7.20.1.2 IOManipPointer() [2/2]

7.20.2 Member Function Documentation

7.20.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.20.2.2 operator=()

7.20.3 Member Data Documentation

```
7.20.3.1 end_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.20.3.2 N_
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.20.3.3 p_
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.20.3.4 separator_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
7.20.3.5 start_
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]


• internal/classes/iomanip.h

template<typename PointerType>


7.21 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- std::string start_
- std::string end_

7.21.1 Constructor & Destructor Documentation

```
7.21.1.1 IOManipRange() [1/2]
```

7.21.1.2 IOManipRange() [2/2]

7.21.2 Member Function Documentation

7.21.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.2.2 operator=()

7.21.3 Member Data Documentation

```
7.21.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.21.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.21.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.21.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.21.3.5 start_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


• internal/classes/iomanip.h

7.22 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.22.1 Detailed Description

template < typename T > struct qpp::is_complex < T >

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:


· traits.h

7.23 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.23.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.24 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.24.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

· traits.h


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), typename T::value_type > >:



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), typename T::value_type > >:



7.25.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < \ T, \ to_void < \ decltype(std::declval < \ T > ().begin()), \ decltype(std::declval < \ T > ().end()), \ typename \ T \leftarrow \\ ::value_type > >$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:


· traits.h

7.26 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is matrix expression< Derived >:



7.26.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived >*. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:

· traits.h

7.27 qpp::make_void < Ts > Struct Template Reference

```
Helper for <a href="mailto:qpp::to_void">qpp::to_void<>> alias template.</a>
```

```
#include <traits.h>
```

Public Types

· typedef void type

7.27.1 Detailed Description

```
template<typename... Ts> struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

```
qpp::to_void<>
```

7.27.2 Member Typedef Documentation

7.27.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


traits.h

7.28 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.28.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.28.2 Member Function Documentation

7.28.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.28.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.29 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.29.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.29.2 Member Function Documentation

7.29.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.29.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.30 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.30.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.30.2 Member Function Documentation

7.30.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.30.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.31 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.31.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.31.2 Member Function Documentation

7.31.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.31.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.32 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.32.2 Member Function Documentation

7.32.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.32.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.33.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.34.2 Member Function Documentation

7.34.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.34.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.35 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

7.36 qpp::experimental::QCircuitDescription::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

Collaboration diagram for qpp::experimental::QCircuitDescription::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, idx step_no, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats_
- std::vector< idx > target_

target where the measurement is applied

idx c_reg_ {}

result is being stored

idx step_no_

step number

• std::string name_

custom name of the step

7.36.1 Detailed Description

One step consisting only of measurements in the circuit.

7.36.2 Constructor & Destructor Documentation

```
7.36.2.1 MeasureStep() [1/2]
```

```
qpp::experimental::QCircuitDescription::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.36.2.2 MeasureStep() [2/2]

```
qpp::experimental::QCircuitDescription::MeasureStep::MeasureStep (
    MeasureType measurement_type,
    const std::vector< cmat > & mats,
    const std::vector< idx > & target,
    idx c_reg,
    idx step_no,
    std::string name = "" ) [inline]
```

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type	
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)	
target	Target qudit indexes	
c_reg	Classical register where the value of the measurement is stored	
step_no	Circuit step number	
name	Optional gate name	

7.36.3 Member Data Documentation

```
7.36.3.1 c_reg_
```

```
idx qpp::experimental::QCircuitDescription::MeasureStep::c_reg_ {}
```

result is being stored

index of the classical register where the measurement

```
7.36.3.2 mats_
std::vector<cmat> qpp::experimental::QCircuitDescription::MeasureStep::mats_
matrix/matrices that specify the measurement
7.36.3.3 measurement_type_
MeasureType qpp::experimental::QCircuitDescription::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.36.3.4 name
std::string qpp::experimental::QCircuitDescription::MeasureStep::name_
custom name of the step
7.36.3.5 step_no_
idx qpp::experimental::QCircuitDescription::MeasureStep::step_no_
step number
7.36.3.6 target
std::vector<idx> qpp::experimental::QCircuitDescription::MeasureStep::target_
target where the measurement is applied
The documentation for this struct was generated from the following file:
```


experimental/experimental.h

7.37 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.37.2 Member Function Documentation

7.37.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.38 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.38.2.2 type_description()

std::string qpp::exception::NotBipartite::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.39 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Code not yet implemented.

7.39.2 Member Function Documentation

7.39.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.39.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.40 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.40.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.41 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.41.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.41.2 Member Function Documentation

7.41.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.41.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.42 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.42.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.42.2 Member Function Documentation

7.42.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.42.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.43 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.43.2 Member Function Documentation

7.43.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.43.2.2 type_description()

std::string qpp::exception::NotQubitSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.44 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.44.2 Member Function Documentation

7.44.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.44.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.45 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Argument out of range exception.

Argument out of range

7.45.2 Member Function Documentation

7.45.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.45.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.46 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.46.2 Member Function Documentation

7.46.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

std::string qpp::exception::PermInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.47 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.47.2 Member Function Documentation

7.47.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.47.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


7.48 qpp::experimental::QCircuit Class Reference

#include <experimental/experimental.h>

Inheritance diagram for qpp::experimental::QCircuit:



Collaboration diagram for qpp::experimental::QCircuit:



Public Member Functions

• QCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

ket get_psi () const

Underlying quantum state.

• $std::vector < idx > get_dits$ () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

- $std::vector < double > get_probs$ () const

Vector of underlying measurement outcome probabilities.

idx get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

• idx get_m_ip () const

Measurement instruction pointer.

idx get_q_ip () const

Quantum instruction pointer.

idx get_ip () const

Total instruction pointer.

const QCircuitDescription & get_circuit_description () const

Quantum circuit description.

QCircuit & set_dit (idx i, idx value)

Sets the classical dit at position i.

· void reset ()

Resets the quantum circuit.

void run (idx step=idx_infty, bool verbose=false)

Executes the quantum circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Private Attributes

const QCircuitDescription qcd

quantum circuit description

· ket psi_

state vector

• $std::vector < idx > dits_$

classical dits

std::vector< double > probs

measurement probabilities

- std::vector< idx > subsys_
- idx m_ip_

measurement instruction pointer

idx q_ip_

quantum gates instruction pointer

• idx ip_

combined (measurements and gates) instruction pointer

7.48.1 Constructor & Destructor Documentation

7.48.1.1 QCircuit()

Constructs a quantum circuit out of a quantum circuit description.

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

qcd Quantum circuit description

7.48.2 Member Function Documentation

7.48.2.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.48.2.2 get_circuit_description()

```
\verb|const| QCircuitDescription& qpp::experimental::QCircuit::get\_circuit\_description ( ) const [inline] \\
```

Quantum circuit description.

Returns

Quantum circuit description

7.48.2.3 get_dit()

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

7.48.2.4 get_dits()

```
std::vector<idx> qpp::experimental::QCircuit::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.48.2.5 get_ip()

```
idx qpp::experimental::QCircuit::get_ip ( ) const [inline]
```

Total instruction pointer.

Returns

The sum of measurement instruction pointer and quantum instruction pointer

7.48.2.6 get_m_ip()

```
idx qpp::experimental::QCircuit::get_m_ip ( ) const [inline]
```

Measurement instruction pointer.

Points to the index of the next measurement to be executed from the std::vector<MeasureStep> of measurements in the circuit description

Returns

Measurement instruction pointer

7.48.2.7 get_measured() [1/2]

Check whether qudit i was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.48.2.8 get_measured() [2/2]
std::vector<idx> qpp::experimental::QCircuit::get_measured ( ) const [inline]
```

Returns

Vector of already measured qudit indexes

Vector of already measured gudit indexes.

```
7.48.2.9 get_not_measured()
```

```
std::vector<idx> qpp::experimental::QCircuit::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.48.2.10 get_probs()
```

```
std::vector<double> qpp::experimental::QCircuit::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.48.2.11 get_psi()
```

```
ket qpp::experimental::QCircuit::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.48.2.12 get_q_ip()
```

```
idx qpp::experimental::QCircuit::get_q_ip ( ) const [inline]
```

Quantum instruction pointer.

Points to the index of the next quantum gate to be executed from the std::vector<GateStep> of quantum gates in the circuit description

Returns

Quantum instruction pointer

7.48.2.13 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters

```
v Qudit index
```

7.48.2.14 reset()

```
void qpp::experimental::QCircuit::reset ( ) [inline]
```

Resets the quantum circuit.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.48.2.15 run()

```
void qpp::experimental::QCircuit::run (
    idx step = idx_infty,
    bool verbose = false ) [inline]
```

Executes the quantum circuit.

Parameters

step	How many steps to execute, by default executes until the end
verbose If true, displays at console every executed step	

7.48.2.16 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.48.2.17 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.48.3 Member Data Documentation

```
7.48.3.1 dits_
std::vector<idx> qpp::experimental::QCircuit::dits_ [private]
classical dits
7.48.3.2 ip_
idx qpp::experimental::QCircuit::ip_ [private]
combined (measurements and gates) instruction pointer
7.48.3.3 m_ip_
idx qpp::experimental::QCircuit::m_ip_ [private]
measurement instruction pointer
7.48.3.4 probs_
std::vector<double> qpp::experimental::QCircuit::probs_ [private]
measurement probabilities
7.48.3.5 psi_
ket qpp::experimental::QCircuit::psi_ [private]
state vector
7.48.3.6 q_ip_
idx qpp::experimental::QCircuit::q_ip_ [private]
quantum gates instruction pointer
```

```
7.48.3.7 qcd_
```

```
const QCircuitDescription qpp::experimental::QCircuit::qcd_ [private]
```

quantum circuit description

7.48.3.8 subsys_

```
std::vector<idx> qpp::experimental::QCircuit::subsys_ [private]
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:

• experimental/experimental.h

7.49 qpp::QCircuit Class Reference

Quantum circuit simulator.

```
#include <experimental/experimental.h>
```

7.49.1 Detailed Description

Quantum circuit simulator.

See also

qpp::QCircuitDescription


The documentation for this class was generated from the following file:

• experimental/experimental.h


7.50 qpp::experimental::QCircuitDescription Class Reference

#include <experimental/experimental.h>

Inheritance diagram for qpp::experimental::QCircuitDescription:



 $Collaboration\ diagram\ for\ qpp::experimental::QCircuit Description:$



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,

GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_CTRL_MULTIPLE_TARGET,

GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGE GateType::MULTIPLE_cCTRL_SINGLE_TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

Public Member Functions

QCircuitDescription (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit description.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

idx get_d () const noexcept

Local dimension of the comprising qudits.

std::vector< idx > get_measurement_steps () const

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

const std::vector< MeasureStep > & get_measurements () const noexcept

Vector of qpp::QCircuitDescription::MeasureStep.

const std::vector< GateStep > & get_gates () const noexcept

Vector of gpp::QCircuitDescription::GateStep.

std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

- $std::vector < idx > get_measured$ () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

idx get_total_count () const noexcept

Quantum circuit total count, i.e. the sum of gate count and measurement count.

QCircuitDescription & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuitDescription & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

• QCircuitDescription & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

• QCircuitDescription & gate_fan (const cmat &U, const std::vector< idx > &target, std::string name=""")

Applies the single qudit gate U on every qudit listed in target.

QCircuitDescription & gate_fan (const cmat &U, std::string name="")

 $\label{lem:applies} \textit{Applies the single qudit gate U on every remaining non-measured qudit.}$

QCircuitDescription & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuitDescription & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & TFQ (const std::vector< idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

• QCircuitDescription & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name=""")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuitDescription & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuitDescription & cCTRL_custom (const cmat &U, const std::vector < idx > &ctrl_dits, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & measureZ (idx i, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuitDescription & measureV (const cmat &V, idx i, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuitDescription & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

```
    const idx nq_
```

number of qudits

const idx nc_

number of classical "dits"

• const idx d_

dimension

std::vector< idx > measurement_steps_{}

measurements take place

std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

· idx step_cnt_

step counter

std::vector< GateStep > gates_{}{}

aates

std::vector< MeasureStep > measurements {}

measurements

Friends

- std::ostream & operator<< (std::ostream &os, const GateType &gate_type)
 - Extraction operator overload for qpp::QCircuitDescription::GateType enum class.
- std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)
 - Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.
- std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)
 - Extraction operator overload for qpp::QCircuitDescription::GateStep class.
- std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

7.50.1 Member Enumeration Documentation

7.50.1.1 GateType

enum qpp::experimental::QCircuitDescription::GateType [strong]

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_MULTIPLE_TARGET	with multiple classical controls and multiple targets controlled 1 qudit unitary gate
CUSTOM_cCTRL	multiple targets custom controlled gate with multiple controls and

7.50.1.2 MeasureType

```
enum qpp::experimental::QCircuitDescription::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix \it{V} measurement of multiple qudits in the orthonormal

7.50.2 Constructor & Destructor Documentation

7.50.2.1 QCircuitDescription()

```
qpp::experimental::QCircuitDescription::QCircuitDescription (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline]
```

Constructs a quantum circuit description.

Note

The measurement results can only be stored in the classical dits of which number is specified by *nc*

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	d Subsystem dimensions (optional, default is qubit, i.e. $d = 2$	
name	Circuit description name (optional)	

7.50.3 Member Function Documentation

```
7.50.3.1 cCTRL() [1/4]
```

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
const std::vector< idx > & ctrl_dits,
idx target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.4 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

7.50.3.5 cCTRL_custom()

```
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target Target qudit indexes where the gate U is applied depending on the values of the classical control of	
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.6 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.7 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.8 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.9 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.50.3.10 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.50.3.11 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit description

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.50.3.15 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

std::string name = "") [inline]

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.50.3.18 get_d()
```

```
idx qpp::experimental::QCircuitDescription::get_d ( ) const [inline], [noexcept]
```

Local dimension of the comprising qudits.

Returns

Local dimension

```
7.50.3.19 get_gate_count()
```

```
idx qpp::experimental::QCircuitDescription::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

Returns

Total gate count

```
7.50.3.20 get_gates()
```

```
\label{lem:const_std::qcircuitDescription::get_gates () const} $$ \end{substrate} $$$ \end{substrate} $$ \end{substrate} $$ \
```

Vector of qpp::QCircuitDescription::GateStep.

Returns

Vector of qpp::QCircuitDescription::GateStep

```
7.50.3.21 get_measured() [1/2]
```

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.50.3.22 get_measured() [2/2]
```

```
std::vector<idx> qpp::experimental::QCircuitDescription::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.50.3.23 get_measurement_count()

```
idx qpp::experimental::QCircuitDescription::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.50.3.24 get_measurement_steps()

```
\verb|std::vector<| idx>| qpp::experimental::QCircuitDescription::get_measurement_steps () const[inline]|
```

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

Note

If there are more consecutive measurements after step S, then their indexes will all be S, i.e. it is always assumed that the measurements taking place immediately after a gate step have the same index as the preceding gate step.

Returns

Vector of measurement positions

7.50.3.25 get_measurements()

```
const std::vector<MeasureStep>& qpp::experimental::QCircuitDescription::get_measurements ( )
const [inline], [noexcept]
```

Vector of qpp::QCircuitDescription::MeasureStep.

Returns

Vector of qpp::QCircuitDescription::MeasureStep

7.50.3.26 get_name()

```
std::string qpp::experimental::QCircuitDescription::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.50.3.27 get_nc()
```

```
idx qpp::experimental::QCircuitDescription::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.50.3.28 get_non_measured()
```

```
std::vector<idx> qpp::experimental::QCircuitDescription::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.50.3.29 get_nq()
```

```
idx qpp::experimental::QCircuitDescription::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

```
7.50.3.30 get_total_count()
```

```
idx qpp::experimental::QCircuitDescription::get_total_count ( ) const [inline], [noexcept]
```

Quantum circuit total count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

```
7.50.3.31 measureV() [1/2]
```

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
i	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

```
7.50.3.32 measureV() [2/2]
```

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.50.3.33 measureZ()

```
QCircuitDescription& qpp::experimental::QCircuitDescription::measureZ (
    idx i,
    idx c_reg,
    std::string name = "" ) [inline]
```

Measurement of single qudit in the computational basis (Z-basis)

Parameters

i	Qudit index
c_reg	Classical register where the value of the measurement is being stored
Generale by อเกรีเดูเกลl measurement name, default is "Measure Z"	

Returns

Reference to the current instance

```
7.50.3.34 QFT()
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.50.3.35 TFQ()
```

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.50.4 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

Parameters

os	Output stream
gate type	qpp::QCircuitDescription::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureStep enum class

Returns

Output stream

7.50.5 Member Data Documentation

keeps track of the measured qudits

```
7.50.5.1 d_
const idx qpp::experimental::QCircuitDescription::d_ [private]
dimension

7.50.5.2 gates_
std::vector<GateStep> qpp::experimental::QCircuitDescription::gates_ {} [private]
gates

7.50.5.3 measured_
std::vector<bool> qpp::experimental::QCircuitDescription::measured_ [private]
```

```
7.50.5.4 measurement_steps_
std::vector<idx> qpp::experimental::QCircuitDescription::measurement_steps_ {} [private]
measurements take place
keeps track of where the
7.50.5.5 measurements
std::vector<MeasureStep> qpp::experimental::QCircuitDescription::measurements_ {} [private]
measurements
7.50.5.6 name_
std::string qpp::experimental::QCircuitDescription::name_ [private]
optional circuit name
7.50.5.7 nc_
const idx qpp::experimental::QCircuitDescription::nc_ [private]
number of classical "dits"
7.50.5.8 nq_
const idx qpp::experimental::QCircuitDescription::nq_ [private]
number of qudits
7.50.5.9 step_cnt_
idx qpp::experimental::QCircuitDescription::step_cnt_ [private]
step counter
The documentation for this class was generated from the following file:
```

• experimental/experimental.h

7.51 qpp::QCircuitDescription Class Reference

Quantum circuit description class.

#include <experimental/experimental.h>

7.51.1 Detailed Description

Quantum circuit description class.

See also

qpp::QCircuit

The documentation for this class was generated from the following file:


• experimental/experimental.h

7.52 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.52.2 Member Function Documentation

7.52.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.52.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

```
#include <classes/random_devices.h>
```

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

- std::mt19937 & get_prng ()
 - Returns a reference to the internal PRNG object.
- std::istream & load (std::istream &is)
 - Loads the state of the PRNG from an input stream.
- std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

• \sim RandomDevices ()=default

Default destructor.

Private Attributes

- std::random_device rd_
 - used to seed std::mt19937 prng_
- std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.53.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std ∴ ::random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.53.2 Constructor & Destructor Documentation

7.53.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.53.2.2 ∼RandomDevices()

```
qpp::RandomDevices::~RandomDevices ( ) [private], [default]
```

Default destructor.

7.53.3 Member Function Documentation

```
7.53.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.53.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.53.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

```
os Output stream
```

Returns

The output stream

7.53.4 Friends And Related Function Documentation

```
7.53.4.1 internal::Singleton < RandomDevices >
```

```
\label{lem:class} \mbox{friend class internal::Singleton} < \mbox{RandomDevices} > \mbox{ [friend]}
```

7.53.5 Member Data Documentation

```
7.53.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

7.53.5.2 rd

```
std::random_device qpp::RandomDevices::rd_ [private]
```

The documentation for this class was generated from the following file:

· classes/random devices.h

used to seed std::mt19937 prng

7.54 qpp::internal::Singleton< T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get instance () noexcept(std::is nothrow constructible < T >::value)
- static T & get thread local instance () noexcept(std::is nothrow constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.54.1 Detailed Description

```
template<typename T>
class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.54.2 Constructor & Destructor Documentation

```
7.54.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton< T >::Singleton ( ) [protected], [default], [noexcept]
7.54.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > & ) [protected], [delete]
7.54.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.54.3 Member Function Documentation
7.54.3.1 get_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_instance ( ) [inline], [static], [noexcept]
7.54.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
```

7.54.3.3 operator=()

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.55 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.55.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.55.2 Member Function Documentation

7.55.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.55.2.2 type_description()

```
std::string qpp::exception::SizeMismatch::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.56 qpp::States Class Reference


const Singleton class that implements most commonly used states

```
#include <classes/states.h>
```

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state (following the convention in Nielsen and Chuang)
ket b01 {ket::Zero(4)}
      Bell-01 state (following the convention in Nielsen and Chuang)

    ket b10 {ket::Zero(4)}

      Bell-10 state (following the convention in Nielsen and Chuang)
ket b11 {ket::Zero(4)}
      Bell-11 state (following the convention in Nielsen and Chuang)

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.56.1 Detailed Description

const Singleton class that implements most commonly used states

7.56.2 Constructor & Destructor Documentation

```
7.56.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.56.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.56.3 Member Function Documentation

```
7.56.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.56.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.56.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.56.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

```
7.56.3.5 plus()
```

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.56.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.56.4 Friends And Related Function Documentation

```
7.56.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.56.5 Member Data Documentation

```
7.56.5.1 b00
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state (following the convention in Nielsen and Chuang)

```
7.56.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state (following the convention in Nielsen and Chuang)

```
7.56.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state (following the convention in Nielsen and Chuang)

```
7.56.5.4 b11
```

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state (following the convention in Nielsen and Chuang)

7.56.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.56.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.56.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.56.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.56.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.56.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.56.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.56.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.56.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.56.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.56.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.56.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.56.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.56.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.56.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.56.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.56.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.56.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.56.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.56.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/states.h

7.57 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.57.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.57.2 Member Function Documentation

7.57.2.1 Exception()

```
qpp::exception::Exception [inline]
```

Constructs an exception.

Parameters

Text representing where the exception of	П
--	---

7.57.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.58 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.58.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.58.2 Constructor & Destructor Documentation

```
7.58.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T = std::chrono::steady}}$ $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp::Timer}}$ $$ \ensuremath{\texttt{T, CLOCK\_T >::Timer}}$ $$ ( ) $$ [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.58.2.2 Timer() [2/3]

Default copy constructor.

```
7.58.2.3 Timer() [3/3]
```

Default move constructor.

7.58.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.58.3 Member Function Documentation

7.58.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.58.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.58.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.58.3.4 operator=() [2/2]
```

Default move assignment operator.

7.58.3.5 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.58.3.6 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.58.3.7 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.58.4 Member Data Documentation

7.58.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.58.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.59 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.59.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.59.2 Member Function Documentation

7.59.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.59.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.60 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.60.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.60.2 Member Function Documentation

7.60.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.60.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.61 qpp::exception::Unknown Class Reference


Unknown exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.61.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.61.2 Member Function Documentation

7.61.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurred	
--	--

7.61.2.2 type_description()

```
std::string qpp::exception::Unknown::type_description ( ) const [inline], [override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.62.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.62.2 Member Function Documentation

7.62.2.1 Exception()

qpp::exception::Exception [inline]

Constructs an exception.

Parameters

where Text representing where the exception occurre	tion occurred
---	---------------

7.62.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

Chapter 8

File Documentation

8.1 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.

8.1.1 Detailed Description


Quantum error correcting codes.

318 File Documentation

8.2 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

• class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

• class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

· class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

• class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

· class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

class gpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

• class qpp::exception::OutOfRange

Argument out of range exception.

• class qpp::exception::TypeMismatch

Type mismatch exception.

class qpp::exception::SizeMismatch

Size mismatch exception.

• class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

Namespaces

• qpp

Quantum++ main namespace.

qpp::exception

Quantum++ exception hierarchy namespace.

320 File Documentation


8.2.1 Detailed Description

Exceptions.

8.3 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.


8.3.1 Detailed Description

Quantum gates.

8.4 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI)

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

Namespaces

qpp

Quantum++ main namespace.


8.4.1 Detailed Description

Display interface via the non-virtual interface (NVI)

8.5 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



322 File Documentation

Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Initialization.

8.6 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Random devices.

8.7 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.

8.7.1 Detailed Description


Support for classical reversible circuits.

8.8 classes/states.h File Reference

Quantum states.

324 File Documentation

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Quantum states.

8.9 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Timing.

8.10 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

326 File Documentation

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double qpp::eps = 1e-12

Used to decide whether a number or expression in double precision is zero or not.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.10.1 Detailed Description

Constants.

8.11 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```

328 File Documentation


8.11.1 Detailed Description

Entanglement functions.

8.12 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >
        double qpp::entropy (const Eigen::MatrixBase< Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.12.1 Detailed Description

Entropy functions.

8.13 experimental/experimental.h File Reference

Experimental/test functions/classes.

Classes

- class qpp::experimental::QCircuitDescription
- struct qpp::experimental::QCircuitDescription::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::experimental::QCircuitDescription::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::experimental::QCircuit

Namespaces

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.13.1 Detailed Description

Experimental/test functions/classes.

8.14 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

```
qpp
```

Quantum++ main namespace.

· qpp::literals

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > gpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.
template<typename Derived >
  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.

    template<typename Derived >

  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar qpp::sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  std::pair< dyn col vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
```

```
Hermitian eigenvalues.
ullet template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn col vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template < typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.
• template<typename Derived >
  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.
ullet template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double <a href="mailto:qpp::schatten">qpp::schatten</a> (const Eigen::MatrixBase</a> Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.
• template<typename T >
  dyn mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
```

```
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.
\bullet \ \ {\it template}{<} {\it typename Derived} >
  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.
• template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.
• std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)
```

Non-negative integer index to multi-index.

```
Multi-index to non-negative integer index.

    ket qpp::mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

      Multi-partite qudit ket.

    ket qpp::mket (const std::vector < idx > &mask, idx d=2)

      Multi-partite qudit ket.

    cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

      Projector onto multi-partite qudit ket.

    cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

      Projector onto multi-partite qudit ket.

    template<typename InputIterator >

  std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
      Computes the absolute values squared of an STL-like range of complex numbers.
• template<typename Container >
  std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container
  >::value >::type *=nullptr)
      Computes the absolute values squared of an STL-like container.

    template<typename Derived >

  std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
      Computes the absolute values squared of an Eigen expression.

    template<typename InputIterator >

  std::iterator_traits < InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
      Element-wise sum of an STL-like range.

    template<typename Container >

  Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container > \leftarrow
  ::value >::type *=nullptr)
      Element-wise sum of the elements of an STL-like container.
• template<typename InputIterator >
  std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
      Element-wise product of an STL-like range.

    template<typename Container >

  Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >←
  ::value >::type *=nullptr)
      Element-wise product of the elements of an STL-like container.
• template<typename Derived >
  dyn col vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
      Finds the pure state representation of a matrix proportional to a projector onto a pure state.

    template<tvpename T >

  std::vector< T > qpp::complement (std::vector< T > subsys, idx N)
      Constructs the complement of a subsystem vector.

    template < typename Derived >

  std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
      Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

    cmat qpp::bloch2rho (const std::vector< double > &r)

      Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.
• template<char... Bits>
  ket qpp::literals::operator"" ket ()
     Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra qpp::literals::operator"" _bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat qpp::literals::operator"" _prj ()
      Multi-partite qubit projector user-defined literal.
```

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)


8.14.1 Detailed Description

Generic quantum computing functions.

8.15 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.15.1 Detailed Description

Input/output functions.

8.16 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.16.1 Detailed Description

Measurement functions.

8.17 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


8.17.1 Detailed Description

Input/output manipulators.

8.18 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.18.1 Detailed Description

Singleton pattern via CRTP.

8.19 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- ullet template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check qubit rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx sz, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.19.1 Detailed Description

Internal utility functions.

8.20 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.20.1 Detailed Description

Input/output interfacing with MATLAB.

8.21 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \ \, \text{std::vector} < \mathsf{idx} > \mathsf{qpp::compperm} \ (\mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{perm}, \ \mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.21.1 Detailed Description

Number theory functions.

8.22 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std \mapsto ::vector < idx > \&dims) $$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.22.1 Detailed Description

Quantum operation functions.

8.23 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.23.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.23.2 Macro Definition Documentation


8.23.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.24 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

dbb

Quantum++ main namespace.

Functions

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

• idx qpp::randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>
 cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.24.1 Detailed Description

Randomness-related functions.

8.25 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

8.26 traits.h File Reference 349


8.25.1 Detailed Description

Statistics functions.

8.26 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), typename T::va
 Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


8.26.1 Detailed Description

Type traits.

8.27 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
using qpp::idx = std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

template<typename Scalar >

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.27.1	Detailed	Descrip	tion
--------	----------	---------	------

Type aliases.

8.28 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 351	qpp::States, 296
~Codes	bigint
qpp::Codes, 136	qpp, 26
~Gates	Bit_circuit
qpp::Gates, 175	gpp::Bit circuit, 131
~IDisplay	bloch2rho
qpp::IDisplay, 191	qpp, 36
~Init	bra
qpp::Init, 193	qpp, 26
~RandomDevices	4PP; = 0
qpp::RandomDevices, 284	c_reg_
~Singleton	qpp::experimental::QCircuitDescription::Measure
qpp::internal::Singleton, 287	Step, 226
~States	cCTRL_custom
	qpp::experimental::QCircuitDescription, 265
qpp::States, 293	cCTRL
~Timer	qpp::experimental::QCircuitDescription, 263–265
qpp::Timer, 304	CNOTba
Λ	qpp::Gates, 184
A_ annuinternal ul OManin Figure 100	CNOT
qpp::internal::IOManipEigen, 196	
absm	qpp::Bit_circuit, 131
qpp, 28	qpp::Bit_circuit::Gate_count, 171
abssq	qpp::Gates, 184
qpp, 28, 29	CTRL_custom
adjoint	qpp::experimental::QCircuitDescription, 268
qpp, 30	CTRL
all	qpp::Gates, 176
qpp::Dynamic_bitset, 158	qpp::experimental::QCircuitDescription, 266, 267
anticomm	check_cvector
qpp, 30	qpp::internal, 120
any	check_dims
qpp::Dynamic_bitset, 158	qpp::internal, 120
apply	check_dims_match_cvect
qpp, 30–32	qpp::internal, 120
applyCTRL	check_dims_match_mat
qpp, 33, 34	qpp::internal, 121
applyQFT	check_dims_match_rvect
qpp, 34	qpp::internal, 121
applyTFQ	check_eq_dims
qpp, 35	qpp::internal, 121
avg	check_matching_sizes
qpp, 35	qpp::internal, 121
-111-1-7	check no duplicates
b00	qpp::internal, 121
qpp::States, 295	check nonzero size
b01	qpp::internal, 121
qpp::States, 296	check perm
b10	qpp::internal, 122
qpp::States, 296	check_qubit_cvector
b11	qpp::internal, 122
	H I

check_qubit_matrix	COV
qpp::internal, 122	qpp, 42
check_qubit_rvector	cplx
qpp::internal, 122	qpp, 26
check_qubit_vector	ctrl_
qpp::internal, 122	qpp::experimental::QCircuitDescription::GateStep,
check_rvector	188
qpp::internal, 122	CustomException
check_square_mat	qpp::exception::CustomException, 138
qpp::internal, 123	cwise
check_subsys_match_dims	qpp, 43
qpp::internal, 123	CZ
check_vector	qpp::Gates, 184
qpp::internal, 123	d_
choi2kraus	qpp::experimental::QCircuitDescription, 278
qpp, 36	data
choi2super	qpp::Dynamic bitset, 158
qpp, 37	det
chop	qpp, 43
qpp, 116	dirsum
chop_	qpp, 44, 45
qpp::internal::IOManipEigen, 196 classes/codes.h, 317	dirsum2
	qpp::internal, 123
classes/exception.h, 318 classes/gates.h, 320	dirsumpow
classes/idisplay.h, 321	qpp, 46
classes/init.h, 321	disp
classes/random_devices.h, 322	qpp, 46–48
classes/reversible.h, 323	display
classes/states.h, 323	qpp::Dynamic_bitset, 159
classes/timer.h, 324	qpp::IDisplay, 191
cmat	qpp::Timer, 304
qpp, 26	qpp::experimental::QCircuit, 252
Codes	qpp::experimental::QCircuitDescription, 268
qpp::Codes, 136	qpp::internal::IOManipEigen, 195
codeword	qpp::internal::IOManipPointer, 198
qpp::Codes, 136	qpp::internal::IOManipRange, 201
comm	display_impl_
qpp, 37	qpp::internal::Display_Impl_, 152
complement	dits_ qpp::experimental::QCircuit, 256
qpp, 38	dmat
compperm	qpp, 26
qpp, 38	dyn_col_vect
concurrence	qpp, 27
qpp, 38	dyn_mat
conjugate	qpp, 27
qpp, 40	dyn_row_vect
constants.h, 325	qpp, 27
contfrac2x	Dynamic_bitset
qpp, 40	qpp::Bit_circuit, 132
convergents	qpp::Dynamic_bitset, 157
qpp, 41	
cor	ee
qpp, 42	qpp, 116
cosm	egcd
qpp, 42	qpp, 48
count	eig
qpp::Dynamic_bitset, 158	qpp, 49

end_	qpp::Bit_circuit::Gate_count, 172
qpp::Timer, 306	qpp::Gates, 184
qpp::internal::IOManipPointer, 198	factors
qpp::internal::IOManipRange, 202	qpp, 52
entanglement	Fd
qpp, 49, 50	qpp::Gates, 178
entanglement.h, 326	first_
entropies.h, 328	qpp::internal::IOManipRange, 202
entropy	flip
qpp, 50, 51	qpp::Dynamic_bitset, 160
eps	functions.h, 329
qpp, 116	funm
evals	qpp, 53
qpp, 51	GHZ
evects	
qpp, 52	qpp::States, 296 gate
Exception	qpp::experimental::QCircuitDescription, 269, 270
qpp::exception::DimsInvalid, 141	gate_
qpp::exception::DimsMismatchCvector, 143	qpp::experimental::QCircuitDescription::GateStep,
qpp::exception::DimsMismatchMatrix, 145	188
qpp::exception::DimsMismatchRvector, 147	gate_count
qpp::exception::DimsMismatchVector, 149	qpp::Bit_circuit, 134
qpp::exception::DimsNotEqual, 151	gate_custom
qpp::exception::Duplicates, 154	qpp::experimental::QCircuitDescription, 270
qpp::exception::Exception, 170	gate_fan
qpp::exception::MatrixMismatchSubsys, 210	qpp::experimental::QCircuitDescription, 270, 271
qpp::exception::MatrixNotCvector, 212	gate_type_
qpp::exception::MatrixNotRvector, 214	qpp::experimental::QCircuitDescription::GateStep,
<pre>qpp::exception::MatrixNotSquare, 216 qpp::exception::MatrixNotSquareNorCvector, 218</pre>	188
qpp::exception::MatrixNotSquareNorRvector, 210	GateStep
qpp::exception::MatrixNotSquareNorNector, 222	qpp::experimental::QCircuitDescription::GateStep,
qpp::exception::MatrixNotVector, 224	187
qpp::exception::NoCodeword, 229	GateType
qpp::exception::NotBipartite, 231	qpp::experimental::QCircuitDescription, 262
qpp::exception::NotImplemented, 233	Gates
qpp::exception::NotQubitCvector, 235	qpp::Gates, 175
qpp::exception::NotQubitMatrix, 237	gates_
qpp::exception::NotQubitRvector, 239	qpp::experimental::QCircuitDescription, 278
qpp::exception::NotQubitSubsys, 241	gcd
qpp::exception::NotQubitVector, 243	qpp, 53, 54
qpp::exception::OutOfRange, 245	gconcurrence
qpp::exception::PermInvalid, 247	qpp, 54
qpp::exception::PermMismatchDims, 249	get
qpp::exception::QuditAlreadyMeasured, 281	qpp::Dynamic_bitset, 160
qpp::exception::SizeMismatch, 289	get_circuit_description
qpp::exception::SubsysMismatchDims, 301	qpp::experimental::QCircuit, 252
qpp::exception::TypeMismatch, 308	get_d
qpp::exception::UndefinedType, 310	qpp::experimental::QCircuitDescription, 271
qpp::exception::Unknown, 312	get_dim_subsys
qpp::exception::ZeroSize, 314	qpp::internal, 123
expandout	get_dit
qpp::Gates, 176, 177	qpp::experimental::QCircuit, 252
experimental/experimental.h, 329	get_dits
expm	qpp::experimental::QCircuit, 253
qpp, 52	get_duration
FDFD	qpp::Timer, 305
FRED	get_gate_count
qpp::Bit_circuit, 132	qpp::experimental::QCircuitDescription, 271

get_gates	qpp::internal::IOManipEigen, 195
qpp::experimental::QCircuitDescription, 272	IOManipPointer
get_instance	qpp::internal::IOManipPointer, 197, 198
qpp::internal::Singleton, 287	IOManipRange qpp::internal::IOManipRange, 201
get_ip qpp::experimental::QCircuit, 253	Id
get_m_ip	qpp::Gates, 179
qpp::experimental::QCircuit, 253	Id2
get_measured	qpp::Gates, 185
qpp::experimental::QCircuit, 253, 254	idx
qpp::experimental::QCircuitDescription, 272	qpp, 27
get_measurement_count	idx_infty
qpp::experimental::QCircuitDescription, 272	qpp, 116
get_measurement_steps	index_
qpp::experimental::QCircuitDescription, 273	qpp::Dynamic_bitset, 161
get_measurements	infty
qpp::experimental::QCircuitDescription, 273	qpp, 116
get_name	Init
qpp::Gates, 179	qpp::Init, 193
qpp::experimental::QCircuitDescription, 273	input_output.h, 334
get_nc	instruments.h, 335
<pre>qpp::experimental::QCircuitDescription, 273 get_non_measured</pre>	internal/classes/iomanip.h, 336 internal/classes/singleton.h, 337
qpp::experimental::QCircuitDescription, 274	internal/util.h, 338
get_not_measured	internal::Singleton< const Codes >
qpp::experimental::QCircuit, 254	qpp::Codes, 137
get_nq	internal::Singleton< const Gates >
qpp::experimental::QCircuitDescription, 274	qpp::Gates, 184
get_num_subsys	internal::Singleton< const Init >
qpp::internal, 123	qpp::Init, 194
get_prng	internal::Singleton< const States >
qpp::RandomDevices, 284	qpp::States, 295
get_probs	internal::Singleton< RandomDevices >
qpp::experimental::QCircuit, 254	qpp::RandomDevices, 285
get_psi	inverse
qpp::experimental::QCircuit, 254	qpp, 57
get_q_ip	invperm
qpp::experimental::QCircuit, 255	qpp, 57
get_relative_pos_ qpp::experimental::QCircuit, 255	ID
get_thread_local_instance	qpp, 58 ip_
qpp::internal::Singleton, 287	qpp::experimental::QCircuit, 257
get_total_count	isprime
qpp::experimental::QCircuitDescription, 274	qpp, 59
grams	H 1 2
qpp, 55	jn
	qpp::States, 293
Н	
qpp::Gates, 184	ket
heig	qpp, 28
qpp, 56	kraus2choi
hevals	qpp, 59 kraus2super
qpp, 56	qpp, 60
hevects	kron
qpp, 57	qpp, 60–62
IDisplay	kron2
qpp::IDisplay, 190, 191	qpp::internal, 124
IOManipEigen	kronpow

	74 7E
qpp, 62	qpp, 74, 75
	modinv
last_	qpp, 75
qpp::internal::IOManipRange, 202	modmul
lcm	qpp, 76
qpp, 63	modpow
load	qpp, 76
qpp, 63	mprj
gpp::RandomDevices, 284	
loadMATLAB	qpp, 77
	msg_
qpp, 64, 65	qpp::exception::Exception, 171
logdet	multiidx2n
qpp, 65	qpp, 78
logm	qpp::internal, 124
qpp, 66	
lognegativity	n2multiidx
qpp, 66, 67	qpp, 78
المارية والمارية	qpp::internal, 124
m_ip_	
qpp::experimental::QCircuit, 257	N_
	qpp::Dynamic_bitset, 167
MATLAB/matlab.h, 340	qpp::internal::IOManipPointer, 199
MODMUL	NOT
qpp::Gates, 179	qpp::Bit_circuit, 132
marginalX	qpp::Bit_circuit::Gate_count, 172
qpp, 67	name
marginalY	qpp::experimental::QCircuitDescription, 279
qpp, 67	qpp::experimental::QCircuitDescription::GateStep,
mats	188
dpp::experimental::QCircuitDescription::Measure ←	
_	qpp::experimental::QCircuitDescription::Measure
Step, 226	Step, 227
•	
maxn	nc_
•	
maxn	nc_
maxn qpp, 116	nc_ qpp::experimental::QCircuitDescription, 279 negativity
maxn qpp, 116 measure	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79
maxn qpp, 116 measure qpp, 68–72 measure_seq	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none
maxn qpp, 116 measure qpp, 68–72 measure_seq qpp, 73, 74	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161
maxn qpp, 116 measure qpp, 68–72 measure_seq qpp, 73, 74 MeasureStep	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_ qpp::experimental::QCircuitDescription, 279
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_ qpp::experimental::QCircuitDescription, 279
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_ qpp::experimental::QCircuitDescription, 279
maxn	nc_ qpp::experimental::QCircuitDescription, 279 negativity qpp, 79 none qpp::Dynamic_bitset, 161 norm qpp, 80 nq_ qpp::experimental::QCircuitDescription, 279 number_theory.h, 340
maxn	nc_
maxn	nc_
maxn	nc
maxn	nc_

qpp::internal::IOManipPointer, 198	py1
qpp::internal::IOManipRange, 201	qpp::States, 298
qpp::internal::Singleton, 287	pz0
operator==	qpp::States, 298
qpp::Dynamic_bitset, 162	pz1
operator""_bra	qpp::States, 298
qpp::literals, 125 operator"" _i	q_ip_
qpp, 80	qpp::experimental::QCircuit, 257
qpp::literals, 125	QCircuit
operator""_ket	qpp::experimental::QCircuit, 251
qpp::literals, 126	QCircuitDescription
operator"" _prj	qpp::experimental::QCircuitDescription, 263
qpp::literals, 126	QFT
***	qpp, 88
p_	qpp::experimental::QCircuitDescription, 276
qpp::internal::IOManipPointer, 199	QPP_UNUSED_
pGHZ	qpp.h, 346
qpp::States, 297	qcd_
pb00	qpp::experimental::QCircuit, 257
qpp::States, 296	qmutualinfo
pb01	qpp, 88, 89
qpp::States, 296	qpp, 13 absm, 28
pb10	absn, 26 abssq, 28, 29
qpp::States, 297 pb11	adjoint, 30
qpp::States, 297	anticomm, 30
pi	apply, 30–32
qpp, 117	applyCTRL, 33, 34
plus	applyQFT, 34
qpp::States, 294	applyTFQ, 35
powm	avg, 35
qpp, 80	bigint, 26
prj	bloch2rho, 36
qpp, 81	bra, 26
prng_	choi2kraus, 36
qpp::RandomDevices, 285	choi2super, 37
probs_	chop, 116
qpp::experimental::QCircuit, 257	cmat, 26
prod	comm, 37
qpp, 81, 82	complement, 38
psi_	compperm, 38
qpp::experimental::QCircuit, 257	concurrence, 38
ptrace	conjugate, 40
qpp, 83	contfrac2x, 40
ptrace1	convergents, 41
qpp, 84	cor, 42
ptrace2	cosm, 42 cov, 42
qpp, 86 ptranspose	cplx, 26
qpp, 87	cwise, 43
pW	det, 43
qpp::States, 297	dirsum, 44, 45
px0	dirsumpow, 46
qpp::States, 297	disp, 46–48
px1	dmat, 26
qpp::States, 297	dyn_col_vect, 27
py0	dyn_mat, 27
qpp::States, 298	dyn_row_vect, 27

440	
ee, 116	ptranspose, 87
egcd, 48	QFT, 88
eig, 49	qmutualinfo, 88, 89
entanglement, 49, 50	rand, 89–91
entropy, 50, 51	randH, 91
eps, 116	randidx, 93
evals, 51	randket, 93
evects, 52	randkraus, 93
expm, 52	randn, 94, 95
factors, 52	randperm, 96
funm, 53	randprime, 96
gcd, 53, 54	randprob, 97
gconcurrence, 54	randrho, 97
grams, 55	randU, 97
heig, 56	randV, 98
hevals, 56	renyi, 98, 99
hevects, 57	reshape, 99
idx, 27	rho2bloch, 100
idx_infty, 116	rho2pure, 100
infty, 116	save, 101
inverse, 57	saveMATLAB, 101, 102
invperm, 57	schatten, 102
ip, 58	schmidtA, 103
isprime, 59	schmidtB, 103, 104
ket, 28	schmidtcoeffs, 104, 105
kraus2choi, 59	schmidtprobs, 105, 106
kraus2super, 60	sigma, 106
kron, 60–62	sinm, 107
kronpow, 62	spectralpowm, 107
lcm, 63	sqrtm, 108
load, 63	sum, 108, 109
loadMATLAB, 64, 65	super2choi, 109
logdet, 65	svals, 110
logm, 66	svd, 110
lognegativity, 66, 67	svdU, 110
marginalX, 67	svdV, 111
marginalY, 67	syspermute, 111, 112
maxn, 116	TFQ, 112
measure, 68–72	to_void, 28
measure_seq, 73, 74	trace, 112
mket, 74, 75	transpose, 113
modiny, 75	tsallis, 113, 114
modmul, 76	uniform, 114
modpow, 76	
•	var, 115 x2contfrac, 115
mprj, 77	ŕ
multiidx2n, 78	qpp.h, 344
n2multiidx, 78	QPP_UNUSED_, 346
negativity, 79	qpp::Bit_circuit, 129
norm, 80	Bit_circuit, 131
omega, 80	CNOT, 131
operator"" _i, 80	Dynamic_bitset, 132
pi, 117	FRED, 132
powm, 80	gate_count, 134
prj, 81	NOT, 132
prod, 81, 82	reset, 132
ptrace, 83	SWAP, 133
ptrace1, 84	TOF, 133
ptrace2, 86	X, 133

qpp::Bit_circuit::Gate_count, 171	RZ, 181
CNOT, 171	S, 185
FRED, 172	SWAPd, 181
NOT, 172	SWAP, 185
SWAP, 172	T, 185
TOF, 172	TOF, 185
X, 172	X, 185
qpp::Codes, 134	Xd, 183
\sim Codes, 136	Y, 186
Codes, 136	Z, 186
codeword, 136	Zd, 183
internal::Singleton< const Codes >, 137	qpp::IDisplay, 189
Type, 135	∼IDisplay, 191
	• •
qpp::Dynamic_bitset, 155	display, 191
all, 158	IDisplay, 190, 191
any, 158	operator<<, 192
count, 158	operator=, 191
data, 158	qpp::Init, 192
display, 159	∼Init, 193
Dynamic_bitset, 157	Init, 193
flip, 160	internal::Singleton< const Init >, 194
get, 160	qpp::QCircuit, 258
index_, 161	qpp::QCircuitDescription, 280
N_, 167	qpp::RandomDevices, 282
none, 161	\sim RandomDevices, 284
offset_, 161	get_prng, 284
operator!=, 162	internal::Singleton < RandomDevices >, 285
operator-, 162	load, 284
operator==, 162	prng_, 285
rand, 164	RandomDevices, 284
reset, 164, 165	rd_, 285
set, 165	save, 285
size, 166	qpp::States, 290
storage_size, 166	~States, 293
storage size , 167	b00, 295
storage_type, 157	b00, 233 b01, 296
to_string, 166	b10, 296
v_, 167	b11, 296
value_type, 157	GHZ, 296
qpp::Gates, 173	internal::Singleton< const States >, 295
~Gates, 175	jn, 293
CNOTba, 184	mes, 293
CNOT, 184	minus, 294
CTRL, 176	one, 294
CZ, 184	pGHZ, 297
expandout, 176, 177	pb00, 296
FRED, 184	pb01, 296
Fd, 178	pb10, 297
Gates, 175	pb11, 297
get_name, 179	plus, 294
H, 184	pW, 297
ld, 179	px0, 297
ld2, 185	px1, 297
internal::Singleton< const Gates >, 184	py0, 298
MODMUL, 179	py1, 298
Rn, 180	pz0, 298
RX, 180	pz1, 298
RY, 181	States, 293
,	Sidios, 200

	W 200	annuavaantianuMatrivNatDvaatar 010
	W, 298	qpp::exception::MatrixNotRvector, 213
	x0, 298	Exception, 214
	x1, 299	type_description, 214
	y0, 299	qpp::exception::MatrixNotSquare, 215
	y1, 299	Exception, 216
	z0, 299	type_description, 216
	z1, 299	qpp::exception::MatrixNotSquareNorCvector, 217
	zero, 295	Exception, 218
	Timer	type_description, 218
	~Timer, 304	qpp::exception::MatrixNotSquareNorRvector, 219
	display, 304	Exception, 220
	end_, 306	type_description, 220
	get_duration, 305	qpp::exception::MatrixNotSquareNorVector, 221
	operator=, 305	Exception, 222
	start_, 306	type_description, 222
	tic, 305	qpp::exception::MatrixNotVector, 223
	tics, 306	Exception, 224
	Timer, 303, 304	type_description, 224
	toc, 306	qpp::exception::NoCodeword, 228
qpp::	Timer $<$ T, CLOCK_T $>$, 302	Exception, 229
qpp::	exception, 117	type_description, 229
qpp::	exception::CustomException, 137	qpp::exception::NotBipartite, 230
	CustomException, 138	Exception, 231
	type_description, 139	type_description, 231
	what_, 139	qpp::exception::NotImplemented, 232
qpp::	exception::DimsInvalid, 140	Exception, 233
	Exception, 141	type_description, 233
	type_description, 141	qpp::exception::NotQubitCvector, 234
	exception::DimsMismatchCvector, 142	Exception, 235
	Exception, 143	type_description, 235
	type_description, 143	qpp::exception::NotQubitMatrix, 236
	exception::DimsMismatchMatrix, 144	Exception, 237
-11-1-	Exception, 145	type_description, 237
	type_description, 145	qpp::exception::NotQubitRvector, 238
	exception::DimsMismatchRvector, 146	Exception, 239
Abb.	Exception, 147	type_description, 239
	type_description, 147	qpp::exception::NotQubitSubsys, 240
	exception::DimsMismatchVector, 148	Exception, 241
чрр.	Exception, 149	type_description, 241
	type_description, 149	qpp::exception::NotQubitVector, 242
	exception::DimsNotEqual, 150	Exception, 243
чрр.	Exception, 151	type_description, 243
	type_description, 151	qpp::exception::OutOfRange, 244
	exception::Duplicates, 153	Exception, 245
чрр	Exception, 154	•
	•	type_description, 245
	type_description, 154	app::exception::PermInvalid, 246
qpp:	exception::Exception, 168	Exception, 247
	Exception, 170	type_description, 247
	msg_, 171	qpp::exception::PermMismatchDims, 248
	type_description, 170	Exception, 249
	what, 170	type_description, 249
	where_, 171	qpp::exception::QuditAlreadyMeasured, 280
dbb::	exception::MatrixMismatchSubsys, 209	Exception, 281
	Exception, 210	type_description, 282
	type_description, 210	qpp::exception::SizeMismatch, 288
dbb::	exception::MatrixNotCvector, 211	Exception, 289
	Exception, 212	type_description, 290
	type_description, 212	qpp::exception::SubsysMismatchDims, 300

Exception, 301	get_measurement_steps, 273
type_description, 301	get_measurements, 273
qpp::exception::TypeMismatch, 307	get_name, 273
Exception, 308	get_nc, 273
type_description, 309	get_non_measured, 274
qpp::exception::UndefinedType, 309	get_nq, 274
Exception, 310	get_total_count, 274
type_description, 311	MeasureType, 263
qpp::exception::Unknown, 311	measured_, 278
Exception, 312	measurement_steps_, 278
type_description, 313	measurements_, 279
qpp::exception::ZeroSize, 313	measureV, 274, 275
Exception, 314	measureZ, 275
type_description, 315	name_, 279
qpp::experimental, 119	nc_, 279
qpp::experimental::QCircuit, 250	nq_, 279
display, 252	operator<<, 276–278
dits_, 256	QCircuitDescription, 263
get_circuit_description, 252	QFT, 276
get_dit, 252	step_cnt_, 279
get_dits, 253	TFQ, 276
get_ip, 253	qpp::experimental::QCircuitDescription::GateStep, 186
get_m_ip, 253	ctrl_, 188
get_measured, 253, 254	gate_, 188
get_not_measured, 254	gate_type_, 188
get_probs, 254	GateStep, 187
get_psi, 254	name_, 188
get_q_ip, 255	step_no_, 188
get_relative_pos_, 255	target_, 189
	- -
ip_, 257	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257	qpp::experimental::QCircuitDescription::MeasureStep, 225
ip_, 257 m_ip_, 257 probs_, 257	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227
ip_, 257 m_ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227
ip_, 257 m_ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227
ip_, 257 m_ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227 qpp::internal, 119
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227 qpp::internal, 119 check_cvector, 120
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227 qpp::internal, 119 check_cvector, 120 check_dims, 120
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227 qpp::internal, 119 check_cvector, 120 check_dims, 120 check_dims_match_cvect, 120
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 pri_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 q_ip_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 268	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 q_ip_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 265 CTRL_custom, 268 CTRL, 266, 267	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 268 CTRL, 263–265 CTRL, 266, 267 d_, 278	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 265 cTRL_custom, 268 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 265 cTRL_custom, 268 CTRL, 263–265 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262 gates_, 278	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL_custom, 265 cTRL_ge6, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262 gates_, 278 get_d, 271	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262 gates_, 278 get_d, 271 get_gate_count, 271	qpp::experimental::QCircuitDescription::MeasureStep,
ip_, 257 m_ip_, 257 probs_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262 gates_, 278 get_d, 271 get_gate_count, 271 get_gates, 272	qpp::experimental::QCircuitDescription::MeasureStep, 225 c_reg_, 226 mats_, 226 MeasureStep, 226 measurement_type_, 227 name_, 227 step_no_, 227 target_, 227 qpp::internal, 119 check_cvector, 120 check_dims_match_cvect, 120 check_dims_match_mat, 121 check_dims_match_rvect, 121 check_eq_dims, 121 check_eq_dims, 121 check_matching_sizes, 121 check_no_duplicates, 121 check_perm, 122 check_qubit_cvector, 122 check_qubit_rvector, 122 check_qubit_rvector, 122 check_rvector, 122 check_square_mat, 123 check_subsys_match_dims, 123
ip_, 257 m_ip_, 257 probs_, 257 psi_, 257 q_ip_, 257 QCircuit, 251 qcd_, 257 reset, 255 run, 255 set_dit, 256 set_measured_, 256 subsys_, 258 qpp::experimental::QCircuitDescription, 259 cCTRL_custom, 265 cCTRL, 263–265 CTRL_custom, 268 CTRL, 266, 267 d_, 278 display, 268 gate, 269, 270 gate_custom, 270 gate_fan, 270, 271 GateType, 262 gates_, 278 get_d, 271 get_gate_count, 271	qpp::experimental::QCircuitDescription::MeasureStep,

get_dim_subsys, 123	randH
get_num_subsys, 123	qpp, 91
kron2, 124	randidx
multiidx2n, 124	qpp, 93
n2multiidx, 124	randket
variadic_vector_emplace, 124	qpp, 93
qpp::internal::Display_Impl_, 152	randkraus
display_impl_, 152	qpp, 93
qpp::internal::IOManipEigen, 194	randn
A , 196	qpp, 94, 95
chop_, 196	random.h, 346
display, 195	RandomDevices
IOManipEigen, 195	qpp::RandomDevices, 284
qpp::internal::IOManipPointer	randperm
display, 198	qpp, 96
end , 198	randprime
IOManipPointer, 197, 198	qpp, 96
N , 199	randprob
operator=, 198	•
·	qpp, 97 randrho
p_, 199	
separator_, 199	qpp, 97
start_, 199	randU
qpp::internal::IOManipPointer< PointerType >, 196	qpp, 97
qpp::internal::IOManipRange	randV
display, 201	qpp, 98
end_, 202	rd_
first_, 202	qpp::RandomDevices, 285
IOManipRange, 201	renyi
last_, 202	qpp, 98, 99
operator=, 201	reset
separator_, 202	qpp::Bit_circuit, 132
start_, 202	qpp::Dynamic_bitset, 164, 165
qpp::internal::IOManipRange< InputIterator >, 200	qpp::experimental::QCircuit, 255
qpp::internal::Singleton	reshape
\sim Singleton, 287	qpp, 99
get_instance, 287	rho2bloch
get_thread_local_instance, 287	qpp, 100
operator=, 287	rho2pure
Singleton, 287	qpp, 100
qpp::internal::Singleton< T >, 286	Rn
qpp::is_complex< std::complex< T >>, 204	qpp::Gates, 180
qpp::is_complex< T >, 203	run
<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T</pre>	qpp::experimental::QCircuit, 255
$>$ ().begin()), decltype(std::declval $<$ T $>$ (). \leftarrow	RX
end()), typename T::value_type > >, 206	qpp::Gates, 180
qpp::is_iterable < T, typename >, 205	RY
qpp::is_matrix_expression< Derived >, 207	qpp::Gates, 181
qpp::literals, 125	RZ
operator"" bra 125	qpp::Gates, 181
operator"" _i, 125 operator"" _ket, 126 operator"" _prj, 126	qppdatos, 101
operator"" ket 126	S
operator"" pri 126	qpp::Gates, 185
qpp::make_void	SWAPd
	qpp::Gates, 181
type, 208	SWAP
qpp::make_void< Ts >, 208	
	gppbit circuit. 133
rand	qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 172
rand app. 89–91	qpp::Bit_circuit::Gate_count, 172
qpp, 89–91 qpp::Dynamic_bitset, 164	

qpp, 101	qpp, 108, 109
qpp::RandomDevices, 285	super2choi
saveMATLAB	qpp, 109
qpp, 101, 102	svals
schatten	qpp, 110
qpp, 102	svd
schmidtA	qpp, 110 svdU
qpp, 103 schmidtB	qpp, 110
qpp, 103, 104	svdV
schmidtcoeffs	qpp, 111
qpp, 104, 105	syspermute
schmidtprobs	qpp, 111, 112
qpp, 105, 106	
separator_	T
qpp::internal::IOManipPointer, 199	qpp::Gates, 185
qpp::internal::IOManipRange, 202	TFQ
set	qpp, 112
gpp::Dynamic bitset, 165	qpp::experimental::QCircuitDescription, 276
set_dit	TOF
qpp::experimental::QCircuit, 256	qpp::Bit_circuit, 133
set_measured_	qpp::Bit_circuit::Gate_count, 172
qpp::experimental::QCircuit, 256	qpp::Gates, 185
sigma	target_
qpp, 106	<pre>qpp::experimental::QCircuitDescription::GateStep,</pre>
Singleton	
qpp::internal::Singleton, 287	qpp::experimental::QCircuitDescription::Measure ←
sinm	Step, 227
qpp, 107	qpp::Timer, 305
size	tics
qpp::Dynamic_bitset, 166	qpp::Timer, 306
spectralpowm	Timer
qpp, 107	qpp::Timer, 303, 304
sqrtm	to string
qpp, 108	qpp::Dynamic_bitset, 166
start_	to_void
qpp::Timer, 306	qpp, 28
qpp::internal::IOManipPointer, 199	toc
qpp::internal::IOManipRange, 202	qpp::Timer, 306
States	trace
qpp::States, 293	qpp, 112
statistics.h, 347	traits.h, 349
step_cnt_	transpose
qpp::experimental::QCircuitDescription, 279	qpp, 113
step_no_	tsallis
qpp::experimental::QCircuitDescription::GateStep,	qpp, 113, 114
188	Type
qpp::experimental::QCircuitDescription::Measure ←	qpp::Codes, 135
Step, 227	type
storage_size	qpp::make_void, 208
qpp::Dynamic_bitset, 166 storage_size_	type_description
qpp::Dynamic_bitset, 167	<pre>qpp::exception::CustomException, 139 qpp::exception::DimsInvalid, 141</pre>
storage_type	qpp::exception::DimsMismatchCvector, 143
qpp::Dynamic_bitset, 157	qpp::exception::DimsMismatchMatrix, 145
subsys_	qpp::exception::DimsMismatchNector, 147
qpp::experimental::QCircuit, 258	qpp::exception::DimsMismatchVector, 149
sum	qpp::exception::DimsNotEqual, 151
	allelie a serlies on messengendamit () ,

	_	
qpp::exception::Duplicates, 154	x2cc	ontfrac
qpp::exception::Exception, 170		qpp, 115
qpp::exception::MatrixMismatchSubsys, 210	Xd	
qpp::exception::MatrixNotCvector, 212		qpp::Gates, 183
qpp::exception::MatrixNotRvector, 214		qpp e.e.c.e.
	Υ	
qpp::exception::MatrixNotSquare, 216	•	ann::Catan 106
qpp::exception::MatrixNotSquareNorCvector, 218	•	qpp::Gates, 186
<pre>qpp::exception::MatrixNotSquareNorRvector, 220</pre>	y0	
qpp::exception::MatrixNotSquareNorVector, 222		qpp::States, 299
qpp::exception::MatrixNotVector, 224	y1	
qpp::exception::NoCodeword, 229		qpp::States, 299
gpp::exception::NotBipartite, 231		
	Z	
qpp::exception::NotImplemented, 233		qpp::Gates, 186
qpp::exception::NotQubitCvector, 235	z0	qppdatoo, 100
qpp::exception::NotQubitMatrix, 237	20	
qpp::exception::NotQubitRvector, 239		qpp::States, 299
qpp::exception::NotQubitSubsys, 241	z1	
qpp::exception::NotQubitVector, 243		qpp::States, 299
	Zd	
qpp::exception::OutOfRange, 245		qpp::Gates, 183
qpp::exception::PermInvalid, 247	zero	
qpp::exception::PermMismatchDims, 249	2610	
qpp::exception::QuditAlreadyMeasured, 282		qpp::States, 295
qpp::exception::SizeMismatch, 290		
qpp::exception::SubsysMismatchDims, 301		
qpp::exception::TypeMismatch, 309		
qpp::exception::UndefinedType, 311		
qpp::exception::Unknown, 313		
qpp::exception::ZeroSize, 315		
types.h, 350		
-31)		
uniform		
uniform		
uniform qpp, 114		
qpp, 114		
qpp, 114 v_		
qpp, 114		
qpp, 114 v_		
<pre>qpp, 114 v_</pre>		
qpp, 114 v_ qpp::Dynamic_bitset, 167 value_type qpp::Dynamic_bitset, 157		
<pre>qpp, 114 v_</pre>		
<pre>qpp, 114 v_</pre>		
qpp, 114 v_		
<pre>qpp, 114 v_</pre>		
qpp, 114 V_		