Quantum++ v1.2

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 		 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 		 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 		 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	ferer	nce .		 	 	 	 		 	 	 		 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 		 26
			6.1.2.1	bi	igint			 	 	 	 		 	 	 		 26
			6.1.2.2	bı	ra .			 	 	 	 		 	 	 		 26
			6.1.2.3	CI	mat			 	 	 	 		 	 	 		 27
			6.1.2.4	c	plx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dı	mat			 	 	 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 		 27
			6.1.2.8	d١	vn ro	ow v	ect		 	 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	hash_eigen()	56
6.1.3.61	heig()	57
6.1.3.62	hevals()	57
6.1.3.63	hevects()	58
6.1.3.64	inverse()	58
6.1.3.65	invperm()	58
6.1.3.66	ip() [1/2]	59
6.1.3.67	ip() [2/2]	59
6.1.3.68	isprime()	60
6.1.3.69	kraus2choi()	60
6.1.3.70	kraus2super()	61
6.1.3.71	kron() [1/4]	61
6.1.3.72	kron() [2/4]	62
6.1.3.73	kron() [3/4]	62
6.1.3.74	kron() [4/4]	63
6.1.3.75	kronpow()	63
6.1.3.76	lcm() [1/2]	64
6.1.3.77	lcm() [2/2]	64
6.1.3.78	load()	64
6.1.3.79	loadMATLAB() [1/2]	65
6.1.3.80	loadMATLAB() [2/2]	66
6.1.3.81	logdet()	66
6.1.3.82	logm()	67
6.1.3.83	lognegativity() [1/2]	67
6.1.3.84	lognegativity() [2/2]	68
6.1.3.85	marginalX()	68
6.1.3.86	marginalY()	68

6.1.3.87 measure() [1/9]
6.1.3.88 measure() [2/9]
6.1.3.89 measure() [3/9]
6.1.3.90 measure() [4/9]
6.1.3.91 measure() [5/9]
6.1.3.92 measure() [6/9]
6.1.3.93 measure() [7/9]
6.1.3.94 measure() [8/9]
6.1.3.95 measure() [9/9]
6.1.3.96 measure_seq() [1/2]
6.1.3.97 measure_seq() [2/2]
6.1.3.98 mket() [1/2]
6.1.3.99 mket() [2/2]
6.1.3.100 modinv()
6.1.3.101 modmul()
6.1.3.102 modpow()
6.1.3.103 mprj() [1/2]
6.1.3.104 mprj() [2/2]
6.1.3.105 multiidx2n()
6.1.3.106 n2multiidx()
6.1.3.107 negativity() [1/2]
6.1.3.108 negativity() [2/2]
6.1.3.109 norm()
6.1.3.110 normalize()
6.1.3.111 omega()
6.1.3.112 operator""""_i()
6.1.3.113 powm()
6.1.3.114 prj()
6.1.3.115 prod() [1/3]
6.1.3.116 prod() [2/3]

vi

6.1.3.117 prod() [3/3]	84
6.1.3.118 ptrace() [1/2]	84
6.1.3.119 ptrace() [2/2]	85
6.1.3.120 ptrace1() [1/2]	85
6.1.3.121 ptrace1() [2/2]	86
6.1.3.122 ptrace2() [1/2]	86
6.1.3.123 ptrace2() [2/2]	87
6.1.3.124 ptranspose() [1/2]	87
6.1.3.125 ptranspose() [2/2]	88
6.1.3.126 QFT()	88
6.1.3.127 qmutualinfo() [1/2]	89
6.1.3.128 qmutualinfo() [2/2]	89
6.1.3.129 rand() [1/5]	90
6.1.3.130 rand() [2/5]	90
6.1.3.131 rand() [3/5]	91
6.1.3.132 rand() [4/5]	91
6.1.3.133 rand() [5/5]	92
6.1.3.134 randH()	92
6.1.3.135 randidx()	93
6.1.3.136 randket()	93
6.1.3.137 randkraus()	93
6.1.3.138 randn() [1/4]	94
6.1.3.139 randn() [2/4]	94
6.1.3.140 randn() [3/4]	95
6.1.3.141 randn() [4/4]	95
6.1.3.142 randperm()	96
6.1.3.143 randprime()	96
6.1.3.144 randprob()	97
6.1.3.145 randrho()	97
6.1.3.146 randU()	97

CONTENTS vii

6.1.3.147 randV()
6.1.3.148 renyi() [1/2]
6.1.3.149 renyi() [2/2]
6.1.3.150 reshape()
6.1.3.151 rho2bloch()
6.1.3.152 rho2pure()
6.1.3.153 save()
6.1.3.154 saveMATLAB() [1/2]
6.1.3.155 saveMATLAB() [2/2]
6.1.3.156 schatten()
6.1.3.157 schmidtA() [1/2]
6.1.3.158 schmidtA() [2/2]
6.1.3.159 schmidtB() [1/2]
6.1.3.160 schmidtB() [2/2]
6.1.3.161 schmidtcoeffs() [1/2]
6.1.3.162 schmidtcoeffs() [2/2]
6.1.3.163 schmidtprobs() [1/2]
6.1.3.164 schmidtprobs() [2/2]
6.1.3.165 sigma()
6.1.3.166 sinm()
6.1.3.167 spectralpowm()
6.1.3.168 sqrtm()
6.1.3.169 sum() [1/3]
6.1.3.170 sum() [2/3]
6.1.3.171 sum() [3/3]
6.1.3.172 super2choi()
6.1.3.173 svals()
6.1.3.174 svd()
6.1.3.175 svdU()
6.1.3.176 svdV()

viii CONTENTS

		6.1.3.177	syspermute() [1/2]	 	 	111
		6.1.3.178	syspermute() [2/2]	 	 	112
		6.1.3.179	TFQ()	 	 	112
		6.1.3.180	trace()	 	 	113
		6.1.3.181	transpose()	 	 	113
		6.1.3.182	tsallis() [1/2]	 	 	113
		6.1.3.183	tsallis() [2/2]	 	 	114
		6.1.3.184	uniform()	 	 	114
		6.1.3.185	var()	 	 	115
		6.1.3.186	x2contfrac()	 	 	115
	6.1.4	Variable	Occumentation	 	 	116
		6.1.4.1	chop	 	 	116
		6.1.4.2	ee	 	 	116
		6.1.4.3	infty	 	 	116
		6.1.4.4	maxn	 	 	116
		6.1.4.5	pi	 	 	116
6.2	qpp::ex	ception N	mespace Reference	 	 	116
	6.2.1	Detailed	Description	 	 	118
6.3	qpp::ex	perimenta	Namespace Reference	 	 	118
	6.3.1	Detailed	Description	 	 	118
6.4	qpp::int	ternal Nan	espace Reference	 	 	118
	6.4.1	Detailed	Description	 	 	120
	6.4.2	Function	Documentation	 	 	120
		6.4.2.1	check_cvector()	 	 	120
		6.4.2.2	check_dims()	 	 	120
		6.4.2.3	check_dims_match_cvect()	 	 	120
		6.4.2.4	check_dims_match_mat()	 	 	120
		6.4.2.5	check_dims_match_rvect()	 	 	121
		6.4.2.6	check_eq_dims()	 	 	121
		6.4.2.7	check_matching_sizes()	 	 	121

		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	21
		6.4.2.10	check_perm()	21
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	22
		6.4.2.16	check_square_mat()	22
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	23
		6.4.2.22	hash_combine()	23
		6.4.2.23	kron2()	24
		6.4.2.24	multiidx2n()	24
		6.4.2.25	n2multiidx()	24
		6.4.2.26	variadic_vector_emplace() [1/2]	24
		6.4.2.27	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator""""_bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator""""_prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	160
		7.12.4.10 none()	161
		7.12.4.11 offset_()	161
		7.12.4.12 operator"!=()	161
		7.12.4.13 operator-()	162
		7.12.4.14 operator==()	162
		7.12.4.15 rand() [1/2]	162
		7.12.4.16 rand() [2/2]	163
		7.12.4.17 reset() [1/2]	163
		7.12.4.18 reset() [2/2]	163
		7.12.4.19 set() [1/2]	164
		7.12.4.20 set() [2/2]	164
		7.12.4.21 size()	164
		7.12.4.22 storage_size()	164
		7.12.4.23 to_string()	165
	7.12.5	Member Data Documentation	165
		7.12.5.1 N	165
		7.12.5.2 storage_size	165
		7.12.5.3 v	166
7.13	qpp::int	ternal::EqualEigen Class Reference	166
	7.13.1	Detailed Description	166
	7.13.2	Member Function Documentation	166
		7.13.2.1 operator()()	166
7.14	qpp::ex	cception::Exception Class Reference	167
	7.14.1	Detailed Description	168
	7.14.2	Constructor & Destructor Documentation	169
		7.14.2.1 Exception()	169
	7.14.3	Member Function Documentation	169
		7.14.3.1 type_description()	169
		7.14.3.2 what()	170

xiv CONTENTS

	7.14.4	Member Data Documentation	170
		7.14.4.1 msg	170
		7.14.4.2 where	170
7.15	qpp::Bi	circuit::Gate_count Struct Reference	170
	7.15.1	Member Data Documentation	170
		7.15.1.1 CNOT	171
		7.15.1.2 FRED	171
		7.15.1.3 NOT	171
		7.15.1.4 SWAP	171
		7.15.1.5 TOF	171
		7.15.1.6 X	171
7.16	qpp::Ga	es Class Reference	172
	7.16.1	Detailed Description	174
	7.16.2	Constructor & Destructor Documentation	174
		7.16.2.1 Gates()	174
		7.16.2.2 ~Gates()	174
	7.16.3	Member Function Documentation	175
		7.16.3.1 CTRL()	175
		7.16.3.2 expandout() [1/3]	175
		7.16.3.3 expandout() [2/3]	176
		7.16.3.4 expandout() [3/3]	177
		7.16.3.5 Fd()	177
		7.16.3.6 get_name()	178
		7.16.3.7 ld()	178
		7.16.3.8 MODMUL()	178
		7.16.3.9 Rn()	179
		7.16.3.10 RX()	179
		7.16.3.11 RY()	180
		7.16.3.12 RZ()	180
		7.16.3.13 SWAPd()	180

CONTENTS xv

		7.16.3.14 Xd()	32
		7.16.3.15 Zd()	32
	7.16.4	Friends And Related Function Documentation	33
		7.16.4.1 internal::Singleton < const Gates >	33
	7.16.5	Member Data Documentation	33
		7.16.5.1 CNOT	33
		7.16.5.2 CNOTba	33
		7.16.5.3 CZ	33
		7.16.5.4 FRED	33
		7.16.5.5 H	34
		7.16.5.6 ld2	34
		7.16.5.7 S	34
		7.16.5.8 SWAP	34
		7.16.5.9 T	34
		7.16.5.10 TOF	34
		7.16.5.11 X	35
		7.16.5.12 Y	35
		7.16.5.13 Z	35
7.17	qpp::Q0	Circuit::GateStep Struct Reference	35
	7.17.1	Detailed Description	36
	7.17.2	Constructor & Destructor Documentation	36
		7.17.2.1 GateStep() [1/2]	36
		7.17.2.2 GateStep() [2/2]	36
	7.17.3	Member Data Documentation	37
		7.17.3.1 ctrl	37
		7.17.3.2 gate_hash	37
		7.17.3.3 gate_type	37
		7.17.3.4 name	37
		7.17.3.5 target	38
7.18	qpp::int	ternal::HashEigen Class Reference	38

xvi CONTENTS

	7.18.1	Detailed Description	188
	7.18.2	Member Function Documentation	188
		7.18.2.1 operator()()	188
7.19	qpp::ID	isplay Class Reference	189
	7.19.1	Detailed Description	190
	7.19.2	Constructor & Destructor Documentation	190
		7.19.2.1 IDisplay() [1/3]	190
		7.19.2.2 IDisplay() [2/3]	190
		7.19.2.3 IDisplay() [3/3]	190
		7.19.2.4 ~IDisplay()	190
	7.19.3	Member Function Documentation	191
		7.19.3.1 display()	191
		7.19.3.2 operator=() [1/2]	191
		7.19.3.3 operator=() [2/2]	191
	7.19.4	Friends And Related Function Documentation	191
		7.19.4.1 operator <<	191
7.20	qpp::IJS	SON Class Reference	192
	7.20.1	Detailed Description	192
	7.20.2	Constructor & Destructor Documentation	192
		7.20.2.1 IJSON() [1/3]	193
		7.20.2.2 IJSON() [2/3]	193
		7.20.2.3 IJSON() [3/3]	193
		7.20.2.4 ~IJSON()	193
	7.20.3	Member Function Documentation	193
		7.20.3.1 operator=() [1/2]	193
		7.20.3.2 operator=() [2/2]	193
		7.20.3.3 to_JSON()	193
7.21	qpp::Ini	t Class Reference	194
	7.21.1	Detailed Description	195
	7.21.2	Constructor & Destructor Documentation	195

CONTENTS xvii

		7.21.2.1 Init()
		7.21.2.2 ~Init()
	7.21.3	Friends And Related Function Documentation
		7.21.3.1 internal::Singleton < const Init >
7.22	qpp::ex	cception::InvalidIterator Class Reference
	7.22.1	Detailed Description
	7.22.2	Member Function Documentation
		7.22.2.1 Exception()
		7.22.2.2 type_description()
7.23	qpp::int	ternal::IOManipEigen Class Reference
	7.23.1	Constructor & Destructor Documentation
		7.23.1.1 IOManipEigen() [1/2]
		7.23.1.2 IOManipEigen() [2/2]
	7.23.2	Member Function Documentation
		7.23.2.1 display()
	7.23.3	Member Data Documentation
		7.23.3.1 A
		7.23.3.2 chop
7.24	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference
	7.24.1	Constructor & Destructor Documentation
		7.24.1.1 IOManipPointer() [1/2]
		7.24.1.2 IOManipPointer() [2/2]
	7.24.2	Member Function Documentation
		7.24.2.1 display()
		7.24.2.2 operator=()
	7.24.3	Member Data Documentation
		7.24.3.1 end
		7.24.3.2 N
		7.24.3.3 p
		7.24.3.4 separator

xviii CONTENTS

		7.24.3.5	S	tart_																	 	 		 	203
7.25	qpp::in	ternal::ION	Maı	nipF	?ange	e<	Inp	putl	Iter	ator	r >	Cla	ass	Ter	mpl	ate	Ref	fere	nce		 	 		 	204
	7.25.1	Construc	ctor	· & C	Destr	ucto	or I	Dod	cun	nen	tati	on									 	 		 	205
		7.25.1.1	IC	ЭMа	anipP	Rang	ge(() [1/2	2]											 	 		 	205
		7.25.1.2	IC	ЭMа	anipP	Rang	ge(() [2/2	2]											 	 		 	205
	7.25.2	Member	Fu	nctio	on D	ocu	ıme	enta	atio	n											 	 		 	205
		7.25.2.1	d	ispla	ay()																 	 		 	205
		7.25.2.2	0	pera	ator=	() .															 	 		 	206
	7.25.3	Member	Da	ıta C	Ocur	men	nta	ıtior	n.												 	 		 	206
		7.25.3.1	е	nd_																	 	 		 	206
		7.25.3.2	fi	rst_																	 	 		 	206
		7.25.3.3	la	ıst_																	 	 		 	206
		7.25.3.4	S	epa	rator																 	 		 	206
		7.25.3.5	S	tart_																	 	 		 	206
7.26	qpp::is_	_complex<	< 1	Γ>	Struc	ct Te	em	ıpla	ate	Ref	ere	nce									 	 		 	207
	7.26.1	Detailed	De	scri	ption	١.															 	 		 	207
7.27	qpp::is_	_complex<	< 8	std::c	comp	olex	: <	T >	> >	> St	ruc	t Te	emp	olate	e R	efei	enc	е			 	 		 	208
	7.27.1	Detailed	De	scri	ption	۱.															 	 		 	208
7.28	qpp::is_	_iterable<	< T ,	typ	enan	ne >	> 5	Strı	uct	Ten	npla	ate	Ref	fere	ence	€.					 	 		 	209
	7.28.1	Detailed	De	scri	ption	۱.															 	 		 	209
7.29		_iterable< d()), decIty																_			 •				210
		Detailed								-															
7.30		matrix ex																							
7.00		Detailed																							
7.31		Circuit::ite																							
7.01		Detailed																							
		Member			•																				
		7.31.2.1																							213
		7.31.2.2																							
		7.31.2.3					_																		
		1.01.2.3	Р	Jirit	ΟI .		•		•			•		٠.		•			٠.	•	 	 •	٠.	 	۲۱4

CONTENTS xix

		7.31.2.4 reference	14
		7.31.2.5 value_type	14
	7.31.3	Constructor & Destructor Documentation	14
		7.31.3.1 iterator() [1/2]	14
		7.31.3.2 iterator() [2/2]	14
	7.31.4	Member Function Documentation	14
		7.31.4.1 operator"!=()	14
		7.31.4.2 operator*()	15
		7.31.4.3 operator++() [1/2]	15
		7.31.4.4 operator++() [2/2]	15
		7.31.4.5 operator=()	16
		7.31.4.6 operator==()	16
		7.31.4.7 set_begin_()	16
		7.31.4.8 set_end_()	16
	7.31.5	Member Data Documentation	17
		7.31.5.1 elem	17
		7.31.5.2 qc	17
7.32	qpp::ma	ake_void < Ts > Struct Template Reference	17
	7.32.1	Detailed Description	17
	7.32.2	Member Typedef Documentation	18
		7.32.2.1 type	18
7.33	qpp::ex	ception::MatrixMismatchSubsys Class Reference	18
	7.33.1	Detailed Description	19
	7.33.2	Member Function Documentation	19
		7.33.2.1 Exception()	19
		7.33.2.2 type_description()	20
7.34	qpp::ex	ception::MatrixNotCvector Class Reference	20
	7.34.1	Detailed Description	21
	7.34.2	Member Function Documentation	21
		7.34.2.1 Exception()	21

		7.34.2.2 type_description()	222
7.35	qpp::ex	cception::MatrixNotRvector Class Reference	222
	7.35.1	Detailed Description	223
	7.35.2	Member Function Documentation	223
		7.35.2.1 Exception()	223
		7.35.2.2 type_description()	224
7.36	qpp::ex	cception::MatrixNotSquare Class Reference	224
	7.36.1	Detailed Description	225
	7.36.2	Member Function Documentation	225
		7.36.2.1 Exception()	225
		7.36.2.2 type_description()	226
7.37	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	226
	7.37.1	Detailed Description	227
	7.37.2	Member Function Documentation	227
		7.37.2.1 Exception()	227
		7.37.2.2 type_description()	228
7.38	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	228
	7.38.1	Detailed Description	229
	7.38.2	Member Function Documentation	229
		7.38.2.1 Exception()	229
		7.38.2.2 type_description()	230
7.39	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	230
	7.39.1	Detailed Description	231
	7.39.2	Member Function Documentation	231
		7.39.2.1 Exception()	231
		7.39.2.2 type_description()	232
7.40	qpp::ex	ception::MatrixNotVector Class Reference	232
	7.40.1	Detailed Description	233
	7.40.2	Member Function Documentation	233
		7.40.2.1 Exception()	233

CONTENTS xxi

		7.40.2.2 type_description()
7.41	qpp::Q	Circuit::MeasureStep Struct Reference
	7.41.1	Detailed Description
	7.41.2	Constructor & Destructor Documentation
		7.41.2.1 MeasureStep() [1/2]
		7.41.2.2 MeasureStep() [2/2]
	7.41.3	Member Data Documentation
		7.41.3.1 c_reg
		7.41.3.2 mats_hash
		7.41.3.3 measurement_type
		7.41.3.4 name
		7.41.3.5 target
7.42	qpp::ex	cception::NoCodeword Class Reference
	7.42.1	Detailed Description
	7.42.2	Member Function Documentation
		7.42.2.1 Exception()
		7.42.2.2 type_description()
7.43	qpp::No	oiseBase< T > Class Template Reference
	7.43.1	Detailed Description
	7.43.2	Member Typedef Documentation
		7.43.2.1 noise_type
	7.43.3	Constructor & Destructor Documentation
		7.43.3.1 NoiseBase() [1/2]
		7.43.3.2 NoiseBase() [2/2]
		7.43.3.3 ~NoiseBase()
	7.43.4	Member Function Documentation
		7.43.4.1 compute_probs_()
		7.43.4.2 compute_state_()
		7.43.4.3 get_d()
		7.43.4.4 get_Ks()

xxii CONTENTS

		7.43.4.5 get_last_idx()	44
		7.43.4.6 get_last_K()	44
		7.43.4.7 get_last_p()	44
		7.43.4.8 get_probs()	44
		7.43.4.9 operator()() [1/3]	44
		7.43.4.10 operator()() [2/3]	45
		7.43.4.11 operator()() [3/3]	45
	7.43.5	Member Data Documentation	46
		7.43.5.1 d	46
		7.43.5.2 generated	46
		7.43.5.3 i	46
		7.43.5.4 Ks	46
		7.43.5.5 probs	47
7.44	qpp::No	oiseType Class Reference	47
	7.44.1	Detailed Description	47
7.45	qpp::ex	cception::NotBipartite Class Reference	47
	7.45.1	Detailed Description	49
	7.45.2	Member Function Documentation	49
		7.45.2.1 Exception()	49
		7.45.2.2 type_description()	49
7.46	qpp::ex	cception::NotImplemented Class Reference	50
	7.46.1	Detailed Description	51
	7.46.2	Member Function Documentation	51
		7.46.2.1 Exception()	51
		7.46.2.2 type_description()	51
7.47	qpp::ex	cception::NotQubitCvector Class Reference	52
	7.47.1	Detailed Description	53
	7.47.2	Member Function Documentation	53
		7.47.2.1 Exception()	53
		7.47.2.2 type_description()	53

CONTENTS xxiii

7.48	qpp::ex	cception::NotQubitMatrix Class Reference	254
	7.48.1	Detailed Description	255
	7.48.2	Member Function Documentation	255
		7.48.2.1 Exception()	255
		7.48.2.2 type_description()	255
7.49	qpp::ex	cception::NotQubitRvector Class Reference	256
	7.49.1	Detailed Description	257
	7.49.2	Member Function Documentation	257
		7.49.2.1 Exception()	257
		7.49.2.2 type_description()	257
7.50	qpp::ex	cception::NotQubitSubsys Class Reference	258
	7.50.1	Detailed Description	259
	7.50.2	Member Function Documentation	259
		7.50.2.1 Exception()	259
		7.50.2.2 type_description()	259
7.51	qpp::ex	cception::NotQubitVector Class Reference	260
	7.51.1	Detailed Description	261
	7.51.2	Member Function Documentation	261
		7.51.2.1 Exception()	261
		7.51.2.2 type_description()	261
7.52	qpp::ex	cception::OutOfRange Class Reference	262
	7.52.1	Detailed Description	263
	7.52.2	Member Function Documentation	263
		7.52.2.1 Exception()	263
		7.52.2.2 type_description()	263
7.53	qpp::ex	cception::PermInvalid Class Reference	264
	7.53.1	Detailed Description	265
	7.53.2	Member Function Documentation	265
		7.53.2.1 Exception()	265
		7.53.2.2 type_description()	265

xxiv CONTENTS

7.54	qpp::ex	ception::PermMismatchDims Class Reference	6
	7.54.1	Detailed Description	3 7
	7.54.2	Member Function Documentation	3 7
		7.54.2.1 Exception()	37
		7.54.2.2 type_description()	57
7.55	qpp::Q	Circuit Class Reference	8
	7.55.1	Detailed Description	'2
	7.55.2	Member Typedef Documentation	'2
		7.55.2.1 const_iterator	'2
	7.55.3	Member Enumeration Documentation	'2
		7.55.3.1 GateType	'2
		7.55.3.2 MeasureType	'3
		7.55.3.3 StepType	'4
	7.55.4	Constructor & Destructor Documentation	'4
		7.55.4.1 QCircuit()	'4
		7.55.4.2 ~QCircuit()	'4
	7.55.5	Member Function Documentation	'4
		7.55.5.1 add_hash_()	'5
		7.55.5.2 begin() [1/2]	'5
		7.55.5.3 begin() [2/2]	'5
		7.55.5.4 cbegin()	'5
		7.55.5.5 cCTRL() [1/4]	'6
		7.55.5.6 cCTRL() [2/4]	'6
		7.55.5.7 cCTRL() [3/4]	'6
		7.55.5.8 cCTRL() [4/4]	'7
		7.55.5.9 cCTRL_custom()	'7
		7.55.5.10 cend()	'8
		7.55.5.11 CTRL() [1/4]	'8
		7.55.5.12 CTRL() [2/4]	'9
		7.55.5.13 CTRL() [3/4]	'9

CONTENTS xxv

7.55.5.14 CTRL() [4/4]
7.55.5.14 CTRL() [4/4]
7.55.5.16 display()
7.55.5.17 end() [1/2]
7.55.5.18 end() [2/2]
7.55.5.19 gate() [1/3]
7.55.5.20 gate() [2/3]
7.55.5.21 gate() [3/3]
7.55.5.22 gate_custom()
7.55.5.23 gate_fan() [1/3]
7.55.5.24 gate_fan() [2/3]
7.55.5.25 gate_fan() [3/3]
7.55.5.26 get_cmat_hash_tbl_()
7.55.5.27 get_d()
7.55.5.28 get_gate_count() [1/2]
7.55.5.29 get_gate_count() [2/2]
7.55.5.30 get_gate_depth() [1/2]
7.55.5.31 get_gate_depth() [2/2]
7.55.5.32 get_gates_()
7.55.5.33 get_measured() [1/2]
7.55.5.34 get_measured() [2/2]
7.55.5.35 get_measurement_count() [1/2]
7.55.5.36 get_measurement_count() [2/2]
7.55.5.37 get_measurements_()
7.55.5.38 get_name()
7.55.5.39 get_nc()
7.55.5.40 get_non_measured()
7.55.5.41 get_nq()
7.55.5.42 get_step_count()
7.55.5.43 measureV() [1/2]

xxvi CONTENTS

		7.55.5.44	measure\	/() [2/2]			 	 	 	 	 	 289
		7.55.5.45	measureZ	<u>'()</u>				 	 	 	 	 	 290
		7.55.5.46	QFT()					 	 	 	 	 	 290
		7.55.5.47	TFQ()					 	 	 	 	 	 290
		7.55.5.48 1	to_JSON()				 	 	 	 	 	 291
	7.55.6	Friends An	nd Related	d Function	on Doo	ument	ation	 	 	 	 	 	 291
		7.55.6.1	operator<	(< [1/4				 	 	 	 	 	 291
		7.55.6.2	operator<	<pre>(< [2/4</pre>				 	 	 	 	 	 292
		7.55.6.3	operator<	(< [3/4	1]			 	 	 	 	 	 292
		7.55.6.4	operator<	(< [4/4	1]			 	 	 	 	 	 292
		7.55.6.5	QEngine					 	 	 	 	 	 293
	7.55.7	Member D	ata Docui	mentatio	on			 	 	 	 	 	 293
		7.55.7.1	cmat_has	h_tbl_				 	 	 	 	 	 293
		7.55.7.2	count					 	 	 	 	 	 293
		7.55.7.3	d					 	 	 	 	 	 293
		7.55.7.4	depth					 	 	 	 	 	 293
		7.55.7.5	gates					 	 	 	 	 	 294
		7.55.7.6	measured	<u>L</u>				 	 	 	 	 	 294
		7.55.7.7	measurer	nent_co	unt			 	 	 	 	 	 294
		7.55.7.8	measurer	nents_				 	 	 	 	 	 294
		7.55.7.9	name					 	 	 	 	 	 294
		7.55.7.10	nc					 	 	 	 	 	 294
		7.55.7.11	nq					 	 	 	 	 	 295
		7.55.7.12	step_type	s				 	 	 	 	 	 295
7.56	qpp::Ql	Engine Clas	ss Referer	nce				 	 	 	 	 	 295
	7.56.1	Detailed D	escription	١				 	 	 	 	 	 297
	7.56.2	Constructo	or & Destr	uctor Do	ocume	ntation		 	 	 	 	 	 297
		7.56.2.1	QEngine() [1/3]				 	 	 	 	 	 297
		7.56.2.2	QEngine() [2/3]				 	 	 	 	 	 298
		7.56.2.3	QEngine() [3/3]				 	 	 	 	 	 298

CONTENTS xxvii

		7.56.2.4 ~QEngine()		298
	7.56.3	Member Function Documentation		298
		7.56.3.1 display()		298
		7.56.3.2 execute() [1/2]		299
		7.56.3.3 execute() [2/2]		299
		7.56.3.4 get_circuit()		299
		7.56.3.5 get_dit()		299
		7.56.3.6 get_dits()		300
		7.56.3.7 get_measured() [1/2]		300
		7.56.3.8 get_measured() [2/2]		300
		7.56.3.9 get_not_measured()		301
		7.56.3.10 get_probs()		301
		7.56.3.11 get_psi()		301
		7.56.3.12 get_ref_psi()		301
		7.56.3.13 get_relative_pos_()		301
		7.56.3.14 operator=()		302
		7.56.3.15 reset()		302
		7.56.3.16 set_dit()		302
		7.56.3.17 set_measured_()		303
		7.56.3.18 to_JSON()		303
	7.56.4	Member Data Documentation		303
		7.56.4.1 dits		303
		7.56.4.2 probs		303
		7.56.4.3 psi		304
		7.56.4.4 qc		304
		7.56.4.5 subsys		304
7.57	qpp::Qı	bitAmplitudeDampingNoise Class Reference		304
	7.57.1	Detailed Description		305
	7.57.2	Constructor & Destructor Documentation		305
		7.57.2.1 QubitAmplitudeDampingNoise()		305

xxviii CONTENTS

7.58 qpp::QubitBitFlipNoise Class Reference
7.58.1 Detailed Description
7.58.2 Constructor & Destructor Documentation
7.58.2.1 QubitBitFlipNoise()
7.59 qpp::QubitBitPhaseFlipNoise Class Reference
7.59.1 Detailed Description
7.59.2 Constructor & Destructor Documentation
7.59.2.1 QubitBitPhaseFlipNoise()
7.60 qpp::QubitDepolarizingNoise Class Reference
7.60.1 Detailed Description
7.60.2 Constructor & Destructor Documentation
7.60.2.1 QubitDepolarizingNoise()
7.61 qpp::QubitPhaseDampingNoise Class Reference
7.61.1 Detailed Description
7.61.2 Constructor & Destructor Documentation
7.61.2.1 QubitPhaseDampingNoise()
7.62 qpp::QubitPhaseFlipNoise Class Reference
7.62.1 Detailed Description
7.62.2 Constructor & Destructor Documentation
7.62.2.1 QubitPhaseFlipNoise()
7.63 qpp::exception::QuditAlreadyMeasured Class Reference
7.63.1 Detailed Description
7.63.2 Member Function Documentation
7.63.2.1 Exception()
7.63.2.2 type_description()
7.64 qpp::QuditDepolarizingNoise Class Reference
7.64.1 Detailed Description
7.64.2 Constructor & Destructor Documentation
7.64.2.1 QuditDepolarizingNoise()
7.64.3 Member Function Documentation

CONTENTS xxix

	7.64.3.1	fill_Ks_()	317
	7.64.3.2	fill_probs_()	317
7.65 qpp	::RandomDe	evices Class Reference	318
7.65	5.1 Detailed	Description	319
7.6	5.2 Constru	ctor & Destructor Documentation	319
	7.65.2.1	RandomDevices()	319
	7.65.2.2	~RandomDevices()	320
7.6	5.3 Member	Function Documentation	320
	7.65.3.1	get_prng()	320
	7.65.3.2	load()	320
	7.65.3.3	save()	320
7.65	5.4 Friends	And Related Function Documentation	321
	7.65.4.1	internal::Singleton< RandomDevices >	321
7.65	5.5 Member	Data Documentation	321
	7.65.5.1	prng	321
	7.65.5.2	rd	321
7.66 qpp	::internal::Sir	ngleton< T > Class Template Reference	321
7.66	6.1 Detailed	Description	322
7.66	6.2 Constru	ctor & Destructor Documentation	322
	7.66.2.1	Singleton() [1/2]	323
	7.66.2.2	Singleton() [2/2]	323
	7.66.2.3	~Singleton()	323
7.66	6.3 Member	Function Documentation	323
	7.66.3.1	get_instance()	323
	7.66.3.2	get_thread_local_instance()	323
	7.66.3.3	operator=()	323
7.67 qpp	::exception::	SizeMismatch Class Reference	324
7.67	7.1 Detailed	Description	325
7.67	7.2 Member	Function Documentation	325
	7.67.2.1	Exception()	325

	7.67.2.2 type_description()	25
7.68 qpp::No	piseType::StateDependent Class Reference	26
7.68.1	Detailed Description	26
7.69 qpp::No	piseType::StateIndependent Class Reference	26
7.69.1	Detailed Description	26
7.70 qpp::St	ates Class Reference	26
7.70.1	Detailed Description	28
7.70.2	Constructor & Destructor Documentation	29
	7.70.2.1 States()	29
	7.70.2.2 ~States()	29
7.70.3	Member Function Documentation	29
	7.70.3.1 jn()	29
	7.70.3.2 mes()	29
	7.70.3.3 minus()	30
	7.70.3.4 one()	30
	7.70.3.5 plus()	31
	7.70.3.6 zero()	31
7.70.4	Friends And Related Function Documentation	31
	7.70.4.1 internal::Singleton < const States >	31
7.70.5	Member Data Documentation	31
	7.70.5.1 b00	32
	7.70.5.2 b01	32
	7.70.5.3 b10	32
	7.70.5.4 b11	32
	7.70.5.5 GHZ	32
	7.70.5.6 pb00	32
	7.70.5.7 pb01	33
	7.70.5.8 pb10	33
	7.70.5.9 pb11	33
	7.70.5.10 pGHZ	33

CONTENTS xxxi

	7.70.5.11 pW
	7.70.5.12 px0
	7.70.5.13 px1
	7.70.5.14 py0
	7.70.5.15 py1
	7.70.5.16 pz0
	7.70.5.17 pz1
	7.70.5.18 W
	7.70.5.19 x0
	7.70.5.20 x1
	7.70.5.21 y0
	7.70.5.22 y1
	7.70.5.23 z0
	7.70.5.24 z1
7.71 qpp::ex	cception::SubsysMismatchDims Class Reference
7.71.1	Detailed Description
7.71.2	Member Function Documentation
	7.71.2.1 Exception()
	7.71.2.2 type_description()
7.72 qpp::Ti	mer< T, CLOCK_T > Class Template Reference
7.72.1	Detailed Description
7.72.2	Constructor & Destructor Documentation
	7.72.2.1 Timer() [1/3]
	7.72.2.2 Timer() [2/3]
	7.72.2.3 Timer() [3/3]
	7.72.2.4 ~Timer()
7.72.3	Member Function Documentation
	7.72.3.1 display()
	7.72.3.2 get_duration()
	7.72.3.3 operator=() [1/2]

xxxii CONTENTS

		7.72.3.4	operator=() [2/2]	. 341
		7.72.3.5	tic()	. 342
		7.72.3.6	tics()	. 342
		7.72.3.7	toc()	. 342
	7.72.4	Member I	Data Documentation	. 342
		7.72.4.1	end	. 342
		7.72.4.2	start	. 343
7.73	qpp::ex	ception::Ty	ypeMismatch Class Reference	. 343
	7.73.1	Detailed I	Description	. 344
	7.73.2	Member I	Function Documentation	. 344
		7.73.2.1	Exception()	. 344
		7.73.2.2	type_description()	. 345
7.74	qpp::ex	ception::U	IndefinedType Class Reference	. 345
	7.74.1	Detailed I	Description	. 346
	7.74.2	Member I	Function Documentation	. 346
		7.74.2.1	Exception()	. 346
		7.74.2.2	type_description()	. 347
7.75	qpp::ex	ception::U	Inknown Class Reference	. 347
	7.75.1	Detailed I	Description	. 348
	7.75.2	Member I	Function Documentation	. 348
		7.75.2.1	Exception()	. 348
		7.75.2.2	type_description()	. 349
7.76	qpp::Q0	Circuit::iter	rator::value_type_ Class Reference	. 349
	7.76.1	Construct	tor & Destructor Documentation	. 350
		7.76.1.1	value_type_() [1/2]	. 350
		7.76.1.2	value_type_() [2/2]	. 350
	7.76.2	Member I	Function Documentation	. 351
		7.76.2.1	display()	. 351
		7.76.2.2	operator=()	. 351
	7.76.3	Member I	Data Documentation	. 351
		7.76.3.1	gates_ip	. 351
		7.76.3.2	ip	. 352
		7.76.3.3	measurements_ip	. 352
		7.76.3.4	type	. 352
		7.76.3.5	value_type_qc	. 352
7.77	qpp::ex	ception::Z	eroSize Class Reference	. 353
	7.77.1	Detailed I	Description	. 354
	7.77.2		Function Documentation	
			Exception()	
		7.77.2.2	type_description()	. 354

CONTENTS xxxiii

8	File I	Documentation	355
	8.1	classes/circuits.h File Reference	355
		8.1.1 Detailed Description	356
	8.2	classes/codes.h File Reference	356
		8.2.1 Detailed Description	356
	8.3	classes/exception.h File Reference	357
		8.3.1 Detailed Description	359
	8.4	classes/gates.h File Reference	359
		8.4.1 Detailed Description	359
	8.5	classes/idisplay.h File Reference	360
		8.5.1 Detailed Description	360
	8.6	classes/init.h File Reference	360
		8.6.1 Detailed Description	361
	8.7	classes/noise.h File Reference	361
		8.7.1 Detailed Description	362
	8.8	classes/random_devices.h File Reference	362
		8.8.1 Detailed Description	362
	8.9	classes/reversible.h File Reference	363
		8.9.1 Detailed Description	363
	8.10	classes/states.h File Reference	363
		8.10.1 Detailed Description	364
	8.11	classes/timer.h File Reference	364
		8.11.1 Detailed Description	365
	8.12	constants.h File Reference	365
		8.12.1 Detailed Description	366
	8.13	entanglement.h File Reference	366
		8.13.1 Detailed Description	368
	8.14	entropies.h File Reference	368
		8.14.1 Detailed Description	369
	8.15	experimental/experimental.h File Reference	369

	8.15.1 Detailed Description	369
8.16	functions.h File Reference	369
	8.16.1 Detailed Description	374
8.17	input_output.h File Reference	374
	8.17.1 Detailed Description	375
8.18	instruments.h File Reference	375
	8.18.1 Detailed Description	377
8.19	internal/classes/iomanip.h File Reference	377
	8.19.1 Detailed Description	377
8.20	internal/classes/singleton.h File Reference	378
	8.20.1 Detailed Description	378
8.21	internal/util.h File Reference	378
	8.21.1 Detailed Description	380
8.22	MATLAB/matlab.h File Reference	380
	8.22.1 Detailed Description	381
8.23	number_theory.h File Reference	381
	8.23.1 Detailed Description	382
8.24	operations.h File Reference	383
	8.24.1 Detailed Description	385
8.25	qpp.h File Reference	385
	8.25.1 Detailed Description	386
	8.25.2 Macro Definition Documentation	386
	8.25.2.1 QPP_UNUSED	386
8.26	random.h File Reference	387
	8.26.1 Detailed Description	388
8.27	statistics.h File Reference	388
	8.27.1 Detailed Description	389
8.28	traits.h File Reference	389
	8.28.1 Detailed Description	390
8.29	types.h File Reference	391
	8.29.1 Detailed Description	392
8.30	/Users/vlad/qpp/README.md File Reference	392

Index

393

Chapter 1

Quantum++

Version 1.2 - 10 February 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

pp	
Quantum++ main namespace	13
p::exception	
Quantum++ exception hierarchy namespace	116
p::experimental	
Experimental/test functions/classes, do not use or modify	118
p::internal	
Internal utility functions, do not use them directly or modify them	118
p::literals	125

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
app::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
app::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	336
qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	345
qpp::exception::Unknown	347
qpp::exception::ZeroSize	353
false_type	
qpp::is complex< T >	207
<pre>qpp::is_iterable < T, typename ></pre>	209
qpp::Bit circuit::Gate count	
gpp::QCircuit::GateStep	
qpp::internal::HashEigen	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QEngine	295
is_base_of	
qpp::is_matrix_expression < Derived >	211
qpp::QCircuit::iterator	212
qpp::make_void < Ts >	217
qpp::QCircuit::MeasureStep	234
qpp::NoiseBase< T >	239
qpp::NoiseBase < NoiseType::StateDependent >	239
qpp::QubitAmplitudeDampingNoise	304
qpp::QubitPhaseDampingNoise	310
qpp::NoiseBase < NoiseType::StateIndependent >	239
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	
qpp::internal::Singleton< T >	
qpp::internal::Singleton < const Codes >	
qpp::Codes	
qpp::internal::Singleton < const Gates >	
qpp::Gates	
qpp::internal::Singleton < const Init >	
qpp::Init	194
qpp::internal::Singleton < const States >	321
qpp::States	326
qpp::internal::Singleton < RandomDevices >	321
qpp::RandomDevices	
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	
true_type	<i>)_</i> _0
qpp::is_complex< std::complex< T >>	วกร
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T	_00
	210
///.ond///, door/po(~doandoorda < 1 / (/.bogin(//// /	0

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit circuit
Classical reversible circuit simulator
qpp::Codes
Const Singleton class that defines quantum error correcting codes
qpp::exception::CustomException
Custom exception
qpp::exception::DimsInvalid
Invalid dimension(s) exception
qpp::exception::DimsMismatchCvector
Dimension(s) mismatch column vector size exception
qpp::exception::DimsMismatchMatrix
Dimension(s) mismatch matrix size exception
qpp::exception::DimsMismatchRvector
Dimension(s) mismatch row vector size exception
qpp::exception::DimsMismatchVector
Dimension(s) mismatch vector size exception
qpp::exception::DimsNotEqual
Dimensions not equal exception
qpp::internal::Display_Impl
qpp::exception::Duplicates
System (e.g. std::vector) has duplicates exception
qpp::Dynamic_bitset
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←
::bitset <n>)</n>
qpp::internal::EqualEigen
Functor for comparing Eigen expressions for equality
qpp::exception::Exception
Base class for generating Quantum++ custom exceptions
qpp::Bit_circuit::Gate_count
qpp::Gates
Const Singleton class that implements most commonly used gates
qpp::QCircuit::GateStep
One step consisting only of gates/operators in the circuit
qpp::internal::HashEigen
Functor for hashing Eigen expressions

8 Class Index

qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream 189	& os) const
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	192
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	194
qpp::exception::InvalidIterator	
Invalid iterator	196
qpp::internal::IOManipEigen	198
qpp::internal::IOManipPointer< PointerType >	200
qpp::internal::IOManipRange < InputIterator >	204
qpp::is_complex< T >	
Checks whether the type is a complex type	207
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable < T, typename >	
Checks whether T is compatible with an STL-like iterable container \dots	209
$qpp::is_iterable < T, \ to_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(std::declval < T > ().end()),$	ecltype(*(std::declval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	212
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	217
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	218
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	220
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	222
qpp::exception::MatrixNotSquare	
Matrix is not square exception	224
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	226
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	228
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	230
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	232
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	234
qpp::exception::NoCodeword	
Codeword does not exist exception	237
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	239
qpp::NoiseType	
Contains template tags used to specify the noise type	247
qpp::exception::NotBipartite	
Not bi-partite exception	247
qpp::exception::NotImplemented	
Code not yet implemented	250
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	252

4.1 Class List

qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	254
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	256
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	258
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	260
qpp::exception::OutOfRange	
Argument out of range exception	262
qpp::exception::PermInvalid	
Invalid permutation exception	264
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	266
pp::QCircuit	200
Quantum circuit class	268
qpp::QEngine	200
Quantum circuit engine, executes qpp::QCircuit	295
qpp::QubitAmplitudeDampingNoise	230
	304
Qubit amplitude damping noise, as described in Nielsen and Chuang	302
qpp::QubitBitFlipNoise	000
Qubit bit flip noise	306
qpp::QubitBitPhaseFlipNoise	00-
Qubit bit-phase flip (dephasing) noise	307
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	309
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	310
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	312
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	313
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	315
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	318
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	321
qpp::exception::SizeMismatch	
Size mismatch exception	324
qpp::NoiseType::StateDependent	
	326
gpp::NoiseType::StateIndependent	
	326
qpp::States	
	326
qpp::exception::SubsysMismatchDims	0_0
	336
qpp::Timer< T, CLOCK_T >	000
Chronometer	338
qpp::exception::TypeMismatch	000
Type mismatch exception	343
qpp::exception::UndefinedType	0+0
Not defined for this type exception	345
qpp::exception::Unknown	J + (
Unknown exception	3/17
·	
qpp::QCircuit::iterator::value_type	348

10		Class Index

qpp::exception::ZeroSize															
Object has zero size exception				 					 		_	 		3	5

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	365
entanglement.h	
Entanglement functions	366
entropies.h	
Entropy functions	368
functions.h	
Generic quantum computing functions	369
input_output.h	
Input/output functions	374
instruments.h	
Measurement functions	375
number_theory.h	
Number theory functions	381
operations.h	
Quantum operation functions	383
qpp.h	
Quantum++ main header file, includes all other necessary headers	385
random.h	
Randomness-related functions	387
statistics.h	
Statistics functions	388
traits.h	
Type traits	389
types.h	
Type aliases	391
classes/circuits.h	
Support for qudit quantum circuits	355
classes/codes.h	
Quantum error correcting codes	356
classes/exception.h	
Exceptions	357
classes/gates.h	
Quantum gates	359

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	360
classes/init.h	
Initialization	360
classes/noise.h	
Noise models	361
classes/random_devices.h	
Random devices	362
classes/reversible.h	
Support for classical reversible circuits	363
classes/states.h	
Quantum states	363
classes/timer.h	
Timing	364
experimental/experimental.h	
Experimental/test functions/classes	369
internal/util.h	
Internal utility functions	378
internal/classes/iomanip.h	
Input/output manipulators	377
internal/classes/singleton.h	
Singleton pattern via CRTP	378
MATLAB/matlab.h	
Input/output interfacing with MATLAB	380

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
template<typename Derived >
  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

 $\frac{internal::IOManipPointer}{internal::IOManipPointer} > disp \ (const \ PointerType \ *p, \ idx \ N, \ const \ std::string \ \&separator, \ const \ std::string \ \&separator, \ const \ std::string \ \&end="]")$

C-style pointer ostream manipulator.

template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)
```

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::← Scalar > >::type loadMATLAB (const std::string &mat file, const std::string &var name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)
 Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

• std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std \leftarrow ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

```
\label{localized_dyn_mat} $$\operatorname{dyn_mat}<\operatorname{typename\ Derived}:Scalar>\operatorname{ptrace1}$ (const\ Eigen::MatrixBase<\operatorname{Derived}>\&A,\ idx\ d=2)$
```

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)
```

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

• template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED =1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

• cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

template<typename Container >
 double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable
 Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

ŀ	prob	Real probability vector representing the probability distribution of X
	Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression	
dims	Dimensions of the bi-partite system	

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Α	Eigen expression
seed	Seed, 0 by default

Hash of its argument

6.1.3.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector


6.1.3.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters



Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.64 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.65 invperm()

Inverse permutation.

Parameters

perm	Permutation

Returns

Inverse of the permutation perm

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

```
6.1.3.67 ip() [2/2]
```

Generalized inner product.

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
Generated by	Subsystem dimensions

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.68 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	p Integer different from 0, 1 or -1	
k	Number of iterations. The probability of a false positive is 2^{-k} .	

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

|--|

Choi matrix

6.1.3.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

```
6.1.3.71 kron() [1/4]
```

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

```
head Eigen expression
```

Returns

Its argument head

```
6.1.3.72 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.73 kron() [3/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

Δc	std::vector of Eigen expressions
713	sidvector or Ligeri expressions

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.75 kronpow()

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

qpp::gcd()

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

qpp::save()

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

fname	Output file name
mamo	Output mo name

6.1.3.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Eigen dynamic matrix

```
6.1.3.80 loadMATLAB() [2/2]
```

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

A Eigen expression

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.3.83 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 lognegativity() [2/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Ylabels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

const std::vector< cmat > & Ks)

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	A Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

const cmat & U)

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

const std::vector< idx > & target,
const std::vector< idx > & dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

ſ	Α	Eigen expression
	Ks	Set of Kraus operators
	target	Subsystem indexes that are measured
	d	Subsystem dimensions

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

```
qpp::measure()
```

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension *d. mask* is a std::vector of non-negative integers, and each element in *mask* has to be strictly smaller than *d*.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.100 modinv()

Modular inverse of a mod p.

See also

qpp::egcd()

Note

a and p must be co-prime

а	Non-negative integer
р	Non-negative integer

Returns

Modular inverse $a^{-1} \mod p$

6.1.3.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.102 modpow()

Fast integer power modulo *p* based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx > \& \ midx, const \ std::vector < \ idx > \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.106 n2multiidx()

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

```
6.1.3.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

```
6.1.3.108 negativity() [2/2]
```

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.109 norm()

Frobenius norm.

Parameters

A Eigen expression

Returns

Frobenius norm of A

6.1.3.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Returns

Normalized state vector or density matrix

6.1.3.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

D-th root of unity $\exp(2\pi i/D)$

6.1.3.113 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.114 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero, as a dynamic matrix over the same scalar field as A

6.1.3.115 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

6.1.3.116 prod() [2/3]

Element-wise product of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Partial trace $Tr_{subsys}(\cdot)$ over the subsystems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.120 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

```
6.1.3.121 ptrace1() [2/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.126 QFT()

Qudit quantum Fourier transform.

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.127 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.128 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.132 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

```
6.1.3.133 rand() [5/5]

template<>>
cmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.134 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.135 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.136 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.137 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.142 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.143 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.144 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.145 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.146 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.147 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.148 renyi() [1/2]
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0.$

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.150 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.151 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.152 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.153 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.154 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.155 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.156 schatten()

Schatten matrix norm.

	Α	Eigen expression
ſ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.159 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.163 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.165 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.166 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.167 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.168 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.169 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.170 sum() [2/3]
```

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.172 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.173 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.174 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.175 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.176 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.177 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.179 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.180 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.181 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.182 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.184 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.185 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.186 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

• class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- · class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- template < class T >
 void hash combine (std::size t &seed, const T &v)
- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check square mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check vector (const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \;\; {\sf template}{<} {\sf typename \; Derived} >$

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check gubit vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool check perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

```
    template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen → ::MatrixBase< Derived2 > &B)
    template<typename T > void variadic_vector_emplace (std::vector< T > &)
    template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
    idx get_num_subsys (idx D, idx d)
```

6.4.1 Detailed Description

idx get_dim_subsys (idx sz, idx N)

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  \mbox{const std::vector} < \mbox{idx} > \& \mbox{dims} \mbox{)} \quad \mbox{[inline]}
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

```
6.4.2.5 check_dims_match_rvect()
```

```
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_eq_dims()
bool qpp::internal::check_eq_dims (
            const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
6.4.2.7 check_matching_sizes()
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
            const T2 & rhs ) [noexcept]
6.4.2.8 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
             std::vector < idx > v) [inline]
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
```

const std::vector< idx > & perm) [inline]

6.4.2.11 check_qubit_cvector()

```
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template < typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
```

```
6.4.2.17 check_subsys_match_dims()
```

```
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
            idx N ) [inline]
6.4.2.21 get_num_subsys()
idx qpp::internal::get_num_subsys (
            idx D,
            idx d ) [inline]
6.4.2.22 hash_combine()
template<class T >
void qpp::internal::hash_combine (
            std::size_t & seed,
            const T & v )
```

6.4.2.23 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.24 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.25 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.26 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.27 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx N ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.

7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

```
7.12.5.3 v_
```

```
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
```

Storage space.

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char \ast what () const no except override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.14.3 Member Function Documentation

7.14.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
Exception type description.
```

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.14.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

```
7.14.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.14.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.15 qpp::Bit_circuit::Gate_count Struct Reference

#include <classes/reversible.h>

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.15.1 Member Data Documentation

7.15.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.15.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.15.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.15.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.15.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.15.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:


• classes/reversible.h

7.16 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::Identity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.16.1 Detailed Description

const Singleton class that implements most commonly used gates

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.16.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.16.3 Member Function Documentation

7.16.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.16.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.16.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.16.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.16.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.16.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N	
N	Positive integer	
n	Number of qubits required for implementing the gat	

Returns

Modular multiplication gate

7.16.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.16.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
ıneıa	Rotation angle

Returns

Rotation gate

7.16.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.16.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.16.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
          idx D = 2) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.16.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.16.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.16.4 Friends And Related Function Documentation

```
7.16.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.16.5 Member Data Documentation

```
7.16.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.16.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.16.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.16.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.16.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.16.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.16.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.16.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.16.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.16.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.16.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.16.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.16.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.17 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    std::size_t gate_hash_
        gate hash
    std::vector< idx > ctrl_
        control
    std::vector< idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.17.1 Detailed Description

7.17.2.1 GateStep() [1/2]

Constructs a gate step instance.

One step consisting only of gates/operators in the circuit.

7.17.2 Constructor & Destructor Documentation

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.17.3 Member Data Documentation

```
7.17.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
7.17.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_
gate hash
7.17.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.17.3.4 name_
std::string qpp::QCircuit::GateStep::name_
```

custom name of the step

7.17.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits.h

7.18 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

```
    template<typename Derived >
        std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const
```

7.18.1 Detailed Description

Functor for hashing Eigen expressions.

7.18.2 Member Function Documentation

7.18.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.19 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

• IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

• IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

Default virtual destructor.

```
7.19.2.4 \simIDisplay() virtual qpp::IDisplay::\simIDisplay ( ) [virtual], [default]
```

7.19.3 Member Function Documentation

7.19.3.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QEngine, qpp::QCircuit, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

```
7.19.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.19.3.3 operator=() [2/2]
```

Default move assignment operator.

7.19.4 Friends And Related Function Documentation

7.19.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.20.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 IJSON() [1/3]
qpp::IJSON::IJSON ( ) [default]
Default constructor.
7.20.2.2 IJSON() [2/3]
qpp::IJSON::IJSON (
             const IJSON & ) [default]
Default copy constructor.
7.20.2.3 IJSON() [3/3]
qpp::IJSON::IJSON (
              IJSON && ) [default]
Default move constructor.
7.20.2.4 ∼IJSON()
virtual qpp::IJSON::~IJSON ( ) [virtual], [default]
Default virtual destructor.
7.20.3 Member Function Documentation
7.20.3.1 operator=() [1/2]
IJSON& qpp::IJSON::operator= (
              {\tt const\ IJSON\ \&\quad)\quad [default]}
Default copy assignment operator.
7.20.3.2 operator=() [2/2]
IJSON& qpp::IJSON::operator= (
              IJSON && ) [default]
Default move assignment operator.
7.20.3.3 to_JSON()
```

JSON representation of the derived instance, must be overridden by all derived classes.

bool enclosed_in_curly_brackets = true) const [pure virtual]

virtual std::string qpp::IJSON::to_JSON (

Parameters

enclosed_in_curly_brackets If true, encloses the result in curly brackets

Implemented in qpp::QEngine, and qpp::QCircuit.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.21 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

#include <classes/init.h>

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

```
• Init ()
```

Additional initializations.

• ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.21.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.21.2 Constructor & Destructor Documentation

```
7.21.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.21.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.21.3 Friends And Related Function Documentation

```
7.21.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.22 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.22.1 Detailed Description

Invalid iterator.

7.22.2 Member Function Documentation

7.22.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.22.2.2 type_description()

```
std::string qpp::exception::InvalidIterator::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.23 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.23.1 Constructor & Destructor Documentation

7.23.2 Member Function Documentation

```
7.23.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.3 Member Data Documentation

7.23.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.23.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.24 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_

7.24.1 Constructor & Destructor Documentation

7.24.1.1 IOManipPointer() [1/2]

7.24.1.2 IOManipPointer() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.24.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.24.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.24.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.24.3.5 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.25 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- · std::string start_
- std::string end_

7.25.1 Constructor & Destructor Documentation

```
7.25.1.1 IOManipRange() [1/2]
```

7.25.1.2 IOManipRange() [2/2]

7.25.2 Member Function Documentation

7.25.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.25.2.2 operator=()

7.25.3 Member Data Documentation

```
7.25.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.25.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.25.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.25.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.25.3.5 start_
template<typename InputIterator>
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]

• internal/classes/iomanip.h

7.26 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.26.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*


The documentation for this struct was generated from the following file:

7.27 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.27.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

7.28 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.28.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.29 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



 $\label{top:condition} \begin{tabular}{ll} Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T>().begin()), decltype(std::declval< T>().begin()))>>: \\ \begin{tabular}{ll} T>().begin())>>: \\ \begin{tabular}{ll} T>().begin()>>: \\ \begin{tabular}{ll} T>().begin()>>: \\ \begin{tabular}{ll} T>().begin()>: \\ \begin{tabular}{ll$



7.29.1 Detailed Description

 $\label{template} $$ \ensuremath{\mathsf{template}}$ $$ $ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ \ensuremath{\mathsf{t$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.30 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.30.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.31 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

• using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

bool operator== (const iterator &rhs) const

Equality operator.

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to const quantum circuit

value_type_ elem_ {nullptr}

7.31.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.31.2 Member Typedef Documentation

```
7.31.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.31.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.31.2.3 pointer
```

```
using qpp::QCircuit::iterator::pointer = const value_type*
```

iterator trait

7.31.2.4 reference

```
using qpp::QCircuit::iterator::reference = const value_type&
```

iterator trait

7.31.2.5 value_type

```
using qpp::QCircuit::iterator::value_type = value_type_
```

iterator trait

7.31.3 Constructor & Destructor Documentation

```
7.31.3.1 iterator() [1/2]
```

```
qpp::QCircuit::iterator::iterator ( ) [default]
```

Default constructor.

```
7.31.3.2 iterator() [2/2]
```

Default copy constructor.

7.31.4 Member Function Documentation

7.31.4.1 operator"!=()

Inequality operator.

Parameters

rhs | Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

7.31.4.2 operator*()

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

7.31.4.3 operator++() [1/2]

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

7.31.4.4 operator++() [2/2]

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.31.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.31.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.31.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.31.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.31.5 Member Data Documentation

```
7.31.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.31.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

< non-owning pointer to const quantum circuit

The documentation for this class was generated from the following file:

· classes/circuits.h

7.32 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.32.1 Detailed Description

```
template < typename... Ts > struct qpp::make_void < Ts >
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.32.2 Member Typedef Documentation

7.32.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.33 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.33.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotSquare:$



 $Collaboration\ diagram\ for\ qpp::exception::MatrixNotSquare:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.36.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occurred
--

7.37.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.38.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.39.2 Member Function Documentation

7.39.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.39.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.40.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits.h>
```

 $Collaboration\ diagram\ for\ qpp:: QCircuit:: Measure Step:$



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size t > mats hash
- std::vector< idx > target_

target where the measurement is applied

- idx c_reg_ {}
- · std::string name_

custom name of the step

7.41.1 Detailed Description

One step consisting only of measurements in the circuit.

7.41.2 Constructor & Destructor Documentation

```
7.41.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.41.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.41.3 Member Data Documentation

```
7.41.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

7.41.3.2 mats_hash_

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_
```

hashes of measurement matrix/matrices

7.41.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.41.3.4 name_

```
std::string qpp::QCircuit::MeasureStep::name_
```

custom name of the step

7.41.3.5 target_

std::vector<idx> qpp::QCircuit::MeasureStep::target_

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.42 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.42.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.42.2 Member Function Documentation

7.42.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.42.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.43 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is_same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector < cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

idx get_last_idx () const

Index of the last occurring noise element.

• double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

• virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

• virtual cmat operator() (const cmat &state, const std::vector< idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

- void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 - Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)
- cmat compute_state_ (const cmat &state, const std::vector< idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector < cmat > Ks_

Kraus operators.

std::vector< double > probs_

probabilities

idx d_ {}

qudit dimension

• idx i {}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.43.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.43.2 Member Typedef Documentation

7.43.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.43.3 Constructor & Destructor Documentation

7.43.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.43.4 Member Function Documentation

7.43.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.43.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.43.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.43.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.43.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.43.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.43.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.43.4.8 get_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.43.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

state	State vector or density matrix	
-------	--------------------------------	--

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

const std::vector< idx > & target) const [inline], [virtual]

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.43.5 Member Data Documentation

```
7.43.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.43.5.2 generated_
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.43.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
7.43.5.4 Ks_
{\tt template}{<}{\tt class} \ {\tt T}{>}
```

const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]

Kraus operators.

7.43.5.5 probs_

probabilities

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

The documentation for this class was generated from the following file:

· classes/noise.h

7.44 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.44.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.45 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

7.45.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.45.2 Member Function Documentation

7.45.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.45.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Code not yet implemented.

7.46.2 Member Function Documentation

7.46.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.48.2 Member Function Documentation

7.48.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.48.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


classes/exception.h

7.50 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.51.2 Member Function Documentation

7.51.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.51.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Argument out of range exception.

Argument out of range

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.52.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.53.2 Member Function Documentation

7.53.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.53.2.2 type_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.54.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.54.2 Member Function Documentation

7.54.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.54.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.55 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
 GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTR
 GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,
 GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_cCTRL_SINGLE_TARGET,
 GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_CCTRL_MULTIPLE_TARGET,
 GateType::CUSTOM_cCTRL)

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

· using const_iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

- $std::vector < idx > get_measured$ () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

• idx get gate count (const std::string &name) const

Quantum circuit gate count.

idx get_gate_depth () const

Quantum circuit total gate depth.

• idx get_gate_depth (const std::string &name QPP_UNUSED_) const

Quantum circuit gate depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

• idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

• QCircuit & gate_fan (const cmat &U, const std::vector< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

• QCircuit & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

• QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

• QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name=""")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name=""")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector < idx > &target, idx c_reg, std::string name=""")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

 std::string to_JSON (bool enclosed_in_curly_brackets=true) const override *qpp::IJOSN::to_JSON() override*

Private Member Functions

void add hash (const cmat &U, std::size t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get_measurements_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates_() const noexcept

Vector of qpp::QCircuit::GateStep.

 $\bullet \ \ const \ std::unordered_map{<} \ std::size_t, \ cmat > \& \ get_cmat_hash_tbl_\ () \ const \ noexcept$

Hash table with the matrices used in the circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

```
    const idx nq
```

number of qudits

const idx nc_

number of classical "dits"

const idx d

qudit dimension

std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

std::unordered_map< std::size_t, cmat > cmat_hash_tbl_{{}}

• std::unordered map< std::string, idx > count {}

keeps track of the gate counts

std::unordered_map< std::string, idx > depth_{{}}

keeps track of the gate depths

std::unordered map< std::string, idx > measurement count {}

keeps track of the measurement counts

std::vector< GateStep > gates_{}

```
gates
• std::vector< MeasureStep > measurements_ {}
    measurements
• std::vector< StepType > step_types_ {}
    type of each step
```

Friends

- class QEngine
- std::ostream & operator << (std::ostream &os, const GateType &gate_type)

 Extraction operator overload for qpp::QCircuit::GateType enum class.

Extraction operator overload for qpp::QCircuit::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

• std::ostream & operator << (std::ostream &os, const MeasureStep &measure_step) Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.55.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.55.2 Member Typedef Documentation

```
7.55.2.1 const_iterator
```

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.55.3 Member Enumeration Documentation

7.55.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

SINGLE SINGLE Unitary gate on a single qudit TWO Unitary gate on 2 qudits THREE Unitary gate on 3 qudits CUSTOM CUSTOM CUSTOM CUSTOM gate on multiple qudits FAN Same unitary gate on multiple qudits QFT Quantum Fourier transform, TFQ Quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET SINGLE_CTRL_MULTIPLE_TARGET MULTIPLE_CTRL_MULTIPLE_TARGET MULTIPLE_CTRL_MULTIPLE_TARGET CUSTOM_CTRL CUSTOM_CTRL CONTrolled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL CONTROLLE 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL CONTROLLE 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL CONTROLLE 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL CONTROLLE 1 qudit unitary gate with one classical control and one target CONTROLLE 1 qudit unitary gate with one classical control and multiple targets CUSTOM_CTRL CONTROLLE 1 qudit unitary gate with one classical control and multiple targets CONTROLLE 1 qudit unitary gate with one classical control and multiple targets CONTROLLE 1 qudit unitary gate with multiple classical control and multiple targets CONTROLLE 1 qudit unitary gate with multiple classical controls and multiple targets CONTROLLE 1 qudit unitary gate with multiple classical controls and multiple targets CONTROLLE 1 qudit unitary gate with multiple classical controls and multiple targets CONTROLLE 2 controlled 1 qudit unitary gate with multiple classical controls and multiple targets CONTROLLE 2 controlled 1 qudit unitary gate with multiple classical controls and multiple targets CUSTOM_CCTRL CUSTOM_COTRL		
TWO unitary gate on 2 qudits THREE unitary gate on 3 qudits CUSTOM custom gate on multiple qudits Same unitary gate on multiple qudits Same unitary gate on multiple qudits quantum Fourier transform, TFQ quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	NONE	represents no gate
THREE Unitary gate on 3 qudits CUSTOM Custom gate on multiple qudits same unitary gate on multiple qudits QFT quantum Fourier transform, TFQ quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET Controlled 1 qudit unitary gate with one control and one target Controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET Controlled 1 qudit unitary gate with multiple controls and single target CUSTOM_CTRL Custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_SINGLE_TARGET Controlled 1 qudit unitary gate with one classical control and one target CUSTOM_CTRL Custom controlled gate with multiple controls and multiple targets CUSTOM_CTRL Custom controlled 1 qudit unitary gate with one classical control and one target CONTROLLE_CCTRL_MULTIPLE_TARGET Controlled 1 qudit unitary gate with one classical control and multiple targets CUSTOM_CTRL Controlled 1 qudit unitary gate with one classical control and multiple targets CONTROLLE_CCTRL_MULTIPLE_TARGET Controlled 1 qudit unitary gate with multiple classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET Controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET Controlled 1 qudit unitary gate with multiple classical controls and multiple targets	SINGLE	unitary gate on a single qudit
CUSTOM custom gate on multiple qudits FAN same unitary gate on multiple qudits QFT quantum Fourier transform, TFQ quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	TWO	unitary gate on 2 qudits
FAN same unitary gate on multiple qudits QFT quantum Fourier transform, TFQ quantum inverse Fourier transform, QUANTUM quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	THREE	unitary gate on 3 qudits
QFT quantum Fourier transform, TFQ quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	CUSTOM	custom gate on multiple qudits
TFQ quantum inverse Fourier transform, SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one control and one target SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_CCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_CCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	QFT	quantum Fourier transform,
SINGLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one control and multiple targets MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	TFQ	quantum inverse Fourier transform,
MULTIPLE_CTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple controls and single target MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	SINGLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one control and one target
MULTIPLE_CTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple controls and multiple targets CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	SINGLE_CTRL_MULTIPLE_TARGET	, , , , , , , , , , , , , , , , , , , ,
CUSTOM_CTRL custom controlled gate with multiple controls and multiple targets SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	MULTIPLE_CTRL_SINGLE_TARGET	
SINGLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with one classical control and one target SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	MULTIPLE_CTRL_MULTIPLE_TARGET	
SINGLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with one classical control and multiple targets MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	CUSTOM_CTRL	custom controlled gate with multiple controls and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	SINGLE_cCTRL_SINGLE_TARGET	, , , , ,
single target MULTIPLE_cCTRL_MULTIPLE_TARGET controlled 1 qudit unitary gate with multiple classical controls and multiple targets	SINGLE_cCTRL_MULTIPLE_TARGET	, , , , ,
multiple targets	MULTIPLE_cCTRL_SINGLE_TARGET	. , , , , , , , , , , , , , , , , , , ,
CUSTOM_cCTRL custom controlled gate with multiple controls and multiple targets	MULTIPLE_cCTRL_MULTIPLE_TARGET	
	CUSTOM_cCTRL	custom controlled gate with multiple controls and multiple targets

7.55.3.2 MeasureType

enum qpp::QCircuit::MeasureType [strong]

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$

7.55.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.55.4 Constructor & Destructor Documentation

7.55.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.55.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.55.5 Member Function Documentation

7.55.5.1 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

```
7.55.5.2 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.55.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.55.5.4 cbegin()
```

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.55.5.5 cCTRL() [1/4]

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

std::string name = "") [inline]

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
const std::vector< idx > & ctrl_dits,
idx target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.8 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.9 cCTRL_custom()

```
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	target Target qudit indexes where the gate <i>U</i> is applied depending on the values of the classical control	
name	Optional gate name	

Returns

Reference to the current instance

7.55.5.10 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.55.5.11 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

std::string name = "") [inline]

idx target,

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

U	Multiple-qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes where the gate <i>U</i> is applied depending on the values of the control qudits	
name	Optional gate name	

Returns

Reference to the current instance

7.55.5.16 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.55.5.17 end() [1/2]
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.55.5.18 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate U on single qudit i.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.55.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate	
target	Subsystem indexes where the gate <i>U</i> is applied	
name	Optional gate name	

Returns

Reference to the current instance

```
7.55.5.23 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target Target qudit indexes; the gate U is applied on every one of ther	
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.24 gate_fan() [2/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.25 gate_fan() [3/3]
```

Applies the single qudit gate *U* on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.26 get_cmat_hash_tbl_()
```

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.55.5.27 get_d()
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
Dimension of the comprising qudits.
Returns
     Qudit dimension
7.55.5.28 get_gate_count() [1/2]
idx qpp::QCircuit::get_gate_count ( ) const [inline], [noexcept]
Quantum circuit total gate count.
Returns
     Total gate count
7.55.5.29 get_gate_count() [2/2]
idx qpp::QCircuit::get_gate_count (
              const std::string & name ) const [inline]
Quantum circuit gate count.
Parameters
 name
         Gate name
Returns
     Gate count
```

```
7.55.5.30 get_gate_depth() [1/2]
idx qpp::QCircuit::get_gate_depth ( ) const [inline]
```

Quantum circuit total gate depth.

Returns

Total gate depth

```
7.55.5.31 get_gate_depth() [2/2]
idx qpp::QCircuit::get_gate_depth (
             const std::string &name QPP_UNUSED_ ) const [inline]
Quantum circuit gate depth.
Parameters
 name
         Gate name
Returns
     Gate depth
7.55.5.32 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
Returns
     Vector of qpp::QCircuit::GateStep
7.55.5.33 get_measured() [1/2]
idx qpp::QCircuit::get_measured (
             idx i ) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit *i* was already measured, false othwewise

```
7.55.5.34 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.55.5.35 get_measurement_count() [1/2]
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.55.5.36 get_measurement_count() [2/2]
```

Quantum circuit measurement count.

Parameters

```
name Measurement name
```

Returns

Measurement count

7.55.5.37 get_measurements_()

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

 $\label{thm:continuous} \mbox{Vector of qpp::QCircuit::MeasureStep.}$

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.55.5.38 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.55.5.39 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.55.5.40 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.5.41 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.55.5.42 get_step_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.55.5.43 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.55.5.44 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
Gen <i>egra</i> neorib	y ூரர்ஞா al measurement name

Returns

Reference to the current instance

7.55.5.45 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.55.5.46 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.47 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.48 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.55.6 Friends And Related Function Documentation

 ${\bf Extraction\ operator\ overload\ for\ qpp::} {\bf QCircuit::} {\bf GateType\ enum\ class.}$

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.55.6.5 QEngine

```
friend class QEngine [friend]
```

7.55.7 Member Data Documentation

```
7.55.7.1 cmat_hash_tbl_
```

```
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
```

hash table with the matrices used in the circuit, with [Key = idx, Value = cmat]

```
7.55.7.2 count_
```

```
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
```

keeps track of the gate counts

```
7.55.7.3 d_
```

```
const idx qpp::QCircuit::d_ [private]
```

qudit dimension

```
7.55.7.4 depth_
```

```
std::unordered_map<std::string, idx> qpp::QCircuit::depth_ {} [private]
```

keeps track of the gate depths

```
7.55.7.5 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.55.7.6 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.55.7.7 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
keeps track of the measurement counts
7.55.7.8 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.55.7.9 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.55.7.10 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
```

```
7.55.7.11 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
```

```
7.55.7.12 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
```

The documentation for this class was generated from the following file:


· classes/circuits.h

7.56 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits.h>
```

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector < idx > get_dits () const

Vector with the values of the underlying classical dits.

idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

• const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

• void reset ()

Resets the engine.

void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::/JOSN::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuit * qc_
        pointer to constant quantum circuit
    ket psi_
        state vector
    std::vector < idx > dits_
        classical dits
    std::vector < double > probs_
        measurement probabilities
    std::vector < idx > subsys_
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.56.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.56.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.56.2.4 \sim QEngine()
```

```
\label{eq:condition} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

7.56.3 Member Function Documentation

```
7.56.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

```
7.56.3.3 execute() [2/2]
```

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

```
7.56.3.4 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.56.3.5 get_dit()
```

```
idx qpp::QEngine::get_dit (
         idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

i Classical dit index

Returns

Value of the classical dit at position i

```
7.56.3.6 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.56.3.7 get_measured() [1/2]
```

Check whether qudit i was already measured.

Parameters

i Qudit index

Returns

True if qudit *i* was already measured, false othwewise

```
7.56.3.8 get_measured() [2/2]
```

```
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.56.3.9 get_not_measured()

```
std::vector<idx> qpp::QEngine::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured gudit indexes

7.56.3.10 get_probs()

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.56.3.11 get_psi()

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.56.3.12 get_ref_psi()

```
ket& qpp::QEngine::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

7.56.3.13 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.56.3.14 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.56.3.15 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.56.3.16 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.56.3.17 set_measured_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.56.3.18 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.56.4 Member Data Documentation

```
7.56.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits

7.56.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
```

```
7.56.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector

7.56.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:

std::vector<idx> qpp::QEngine::subsys_ [protected]

· classes/circuits.h


7.56.4.5 subsys_

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

gamma	Phase damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description


Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters



The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occur	urred
---	-------

7.63.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.64.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.64.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.65.2.2 ∼RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get thread local instance () noexcept(std::is nothrow constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{split} & template {<} typename \ T {>} \\ & class \ qpp::internal::Singleton {<} \ T {>} \end{split}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton< T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.67.2.2 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

```
7.70.3.5 plus()
```

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

```
Plus state |+\rangle^{\otimes n} of n qubits
```

7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.70.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.70.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.71.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.72.2 Constructor & Destructor Documentation

7.72.2.1 Timer() [1/3]

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T = std::chrono::steady}}$ $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp::Timer}}$ $$ \ensuremath{\texttt{T, CLOCK\_T >::Timer}}$ ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.72.2.2 Timer() [2/3]

Default copy constructor.

7.72.2.3 Timer() [3/3]

Default move constructor.

7.72.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.3 operator=() [1/2]

Default copy assignment operator.

7.72.3.4 operator=() [2/2]

Default move assignment operator.

7.72.3.5 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.6 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.7 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.73.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.74.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.75.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the parent iterator</li>
    StepType type_ {StepType::NONE}
        step type
        idx ip_ {static_cast<idx>(-1)}
            instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_ {}
            gates instruction pointer
    std::vector< MeasureStep >::const_iterator measurements_ip_ {}
            measurements instruction pointer
```

Private Member Functions

7.76.1 Constructor & Destructor Documentation

```
7.76.1.2 value_type_() [2/2]

qpp::QCircuit::iterator::value_type_::value_type_ (
```

```
const value_type_ & ) [default]
```

Default copy constructor.

7.76.2 Member Function Documentation

7.76.2.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.3 Member Data Documentation

```
7.76.3.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
```

```
7.76.3.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.3.3 measurements_ip_
\verb|std::vector<| MeasureStep>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| terator| terato
ip_ {}
measurements instruction pointer
7.76.3.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.3.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the parent iterator
The documentation for this class was generated from the following file:
```


classes/circuits.h

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.77.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

- class qpp::QCircuit::iterator::value_type_
- class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

356 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

358 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

360 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Eigenvectors.

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template < typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
      Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.
template<typename Derived >
  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template < typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
ullet template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.
```

dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

• cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >--:value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container > ::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator"" _prj ()

Multi-partite qubit projector user-defined literal.

template<class T >

void qpp::internal::hash_combine (std::size_t &seed, const T &v)

• template<typename Derived >

std::size_t qpp::hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)

Computes the hash of en Eigen matrix/vector/expression.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

- template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

 Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const

Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat $> qpp::measure_seq$ (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer
 PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton < T >
 Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool qpp::internal::check no duplicates (std::vector < idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get dim subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

• std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint dpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)

Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat gpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
```

```
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



8.28 traits.h File Reference 389

Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::sigma (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_{\leftarrow} iterable< Container >::value >::type *=nullptr)$

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltyp
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex< double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.29.1 Detailed Description

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 392	applyTFQ
~Codes	qpp, 35
qpp::Codes, 136	avg
\sim Dynamic_bitset	qpp, 36
qpp::Dynamic_bitset, 158	
\sim Gates	b00
qpp::Gates, 174	qpp::States, 331
\sim IDisplay	b01
qpp::IDisplay, 190	qpp::States, 332
\sim IJSON	b10
qpp::IJSON, 193	qpp::States, 332
\sim Init	b11
qpp::Init, 195	qpp::States, 332
\sim NoiseBase	begin
qpp::NoiseBase, 242	qpp::QCircuit, 275
\sim QCircuit	bigint
qpp::QCircuit, 274	qpp, 26
\sim QEngine	Bit_circuit
qpp::QEngine, 298	qpp::Bit_circuit, 131
\sim RandomDevices	bloch2rho
qpp::RandomDevices, 319	qpp, 36
~Singleton	bra
qpp::internal::Singleton, 323	qpp, 26
~States	
qpp::States, 329	c_reg_
\sim Timer	qpp::QCircuit::MeasureStep, 236
qpp::Timer, 340	cCTRL_custom
""	qpp::QCircuit, 277
A_	cCTRL
qpp::internal::IOManipEigen, 199	qpp::QCircuit, 275–277
absm	CNOTba
qpp, 28	qpp::Gates, 183
abssq	CNOT
qpp, 29	qpp::Bit_circuit, 131
add_hash_	qpp::Bit_circuit::Gate_count, 170
qpp::QCircuit, 274	qpp::Gates, 183
adjoint	CTRL_custom
qpp, 30	qpp::QCircuit, 280
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuit, 278-280
qpp, 30	cbegin
any	qpp::QCircuit, 275
qpp::Dynamic_bitset, 158	cend
apply	qpp::QCircuit, 278
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check_dims_match_cvect

qpp::internal, 120	comm
check_dims_match_mat	qpp, 37
qpp::internal, 120	complement
check_dims_match_rvect	qpp, 38
qpp::internal, 120	compperm
check_eq_dims	qpp, 38
qpp::internal, 121	compute_probs_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_no_duplicates	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_nonzero_size	qpp, 40
qpp::internal, 121	conjugate
check_perm	qpp, 40
qpp::internal, 121	const_iterator
check_qubit_cvector	qpp::QCircuit, 272 constants.h, 365
qpp::internal, 121	contfrac2x
check_qubit_matrix	
qpp::internal, 122	qpp, 40
check_qubit_rvector	convergents
qpp::internal, 122	qpp, 41 cor
check_qubit_vector	qpp, 42
qpp::internal, 122	cosm
check_rvector	qpp, 42
qpp::internal, 122	count
check_square_mat	qpp::Dynamic_bitset, 158
qpp::internal, 122	count
check_subsys_match_dims	qpp::QCircuit, 293
qpp::internal, 122	COV
check_vector	qpp, 43
qpp::internal, 123	cplx
choi2kraus	qpp, 27
qpp, 36	ctrl
choi2super	qpp::QCircuit::GateStep, 187
qpp, 37	CustomException
chop	qpp::exception::CustomException, 138
qpp, 116	cwise
chop_	qpp, 43
qpp::internal::IOManipEigen, 200	CZ
classes/circuits.h, 355	qpp::Gates, 183
classes/codes.h, 356	,
classes/exception.h, 357	d_
classes/gates.h, 359	qpp::NoiseBase, 246
classes/idisplay.h, 360	qpp::QCircuit, 293
classes/init.h, 360	data
classes/noise.h, 361	qpp::Dynamic_bitset, 158
classes/random_devices.h, 362	depth_
classes/reversible.h, 363	qpp::QCircuit, 293
classes/states.h, 363	det
classes/timer.h, 364	qpp, 44
cmat	difference_type
qpp, 26	qpp::QCircuit::iterator, 213
cmat_hash_tbl_	dirsum
qpp::QCircuit, 293	qpp, 44–46
Codes	dirsum2
qpp::Codes, 136	qpp::internal, 123
codeword	dirsumpow
qpp::Codes, 136	qpp, 46

disp	qpp::exception::Duplicates, 154
qpp, 47, 48	qpp::exception::Exception, 169
display	qpp::exception::InvalidIterator, 197
qpp::Dynamic_bitset, 159	qpp::exception::MatrixMismatchSubsys, 219
qpp::IDisplay, 191	qpp::exception::MatrixNotCvector, 221
qpp::QCircuit, 281	qpp::exception::MatrixNotRvector, 223
qpp::QCircuit::iterator::value_type_, 351	qpp::exception::MatrixNotSquare, 225
qpp::QEngine, 298	qpp::exception::MatrixNotSquareNorCvector, 227
qpp::Timer, 340	qpp::exception::MatrixNotSquareNorRvector, 229
qpp::internal::IOManipEigen, 199	qpp::exception::MatrixNotSquareNorVector, 231
qpp::internal::IOManipPointer, 202	qpp::exception::MatrixNotVector, 233
qpp::internal::IOManipRange, 205	qpp::exception::NoCodeword, 238
display_impl_	qpp::exception::NotBipartite, 249
qpp::internal::Display_Impl_, 152	qpp::exception::NotImplemented, 251
dits_	qpp::exception::NotQubitCvector, 253
qpp::QEngine, 303	qpp::exception::NotQubitMatrix, 255
dmat	qpp::exception::NotQubitRvector, 257
qpp, 27	qpp::exception::NotQubitSubsys, 259
dyn_col_vect	qpp::exception::NotQubitVector, 261
qpp, 27	qpp::exception::OutOfRange, 263
dyn_mat	qpp::exception::PermInvalid, 265
qpp, 27	qpp::exception::PermMismatchDims, 267
dyn_row_vect	qpp::exception::QuditAlreadyMeasured, 314
qpp, 27	qpp::exception::SizeMismatch, 325
Dynamic_bitset	qpp::exception::SubsysMismatchDims, 337
qpp::Bit_circuit, 132	qpp::exception::TypeMismatch, 344
qpp::Dynamic_bitset, 157	qpp::exception::UndefinedType, 346
	qpp::exception::Unknown, 348
ee	qpp::exception::ZeroSize, 354
qpp, 116	execute
egcd	qpp::QEngine, 299
qpp, 49	expandout
eig	qpp::Gates, 175, 176
qpp, 49	experimental/experimental.h, 369
elem_	expm
qpp::QCircuit::iterator, 217	qpp, 52
end	-II-1-7
qpp::QCircuit, 281	FRED
end_	qpp::Bit circuit, 132
qpp::Timer, 342	qpp::Bit_circuit::Gate_count, 171
qpp::internal::IOManipPointer, 202	qpp::Gates, 183
qpp::internal::IOManipRange, 206	factors
entanglement	qpp, 53
qpp, 50	Fd
entanglement.h, 366	qpp::Gates, 177
entropies.h, 368	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 317
qpp, 51	fill_probs_
evals	qpp::QuditDepolarizingNoise, 317
qpp, 51	first_
evects	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	. qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 369
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	qpp, 53
qpp::exception::DimsMismatchRvector, 147	н 177 7 7
qpp::exception::DimsMismatchVector, 149	GHZ
qpp::exception::DimsNotEqual, 151	qpp::States, 332
	

gate	qpp::NoiseBase, 244
qpp::QCircuit, 281, 282	get_last_p
gate_count	qpp::NoiseBase, 244
qpp::Bit_circuit, 134	get_measured
gate_custom	qpp::QCircuit, 286
qpp::QCircuit, 283	qpp::QEngine, 300
gate_fan	get_measurement_count
qpp::QCircuit, 283, 284	qpp::QCircuit, 287
gate_hash_	get_measurements_
qpp::QCircuit::GateStep, 187	qpp::QCircuit, 287
gate_type_	get_name
qpp::QCircuit::GateStep, 187	qpp::Gates, 178 qpp::QCircuit, 287
GateStep	get_nc
qpp::QCircuit::GateStep, 186	qpp::QCircuit, 288
GateType qpp::QCircuit, 272	get_non_measured
Gates	qpp::QCircuit, 288
qpp::Gates, 174	get not measured
gates_	qpp::QEngine, 300
qpp::QCircuit, 293	get_nq
gates ip	qpp::QCircuit, 288
qpp::QCircuit::iterator::value_type_, 351	get_num_subsys
gcd	qpp::internal, 123
qpp, 54	get_prng
gconcurrence	qpp::RandomDevices, 320
qpp, 54	get_probs
generated_	qpp::NoiseBase, 244
qpp::NoiseBase, 246	qpp::QEngine, 301
get	get_psi
qpp::Dynamic_bitset, 160	qpp::QEngine, 301 get_ref_psi
get_Ks	qpp::QEngine, 301
qpp::NoiseBase, 243	get_relative_pos_
get_circuit	qpp::QEngine, 301
qpp::QEngine, 299	get_step_count
get_cmat_hash_tbl_	qpp::QCircuit, 288
qpp::QCircuit, 284	get_thread_local_instance
get_d qpp::NoiseBase, 243	qpp::internal::Singleton, 323
qpp::RoiseBase, 240 qpp::QCircuit, 284	grams
get_dim_subsys	qpp, 55, 56
qpp::internal, 123	
get dit	H appuCates 192
qpp::QEngine, 299	qpp::Gates, 183 hash combine
get_dits	qpp::internal, 123
qpp::QEngine, 300	hash eigen
get_duration	qpp, 56
qpp::Timer, 341	heig
get_gate_count	qpp, 57
qpp::QCircuit, 285	hevals
get_gate_depth	qpp, 57
qpp::QCircuit, 285	hevects
get_gates_	qpp, 57
qpp::QCircuit, 286	
get_instance	i_ N.: B. 040
app::internal::Singleton, 323	qpp::NoiseBase, 246
get_last_idx	IDisplay 100
qpp::NoiseBase, 243	qpp::IDisplay, 190
get_last_K	IJSON

qpp::IJSON, 192, 193 IOManipEigen	qpp, 61, 62 kron2
qpp::internal::IOManipEigen, 199 IOManipPointer	qpp::internal, 123 kronpow
qpp::internal::IOManipPointer, 201, 202	qpp, 63
IOManipRange	Ks_
qpp::internal::IOManipRange, 205	qpp::NoiseBase, 246
qpp::Gates, 178	last
Id2	qpp::internal::IOManipRange, 206
qpp::Gates, 184	lcm
idx	qpp, 63, 64
qpp, 28	load
index	qpp, 64
qpp::Dynamic_bitset, 160	qpp::RandomDevices, 320
infty	loadMATLAB
•	qpp, 65, 66
qpp, 116	logdet
Init	
qpp::Init, 195	qpp, 66
input_output.h, 374	logm
instruments.h, 375	qpp, 67
internal/classes/iomanip.h, 377	lognegativity
internal/classes/singleton.h, 378	qpp, 67
internal/util.h, 378	MATI AD/motlob b 200
internal::Singleton < const Codes >	MATLAB/matlab.h, 380
qpp::Codes, 137	MODMUL
internal::Singleton < const Gates >	qpp::Gates, 178
qpp::Gates, 183	marginalX
internal::Singleton< const Init >	qpp, 68
qpp::Init, 195	marginalY
internal::Singleton < const States >	qpp, 68
qpp::States, 331	mats_hash_
internal::Singleton < RandomDevices >	qpp::QCircuit::MeasureStep, 236
gpp::RandomDevices, 321	maxn
inverse	qpp, 116
qpp, 58	measure
invperm	qpp, 69–73
qpp, 58	measure_seq
ip	qpp, 74
qpp, 59	MeasureStep
	qpp::QCircuit::MeasureStep, 235
ip_ gpp://Circuit::iterator::yelue_type_3E1	MeasureType
qpp::QCircuit::iterator::value_type_, 351	qpp::QCircuit, 273
isprime	measured
qpp, 60	qpp::QCircuit, 294
iterator	measurement count
qpp::QCircuit::iterator, 214	qpp::QCircuit, 294
iterator_category	measurement_type_
qpp::QCircuit::iterator, 213	
	qpp::QCircuit::MeasureStep, 236
jn	measurements_
qpp::States, 329	qpp::QCircuit, 294
la	measurements_ip_
ket	qpp::QCircuit::iterator::value_type_, 352
qpp, 28	measureV
kraus2choi	qpp::QCircuit, 289
qpp, 60	measureZ
kraus2super	qpp::QCircuit, 290
qpp, 61	mes
kron	qpp::States, 329

minus	operator<<
qpp::States, 330	qpp::IDisplay, 191
mket	qpp::QCircuit, 291, 292
qpp, 75, 76	operator*
modiny	qpp::QCircuit::iterator, 215
qpp, 76	
	operator()
modmul	qpp::NoiseBase, 244, 245
qpp, 77	qpp::internal::EqualEigen, 166
modpow	qpp::internal::HashEigen, 188
qpp, 77	operator++
mprj	qpp::QCircuit::iterator, 215
qpp, 78	operator-
msg	qpp::Dynamic_bitset, 161
qpp::exception::Exception, 170	operator=
multiidx2n	qpp::IDisplay, 191
qpp, 79	qpp::IJSON, 193
	qpp::QCircuit::iterator, 215
qpp::internal, 124	
n2multiidx	qpp::QCircuit::iterator::value_type_, 351
	qpp::QEngine, 302
qpp, 79	qpp::Timer, 341
qpp::internal, 124	qpp::internal::IOManipPointer, 202
N_	qpp::internal::IOManipRange, 205
qpp::Dynamic_bitset, 165	qpp::internal::Singleton, 323
qpp::internal::IOManipPointer, 203	operator==
NOT	qpp::Dynamic_bitset, 162
qpp::Bit_circuit, 132	qpp::QCircuit::iterator, 216
qpp::Bit_circuit::Gate_count, 171	operator"" _bra
name	
_	qpp::literals, 125
qpp::QCircuit, 294	operator"" _i
qpp::QCircuit::GateStep, 187	qpp, 82
qpp::QCircuit::MeasureStep, 236	qpp::literals, 125
nc_	operator"" _ket
qpp::QCircuit, 294	qpp::literals, 126
negativity	operator"" _prj
qpp, 80	qpp::literals, 126
noise_type	4pp
qpp::NoiseBase, 241	р
NoiseBase	qpp::internal::IOManipPointer, 203
	pGHZ
qpp::NoiseBase, 241	qpp::States, 333
none	
qpp::Dynamic_bitset, 160	pb00
norm	qpp::States, 332
qpp, 81	pb01
normalize	qpp::States, 332
qpp, 81	pb10
nq_	qpp::States, 333
qpp::QCircuit, 294	pb11
number_theory.h, 381	qpp::States, 333
number_meory.n, 301	pi
offset	qpp, 116
_	
qpp::Dynamic_bitset, 161	plus
omega	qpp::States, 330
qpp, 81	pointer
one	qpp::QCircuit::iterator, 213
qpp::States, 330	powm
operations.h, 383	qpp, 82
operator!=	prj
qpp::Dynamic_bitset, 161	qpp, 82
qpp::QCircuit::iterator, 214	prng_
المالية	r···9_

qpp::RandomDevices, 321	choi2kraus, 36
probs_	choi2super, 37
qpp::NoiseBase, 246	chop, 116
qpp::QEngine, 303	cmat, 26
prod	comm, 37
qpp, 83, 84	complement, 38
psi_	compperm, 38
qpp::QEngine, 303	concurrence, 40
ptrace qpp, 84, 85	conjugate, 40
ptrace1	contfrac2x, 40
qpp, 85, 86	convergents, 41
ptrace2	cor, 42 cosm, 42
qpp, 86, 87	cov, 43
ptranspose	cov, 43 cplx, 27
qpp, 87, 88	cwise, 43
Wq	det, 44
qpp::States, 333	dirsum, 44–46
px0	dirsumpow, 46
qpp::States, 333	disp, 47, 48
px1	dmat, 27
qpp::States, 333	dyn col vect, 27
py0	dyn_mat, 27
qpp::States, 334	dyn_row_vect, 27
py1	ee, 116
qpp::States, 334	egcd, 49
pz0	eig, 49
qpp::States, 334	entanglement, 50
pz1	entropy, 51
qpp::States, 334	evals, 51
OC: marrie	evects, 52
QCircuit	expm, 52
qpp::QCircuit, 274 QEngine	factors, 53
qpp::QCircuit, 293	funm, 53
qpp::QEngine, 297, 298	gcd, 54
QFT	gconcurrence, 54
qpp, 88	grams, 55, 56
app::QCircuit, 290	hash_eigen, 56
QPP_UNUSED_	heig, 57
qpp.h, 386	hevals, 57
qc_	hevects, 57
qpp::QCircuit::iterator, 217	idx, 28
qpp::QEngine, 304	infty, 116
qmutualinfo	inverse, 58
qpp, 89	invperm, 58
qpp, 13	ip, 59
absm, 28	isprime, 60
abssq, 29	ket, 28
adjoint, 30	kraus2choi, 60
anticomm, 30	kraus2super, 61
apply, 31–33	kron, 61, 62
applyCTRL, 33, 34	kronpow, 63
applyQFT, 35	lcm, 63, 64
applyTFQ, 35	load, 64
avg, 36	loadMATLAB, 65, 66
bigint, 26	logdet, 66
bloch2rho, 36	logm, 67
bra, 26	lognegativity, 67

marginalX, 68	svdU, 110
marginalY, 68	svdV, 111
maxn, 116	syspermute, 111, 112
measure, 69–73	TFQ, 112
measure_seq, 74	to_void, 28
mket, 75, 76	trace, 112
modinv, 76	transpose, 113
modmul, 77	tsallis, 113, 114
modpow, 77	uniform, 114
mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 385
negativity, 80	QPP_UNUSED_, 386
norm, 81	qpp::Bit_circuit, 129
normalize, 81	Bit_circuit, 131
omega, 81	CNOT, 131
operator"" _i, 82	Dynamic bitset, 132
pi, 116	FRED, 132
powm, 82	gate_count, 134
prj, 82	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	∼Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton < const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	∼Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110	size, 164

storage_size, 164	get_d, 243
storage_size_, 165	get_last_idx, 243
storage_type, 157	get_last_K, 244
to_string, 164	get_last_p, 244
v_, 165	get_probs, 244
value_type, 157	i_, 246
qpp::Gates, 172	Ks_, 246
\sim Gates, 174	noise_type, 241
CNOTba, 183	NoiseBase, 241
CNOT, 183	operator(), 244, 245
CTRL, 175	probs_, 246
CZ, 183	qpp::NoiseBase< T >, 239
expandout, 175, 176	qpp::NoiseType, 247
FRED, 183	qpp::NoiseType::StateDependent, 326
Fd, 177	qpp::NoiseType::StateIndependent, 326
Gates, 174	qpp::QCircuit, 268
get name, 178	~QCircuit, 274
H, 183	add_hash_, 274
ld, 178	begin, 275
ld2, 184	cCTRL_custom, 277
internal::Singleton< const Gates >, 183	cCTRL, 275–277
MODMUL, 178	
	CTRL_custom, 280
Rn, 179	CTRL, 278–280
RX, 179	cbegin, 275
RY, 180	cend, 278
RZ, 180	cmat_hash_tbl_, 293
S, 184	const_iterator, 272
SWAPd, 180	count_, 293
SWAP, 184	d_, 293
T, 184	depth_, 293
TOF, 184	display, 281
X, 184	end, 281
Xd, 182	gate, 281, 282
Y, 185	gate_custom, 283
Z, 185	gate_fan, 283, 284
Zd, 182	GateType, 272
qpp::IDisplay, 189	gates_, 293
\sim IDisplay, 190	get_cmat_hash_tbl_, 284
display, 191	get_d, <mark>284</mark>
IDisplay, 190	get_gate_count, 285
operator<<, 191	get_gate_depth, 285
operator=, 191	get_gates_, 286
qpp::IJSON, 192	get_measured, 286
\sim IJSON, 193	get_measurement_count, 287
IJSON, 192, 193	get_measurements_, 287
operator=, 193	get_name, 287
to_JSON, 193	get_nc, 288
qpp::lnit, 194	get_non_measured, 288
\sim Init, 195	get_nq, 288
Init, 195	get_step_count, 288
internal::Singleton< const Init >, 195	MeasureType, 273
qpp::NoiseBase	measured_, 294
\sim NoiseBase, 242	measurement_count_, 294
compute_probs_, 242	measurements_, 294
compute_state_, 242	measureV, 289
d_, 246	measureZ, 290
generated_, 246	name_, 294
get_Ks, 243	nc_, 294
 -	_

	nq_, 294	get_probs, 301
	operator<<, 291, 292	get_psi, 301
	QCircuit, 274	get_ref_psi, 301
	QEngine, 293	get relative pos , 301
	QFT, 290	operator=, 302
	step_types_, 295	probs_, 303
	StepType, 273	psi_, 303
	TFQ, 290	QEngine, 297, 298
	to_JSON, 291	qc_, 304
app:	:QCircuit::GateStep, 185	reset, 302
91919	ctrl_, 187	set dit, 302
	gate_hash_, 187	set_measured_, 302
	gate_type_, 187	subsys_, 304
	GateStep, 186	to_JSON, 303
	name_, 187	qpp::QubitAmplitudeDampingNoise, 304
	target_, 187	QubitAmplitudeDampingNoise, 305
ann:	:QCircuit::MeasureStep, 234	qpp::QubitBitFlipNoise, 306
чрр.	c_reg_, 236	QubitBitFlipNoise, 307
	mats hash , 236	qpp::QubitBitPhaseFlipNoise, 307
	— — — — ·	
	MeasureStep, 235	QubitBitPhaseFlipNoise, 308
	measurement_type_, 236	qpp::QubitDepolarizingNoise, 309
	name_, 236	QubitDepolarizingNoise, 310
	target_, 236	qpp::QubitPhaseDampingNoise, 310
qpp:	:QCircuit::iterator, 212	QubitPhaseDampingNoise, 311
	difference_type, 213	qpp::QubitPhaseFlipNoise, 312
	elem_, 217	QubitPhaseFlipNoise, 313
	iterator, 214	qpp::QuditDepolarizingNoise, 315
	iterator_category, 213	fill_Ks_, 317
	operator!=, 214	fill_probs_, 317
	operator*, 215	QuditDepolarizingNoise, 316
	operator++, 215	qpp::RandomDevices, 318
	operator=, 215	\sim RandomDevices, 319
	operator==, 216	get_prng, 320
	pointer, 213	internal::Singleton < RandomDevices >, 321
	qc_, 217	load, 320
	reference, 214	prng_, 321
	set_begin_, 216	RandomDevices, 319
	set_end_, 216	rd_, 321
	value_type, 214	save, 320
qpp:	:QCircuit::iterator::value_type_, 349	qpp::States, 326
	display, 351	\sim States, 329
	gates_ip_, 351	b00, 331
	ip_, 351	b01, 332
	measurements_ip_, 352	b10, 332
	operator=, 351	b11, 332
	type_, 352	GHZ, 332
	value_type_, 350	internal::Singleton < const States >, 331
	value_type_qc_, 352	jn, 329
qpp:	:QEngine, 295	mes, 329
	~QEngine, 298	minus, 330
	display, 298	one, 330
	dits_, 303	pGHZ, 333
	execute, 299	pb00, 332
	get_circuit, 299	pb01, 332
	get_dit, 299	pb10, 333
	get_dits, 300	pb11, 333
	get_measured, 300	plus, 330
	get_not_measured, 300	pW, 333
	<u></u>	F 2.1, 000

px0, 333	whore 170
px1, 333	where_, 170 qpp::exception::InvalidIterator, 196
py0, 334	Exception, 197
py1, 334	type_description, 197
pz0, 334	qpp::exception::MatrixMismatchSubsys, 218
pz1, 334	Exception, 219
States, 329	type_description, 220
W, 334	qpp::exception::MatrixNotCvector, 220
x0, 334	Exception, 221
x1, 335	type_description, 222
y0, 335	qpp::exception::MatrixNotRvector, 222
y1, 335	Exception, 223
z0, 335	type_description, 224
z1, 335	qpp::exception::MatrixNotSquare, 224
zero, 331	Exception, 225
qpp::Timer	type_description, 226
∼Timer, 340	qpp::exception::MatrixNotSquareNorCvector, 226
display, 340	Exception, 227
end , 342	type_description, 228
get duration, 341	qpp::exception::MatrixNotSquareNorRvector, 228
operator=, 341	Exception, 229
start_, 342	type_description, 230
tic, 341	qpp::exception::MatrixNotSquareNorVector, 230
tics, 342	Exception, 231
Timer, 339, 340	type_description, 232
toc, 342	qpp::exception::MatrixNotVector, 232
qpp::Timer< T, CLOCK_T >, 338	Exception, 233
qpp::exception, 116	type_description, 234
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 237
CustomException, 138	Exception, 238
type_description, 139	type_description, 239
what_, 139	qpp::exception::NotBipartite, 247
qpp::exception::DimsInvalid, 140	Exception, 249
Exception, 141	type description, 249
type_description, 141	qpp::exception::NotImplemented, 250
qpp::exception::DimsMismatchCvector, 142	Exception, 251
Exception, 143	type_description, 251
type_description, 143	qpp::exception::NotQubitCvector, 252
qpp::exception::DimsMismatchMatrix, 144	Exception, 253
Exception, 145	type_description, 253
type_description, 145	qpp::exception::NotQubitMatrix, 254
qpp::exception::DimsMismatchRvector, 146	Exception, 255
Exception, 147	type_description, 255
type_description, 147	qpp::exception::NotQubitRvector, 256
qpp::exception::DimsMismatchVector, 148	Exception, 257
Exception, 149	type_description, 257
type_description, 149	qpp::exception::NotQubitSubsys, 258
qpp::exception::DimsNotEqual, 150	Exception, 259
Exception, 151	type_description, 259
type_description, 151	qpp::exception::NotQubitVector, 260
qpp::exception::Duplicates, 153	Exception, 261
Exception, 154	type_description, 261
type_description, 154	qpp::exception::OutOfRange, 262
qpp::exception::Exception, 167	Exception, 263
Exception, 169	type_description, 263
msg_, 170	qpp::exception::PermInvalid, 264
type_description, 169	Exception, 265
what, 169	type_description, 265

annuayaantianuBarmMiamatahDima 266	annuinternalulOMeninEigen 100
app::exception::PermMismatchDims, 266	qpp::internal::IOManipEigen, 198
Exception, 267	A_, 199
type_description, 267	chop_, 200
app::exception::QuditAlreadyMeasured, 313	display, 199
Exception, 314	IOManipEigen, 199
type_description, 315	qpp::internal::IOManipPointer
qpp::exception::SizeMismatch, 324	display, 202
Exception, 325	end_, 202
type_description, 325	IOManipPointer, 201, 202
qpp::exception::SubsysMismatchDims, 336	N_, 203
Exception, 337	operator=, 202
type_description, 337	p_, 203
qpp::exception::TypeMismatch, 343	separator_, 203
Exception, 344	start_, 203
type_description, 345	qpp::internal::IOManipPointer< PointerType >, 200
qpp::exception::UndefinedType, 345	qpp::internal::IOManipRange
Exception, 346	display, 205
type_description, 347	end_, 206
qpp::exception::Unknown, 347	first_, 206
Exception, 348	IOManipRange, 205
type_description, 349	last_, 206
qpp::exception::ZeroSize, 353	operator=, 205
Exception, 354	separator_, 206
type_description, 354	start_, 206
qpp::experimental, 118	qpp::internal::IOManipRange< InputIterator >, 204
qpp::internal, 118	qpp::internal::Singleton
check_cvector, 120	∼Singleton, 323
check_dims, 120	get_instance, 323
check_dims_match_cvect, 120	get_thread_local_instance, 323
check_dims_match_mat, 120	operator=, 323
check_dims_match_rvect, 120	Singleton, 322, 323
check_eq_dims, 121	qpp::internal::Singleton< T >, 321
check matching sizes, 121	qpp::is complex $<$ std::complex $<$ T $>>$, 208
check_no_duplicates, 121	qpp::is_complex< T >, 207
check nonzero size, 121	<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T</pre>
check_perm, 121	>().begin()), decltype(std::declval< T >().↔
check_qubit_cvector, 121	end()), decitype(std::decival< T >().←
check_qubit_matrix, 122	begin()))>>, 210
check_qubit_rivector, 122	qpp::is iterable < T, typename >, 209
-· -	qpp:.is_nerable< 1, typerlame >, 209 qpp::is_matrix_expression< Derived >, 211
check_qubit_vector, 122 check_rvector, 122	
-	qpp::literals, 125
check_square_mat, 122	operator"" _bra, 125
check_subsys_match_dims, 122	operator"" _i, 125
check_vector, 123	operator""_ket, 126
dirsum2, 123	operator""_prj, 126
get_dim_subsys, 123	qpp::make_void
get_num_subsys, 123	type, 218
hash_combine, 123	qpp::make_void < Ts >, 217
kron2, 123	QubitAmplitudeDampingNoise
multiidx2n, 124	qpp::QubitAmplitudeDampingNoise, 305
n2multiidx, 124	QubitBitFlipNoise
variadic_vector_emplace, 124	qpp::QubitBitFlipNoise, 307
qpp::internal::Display_Impl_, 152	QubitBitPhaseFlipNoise
display_impl_, 152	qpp::QubitBitPhaseFlipNoise, 308
qpp::internal::EqualEigen, 166	QubitDepolarizingNoise
operator(), 166	qpp::QubitDepolarizingNoise, 310
qpp::internal::HashEigen, 188	QubitPhaseDampingNoise
operator(), 188	qpp::QubitPhaseDampingNoise, 311

Coultribrase FlipNoise, 313 QuditDepolarizingNoise, 316 qpp:QuditDepolarizingNoise, 316 rand qpp, 90–92 qpp:Dynamic_bitset, 162, 163 randH qpp, 92 randket qpp, 93 randket qpp, 93 randket qpp, 93 randkraus qpp, 94, 95 random Devices, 319 randomDevices, 319 randpme qpp, 96 qpp, 97 randU qpp, 98 reference qpp;QCircuit:iterator, 214 renyi qpp, 99 reset qpp;Dynamic_bitset, 163 qpp, 99 reset qpp, 99 reset qpp;Dynamic_bitset, 163 qpp, 99 reset qpp;Dynamic_bitset, 163 qpp, 101 qpp;Dynamic_bitset, 163 qpp, 106 Singleton qpp, 106 Singleton qpp, 107 size qpp;Dynamic_bitset, 164 spectralpown qpp, 106 Rn qpp, 100 Rn qpp;Gates, 179 RX qpp;Gates, 180 SWMP qpp:Circuit; 133 qpp;Bit_circuit, 132 qpp;Dynamic_bitset, 164 spectralpown qpp, 106 States qpp:Dynamic_bitset, 164 spectralpown qpp, 107 sqrtm qpp, 108 States qpp:Dynamic_bitset, 164 spectralpown qpp, 107 sqrtm qpp, 108 States qpp:States, 329 statistics, 3, 388 States qpp:States, 329 statistics, 329	OubitPhaseElipNoise	gnn::Gatos 194
QuditDepolarizingNoise qpp::Gates, 180 qpp:QuditDepolarizingNoise, 316 SWAP rand qpp::Bit_circuit; 133 qpp::Bit_circuit; 133 qpp::Dynamic_bitset, 162, 163 save randH qpp. 92 qpp::Gates, 184 randkd qpp. 93 qpp::Gates, 184 qpp. 93 qpp. 101 qpp::Gates, 180 randkraus qpp. 101, 102 schmidth qpp. 93 qpp. 101, 102 schmidth randcmus, 387 qpp. 103 schmidth random-h, 387 schmidth qpp. 103 random-bevices qpp. 104, 105 schmidthotoeffs qpp. 96 sep. 104, 105 schmidtprobs qpp. 96 sep. 104, 105 schmidtprobs qpp. 97 qpp. 106 sep. 104, 105 schmidtprobs qpp. 97 qpp. 106 sep. 104, 105 schmidtprobs qpp. 97 qpp. 106 sep. 104, 105 schmidtprobs qpp. 97 qpp. 107 set ppp::Dynamic_bitset, 163, 164 set_begin qpp::GarndomDevices, 321 <	QubitPhaseFlipNoise	qpp::Gates, 184
qpp::QuditDepolarizingNoise, 316 SWAP rand qpp. 90–92 qpp::Dynamic_bitset, 162, 163 qpp::Bit_circuit, 133 randH qpp. 92 randIdX qpp::Bat_circuit, 131 qpp, 93 qpp. 101 randket qpp. 101, 102 qpp, 93 qpp. 101, 102 randket qpp. 102 qpp. 93 qpp. 103 rand qpp, 94, 95 qpp. 103 randdmus qpp. 103 qpp. 94, 95 qpp. 103, 104 randdmus qpp. 103, 104 schmidtLoeffs qpp. 103, 104 schmidtLoeffs qpp. 103, 104 schmidtLoeffs qpp. 104, 105 schmidtLoeffs qpp. 104, 105 schmidtLoeffs qpp. 104, 105 schmidtLoeffs qpp. 104, 105 schmidtLoeffs qpp. 106, 106 separator		· · · · · ·
rand	•	•••
rand	appadditBopolari2ingriolog, 010	
qpp; 90-92 qpp:Gates, 184 randH qpp, 92 randket qpp; 101 qpp, 93 qpp; 101, 102 schatten qpp, 101, 102 schatten qpp, 101, 102 schatten qpp, 102 qpp, 99, 39 qpp, 103 randkraus qpp, 103 qpp, 99 schmidtA qpp, 103 qpp, 103 randmon qpp, 94, 95 schmidta random pp; RandomDevices, 319 schmidtcoeffs randperm qpp, 104, 105 schmidtprobs qpp, 104, 105 schmidtprobs qpp, 105, 106 separator_ qpp;internal;:IOManipPointer, 203 qpp, 96 qpp;internal;:IOManipPointer, 203 randfrob set begin_ qpp, 97 qpp;internal;:IOManipPointer, 203 randU qpp; 98 rd_ qpp;:Qp;internal;:IOManipPointer, 203 qpp; 10 qpp;internal;:Singleton, 302 set_end_ qpp;:OEngine, 302 rest_end_ qpp;internal;:Singleton, 322, 323 sinm	rand	
app:Dynamic_bitset, 162, 163 save randH app, 92 randkdx app, 101 app, 93 app, 101, 102 randkat schatten app, 93 app, 101, 102 randkraus app, 102 app, 93 aph, 102 randn app, 103 app, 94, 95 app, 103 random, 387 schmidted RandomDevices, 319 app, 103, 104 randperm app, 104, 105 app, 104, 105 schmidtprobs randprime app, 104, 105 app, 104, 105 separator app, 106, 106 separator app, 107, 106 separator app, 107 app; 108 set begin app, 107 app; 108 set begin app; 20Circuit::i	qpp, 90–92	
randH		
qpp, 92 qpp:RandomDevices, 320 randidx saveMATLAB qpp, 93 qpp, 101, 102 randkraus qpp, 102 qpp, 93 qpp, 102 randkraus qpp, 103 qpp, 94, 95 qpp, 103 randomh, 387 schmidtla RandomDevices qpp, 103, 104 randperm qpp, 104, 105 schmidtprobs qpp, 105, 106 randprime qpp, 105, 106 qpp, 97 qpp;internal::IOManipPointer, 203 randrho qpp;internal::IOManipPointer, 203 qpp, 97 qp;internal::IOManipPointer, 203 randrho qpp;internal::IOManipRange, 206 set_did qpp;internal::IOManipRange, 206 set_did qpp;internal::IOManipRange, 206 set_end_ qpp;iOcircuit::iterator, 216 set_end_ qpp;iOcircuit::iterator, 216 set_end_ qpp;iOcircuit::iterator, 216 restrace qpp;iOcircuit::iterator, 216 set_end_ qpp;iOcircuit::iterator, 216 restrace qpp;iOcircuit::iterator, 216 restr		
randidx	qpp, 92	
qpp, 93 qpp, 101, 102 randkaus qpp, 102 qpp, 93 qpp, 103 randn qpp, 103 qpp, 94, 95 schmidtB randomh, 387 schmidtCoeffs RandomDevices qpp, 103, 104 qpp:RandomDevices, 319 schmidtcoeffs randprime qpp, 104, 105 qpp, 96 separator. randprime qpp, 105, 106 qpp, 97 separator. randrine qpp:Internal::IOManipRange, 206 set set begin qpp, 97 qpp:Internal::IOManipRange, 206 randru set begin qpp, 97 qpp:Internal::IOManipRange, 206 randru set begin qpp:Internal::IOManipRange, 206 set begin qpp:Internal::IOManipRange, 206 set begin qpp:Internal::IOManipRange, 206 set_end qpp:Internal::IOManipRange, 206 set_end qpp:Internal::IOmanipRange, 206 set_end qpp:Internal::IOmanipRange, 206 set_measured qpp:Internal::IomanipRange, 206 set_measured<	randidx	
randket	qpp, 93	
qpp, 93 qpp, 102 randkraus schmidtA qpp, 93 qpp, 103 randn qpp, 103, 104 randomh, 387 schmidtB RandomDevices qpp, 104, 105 qpp:RandomDevices, 319 schmidtprobs qpp, 96 spp, 105, 106 randprime qpp, 105, 106 qpp, 96 separator_ qpp, 97 qpp:Internal::IOManipPointer, 203 qpp, 97 qpp:Internal::IOManipPointer, 203 qpp, 97 qpp:Internal::IOManipPointer, 203 qpp, 97 qpp:Internal::IOManipPointer, 203 qpp:Internal::IOManipPointer, 203 qpp:Internal::IOManipRange, 206 set_begin_ qpp:IDynamic_bitset, 163, 164 qpp, 98 qpp:IDynamic_bitset, 216 qpp:IDynamic_bitset, 163 qpp:IDynamic_bitset, 216 qpp:IDynamic_bitset, 163 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 163 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164 qpp:IDynamic_bitset, 164	randket	• •
randkraus	qpp, 93	
qpp, 93 qpp, 103 random dpp, 94, 95 qpp, 103, 104 random.h. 387 schmidtlB RandomDevices qpp, 104, 105 qpp, 96 schmidtprobs qpp, 96 separator_ qpp, 105, 106 separator_ randprime qpp, 105, 106 qpp, 96 separator_ randprob qpp::Internal::IOManipPointer, 203 qpp, 97 qpp::Internal::IOManipRange, 206 randro set_dit qpp. 97 qpp::Dynamic_bitset, 163, 164 randro set_dit qpp::Qergine, 302 set_end qpp::Qergine, 302 set_end qpp::Qergine, 302 set_end qpp::Qergine, 302 set_measured_ qpp::Qergine, 302 sigma qpp::Qergine, 302 sigma qpp::Dynamic_bitset, 163 qpp::Qergine, 302 reset qpp::Internal::Singleton, 322, 323 sinm qpp::Dynamic_bitset, 164 qpp::Dynamic_bitset, 164 qpp::Dynamic_bitset, 164 qpp::Dynamic_bitset, 164 qpp::Dynamic_bitset, 164	randkraus	
randn	qpp, 93	
app. 94, 95 qpp, 103, 104 random.h., 387 schmidtcoeffs RandomDevices qpp. 104, 105 app::RandomDevices, 319 schmidtprobs randprime qpp, 105, 106 app. 96 app::Internal::IOManipPointer, 203 randprob app::internal::IOManipPointer, 203 app. 97 app::Dynamic_bitset, 163, 164 randro set_begin app.:QCircuit::iterator, 216 set_begin app::QCircuit::iterator, 216 set_end app::QCircuit::iterator, 216 set_end app::QCircuit::iterator, 216 set_measured_ app::QCircuit::iterator, 216 set_measured_ app::QCircuit::iterator, 216 set_measured_ app::QEngine, 302 sigma app::QEngine, 302 sigma app::QEngine, 302 sigma app::QEngine, 302 sigma app::Dynamic_bitset, 163 app::Dynamic_bitset, 164 app::Dynamic_bitset, 163 app::Dynamic_bitset, 164 app::Dynamic_bitset, 163 app::Dynamic_bitset, 164 app::Dynamic_bitset, 164 spectralpowm	randn	
randomDevices	qpp, 94, 95	
RandomDevices qpp, 104, 105 qpp:RandomDevices, 319 schmidtprobs randprime qpp, 105, 106 qpp, 96 separator	random.h, 387	
app::HandomDevices, 319 schmidtprobs randperm qpp, 105, 106 separator_ qpp; 105, 106 randprime qpp; 96 randprob qpp; internal::IOManipPointer, 203 qpp, 97 qpp; internal::IOManipRange, 206 randrho set qpp, 97 qpp; internal::IOManipRange, 206 randV set_ begin_ qpp; QCircuit::iterator, 216 set_ dit qpp; QCircuit::iterator, 216 set_ end_ qpp; QCircuit::iterator, 216 set_ measured_ qpp; QCircuit::iterator, 216	RandomDevices	
randperm	qpp::RandomDevices, 319	
qpp, 96 separator_ randprime qpp, 96 randprob qpp; 37 randrho qpp; 37 randHo qpp; 97 randU qpp, 97 randV qpp; 38 rd_ qpp; RandomDevices, 321 reference qpp; QEngine, 302 qpp; QEngine, 302 set_measured_ qpp; QEngine, 302 sigma	randperm	•
randprime	qpp, 96	
qpp, 96 qpp::internal::IOManipRange, 206 randprob set qpp, 97 qpp::Dynamic_bitset, 163, 164 randU set_begin_ qpp, 97 qpp::QCircuit::iterator, 216 randV set_dit qpp::QEngine, 302 set_end_ rd_ qpp::QEngine, 302 reference set_measured_ qpp::QCircuit::iterator, 214 sigma renyi qpp, 106 singleton qpp::Dengine, 302 reset singleton qpp::Dynamic_bitset, 163 qpp::Dynamic_bitset, 164 qpp::Dynamic_bitset, 163 qpp, 107 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ qpp::Gates, 179 qpp::Timer, 342 qpp::Internal::IOManipRange, 206 States qpp::Gates, 179 States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates	randprime	. –
randprob	qpp, 96	
qpp, 97 qpp:Dynamic_bitset, 163, 164 qpp, 97 set_begin	randprob	
qpp, 97 set_begin_ qpp::QCircuit::iterator, 216 randU set_dit qpp::QEngine, 302 qpp, 98 set_end_ qpp::QCircuit::iterator, 216 rd_ qpp::RandomDevices, 321 set_end_ qpp::QCircuit::iterator, 216 reference qpp::QCircuit::iterator, 214 sigma qpp::QEngine, 302 reset qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 302 size qpp, 107 size qpp, 99 spectralpowm rho2bloch qpp, 100 qpp, 107 qpp, 100 sqpr. Rn qpp::Gates, 179 states RY qpp::Gates, 180 states RZ qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 stepType	qpp, 97	
dpp, 97 qpp::QCircuit::iterator, 216 randV set_dit qpp, 98 set_end_ rd_ qpp::QCircuit::iterator, 216 set_measured_ qpp::QEngine, 302 reference set_measured_ qpp::QEngine, 302 sigma qpp, 106 singleton qpp::Bit_circuit, 132 sinm qpp::Dynamic_bitset, 163 qpp;:Ior qpp::Dynamic_bitset, 163 qpp;:Dynamic_bitset, 164 qpp, 99 spectralpowm rbo2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 states RY qpp::Gates, 180 RZ qpp::States, 329 qpp::Gates, 180 statistics.h, 388 step_types_ qpp::QCircuit, 295 StepType qpp:QCircuit, 295	randrho	
qpp, 97 set_dit qpp, 98 qpp::QEngine, 302 rd_ qpp::RandomDevices, 321 set_end_ qpp::QCircuit::iterator, 216 set_end_ qpp::QEngine, 302 sigma qpp::QEngine, 302 sigma qpp, 106 singleton qpp::Bit_circuit, 132 qpp::internal::Singleton, 322, 323 qpp::Dynamic_bitset, 163 qpp, 107 qpp::QEngine, 302 size reshape qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ RN qpp::Timer, 342 qpp::Gates, 179 qpp::Timer, 342 qpp::Gates, 179 statistics.h, 38 RY qpp::Gates, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 RZ qpp::QCircuit, 295 StepType qpp::QCircuit, 295	qpp, 97	
qpp, 97 qpp::QEngine, 302 qpp, 98 set_end_ rd_ qpp::QCircuit::iterator, 216 qpp::RandomDevices, 321 set_measured_ qpp::QEngine, 302 sigma qpp, 106 singleton qpp::Bit_circuit, 132 qpp::internal::Singleton, 322, 323 qpp::Dynamic_bitset, 163 qpp, 107 qpp::Dynamic_bitset, 163 qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ RN qpp::Timer, 342 qpp::Gates, 179 qpp::Internal::IOManipPointer, 203 RX qpp::Gates, 179 RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 RZ qpp::Gates, 180	randU	
ratiot set_end_ rd_ qpp::QCircuit::iterator, 216 reference set_measured_ qpp::QEngine, 302 sigma renyi qpp, 106 reset qpp::Internal::Singleton, 322, 323 qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 302 size reshape qpp, 107 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 qpp::Internal::IOManipPointer, 203 RX qpp::Gates, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 RZ qpp::QCircuit, 295 StepType	qpp, 97	_
rd_ qpp::RandomDevices, 321 qpp::QCircuit::iterator, 216 reference qpp::QCircuit::iterator, 214 set_measured_ qpp::QEngine, 302 renyi qpp, 106 sigma qpp, 106 singleton qpp::internal::Singleton, 322, 323 qpp::Dynamic_bitset, 163 qpp, 107 qpp::QEngine, 302 size reshape qpp, 107 qpp, 100 sqpt. rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 qpp::Internal::IOManipPointer, 203 RX qpp::Internal::IOManipRange, 206 States qpp::States, 329 RY qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 qpp::Gates, 180 StepType	randV	
rd qpp::RandomDevices, 321 set_measured_ qpp::QEngine, 302 reference qpp::QEngine, 302 qpp::QEriquit::iterator, 214 qpp, 106 renyi qpp, 106 sigma qpp, 106 Singleton qpp::internal::Singleton, 322, 323 sipmin qpp::internal::Singleton, 322, 323 sipmin qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqpp, 100 sqpp, 107 respance qpp, 107 sqpp, 100 sqpp, 108 Rn qpp::Timer, 342 qpp::Timer, 342 qpp::Timer, 342 qpp::Internal::IOManipPointer, 203 qpp::internal::IOManipPointer, 203 RX qpp::States, 329 statistics.h, 388 step_types_ qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 StepType StepType	qpp, 98	— — —
reference		
renyi sigma qpp, 98, 99 qpp, 106 reset qpp, 106 qpp, 98, 99 singleton qpp::Bit_circuit, 132 qpp, 107 qpp::Dynamic_bitset, 163 qpp, 107 qpp, 99 spectralpowm qpp, 100 qpp, 107 qpp, 100 sqrtm rbo2pure qpp, 108 qpp, 100 start_ qpp::Gates, 179 qpp::Timer, 342 qpp::Internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 RX qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 StepType StepType		
qpp. 38, 99 qpp, 106 reset qpp::internal::Singleton, 322, 323 qpp::Bit_circuit, 132 sinm qpp::Opnamic_bitset, 163 qpp, 107 qpp::Opnamic_bitset, 163 size qpp, 99 qpp::Dynamic_bitset, 164 reshape qpp, 107 qpp, 100 sqpp, 107 rho2bloch qpp, 107 qpp, 100 sqpp, 108 rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Timer, 342 qpp::Internal::IOManipPointer, 203 qpp::dates, 179 States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 qpp::QCircuit, 295 StepType		
reset Singleton qpp::Bit_circuit, 132 sinm qpp::Dynamic_bitset, 163 qpp, 107 qpp::QEngine, 302 size reshape qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RX qpp::Gates, 180 RZ qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 qpp::QCircuit, 295 StepType		
qpp::Bit_circuit, 132 sinm qpp::Dynamic_bitset, 163 qpp, 107 qpp::QEngine, 302 size reshape qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::dates, 179 qpp::internal::IOManipPointer, 203 RX qpp::Gates, 179 RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 RZ qpp::QCircuit, 295 Qpp::Gates, 180 StepType	-	
qpp::Bit_circuit, 132 sinm qpp::Dynamic_bitset, 163 qpp, 107 qpp::QEngine, 302 size reshape qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RX qpp::Gates, 179 RY States qpp::Gates, 180 statistics.h, 388 RZ qpp::Gates, 180 RZ qpp::Gates, 180 RZ qpp::QCircuit, 295 StepType		
qpp::Bit_circuit, 132 qpp, 107 qpp::QEngine, 302 size reshape qpp::Dynamic_bitset, 164 qpp, 99 spectralpowm rho2bloch qpp, 107 qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 RX states qpp::Gates, 179 States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 Qpp::QCircuit, 295 StepType		
qpp::Dyflamic_bitset, 168 qpp::QEngine, 302 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 342 qpp::Internal::IOManipPointer, 203 qpp::Internal::IOManipPointer, 203 qpp::States, 329 statistics.h, 388 step_types_ qpp::Gates, 180 StepType		-
qpp::Gengine, 302 qpp::Dynamic_bitset, 164 reshape spectralpowm qpp, 100 qpp, 107 rho2pure qpp, 108 qpp, 100 start Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RX qpp::dates, 10ManipRange, 206 RY states qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 qpp::Gates, 180 StepType		
restrape spectralpowm qpp, 99 qpp, 107 qpp, 100 sqrtm qpp, 100 qpp, 108 Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RX qpp::Gates, 10ManipRange, 206 RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 StepType StepType		
rho2bloch	•	
qpp, 100 sqrtm rho2pure qpp, 108 qpp, 100 start_ Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 StepType		·
rho2pure		
Rn qpp::Timer, 342 qpp::Gates, 179 qpp::internal::IOManipPointer, 203 RX qpp::internal::IOManipRange, 206 RY States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ qpp::QCircuit, 295 Qpp::Gates, 180 StepType		•
App::Too		
qpp::Gates, 179 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipPange, 206 qpp::Gates, 179 States qpp::States, 329 RY qpp::Gates, 180 RZ statistics.h, 388 step_types_ qpp::QCircuit, 295 Qpp::Gates, 180 StepType	_	_
RX qpp::internal::IOManipRange, 206 qpp::Gates, 179 States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ step_types_ qpp::Gates, 180 qpp::QCircuit, 295 StepType StepType		
qpp::Gates, 179 States RY qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ step_types_ qpp::Gates, 180 qpp::QCircuit, 295 StepType StepType		
Qpp::Gates, 170 qpp::States, 329 qpp::Gates, 180 statistics.h, 388 RZ step_types_ qpp::Gates, 180 qpp::QCircuit, 295 StepType StepType		
qpp::Gates, 180 statistics.h, 388 RZ step_types_ qpp::Gates, 180 qpp::QCircuit, 295 StepType		
RZ step_types_ qpp::Gates, 180 qpp::QCircuit, 295 StepType		
qpp::Gates, 180 qpp::QCircuit, 295 StepType		
StepType		
	qpp::Gates, 180	
qpp::Qoircuit, 2/3	C	
	S	qppQoircuit, 2/3

storage_size	qpp::Codes, 135
qpp::Dynamic_bitset, 164	type
storage_size_	qpp::make_void, 218
qpp::Dynamic_bitset, 165	type_
storage_type	qpp::QCircuit::iterator::value_type_, 352
qpp::Dynamic_bitset, 157	type_description
subsys_	qpp::exception::CustomException, 139
qpp::QEngine, 304	qpp::exception::DimsInvalid, 141
sum	qpp::exception::DimsMismatchCvector, 143
qpp, 108, 109	qpp::exception::DimsMismatchMatrix, 145
super2choi	qpp::exception::DimsMismatchRvector, 147
qpp, 109	qpp::exception::DimsMismatchVector, 149
svals	qpp::exception::DimsNotEqual, 151
qpp, 110	qpp::exception::Duplicates, 154
svd	qpp::exception::Exception, 169
qpp, 110	qpp::exception::InvalidIterator, 197
svdU	qpp::exception::MatrixMismatchSubsys, 220
qpp, 110	qpp::exception::MatrixNotCvector, 222
svdV	qpp::exception::MatrixNotRvector, 224
qpp, 111	qpp::exception::MatrixNotSquare, 226
syspermute	qpp::exception::MatrixNotSquareNorCvector, 228
qpp, 111, 112	qpp::exception::MatrixNotSquareNorRvector, 230
Т	qpp::exception::MatrixNotSquareNorVector, 232
qpp::Gates, 184	qpp::exception::MatrixNotVector, 234
TFQ	app::exception::NoCodeword, 239
qpp, 112	qpp::exception::NotBipartite, 249
qpp::QCircuit, 290	qpp::exception::NotImplemented, 251 qpp::exception::NotQubitCvector, 253
TOF	qpp::exception::NotQubitMatrix, 255
qpp::Bit_circuit, 133	qpp::exception::NotQubitRvector, 257
qpp::Bit_circuit::Gate_count, 171	qpp::exception::NotQubitNector, 257
qpp::Gates, 184	qpp::exception::NotQubitVector, 261
target_	qpp::exception::OutOfRange, 263
qpp::QCircuit::GateStep, 187	qpp::exception::PermInvalid, 265
qpp::QCircuit::MeasureStep, 236	qpp::exception::PermMismatchDims, 267
tic	qpp::exception::QuditAlreadyMeasured, 315
qpp::Timer, 341	qpp::exception::SizeMismatch, 325
tics	qpp::exception::SubsysMismatchDims, 337
qpp::Timer, 342	qpp::exception::TypeMismatch, 345
Timer	qpp::exception::UndefinedType, 347
qpp::Timer, 339, 340	qpp::exception::Unknown, 349
to_JSON	qpp::exception::ZeroSize, 354
qpp::IJSON, 193	types.h, 391
qpp::QCircuit, 291	
qpp::QEngine, 303	uniform
to_string	qpp, 114
qpp::Dynamic_bitset, 164	V
to_void	v_ qpp::Dynamic_bitset, 165
qpp, 28 toc	value_type
qpp::Timer, 342	qpp::Dynamic_bitset, 157
trace	qpp::QCircuit::iterator, 214
qpp, 112	value_type_
traits.h, 389	qpp::QCircuit::iterator::value_type_, 350
transpose	value_type_qc_
qpp, 113	qpp::QCircuit::iterator::value_type_, 352
tsallis	var
qpp, 113, 114	qpp, 115
Type	variadic_vector_emplace

```
qpp::internal, 124
W
     qpp::States, 334
what
     qpp::exception::Exception, 169
what_
    qpp::exception::CustomException, 139
where
    qpp::exception::Exception, 170
Χ
     qpp::Bit_circuit, 133
     qpp::Bit_circuit::Gate_count, 171
     qpp::Gates, 184
x0
     qpp::States, 334
х1
     qpp::States, 335
x2contfrac
     qpp, 115
Xd
     qpp::Gates, 182
Υ
     qpp::Gates, 185
y0
     qpp::States, 335
у1
    qpp::States, 335
Ζ
     qpp::Gates, 185
z0
     qpp::States, 335
z1
     qpp::States, 335
Zd
     qpp::Gates, 182
zero
    qpp::States, 331
```