Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++																	1
2	Nam	nespace	space Index 3																
	2.1	Names	space List									 	 		 	 	 		 3
3	Hier	archica	l Index																5
	3.1	Class	Hierarchy									 	 		 	 	 		 5
4	Clas	s Index																	7
	4.1	Class	List									 	 		 	 	 		 7
5	File	Index																	11
	5.1	File Lis	st									 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion														13
	6.1	qpp Na	amespace	Re	ferer	nce .						 	 		 		 		 13
		6.1.1	Detailed	De	scrip	tion						 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .					 	 		 	 	 		 26
			6.1.2.1	bi	igint							 	 		 	 	 		 26
			6.1.2.2	bı	ra .							 	 		 	 	 		 26
			6.1.2.3	CI	mat							 	 		 	 	 		 27
			6.1.2.4	c	plx .							 	 		 	 	 		 27
			6.1.2.5	dı	mat							 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .					 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .						 	 		 	 	 		 27
			6.1.2.8	d١	vn ro	ow v	ect					 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	57
6.1.3.62	hevects()	57
6.1.3.63	inverse()	58
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	59
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	60
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	61
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	62
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	67
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	69
6.1.3.86	measure() [1/9]	69

6.1.3.87 measure() [2/9]	70
6.1.3.88 measure() [3/9]	70
6.1.3.89 measure() [4/9]	70
6.1.3.90 measure() [5/9]	'1
6.1.3.91 measure() [6/9]	2
6.1.3.92 measure() [7/9]	72
6.1.3.93 measure() [8/9]	73
6.1.3.94 measure() [9/9]	74
6.1.3.95 measure_seq() [1/2]	⁷ 4
6.1.3.96 measure_seq() [2/2]	75
6.1.3.97 mket() [1/2]	75
6.1.3.98 mket() [2/2]	76
6.1.3.99 modinv()	76
6.1.3.100 modmul()	7
6.1.3.101 modpow()	7
6.1.3.102 mprj() [1/2]	78
6.1.3.103 mprj() [2/2]	79
6.1.3.104 multiidx2n()	79
6.1.3.105 n2multiidx()	30
6.1.3.106 negativity() [1/2]	30
6.1.3.107 negativity() [2/2]	30
6.1.3.108 norm()	31
6.1.3.109 normalize()	31
6.1.3.110 omega()	32
6.1.3.111 operator""""_i()	32
6.1.3.112 powm()	32
6.1.3.113 prj()	33
6.1.3.114 prod() [1/3]	33
6.1.3.115 prod() [2/3]	34
6.1.3.116 prod() [3/3]	34

vi

6.1.3.117 ptrace() [1/2]
6.1.3.118 ptrace() [2/2]
6.1.3.119 ptrace1() [1/2]
6.1.3.120 ptrace1() [2/2]
6.1.3.121 ptrace2() [1/2]
6.1.3.122 ptrace2() [2/2]
6.1.3.123 ptranspose() [1/2]
6.1.3.124 ptranspose() [2/2]
6.1.3.125 QFT()
6.1.3.126 qmutualinfo() [1/2]
6.1.3.127 qmutualinfo() [2/2]
6.1.3.128 rand() [1/5] 90
6.1.3.129 rand() [2/5] 90
6.1.3.130 rand() [3/5] 91
6.1.3.131 rand() [4/5] 91
6.1.3.132 rand() [5/5]
6.1.3.133 randH()
6.1.3.134 randidx()
6.1.3.135 randket()
6.1.3.136 randkraus()
6.1.3.137 randn() [1/4] 94
6.1.3.138 randn() [2/4] 94
6.1.3.139 randn() [3/4]
6.1.3.140 randn() [4/4]
6.1.3.141 randperm()
6.1.3.142 randprime()
6.1.3.143 randprob()
6.1.3.144 randrho()
6.1.3.145 randU()
6.1.3.146 randV()

CONTENTS vii

6.1.3.147 renyi() [1/2]
6.1.3.148 renyi() [2/2]
6.1.3.149 reshape()
6.1.3.150 rho2bloch()
6.1.3.151 rho2pure()
6.1.3.152 save()
6.1.3.153 saveMATLAB() [1/2]
6.1.3.154 saveMATLAB() [2/2]
6.1.3.155 schatten()
6.1.3.156 schmidtA() [1/2]
6.1.3.157 schmidtA() [2/2]
6.1.3.158 schmidtB() [1/2]
6.1.3.159 schmidtB() [2/2]
6.1.3.160 schmidtcoeffs() [1/2]
6.1.3.161 schmidtcoeffs() [2/2]
6.1.3.162 schmidtprobs() [1/2]
6.1.3.163 schmidtprobs() [2/2]
6.1.3.164 sigma()
6.1.3.165 sinm()
6.1.3.166 spectralpowm()
6.1.3.167 sqrtm()
6.1.3.168 sum() [1/3]
6.1.3.169 sum() [2/3]
6.1.3.170 sum() [3/3]
6.1.3.171 super2choi()
6.1.3.172 svals()
6.1.3.173 svd()
6.1.3.174 svdU()
6.1.3.175 svdV()
6.1.3.176 syspermute() [1/2]

viii CONTENTS

		6.1.3.177	7 syspermute() [2/2]	112
		6.1.3.178	B TFQ()	112
		6.1.3.179	9 trace()	113
		6.1.3.180	0 transpose()	113
		6.1.3.181	1 tsallis() [1/2]	113
		6.1.3.182	2 tsallis() [2/2]	114
		6.1.3.183	3 uniform()	114
		6.1.3.184	4 var()	115
		6.1.3.185	5 x2contfrac()	115
	6.1.4	Variable	Documentation	116
		6.1.4.1	chop	116
		6.1.4.2	ee	116
		6.1.4.3	eps	116
		6.1.4.4	idx_infty	116
		6.1.4.5	infty	116
		6.1.4.6	maxn	117
		6.1.4.7	pi	117
6.2	qpp::ex	ception N	lamespace Reference	117
	6.2.1	Detailed	Description	118
6.3	qpp::ex	perimenta	al Namespace Reference	119
	6.3.1	Detailed	Description	119
6.4	qpp::in	ternal Nan	mespace Reference	119
	6.4.1	Detailed	Description	120
	6.4.2	Function	Documentation	120
		6.4.2.1	check_cvector()	120
		6.4.2.2	check_dims()	120
		6.4.2.3	check_dims_match_cvect()	121
		6.4.2.4	check_dims_match_mat()	121
		6.4.2.5	check_dims_match_rvect()	121
		6.4.2.6	check_eq_dims()	121

		6.4.2.7	check_matching_sizes()	21
		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	22
		6.4.2.10	check_perm()	22
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	23
		6.4.2.16	check_square_mat()	23
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	24
		6.4.2.22	kron2()	24
		6.4.2.23	multiidx2n()	24
		6.4.2.24	n2multiidx()	24
		6.4.2.25	variadic_vector_emplace() [1/2]	24
		6.4.2.26	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator"""" _bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator"""" _prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

7.1	.5 Member Data Documentation
	7.15.5.1 CNOT
	7.15.5.2 CNOTba
	7.15.5.3 CZ
	7.15.5.4 FRED
	7.15.5.5 H
	7.15.5.6 ld2
	7.15.5.7 S
	7.15.5.8 SWAP
	7.15.5.9 T
	7.15.5.10 TOF
	7.15.5.11 X
	7.15.5.12 Y
	7.15.5.13 Z
7.16 qpp	:QCircuitDescription::GateStep Struct Reference
7.10	.1 Detailed Description
7.10	.2 Constructor & Destructor Documentation
	7.16.2.1 GateStep() [1/2]
	7.16.2.2 GateStep() [2/2]
7.10	3 Member Data Documentation
	7.16.3.1 ctrl
	7.16.3.2 gate
	7.16.3.3 gate_type
	7.16.3.4 name
	7.16.3.5 target
7.17 qpp	:IDisplay Class Reference
7.1	.1 Detailed Description
7.1	.2 Constructor & Destructor Documentation
	7.17.2.1 IDisplay() [1/3]
	7.17.2.2 IDisplay() [2/3]

xvi CONTENTS

		7.17.2.3 IDisplay() [3/3]	90
		7.17.2.4 ~IDisplay()	90
	7.17.3	Member Function Documentation	90
		7.17.3.1 display()	90
		7.17.3.2 operator=() [1/2]	90
		7.17.3.3 operator=() [2/2]	90
	7.17.4	Friends And Related Function Documentation	91
		7.17.4.1 operator<< 1	91
7.18	qpp::In	it Class Reference	91
	7.18.1	Detailed Description	92
	7.18.2	Constructor & Destructor Documentation	92
		7.18.2.1 Init()	92
		7.18.2.2 ~Init()	92
	7.18.3	Friends And Related Function Documentation	92
		7.18.3.1 internal::Singleton < const Init >	92
7.19	qpp::ex	cception::InvalidIterator Class Reference	93
	7.19.1	Detailed Description	94
	7.19.2	Member Function Documentation	94
		7.19.2.1 Exception()	94
		7.19.2.2 type_description()	94
7.20	qpp::in	ternal::IOManipEigen Class Reference	95
	7.20.1	Constructor & Destructor Documentation	96
		7.20.1.1 IOManipEigen() [1/2]	96
		7.20.1.2 IOManipEigen() [2/2]	96
	7.20.2	Member Function Documentation	96
		7.20.2.1 display()	96
	7.20.3	Member Data Documentation	96
		7.20.3.1 A	97
		7.20.3.2 chop	97
7.21	qpp::in	ternal::IOManipPointer< PointerType > Class Template Reference	97

CONTENTS xvii

	7.21.1	Constructor & Destructor Documentation	98
		7.21.1.1 IOManipPointer() [1/2]	99
		7.21.1.2 IOManipPointer() [2/2]	99
	7.21.2	Member Function Documentation	99
		7.21.2.1 display()	99
		7.21.2.2 operator=()	99
	7.21.3	Member Data Documentation	99
		7.21.3.1 end)0
		7.21.3.2 N)0
		7.21.3.3 p)0
		7.21.3.4 separator)0
		7.21.3.5 start)0
7.22	qpp::int	ternal::IOManipRange< InputIterator > Class Template Reference)1
	7.22.1	Constructor & Destructor Documentation)2
		7.22.1.1 IOManipRange() [1/2])2
		7.22.1.2 IOManipRange() [2/2])2
	7.22.2	Member Function Documentation)2
		7.22.2.1 display())2
		7.22.2.2 operator=())3
	7.22.3	Member Data Documentation)3
		7.22.3.1 end)3
		7.22.3.2 first)3
		7.22.3.3 last)3
		7.22.3.4 separator)3
		7.22.3.5 start)3
7.23	qpp::IQ	Circuit Class Reference)4
	7.23.1	Detailed Description)6
	7.23.2	Constructor & Destructor Documentation)6
		7.23.2.1 IQCircuit() [1/2])6
		7.23.2.2 IQCircuit() [2/2])6

xviii CONTENTS

	7.23.2.3 ~IQCircuit()	207
7.23.3	Member Function Documentation	207
	7.23.3.1 display()	207
	7.23.3.2 get_circuit_description()	207
	7.23.3.3 get_dit()	207
	7.23.3.4 get_dits()	208
	7.23.3.5 get_ip()	208
	7.23.3.6 get_iter()	208
	7.23.3.7 get_m_ip()	209
	7.23.3.8 get_measured() [1/2]	209
	7.23.3.9 get_measured() [2/2]	209
	7.23.3.10 get_not_measured()	209
	7.23.3.11 get_probs()	210
	7.23.3.12 get_psi()	210
	7.23.3.13 get_q_ip()	210
	7.23.3.14 get_ref_psi()	210
	7.23.3.15 get_relative_pos_()	210
	7.23.3.16 reset()	211
	7.23.3.17 run()	211
	7.23.3.18 set_dit()	211
	7.23.3.19 set_measured_()	212
7.23.4	Member Data Documentation	212
	7.23.4.1 dits	212
	7.23.4.2 it	212
	7.23.4.3 probs	212
	7.23.4.4 psi	212
	7.23.4.5 qcd	213
	7.23.4.6 subsys	213
7.24 qpp::is	_complex< T > Struct Template Reference	213
7.24.1	Detailed Description	214

CONTENTS xix

7.25	qpp::is_	_complex< std::complex< T >> Struct Template Reference	214
	7.25.1	Detailed Description	215
7.26	qpp::is_	_iterable < T, typename > Struct Template Reference	215
	7.26.1	Detailed Description	216
7.27		_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T d()), decltype(*(std::declval < T >().begin())) > Struct Template Reference	216
	7.27.1	Detailed Description	217
7.28	qpp::is_	_matrix_expression< Derived > Struct Template Reference	217
	7.28.1	Detailed Description	218
7.29	qpp::Q	CircuitDescription::iterator Class Reference	218
	7.29.1	Detailed Description	219
	7.29.2	Member Typedef Documentation	220
		7.29.2.1 difference_type	220
		7.29.2.2 iterator_category	220
		7.29.2.3 pointer	220
		7.29.2.4 reference	220
		7.29.2.5 value_type	220
	7.29.3	Constructor & Destructor Documentation	220
		7.29.3.1 iterator() [1/2]	221
		7.29.3.2 iterator() [2/2]	221
	7.29.4	Member Function Documentation	221
		7.29.4.1 operator"!=()	221
		7.29.4.2 operator*()	221
		7.29.4.3 operator++() [1/2]	222
		7.29.4.4 operator++() [2/2]	222
		7.29.4.5 operator=()	222
		7.29.4.6 operator==()	222
		7.29.4.7 set_begin_()	223
		7.29.4.8 set_end_()	223
	7.29.5	Member Data Documentation	223
		7.29.5.1 elem	223

		7.29.5.2 qcd	223
7.30	qpp::ma	ake_void< Ts > Struct Template Reference	224
	7.30.1	Detailed Description	224
	7.30.2	Member Typedef Documentation	224
		7.30.2.1 type	224
7.31	qpp::ex	cception::MatrixMismatchSubsys Class Reference	225
	7.31.1	Detailed Description	226
	7.31.2	Member Function Documentation	226
		7.31.2.1 Exception()	226
		7.31.2.2 type_description()	226
7.32	qpp::ex	cception::MatrixNotCvector Class Reference	227
	7.32.1	Detailed Description	228
	7.32.2	Member Function Documentation	228
		7.32.2.1 Exception()	228
		7.32.2.2 type_description()	228
7.33	qpp::ex	cception::MatrixNotRvector Class Reference	229
	7.33.1	Detailed Description	230
	7.33.2	Member Function Documentation	230
		7.33.2.1 Exception()	230
		7.33.2.2 type_description()	230
7.34	qpp::ex	cception::MatrixNotSquare Class Reference	231
	7.34.1	Detailed Description	232
	7.34.2	Member Function Documentation	232
		7.34.2.1 Exception()	232
		7.34.2.2 type_description()	232
7.35	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	233
	7.35.1	Detailed Description	234
	7.35.2	Member Function Documentation	234
		7.35.2.1 Exception()	234
		7.35.2.2 type_description()	234

CONTENTS xxi

7.36	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	235
	7.36.1	Detailed Description	236
	7.36.2	Member Function Documentation	236
		7.36.2.1 Exception()	236
		7.36.2.2 type_description()	236
7.37	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	237
	7.37.1	Detailed Description	238
	7.37.2	Member Function Documentation	238
		7.37.2.1 Exception()	238
		7.37.2.2 type_description()	238
7.38	qpp::ex	cception::MatrixNotVector Class Reference	239
	7.38.1	Detailed Description	240
	7.38.2	Member Function Documentation	240
		7.38.2.1 Exception()	240
		7.38.2.2 type_description()	240
7.39	qpp::Q	CircuitDescription::MeasureStep Struct Reference	241
	7.39.1	Detailed Description	241
	7.39.2	Constructor & Destructor Documentation	242
		7.39.2.1 MeasureStep() [1/2]	242
		7.39.2.2 MeasureStep() [2/2]	242
	7.39.3	Member Data Documentation	242
		7.39.3.1 c_reg	242
		7.39.3.2 mats	242
		7.39.3.3 measurement_type	243
		7.39.3.4 name	243
		7.39.3.5 target	243
7.40	qpp::ex	cception::NoCodeword Class Reference	243
	7.40.1	Detailed Description	244
	7.40.2	Member Function Documentation	244
		7.40.2.1 Exception()	244

xxii CONTENTS

		7.40.2.2 type_description()	45
7.41	qpp::No	oiseBase < T > Class Template Reference	45
	7.41.1	Detailed Description	47
	7.41.2	Member Typedef Documentation	47
		7.41.2.1 noise_type	47
	7.41.3	Constructor & Destructor Documentation	47
		7.41.3.1 NoiseBase() [1/2]	47
		7.41.3.2 NoiseBase() [2/2]	47
		7.41.3.3 ~NoiseBase()	48
	7.41.4	Member Function Documentation	48
		7.41.4.1 compute_probs_()	48
		7.41.4.2 compute_state_()	49
		7.41.4.3 get_d()	49
		7.41.4.4 get_Ks()	49
		7.41.4.5 get_last_idx()	50
		7.41.4.6 get_last_K()	50
		7.41.4.7 get_last_p()	50
		7.41.4.8 get_probs()	50
		7.41.4.9 operator()() [1/2]	50
		7.41.4.10 operator()() [2/2]	51
	7.41.5	Member Data Documentation	51
		7.41.5.1 d	51
		7.41.5.2 generated	51
		7.41.5.3 i	52
		7.41.5.4 Ks	52
		7.41.5.5 probs	52
7.42	qpp::No	oiseType Class Reference	52
	7.42.1	Detailed Description	52
7.43	qpp::ex	cception::NotBipartite Class Reference	53
	7.43.1	Detailed Description	54

CONTENTS xxiii

	7.43.2	Member Function Documentation	54
		7.43.2.1 Exception()	54
		7.43.2.2 type_description()	54
7.44	qpp::ex	ception::NotImplemented Class Reference	55
	7.44.1	Detailed Description	56
	7.44.2	Member Function Documentation	56
		7.44.2.1 Exception()	56
		7.44.2.2 type_description()	56
7.45	qpp::ex	ception::NotQubitCvector Class Reference	57
	7.45.1	Detailed Description	58
	7.45.2	Member Function Documentation	58
		7.45.2.1 Exception()	58
		7.45.2.2 type_description()	58
7.46	qpp::ex	ception::NotQubitMatrix Class Reference	59
	7.46.1	Detailed Description	60
	7.46.2	Member Function Documentation	60
		7.46.2.1 Exception()	60
		7.46.2.2 type_description()	60
7.47	qpp::ex	ception::NotQubitRvector Class Reference	61
	7.47.1	Detailed Description	62
	7.47.2	Member Function Documentation	62
		7.47.2.1 Exception()	62
		7.47.2.2 type_description()	62
7.48	qpp::ex	ception::NotQubitSubsys Class Reference	63
	7.48.1	Detailed Description	64
	7.48.2	Member Function Documentation	64
		7.48.2.1 Exception()	64
		7.48.2.2 type_description()	64
7.49	qpp::ex	ception::NotQubitVector Class Reference	65
	7.49.1	Detailed Description	66

xxiv CONTENTS

	7.49.2	Member Function Do	cumentation		 	 	 	266
		7.49.2.1 Exception(266
		7.49.2.2 type_descr	iption()		 	 	 	266
7.50	qpp::ex	ception::OutOfRange	Class Reference		 	 	 	267
	7.50.1	Detailed Description			 	 	 	268
	7.50.2	Member Function Do	cumentation		 	 	 	268
		7.50.2.1 Exception(268
		7.50.2.2 type_descr	iption()		 	 	 	268
7.51	qpp::ex	ception::PermInvalid (class Reference .		 	 	 	269
	7.51.1	Detailed Description			 	 	 	270
	7.51.2	Member Function Do	cumentation		 	 	 	270
		7.51.2.1 Exception(270
		7.51.2.2 type_descr	iption()		 	 	 	270
7.52	qpp::ex	ception::PermMismato	hDims Class Refe	erence .	 	 	 	271
	7.52.1	Detailed Description			 	 	 	272
	7.52.2	Member Function Do	cumentation		 	 	 	272
		7.52.2.1 Exception(272
		7.52.2.2 type_descr	iption()		 	 	 	272
7.53	qpp::Q	Circuit Class Referenc	9		 	 	 	273
	7.53.1	Detailed Description			 	 	 	274
	7.53.2	Member Function Do	cumentation		 	 	 	274
		7.53.2.1 IQCircuit()	[1/2]		 	 	 	274
		7.53.2.2 IQCircuit()	[2/2]		 	 	 	274
		7.53.2.3 run()			 	 	 	275
7.54	qpp::Q	CircuitDescription Clas	s Reference		 	 	 	275
	7.54.1	Detailed Description			 	 	 	279
	7.54.2	Member Typedef Doo	umentation		 	 	 	279
		7.54.2.1 const_itera	tor		 	 	 	279
	7.54.3	Member Enumeration	Documentation		 	 	 	279
		7.54.3.1 GateType .			 	 	 	279

CONTENTS xxv

	7.54.3.2	Meas	sureTy	/pe .														280
	7.54.3.3	Step	Type .														 	280
7.54.4	Construc	tor & E)estru	ıctor E	Doci	ume	enta	tior	١.								 	280
	7.54.4.1	QCirc	cuitDe	escript	tion	() .											 	280
	7.54.4.2	\sim QC	ircuit[Descr	iptic	on()											 	281
7.54.5	Member	Function	on Do	cume	nta	tion											 	281
	7.54.5.1	begir	n() [1/	/2]													 	281
	7.54.5.2	begir	1() [2/	/2]													 	281
	7.54.5.3	cbeg	in()														 	282
	7.54.5.4	cCTF	RL() [:	1/4]													 	282
	7.54.5.5	cCTF	RL() [:	2/4]													 	282
	7.54.5.6	cCTF	?L() [:	3/4]													 	283
	7.54.5.7	cCTF	RL() [4/4]													 	283
	7.54.5.8	cCTF	RL_cu	stom(() .												 	284
	7.54.5.9	cend	()														 	284
	7.54.5.10	CTRI	L () [1	/4]													 	284
	7.54.5.11	CTRI	L () [2	/4]													 	285
	7.54.5.12	2 CTRI	L () [3	/4]													 	285
	7.54.5.13	3 CTRI	L() [4	/4]													 	286
	7.54.5.14	4 CTRI	L_cus	tom()													 	286
	7.54.5.15	5 displa	ay() .														 	287
	7.54.5.16	6 end()	[1/2	:].													 	287
	7.54.5.17	7 end()	[2/2	:] .													 	288
	7.54.5.18	3 gate() [1/3	3] .													 	288
	7.54.5.19	gate() [2/3	3] .													 	288
	7.54.5.20	gate() [3/3	3] .													 	289
	7.54.5.21	gate_	_custo	om()													 	289
	7.54.5.22	2 gate_	_fan()	[1/2]] .							 -					 	290
	7.54.5.23	3 gate_	_fan()	[2/2]] .							 -					 	290
	7.54.5.24	4 get_c	()k															290

xxvi CONTENTS

	7.54.5.25	get_gate_	_count()					 ٠.	٠.	 	٠.	٠.	-	 	٠.	291
	7.54.5.26	get_gates	s()					 		 				 		291
	7.54.5.27	get_meas	sured() [1/2].				 		 				 		291
	7.54.5.28	get_meas	sured() [2/2] .				 		 				 		291
	7.54.5.29	get_meas	urement	_count	:() -			 		 				 		292
	7.54.5.30	get_meas	urement	s()				 		 				 		292
	7.54.5.31	get_name) ()					 		 				 		292
	7.54.5.32	get_nc()						 		 				 		292
	7.54.5.33	get_non_	measure	ed()				 		 				 		293
	7.54.5.34	get_nq()						 		 				 		293
	7.54.5.35	get_step_	_count()					 		 				 		293
	7.54.5.36	measure\	/() [1/2]					 		 				 		293
	7.54.5.37	measure\	/() [2/2]					 		 				 		294
	7.54.5.38	measurez	<u>"()</u>					 		 				 		294
	7.54.5.39	QFT()						 		 				 		295
	7.54.5.40	TFQ()						 		 				 		295
	7.54.5.41	to_JSON(0					 		 				 		295
7.54.6	Friends An	nd Related	d Functio	n Docu	ımen	itatio	ı	 		 				 		296
	7.54.6.1	operator<	< [1/4	1				 		 				 		296
	7.54.6.2	operator<	<< [2/4	1				 		 				 		296
	7.54.6.3	operator<	<< [3/4	1				 		 				 		297
	7.54.6.4	operator<	< [4/4	1				 		 				 		297
7.54.7	Member D	ata Docu	mentatio	n				 		 				 		297
	7.54.7.1	d						 		 				 		297
	7.54.7.2	gates						 		 				 		298
	7.54.7.3	measured	<u>.</u>					 		 				 		298
	7.54.7.4	measurer	nents_					 		 				 		298
	7.54.7.5	name						 		 				 		298
	7.54.7.6	nc						 		 				 		298
	7.54.7.7	nq						 		 				 		298

CONTENTS xxvii

		7.54.7.8 step_types	299
7.55	qpp::Qı	ubitAmplitudeDampingNoise Class Reference	299
	7.55.1	Detailed Description	300
	7.55.2	Constructor & Destructor Documentation	300
		7.55.2.1 QubitAmplitudeDampingNoise()	300
7.56	qpp::Q	ubitBitFlipNoise Class Reference	300
	7.56.1	Detailed Description	301
	7.56.2	Constructor & Destructor Documentation	302
		7.56.2.1 QubitBitFlipNoise()	302
7.57	qpp::Q	ubitBitPhaseFlipNoise Class Reference	302
	7.57.1	Detailed Description	303
	7.57.2	Constructor & Destructor Documentation	303
		7.57.2.1 QubitBitPhaseFlipNoise()	303
7.58	qpp::Q	ubitDepolarizingNoise Class Reference	304
	7.58.1	Detailed Description	305
	7.58.2	Constructor & Destructor Documentation	305
		7.58.2.1 QubitDepolarizingNoise()	305
7.59	qpp::Q	ubitPhaseDampingNoise Class Reference	305
	7.59.1	Detailed Description	306
	7.59.2	Constructor & Destructor Documentation	306
		7.59.2.1 QubitPhaseDampingNoise()	306
7.60	qpp::Q	ubitPhaseFlipNoise Class Reference	307
	7.60.1	Detailed Description	308
	7.60.2	Constructor & Destructor Documentation	308
		7.60.2.1 QubitPhaseFlipNoise()	308
7.61	qpp::ex	cception::QuditAlreadyMeasured Class Reference	308
	7.61.1	Detailed Description	309
	7.61.2	Member Function Documentation	309
		7.61.2.1 Exception()	309
		7.61.2.2 type_description()	310

xxviii CONTENTS

7.62	qpp::Qı	uditDepolarizingNoise Class Reference	0
	7.62.1	Detailed Description	1
	7.62.2	Constructor & Destructor Documentation	1
		7.62.2.1 QuditDepolarizingNoise()	1
	7.62.3	Member Function Documentation	2
		7.62.3.1 fill_Ks_()	2
		7.62.3.2 fill_probs_()	2
7.63	qpp::Ra	andomDevices Class Reference	3
	7.63.1	Detailed Description	4
	7.63.2	Constructor & Destructor Documentation	4
		7.63.2.1 RandomDevices()	4
		7.63.2.2 ~RandomDevices()	5
	7.63.3	Member Function Documentation	5
		7.63.3.1 get_prng()	5
		7.63.3.2 load()	5
		7.63.3.3 save()	5
	7.63.4	Friends And Related Function Documentation	6
		7.63.4.1 internal::Singleton< RandomDevices >	6
	7.63.5	Member Data Documentation	6
		7.63.5.1 prng	6
		7.63.5.2 rd	6
7.64	qpp::int	ternal::Singleton< T > Class Template Reference	6
	7.64.1	Detailed Description	7
	7.64.2	Constructor & Destructor Documentation	7
		7.64.2.1 Singleton() [1/2]	8
		7.64.2.2 Singleton() [2/2]	8
		7.64.2.3 ~Singleton()	8
	7.64.3	Member Function Documentation	8
		7.64.3.1 get_instance()	8
		7.64.3.2 get_thread_local_instance()	8

CONTENTS xxix

	7.64.3.3 operator=()
7.65 qpp::e	xception::SizeMismatch Class Reference
7.65.1	Detailed Description
7.65.2	Member Function Documentation
	7.65.2.1 Exception()
	7.65.2.2 type_description()
7.66 qpp::N	loiseType::StateDependent Class Reference
7.66.1	Detailed Description
7.67 qpp::N	loiseType::StateIndependent Class Reference
7.67.1	Detailed Description
7.68 qpp::S	States Class Reference
7.68.1	Detailed Description
7.68.2	Constructor & Destructor Documentation
	7.68.2.1 States()
	7.68.2.2 ~States()
7.68.3	Member Function Documentation
	7.68.3.1 jn()
	7.68.3.2 mes()
	7.68.3.3 minus()
	7.68.3.4 one()
	7.68.3.5 plus()
	7.68.3.6 zero()
7.68.4	Friends And Related Function Documentation
	7.68.4.1 internal::Singleton < const States >
7.68.5	Member Data Documentation
	7.68.5.1 b00
	7.68.5.2 b01
	7.68.5.3 b10
	7.68.5.4 b11
	7.68.5.5 GHZ

7.68.5.6 pb00	 327
7.68.5.7 pb01	 328
7.68.5.8 pb10	 328
7.68.5.9 pb11	 328
7.68.5.10 pGHZ	 328
7.68.5.11 pW	 328
7.68.5.12 px0	 328
7.68.5.13 px1	 329
7.68.5.14 py0	 329
7.68.5.15 py1	 329
7.68.5.16 pz0	 329
7.68.5.17 pz1	 329
7.68.5.18 W	 329
7.68.5.19 x0	 330
7.68.5.20 x1	 330
7.68.5.21 y0	 330
7.68.5.22 y1	 330
7.68.5.23 z0	 330
7.68.5.24 z1	 330
7.69 qpp::exception::SubsysMismatchDims Class Reference .	 331
7.69.1 Detailed Description	 332
7.69.2 Member Function Documentation	 332
7.69.2.1 Exception()	 332
7.69.2.2 type_description()	 332
7.70 qpp::Timer< T, CLOCK_T > Class Template Reference .	 333
7.70.1 Detailed Description	 334
7.70.2 Constructor & Destructor Documentation	 334
7.70.2.1 Timer() [1/3]	 334
7.70.2.2 Timer() [2/3]	 335
7.70.2.3 Timer() [3/3]	 335

CONTENTS xxxi

		7.70.2.4 ~Timer()	35
	7.70.3	Member Function Documentation	35
		7.70.3.1 display()	35
		7.70.3.2 get_duration()	36
		7.70.3.3 operator=() [1/2]	36
		7.70.3.4 operator=() [2/2]	36
		7.70.3.5 tic()	37
		7.70.3.6 tics()	37
		7.70.3.7 toc()	37
	7.70.4	Member Data Documentation	37
		7.70.4.1 end	37
		7.70.4.2 start	38
7.71	qpp::ex	cception::TypeMismatch Class Reference	38
	7.71.1	Detailed Description	39
	7.71.2	Member Function Documentation	39
		7.71.2.1 Exception()	39
		7.71.2.2 type_description()	40
7.72	qpp::ex	cception::UndefinedType Class Reference	40
	7.72.1	Detailed Description	41
	7.72.2	Member Function Documentation	41
		7.72.2.1 Exception()	41
		7.72.2.2 type_description()	42
7.73	qpp::ex	cception::Unknown Class Reference	42
	7.73.1	Detailed Description	43
	7.73.2	Member Function Documentation	43
		7.73.2.1 Exception()	43
		7.73.2.2 type_description()	44
7.74	qpp::Q	CircuitDescription::iterator::value_type_ Struct Reference	44
	7.74.1	Constructor & Destructor Documentation	45
		7.74.1.1 value_type_() [1/2]	45

xxxii CONTENTS

			7.74.1.2	value_typ	pe_() [2	2/2] .		 	 	 	 	 	345
		7.74.2	Member F	Function [Docume	ntation		 	 	 	 	 	346
			7.74.2.1	display()				 	 	 	 	 	346
			7.74.2.2	operator	=()			 	 	 	 	 	346
		7.74.3	Member [Data Docu	umentat	ion		 	 	 	 	 	346
			7.74.3.1	gates_ip				 	 	 	 	 	346
			7.74.3.2	ip				 	 	 	 	 	347
			7.74.3.3	measure	ments_	ip		 	 	 	 	 	347
			7.74.3.4	type				 	 	 	 	 	347
			7.74.3.5	value_typ	pe_qcd_			 	 	 	 	 	347
	7.75	qpp::ex	ception::Ze	eroSize C	lass Re	ference	9	 	 	 	 	 	348
		7.75.1	Detailed [Descriptio	n			 	 	 	 	 	349
		7.75.2	Member F	Function [Docume	ntation		 	 	 	 	 	349
			7.75.2.1	Exceptio	n()			 	 	 	 	 	349
			7.75.2.2	type_des	scription	n()		 	 	 	 	 	349
8	File	Docume	entation										351
8			entation	File Refe	rence								351
8	File 8.1	classes	s/circuits.h										351
8	8.1	classes	s/circuits.h Detailed [Descriptio	n			 	 	 	 	 	351 352
8		classes	s/circuits.h Detailed [s/codes.h F	Descriptio	n ence .			 	 	 	 	 	351 352
8	8.1	classes 8.1.1 classes 8.2.1	s/circuits.h Detailed [s/codes.h F Detailed [Descriptio File Refere	n ence . n			 	 	 	 	 	351 352 352
8	8.1	classes 8.1.1 classes 8.2.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception	Descriptio File Refere Descriptio I.h File Re	ence . In eference			 	 	 	 	 	351 352 352 352
8	8.1	classes 8.1.1 classes 8.2.1 classes 8.3.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [Descriptio File Refere Descriptio I.h File Re Descriptio	n ence . n eference			 	 	 	 	 	351 352 352 352 353
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception	Description File Reference Description In File Reference Description Ile Reference	n ence			 		 	 	 	351 352 352 352 353 353
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [s/exception]	Description File Refere Description I.h File Re Description Ile Refere Description	n ence . n eference n ence . n			 			 	 	351 352 352 352 353 355 355
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [s/gates.h F Detailed [Description File Reference Lh File Reference Description ile Reference Description File Reference	n ence								351 352 352 352 353 355 355
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1	betailed [Description File Reference Description I.h File Reference Description File Reference Description File Reference Description	n ence . eference	· · · · · · · · · · · · · · · · · · ·							351 352 352 352 353 355 355 355 356
8	8.1 8.2 8.3 8.4	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [s/gates.h F Detailed [s/gates.h F Detailed [s/idisplay.h Detailed [Description File Reference Description In File Reference Description File Reference Description Reference	n ence								351 352 352 352 353 355 355 356 356 356
8	8.1 8.2 8.3 8.4	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1 classes 8.6.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [s/gates.h F Detailed [s/idisplay.h Detailed [s/idisplay.h Detailed [s/init.h File	Description File Reference Description I.h File Reference Description File Reference Description Reference	n ence . n eference n rence . n rence								351 352 352 353 355 355 356 356 356 357
8	8.1 8.2 8.3 8.4 8.5	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1 classes 8.6.1	s/circuits.h Detailed [s/codes.h F Detailed [s/exception Detailed [s/gates.h F Detailed [s/idisplay.h Detailed [s/init.h File Detailed [Description File Reference Description I.h File Reference Description File Reference Description Reference Description Reference Description Reference Description	n ence n eference n ence n ence n ence n ence n								351 352 352 353 355 355 356 356 356 357 357

CONTENTS xxxiii

8.8	classes/random_devices.h File Reference	358
	8.8.1 Detailed Description	358
8.9	classes/reversible.h File Reference	359
	8.9.1 Detailed Description	359
8.10	classes/states.h File Reference	359
	8.10.1 Detailed Description	360
8.11	classes/timer.h File Reference	360
	8.11.1 Detailed Description	361
8.12	constants.h File Reference	361
	8.12.1 Detailed Description	362
8.13	entanglement.h File Reference	362
	8.13.1 Detailed Description	364
8.14	entropies.h File Reference	364
	8.14.1 Detailed Description	365
8.15	experimental/experimental.h File Reference	365
	8.15.1 Detailed Description	365
8.16	functions.h File Reference	365
	8.16.1 Detailed Description	370
8.17	input_output.h File Reference	370
	8.17.1 Detailed Description	371
8.18	instruments.h File Reference	371
	8.18.1 Detailed Description	372
8.19	internal/classes/iomanip.h File Reference	372
	8.19.1 Detailed Description	373
8.20	internal/classes/singleton.h File Reference	373
	8.20.1 Detailed Description	374
8.21	internal/util.h File Reference	374
	8.21.1 Detailed Description	375
8.22	MATLAB/matlab.h File Reference	376
	8.22.1 Detailed Description	376

8.26	random.h File Reference	382
	8.26.1 Detailed Description	383
	statistics.h File Reference	
	8.27.1 Detailed Description	
	traits.h File Reference	
	8.28.1 Detailed Description	
	8.29.1 Detailed Description	
	·	
8.30	/Users/vlad/qpp/README.md File Reference	387
Index		389

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
qpp::exception::SubsysMismatchDims

6 Hierarchical Index

<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< >().end()), decltype(*(std::declval< T >().begin()))>></pre>	Т
true_type qpp::is complex< std::complex< T >>	
qpp::NoiseType::StateDependent	
qpp::RandomDevices	
qpp::internal::Singleton< RandomDevices >	
qpp::States	
qpp::internal::Singleton < const States >	
qpp::Init	
qpp::internal::Singleton< const Init >	
qpp::Gates	
qpp::internal::Singleton< const Gates >	
qpp::Codes	
qpp::internal::Singleton< const Codes >	
qpp::internal::Singleton < T >	
qpp::NoiseType	
qpp::QuditDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitBitFlipNoise	
<pre>qpp::NoiseBase< NoiseType::StateIndependent ></pre>	
qpp::QubitPhaseDampingNoise	
qpp::NoiseBase< NoiseType::StateBependent >	
qpp::NoiseBase< 1 >	
qpp::QCircuitDescription::MeasureStep	
qpp::make_void< Ts >	
qpp::QCircuitDescription::iterator	
qpp::is_matrix_expression< Derived >	
is_base_of	
qpp::Timer $<$ T, CLOCK_T $>$	333
qpp::QCircuitDescription::iterator::value_type	
qpp::QCircuitDescription	
qpp::QCircuit	273
qpp::IQCircuit	
qpp::internal::IOManipRange< InputIterator >	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipEigen	
app::Bit circuit	
qpp::Dynamic_bitset	
qpp::IDisplay	
qpp::Bit_circuit::Gate_count	
qpp::is_iterable < T, typename >	
qpp::is_complex< T >	
false_type	
qpp::exception::ZeroSize	348
qpp::exception::Unknown	
app::exception::UndefinedType	
qpp::exception::TypeMismatch	338

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
-, (- 9 , ,	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
,	155
qpp::exception::Exception	
	166
	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuitDescription::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
188	
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	191

8 Class Index

qpp::exception::InvalidIterator	
Invalid iterator	193
qpp::internal::IOManipEigen	195
qpp::internal::IOManipPointer< PointerType >	197
qpp::internal::IOManipRange < InputIterator >	201
qpp::IQCircuit	
Quantum circuit simulator abstract class	204
qpp::is_complex< T >	
Checks whether the type is a complex type	213
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	214
qpp::is_iterable< T, typename >	211
Checks whether <i>T</i> is compatible with an STL-like iterable container	215
qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(std::declty	ecitype(*(Stddecival<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	010
iterable containers	216
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	217
qpp::QCircuitDescription::iterator	
Quantum circuit description bound-checking (safe) iterator	218
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	224
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	225
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	227
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	229
qpp::exception::MatrixNotSquare	LLU
Matrix is not square exception	001
·	231
qpp::exception::MatrixNotSquareNorCvector	000
Matrix is not square nor column vector exception	233
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	235
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	237
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	239
qpp::QCircuitDescription::MeasureStep	
One step consisting only of measurements in the circuit	241
qpp::exception::NoCodeword	
Codeword does not exist exception	243
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	245
qpp::NoiseType	240
	050
Contains template tags used to specify the noise type	202
qpp::exception::NotBipartite	050
'	253
qpp::exception::NotImplemented	
Code not yet implemented	255
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	257
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	259
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	261
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	263
-A	· -

4.1 Class List

annuavaantianuNatOubitVaatar	
qpp::exception::NotQubitVector Vector is not 2 x 1 nor 1 x 2 exception	265
qpp::exception::OutOfRange	200
Argument out of range exception	267
qpp::exception::PermInvalid	
Invalid permutation exception	269
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	271
qpp::QCircuit	
Quantum circuit simulator class	273
qpp::QCircuitDescription	
Quantum circuit description class	275
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	299
qpp::QubitBitFlipNoise	
Qubit bit flip noise	300
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	302
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	304
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	305
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	307
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	308
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	310
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	313
app::internal::Singleton < T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	210
recurring template pattern)	316
Size mismatch exception	319
qpp::NoiseType::StateDependent	318
Template tag, used whenever the noise is state-dependent	321
qpp::NoiseType::StateIndependent	32
Template tag, used whenever the noise is state-independent	321
qpp::States	02
Const Singleton class that implements most commonly used states	321
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	331
qpp::Timer< T, CLOCK T >	
Chronometer	333
qpp::exception::TypeMismatch	
Type mismatch exception	338
qpp::exception::UndefinedType	
Not defined for this type exception	340
qpp::exception::Unknown	
Unknown exception	342
qpp::QCircuitDescription::iterator::value_type	344
qpp::exception::ZeroSize	
Object has zero size exception	348

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	61
entanglement.h	
Entanglement functions	62
entropies.h	
Entropy functions	64
functions.h	
Generic quantum computing functions	65
input_output.h	
Input/output functions	70
instruments.h	
Measurement functions	71
number_theory.h	
Number theory functions	76
operations.h	
Quantum operation functions	78
qpp.h	
Quantum++ main header file, includes all other necessary headers	80
random.h	٠.
Randomness-related functions	82
statistics.h	٥,
Statistics functions	84
traits.h	۰,
Type traits	80
types.h Type aliases	۰,
Type aliases	80
	EH
Support for qudit quantum circuits	וכ
	Er
Quantum error correcting codes	2
Exceptions	5 5
classes/gates.h	J
Quantum gates	55
classes/idisplay.h	JĆ
Display interface via the non-virtual interface (NVI)	54
Display interiace via the hori-virtual interiace (INVI)	JC

12 File Index

classes/init.h	
Initialization	 356
classes/noise.h	
Noise models	 357
classes/random_devices.h	
Random devices	 358
classes/reversible.h	
Support for classical reversible circuits	 359
classes/states.h	
Quantum states	 359
classes/timer.h	
Timing	 360
experimental/experimental.h	
Experimental/test functions/classes	 365
internal/util.h	
Internal utility functions	 374
internal/classes/iomanip.h	
Input/output manipulators	 372
internal/classes/singleton.h	
Singleton pattern via CRTP	 373
MATLAB/matlab.h	
Input/output interfacing with MATLAR	376

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

 $\textit{Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset < N >) \\$

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class Init

const Singleton class that performs additional initializations/cleanups

class IQCircuit

Quantum circuit simulator abstract class.

· struct is complex

Checks whether the type is a complex type.

- struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit simulator class.

· class QCircuitDescription

Quantum circuit description class.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
template<typename Derived >
  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template<typename Derived >

```
void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)
```

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

 $\label{lem:dyn_col_vect} $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{typename \ Derived}::Scalar > ip (const \ Eigen::MatrixBase < \operatorname{Derived} > & phi, const \ Eigen:: \longleftrightarrow \\ \operatorname{MatrixBase} < \operatorname{Derived} > & psi, const \ std::vector < idx > & subsys, const \ std::vector < idx > & dims) \\ $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{dyn_col_v$

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

 $std::tuple < std::vector < idx >, \ double, \ cmat > measure_seq \ (const \ Eigen::MatrixBase < Derived > \&A, \\ std::vector < idx > target, \ idx \ d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

 $std::enable_if < std::is_same < typename Derived::Scalar, cplx >::value, dyn_mat < cplx > ::type \\ loadMATLAB (const std::string &mat_file, const std::string &var_name)$

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std} \\ \mbox{::vector} < \mbox{idx} > \&\mbox{dims})
```

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.
```

template<typename Derived >

```
\frac{dyn\_mat<}{typename} \ Derived::Scalar > ptrace2 \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ const \ std \\ \because vector < idx > \&dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

ullet template<typename Derived >

 $\frac{dyn_mat}{dx}$ typename Derived::Scalar > $\frac{dyn_mat}{dx}$ (const Eigen::MatrixBase < Derived > &A, const std::vector < $\frac{dx}{dx}$ > &target, const std::vector < $\frac{dx}{dx}$ > &dims)

Partial trace.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (gpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

• ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Variance.

template<typename Container >
 double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

const idx idx infty = static cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm Permut	ation
-------------	-------

Returns

Inverse of the permutation perm

6.1.3.65 ip() [1/2]

Generalized inner product.

Parameters

phi	hi Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

p	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.71 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded]

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

е
е

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.83 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.86 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.87 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
                bigint a,
                bigint b,
                bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

const std::vector< idx > & dims) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.108 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.109 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Normalized state vector or density matrix

```
6.1.3.110 omega()

cplx qpp::omega (
          idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

6.1.3.111 operator""" _i()

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.113 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

6.1.3.114 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

See also

Partial trace.

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.119 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.120 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.126 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

a	ì	Beginning of the interval, belongs to it
b)	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.133 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.135 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.142 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.143 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.145 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.147 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.3.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.153 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

6.1.3.155 schatten()

Schatten matrix norm.

Α	Eigen expression
p	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

6.1.3.168 sum() [1/3]

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

6.1.3.169 sum() [2/3]

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.171 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.173 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.174 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.175 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.180 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.185 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Χ	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = std::numeric_limits<double>::epsilon()
```

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool bool check_vector (const Eigen::MatrixBase Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

bool check_perm (const std::vector< idx > &perm)

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)

template<typename T > void variadic_vector_emplace (std::vector< T > &)

- $\begin{tabular}{ll} & \textbf{template}$<&typename T$, typename First , typename... Args>&void variadic_vector_emplace (std::vector< T>&v, First &&first, Args &&... args) \\ \end{tabular}$
- idx get num subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx D,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

```
#include <classes/reversible.h>
```

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:

• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.16 qpp::QCircuitDescription::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

 $Collaboration\ diagram\ for\ qpp:: QCircuit Description:: Gate Step:$



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuitDescription::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuitDescription::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuitDescription::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuitDescription::GateStep::name_
```

custom name of the step

7.16.3.5 target_

std::vector<idx> qpp::QCircuitDescription::GateStep::target_

target where the gate is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

- IDisplay ()=default
 - Default constructor.
- IDisplay (const IDisplay &)=default
 - Default copy constructor.
- IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]

Default constructor.
```

Default copy constructor.

Default move constructor.

```
7.17.2.4 ~|Display()
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::IQCircuit, qpp::QCircuitDescription, qpp::QCircuitDescription::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

Default copy assignment operator.

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

7.17.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.18 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

```
• Init ()
```

Additional initializations.

• ∼Init ()

Cleanups.

Friends

• class internal::Singleton< const Init >

Additional Inherited Members

7.18.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 Init()

qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.18.2.2 \simInit() 
 qpp::Init::\simInit ( ) [inline], [private] 
 Cleanups.
```

7.18.3 Friends And Related Function Documentation

```
7.18.3.1 internal::Singleton < const Init >
friend class internal::Singleton < const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.19 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.19.1 Detailed Description

Invalid iterator.

7.19.2 Member Function Documentation

7.19.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.19.2.2 type_description()

```
std::string qpp::exception::InvalidIterator::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.20 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.20.1 Constructor & Destructor Documentation

7.20.2 Member Function Documentation

```
7.20.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.20.3 Member Data Documentation

7.20.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.20.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.21 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_

7.21.1 Constructor & Destructor Documentation

7.21.1.1 IOManipPointer() [1/2]

7.21.1.2 IOManipPointer() [2/2]

7.21.2 Member Function Documentation

7.21.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.2.2 operator=()

7.21.3 Member Data Documentation

```
7.21.3.1 end_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.21.3.2 N_
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.21.3.3 p_
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.21.3.4 separator_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.21.3.5 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.22 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- std::string start_
- · std::string end_

7.22.1 Constructor & Destructor Documentation

```
7.22.1.1 IOManipRange() [1/2]
```

7.22.1.2 IOManipRange() [2/2]

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.2.2 operator=()

7.22.3 Member Data Documentation

```
7.22.3.1 end
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
```

7.22.3.2 first_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
```

7.22.3.3 last_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
```

7.22.3.4 separator_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

7.22.3.5 start_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


internal/classes/iomanip.h

7.23 qpp::IQCircuit Class Reference


Quantum circuit simulator abstract class.

#include <classes/circuits.h>

Inheritance diagram for qpp::IQCircuit:



Collaboration diagram for qpp::IQCircuit:



Public Member Functions

• IQCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

• IQCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

virtual ∼IQCircuit ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• idx get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

idx get_m_ip () const

Measurement instruction pointer.

idx get_q_ip () const

Quantum instruction pointer.

idx get_ip () const

Total instruction pointer.

QCircuitDescription::const_iterator get_iter () const

Iterator to current step.

· const QCircuitDescription & get_circuit_description () const noexcept

Quantum circuit description.

• IQCircuit & set_dit (idx i, idx value)

Sets the classical dit at position i.

· void reset ()

Resets the quantum circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

virtual void run (bool verbose=false, idx step=idx infty)=0

Executes the quantum circuit, pure virtual member function that must be overridden by all derived classes.

Protected Member Functions

• void set measured (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

· const QCircuitDescription & qcd_

quantum circuit description

ket psi_

state vector

std::vector< idx > dits_

classical dits

std::vector< double > probs_

measurement probabilities

- std::vector< idx > subsys
- · QCircuitDescription::const_iterator it_

iterator to current step

7.23.1 Detailed Description

Quantum circuit simulator abstract class.

See also

```
qpp::QCircuitDescription
```

Note

Every further derived class has to override the run() member function

7.23.2 Constructor & Destructor Documentation

Constructs a quantum circuit out of a quantum circuit description.

Note

The quantum circuit description must be an Ivalue

See also

```
qpp::QCircuit(QCircuitDescription&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qcd Quantum circuit description
```

Disables rvalue QCircuitDescription.

```
7.23.2.3 ∼IQCircuit()
```

```
virtual qpp::IQCircuit::~IQCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.23.3 Member Function Documentation

7.23.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.23.3.2 get_circuit_description()

```
const QCircuitDescription& qpp::IQCircuit::get_circuit_description ( ) const [inline], [noexcept]
```

Quantum circuit description.

Returns

Quantum circuit description

7.23.3.3 get_dit()

Value of the classical dit at position i.

Parameters

i Classical dit index

Returns

Value of the classical dit at position i

7.23.3.4 get_dits()

```
std::vector<idx> qpp::IQCircuit::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.23.3.5 get_ip()

```
idx qpp::IQCircuit::get_ip ( ) const [inline]
```

Total instruction pointer.

Returns

The sum of measurement instruction pointer and quantum instruction pointer

7.23.3.6 get_iter()

```
QCircuitDescription::const_iterator qpp::IQCircuit::get_iter ( ) const [inline]
```

Iterator to current step.

Returns

Iterator to current step in the circuit

```
7.23.3.7 get_m_ip()
```

```
idx qpp::IQCircuit::get_m_ip ( ) const [inline]
```

Measurement instruction pointer.

Points to the index of the next measurement to be executed from the std::vector<MeasureStep> of measurements in the circuit description

Returns

Measurement instruction pointer

7.23.3.8 get_measured() [1/2]

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.23.3.9 get_measured() [2/2]
```

```
std::vector<idx> qpp::IQCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.23.3.10 get_not_measured()

```
std::vector<idx> qpp::IQCircuit::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.23.3.11 get_probs()

```
std::vector<double> qpp::IQCircuit::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.23.3.12 get_psi()

```
ket qpp::IQCircuit::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.23.3.13 get_q_ip()

```
idx qpp::IQCircuit::get_q_ip ( ) const [inline]
```

Quantum instruction pointer.

Points to the index of the next quantum gate to be executed from the std::vector<GateStep> of quantum gates in the circuit description

Returns

Quantum instruction pointer

7.23.3.14 get_ref_psi()

```
ket& qpp::IQCircuit::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

7.23.3.15 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters

```
v Qudit index
```

7.23.3.16 reset()

```
void qpp::IQCircuit::reset ( ) [inline]
```

Resets the quantum circuit.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.23.3.17 run()

Executes the quantum circuit, pure virtual member function that must be overridden by all derived classes.

Parameters

verbose	If true, displays at console every executed step
step	How many steps to execute, by default executes until the end

Implemented in qpp::QCircuit.

7.23.3.18 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

```
7.23.3.19 set_measured_()
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.23.4 Member Data Documentation

```
7.23.4.1 dits_
std::vector<idx> qpp::IQCircuit::dits_ [protected]
classical dits

7.23.4.2 it_
QCircuitDescription::const_iterator qpp::IQCircuit::it_ [protected]
iterator to current step

7.23.4.3 probs_
std::vector<double> qpp::IQCircuit::probs_ [protected]
measurement probabilities
```

```
state vector
```

7.23.4.4 psi_

ket qpp::IQCircuit::psi_ [protected]

```
7.23.4.5 qcd_
```

```
const QCircuitDescription& qpp::IQCircuit::qcd_ [protected]
quantum circuit description
```

7.23.4.6 subsys_

```
std::vector<idx> qpp::IQCircuit::subsys_ [protected]
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:


· classes/circuits.h

7.24 qpp::is_complex < T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.24.1 Detailed Description

```
template < typename T > struct qpp::is_complex < T >
```

Checks whether the type is a complex type.

Provides the constant member value which is equal to true, if the type is a complex type, i.e. std::complex<T>

The documentation for this struct was generated from the following file:


· traits.h

7.25 qpp::is_complex< std::complex< T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< std::complex< T >>:



 $\label{local_complex} \mbox{Collaboration diagram for qpp::is_complex} < \mbox{std::complex} < \mbox{T} >>:$



7.25.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.26 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.26.1 Detailed Description

```
template<typename T, typename = void>
struct qpp::is_iterable< T, typename >
```

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



7.27.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ \\ ::declval < T > ().begin())) > \\ \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:


• traits.h

7.28 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

 $Inheritance\ diagram\ for\ qpp::is_matrix_expression < Derived >:$



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.28.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


• traits.h

7.29 qpp::QCircuitDescription::iterator Class Reference

Quantum circuit description bound-checking (safe) iterator.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuitDescription::iterator:



Classes

struct value_type_

Public Types

```
• using difference_type = long long
```

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

bool operator== (const iterator &rhs) const

Equality operator.

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuitDescription *qcd)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuitDescription *qcd)

Sets the iterator to std::begin(this)

Private Attributes

```
    const QCircuitDescription * qcd_ {nullptr}
```

< non-owning pointer to const circuit description

value_type_ elem_ {nullptr}

7.29.1 Detailed Description

Quantum circuit description bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.29.2 Member Typedef Documentation

7.29.3 Constructor & Destructor Documentation

```
7.29.2.1 difference_type
using qpp::QCircuitDescription::iterator::difference_type = long long
iterator trait
7.29.2.2 iterator_category
using qpp::QCircuitDescription::iterator::iterator_category = std::forward_iterator_tag
iterator trait
7.29.2.3 pointer
using qpp::QCircuitDescription::iterator::pointer = const value_type*
iterator trait
7.29.2.4 reference
using qpp::QCircuitDescription::iterator::reference = const value_type&
iterator trait
7.29.2.5 value_type
using qpp::QCircuitDescription::iterator::value_type = value_type_
iterator trait
```

```
7.29.3.1 iterator() [1/2]

qpp::QCircuitDescription::iterator::iterator ( ) [default]

Default constructor.

7.29.3.2 iterator() [2/2]

qpp::QCircuitDescription::iterator::iterator (
```

const iterator &) [default]

Default copy constructor.

7.29.4 Member Function Documentation

7.29.4.1 operator"!=()

Inequality operator.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.29.4.2 operator*()
```

```
const value_type_& qpp::QCircuitDescription::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.29.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuitDescription::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.29.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

7.29.4.5 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.29.4.6 operator==()

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.29.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qcd | Constant pointer to a quantum circuit description

7.29.4.8 set_end_()

Sets the iterator to std::begin(this)

Parameters

qcd | Constant pointer to a quantum circuit description

7.29.5 Member Data Documentation

```
7.29.5.1 elem_
```

```
value_type_ qpp::QCircuitDescription::iterator::elem_ {nullptr} [private]
```

7.29.5.2 qcd_

```
const QCircuitDescription* qpp::QCircuitDescription::iterator::qcd_ {nullptr} [private]
```

< non-owning pointer to const circuit description

The documentation for this class was generated from the following file:

· classes/circuits.h

7.30 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.30.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.30.2 Member Typedef Documentation

7.30.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.31 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.31.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.31.2 Member Function Documentation

7.31.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.31.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.32 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.32.2 Member Function Documentation

7.32.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.32.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.33 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.33.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.34 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.34.2 Member Function Documentation

7.34.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.34.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquare::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.35 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.35.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.36 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.36.2 Member Function Documentation

7.36.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.36.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.37 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.38 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.38.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.39 qpp::QCircuitDescription::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuitDescription::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement type = MeasureType::NONE

measurement type

- std::vector< cmat > mats_
- std::vector< idx > target_

measurement

idx c_reg_ {}

result is being stored

• std::string name_

custom name of the step

7.39.1 Detailed Description

One step consisting only of measurements in the circuit.

7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 MeasureStep() [1/2]

qpp::QCircuitDescription::MeasureStep::MeasureStep ( ) [default]

Default constructor.

7.39.2.2 MeasureStep() [2/2]
```

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.39.3 Member Data Documentation

```
7.39.3.1 c_reg_
idx qpp::QCircuitDescription::MeasureStep::c_reg_ {}
result is being stored
```

index of the classical register where the measurement

```
7.39.3.2 mats_
std::vector<cmat> qpp::QCircuitDescription::MeasureStep::mats_
matrix/matrices that specify the
```

7.39.3.3 measurement_type_

MeasureType qpp::QCircuitDescription::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type

7.39.3.4 name_

std::string qpp::QCircuitDescription::MeasureStep::name_

custom name of the step

7.39.3.5 target_

std::vector<idx> qpp::QCircuitDescription::MeasureStep::target_

measurement

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.40 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.40.2.2 type_description()

std::string qpp::exception::NoCodeword::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

using noise_type = T

Public Member Functions

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

• void compute_probs_ (const cmat &state, const std::vector< idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

cmat compute_state_ (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs_

probabilities

idx d_ {}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.41.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.41.2 Member Typedef Documentation

7.41.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.41.3 Constructor & Destructor Documentation

7.41.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.41.4 Member Function Documentation

7.41.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.41.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.41.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.41.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.41.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.41.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.41.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.41.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.41.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.41.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.41.5 Member Data Documentation

7.41.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
```

qudit dimension

7.41.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.41.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.41.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.41.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

7.42 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.42.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


· classes/noise.h

7.43 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.43.2 Member Function Documentation

7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.43.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.44 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Code not yet implemented.

7.44.2 Member Function Documentation

7.44.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.44.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.45 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.45.2 Member Function Documentation

7.45.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.45.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.46 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.46.2 Member Function Documentation

7.46.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.46.2.2 type_description()

```
std::string qpp::exception::NotQubitMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.47 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.48 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.48.2 Member Function Documentation

7.48.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.48.2.2 type_description()

std::string qpp::exception::NotQubitSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.49 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.50 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Argument out of range exception.

Argument out of range

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.51 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.51.2 Member Function Documentation

7.51.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.51.2.2 type_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.52 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.52.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.53 qpp::QCircuit Class Reference

Quantum circuit simulator class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Public Member Functions

- void run (bool verbose=false, idx step=idx_infty) override
 - < Uses the base IQCircuit constructor
- IQCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

• IQCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

Additional Inherited Members

7.53.1 Detailed Description

Quantum circuit simulator class.

See also

qpp::QCircuitDescription

7.53.2 Member Function Documentation

```
7.53.2.1 IQCircuit() [1/2]
```

```
qpp::IQCircuit::IQCircuit [inline], [explicit]
```

Constructs a quantum circuit out of a quantum circuit description.

Note

The quantum circuit description must be an Ivalue

See also

qpp::QCircuit(QCircuitDescription&&)

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

qcd Quantum circuit description

```
7.53.2.2 IQCircuit() [2/2]
```

```
qpp::IQCircuit::IQCircuit [delete]
```

Disables rvalue QCircuitDescription.

7.53.2.3 run()

< Uses the base IQCircuit constructor

Executes the quantum circuit, qpp::IQCircuit::run() override

Parameters

verbose	If true, displays at console every executed step
step	How many steps to execute, by default executes until the end

Implements qpp::IQCircuit.

The documentation for this class was generated from the following file:


· classes/circuits.h

7.54 qpp::QCircuitDescription Class Reference


Quantum circuit description class.

```
#include <classes/circuits.h>
```

Inheritance diagram for qpp::QCircuitDescription:



Collaboration diagram for qpp::QCircuitDescription:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit description bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,

 ${\tt GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_$

GateType::MULTIPLE CTRL MULTIPLE TARGET,

GateType::CUSTOM CTRL, GateType::SINGLE cCTRL SINGLE TARGET, GateType::SINGLE cCTRL MULTIPLE TARGET

GateType::MULTIPLE_cCTRL_SINGLE_TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

• using const_iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

· const_iterator begin () const noexcept

Constant iterator to the first element.

• const_iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

const_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuitDescription (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit description.

virtual ~QCircuitDescription ()=default

Default virtual destructor.

idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get nc () const noexcept

Total number of classical dits in the circuit.

idx get_d () const noexcept

Dimension of the comprising qudits.

const std::vector< MeasureStep > & get_measurements () const noexcept

Vector of qpp::QCircuitDescription::MeasureStep.

const std::vector < GateStep > & get_gates () const noexcept

Vector of qpp::QCircuitDescription::GateStep.

• std::string get_name () const

Quantum circuit name.

• idx get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

• idx get_gate_count () const noexcept

Quantum circuit total gate count.

· idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuitDescription & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

• QCircuitDescription & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuitDescription & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuitDescription & gate fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuitDescription & gate_fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuitDescription & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuitDescription & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & TFQ (const std::vector< idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

• QCircuitDescription & CTRL (const cmat &U, idx ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuitDescription & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuitDescription & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuitDescription & cCTRL_custom (const cmat &U, const std::vector < idx > &ctrl_dits, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & measureZ (idx i, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuitDescription & measureV (const cmat &V, idx i, idx c reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuitDescription & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

std::string to JSON (bool enclosed in curly brackets=true) const

Displays the circuit description in JSON format.

Private Attributes

const idx nq_

number of qudits

· const idx nc_

number of classical "dits"

const idx d_

qudit dimension

• std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

std::vector< GateStep > gates_{}

gates

 $\bullet \ \, std::vector < MeasureStep > measurements_\{\}\\$

measurements

std::vector< StepType > step_types_{}

type of each step

Friends

std::ostream & operator<< (std::ostream &os, const GateType &gate_type)

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

7.54.1 Detailed Description

Quantum circuit description class.

See also

qpp::QCircuit

7.54.2 Member Typedef Documentation

7.54.2.1 const_iterator

```
using qpp::QCircuitDescription::const_iterator = iterator
```

both iterators are const_iterators

7.54.3 Member Enumeration Documentation

7.54.3.1 GateType

```
enum qpp::QCircuitDescription::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
Genera பிழிக்க முள் TRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with

7.54.3.2 MeasureType

```
enum qpp::QCircuitDescription::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix \it{V} measurement of multiple qudits in the orthonormal

7.54.3.3 StepType

```
enum qpp::QCircuitDescription::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuitDescription()

```
qpp::QCircuitDescription::QCircuitDescription (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit description.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit description name (optional)	

7.54.4.2 ~QCircuitDescription()

```
\label{local_problem} \mbox{virtual qpp::QCircuitDescription::} \sim \mbox{QCircuitDescription ( ) [virtual], [default]}
```

Default virtual destructor.

7.54.5 Member Function Documentation

```
7.54.5.1 begin() [1/2]
```

```
iterator qpp::QCircuitDescription::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.2 begin() [2/2]
```

```
const_iterator qpp::QCircuitDescription::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.54.5.3 cbegin()

```
const_iterator qpp::QCircuitDescription::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name Generated by Doxygen

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.7 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.8 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.9 cend()

```
const_iterator qpp::QCircuitDescription::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.54.5.10 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.12 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.14 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.15 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit description

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.16 end() [1/2]
```

```
iterator qpp::QCircuitDescription::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.17 end() [2/2]
```

```
const_iterator qpp::QCircuitDescription::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.54.5.21 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.22 gate_fan() [1/2]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.23 gate_fan() [2/2]
```

Applies the single qudit gate *U* on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.24 get_d()
```

```
idx qpp::QCircuitDescription::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

```
7.54.5.25 get_gate_count()
```

```
idx qpp::QCircuitDescription::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

Returns

Total gate count

7.54.5.26 get_gates()

```
const std::vector<GateStep>& qpp::QCircuitDescription::get_gates ( ) const [inline], [noexcept]
```

Vector of qpp::QCircuitDescription::GateStep.

Returns

Vector of qpp::QCircuitDescription::GateStep

7.54.5.27 get_measured() [1/2]

Check whether qudit i was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.54.5.28 get_measured() [2/2]
```

```
std::vector<idx> qpp::QCircuitDescription::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.54.5.29 get_measurement_count()
```

```
idx qpp::QCircuitDescription::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.54.5.30 get_measurements()

```
const std::vector<MeasureStep>& qpp::QCircuitDescription::get_measurements ( ) const [inline],
[noexcept]
```

Vector of qpp::QCircuitDescription::MeasureStep.

Returns

Vector of qpp::QCircuitDescription::MeasureStep

7.54.5.31 get_name()

```
std::string qpp::QCircuitDescription::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.54.5.32 get_nc()
```

```
idx qpp::QCircuitDescription::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.54.5.33 get_non_measured()
```

```
\verb|std::vector<| idx>| qpp::QCircuitDescription::get_non_measured () const [inline]|
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.54.5.34 get_nq()
```

```
idx qpp::QCircuitDescription::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.54.5.35 get_step_count()

```
idx qpp::QCircuitDescription::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.54.5.36 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
i	Qudit index	
Generated b	প শুরুজ্জী al register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

```
7.54.5.37 measureV() [2/2]
```

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.54.5.38 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

i	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.54.5.39 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.54.5.40 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.54.5.41 to_JSON()

Displays the circuit description in JSON format.

Parameters

Returns

String containing the JSON representation of the circuit description

7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureStep enum class

Returns

Output stream

7.54.7 Member Data Documentation

```
7.54.7.1 d_
```

```
const idx qpp::QCircuitDescription::d_ [private]
```

qudit dimension

```
7.54.7.2 gates_
std::vector<GateStep> qpp::QCircuitDescription::gates_ {} [private]
gates
7.54.7.3 measured_
std::vector<bool> qpp::QCircuitDescription::measured_ [private]
keeps track of the measured qudits
7.54.7.4 measurements_
std::vector<MeasureStep> qpp::QCircuitDescription::measurements_ {} [private]
measurements
7.54.7.5 name_
std::string qpp::QCircuitDescription::name_ [private]
optional circuit name
7.54.7.6 nc
const idx qpp::QCircuitDescription::nc_ [private]
number of classical "dits"
7.54.7.7 nq_
const idx qpp::QCircuitDescription::nq_ [private]
number of qudits
```

7.54.7.8 step_types_

```
std::vector<StepType> qpp::QCircuitDescription::step_types_ {} [private]
```

type of each step

The documentation for this class was generated from the following file:


· classes/circuits.h

7.55 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.55.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.55.2 Constructor & Destructor Documentation

7.55.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability
-------	-------------------------------

The documentation for this class was generated from the following file:


· classes/noise.h

7.56 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.56.1 Detailed Description

Qubit bit flip noise.

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

```
p Noise probability
```

The documentation for this class was generated from the following file:


• classes/noise.h

7.57 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Bit Phase Flip Noise:$



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \mbox{double } p \mbox{ ) [inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit depolarizing noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.59 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

gamma	Phase damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.61 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.61.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.61.2 Member Function Documentation

7.61.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.61.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.62.1 Detailed Description

Qudit depolarizing noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.62.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.62.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.63 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.63.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.63.2 Constructor & Destructor Documentation

7.63.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.63.2.2 ∼RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.63.3 Member Function Documentation

```
7.63.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.63.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.63.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.63.4 Friends And Related Function Documentation

```
7.63.4.1 internal::Singleton < RandomDevices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.63.5 Member Data Documentation

```
7.63.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.63.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.64 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.64.1 Detailed Description

```
\label{template} \begin{split} & template {<} typename \ T {>} \\ & class \ qpp::internal::Singleton {<} \ T {>} \end{split}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.64.2 Constructor & Destructor Documentation

```
7.64.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.64.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.64.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.64.3 Member Function Documentation
7.64.3.1 get_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_instance ( ) [inline], [static], [noexcept]
7.64.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.64.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
             const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.65 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.65.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.65.2 Member Function Documentation

7.65.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.65.2.2 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.66 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.66.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.67 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.67.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.68 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.68.1 Detailed Description

const Singleton class that implements most commonly used states

7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.68.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

Default destructor.

7.68.3 Member Function Documentation

```
7.68.3.1 jn()
```

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.68.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.68.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.68.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.68.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.68.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.68.5 Member Data Documentation

```
7.68.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.68.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

7.68.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.68.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.68.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.68.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.68.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.68.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.68.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.68.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.68.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.68.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.68.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.68.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.68.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.68.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.68.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.68.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.68.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.68.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.68.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.68.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.68.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.68.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.69 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.69.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.69.2 Member Function Documentation

7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	П
--	---

7.69.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.70 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

 ${\it Stops the chronometer.}$

· double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.70.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 Timer() [1/3]
```

```
\label{template} $$ \text{template}$ \xrightarrow{T = std::chrono::duration}$ & \text{double}$, typename CLOCK_T = std::chrono::steady$ $$ \_clock$ & \\ & \text{qpp}::Timer< T, CLOCK_T >::Timer ( ) [inline], [noexcept] \\ \end{aligned}
```

Constructs an instance with the current time as the starting point.

```
7.70.2.2 Timer() [2/3]
```

Default copy constructor.

```
7.70.2.3 Timer() [3/3]
```

Default move constructor.

7.70.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.70.3 Member Function Documentation

7.70.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.70.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.70.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.70.3.4 operator=() [2/2]
```

Default move assignment operator.

7.70.3.5 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

7.70.3.6 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.70.4 Member Data Documentation

7.70.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.70.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.71 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.71.2 Member Function Documentation

7.71.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.71.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.72.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.72.2 Member Function Documentation

7.72.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.72.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.73 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred]
-------	--	---

7.73.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::QCircuitDescription::iterator::value_type_ Struct Reference

Inheritance diagram for qpp::QCircuitDescription::iterator::value_type_:



Collaboration diagram for qpp::QCircuitDescription::iterator::value_type_:



Public Member Functions

```
    value_type_ (const value_type_ &)=default
        Default copy constructor.

    value_type_ & operator= (const value_type_ &)=default
```

Default copy assignment operator.

value_type_ (const QCircuitDescription *value_type_qcd)
 Default value_type_constructor.

Public Attributes

```
    const QCircuitDescription * value_type_qcd_
    < non-owning pointer to the parent iterator</li>
```

StepType type_{StepType::NONE}

step type

• idx ip_ {idx_infty}

instruction pointer

std::vector < GateStep >::const_iterator gates_ip_ {}
 gates instruction pointer

std::vector< MeasureStep >::const_iterator measurements_ip_ {}

measurements instruction pointer

7.74.1 Constructor & Destructor Documentation

Default copy constructor.

Default value_type_ constructor.

Parameters

value_type_qcd | Constant pointer to quantum circuit description

7.74.2 Member Function Documentation

7.74.2.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.74.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.74.3 Member Data Documentation

```
7.74.3.1 gates_ip_
```

```
std::vector<GateStep>::const_iterator qpp::QCircuitDescription::iterator::value_type_::gates
_ip_ {}
```

gates instruction pointer


```
7.74.3.2 ip_
idx qpp::QCircuitDescription::iterator::value_type_::ip_ {idx_infty}
instruction pointer
7.74.3.3 measurements_ip_
std::vector<MeasureStep>::const_iterator qpp::QCircuitDescription::iterator::value_type_←
::measurements_ip_ {}
measurements instruction pointer
7.74.3.4 type_
StepType qpp::QCircuitDescription::iterator::value_type_::type_ {StepType::NONE}
step type
7.74.3.5 value_type_qcd_
const QCircuitDescription* qpp::QCircuitDescription::iterator::value_type_::value_type_qcd_
< non-owning pointer to the parent iterator
The documentation for this struct was generated from the following file:
    · classes/circuits.h
```

7.75 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.75.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuitDescription

Quantum circuit description class.

• struct qpp::QCircuitDescription::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuitDescription::MeasureStep

One step consisting only of measurements in the circuit.

• class qpp::QCircuitDescription::iterator

Quantum circuit description bound-checking (safe) iterator.

- struct qpp::QCircuitDescription::iterator::value_type_
- class qpp::IQCircuit

Quantum circuit simulator abstract class.

· class qpp::QCircuit

Quantum circuit simulator class.

352 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

354 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

· class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

• class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

356 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI)

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

Namespaces

qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI)

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

358 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.

8.9.1 Detailed Description


Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

360 File Documentation

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
- $\textit{User-defined literal for complex } i = \sqrt{-1} \; \textit{(integer overload)} \\ \bullet \; \textit{constexpr cplx qpp::operator} \\ \text{"} \; \underline{-i} \; \textit{(long double x) noexcept} \\$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double qpp::eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double qpp::renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

qpp::literals

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template < typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.
```

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

```
std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

```
std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

ullet template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator_traits < InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

```
Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

• std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

• template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

```
cmat qpp::literals::operator"" _prj ()
```

Multi-partite qubit projector user-defined literal.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::Singleton < T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

template<typename T >

bool qpp::internal::check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

• template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $bool\ qpp::internal::check_qubit_matrix\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

• template<typename Derived >

 $bool\ qpp::internal::check_qubit_cvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

- template<typename Derived1 , typename Derived2 >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B) $$$

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - $\label{eq:condition} \mbox{void qpp::internal::variadic_vector_emplace (std::vector< T > \&v, First \&\& first, Args \&\&... args) \\$
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

• double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \ \, \text{std::vector} < \mathsf{idx} > \mathsf{qpp::compperm} \ (\mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{perm}, \ \mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std \mapsto ::vector < idx > \&dims) $$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

 $\label{lem:const} \begin{tabular}{ll} double & qpp::cor (const dmat & probXY, const Container & X, const Container & Y, typename & std::enable_if < is_iterable < Container >::value >::type *=nullptr) \\ \end{tabular}$

Correlation.

8.28 traits.h File Reference 385


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end(
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

```
using <a href="mailto:qpp::dyn_mat">qpp::dyn_mat</a> = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.29.1	Detailed	Descri	ntion
0.20.1	Detailed	DCGCII	DUVII

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 387	b00
\sim Codes	qpp::States, 326
qpp::Codes, 136	b01
\sim Dynamic_bitset	qpp::States, 327
qpp::Dynamic_bitset, 158	b10
\sim Gates	qpp::States, 327
qpp::Gates, 174	b11
~IDisplay	qpp::States, 327
qpp::IDisplay, 190	begin
~IQCircuit	qpp::QCircuitDescription, 281
qpp::IQCircuit, 206	bigint
	_
~Init	qpp, 26
qpp::Init, 192	Bit_circuit
~NoiseBase	qpp::Bit_circuit, 131
qpp::NoiseBase, 248	bloch2rho
\sim QCircuitDescription	qpp, 36
qpp::QCircuitDescription, 281	bra
\sim RandomDevices	qpp, 26
qpp::RandomDevices, 314	
~Singleton	c_reg_
qpp::internal::Singleton, 318	qpp::QCircuitDescription::MeasureStep, 242
~States	cCTRL custom
	gpp::QCircuitDescription, 284
qpp::States, 324	cCTRL
~Timer	
qpp::Timer, 335	qpp::QCircuitDescription, 282, 283
	CNOTba
A_	qpp::Gates, 183
qpp::internal::IOManipEigen, 196	CNOT
absm	qpp::Bit_circuit, 131
qpp, 28	qpp::Bit_circuit::Gate_count, 170
abssq	qpp::Gates, 183
qpp, 29	CTRL_custom
adjoint	app::QCircuitDescription, 286
qpp, 30	CTRL
all	qpp::Gates, 175
qpp::Dynamic_bitset, 158	qpp::QCircuitDescription, 284–286
anticomm	cbegin
qpp, 30	qpp::QCircuitDescription, 281
any	cend
qpp::Dynamic_bitset, 158	qpp::QCircuitDescription, 284
apply	check_cvector
qpp, 31–33	qpp::internal, 120
applyCTRL	check_dims
qpp, 33, 34	gpp::internal, 120
applyQFT	check_dims_match_cvect
qpp, 35	qpp::internal, 120
applyTFQ	check_dims_match_mat
qpp, 35	qpp::internal, 121
avg	check_dims_match_rvect
app. 36	app::internal, 121

check_eq_dims	qpp::NoiseBase, 248
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 248
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuitDescription, 279
qpp::internal, 122	constants.h, 361
check_qubit_cvector	contfrac2x
qpp::internal, 122	qpp, 40
check_qubit_matrix	convergents
qpp::internal, 122	qpp, 41 cor
check_qubit_rvector	qpp, 42
qpp::internal, 122	cosm
check_qubit_vector	qpp, 42
qpp::internal, 122	count
check_rvector	qpp::Dynamic_bitset, 158
qpp::internal, 122	COV
check_square_mat qpp::internal, 123	qpp, 43
check_subsys_match_dims	cplx
qpp::internal, 123	qpp, <u>2</u> 7
check_vector	ctrl_
qpp::internal, 123	qpp::QCircuitDescription::GateStep, 187
choi2kraus	CustomException
qpp, 36	qpp::exception::CustomException, 138
choi2super	cwise
qpp, 37	qpp, 43
chop	CZ
qpp, 116	qpp::Gates, 183
chop_	d_
qpp::internal::IOManipEigen, 197	qpp::NoiseBase, 251
classes/circuits.h, 351	qpp::QCircuitDescription, 297
classes/codes.h, 352	data
classes/exception.h, 353	qpp::Dynamic_bitset, 158
classes/gates.h, 355	det
classes/idisplay.h, 356	qpp, 44
classes/init.h, 356	difference_type
classes/noise.h, 357	qpp::QCircuitDescription::iterator, 220
classes/random_devices.h, 358	dirsum
classes/reversible.h, 359	qpp, 44–46
classes/states.h, 359	dirsum2
classes/timer.h, 360	qpp::internal, 123
cmat	dirsumpow
qpp, 26	qpp, 46
Codes	disp
qpp::Codes, 136	qpp, 47, 48
codeword	display
qpp::Codes, 136	qpp::Dynamic_bitset, 159
comm	qpp::IDisplay, 190
qpp, 37	qpp::IQCircuit, 207
complement	qpp::QCircuitDescription, 287
qpp, 38	<pre>qpp::QCircuitDescription::iterator::value_type_← , 346</pre>
compperm	, 346 qpp::Timer, 335
qpp, 38 compute_probs_	qpp::internal::IOManipEigen, 196

qpp::internal::IOManipPointer, 199	qpp::exception::MatrixNotSquareNorRvector, 236
qpp::internal::IOManipRange, 202	qpp::exception::MatrixNotSquareNorVector, 238
display_impl_	qpp::exception::MatrixNotVector, 240
qpp::internal::Display_Impl_, 152	qpp::exception::NoCodeword, 244
dits_	qpp::exception::NotBipartite, 254
qpp::IQCircuit, 212	qpp::exception::NotImplemented, 256
dmat	qpp::exception::NotQubitCvector, 258
qpp, 27	qpp::exception::NotQubitMatrix, 260
dyn_col_vect	qpp::exception::NotQubitRvector, 262
qpp, 27	qpp::exception::NotQubitSubsys, 264
dyn_mat	qpp::exception::NotQubitVector, 266
qpp, 27	qpp::exception::OutOfRange, 268
dyn_row_vect	qpp::exception::PermInvalid, 270
qpp, 27	qpp::exception::PermMismatchDims, 272
Dynamic_bitset	qpp::exception::QuditAlreadyMeasured, 309
qpp::Bit_circuit, 132	qpp::exception::SizeMismatch, 320
qpp::Dynamic_bitset, 157	qpp::exception::SubsysMismatchDims, 332
ee	qpp::exception::TypeMismatch, 339
qpp, 116	qpp::exception::UndefinedType, 341
	qpp::exception::Unknown, 343
egcd	qpp::exception::ZeroSize, 349
qpp, 49	expandout
eig	qpp::Gates, 175, 176
qpp, 49	experimental/experimental.h, 365
elem_	expm
qpp::QCircuitDescription::iterator, 223	qpp, 52
end	4FF7 *-
qpp::QCircuitDescription, 287	FRED
end_	qpp::Bit_circuit, 132
qpp::Timer, 337	qpp::Bit_circuit::Gate_count, 171
qpp::internal::IOManipPointer, 199	qpp::Gates, 183
qpp::internal::IOManipRange, 203	factors
entanglement	
qpp, 50	qpp, 53
entanglement.h, 362	Fd
	qpp::Gates, 177
entropies.h, 364	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 312
qpp, 51	fill_probs_
eps	qpp::QuditDepolarizingNoise, 312
qpp, 116	first_
evals	qpp::internal::IOManipRange, 203
qpp, 51	flip
evects	qpp::Dynamic_bitset, 159
qpp, 52	functions.h, 365
Exception	funm
qpp::exception::DimsInvalid, 141	qpp, 53
qpp::exception::DimsMismatchCvector, 143	-11-17
qpp::exception::DimsMismatchMatrix, 145	GHZ
qpp::exception::DimsMismatchRvector, 147	qpp::States, 327
qpp::exception::DimsMismatchVector, 149	gate
qpp::exception::DimsNotEqual, 151	qpp::QCircuitDescription, 288, 289
qpp::exception::Duplicates, 154	gategan::OCircuitDescription::GateStep_197
qpp::exception::Exception, 169	qpp::QCircuitDescription::GateStep, 187
qpp::exception::InvalidIterator, 194	gate_count
qpp::exception::MatrixMismatchSubsys, 226	qpp::Bit_circuit, 134
qpp::exception::MatrixNotCvector, 228	gate_custom
qpp::exception::MatrixNotRvector, 230	qpp::QCircuitDescription, 289
qpp::exception::MatrixNotSquare, 232	gate_fan
qpp::exception::MatrixNotSquareNorCvector, 234	qpp::QCircuitDescription, 289, 290

gate_type_	qpp::QCircuitDescription, 291
qpp::QCircuitDescription::GateStep, 187	get_measurements
GateStep	qpp::QCircuitDescription, 292
qpp::QCircuitDescription::GateStep, 186	get_name
GateType	qpp::Gates, 178
qpp::QCircuitDescription, 279	qpp::QCircuitDescription, 292
Gates	get_nc
qpp::Gates, 174	qpp::QCircuitDescription, 292
gates	get_non_measured
qpp::QCircuitDescription, 297	qpp::QCircuitDescription, 292
gates_ip_	get not measured
qpp::QCircuitDescription::iterator::value_type_←	qpp::IQCircuit, 209
, 346	get_nq
gcd	qpp::QCircuitDescription, 293
	get_num_subsys
qpp, 54	qpp::internal, 123
gconcurrence	get_prng
qpp, 54	qpp::RandomDevices, 315
generated_	get probs
qpp::NoiseBase, 251	5 —
get	qpp::IQCircuit, 209
qpp::Dynamic_bitset, 160	qpp::NoiseBase, 250
get_Ks	get_psi
qpp::NoiseBase, 249	qpp::IQCircuit, 210
get_circuit_description	get_q_ip
qpp::IQCircuit, 207	qpp::IQCircuit, 210
get_d	get_ref_psi
qpp::NoiseBase, 249	qpp::IQCircuit, 210
qpp::QCircuitDescription, 290	get_relative_pos_
get_dim_subsys	qpp::IQCircuit, 210
qpp::internal, 123	get_step_count
get_dit	qpp::QCircuitDescription, 293
qpp::IQCircuit, 207	get_thread_local_instance
	qpp::internal::Singleton, 318
get_dits	grams
qpp::IQCircuit, 208	qpp, 55, 56
get_duration	
qpp::Timer, 336	Н
get_gate_count	qpp::Gates, 183
qpp::QCircuitDescription, 290	heig
get_gates	qpp, 56
qpp::QCircuitDescription, 291	hevals
get_instance	qpp, 57
qpp::internal::Singleton, 318	hevects
get_ip	qpp, 57
qpp::IQCircuit, 208	4PP, 07
get_iter	i
qpp::IQCircuit, 208	qpp::NoiseBase, 251
get_last_idx	IDisplay
qpp::NoiseBase, 249	qpp::IDisplay, 189
get_last_K	IOManipEigen
qpp::NoiseBase, 250	
get_last_p	qpp::internal::IOManipEigen, 196
	IOManipPointer
qpp::NoiseBase, 250	qpp::internal::IOManipPointer, 198, 199
get_m_ip	IOManipRange
qpp::IQCircuit, 208	qpp::internal::IOManipRange, 202
get_measured	IQCircuit
qpp::IQCircuit, 209	qpp::IQCircuit, 206
qpp::QCircuitDescription, 291	qpp::QCircuit, 274
get_measurement_count	ld

qpp::Gates, 178	kronpow
Id2 qpp::Gates, 184	qpp, 62 Ks_
idx	qpp::NoiseBase, 252
qpp, 28	
idx_infty	last
qpp, 116	qpp::internal::IOManipRange, 203
qpp::Dynamic_bitset, 160	qpp, 63
infty	load
qpp, 116	qpp, 64
Init	qpp::RandomDevices, 315
qpp::Init, 192	loadMATLAB
input_output.h, 370	qpp, 64, 65
instruments.h, 371	logdet
internal/classes/iomanip.h, 372	qpp, 66
internal/classes/singleton.h, 373	logm
internal/util.h, 374	qpp, 66
internal::Singleton < const Codes >	lognegativity
qpp::Codes, 137	qpp, 67
internal::Singleton < const Gates >	MATLAB/matlab.h, 376
qpp::Gates, 183 internal::Singleton< const Init >	MODMUL
qpp::Init, 192	qpp::Gates, 178
internal::Singleton < const States >	marginalX
qpp::States, 326	qpp, 67
internal::Singleton< RandomDevices >	marginalY
qpp::RandomDevices, 316	qpp, 69
inverse	mats_
qpp, 57	qpp::QCircuitDescription::MeasureStep, 242
invperm	maxn
qpp, 58	qpp, 116
ip	measure
qpp, 58, 59	qpp, 69–74
ip_	measure_seq qpp, 74, 75
qpp::QCircuitDescription::iterator::value_type_←	MeasureStep
, 346	qpp::QCircuitDescription::MeasureStep, 242
isprime qpp, 59	MeasureType
it_	qpp::QCircuitDescription, 280
qpp::IQCircuit, 212	measured_
iterator	qpp::QCircuitDescription, 298
qpp::QCircuitDescription::iterator, 220, 221	measurement_type_
iterator_category	qpp::QCircuitDescription::MeasureStep, 242
qpp::QCircuitDescription::iterator, 220	measurements_
	qpp::QCircuitDescription, 298
jn	measurements_ip_
qpp::States, 324	<pre>qpp::QCircuitDescription::iterator::value_type_← , 347</pre>
ket	measureV
qpp, 28	qpp::QCircuitDescription, 293, 294
kraus2choi	measureZ
qpp, 59	qpp::QCircuitDescription, 294
kraus2super	mes
qpp, 60	qpp::States, 324
kron	minus
qpp, 60–62	qpp::States, 325
kron2	mket
qpp::internal, 124	qpp, 75, 76

modinv	qpp::QCircuitDescription::iterator, 221
qpp, 76	operator()
modmul	qpp::NoiseBase, 250, 251
qpp, 77	operator++
modpow	qpp::QCircuitDescription::iterator, 221, 222
qpp, 77	operator-
mprj	qpp::Dynamic_bitset, 161
qpp, 78	operator=
msg_ approxecution::Evention 170	qpp::IDisplay, 190 qpp::QCircuitDescription::iterator, 222
qpp::exception::Exception, 170 multiidx2n	qpp::QCircuitDescription::iterator::value_type_←
qpp, 79	, 346
qpp::internal, 124	qpp::Timer, 336
appnornat, 124	qpp::internal::IOManipPointer, 199
n2multiidx	qpp::internal::IOManipRange, 202
qpp, 79	qpp::internal::Singleton, 318
qpp::internal, 124	operator==
N_	qpp::Dynamic_bitset, 162
qpp::Dynamic_bitset, 165	qpp::QCircuitDescription::iterator, 222
qpp::internal::IOManipPointer, 200	operator"" _bra
NOT	qpp::literals, 125
qpp::Bit_circuit, 132	operator""_i
qpp::Bit_circuit::Gate_count, 171	qpp, 82
name_	qpp::literals, 125
qpp::QCircuitDescription, 298	operator"" _ket
qpp::QCircuitDescription::GateStep, 187	qpp::literals, 126
qpp::QCircuitDescription::MeasureStep, 243	operator"" _prj
nc_	qpp::literals, 126
qpp::QCircuitDescription, 298	n
negativity	p_ qpp::internal::IOManipPointer, 200
qpp, 80 noise_type	pGHZ
qpp::NoiseBase, 247	qpp::States, 328
NoiseBase	pb00
qpp::NoiseBase, 247	qpp::States, 327
none	pb01
qpp::Dynamic_bitset, 160	qpp::States, 327
norm	pb10
qpp, 81	qpp::States, 328
normalize	pb11
qpp, 81	qpp::States, 328
nq_	pi
qpp::QCircuitDescription, 298	qpp, 117
number_theory.h, 376	plus qpp::States, 325
offset_	pointer
qpp::Dynamic bitset, 161	qpp::QCircuitDescription::iterator, 220
omega	powm
qpp, 82	qpp, 82
one	prj
qpp::States, 325	qpp, 83
operations.h, 378	prng_
operator!=	qpp::RandomDevices, 316
qpp::Dynamic_bitset, 161	probs_
qpp::QCircuitDescription::iterator, 221	qpp::IQCircuit, 212
operator<<	qpp::NoiseBase, 252
qpp::IDisplay, 191	prod
qpp::QCircuitDescription, 296, 297	qpp, 83, 84
operator*	psi_

qpp::IQCircuit, 212	convergents, 41
ptrace	cor, 42
qpp, 84, 85	cosm, 42
ptrace1	cov, 43
qpp, 85, 86	cplx, 27
ptrace2	cwise, 43
qpp, 86, 87	det, 44
ptranspose	dirsum, 44–46
qpp, 87, 88	dirsumpow, 46
pW	disp, 47, 48
qpp::States, 328	dmat, 27
px0	dyn_col_vect, 27
qpp::States, 328	dyn_mat, 27
px1	dyn_row_vect, 27
qpp::States, 328	ee, 116
py0 qpp::States, 329	egcd, 49
	eig, 49
py1 qpp::States, 329	entanglement, 50
pz0	entropy, 51
gpp::States, 329	eps, 116
pz1	evals, 51
qpp::States, 329	evects, 52
4ppotatos, 020	expm, 52
QCircuitDescription	factors, 53
qpp::QCircuitDescription, 280	funm, 53
QFT	gcd, 54
qpp, 88	gconcurrence, 54
qpp::QCircuitDescription, 294	grams, 55, 56
QPP_UNUSED_	heig, 56
qpp.h, 382	hevals, 57
qcd_	hevects, 57
qpp::IQCircuit, 212	idx, 28
qpp::QCircuitDescription::iterator, 223	idx_infty, 116
qmutualinfo	infty, 116
qpp, 89	inverse, 57
qpp, 13	invperm, 58
absm, 28	ip, 58, 59
abssq, 29	isprime, 59
adjoint, 30	ket, 28
anticomm, 30	kraus2choi, 59
apply, 31–33	kraus2super, 60
applyCTRL, 33, 34	kron, 60–62
applyQFT, 35	kronpow, 62
applyTFQ, 35	lcm, 63
avg, 36	load, 64 loadMATLAB, 64, 65
bigint, 26	logdet, 66
bloch2rho, 36	-
bra, 26	logm, 66 lognegativity, 67
choi2kraus, 36	marginalX, 67
choi2super, 37	marginalY, 69
chop, 116 cmat, 26	maxn, 116
comm, 37	measure, 69–74
complement, 38	measure_seq, 74, 75
comperm, 38	mket, 75, 76
concurrence, 40	modiny, 76
conjugate, 40	modmul, 77
confraç2x, 40	modpow, 77
Continuous, 10	

mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 380
negativity, 80	QPP_UNUSED_, 382
norm, 81	qpp::Bit_circuit, 129
normalize, 81	Bit_circuit, 131
omega, 82	CNOT, 131
operator"" _i, 82	Dynamic_bitset, 132
pi, 117	FRED, 132
powm, 82	gate_count, 134
prj, 83	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
	FRED, 171
qmutualinfo, 89	
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	~Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	\sim Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset , 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110	size, 164
svdU, 110	storage_size, 164
svdV, 111	storage_size_, 165
syspermute, 111, 112	storage_type, 157
TFQ, 112	
	to_string, 164
to_void, 28	v_, 165
trace, 112	value_type, 157
transpose, 113	qpp::Gates, 172
tsallis, 113, 114	~Gates, 174
uniform, 114	CNOTba, 183

CNOT, 183	set_measured_, 211
CTRL, 175	subsys_, 213
CZ, 183	qpp::Init, 191
expandout, 175, 176	∼Init, 192
FRED, 183	Init, 192
Fd, 177	internal::Singleton< const Init >, 192
Gates, 174	qpp::NoiseBase
get_name, 178	\sim NoiseBase, 248
H, 183	compute_probs_, 248
ld, 178	compute_state_, 248
ld2, 184	d_, 251
internal::Singleton< const Gates >, 183	generated_, 251
MODMUL, 178	get_Ks, 249
Rn, 179	get_d, 249
RX, 179	get_last_idx, 249
RY, 180	get_last_K, 250
RZ, 180	get_last_p, 250
S, 184	get_probs, 250
SWAPd, 180	i_, 251
SWAP, 184	Ks_, 252
T, 184	noise_type, 247
TOF, 184	NoiseBase, 247
X, 184	operator(), 250, 251
Xd, 182	probs_, 252
Y, 185	qpp::NoiseBase< T >, 245
Z, 185	qpp::NoiseType, 252
Zd, 182	qpp::NoiseType::StateDependent, 321
qpp::IDisplay, 188	qpp::NoiseType::StateIndependent, 321
∼IDisplay, 190	qpp::QCircuit, 273
display, 190	IQCircuit, 274
IDisplay, 189	run, 274
operator<<, 191	qpp::QCircuitDescription, 275
operator=, 190	\sim QCircuitDescription, 281
qpp::IQCircuit, 204	begin, 281
\sim IQCircuit, 206	cCTRL_custom, 284
display, 207	cCTRL, 282, 283
dits_, 212	CTRL custom, 286
get_circuit_description, 207	CTRL, 284–286
get_dit, 207	cbegin, 281
get dits, 208	cend, 284
get ip, 208	const iterator, 279
get_iter, 208	d , 297
get_m_ip, 208	display, 287
get_measured, 209	end, 287
get_not_measured, 209	gate, 288, 289
get_probs, 209	gate_custom, 289
get_psi, 210	gate fan, 289, 290
get_q_ip, 210	GateType, 279
get_ref_psi, 210	gates_, 297
get_relative_pos_, 210	get_d, 290
IQCircuit, 206	get_gate_count, 290
it_, 212	get_gates, 291
probs_, 212	get_measured, 291
psi_, 212	get measurement count, 291
qcd_, 212	get_measurements, 292
reset, 211	get_name, 292
run, 211	get_nc, 292
set_dit, 211	get_non_measured, 292

get_nq, 293	qpp::QubitBitFlipNoise, 300
get_step_count, 293	QubitBitFlipNoise, 302
MeasureType, 280	qpp::QubitBitPhaseFlipNoise, 302
measured_, 298	QubitBitPhaseFlipNoise, 303
measurements_, 298	qpp::QubitDepolarizingNoise, 304
measureV, 293, 294	QubitDepolarizingNoise, 305
measureZ, 294	qpp::QubitPhaseDampingNoise, 305
name_, 298	QubitPhaseDampingNoise, 306
nc_, 298	qpp::QubitPhaseFlipNoise, 307
nq_, 298	QubitPhaseFlipNoise, 308
operator<<, 296, 297	qpp::QuditDepolarizingNoise, 310
QCircuitDescription, 280	fill_Ks_, 312
QFT, 294	fill_probs_, 312
step_types_, 298	QuditDepolarizingNoise, 311
StepType, 280	qpp::RandomDevices, 313
TFQ, 295	∼RandomDevices, 314
to_JSON, 295	get_prng, 315
qpp::QCircuitDescription::GateStep, 185	internal::Singleton< RandomDevices >, 316
ctrl_, 187	load, 315
gate_, 187	prng_, 316
gate_type_, 187	RandomDevices, 314
GateStep, 186	rd_, 316
name_, <mark>187</mark>	save, 315
target , 187	qpp::States, 321
qpp::QCircuitDescription::MeasureStep, 241	~States, 324
c_reg_, 242	b00, 326
mats_, 242	b01, 327
MeasureStep, 242	b10, 327
measurement_type_, 242	b11, 327
name_, 243	GHZ, 327
target_, 243	internal::Singleton< const States >, 326
qpp::QCircuitDescription::iterator, 218	jn, 324
difference_type, 220	mes, 324
elem_, 223	minus, 325
iterator, 220, 221	one, 325
iterator_category, 220	pGHZ, 328
operator!=, 221	pb00, 327
operator*, 221	pb01, 327
operator++, 221, 222	pb10, 328
operator=, 222	pb11, 328
operator==, 222	plus, 325
pointer, 220	pW, 328
qcd_, 223	px0, 328
reference, 220	px1, 328
set_begin_, 223	py0, 329
set_end_, 223	py1, 329
value type, 220	pz0, 329
qpp::QCircuitDescription::iterator::value_type_, 344	pz1, 329
display, 346	States, 324
gates_ip_, 346	W, 329
ip_, 346	x0, 329
measurements_ip_, 347	x1, 330
operator=, 346	y0, 330
type_, 347	y1, 330
value_type_, 345	z0, 330
value_type_qcd_, 347	z1, 330
qpp::QubitAmplitudeDampingNoise, 299	zero, 326
QubitAmplitudeDampingNoise, 200	qpp::Timer
addit impiliadobampingriolog, ooo	466

\sim Timer, 335	qpp::exception::MatrixNotSquareNorCvector, 233
display, 335	Exception, 234
end_, 337	type_description, 234
get_duration, 336	qpp::exception::MatrixNotSquareNorRvector, 235
operator=, 336	Exception, 236
start_, 337	type_description, 236
tic, 336	qpp::exception::MatrixNotSquareNorVector, 237
tics, 337	Exception, 238
Timer, 334, 335	type_description, 238
toc, 337	qpp::exception::MatrixNotVector, 239
qpp::Timer< T, CLOCK_T >, 333	Exception, 240
qpp::exception, 117	type_description, 240
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 243
CustomException, 138	Exception, 244
type_description, 139	type_description, 245
what_, 139	qpp::exception::NotBipartite, 253
qpp::exception::DimsInvalid, 140	Exception, 254
Exception, 141	type_description, 254
type_description, 141	qpp::exception::NotImplemented, 255
qpp::exception::DimsMismatchCvector, 142	Exception, 256
Exception, 143	type_description, 256
type_description, 143	qpp::exception::NotQubitCvector, 257
qpp::exception::DimsMismatchMatrix, 144	Exception, 258
Exception, 145	type_description, 258
type_description, 145	qpp::exception::NotQubitMatrix, 259
qpp::exception::DimsMismatchRvector, 146	Exception, 260
Exception, 147	type_description, 260
type_description, 147	qpp::exception::NotQubitRvector, 261
qpp::exception::DimsMismatchVector, 148	Exception, 262
Exception, 149	type_description, 262
type_description, 149	qpp::exception::NotQubitSubsys, 263
qpp::exception::DimsNotEqual, 150	Exception, 264
Exception, 151	type_description, 264
type_description, 151	qpp::exception::NotQubitVector, 265
qpp::exception::Duplicates, 153	Exception, 266
Exception, 154	type_description, 266
type_description, 154	qpp::exception::OutOfRange, 267
qpp::exception::Exception, 166	Exception, 268
Exception, 169	type_description, 268
msg_, 170	qpp::exception::PermInvalid, 269
type_description, 169	Exception, 270
what, 169	type_description, 270
where_, 170	qpp::exception::PermMismatchDims, 271
app::exception::InvalidIterator, 193	Exception, 272
Exception, 194	type_description, 272
type_description, 194	qpp::exception::QuditAlreadyMeasured, 308
qpp::exception::MatrixMismatchSubsys, 225	Exception, 309
Exception, 226	type_description, 310
type_description, 226	qpp::exception::SizeMismatch, 319
qpp::exception::MatrixNotCvector, 227	Exception, 320
Exception, 228	type_description, 320
type_description, 228	qpp::exception::SubsysMismatchDims, 331
qpp::exception::MatrixNotRvector, 229	Exception, 332
Exception, 230	type_description, 332
type_description, 230	qpp::exception::TypeMismatch, 338
qpp::exception::MatrixNotSquare, 231	Exception, 339
Exception, 232	type_description, 340
type_description, 232	qpp::exception::UndefinedType, 340

Exception, 341	operator=, 202
type_description, 342	separator_, 203
qpp::exception::Unknown, 342	start_, 203
Exception, 343	qpp::internal::IOManipRange< InputIterator >, 201
type_description, 344	qpp::internal::Singleton
qpp::exception::ZeroSize, 348	\sim Singleton, 318
Exception, 349	get_instance, 318
type_description, 349	get_thread_local_instance, 318
qpp::experimental, 119	operator=, 318
qpp::internal, 119	Singleton, 317, 318
check_cvector, 120	qpp::internal::Singleton $<$ T $>$, 316
check_dims, 120	qpp::is_complex< std::complex< T >>, 214
check_dims_match_cvect, 120	qpp::is_complex< T >, 213
check_dims_match_mat, 121	<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T</pre>
check_dims_match_rvect, 121	$>$ ().begin()), decltype(std::declval $<$ T $>$ (). \leftarrow
check_eq_dims, 121	end()), decltype(*(std::declval $<$ T $>$ (). \leftarrow
check_matching_sizes, 121	begin()))>>, 216
check_no_duplicates, 121	qpp::is_iterable< T, typename >, 215
check_nonzero_size, 121	qpp::is_matrix_expression< Derived >, 217
check_perm, 122	qpp::literals, 125
check_qubit_cvector, 122	operator"" _bra, 125
check_qubit_matrix, 122	operator"" _i, 125
check_qubit_rvector, 122	operator"" _ket, 126
check_qubit_vector, 122	operator"" _prj, 126
check_rvector, 122	qpp::make_void
check_square_mat, 123	type, 224
check_subsys_match_dims, 123	qpp::make_void $<$ Ts $>$, 224
check_vector, 123	QubitAmplitudeDampingNoise
dirsum2, 123	qpp::QubitAmplitudeDampingNoise, 300
get_dim_subsys, 123	QubitBitFlipNoise
get_num_subsys, 123	qpp::QubitBitFlipNoise, 302
kron2, 124	QubitBitPhaseFlipNoise
multiidx2n, 124	qpp::QubitBitPhaseFlipNoise, 303
n2multiidx, 124	QubitDepolarizingNoise
variadic_vector_emplace, 124	qpp::QubitDepolarizingNoise, 305
qpp::internal::Display_Impl_, 152	QubitPhaseDampingNoise
display_impl_, 152	qpp::QubitPhaseDampingNoise, 306
qpp::internal::IOManipEigen, 195	QubitPhaseFlipNoise
A_, 196	qpp::QubitPhaseFlipNoise, 308
chop_, 197	QuditDepolarizingNoise
display, 196	qpp::QuditDepolarizingNoise, 311
IOManipEigen, 196	rand
qpp::internal::IOManipPointer	rand
display, 199	qpp, 90–92
end_, 199	qpp::Dynamic_bitset, 162, 163 randH
IOManipPointer, 198, 199	
N , 200	qpp, 92 randidx
operator=, 199	
p_, 200	qpp, 93 randket
separator_, 200	
start_, 200	qpp, 93 randkraus
qpp::internal::IOManipPointer< PointerType >, 197	
qpp::internal::IOManipRange	qpp, 93 randn
display, 202	qpp, 94, 95
end_, 203	qpp, 94, 95 random.h, 382
first_, 203	RandomDevices
IOManipRange, 202	
· -	qpp::RandomDevices, 314
last_, 203	randperm

qpp, 96	qpp, 104, 105
randprime	schmidtprobs
qpp, 96	qpp, 105, 106
randprob	separator_
qpp, 97	qpp::internal::IOManipPointer, 200
randrho	qpp::internal::IOManipRange, 203
qpp, 97	set
randU	qpp::Dynamic_bitset, 163, 164
qpp, 97 randV	set_begin_
	qpp::QCircuitDescription::iterator, 223
qpp, 98 rd_	set_dit
	qpp::IQCircuit, 211
qpp::RandomDevices, 316 reference	set_end_
qpp::QCircuitDescription::iterator, 220	qpp::QCircuitDescription::iterator, 223
renyi	set_measured_
qpp, 98, 99	qpp::IQCircuit, 211
reset	sigma
qpp::Bit_circuit, 132	qpp, 106
qpp::Dynamic_bitset, 163	Singleton qpp::internal::Singleton, 317, 318
qpp::IQCircuit, 211	sinm
reshape	qpp, 107
qpp, 99	size
rho2bloch	qpp::Dynamic_bitset, 164
qpp, 100	spectralpowm
rho2pure	qpp, 107
qpp, 100	sqrtm
Rn	qpp, 108
qpp::Gates, 179	start
run	qpp::Timer, 337
qpp::IQCircuit, 211	qpp::internal::IOManipPointer, 200
qpp::QCircuit, 274	qpp::internal::IOManipRange, 203
RX	States
qpp::Gates, 179	qpp::States, 324
RY	statistics.h, 384
qpp::Gates, 180	step_types_
RZ	qpp::QCircuitDescription, 298
qpp::Gates, 180	StepType
S	qpp::QCircuitDescription, 280
qpp::Gates, 184	storage_size
SWAPd	qpp::Dynamic_bitset, 164
qpp::Gates, 180	storage_size_
SWAP	qpp::Dynamic_bitset, 165
qpp::Bit_circuit, 133	storage_type
qpp::Bit_circuit::Gate_count, 171	qpp::Dynamic_bitset, 157
qpp::Gates, 184	subsys_
save	qpp::IQCircuit, 213
qpp, 101	sum
qpp::RandomDevices, 315	qpp, 108, 109
saveMATLAB	super2choi
qpp, 101, 102	qpp, 109
schatten	svals
qpp, 102	qpp, 110
schmidtA	svd
qpp, 103	qpp, 110
schmidtB	svdU
qpp, 103, 104	qpp, 110
schmidtcoeffs	svdV

qpp, 111	qpp::exception::MatrixNotSquareNorCvector, 234
syspermute	qpp::exception::MatrixNotSquareNorRvector, 236
qpp, 111, 112	qpp::exception::MatrixNotSquareNorVector, 238
Т	qpp::exception::MatrixNotVector, 240
	qpp::exception::NoCodeword, 245
qpp::Gates, 184 TFQ	qpp::exception::NotBipartite, 254
qpp, 112	qpp::exception::NotImplemented, 256
qpp::QCircuitDescription, 295	qpp::exception::NotQubitCvector, 258
TOF	qpp::exception::NotQubitMatrix, 260
qpp::Bit_circuit, 133	qpp::exception::NotQubitRvector, 262
qpp::Bit_circuit::Gate_count, 171	<pre>qpp::exception::NotQubitSubsys, 264 qpp::exception::NotQubitVector, 266</pre>
qpp::Gates, 184	app::exception::OutOfRange, 268
target_	qpp::exception::PermInvalid, 270
qpp::QCircuitDescription::GateStep, 187	qpp::exception::PermMismatchDims, 272
qpp::QCircuitDescription::MeasureStep, 243	qpp::exception::QuditAlreadyMeasured, 310
tic	qpp::exception::SizeMismatch, 320
qpp::Timer, 336	qpp::exception::SubsysMismatchDims, 332
tics	qpp::exception::TypeMismatch, 340
qpp::Timer, 337	qpp::exception::UndefinedType, 342
Timer	qpp::exception::Unknown, 344
qpp::Timer, 334, 335	qpp::exception::ZeroSize, 349
to_JSON	types.h, 386
qpp::QCircuitDescription, 295	
to_string	uniform
qpp::Dynamic_bitset, 164	qpp, 114
to_void	
qpp, 28	V
toc	qpp::Dynamic_bitset, 165
qpp::Timer, 337	value_type
trace	qpp::Dynamic_bitset, 157
qpp, 112	qpp::QCircuitDescription::iterator, 220
traits.h, 385	value_type_
transpose qpp, 113	qpp::QCircuitDescription::iterator::value_type_←
tsallis	, 345
qpp, 113, 114	value_type_qcd_ qpp::QCircuitDescription::iterator::value_type_←
Type	, 347
qpp::Codes, 135	var
type	qpp, 115
qpp::make_void, 224	variadic_vector_emplace
type_	qpp::internal, 124
qpp::QCircuitDescription::iterator::value_type_←	apptoa., 121
, 347	W
type_description	qpp::States, 329
qpp::exception::CustomException, 139	what
qpp::exception::DimsInvalid, 141	qpp::exception::Exception, 169
qpp::exception::DimsMismatchCvector, 143	what_
qpp::exception::DimsMismatchMatrix, 145	qpp::exception::CustomException, 139
qpp::exception::DimsMismatchRvector, 147	where_
qpp::exception::DimsMismatchVector, 149	qpp::exception::Exception, 170
qpp::exception::DimsNotEqual, 151	
qpp::exception::Duplicates, 154	X
qpp::exception::Exception, 169	qpp::Bit_circuit, 133
qpp::exception::InvalidIterator, 194	qpp::Bit_circuit::Gate_count, 171
qpp::exception::MatrixMismatchSubsys, 226	qpp::Gates, 184
qpp::exception::MatrixNotCvector, 228	x0
qpp::exception::MatrixNotRvector, 230	qpp::States, 329
qpp::exception::MatrixNotSquare, 232	x1

```
qpp::States, 330
x2contfrac
     qpp, 115
Χd
     qpp::Gates, 182
Υ
     qpp::Gates, 185
y0
     qpp::States, 330
у1
     qpp::States, 330
Ζ
     qpp::Gates, 185
z0
     qpp::States, 330
z1
     qpp::States, 330
\operatorname{\mathsf{Zd}}
     qpp::Gates, 182
zero
     qpp::States, 326
```