Quantum++ v1.3

Generated by Doxygen 1.8.13

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 	 	 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 	 	 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 	 	 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	feren	ice .		 	 	 	 		 	 	 	 	 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 	 	 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 	 	 26
			6.1.2.1	bi	gint			 	 	 	 		 	 	 	 	 26
			6.1.2.2	br	ra .			 	 	 	 		 	 	 	 	 27
			6.1.2.3	cr	mat			 	 	 	 		 	 	 	 	 27
			6.1.2.4	cp	olx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dr	mat			 	 	 	 		 	 	 	 	 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 	 	 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 	 	 28
			6.1.2.8	d١	vn ro	ow v	ect	 	 	 	 		 	 	 	 	 28

ii CONTENTS

	6.1.2.9	idx	 28
	6.1.2.10	ket	 28
	6.1.2.11	to_void	 28
6.1.3	Enumera	ation Type Documentation	 28
	6.1.3.1	anonymous enum	 28
6.1.4	Function	Documentation	 29
	6.1.4.1	absm()	 29
	6.1.4.2	abssq() [1/3]	 29
	6.1.4.3	abssq() [2/3]	 30
	6.1.4.4	abssq() [3/3]	 30
	6.1.4.5	adjoint()	 30
	6.1.4.6	anticomm()	 31
	6.1.4.7	apply() [1/5]	 31
	6.1.4.8	apply() [2/5]	 32
	6.1.4.9	apply() [3/5]	 32
	6.1.4.10	apply() [4/5]	 33
	6.1.4.11	apply() [5/5]	 33
	6.1.4.12	applyCTRL() [1/2]	 34
	6.1.4.13	applyCTRL() [2/2]	 34
	6.1.4.14	applyQFT()	 35
	6.1.4.15	applyTFQ()	 35
	6.1.4.16	avg()	 36
	6.1.4.17	bloch2rho()	 36
	6.1.4.18	choi2kraus()	 37
	6.1.4.19	choi2super()	 37
	6.1.4.20	comm()	 38
	6.1.4.21	complement()	 38
	6.1.4.22	compperm()	 39
	6.1.4.23	concurrence()	 39
	6.1.4.24	conjugate()	 39

6.1.4.25	contfrac2x()	40
6.1.4.26	convergents() [1/2]	40
6.1.4.27	convergents() [2/2]	41
6.1.4.28	cor()	41
6.1.4.29	cosm()	42
6.1.4.30	cov()	42
6.1.4.31	cwise()	43
6.1.4.32	det()	43
6.1.4.33	dirsum() [1/4]	43
6.1.4.34	dirsum() [2/4]	44
6.1.4.35	dirsum() [3/4]	44
6.1.4.36	dirsum() [4/4]	45
6.1.4.37	dirsumpow()	45
6.1.4.38	disp() [1/5]	46
6.1.4.39	disp() [2/5]	46
6.1.4.40	disp() [3/5]	47
6.1.4.41	disp() [4/5]	47
6.1.4.42	disp() [5/5]	48
6.1.4.43	egcd()	48
6.1.4.44	eig()	49
6.1.4.45	entanglement() [1/2]	49
6.1.4.46	entanglement() [2/2]	50
6.1.4.47	entropy() [1/2]	50
6.1.4.48	entropy() [2/2]	51
6.1.4.49	evals()	51
6.1.4.50	evects()	51
6.1.4.51	expm()	52
6.1.4.52	factors()	52
6.1.4.53	funm()	53
6.1.4.54	gcd() [1/2]	53

iv CONTENTS

6.1.4.55	gcd() [2/2]	53
6.1.4.56	gconcurrence()	54
6.1.4.57	grams() [1/3]	54
6.1.4.58	grams() [2/3]	55
6.1.4.59	grams() [3/3]	55
6.1.4.60	hash_eigen()	56
6.1.4.61	heig()	56
6.1.4.62	hevals()	57
6.1.4.63	hevects()	57
6.1.4.64	inverse()	57
6.1.4.65	invperm()	58
6.1.4.66	ip() [1/2]	58
6.1.4.67	ip() [2/2]	59
6.1.4.68	isprime()	59
6.1.4.69	kraus2choi()	59
6.1.4.70	kraus2super()	60
6.1.4.71	kron() [1/4]	60
6.1.4.72	kron() [2/4]	62
6.1.4.73	kron() [3/4]	62
6.1.4.74	kron() [4/4]	63
6.1.4.75	kronpow()	63
6.1.4.76	lcm() [1/2]	64
6.1.4.77	lcm() [2/2]	64
6.1.4.78	load()	65
6.1.4.79	loadMATLAB() [1/2]	65
6.1.4.80	loadMATLAB() [2/2]	66
6.1.4.81	logdet()	67
6.1.4.82	logm()	67
6.1.4.83	lognegativity() [1/2]	67
6.1.4.84	lognegativity() [2/2]	69

6.1.4.85 marginalX()	69
6.1.4.86 marginalY()	70
6.1.4.87 measure() [1/9]	70
6.1.4.88 measure() [2/9]	70
6.1.4.89 measure() [3/9]	71
6.1.4.90 measure() [4/9]	71
6.1.4.91 measure() [5/9]	72
6.1.4.92 measure() [6/9]	73
6.1.4.93 measure() [7/9]	73
6.1.4.94 measure() [8/9]	74
6.1.4.95 measure() [9/9]	75
6.1.4.96 measure_seq() [1/2]	75
6.1.4.97 measure_seq() [2/2]	76
6.1.4.98 mket() [1/2]	76
6.1.4.99 mket() [2/2]	77
6.1.4.100 modinv()	77
6.1.4.101 modmul()	78
6.1.4.102 modpow()	78
6.1.4.103 mprj() [1/2]	79
6.1.4.104 mprj() [2/2]	79
6.1.4.105 multiidx2n()	80
6.1.4.106 n2multiidx()	80
6.1.4.107 negativity() [1/2]	81
6.1.4.108 negativity() [2/2]	81
6.1.4.109 norm()	82
6.1.4.110 normalize()	82
6.1.4.111 omega()	82
6.1.4.112 powm()	83
6.1.4.113 prj()	83
6.1.4.114 prod() [1/3]	84

vi

6.1.4.115 prod() [2/3]	34
6.1.4.116 prod() [3/3]	34
6.1.4.117 ptrace() [1/2] 8	35
6.1.4.118 ptrace() [2/2] 8	35
6.1.4.119 ptrace1() [1/2] 8	36
6.1.4.120 ptrace1() [2/2] 8	36
6.1.4.121 ptrace2() [1/2] 8	37
6.1.4.122 ptrace2() [2/2] 8	38
6.1.4.123 ptranspose() [1/2]	38
6.1.4.124 ptranspose() [2/2]	39
6.1.4.125 QFT()	39
6.1.4.126 qmutualinfo() [1/2]	39
6.1.4.127 qmutualinfo() [2/2] 9	90
6.1.4.128 rand() [1/5]	90
6.1.4.129 rand() [2/5] 9	91
6.1.4.130 rand() [3/5] 9	91
6.1.4.131 rand() [4/5]	92
6.1.4.132 rand() [5/5] 9	92
6.1.4.133 randH()	93
6.1.4.134 randidx()	93
6.1.4.135 randket()	94
6.1.4.136 randkraus()	94
6.1.4.137 randn() [1/4] 9	94
6.1.4.138 randn() [2/4] 9	95
6.1.4.139 randn() [3/4] 9	95
6.1.4.140 randn() [4/4] 9	96
6.1.4.141 randperm()	96
6.1.4.142 randprime()	97
6.1.4.143 randprob()	97
6.1.4.144 randrho()	97

CONTENTS vii

6.1.4.145 randU()
6.1.4.146 randV()
6.1.4.147 renyi() [1/2]
6.1.4.148 renyi() [2/2]
6.1.4.149 reshape()
6.1.4.150 rho2bloch()
6.1.4.151 rho2pure()
6.1.4.152 save()
6.1.4.153 saveMATLAB() [1/2]
6.1.4.154 saveMATLAB() [2/2]
6.1.4.155 schatten()
6.1.4.156 schmidtA() [1/2]
6.1.4.157 schmidtA() [2/2]
6.1.4.158 schmidtB() [1/2]
6.1.4.159 schmidtB() [2/2]
6.1.4.160 schmidtcoeffs() [1/2]
6.1.4.161 schmidtcoeffs() [2/2]
6.1.4.162 schmidtprobs() [1/2]
6.1.4.163 schmidtprobs() [2/2]
6.1.4.164 sigma()
6.1.4.165 sinm()
6.1.4.166 spectralpowm()
6.1.4.167 sqrtm()
6.1.4.168 sum() [1/3]
6.1.4.169 sum() [2/3]
6.1.4.170 sum() [3/3]
6.1.4.171 super2choi()
6.1.4.172 svals()
6.1.4.173 svd()
6.1.4.174 svdU()

viii CONTENTS

		6.1.4.175	5 svdV()	 111
		6.1.4.176	6 syspermute() [1/2]	 112
		6.1.4.177	7 syspermute() [2/2]	 112
		6.1.4.178	8 TFQ()	 113
		6.1.4.179	9 trace()	 113
		6.1.4.180	0 transpose()	 113
		6.1.4.181	11 tsallis() [1/2]	 114
		6.1.4.182	2 tsallis() [2/2]	 114
		6.1.4.183	3 uniform()	 115
		6.1.4.184	4 var()	 115
		6.1.4.185	5 x2contfrac()	 116
	6.1.5	Variable	Documentation	 116
		6.1.5.1	chop	 116
		6.1.5.2	ee	 116
		6.1.5.3	infty	 116
		6.1.5.4	maxn	 117
		6.1.5.5	pi	 117
6.2	qpp::ex	ception N	Namespace Reference	 117
	6.2.1	Detailed	Description	 118
6.3	qpp::ex	kperimenta	al Namespace Reference	 119
	6.3.1	Detailed	Description	 119
6.4	qpp::in	ternal Nar	mespace Reference	 119
	6.4.1	Detailed	Description	 120
	6.4.2	Function	Documentation	 120
		6.4.2.1	abs_chop() [1/2]	 120
		6.4.2.2	abs_chop() [2/2]	 121
		6.4.2.3	check_cvector()	 121
		6.4.2.4	check_dims()	 121
		6.4.2.5	check_dims_match_cvect()	 121
		6.4.2.6	check_dims_match_mat()	 121

		6.4.2.7	check_dims_match_rvect()	121
		6.4.2.8	check_eq_dims()	122
		6.4.2.9	check_matching_sizes()	122
		6.4.2.10	check_no_duplicates()	122
		6.4.2.11	check_nonzero_size()	122
		6.4.2.12	check_perm()	122
		6.4.2.13	check_qubit_cvector()	122
		6.4.2.14	check_qubit_matrix()	123
		6.4.2.15	check_qubit_rvector()	123
		6.4.2.16	check_qubit_vector()	123
		6.4.2.17	check_rvector()	123
		6.4.2.18	check_square_mat()	123
		6.4.2.19	check_subsys_match_dims()	123
		6.4.2.20	check_vector()	124
		6.4.2.21	dirsum2()	124
		6.4.2.22	get_dim_subsys()	124
		6.4.2.23	get_num_subsys()	124
		6.4.2.24	hash_combine()	124
		6.4.2.25	kron2()	125
		6.4.2.26	multiidx2n()	125
		6.4.2.27	n2multiidx()	125
		6.4.2.28	variadic_vector_emplace() [1/2]	125
		6.4.2.29	variadic_vector_emplace() [2/2]	125
6.5	qpp::lit	erals Nam	espace Reference	126
	6.5.1	Function	Documentation	126
		6.5.1.1	operator""""_bra()	126
		6.5.1.2	operator""""_i() [1/2]	127
		6.5.1.3	operator""""_i() [2/2]	127
		6.5.1.4	operator""""_if() [1/2]	127
		6.5.1.5	operator""""_if() [2/2]	127
		6.5.1.6	operator""""_ket()	127
		6.5.1.7	operator"""" _prj()	128

7	Clas	s Docu	mentation	129
	7.1	qpp::B	t_circuit Class Reference	. 129
		7.1.1	Detailed Description	. 131
		7.1.2	Constructor & Destructor Documentation	. 131
			7.1.2.1 Bit_circuit() [1/2]	. 131
			7.1.2.2 Bit_circuit() [2/2]	. 131
			7.1.2.3 ~Bit_circuit()	. 132
		7.1.3	Member Function Documentation	. 132
			7.1.3.1 CNOT()	. 132
			7.1.3.2 FRED()	. 132
			7.1.3.3 get_gate_count()	. 133
			7.1.3.4 get_gate_depth()	. 133
			7.1.3.5 NOT()	. 134
			7.1.3.6 reset()	. 134
			7.1.3.7 SWAP()	. 134
			7.1.3.8 TOF()	. 135
			7.1.3.9 X()	. 135
		7.1.4	Member Data Documentation	. 136
			7.1.4.1 bCNOT	. 136
			7.1.4.2 bFRED	. 136
			7.1.4.3 bNOT	. 136
			7.1.4.4 bSWAP	. 136
			7.1.4.5 bTOF	. 136
			7.1.4.6 btotal	. 136
			7.1.4.7 count	. 137
			7.1.4.8 depth	. 137
	7.2	qpp::C	odes Class Reference	. 137
		7.2.1	Detailed Description	. 138
		7.2.2	Member Enumeration Documentation	. 138
			7.2.2.1 Type	. 138

CONTENTS xi

	7.2.3	Constructor & Destructor Documentation
		7.2.3.1 Codes()
		7.2.3.2 ~Codes()
	7.2.4	Member Function Documentation
		7.2.4.1 codeword()
	7.2.5	Friends And Related Function Documentation
		7.2.5.1 internal::Singleton < const Codes >
7.3	qpp::ex	xception::CustomException Class Reference
	7.3.1	Detailed Description
	7.3.2	Constructor & Destructor Documentation
		7.3.2.1 CustomException()
	7.3.3	Member Function Documentation
		7.3.3.1 description()
	7.3.4	Member Data Documentation
		7.3.4.1 what
7.4	qpp::ex	cception::DimsInvalid Class Reference
	7.4.1	Detailed Description
	7.4.2	Member Function Documentation
		7.4.2.1 description()
7.5	qpp::ex	cception::DimsMismatchCvector Class Reference
	7.5.1	Detailed Description
	7.5.2	Member Function Documentation
		7.5.2.1 description()
7.6	qpp::ex	cception::DimsMismatchMatrix Class Reference
	7.6.1	Detailed Description
	7.6.2	Member Function Documentation
		7.6.2.1 description()
7.7	qpp::ex	cception::DimsMismatchRvector Class Reference
	7.7.1	Detailed Description
	7.7.2	Member Function Documentation

xii CONTENTS

		7.7.2.1 description()	50
7.8	qpp::ex	ception::DimsMismatchVector Class Reference	50
	7.8.1	Detailed Description	51
	7.8.2	Member Function Documentation	51
		7.8.2.1 description()	52
7.9	qpp::ex	ception::DimsNotEqual Class Reference	52
	7.9.1	Detailed Description	53
	7.9.2	Member Function Documentation	53
		7.9.2.1 description()	53
7.10	qpp::in	ernal::Display_Impl_ Struct Reference	54
	7.10.1	Member Function Documentation	54
		7.10.1.1 display_impl_()	54
7.11	qpp::ex	ception::Duplicates Class Reference	55
	7.11.1	Detailed Description	56
	7.11.2	Member Function Documentation	56
		7.11.2.1 description()	56
7.12	qpp::D	namic_bitset Class Reference	56
	7.12.1	Detailed Description	58
	7.12.2	Member Typedef Documentation	59
		7.12.2.1 storage_type	59
		7.12.2.2 value_type	59
	7.12.3	Constructor & Destructor Documentation	59
		7.12.3.1 Dynamic_bitset()	59
		7.12.3.2 ~Dynamic_bitset()	59
	7.12.4	Member Function Documentation	59
		7.12.4.1 all()	30
		7.12.4.2 any()	30
		7.12.4.3 count()	30
		7.12.4.4 data()	30
		7.12.4.5 display()	30

CONTENTS xiii

		7.12.4.6 flip() [1/2]	61
		7.12.4.7 flip() [2/2]	61
		7.12.4.8 get()	61
		7.12.4.9 index_()	62
		7.12.4.10 none()	62
		7.12.4.11 offset_()	62
		7.12.4.12 operator"!=()	63
		7.12.4.13 operator-()	63
		7.12.4.14 operator==()	63
		7.12.4.15 rand() [1/2]	65
		7.12.4.16 rand() [2/2]	65
		7.12.4.17 reset() [1/2]	66
		7.12.4.18 reset() [2/2]	66
		7.12.4.19 set() [1/2]	66
		7.12.4.20 set() [2/2]	67
		7.12.4.21 size()	67
		7.12.4.22 storage_size()	67
		7.12.4.23 to_string()	67
	7.12.5	Member Data Documentation	68
		7.12.5.1 n	68
		7.12.5.2 storage_size	68
		7.12.5.3 v	68
7.13	qpp::int	ternal::EqualEigen Class Reference	68
	7.13.1	Detailed Description	69
	7.13.2	Member Function Documentation	69
		7.13.2.1 operator()()	69
7.14	qpp::ex	ception::Exception Class Reference	69
	7.14.1	Detailed Description	71
	7.14.2	Constructor & Destructor Documentation	72
		7.14.2.1 Exception()	72

xiv CONTENTS

	7.14.3	Member Function Documentation
		7.14.3.1 description()
		7.14.3.2 what()
	7.14.4	Member Data Documentation
		7.14.4.1 msg
		7.14.4.2 where
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >
	7.15.5	Member Data Documentation

CONTENTS xv

		7.15.5.1 CNOT	85
		7.15.5.2 CNOTba	85
		7.15.5.3 CZ	85
		7.15.5.4 FRED	85
		7.15.5.5 H	86
		7.15.5.6 ld2	86
		7.15.5.7 S	86
		7.15.5.8 SWAP	86
		7.15.5.9 T	86
		7.15.5.10 TOF	86
		7.15.5.11 X	87
		7.15.5.12 Y	87
		7.15.5.13 Z	87
7.16	qpp::Q	Circuit::GateStep Struct Reference	87
	7.16.1	Detailed Description	88
	7.16.2	Constructor & Destructor Documentation	88
		7.16.2.1 GateStep() [1/2]	88
		7.16.2.2 GateStep() [2/2]	88
	7.16.3	Member Data Documentation	89
		7.16.3.1 ctrl	89
		7.16.3.2 gate_hash	89
		7.16.3.3 gate_type	89
		7.16.3.4 name	89
		7.16.3.5 target	90
7.17	qpp::int	ternal::HashEigen Class Reference	90
	7.17.1	Detailed Description	90
	7.17.2	Member Function Documentation	90
		7.17.2.1 operator()()	90
7.18	qpp::ID	Display Class Reference	91
	7.18.1	Detailed Description	92

xvi CONTENTS

	7.18.2	Constructor & Destructor Documentation	192
		7.18.2.1 ~IDisplay()	192
	7.18.3	Member Function Documentation	192
		7.18.3.1 display()	192
	7.18.4	Friends And Related Function Documentation	192
		7.18.4.1 operator<<	192
7.19	qpp::lJ	SON Class Reference	193
	7.19.1	Detailed Description	193
	7.19.2	Constructor & Destructor Documentation	193
		7.19.2.1 ~IJSON()	193
	7.19.3	Member Function Documentation	194
		7.19.3.1 to_JSON()	194
7.20	qpp::ln	it Class Reference	194
	7.20.1	Detailed Description	195
	7.20.2	Constructor & Destructor Documentation	195
		7.20.2.1 Init()	195
		7.20.2.2 ~Init()	196
	7.20.3	Friends And Related Function Documentation	196
		7.20.3.1 internal::Singleton < const Init >	196
7.21	qpp::ex	ception::InvalidIterator Class Reference	196
	7.21.1	Detailed Description	197
	7.21.2	Member Function Documentation	197
		7.21.2.1 description()	197
7.22	qpp::in	ternal::IOManipEigen Class Reference	198
	7.22.1	Constructor & Destructor Documentation	199
		7.22.1.1 IOManipEigen() [1/2]	199
		7.22.1.2 IOManipEigen() [2/2]	199
	7.22.2	Member Function Documentation	199
		7.22.2.1 display()	199
	7.22.3	Member Data Documentation	199

CONTENTS xvii

	7.22.3.1 A
	7.22.3.2 chop
7.23 qpp::in	nternal::IOManipPointer< PointerType > Class Template Reference
7.23.1	Constructor & Destructor Documentation
	7.23.1.1 IOManipPointer() [1/2]
	7.23.1.2 IOManipPointer() [2/2]
7.23.2	Member Function Documentation
	7.23.2.1 display()
	7.23.2.2 operator=()
7.23.3	Member Data Documentation
	7.23.3.1 chop
	7.23.3.2 end
	7.23.3.3 N
	7.23.3.4 p
	7.23.3.5 separator
	7.23.3.6 start
7.24 qpp::in	nternal::IOManipRange< InputIterator > Class Template Reference
7.24.1	Constructor & Destructor Documentation
	7.24.1.1 IOManipRange() [1/2]
	7.24.1.2 IOManipRange() [2/2]
7.24.2	Member Function Documentation
	7.24.2.1 display()
	7.24.2.2 operator=()
7.24.3	Member Data Documentation
	7.24.3.1 chop
	7.24.3.2 end
	7.24.3.3 first
	7.24.3.4 last
	7.24.3.5 separator
	7.24.3.6 start

xviii CONTENTS

7.25	qpp::is_	_complex< T > Struct Template Reference	07
	7.25.1	Detailed Description	80
7.26	qpp::is_	_complex< std::complex< T > > Struct Template Reference	80
	7.26.1	Detailed Description	09
7.27	qpp::is_	_iterable < T, typename > Struct Template Reference	09
	7.27.1	Detailed Description	10
7.28			10
	7.28.1	Detailed Description	11
7.29	qpp::is_	_matrix_expression< Derived > Struct Template Reference	12
	7.29.1	Detailed Description	12
7.30	qpp::Q	Circuit::iterator Class Reference	13
	7.30.1	Detailed Description	14
	7.30.2	Member Typedef Documentation	14
		7.30.2.1 difference_type	14
		7.30.2.2 iterator_category	14
		7.30.2.3 pointer	15
		7.30.2.4 reference	15
		7.30.2.5 value_type	15
	7.30.3	Constructor & Destructor Documentation	15
		7.30.3.1 iterator() [1/2]	15
		7.30.3.2 iterator() [2/2]	15
	7.30.4	Member Function Documentation	15
		7.30.4.1 operator"!=()	15
		7.30.4.2 operator*()	16
		7.30.4.3 operator++() [1/2]	16
		7.30.4.4 operator++() [2/2]	16
		7.30.4.5 operator=()	17
		7.30.4.6 operator==()	17
		7.30.4.7 set_begin_()	17
		7.30.4.8 set_end_()	17

CONTENTS xix

	7.30.5	Member Data Documentation	218
		7.30.5.1 elem	218
		7.30.5.2 qc	218
7.31	qpp::ma	ake_void < Ts > Struct Template Reference	218
	7.31.1	Detailed Description	218
	7.31.2	Member Typedef Documentation	219
		7.31.2.1 type	219
7.32	qpp::ex	cception::MatrixMismatchSubsys Class Reference	219
	7.32.1	Detailed Description	220
	7.32.2	Member Function Documentation	220
		7.32.2.1 description()	221
7.33	qpp::ex	cception::MatrixNotCvector Class Reference	221
	7.33.1	Detailed Description	222
	7.33.2	Member Function Documentation	222
		7.33.2.1 description()	223
7.34	qpp::ex	cception::MatrixNotRvector Class Reference	223
	7.34.1	Detailed Description	224
	7.34.2	Member Function Documentation	224
		7.34.2.1 description()	225
7.35	qpp::ex	cception::MatrixNotSquare Class Reference	225
	7.35.1	Detailed Description	226
	7.35.2	Member Function Documentation	226
		7.35.2.1 description()	227
7.36	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	227
	7.36.1	Detailed Description	228
	7.36.2	Member Function Documentation	228
		7.36.2.1 description()	229
7.37	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	229
	7.37.1	Detailed Description	230
	7.37.2	Member Function Documentation	230

		7.37.2.1 description()	31
7.38	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	31
	7.38.1	Detailed Description	32
	7.38.2	Member Function Documentation	32
		7.38.2.1 description()	33
7.39	qpp::ex	cception::MatrixNotVector Class Reference	33
	7.39.1	Detailed Description	34
	7.39.2	Member Function Documentation	34
		7.39.2.1 description()	35
7.40	qpp::Q	Circuit::MeasureStep Struct Reference	35
	7.40.1	Detailed Description	36
	7.40.2	Constructor & Destructor Documentation	36
		7.40.2.1 MeasureStep() [1/2]	36
		7.40.2.2 MeasureStep() [2/2]	36
	7.40.3	Member Data Documentation	37
		7.40.3.1 c_reg	37
		7.40.3.2 mats_hash	37
		7.40.3.3 measurement_type	37
		7.40.3.4 name	37
		7.40.3.5 target	37
7.41	qpp::ex	cception::NoCodeword Class Reference	38
	7.41.1	Detailed Description	39
	7.41.2	Member Function Documentation	39
		7.41.2.1 description()	39
7.42	qpp::No	oiseBase < T > Class Template Reference	39
	7.42.1	Detailed Description	41
	7.42.2	Member Typedef Documentation	41
		7.42.2.1 noise_type	41
	7.42.3	Constructor & Destructor Documentation	41
		7.42.3.1 NoiseBase() [1/2]	41

CONTENTS xxi

		7.42.3.2 NoiseBase() [2/2]	242
		7.42.3.3 ~NoiseBase()	242
	7.42.4	Member Function Documentation	242
		7.42.4.1 compute_probs_()	242
		7.42.4.2 compute_state_()	243
		7.42.4.3 get_d()	243
		7.42.4.4 get_Ks()	243
		7.42.4.5 get_last_idx()	244
		7.42.4.6 get_last_K()	244
		7.42.4.7 get_last_p()	244
		7.42.4.8 get_probs()	244
		7.42.4.9 operator()() [1/3]	244
		7.42.4.10 operator()() [2/3]	245
		7.42.4.11 operator()() [3/3]	245
	7.42.5	Member Data Documentation	246
		7.42.5.1 d	246
		7.42.5.2 generated	246
		7.42.5.3 i	246
		7.42.5.4 Ks	246
		7.42.5.5 probs	247
7.43	qpp::No	oiseType Class Reference	247
	7.43.1	Detailed Description	247
7.44	qpp::ex	cception::NotBipartite Class Reference	247
	7.44.1	Detailed Description	249
	7.44.2	Member Function Documentation	249
		7.44.2.1 description()	249
7.45	qpp::ex	cception::NotImplemented Class Reference	249
	7.45.1	Detailed Description	250
	7.45.2	Member Function Documentation	250
		7.45.2.1 description()	250

xxii CONTENTS

7.46	qpp::ex	cception::NotQubitCvector Class Reference	251
	7.46.1	Detailed Description	252
	7.46.2	Member Function Documentation	252
		7.46.2.1 description()	252
7.47	qpp::ex	cception::NotQubitMatrix Class Reference	252
	7.47.1	Detailed Description	254
	7.47.2	Member Function Documentation	254
		7.47.2.1 description()	254
7.48	qpp::ex	cception::NotQubitRvector Class Reference	254
	7.48.1	Detailed Description	255
	7.48.2	Member Function Documentation	255
		7.48.2.1 description()	256
7.49	qpp::ex	cception::NotQubitSubsys Class Reference	256
	7.49.1	Detailed Description	257
	7.49.2	Member Function Documentation	257
		7.49.2.1 description()	258
7.50	qpp::ex	cception::NotQubitVector Class Reference	258
	7.50.1	Detailed Description	259
	7.50.2	Member Function Documentation	259
		7.50.2.1 description()	260
7.51	qpp::ex	cception::OutOfRange Class Reference	260
	7.51.1	Detailed Description	261
	7.51.2	Member Function Documentation	261
		7.51.2.1 description()	261
7.52	qpp::ex	cception::PermInvalid Class Reference	262
	7.52.1	Detailed Description	263
	7.52.2	Member Function Documentation	263
		7.52.2.1 description()	263
7.53	qpp::ex	cception::PermMismatchDims Class Reference	263
	7.53.1	Detailed Description	265

CONTENTS xxiii

	7.53.2	Member Function Documentation
		7.53.2.1 description()
7.54	qpp::Q	Circuit Class Reference
	7.54.1	Detailed Description
	7.54.2	Member Typedef Documentation
		7.54.2.1 const_iterator
	7.54.3	Member Enumeration Documentation
		7.54.3.1 GateType
		7.54.3.2 MeasureType
		7.54.3.3 StepType
	7.54.4	Constructor & Destructor Documentation
		7.54.4.1 QCircuit()
		7.54.4.2 ~QCircuit()
	7.54.5	Member Function Documentation
		7.54.5.1 add_circuit()
		7.54.5.2 add_dit()
		7.54.5.3 add_hash_()
		7.54.5.4 add_qudit()
		7.54.5.5 begin() [1/2]
		7.54.5.6 begin() [2/2]
		7.54.5.7 cbegin()
		7.54.5.8 cCTRL() [1/4]
		7.54.5.9 cCTRL() [2/4]
		7.54.5.10 cCTRL() [3/4]
		7.54.5.11 cCTRL() [4/4]
		7.54.5.12 cCTRL_custom()
		7.54.5.13 cend()
		7.54.5.14 CTRL() [1/4]
		7.54.5.15 CTRL() [2/4]
		7.54.5.16 CTRL() [3/4]

xxiv CONTENTS

7.54.5.17 CTRL() [4/4]
7.54.5.18 CTRL_custom()
7.54.5.19 display()
7.54.5.20 end() [1/2]
7.54.5.21 end() [2/2]
7.54.5.22 gate() [1/3]
7.54.5.23 gate() [2/3]
7.54.5.24 gate() [3/3]
7.54.5.25 gate_custom()
7.54.5.26 gate_fan() [1/3]
7.54.5.27 gate_fan() [2/3]
7.54.5.28 gate_fan() [3/3]
7.54.5.29 get_cmat_hash_tbl_()
7.54.5.30 get_d()
7.54.5.31 get_depth()
7.54.5.32 get_gate_count()
7.54.5.33 get_gates_()
7.54.5.34 get_measured() [1/2]
7.54.5.35 get_measured() [2/2]
7.54.5.36 get_measurement_count() [1/2]
7.54.5.37 get_measurement_count() [2/2]
7.54.5.38 get_measurements_()
7.54.5.39 get_name()
7.54.5.40 get_nc()
7.54.5.41 get_non_measured()
7.54.5.42 get_nop_count()
7.54.5.43 get_nq()
7.54.5.44 get_step_count()
7.54.5.45 kron()
7.54.5.46 measureV() [1/2]

CONTENTS xxv

	7.54.5.47 measureV() [2/2]	289
	7.54.5.48 measureZ()	290
	7.54.5.49 nop()	290
	7.54.5.50 QFT() [1/3]	290
	7.54.5.51 QFT() [2/3]	291
	7.54.5.52 QFT() [3/3]	291
	7.54.5.53 replicate()	292
	7.54.5.54 TFQ() [1/3]	292
	7.54.5.55 TFQ() [2/3]	292
	7.54.5.56 TFQ() [3/3]	293
	7.54.5.57 to_JSON()	293
7.54.6	Friends And Related Function Documentation	294
	7.54.6.1 operator << [1/4]	294
	7.54.6.2 operator << [2/4]	294
	7.54.6.3 operator << [3/4]	294
	7.54.6.4 operator << [4/4]	295
	7.54.6.5 QEngine	295
7.54.7	Member Data Documentation	295
	7.54.7.1 cmat_hash_tbl	295
	7.54.7.2 count	296
	7.54.7.3 d	296
	7.54.7.4 gates	296
	7.54.7.5 measured	296
	7.54.7.6 measurement_count	296
	7.54.7.7 measurements	296
	7.54.7.8 name	297
	7.54.7.9 nc	297
	7.54.7.10 nq	297
	7.54.7.11 step_types	297
7.55 qpp::Q	Engine Class Reference	298

xxvi CONTENTS

7.55.1	Detailed Description	0
7.55.2	Constructor & Destructor Documentation	0
	7.55.2.1 QEngine() [1/3]	0
	7.55.2.2 QEngine() [2/3]	1
	7.55.2.3 QEngine() [3/3]	1
	7.55.2.4 ~QEngine()	1
7.55.3	Member Function Documentation	1
	7.55.3.1 display()	1
	7.55.3.2 execute() [1/3]	2
	7.55.3.3 execute() [2/3]	2
	7.55.3.4 execute() [3/3]	2
	7.55.3.5 get_circuit()	3
	7.55.3.6 get_dit()	3
	7.55.3.7 get_dits()	3
	7.55.3.8 get_measured() [1/2]	3
	7.55.3.9 get_measured() [2/2]	4
	7.55.3.10 get_non_measured()	4
	7.55.3.11 get_probs()	4
	7.55.3.12 get_psi()	5
	7.55.3.13 get_relative_pos_()	5
	7.55.3.14 get_stats()	5
	7.55.3.15 operator=()	5
	7.55.3.16 reset()	6
	7.55.3.17 reset_stats()	6
	7.55.3.18 set_dit()	6
	7.55.3.19 set_measured_()	6
	7.55.3.20 set_psi()	7
	7.55.3.21 to_JSON()	7
7.55.4	Member Data Documentation	7
	7.55.4.1 dits	8

CONTENTS xxvii

		7.55.4.2 probs	308
		7.55.4.3 psi	308
		7.55.4.4 qc	308
		7.55.4.5 stats	308
		7.55.4.6 subsys	308
7.56	qpp::Ql	NoisyEngine < NoiseModel > Class Template Reference	309
	7.56.1	Detailed Description	310
	7.56.2	Constructor & Destructor Documentation	310
		7.56.2.1 QNoisyEngine()	310
	7.56.3	Member Function Documentation	311
		7.56.3.1 execute()	311
		7.56.3.2 get_noise_results()	311
	7.56.4	Member Data Documentation	311
		7.56.4.1 noise	311
		7.56.4.2 noise_results	312
7.57	qpp::Q	ubitAmplitudeDampingNoise Class Reference	312
	7.57.1	Detailed Description	313
	7.57.2	Constructor & Destructor Documentation	313
		7.57.2.1 QubitAmplitudeDampingNoise()	313
7.58	qpp::Q	ubitBitFlipNoise Class Reference	313
	7.58.1	Detailed Description	314
	7.58.2	Constructor & Destructor Documentation	315
		7.58.2.1 QubitBitFlipNoise()	315
7.59	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	315
	7.59.1	Detailed Description	316
	7.59.2	Constructor & Destructor Documentation	316
		7.59.2.1 QubitBitPhaseFlipNoise()	316
7.60	qpp::Qı	ubitDepolarizingNoise Class Reference	317
	7.60.1	Detailed Description	318
	7.60.2	Constructor & Destructor Documentation	318

xxviii CONTENTS

		7.60.2.1 QubitDepolarizingNoise()	18
7.61	qpp::Qı	ubitPhaseDampingNoise Class Reference	18
	7.61.1	Detailed Description	19
	7.61.2	Constructor & Destructor Documentation	19
		7.61.2.1 QubitPhaseDampingNoise()	19
7.62	qpp::Qı	ubitPhaseFlipNoise Class Reference	20
	7.62.1	Detailed Description	21
	7.62.2	Constructor & Destructor Documentation	21
		7.62.2.1 QubitPhaseFlipNoise()	21
7.63	qpp::ex	xception::QuditAlreadyMeasured Class Reference	21
	7.63.1	Detailed Description	22
	7.63.2	Member Function Documentation	22
		7.63.2.1 description()	23
7.64	qpp::Qı	uditDepolarizingNoise Class Reference	23
	7.64.1	Detailed Description	24
	7.64.2	Constructor & Destructor Documentation	24
		7.64.2.1 QuditDepolarizingNoise()	24
	7.64.3	Member Function Documentation	25
		7.64.3.1 fill_Ks_()	25
		7.64.3.2 fill_probs_()	25
7.65	qpp::Ra	andomDevices Class Reference	26
	7.65.1	Detailed Description	27
	7.65.2	Constructor & Destructor Documentation	27
		7.65.2.1 RandomDevices()	
		7.65.2.2 ~RandomDevices()	
	7.65.3	Member Function Documentation	
		7.65.3.1 get_prng()	
		7.65.3.2 load()	
		7.65.3.3 save()	
	7 65 4	Friends And Related Function Documentation	
	7.00.4	Thomas And Helated Function Decumentation	_3

CONTENTS xxix

		7.65.4.1 internal::Singleton < RandomDevices >	29
	7.65.5	Member Data Documentation	29
		7.65.5.1 prng	29
		7.65.5.2 rd	29
7.66	qpp::int	ternal::Singleton< T > Class Template Reference	29
	7.66.1	Detailed Description	30
	7.66.2	Constructor & Destructor Documentation	30
		7.66.2.1 Singleton() [1/2]	31
		7.66.2.2 Singleton() [2/2]	31
		7.66.2.3 ~Singleton()	31
	7.66.3	Member Function Documentation	31
		7.66.3.1 get_instance()	31
		7.66.3.2 get_thread_local_instance()	31
		7.66.3.3 operator=()	31
7.67	qpp::ex	ception::SizeMismatch Class Reference	32
	7.67.1	Detailed Description	33
	7.67.2	Member Function Documentation	33
		7.67.2.1 description()	33
7.68	qpp::No	piseType::StateDependent Class Reference	33
	7.68.1	Detailed Description	33
7.69	qpp::No	piseType::StateIndependent Class Reference	34
	7.69.1	Detailed Description	34
7.70	qpp::St	ates Class Reference	34
	7.70.1	Detailed Description	36
	7.70.2	Constructor & Destructor Documentation	36
		7.70.2.1 States()	36
		7.70.2.2 ~States()	36
	7.70.3	Member Function Documentation	37
		7.70.3.1 jn()	37
		7.70.3.2 mes()	37

	7.70.3.3	mini	us()										 	 						337
	7.70.3.4	one	() .										 	 						338
	7.70.3.5	plus	s() .										 	 						338
	7.70.3.6	zero	o() .										 	 						339
7.70.4	Friends A	nd R	lelat	ed F	unc	tion	Do	cur	mer	ıtati	on		 	 						339
	7.70.4.1	inte	rnal	::Sin	glet	on<	< co	nst	Sta	ates	>		 	 						339
7.70.5	Member [Data	Doc	cume	enta	tion							 	 						339
	7.70.5.1	b00											 	 						339
	7.70.5.2	b01											 	 						339
	7.70.5.3	b10											 	 						340
	7.70.5.4	b11											 	 						340
	7.70.5.5	GHZ	Ζ.										 	 						340
	7.70.5.6	pb0	0 .										 	 						340
	7.70.5.7	pb0	1 .										 	 						340
	7.70.5.8	pb1	0 .										 	 						340
	7.70.5.9	pb1	1 .										 	 						341
	7.70.5.10	pGF	ΗZ .										 	 						341
	7.70.5.11	pW											 	 						341
	7.70.5.12	px0											 	 						341
	7.70.5.13	px1											 	 						341
	7.70.5.14	py0											 	 						341
	7.70.5.15	py1											 	 						342
	7.70.5.16	pz0											 	 						342
	7.70.5.17	pz1											 	 						342
	7.70.5.18	W .											 	 						342
	7.70.5.19	x0											 	 						342
	7.70.5.20	x1											 	 						342
	7.70.5.21	y0											 	 						343
	7.70.5.22	y1											 	 						343
	7.70.5.23	z0											 	 						343

CONTENTS xxxi

7.71 qpp::exception::SubsysMismatchDims Class Reference 7.71.1 Detailed Description 7.71.2 Member Function Documentation 7.71.2.1 description() 7.72 qpp::Timer< T, CLOCK_T > Class Template Reference 7.72.1 Detailed Description 7.72.2 Constructor & Destructor Documentation 7.72.2.1 Timer()	345 345 345 346 347 347
7.71.2 Member Function Documentation 7.71.2.1 description() 7.72 qpp::Timer < T, CLOCK_T > Class Template Reference 7.72.1 Detailed Description 7.72.2 Constructor & Destructor Documentation	345 345 345 346 347 347
7.71.2.1 description()	345 345 346 347 347
7.72 qpp::Timer < T, CLOCK_T > Class Template Reference	 345 346 347 347
7.72.1 Detailed Description	 346 347 347
7.72.2 Constructor & Destructor Documentation	 347 347 347
	 347 347
7.72.2.1 Timer()	 347
v · · · · · · · · · · · · · · · · · · ·	
7.72.2.2 ~Timer()	 347
7.72.3 Member Function Documentation	J-77
7.72.3.1 display()	 347
7.72.3.2 get_duration()	 348
7.72.3.3 tic()	 348
7.72.3.4 tics()	 348
7.72.3.5 toc()	 349
7.72.4 Member Data Documentation	 349
7.72.4.1 end	 349
7.72.4.2 start	 349
7.73 qpp::exception::TypeMismatch Class Reference	 350
7.73.1 Detailed Description	 351
7.73.2 Member Function Documentation	 351
7.73.2.1 description()	 351
7.74 qpp::exception::UndefinedType Class Reference	 351
7.74.1 Detailed Description	 353
7.74.2 Member Function Documentation	 353
7.74.2.1 description()	 353
7.75 qpp::exception::Unknown Class Reference	
7.75.1 Detailed Description	
7.75.2 Member Function Documentation	

xxxii CONTENTS

		7.75.2.1	description()			 		 	. 354
	7.76	qpp::QCircuit::ite	rator::value_type_	Class Referer	ice	 		 	. 355
		7.76.1 Detailed	Description			 		 	. 356
		7.76.2 Construc	tor & Destructor D	ocumentation		 		 	. 356
		7.76.2.1	value_type_() [1	/2]		 		 	. 356
		7.76.2.2	value_type_() [2	/2]		 		 	. 356
		7.76.3 Member	Function Documer	ntation		 		 	. 356
		7.76.3.1	display()			 		 	. 357
		7.76.3.2	operator=()			 		 	. 357
		7.76.4 Member	Data Documentation	on		 		 	. 357
		7.76.4.1	gates_ip			 		 	. 357
		7.76.4.2	ip			 		 	. 357
		7.76.4.3	measurements_i	p		 		 	. 358
		7.76.4.4	type			 		 	. 358
		7.76.4.5	value_type_qc_			 		 	. 358
	7.77	qpp::exception::Z	eroSize Class Ref	erence		 		 	. 358
		7.77.1 Detailed	Description			 		 	. 359
		7.77.2 Member	Function Documer	ntation		 		 	. 359
		7.77.2.1	description()			 		 	. 359
8	File	Documentation							361
	8.1		ircuits.h File Refer	ence					
			Description						
	8.2		ngines.h File Refe						
			Description						
	8.3		File Reference						
			Description						
	8.4		n.h File Reference						
		•	Description						
	8.5		ile Reference						
	- : =		Description						
			an bearing a second			 	'	 	

CONTENTS xxxiii

8.6	classes/idisplay.h File Reference	366
	8.6.1 Detailed Description	367
8.7	classes/init.h File Reference	367
	8.7.1 Detailed Description	367
8.8	classes/noise.h File Reference	368
	8.8.1 Detailed Description	368
8.9	classes/random_devices.h File Reference	369
	8.9.1 Detailed Description	369
8.10	classes/reversible.h File Reference	369
	8.10.1 Detailed Description	370
8.11	classes/states.h File Reference	370
	8.11.1 Detailed Description	371
8.12	classes/timer.h File Reference	371
	8.12.1 Detailed Description	371
8.13	constants.h File Reference	372
	8.13.1 Detailed Description	373
8.14	entanglement.h File Reference	373
	8.14.1 Detailed Description	375
8.15	entropies.h File Reference	375
	8.15.1 Detailed Description	376
8.16	experimental/experimental.h File Reference	376
	8.16.1 Detailed Description	376
8.17	functions.h File Reference	376
	8.17.1 Detailed Description	381
8.18	input_output.h File Reference	381
	8.18.1 Detailed Description	382
8.19	instruments.h File Reference	382
	8.19.1 Detailed Description	384
8.20	internal/classes/iomanip.h File Reference	384
	8.20.1 Detailed Description	384

8.21	internal/classes/singleton.h File Reference	385
	8.21.1 Detailed Description	385
8.22	2 internal/util.h File Reference	385
	8.22.1 Detailed Description	387
8.23	B MATLAB/matlab.h File Reference	387
	8.23.1 Detailed Description	388
8.24	Inumber_theory.h File Reference	388
	8.24.1 Detailed Description	389
8.25	operations.h File Reference	390
	8.25.1 Detailed Description	392
8.26	S qpp.h File Reference	392
	8.26.1 Detailed Description	393
	8.26.2 Macro Definition Documentation	393
	8.26.2.1 QPP_UNUSED	393
8.27	random.h File Reference	394
	8.27.1 Detailed Description	395
8.28	3 statistics.h File Reference	395
	8.28.1 Detailed Description	396
8.29	traits.h File Reference	396
	8.29.1 Detailed Description	397
8.30	types.h File Reference	398
	8.30.1 Detailed Description	399
8.31	/home/vlad/qpp/README.md File Reference	399

Index

401

Chapter 1

Quantum++

Version 1.3 - 25 July 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "'INSTALL.md'" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

op
Quantum++ main namespace
pp::exception
Quantum++ exception hierarchy namespace
pp::experimental
Experimental/test functions/classes, do not use or modify
op::internal
Internal utility functions, do not use them directly or modify them
pp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
app::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	. 344
qpp::exception::TypeMismatch	. 350
qpp::exception::UndefinedType	. 351
qpp::exception::Unknown	. 353
qpp::exception::ZeroSize	. 358
false_type	
qpp::is_complex< T >	 . 207
qpp::is_iterable < T, typename >	 . 209
qpp::QCircuit::GateStep	 187
qpp::internal::HashEigen	 190
qpp::IDisplay	
qpp::Dynamic bitset	
qpp::Bit circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QEngine	 . 298
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuit::iterator	
qpp::make_void < Ts >	
qpp::QCircuit::MeasureStep	 235
qpp::NoiseBase< T >	
qpp::NoiseBase< NoiseType::StateDependent >	 239
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	 . 318
qpp::NoiseBase < NoiseType::StateIndependent >	 239
qpp::QubitBitFlipNoise	 . 313
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	
qpp::internal::Singleton< T >	
qpp::internal::Singleton< const Codes >	
qpp::Codes	
qpp::internal::Singleton< const Gates >	
qpp::Gates	
qpp::internal::Singleton< const Init >	
qpp::Init	
qpp::internal::Singleton < const States >	
qpp::States	 . 334
qpp::internal::Singleton< RandomDevices >	 329
qpp::RandomDevices	 . 326
qpp::NoiseType::StateDependent	 333
qpp::NoiseType::StateIndependent	
true_type	
qpp::is_complex< std::complex< T >>	 . 208
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval<	
>().end()), decltype(*(std::declval< T >().begin()))>>	 . 210

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<pre>qpp::Bit_circuit</pre>	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	137
qpp::exception::CustomException	
Custom exception	140
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	143
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	144
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	146
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	148
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	150
qpp::exception::DimsNotEqual	
Dimensions not equal exception	152
qpp::internal::Display_Impl	154
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	155
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime	156
qpp::internal::EqualEigen	
Functor for comparing Eigen expressions for equality	168
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	169
qpp::Gates	
Const Singleton class that implements most commonly used gates	174
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	187
qpp::internal::HashEigen	
Functor for hashing Eigen expressions	190
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std←	
::ostream& os) const	191

8 Class Index

qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	193
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	194
qpp::exception::InvalidIterator Invalid iterator	196
Invalid iterator	198
qpp::internal::IOManipPointer< PointerType >	200
pp::internal::IOManipRange < InputIterator >	204
qpp::is_complex< T >	
Checks whether the type is a complex type	207
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable< T, typename >	000
Checks whether <i>T</i> is compatible with an STL-like iterable container	209
$\begin{aligned} \text{qpp::is_iterable} < \text{T, to_void} < \text{ decltype(std::declval} < \text{T} > ().\text{begin()}), \ \text{decltype(std::declval} < \text{T} > ().\text{end()}), \\ \text{decltype(*(std::declval} < \text{T} > ().\text{begin()})) > > \end{aligned}$	
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	212
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	213
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	218
qpp::exception::MatrixMismatchSubsys	040
Matrix mismatch subsystems exception	219
qpp::exception::MatrixNotCvector Matrix is not a column vector exception	221
qpp::exception::MatrixNotRvector	221
Matrix is not a row vector exception	223
qpp::exception::MatrixNotSquare	
Matrix is not square exception	225
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	227
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	229
qpp::exception::MatrixNotSquareNorVector	004
Matrix is not square nor vector exception	231
Matrix is not a vector exception	233
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	235
qpp::exception::NoCodeword	
Codeword does not exist exception	238
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	239
qpp::NoiseType	
Contains template tags used to specify the noise type	247
qpp::exception::NotBipartite Not bi-partite exception	247
qpp::exception::NotImplemented	24/
Code not yet implemented	249
qpp::exception::NotQubitCvector	0
Column vector is not 2 x 1 exception	251
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	252

4.1 Class List

qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	254
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	256
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	258
qpp::exception::OutOfRange	
	260
qpp::exception::PermInvalid	
·	262
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	263
qpp::QCircuit	
·	265
qpp::QEngine	
	298
qpp::QNoisyEngine < NoiseModel >	
	309
qpp::QubitAmplitudeDampingNoise	
	312
qpp::QubitBitFlipNoise	
•	313
qpp::QubitBitPhaseFlipNoise	
1 1 1 1 3	315
qpp::QubitDepolarizingNoise	
	317
qpp::QubitPhaseDampingNoise	
· · · · · · · · · · · · · · · · · · ·	318
qpp::QubitPhaseFlipNoise	
	320
qpp::exception::QuditAlreadyMeasured	
·	321
qpp::QuditDepolarizingNoise	
· · · · · · · · · · · · · · · · · · ·	323
qpp::RandomDevices	
,	326
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
	329
qpp::exception::SizeMismatch	
•	332
qpp::NoiseType::StateDependent	
,	333
qpp::NoiseType::StateIndependent	
1 0,	334
qpp::States	
ě ,	334
qpp::exception::SubsysMismatchDims	
,	344
qpp::Timer< T, CLOCK_T >	145
	345
qpp::exception::TypeMismatch)E0
21	350
qpp::exception::UndefinedType) E 4
71 1	351
qpp::exception::Unknown Unknown exception) E ר
Olikilowii exception	JOJ

10 Class Index

qpp::QCircuit::iterator::value_type_	
Value type class for qpp::QCircuit::iterator	355
qpp::exception::ZeroSize	
Object has zero size exception	358

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	72
entanglement.h	
Entanglement functions	73
entropies.h	
Entropy functions	75
functions.h	
Generic quantum computing functions	76
input_output.h	
Input/output functions	81
instruments.h	
	82
number_theory.h	
Number theory functions	88
operations.h	
Quantum operation functions	90
qpp.h	
•	92
random.h	
Randomness-related functions	94
statistics.h	
Statistics functions	95
traits.h	
Type traits	96
types.h	
Type aliases	98
classes/codes.h	
Quantum error correcting codes	63
classes/exception.h	
Exceptions	63
classes/gates.h	
Quantum gates	65
classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	66

12 File Index

classes/init.h	
Initialization	. 367
classes/noise.h	
Noise models	. 368
classes/random_devices.h	
Random devices	. 369
classes/reversible.h	
Support for classical reversible circuits	. 369
classes/states.h	
Quantum states	. 370
classes/timer.h	
Timing	. 371
classes/circuits/circuits.h	
Qudit quantum circuits	. 361
classes/circuits/engines.h	
Qudit quantum engines	. 362
experimental/experimental.h	
Experimental/test functions/classes	. 376
internal/util.h	
Internal utility functions	. 385
internal/classes/iomanip.h	
Input/output manipulators	. 384
internal/classes/singleton.h	
Singleton pattern via CRTP	. 385
MATLAB/matlab.h	
Input/output interfacing with MATLAB	. 387

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

struct is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(*(std::declval< T >().begin()))> >

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

· class QCircuit

Quantum circuit description.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
template<typename... Ts>
```

using to_void = typename make_void < Ts... >::type

Alias template that implements the proposal for void_t.

using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

```
15
    using cplx = std::complex< double >
          Complex number in double precision.
    using ket = Eigen::VectorXcd
          Complex (double precision) dynamic Eigen column vector.

    using bra = Eigen::RowVectorXcd

          Complex (double precision) dynamic Eigen row vector.
    • using cmat = Eigen::MatrixXcd
          Complex (double precision) dynamic Eigen matrix.

    using dmat = Eigen::MatrixXd

          Real (double precision) dynamic Eigen matrix.

    template<typename Scalar >

      using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
          Dynamic Eigen matrix over the field specified by Scalar.

    template<typename Scalar >

      using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
          Dynamic Eigen column vector over the field specified by Scalar.

    template<typename Scalar >

      using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
          Dynamic Eigen row vector over the field specified by Scalar.
Enumerations
    • enum { RES, PROB, ST }
          Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.
Functions

    cplx omega (idx D)

          D-th root of unity.

    template<typename Derived >

      dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
      &dims)
          Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

      dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
          Schmidt coefficients of the bi-partite pure state A.
    • template<typename Derived >
      cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
          Schmidt basis on Alice side.
    • template<typename Derived >
      cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
          Schmidt basis on Alice side.

    template<typename Derived >

      cmat schmidtB (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims)
          Schmidt basis on Bob side.
    template<typename Derived >
```

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >

&dims)

Schmidt basis on Bob side.

template<typename Derived >

cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)

Schmidt probabilities of the bi-partite pure state A. • template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt probabilities of the bi-partite pure state A. template<typename Derived > double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Entanglement of the bi-partite pure state A. template<typename Derived > double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2) Entanglement of the bi-partite pure state A. template<typename Derived > double gconcurrence (const Eigen::MatrixBase< Derived > &A) G-concurrence of the bi-partite pure state A. template < typename Derived > double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Negativity of the bi-partite mixed state A. template<typename Derived > double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2) Negativity of the bi-partite mixed state A. template<typename Derived > double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Logarithmic negativity of the bi-partite mixed state A. template<typename Derived > double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2) Logarithmic negativity of the bi-partite mixed state A. • template<typename Derived > double concurrence (const Eigen::MatrixBase< Derived > &A) Wootters concurrence of the bi-partite qubit mixed state A. template < typename Derived > double entropy (const Eigen::MatrixBase< Derived > &A) von-Neumann entropy of the density matrix A double entropy (const std::vector< double > &prob) Shannon entropy of the probability distribution prob. template<typename Derived > double renyi (const Eigen::MatrixBase< Derived > &A, double alpha) Renyi- α entropy of the density matrix A, for $\alpha \geq 0$. double renyi (const std::vector< double > &prob, double alpha) Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$. • template<typename Derived > double tsallis (const Eigen::MatrixBase< Derived > &A, double q) Tsallis- q entropy of the density matrix A, for q > 0. double tsallis (const std::vector< double > &prob, double q) Tsallis- q entropy of the probability distribution prob, for $q \geq 0$. template<typename Derived > double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector<math>< idx > &dims)Quantum mutual information between 2 subsystems of a composite system. template<typename Derived > double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const

std::vector < idx > &subsysB, idx d=2)

template<typename Derived >

Quantum mutual information between 2 subsystems of a composite system.

dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

Generated by Doxygen

Transpose. • template<typename Derived > dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A) Complex conjugate. template<typename Derived > dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A) Adjoint. template<typename Derived > dyn mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A) Inverse. template<typename Derived > Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A) template<typename Derived > Derived::Scalar det (const Eigen::MatrixBase< Derived > &A) template<typename Derived > Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A) Logarithm of the determinant. template<typename Derived > Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A) Element-wise sum of A. template<typename Derived > Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A) Element-wise product of A. template<typename Derived > double norm (const Eigen::MatrixBase< Derived > &A) Frobenius norm. • template<typename Derived > dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A) Normalizes state vector (column or row vector) or density matrix. • template<typename Derived > std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A) Full eigen decomposition. template<typename Derived > dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A) Eigenvalues. template<typename Derived > cmat evects (const Eigen::MatrixBase< Derived > &A) Eigenvectors. template<typename Derived > std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A) Full eigen decomposition of Hermitian expression. template<typename Derived > dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A) Hermitian eigenvalues. template<typename Derived > cmat hevects (const Eigen::MatrixBase< Derived > &A)

std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)

Eigenvectors of Hermitian matrix.

Full singular value decomposition.

• template<typename Derived >

Kronecker product.

```
• template<typename Derived >
  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template < typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
ullet template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::←
  MatrixBase< Derived2 > &B)
     Commutator.
• template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector < idx > &mask, idx d=2)
```

Multi-partite qudit ket.

cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

std::vector< double > abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector < double > rho2bloch \ (const \ Eigen::MatrixBase < Derived > \&A) \\
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

template<typename Derived >

```
internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
```

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std ::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

 $\label{eq:std::tuple} $$ std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const cmat &U) $$$

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)\\$

 $\textit{Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators \textit{Ks}.}$

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

```
std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

ullet template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadM ← ATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

• bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

d=2

• template<typename Derived1 , typename Derived2 >

 $\frac{\text{dyn_mat} < \text{typename Derived1::Scalar} > \frac{\text{applyCTRL}}{\text{const Eigen::MatrixBase} < \text{Derived1} > \text{\&state, const Eigen::MatrixBase} < \text{Derived2} > \text{\&A, const std::vector} < \frac{\text{idx}}{\text{idx}} > \text{\&trl, const std::vector} < \frac{\text{idx}}{\text{idx}} > \text{\&target, const std::vector} < \frac{\text{idx}}{\text{idx}} > \text{\&dims})$

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived1, typename Derived2 >

 $\frac{\text{dyn_mat}<\text{typename Derived1::Scalar}>\text{apply (const Eigen::MatrixBase}<\text{Derived1}>\text{\&state, const Eigen} \\ \text{::MatrixBase}<\text{Derived2}>\text{\&A, const std::vector}<\text{idx}>\text{\&target, const std::vector}<\text{idx}>\text{\&dims})}$

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix

• std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyQFT (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

 $\frac{dyn_mat}{<} typename \ Derived::Scalar > \frac{applyTFQ}{(const \ Eigen::MatrixBase} < Derived > &A, \ const \ std \\ \therefore vector < \frac{idx}{>} & target, \frac{idx}{>} & target$

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_ iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

```
6.1.2.7 dyn_mat
```

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Enumeration Type Documentation

6.1.3.1 anonymous enum

```
anonymous enum
```

Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Enumerator

RES	Measurement result(s)
PROB	Probabilit(y)/(ies)
ST	Output state(s)

6.1.4 Function Documentation

6.1.4.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

6.1.4.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.4.5 adjoint()

Adjoint.

```
A Eigen expression
```

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.4.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\}=AB+BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.4.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

state	Eigen expression
Α	Eigen expression
Gataligaeti k	y Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Gate A applied to the part target of state

```
6.1.4.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

```
6.1.4.9 apply() [3/5]
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Output density matrix after the action of the channel

6.1.4.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.4.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.4.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.4.15 applyTFQ()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::applyTFQ (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
idx d = 2,
bool swap = true )
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.4.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.4.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

See also

qpp::rho2bloch()

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.4.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^\dagger K_j) = \delta_{ij}$ for all $i \neq j$

Parameters

A Choi matrix

Returns

Set of orthogonal Kraus operators

6.1.4.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.4.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

subsys	Subsystem vector
n	Total number of systems

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.4.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations $perm \circ sigma = perm(sigma)$

6.1.4.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.4.24 conjugate()

Complex conjugate.

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.4.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

cf	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.4.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.4.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Χ	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number x

6.1.4.28 cor()

Correlation.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.4.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.4.30 cov()

Covariance.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Covariance of X and Y

6.1.4.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.4.32 det()

Determinant.

Parameters

```
A Eigen expression
```

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

```
head Eigen expression
```

Returns

Its argument head

6.1.4.34 dirsum() [2/4]

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.35 dirsum() [3/4]

Direct sum.

See also

qpp::dirsumpow()

As std::vector of Eigen expressions

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipRange

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

С	Container
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipPointer

6.1.4.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

а	Integer
b	Integer

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.4.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Α	Eigen expression	
dims	Dimensions of the bi-partite system	

Entanglement, with the logarithm in base 2

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.4.49 evals()

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.4.50 evects()

Eigenvectors.

See also

qpp::hevects()

A Eigen expression

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.4.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.4.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.4.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

```
qpp::logdet()
```

Parameters

```
A Eigen expression
```

Returns

G-concurrence

```
6.1.4.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.4.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Parameters

Α	Eigen expression
seed	Seed, 0 by default

Returns

Hash of its argument

6.1.4.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.4.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.4.64 inverse()

Inverse.

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.4.65 invperm()

Inverse permutation.

Parameters

perm	Permutation
------	-------------

Returns

Inverse of the permutation perm

6.1.4.66 ip() [1/2]

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.4.68 isprime()

```
bool qpp::isprime ( bigint p, idx k = 80 ) [inline]
```

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1	
k	Number of iterations. The probability of a false positive is 2^{-k} .	

Returns

True if the number is (most-likely) prime, false otherwise

6.1.4.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

```
Ks Set of Kraus operators
```

Returns

Choi matrix

6.1.4.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

Kronecker product.

•		
See	а	เรด

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

head Eigen expressio	n
------------------------	---

Returns

Its argument head

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

```
As std::vector of Eigen expressions
```

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.75 kronpow()

Kronecker power.

See also

qpp::kron()

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

qpp::gcd()

Parameters

as List of integers

Least common multiple of all numbers in as

6.1.4.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.4.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLAB<ket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.4.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

most file MATALD most file		MATALB .mat file
	mat_file	MATALD .mai me
	var_name	Variable name in the .mat file representing the matrix to be loaded

Eigen dynamic matrix

6.1.4.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.4.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.4.83 lognegativity() [1/2]

```
template<typename Derived >
double qpp::lognegativity (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Logarithmic negativity of the bi-partite mixed state A.

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.4.84 lognegativity() [2/2]

```
template<typename Derived > double qpp::lognegativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.4.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Ylabels the columns)

Returns

Real vector consisting of the marginal distribution of X

6.1.4.86 marginalY()

Marginal distribution.

Parameters

probX\	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.88 measure() [2/9]

Measures the state vector or density matrix \boldsymbol{A} using the set of Kraus operators \boldsymbol{Ks} .

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.89 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

ſ	Α	A Eigen expression	
	U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.90 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.91 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.94 measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
dims	Dimensions of the multi-partite system	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.4.95 measure() [9/9]
```

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.4.96 measure_seq() [1/2]
```

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.4.99 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.4.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.4.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.4.102 modpow()

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

I	mask	std::vector of non-negative integers
(dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.4.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.4.106 n2multiidx()

Non-negative integer index to multi-index.

See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.4.107 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.4.108 negativity() [2/2]

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.4.109 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.4.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

```
A Eigen expression
```

Returns

Normalized state vector or density matrix

6.1.4.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

```
D Non-negative integer
```

Returns

D-th root of unity $\exp(2\pi i/D)$

6.1.4.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix ${\it A}$ with itself ${\it n}$ times. By convention ${\it A}^0={\it I}$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.113 prj()

Projector.

Normalized projector onto state vector

Parameters

A Eigen expression

Returns

Projector onto the state vector *A*, or the matrix *Zero* if *A* has norm zero, as a dynamic matrix over the same scalar field as *A*

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

```
6.1.4.116 prod() [3/3]

template<typename Container >
Container::value_type qpp::prod (
```

```
const Container & c,
typename std::enable_if< is_iterable< Container >::value >::type * = nullptr )
```

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.119 ptrace1() [1/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.120 ptrace1() [2/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptrace1 (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.121 ptrace2() [1/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.122 ptrace2() [2/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.123 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.125 QFT()

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.4.126 qmutualinfo() [1/2]

```
template<typename Derived >
double qpp::qmutualinfo (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & subsysA,
const std::vector< idx > & subsysB,
const std::vector< idx > & dims )
```

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.4.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a,b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.4.133 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random Hermitian matrix

6.1.4.134 randidx()

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.4.135 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

```
D Dimension of the Hilbert space
```

Returns

Random normalized ket

6.1.4.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

6.1.4.137 randn() [1/4]

```
template<typename Derived >
Derived qpp::randn (
    idx rows QPP_UNUSED_,
    idx cols QPP_UNUSED_,
    double mean QPP_UNUSED_ = 0,
    double sigma QPP_UNUSED_ = 1)
```

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.4.138 randn() [2/4]

template<>
dmat qpp::randn (
         idx rows ,
         idx cols ,
         double mean ,
         double sigma ) [inline]
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

```
6.1.4.139 randn() [3/4]

template<>
cmat qpp::randn (
        idx rows ,
        idx cols ,
        double mean ,
        double sigma ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, // with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.4.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

N Size of the permutation

Returns

Random permutation of size N

6.1.4.142 randprime()

Generates a random big prime uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
Ν	Maximum number of candidates

Returns

Random big integer uniformly distributed in the interval [a, b]

6.1.4.143 randprob()

```
std::vector<double> qpp::randprob (
    idx N ) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.4.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.4.145 randU()

```
cmat qpp::randU (
    idx D = 2 ) [inline]
```

Generates a random unitary matrix.

Parameters

D | Dimension of the Hilbert space

Returns

Random unitary

6.1.4.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double alpha)

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Parameters

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.4.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Parameters

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Returns

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.4.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.4.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

Returns

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.4.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.4.153 saveMATLAB() [1/2]

```
template<typename Derived >
std::enable_if< std::is_same<typename Derived::Scalar, cplx>::value>::type qpp::saveMATLAB (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::string & mat_file,
const std::string & var_name,
const std::string & mode )
```

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

```
qpp::loadMATLAB()
```

Template Parameters

Complex	Eigen type
---------	------------

Parameters

Α	Eigen expression over the complex field	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

6.1.4.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

```
qpp::loadMATLAB()
```

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB <i>matOpen()</i> documentation for details

6.1.4.155 schatten()

Schatten matrix norm.

Parameters

Α	Eigen expression
р	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Returns

Schatten-p matrix norm of A

6.1.4.156 schmidtA() [1/2]

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

6.1.4.157 schmidtA() [2/2]

Schmidt basis on Alice side.

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal U}$ whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

6.1.4.160 schmidtcoeffs() [1/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.164 sigma()

Standard deviation.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.4.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.4.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of A to compute the matrix power. By convention $A^0 = I$.

Parameters

Α	Eigen expression
Z	Complex number

Returns

Matrix power A^z

6.1.4.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

Element-wise sum of A.

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

Element-wise sum of an STL-like range.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

```
6.1.4.171 super2choi()
```

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.4.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.173 svd()

Full singular value decomposition.

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.4.174 svdU()

Left singular vectors.

Parameters

A Eigen expression

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.4.175 svdV()

Right singular vectors.

Parameters

A Eigen expression

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.4.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.4.177 syspermute() [2/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.4.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.4.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.4.180 transpose()

Transpose.

A Eigen expression

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.4.181 tsallis() [1/2]  \begin{tabular}{ll} template < typename Derived > \\ double qpp::tsallis ( & const Eigen::MatrixBase < Derived > & A, \\ double $q$ ) \\ \end{tabular}
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.4.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.4.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.4.185 x2contfrac()

Simple continued fraction expansion.

See also

qpp::contfrac2x()

Parameters

X	Real number
N	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than <i>cut</i>

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.5 Variable Documentation

6.1.5.1 chop

```
constexpr double qpp::chop = 1e-16
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.5.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.5.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.5.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.5.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

```
    template < class T >
        void hash_combine (std::size_t &seed, const T &v)
```

Hash combine.

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check_vector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check dims (const std::vector < idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

- template < typename Derived >
 bool check dims match cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)
- template<typename Derived >
 bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool check_eq_dims (const std::vector < idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector < idx > &subsys, const std::vector < idx > &dims)
- template<typename Derived >
 bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)
- template<typename T >
 void variadic_vector_emplace (std::vector< T > &)
- template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx get_num_subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr>
 T abs_chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr>
 T abs_chop (const T &x, double QPP_UNUSED_ chop=qpp::chop)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 abs_chop() [1/2]

```
6.4.2.2 abs_chop() [2/2]
\texttt{template} < \texttt{typename T , typename std::enable\_if} < ! (\texttt{std::numeric\_limits} < \texttt{T} > :: \texttt{is\_iec559} | \texttt{is\_} \leftarrow \texttt{typename T} | \texttt{type
complex< T >::value)>::type * = nullptr>
T qpp::internal::abs_chop (
                                                const T & x,
                                                  double QPP_UNUSED_ chop = qpp::chop )
6.4.2.3 check_cvector()
template<typename Derived >
bool qpp::internal::check_cvector (
                                                 const Eigen::MatrixBase< Derived > & A )
6.4.2.4 check_dims()
bool qpp::internal::check_dims (
                                                const std::vector< idx > & dims ) [inline]
6.4.2.5 check_dims_match_cvect()
template<typename Derived >
bool qpp::internal::check_dims_match_cvect (
                                               const std::vector< idx > & dims,
                                                const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_dims_match_mat()
{\tt template}{<}{\tt typename \ Derived} >
bool qpp::internal::check_dims_match_mat (
                                               const std::vector< idx > & dims,
                                                 const Eigen::MatrixBase< Derived > & A )
6.4.2.7 check_dims_match_rvect()
template<typename Derived >
bool qpp::internal::check\_dims\_match\_rvect (
                                                 const std::vector< idx > & dims,
                                                  const Eigen::MatrixBase< Derived > & A )
```

6.4.2.8 check_eq_dims()

6.4.2.9 check_matching_sizes()

6.4.2.10 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( std::vector < \ idx \ > \ v \ ) \quad [inline]
```

6.4.2.11 check_nonzero_size()

6.4.2.12 check_perm()

```
bool qpp::internal::check_perm (  \mbox{const std::vector} < \mbox{idx} \ > \mbox{\& perm} \ ) \quad \mbox{[inline]}
```

6.4.2.13 check_qubit_cvector()

```
6.4.2.14 check_qubit_matrix()
```

```
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.16 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.17 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.18 check_square_mat()
template<typename Derived >
bool qpp::internal::check\_square\_mat (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.19 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
             const std::vector< idx > & dims ) [inline]
```

6.4.2.20 check_vector()

6.4.2.21 dirsum2()


6.4.2.22 get_dim_subsys()

6.4.2.23 get_num_subsys()

6.4.2.24 hash_combine()

Hash combine.

Template Parameters



Parameters

seed Initial seed, will be updated by the function

Value with which the hash is combined

```
6.4.2.25 kron2()
```

6.4.2.26 multiidx2n()

6.4.2.27 n2multiidx()

6.4.2.28 variadic_vector_emplace() [1/2]

```
template<typename T > void qpp::internal::variadic_vector_emplace ( std::vector < T \, > \, \& \quad )
```

6.4.2.29 variadic_vector_emplace() [2/2]

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr cplx operator"" _i (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)

    constexpr std::complex< float > operator""_if (unsigned long long int x) noexcept

      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr std::complex< float > operator"" _if (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)
• template<char... Bits>
  ket operator"" _ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra operator"" _bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat operator"" _prj ()
      Multi-partite qubit projector user-defined literal.
```

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle Bits |$

Template Parameters

Bits String of binary numbers representing the qubit bra

Returns

Multi-partite qubit bra, as a complex dynamic row vector

```
6.5.1.2 operator""" _i() [1/2]
constexpr cplx qpp::literals::operator"" _i (
               unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
cplx z = 4_i; // type of z is std::complex<double>
6.5.1.3 operator""" _i() [2/2]
constexpr cplx qpp::literals::operator"" _i (
               long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
cplx z = 4.5_i; // type of z is std::complex<double>
6.5.1.4 operator""" _if() [1/2]
constexpr std::complex<float> qpp::literals::operator"" _if (
               unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
auto z = 4_if; // type of z is std::complex<double>
6.5.1.5 operator"""_if() [2/2]
constexpr std::complex<float> qpp::literals::operator"" _if (
               long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
auto z = 4.5_{if}; // type of z is std::complex<float>
6.5.1.6 operator""" _ket()
template<char... Bits>
{\color{red} \texttt{ket} \ \textit{qpp::literals::operator""} \ \_\texttt{ket} \ (\ )}
Multi-partite qubit ket user-defined literal.
See also
     qpp::mket()
Constructs the multi-partite qubit ket |Bits>
```

Template Parameters

Bits	String of binary numbers representing the qubit ket	
------	---	--

Returns

Multi-partite qubit ket, as a complex dynamic column vector

```
6.5.1.7 operator"""_prj()

template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|Bits\rangle\langle Bits|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

Returns

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7


Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Public Member Functions

• Bit_circuit (idx n)

Constructs a bit circuit instance.

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx i)

Bit flip.

virtual ∼Bit_circuit ()=default

Default virtual destructor.

Bit_circuit & NOT (idx i)

Bit flip.

Bit_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get_gate_count (const std::string &name={}) const Bit circuit gate count.
- idx get_gate_depth (const std::string &name={}) const

Bit circuit gate depth.

Private Attributes

- std::unordered_map< std::string, idx > depth_ {}
 gate depths
- Dynamic_bitset bNOT_
- Dynamic_bitset bCNOT_
- Dynamic_bitset bSWAP_
- Dynamic_bitset bTOF_
- Dynamic_bitset bFRED_
- Dynamic_bitset btotal_

used for depth calculations

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

Parameters

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

ctrl	Control bit index
target	Target bit index

Returns

Reference to the current instance

7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

i	Control bit index
j	Target first bit index
k	Target second bit index

Returns

Reference to the current instance

7.1.3.3 get_gate_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.
------	--

Returns

Gate count

7.1.3.4 get_gate_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

Parameters

```
i Bit position in the circuit
```

Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
        idx i,
        idx j) [inline]
```

Swap bits.

i	Bit index
j	Bit index

Returns

Reference to the current instance

7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

Parameters

i	Control first bit index
j	Control second bit index
k	Target bit index

Returns

Reference to the current instance

7.1.3.9 X()

```
Bit_circuit@ qpp::Bit_circuit::X (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

Parameters

i Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

7.1.4.8 depth_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

enum Type { Type::FIVE_QUBIT, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

• CustomException (const std::string &where, const std::string &what)

Private Member Functions

• std::string description () const override Exception description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference


Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

std::string description () const override
 Exception description.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string description () const override Exception description.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

std::string description () const override
 Exception description.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 description()

std::string qpp::exception::DimsMismatchMatrix::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



 $Collaboration\ diagram\ for\ qpp::exception::DimsMismatchRvector:$



Public Member Functions

• std::string description () const override Exception description.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

std::string description () const override
 Exception description.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 description()

std::string qpp::exception::DimsMismatchVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string description () const override Exception description.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string description () const override Exception description.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 description()

std::string qpp::exception::Duplicates::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 - type of the storage elements
- using storage_type = std::vector< value_type >

type of the storage

Public Member Functions

• Dynamic_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic_bitset ()=default

Default virtual destructor.

• const storage_type & data () const

Raw storage space of the bitset.

· idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic_bitset & set () noexcept

Set all bits to true.

Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

• Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

· idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
```

storage size

idx n_

number of bits

std::vector< value_type > v_

storage space

Private Member Functions

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type

using qpp::Dynamic_bitset::storage_type = std::vector<value_type>

type of the storage

7.12.2.2 value_type

using qpp::Dynamic_bitset::value_type = unsigned int
```

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

type of the storage elements

```
qpp::Dynamic_bitset ::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

Parameters

n Number of bits in the bitset

7.12.3.2 \sim Dynamic_bitset()

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
Checks whether all bits are set.
Returns
    True if all of the bits are set
7.12.4.2 any()
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
Checks whether any bit is set.
Returns
    True if any of the bits is set
7.12.4.3 count()
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
Number of bits set to one in the bitset (Hamming weight)
Returns
    Hamming weight
7.12.4.4 data()
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
Raw storage space of the bitset.
Returns
     Const reference to the underlying storage space
7.12.4.5 display()
std::ostream& qpp::Dynamic_bitset::display (
```

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Pos	ition in the bitset
---------	---------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the *pos* bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

rhs Dynamic_bitset against which the inequality is being tested

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

rhs Dynamic_bitset against which the equality is being tested

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand ( idx pos, double p = 0.5) [inline]
```

Sets the bit at position pos according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns


Reference to the current instance

7.12.4.16 rand() [2/2]

```
\label{eq:double_p} \begin{split} & \texttt{Dynamic\_bitset\& qpp::Dynamic\_bitset::rand (} \\ & & \texttt{double} \ p = 0.5 \ ) \quad [inline] \end{split}
```

Sets all bits according to a Bernoulli(p) distribution.

Parameters



Returns

Reference to the current instance

7.12.4.17 reset() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::reset (
        idx pos ) [inline]
```

Sets the bit at position pos to false.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
```

Sets all bits to false.

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

7.12.4.21 size()

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

7.12.4.22 storage_size()

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Gе д¢∤⊘јед∤ ⊘угD	x % ₱₱ng Allocator

Parameters

zero	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
number of bits
```

7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

storage size

```
7.12.5.3 v_
```

```
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
```

storage space

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case it simply returns false)

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string description () const =0
 - Exception description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception() in the derived class and to inherit the constructor qpp::exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

```
namespace qpp
{
  namespace exception
{
    class ZeroSize : public Exception
    {
       public:
            std::string description() const override
            {
                 return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor
            using Exception::Exception;
       };
} // namespace exception
} // namespace qpp
```

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.14.3 Member Function Documentation

7.14.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
```

Exception description.

Returns

Exception description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::Custom ← Exception, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType,

qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOcodeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp⇔::exception::NotQubitRvector, qpp::exception::NotQubitCvector, qpp::exception::NotQubitMatrix, qpp::exception⇔::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchDims, qpp::exception⇔::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp⇔::exception::DimsMismatchCvector, qpp⇔::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception⇔::MatrixMismatchSubsys, qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotVector, qpp::exception::MatrixNotVector, qpp::exception::MatrixNotVector, qpp::exception::ZeroSize, and qpp::exception::Unknown.

7.14.3.2 what()

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

```
7.14.4.1 msg
```

```
std::string qpp::exception::Exception::msg_ [mutable], [private]
```

7.14.4.2 where

```
std::string qpp::exception::Exception::where_ [private]
```

The documentation for this class was generated from the following file:


classes/exception.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N	
Ν	Positive integer	
n	Number of qubits required for implementing the gate	

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

theta Rotation an	gle
-------------------	-----

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name={})

Constructs a gate step instance.

Public Attributes

7.16.1 Detailed Description

7.16.2.1 GateStep() [1/2]

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_ {}
control
7.16.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_ {}
gate hash
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_ {}
```

custom name of the step

7.16.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_ {}
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits/circuits.h

7.17 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

```
    template<typename Derived >
        std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const
```

7.17.1 Detailed Description

Functor for hashing Eigen expressions.

7.17.2 Member Function Documentation

7.17.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.18 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

virtual ~IDisplay ()=default
 Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

7.18.3 Member Function Documentation

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp \leftrightarrow ::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp \leftrightarrow ::internal::IOManipRange< InputIterator >.

7.18.4 Friends And Related Function Documentation

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

- virtual \sim IJSON ()=default
 - Default virtual destructor.
- virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0
 JSON representation of the derived instance, must be overridden by all derived classes.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.19.2 Constructor & Destructor Documentation

7.19.2.1 ∼IJSON()

```
virtual qpp::IJSON::~IJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.19.3 Member Function Documentation

7.19.3.1 to_JSON()

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

<i>enciosed in curiv prackels</i> Il true, encioses the result in curiv prackets	enclosed in curly brackets	If true, encloses the result in curly brackets
--	----------------------------	--

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

• Init ()

Additional initializations.

• ∼Init ()

Cleanups.

Friends

- class internal::Singleton < const Init >

Additional Inherited Members

7.20.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.20.2 Constructor & Destructor Documentation

7.20.2.1 Init()

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.20.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.20.3 Friends And Related Function Documentation

```
7.20.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.21 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception::InvalidIterator:$



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string description () const override Exception description.

7.21.1 Detailed Description

Invalid iterator.

7.21.2 Member Function Documentation

7.21.2.1 description()

std::string qpp::exception::InvalidIterator::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

classes/exception.h


7.22 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.22.1 Constructor & Destructor Documentation

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.3 Member Data Documentation

7.22.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.22.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_
- double chop_

7.23.1 Constructor & Destructor Documentation

7.23.1.1 IOManipPointer() [1/2]

7.23.1.2 IOManipPointer() [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 chop_
template<typename PointerType>
double qpp::internal::IOManipPointer< PointerType >::chop_ [private]
7.23.3.2 end
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.23.3.3 N_
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.23.3.4 p_
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.23.3.5 separator_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
7.23.3.6 start
template<typename PointerType>
```

The documentation for this class was generated from the following file:


std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]

internal/classes/iomanip.h


7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- · std::string end_
- double chop_

7.24.1 Constructor & Destructor Documentation

7.24.1.1 IOManipRange() [1/2]

7.24.1.2 IOManipRange() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 chop_
```

```
template<typename InputIterator>
double qpp::internal::IOManipRange< InputIterator >::chop_ [private]
```

7.24.3.2 end_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
```

7.24.3.3 first_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
```

7.24.3.4 last_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
```

7.24.3.5 separator_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

7.24.3.6 start_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


• internal/classes/iomanip.h

7.25 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < T >:



Collaboration diagram for qpp::is_complex< T >:



7.25.1 Detailed Description

 $\label{eq:typename} \begin{array}{l} \text{template}{<} \text{typename T}{>} \\ \text{struct qpp::is_complex}{<} \text{T}{>} \end{array}$

Checks whether the type is a complex type.

Provides the constant member value which is equal to true, if the type is a complex type, i.e. std::complex<T>

The documentation for this struct was generated from the following file:


• traits.h

7.26 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is_complex< std::complex< T >>:



Collaboration diagram for qpp::is_complex< std::complex< T > >:



7.26.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename > :



Collaboration diagram for qpp::is_iterable< T, typename >:



7.27.1 Detailed Description

template < typename T, typename = void > struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

- · traits.h
- 7.28 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std :: declval < T >().end()), decltype(*(std::declval < T >().begin())) > > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



7.28.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ \\ ::declval < T > ().begin())) > \\ \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.29 qpp::is_matrix_expression < Derived > Struct Template Reference

Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:

```
std::is_base_of< Eigen
::MatrixBase< std::decay
< Derived >::type >, std
::decay< Derived >::type >
```

Collaboration diagram for qpp::is matrix expression< Derived >:

```
std::is_base_of< Eigen
::MatrixBase< std::decay
< Derived >::type >, std
::decay< Derived >::type >
```

7.29.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

7.30 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Value type class for qpp::QCircuit::iterator.

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

• iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value_type_ elem_ {nullptr}

7.30.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.30.2 Member Typedef Documentation

```
7.30.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.30.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.30.2.3 pointer

using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait

7.30.2.4 reference

using qpp::QCircuit::iterator::reference = const value_type&
iterator trait

7.30.2.5 value_type

using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
```

7.30.3 Constructor & Destructor Documentation

7.30.4 Member Function Documentation

Default copy constructor.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.30.4.2 operator*()
```

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.30.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.30.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.30.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.30.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.30.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.30.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.30.5 Member Data Documentation

```
7.30.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.30.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
< non-owning pointer to the parent const quantum circuit</pre>
```

The documentation for this class was generated from the following file:

• classes/circuits/circuits.h

7.31 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.31.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.31.2 Member Typedef Documentation

7.31.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.32 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

• std::string description () const override Exception description.

7.32.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.32.2 Member Function Documentation

7.32.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string description () const override Exception description.

7.33.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.33.2 Member Function Documentation

7.33.2.1 description()

std::string qpp::exception::MatrixNotCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string description () const override Exception description.

7.34.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.34.2 Member Function Documentation

7.34.2.1 description()

std::string qpp::exception::MatrixNotRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string description () const override Exception description.

7.35.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.35.2 Member Function Documentation

7.35.2.1 description()

```
std::string qpp::exception::MatrixNotSquare::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string description () const override Exception description.

7.36.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.36.2 Member Function Documentation

7.36.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string description () const override Exception description.

7.37.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.37.2 Member Function Documentation

7.37.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string description () const override Exception description.

7.38.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.38.2 Member Function Documentation

7.38.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string description () const override Exception description.

7.39.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.39.2 Member Function Documentation

7.39.2.1 description()

std::string qpp::exception::MatrixNotVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name={})

Constructs a measurement step instance.

Public Attributes

```
    MeasureType measurement_type_ = MeasureType::NONE
        measurement type
    std::vector< std::size_t > mats_hash_ {}
    std::vector< idx > target_ {}
```

target where the measurement is applied

```
idx c_reg_ {}
```

```
• std::string name_{}
```

custom name of the step

7.40.1 Detailed Description

One step consisting only of measurements in the circuit.

7.40.2 Constructor & Destructor Documentation

```
7.40.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

```
7.40.2.2 MeasureStep() [2/2]
```

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

7.40.3 Member Data Documentation

```
7.40.3.1 c_reg_
idx qpp::QCircuit::MeasureStep::c_reg_ {}
index of the classical register where the measurement result is being stored
7.40.3.2 mats_hash_
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_ {}
hashes of measurement matrix/matrices
7.40.3.3 measurement_type_
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.40.3.4 name_
std::string qpp::QCircuit::MeasureStep::name_ {}
custom name of the step
7.40.3.5 target_
std::vector<idx> qpp::QCircuit::MeasureStep::target_ {}
target where the measurement is applied
```

• classes/circuits/circuits.h


The documentation for this struct was generated from the following file:

7.41 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

 std::string description () const override Exception description.

7.41.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.41.2 Member Function Documentation

7.41.2.1 description()

std::string qpp::exception::NoCodeword::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::State
 Dependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is_same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

• idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

idx get_last_idx () const

Index of the last occurring noise element.

• double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

```
    const std::vector < cmat > Ks_
        Kraus operators.
    std::vector < double > probs_
        probabilities
    idx d_ {}
        qudit dimension
    idx i_ {}
        index of the last occurring noise element
    bool generated_ {false}
        invoked, or if the noise is state-independent
```

7.42.1 Detailed Description

```
template < class T > class qpp::NoiseBase < T >
```

Base class for all noise models, derive your particular noise model.

7.42.2 Member Typedef Documentation

7.42.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.42.3 Constructor & Destructor Documentation

```
7.42.3.1 NoiseBase() [1/2]
```

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Ks | Vector of noise (Kraus) operators that specify the noise

7.42.3.2 NoiseBase() [2/2]

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Ks Vec	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

7.42.3.3 ~NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

7.42.4 Member Function Documentation

```
7.42.4.1 compute_probs_()
```

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.42.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.42.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.42.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.42.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.42.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.42.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.42.4.8 get_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.42.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

state	State vector or density matrix
-------	--------------------------------

Returns

Resulting state vector or density matrix

idx target) const [inline], [virtual]

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.42.4.11 operator()() [3/3]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.42.5 Member Data Documentation

```
7.42.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.42.5.2 generated_
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.42.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
7.42.5.4 Ks_
{\tt template}{<}{\tt class} \ {\tt T}{>}
```

const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]

Kraus operators.

7.42.5.5 probs_

probabilities

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

The documentation for this class was generated from the following file:

· classes/noise.h

7.43 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.43.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.44 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string description () const override Exception description.

7.44.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.44.2 Member Function Documentation

7.44.2.1 description()

std::string qpp::exception::NotBipartite::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string description () const override Exception description.

7.45.1 Detailed Description

Code not yet implemented.

7.45.2 Member Function Documentation

7.45.2.1 description()

std::string qpp::exception::NotImplemented::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string description () const override Exception description.

7.46.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.46.2 Member Function Documentation

7.46.2.1 description()

std::string qpp::exception::NotQubitCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.47 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string description () const override Exception description.

7.47.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.47.2 Member Function Documentation

7.47.2.1 description()

 $\verb|std::string qpp::exception::NotQubitMatrix::description () const [inline], [override], [virtual]|\\$

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitRvector:$



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string description () const override Exception description.

7.48.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.48.2 Member Function Documentation

7.48.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string description () const override Exception description.

7.49.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.49.2 Member Function Documentation

7.49.2.1 description()

std::string qpp::exception::NotQubitSubsys::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string description () const override Exception description.

7.50.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.50.2 Member Function Documentation

7.50.2.1 description()

std::string qpp::exception::NotQubitVector::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.51 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string description () const override Exception description.

7.51.1 Detailed Description

Argument out of range exception.

Argument out of range

7.51.2 Member Function Documentation

7.51.2.1 description()

std::string qpp::exception::OutOfRange::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


classes/exception.h

7.52 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

 std::string description () const override Exception description.

7.52.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.52.2 Member Function Documentation

7.52.2.1 description()

std::string qpp::exception::PermInvalid::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string description () const override Exception description.

7.53.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.53.2 Member Function Documentation

7.53.2.1 description()

std::string qpp::exception::PermMismatchDims::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::QCircuit Class Reference


Quantum circuit description.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE, GateType::CUSTOM, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE←CTRL_MULTIPLE TARGET,

GateType::MULTIPLE_CTRL_SINGLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,

 ${\tt GateType::CUSTOM_CTRL}, {\tt GateType::SINGLE_cCTRL_SINGLE_TARGET},$

GateType::SINGLE_cCTRL_MULTIPLE_TARGET, GateType::MULTIPLE_cCTRL_SINGLE_TARGET, GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

• using const_iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

· const_iterator begin () const noexcept

Constant iterator to the first element.

const_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

• idx get_measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

• idx get_gate_count (const std::string &name={}) const

Quantum circuit gate count.

• idx get_depth (const std::string &name={}) const

Quantum circuit depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get_measurement_count (const std::string &name) const

Quantum circuit measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

idx get_nop_count () const

No-op count.

QCircuit & add_qudit (idx n=1, idx i=-1)

Adds n additional qudits before qudit i (by default adds them at the end)

QCircuit & add_dit (idx n=1, idx i=-1)

Adds n additional classical dits before dit i (by default adds them at the end)

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

• QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, std::string name={})

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer_list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c_reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

• QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix

• QCircuit & nop ()

No operation (no-op)

· QCircuit & replicate (idx n)

Replicates the circuit.

• QCircuit & add_circuit (QCircuit other, bigint pos_qudit, idx pos_dit=-1)

Appends a quantum circuit description to the current one.

QCircuit & kron (const QCircuit & other)

Kronecker product with another quantum circuit description.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

```
qpp::IJSON::to_JSON() override
```

Private Member Functions

```
    void add_hash_ (const cmat &U, std::size_t hashU)
```

Adds matrix to the hash table.

const std::vector < MeasureStep > & get_measurements_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates_() const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_() const noexcept

Hash table with the matrices used in the circuit.

std::ostream & display (std::ostream &os) const override

```
qpp::IDisplay::display() override
```

Private Attributes

```
idx nq
```

number of qudits

• idx nc_

number of classical "dits"

const idx d

qudit dimension

• std::string name_

optional circuit name

std::vector< bool > measured

keeps track of the measured qudits

• std::unordered map< std::size t, cmat > cmat hash tbl {}

std::unordered_map< std::string, idx > count_{{}}

gate counts

std::unordered_map< std::string, idx > measurement_count_{}{}

measurement counts

std::vector< GateStep > gates_{}{}

aates

std::vector< MeasureStep > measurements_{}{}

measurements

std::vector< StepType > step_types_{}

type of each step

Friends

- · class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

• std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

• std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.54.1 Detailed Description

Quantum circuit description.

See also

qpp::QEngine

7.54.2 Member Typedef Documentation

7.54.2.1 const_iterator

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.54.3 Member Enumeration Documentation

7.54.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits

Enumerator

FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	controls and multiple targets custom controlled gate with multiple classical

7.54.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V

7.54.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

|--|

Enumerator

GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by *nc*

Parameters

nq	Number of qbits	
nc	Number of classical dits (optional)	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.54.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.54.5 Member Function Documentation

7.54.5.1 add_circuit()

Appends a quantum circuit description to the current one.

Note

If qudit indexes of the added quantum circuit description do not totally overlap with the indexes of the current quantum circuit description, then the required number of additional qudits are automatically added to the current quantum circuit description

Parameters

other	Quantum circuit description
pos_qudit The index of the first qudit of other relative to the index of the first qudit of the current quantum circuit description, with the rest following in order. If negative or greater than the total number qudits of the current quantum circuit description, the required number of additional qudits are automatically added to the current quantum circuit description.	
pos_dit	The first classical dit of <i>other</i> is inserted before the <i>pos_dit</i> classical dit index of the current quantum circuit description (in the classical dits array), the rest following in order. By default, insertion is performed at the end.

Returns

Reference to the current instance

7.54.5.2 add_dit()

```
QCircuit& qpp::QCircuit::add_dit (
    idx n = 1,
    idx i = -1 ) [inline]
```

Adds *n* additional classical dits before dit *i* (by default adds them at the end)

Note

Classical dits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

Parameters

n	Number of classical dits
i	Classical dit index

Returns

Reference to the current instance

7.54.5.3 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

7.54.5.4 add_qudit()

```
QCircuit& qpp::QCircuit::add_qudit (
    idx n = 1,
    idx i = -1) [inline]
```

Adds n additional qudits before qudit i (by default adds them at the end)

Note

Qudits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

Parameters

n	Number of qudits
i	Qudit index

Returns

Reference to the current instance

```
7.54.5.5 begin() [1/2]
```

iterator qpp::QCircuit::begin () [inline]

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.6 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.7 cbegin()
```

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
с <i>‡аға</i> ей ы рТауде qudit index	
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl_dit	lit Classical control dit index	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.12 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.13 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

const std::vector< idx > & target,
std::string name = {}) [inline]

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name Generated by Doxygen

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.17 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.18 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.19 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

os	Output stream passed by reference
----	-----------------------------------

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.20 end() [1/2]
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.21 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = {} ) [inline]
```

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

std::string name = {}) [inline]

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.54.5.25 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate U on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

7.54.5.29 get_cmat_hash_tbl_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.54.5.30 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

7.54.5.31 get_depth()

Quantum circuit depth.

Note

If name is empty (default), returns the total depth of the circuit

Parameters

name Gate/measurement name (optional)

Returns

Gate/measurement depth

7.54.5.32 get_gate_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional)

Returns

Gate count

7.54.5.33 get_gates_()

```
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

Returns

Vector of qpp::QCircuit::GateStep

```
7.54.5.34 get_measured() [1/2]
```

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.54.5.35 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.54.5.36 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.54.5.37 get_measurement_count() [2/2]
```

Quantum circuit measurement count.

Parameters

name Measurement name

Returns

Measurement count

7.54.5.38 get_measurements_()

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

7.54.5.39 get_name()

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

7.54.5.40 get_nc()

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.54.5.41 get_non_measured()
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
Vector of non-measured qudit indexes.
Returns
     Vector of non-measured qudit indexes
7.54.5.42 get_nop_count()
idx qpp::QCircuit::get_nop_count ( ) const [inline]
No-op count.
Returns
     No-op count
7.54.5.43 get_nq()
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
Total number of qudits in the circuit.
Returns
     Total number of qudits
7.54.5.44 get_step_count()
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
Quantum circuit total steps count, i.e. the sum of gate count and measurement count.
Returns
     Total (gates + measurements) count
7.54.5.45 kron()
```

Kronecker product with another quantum circuit description.

const QCircuit & other) [inline]

QCircuit& qpp::QCircuit::kron (

Parameters

other	Quantum circuit description
-------	-----------------------------

Returns

Reference to the current instance

7.54.5.46 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.54.5.47 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.54.5.48 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Z"

Returns

Reference to the current instance

```
7.54.5.49 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

Returns

Reference to the current instance

```
7.54.5.50 QFT() [1/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.51 QFT() [2/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.52 QFT() [3/3]
```

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

7.54.5.53 replicate()

Replicates the circuit.

Note

The circuit should not contain any measurements when invoking this member function

Parameters

```
n Number of repetitions. If n == 1, returns the original circuit.
```

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	et Subsystem indexes where the inverse quantum Fourier transform is applie	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

```
7.54.5.57 to_JSON()
```

qpp::IJSON::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

```
7.54.6.2 operator << [2/4]
```

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_step	qpp::QCircuit::GateStep class

Returns

Output stream

```
7.54.6.3 operator << [3/4]
```

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
measure_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

```
7.54.6.4 operator << [4/4]
```

```
std::ostream& operator<< (
          std::ostream & os,
          const MeasureStep & measure_step ) [friend]</pre>
```

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.54.6.5 QEngine

```
friend class QEngine [friend]
```

7.54.7 Member Data Documentation

7.54.7.1 cmat_hash_tbl_

```
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
```

hash table with the matrices used in the circuit, with [Key = std::size_t, Value = cmat]

```
7.54.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.54.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.54.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.54.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.54.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
7.54.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
```

```
7.54.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.54.7.9 nc_
idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.54.7.10 nq_
idx qpp::QCircuit::nq_ [private]
number of qudits
7.54.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits/circuits.h

7.55 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

• QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

ket get_psi () const

Underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

idx get_dit (idx i) const

Value of the classical dit at position i.

• std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• bool get_measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured gudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

• const std::map < idx, idx > & get_stats () const

Measurement statistics for multiple runs.

• QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set_psi (const ket &psi)

Sets the underlying quantum state to psi.

• QEngine & reset_stats ()

Resets the collected measurement statistics hash table.

void reset (bool clear_stats=true)

Resets the engine.

virtual void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

void execute (idx reps=1, bool clear stats=true)

Executes the entire quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJSON::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

• std::vector< idx > get relative pos (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.55.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.55.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

qpp::QEngine(QCircuit&&)

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.55.2.4 ~QEngine()
```

```
\label{eq:condition} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

7.55.3 Member Function Documentation

```
7.55.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

```
7.55.3.4 execute() [3/3]

void qpp::QEngine::execute (
        idx reps = 1,
        bool clear_stats = true ) [inline]
```

Executes the entire quantum circuit.

Parameters

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

```
7.55.3.5 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.55.3.6 get_dit()
```

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

```
7.55.3.7 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.55.3.8 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit \emph{i} was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.55.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.55.3.10 get_non_measured()

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state $(|00\rangle + |11\rangle)/\sqrt{2}$, then the vector of outcome probabilities will be [0.5, 1].

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.55.3.12 get_psi()

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.55.3.13 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.55.3.14 get_stats()

```
const std::map<idx, idx>& qpp::QEngine::get_stats ( ) const [inline]
```

Measurement statistics for multiple runs.

Returns

Hash table with collected measurement statistics for multiple runs, with hash key being the decimal value of the vector of measurement results and value being the number of occurrences (of the vector of measurement results), with the most significant bit located at index 0 (i.e. top/left) of the classical dits array.

7.55.3.15 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.55.3.16 reset()

```
void qpp::QEngine::reset (
          bool clear_stats = true ) [inline]
```

Resets the engine.

Parameters

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.55.3.17 reset_stats()

```
QEngine& qpp::QEngine::reset_stats ( ) [inline]
```

Resets the collected measurement statistics hash table.

Returns

Reference to the current instance

7.55.3.18 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.55.3.19 set_measured_()

```
void qpp::QEngine::set_measured_ (
         idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.55.3.20 set_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

Parameters

```
psi State vector
```

Returns

Reference to the current instance

7.55.3.21 to_JSON()

qpp::IJSON::to_JSON() override

Displays the state of the engine in JSON format

Parameters

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.55.4 Member Data Documentation

```
7.55.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.55.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.55.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector
7.55.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit
7.55.4.5 stats_
std::map<idx, idx> qpp::QEngine::stats_ [protected]
measurement statistics for multiple runs
7.55.4.6 subsys_
std::vector<idx> qpp::QEngine::subsys_ [protected]
keeps track of the measured subsystems, re-label them after measurements
```

• classes/circuits/engines.h


The documentation for this class was generated from the following file:

7.56 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



Public Member Functions

- QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)
 - Constructs a noisy quantum engine out of a quantum circuit.
- void execute (const QCircuit::iterator::value_type &elem) override
 Executes one step in the quantum circuit.
- std::vector< std::vector< idx >> get_noise_results () const

Vector of noise results obtained before every step in the circuit.

Private Attributes

```
• const NoiseModel noise_
```

quantum noise model

 std::vector< std::vector< idx >> noise_results_ noise results

Additional Inherited Members

7.56.1 Detailed Description

```
\label{local_total_constraints} \begin{tabular}{ll} template < typename NoiseModel > \\ class qpp::QNoisyEngine < NoiseModel > \\ \end{tabular}
```

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

```
qpp::QEngine, qpp::QCircuit, qpp::NoiseBase
```

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every non-measurement step in the logical circuit. To add noise before a measurement, insert a no-op via qpp::QCircuit::nop().

Template Parameters

```
NoiseModel Quantum noise model, should be derived from qpp::NoiseBase
```

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

Parameters

qc	Quantum circuit
noise	Quantum noise model

7.56.3 Member Function Documentation

7.56.3.1 execute()

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

7.56.3.2 get_noise_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

Returns

Vector of noise results

7.56.4 Member Data Documentation

```
7.56.4.1 noise_
```

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

7.56.4.2 noise_results_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

noise results

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping coefficient

The documentation for this class was generated from the following file:


• classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

```
p Noise probability
```

The documentation for this class was generated from the following file:


• classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Bit Phase Flip Noise:$



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

• QubitDepolarizingNoise (double p)

Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Phase Damping Noise:$



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

• std::string description () const override Exception description.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Qudit dimension

7.64.3 Member Function Documentation

```
7.64.3.1 fill_Ks_()
```

Fills the Kraus operator vector.

Parameters

```
d Qudit dimension
```

Returns

Vector of Kraus operators representing the depolarizing noise

```
7.64.3.2 fill_probs_()
```

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.65.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_cinstance()), which returns a reference (thread_local reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton< T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template < typename T >
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

 std::string description () const override Exception description.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 description()

std::string qpp::exception::SizeMismatch::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

```
#include <classes/noise.h>
```

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

• classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


· classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

· ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate | y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

cmat py0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.

cmat py1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

cmat pz0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.

• cmat pz1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.

ket b00 {ket::Zero(4)}

Bell-00 state, as described in Nielsen and Chuang.

ket b01 {ket::Zero(4)}

Bell-01 state, as described in Nielsen and Chuang.

ket b10 {ket::Zero(4)}

Bell-10 state, as described in Nielsen and Chuang.

ket b11 {ket::Zero(4)}

Bell-11 state, as described in Nielsen and Chuang.

cmat pb00 {cmat::Zero(4, 4)}

Projector onto the Bell-00 state.

cmat pb01 {cmat::Zero(4, 4)}

Projector onto the Bell-01 state.

cmat pb10 {cmat::Zero(4, 4)}

Projector onto the Bell-10 state.

cmat pb11 {cmat::Zero(4, 4)}

Projector onto the Bell-11 state.

ket GHZ {ket::Zero(8)}

GHZ state.

ket W {ket::Zero(8)}

W state.

cmat pGHZ {cmat::Zero(8, 8)}

Projector onto the GHZ state.

cmat pW {cmat::Zero(8, 8)}

Projector onto the W state.

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

Default destructor.

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.70.3 Member Function Documentation

7.70.3.1 jn()

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of n qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
        idx n ) const [inline]
```

Minus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

	n	Non-negative integer
ſ	d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.70.3.5 plus()

```
ket qpp::States::plus (
        idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.70.3.6 zero()

```
ket qpp::States::zero (
        idx n,
        idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.70.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.70.5.3 b10
ket qpp::States::b10 {ket::Zero(4)}
Bell-10 state, as described in Nielsen and Chuang.
7.70.5.4 b11
ket qpp::States::b11 {ket::Zero(4)}
Bell-11 state, as described in Nielsen and Chuang.
7.70.5.5 GHZ
ket qpp::States::GHZ {ket::Zero(8)}
GHZ state.
7.70.5.6 pb00
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
Projector onto the Bell-00 state.
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
```

```
7.70.5.8 pb10
```

```
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
```

Projector onto the Bell-10 state.

```
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-Y 0-eigenstate |y+><y+|.

```
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
```

```
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string description () const override Exception description.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std \leftrightarrow ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual \sim Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

 $template < typename\ T = std::chrono::duration < double >, typename\ CLOCK_T = std::chrono::steady_clock > class\ qpp::Timer < T,\ CLOCK_T >$

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_T	

7.72.2 Constructor & Destructor Documentation

7.72.2.1 Timer()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady &clock> \\ qpp::Timer < T, CLOCK_T >::Timer ( ) [inline], [noexcept] \\ \end{tabular}
```

Constructs an instance with the current time as the starting point.

7.72.2.2 \sim Timer()

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.3 tic()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.4 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.5 toc()

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

• std::string description () const override Exception description.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 description()

std::string qpp::exception::TypeMismatch::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

• std::string description () const override Exception description.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 description()

std::string qpp::exception::UndefinedType::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

• std::string description () const override Exception description.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 description()

std::string qpp::exception::Unknown::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

classes/exception.h


7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

- value_type_ (const QCircuit *value_type_qc)
- Default value_type_ constructor.value_type_ (const value_type_ &)=default

Default copy constructor.

value_type_ & operator= (const value_type_ &)=default

Default copy assignment operator.

Public Attributes

- const QCircuit * value_type_qc_
 - < non-owning pointer to the grand-parent const quantum circuit
- StepType type_{StepType::NONE}

step type

```
    idx ip_ {static_cast < idx > (-1)}
        instruction pointer
    std::vector < GateStep >::const_iterator gates_ip_ {}
        gates instruction pointer
    std::vector < MeasureStep >::const_iterator measurements_ip_ {}
        measurements instruction pointer
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.76.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

7.76.2 Constructor & Destructor Documentation

Parameters

```
        value_type_qc
        Pointer to constant quantum circuit
```

Default copy constructor.

7.76.3 Member Function Documentation

```
7.76.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.4 Member Data Documentation

```
7.76.4.1 gates_ip_
```

gates instruction pointer

```
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
```

7.76.4.2 ip_

```
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
```

instruction pointer

7.76.4.3 measurements_ip_

 $\verb|std::vector<MeasureStep>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements_{\leftarrow ip_ {}}|$

measurements instruction pointer

7.76.4.4 type_

StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}

step type

7.76.4.5 value_type_qc_

```
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
```

< non-owning pointer to the grand-parent const quantum circuit

The documentation for this class was generated from the following file:


· classes/circuits/circuits.h

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string description () const override Exception description.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 description()

std::string qpp::exception::ZeroSize::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit description.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value_type_

Value type class for qpp::QCircuit::iterator.

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Qudit quantum circuits.

8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Qudit quantum engines.

8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.3.1 Detailed Description

Quantum error correcting codes.

8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

• class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

· class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.4.1 Detailed Description

Exceptions.

8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Quantum gates.

8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Initialization.

8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Noise models.

8.9 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Random devices.

8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit_circuit

Classical reversible circuit simulator.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Support for classical reversible circuits.

8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::States

const Singleton class that implements most commonly used states

Namespaces

qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Quantum states.

8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.12.1 Detailed Description

Timing.

8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

· qpp::literals

Enumerations

enum { qpp::RES, qpp::PROB, qpp::ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (integer overload)
- constexpr cplx qpp::literals::operator"" _i (long double x) noexcept
 - User-defined literal for complex $i=\sqrt{-1}$ (real overload)
- constexpr std::complex< float > qpp::literals::operator""_if (unsigned long long int x) noexcept
 - User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr std::complex< float > qpp::literals::operator"" _if (long double x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (real overload)
- cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.13.1 Detailed Description

Constants.

8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >

  dyn col vect< double > gpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.14.1 Detailed Description

Entanglement functions.

8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

• template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.15.1 Detailed Description

Entropy functions.

8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.16.1 Detailed Description

Experimental/test functions/classes.

8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.
• template<typename Derived >
  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
ullet template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

Eigenvectors.

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
      Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double <a href="mailto:qpp::schatten">qpp::schatten</a> (const Eigen::MatrixBase</a> Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

Functor. • template<typename T > dyn_mat< typename T::Scalar > qpp::kron (const T &head) Kronecker product. • template<typename T , typename... Args> dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail) Kronecker product. • template<typename Derived >dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As) Kronecker product. template<typename Derived > dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As) Kronecker product. template<typename Derived > dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n) Kronecker power. template<typename T > dyn_mat< typename T::Scalar > qpp::dirsum (const T &head) Direct sum. • template<typename T , typename... Args> dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail) ullet template<typename Derived >dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As) Direct sum. template<typename Derived > dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As) Direct sum. template<typename Derived > dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n) Direct sum power. template<typename Derived > dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx cols) Reshape. template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B) Commutator. template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B) Anti-commutator. ullet template<typename Derived >dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

Projector

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)

Gram-Schmidt orthogonalization.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)

Gram-Schmidt orthogonalization.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $dyn_mat < typename Derived::Scalar > dpp::grams (const Eigen::MatrixBase < Derived > &A)$

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >--:value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

• template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if < is_iterable < Container > \leftarrow ::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator"" _prj ()

Multi-partite qubit projector user-defined literal.

template<class T >

void qpp::internal::hash_combine (std::size_t &seed, const T &v)

Hash combine.

• template<typename Derived >

 $std::size_t \; qpp::hash_eigen \; (const \; Eigen::MatrixBase < \; Derived > \&A, \; std::size_t \; seed=0)$

Computes the hash of en Eigen matrix/vector/expression.


8.17.1 Detailed Description

Generic quantum computing functions.

8.18 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

- template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container >
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std::enable if< is iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.18.1 Detailed Description

Input/output functions.

8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >

 $\label{lem:dyn_col_vect} $$ dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims) $$$

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat $> qpp::measure_seq$ (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.19.1 Detailed Description

Measurement functions.

8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Input/output manipulators.

8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.21.1 Detailed Description

Singleton pattern via CRTP.

8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

• struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool gpp::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr> T qpp::internal::abs chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr>
 T qpp::internal::abs_chop (const T &x, double QPP_UNUSED_chop=qpp::chop)

8.22.1 Detailed Description

Internal utility functions.

8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if < std::is_same < typename Derived::Scalar, cplx >::value, dyn_mat < cplx > >::type qpp
 ::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::← Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.23.1 Detailed Description

Input/output interfacing with MATLAB.

8.24 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int >> qpp::convergents (double x, idx N)

Convergents.


8.24.1 Detailed Description

Number theory functions.

8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
 ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat gpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

8.25.1 Detailed Description

Quantum operation functions.

8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <map>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
```

```
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.26.2 Macro Definition Documentation


```
8.26.2.1 QPP_UNUSED_
```

#define QPP_UNUSED_

8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED =1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.27.1 Detailed Description

Randomness-related functions.

8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::sigma (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_{\leftarrow} iterable< Container >::value >::type *=nullptr)$

Standard deviation.

• template<typename Container >

double double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.

8.28.1 Detailed Description


Statistics functions.

8.29 traits.h File Reference

Type traits.

8.29 traits.h File Reference 397

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void < Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().⇔ end()), decltype(*(std::declval< T >().begin()))>>

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```

8.29.1 Detailed Description


Type traits.

398 File Documentation

8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.30.1 Detailed Detai	escription
--	------------

Type aliases.

8.31 /home/vlad/qpp/README.md File Reference

400 File Documentation

Index

/home/vlad/qpp/README.md, 399	anticomm
~Bit circuit	qpp, 31
qpp::Bit_circuit, 132	any
~Codes	qpp::Dynamic bitset, 160
qpp::Codes, 139	apply
~Dynamic_bitset	qpp, 31–33
qpp::Dynamic_bitset, 159	applyCTRL
~Gates	qpp, 34
qpp::Gates, 176	applyQFT
~IDisplay	qpp, 35
qpp::IDisplay, 192	applyTFQ
~IJSON	
	qpp, 35
qpp::IJSON, 193	avg
~Init	qpp, 36
qpp::Init, 195	b00
~NoiseBase	_
qpp::NoiseBase, 242	qpp::States, 339
~QCircuit	b01
qpp::QCircuit, 272	qpp::States, 339
~QEngine	b10
qpp::QEngine, 301	qpp::States, 339
\sim RandomDevices	b11
qpp::RandomDevices, 327	qpp::States, 340
\sim Singleton	bCNOT_
qpp::internal::Singleton, 331	qpp::Bit_circuit, 136
\sim States	bFRED_
qpp::States, 336	qpp::Bit_circuit, 136
~Timer	bNOT_
qpp::Timer, 347	qpp::Bit_circuit, 136
" 1	bSWAP_
A_	qpp::Bit_circuit, 136
qpp::internal::IOManipEigen, 199	bTOF
abs_chop	qpp::Bit_circuit, 136
qpp::internal, 120	begin
absm	qpp::QCircuit, 274, 275
qpp, 29	bigint
abssq	qpp, 26
qpp, 29, 30	Bit circuit
add_circuit	qpp::Bit circuit, 131
qpp::QCircuit, 272	bloch2rho
add dit	
qpp::QCircuit, 273	qpp, 36
add_hash_	bra
qpp::QCircuit, 274	qpp, 26
	btotal_
add_qudit	qpp::Bit_circuit, 136
qpp::QCircuit, 274	
adjoint	c_reg_
qpp, 30	qpp::QCircuit::MeasureStep, 237
all	cCTRL_custom
qpp::Dynamic_bitset, 159	qpp::QCircuit, 277

OTP!	
cCTRL	chop_
qpp::QCircuit, 275–277	qpp::internal::IOManipEigen, 200
CNOTba	qpp::internal::IOManipPointer, 202
qpp::Gates, 185	qpp::internal::IOManipRange, 206
CNOT	classes/circuits/circuits.h, 361
qpp::Bit_circuit, 132	classes/circuits/engines.h, 362
qpp::Gates, 185	classes/codes.h, 363
CTRL_custom	classes/exception.h, 363
qpp::QCircuit, 280	classes/gates.h, 365
CTRL	classes/idisplay.h, 366
qpp::Gates, 177	classes/init.h, 367
qpp::QCircuit, 278, 279	classes/noise.h, 368
cbegin	classes/random_devices.h, 369
qpp::QCircuit, 275	classes/reversible.h, 369
cend	classes/states.h, 370
qpp::QCircuit, 277	classes/timer.h, 371
check_cvector	cmat
qpp::internal, 121	qpp, 27
check_dims	cmat_hash_tbl_
qpp::internal, 121	qpp::QCircuit, 295
check_dims_match_cvect	Codes
qpp::internal, 121	qpp::Codes, 139
check_dims_match_mat	codeword
qpp::internal, 121	qpp::Codes, 139
check_dims_match_rvect	comm
qpp::internal, 121	qpp, 38
check_eq_dims	complement
qpp::internal, 121	qpp, 38
check_matching_sizes	compperm
qpp::internal, 122	qpp, 39
check_no_duplicates	compute_probs_
qpp::internal, 122	qpp::NoiseBase, 242
check_nonzero_size	compute_state_
qpp::internal, 122	qpp::NoiseBase, 243
check_perm	concurrence
qpp::internal, 122	qpp, 39
check_qubit_cvector	conjugate
qpp::internal, 122	qpp, 39
check_qubit_matrix	const_iterator
qpp::internal, 122	qpp::QCircuit, 270
check_qubit_rvector	constants.h, 372
qpp::internal, 123	contfrac2x
check_qubit_vector	qpp, 40
qpp::internal, 123	convergents
check_rvector	qpp, 40, 41
qpp::internal, 123	cor
check_square_mat	qpp, 4 1
qpp::internal, 123	cosm
check_subsys_match_dims	qpp, 42
qpp::internal, 123	count
check_vector	qpp::Dynamic_bitset, 160
qpp::internal, 123	count_
choi2kraus	qpp::Bit_circuit, 136
qpp, 37	qpp::QCircuit, 295
choi2super	cov
qpp, 37	qpp, <mark>42</mark>
chop	cplx
qpp, 116	qpp, <mark>27</mark>

ctrl_		dirsu	um2
	qpp::QCircuit::GateStep, 189		qpp::internal, 124
Cust	tomException	dirsu	umpow
	qpp::exception::CustomException, 141		qpp, 45
cwis	e	disp	
	qpp, 43	•	qpp, 46–48
CZ	dbb,	disp	
02	qpp::Gates, 185	alop	qpp::Dynamic_bitset, 160
	qppdates, 100		
d_			qpp::IDisplay, 192
_ _	qpp::NoiseBase, 246		qpp::QCircuit, 280
	qpp::QCircuit, 296		qpp::QCircuit::iterator::value_type_, 356
data			qpp::QEngine, 301
data			qpp::Timer, 347
	qpp::Dynamic_bitset, 160		qpp::internal::IOManipEigen, 199
dept			qpp::internal::IOManipPointer, 202
	qpp::Bit_circuit, 137		qpp::internal::IOManipRange, 205
desc	cription	disp	lay_impl_
	qpp::exception::CustomException, 142		qpp::internal::Display_Impl_, 154
	qpp::exception::DimsInvalid, 144	dits_	
	qpp::exception::DimsMismatchCvector, 146	unto_	- qpp::QEngine, 307
	qpp::exception::DimsMismatchMatrix, 147	dma	
	qpp::exception::DimsMismatchRvector, 149	uma	
	qpp::exception::DimsMismatchVector, 151		qpp, 27
	qpp::exception::DimsNotEqual, 153	ayn_	_col_vect
			qpp, 27
	qpp::exception::Duplicates, 156	dyn_	_mat
	qpp::exception::Exception, 172		qpp, 27
	qpp::exception::InvalidIterator, 197	dyn_	_row_vect
	qpp::exception::MatrixMismatchSubsys, 220		qpp, 28
	qpp::exception::MatrixNotCvector, 222	Dyna	amic_bitset
	qpp::exception::MatrixNotRvector, 224	•	qpp::Dynamic_bitset, 159
	qpp::exception::MatrixNotSquare, 226		_ /
	qpp::exception::MatrixNotSquareNorCvector, 228	ee	
	qpp::exception::MatrixNotSquareNorRvector, 230		qpp, 116
	qpp::exception::MatrixNotSquareNorVector, 232	egco	
	qpp::exception::MatrixNotVector, 234	J	qpp, 48
	qpp::exception::NoCodeword, 239	eig	-11-11-7 -
	qpp::exception::NotBipartite, 249	9	qpp, 49
	qpp::exception::NotImplemented, 250	elen	
		CICII	-
	app::exception::NotQubitCvector, 252	اء ء، ء	qpp::QCircuit::iterator, 218
	qpp::exception::NotQubitMatrix, 254	end	00: 1,000,004
	qpp::exception::NotQubitRvector, 255		qpp::QCircuit, 280, 281
	qpp::exception::NotQubitSubsys, 257	end_	
	qpp::exception::NotQubitVector, 259		qpp::Timer, 349
	qpp::exception::OutOfRange, 261		qpp::internal::IOManipPointer, 203
	qpp::exception::PermInvalid, 263		qpp::internal::IOManipRange, 206
	qpp::exception::PermMismatchDims, 265	enta	nglement
	qpp::exception::QuditAlreadyMeasured, 322		qpp, 49, 50
	qpp::exception::SizeMismatch, 333	enta	inglement.h, 373
	qpp::exception::SubsysMismatchDims, 345		opies.h, 375
	qpp::exception::TypeMismatch, 351	entro	•
	qpp::exception::UndefinedType, 353	Citti	• •
	qpp::exception::Unknown, 354	eval	qpp, 50
		evai	
.11	qpp::exception::ZeroSize, 359		qpp, 51
det	40	evec	
	qpp, 43	_	qpp, 51
diffe	rence_type	Exce	eption
	qpp::QCircuit::iterator, 214		qpp::exception::Exception, 172
dirsu	ım	exec	cute
	qpp, 43–45		qpp::QEngine, 302

qpp::QNoisyEngine, 311	qpp::QEngine, 303
expandout	get_cmat_hash_tbl_
qpp::Gates, 177, 178	qpp::QCircuit, 284
experimental/experimental.h, 376	get_d
expm	qpp::NoiseBase, 243
qpp, 52	qpp::QCircuit, 284
FDFD	get_depth
FRED	qpp::QCircuit, 284
qpp::Bit_circuit, 132	get_dim_subsys
qpp::Gates, 185	qpp::internal, 124
factors	get_dit
qpp, 52	qpp::QEngine, 303
Fd	get_dits
qpp::Gates, 179	qpp::QEngine, 303
fill_Ks_	get_duration
qpp::QuditDepolarizingNoise, 325	qpp::Timer, 348
fill_probs_	get_gate_count
qpp::QuditDepolarizingNoise, 325	qpp::Bit_circuit, 133
first	qpp::QCircuit, 285
qpp::internal::IOManipRange, 206	get_gate_depth
flip	qpp::Bit_circuit, 133
qpp::Dynamic_bitset, 161 functions.h, 376	get_gates_
	qpp::QCircuit, 285
funm	get_instance
qpp, 52	qpp::internal::Singleton, 331
GHZ	get_last_idx
qpp::States, 340	qpp::NoiseBase, 243
gate	get_last_K
qpp::QCircuit, 281, 282	qpp::NoiseBase, 244
gate_custom	get_last_p
qpp::QCircuit, 282	qpp::NoiseBase, 244
gate_fan	get_measured
qpp::QCircuit, 283, 284	qpp::QCircuit, 285, 286
gate_hash_	qpp::QEngine, 303, 304
qpp::QCircuit::GateStep, 189	get_measurement_count
gate_type_	qpp::QCircuit, 286
qpp::QCircuit::GateStep, 189	get_measurements_
GateStep	qpp::QCircuit, 287
qpp::QCircuit::GateStep, 188	get_name
GateType	qpp::Gates, 180
qpp::QCircuit, 270	qpp::QCircuit, 287
Gates	get_nc
qpp::Gates, 176	qpp::QCircuit, 287
gates_	get_noise_results
qpp::QCircuit, 296	qpp::QNoisyEngine, 311
gates_ip_	get_non_measured
qpp::QCircuit::iterator::value_type_, 357	qpp::QCircuit, 287
gcd	qpp::QEngine, 304
qpp, 53	get_nop_count
gconcurrence	qpp::QCircuit, 288
qpp, 54	get_nq
generated_	qpp::QCircuit, 288
qpp::NoiseBase, 246	get_num_subsys
get	qpp::internal, 124
qpp::Dynamic_bitset, 161	get_prng
get_Ks	qpp::RandomDevices, 328
qpp::NoiseBase, 243	get_probs
get_circuit	qpp::NoiseBase, 244
3 <u>-</u> - · · 	

qpp::QEngine, 304	qpp::States, 339
get_psi	internal::Singleton< RandomDevices >
qpp::QEngine, 304	qpp::RandomDevices, 329
get_relative_pos_	inverse
qpp::QEngine, 305	qpp, 57
get_stats	invperm
qpp::QEngine, 305	qpp, 58
get_step_count	ip
qpp::QCircuit, 288	qpp, 58, 59
get_thread_local_instance	ip_
qpp::internal::Singleton, 331	qpp::QCircuit::iterator::value_type_, 357
grams	
	isprime
qpp, 54, 55	qpp, 59
Н	iterator
	qpp::QCircuit::iterator, 215
qpp::Gates, 185	iterator_category
hash_combine	qpp::QCircuit::iterator, 214
qpp::internal, 124	
hash_eigen	jn
qpp, 55	qpp::States, 337
heig	
qpp, 56	ket
hevals	qpp, 28
qpp, 56	kraus2choi
hevects	qpp, 59
qpp, 57	kraus2super
4ρρ, 37	•
i	qpp, 60
I_ app::NoicePace 246	kron
qpp::NoiseBase, 246	qpp, 60, 62, 63
IOManipEigen	qpp::QCircuit, 288
qpp::internal::IOManipEigen, 199	kron2
IOManipPointer	qpp::internal, 125
qpp::internal::IOManipPointer, 201, 202	kronpow
IOManipRange	qpp, 63
qpp::internal::IOManipRange, 205	Ks
Id	qpp::NoiseBase, 246
qpp::Gates, 180	,
ld2	last
qpp::Gates, 186	qpp::internal::IOManipRange, 206
idx	lcm
qpp, 28	-
index	qpp, 64
_	load
qpp::Dynamic_bitset, 162	qpp, 65
infty	qpp::RandomDevices, 328
qpp, 116	loadMATLAB
Init	qpp, 65, 66
qpp::Init, 195	logdet
input_output.h, 381	qpp, 67
instruments.h, 382	logm
internal/classes/iomanip.h, 384	qpp, 67
internal/classes/singleton.h, 385	lognegativity
internal/util.h, 385	qpp, 67, 69
internal::Singleton< const Codes >	qpp, 07, 09
	MATI AP/motleb b 207
qpp::Codes, 139	MATLAB/matlab.h, 387
internal::Singleton < const Gates >	MODMUL
qpp::Gates, 185	qpp::Gates, 180
internal::Singleton< const Init >	marginalX
qpp::Init, 196	qpp, 69
internal::Singleton < const States >	marginalY

qpp, 69	qpp::QCircuit::MeasureStep, 237
mats_hash_	nc_
qpp::QCircuit::MeasureStep, 237	qpp::QCircuit, 297
maxn	negativity
qpp, 116	qpp, 81
measure	noise
qpp, 70–74	qpp::QNoisyEngine, 311
	noise_results_
measure_seq	
qpp, 75, 76	qpp::QNoisyEngine, 311
MeasureStep	noise_type
qpp::QCircuit::MeasureStep, 236	qpp::NoiseBase, 241
MeasureType	NoiseBase
qpp::QCircuit, 271	qpp::NoiseBase, 241, 242
measured_	none
qpp::QCircuit, 296	qpp::Dynamic_bitset, 162
measurement_count_	nop
qpp::QCircuit, 296	qpp::QCircuit, 290
measurement_type_	norm
qpp::QCircuit::MeasureStep, 237	qpp, 82
measurements_	normalize
qpp::QCircuit, 296	qpp, <mark>82</mark>
measurements_ip_	nq_
<pre>qpp::QCircuit::iterator::value_type_, 357</pre>	qpp::QCircuit, 297
measureV	number_theory.h, 388
qpp::QCircuit, 289	_ , ,
measureZ	offset_
qpp::QCircuit, 290	qpp::Dynamic_bitset, 162
	omega
mes	qpp, 82
qpp::States, 337	one
minus	
qpp::States, 337	qpp::States, 338
mket	operations.h, 390
qpp, 76, 77	operator!=
modinv	qpp::Dynamic_bitset, 163
qpp, 77	qpp::QCircuit::iterator, 215
modmul	operator<<
qpp, 78	qpp::IDisplay, 192
modpow	qpp::QCircuit, 294, 295
	operator*
qpp, 78	qpp::QCircuit::iterator, 216
mprj	operator()
qpp, 79	•
msg_	qpp::NoiseBase, 244, 245
qpp::exception::Exception, 173	qpp::internal::EqualEigen, 169
multiidx2n	qpp::internal::HashEigen, 190
qpp, 80	operator++
qpp::internal, 125	qpp::QCircuit::iterator, 216
qpp	operator-
n2multiidx	qpp::Dynamic_bitset, 163
qpp, 80	operator=
qpp::internal, 125	qpp::QCircuit::iterator, 216
N_	qpp::QCircuit::iterator::value_type_, 357
qpp::internal::IOManipPointer, 203	qpp::QEngine, 305
n_	qpp::internal::IOManipPointer, 202
qpp::Dynamic_bitset, 168	qpp::internal::IOManipRange, 206
NOT	qpp::internal::Singleton, 331
qpp::Bit_circuit, 134	apptorriag.otori, oo i
	operator==
name_	
_	operator== qpp::Dynamic_bitset, 163
name_ qpp::QCircuit, 296 qpp::QCircuit::GateStep, 189	operator==

qpp::literals, 126	pz0
operator"" _i	qpp::States, 342
qpp::literals, 126, 127	pz1
operator"" _if	qpp::States, 342
qpp::literals, 127	
operator"" _ket	QCircuit
qpp::literals, 127	qpp::QCircuit, 272
operator"" _prj	QEngine
qpp::literals, 128	qpp::QCircuit, 295
• • •	qpp::QEngine, 300, 301
p_	QFT
qpp::internal::IOManipPointer, 203	qpp, 89
pGHZ	qpp::QCircuit, 290, 291
qpp::States, 341	QNoisyEngine
pb00	qpp::QNoisyEngine, 310
qpp::States, 340	QPP_UNUSED_
pb01	qpp.h, 393
qpp::States, 340	qc_
pb10	qpp::QCircuit::iterator, 218
qpp::States, 340	qpp::QEngine, 308
pb11	qmutualinfo
qpp::States, 340	qpp, 89, 90
pi	qpp, 13
qpp, 117	absm, 29
plus	abssq, 29, 30
qpp::States, 338	adjoint, 30
	anticomm, 31
pointer	
qpp::QCircuit::iterator, 214	apply, 31–33
powm	applyCTRL, 34
qpp, 83	applyQFT, 35
prj	applyTFQ, 35
qpp, 83	avg, 36
prng_	bigint, 26
qpp::RandomDevices, 329	bloch2rho, 36
probs_	bra, 26
qpp::NoiseBase, 246	choi2kraus, 37
qpp::QEngine, 308	choi2super, 37
prod	chop, 116
qpp, 84	cmat, 27
psi_	comm, 38
qpp::QEngine, 308	complement, 38
ptrace	compperm, 39
qpp, 85	concurrence, 39
ptrace1	conjugate, 39
qpp, 86	contfrac2x, 40
ptrace2	convergents, 40, 41
qpp, 87	cor, 41
ptranspose	cosm, 42
qpp, 88	cov, 42
Wq	cplx, 27
qpp::States, 341	cwise, 43
px0	det, 43
qpp::States, 341	dirsum, 43–45
px1	dirsumpow, 45
qpp::States, 341	disp, 46–48
py0	dmat, 27
qpp::States, 341	dyn_col_vect, 27
py1	dyn_col_veet, 27
qpp::States, 341	dyn_mat, 27 dyn_row_vect, 28
Approximos, or i	3, <u>.</u>

ee, 116	QFT, 89
egcd, 48	qmutualinfo, 89, 90
eig, 49	rand, 90–92
entanglement, 49, 50	randH, 93
entropy, 50	randidx, 93
evals, 51	randket, 93
evects, 51	randkraus, 94
expm, 52	randn, 94–96
factors, 52	randperm, 96
funm, 52	randprime, 97
gcd, 53	randprob, 97
gconcurrence, 54	randrho, 97
grams, 54, 55	randU, 98
hash_eigen, 55	randV, 98
heig, 56	renyi, 98, 99
hevals, 56	reshape, 99
hevects, 57	rho2bloch, 100
idx, 28	rho2pure, 100
infty, 116	save, 101
inverse, 57	saveMATLAB, 101, 102
invperm, 58	schatten, 103
ip, 58, 59	schmidtA, 103 schmidtB, 104
isprime, 59 ket, 28	schmidtcoeffs, 105
kraus2choi, 59	schmidtprobs, 106
kraus2super, 60	sigma, 107
kron, 60, 62, 63	sinm, 107
kronpow, 63	spectralpowm, 107
lcm, 64	sqrtm, 108
load, 65	ST, 29
loadMATLAB, 65, 66	sum, 108, 109
logdet, 67	super2choi, 109
logm, 67	svals, 110
lognegativity, 67, 69	svd, 110
marginalX, 69	svdU, 111
marginaly, 69	svdV, 111
maxn, 116	syspermute, 111, 112
measure, 70–74	TFQ, 112
measure_seq, 75, 76	to_void, 28
mket, 76, 77	trace, 113
modiny, 77	transpose, 113
modmul, 78	tsallis, 114
modpow, 78	uniform, 115
mprj, 79	var, 115
multiidx2n, 80	x2contfrac, 115
n2multiidx, 80	qpp.h, 392
negativity, 81	QPP_UNUSED_, 393
norm, 82	qpp::Bit_circuit, 129
normalize, 82	\sim Bit_circuit, 132
omega, 82	bCNOT_, 136
pi, 117	bFRED_, 136
powm, 83	bNOT_, 136
prj, 83	bSWAP_, 136
prod, 84	bTOF_, 136
ptrace, 85	Bit_circuit, 131
ptrace1, 86	btotal_, 136
ptrace2, 87	CNOT, 132
ptranspose, 88	count_, 136

depth_ 137 FRED, 132 get_gate_count, 133 get_gate_depth, 133 NOT, 134 reset, 134 reset, 134 TOF, 135 X, 135 TOF, 135 X, 135 TOF, 186 XMAPd, 182 SWAPd, 186 TOF, 186 XM, 186 Codes, 139 Codes, 139 Codes, 139 Codeword, 139 Type, 138 dpp::Dynamic_bitset, 156		
get_gate_depth, 133	depth_, 137	Rn, 181
get_gate_depth, 133 NOT, 134 SWAP, 134 SWAP, 134 SWAP, 135 TOF, 135 X, 135 QpD:Codes, 137 ~Codes, 139 Codes, 139 Codes, 139 codeword, 139 internal::Singleton < const Codes >, 139 internal::Singleton < const Init >, 187 coperator <, 192 dpp::IJSON, 193 ~IJSON, 193 ~IJSON, 193 ~IJSON, 193 ~IJSON, 193 v_IJSON, 193 v_I	FRED, 132	RX, 181
NOT. 134 reset, 134 reset, 134 SWAP, 134 TOF, 135 X, 135 QPD::Codes, 137	get_gate_count, 133	RY, 182
reset, 134 SWAP, 135 TOF, 135 X, 135 Qp::Codes, 137	get_gate_depth, 133	RZ, 182
SWAP, 134 TOF, 135 X, 135 X, 135 TOF, 186 X, 136 Codes, 139 Codes, 139 Codes, 139 Codes, 139 Type, 138 Type, 139 Type, 130 Type, 134 Type, 139 Type, 131 Type, 132 Type, 131 Type, 131 Type, 139 Type, 131 Type, 131 Type, 131 Type, 139 Type, 131 Type, 131 Typ	NOT, 134	S, 186
TOF, 135 X, 135 qpp::Codes, 137	reset, 134	SWAPd, 182
x, 135 qpp:Codes, 137	SWAP, 134	SWAP, 186
qpp::Codes, 139	TOF, 135	T, 186
qpp::Codes, 139	X, 135	TOF, 186
Codes, 139		
Codes, 139	∼Codes, 139	Xd, 184
codeword, 139 internal::Singleton < const Codes >, 139 Type, 138 qpp::Dynamic_bitset, 156 ~Dynamic_bitset, 159 all, 159 any, 160 count, 160 display, 160 Dynamic_bitset, 159 ilip, 161 get, 161 get, 161 get, 162 operator =, 163 reset, 165, 166 set, 166 set, 166 set, 166 set, 167 storage_size_, 167 storage_size_, 167 storage_type, 159 to_string, 167 v168 value_type, 159 to_string, 167 v168 cNOTDa, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 ld, 180 ld, 180 ld, 180 internal::Singleton < const Codes >, 185 internal:Bispleton < const Codes >, 185 cTRL, 273 add_hash_, 274 add_qudit, 273 add_hash_, 274 add_qudit, 277 cCTRL_custom, 280		
internal::Singleton < const Codes >, 139 Type, 138 qpp::Dynamic_bitset, 156		
Type, 138 app::Dynamic_bitset, 156 ~Dynamic_bitset, 159 all, 159 any, 160 count, 160 data, 160 display, 160 Dynamic_bitset, 159 flip, 161 get, 161 get, 162 none, 162 operator-, 163 operator-, 165 reset, 165, 166 set, 166 set, 166 sot, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 v_, 168 storage_type, 159 to_string, 167 v_, 168 control, 185 CNOT, 185 CNOT, 185 CNOT, 185 CNOT, 185 CNOT, 185 CTRL, 177 Gates, 176 Gates, 176 get_name, 180 H, 185 ld, 180 ld, 180 ld, 180 ld, 180 ld, 180 ld, 186 internal::Singleton < const Init >, 196 display, 192 operator <<, 192 operator <<, 192 operator <<, 192 operator < , 192 operator < operator <		
qpp::Dynamic_bitset, 156	_	
~Dynamic_bitset, 159 all, 159 all, 159 count, 160 count, 160 data, 160 display, 160 Dynamic_bitset, 159 flip, 161 get, 161 get, 162 operator-, 163 stand, 165 reset, 165, 166 set, 166 size, 167 storage_size, 167 storage_size, 167 storage_size, 168 value_type, 159 to_string, 167 v168 value_type, 159 cOKOTba, 185 CNOT, 185 CNOT, 185 CNOT, 185 CNOT, 185 CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Id, 180 Id, 180 Id, 186		
all, 159 any, 160 count, 160 data, 160 display, 160 Dynamic_bitset, 159 flip, 161 index, 162 operator , 163 operator , 165 set, 166 size, 167 storage_size_, 167 storage_size_, 168 value_type, 159 to_string, 167 v168 count, 167 v168 count, 167 count, 168 count, 169 count, 199 count, 194 count, 194 count, 194 count, 194 count, 194 count, 195 count, 194 count, 194 count, 194 count, 194 count, 195 count, 194 count, 195 count, 195 count, 195 count, 195 count, 195 count, 195 count, 274 count, 275		
any, 160 count, 160 data, 160 display, 160 Dynamic_bitset, 159 flip, 161 index, 162 n, 168 none, 162 operator!_, 163 operator!_, 163 operator!_, 163 reset, 165, 166 size, 167 storage_size_, 167 storage_size_, 168 value_type, 159 to_string, 167 V, 168 value_type, 159 count, 177, 178 FRED, 185 FG, 179 Gates, 176 get_name, 180 H, 185 id, 180 id2, 186 internal::Singleton < const Gates >, 185 respiration, 193 valusON, 193 valusO		
count, 160 data, 160 data, 160 display, 160 Dynamic_bitset, 159 flip, 161 get, 161 get, 162 none, 162 none, 162 operator!=, 163 operator-, 163 operator-=, 163 rand, 165 set, 166 size, 167 storage_size_, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 cynor_, 168 cynor_, 169 cynor_, 168 cynor_, 169 cynor_, 193 cynor_, 194 cynor_, 194 cynor_, 195 cynor_, 195 cynor_, 195 cynor_, 195 cynor_, 195 cynor_, 196 cynor_, 195 cynor_, 195 cynor_, 193 cylat, 195 cynor_, 196		•
data, 160 display, 160 Dynamic_bitset, 159 flip, 161 get, 161 index_, 162 n_, 168 none, 162 operator!=, 163 operator.=, 163 reset, 165, 166 set, 166 size, 167 storage_size_, 167 storage_size_, 168 value_type, 159 to_string, 167 v_, 168 value_type, 159 dpp::RoiseBase, 241 compute_probs_, 242 compute_probs_, 242 compute_state_, 243 d_, 246 generated_, 246 generated_, 246 get_last_ldx, 243 get_last_ldx, 243 get_last_jdx, 243 get_last_jdx, 243 get_last_p, 244 size, 167 storage_size_, 167 storage_size_, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 dpp::Gates, 174		
display, 160 Dynamic_bitset, 159 flip, 161 get, 161 index_, 162 n_, 168 none, 162 offset_, 162 operator!=, 163 operator=, 163 operator=, 163 rand, 165 reset, 165, 166 size, 167 storage_size_, 168 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::NoiseBase, 242 compute_state_, 243 d_, 246 generated_, 246 get_ks, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_p, 244 storage_size_, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::RoiseBase, 241, 242 operator(), 244, 245 probs_, 246 compute_probs_, 241 i_, 246 storage_type, 159 conse_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs_, 246 conse_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs_, 246 conse_type, 247 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::NoiseType::StateIndependent, 335 qpp::NoiseType::StateIndependent, 336 qpp::NoiseType::StateIndependent, 336 qpp::NoiseType::StateIndependent, 336 qpp::NoiseType::StateIndepend		
Dynamic_bitset, 159 flip, 161 get, 161 get, 161 index_, 162 n_, 168 none, 162 operatorl=, 163 operator-, 163 operator==, 163 rand, 165 reset, 165, 166 site, 166 size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 cNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Init, 195 Internal:Singleton < const Init >, 196 Internal:Singleton < const Internal:Singleton < const Init >, 196 Internal:Singleton < const		
flip, 161 get, 161 get, 161 get, 161 index_, 162 n_, 168 none, 162 operatorle, 163 operator, 163 operator, 163 operatore, 165 reset, 165, 166 set, 166 size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 ~Gates, 176 CNOTba, 185 CNOTba, 185 CNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Init, 195 internal::Singleton < const Init >, 196 qpp::NoiseBase, 242 compute_probs_, 242 compute_probs_, 242 compute_state_, 243 d, 246 generated_, 246 generated_, 246 generated_, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_p, 244 get_probs, 244 storage_size_, 167 storage_size_, 168 storage_type, 159 to_string, 167 v, 168 value_type, 159 qpp::NoiseBase < T >, 239 qpp::NoiseType::StateDependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 324 dpp::NoiseType::StateIndependent, 324 qpp::NoiseType::StateIndependent, 324 qpp::NoiseT	• •	
get, 161 index_, 162 n_, 168 none, 162 operatorle, 163 operator-=, 163 operator-=, 163 rand, 165 reset, 166 set, 166 size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 cNOTba, 185 CNOTba, 185 CNOTba, 185 CNOTba, 185 CNOTb, 185 CNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Id, 180 Id, 180 Id, 186 Ide oppriNoiseBase, 242 compute_probs, 242 compute_state_, 243 generated_, 246 generated_, 246 generated_, 246 generated_, 246 generated_, 243 get_last_idx, 243 get_last_idx, 243 get_last_bx, 244 get_probs, 244 i_, 246 Ks_, 246 NoiseBase, 241, 242 operator(), 244, 245 probs 246 qpp::NoiseBase < T >, 239 qpp::NoiseBase < T >, 239 qpp::NoiseType, 247 qpp::NoiseType, 247 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::QCircuit, 265 ~QCircuit, 272 add_circuit, 272 add_dit, 273 add_hash_, 274 add_qudit, 274 begin, 274, 275 Id, 180 Id2, 186 internal::Singleton< const Gates >, 185 Id, 180 Idc2, 186 internal::Singleton< const Gates >, 185 Id, 180 Idc2, 186 Idcaption Internal::Singleton< const Init >, 196 qpp::NoiseBase, 242 compute_probs 242 compute_probs 244 generated_, 246 generated_, 246 generated_, 246 generated_, 246 get_LastD, 244 get_lastD, 24		•
index 162 n 168 n 168 none, 162 offset 162 operatorl=, 163 operator-=, 163 reset, 165, 166 set, 166 size, 167 storage_size_, 167 storage_size_, 168 storage_type, 159 do_string, 167 v 168 value_type, 159 qpp::RoiseBase ~NoiseBase, 242 compute_probs_, 242 compute_state_, 243 d 246 generated_, 246 get_Ks, 243 get_d, 243 get_d, 243 get_last_idx, 243 get_last_idx, 243 get_last_jdx, 244 get_probs, 244 storage_size_, 167 storage_size_, 168 storage_type, 159 fo_string, 167 v 168 value_type, 159 qpp::RoiseBase, 241, 242 operator(), 244, 245 probs, 246 dpp::NoiseBase, 241, 242 operator(), 244, 245 probs, 246 cNOT, 185 CNOT, 185 CNOT, 185 cNOT, 185 cTRL, 177 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::Ocircuit, 272 add_dit, 273 add_hash, 274 add_qudit, 274 begin, 274, 275 internal::Singleton< const Gates >, 185 cTRL_custom, 280	·	•
n_, 168 none, 162 offset_, 162 offset_, 163 operatorl=, 163 operator-, 163 operator-=, 163 rand, 165 reset, 165, 166 set, 166 size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 ~Gates, 176 CNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 FRED, 185 Fed, 179 Gates, 176 get_name, 180 H, 185 ld, 180 ld2, 186 index date decrease intermal::Singleton< const Gates >, 185 compute probs_, 242 compute probs_, 244 ocmpute_state_, 243 d_, 246 generated_, 246 get_ks, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_p, 244 get_probs, 244 i_, 246 get_probs, 244 i_, 246 storage_type, 159 noise_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs 246 qpp::NoiseBase dpp::NoiseType, 247 qpp::NoiseType; 247 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::QCircuit, 265 ~QCircuit, 272 add_dit, 273 add_hash_, 274 add_qudit, 274 begin, 274, 275 ld, 180 internal::Singleton< const Gates >, 185 CTRL_custom, 280	-	-
none, 162 offset_, 162 offset_, 162 operator!=, 163 operator-=, 163 operator.=, 163 operator.=, 163 operator.=, 163 operator.=, 163 operator.=, 163 operator.=, 163 rand, 165 reset, 165, 166 set, 166 set, 167 storage_size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 operator.=, 168 consider type, 159 operator.=, 246 compute_state_, 243 operator.=, 243 opet_last_idx, 243 opet_last_idx, 243 opet_last_idx, 243 opet_last_p, 244 storage_size, 167 storage_size, 167 onise_type, 241 NoiseBase, 241, 242 operator.(), 244, 245 operator.e. v, 168 consider type, 247 consider type, 247 color.cuit, 272 add_circuit, 274 add_quit, 274 begin, 274, 275 consider type.		
offset_, 162 operatorl=, 163 operator-, 163 operator-, 163 operator-=, 163 operator-a, 165 operator-a, 165 operator-a, 165 operator-a, 165 operator-a, 165 operator-a, 164 operator-a, 167 operator-a, 167 operator-a, 168 ope		
operator!=, 163 operator-, 163 operator-=, 163 operator-=, 163 operator-=, 163 operator-=, 163 rand, 165 reset, 165, 166 set, 166 set, 167 size, 167 storage_size, 167 storage_size, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 ~Gates, 176 CNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 FRED, 185 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 ld, 180 lc_TSB_CTRL_custom, 280 lc_TSB_CTRL_custom, 280 lc_TSB_CTRL_custom, 280 lc_TSB_CTRL_custom, 280		. – –
operator-, 163 operator==, 163 rand, 165 reset, 165, 166 set, 166 size, 167 storage_size, 167 storage_size_, 168 value_type, 159 cNOTba, 185 CNOT, 185 CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 generated_, 246 get_Ks, 243 get_Last_k, 244 get_last_idx, 243 get_last_K, 244 get_last_p, 244 get_last_p, 244 get_last_p, 244 storage_size, 167 get_probs, 244 i., 246 storage_type, 159 Ks_, 246 noise_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs_, 246 cpp::NoiseBase < T >, 239 cpp::NoiseType, 247 cpp::NoiseType::StateDependent, 333 ctrl, 177 cpp::NoiseType::StateDependent, 334 ctrl, 179 cates, 176 get_name, 180 del_nash_, 274 get_name, 180 h, 185 ld, 180 lcCTRL_custom, 277 cCTRL_custom, 277 ld2, 186 internal::Singleton< const Gates >, 185 ctrl_custom, 280		. — —
operator==, 163 rand, 165 reset, 165, 166 set, 166 set, 166 set, 167 storage_size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 dpp::Gates, 176 CNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 ld, 186 lcase get_Ks, 243 get_d, 243 get_d, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 244 get_last_ox, 244 storage det_last_ox, 244 get_last_ox, 244 storage det_last_ox, 244 get_last_ox, 244 get_last_ox, 244 get_last_ox, 244 get_last_ox, 244 get_last_ox, 244 get_last_ox, 246 get_last_ox, 248 get_last_ox, 244 get_last_ox, 246 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 get_last_ox, 244 get_last_ox, 246 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 get_last_ox, 244 get_last_ox, 244 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 246 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox, 244 noise_last_ox,		
rand, 165 reset, 165, 166 set, 166 set, 166 set, 167 storage_size, 167 storage_size, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 CNOT, 185 CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 FRED, 185 FR, 176 get_d, 243 get_last_idx, 243 get_last_idx, 244 get_last_p, 244 get_last_p, 244 get_last_p, 244 storage_size_, 168 i., 246 storage_type, 159 ks_, 246 noise_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs_, 246 qpp::NoiseBase < T >, 239 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType, 247 qpp::NoiseType, 247 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateIndependent, 334 qpp::QCircuit, 265	•	-
reset, 165, 166 set, 166 set, 166 size, 167 storage_size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 cNOTba, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 FRED, 185 FRED, 185 FR, 176 Gates, 176 get_last_idx, 243 get_last_idx, 244 get_last_p, 244 get_last_p, 244 get_last_p, 244 get_last_p, 244 get_last_mx, 246 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 244 get_last_idx, 244 get_last_p, 244 get_last_p, 244 get_last_idx, 243 get_last_idx, 243 get_last_idx, 243 get_last_idx, 244 get_last_p, 244 get_last_p, 244 get_last_p, 244 i., 246 sts_, 246 sts_, 246 sts_, 246 sts_, 246 sts_, 244 sts_, 246	•	
set, 166 size, 167 storage_size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 cNOTba, 185 cTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_last_K, 244 get_last_p, 246 storaget_last_p, 244 get_last_p, 244 get_last_p, 246 storaget_last_p, 244 get_last_p, 246 storaget_last_p, 244 get_last_p, 246 storaget_last_p, 244 get_last_p, 246 storaget_last_p, 246 get_last_p, 246 storaget_last_p, 246 get_last_p, 246 storaget_last_p, 246 get_last_p, 246 storaget_last_p, 246 storaget_last_p, 246 get_last_p, 246 storaget_last_p, 246 get_last_p, 246 storaget_last_p, 246 storaget_last_pet_	rand, 165	get_d, 243
size, 167 storage_size, 167 storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 cNOTba, 185 cTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_last_p, 244 get_probs, 244 i_, 246 ks, 246 noise_type, 241 NoiseBase, 241, 242 operator(), 244, 245 probs, 246 qpp::NoiseBase < T >, 239 qpp::NoiseType, 247 cNOT, 185 qpp::NoiseType::StateDependent, 333 cTRL, 177 qpp::NoiseType::StateIndependent, 334 qpp::QCircuit, 265 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 ld, 180 ld2, 186 internal::Singleton < const Gates >, 185 cTRL_custom, 280	reset, 165, 166	get_last_idx, 243
storage_size, 167 get_probs, 244 storage_size_, 168 i_, 246 storage_type, 159 Ks_, 246 to_string, 167 noise_type, 241 v_, 168 NoiseBase, 241, 242 value_type, 159 operator(), 244, 245 qpp::Gates, 174 probs_, 246 ~Gates, 176 qpp::NoiseBase T >, 239 CNOTba, 185 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType::StateDependent, 333 CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 id2, 186 cCTRL_custom, 280	set, 166	get_last_K, 244
storage_size_, 168 storage_type, 159 to_string, 167 v_, 168 value_type, 159 qpp::Gates, 174 cNoTba, 185 CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 FRED, 185 Gates, 176 Gates, 176 Gates, 176 CX, 185 Expandout, 177, 178 FRED, 185 Gates, 176 Gates, 176 Gates, 176 CX, 185 Expandout, 177, 178 FRED, 185 Gates, 176 Gates	size, 167	get_last_p, <mark>244</mark>
storage_type, 159 Ks_, 246 to_string, 167 noise_type, 241 v_, 168 NoiseBase, 241, 242 value_type, 159 operator(), 244, 245 qpp::Gates, 174 probs_, 246 ~Gates, 176 qpp::NoiseBase < T >, 239 CNOTba, 185 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType::StateDependent, 333 CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL_custom, 277 internal::Singleton < const Gates >, 185 CTRL_custom, 280	storage_size, 167	get_probs, 244
to_string, 167 v_, 168 v_, 168 value_type, 159 operator(), 244, 245 operator(), 244 operator(), 244, 245 operator(), 244 operator(), 246 operator(), 244 operator(), 246 operator(), 244 operator(), 246 operator(), 247 operator()	storage_size_, 168	i_, 246
v_, 168 NoiseBase, 241, 242 value_type, 159 operator(), 244, 245 qpp::Gates, 174 probs_, 246 ~Gates, 176 qpp::NoiseBase < T >, 239 CNOTba, 185 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType::StateDependent, 333 CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL_custom, 277 internal::Singleton < const Gates >, 185 CTRL_custom, 280	storage_type, 159	Ks_, 246
value_type, 159 qpp::Gates, 174 ~Gates, 176 Qpp::NoiseBase< T >, 239 QNOTba, 185 Qpp::NoiseType, 247 QNOT, 185 Qpp::NoiseType, 247 Qpp::NoiseType::StateDependent, 333 QTRL, 177 Qpp::NoiseType::StateIndependent, 334 QZ, 185 expandout, 177, 178 FRED, 185 Expandout, 177 Gates, 176 Qates, 176 Qates, 176 Qates, 176 Qates, 176 Qet_name, 180 H, 185 Id, 180 CCTRL_custom, 277 Id2, 186 internal::Singleton< const Gates >, 185 Operator(), 244, 245 probs_, 246 qpp::NoiseBase< T >, 239 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateIndependent, 334 qpp::QCircuit, 265 ~QCircuit, 272 add_circuit, 272 add_dit, 273 add_hash_, 274 begin, 274, 275 CTRL_custom, 277 CTRL_custom, 280	to_string, 167	noise_type, 241
qpp::Gates, 174 probs_, 246 ~Gates, 176 qpp::NoiseBase < T >, 239 CNOTba, 185 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType::StateDependent, 333 CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL_custom, 277 internal::Singleton < const Gates >, 185 CTRL_custom, 280	v_, 168	NoiseBase, 241, 242
~Gates, 176 qpp::NoiseBase< T >, 239 CNOTba, 185 qpp::NoiseType, 247 CNOT, 185 qpp::NoiseType::StateDependent, 333 CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL_custom, 280	value_type, 159	operator(), 244, 245
CNOTba, 185 CNOT, 185 CNOT, 185 CTRL, 177 CRL, 178 CRL, 179 CRL, 180 CRL, 1	qpp::Gates, 174	probs_, 246
CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Id, 180 Id, 186 CNOT, 185 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::NoiseType::Sta	\sim Gates, 176	qpp::NoiseBase< T >, 239
CNOT, 185 CTRL, 177 CZ, 185 expandout, 177, 178 FRED, 185 Fd, 179 Gates, 176 get_name, 180 H, 185 Id, 180 Id, 186 CNOT, 185 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateIndependent, 334 qpp::NoiseType::StateDependent, 333 qpp::NoiseType::StateDependent, 334 qpp::NoiseType::Sta	CNOTba, 185	qpp::NoiseType, 247
CTRL, 177 qpp::NoiseType::StateIndependent, 334 CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_nash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185	CNOT, 185	
CZ, 185 qpp::QCircuit, 265 expandout, 177, 178 ~QCircuit, 272 FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185		
expandout, 177, 178 FRED, 185 FRED, 185 add_circuit, 272 Fd, 179 Gates, 176 get_name, 180 H, 185 Id, 180 cCTRL_custom, 277 ld2, 186 cTRL_custom, 280 CTRL_custom, 280		
FRED, 185 add_circuit, 272 Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185 CTRL_custom, 280		
Fd, 179 add_dit, 273 Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185 CTRL_custom, 280	•	
Gates, 176 add_hash_, 274 get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185 CTRL_custom, 280		
get_name, 180 add_qudit, 274 H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185 CTRL_custom, 280		
H, 185 begin, 274, 275 Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton< const Gates >, 185 CTRL_custom, 280		
Id, 180 cCTRL_custom, 277 Id2, 186 cCTRL, 275–277 internal::Singleton const Gates >, 185 CTRL_custom, 280	- -	— ·
ld2, 186 cCTRL, 275–277 internal::Singleton< const Gates >, 185 CTRL_custom, 280		
internal::Singleton < const Gates >, 185 CTRL_custom, 280		
WICDWICE, 100 OTTL, 270, 279		
	IVIODIVIOL, 100	OTTL, 210, 213

cbegin, 275	measurement_type_, 237
cend, 277	name_, 237
cmat_hash_tbl_, 295	target_, 237
const_iterator, 270	qpp::QCircuit::iterator, 213
count_, 295	difference_type, 214
d_, 296	elem_, 218
display, 280	iterator, 215
end, 280, 281	iterator_category, 214
gate, 281, 282	operator!=, 215
gate_custom, 282	operator*, 216
gate_fan, 283, 284	operator++, 216
GateType, 270	operator=, 216
gates_, 296	operator==, 217
get_cmat_hash_tbl_, 284	pointer, 214
get_d, 284	qc_, 218
get_depth, 284	reference, 215
get_gate_count, 285	set_begin_, 217
get_gates_, 285	set_end_, 217
get_measured, 285, 286	value_type, 215
get measurement count, 286	qpp::QCircuit::iterator::value_type_, 355
get_measurements_, 287	display, 356
get_name, 287	gates_ip_, 357
get_nc, 287	ip_, 357
get_non_measured, 287	measurements ip , 357
get_nop_count, 288	operator=, 357
get_nq, 288	type_, 358
get step count, 288	value_type_, 356
kron, 288	value_type_qc_, 358
MeasureType, 271	qpp::QEngine, 298
measured_, 296	\sim QEngine, 301
measurement_count_, 296	display, 301
measurements_, 296	dits_, 307
measureV, 289	execute, 302
measureZ, 290	get_circuit, 303
name_, 296	get_dit, 303
nc_, 297	get_dits, 303
nop, 290	get_measured, 303, 304
nq_, 297	get_non_measured, 304
operator<<, 294, 295	get_probs, 304
QCircuit, 272	get_psi, 304
QEngine, 295	get_relative_pos_, 305
QFT, 290, 291	get_stats, 305
replicate, 291	operator=, 305
step_types_, 297	probs_, 308
StepType, 271	psi_, 308
TFQ, 292, 293	QEngine, 300, 301
to_JSON, 293	qc_, 308
qpp::QCircuit::GateStep, 187	reset, 305
ctrl_, 189	reset_stats, 306
gate_hash_, 189	set_dit, 306
gate_type_, 189	set_measured_, 306
GateStep, 188	set_psi, 307
name_, 189	stats_, 308
target_, 189	subsys_, 308
qpp::QCircuit::MeasureStep, 235	to_JSON, 307
c_reg_, 237	qpp::QNoisyEngine
mats_hash_, 237	execute, 311
MeasureStep, 236	get_noise_results, 311

noine 011	v0. 040
noise_, 311	y0, 342
noise_results_, 311 QNoisyEngine, 310	y1, 343 z0, 343
• •	
qpp::QNoisyEngine < NoiseModel >, 309	z1, 343
qpp::QubitAmplitudeDampingNoise, 312	zero, 338
QubitAmplitudeDampingNoise, 313	qpp::Timer
qpp::QubitBitFlipNoise, 313	~Timer, 347
QubitBitFlipNoise, 315	display, 347
qpp::QubitBitPhaseFlipNoise, 315	end_, 349
QubitBitPhaseFlipNoise, 316	get_duration, 348
qpp::QubitDepolarizingNoise, 317	start_, 349
QubitDepolarizingNoise, 318	tic, 348
qpp::QubitPhaseDampingNoise, 318	tics, 348
QubitPhaseDampingNoise, 319	Timer, 347
qpp::QubitPhaseFlipNoise, 320	toc, 348
QubitPhaseFlipNoise, 321	qpp::Timer< T, CLOCK_T >, 345 qpp::exception, 117
qpp::QuditDepolarizingNoise, 323	
fill_Ks_, 325 fill probs , 325	qpp::exception::CustomException, 140
QuditDepolarizingNoise, 324	CustomException, 141
	description, 142
qpp::RandomDevices, 326	what_, 142
~RandomDevices, 327	qpp::exception::DimsInvalid, 143
get_prng, 328	description, 144
internal::Singleton < RandomDevices >, 329	qpp::exception::DimsMismatchCvector, 144
load, 328	description, 146
prng_, 329	qpp::exception::DimsMismatchMatrix, 146
RandomDevices, 327	description, 147
rd_, 329	qpp::exception::DimsMismatchRvector, 148 description, 149
save, 328 qpp::States, 334	•
	qpp::exception::DimsMismatchVector, 150
~States, 336	description, 151
b00, 339	qpp::exception::DimsNotEqual, 152 description, 153
b01, 339	•
b10, 339	qpp::exception::Duplicates, 155 description, 156
b11, 340 GHZ, 340	•
internal::Singleton< const States >, 339	qpp::exception::Exception, 169
	description, 172 Exception, 172
jn, 337 mes, 337	msg , 173
minus, 337	what, 173
one, 338	where , 173
pGHZ, 341	qpp::exception::InvalidIterator, 196
pb00, 340	description, 197
pb00, 340 pb01, 340	qpp::exception::MatrixMismatchSubsys, 219
pb01, 340 pb10, 340	description, 220
pb10, 340 pb11, 340	qpp::exception::MatrixNotCvector, 221
•	description, 222
plus, 338 pW, 341	qpp::exception::MatrixNotRvector, 223
px0, 341	description, 224
•	qpp::exception::MatrixNotSquare, 225
px1, 341 py0, 341	description, 226
py0, 341 py1, 341	qpp::exception::MatrixNotSquareNorCvector, 227
	description, 228
pz0, 342	qpp::exception::MatrixNotSquareNorRvector, 229
pz1, 342 States, 336	description, 230
W, 342	qpp::exception::MatrixNotSquareNorVector, 231
	description, 232
x0, 342 x1, 342	qpp::exception::MatrixNotVector, 233
۸۱, ۵۹۷	qppexceptioniviathxivotvector, 233

description, 234	dirsum2, 124
qpp::exception::NoCodeword, 238	get_dim_subsys, 124
description, 239	get_num_subsys, 124
qpp::exception::NotBipartite, 247	hash_combine, 124
description, 249	kron2, 125
qpp::exception::NotImplemented, 249	multiidx2n, 125
description, 250	n2multiidx, 125
qpp::exception::NotQubitCvector, 251	variadic_vector_emplace, 125
description, 252	qpp::internal::Display_Impl_, 154
qpp::exception::NotQubitMatrix, 252	display_impl_, 154
description, 254	qpp::internal::EqualEigen, 168
qpp::exception::NotQubitRvector, 254	operator(), 169
description, 255	qpp::internal::HashEigen, 190
qpp::exception::NotQubitSubsys, 256	operator(), 190
description, 257	qpp::internal::IOManipEigen, 198
qpp::exception::NotQubitVector, 258	A_, 199
description, 259	chop_, 200
qpp::exception::OutOfRange, 260	display, 199
description, 261	IOManipEigen, 199
qpp::exception::PermInvalid, 262	qpp::internal::IOManipPointer
description, 263	chop_, 202
qpp::exception::PermMismatchDims, 263	display, 202
description, 265	end_, 203
qpp::exception::QuditAlreadyMeasured, 321	IOManipPointer, 201, 202
description, 322	N_, 203
qpp::exception::SizeMismatch, 332	operator=, 202
description, 333	p_, 203
qpp::exception::SubsysMismatchDims, 344	separator_, 203
description, 345	start_, 203
qpp::exception::TypeMismatch, 350	qpp::internal::IOManipPointer $<$ PointerType $>$, 200
description, 351	qpp::internal::IOManipRange
qpp::exception::UndefinedType, 351	chop_, 206
description, 353	display, 205
qpp::exception::Unknown, 353	end_, <mark>206</mark>
description, 354	first_, 206
qpp::exception::ZeroSize, 358	IOManipRange, 205
description, 359	last_, 206
qpp::experimental, 119	operator=, 206
qpp::internal, 119	separator_, 207
abs_chop, 120	start_, 207
check_cvector, 121	qpp::internal::IOManipRange< InputIterator >, 204
check_dims, 121	qpp::internal::Singleton
check_dims_match_cvect, 121	∼Singleton, 331
check_dims_match_mat, 121	get_instance, 331
check_dims_match_rvect, 121	get_thread_local_instance, 331
check_eq_dims, 121	operator=, 331
check_matching_sizes, 122	Singleton, 330, 331
check_no_duplicates, 122	qpp::internal::Singleton < T >, 329
check_nonzero_size, 122	qpp::is_complex < std::complex < T > >, 208
check_perm, 122	qpp::is_complex < T >, 207
check_qubit_cvector, 122	<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T</pre>
check_qubit_matrix, 122	>().begin()), decltype(std::declval< T >().
check_qubit_rvector, 123	end()), decltype(*(std::declval< T >().
check_qubit_vector, 123	begin()))>>, 210
check_rvector, 123	qpp::is_iterable < T, typename >, 209
check_square_mat, 123	qpp::is_matrix_expression< Derived >, 212
check_subsys_match_dims, 123	qpp::literals, 126
check_vector, 123	operator"" _bra, 126

perator"" _i, 126, 127 perator"" _if, 127 perator"" _if, 127 perator"" _ket, 127 perator"" _prj, 128 perator"" _prj, 128 perator"" _prj, 128 perator _ prj, 128
perator"" _if, 127
perator"" _ket, 127
reset_stats ake_void qpp::QEngine, 306 pe, 219 reshape ake_void qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void< Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pp::QubitAmplitudeDampingNoise, 313 qpp, 100
rno-vnuro
·
pp::QubitBitFlipNoise, 315 qpp, 100
itPhaseFlipNoise Rn
itPhaseFlipNoise Rn p::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181
itPhaseFlipNoise Rn pp::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 epolarizingNoise RX
titPhaseFlipNoise Rn pp::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 qpp::Gates, 181
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise, 318 qpp::QubitDepolarizingNoise, 318 haseDampingNoise RY
hitPhaseFlipNoise Rn pp::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 pepolarizingNoise RX pp::QubitDepolarizingNoise, 318 qpp::Gates, 181 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 qpp::Gates, 182
haseFlipNoise Rn qpp::QubitBitPhaseFlipNoise, 316 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ qpp::Gates, 181 qpp::Gates, 181 RY qpp::Gates, 182 RZ
hitPhaseFlipNoise Rn pp::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 pepolarizingNoise RX pp::QubitDepolarizingNoise, 318 qpp::Gates, 181 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 qpp::Gates, 182
titPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 pepolarizingNoise pp::QubitDepolarizingNoise, 318 phaseDampingNoise pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseFlipNoise pp::QubitPhaseFlipNoise, 321 RX pp::Gates, 181 pp::Gates, 182 pp::Gates, 182 pp::Gates, 182
haseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise RY pp::Gates, 181 app::Gates, 181 pp::Gates, 182 app::Gates, 182 app::Gates, 182 app::Gates, 182 app::Gates, 182 app::Gates, 182
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 pepolarizingNoise pp::QubitDepolarizingNoise, 318 phaseDampingNoise pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseFlipNoise pp::QubitPhaseFlipNoise, 321 pp::QubitPhaseFlipNoise, 321 pp::QuditDepolarizingNoise, 324 S R R R R R R R R R R R R
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 pepolarizingNoise pp::QubitDepolarizingNoise, 318 phaseDampingNoise pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseDampingNoise, 319 pp::QubitPhaseFlipNoise pp::QubitPhaseFlipNoise, 321 pp::QubitPhaseFlipNoise, 321 pp::QubitPhaseFlipNoise pp::QuditDepolarizingNoise, 324 pp::Gates, 182 pp::Gates, 182 pp::Gates, 182
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise RX pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QuditDepolarizingNoise, 324 App::Gates, 182 App::Gates, 182 App::Gates, 182 App::Gates, 182 App::Gates, 186 A
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise RX pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ pp::QubitPhaseFlipNoise, 321 qpp::Gates, 182 epolarizingNoise RZ pp::QuditDepolarizingNoise, 324 pp::QuditDepolarizingNoise, 324 pp::Gates, 186 SWAPd pp, 90–92 qpp::Gates, 182
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ pp::QubitPhaseFlipNoise, 321 qpp::Gates, 182 epolarizingNoise RZ pp::QubitDepolarizingNoise, 321 qpp::Gates, 182 epolarizingNoise Spp::QuditDepolarizingNoise, 324 qpp::Gates, 186 SWAPd pp, 90–92 qpp::Gates, 182 pp::Dynamic_bitset, 165 SWAP
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise RX pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ pp::QubitPhaseFlipNoise, 321 qpp::Gates, 182 epolarizingNoise RZ pp::QuditDepolarizingNoise, 324 pp::QuditDepolarizingNoise, 324 pp::Gates, 186 SWAPd pp, 90–92 qpp::Gates, 182
hasePlipNoise Rn qpp::Gates, 181 epolarizingNoise RX pp::QubitDepolarizingNoise, 318 haseDampingNoise RY pp::QubitPhaseDampingNoise, 319 haseFlipNoise RZ pp::QubitPhaseFlipNoise, 321 qpp::Gates, 182 epolarizingNoise RZ pp::QubitDepolarizingNoise, 321 qpp::Gates, 182 epolarizingNoise Spp::QuditDepolarizingNoise, 324 qpp::Gates, 186 SWAPd pp, 90–92 qpp::Gates, 182 pp::Dynamic_bitset, 165 SWAP
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QuditDepolarizingNoise, 324 epolarizingNoise pp::QuditDepolarizingNoise, 324 pp::Gates, 182 qpp::Gates, 182 qpp::Gates, 186 SWAPd qpp::Gates, 186 SWAPd qpp::Gates, 182 syxAP qpp::Bit_circuit, 134
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QuditDepolarizingNoise, 324 pp::Gates, 182 qpp::Gates, 182 qpp::Gates, 186 SWAPd qpp::Gates, 182 pp::Dynamic_bitset, 165 SWAP qpp::Bit_circuit, 134 qpp::Gates, 186 save
ItPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhaseFlipNoise IttPhasePlipNoise IttPhasePlipNoise IttPhasePlipNoise IttPhaseFlipNoise IttPh
ItPhaseFlipNoise ItPhaseFlipN
ItPhaseFlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphaseFlipNoise ItphasePlipNoise ItphasePlipN
ItPhaseFlipNoise ItPhaseFlipN
ItPhaseFlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphasePlipNoise ItphaseFlipNoise ItphasePlipNoise ItphasePlipN
ItPhaseFlipNoise Rn qpp::Gates, 181 ItphaseFlipNoise, 316 ItepolarizingNoise, 316 ItepolarizingNoise, 316 ItepolarizingNoise, 316 ItepolarizingNoise ItepolarizingNoise ItepolarizingNoise ItepolarizingNoise ItepolarizingNoise, 318 ItepolarizingNoise, 318 ItepolarizingNoise ItepolarizingNoise, 321 ItepolarizingNoise, 324 Itepolarizi
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Gates, 182 qpp::Gates, 182 qpp::Gates, 186 SWAPd qpp::Gates, 182 pp::Dynamic_bitset, 165 SWAP qpp::Bit_circuit, 134 qpp::Gates, 186 save pp, 93 qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101, 102 schatten qpp, 103
itPhaseFlipNoise
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QuditDepolarizingNoise, 324 pp::Qates, 182 SWAPd qpp::Gates, 182 SWAP qpp::Gates, 182 SWAP qpp::Gates, 186 save qpp::Gates, 186 save qpp::Gates, 186 save qpp::Gates, 180 sove qpp::Gates, 180 sov
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 SWAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101, 102 schatten qpp, 103 schmidtA qpp, 103 schmidtB
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 SWAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101 qpp::RandomDevices, 328 schatten qpp, 103 schmidtA qpp, 103 schmidtB mDevices pp::RandomDevices, 327
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 SWAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101, 102 schatten qpp, 103 schmidtA qpp, 103 schmidtB
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 SWAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101 qpp::RandomDevices, 328 schatten qpp, 103 schmidtA qpp, 103 schmidtB mDevices pp::RandomDevices, 327
ItPhaseFlipNoise IttphaseFlipNoise Ittph
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBopolarizingNoise, 318 pp::QubitPaseDampingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 SWAP qpp::Gates, 186 SWAPd qpp::Gates, 182 SWAP qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101 qpp, 103 schatten qpp, 103 schatten qpp, 103 schmidtA qpp, 103 schmidtB qpp, 104 schmidtcoeffs qpp, 96 me schmidtprobs
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 pp::QubitBitPhaseFlipNoise, 316 pp::QubitBitPhaseFlipNoise, 318 pp::QubitDepolarizingNoise, 318 pp::QubitPhaseDampingNoise, 319 phaseFlipNoise pp::QubitPhaseDampingNoise, 319 phaseFlipNoise pp::QubitPhaseFlipNoise, 321 pp::QubitPhaseFlipNoise, 321 pp::QubitPhaseFlipNoise, 324 pp::Qubit
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 S qpp::Gates, 182 qpp::Gates, 182 swAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Bates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtB qpp, 104 schmidtcoeffs qpp, 96 me schmidtprobs qpp, 106 separator_
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Gates, 182 S
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 324 pp::Qates, 182 S qpp::Gates, 182 qpp::Gates, 182 swAPd qpp::Gates, 186 SWAPd qpp::Bit_circuit, 134 qpp::Bates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtB qpp, 104 schmidtcoeffs qpp, 96 me schmidtprobs qpp, 106 separator_
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::Gates, 182 S
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 hasePlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 spp::Gates, 182 pp::Gates, 182 pp::Gates, 186 SWAPd
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QuditDepolarizingNoise, 324 pp::Gates, 182 RZ qpp::Gates, 182 pp::Gates, 182 pp::Gates, 186 SWAPd qpp::Gates, 182 SWAP qpp::Bit_circuit, 134 qpp::Gates, 186 save qpp, 101 qpp::RandomDevices, 328 saveMATLAB qpp, 101, 102 schatten qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtA qpp, 103 schmidtB qpp, 104 schmidtcoeffs qpp, 105 schmidtDevices pp::RandomDevices, 327 rm schmidtCoeffs qpp, 105 schmidtprobs qpp, 106 separator qpp::Dynamic_bitset, 166
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 318 RX epp::Gates, 181 RX epp::Gates, 182 epp::Gates, 18
itPhaseFlipNoise pp::QubitBitPhaseFlipNoise, 316 epolarizingNoise pp::QubitBitPhaseFlipNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 321 epolarizingNoise pp::QubitPhaseFlipNoise, 324 pp::QubitPhaseFlipNoise, 325 pp::QubitPhaseFlipNoise, 319 pp::QubitPhaseFlipNoise, 319 pp::QubitPhaseFlipNoise, 319 pp::QubitPhaseFlipNoise, 319 pp::QubitPhaseFlipNoise, 318 RY ppp::Qates, 182 pppp::Qates, 182 ppp::Qates, 182 ppp::Qates, 182 ppp::Qates, 182 ppp::Qate
itPhaseFlipNoise pp::Gates, 181 pp::QubitBitPhaseFlipNoise, 316 pp::QubitBitPhaseFlipNoise, 316 pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 pp::Gates, 182 pp::Gates, 186 SWAPd pp::Gates, 180 pp::Gates, 182
in Phase Flip Noise pp: Cubit Bit Phase Flip Noise, 316 pp. (Qubit Bit Phase Flip Noise, 316 pp. (Qubit Bit Phase Flip Noise, 318 phase Damping Noise, 318 pp. (Qubit Phase Damping Noise, 319 pp. (Qubit Phase Damping Noise, 319 pp. (Qubit Phase Plip Noise, 321 pp. (Qubit Phase Flip Noise, 324 pp. (Qubit Phase Flip Noise, 325 pp. (Qubit Phase Flip Noise, 324 pp.
itPhaseFlipNoise pp::Gates, 181 pp::QubitBitPhaseFlipNoise, 316 pp::QubitBitPhaseFlipNoise, 316 pp::QubitDepolarizingNoise, 318 haseDampingNoise pp::QubitPhaseDampingNoise, 319 haseFlipNoise pp::QubitPhaseFlipNoise, 321 pp::Gates, 182 pp::Gates, 186 SWAPd pp::Gates, 180 pp::Gates, 182
in Phase Flip Noise pp: Cubit Bit Phase Flip Noise, 316 pp. (Qubit Bit Phase Flip Noise, 316 pp. (Qubit Bit Phase Flip Noise, 318 phase Damping Noise, 318 pp. (Qubit Phase Damping Noise, 319 pp. (Qubit Phase Damping Noise, 319 pp. (Qubit Phase Plip Noise, 321 pp. (Qubit Phase Flip Noise, 324 pp. (Qubit Phase Flip Noise, 325 pp. (Qubit Phase Flip Noise, 324 pp.
in Phase Flip Noise pp: Cubit Bitt Phase Flip Noise, 316 pp: Cubit Bitt Phase Flip Noise, 316 pp: Cubit Bitt Phase Flip Noise, 318 pase Damping Noise, 318 pp: Cubit Depolarizing Noise, 319 pp: Cubit Phase Damping Noise, 319 pp: Cubit Phase Flip Noise, 321 pp: Cubit Phase Flip Noise, 324 pp: Cates, 182 pp: Cubit Phase Flip Noise, 324 pp: Cates, 182 pp: Cates, 186 pp: Cates, 182 pp: Cate
Introduction Rn
ItPhaseFlipNoise
itPhaseFlipNoise Rn op::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 op::QubitImagnoise RX op::QubitImagnoise RX op::QubitPhaseDampingNoise, 319 RY haseEplipNoise RZ op::QubitPhaseFlipNoise, 321 qpp::Gates, 182 op::QubitPhaseFlipNoise, 321 qpp::Gates, 182 op::QuditDepolarizingNoise, 324 S op::QuitDepolarizingNoise, 324
ItPhaseFlipNoise
itPhaseFlipNoise Rn op::QubitBitPhaseFlipNoise, 316 qpp::Gates, 181 op::QubitImagnoise RX op::QubitImagnoise RX op::QubitPhaseDampingNoise, 319 RY haseEplipNoise RZ op::QubitPhaseFlipNoise, 321 qpp::Gates, 182 op::QubitPhaseFlipNoise, 321 qpp::Gates, 182 op::QuditDepolarizingNoise, 324 S op::QuitDepolarizingNoise, 324
p.: &dbitbiti iipi (000; 010 qpp; 100
AFINDROISE TROUBLE
pp::QubitAmplitudeDampingNoise, 313 qpp, 100
mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void< Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void qpp::QEngine, 306 pe, 219 reshape ake_void qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void qpp::QEngine, 306 pe, 219 reshape ake_void qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void qpp::QEngine, 306 pe, 219 reshape ake_void qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
perator"" _ket, 127
perator"" _ket, 127
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
perator"" _ket, 127
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
perator"" _ket, 127
reset_stats ake_void app::QEngine, 306 pe, 219 reshape ake_void app, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 reset_stats app::QEngine, 306 reshape app, 99 rho2bloch app::QubitAmplitudeDampingNoise, 313
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void qpp::QEngine, 306 pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
pe, 219 reshape ake_void < Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void< Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void< Ts >, 218 qpp, 99 mplitudeDampingNoise rho2bloch pp::QubitAmplitudeDampingNoise, 313 qpp, 100
ake_void< Ts >, 218

Cinalatan	tic
Singleton qpp::internal::Singleton, 330, 331	qpp::Timer, 348
sinm	tics
qpp, 107	qpp::Timer, 348
size	Timer
qpp::Dynamic_bitset, 167	qpp::Timer, 347
spectralpowm	to_JSON
qpp, 107	qpp::IJSON, 194
sqrtm	qpp::QCircuit, 293
qpp, 108	qpp::QEngine, 307
ST	to_string
qpp, 29	qpp::Dynamic_bitset, 167
start	to_void
qpp::Timer, 349	
qpp::internal::IOManipPointer, 203	qpp, 28 toc
qpp::internal::IOManipRange, 207	qpp::Timer, 348
States	trace
qpp::States, 336	
statistics.h, 395	qpp, 113
stats	traits.h, 396
	transpose
qpp::QEngine, 308 step_types_	qpp, 113 tsallis
qpp::QCircuit, 297 StepType	qpp, 114
	Type
qpp::QCircuit, 271	qpp::Codes, 138
storage_size	type
qpp::Dynamic_bitset, 167	qpp::make_void, 219
storage_size_	type_
qpp::Dynamic_bitset, 168 storage type	qpp::QCircuit::iterator::value_type_, 358
qpp::Dynamic_bitset, 159	types.h, 398
subsys	uniform
qpp::QEngine, 308	qpp, 115
sum	дрр, 110
gpp, 108, 109	v _
super2choi	qpp::Dynamic bitset, 168
•	value_type
ann 109	
qpp, 109	
svals	qpp::Dynamic_bitset, 159
svals qpp, 110	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215
svals qpp, 110 svd	<pre>qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_</pre>
svals qpp, 110 svd qpp, 110	<pre>qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356</pre>
svals	<pre>qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_</pre>
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358
svals	<pre>qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var</pre>
svals	<pre>qpp::Dynamic_bitset, 159</pre>
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace
svals	<pre>qpp::Dynamic_bitset, 159</pre>
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125 W qpp::States, 342 what
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125 W qpp::States, 342
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125 W qpp::States, 342 what qpp::exception::Exception, 173 what_
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125 W qpp::States, 342 what qpp::exception::Exception, 173 what_ qpp::exception::CustomException, 142
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_ qpp::QCircuit::iterator::value_type_, 356 value_type_qc_ qpp::QCircuit::iterator::value_type_, 358 var qpp, 115 variadic_vector_emplace qpp::internal, 125 W qpp::States, 342 what qpp::exception::Exception, 173 what_ qpp::exception::CustomException, 142
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_
svals	qpp::Dynamic_bitset, 159 qpp::QCircuit::iterator, 215 value_type_

```
qpp::Gates, 186
х0
     qpp::States, 342
х1
     qpp::States, 342
x2contfrac
     qpp, 115
Χd
     qpp::Gates, 184
Υ
     qpp::Gates, 187
y0
     qpp::States, 342
у1
     qpp::States, 343
Ζ
     qpp::Gates, 187
z0
     qpp::States, 343
z1
     qpp::States, 343
\operatorname{\mathsf{Zd}}
     qpp::Gates, 184
zero
     qpp::States, 338
```