Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 		 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 		 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 		 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	ferer	nce .		 	 	 	 		 	 	 		 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 		 26
			6.1.2.1	bi	igint			 	 	 	 		 	 	 		 26
			6.1.2.2	bı	ra .			 	 	 	 		 	 	 		 26
			6.1.2.3	CI	mat			 	 	 	 		 	 	 		 27
			6.1.2.4	c	plx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dı	mat			 	 	 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 		 27
			6.1.2.8	d	vn ro	ow v	ect		 	 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	hash_eigen()	56
6.1.3.61	heig()	57
6.1.3.62	hevals()	57
6.1.3.63	hevects()	58
6.1.3.64	inverse()	58
6.1.3.65	invperm()	58
6.1.3.66	ip() [1/2]	59
6.1.3.67	ip() [2/2]	59
6.1.3.68	isprime()	60
6.1.3.69	kraus2choi()	60
6.1.3.70	kraus2super()	61
6.1.3.71	kron() [1/4]	61
6.1.3.72	kron() [2/4]	62
6.1.3.73	kron() [3/4]	62
6.1.3.74	kron() [4/4]	63
6.1.3.75	kronpow()	63
6.1.3.76	lcm() [1/2]	64
6.1.3.77	lcm() [2/2]	64
6.1.3.78	load()	64
6.1.3.79	loadMATLAB() [1/2]	65
6.1.3.80	loadMATLAB() [2/2]	66
6.1.3.81	logdet()	66
6.1.3.82	logm()	67
6.1.3.83	lognegativity() [1/2]	67
6.1.3.84	lognegativity() [2/2]	68
6.1.3.85	marginalX()	68
6.1.3.86	marginalY()	68

6.1.3.87 measure() [1/9]
6.1.3.88 measure() [2/9]
6.1.3.89 measure() [3/9]
6.1.3.90 measure() [4/9]
6.1.3.91 measure() [5/9]
6.1.3.92 measure() [6/9]
6.1.3.93 measure() [7/9]
6.1.3.94 measure() [8/9]
6.1.3.95 measure() [9/9]
6.1.3.96 measure_seq() [1/2]
6.1.3.97 measure_seq() [2/2]
6.1.3.98 mket() [1/2]
6.1.3.99 mket() [2/2]
6.1.3.100 modinv()
6.1.3.101 modmul()
6.1.3.102 modpow()
6.1.3.103 mprj() [1/2]
6.1.3.104 mprj() [2/2]
6.1.3.105 multiidx2n()
6.1.3.106 n2multiidx()
6.1.3.107 negativity() [1/2]
6.1.3.108 negativity() [2/2]
6.1.3.109 norm()
6.1.3.110 normalize()
6.1.3.111 omega()
6.1.3.112 operator""""_i()
6.1.3.113 powm()
6.1.3.114 prj()
6.1.3.115 prod() [1/3]
6.1.3.116 prod() [2/3]

vi

6.1.3.117 prod() [3/3]	84
6.1.3.118 ptrace() [1/2]	84
6.1.3.119 ptrace() [2/2]	85
6.1.3.120 ptrace1() [1/2]	85
6.1.3.121 ptrace1() [2/2]	86
6.1.3.122 ptrace2() [1/2]	86
6.1.3.123 ptrace2() [2/2]	87
6.1.3.124 ptranspose() [1/2]	87
6.1.3.125 ptranspose() [2/2]	88
6.1.3.126 QFT()	88
6.1.3.127 qmutualinfo() [1/2]	89
6.1.3.128 qmutualinfo() [2/2]	89
6.1.3.129 rand() [1/5]	90
6.1.3.130 rand() [2/5]	90
6.1.3.131 rand() [3/5]	91
6.1.3.132 rand() [4/5]	91
6.1.3.133 rand() [5/5]	92
6.1.3.134 randH()	92
6.1.3.135 randidx()	93
6.1.3.136 randket()	93
6.1.3.137 randkraus()	93
6.1.3.138 randn() [1/4]	94
6.1.3.139 randn() [2/4]	94
6.1.3.140 randn() [3/4]	95
6.1.3.141 randn() [4/4]	95
6.1.3.142 randperm()	96
6.1.3.143 randprime()	96
6.1.3.144 randprob()	97
6.1.3.145 randrho()	97
6.1.3.146 randU()	97

CONTENTS vii

6.1.3.147 randV()
6.1.3.148 renyi() [1/2]
6.1.3.149 renyi() [2/2]
6.1.3.150 reshape()
6.1.3.151 rho2bloch()
6.1.3.152 rho2pure()
6.1.3.153 save()
6.1.3.154 saveMATLAB() [1/2]
6.1.3.155 saveMATLAB() [2/2]
6.1.3.156 schatten()
6.1.3.157 schmidtA() [1/2]
6.1.3.158 schmidtA() [2/2]
6.1.3.159 schmidtB() [1/2]
6.1.3.160 schmidtB() [2/2]
6.1.3.161 schmidtcoeffs() [1/2]
6.1.3.162 schmidtcoeffs() [2/2]
6.1.3.163 schmidtprobs() [1/2]
6.1.3.164 schmidtprobs() [2/2]
6.1.3.165 sigma()
6.1.3.166 sinm()
6.1.3.167 spectralpowm()
6.1.3.168 sqrtm()
6.1.3.169 sum() [1/3]
6.1.3.170 sum() [2/3]
6.1.3.171 sum() [3/3]
6.1.3.172 super2choi()
6.1.3.173 svals()
6.1.3.174 svd()
6.1.3.175 svdU()
6.1.3.176 svdV()

viii CONTENTS

		6.1.3.177	syspermute() [1/2]	 	 	111
		6.1.3.178	syspermute() [2/2]	 	 	112
		6.1.3.179	TFQ()	 	 	112
		6.1.3.180	trace()	 	 	113
		6.1.3.181	transpose()	 	 	113
		6.1.3.182	tsallis() [1/2]	 	 	113
		6.1.3.183	tsallis() [2/2]	 	 	114
		6.1.3.184	uniform()	 	 	114
		6.1.3.185	var()	 	 	115
		6.1.3.186	x2contfrac()	 	 	115
	6.1.4	Variable	Occumentation	 	 	116
		6.1.4.1	chop	 	 	116
		6.1.4.2	ee	 	 	116
		6.1.4.3	infty	 	 	116
		6.1.4.4	maxn	 	 	116
		6.1.4.5	pi	 	 	116
6.2	qpp::ex	ception N	mespace Reference	 	 	116
	6.2.1	Detailed	Description	 	 	118
6.3	qpp::ex	perimenta	Namespace Reference	 	 	118
	6.3.1	Detailed	Description	 	 	118
6.4	qpp::int	ternal Nan	espace Reference	 	 	118
	6.4.1	Detailed	Description	 	 	120
	6.4.2	Function	Documentation	 	 	120
		6.4.2.1	check_cvector()	 	 	120
		6.4.2.2	check_dims()	 	 	120
		6.4.2.3	check_dims_match_cvect()	 	 	120
		6.4.2.4	check_dims_match_mat()	 	 	120
		6.4.2.5	check_dims_match_rvect()	 	 	121
		6.4.2.6	check_eq_dims()	 	 	121
		6.4.2.7	check_matching_sizes()	 	 	121

		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	21
		6.4.2.10	check_perm()	21
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	22
		6.4.2.16	check_square_mat()	22
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	23
		6.4.2.22	hash_combine()	23
		6.4.2.23	kron2()	24
		6.4.2.24	multiidx2n()	24
		6.4.2.25	n2multiidx()	24
		6.4.2.26	variadic_vector_emplace() [1/2]	24
		6.4.2.27	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator""""_bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator""""_prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	160
		7.12.4.10 none()	161
		7.12.4.11 offset_()	161
		7.12.4.12 operator"!=()	161
		7.12.4.13 operator-()	162
		7.12.4.14 operator==()	162
		7.12.4.15 rand() [1/2]	162
		7.12.4.16 rand() [2/2]	163
		7.12.4.17 reset() [1/2]	163
		7.12.4.18 reset() [2/2]	163
		7.12.4.19 set() [1/2]	164
		7.12.4.20 set() [2/2]	164
		7.12.4.21 size()	164
		7.12.4.22 storage_size()	164
		7.12.4.23 to_string()	165
	7.12.5	Member Data Documentation	165
		7.12.5.1 N	165
		7.12.5.2 storage_size	165
		7.12.5.3 v	166
7.13	qpp::int	ternal::EqualEigen Class Reference	166
	7.13.1	Detailed Description	166
	7.13.2	Member Function Documentation	166
		7.13.2.1 operator()()	166
7.14	qpp::ex	cception::Exception Class Reference	167
	7.14.1	Detailed Description	168
	7.14.2	Constructor & Destructor Documentation	169
		7.14.2.1 Exception()	169
	7.14.3	Member Function Documentation	169
		7.14.3.1 type_description()	169
		7.14.3.2 what()	170

xiv CONTENTS

	7.14.4	Member Data Documentation	170
		7.14.4.1 msg	170
		7.14.4.2 where	170
7.15	qpp::Bit	circuit::Gate_count Struct Reference	170
	7.15.1	Member Data Documentation	170
		7.15.1.1 CNOT	171
		7.15.1.2 FRED	171
		7.15.1.3 NOT	171
		7.15.1.4 SWAP	171
		7.15.1.5 TOF	171
		7.15.1.6 X	171
7.16	qpp::Ga	es Class Reference	172
	7.16.1	Detailed Description	174
	7.16.2	Constructor & Destructor Documentation	174
		7.16.2.1 Gates()	174
		7.16.2.2 ~Gates()	174
	7.16.3	Member Function Documentation	175
		7.16.3.1 CTRL()	175
		7.16.3.2 expandout() [1/3]	175
		7.16.3.3 expandout() [2/3]	176
		7.16.3.4 expandout() [3/3]	177
		7.16.3.5 Fd()	177
		7.16.3.6 get_name()	178
		7.16.3.7 ld()	178
		7.16.3.8 MODMUL()	178
		7.16.3.9 Rn()	179
		7.16.3.10 RX()	179
		7.16.3.11 RY()	180
		7.16.3.12 RZ()	180
		7.16.3.13 SWAPd()	180

CONTENTS xv

		7.16.3.14 Xd()	32
		7.16.3.15 Zd()	32
	7.16.4	Friends And Related Function Documentation	33
		7.16.4.1 internal::Singleton < const Gates >	33
	7.16.5	Member Data Documentation	33
		7.16.5.1 CNOT	33
		7.16.5.2 CNOTba	33
		7.16.5.3 CZ	33
		7.16.5.4 FRED	33
		7.16.5.5 H	34
		7.16.5.6 ld2	34
		7.16.5.7 S	34
		7.16.5.8 SWAP	34
		7.16.5.9 T	34
		7.16.5.10 TOF	34
		7.16.5.11 X	35
		7.16.5.12 Y	35
		7.16.5.13 Z	35
7.17	qpp::Q0	Circuit::GateStep Struct Reference	35
	7.17.1	Detailed Description	36
	7.17.2	Constructor & Destructor Documentation	36
		7.17.2.1 GateStep() [1/2]	36
		7.17.2.2 GateStep() [2/2]	36
	7.17.3	Member Data Documentation	37
		7.17.3.1 ctrl	37
		7.17.3.2 gate_hash	37
		7.17.3.3 gate_type	37
		7.17.3.4 name	37
		7.17.3.5 target	38
7.18	qpp::int	ternal::HashEigen Class Reference	38

xvi CONTENTS

	7.18.1	Detailed Description	188
	7.18.2	Member Function Documentation	188
		7.18.2.1 operator()()	188
7.19	qpp::ID	isplay Class Reference	189
	7.19.1	Detailed Description	190
	7.19.2	Constructor & Destructor Documentation	190
		7.19.2.1 IDisplay() [1/3]	190
		7.19.2.2 IDisplay() [2/3]	190
		7.19.2.3 IDisplay() [3/3]	190
		7.19.2.4 ~IDisplay()	190
	7.19.3	Member Function Documentation	191
		7.19.3.1 display()	191
		7.19.3.2 operator=() [1/2]	191
		7.19.3.3 operator=() [2/2]	191
	7.19.4	Friends And Related Function Documentation	191
		7.19.4.1 operator <<	191
7.20	qpp::IJS	SON Class Reference	192
	7.20.1	Detailed Description	192
	7.20.2	Constructor & Destructor Documentation	192
		7.20.2.1 IJSON() [1/3]	193
		7.20.2.2 IJSON() [2/3]	193
		7.20.2.3 IJSON() [3/3]	193
		7.20.2.4 ~IJSON()	193
	7.20.3	Member Function Documentation	193
		7.20.3.1 operator=() [1/2]	193
		7.20.3.2 operator=() [2/2]	193
		7.20.3.3 to_JSON()	193
7.21	qpp::Ini	t Class Reference	194
	7.21.1	Detailed Description	195
	7.21.2	Constructor & Destructor Documentation	195

CONTENTS xvii

		7.21.2.1 Init()
		7.21.2.2 ~Init()
	7.21.3	Friends And Related Function Documentation
		7.21.3.1 internal::Singleton < const Init >
7.22	qpp::ex	cception::InvalidIterator Class Reference
	7.22.1	Detailed Description
	7.22.2	Member Function Documentation
		7.22.2.1 Exception()
		7.22.2.2 type_description()
7.23	qpp::int	ternal::IOManipEigen Class Reference
	7.23.1	Constructor & Destructor Documentation
		7.23.1.1 IOManipEigen() [1/2]
		7.23.1.2 IOManipEigen() [2/2]
	7.23.2	Member Function Documentation
		7.23.2.1 display()
	7.23.3	Member Data Documentation
		7.23.3.1 A
		7.23.3.2 chop
7.24	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference
	7.24.1	Constructor & Destructor Documentation
		7.24.1.1 IOManipPointer() [1/2]
		7.24.1.2 IOManipPointer() [2/2]
	7.24.2	Member Function Documentation
		7.24.2.1 display()
		7.24.2.2 operator=()
	7.24.3	Member Data Documentation
		7.24.3.1 end
		7.24.3.2 N
		7.24.3.3 p
		7.24.3.4 separator

xviii CONTENTS

		7.24.3.5	S	tart_																	 	 		 	203
7.25	qpp::in	ternal::ION	Maı	nipF	Range	e<	Inp	putl	Iter	ator	r >	Cla	ass	Ter	mpl	ate	Ref	fere	nce		 	 		 	204
	7.25.1	Construc	ctor	· & C	Destr	ucto	or I	Dod	cun	nen	tati	on									 	 		 	205
		7.25.1.1	IC	ЭMа	anipP	Rang	ge(() [1/2	2]											 	 		 	205
		7.25.1.2	IC	ЭMа	anipP	Rang	ge(() [2/2	2]											 	 		 	205
	7.25.2	Member	Fu	nctio	on D	ocu	ıme	enta	atio	n											 	 		 	205
		7.25.2.1	d	ispla	ay()																 	 		 	205
		7.25.2.2	0	pera	ator=	() .															 	 		 	206
	7.25.3	Member	Da	ıta C	Ocur	men	nta	ıtior	n.												 	 		 	206
		7.25.3.1	е	nd_																	 	 		 	206
		7.25.3.2	fi	rst_																	 	 		 	206
		7.25.3.3	la	ıst_																	 	 		 	206
		7.25.3.4	S	epa	rator																 	 		 	206
		7.25.3.5	S	tart_																	 	 		 	206
7.26	qpp::is_	_complex<	< 1	Γ>	Struc	ct Te	em	ıpla	ate	Ref	ere	nce									 	 		 	207
	7.26.1	Detailed	De	scri	ption	١.															 	 		 	207
7.27	qpp::is_	_complex<	< 8	std::c	comp	olex	: <	T >	> >	> St	ruc	t Te	emp	olate	e R	efei	enc	е			 	 		 	208
	7.27.1	Detailed	De	scri	ption	١.															 	 		 	208
7.28	qpp::is_	_iterable<	< T ,	typ	enan	ne >	> 5	Strı	uct	Ten	npla	ate	Ref	fere	ence	€.					 	 		 	209
	7.28.1	Detailed	De	scri	ption	١.															 	 		 	209
7.29		_iterable< d()), decIty																_			 •				210
		Detailed								-															
7.30		matrix ex																							
7.00		Detailed																							
7.31		Circuit::ite																							
7.01		Detailed																							
		Member			•																				
		7.31.2.1																							213
		7.31.2.2																							
		7.31.2.3					_																		
		1.01.2.3	Ρ	Jirit	ΟI .		•		•			•		٠.		•			٠.	•	 	 •	٠.	 	۲۱4

CONTENTS xix

		7.31.2.4 reference	14
		7.31.2.5 value_type	14
	7.31.3	Constructor & Destructor Documentation	14
		7.31.3.1 iterator() [1/2]	14
		7.31.3.2 iterator() [2/2]	14
	7.31.4	Member Function Documentation	14
		7.31.4.1 operator"!=()	14
		7.31.4.2 operator*()	15
		7.31.4.3 operator++() [1/2]	15
		7.31.4.4 operator++() [2/2]	15
		7.31.4.5 operator=()	16
		7.31.4.6 operator==()	16
		7.31.4.7 set_begin_()	16
		7.31.4.8 set_end_()	16
	7.31.5	Member Data Documentation	17
		7.31.5.1 elem	17
		7.31.5.2 qc	17
7.32	qpp::ma	ake_void < Ts > Struct Template Reference	17
	7.32.1	Detailed Description	17
	7.32.2	Member Typedef Documentation	18
		7.32.2.1 type	18
7.33	qpp::ex	ception::MatrixMismatchSubsys Class Reference	18
	7.33.1	Detailed Description	19
	7.33.2	Member Function Documentation	19
		7.33.2.1 Exception()	19
		7.33.2.2 type_description()	20
7.34	qpp::ex	ception::MatrixNotCvector Class Reference	20
	7.34.1	Detailed Description	21
	7.34.2	Member Function Documentation	21
		7.34.2.1 Exception()	21

		7.34.2.2 type_description()	222
7.35	qpp::ex	cception::MatrixNotRvector Class Reference	222
	7.35.1	Detailed Description	223
	7.35.2	Member Function Documentation	223
		7.35.2.1 Exception()	223
		7.35.2.2 type_description()	224
7.36	qpp::ex	cception::MatrixNotSquare Class Reference	224
	7.36.1	Detailed Description	225
	7.36.2	Member Function Documentation	225
		7.36.2.1 Exception()	225
		7.36.2.2 type_description()	226
7.37	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	226
	7.37.1	Detailed Description	227
	7.37.2	Member Function Documentation	227
		7.37.2.1 Exception()	227
		7.37.2.2 type_description()	228
7.38	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	228
	7.38.1	Detailed Description	229
	7.38.2	Member Function Documentation	229
		7.38.2.1 Exception()	229
		7.38.2.2 type_description()	230
7.39	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	230
	7.39.1	Detailed Description	231
	7.39.2	Member Function Documentation	231
		7.39.2.1 Exception()	231
		7.39.2.2 type_description()	232
7.40	qpp::ex	ception::MatrixNotVector Class Reference	232
	7.40.1	Detailed Description	233
	7.40.2	Member Function Documentation	233
		7.40.2.1 Exception()	233

CONTENTS xxi

		7.40.2.2 type_description()
7.41	qpp::Q	Circuit::MeasureStep Struct Reference
	7.41.1	Detailed Description
	7.41.2	Constructor & Destructor Documentation
		7.41.2.1 MeasureStep() [1/2]
		7.41.2.2 MeasureStep() [2/2]
	7.41.3	Member Data Documentation
		7.41.3.1 c_reg
		7.41.3.2 mats_hash
		7.41.3.3 measurement_type
		7.41.3.4 name
		7.41.3.5 target
7.42	qpp::ex	cception::NoCodeword Class Reference
	7.42.1	Detailed Description
	7.42.2	Member Function Documentation
		7.42.2.1 Exception()
		7.42.2.2 type_description()
7.43	qpp::No	oiseBase< T > Class Template Reference
	7.43.1	Detailed Description
	7.43.2	Member Typedef Documentation
		7.43.2.1 noise_type
	7.43.3	Constructor & Destructor Documentation
		7.43.3.1 NoiseBase() [1/2]
		7.43.3.2 NoiseBase() [2/2]
		7.43.3.3 ~NoiseBase()
	7.43.4	Member Function Documentation
		7.43.4.1 compute_probs_()
		7.43.4.2 compute_state_()
		7.43.4.3 get_d()
		7.43.4.4 get_Ks()

xxii CONTENTS

		7.43.4.5 get_last_idx()	14
		7.43.4.6 get_last_K()	14
		7.43.4.7 get_last_p()	14
		7.43.4.8 get_probs()	14
		7.43.4.9 operator()() [1/2]	14
		7.43.4.10 operator()() [2/2]	1 5
	7.43.5	Member Data Documentation	1 5
		7.43.5.1 d	1 5
		7.43.5.2 generated	1 5
		7.43.5.3 i	1 6
		7.43.5.4 Ks	1 6
		7.43.5.5 probs	1 6
7.44	qpp::No	piseType Class Reference	1 6
	7.44.1	Detailed Description	1 6
7.45	qpp::ex	cception::NotBipartite Class Reference	1 7
	7.45.1	Detailed Description	1 8
	7.45.2	Member Function Documentation	1 8
		7.45.2.1 Exception()	1 8
		7.45.2.2 type_description()	1 8
7.46	qpp::ex	cception::NotImplemented Class Reference	1 9
	7.46.1	Detailed Description	50
	7.46.2	Member Function Documentation	50
		7.46.2.1 Exception()	50
		7.46.2.2 type_description()	50
7.47	qpp::ex	cception::NotQubitCvector Class Reference	51
	7.47.1	Detailed Description	52
	7.47.2	Member Function Documentation	52
		7.47.2.1 Exception()	52
		7.47.2.2 type_description()	52
7.48	qpp::ex	cception::NotQubitMatrix Class Reference	53

CONTENTS xxiii

	7.48.1	Detailed Description	54
	7.48.2	Member Function Documentation	54
		7.48.2.1 Exception()	54
		7.48.2.2 type_description()	54
7.49	qpp::ex	cception::NotQubitRvector Class Reference	55
	7.49.1	Detailed Description	56
	7.49.2	Member Function Documentation	56
		7.49.2.1 Exception()	56
		7.49.2.2 type_description()	56
7.50	qpp::ex	cception::NotQubitSubsys Class Reference	57
	7.50.1	Detailed Description	58
	7.50.2	Member Function Documentation	58
		7.50.2.1 Exception()	58
		7.50.2.2 type_description()	58
7.51	qpp::ex	cception::NotQubitVector Class Reference	59
	7.51.1	Detailed Description	30
	7.51.2	Member Function Documentation	30
		7.51.2.1 Exception()	30
		7.51.2.2 type_description()	60
7.52	qpp::ex	cception::OutOfRange Class Reference	61
	7.52.1	Detailed Description	62
		Member Function Documentation	
		7.52.2.1 Exception()	
		7.52.2.2 type_description()	
7 53	annex	cception::PermInvalid Class Reference	
7.00		Detailed Description	
		Member Function Documentation	
	1.00.2		
		7.53.2.1 Exception()	
		7.53.2.2 type_description()	
7.54	qpp::ex	cception::PermMismatchDims Class Reference	<i>i</i> 5

xxiv CONTENTS

7.54.	1 Detailed Description
7.54.	2 Member Function Documentation
	7.54.2.1 Exception()
	7.54.2.2 type_description()
7.55 qpp::	QCircuit Class Reference
7.55.	1 Detailed Description
7.55.	2 Member Typedef Documentation
	7.55.2.1 const_iterator
7.55.	3 Member Enumeration Documentation
	7.55.3.1 GateType
	7.55.3.2 MeasureType
	7.55.3.3 StepType
7.55.	4 Constructor & Destructor Documentation
	7.55.4.1 QCircuit()
	7.55.4.2 ~QCircuit()
7.55.	5 Member Function Documentation
	7.55.5.1 add_hash_()
	7.55.5.2 begin() [1/2]
	7.55.5.3 begin() [2/2]
	7.55.5.4 cbegin()
	7.55.5.5 cCTRL() [1/4]
	7.55.5.6 cCTRL() [2/4]
	7.55.5.7 cCTRL() [3/4]
	7.55.5.8 cCTRL() [4/4]
	7.55.5.9 cCTRL_custom()
	7.55.5.10 cend()
	7.55.5.11 CTRL() [1/4]
	7.55.5.12 CTRL() [2/4]
	7.55.5.13 CTRL() [3/4]
	7.55.5.14 CTRL() [4/4]

CONTENTS xxv

7.55.5.15 CTRL_custom()
7.55.5.16 display()
7.55.5.17 end() [1/2]
7.55.5.18 end() [2/2]
7.55.5.19 gate() [1/3]
7.55.5.20 gate() [2/3]
7.55.5.21 gate() [3/3]
7.55.5.22 gate_custom()
7.55.5.23 gate_fan() [1/3]
7.55.5.24 gate_fan() [2/3]
7.55.5.25 gate_fan() [3/3]
7.55.5.26 get_cmat_hash_tbl_()
7.55.5.27 get_d()
7.55.5.28 get_gate_count() [1/2]
7.55.5.29 get_gate_count() [2/2]
7.55.5.30 get_gate_depth() [1/2]
7.55.5.31 get_gate_depth() [2/2]
7.55.5.32 get_gates_()
7.55.5.33 get_measured() [1/2]
7.55.5.34 get_measured() [2/2]
7.55.5.35 get_measurement_count() [1/2]
7.55.5.36 get_measurement_count() [2/2]
7.55.5.37 get_measurements_()
7.55.5.38 get_name()
7.55.5.39 get_nc()
7.55.5.40 get_non_measured()
7.55.5.41 get_nq()
7.55.5.42 get_step_count()
7.55.5.43 measureV() [1/2]
7.55.5.44 measureV() [2/2]

xxvi CONTENTS

		7.55.5.45	5 m	neas	sureZ	Z () .							 	 	 					289
		7.55.5.46	6 G	QFT(()								 	 	 					289
		7.55.5.47	7 T	FQ(()								 		 					289
		7.55.5.48	3 to	o_J8	SON(() .							 	 	 					290
	7.55.6	Friends A	٩nc	d Re	elated	d Fu	nctio	on D	ocu	men	tatio	on	 	 	 					290
		7.55.6.1	0	pera	ator<	<<	[1/4	1].					 		 					290
		7.55.6.2	0	pera	ator<	<<	[2/4	1].					 		 					291
		7.55.6.3	0	pera	ator<	<<	[3/4	1].					 	 	 					291
		7.55.6.4	0	pera	ator<	<<	[4/4	1].					 	 	 					291
		7.55.6.5	Q	QEng	gine								 	 	 					292
	7.55.7	Member [Da	ata C	Docur	men	ntatio	on .					 	 	 					292
		7.55.7.1	CI	mat	_has	sh_tk	ol_						 	 	 					292
		7.55.7.2	C	oun	t								 	 	 					292
		7.55.7.3	d	<u>.</u>									 		 					292
		7.55.7.4	d	lepth	h								 	 	 					292
		7.55.7.5	g	ates	S								 		 					293
		7.55.7.6	m	neas	sured	d							 	 	 					293
		7.55.7.7	m	neas	suren	nent	t_co	unt_					 		 					293
		7.55.7.8	m	neas	suren	nent	ts_						 	 	 					293
		7.55.7.9	n	ame	е								 	 	 					293
		7.55.7.10) n	nc									 	 	 					293
		7.55.7.11	1 n	nq									 	 	 					294
		7.55.7.12	2 st	tep_	_type	es_							 	 	 					294
7.56	qpp::Ql	Engine Cla	ass	s Re	eferer	nce							 	 	 					294
	7.56.1	Detailed [De	escri	iption	١.							 	 	 					296
	7.56.2	Construct	ctor	r & E	Destr	ucto	or Do	ocun	nent	atio	1		 	 	 					296
		7.56.2.1	C	QEng	gine() [1	/3]						 	 	 					296
		7.56.2.2	C	QΕn	gine() [2	/3]						 	 	 					297
		7.56.2.3	G	QΕng	gine() [3	/3]						 	 	 					297
		7.56.2.4	~	~QE	Engin	e()							 	 	 					297

CONTENTS xxvii

	7.56.3	Member Function Documentation	297
		7.56.3.1 display()	<u>2</u> 97
		7.56.3.2 execute() [1/2]	298
		7.56.3.3 execute() [2/2]	298
		7.56.3.4 get_circuit()	298
		7.56.3.5 get_dit()	298
		7.56.3.6 get_dits()	299
		7.56.3.7 get_measured() [1/2]	299
		7.56.3.8 get_measured() [2/2]	299
		7.56.3.9 get_not_measured()	300
		7.56.3.10 get_probs()	300
		7.56.3.11 get_psi()	300
		7.56.3.12 get_ref_psi()	300
		7.56.3.13 get_relative_pos_()	300
		7.56.3.14 operator=()	301
		7.56.3.15 reset()	301
		7.56.3.16 set_dit()	301
		7.56.3.17 set_measured_()	302
		7.56.3.18 to_JSON()	302
	7.56.4	Member Data Documentation	302
		7.56.4.1 dits	302
		7.56.4.2 probs	302
		7.56.4.3 psi	303
		7.56.4.4 qc	303
		7.56.4.5 subsys	303
7.57	qpp::Q	ubitAmplitudeDampingNoise Class Reference	303
	7.57.1	Detailed Description	304
	7.57.2	Constructor & Destructor Documentation	304
		7.57.2.1 QubitAmplitudeDampingNoise()	304
7.58	qpp::Qı	ubitBitFlipNoise Class Reference	305

xxviii CONTENTS

	7.58.1	Detailed Description	306
	7.58.2	Constructor & Destructor Documentation	306
		7.58.2.1 QubitBitFlipNoise()	306
7.59	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	306
	7.59.1	Detailed Description	307
	7.59.2	Constructor & Destructor Documentation	307
		7.59.2.1 QubitBitPhaseFlipNoise()	307
7.60	qpp::Qı	ubitDepolarizingNoise Class Reference	308
	7.60.1	Detailed Description	309
	7.60.2	Constructor & Destructor Documentation	309
		7.60.2.1 QubitDepolarizingNoise()	309
7.61	qpp::Qı	ubitPhaseDampingNoise Class Reference	309
	7.61.1	Detailed Description	310
	7.61.2	Constructor & Destructor Documentation	310
		7.61.2.1 QubitPhaseDampingNoise()	310
7.62	qpp::Qı	ubitPhaseFlipNoise Class Reference	311
	7.62.1	Detailed Description	312
	7.62.2	Constructor & Destructor Documentation	312
		7.62.2.1 QubitPhaseFlipNoise()	312
7.63	qpp::ex	ception::QuditAlreadyMeasured Class Reference	312
	7.63.1	Detailed Description	313
	7.63.2	Member Function Documentation	313
		7.63.2.1 Exception()	313
		7.63.2.2 type_description()	314
7.64	qpp::Qı	uditDepolarizingNoise Class Reference	314
	7.64.1	Detailed Description	315
	7.64.2	Constructor & Destructor Documentation	315
		7.64.2.1 QuditDepolarizingNoise()	315
	7.64.3	Member Function Documentation	316
		7.64.3.1 fill_Ks_()	316

CONTENTS xxix

		7.64.3.2 fill_probs_()	16
7.65	qpp::Ra	andomDevices Class Reference	17
	7.65.1	Detailed Description	18
	7.65.2	Constructor & Destructor Documentation	18
		7.65.2.1 RandomDevices()	18
		7.65.2.2 ~RandomDevices()	19
	7.65.3	Member Function Documentation	19
		7.65.3.1 get_prng()	19
		7.65.3.2 load()	19
		7.65.3.3 save()	19
	7.65.4	Friends And Related Function Documentation	20
		7.65.4.1 internal::Singleton < RandomDevices >	20
	7.65.5	Member Data Documentation	20
		7.65.5.1 prng	20
		7.65.5.2 rd	20
7.66	qpp::int	ternal::Singleton< T > Class Template Reference	20
	7.66.1	Detailed Description	21
	7.66.2	Constructor & Destructor Documentation	
	7.66.2	Constructor & Destructor Documentation 3 7.66.2.1 Singleton() [1/2] 3	21
	7.66.2		21 22
	7.66.2	7.66.2.1 Singleton() [1/2]	21 22 22
		7.66.2.1 Singleton() [1/2]	21 22 22 22
		7.66.2.1 Singleton() [1/2]	22 22 22 22
		7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3	22 22 22 22 22
		7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3 7.66.3.1 get_instance() 3	22 22 22 22 22 22
	7.66.3	7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3 7.66.3.1 get_instance() 3 7.66.3.2 get_thread_local_instance() 3	21 22 22 22 22 22 22
7.67	7.66.3 qpp::ex	7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3 7.66.3.1 get_instance() 3 7.66.3.2 get_thread_local_instance() 3 7.66.3.3 operator=() 3	21 22 22 22 22 22 22 22
7.67	7.66.3 qpp::ex 7.67.1	7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3 7.66.3.1 get_instance() 3 7.66.3.2 get_thread_local_instance() 3 7.66.3.3 operator=() 3 **Cception::SizeMismatch Class Reference 3	221 222 222 222 222 222 223
7.67	7.66.3 qpp::ex 7.67.1	7.66.2.1 Singleton() [1/2] 3 7.66.2.2 Singleton() [2/2] 3 7.66.2.3 ~Singleton() 3 Member Function Documentation 3 7.66.3.1 get_instance() 3 7.66.3.2 get_thread_local_instance() 3 7.66.3.3 operator=() 3 **Coeption::SizeMismatch Class Reference 3 Detailed Description 3	22 22 22 22 22 22 22 22 22 22 22

7.68	qpp::No	oiseType::StateDependent Class Reference
	7.68.1	Detailed Description
7.69	qpp::No	oiseType::StateIndependent Class Reference
	7.69.1	Detailed Description
7.70	qpp::St	tates Class Reference
	7.70.1	Detailed Description
	7.70.2	Constructor & Destructor Documentation
		7.70.2.1 States()
		7.70.2.2 ~States()
	7.70.3	Member Function Documentation
		7.70.3.1 jn()
		7.70.3.2 mes()
		7.70.3.3 minus()
		7.70.3.4 one()
		7.70.3.5 plus()
		7.70.3.6 zero()
	7.70.4	Friends And Related Function Documentation
		7.70.4.1 internal::Singleton < const States >
	7.70.5	Member Data Documentation
		7.70.5.1 b00
		7.70.5.2 b01
		7.70.5.3 b10
		7.70.5.4 b11
		7.70.5.5 GHZ
		7.70.5.6 pb00
		7.70.5.7 pb01
		7.70.5.8 pb10
		7.70.5.9 pb11
		7.70.5.10 pGHZ
		7.70.5.11 pW

CONTENTS xxxi

		7.70.5.12 px0
		7.70.5.13 px1
		7.70.5.14 py0
		7.70.5.15 py1
		7.70.5.16 pz0
		7.70.5.17 pz1
		7.70.5.18 W
		7.70.5.19 x0
		7.70.5.20 x1
		7.70.5.21 y0
		7.70.5.22 y1
		7.70.5.23 z0
		7.70.5.24 z1
7.71	qpp::ex	cception::SubsysMismatchDims Class Reference
	7.71.1	Detailed Description
	7.71.2	Member Function Documentation
		7.71.2.1 Exception()
		7.71.2.2 type_description()
7.72	qpp::Ti	mer < T, CLOCK_T > Class Template Reference
	7.72.1	Detailed Description
	7.72.2	Constructor & Destructor Documentation
		7.72.2.1 Timer() [1/3]
		7.72.2.2 Timer() [2/3]
		7.72.2.3 Timer() [3/3]
		7.72.2.4 ~Timer()
	7.72.3	Member Function Documentation
		7.72.3.1 display()
		7.72.3.2 get_duration()
		7.72.3.3 operator=() [1/2]
		7.72.3.4 operator=() [2/2]

xxxii CONTENTS

		7.72.3.5	tic()	341
		7.72.3.6	tics()	341
		7.72.3.7	toc()	341
	7.72.4	Member D	Data Documentation	341
		7.72.4.1	end	341
		7.72.4.2	start	342
7.73	qpp::ex	ception::Ty	peMismatch Class Reference	342
	7.73.1	Detailed D	Description	343
	7.73.2	Member F	Function Documentation	343
		7.73.2.1	Exception()	343
		7.73.2.2	type_description()	344
7.74	qpp::ex	ception::Ur	ndefinedType Class Reference	344
	7.74.1	Detailed D	Description	345
	7.74.2	Member F	Function Documentation	345
		7.74.2.1	Exception()	345
		7.74.2.2	type_description()	346
7.75	qpp::ex	ception::Ur	nknown Class Reference	346
	7.75.1	Detailed D	Description	347
	7.75.2	Member F	Function Documentation	347
		7.75.2.1	Exception()	347
		7.75.2.2	type_description()	348
7.76	qpp::Q0	Circuit::itera	ator::value_type_ Class Reference	348
	7.76.1	Construct	or & Destructor Documentation	349
		7.76.1.1	value_type_() [1/2]	349
		7.76.1.2	value_type_() [2/2]	349
	7.76.2	Member F	Function Documentation	350
		7.76.2.1	display()	350
		7.76.2.2	operator=()	350
	7.76.3	Member D	Data Documentation	350
		7.76.3.1	gates_ip	350
		7.76.3.2	ip	351
		7.76.3.3	measurements_ip	351
		7.76.3.4	type	351
		7.76.3.5	value_type_qc	351
7.77	qpp::ex	ception::Ze	eroSize Class Reference	352
	7.77.1	Detailed D	Description	353
	7.77.2	Member F	Function Documentation	353
		7.77.2.1	Exception()	353
		7.77.2.2	type_description()	353

CONTENTS xxxiii

8	File I	Documentation	355
	8.1	classes/circuits.h File Reference	355
		8.1.1 Detailed Description	356
	8.2	classes/codes.h File Reference	356
		8.2.1 Detailed Description	356
	8.3	classes/exception.h File Reference	357
		8.3.1 Detailed Description	359
	8.4	classes/gates.h File Reference	359
		8.4.1 Detailed Description	359
	8.5	classes/idisplay.h File Reference	360
		8.5.1 Detailed Description	360
	8.6	classes/init.h File Reference	360
		8.6.1 Detailed Description	361
	8.7	classes/noise.h File Reference	361
		8.7.1 Detailed Description	362
	8.8	classes/random_devices.h File Reference	362
		8.8.1 Detailed Description	362
	8.9	classes/reversible.h File Reference	363
		8.9.1 Detailed Description	363
	8.10	classes/states.h File Reference	363
		8.10.1 Detailed Description	364
	8.11	classes/timer.h File Reference	364
		8.11.1 Detailed Description	365
	8.12	constants.h File Reference	365
		8.12.1 Detailed Description	366
	8.13	entanglement.h File Reference	366
		8.13.1 Detailed Description	368
	8.14	entropies.h File Reference	368
		8.14.1 Detailed Description	369
	8.15	experimental/experimental.h File Reference	369

	8.15.1 Detailed Description	369
8.16	functions.h File Reference	369
	8.16.1 Detailed Description	374
8.17	input_output.h File Reference	374
	8.17.1 Detailed Description	375
8.18	instruments.h File Reference	375
	8.18.1 Detailed Description	377
8.19	internal/classes/iomanip.h File Reference	377
	8.19.1 Detailed Description	377
8.20	internal/classes/singleton.h File Reference	378
	8.20.1 Detailed Description	378
8.21	internal/util.h File Reference	378
	8.21.1 Detailed Description	380
8.22	MATLAB/matlab.h File Reference	380
	8.22.1 Detailed Description	381
8.23	number_theory.h File Reference	381
	8.23.1 Detailed Description	382
8.24	operations.h File Reference	383
	8.24.1 Detailed Description	385
8.25	qpp.h File Reference	385
	8.25.1 Detailed Description	386
	8.25.2 Macro Definition Documentation	386
	8.25.2.1 QPP_UNUSED	386
8.26	random.h File Reference	387
	8.26.1 Detailed Description	388
8.27	statistics.h File Reference	388
	8.27.1 Detailed Description	389
8.28	traits.h File Reference	389
	8.28.1 Detailed Description	390
8.29	types.h File Reference	391
	8.29.1 Detailed Description	392
8.30	/Users/vlad/qpp/README.md File Reference	392

Index

393

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

pp	
Quantum++ main namespace	13
p::exception	
Quantum++ exception hierarchy namespace	116
p::experimental	
Experimental/test functions/classes, do not use or modify	118
p::internal	
Internal utility functions, do not use them directly or modify them	118
p::literals	125

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
gpp::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	. 335
qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	
false_type	
<pre>app::is_complex< T ></pre>	207
<pre>qpp::is_iterable < T, typename ></pre>	
qpp::Bit circuit::Gate count	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen	
""	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange < InputIterator >	
qpp::QCircuit	. 267
qpp::QCircuit::iterator::value_type	. 348
qpp::QEngine	. 294
qpp::Timer < T, CLOCK_T >	. 337
qpp::IJSON	192
app::QCircuit	
app::QEngine	
is_base_of	. 20
qpp::is_matrix_expression< Derived >	211
qpp::QCircuit::iterator	
qpp::make_void < Ts >	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase< NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	. 309
qpp::NoiseBase < NoiseType::StateIndependent >	239
qpp::QubitBitFlipNoise	. 305
qpp::QubitBitPhaseFlipNoise	. 306
qpp::QubitDepolarizingNoise	. 308
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	
qpp::internal::Singleton < T >	
qpp::internal::Singleton < const Codes >	
qpp::Codes	
qpp::internal::Singleton < const Gates >	
qpp::Gates	
qpp::internal::Singleton< const Init >	320
qpp::Init	. 194
qpp::internal::Singleton < const States >	320
qpp::States	. 325
qpp::internal::Singleton< RandomDevices >	
qpp::RandomDevices	
···	
	325
qpp::NoiseType::StateIndependent	325
true_type	000
qpp::is_complex< std::complex< T >>	. 208
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T	
>().end()), decltype(*(std::declval< T >().begin()))>>	. 210

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit circuit
Classical reversible circuit simulator
qpp::Codes
Const Singleton class that defines quantum error correcting codes
qpp::exception::CustomException
Custom exception
qpp::exception::DimsInvalid
Invalid dimension(s) exception
qpp::exception::DimsMismatchCvector
Dimension(s) mismatch column vector size exception
qpp::exception::DimsMismatchMatrix
Dimension(s) mismatch matrix size exception
qpp::exception::DimsMismatchRvector
Dimension(s) mismatch row vector size exception
qpp::exception::DimsMismatchVector
Dimension(s) mismatch vector size exception
qpp::exception::DimsNotEqual
Dimensions not equal exception
qpp::internal::Display_Impl
qpp::exception::Duplicates
System (e.g. std::vector) has duplicates exception
qpp::Dynamic_bitset
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←
::bitset <n>)</n>
qpp::internal::EqualEigen
Functor for comparing Eigen expressions for equality
qpp::exception::Exception
Base class for generating Quantum++ custom exceptions
qpp::Bit_circuit::Gate_count
qpp::Gates
Const Singleton class that implements most commonly used gates
qpp::QCircuit::GateStep
One step consisting only of gates/operators in the circuit
qpp::internal::HashEigen
Functor for hashing Eigen expressions

8 Class Index

qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream 189	& os) const
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	192
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	194
qpp::exception::InvalidIterator	
Invalid iterator	196
qpp::internal::IOManipEigen	198
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	204
qpp::is_complex< T >	
Checks whether the type is a complex type	207
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container	
$qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \$	ecltype(*(std::declval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	212
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	217
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	218
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	220
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	222
qpp::exception::MatrixNotSquare	004
Matrix is not square exception	224
qpp::exception::MatrixNotSquareNorCvector	000
Matrix is not square nor column vector exception	226
qpp::exception::MatrixNotSquareNorRvector	000
Matrix is not square nor row vector exception	228
qpp::exception::MatrixNotSquareNorVector	000
Matrix is not square nor vector exception	230
qpp::exception::MatrixNotVector	000
Matrix is not a vector exception	232
qpp::QCircuit::MeasureStep	004
One step consisting only of measurements in the circuit	234
qpp::exception::NoCodeword Codeword does not exist exception	237
qpp::NoiseBase < T >	231
Base class for all noise models, derive your particular noise model	239
·	239
<pre>qpp::NoiseType</pre>	246
· · · · · · · · · · · · · · · · · · ·	240
qpp::exception::NotBipartite Not bi-partite exception	247
qpp::exception::NotImplemented	LTI
Code not yet implemented	249
qpp::exception::NotQubitCvector	L 10
Column vector is not 2 x 1 exception	251

4.1 Class List

qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	253
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	255
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	257
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	259
qpp::exception::OutOfRange	
Argument out of range exception	261
qpp::exception::PermInvalid	
Invalid permutation exception	263
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	265
qpp::QCircuit	
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	294
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	303
qpp::QubitBitFlipNoise	000
Qubit bit flip noise	305
qp::Qubit bit hip noise	300
Qubit bit-phase flip (dephasing) noise	306
• • • • •	300
qpp::QubitDepolarizingNoise	200
Qubit depolarizing noise	308
qpp::QubitPhaseDampingNoise	000
Qubit phase damping noise, as described in Nielsen and Chuang	309
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	311
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	312
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	314
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	317
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	320
qpp::exception::SizeMismatch	
Size mismatch exception	323
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	325
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	325
qpp::States	
Const Singleton class that implements most commonly used states	325
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	335
qpp::Timer< T, CLOCK_T >	
Chronometer	337
qpp::exception::TypeMismatch	
Type mismatch exception	342
<pre>qpp::exception::UndefinedType</pre>	
Not defined for this type exception	344
qpp::exception::Unknown	
Unknown exception	346
qpp::QCircuit::iterator::value_type	
alleboration and the second se	•

10		Class Index

qpp::exception::ZeroSize														
Object has zero size exception												 	. (352

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	365
entanglement.h	
Entanglement functions	366
entropies.h	
Entropy functions	368
functions.h	
Generic quantum computing functions	369
input_output.h	
Input/output functions	374
instruments.h	
Measurement functions	375
number_theory.h	
Number theory functions	381
operations.h	
Quantum operation functions	383
qpp.h	
Quantum++ main header file, includes all other necessary headers	385
random.h	
Randomness-related functions	387
statistics.h	
Statistics functions	388
traits.h	
Type traits	389
types.h	
Type aliases	391
classes/circuits.h	
Support for qudit quantum circuits	355
classes/codes.h	
Quantum error correcting codes	356
classes/exception.h	
Exceptions	357
classes/gates.h	
Quantum gates	359

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	360
classes/init.h	
Initialization	360
classes/noise.h	
Noise models	361
classes/random_devices.h	
Random devices	362
classes/reversible.h	
Support for classical reversible circuits	363
classes/states.h	
Quantum states	363
classes/timer.h	
Timing	364
experimental/experimental.h	
Experimental/test functions/classes	369
internal/util.h	
Internal utility functions	378
internal/classes/iomanip.h	
Input/output manipulators	377
internal/classes/singleton.h	
Singleton pattern via CRTP	378
MATLAB/matlab.h	
Input/output interfacing with MATLAB	380

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
template<typename Derived >
  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

 $\frac{internal::IOManipPointer}{internal::IOManipPointer} > disp \ (const \ PointerType \ *p, \ idx \ N, \ const \ std::string \ \&separator, \ const \ std::string \ \&separator, \ const \ std::string \ \&end="]")$

C-style pointer ostream manipulator.

template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)
```

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::← Scalar > >::type loadMATLAB (const std::string &mat file, const std::string &var name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)
 Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

• std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std \leftarrow ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

```
\label{localized_dyn_mat} $$\operatorname{dyn_mat}<\operatorname{typename\ Derived}:Scalar>\operatorname{ptrace1}$ (const\ Eigen::MatrixBase<\operatorname{Derived}>\&A,\ idx\ d=2)$
```

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)
```

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

• template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED =1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

• cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

template<typename Container >
 double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable
 Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

ŀ	prob	Real probability vector representing the probability distribution of X
	Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression	
dims	Dimensions of the bi-partite system	

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Α	Eigen expression
seed	Seed, 0 by default

Hash of its argument

6.1.3.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector


6.1.3.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters



Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.64 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.65 invperm()

Inverse permutation.

Parameters

perm	Permutation

Returns

Inverse of the permutation perm

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

```
6.1.3.67 ip() [2/2]
```

Generalized inner product.

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
Generated by	Subsystem dimensions

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.68 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	p Integer different from 0, 1 or -1	
k	Number of iterations. The probability of a false positive is 2^{-k} .	

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

|--|

Choi matrix

6.1.3.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

```
6.1.3.71 kron() [1/4]
```

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

```
head Eigen expression
```

Returns

Its argument head

```
6.1.3.72 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.73 kron() [3/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

Δc	std::vector of Eigen expressions
713	sidvector or Ligeri expressions

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.75 kronpow()

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

qpp::gcd()

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

qpp::save()

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

fname	Output file name
mamo	Output mo name

6.1.3.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Eigen dynamic matrix

```
6.1.3.80 loadMATLAB() [2/2]
```

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

A Eigen expression

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.3.83 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 lognegativity() [2/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Ylabels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

const std::vector< cmat > & Ks)

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	A Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

const cmat & U)

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

const std::vector< idx > & target,
const std::vector< idx > & dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

ſ	Α	Eigen expression
	Ks	Set of Kraus operators
	target	Subsystem indexes that are measured
	d	Subsystem dimensions

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

```
qpp::measure()
```

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension *d. mask* is a std::vector of non-negative integers, and each element in *mask* has to be strictly smaller than *d*.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.100 modinv()

Modular inverse of a mod p.

See also

qpp::egcd()

Note

a and p must be co-prime

а	Non-negative integer
р	Non-negative integer

Returns

Modular inverse $a^{-1} \mod p$

6.1.3.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.102 modpow()

Fast integer power modulo *p* based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx > \& \ midx, const \ std::vector < \ idx > \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.106 n2multiidx()

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

```
6.1.3.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

```
6.1.3.108 negativity() [2/2]
```

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.109 norm()

Frobenius norm.

Parameters

A Eigen expression

Returns

Frobenius norm of A

6.1.3.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Returns

Normalized state vector or density matrix

6.1.3.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

D-th root of unity $\exp(2\pi i/D)$

6.1.3.113 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.114 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero, as a dynamic matrix over the same scalar field as A

6.1.3.115 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

6.1.3.116 prod() [2/3]

Element-wise product of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Partial trace $Tr_{subsys}(\cdot)$ over the subsystems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.120 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

```
6.1.3.121 ptrace1() [2/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.126 QFT()

Qudit quantum Fourier transform.

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.127 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.128 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.132 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

```
6.1.3.133 rand() [5/5]

template<>>
cmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.134 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.135 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.136 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.137 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.142 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.143 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.144 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.145 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.146 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.147 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.148 renyi() [1/2]
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0.$

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.150 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.151 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.152 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.153 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.154 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.155 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.156 schatten()

Schatten matrix norm.

	Α	Eigen expression
ſ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.159 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.163 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.165 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.166 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.167 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.168 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.169 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.170 sum() [2/3]
```

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.172 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.173 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.174 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.175 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.176 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.177 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.179 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.180 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.181 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.182 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.184 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.185 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.186 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

• class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- · class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- template < class T >
 void hash combine (std::size t &seed, const T &v)
- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check square mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check vector (const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \;\; {\sf template}{<} {\sf typename \; Derived} >$

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check gubit vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool check perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

```
    template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen → ::MatrixBase< Derived2 > &B)
    template<typename T > void variadic_vector_emplace (std::vector< T > &)
    template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
    idx get_num_subsys (idx D, idx d)
```

6.4.1 Detailed Description

idx get_dim_subsys (idx sz, idx N)

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  \mbox{const std::vector} < \mbox{idx} > \& \mbox{dims} \mbox{)} \quad \mbox{[inline]}
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

```
6.4.2.5 check_dims_match_rvect()
```

```
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_eq_dims()
bool qpp::internal::check_eq_dims (
            const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
6.4.2.7 check_matching_sizes()
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
            const T2 & rhs ) [noexcept]
6.4.2.8 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
             std::vector < idx > v) [inline]
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
```

const std::vector< idx > & perm) [inline]

6.4.2.11 check_qubit_cvector()

```
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template < typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
```

```
6.4.2.17 check_subsys_match_dims()
```

```
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
            idx N ) [inline]
6.4.2.21 get_num_subsys()
idx qpp::internal::get_num_subsys (
            idx D,
            idx d ) [inline]
6.4.2.22 hash_combine()
template<class T >
void qpp::internal::hash_combine (
            std::size_t & seed,
            const T & v )
```

6.4.2.23 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.24 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.25 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.26 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.27 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx N ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.

7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

```
7.12.5.3 v_
```

```
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
```

Storage space.

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char \ast what () const no except override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.14.3 Member Function Documentation

7.14.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
Exception type description.
```

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.14.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

```
7.14.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.14.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.15 qpp::Bit_circuit::Gate_count Struct Reference

#include <classes/reversible.h>

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.15.1 Member Data Documentation

7.15.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.15.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.15.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.15.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.15.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.15.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:


• classes/reversible.h

7.16 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::Identity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.16.1 Detailed Description

const Singleton class that implements most commonly used gates

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.16.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.16.3 Member Function Documentation

7.16.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.16.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.16.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.16.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.16.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.16.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N	
N	Positive integer	
n	Number of qubits required for implementing the gat	

Returns

Modular multiplication gate

7.16.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.16.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
ıneıa	Rotation angle

Returns

Rotation gate

7.16.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.16.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.16.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
          idx D = 2) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.16.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.16.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.16.4 Friends And Related Function Documentation

```
7.16.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.16.5 Member Data Documentation

```
7.16.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.16.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.16.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.16.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.16.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.16.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.16.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.16.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.16.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.16.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.16.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.16.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.16.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.17 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    std::size_t gate_hash_
        gate hash
    std::vector< idx > ctrl_
        control
    std::vector< idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.17.1 Detailed Description

7.17.2.1 GateStep() [1/2]

Constructs a gate step instance.

One step consisting only of gates/operators in the circuit.

7.17.2 Constructor & Destructor Documentation

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.17.3 Member Data Documentation

```
7.17.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
7.17.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_
gate hash
7.17.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.17.3.4 name_
std::string qpp::QCircuit::GateStep::name_
```

custom name of the step

7.17.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits.h

7.18 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

```
    template<typename Derived >
        std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const
```

7.18.1 Detailed Description

Functor for hashing Eigen expressions.

7.18.2 Member Function Documentation

7.18.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.19 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

• IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

• IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

Default virtual destructor.

```
7.19.2.4 \simIDisplay() virtual qpp::IDisplay::\simIDisplay ( ) [virtual], [default]
```

7.19.3 Member Function Documentation

7.19.3.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QEngine, qpp::QCircuit, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

```
7.19.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.19.3.3 operator=() [2/2]
```

Default move assignment operator.

7.19.4 Friends And Related Function Documentation

7.19.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.20.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 IJSON() [1/3]
qpp::IJSON::IJSON ( ) [default]
Default constructor.
7.20.2.2 IJSON() [2/3]
qpp::IJSON::IJSON (
             const IJSON & ) [default]
Default copy constructor.
7.20.2.3 IJSON() [3/3]
qpp::IJSON::IJSON (
              IJSON && ) [default]
Default move constructor.
7.20.2.4 ∼IJSON()
virtual qpp::IJSON::~IJSON ( ) [virtual], [default]
Default virtual destructor.
7.20.3 Member Function Documentation
7.20.3.1 operator=() [1/2]
IJSON& qpp::IJSON::operator= (
              {\tt const\ IJSON\ \&\quad)\quad [default]}
Default copy assignment operator.
7.20.3.2 operator=() [2/2]
IJSON& qpp::IJSON::operator= (
              IJSON && ) [default]
Default move assignment operator.
7.20.3.3 to_JSON()
```

JSON representation of the derived instance, must be overridden by all derived classes.

bool enclosed_in_curly_brackets = true) const [pure virtual]

virtual std::string qpp::IJSON::to_JSON (

Parameters

enclosed_in_curly_brackets If true, encloses the result in curly brackets

Implemented in qpp::QEngine, and qpp::QCircuit.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.21 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

#include <classes/init.h>

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

```
• Init ()
```

Additional initializations.

• ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.21.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.21.2 Constructor & Destructor Documentation

```
7.21.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.21.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.21.3 Friends And Related Function Documentation

```
7.21.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.22 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.22.1 Detailed Description

Invalid iterator.

7.22.2 Member Function Documentation

7.22.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.22.2.2 type_description()

```
std::string qpp::exception::InvalidIterator::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.23 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.23.1 Constructor & Destructor Documentation

7.23.2 Member Function Documentation

```
7.23.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.3 Member Data Documentation

7.23.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.23.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.24 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_

7.24.1 Constructor & Destructor Documentation

7.24.1.1 IOManipPointer() [1/2]

7.24.1.2 IOManipPointer() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.24.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.24.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.24.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.24.3.5 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.25 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- · std::string start_
- std::string end_

7.25.1 Constructor & Destructor Documentation

```
7.25.1.1 IOManipRange() [1/2]
```

7.25.1.2 IOManipRange() [2/2]

7.25.2 Member Function Documentation

7.25.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.25.2.2 operator=()

7.25.3 Member Data Documentation

```
7.25.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.25.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.25.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.25.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.25.3.5 start_
template<typename InputIterator>
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]

• internal/classes/iomanip.h

7.26 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.26.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*


The documentation for this struct was generated from the following file:

7.27 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.27.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

7.28 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.28.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.29 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



 $\label{top:condition} \begin{tabular}{ll} Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T>().begin()), decltype(std::declval< T>().begin()))>>: \\ \begin{tabular}{ll} T>().begin())>>: \\ \begin{tabular}{ll} T>().begin()>>: \\ \begin{tabular}{ll} T>().begin()>>: \\ \begin{tabular}{ll} T>().begin()>: \\ \begin{tabular}{ll$



7.29.1 Detailed Description

 $\label{template} $$ \ensuremath{\mathsf{template}}$ $$ $ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ \ensuremath{\mathsf{t$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.30 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.30.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.31 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

• using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

bool operator== (const iterator &rhs) const

Equality operator.

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to const quantum circuit

value_type_ elem_ {nullptr}

7.31.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.31.2 Member Typedef Documentation

```
7.31.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.31.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.31.2.3 pointer
```

```
using qpp::QCircuit::iterator::pointer = const value_type*
```

iterator trait

7.31.2.4 reference

```
using qpp::QCircuit::iterator::reference = const value_type&
```

iterator trait

7.31.2.5 value_type

```
using qpp::QCircuit::iterator::value_type = value_type_
```

iterator trait

7.31.3 Constructor & Destructor Documentation

```
7.31.3.1 iterator() [1/2]
```

```
qpp::QCircuit::iterator::iterator ( ) [default]
```

Default constructor.

```
7.31.3.2 iterator() [2/2]
```

Default copy constructor.

7.31.4 Member Function Documentation

7.31.4.1 operator"!=()

Inequality operator.

Parameters

rhs | Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

7.31.4.2 operator*()

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

7.31.4.3 operator++() [1/2]

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

7.31.4.4 operator++() [2/2]

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.31.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.31.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.31.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.31.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.31.5 Member Data Documentation

```
7.31.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.31.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

< non-owning pointer to const quantum circuit

The documentation for this class was generated from the following file:

· classes/circuits.h

7.32 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.32.1 Detailed Description

```
template < typename... Ts > struct qpp::make_void < Ts >
```

Helper for qpp::to_void<> alias template.

See also

qpp::to_void<>

7.32.2 Member Typedef Documentation

7.32.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.33 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.33.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotSquare:$



 $Collaboration\ diagram\ for\ qpp::exception::MatrixNotSquare:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.36.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occurred
--

7.37.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.38.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.39.2 Member Function Documentation

7.39.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.39.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.40.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits.h>
```

 $Collaboration\ diagram\ for\ qpp:: QCircuit:: Measure Step:$



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size t > mats hash
- std::vector< idx > target_

target where the measurement is applied

- idx c_reg_ {}
- · std::string name_

custom name of the step

7.41.1 Detailed Description

One step consisting only of measurements in the circuit.

7.41.2 Constructor & Destructor Documentation

```
7.41.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.41.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.41.3 Member Data Documentation

```
7.41.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

7.41.3.2 mats_hash_

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_
```

hashes of measurement matrix/matrices

7.41.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.41.3.4 name_

```
std::string qpp::QCircuit::MeasureStep::name_
```

custom name of the step

7.41.3.5 target_

std::vector<idx> qpp::QCircuit::MeasureStep::target_

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.42 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.42.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.42.2 Member Function Documentation

7.42.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.42.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.43 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs_

probabilities

• idx d_ {}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.43.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.43.2 Member Typedef Documentation

7.43.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.43.3 Constructor & Destructor Documentation

7.43.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.43.4 Member Function Documentation

7.43.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.43.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.43.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.43.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.43.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.43.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.43.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.43.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.43.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.43.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.43.5 Member Data Documentation

7.43.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
```

7.43.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.43.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.43.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.43.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

7.44 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.44.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.45 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.45.2 Member Function Documentation

7.45.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.45.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Code not yet implemented.

7.46.2 Member Function Documentation

7.46.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.48.2 Member Function Documentation

7.48.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.48.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.50.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.51.2 Member Function Documentation

7.51.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.51.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Argument out of range exception.

Argument out of range

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.52.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.53.2 Member Function Documentation

7.53.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.53.2.2 type_description()

std::string qpp::exception::PermInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.54.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.54.2 Member Function Documentation

7.54.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception

7.54.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.55 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
 GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTR

GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,

GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGE GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

· using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get gate count (const std::string &name) const

Quantum circuit gate count.

idx get_gate_depth () const

Quantum circuit total gate depth.

• idx get_gate_depth (const std::string &name QPP_UNUSED_) const

Quantum circuit gate depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

• idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate_fan (const cmat &U, const std::vector< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

• QCircuit & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix ν

 std::string to_JSON (bool enclosed_in_curly_brackets=true) const override *qpp::IJOSN::to_JSON() override*

Private Member Functions

void add hash (const cmat &U, std::size t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get measurements () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates_() const noexcept

Vector of qpp::QCircuit::GateStep.

• const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_ () const noexcept

Hash table with the matrices used in the circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

```
    const idx nq
```

number of qudits

const idx nc_

number of classical "dits"

const idx d

qudit dimension

std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

std::unordered_map< std::size_t, cmat > cmat_hash_tbl_{{}}

• std::unordered map< std::string, idx > count {}

keeps track of the gate counts

std::unordered_map< std::string, idx > depth_{{}}

keeps track of the gate depths

std::unordered map< std::string, idx > measurement count {}

keeps track of the measurement counts

std::vector< GateStep > gates_{}{}

type of each step

```
gates
• std::vector< MeasureStep > measurements_ {}
    measurements
• std::vector< StepType > step_types_ {}
```

Friends

- class QEngine
- std::ostream & operator << (std::ostream &os, const GateType &gate_type)

 Extraction operator overload for qpp::QCircuit::GateType enum class.
- std::ostream & operator << (std::ostream &os, const GateStep &gate_step)

 Extraction operator overload for qpp::QCircuit::GateStep class.
- std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)
- Extraction operator overload for qpp::QCircuit::MeasureType enum class.

 std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.55.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.55.2 Member Typedef Documentation

```
7.55.2.1 const_iterator
```

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.55.3 Member Enumeration Documentation

7.55.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one control and one target
SINGLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one control and multiple targets
MULTIPLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple controls and single target
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	custom controlled gate with multiple controls and multiple targets
SINGLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one classical control and one target
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	custom controlled gate with multiple controls and multiple targets

7.55.3.2 MeasureType

enum qpp::QCircuit::MeasureType [strong]

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$

7.55.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.55.4 Constructor & Destructor Documentation

7.55.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits
nc	Number of classical dits
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)
name	Circuit name (optional)

7.55.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.55.5 Member Function Documentation

7.55.5.1 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

```
7.55.5.2 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.55.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.55.5.4 cbegin()
```

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.55.5.5 cCTRL() [1/4]
```

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

const std::vector< idx > & target,
std::string name = "") [inline]

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
const std::vector< idx > & ctrl_dits,
idx target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.8 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.9 cCTRL_custom()

```
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

7.55.5.10 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.55.5.11 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.13 CTRL() [3/4]

QCircuit& qpp::QCircuit::CTRL (
```

```
const cmat & U,
const std::vector< idx > & ctrl,
idx target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

U	Multiple-qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes where the gate <i>U</i> is applied depending on the values of the control qudits	
name	Optional gate name	

Returns

Reference to the current instance

```
7.55.5.16 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.55.5.17 end() [1/2]
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.55.5.18 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate U on single qudit i.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

U	Three qudit quantum gate		
i	Qudit index		
Generated b	Qudit index by Boxygen		
k	Qudit index		
name	Optional gate name		

Returns

Reference to the current instance

7.55.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate U is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.23 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.24 gate_fan() [2/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them	
name	Optional gate name	

Returns

Reference to the current instance

```
7.55.5.25 gate_fan() [3/3]
```

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

7.55.5.26 get_cmat_hash_tbl_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.55.5.27 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

```
7.55.5.28 get_gate_count() [1/2]
idx qpp::QCircuit::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

Returns

Total gate count

```
7.55.5.29 get_gate_count() [2/2]
```

Quantum circuit gate count.

Parameters

name	Gate name

Returns

Gate count

```
7.55.5.30 get_gate_depth() [1/2]
```

```
idx qpp::QCircuit::get_gate_depth ( ) const [inline]
```

Quantum circuit total gate depth.

Returns

Total gate depth

```
7.55.5.31 get_gate_depth() [2/2]
idx qpp::QCircuit::get_gate_depth (
             const std::string &name QPP_UNUSED_ ) const [inline]
Quantum circuit gate depth.
Parameters
 name
         Gate name
Returns
     Gate depth
7.55.5.32 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
Returns
     Vector of qpp::QCircuit::GateStep
7.55.5.33 get_measured() [1/2]
idx qpp::QCircuit::get_measured (
             idx i ) const [inline]
Check whether qudit i was already measured.
```

Parameters

Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.55.5.34 get_measured() [2/2]
```

```
\verb|std::vector<| idx>| qpp::QCircuit::get_measured () const [inline]|
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.55.5.35 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.55.5.36 get_measurement_count() [2/2]

Quantum circuit measurement count.

Parameters

```
name | Measurement name
```

Returns

Measurement count

7.55.5.37 get_measurements_()

```
\verb|const| std::vector<| MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private], [noexcept] \\
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.55.5.38 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.55.5.39 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.55.5.40 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.5.41 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.55.5.42 get_step_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.55.5.43 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.55.5.44 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	Generated by Doxygen

Returns

Reference to the current instance

7.55.5.45 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.55.5.46 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.47 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.48 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.55.6 Friends And Related Function Documentation

 ${\bf Extraction\ operator\ overload\ for\ qpp::} {\bf QCircuit::} {\bf GateType\ enum\ class.}$

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

```
7.55.6.5 QEngine
```

```
friend class QEngine [friend]
```

7.55.7 Member Data Documentation

```
7.55.7.1 cmat_hash_tbl_
```

```
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
```

hash table with the matrices used in the circuit, with [Key = idx, Value = cmat]

```
7.55.7.2 count_
```

```
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
```

keeps track of the gate counts

```
7.55.7.3 d_
```

```
const idx qpp::QCircuit::d_ [private]
```

qudit dimension

```
7.55.7.4 depth_
```

```
std::unordered_map<std::string, idx> qpp::QCircuit::depth_ {} [private]
```

keeps track of the gate depths

```
7.55.7.5 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.55.7.6 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.55.7.7 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
keeps track of the measurement counts
7.55.7.8 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.55.7.9 name
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.55.7.10 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
```

```
7.55.7.11 nq_
const idx qpp::QCircuit::nq_ [private]
```

7.55.7.12 step_types_

number of qudits

```
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
```

type of each step

The documentation for this class was generated from the following file:


· classes/circuits.h

7.56 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits.h>
```

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector < idx > get_dits () const

Vector with the values of the underlying classical dits.

idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

• void reset ()

Resets the engine.

void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuit * qc_
        pointer to constant quantum circuit
    ket psi_
        state vector
    std::vector < idx > dits_
        classical dits
    std::vector < double > probs_
        measurement probabilities
    std::vector < idx > subsys_
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.56.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.56.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.56.2.4 ~QEngine()
```

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.56.3 Member Function Documentation

```
7.56.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

```
7.56.3.3 execute() [2/2]
```

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

```
7.56.3.4 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.56.3.5 get_dit()
```

```
idx qpp::QEngine::get_dit (
         idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

7.56.3.6 get_dits()

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.56.3.7 get_measured() [1/2]

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit i was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

7.56.3.8 get_measured() [2/2]

```
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.56.3.9 get_not_measured()

```
std::vector<idx> qpp::QEngine::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.56.3.10 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.56.3.11 get_psi()

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.56.3.12 get_ref_psi()

```
ket& qpp::QEngine::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

7.56.3.13 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.56.3.14 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.56.3.15 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.56.3.16 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.56.3.17 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.56.3.18 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.56.4 Member Data Documentation

```
7.56.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits

7.56.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
```

```
7.56.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector

7.56.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit

7.56.4.5 subsys_
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:

std::vector<idx> qpp::QEngine::subsys_ [protected]


classes/circuits.h

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \mbox{double } p \mbox{ ) [inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

gamma	Phase damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

```
p Noise probability
```

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.63.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.64.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.64.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

```
7.65.2.2 ∼RandomDevices()
```

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
             const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static} \ \texttt{T\& qpp::internal::Singleton} < \ \texttt{T} \ > :: \texttt{get\_instance} \ ( \ ) \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.67.2.2 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.

    ket b00 {ket::Zero(4)}

      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.70.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

friend class internal::Singleton< const States > [friend]

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.70.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

7.70.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	П
--	---

7.71.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

· double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.72.2 Constructor & Destructor Documentation

```
7.72.2.1 Timer() [1/3]
```

```
\label{lock-type-ame} $$ $$ template<type-name T = std::chrono::steady \leftarrow \_clock> $$ $$ qpp::Timer< T, CLOCK_T >::Timer ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.72.2.2 Timer() [2/3]

Default copy constructor.

7.72.2.3 Timer() [3/3]

Default move constructor.

7.72.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.72.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.72.3.4 operator=() [2/2]
```

Default move assignment operator.

7.72.3.5 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.6 tics()

```
\label{lock_typename} $$ $$ template< typename T = std::chrono::steady \leftarrow \_clock> $$ double $$ qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept] $$
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
\label{lock_typename} $$ $$ template < typename $$ CLOCK_T = std::chrono::steady \hookrightarrow \_clock > $$ CLOCK_T::time\_point $$ qpp::Timer < T, CLOCK_T >::start_ [protected] $$
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.73.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.74.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.75.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the parent iterator</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

7.76.1 Constructor & Destructor Documentation

```
7.76.1.2 value_type_() [2/2]
qpp::QCircuit::iterator::value_type_::value_type_ (
```

```
const value_type_ & ) [default]
```

Default copy constructor.

7.76.2 Member Function Documentation

```
7.76.2.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.3 Member Data Documentation

```
7.76.3.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
```

```
7.76.3.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.3.3 measurements_ip_
\verb|std::vector<| MeasureStep| > ::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| | qpp::QCircuit::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_:
ip_ {}
measurements instruction pointer
7.76.3.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.3.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the parent iterator
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.77.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

- class qpp::QCircuit::iterator::value_type_
- class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

356 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

358 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

360 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Eigenvectors.

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template < typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
      Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.
template<typename Derived >
  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template < typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
ullet template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.
```

dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

• cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >--:value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container > ::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator"" _prj ()

Multi-partite qubit projector user-defined literal.

template<class T >

void qpp::internal::hash_combine (std::size_t &seed, const T &v)

• template<typename Derived >

std::size_t qpp::hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)

Computes the hash of en Eigen matrix/vector/expression.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

- template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

 Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const

Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat $> qpp::measure_seq$ (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer
 PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton < T >
 Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool qpp::internal::check no duplicates (std::vector < idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get dim subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

• std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint dpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)

Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat gpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
```

```
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



8.28 traits.h File Reference 389

Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::sigma (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_{\leftarrow} iterable< Container >::value >::type *=nullptr)$

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltyp
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex< double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.29.1 Detailed Description

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 392	applyTFQ
\sim Codes	qpp, 35
qpp::Codes, 136	avg
~Dynamic_bitset	qpp, 36
qpp::Dynamic_bitset, 158	11.17
~Gates	b00
	qpp::States, 330
qpp::Gates, 174	b01
~IDisplay	
qpp::IDisplay, 190	qpp::States, 331
∼IJSON	b10
qpp::IJSON, 193	qpp::States, 331
\sim Init	b11
qpp::Init, 195	qpp::States, 331
~NoiseBase	begin
qpp::NoiseBase, 242	qpp::QCircuit, 274
~QCircuit	bigint
	-
qpp::QCircuit, 273	qpp, 26
~QEngine	Bit_circuit
qpp::QEngine, 297	qpp::Bit_circuit, 131
\sim RandomDevices	bloch2rho
qpp::RandomDevices, 318	qpp, 36
~Singleton	bra
qpp::internal::Singleton, 322	qpp, <mark>26</mark>
~States	-11-1-7 -
	c_reg_
qpp::States, 328	qpp::QCircuit::MeasureStep, 236
~Timer	
qpp::Timer, 339	cCTRL_custom
	qpp::QCircuit, 276
A_	cCTRL
qpp::internal::IOManipEigen, 199	qpp::QCircuit, 274–276
absm	CNOTba
qpp, 28	qpp::Gates, 183
abssq	CNOT
qpp, 29	qpp::Bit circuit, 131
add_hash_	qpp::Bit_circuit::Gate_count, 170
qpp::QCircuit, 273	qpp::Gates, 183
adjoint	CTRL_custom
qpp, 30	qpp::QCircuit, 279
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuit, 277-279
qpp, 30	cbegin
any	qpp::QCircuit, 274
qpp::Dynamic_bitset, 158	cend
apply	qpp::QCircuit, 277
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
app. 35	check dims match cyect

qpp::internal, 120	comm
check_dims_match_mat	qpp, 37
qpp::internal, 120	complement
check_dims_match_rvect	qpp, 38
qpp::internal, 120	compperm
check_eq_dims	qpp, 38
qpp::internal, 121	compute_probs_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_no_duplicates	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_nonzero_size	qpp, 40 conjugate
qpp::internal, 121	qpp, 40
check_perm	const_iterator
qpp::internal, 121	qpp::QCircuit, 271
check_qubit_cvector	constants.h, 365
qpp::internal, 121	contfrac2x
check_qubit_matrix	gpp, 40
qpp::internal, 122	convergents
check_qubit_rvector	qpp, 41
qpp::internal, 122	cor
check_qubit_vector	qpp, 42
qpp::internal, 122	cosm
check_rvector	qpp, 42
qpp::internal, 122	count
check_square_mat	qpp::Dynamic_bitset, 158
qpp::internal, 122	count
check_subsys_match_dims	qpp::QCircuit, 292
qpp::internal, 122	COV
check_vector	qpp, 43
qpp::internal, 123	cplx
choi2kraus	qpp, 27
qpp, 36	ctrl_
choi2super	qpp::QCircuit::GateStep, 187
qpp, 37 chop	CustomException
qpp, 116	qpp::exception::CustomException, 138
chop_	cwise
qpp::internal::IOManipEigen, 200	qpp, 43
classes/circuits.h, 355	CZ
classes/codes.h, 356	qpp::Gates, 183
classes/exception.h, 357	_
classes/gates.h, 359	d_
classes/idisplay.h, 360	qpp::NoiseBase, 245 qpp::QCircuit, 292
classes/init.h, 360	data
classes/noise.h, 361	
classes/random_devices.h, 362	qpp::Dynamic_bitset, 158 depth_
classes/reversible.h, 363	qpp::QCircuit, 292
classes/states.h, 363	det
classes/timer.h, 364	qpp, 44
cmat	difference_type
qpp, 26	qpp::QCircuit::iterator, 213
cmat_hash_tbl_	dirsum
qpp::QCircuit, 292	qpp, 44–46
Codes	dirsum2
qpp::Codes, 136	qpp::internal, 123
codeword	dirsumpow
qpp::Codes, 136	qpp, 46
٩٣٥٠٠٠٥٥٠ ، ١٥٥	אוררי

disp	qpp::exception::Duplicates, 154
qpp, 47, 48	qpp::exception::Exception, 169
display	qpp::exception::InvalidIterator, 197
qpp::Dynamic_bitset, 159	qpp::exception::MatrixMismatchSubsys, 219
qpp::IDisplay, 191	qpp::exception::MatrixNotCvector, 221
qpp::QCircuit, 280	qpp::exception::MatrixNotRvector, 223
<pre>qpp::QCircuit::iterator::value_type_, 350</pre>	qpp::exception::MatrixNotSquare, 225
qpp::QEngine, 297	qpp::exception::MatrixNotSquareNorCvector, 227
qpp::Timer, 339	qpp::exception::MatrixNotSquareNorRvector, 229
qpp::internal::IOManipEigen, 199	qpp::exception::MatrixNotSquareNorVector, 231
qpp::internal::IOManipPointer, 202	qpp::exception::MatrixNotVector, 233
qpp::internal::IOManipRange, 205	qpp::exception::NoCodeword, 238
display_impl_	qpp::exception::NotBipartite, 248
qpp::internal::Display_Impl_, 152	qpp::exception::NotImplemented, 250
dits_	qpp::exception::NotQubitCvector, 252
qpp::QEngine, 302	qpp::exception::NotQubitMatrix, 254
dmat	qpp::exception::NotQubitRvector, 256
qpp, 27	qpp::exception::NotQubitSubsys, 258
dyn_col_vect	qpp::exception::NotQubitVector, 260
qpp, 27	qpp::exception::OutOfRange, 262
dyn_mat	qpp::exception::PermInvalid, 264
qpp, 27	qpp::exception::PermMismatchDims, 266
dyn_row_vect	qpp::exception::QuditAlreadyMeasured, 313
qpp, 27	qpp::exception::SizeMismatch, 324
Dynamic_bitset	qpp::exception::SubsysMismatchDims, 336
qpp::Bit_circuit, 132	qpp::exception::TypeMismatch, 343
qpp::Dynamic_bitset, 157	qpp::exception::UndefinedType, 345
	qpp::exception::Unknown, 347
ee	qpp::exception::ZeroSize, 353
qpp, 116	execute
egcd	qpp::QEngine, 298
qpp, 49	expandout
eig	qpp::Gates, 175, 176
qpp, 49	experimental/experimental.h, 369
elem_	expm
qpp::QCircuit::iterator, 217	qpp, 52
end	- 11-11-7
qpp::QCircuit, 280	FRED
end_	qpp::Bit circuit, 132
qpp::Timer, 341	qpp::Bit_circuit::Gate_count, 171
qpp::internal::IOManipPointer, 202	qpp::Gates, 183
qpp::internal::IOManipRange, 206	factors
entanglement	qpp, 53
qpp, 50	Fd
entanglement.h, 366	qpp::Gates, 177
entropies.h, 368	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 316
qpp, 51	fill_probs_
evals	qpp::QuditDepolarizingNoise, 316
qpp, 51	first_
evects	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 369
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	qpp, 53
qpp::exception::DimsMismatchRvector, 147	4PP) 00
qpp::exception::DimsMismatchVector, 149	GHZ
qpp::exception::DimsNotEqual, 151	qpp::States, 331
-like manage and manage and and to t	-المات مصدورة .

	N : D 044
gate	qpp::NoiseBase, 244
qpp::QCircuit, 280, 281	get_last_p
gate_count	qpp::NoiseBase, 244
qpp::Bit_circuit, 134	get_measured
gate_custom	qpp::QCircuit, 285
qpp::QCircuit, 282	qpp::QEngine, 299
gate_fan	get_measurement_count
qpp::QCircuit, 282, 283	qpp::QCircuit, 286
gate_hash_	get measurements
qpp::QCircuit::GateStep, 187	qpp::QCircuit, 286
	get_name
gate_type_	qpp::Gates, 178
qpp::QCircuit::GateStep, 187	qpp::QCircuit, 286
GateStep	
qpp::QCircuit::GateStep, 186	get_nc
GateType	qpp::QCircuit, 287
qpp::QCircuit, 271	get_non_measured
Gates	qpp::QCircuit, 287
qpp::Gates, 174	get_not_measured
gates	qpp::QEngine, 299
gpp::QCircuit, 292	get_nq
gates ip	qpp::QCircuit, 287
qpp::QCircuit::iterator::value_type_, 350	get_num_subsys
	qpp::internal, 123
gcd	get_prng
qpp, 54	qpp::RandomDevices, 319
gconcurrence	get_probs
qpp, 54	qpp::NoiseBase, 244
generated_	
qpp::NoiseBase, 245	qpp::QEngine, 300
get	get_psi
qpp::Dynamic_bitset, 160	qpp::QEngine, 300
get_Ks	get_ref_psi
qpp::NoiseBase, 243	qpp::QEngine, 300
get_circuit	get_relative_pos_
qpp::QEngine, 298	qpp::QEngine, 300
	get_step_count
get_cmat_hash_tbl_	qpp::QCircuit, 287
qpp::QCircuit, 283	get_thread_local_instance
get_d	qpp::internal::Singleton, 322
qpp::NoiseBase, 243	grams
qpp::QCircuit, 283	qpp, 55, 56
get_dim_subsys	qpp, 33, 30
qpp::internal, 123	Н
get dit	
qpp::QEngine, 298	qpp::Gates, 183
get_dits	hash_combine
gpp::QEngine, 299	qpp::internal, 123
get_duration	hash_eigen
- -	qpp, <mark>56</mark>
qpp::Timer, 340	heig
get_gate_count	qpp, 57
qpp::QCircuit, 284	hevals
get_gate_depth	qpp, <mark>57</mark>
qpp::QCircuit, 284	hevects
get_gates_	qpp, 57
qpp::QCircuit, 285	حاادات
get_instance	<u>i_</u>
qpp::internal::Singleton, 322	qpp::NoiseBase, 245
get_last_idx	IDisplay
qpp::NoiseBase, 243	• •
	qpp::IDisplay, 190
get_last_K	IJSON

qpp::IJSON, 192, 193 IOManipEigen	qpp, 61, 62 kron2
qpp::internal::IOManipEigen, 199 IOManipPointer	qpp::internal, 123 kronpow
qpp::internal::IOManipPointer, 201, 202	qpp, 63
IOManipRange	Ks_
qpp::internal::IOManipRange, 205	qpp::NoiseBase, 246
ld	last
qpp::Gates, 178	qpp::internal::IOManipRange, 206
Id2	lcm
qpp::Gates, 184	qpp, 63, 64
idx	load
qpp, 28	qpp, 64
index_	qpp::RandomDevices, 319
qpp::Dynamic_bitset, 160	loadMATLAB
infty	
qpp, 116	qpp, 65, 66
Init	logdet
qpp::Init, 195	qpp, 66
input_output.h, 374	logm
instruments.h, 375	qpp, 67
internal/classes/iomanip.h, 377	lognegativity
internal/classes/singleton.h, 378	qpp, 67
internal/util.h, 378	MATI AD/
internal::Singleton < const Codes >	MATLAB/matlab.h, 380
qpp::Codes, 137	MODMUL
internal::Singleton < const Gates >	qpp::Gates, 178
qpp::Gates, 183	marginalX
internal::Singleton < const Init >	qpp, 68
qpp::Init, 195	marginalY
internal::Singleton < const States >	qpp, 68
qpp::States, 330	mats_hash_
internal::Singleton < RandomDevices >	qpp::QCircuit::MeasureStep, 236
qpp::RandomDevices, 320	maxn
inverse	qpp, 116
qpp, 58	measure
invperm	qpp, 69–73
qpp, 58	measure_seq
ip	qpp, 74
qpp, 59	MeasureStep
ip_	qpp::QCircuit::MeasureStep, 235
qpp::QCircuit::iterator::value_type_, 350	MeasureType
isprime	qpp::QCircuit, 272
qpp, 60	measured_
iterator	qpp::QCircuit, 293
qpp::QCircuit::iterator, 214	measurement_count_
iterator_category	qpp::QCircuit, 293
qpp::QCircuit::iterator, 213	measurement_type_
dbbdollouitterator, 210	qpp::QCircuit::MeasureStep, 236
jn	measurements_
qpp::States, 328	qpp::QCircuit, 293
4ppotatoo, 020	measurements ip
ket	qpp::QCircuit::iterator::value_type_, 351
qpp, 28	measureV
kraus2choi	qpp::QCircuit, 288
qpp, 60	measureZ
kraus2super	qpp::QCircuit, 289
qpp, 61	mes
kron	qpp::States, 328
MOII	ηρροιαιου, υ Συ

minus	operator<<
qpp::States, 329	qpp::IDisplay, 191
mket	qpp::QCircuit, 290, 291
qpp, 75, 76	operator*
modinv	qpp::QCircuit::iterator, 215
qpp, 76	operator()
modmul	qpp::NoiseBase, 244, 245
qpp, 77	qpp::internal::EqualEigen, 166
modpow	qpp::internal::HashEigen, 188
qpp, 77	operator++
mprj	qpp::QCircuit::iterator, 215
qpp, 78	operator-
msg_	qpp::Dynamic_bitset, 161
qpp::exception::Exception, 170	operator=
multiidx2n	qpp::IDisplay, 191
qpp, 79	qpp::IJSON, 193
qpp::internal, 124	qpp::QCircuit::iterator, 215
	qpp::QCircuit::iterator::value_type_, 350
n2multiidx	qpp::QEngine, 301
qpp, 79	qpp::Timer, 340
qpp::internal, 124	qpp::internal::IOManipPointer, 202
N_	qpp::internal::IOManipRange, 205
qpp::Dynamic_bitset, 165	qpp::internal::Singleton, 322
qpp::internal::IOManipPointer, 203	operator==
NOT	qpp::Dynamic_bitset, 162
qpp::Bit_circuit, 132	qpp::QCircuit::iterator, 216
qpp::Bit_circuit::Gate_count, 171	operator"" _bra
name	qpp::literals, 125
qpp::QCircuit, 293	operator"" _i
qpp::QCircuit::GateStep, 187	qpp, 82
qpp::QCircuit::MeasureStep, 236	
nc	qpp::literals, 125
qpp::QCircuit, 293	operator"" _ket
negativity	qpp::literals, 126
qpp, 80	operator"" _prj
	qpp::literals, 126
noise_type	p_
qpp::NoiseBase, 241	qpp::internal::IOManipPointer, 203
NoiseBase	pGHZ
qpp::NoiseBase, 241	qpp::States, 332
none	pb00
qpp::Dynamic_bitset, 160	•
norm	qpp::States, 331
qpp, 81	pb01
normalize	qpp::States, 331
qpp, 81	pb10
nq_	qpp::States, 332
qpp::QCircuit, 293	pb11
number_theory.h, 381	qpp::States, 332
	pi
offset_	qpp, 116
qpp::Dynamic_bitset, 161	plus
omega	qpp::States, 329
qpp, 81	pointer
one	qpp::QCircuit::iterator, 213
qpp::States, 329	powm
operations.h, 383	qpp, 82
operator!=	prj
qpp::Dynamic_bitset, 161	qpp, 82
qpp::QCircuit::iterator, 214	prng_

qpp::RandomDevices, 320	choi2kraus, 36
probs_	choi2super, 37
qpp::NoiseBase, 246	chop, 116
qpp::QEngine, 302	cmat, 26
prod	comm, 37
qpp, 83, 84	complement, 38
psi_	compperm, 38
qpp::QEngine, 302	concurrence, 40
ptrace	conjugate, 40
qpp, 84, 85	contfrac2x, 40
ptrace1	convergents, 41
qpp, 85, 86	cor, 42
ptrace2	cosm, 42
qpp, 86, 87	cov, 43
ptranspose	cplx, 27
qpp, 87, 88	cwise, 43
pW	det, 44
qpp::States, 332	dirsum, 44–46
px0	dirsumpow, 46
qpp::States, 332	• •
px1	disp, 47, 48
qpp::States, 332	dmat, 27
py0	dyn_col_vect, 27
qpp::States, 333	dyn_mat, 27
	dyn_row_vect, 27
py1	ee, 116
qpp::States, 333	egcd, 49
pz0	eig, 49
qpp::States, 333	entanglement, 50
pz1	entropy, 51
qpp::States, 333	evals, 51
QCircuit	evects, 52
qpp::QCircuit, 273	expm, 52
QEngine	factors, 53
qpp::QCircuit, 292	funm, 53
qpp::QEngine, 296, 297	gcd, 54
QFT	gconcurrence, 54
	grams, 55, 56
qpp, 88 qpp::QCircuit, 289	hash eigen, 56
	heig, 57
QPP_UNUSED_	hevals, 57
qpp.h, 386	hevects, 57
qc_	idx, 28
qpp::QCircuit::iterator, 217	infty, 116
qpp::QEngine, 303	inverse, 58
qmutualinfo	
qpp, 89	invperm, 58
qpp, 13	ip, 59
absm, 28	isprime, 60
abssq, 29	ket, 28
adjoint, 30	kraus2choi, 60
anticomm, 30	kraus2super, 61
apply, 31–33	kron, 61, 62
applyCTRL, 33, 34	kronpow, 63
applyQFT, 35	lcm, 63, 64
applyTFQ, 35	load, 64
avg, 36	loadMATLAB, 65, 66
bigint, 26	logdet, 66
bloch2rho, 36	logm, 67
bra, 26	lognegativity, 67

marginalX, 68	svdU, 110
marginalY, 68	svdV, 111
maxn, 116	syspermute, 111, 112
measure, 69–73	TFQ, 112
measure_seq, 74	to_void, 28
mket, 75, 76	trace, 112
modinv, 76	transpose, 113
modmul, 77	tsallis, 113, 114
modpow, 77	uniform, 114
mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 385
negativity, 80	QPP_UNUSED_, 386
norm, 81	qpp::Bit_circuit, 129
normalize, 81	Bit_circuit, 131
omega, 81	CNOT, 131
operator"" _i, 82	Dynamic bitset, 132
pi, 116	FRED, 132
powm, 82	gate_count, 134
prj, 82	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	∼Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton < const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	∼Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110	size, 164

storage_size_, 164 storage_type, 157 to_string, 164 v, 165 storage_type, 157 to_string, 164 v, 165 storage_type, 157 qpp::Gates, 172 cates, 174 CNOTba, 183 CNOT, 183 CNOT, 183 cNOT, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 Gates, 174 get_name, 178 H, 183 Id, 178 H, 183 Id, 178 Rn, 179 RX, 179 RX, 179 RX, 179 RX, 180 R2, 180 SWAP, 184 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 Xd, 182 X, 184 Xd, 182 X, 185 Z, 185		
storage_type, 157 to_string, 164 v165 v165 v165 v21le_type, 157 qpp::Gates, 172 Gates, 174 CNOTDa, 183 CNOT, 183 CNOT, 183 CNOT, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 FRED, 183 expandout, 175 get_name, 178 H, 183 ld, 178 ld, 178 ld, 178 Rn, 179 RX, 179 RX, 179 RX, 180 S, 184 T, 184 T, 184 T, 184 X, 184 X, 184 X, 184 X, 184 X, 182 Xd, 182 Qpp::Moise Pige. Xd, 182 Qpp::Moise Pige. Xd, 182 Qpp::Moise Pige. Xd, 182 Qpp::Moise Type. Xd, 185 Qpp::Mo	storage_size, 164	get_d, 243
to_string, 164 v_165 value_type, 157 qpp::Gates, 172		
v_1 165 value_type, 157 qpp::Gates, 172 ~Gates, 174 CNOTba, 183 CNOT, 183 CNOT, 183 crRL, 175 GZ, 183 expandout, 175, 176 FRED, 183 expandout, 177 Gates, 174 Gates, 177 Gates, 178 H, 183 Id, 178 Id, 178 Id, 178 RA, 179 RA, 179 RA, 179 RX, 179 RX, 179 RX, 180 RZ, 180 S, 184 TOF, 184 X, 184 X, 184 X, 184 X, 184 X, 184 X, 185 Z, 189 ANDINGRAPH, 190 display, 191 In losplay, 190 operator<, 191 operators, 193 operators, 193 operators, 191 operators, 193 operators, 194 operators, 295 operators, 295 operators, 295 operators, 295 operators, 295 operators, 295 operators		get_last_K, 244
value_type, 157 qpp:Gates, 172	to_string, 164	get_last_p, 244
qpp::Gates, 172	v_, 165	get_probs, 244
~ Gates, 174 CNOTba, 183 CNOT, 183 CNOT, 183 CNOT, 183 CTRL, 175 CZ, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 Internal::Singleton < const Gates >, 183 MODMUL, 178 Rn, 179 RX, 179 RX, 179 RX, 179 RY, 180 RZ, 180 SWAP, 184 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 X, 184 X, 184 X, 184 X, 185 Z, 185 Z	value_type, 157	i_, 245
CNOTba, 183 CNOT, 183 CNOT, 183 CNOT, 183 CTRL, 175 CZ, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 Id, 183 Id, 178 Id, 184 Internal::Singleton < const Gates >, 183 MODMUL, 178 RN, 179 RX, 179 RX, 180 S, 184 SWAP, 180 S, 184 T, 184 T, 184 TOF, 185 Z, 1	qpp::Gates, 172	Ks_, 246
CNOT, 183 CTRL, 175 CZ, 183 expandout, 175, 176 FRED, 183 expandout, 177 Gates, 177 Gates, 177 Gates, 178 Id, 179 RY, 180 RZ, 180 SWAP, 184 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 X, 184 X, 185 Z, 185	\sim Gates, 174	noise_type, 241
CTRL, 175 C2, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 internal::Singleton < const Gates >, 183 MODMUL, 178 RN, 179 RN, 179 RY, 180 RZ, 180 S, 184 SWAPd, 180 SWAP, 184 TOF, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 qpp::Ibisplay, 189 ~ Ibisplay, 191 IDisplay, 190 display, 191 IDisplay, 190 display, 191 qpp::Ibisplay, 190 qperator =, 191 qpp::Ibisplay, 193 qpp::Ibisplashase NolseBase = 242 compute state, 245 generated_, 245	CNOTba, 183	NoiseBase, 241
CTRL, 175 C2, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 internal::Singleton < const Gates >, 183 MODMUL, 178 RN, 179 RN, 179 RY, 180 RZ, 180 S, 184 SWAPd, 180 SWAP, 184 TOF, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 qpp::Ibisplay, 189 ~ Ibisplay, 191 IDisplay, 190 display, 191 IDisplay, 190 display, 191 qpp::Ibisplay, 190 qperator =, 191 qpp::Ibisplay, 193 qpp::Ibisplashase NolseBase = 242 compute state, 245 generated_, 245	CNOT, 183	operator(), 244, 245
expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 CCTRL_custom, 279 RN, 179 RN, 179 RX, 179 RY, 180 RZ, 180 S, 184 SWAP, 184 TOF, 184 Xd, 182 TOF, 184 Xd, 182 Y, 185 Z,		probs , 246
expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 CCTRL_custom, 279 RN, 179 RN, 179 RX, 179 RY, 180 RZ, 180 S, 184 SWAP, 184 TOF, 184 Xd, 182 TOF, 184 Xd, 182 Y, 185 Z,	CZ, 183	qpp::NoiseBase< T >, 239
FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 id, 178 id, 178 id, 184 internal::Singleton	expandout, 175, 176	
Fd, 177 Gates, 174 get_name, 178 H, 183 H, 183 Id, 178 Hobby 182 Hn 183 Id, 178 Gates, 174 get_name, 178 H, 183 Id, 178 H, 183 Id, 178 Id2, 184 Internal::Singleton < const Gates >, 183 MCDMUL, 178 Rn, 179 RX, 179 RX, 179 RY, 180 RZ, 180 SWAP, 184 TOF, 184 TOF, 184 Xd, 182 Y, 185 Zd, 182 qpp::Display, 190 display, 191 IDisplay, 190 operator <, 191 qpp::JISON, 193 IJSON, 192 qpp::JISINSN, 193 qpp::Noise Base	•	
Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 internal::Singleton < const Gates >, 183 MODMUL, 178 Rn, 179 RX, 179 RX, 180 RY, 180 SWAPd, 180 SWAPd, 180 SWAP, 184 T, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Zd, 182 Zd, 182 Qpp::Display, 190 Qperator <, 191 Qpp::Display, 190 Qperator <, 191 Qpp::Display, 193 Qpp::Display, 193 Qpp::Init, 194 ~\nit, 195 Init, 195 Init probab. Qpp: Qate Qa		
get_name, 178 H, 183 Id, 178 Id, 184 internal::Singleton < const Gates >, 183 MODMUL, 178 Rn, 179 RX, 179 RX, 179 RX, 179 RX, 180 SWAPd, 180 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 Gpp::IDisplay, 190 Gisplay, 191 IDisplay, 190 Operator < , 191 Operator = , 193 Operator = , 193 Operator < , 193 Operator = , 193 Operator < , 193 Operator = , 193 Operator < , 193 Operator = , 193 Operator = , 193 Operator < , 193 Operator = , 193 Operator < , 193 Operato		
Internal		
Id, 178 Id2, 184 CCTRL_custom, 276 Id2, 184 Internal::Singleton < const Gates > , 183 CCTRL_custom, 276 CTRL_custom, 279 CTRL_custom, 279 CTRL_277–279 CTRL_277–279 CTRL_277–279 CTRL_277–279 CDRL_277 CDRL	-	
Id2, 184		
internal::Singleton < const Gates > , 183 MODMUL, 178 Rn, 179 Rn, 179 RX, 179 RY, 180 RZ, 180 S, 184 SWAPd, 180 SWAP, 184 T, 184 TOF, 184 X, 184 X, 182 Y, 185 Z, 185 Z, 185 Z, 185 Z, 185 Z, 185 Z, 182 qpp::IDisplay, 190 display, 190 display, 191 IDisplay, 190 operator < , 191 operator = , 191 qpp::IJSON, 192 App::IJSON, 193 IJSON, 192, 193 operator = , 193 qpp::Ilnit, 194 ~Init, 195 Init, 195 Init, 195 Init, 195 Init, 195 Init rank: Singleton < const last she in a searce 2, 283 measurements _ 282 measurement _ 293 measure, 288 measure, 289 name _ 293		
MODMUL, 178 Rn, 179 Rn, 179 RX, 179 RX, 180 RZ, 180 RZ, 180 SWAPd, 180 SWAPd, 184 SWAPd, 184 Count_, 292 SWAP, 184 Count_, 292 TOF, 184 Xd, 182 Xd, 184 Xd, 182 Xd, 184 Xd, 182 Xd, 184 Xd, 182 Xd, 18		
Rn, 179 RX, 179 RX, 179 RY, 180 cend, 277 RZ, 180 s, 184 cond, 292 s, 184 cond, 292 const_iterator, 271 count_, 292 depth_, 280 cond_, 273 count_, 292 depth_, 292 TOF, 184 depth_, 292 TOF, 184 X, 184 depth_, 292 TOF, 185 gate_, 280, 281 y, 185 gate_, 280, 281 gate_, 282 gate_, 282 gate_, 283 gate_, 282 gate_, 283 gate_, 282 gate_, 283 gate_, 280 gate_, 283 gate_, 283 gate_, 280 gate_, 283 gate_, 282 gate_, 283 gate_, 280		
RX, 179 RY, 180 RZ, 180 S, 184 const_iterator, 271 SWAPd, 180 SWAP, 184 T, 184 TOF, 184 X, 184 X, 182 Y, 185 Z, 185 Zd, 182 qpp::IDisplay, 190 display, 191 IDisplay, 190 operator<, 191 operator<, 191 operator<, 191 operator<, 191 operator-, 193 IJSON, 192 ~IJSON, 193 qpp::Init, 194 ~Init, 195 Init, 195 Init, 195 Init, 195 Init rnal::Singleton < const Init >, 195 qpenator , 288 RAMP, 180 const_iterator, 271 const_ 282 compute_state_, 242 compute_state_, 242 compute_state_, 242 compute_state_, 283 const_iterator, 271 const_ 292 const_iterator, 271 const_ 192 const_iterator, 271 const_ 292 const_iterator, 271 display, 292 const_iterator, 271 display, 292 display, 190 get_count, 283 get_measure, 285 get_measure, 285 get_measurement_count, 286 get_nc, 287 qet_nc, 287 qet_nc, 287 qet_nc, 287 measured_, 293 measureve, 288 measurevel, 289 measurevel, 288 measurevel, 289 measurev		_ ,
RY, 180 RZ, 180 RZ, 180 S, 184 Const_lerator, 271 SWAPd, 180 SWAP, 184 Cy22 T, 184 Cy22 T, 184 Cy22 TOF, 184 Cy, 185 Cy4, 189 Cy1Display, 190 Cy1Display, 190 Cy1Display, 191 Cy1Display, 190 Cy1Di		
RZ, 180 S, 184 SWAPd, 180 Count_, 292 SWAP, 184 T, 184 Copply, 292 TOF, 184 Count_, 292 Const_iterator, 271 Count_, 292 Count_, 280 Count_, 282 Count_, 282 Count_, 282 Count_, 282 Count_, 283 Count_, 283 Count_, 283 Count_, 283 Count_, 284 Count_, 284 Count_, 284 Count_, 284 Count_, 284 Count_, 285 Count_, 286 Count_, 287 Count_, 193 Count_, 287 Count_, 193 Count_, 287 Count_, 194 Count_, 195 Count_, 195 Count_, 196 Count_, 197 Count_, 197 Count_, 198 Count_, 287 Count_, 198 Count_, 198 Count_, 287 Count_		_
S, 184 SWAPd, 180 SWAP, 184 T, 184 TOF, 184 X, 184 Xd, 182 Z, 185 Zd, 182 Qate_ Marty Mart		•
SWAPd, 180 SWAP, 184 T, 184 Cdepth 292 TOF, 184 X, 184 Cdsplay, 280 Xd, 182 Xd, 182 Y, 185 Z, 185 Zd, 182 Cupp:://display, 190 Cuplosplay, 190 Cuplosplay, 190 Cuprostor=(, 191 Cuprostor=(, 191 Cuprostor=(, 191 Cuprostor=(, 193 Cuprostor=(, 194 Cuprostor=(, 195 Cuprostor=(, 196 Cuprostor=(, 197 Cuprostor=(, 197 Cuprostor=(, 198 Cuprostor=(, 19		
SWAP, 184 T, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 qpp::IDisplay, 189 ~IDisplay, 190 display, 190 operator <, 191 operator =, 191 qpp::IJSON, 192 ~IJSON, 193 IJSON, 192 AUSON, 193 to JSON, 193 qpp::Init, 194 ~Init, 195 internal::Singleton < const Init >, 195 qpp::NoiseBase ~NoiseBase Aude page depth, 283 depth, 292 depth, 292 depth, 292 depth, 280 display, 280 end, 280 gate_and, 282 gate_and, 282, 283 GateType, 271 gates_, 292 gate_and_hash_tbl_, 283 gate_depth, 284 gate_depth, 284 gate_depth, 284 gate_depth, 284 gate_depth, 284 gate_measured, 285 gate_measurement_count, 286 gate_measurements_, 286 gate_neasurements_, 286 gate_neasurements_, 286 gate_neasurements_, 286 gate_neasurements_, 286 gate_neasured, 287 gate_neasured, 287 gate_neasured, 287 gate_neasured, 287 measured_, 287 measured_, 287 measured_, 293 measurement_, 293 measurements_, 293 measurements_, 293 measured_, 288 measureZ, 289 name_, 293		
T, 184 TOF, 184 TOF, 184 X, 184 X, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 qpp::IDisplay, 189	· · · · · · · · · · · · · · · · · · ·	
TOF, 184 X, 184 Xd, 182 Y, 185 Y, 185 Zd, 182 Gate_Custom, 282 Z, 185 Zd, 182 GateType, 271 qpp::IDisplay, 190 display, 191 IDisplay, 190 operator operator "IJSON, 192 "IJSON, 193 JJSON, 193 qpp::Init, 195 init, 195 internal::Singleton const lost Xd, 182 gate_custom, 282 gate_custom, 282 gate_fan, 282, 283 GateType, 271 gates_, 292 qpe:_cmat_hash_tbl_, 283 get_d, 283 idisplay, 190 get_gate_count, 284 get_gate_count, 284 get_gate_depth, 284 get_gates_, 285 get_measurement_count, 286 inget_gates_, 285 get_measurement_count, 286 inget_gates_, 285 get_measurement_count, 286 inget_gates_, 285 get_measurement_count, 286 inget_gates_, 287 get_measurement_count, 286 inget_gates_, 287 get_measurement_count, 286 inget_gates_, 287 get_measurement_gates measured_, 287 get_non_measured, 287 get_non_measured, 287 get_non_measured, 287 get_non_measured_, 287 measureType, 272 measureMents_, 293 measureMents_, 293 measureMents_, 293 measureMents_, 293 measureW, 288 measureV, 288 measureV, 288 measureZ, 289 name_, 293		
X, 184 Xd, 182 Y, 185 Z, 185 Zd, 182 Qpp::/Display, 189	•	
Xd, 182 Y, 185 Z, 185 Zd, 182 gate_custom, 282 gate_fan, 282, 283 Zd, 182 gpp::IDisplay, 189 also_lisplay, 190 display, 190 operator<<, 191 operator<=, 191 qpp::IJSON, 192 also_lisplay, 193 operator=, 193 to_JSON, 193 gpt_masurement_count, 286 to_JSON, 193 qpp::Init, 194 also_lisplay, 195 operator<= count, 195 internal::Singleton<= const Init >, 195 qpp::NoiseBase also_lisplay, 285 qate_custom, 282 gate_cate, 283 GateType, 271 gate_fan, 282, 283 gate_fan, 282, 283 gate_fan, 282 gate_fan, 282 get_mas_inso_lisplay get_d, 283 get_det_depth, 284 get_gates_, 285 get_measurement_count, 286 get_measurement_count, 286 get_measurements_, 286 get_name, 286 get_nc, 287 get_non_measured, 287 get_nq, 287 lnit, 195 get_nq, 287 qpp::NoiseBase also_lisplay also_lis		• •
Y, 185 Z, 185 Zd, 182 qpp::IDisplay, 189		
Z, 185 Zd, 182 GateType, 271 qpp::IDisplay, 189		
Zd, 182 GateType, 271 qpp::IDisplay, 189 gates_, 292 ~IDisplay, 190 get_cmat_hash_tbl_, 283 display, 191 get_d, 283 IDisplay, 190 get_gate_count, 284 operator<<, 191	Y, 185	- -
qpp::IDisplay, 189 gates_, 292 ~IDisplay, 190 get_cmat_hash_tbl_, 283 display, 191 get_d, 283 IDisplay, 190 get_gate_count, 284 operator<<, 191	Z, 185	
~IDisplay, 190 get_cmat_hash_tbl_, 283 display, 191 get_d, 283 IDisplay, 190 get_gate_count, 284 operator<<, 191	Zd, 182	GateType, 271
display, 191 get_d, 283 IDisplay, 190 get_gate_count, 284 operator<<, 191	qpp::IDisplay, 189	gates_, 292
IDisplay, 190	\sim IDisplay, 190	get_cmat_hash_tbl_, 283
operator < < , 191	• •	get_d, 283
operator=, 191 qpp::IJSON, 192 qpp::IJSON, 193 qst_measured, 285 qst_measurement_count, 286 IJSON, 192, 193 operator=, 193 to_JSON, 193 qpp::Init, 194 qpp::Init, 195 Init, 195 internal::Singleton< const Init >, 195 qpp::NoiseBase ~NoiseBase, 242 compute_probs_, 242 compute_state_, 242 d_, 245 get_measured, 285 get_measurement_count, 286 get_name, 286 get_name, 286 get_name, 287 get_non_measured, 287 get_nq, 287 MeasureType, 272 measured_, 293 measured_, 293 measurement_count_, 293 measureV, 288 measureZ, 289 generated_, 245 name_, 293	IDisplay, 190	get_gate_count, 284
qpp::IJSON, 192 get_measured, 285 ~IJSON, 193 get_measurement_count, 286 IJSON, 192, 193 get_measurements_, 286 operator=, 193 get_name, 286 to_JSON, 193 get_nc, 287 qpp::Init, 194 get_non_measured, 287 ~Init, 195 get_step_count, 287 internal::Singleton measureType, 272 qpp::NoiseBase measured_, 293 ~NoiseBase, 242 measurement_count_, 293 compute_probs_, 242 measurements_, 293 compute_state_, 242 measureV, 288 d_, 245 measureZ, 289 generated_, 245 name_, 293	operator<<, 191	get_gate_depth, 284
 ~IJSON, 193 JSON, 192, 193 Operator=, 193 Operator=, 193 Operator=, 194 Operator=, 195 Operator=, 196 Operator=, 197 Operator=, 198 Operator=, 199 Operator=, 193 Operator=, 286 Operator=, 287 Operator=, 286 Operator=, 286 Operator=, 286 Operator=, 287 Operator=, 286 Operator=, 287 Operator=, 287 Operator=, 287 Operator=, 287 Operator=, 287 Operator=, 286 Operator=, 287 Operator=, 286 Operator=, 287 Operator=, 287	operator=, 191	get_gates_, 285
IJSON, 192, 193 get_measurements_, 286 operator=, 193 get_name, 286 to_JSON, 193 get_nc, 287 get_non_measured, 287 get_non_measured, 287 compute_probs_, 242 compute_state_, 242 compute_state_, 242 get_ncessurement_, 293 compute_state_, 245 get_step_count_, 289 compute_state_, 245 get_step_count_, 293 compute_state_, 245 get_step_count_, 293 compute_state_, 245 generated_, 293 compute_state_, 245 generated_, 293 compute_state_, 245 generated_, 245 generated_, 245 generated_, 245 compute_state_, 245 compute_state	qpp::IJSON, 192	get_measured, 285
operator=, 193	\sim IJSON, 193	get_measurement_count, 286
to_JSON, 193 qpp::Init, 194	IJSON, 192, 193	get_measurements_, 286
qpp::Init, 194	operator=, 193	get_name, 286
qpp::Init, 194	to JSON, 193	get nc, 287
~Init, 195 Init, 195 Init, 195 Init, 195 Init, 195 Init, 195 Internal::Singleton < const Init > , 195 qet_step_count, 287 MeasureType, 272 qpp::NoiseBase ~NoiseBase, 242 compute_probs_, 242 compute_probs_, 242 compute_state_, 242 d_, 245 generated_, 245 get_nq, 287 get_step_count, 287 MeasureType, 272 measured_, 293 measurement_count_, 293 measureV, 288 measureZ, 289 name_, 293	gpp::Init, 194	
Init, 195 internal::Singleton < const Init >, 195 qpp::NoiseBase NoiseBase, 242 compute_probs_, 242 compute_state_, 242 d_, 245 get_step_count, 287 MeasureType, 272 measured_, 293 measurement_count_, 293 measurements_, 293 measureV, 288 measureZ, 289 generated_, 245 name_, 293		
internal::Singleton< const Init >, 195 qpp::NoiseBase	Init, 195	· - ·
qpp::NoiseBase measured_, 293		
~NoiseBase, 242 measurement_count_, 293 compute_probs_, 242 measurements_, 293 compute_state_, 242 measureV, 288 d_, 245 measureZ, 289 generated_, 245 name_, 293	,	
compute_probs_, 242 measurements_, 293 compute_state_, 242 measureV, 288 d_, 245 measureZ, 289 generated_, 245 name_, 293		<u>—</u> ·
compute_state_, 242 measureV, 288 d_, 245 measureZ, 289 generated_, 245 name_, 293		
d_, 245 measureZ, 289 generated_, 245 name_, 293		-
generated_, 245 name_, 293	. – –	
_		
901.0, 270	_	_
	901_100, 210	110_, 200

nq_, 293	get_probs, 300
operator<<, 290, 291	get_psi, 300
QCircuit, 273	get_ref_psi, 300
QEngine, 292	get relative pos , 300
QFT, 289	operator=, 301
step_types_, 294	probs_, 302
StepType, 272	psi_, 302
TFQ, 289	QEngine, 296, 297
to_JSON, 290	qc_, 303
qpp::QCircuit::GateStep, 185	reset, 301
ctrl , 187	set_dit, 301
gate_hash_, 187	set_measured_, 301
gate_type_, 187	subsys_, 303
GateStep, 186	to JSON, 302
name_, 187	qpp::QubitAmplitudeDampingNoise, 303
target_, 187	QubitAmplitudeDampingNoise, 304
qpp::QCircuit::MeasureStep, 234	qpp::QubitBitFlipNoise, 305
• •	
c_reg_, 236	QubitBitFlipNoise, 306
mats_hash_, 236	qpp::QubitBitPhaseFlipNoise, 306
MeasureStep, 235	QubitBitPhaseFlipNoise, 307
measurement_type_, 236	qpp::QubitDepolarizingNoise, 308
name_, 236	QubitDepolarizingNoise, 309
target_, 236	qpp::QubitPhaseDampingNoise, 309
qpp::QCircuit::iterator, 212	QubitPhaseDampingNoise, 310
difference_type, 213	qpp::QubitPhaseFlipNoise, 311
elem_, 217	QubitPhaseFlipNoise, 312
iterator, 214	qpp::QuditDepolarizingNoise, 314
iterator_category, 213	fill_Ks_, 316
operator!=, 214	fill_probs_, 316
operator*, 215	QuditDepolarizingNoise, 315
operator++, 215	qpp::RandomDevices, 317
operator=, 215	\sim RandomDevices, 318
operator==, 216	get_prng, 319
pointer, 213	internal::Singleton < RandomDevices >, 320
qc_, 217	load, 319
reference, 214	prng_, <mark>320</mark>
set_begin_, 216	RandomDevices, 318
set_end_, 216	rd_, 320
value_type, 214	save, 319
qpp::QCircuit::iterator::value_type_, 348	qpp::States, 325
display, 350	\sim States, 328
gates_ip_, 350	b00, 330
ip_, 350	b01, 331
measurements_ip_, 351	b10, 331
operator=, 350	b11, 331
type_, 351	GHZ, 331
value type , 349	internal::Singleton < const States >, 330
value_type_qc_, 351	jn, 328
qpp::QEngine, 294	mes, 328
~QEngine, 297	minus, 329
display, 297	one, 329
dits_, 302	pGHZ, 332
execute, 298	pb00, 331
get_circuit, 298	pb01, 331
get_dit, 298	pb10, 332
get_dits, 299	pb11, 332
get_measured, 299	plus, 329
get_not_measured, 299	pW, 332

	px0, 332	where_, 170
	px1, 332	qpp::exception::InvalidIterator, 196
	py0, 333	Exception, 197
	py1, 333	type_description, 197
	pz0, 333	qpp::exception::MatrixMismatchSubsys, 218
	pz1, 333	Exception, 219
	States, 328	type_description, 220
	W, 333	qpp::exception::MatrixNotCvector, 220
	x0, 333	Exception, 221
	x1, 334	type_description, 222
	y0, 334	qpp::exception::MatrixNotRvector, 222
	y1, 334	Exception, 223
	z0, 334	type_description, 224
	z1, 334	qpp::exception::MatrixNotSquare, 224
	zero, 330	Exception, 225
qqp	::Timer	type_description, 226
	∼Timer, 339	qpp::exception::MatrixNotSquareNorCvector, 226
	display, 339	Exception, 227
	end_, 341	type_description, 228
	get_duration, 340	qpp::exception::MatrixNotSquareNorRvector, 228
	operator=, 340	Exception, 229
	start_, 341	type_description, 230
	tic, 340	qpp::exception::MatrixNotSquareNorVector, 230
	tics, 341	Exception, 231
	Timer, 338, 339	type_description, 232
	toc, 341	qpp::exception::MatrixNotVector, 232
ann	::Timer< T, CLOCK_T >, 337	Exception, 233
	::exception, 116	type_description, 234
	::exception::CustomException, 137	qpp::exception::NoCodeword, 237
-11-1-	CustomException, 138	Exception, 238
	type_description, 139	type_description, 239
	what_, 139	qpp::exception::NotBipartite, 247
aab	::exception::DimsInvalid, 140	Exception, 248
-11-1-	Exception, 141	type description, 248
	type_description, 141	qpp::exception::NotImplemented, 249
aab	::exception::DimsMismatchCvector, 142	Exception, 250
-11-1-	Exception, 143	type_description, 250
	type_description, 143	qpp::exception::NotQubitCvector, 251
aab	::exception::DimsMismatchMatrix, 144	Exception, 252
-11-1-	Exception, 145	type_description, 252
	type_description, 145	qpp::exception::NotQubitMatrix, 253
aap	::exception::DimsMismatchRvector, 146	Exception, 254
-11-1-	Exception, 147	type_description, 254
	type_description, 147	qpp::exception::NotQubitRvector, 255
aap	::exception::DimsMismatchVector, 148	Exception, 256
-11-1-	Exception, 149	type_description, 256
	type_description, 149	qpp::exception::NotQubitSubsys, 257
aab	::exception::DimsNotEqual, 150	Exception, 258
-11-1-	Exception, 151	type_description, 258
	type_description, 151	qpp::exception::NotQubitVector, 259
aab	::exception::Duplicates, 153	Exception, 260
-11-1-	Exception, 154	type_description, 260
	type_description, 154	qpp::exception::OutOfRange, 261
agp	::exception::Exception, 167	Exception, 262
-11-12	Exception, 169	type_description, 262
	msg_, 170	qpp::exception::PermInvalid, 263
	type_description, 169	Exception, 264
	what, 169	type_description, 264
		7 bo_2001,buoti, 201

qpp::exception::PermMismatchDims, 265 Exception, 266	qpp::internal::IOManipEigen, 198 A_, 199
type_description, 266	chop_, 200
qpp::exception::QuditAlreadyMeasured, 312	display, 199
Exception, 313	IOManipEigen, 199
type_description, 314	qpp::internal::IOManipPointer
qpp::exception::SizeMismatch, 323	display, 202
Exception, 324	end_, 202
type_description, 324	IOManipPointer, 201, 202
qpp::exception::SubsysMismatchDims, 335	N_, 203
Exception, 336	operator=, 202
type_description, 336	p_, 203
qpp::exception::TypeMismatch, 342	separator_, 203
Exception, 343	start_, 203
type_description, 344	qpp::internal::IOManipPointer< PointerType >, 200
qpp::exception::UndefinedType, 344	qpp::internal::IOManipRange
Exception, 345	display, 205
type_description, 346	end_, 206
qpp::exception::Unknown, 346	first_, 206
Exception, 347	IOManipRange, 205
type_description, 348	last_, 206
qpp::exception::ZeroSize, 352	operator=, 205
Exception, 353	separator_, 206
type_description, 353	start_, 206
qpp::experimental, 118	qpp::internal::IOManipRange< InputIterator >, 204
qpp::internal, 118	qpp::internal::Singleton
check_cvector, 120	\sim Singleton, 322
check_dims, 120	get_instance, 322
check_dims_match_cvect, 120	get_thread_local_instance, 322
check_dims_match_mat, 120	operator=, 322
check_dims_match_rvect, 120	Singleton, 321, 322
check_eq_dims, 121	qpp::internal::Singleton< T >, 320
check_matching_sizes, 121	qpp::is_complex< std::complex< T >>, 208
check_no_duplicates, 121	qpp::is_complex< T >, 207
check_nonzero_size, 121	$qpp::is_iterable < T, \ to_void < \ decltype(std::declval < T$
check_perm, 121	$>$ ().begin()), decltype(std::declval $<$ T $>$ (). \leftarrow
check_qubit_cvector, 121	end()), $decltype(*(std::declval < T > (). \leftarrow$
check_qubit_matrix, 122	begin()))>>, 210
check_qubit_rvector, 122	qpp::is_iterable< T, typename >, 209
check_qubit_vector, 122	qpp::is_matrix_expression< Derived >, 211
check_rvector, 122	qpp::literals, 125
check_square_mat, 122	operator"" _bra, 125
check_subsys_match_dims, 122	operator"" _i, 125
check_vector, 123	operator""_ket, 126
dirsum2, 123	operator"" _prj, 126
get_dim_subsys, 123	qpp::make_void
get_num_subsys, 123	type, 218
hash_combine, 123	qpp::make_void< Ts >, 217
kron2, 123	QubitAmplitudeDampingNoise
multiidx2n, 124	qpp::QubitAmplitudeDampingNoise, 304
n2multiidx, 124	QubitBitFlipNoise
variadic_vector_emplace, 124	qpp::QubitBitFlipNoise, 306
qpp::internal::Display_Impl_, 152	QubitBitPhaseFlipNoise
display_impl_, 152	qpp::QubitBitPhaseFlipNoise, 307
qpp::internal::EqualEigen, 166	QubitDepolarizingNoise
operator(), 166	qpp::QubitDepolarizingNoise, 309
qpp::internal::HashEigen, 188	QubitPhaseDampingNoise
operator(), 188	qpp::QubitPhaseDampingNoise, 310

QubitPhaseFlipNoise	qpp::Gates, 184
qpp::QubitPhaseFlipNoise, 312	SWAPd
QuditDepolarizingNoise qpp::QuditDepolarizingNoise, 315	qpp::Gates, 180 SWAP
qppQualibepolarizingNoise, 313	qpp::Bit_circuit, 133
rand	qpp::Bit_circuit::Gate_count, 171
qpp, 90–92	qpp::Gates, 184
qpp::Dynamic_bitset, 162, 163	save
randH	qpp, 101
qpp, 92	qpp::RandomDevices, 319
randidx	saveMATLAB
qpp, 93	qpp, 101, 102
randket	schatten
qpp, 93	qpp, 102
randkraus	schmidtA
qpp, 93	qpp, 103
randn	schmidtB
qpp, 94, 95	qpp, 103, 104
random.h, 387	schmidtcoeffs
RandomDevices	qpp, 104, 105
qpp::RandomDevices, 318	schmidtprobs
randperm	qpp, 105, 106
qpp, 96	separator_
randprime	qpp::internal::IOManipPointer, 203
qpp, 96	qpp::internal::IOManipRange, 206
randprob	set
qpp, 97	qpp::Dynamic_bitset, 163, 164
randrho	set_begin_
qpp, 97	qpp::QCircuit::iterator, 216
randU	set_dit
qpp, 97	qpp::QEngine, 301
randV	set_end_
qpp, 98	qpp::QCircuit::iterator, 216
rd_	set_measured_
qpp::RandomDevices, 320	qpp::QEngine, 301
reference	sigma
qpp::QCircuit::iterator, 214	qpp, 106
renyi	Singleton
qpp, 98, 99	qpp::internal::Singleton, 321, 322
reset qpp::Bit_circuit, 132	sinm
qpp::Dynamic_bitset, 163	qpp, 107
qpp::QEngine, 301	size
reshape	qpp::Dynamic_bitset, 164
qpp, 99	spectralpowm
rho2bloch	qpp, 107
qpp, 100	sqrtm
rho2pure	qpp, 108
qpp, 100	start
Rn	qpp::Timer, 341
qpp::Gates, 179	qpp::internal::IOManipPointer, 203
RX	qpp::internal::IOManipRange, 206
qpp::Gates, 179	States
RY	qpp::States, 328
qpp::Gates, 180	statistics.h, 388
RZ	step_types_
qpp::Gates, 180	qpp::QCircuit, 294
approaces, 100	StepType
S	qpp::QCircuit, 272
	H 1

storage_size	qpp::Codes, 135
qpp::Dynamic_bitset, 164	type
storage_size_	qpp::make_void, 218
qpp::Dynamic_bitset, 165	type_
storage_type	qpp::QCircuit::iterator::value_type_, 351
qpp::Dynamic_bitset, 157	type_description
subsys_	qpp::exception::CustomException, 139
qpp::QEngine, 303	qpp::exception::DimsInvalid, 141
sum	qpp::exception::DimsMismatchCvector, 143
qpp, 108, 109	qpp::exception::DimsMismatchMatrix, 145
super2choi	qpp::exception::DimsMismatchRvector, 147
qpp, 109	qpp::exception::DimsMismatchVector, 149
svals	qpp::exception::DimsNotEqual, 151
qpp, 110	qpp::exception::Duplicates, 154
svd	qpp::exception::Exception, 169
qpp, 110	qpp::exception::InvalidIterator, 197
svdU	qpp::exception::MatrixMismatchSubsys, 220
qpp, 110	qpp::exception::MatrixNotCvector, 222
svdV	qpp::exception::MatrixNotRvector, 224
qpp, 111	qpp::exception::MatrixNotSquare, 226
syspermute	qpp::exception::MatrixNotSquareNorCvector, 228
qpp, 111, 112	qpp::exception::MatrixNotSquareNorRvector, 230
Т	qpp::exception::MatrixNotSquareNorVector, 232
qpp::Gates, 184	qpp::exception::MatrixNotVector, 234
TFQ	app::exception::NoCodeword, 239
qpp, 112	qpp::exception::NotBipartite, 248
qpp::QCircuit, 289	app::exception::NotImplemented, 250
TOF	app::exception::NotQubitCvector, 252
qpp::Bit_circuit, 133	qpp::exception::NotQubitMatrix, 254
qpp::Bit_circuit::Gate_count, 171	app::exception::NotQubitRvector, 256
qpp::Gates, 184	qpp::exception::NotQubitSubsys, 258
target_	qpp::exception::NotQubitVector, 260 qpp::exception::OutOfRange, 262
qpp::QCircuit::GateStep, 187	qpp::exception::PermInvalid, 264
qpp::QCircuit::MeasureStep, 236	qpp::exception::PermMismatchDims, 266
tic	qpp::exception::QuditAlreadyMeasured, 314
qpp::Timer, 340	qpp::exception::SizeMismatch, 324
tics	qpp::exception::SubsysMismatchDims, 336
qpp::Timer, 341	qpp::exception::TypeMismatch, 344
Timer	qpp::exception::UndefinedType, 346
qpp::Timer, 338, 339	qpp::exception::Unknown, 348
to_JSON	qpp::exception::ZeroSize, 353
qpp::IJSON, 193	types.h, 391
qpp::QCircuit, 290	
qpp::QEngine, 302	uniform
to_string	qpp, 114
qpp::Dynamic_bitset, 164	
to_void	V_
qpp, 28	qpp::Dynamic_bitset, 165
toc	value_type
qpp::Timer, 341	qpp::Dynamic_bitset, 157
trace	qpp::QCircuit::iterator, 214
qpp, 112	value_type_
traits.h, 389	qpp::QCircuit::iterator::value_type_, 349
transpose	value_type_qc_
qpp, 113 tsallis	qpp::QCircuit::iterator::value_type_, 351
qpp, 113, 114	var
	qpp, 115 variadic_vector_emplace
Туре	variauic_vectoi_emplace

```
qpp::internal, 124
W
    qpp::States, 333
what
    qpp::exception::Exception, 169
what_
    qpp::exception::CustomException, 139
where
    qpp::exception::Exception, 170
Χ
    qpp::Bit_circuit, 133
    qpp::Bit_circuit::Gate_count, 171
    qpp::Gates, 184
x0
    qpp::States, 333
х1
    qpp::States, 334
x2contfrac
    qpp, 115
Xd
    qpp::Gates, 182
Υ
    qpp::Gates, 185
y0
    qpp::States, 334
у1
    qpp::States, 334
Ζ
    qpp::Gates, 185
z0
    qpp::States, 334
z1
    qpp::States, 334
Zd
    qpp::Gates, 182
zero
    qpp::States, 330
```